

# Chapter 6: Static Routing



## **Routing Protocols**

Cisco | Networking Academy® | Mind Wide Open™



- 6.1 Static Routing Implementation
- 6.2 Configure Static and Default Routes
- 6.3 Review of CIDR and VLSM
- 6.4 Configure Summary and Floating Static Routes
- 6.5 Troubleshoot Static and Default Route Issues
- 6.6 Summary

# **Chapter 6: Objectives**

- Explain the advantages and disadvantages of static routing.
- Explain the purpose of different types of static routes.
- Configure IPv4 and IPv6 static routes by specifying a next-hop address.
- Configure an IPv4 and IPv6 default routes.
- Explain the use of legacy classful addressing in network implementation.
- Explain the purpose of CIDR in replacing classful addressing.

# **Chapter 6: Objectives (continued)**

- Design and implement a hierarchical addressing scheme.
- Configure an IPv4 and IPv6 summary network address to reduce the number of routing table updates.
- Configure a floating static route to provide a backup connection.
- Explain how a router processes packets when a static route is configured.
- Troubleshoot common static and default route configuration issues.

### **Static Routing**

## **Reach Remote Networks**

A router can learn about remote networks in one of two ways:

- Manually Remote networks are manually entered into the route table using static routes.
- Dynamically Remote routes are automatically learned using a dynamic routing protocol.

# Why Use Static Routing?

Static routing provides some advantages over dynamic routing, including:

- Static routes are not advertised over the network, resulting in better security.
- Static routes use less bandwidth than dynamic routing protocols, no CPU cycles are used to calculate and communicate routes.
- The path a static route uses to send data is known.

### **Static Routing**

# Why Use Static Routing? (continued)

## Static routing has the following disadvantages:

- Initial configuration and maintenance is timeconsuming.
- Configuration is error-prone, especially in large networks.
- Administrator intervention is required to maintain changing route information.
- Does not scale well with growing networks;
   maintenance becomes cumbersome.
- Requires complete knowledge of the whole network for proper implementation.

# Static Routing When to Use Static Routes

## Static routing has three primary uses:

- Providing ease of routing table maintenance in smaller networks that are not expected to grow significantly.
- Routing to and from stub networks. A stub network is a network accessed by a single route, and the router has no other neighbors.
- Using a single default route to represent a path to any network that does not have a more specific match with another route in the routing table. Default routes are used to send traffic to any destination beyond the next upstream router.


# Static Routes Static Route Applications

#### Static Routes are often used to:

- Connect to a specific network
- Provide a Gateway of Last Resort for a stub network
- Reduce the number of routes advertised by summarizing several contiguous networks as one static route
- Create a backup route in case a primary route link fails

# Types of Static Routes Standard Static Route

#### Connecting to a Stub Network



Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential '




- A default static route is a route that matches all packets.
- A default route identifies the gateway IP address to which the router sends all IP packets that it does not have a learned or static route.
- A default static route is simply a static route with 0.0.0.0/0 as the destination IPv4 address.

resentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 1

# Types of Static Routes Summary Static Route

#### **Using One Summary Static Route**




Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential

# Types of Static Routes Floating Static Route

 Floating static routes are static routes that are used to provide a backup path to a primary static or dynamic route, in the event of a link failure.

 The floating static route is only used when the primary route is not available.

 In order to accomplish this, the floating static route is configured with a higher administrative distance than the primary route.





#### ip route Command Syntax

Router(config) #ip route network-address subnet-mask {ip-address | exit-intf}

Parameter	Description			
network-address	Destination network address of the remote network to be added to the routing table.			
subnet-mask	<ul> <li>Subnet mask of the remote network to be added to the rout table.</li> <li>The subnet mask can be modified to summarize a group of networks.</li> </ul>			
ip-address	<ul> <li>Commonly referred to as the next-hop router's IP address.</li> <li>Typically used when connecting to a broadcast media (i.e., Ethernet).</li> <li>Commonly creates a recursive lookup.</li> </ul>			
exit-intf	<ul> <li>Use the outgoing interface to forward packets to the destination network.</li> <li>Also referred to as a directly attached static route.</li> <li>Typically used when connecting in a point-to-point configuration.</li> </ul>			

Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 14

# **Next-Hop Options**

The next hop can be identified by an IP address, exit interface, or both. How the destination is specified creates one of the three following route types:

- Next-hop route Only the next-hop IP address is specified.
- Directly connected static route Only the router exit interface is specified.
- Fully specified static route The next-hop IP address and exit interface are specified.


esentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 15

# Configure a Next-Hop Static Route


When a packet is destined for the 192.168.2.0/24 network, R1:

- 1. Looks for a match in the routing table and finds that it has to forward the packets to the next-hop IPv4 address 172.16.2.2.

  Verify the Routing Table of R1
- 2. R1 must now determine how to reach 172.16.2.2; therefore, it searches a second time for a 172.16.2.2 match.



# **Configure Directly Connected Static Route**



# Configure a Fully Specified Static Route

- In a fully specified static route, both the output interface and the next-hop IP address are specified.
- This is another type of static route that is used in older IOS's, prior to CEF.
- This form of static route is used when the output interface is a multi-access interface and it is necessary to explicitly identify the next hop.
- The next hop must be directly connected to the specified exit interface.

esentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 18



Along with ping and traceroute, useful commands to verify static routes include:

- show ip route
- show ip route static
- show ip route network

Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 19



#### **Default Static Route Syntax**

Router(config)#ip route 0.0.0.0 0.0.0.0 {ip-address | exit-intf}


Parameter	Description
0.0.0.0	Matches any network address.
0.0.0.0	Matches any subnet mask.
ip-address	<ul> <li>Commonly referred to as the next-hop router's IP address.</li> <li>Typically used when connecting to a broadcast media (i.e., Ethernet).</li> <li>Commonly creates a recursive lookup.</li> </ul>
exit-intf	<ul> <li>Use the outgoing interface to forward packets to the destination network.</li> <li>Also referred to as a directly attached static route.</li> <li>Typically used when connecting in a point-to-point configuration.</li> </ul>

Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential

### **Configure IPv4 Default Routes**


# **Configure a Default Static Route**

#### Configuring a Default Static Route



### **Configure IPv4 Default Routes**

# Verify a Default Static Route





# The ipv6 route Command

Most of parameters are identical to the IPv4 version of the command. IPv6 static routes can also be implemented as:

- Standard IPv6 static route
- Default IPv6 static route
- Summary IPv6 static route
- Floating IPv6 static route

Router(config) #ipv6 route ipv6-prefix/ipv6-mask {ipv6-address | exit-intf}




# **Next-Hop Options**

The next hop can be identified by an IPv6 address, exit interface, or both. How the destination is specified creates one of three route types:

- Next-hop IPv6 route Only the next-hop IPv6 address is specified.
- Directly connected static IPv6 route Only the router exit interface is specified.
- Fully specified static IPv6 route The next-hop IPv6 address and exit interface are specified.


## Configure a Next-Hop Static IPv6 Route

#### Configure Next-hop Static IPv6 Routes



# Configure IPv6 Static Routes Configure Directly connected Static IPv6 Route

#### Configure Directly Connected Static IPv6 Routes on R1



# Configure Fully Specified Static IPv6 Route

#### Configure Fully Specified Static IPv6 Routes on R1



```
R1 (config) # ipv6 route 2001:db8:acad:2::/64 fe80::2
% Interface has to be specified for a link-local nexthop
R1 (config) # ipv6 route 2001:db8:acad:2::/64 s0/0/0 fe80::2
R1 (config) #
```



Along with ping and traceroute, useful commands to verify static routes include:

- show ipv6 route
- show ipv6 route static
- show ipv6 route network

esentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 28



## **Default Static IPv6 Route**

#### Default Static IPv6 Route Syntax


Router(config) #ipv6 route ::/0 {ipv6-address | exit-intf}

Parameter	Description			
::/0	Matches any IPv6 prefix regardless of IPv6 mask.			
ip-address	<ul> <li>Commonly referred to as the next-hop router's IPv6 address.</li> <li>Typically used when connecting to a broadcast media (i.e., Ethernet).</li> <li>Commonly creates a recursive lookup.</li> </ul>			
exit-intf	<ul> <li>Use the outgoing interface to forward packets to the destination network.</li> <li>Also referred to as a directly attached static route.</li> <li>Typically used when connecting in a point-to-point configuration.</li> </ul>			

### **Configure IPv6 Default Routes**

# Configure a Default Static IPv6 Route


#### Configuring a Default Static IPv6 Route



Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential

### **Configure IPv6 Default Routes**

## Verify a Default Static Route







# **Classful Network Addressing**

Class	High Order Bits	Start	End
Class A	0xxxxxxx	0.0.0.0	127.255.255.255
Class B	10xxxxxx	128.0.0.0	191.255.255.255
Class C	110xxxxx	192.0.0.0	223.255.255.255
Multicast	1110xxxx	224.0.0.0	239.255.255.255
Reserved	1111xxxx	240.0.0.0	255.255.255.255



## **Classful Subnet Masks**

### Class A

	Network	Host	Host	Host
Subnet mask	255	.0	.0	.0

### Class B


	Network	Network	Host	Host
Subnet mask	255	.255	0	0


### Class C

	Network	Network	Network	Host
Subnet mask	255	.255	.255	.0

### **Classful Addressing**

# Classful Routing Protocol Example







# Classful Addressing Waste

#### Classfull IP Address Allocation = Inefficient

#### Class A (1 - 126)

# of possible networks: 126 # of Hosts/Net: 16,777,214 Max. # Hosts: 2,113,928,964

#### Class B (128 - 191)

# of possible networks: 16,384 # of Hosts/Net: 65,534


Max. # Hosts: 1,073,709,056

#### Class C (192 - 223)

# of possible networks: 2,097,152

# of Hosts/Net: 254

Max. # Hosts: 532,676,608



#### **CIDR**


# **Classless Inter-Domain Routing**

#### CIDR = Efficient


Class A (1 – 126) # of possible networks: 126 # of Hosts/Net: 16, 77,214 Max. # Hosts: 16,77,214

Class B (128 - 191) # of possible networks: 16,384 # of Hosts/Net: 65,534 Max. # Hosts: 1,73, 109,056

Class C (192 – 2.3) # of possible networks: 2,097,152 # of Hosts/Net: 254 Max. # Hosts: 522,673,608




## CIDR and Route Summarization



## Static Routing CIDR Example


#### **One Summary Static Route**



#### **CIDR**


### **Classless Routing Protocol Example**

#### **Classless Routing Update**



## Fixed Length Subnet Masking

#### Basic Subnet Scheme




Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 40



#### **Subnets of Varying Sizes**

One subnet was further divided to create 8 smaller subnets of 2 hosts each.





- VLSM allows the use of different masks for each subnet.
- After a network address is subnetted, those subnets can be further subnetted.
- VLSM is simply subnetting a subnet. VLSM can be thought of as sub-subnetting.
- Individual host addresses are assigned from the addresses of "sub-subnets".



#### Subnetting the Subnet 10.2.0.0/16 to 10.2.0.0/24

Starting Address Space



Network 10.0.0.0/8 1st Round of Subnets

Subnets
10.0.0.0/16
10.1.0.0/16
10.2.0.0/16
10.3.0.0/16
10.4.0.0/16
10.5.0.0/16
10.255.0.0/16

256 Subnets


Subnets of the Subnet

Sub-Subnets
10.2.0.0/24
10.2.1.0/24
10.2.2.0/24
10.2.3.0/24
10.2.4.0/24
10.2.5.0/24
10.2.255.0/24

256 Subnets

## VLSM Example

#### Subnetting Subnet 192.168.20.224/27 to 192.168.20.224/30



## Configure IPv4 Summary Routes Route Summarization

- Route summarization, also known as route aggregation, is the process of advertising a contiguous set of addresses as a single address with a lessspecific, shorter subnet mask.
- CIDR is a form of route summarization and is synonymous with the term supernetting.
- CIDR ignores the limitation of classful boundaries, and allows summarization with masks that are smaller than that of the default classful mask.
- This type of summarization helps reduce the number of entries in routing updates and lowers the number of entries in local routing tables.



### **Calculate a Summary Route**

#### Calculating a Route Summary

Step 2: Count the number of far-left matching bits to determine the mask.


Answer: 14 matching bits = /14 or 255.252.0.0


Step 3: Copy the matching bits and add zero bits to determine the network address.

Answer: 172.20.0.0

Presentation\_ID © 2008 Cisco Systems, Inc. All rights reserved. Cisco Confidential 40

## Configure IPv4 Summary Routes Summary Static Route Example





172.16.0.0 255.255.252.0

### **Configure IPv6 Summary Routes**

### Summarize IPv6 Network Addresses

- Aside from the fact that IPv6 addresses are 128 bits long and written in hexadecimal, summarizing IPv6 addresses is actually similar to the summarization of IPv4 addresses. It just requires a few extra steps due to the abbreviated IPv6 addresses and hex conversion.
- Multiple static IPv6 routes can be summarized into a single static IPv6 route if:
  - The destination networks are contiguous and can be summarized into a single network address.
  - The multiple static routes all use the same exit interface or next-hop IPv6 address.

### **Configure IPv6 Summary Routes**


### Calculate IPv6 Network Addresses

- Step 1. List the network addresses (prefixes) and identify the part where the addresses differ.
- Step 2. Expand the IPv6 if it is abbreviated.
- Step 3. Convert the differing section from hex to binary.
- Step 4. Count the number of far left matching bits to determine the prefix-length for the summary route.
- Step 5. Copy the matching bits and then add zero bits to determine the summarized network address (prefix).
- Step 6. Convert the binary section back to hex.
- Step 7. Append the prefix of the summary route (result of Step 4).

### **Configure IPv6 Summary Routes**

## **Configure an IPv6 Summary Address**

#### Remove Static Routes and Configure Summary IPv6 Route




## Floating Static Routes Floating Static Routes

- Floating static routes are static routes that have an administrative distance greater than the administrative distance of another static route or dynamic routes.
- The administrative distance of a static route can be increased to make the route less desirable than that of another static route or a route learned through a dynamic routing protocol.
- In this way, the static route "floats" and is not used when the route with the better administrative distance is active.
- However, if the preferred route is lost, the floating static route can take over, and traffic can be sent through this alternate route.

### Configure Floating Static Routes

## **Configure a Floating Static Route**

#### Configuring a Floating Static Route to R3





## **Test the Floating Static Route**

- Use a show ip route command to verify that the routing table is using the default static route.
- Use a traceroute command to follow the traffic flow out the primary route.
- Disconnect the primary link or shutdown the primary exit interface.
- Use a show ip route command to verify that the routing table is using the floating static route.
- Use a traceroute command to follow the traffic flow out the backup route.



Common IOS troubleshooting commands include:

- ping
- traceroute
- show ip route
- show ip interface brief
- show cdp neighbors detail

## **Chapter 6: Summary**

- Static routes can be configured with a next-hop IP address, which is commonly the IP address of the next-hop router.
- When a next-hop IP address is used, the routing table process must resolve this address to an exit interface.
- On point-to-point serial links, it is usually more efficient to configure the static route with an exit interface.
- On multi-access networks, such as Ethernet, both a nexthop IP address and an exit interface can be configured on the static route.
- Static routes have a default administrative distance of "1".

## **Chapter 6: Summary (continued)**

- A static route is only entered in the routing table if the next-hop IP address can be resolved through an exit interface.
- Whether the static route is configured with a next-hop IP address or exit interface, if the exit interface that is used to forward that packet is not in the routing table, the static route is not included in the routing table.
- In many cases, several static routes can be configured as a single summary route.

## **Chapter 6: Summary (continued)**

- The ultimate summary route is a default route, configured with a 0.0.0.0 network address and a 0.0.0.0 subnet mask.
- If there is not a more specific match in the routing table, the routing table uses the default route to forward the packet to another router.
- A floating static route can be configured to back up a main link by manipulating its administrative value.

# Cisco | Networking Academy® | Mind Wide Open™