4 - MIPS II

4.1 Memory Organization

- The main memory can be viewed as a large, single-dimension array of memory locations
- Each location of the memory has an address, which is an index into the array
 - \circ Given a ${f k}$ -bit address, the address space is of size 2^k
- The memory map on the below contains one byte (8 bits) in every location/address.
 - This is called byte addressing

Address	s Content
0	8 bits
1	8 bits
2	8 bits
3	8 bits
4	8 bits
5	8 bits
6	8 bits
7	8 bits
8	8 bits
9	8 bits
10	8 bits
11	8 bits

•

Byte Addressing 字节寻址

Byte addressing (字节寻址)是指在计算机内存中,每个字节都有其独特的地址。这意味着,即使一个数据项 (例如32位整数)需要多个字节来存储,我们仍然可以分别访问这些字节。

为了更加清晰地说明,我们可以拿一个32位整数来做例子:

假设我们有一个32位的整数,它需要4个字节来存储(因为32位等于4字节)。在byte addressing系统中,这4个字节会被存放在连续的内存地址中。假设该整数的第一个字节存储在地址0x1000处,那么:

• 第一个字节的地址是: 0x1000

第二个字节的地址是: 0x1001第三个字节的地址是: 0x1002第四个字节的地址是: 0x1003

这就是byte addressing的核心思想,即每个字节在内存中都有唯一的地址。这种方式使得硬件和软件可以非常灵活地访问内存,但与此同时,也需要在内存管理方面投入更多的精力,以确保有效地使用这种精细级别的寻址机制。


4.1.1 Memory: Transfer Unit

- Using distinct memory address, we can access:
 - o a single byte (byte addressable) or
 - a single word (word addressable)
- Word is:
 - \circ Usually 2^n bytes
 - The common unit of transfer between processor and memory
 - Also commonly coincide with the register size, the integer size and instruction size in most architecture

Word的大小通常与寄存器大小相同,例如32位架构中,通常由32位的寄存器(4字节),一个word就是32位

4.1.2 Memory: Word Alignment

- Word alignment:
 - Words are aligned in memory if they begin at a byte address that is a multiple of the number of bytes in the word
- Example: If a word consists of 4 bytes, then:



"Word Alignment" (或简称 "Alignment") 是计算机存储和内存管理中的一个概念,它指的是数据项在内存中的开始地址应该是其大小 (通常是数据项大小或特定架构的word大小) 的某个倍数。

为什么需要对齐?

1. **性能**:在许多架构上,访问对齐的数据比非对齐的数据要快。当数据对齐时,数据可能完全位于一个或多个缓存行内,从而减少了需要访问的缓存行数量。

- 2. 硬件要求:一些处理器不支持非对齐的数据访问,或者在尝试这样做时可能导致性能损失或异常。
- 以32位系统为例,其中word的大小为4字节(32位):
 - 如果一个32位的整数地址为0×1004或0×1008,那么这个整数是对齐的,因为这些地址都是4的倍数。
- 但是,如果这个32位的整数的地址为0x1005或0x1006,那么它就不是对齐的,因为这些地址不是4的倍数。

为了确保对齐,编译器和内存分配器通常会自动处理数据对齐的问题,为变量分配适当对齐的地址。但在低级编程或嵌入式系统开发中,程序员可能需要更加关注对齐的问题,因为它可能会影响性能或正确性。

如果是64位系统,则应该是8的倍数。

4.2 MIPS Memory Instructions

- MIPS is a load-store register architecture
 - o 32 registers, each 32-bit (4 bytes) long
 - Each word contains 32-bit (4 bytes)
 - o Memory addresses are 32-bit long


Name	Examples	Comments
32 registers	\$s0-\$s7, \$t0-\$t9, \$zero, \$a0-\$a3, \$v0-\$v1, \$gp, \$fp, \$sp, \$ra, \$at	Fast processor storage for data. In MIPS, data must be in registers to perform arithmetic.
2^{30} memory words	Mem[0] , Mem[1] ,, Mem[4294967292]	Accessed only by data transfer instructions. MIPS uses byte addresses, so consecutive words differ by 4. Memory holds data structures, such as arrays, and spilled registers, such as those saved on procedure calls

- 32 registers:
 - 1. \$0 或 \$zero: 这个寄存器始终包含值0,任何尝试向其写入的操作都会被忽略。
 - 2. \$1 或 \$at: 为汇编器预留的临时寄存器。
 - 3. \$2-\$3 或 \$v0-\$v1:用于返回函数值的寄存器。
 - 4. \$4-\$7 或 \$a0-\$a3: 用于传递函数参数的寄存器。
 - 5. \$8-\$15 、 \$24-\$25 或 \$t0-\$t7 和 \$t8-\$t9 : 临时寄存器,函数调用不会保存它们。
 - 6. \$16-\$23 或 \$s0-\$s7: 保存的寄存器,函数调用会保存它们。
 - 7. \$26-\$27 或 \$k0-\$k1: 为操作系统预留的寄存器。
 - 8. \$28 或 \$gp:全局指针。
 - 9. \$29 或 \$sp: 堆栈指针。
 - 10. \$30 或 \$fp:帧指针(在某些约定中使用)。
 - 11. \$31 或 \$ra:返回地址。

- memory words
 - 。 指内存中的数据单元。一个 "word" 在 MIPS 中通常指代一个固定大小的数据块, 其大小在传统的 MIPS 架构中为 32 位, 或 4 字节。
 - 。 如果 MIPS 系统有 2^{30} 个 "memory words", 这意味着这个系统有 2^{30} 个独立的 32 位数据 块。换句话说,该系统的总内存大小是 2^{30} ×32 位,或 2^{30} ×4 字节 (4GB)。
- Words and Memory words
 - o Word: 是指数据的大小。在 32 位 MIPS 架构中, 一个 word 是 32 位或 4 字节。
 - 。 Memory Words: 是指内存中的 word 单元的数量。如果一个系统有 2^{30} 个 memory words, 那么它具有 2^{30} 个独立的 32 位数据单元。

4.2.1 Memory Instruction: Load Word

• lw \$t0, 4(\$t0)




- Steps:
 - 1. Memory Address = \$s0 + 4 = 8000 + 4 = 8004
 - 2. Memory word at Mem[8004] is loaded into \$t0
 - 1. lw: 这是 "load word" 的指令, 意味着从内存中加载一个 32 位的数据块。
 - 2. \$t0: 这是目标寄存器,指示数据从内存加载到哪个寄存器中。
 - 3. 4(\$t0): 这是源操作数,表示内存的地址。这个地址是通过取 \$t0 寄存器中的值,并加上偏移量 4 来计算的。这里的偏移量是以字节为单位的,因此 4 实际上是 4 字节的偏移量。

所以,整体上,这条指令的意思是: 从地址为 \$t0 + 4 的位置加载一个 word (32 位的数据块)到 \$t0 寄存器中。

例如,假设 \$t0 中原来的值是 0x8000 ,那么这条指令会从内存地址 0x8004 加载一个 word 到 \$t0 寄存器中。

4.2.2 Memory Instruction: Store Word

• sw \$t0, 12(\$s0)



- Steps:
 - 1. Memory Address = \$t0 + 12 = 8000 + 12 = 8012
 - 2. Content of \$t0 is stored into word at Mem[8012]
 - 1. sw: 这是 "store word" 的指令, 意味着将一个 32 位的数据块存储到内存中。
- 2. \$t0: 这是源寄存器,它表示要存储到内存中的数据来源于哪个寄存器。
- 3. **12(\$s0)** : 这是目标操作数,表示内存的地址。这个地址是通过取 **\$s0** 寄存器中的值,并加上偏移 量 **12** 来计算的。这里的偏移量是以字节为单位的,所以 **12** 实际上是 **12** 字节的偏移量。

因此,整体上,这条指令的意思是: 将 \$t0 寄存器中的 word (32 位的数据块) 存储到地址为 \$s0 + 12 的内存位置。

例如,假设 \$s0 中的值是 0x8000 ,那么这条指令会将 \$t0 寄存器中的内容存储到内存地址 0x8012 的位置。

4.2.3 Load and Store Instructions

- Only load and store instructions can access data in memory
- Example: Each array element occupies a word


C Code	MIPS Code
A[7] = h + A[10]	lw \$t0, 40(\$s3) add \$t0, \$s2, \$t0 sw \$t0, 28(\$s3)

- Each array element occupies a word(4 bytes)
- \$s3 contains the base address (address of first element, A[0]) of array A.
 Variable h is mapped to \$s2

4.2.4 Memory Instructions: Others

- Other than load word (lw) and store word (sw), there are other variants, example:
 - o load byte (lb)
 - o store byte (sb)
- Similar in format:
 - o lb \$t1, 12(\$s3)
 - o lb \$t2, 13(\$s3)
- · Similar in working except that one byte, instead of one word, is loaded or stored
 - o Note that the offset no longer needs to be a multiple of 4
- MIPS disallows loading/storing unaligned word using lw / sw
 - Pseudo-Instructions unaligned load word ulw and unaligned store word usw are provided for this purpose
- Other memory instructions:
 - o lh and sh : load and store halfword
 - o lwl , lwr , swl , swr : load word left/right, store word left/right

4.2.5 Example: Array



- 1. **C Statement to translate**: 我们要转换的 C 语句是 A[3] = h + A[1]; 。这个语句表示要将 变量 h 与数组 A 的第二个元素(索引为1的元素)相加,然后将结果存储在数组 A 的第四个元素中(索引为3的元素)。
- 2. Variables Mapping: 这部分为我们提供了 C 语句中变量与 MIPS 寄存器之间的映射关系。即变量 h 映射到寄存器 \$s2 , 而数组 A 的基地址 (第一个元素的地址) 映射到寄存器 \$s3 。
- 3. MIPS Instructions:

- 。 lw \$t0, 4(\$s3) : 这条指令从数组 A 中加载第二个元素 (由于每个元素占 4 字节, 所以索引为1的元素的偏移是 4 字节) 到临时寄存器 \$t0 中。
- o add \$t0, \$s2, \$t0 : 这条指令将寄存器 \$s2 (存储变量 h 的值)与寄存器 \$t0 中的值相加,并将结果存储在 \$t0 中。
- 。 sw \$t0, 12(\$s3): 这条指令将 \$t0 中的值存储到数组 A 的第四个元素 (由于每个元素 占 4 字节, 所以索引为3的元素的偏移是 12 字节)。
- 4. Memory Representation: 这部分展示了数组 A 在内存中的表示方式。从基地址 \$s3 开始,每个格子表示数组的一个元素。每个元素都是一个 word,这里假设一个 word 的大小是 4 字节。

4.2.6 Common Questions

Address vs Value

Registers do NOT have types

- A register can hold any 32-bit number:
 - The number has no implicit data type and is interpreted according to the instruction that use it
- Examples:
 - add \$t2, \$t1, \$t0
 - \$t0 and \$t1 should contain data values
 - lw \$t2, 0(\$t0)
 - \$t0 should contain a memory address

Byte vs Word

Consecutive word addresses in machines with byte-addressing do not differ by 1

- Common error:
 - Assume that the address of the next word can be found by incrementing the address in a register by 1 instead of by the word size in bytes
- For both <code>lw</code> and <code>sw</code>:
 - The sum of base address and offset must be a multiple of 4 (i.e. to adhere to word boundary)

4.2.7 Example: Swapping Elements

```
C Statement to translate
                                                 Variables Mapping
                                       k → $5
swap( int v[], int k )
                                       Base address of \mathbf{v}[] \rightarrow \$4
{
                                       temp → $15
    int temp;
    temp = v[k]
    v[k] = v[k+1];
                                       Example: k = 3; to swap v[3] with v[4].
                                       Assume base address of v is 2000.
    v[k+1] = temp;
}
                                        5 (k) \leftarrow 3
                                        $4 (base addr. of v) \leftarrow 2000
       swap:
                   $2, $5, 2
           sll
                                        $2 ← 12
            add $2, $4, $2
                                        $2 ← 2012
                  $15, 0($2)
           lw
                                        $15 \leftarrow content of mem. addr. 2012 (v[3])
           lw
                   $16, 4($2)
                                        $16 \leftarrow content of mem. addr. 2016 (v[4])
                   $16, 0($2)
            SW
                                        content of mem. addr. 2012 (v[3]) \leftarrow $16
                   $15, 4($2)
            SW
                                        content of mem. addr. 2016 (v[4]) \leftarrow $15
```

交换数组中两个连续元素的值 (C和MIPS)

- 我们要转换的C函数是swap,函数的主要逻辑是交换数组 v 中索引为 k 和 k+1 的两个连续元素。
- Variables Mapping: 这部分为我们提供了 C 函数中变量与 MIPS 寄存器之间的映射关系。即参数 k 映射到寄存器 \$5 ,数组 v 的基地址映射到寄存器 \$4 ,局部变量 temp 映射到寄存器 \$15 。
- **Example**: 提供了一个具体的例子,即当 k=3 时,交换数组 v 的第四和第五个元素 (v[3] 和 v[4])。假设数组的基地址是 2000。
- MIPS Instructions:
 - 。 **sll** \$2, \$5, 2 : 这条指令是将 k (存储在 \$5 中) 乘以 4 (因为每个整数大小是4字 节) ,结果保存在 \$2 。这是为了计算数组中索引为 k 的元素的偏移量。
 - add \$2, \$4, \$2 : 将基地址(存储在 \$4) 和偏移量(存储在 \$2) 相加, 计算出 v[k] 的地址, 并将其保存在 \$2 中。
 - o lw \$15, 0(\$2): 加载 v[k] 的值到 \$15。
 - o lw \$16, 4(\$2): 加载 v[k+1] 的值到 \$16。
 - o sw \$16, 0(\$2): 将 v[k+1] 的值存储到 v[k] 的位置。
 - o sw \$15, 4(\$2): 将 v[k] 的值存储到 v[k+1] 的位置。

4.3 Making Decisions

- Decision make in high-level language:
 - o if and goto statement
 - o MIPS decision making instructions are similar to if statement with a goto
- Decision making instructions
 - Alter the control flow of the program
 - Change the next instruction to be executed
- Two types of decision-making statements in MIPS
 - Conditional (branch)bne \$t0, \$t1, labelbeq \$t0, \$t1, label
 - Unconditional (jump)j label
- A label is an anchor in the assembly code to indicate point of interest, usually as branch target
 - Labels are NOT instructions

1. Decision make in high-level language:

- 。 当我们在高级编程语言(如 C、Java 或 Python)中进行决策时,通常使用的是 if 语句和 goto 语句。
- 。 MIPS 的决策制定指令与高级编程语言中的 **if** 语句相似,并经常与 **goto** 语句一起使用,以 决定程序的执行流程。
- 2. Decision making instructions:
 - 。 这些指令用于改变程序的控制流程。
 - 。 它们会改变下一条要执行的指令,从而使程序可能跳转到不同的部分执行。


4.3.1 Conditional Branch: beq and bne

- Processor follows the branch only when the condition is satisfied (True)
- beq \$r1, \$r2, L1
 - Go to statement labeled L1 if the value in register \$r1 equals the value in register \$r2
 - o beq is "branch if equal"
 - o C code: if (a==b) goto L1
- bne \$r1, \$r2, L1
 - o Go to statement labeled L1 if the value in register \$r1 does not equal the value in register \$r2
 - o bne is "branch if not equal"
 - o C code: if (a != b) goto L1


4.3.2 Unconditional Jump: j

- Processor always follows the branch
- j L1
 - ∘ Jump to label L1 unconditionally
 - o C code: goto L1
- Technically equivalent to such statement beq \$50, \$50, L1

4.3.3 IF statement



The right one is more efficient



Re-write to beq

```
1 beq $s3, $s4, Else
2 sub $s0, $s1, $s2
3 j Exit
4 Else: add $s0, $s1, $s2
5 Exit:
```

4.3.4 Exercise #1: IF statement

MIPS code to translate into C	Variables Mapping
<pre>beq \$s1, \$s2, Exit add \$s0, \$zero, \$zero Exit:</pre>	f → \$s0 i → \$s1 j → \$s2

What is the corresponding high-level statement?

4.4 Loops

C while-loop:

Rewritten with goto

Key concept:

Any form of loop can be written in assembly with the help of conditional branches and jumps.

4.4.1 Exercise #2: FOR loop

4.4.2 Inequalities

- We have beq and bne, what about branch-if-less-than?
 There is no real blt instruction in MIPS
- Use slt (set on less than) or slti

```
1 slt $t0, $s1, $s2

1 if ($s1 < $s2)

2 $t0 = 1;

3 else

4 $t0 = 0;
```

• To build a blt \$s1, \$s2, L in instruction

```
1 slt $t0, $s1, $s2
2 bne $t0, $zero, L

1 if ($t1 < $t2)
2 goto L;
```

- This is another example of pseudo-instruction
 - Assembler translates (blt) instruction in an assembly program into the equivalent MIPS(two) instructions

4.5 Array and Loop

• Typical example of accessing array elements in a loop:

4.6 Exercises