
Chapter 8: Main Memory





Chapter 8: Memory Management

- Background
- Swapping
- Contiguous Memory Allocation
- Segmentation
- Paging
- Structure of the Page Table
- Example: The Intel 32 and 64-bit Architectures
- Example: ARM Architecture





Background


- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
- Memory unit only sees a stream of addresses + read requests, or address + data and write requests
- Register access in one CPU clock (or less)
- Main memory can take many cycles, causing a stall
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation





Base and Limit Registers


- ☐ A pair of base and limit registers define the logical address space
- CPU must check every memory access generated in user mode to be sure it is between base and limit for that user







Hardware Address Protection







Address Binding

- Programs on disk, ready to be brought into memory to execute form an input queue
 - Without support, must be loaded into address 0000
- Inconvenient to have first user process physical address always at 0000
 - How can it not be?
- Further, addresses represented in different ways at different stages of a program's life
 - Source code addresses usually symbolic
 - Compiled code addresses bind to relocatable addresses
 - i.e. "14 bytes from beginning of this module"
 - Linker or loader will bind relocatable addresses to absolute addresses
 - i.e. 74014
 - Each binding maps one address space to another






Binding of Instructions and Data to Memory

- Address binding of instructions and data to memory addresses can happen at three different stages
 - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
 - Load time: Must generate relocatable code if memory location is not known at compile time
 - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
 - Need hardware support for address maps (e.g., base and limit registers)





Multistep Processing of a User Program







Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
 - Logical address generated by the CPU; also referred to as virtual address
 - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program





Memory-Management Unit (MMU)


- Hardware device that at run time maps virtual to physical address
- To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
 - Base register now called relocation register
 - MS-DOS on Intel 80x86 used 4 relocation registers
- The user program deals with *logical* addresses; it never sees the real physical addresses
 - Execution-time binding occurs when reference is made to location in memory
 - Logical address bound to physical addresses





Dynamic relocation using a relocation register

- Routine is not loaded until it is called
- All routines kept on disk in relocatable load format
- No special support from the operating system is required







Dynamic Linking

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, stub, used to locate the appropriate memory-resident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
 - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries





Swapping

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
 - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk






Swapping (Cont.)

- Does the swapped out process need to swap back in to same physical addresses?
- Depends on address binding method
 - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
 - Swapping normally disabled
 - Started if more than threshold amount of memory allocated
 - Disabled again once memory demand reduced below threshold





Schematic View of Swapping



main memory





Context Switch Time including Swapping

- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
 - Swap out time of 2000 ms
 - Plus swap in of same sized process
 - Total context switch swapping component time of 4000ms (4 seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
 - System calls to inform OS of memory use via request_memory() and release_memory()





Context Switch Time and Swapping (Cont.)

- Other constraints as well on swapping
 - Pending I/O can't swap out as I/O would occur to wrong process
 - Or always transfer I/O to kernel space, then to I/O device
 - Known as double buffering, adds overhead
- Standard swapping not used in modern operating systems
 - But modified version common
 - Swap only when free memory extremely low





Contiguous Allocation

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually into two partitions:
 - Resident operating system, usually held in low memory with interrupt vector
 - User processes then held in high memory
 - Each process contained in single contiguous section of memory






Contiguous Allocation (Cont.)

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
 - Base register contains value of smallest physical address
 - Limit register contains range of logical addresses each logical address must be less than the limit register
 - MMU maps logical address dynamically
 - Can then allow actions such as kernel code being transient and kernel changing size





Hardware Support for Relocation and Limit Registers








Multiple-partition allocation

- Multiple-partition allocation
 - Degree of multiprogramming limited by number of partitions
 - Variable-partition sizes for efficiency (sized to a given process' needs)
 - When a process arrives, it is allocated memory from a hole large enough to accommodate it
 - Process exiting frees its partition, adjacent free partitions combined
 - Operating system maintains information about:
 a) allocated partitions
 b) free partitions (Hole block of available memory; holes of various size scattered throughout memory)





Dynamic Storage-Allocation Problem

How to satisfy a request of size *n* from a list of free holes?

- ☐ First-fit: Allocate the *first* hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size
 - Produces the smallest leftover hole
- □ Worst-fit: Allocate the *largest* hole; must also search entire list
 - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization





Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used and cant be used by any other process small enough to fit in that space
- First fit analysis reveals that given N blocks allocated, 0.5 N blocks lost to fragmentation
 - □ 1/3 may be unusable -> 50-percent rule





Fragmentation (Cont.)

- Reduce external fragmentation by compaction
 - Shuffle memory contents to place all free memory together in one large block
 - Compaction is possible only if relocation is dynamic, and is done at execution time
- Now consider that backing store has same fragmentation problems





Segmentation

- Memory-management scheme that supports user view of memory
- A program is a collection of segments
 - A segment is a logical unit such as:

```
main program
```

procedure

function

method

object

local variables, global variables

common block

stack


symbol table

arrays






User's View of a Program







Logical View of Segmentation



4 2 3

physical memory space





Segmentation Architecture

- Logical address consists of a two tuple:
 - <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory
 - limit specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;
 - segment number s is legal if s < STLR






Segmentation Architecture (Cont.)

- Protection
 - With each entry in segment table associate:
 - validation bit = $0 \Rightarrow$ illegal segment
 - read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level
- Since segments vary in length, memory allocation is a dynamic storage-allocation problem
- □ A segmentation example is shown in the following diagram





Segmentation Hardware







Paging

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
- □ Divide physical memory into fixed-sized blocks called frames
 - □ Size is power of 2, between 512 bytes and 16 Mbytes
- □ Divide logical memory into blocks of same size called pages
- □ Keep track of all free frames
- □ To run a program of size N pages, need to find N free frames and load program
- ☐ Set up a page table to translate logical to physical addresses
- □ Backing store likewise split into pages





Address Translation Scheme

- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory
 - □ Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit


| page number | page offset |
|-------------|-------------|
| р | d |
| m -n | n |

□ For given logical address space 2^m and page size 2ⁿ






Paging Hardware








Paging Model of Logical and Physical Memory





Paging Example




n=2 and m=4 32-byte memory and 4-byte pages





Free Frames



Before allocation

After allocation





Paging (Cont.)

- Avoids external fragmentation
- Avoids problem of varying sized memory chunks
- Suffers from Internal fragmentation





Paging (Cont.)

- Calculating internal fragmentation
 - □ Page size = 2,048 bytes
 - □ Process size = 72,766 bytes
 - 35 pages + 1,086 bytes
 - □ Internal fragmentation of 2,048 1,086 = 962 bytes
 - Worst case fragmentation = 1 frame 1 byte
 - On average fragmentation = 1 / 2 frame size
 - So small frame sizes desirable?
 - But each page table entry takes memory to track
 - Page sizes growing over time
 - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation process can only access its own memory





Implementation of Page Table

- Page table is kept in main memory
- □ Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
 - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





Implementation of Page Table (Cont.)

- Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide address-space protection for that process
 - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1,024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
 - Replacement policies must be considered
 - Some entries can be wired down for permanent fast access





Associative Memory

□ Associative memory – parallel search


| Page # | Frame # |
|--------|---------|
| | |
| | |
| | |
| | |

- □ Address translation (p, d)
 - ☐ If p is in associative register, get frame # out
 - Otherwise get frame # from page table in memory





Paging Hardware With TLB







Effective Access Time

- \square Associative Lookup = ε time unit
 - □ Can be < 10% of memory access time
- □ Hit ratio = α
 - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Consider $\alpha = 80\%$, $\varepsilon = 20$ ns for TLB search, 100ns for memory access
- □ Effective Access Time (EAT)

EAT =
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$

= $2 + \varepsilon - \alpha$

- Consider α = 80%, ϵ = 20ns for TLB search, 100ns for memory access
 - \blacksquare EAT = 0.80 x 100 + 0.20 x 200 = 120ns
- Consider more realistic hit ratio -> α = 99%, ϵ = 20ns for TLB search, 100ns for memory access
 - \blacksquare EAT = 0.99 x 100 + 0.01 x 200 = 101ns







Memory Protection

- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
 - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
 - "invalid" indicates that the page is not in the process' logical address space
 - Or use page-table length register (PTLR)
- Any violations result in a trap to the kernel





Valid (v) or Invalid (i) Bit In A Page Table







Shared Pages

□ Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space





Shared Pages Example







Structure of the Page Table

- Memory structures for paging can get huge using straightforward methods
 - Consider a 32-bit logical address space as on modern computers
 - Page size of 4 KB (2¹²)
 - Page table would have 1 million entries (2³² / 2¹²)
 - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
 - That amount of memory used to cost a lot
 - Don't want to allocate that contiguously in main memory
- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables






Hierarchical Page Tables

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- We then page the page table





Two-Level Page-Table Scheme







Two-Level Paging Example

- □ A logical address (on 32-bit machine with 1K page size) is divided into:
 - a page number consisting of 22 bits
 - a page offset consisting of 10 bits
- □ Since the page table is paged, the page number is further divided into:

nage offert

- a 12-bit page number
- a 10-bit page offset
- ☐ Thus, a logical address is as follows:


| page nu | mber | page onset | | |
|---------|----------|------------|--|--|
| p_1 | ρ_2 | d | | |
| 12 | 10 | 10 | | |

- where p_1 is an index into the outer page table, and p_2 is the displacement within the page of the inner page table
- Known as forward-mapped page table





Address-Translation Scheme







64-bit Logical Address Space

- Even two-level paging scheme not sufficient
- □ If page size is 4 KB (2¹²)
 - ☐ Then page table has 2⁵² entries
 - ☐ If two level scheme, inner page tables could be 2¹⁰ 4-byte entries
 - Address would look like

| | outer page | inner page | page offset | |
|-----|------------|------------|-------------|--|
| 100 | p_1 | ρ_2 | d | |
| | 42 | 10 | 12 | |

- Outer page table has 2⁴² entries or 2⁴⁴ bytes
- One solution is to add a 2nd outer page table
- But in the following example the 2nd outer page table is still 2³⁴ bytes in size
 - And possibly 4 memory access to get to one physical memory location



Three-level Paging Scheme

| outer page | inner page | offset |
|------------|------------|--------|
| p_1 | p_2 | d |
| 42 | 10 | 12 |

| 2nd outer page | outer page | inner page | offset | | |
|----------------|------------|------------|--------|--|--|
| p_1 | p_2 | p_3 | d | | |
| 32 | 10 | 10 | 12 | | |






Hashed Page Tables

- □ Common in address spaces > 32 bits
- ☐ The virtual page number is hashed into a page table
 - This page table contains a chain of elements hashing to the same location
- Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element
- Virtual page numbers are compared in this chain searching for a match
 - If a match is found, the corresponding physical frame is extracted
- Variation for 64-bit addresses is clustered page tables
 - Similar to hashed but each entry refers to several pages (such as 16) rather than 1
 - Especially useful for sparse address spaces (where memory references are non-contiguous and scattered)





Hashed Page Table








Inverted Page Table

- Rather than each process having a page table and keeping track of all possible logical pages, track all physical pages
- One entry for each real page of memory
- Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs





Inverted Page Table Architecture







Example: The Intel 32 and 64-bit Architectures

- Dominant industry chips
- Pentium CPUs are 32-bit and called IA-32 architecture
- Current Intel CPUs are 64-bit and called IA-64 architecture
- Many variations in the chips, cover the main ideas here





Example: The Intel IA-32 Architecture


- Supports both segmentation and segmentation with paging
 - Each segment can be 4 GB
 - Up to 16 K segments per process
 - Divided into two partitions
 - First partition of up to 8 K segments are private to process (kept in local descriptor table (LDT))
 - Second partition of up to 8K segments shared among all processes (kept in global descriptor table (GDT))





Example: The Intel IA-32 Architecture (Cont.)

- CPU generates logical address
 - Selector given to segmentation unit
 - Which produces linear addresses




- Linear address given to paging unit
 - Which generates physical address in main memory
 - Paging units form equivalent of MMU
 - Pages sizes can be 4 KB or 4 MB





Logical to Physical Address Translation in IA-32




| page r | number | page offset |
|--------|--------|-------------|
| p_1 | p_2 | d |
| 10 | 10 | 12 |






Intel IA-32 Segmentation







Intel IA-32 Paging Architecture








Intel IA-32 Page Address Extensions

- 32-bit address limits led Intel to create page address extension (PAE), allowing 32-bit apps access to more than 4GB of memory space
 - Paging went to a 3-level scheme
 - Top two bits refer to a page directory pointer table
 - Page-directory and page-table entries moved to 64-bits in size
 - Net effect is increasing address space to 36 bits 64GB of physical memory





Intel x86-64

- Current generation Intel x86 architecture
- ☐ 64 bits is ginormous (> 16 exabytes)
- ☐ In practice only implement 48 bit addressing
 - Page sizes of 4 KB, 2 MB, 1 GB
 - Four levels of paging hierarchy
- Can also use PAE so virtual addresses are 48 bits and physical addresses are 52 bits

| HDHOOG | J | page map | | page directory | page | | page | | offoot | |
|--------|------|----------|------|----------------|-----------|-------|-------|-------|--------|---|
| unused | ן ג | level 4 | | pointer table | directory | | table | | offset | |
| 63 | 48 4 | 17 | 39 3 | 38 30 | 29 | 21 20 | | 12 11 | | 0 |



End of Chapter 8

