Ad Hoc Matching Library Overview

© 2013 Sony Computer Entertainment Inc. All Rights Reserved. SCE Confidential

Table of Contents

1 Library Overview	3
Functional Overview and Features	3
Used Resources	4
Files	4
Sample Programs	4
Reference Materials	4
2 Using the Library	5
Initialization	5
Matching Process	5
Termination	7
Event Handler Function Sample	7
3 Explanation of Operation	
Group Models	11
Matching Protocol	12
Event Model	13
Optional Data	15
Data Transmission and Reception	16
4 Precautions	17
Specifying the Pool Size When Initializing the Library	
Conditions for Sending Hello Messages	
When the Number of Connected Players Reaches the Maximum	
SCE_NET_CTL_ERROR_NOT_CONNECTED	

Library Overview

Functional Overview and Features

The Ad hoc Matching library (adhoc_matching) provides services for configuring (matching) a group of participating game players in ad hoc mode. The main services provided by the library are as follows.

- Handling notifications for players waiting to join the group and discovering their peers
- Negotiation
 - Notification of join requests
 - Notification of acceptance/denial of join requests
- Group management
 - Confirming that a player exists who has agreed to participate
 - Handling notifications for players who cancel their participation agreements

A matching protocol is implemented in the library using the ad hoc mode communication protocol. An application uses these services through the library API and through event handlers that are called from the library.

API call

Event handler call

adhoc_matching

Matching protocol

network

ifhandle

Ad hoc mode communication protocol

Figure 1 Library Configuration

Used Resources

The following are the system resources consumed by the Ad hoc Matching library.

Resource	Description		
Footprint	Approximately 20 KB		
	(Total of Text, Data, RO-Data and BSS of		
	SCE_SYSMODULE_NET_ADHOC_MATCHING)		
Work memory	Only uses the memory passed from the application. Refer to the "Precautions"		
	chapter for the appropriate memory size.		
Thread	The following 3 threads are created in the application process.		
	"SceNetAdhocMatchingEvent"		
	"SceNetAdhocMatchingInput"		
	"SceNetAdhocMatchingCallout"		
Processor time	Negligible		

Files

The files required for using the Ad hoc Matching library are as follows.

Description	File	
Header file	adhoc_matching.h	
Stub library file	libSceNetAdhocMatching_stub.a	
	libSceNetAdhocMatching_stub_w	eak.a

The Ad hoc Matching library can be linked in the PRX format only. Link libSceNetAdhocMatching_stub.a or libSceNetAdhocMatching_stub_weak.a statically to use the Ad hoc Matching library. The PRX module is stored in storage managed by system software and can be loaded/unloaded using API of libsysmodule.

For details on the PRX format, refer to the "libsysmodule Overview" document.

Sample Programs

The following program is provided as an Ad hoc Matching library sample program for reference purposes.

sample_code/network/api_adhoc_matching/adhoc_matching_robot/

This is a sample using Ad hoc Matching in game form.

For sample information, refer to the readme.

Reference Materials

Concerning connection in the ad hoc communication mode, refer to the following document.

• Network Overview

2 Using the Library

Initialization

To use the Ad hoc Matching library, first initialize libnet and then initialize the Ad hoc Matching library.

(1) Loading the PRX

 $Call \ \verb|sceSysmodule| LoadModule| () \ with \verb|SCE_SYSMODULE_NET_ADHOC_MATCHING| specified \ as the module ID to load the PRX.$

(2) Initializing the library

Load NET module, and perform initialization. For details, refer to the "libnet Overview" and "libnet Reference" documents.

Then, initialize the Ad hoc Matching library by sceNetAdhocMatchingInit().

Matching Process

(1) Start Matching

To start matching, create a context and call the start function.

```
int ctx id;
// Specify the operating mode by mode and create a context
                               20000
#define MATCHING PORT
#define MATCHING RXBUFLEN
                               1024 // Approximately twice the maximum size of the
optional data that is handled
#define HELLO INTERVAL
                                 * 1000 * 1000 //msec
                               1
#define KEEPALIVE INTERVAL
                               5 * 1000 * 1000 //msec
#define INIT_COUNT
#define REXMT_INTERVAL
                               1 * 1000 * 1000 //msec
ret = sceNetAdhocMatchingCreate(
         mode,
SCE_NET_ADHOC_MATCHING_MAXNUM,
         MATCHING PORT,
MATCHING RXBUFLEN,
         HELLO_INTERVAL,
         KEEPALIVE INTERVAL,
         INIT COUNT,
         REXMT INTERVAL,
         eventHandler
         );
if (ret < 0) {
         // Error handling
ctx id = ret;
```

(2) Select/Accept a Target Participating Player

Call sceNetAdhocMatchingSelectTarget() to select and accept a target participating player associated with a Hello or Request event.

(3) Cancel/Deny Selection of Target Participating Player

Call sceNetAdhocMatchingCancelTarget() or sceNetAdhocMatchingCancelTargetWithOpt() to deny a Request event or cancel an agreement with a participating player who had previously been selected.

(4) Get Member List

During the matching operation, you can get a list of members who belong to a group of participating game players by calling the sceNetAdhocMatchingGetMembers().

(5) Stop Matching

Call the stop matching function and delete the context.

```
// Stop matching
sceNetAdhocMatchingStop(ctx_id);
// Delete context
sceNetAdhocMatchingDelete(ctx id);
```

Termination

(1) Termination Processing

Terminate the Ad hoc Matching library by calling sceNetAdhocMatchingTerm(). Delete all contexts before calling sceNetAdhocMatchingTerm().

(2) Unloading the PRX

Call sceSysmoduleUnloadModule() with SCE_SYSMODULE_NET_ADHOC_MATCHING specified as the module ID to unload the PRX.

Event Handler Function Sample

The Ad hoc Matching library reports various types of events by calling event handler functions. The following samples show the operations that should be performed by the event handlers.

(1) Start Matching

```
static char *eventtypestr[] = {
         "NONE",
         "HELLO",
         "REQUEST",
         "LEAVE",
         "DENY",
         "CANCEL",
         "ACCEPT",
         "ESTABLISHED",
         "TIMEOUT",
         "ERROR",
         "BYE",
         "DATA",
         "DATA_ACK",
         "DATA TIMEOUT"
};
static void
handler default(
         int id,
         int
             ev,
                SceNetEtherAddr *peer,
         struct
         int optlen,
          oid
         char addrStr[16];
         sceNetInetNtop(
               SCE NET AF INET,
               peer,
               addrStr,
               sizeof(addrStr)
         printf("%s from %s", eventtypestr[ev], addrStr);
         for (i = 0; i < optlen; i++) {
```

©SCEI

```
printf("%02x", *((char *)opt+i));
}
printf("\n");
}
```

(2) Multiplayer Mode (Parent) Sample

```
static void
handler parent (
         int id,
         int ev,
         struct SceNetEtherAddr *peer,
         int optlen,
         void *opt
         int ret;
         switch (ev) {
         case SCE NET ADHOC MATCHING EVENT REQUEST:
                                                           to participate
                // Ask user whether to accept request
         case SCE NET ADHOC MATCHING EVENT CANCEL:
                // Notify user that request to participate was canceled
         case SCE NET ADHOC MATCHING EVENT LEAVE:
                // Notify user that agreement with target participating player
was canceled
                break;
         case SCE NET ADHOC MATCHING EVENT ESTABLISHED:
                // Notify user that agreement with target participating player
was established
                break;
         case SCE NET ADHOC MATCHING EVENT TIMEOUT:
                // Notify user that there was no response from target participating
player
                break;
         case SCE_NET_ADHOC_MATCHING_EVENT_HELLO: case SCE_NET_ADHOC_MATCHING_EVENT_DENY: case SCE_NET_ADHOC_MATCHING_EVENT_ACCEPT:
               // These events do not occur
break;
         case SCE_NET_ADHOC_MATCHING_EVENT_ERROR:
                  Communication state error (perform error handling)
                break;
         case SCE NET ADHOC MATCHING EVENT BYE:
                   Target participating player terminated Ad hoc Matching library
                break;
```

(3) Multiplayer Mode (Child) Sample

```
static void
handler child(
        int id,
        int ev,
        struct SceNetEtherAddr *peer,
        int optlen,
        void *opt
        int ret;
        switch (ev) {
        case SCE NET ADHOC MATCHING EVENT HELLO:
              // Notify user that a target participating player exists
              break;
        case SCE NET ADHOC MATCHING EVENT LEAVE:
              // Notify user that an agreement with a target participating player
was canceled
              break;
        case SCE NET ADHOC MATCHING EVENT DENY:
              // Notify user that a request to participate was denied
              break;
        case SCE_NET_ADHOC_MATCHING_EVENT_ACCEPT:
              // Notify user that a request to participate was accepted
              break;
        case SCE_NET_ADHOC_MATCHING EVENT_ESTABLISHED:
              // Notify user that an agreement with a target participating player
was established
              break:
        case SCE NET ADHOC_MATCHING_EVENT_TIMEOUT:
              // Notify user that there was no response from a target
participating player
              break;
        case SCE_NET_ADHOC_MATCHING_EVENT_REQUEST:
        case SCE_NET_ADHOC_MATCHING_EVENT_CANCEL:
              // These events do not occur
              break;
        case SCE_NET_ADHOC_MATCHING EVENT ERROR:
              // Communication state error (perform error handling)
              break;
        case SCE NET ADHOC MATCHING EVENT BYE:
              // Target participating player terminated Ad hoc Matching library
              break;
```

(4) Peer-to-Peer Mode Sample

```
static void
handler p2p(
        int id,
        int ev,
        struct SceNetEtherAddr *peer,
        int optlen,
        void *opt
        int ret;
        switch (ev) {
        case SCE NET ADHOC MATCHING EVENT HELLO:
              // Notify user that a target participating player exists
              break;
        case SCE NET ADHOC MATCHING EVENT REQUEST:
              // Ask user whether to accept request to participate
        case SCE NET ADHOC MATCHING EVENT LEAVE:
              // Notify user that an agreement with a target participating player
was canceled
              break;
        case SCE NET ADHOC MATCHING EVENT DENY:
              // Notify user that a request
                                             to participate was denied
              break;
        case SCE_NET_ADHOC_MATCHING_EVENT_CANCEL:
              // Notify user that a request to participate was canceled
              break;
        case SCE NET ADHOC MATCHING EVENT ACCEPT:
              // Notify user that a request to participate was accepted
              break;
        case SCE_NET_ADHOC_MATCHING_EVENT_ESTABLISHED:
              // Notify user that an agreement with a target participating player
was established
              break;
        case SCE NET ADHOC MATCHING EVENT TIMEOUT:
              // Notify user that there was no response from a target
participating player
              break;
        case SCE NET ADHOC MATCHING EVENT ERROR:
               // Communication state error (perform error handling)
              break;
        case SCE NET ADHOC MATCHING EVENT BYE:
              // Target participating player terminated Ad hoc Matching library
             break;
}
```

3 Explanation of Operation


Group Models

The Ad hoc Matching library supports two models for setting up groups of participating players.

(1) Peer-to-Peer (Two-Player Competition)

A two-player model in which the participants are connected in a symmetric configuration. No parent-child relationship is required between the players. Each peer is configured such that it forms a group with one other arbitrary peer.


Figure 2 Peer-to-Peer Group Model



(2) Multiplayer

A model in which two or more participants are connected in a star configuration. This model has explicit parent-child relationships between the players. A parent peer is configured such that it forms a group with one or more child peers. Groups with two or more parent peers or groups consisting of only child peers are not permitted.

Figure 3 Multiplayer Group Model



When the library creates a context, the group model to be used for the group of participating game players is specified as the operating mode. If the multiplayer group model is specified, the choice of parent or child for the peer is also specified at the same time. The Ad hoc Matching library requires that peers that will be playing in the same group use the same group model and that the group model will be decided beforehand. In other words, a group cannot be made up of peers that use different group models.

The group model prescribes the structure of the group, but does not impose any restrictions on the communication paths used during actual game play. In other words, in the multiplayer model, each player can arbitrarily communicate with any other player or players without restriction.

Matching Protocol

The Ad hoc Matching library defines a matching protocol which is used to exchange matching information between peers.

Overview of Protocol Operation

The following is an overview of the matching protocol from initial negotiation until a group of participating game players is formed.

- (1) A peer advertises that it is waiting to join a group A peer set up in Peer-to-Peer or multiplayer (parent) mode starts sending a Hello message indicating that it is waiting to join a group. The Hello message is broadcast at regular intervals.
- (2) Another peer makes a request to join the group Another peer set up in Peer-to-Peer or multiplayer (child) mode discovers a waiting target by receiving its Hello message. If the user chooses, a JoinRequest message will be sent to the target.
- (3) The first peer replies to the join request
 The waiting peer discovers the target (the other player) by receiving its JoinRequest message. The
 user can choose to accept the target, in which case the peer sends a JoinReply message, or to deny
 the target, in which case it sends a Leave message.
- (4) The peers establish an agreement or the request is denied

 If the peer that sent the join request receives a JoinReply message it knows that its request has been accepted, and that an agreement for it to participate has been established. On the other hand, if the peer receives a Leave message, it knows that its join request was denied.
- (5) Keep the connection alive
 After an agreement to participate in the group has been established between the peers, they each confirm that their targets are alive by exchanging KeepAlive messages at regular intervals.

(6) Terminate the matching protocol

After the structure of the group has been decided, the matching protocol is terminated. A Bye message will be broadcast at this time to report the termination of the Ad hoc Matching library.

Timers and Counters

SCE CONFIDENTIAL

The matching protocol makes use of the following timers and counters.

• Hello interval timer

This timer sets the interval between successive Hello message transmissions.

• KeepAlive interval timer

This timer sets the interval between KeepAlive message transmissions.

KeepAlive counter

Once an agreement to participate in a group has been established with a target player, the KeepAlive counter is used to check that the target is still alive. Every time the KeepAlive interval timer is started, the KeepAlive counter is decremented by 1. After KeepAlive messages are successfully exchanged between the peers, the counter is reset to its initial (non-zero) value. Whenever the counter reaches 0, a timeout is reported to the application.

• Resend timer

This timer sets the resend interval for JoinRequest messages, JoinReply messages, or data transmissions.

• Resend counter

This counter is used to monitor whether the target exists when JoinRequest or JoinReply messages are sent, or when data transmission takes place. Every time the resend timer is activated, the counter decrements by 1. Upon successful confirmation that the target exists, the counter is reset to its initial (non-zero) value. When the counter reaches 0, a timeout is reported to the application.

Event Model

The Ad hoc Matching library is designed so that an application can set up a group of participating players without having to be directly aware of the details of the matching protocol described above. This is accomplished by using events to exchange information between the application and the Ad hoc Matching library.

Application -> Ad hoc Matching library

An application reports events to the Ad hoc Matching library through API calls.

• Start event

Start matching. Corresponds to a call to sceNetAdhocMatchingStart().

• Stop event

Stop matching. Corresponds to a call to sceNetAdhocMatchingStop().

Select event

Report a join request to the target player. Or, report that a previously received join request has been accepted. Corresponds to a call to sceNetAdhocMatchingSelectTarget().

Cancel event

Report a denial to a previously received join request. Alternatively, report the cancellation of a participation agreement with the target player. Corresponds to a call to

```
sceNetAdhocMatchingCancelTarget() or
sceNetAdhocMatchingCancelTargetWithOpt().
```

Ad hoc Matching library -> Application

The Ad hoc Matching library reports events to an application by calling an event handler function.

- Hello event (SCE_NET_ADHOC_MATCHING_EVENT_HELLO) Reported when a Hello message is received.
- Request event (SCE_NET_ADHOC_MATCHING_EVENT_REQUEST) Reported when a join request is received.
- Accept event (SCE_NET_ADHOC_MATCHING_EVENT_ACCEPT) Reported when a join request is accepted.
- Deny event (SCE_NET_ADHOC_MATCHING_EVENT_DENY) Reported when a join request is denied.
- Cancel event (SCE_NET_ADHOC_MATCHING_EVENT_CANCEL) Reported when a join request is canceled.
- Established event (SCE_NET_ADHOC_MATCHING_EVENT_ESTABLISHED)
 Reported when a participation agreement is established. This event will not occur between CHILD peers.
- Leave event (SCE_NET_ADHOC_MATCHING_EVENT_LEAVE)
 Reported when a participation agreement is canceled (Leave is received).
- Timeout event (SCE_NET_ADHOC_MATCHING_EVENT_TIMEOUT)
 Reported when either the Resend counter or the Keep Alive counter has decremented to 0.
- Error event (SCE_NET_ADHOC_MATCHING_EVENT_ERROR)
 Reported when some error occurred in the matching protocol.
- Bye event (SCE_NET_ADHOC_MATCHING_EVENT_BYE)
 Reported when a Bye message is received.

State Transition Diagram

SCE CONFIDENTIAL

Figure 4 shows the relationships between state transitions and events between two peers.

→ Ad Hoc Matching library Ad Hoc Matching library → Application For all states, when a Hello message received → Hello event Bye message is received → Bye event Select event Initial state → Send JoinRequest message JoinRequest message received → Request event Cancel event → Sønd Leave message Send Leave message _e∕ave message received Leave message received Deny event Cancel event Resend counter is 0 Join request → Timeout Event received Cancel event Wait for reply → Send Leave message to join request → Send Leave message Leave message received Select event → Leave event Leave message received →Send JoinReply message Leave event KeepAlive counter is 0 → Timeout event Resend counter is 0 Timeout Event JoinReply message received Accept join → Accept event &Established event **Participation** request agreement established JoinConfirm message received →Established event KeepAlive message received →Reset KeepAlive counter to initial value

Figure 4 Matching Protocol State Transition Diagram

Optional Data

The Ad hoc Matching library enables additional messages to be exchanged between peers by specifying optional data. The following messages can be extended by optional data.

(1) Hello message

The optional data specified in the argument of sceNetAdhocMatchingStart() is added to the Hello message. The optional data is reported to the target player together with the Hello event.

Optional data can be dynamically changed by using sceNetAdhocMatchingSetHelloOpt(). Also, the currently set optional data can be obtained by using sceNetAdhocMatchingGetHelloOpt().

(2) JoinRequest message

The optional data specified in the argument of sceNetAdhocMatchingSelectTarget() is added to the JoinRequest message. The optional data is reported to the target player together with the JoinRequest event.

(3) JoinReply message

SCE CONFIDENTIAL

The optional data specified in the argument of sceNetAdhocMatchingSelectTarget() is added to the JoinReply message. The optional data is reported to the target player together with the Accept event.

(4) Leave message

The optional data that was specified in the argument of sceNetAdhocMatchingCancelTargetWithOpt() is added. The optional data that was added to the Leave message is reported to the target player together with the Cancel, Deny, or Leave event.

Data Transmission and Reception

The Ad hoc Matching library can send and receive arbitrary data between peers that are in an ESTABLISHED state. Therefore, direct means of communication between CHILD peers cannot be used in this library. The transmission and reception of data provided with this library are intended to be used for exchanging auxiliary data for matching. Use the socket for communication beyond this scope.

(1) Data Transmission

sceNetAdhocMatchingSendData () is used to send data to a specific peer. The data is resent the number of times indicated by the resend counter with the interval specified by the resend timer until a confirmation response is received from the peer. The reception of a confirmation response is reported by a Data Ack event. If a confirmation response is not received, such as in the case of a timeout, then a Data Timeout event is reported.

New data cannot be sent until a Data Ack or Data Timeout event is reported. To send new data before that time, first use sceNetAdhocMatchingAbortSendData() to cancel the current data transmission.

If the peer was not in an ESTABLISHED state (a Leave event, Timeout event, or Error event was reported), no Data Ack or Data Timeout event is generated.

(2) Reception

When data is received, a Data event is reported along with the data.



4 Precautions

Specifying the Pool Size When Initializing the Library

Memory that the Ad hoc Matching library uses internally is allocated from an independent memory pool, which is allocated when the Ad hoc Matching library is initialized. The amount of memory required depends on such factors as the number of contexts that are used, number of members that are handled by each context, and the size of the optional data that is handled.

The maximum amount of memory needed per context is determined by the items listed below. Use approximately 100 bytes for the maximum optional data size if no optional data is used.

- rxbuflen size specified in sceNetAdhocMatchingCreate()
 (approximately twice the maximum size of the optional data that is handled)
- hellooplen size specified in sceNetAdhocMatchingStart()
- optlen size specified in sceNetAdhocMatchingSelectTarget()
- optlen size specified in sceNetAdhocMatchingCancelTargetWithOpt()
- Size of temporary buffer when sending a message (approximately twice the maximum size of the optional data that is handled)
- Size of temporary buffer when receiving a message (approximately twice the maximum size of the optional data that is handled)
- Size of context management area (approximately 200 bytes)
- Size of member list management area (approximately 300 bytes)

The amount of memory needed for each member that is handled by each context is as follows.

• Size of member management area (approximately 100 bytes)

Therefore, using the following values:

- Number of contexts: 1
- Maximum size of optional data that is handled: 1000 bytes
- hellooptlen: 1000 bytes
- optlen: 1000 bytes
- Number of members: 4

the total amount of memory needed would be at most approximately 9900 bytes.

However, this value assumes no memory fragmentation, so in actuality a larger pool size must be specified.

Conditions for Sending Hello Messages

Although Peer-to-Peer mode and multiplayer mode parents send Hello messages at a specified interval, transmission is automatically stopped when the number of members of a matching group who have established a participation agreement reaches the maximum number of members as specified by sceNetAdhocMatchingCreate(). When a participation agreement is canceled and the number of members becomes less than the maximum number of members, the sending of Hello messages is automatically restarted.

When the Number of Connected Players Reaches the Maximum

When a Peer-to-Peer mode player or multiplayer mode parent has already established a participation agreement with the maximum number of members allowed (the maximum capacity has been reached), then even if a new JoinRequest message is sent to this peer, no Request event will be generated. In this case, the library automatically returns a Leave message internally, and a Deny event is reported to the peer that sent the JoinRequest message.

Moreover, because the sending of Hello messages will be stopped when a Peer-to-Peer mode player or multiplayer mode parent establishes participation agreement with the maximum number of members allowed, subsequent devices that attempt to join will be unable to discover the parent device until the participation agreement is canceled and the number of members becomes less than the maximum number of members.

SCE_NET_CTL_ERROR_NOT_CONNECTED

The following function will return SCE_NET_CTL_ERROR_NOT_CONNECTED if no connection has been established to the ad hoc network. Be sure to call this function only after a connection is established.

• sceNetAdhocMatchingStart()

