


© 2011 Sony Computer Entertainment Inc. All Rights Reserved. SCE Confidential

# **Table of Contents**

Datatypes		4
<del>-</del> -		
SceSsSmfCtx		6
SceSsKeyOnParam		7
SceSsEffectParam		8
Initialization / Termination Functions		10
sceSsGetNeededMemorySize		11
Sound Functions		17
sceSsSynthesis		18
sceSsSynthesisWithMix		19
sceSsVoiceSetReserveMode		21
sceSsBindSoundData		22
sceSsUnbindSoundData		24
sceSsNoteOnByTone		25
sceSsKeyOnByTone		27
sceSsVoiceNoteOnByTone		29
sceSsVoiceKeyOnByTone		31
sceSsVoiceSetSustainHold		33
sceSsVoiceKeyoff		34
sceSsVoiceSoundOff		35
sceSsVoiceSetPitch		37
	,	
sceSsVoiceSetPanpot	l	39
sceSsVoiceSetPitchBend		40
·		
Effect Function		62

sceSsSetEffectParam	63
Service Functions	65
sceSsNote2Pitch	66
sceSsPitch2Note	67
SMF Functions	68
sceSsSMFBind	69
sceSsSMFUnbind	71
sceSsSMFPlay	72
sceSsSMFPause	
sceSsSMFResume	75
sceSsSMFStop	76
sceSsSMFAddTempo	77
sceSsSMFGetTempo	78
sceSsSMFSetPlayVelocity	79
sceSsSMFGetPlayVelocity	80
sceSsSMFSetPlaySendVelocity	81
sceSsSMFGetPlaySendVelocity	82
sceSsSMFSetPlayPanpot	
sceSsSMFGetPlayPanpot	84
sceSsSMFSetPlaySendPanpot	
sceSsSMFGetPlaySendPanpot	
sceSsSMFGetPlayStatus	
sceSsSMFSetChannelMute	
sceSsSMFResetChannelMute	
sceSsSMFSetPlayChannel	
sceSsSMFGetPlayChannel	
sceSsSMFGetKeyOnID	
Constants	93
List of Error Codes	94



# SceSsSndpCtx

## sndp environment

#### **Definition**

#### **Members**

system Used internally by libsndp.

## **Description**

This structure should be provided for each set of sound data (PHD, PBD).

## See Also

sceSsBindSoundData()

# **SceSsSmfCtx**

## smf environment

## **Definition**

#### **Members**

system Used internally by libsndp.

## **Description**

This structure should be provided for each SMF to be used.

## See Also

sceSsSMFBind()



# **SceSsKeyOnParam**

## Key on parameters

#### **Definition**

```
#include <libsndp.h>
typedef struct{
        unsigned char vel;
        unsigned char pan;
        unsigned char sendVel;
        unsigned char sendPan;
        int addPitch;
} SceSsKeyOnParam;
```

#### **Members**

vel Velocity (0 - 127) pan Panpot (0 - 64 - 127) sendVel Effect send velocity (0 - 127) sendPan Effect send panpot (0 - 64 - 127) addPitch Added pitch

## **Description**

This structure is used for setting the velocity and added pitch when starting the production of sound specified by key on and note on.

The values of the members are modified based on the tone parameter settings.

If the results when the values are modified exceed the upper or lower limit for the respective values, the result is clamped to the upper or lower limit, respectively.

For the panpot or effect send panpot, 0 corresponds to the leftmost position, 64 to the middle, and 127 to the rightmost position.

#### See Also

sceSsNoteOnByTone(), sceSsKeyOnByTone(), sceSsVoiceNoteOnByTone() sceSsVoiceKeyOnByTone(), sceSsNoteOn()



## **SceSsEffectParam**

## Effect parameters

#### **Definition**

```
#include <libsndp.h>
typedef struct{
    unsigned int setMask;
    signed int type;
    unsigned int delayTime;
    unsigned int feedBack;
    unsigned int effectVolumeLeft;
    unsigned int effectVolumeRight;
    unsigned int drySwitch;
    unsigned int wetSwitch;
}
SceSsEffectParam;
```

#### **Members**

setMask Bitwise OR of the desired parameters that are set (see below).

type Effect type

 $\begin{array}{ll} \textit{delayTime} & \textit{Delay time (0 - 127)} \\ \textit{feedBack} & \textit{Feedback (0 - 127)} \end{array}$ 

effectVolumeLeft Left channel (Lch) effect volume (0 - 4096) effectVolumeRight Right channel (Rch) effect volume (0 - 4096)

drySwitch Dry-side sound ON/OFF switch

(SCE SNDP OFF = OFF, SCE SNDP ON = ON)

wetSwitch Wet-side (sound with effect applied) sound ON/OFF switch

(SCE\_SNDP\_OFF = OFF, SCE\_SNDP\_ON = ON)

#### **Description**

To setMask, specify the bitwise OR of the following parameter types.

Value	Description
SCE_SNDP_FX_PARAM_ALL	Set all parameters
SCE_SNDP_FX_PARAM_TYPE	Set the effect type
	(set the specified value for type)
SCE_SNDP_FX_PARAM_PARAM	Set the effect parameters
	(set the specified values for delayTime and feedBack)
SCE_SNDP_FX_PARAM_EFFECTVOLUME	Set the effect volume
	(set the specified values for effectVolumeLeft and
	effectVolumeRight)
SCE_SNDP_FX_PARAM_SWITCH	Set the effect switches
	(set the specified values for drySwitch and wetSwitch)

*type* specifies the effect type. The following constants are provided.

```
SCE_SNDP_FX_TYPE_OFF
SCE_SNDP_FX_TYPE_ROOM
SCE_SNDP_FX_TYPE_STUDIOA
SCE_SNDP_FX_TYPE_STUDIOB
SCE_SNDP_FX_TYPE_STUDIOC
SCE_SNDP_FX_TYPE_HALL
SCE_SNDP_FX_TYPE_SPACE
SCE_SNDP_FX_TYPE_SPACE
```

SCE\_SNDP\_FX\_TYPE\_DELAY SCE\_SNDP\_FX\_TYPE\_PIPE

delayTime specifies the delay time.

feedBack specifies the amount of feedback.

effectVolumeLeft and effectVolumeRight specify the left and right effect volumes.
drySwitch specifies the dry-side switch, and wetSwitch specifies the wet-side switch.
For details about effect settings, refer to the "SAS Overview" and "SAS Reference" documents.





# sceSsGetNeededMemorySize

Get memory size (in bytes) required for initialization

### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler.

Can be called from a thread (does not depend on interrupt-disabled or -enabled state).

Not multithread safe.

## **Arguments**

```
config For future expansion (currently specify an empty string ".)
outSize Pointer to variable for storing memory size required for initialization
```

#### **Return Values**

When the function completes normally, then SCE OK is returned.

When an error occurs, a negative value (< 0) is returned.

(For details, see the List of Error Codes.)

## **Description**

This function obtains the memory size required for libsndp initialization.

This function internally calls sceSasGetNeededMemorySize() of SAS.

Be sure to allocate the size obtained with this function for the memory size required for libsndp initialization.

## **Examples**

```
#include <libsndp.h>
int main(void)
{
    SceSize bufferSize;
    void *buffer;
    SceInt32 result;

    result = sceSsGetNeededMemorySize("", &bufferSize);
    buffer = malloc(bufferSize);
    result = sceSsInit(32, "", buffer, bufferSize);
    return 0;
}
```

## sceSsInit

## Initialization processing

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

#### **Arguments**

maxVoice	Number of voices to be used (1-32)
config	For future expansion (currently specify pointer to an empty string)
buffer	Pointer to Initialization buffer
bufferSize	Initialization buffer size

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

#### **Description**

This function initializes libshdp's voice management system, the SMF sequencer, and SAS.

To use libsndp, this function or sceSsInitWithGrain() must be called first.

Since this function performs SAS initialization, when you use libsndp, do not try to initialize SAS by calling the SAS initialization function.

Calling this function sets the time for one unit of granularity to 256 samples.

Be sure to allocate the size obtained with sceSsGetNeededMemorySize() for the memory size required for libshdp initialization.

## **Example**

```
#include <libsndp.h>
int main(void)
{
    unsigned int useVoice = 32; /* Number of voices to use */
    void* buffer;
    SceSize bufferSize;
    void *buffer;
    int result;

    result = sceSsGetNeededMemorySize("", &bufferSize);
    buffer = malloc(bufferSize);
    result = sceSsInit(useVoice, "", buffer, bufferSize);
    return 0;
}
```

## sceSsInitWithGrain

Initialization processing (with granularity specification)

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

maxVoice	Number of voices to use (1 - 32)
config	For future expansion (currently specify NULL)
grain	Granularity (valid range is 64 to 2048 in multiples of 32; i.e., 64, 96, 128,, 2016, 2048)
buffer	Pointer to Initialization buffer
bufferSize	Initialization buffer size

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it means that an error occurred.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

#### Description

This function initializes the voice management system within libsndp, the SMF sequencer, and SAS.

To use libsndp, this function or sceSsInit() must be called first.

Since this function also performs SAS initialization, do not use a SAS function to initialize SAS if you are also using libshdp.

As the value of *grain* decreases, sound production changes can be expressed in a shorter granularity time, but the CPU processing load will increase.

## **Example**

## sceSsExit

## Termination processing

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

outBuffer	Pointer to variable for storing pointer to memory specified by initialization
	Specify NULL when not used.
outBufferSize	Pointer to variable for storing memory size specified by initialization
	Specify NULL when not used.

#### **Return Value**

When the function completes normally, SCE\_OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)


#### Description

This function performs libsndp termination processing and SAS termination processing.

Always execute this function when exiting an application that has been using libsndp.

Since this function performs SAS termination processing, do not execute the SAS termination function.

#### Example



## sceSsSynthesis

## libsndp periodic processing

#### **Definition**

## **Calling Conditions**

Cannot be called from an interrupt handler

Can be called from a thread (must be called in an interrupt-enabled state)

Multithread safe for key on, key off, note on, and note off functions

## **Arguments**

pout Pointer to waveform output buffer

#### **Return Value**

When the function completes normally, SCE\_OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

### **Description**

Calling this function causes SMF sequence processing and voice processing to be performed for one unit of granularity. Note that this function also calls <code>sceSasCore()</code> internally. After processing is completed, the voice states are updated to prepare for voice processing until the next time this function is called.

Since sceSasCore() is called internally by this function, do not call sceSasCoreWithMix() or sceSasCore().

Operations that cause a change in voice state (such as note on, note off, key on, and key off) can be performed by another thread while this function is executing.

#### Example

```
#include libsndp.h>
int main(void)
{
    int result;
    short *pOut;

    result = sceSsSynthesis(pOut);
    return 0;
}
```

# sceSsSynthesisWithMix

libsndp periodic processing (with external PCM mixing function)

#### **Definition**

## **Calling Conditions**

Cannot be called from an interrupt handler

Can be called from a thread (must be called in an interrupt-enabled state)

Multithread safe for key on, key off, note on, and note off functions

## **Arguments**

pInOut	Pointer to waveform output buffer
lVol	Volume value for left channel of external PCM input
rVol	Volume value for right channel of external PCM input

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it means that an error occurred.

(For details, see the List of Error Codes.)

#### Description

Calling this function causes SMF sequence processing and voice processing for one unit of granularity to be performed. This function also calls <code>sceSasCoreWithMix()</code> internally. Consequently, PCM data in a specified area is mixed to produce the resultant output. Then, the voice states are updated to prepare for voice processing until the next time this function is called.

pInOut must have 64-byte alignment.

During mixing, the volume of the input PCM can be changed. The following shows the valid range for the volume.

```
0 \le 1 Vol, rvol \le SCE SNDP VOLUME MAX
```

Since sceSasCoreWithMix() is called internally by this function, be sure not to use sceSasCore() or sceSasCoreWithMix().

Operations that cause a change in voice state (such as note on, note off, key on, and key off) can be performed by another thread while this function is executing.

#### Example

```
#include #include int main(void)
{
    int result;
    short *pInOut;
    SceInt32 lvol = SCE_SNDP_VOLUME_MAX;
    SceInt32 rvol = SCE_SNDP_VOLUME_MAX;

    /*
        After lvol and rvol processing are performed for the sound in the
        pInOut buffer (such as background music), the sound is mixed with
        the sound generated by SAS.
    */
    result = sceSsSynthesisWithMix(pInOut,lVol,rVol);
    return 0;
}
```

# sceSsVoiceSetReserveMode

Set a voice to be managed by libsndp

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
voiceNumVoice number for which the management status is to be setreserveModeStatus to be setSCE_SNDP_ONPlace voice under libsndp managementSCE_SNDP_OFFRemove voice from libsndp management
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function turns ON/OFF the management state of libsndp for voices reserved by sceSsInit().

It returns an error if a voice is specified that has not been reserved by sceSsInit().

The default voice management status is SCE SNDP ON.

libsndp will not use voices that were removed from management.

A voice that was removed from libsndp management can be used by libsas.

To set the management status of a voice, execute this function after stopping sound production for that voice.

### Example

```
#include <libsndp.h>
int main(void)
{
    int result;

    /* Remove voice 0 from libsndp management */
    result = sceSsVoiceSetReserveMode(0, SCE_SNDP_OFF);
    return 0;
}
```

# sceSsBindSoundData

## Register sound data

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

#### **Arguments**

sndpCtx Pointer to libsndp environment structure

phd Pointer to PHD datapbd Pointer to PBD data

pbfs Output sampling frequency (44100 or 48000)

#### **Return Value**

The allocated phd ID is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function registers one set of sound data (phd, pbd) in libsndp.

Be sure to prepare an sndp environment structure for each set of sound data.

Sound data is accessed using the phd ID returned by this function.

Specify the output sampling frequency of libsndp in the pbfs argument. Specify 44100 or 48000.

Up to 128 sets of sound data can be registered.

#### Example

```
#include <libsndp.h>
int main(void)
{
    int phdID;
    SceSsSndpCtx sndpCtx;
    unsigned char *phd, *pbd;

    phdID = sceSsBindSoundData(&sndpCtx, phd, pbd, 48000);
    return 0;
}
```

#### **Notes**

The *sndpCtx* structure in the argument does not need to be initialized. Be sure to allocate memory and pass it as a work area.

For details about sound data (phd, pbd), refer to the document entitled, "PHD/PBD Formats." If 48000 is specified in argument <code>pbfs</code> and PSP<sup>TM</sup> (PlayStation®Portable) data (created for playback at 44.1 KHz) is specified for <code>phd</code> and <code>pbd</code>, a pitch conversion that differs from that of the PSP<sup>TM</sup> environment may occur, creating a difference in sound quality.

#### See Also

SceSsSndpCtx

## sceSsUnbindSoundData

## Cancel registered sound data

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

## **Arguments**

phdID phd ID for which registered sound data is to be canceled

#### **Return Value**

When the function completes normally,  $SCE_OK$  is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

### **Description**

This function cancels sound data (phd, pbd) that has been registered.

After the sound data corresponding to the phd ID is canceled by this function, that sound data can no longer be used.

#### Example

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsUnbindSoundData(0);
    return 0;
}
```

#### See Also

sceSsBindSoundData()

## sceSsNoteOnByTone

## Note on by tone

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

phdID phd ID that contains tone for which note on is to be performed

toneIndex Tone index for which note on is to be performed

note Note number (0 - 127)

keyOnID Key on ID

keyOnParam Pointer to SceSsKeyOnParam structure

#### **Return Value**

The voice number for which note on was performed is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### Description

This function produces sound using the pitch specified by <code>note</code> and based on the tone parameters within the <code>phd</code> indicated by <code>toneIndex</code> (index of structure <code>toneParamCtx</code> of tone attribute data). Although the voice to be used is allocated automatically, sound may not actually be produced, depending on the priority that was set in the tone parameters. (Please refer to the "PHD/PBD Formats" document for details on the format of tone data.)

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

The actual note for which sound is produced is determined from the note number that is set in the argument and the center note in the tone parameter. For example, if note on is performed for the same note as the center note in the tone parameter, the pitch of the fundamental tone is used to generate sound for its waveform.

(The center detune and detune values are also taken into consideration for the actual pitch.)

Actual sound generation starts after <code>sceSsSynthesis()</code> is called. However, if sound generation is stopped or another sound is generated for the allocated voice before <code>sceSsSynthesis()</code> is called, no sound is actually generated.

The volume and added pitch are set in the SceSsKeyOnParam structure.

The key on ID is an identifier used for generating sound.

Note that since the key on IDs 0x80000000 to 0xFFFFFFFF are reserved by libsndp, they should not be used.

## **Example**

```
#include sndp.h>
int main(void)
{
    int voiceNum;
    SceSsKeyOnParam keyOnParam;

    keyOnParam.vel = 127;
    keyOnParam.pan = 64;
    keyOnParam.sendVel = 127;
    keyOnParam.sendPan = 64;
    keyOnParam.addPitch = 0;

    /* Generate sound for phdID = 0, tone index = 0, note = 64, and */
    /* key on Id = 0 */
    voiceNum = sceSsNoteOnByTone(0, 0, 64, 0, &keyOnParam);
    return 0;
}
```

#### See Also

SceSsKeyOnParam

## sceSsKeyOnByTone

## Key on by tone

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

phdID phd ID that includes the tone for which key on is to be performed

toneIndex Tone index for which key on is to be performed

pitch Pitch (0x0001 - 0x4000)

keyOnID Key on ID

keyOnParam Pointer to SceSsKeyOnParam structure

#### **Return Value**

The voice number for which note on was performed is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### Description

This function produces sound using the pitch specified by pitch and based on the tone parameters within the phd indicated by toneIndex. Although the voice to be used is allocated automatically, sound may not actually be produced, depending on the priority that was set in the tone parameters.

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

The actual note for which sound is produced is determined from the note number that is set in the argument and the center note in the tone parameter. For example, if note on is performed for the same note as the center note in the tone parameter, the pitch of the fundamental tone is used to generate sound for its waveform.

(The center detune and detune values are also taken into consideration for the actual pitch.)

Actual sound generation starts after sceSsSynthesis() is called. However, if sound generation is stopped or another sound is generated for the allocated voice before sceSsSynthesis() is called, no sound is actually generated.

The volume and added pitch are set in the SceSsKeyOnParam structure.

The key on ID is an identifier used for generating sound.

Note that since the key on IDs 0x80000000 to 0xFFFFFFFF are reserved by libsndp, they should not be used.

## **Example**

```
#include <libsndp.h>
int main(void)
        int voiceNum;
        SceSsKeyOnParam keyOnParam;
        keyOnParam.vel = 127;
        keyOnParam.pan = 64;
        keyOnParam.sendVel = 127;
        keyOnParam.sendPan = 64;
        keyOnParam.addPitch = 0;
                                                          pitch = 0x1000, */
        /* Generate sound for phdID = 0, tone index
        /* and key on Id = 0 */
        voiceNum = sceSsKeyOnByTone(0, 0, 0x1000,
                                                   0, &keyOnParam);
        return 0;
}
```

#### See Also

SceSsKeyOnParam

## sceSsVoiceNoteOnByTone

Note on by tone (specifying voice)

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

phdID phd ID that includes the tone for which note on is to be performed

voiceNum Voice number for which note on is to be performed

toneIndex Tone index for which note on is to be performed

Note number (0 - 127)

keyOnID KeyOnParam Pointer to SceSsKeyOnParam structure

## **Return Value**

The voice number for which note on was performed is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function produces sound using the pitch specified by *note* and based on the tone parameters within the *phd* indicated by *toneIndex*. Sound is forcibly produced by the specified voice.

The actual note for which sound is produced is determined from the note number that is set in the argument and the center note in the tone parameter. For example, if note on is performed for the same note as the center note in the tone parameter, the pitch of the fundamental tone is used to generate sound for its waveform.

(The center detune and detune values are also taken into consideration for the actual pitch.)

Actual sound generation starts after sceSsSynthesis() is called. However, if sound generation is stopped or another sound is generated for the voice that is set before sceSsSynthesis() is called, no sound is actually generated.

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

The volume and added pitch are set in the SceSsKeyOnParam structure.

Voices that can be specified in the *voiceNum* argument can only be voices that were previously registered using sceSsInit().

The key on ID is an identifier used for generating sound .

Note that since the key on IDs 0x80000000 to 0xFFFFFFFF are reserved by libsndp, they should not be used.

### **Example**

```
#include libsndp.h>

int main(void)
{
    int voiceNum;
    SceSsKeyOnParam keyOnParam;

    keyOnParam.vel = 127;
    keyOnParam.pan = 64;
    keyOnParam.sendVel = 127;
    keyOnParam.sendPan = 64;
    keyOnParam.addPitch = 0;

/* Generate sound for phdID = 0, tone index = 0, note = 64, */
    /* and key on Id = 0 */
    voiceNum = sceSsVoiceNoteOnByTone(0, 0, 0, 64, 0, &keyOnParam);
    return 0;
}
```

## See Also

SceSsKeyOnParam

# sceSsVoiceKeyOnByTone

Key on by tone (voice specification)

#### **Definition**

```
#include <libsndp.h>
SceInt32 sceSsVoiceKeyOnByTone(
        SceUInt32 phdID,
        SceUInt32 voiceNum,
        SceUInt32 toneIndex,
        SceUInt32 pitch,
        SceUInt32 keyOnID,
        SceSsKeyOnParam *keyOnParam
);
```

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

### Arguments

phd ID that includes the tone for which key on is to be performed phdID voiceNum Voice number for which key on is to be performed toneIndex Tone index for which key on is to be performed Pitch (0x0001 - 0x4000) pitch *keyOnID* Key on ID

keyOnParam Pointer to SceSsKeyOnParam structure

#### **Return Value**

The voice number for which key on was performed is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## Description

This function produces sound using the pitch specified by pitch and based on the tone parameters within the phd indicated by tone Index. Sound is forcibly produced by the specified voice.

The actual note for which sound is produced is determined from the note number that is set in the argument and the center note in the tone parameter. For example, if note on is performed for the same note as the center note in the tone parameter, the pitch of the fundamental tone is used to generate sound for its waveform.

(The center detune and detune values are also taken into consideration for the actual pitch.)

Actual sound generation starts after scesssynthesis () is called. However, if sound generation is stopped or another sound is generated for the voice that is set before sceSsSynthesis() is called, no sound is actually generated.

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

The volume and added pitch are set in the SceSsKeyOnParam structure.

The key on ID is an identifier used for generating sound.

Note that since the key on IDs 0x80000000 to 0xFFFFFFFF are reserved by libshdp, they should not be used

## **Example**

```
#include libsndp.h>
int main(void)
{
    int voiceNum;
    SceSsKeyOnParam keyOnParam;

    keyOnParam.vel = 127;
    keyOnParam.pan = 64;
    keyOnParam.sendVel = 127;
    keyOnParam.sendPan = 64;
    keyOnParam.addPitch = 0;

    /* Generate sound for phdID = 0, tone index = 0, pitch = 0x1000, */
    /* and key on Id = 0 */
    voiceNum = sceSsVoiceKeyOnByTone(0, 0, 0, 0x1000, 0, &keyOnParam);
    return 0;
}
```

#### See Also

SceSsKeyOnParam

## sceSsVoiceSetSustainHold

Set sustain hold state for a voice

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
voiceNumVoice number for which sustain hold state is to be setsustainHoldSustain hold state to be setSCE_SNDP_OFFSustain hold offSCE_SNDP_ONSustain hold on
```

#### **Return Value**

When the function completes normally, SCE\_OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

### **Description**

This function sets the sustain state for a voice. If an operation is performed to stop sound generation for a voice that has sustain hold on, and if the sound being generated is a loop waveform, sound generation will not be stopped and the voice will transition to sustain state. To stop sound generation for a voice in sustain state, sustain hold must be switched off.

Also, when the corresponding voice is paused, SCE\_SNDP\_ERROR\_PAUSEVOICE is returned.

#### Example

```
#include <libsndp.h>
int main(void)
{
    int result;

    result = sceSsVoiceSetSustainHold(0, SCE_SNDP_ON);
    return 0;
}
```

# sceSsVoiceKeyoff

## Voice key off

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

voiceNum Voice for which key off is to be performed

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

## **Description**

This function performs key off for the specified voice. The voice will transition to sustain state when sustain hold is on. The actual key off is performed when sustain hold is turned off.

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

## **Example**

```
#include <libsndp.h>
int main(void)
{
    int result;
    /* Perform key off for voice 0 */
    result = sceSsVoiceKeyoff(0);
    return 0;
}
```

## sceSsVoiceSoundOff

#### Voice sound off

#### **Definition**

#### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

voiceNum Voice for which sound off is to be performed

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

## Description

This function quickly ends sound production for the specified voice. It turns sustain hold off, performs key off, and sets the shortest possible ADSR release time. It is useful when you want to quickly end sound production for a voice while calling scessSynthesis() successively. Also, when the corresponding voice is paused, SCE\_SNDP\_ERROR\_PAUSEVOICE is returned.

## **Example**

```
This example performs sound off for the voice of the specified MIDI channel.
#include <libsndp.h>

/*
   Arguments
   midich: MIDI channel
   id: Key-on ID
   */
int main(int midich, int id)
{
   int result;
   int vnum;
   unsigned int vbit;

   /* Get bit pattern of voice which is generating sound for the specified
        MIDI channel */
   vbit = sceSsGetVoice(midich, id);

   for(vnum=0; (vnum<SCE SAS VOICE MAX) || (vbit!=0); vnum++) {</pre>
```



## sceSsVoiceSetPitch

Add pitch to a voice producing sound

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
voiceNum Target voice number
addPitch Added pitch to be set
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function adds the pitch to the specified voice. If a negative value was set for the added pitch, the pitch is reduced. A negative number can also be specified for addPitch.

If the added pitch falls below 0x1 or exceeds 0x4000, it is clamped to 0x1 or 0x4000, respectively.

```
#include <libsndp.h>
int main(void)
{
    int result;
    /* Add pitch 0x200 to voice 0 */
    result = sceSsVoiceSetPitch(0, 0x200);
    return 0;
}
```

# sceSsVoiceSetVelocity

## Set voice velocity

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
voiceNum Target voice number
velocity Velocity to be set (0 - 127)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function sets the velocity of a voice. The velocity is a value that is relative to the volume that was set in the tone parameters in the PHD.

```
#include <libsndp.h>
int main(void)
{
    int result;
    /* Set velocity 127 for voice 0 */
    result = sceSsVoiceSetVelocity(0, 127);
    return 0;
}
```

# sceSsVoiceSetPanpot

## Set voice panpot

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
voiceNum Target voice number
panpot Panpot to be set (0 - 64 - 127)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function sets the panpot of a voice. The value 0 corresponds to the leftmost position, 127 to the rightmost position, and 64 to the middle.

This value is added to the actual panpot that was set for the tone parameters in the PHD. If the result falls below 0 or exceeds 127, it is clamped to 0 or 127, respectively.

```
#include <libsndp.h>
int main(void)
{
    int result;
        /* Set panpot 127 for voice 0 */
    result = sceSsVoiceSetPanpot(0, 127);
    return 0;
}
```

## sceSsVoiceSetPitchBend

## Set pitch bend of voice

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

voiceNum
bendValue

Voice number for which pitch bend is to be set

Value Pitch bend value to be set

0 to 8191 (Bend Down)

8192 (Center)

8193 to 16383 (Bend Up)

#### **Return Value**

If processing completes normally,  $SCE_OK$  is returned. If an error occurs, the return value is negative (< 0).

(For details, see the List of Error Codes.)

#### **Description**

This function sets the pitch bend of a voice.

The pitch varies within the range that was set by the bend range of the tone parameter in the PHD. bendValue is a range that matches the MIDI pitch bend value.

bendValue and pitch vary linearly relative to the musical scale (cents).

The pitch bend effect is effective only for a voice for which sound is being produced according to a specified note (sceSsNoteOnByTone(), sceSsVoiceNoteOnByTone(), or sceSsNoteOn()).

Since the bend range width is ambiguous for a voice for which sound is produced by directly specifying the pitch, the pitch bend effect is not effective in those cases (it is not effective for sceSsKeyOnByTone() or sceSsVoiceKeyOnByTone()).

```
#include <libsndp.h>
int main(void)
          int result;
          /\!\!^{\star} Set a maximum pitch bend of 16383 for voice 0 ^{\star}/\!\!^{\star}
          result = sceSsVoiceSetPitchBend(0, 16383);
          return 0;
}
```

# sceSsVoiceSetSendVelocity

Set effect send velocity of a voice

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

#### **Arguments**

```
voiceNum Voice number that is set sendVelocity Effect send velocity that is set (0 - 127)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function sets the velocity of a voice. The velocity is a value that is relative to the volume that was set in the tone parameters in the PHD.

```
#include <libsndp.h>
int main(void)
{
    int result;

    /* Set effect send velocity 127 for voice 0 */
    result = sceSsVoiceSetSendVelocity(0, 127);
    return 0;
}
```

# sceSsVoiceSetSendPanpot

Set effect send panpot of a voice

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
voiceNum Target voice number sendPanpot Effect send panpot to be set (0 - 64 - 127)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function sets the effect send panpot of a voice. The value 0 corresponds to the leftmost position, 127 to the rightmost position, and 64 to the middle.

This value is added to the actual effect send panpot that was set for the tone parameters in the PHD. If the result falls below 0 or exceeds 127, it is clamped to 0 or 127, respectively.

```
#include <libsndp.h>
int main(void)
{
    int result;

    /* Set effect send panpot 127 for voice 0 */
    result = sceSsVoiceSetSendPanpot(0, 127);
    return 0;
}
```

# sceSsVoiceAllKeyOff

## All key off

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

None

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

If voices are included that have errors, the error code of the last voice that caused an error is returned. (For details, see the List of Error Codes.)

#### **Description**

This function keys off all voices that are being managed by libsndp (performs key off and puts ADSR in release state).

Sound production is stopped after turning sustain hold state off for any voice for which sustain hold has been set.

Also, when the corresponding voice is paused, SCE SNDP ERROR PAUSEVOICE is returned.

```
#include <libsndp.h>
int main(void)
{
    int result;
    /* Stop sound production of all voices */
    result = sceSsVoiceAllKeyOff();
    return 0;
}
```

# sceSsVoiceAllSoundOff

#### All sound off

#### **Definition**

#### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

#### **Arguments**

None

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

If voices are included that have errors, the error code of the last voice that caused an error is returned. (For details, see the List of Error Codes.)

#### Description

This function quickly ends sound production for all voices under libsndp management. It turns sustain hold off, performs key off and sets the shortest possible ADSR release time. It is useful when you want to quickly end sound production for all voices while calling scesssynthesis() successively.

When scessVoiceAllKeyOff() is used, the ADSR release time of the voices which were keyed off is long and it will take time before the voices stop producing sound. By comparison, the voices will take less time to finish when scessVoiceAllSoundOff() is used. However, note that reverberation will not stop. Also, when any one of the voices is paused, SCE\_SNDP\_ERROR\_PAUSEVOICE is returned.

```
#include #include int main(void)
{
    int result;

    /* Stop sound production for all voices */
    result = sceSsVoiceAllSoundOff();
    return 0;
}
```

## sceSsVoiceSetPause

## Pause voice playback

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

voiceNum Voice number to be paused or for which pause is to be canceled (0 to 31)
mode Pause state (1: Set pause; 0: Cancel pause)

#### **Return Value**

If the function completes normally, SCE OK is returned.

When an error occurs, a negative value (< 0) is returned.

(For details, see the List of Error Codes.)

#### **Description**

This function sets or cancels pause state for the voice having the specified number.

If sceSsVoiceGetStatus () is executed for the voice during a pause, the value in effect immediately before the pause is returned.

If a reserved pause is specified, an error (SCE SNDP ERROR RESERVEDVOICE) is returned.

If a note on or note off is performed for a paused voice, it will be ignored by the voice. An error (SCE SNDP ERROR PAUSEVOICE) may be returned, depending on the function.

# sceSsVoiceGetEndFlag

Get sound production end flag for a voice

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

#### **Arguments**

voiceNum Voice number for which end flag is to be obtained

#### **Return Value**

The sound production end flag status is returned.

- 0: The end of sound production has not been reached
- 1: The end of sound production has been reached

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function gets the sound production end flag for a voice.

If envelope processing has ended and sound production has ended, the end flag is 1. If sound is being produced, the end flag is 0. All end flags will be set to 1 immediately after initialization (sceSsInit()).

```
#include sndp.h>
int main(void)
{
    int result;

    /* Get the sound production end flag status of voice 0 */
    result = sceSsVoiceGetEndFlag(0);

    return 0;
}
```

# sceSsVoiceGetEnvelope

Get envelope value of a voice

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

## **Arguments**

voiceNum Voice number for which envelope value is to be obtained

#### **Return Value**

Envelope value

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

#### **Description**

Returns the envelope peak value of the specified voice.

```
#include <libsndp.h>
int main(void)
{
    int result;
    /* Get envelope value of voice 0 */
    result = sceSsVoiceGetEnvelope(0);
    return 0;
}
```

## sceSsVoiceGetStatus

#### Get voice state

#### **Definition**

#### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state) Multithread safe

#### **Arguments**

voiceNum Voice number for which voice state is to be obtained

#### **Return Value**

The state of the specified voice is returned.

```
SCE_SNDP_VOICESTATUS_RESERVED
SCE_SNDP_VOICESTATUS_IDLE
SCE_SNDP_VOICESTATUS_BUSY
SCE_SNDP_VOICESTATUS_RELEASE
SCE_SNDP_VOICESTATUS_SUSTAIN
```

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

## **Description**

This function gets the state of a voice.

SCE\_SNDP\_VOICESTATUS\_RESERVED corresponds to a voice that was removed from libsndp management.

(To remove a voice from libsndp management, use sceSsVoiceSetReserveMode().)


SCE\_SNDP\_VOICESTATUS\_IDLE corresponds to a voice that is first used as a result of a note on event that immediately follows libsndp initialization, or a voice that has finished vocalization.

SCE\_SNDP\_VOICESTATUS\_RELEASE corresponds to a voice when ADSR is being released by a vocalization stop (note off) event, or a voice when ADSR is released by the next sceSsSynthesis() call.

SCE\_SNDP\_VOICESTATUS\_SUSTAIN corresponds to a voice for which the vocalization stop (note off) event occurred but hold is being sustained by the sceSsVoiceSetSustainHold() function.

SCE\_SNDP\_VOICESTATUS\_BUSY corresponds to a voice that is vocalized by the next sceSsSynthesis() call or a voice for which vocalization is being sustained by a vocalization start (note on) event.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsVoiceGetStatus(0);
    return 0;
}
```



## sceSsVoiceGetLevel

## Get voice level setting

## **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

## **Arguments**

voiceNum	Voice number for which level is to be obtaine
lVol	Pointer for returning the left volume value
rVol	Pointer for returning the right volume value

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it means that an error occurred.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

#### **Description**

This function gets the volume of a voice.

Specifically, it gets the setting of the sceSasSetVolume () function that is called internally by libsndp. The range of volume values is as follows.

```
-SCE_SNDP_VOLUME_MAX <= 1Vol, rVol <= SCE_SNDP_VOLUME_MAX
```

A negative value inverts the phase.

```
#include <libsndp.h>
int main(void)
         int result;
         int nvoice;
         int VolumeL, VolumeR;
         /* Get the voice envelope value */ nvoice = 0; /* Voice 0 */  
         result = sceSsVoiceGetLevel(nvoice, &VolumeL, &VolumeR);
         return 0;
}
```

## sceSsVoiceGetSendLevel

Get effect send level setting of voice

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

### **Arguments**

voiceNum	Voice number for which level is to be obtained
1 <i>Vo1</i>	Pointer for returning the left effect send volume value
rVol	Pointer for returning the right effect send volume value

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it means that an error occurred.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

#### **Description**

This function gets the effect send volume of a voice.

Specifically it gets the setting of the  ${\tt sceSasSetVolume}$  () function that is called internally by libsndp.

The range of volume values is as follows.

```
-SCE_SNDP_VOLUME_MAX <= Vol, rVol <= SCE_SNDP_VOLUME_MAX
```

A negative value inverts the phase.

### **Example**

```
#include #include h>

int main(void)
{
    int result;
    int nvoice;
    int VolumeL, VolumeR;

    /* Get the voice envelope value */
    nvoice = 0; /* Voice 0 */
    result = sceSsVoiceGetSendLevel(nvoice, &VolumeL, &VolumeR);
    return 0;
}
```

**©SCEI** 

# sceSsKeyOffByID

Key off a voice producing sound by its key on ID

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

#### **Arguments**

keyOnID Key on ID for which key off is to be performed

#### **Return Value**

The bit pattern of the voice for which key off was performed is returned.

If the return value is zero, it means key off was not performed for any voice.

The relationship between the bit No. and voice No. is shown below.

voice31	voice30		voice1	voice0
bit31	bit30	·	bit1	bit0

#### **Description**

This function performs key off for a voice that is producing sound corresponding to key on ID.

However, a voice for which the sustain hold state was set to on switches to sustain state, and key off is performed when the sustain hold state is turned off.

Also, when the corresponding voices include a paused voice, the operation for the paused voice is ignored.

```
#include <libsndp.h>
int main(void)
{
    unsigned int result;

    /* Stop sound production of voice with key on ID = 0 */
    result = sceSsKeyOffByID(0);

    return 0;
}
```

## sceSsGetVoice

Get sound-producing voice using MIDI channel and key on ID

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

#### **Arguments**

```
midiChannel MIDI channel for which voice is to be obtained (0 to 15 = MIDI channels 1 to 16)

keyOnID Key on ID for which voice is to be obtained
```

#### **Return Value**

The bit pattern of the voice that was obtained is returned.

If the return value is zero, it means that no voice was obtained.

The relationship between the bit No. and voice No. is shown below.

voice31	voice30	voice1	voice0
bit31	bit30	 bit1	bit0

#### **Description**

This function gets the voice producing sound from its MIDI channel and key on ID.

```
#include <libsndp.h>
int main(void)
{
    unsigned int result;

    /* Get voice with key on MIDI channel = 1 and key on ID = 0 */
    result = sceSsGetVoice(0, 0);

    return 0;
}
```

## sceSsGetPause

Get pause states of voices

#### **Definition**

```
#include <libsndp.h>
SceUInt32 sceSsGetPause(
        void
);
```

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state) Multithread safe

## **Arguments**

None

#### **Return Value**

A bit pattern indicating the pause states of the voices that were obtained is returned. A 1 indicates that the voice is paused, and a 0 indicates that the pause was canceled. The relationship between the bit No. and voice No. is as follows.

voice31	voice30	voice1	voice0
bit31	bit30	 bit1	bit0

### **Description**

This function gets the pause state of each voice.



## sceSsNoteOn

#### Note on

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

phdID	phd ID that contains the program for which note on is to be performed		
midiChannel			
	(0 to 15 = MIDI channels 1 to 16)		
midiProgram	MIDI program number for which note on is to be performed (0 - 127)		
midiNote	Note number for which note on is to be performed (0 - 127)		
sustain	Sustain hold state when note on is performed		
	SCE_SNDP_ON Sustain hold on		
	SCE_SNDP_OFF Sustain hold off		
keyOnParam	Pointer to SceSsKeyOnParam structure		
keyOnID	Key on ID		

### **Return Value**

The bit pattern of the voice for which note on was performed is returned.

If the return value is zero, it means that sound was not produced for any voice.

The relationship between the bit No. and voice No. is shown below.

voice31	voice30		voice1	voice0
bit31	bit30	•••	bit1	bit0

### **Description**

This function performs note on for <code>midiChannel</code> using the tone parameters corresponding to the MIDI program number and note number. If there are multiple corresponding MIDI program numbers and note numbers, sound is produced for all the matching entries.

If no relevant program exists or if the note is outside of the tone parameter range, sound is not produced. Also, when the corresponding voices include a paused voice, the operation for the paused voice is ignored.

The actual note for which sound is produced is determined from the note number that is set in the argument and the center note in the tone parameter. For example, if note on is performed for the same note as the center note in the tone parameter, the pitch of the fundamental tone is used to generate sound for its waveform.

(The center detune and detune values are also taken into consideration for the actual pitch.)

Actual sound generation starts after scessynthesis() is called. However, if sound generation is stopped or another sound is generated for the voice that generated sound before scessynthesis() is called, no sound is actually generated.

The volume and added pitch are set in the SceSsKeyOnParam structure.

The key on ID is an identifier used for generating sound.

Note that since the key on IDs 0x80000000 to 0xFFFFFFFF are reserved by libsndp, they should not be used.

#### Example

```
#include #include libsndp.h>
int main(void)
{
         unsigned int result;
         SceSsKeyOnParam keyOnParam;
         keyOnParam.vel = 127;
         keyOnParam.pan = 64;
         keyOnParam.sendVel = 127;
         keyOnParam.sendPan = 64;
         keyOnParam.addPitch = 0;

         /* Generate sound using phdID = 0, MIDI channel = 1, */
         /* program number = 0, note = 64, sustain state = off, and key on Id
= 0 */
         result= sceSsNoteOn(0, 0, 0, 64, SCE_SNDP_OFF, &keyOnParam, 0);
         return 0;
}
```

#### See Also

SceSsKeyOnParam

## sceSsNoteOff

#### Note off

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

## **Arguments**

```
midiChannel MIDI channel for which note off is to be performed (0 to 15 = MIDI channels 1 to 16)

midiNote
keyOnID

Note number for which note off is to be performed (0 - 127)

Key on ID for which note off is to be performed
```

#### **Return Value**

The bit pattern of the voice for which note off was performed is returned.

If the return value is zero, note off is not performed for any voice.

#### Description

This function performs note off for the sound-producing voice corresponding to midiChannel, midiNote, and keyOnID.

However, if the voice has its sustain hold state set to on, it will transition to sustain state and note off will be performed when the sustain hold state is turned off.

Also, when the corresponding voices include a paused voice, the operation for the paused voice is ignored

```
#include #include sandp.h>
int main(void)
{
    unsigned int result;

    /* Stop the sound-producing voice with MIDI channel = 1, note = 64, */
    /* and key on ID = 0 */
    result= sceSsNoteOff(0, 64, 0);
    return 0;
}
```

## sceSsSetSustainHold

Set sustain hold state of voice by specifying MIDI channel and key on ID

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe for the sceSsSynthesisWithMix() and sceSsSynthesis() functions

#### **Arguments**

```
midiChannelMIDI channel for which sustain hold state is to be set<br/>(0 to 15 = MIDI channels 1 to 16)sustainHoldSustain hold state<br/>SCE_SNDP_ONSUSTAIN HOLDSustain hold on<br/>SUSTAIN HOLD OFFSUSTAIN HOLD OFFSustain hold offkeyOnIDKey on ID for which sustain hold state is to be set
```

#### **Return Value**

The bit pattern of the voice for which sustain hold state was set is returned.

If the return value is zero, it means that sustain hold state was not set for any voice.

#### Description

This function sets the sustain state for a voice with the specified MIDI channel and key on ID. If an operation is performed to stop sound generation for a voice that has sustain hold on, and if the sound being generated is a loop waveform, sound generation will not be stopped and the voice will transition to sustain state. To stop sound generation for a voice in sustain state, sustain hold must be switched off.

Also, when the corresponding voices include a paused voice, the operation for the paused voice is ignored.

#### Example


```
#include <libsndp.h>
int main(void)
{
    unsigned int result;

    /* Set sustain state to on for the voice with MIDI channel = 1 and */
    /* key on ID = 0 */
    result= sceSsSetSustainHold(0, SCE_SNDP_ON, 0);
```

**©SCEI** 

return 0;
}





## sceSsSetEffectParam

#### Set effect contents

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

#### **Arguments**

effectParam Pointer to SceSsEffectParam structure

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes in this document and the "SAS Reference" document.)

### **Description**

This function sets parameters for the effects you wish to perform in the members of the SceSsEffectParam structure.

The bitwise OR of the types of parameters to be set is specified for <code>setMask</code>, which is a member of the <code>SceSsEffectParam</code> structure. For example, if <code>SCE\_SNDP\_FX\_PARAM\_TYPE</code> is specified for <code>setMask</code>, the <code>type</code> parameter, which is a member of the <code>SceSsEffectParam</code> structure, is set.

Also, if SCE SNDP FX PARAM ALL is specified for setMask, all parameters are set.

For details about the settings, refer to the "SAS Overview" and "SAS Reference" documents.

The following parameters can be specified for type.

```
SCE_SNDP_FX_TYPE_OFF
SCE_SNDP_FX_TYPE_ROOM
SCE_SNDP_FX_TYPE_STUDIOA
SCE_SNDP_FX_TYPE_STUDIOC
SCE_SNDP_FX_TYPE_HALL
SCE_SNDP_FX_TYPE_SPACE
SCE_SNDP_FX_TYPE_ECHO
SCE_SNDP_FX_TYPE_DELAY
SCE_SNDP_FX_TYPE_DELAY
```

### **Example**

```
#include <libsndp.h>
int main(void)
        int result;
        SceSsEffectParam effectParam;
        /* Set SCE_SNDP_FX_TYPE_STUDIOC for the effect type,
        4096 for the left and right effect volume, and set the effect
        switch on for both the dry and wet sides */
        effectParam.setMask = SCE_SNDP_FX_PARAM_TYPE
                     SCE_SNDP_FX_PARAM_EFFECTVOLUME
                     SCE_SNDP_FX_PARAM_SWITCH;
        effectParam.type = SCE_SNDP_FX_TYPE_STUDIOC;
        effectParam.effectVolumeLeft = 4096;
        effectParam.effectVolumeRight = 4096;
        effectParam.drySwitch = SCE SNDP ON;
        effectParam.wetSwitch = SCE SNDP ON;
        result= sceSsSetEffectParam(&effectParam)
        return 0;
}
```

#### See Also

SceSsEffectParam



## sceSsNote2Pitch

Convert note value to pitch value

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)
Multithread safe

## **Arguments**

#### **Return Value**

The pitch is returned.

### Description

This function calculates the pitch from the center note and sound-producing note. Since the return value may exceed 0x4000, verify that the upper bound is not exceeded.

```
#include <libsndp.h>
int main(void)
{
    unsigned short pitch;
    pitch= sceSsNote2Pitch(64, 0, 64, 0);
    return 0;
}
```

# sceSsPitch2Note

## Convert pitch to note

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

## **Arguments**

```
centerNote Base note during sampling
centerFine Fine for base note during sampling
pitch Pitch
```


#### **Return Value**

The note value (upper 8 bits are the note and lower 8 bits are the fine) is returned.

## Description

This function calculates the sound-producing note from the center note and sound-producing pitch.

```
#include <libsndp.h>
int main(void)
{
    unsigned short note;
    note = sceSsPitch2Note(64, 0, 64, 0x1000);
    return 0;
}
```



## sceSsSMFBind

## Register SMF

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

## **Arguments**

smfCtx Pointer to smf environment structure

smf Pointer to smf data

phdID phd ID for which binding is to be performed tbfs Output sampling frequency (44100 or 48000)

#### **Return Value**

The smf ID that was assigned is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

An SceSsSmfCtx must be prepared for each set of data.

Note that separate SceSsSmfCtx structures must be prepared for different playback environments, even if the data is the same.

The *smfCtx* structure in the arguments does not need to be initialized. Be sure to allocate memory for it and pass it as a work area.

Specify the output sampling frequency of libsndp in the tbfs argument. Specify 44100 or 48000.

This function associates an SMF (Standard MIDI Format) with a PHD and returns the smf ID.

Up to 127 associations can be made.

If registration fails, it means that there may be a problem with the SMF format.

The SMF that can be used is only type 0.

### **Example**

```
#include <libsndp.h>
int main(void)
{
    int result;
    SceSsSmfCtx smfCtx;
    char *smf;

    result = sceSsSMFBind(&smfCtx, smf, 0, 48000);
    return 0;
}
```

#### **Notes**

When the tempo is 60, the SMF processing resolution is 1/172 for a quarter note. As a result, MIDI events that are generated with a lower resolution are quantized according to this resolution.

If a large number of MIDI events occur during the same unit of granularity, playback may get delayed. Therefore, either disperse the event timings or reduce the number of MIDI events to the minimum that are required.

Argument *tbfs* is used to generate the playback tempo of SMF

## See Also

SceSsSmfCtx

# sceSsSMFUnbind

#### Cancel SMF

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-enabled or disabled state)

Not multithread safe

## **Arguments**

smfID smfID to cancel

#### **Return Value**

The smfID that was assigned is returned.

If the return value is negative (< 0), an error is returned.

(For details, refer to the List of Error Codes.)

#### **Description**

This function cancels the association of the data with the registered smfID.

#### **Example**

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFUnbind(&smfCtx, smf, 0);
    return 0;
}
```

#### **Notes**

Since operations can no longer be performed for a canceled smfID, first stop playback for the smfID if it is being played before using this function.

## sceSsSMFPlay

## Start performance of SMF

#### **Definition**

## **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smf IDsmf ID for which performance is to be startedplayVelocityPerformance velocity (0 - 127)playPanPerformance panpot (0 - 64 - 127)playSendVelocityPerformance send velocity (0 - 127)playSendPanPerformance send panpot (0 - 64 - 127)playCountNumber of performances (>= 1; set SCE SNDP INFINITY for continuous looping)
```

## **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function starts the performance of an SMF.

playVelocity is a relative value of volume for the entire performance.

playPan is the orientation for the entire performance.

playSendVelocity is the a relative value of the effect send volume for the entire performance.

playSendPan is the orientation for the effect for the entire performance.

playCount is the total number of performances. If SCE\_SNDP\_INFINITY is specified, playback will loop continuously.

```
#include <libsndp.h>
int main(void)
        int result;
        char *smf;
        result = sceSsSMFPlay(0, 127, 64, 127, 64, SCE_SNDP_INFINITY);
        return 0;
}
```

# sceSsSMFPause

# Pause performance of SMF

### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

# **Arguments**

smf ID for which performance is to be paused

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

### **Description**

This function pauses the performance of an SMF that is being performed.

It turns off the suspend hold state of all sound-producing voices in the SMF to forcibly stop sound production.

#### Example

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFPause(0);
    return 0;
}
```

#### See Also

sceSsSMFResume()

# sceSsSMFResume

Resume performance of paused SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

# **Arguments**

smfID smf ID for which performance is to be resumed

# **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

# **Description**

This function resumes the performance of the SMF from the point where it was paused by sceSsSMFPause().

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFResume(0);
    return 0;
}
```

# sceSsSMFStop

# Stop performance of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

# **Arguments**

smfID smf ID for which performance is to be stopped

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

### **Description**

This function stops the performance of an SMF and returns its playback position to the beginning of the sequence data.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFStop(0);
    return 0;
}
```

# sceSsSMFAddTempo

Add tempo to performance of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfIDsmf ID for which tempo is to be added to performanceaddTempoMicroseconds per quarter note to be added
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function adds tempo to the performance of an SMF. <code>addTempo</code> is the number of microseconds per quarter note to be added to the current tempo. If it is positive, playback slows down. If it is negative, playback speeds up.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFAddTempo(0, 10000);
    return 0;
}
```

# sceSsSMFGetTempo

Get performance tempo of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

# **Arguments**

smfID smf ID for which tempo is to be obtained

#### **Return Value**

The number of microseconds per quarter note is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function gets the tempo of the performance. The return value is the number of microseconds per quarter note.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFGetTempo(0);
    return 0;
}
```

# sceSsSMFSetPlayVelocity

Set performance velocity of SMF

### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

# **Arguments**

```
smfID smf ID for which performance velocity is to be set
playVelocity Performance velocity (0 - 127)
```

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

# **Description**

This function sets the velocity for the entire SMF performance.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFSetPlayVelocity(0, 127);
    return 0;
}
```

# sceSsSMFGetPlayVelocity

Get performance velocity of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

# **Arguments**

smf ID for which performance velocity is to be obtained

## **Return Value**

The performance velocity is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function gets the performance velocity.

Returns value set by sceSsSMFSetPlayVelocity().

```
int main(void)
{
    int result;
    result = sceSsSMFGetPlayVelocity(0);
    return 0;
}
```

# sceSsSMFSetPlaySendVelocity

Set performance effect send velocity of SMF

### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfID smf ID for which performance velocity is to be set playSendVelocity Performance velocity (0 - 127)
```

#### **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function sets the effect send velocity for the entire SMF performance.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFSetPlaySendVelocity(0, 127);
    return 0;
}
```

# sceSsSMFGetPlaySendVelocity

Get performance effect send velocity of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state) Multithread safe

# Arguments

smf ID for which performance effect send velocity is to be obtained

#### **Return Value**

The performance effect send velocity is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

#### **Description**

This function gets the performance velocity.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFGetPlaySendVelocity(0);
    return 0;
}
```

# sceSsSMFSetPlayPanpot

Set performance panpot of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smf ID for which performance panpot is to be set playPanpot Performance panpot (0 - 64 - 127)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function sets the orientation for the entire performance of the SMF.

0 corresponds to the leftmost position, 64 to the middle, and 127 to the rightmost position.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFSetPlayPanpot(0, 127);
    return 0;
}
```

# sceSsSMFGetPlayPanpot

Get performance panpot of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

# **Arguments**

smf ID for which performance panpot is to be obtained

#### **Return Value**

The performance panpot is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function gets the performance panpot.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFGetPlayPanpot(0);
    return 0;
}
```

# sceSsSMFSetPlaySendPanpot

Set performance effect send panpot of SMF

#### **Definition**

```
#include <libsndp.h>
SceInt32 sceSsSMFSetPlaySendPanpot(
        SceUInt32 smfID,
        SceUInt32 playSendPanpot
);
```

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfID
```

smf ID for which the performance effect send panpot is to be set playSendPanpot Performance effect send panpot (0 - 64 - 127)

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function sets the effect send orientation for the entire performance of the SMF.

0 corresponds to the leftmost position, 64 to the middle, and 127 to the rightmost position.

```
#include <libsndp.h>
int main (void)
             result;
                  sceSsSMFSetPlaySendPanpot(0, 127);
        return 0;
```

# sceSsSMFGetPlaySendPanpot

Get performance effect send panpot of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Multithread safe

# **Arguments**

smf ID for which performance effect send panpot is to be obtained

#### **Return Value**

The performance panpot is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

#### **Description**

This function gets the performance effect send panpot.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFGetPlaySendPanpot(0);
    return 0;
}
```

# sceSsSMFGetPlayStatus

# Get performance status of SMF

### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state) Multithread safe

# **Arguments**

smf ID for which performance status is to be obtained

# **Return Value**

The performance status is returned.

Macro	Description
SCE_SNDP_PLAYSTATUS_READY	Performance can be started
SCE_SNDP_PLAYSTATUS_PLAY	Performance is in progress
SCE_SNDP_PLAYSTATUS_STOP	Performance is stopped
SCE SNDP PLAYSTATUS ERROR	Performance cannot take place

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function gets the performance status of an SMF.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFGetPlayStatus(0);
    return 0;
}
```

# sceSsSMFSetChannelMute

#### Set channel mute of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfID smf ID for which channel mute is to be set
midiChannel
MIDI channel to be muted
(0 to 15 = MIDI channels 1 to 16)
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# Description

This function mutes the performance of the MIDI channel specified by the SMF.

If sound is currently being produced, this function internally performs a key off, and then subsequently prohibits any key on from being performed.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFSetChannelMute(0, 0);
    return 0;
}
```

# sceSsSMFResetChannelMute

#### Cancel channel mute of SMF

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

# **Arguments**

smfID smf ID for which channel mute is to be canceled

# **Return Value**

When the function completes normally, SCE\_OK is returned. If the return value is negative (< 0), it indicates an error. (For details, see the List of Error Codes.)

#### **Description**

This function cancels all channel muting.

```
#include <libsndp.h>
int main(void)
{
    int result;
    result = sceSsSMFResetChannelMute(0);
    return 0;
}
```

# sceSsSMFSetPlayChannel

Simultaneously set muting for all channels of an SMF

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfID smf ID for which channel muting is to be set playChannelBit Sets mute ON or OFF for all MIDI channels bits 0 to 15 = MIDI channels 1 to 16; bit value 0 = Mute ON, 1 = Mute OFF
```

#### **Return Value**

When the function completes normally, SCE\_OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

# **Description**

This function sets the mute state of all MIDI channels of an SMF.

The bits of playChannelBit correspond to each of the MIDI channels, and the value of each bit indicates whether muting should be set ON or OFF for the respective channel.

If sound is being produced, the function internally performs a key off, then disables key on.

```
#include #include int main(void)
{
    int result;
    result = sceSsSMFSetPlayChannel(0, 0xFFFF); /* Cancel all muting */
    return 0;
}
```

# sceSsSMFGetPlayChannel

Get the mute states for all channels of an SMF

#### **Definition**

### **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
\begin{array}{ll} \textit{smfID} & \textit{smf ID for which channel muting is to be obtained} \\ \textit{playChannelBit} & \textit{Pointer for storing mute states of all MIDI channels} \\ \textit{bits 0 to 15} = \textit{MIDI channels 1 to 16;} \\ \textit{bit value 0} = \textit{Mute ON, 1} = \textit{Mute OFF} \end{array}
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it indicates an error.

(For details, see the List of Error Codes.)

### **Description**

This function gets the mute states of all MIDI channels of an SMF.

The bits of playChannelBit correspond to each of the MIDI channels, and the value of each bit indicates whether muting is turned ON or OFF for the respective channel.

```
#include <libsndp.h>
/* Return mute states of each MIDI channel in MuteBit */
int func(unsigned int *MuteBit)
{
    int result;
    result = sceSsSMFGetPlayChannel(0, MuteBit);
    return result;
}
```

# sceSsSMFGetKeyOnID

Get key on ID during an SMF performance

#### **Definition**

# **Calling Conditions**

Can be called from an interrupt handler

Can be called from a thread (does not depend on interrupt-disabled or -enabled state)

Not multithread safe

### **Arguments**

```
smfID smfID that was obtained by sceSsSMFBind()
midich MIDI channel
keyonID ID value return value
```

#### **Return Value**

When the function completes normally, SCE OK is returned.

If the return value is negative (< 0), it means that an error occurred.


(For details, see the List of Error Codes.)

#### Description

This function gets the key on ID value for an arbitrary midich during the performance of an SMF indicated by smfID.

```
#include <libsndp.h>
/* Get key on ID of the SMF midich channel during a performance by smfID */
int GetSMFKeyOnVoiceBit(unsigned int smfID, unsigned int midich)
{
   int result;
   unsigned int keyonID;

   result = sceSsSMFGetKeyOnID (smfID, midich, &keyonID);
   return result;
}
```



# **List of Error Codes**

List of error codes returned by libsndp

# Definition

Macro	Value	Description
SCE_SNDP_ERROR_NOTINIT	0x80450001	Initialization has not been performed
SCE_SNDP_ERROR_PHDID	0x80450002	phd ID is invalid
SCE_SNDP_ERROR_SMF	0x80450003	Pointer to SMF data is invalid
SCE_SNDP_ERROR_SMFCTX	0x80450004	Pointer to SMF environment structure is invalid
SCE_SNDP_ERROR_FORMAT	0x80450005	SMF format is invalid
SCE_SNDP_ERROR_SMFFULL	0x80450006	Max. number of SMF registrations was exceeded
SCE_SNDP_ERROR_SMFID	0x80450007	smf ID is invalid
SCE_SNDP_ERROR_PLAYCOUNT	0x80450008	Specified performance count is invalid
SCE_SNDP_ERROR_NOTREADY	0x80450009	Status is such that performance cannot be started
SCE_SNDP_ERROR_PARAM	0x8045000a	Parameter is invalid
SCE_SNDP_ERROR_NOTPLAY	0x8045000b	Not being performed
SCE_SNDP_ERROR_NOTPAUSE	0x8045000c	Not paused
SCE_SNDP_ERROR_DONTSTOP	0x8045000d	Status is such that performance cannot be stopped
SCE_SNDP_ERROR_ALREADY	0x8045000e	Status has already been set
SCE_SNDP_ERROR_SOUNDDATAFULL	0x8045000f	Max. number of sound data registrations was
		exceeded
SCE_SNDP_ERROR_CANTALLOCATEVOICE	0x80450010	Voice cannot be allocated
SCE_SNDP_ERROR_VOICENUM	0x80450011	Voice number is invalid
SCE_SNDP_ERROR_RESERVEDVOICE	0x80450012	Voice is not being managed by libsndp
SCE_SNDP_ERROR_PAUSEVOICE	0x80450013	A paused voice is included

