STRATUH | COPIER

QUICK-START GUIDE · FORMERLY VEST COPIER

Trade one account. The rest follow.

✓ In-browser ✓ No server ✓ No sign-up

Tampermonkey userscript for next.vestmarkets.com
Version 0.39.2

STRATUH Copier mirrors trades from your **master** account to your **follower** accounts, live, inside the Vest page. It runs in your own logged-in browser, acts only on your trades, and only while **copying**.

You trade the master
Place, manage and close trades on Vest exactly as you normally do.

→

The copier sees the order
It watches your master's order requests in the page, then fires matching orders.

→

Followers mirror it
Open · Add · Reduce · Stop / TP · Close · Cancel

01 INSTALL

1. Use **Chrome** (recommended: every release is tested on it; Edge, Brave and Firefox also work). Add **Tampermonkey** from your browser's store. In Chrome, Edge or Brave: `chrome://extensions` > Tampermonkey > Details > turn on **Allow User Scripts**.
2. Install from `github.com/xAmped/Vest-Copier` (it then auto-updates), or paste `vest-copier.user.js` into a new Tampermonkey script.
3. Open or refresh **next.vestmarkets.com** — the panel appears on the chart, left.
   New versions show as a row in the panel: click Install. Settings are kept.

02 SET UP & START

1. Your accounts load by themselves. In **Choose accounts**, pick your master (round button), tick each follower, then `Done`.
   Cap-to-fit (default) sizes each follower to its equity. Strict 1:1 needs matching size & type.
2. Set the leverage you'll use on Vest for the session.
3. Click `Start copying`. The first time, accept the one-time agreement.
   Everyone flat, or already in the same trade (it's adopted).
4. Trade the master normally. Every copy is logged.
5. `Stop copying` when you're done. It doesn't close positions.

Trade tab: follows Vest's market. Market, limit or stop orders, a price ladder in points (drawn on the chart), risk, % or max sizing, minis and micros on NQ, ES and RTY, and in a trade Breakeven, Close, Add and Reduce. Changed leverage or market? **Stop and start again.**

03 SIZING

EDIT > 1:1
Strict 1:1
Followers copy the master's exact size. Same size & type only.

DEFAULT
Sized to each account
Sized to its own equity. Same stop, same % risk.

```
follower size =
  master size × follower equity ÷ master equity
// e.g. 25k master 10.00 · 5k follower 1.90
```

04 OPTIONS & SAFETY

Fast mode	Fires follower entries the instant you send yours, before the master confirms.
Auto-flatten	Closes followers left in a trade without the master.
Flatten all	Closes all positions and orders on every loaded account. Instant, no confirmation. Copying keeps running.
Fill check	Names any account that didn't fill, master included.
Not copied	Refused orders; closes Vest forces (breach, liquidation).
Records	`P&L` today & totals, Share · `Download`: log & diagnostics in one file (token-free, safe to send).
Status	The dot, bottom right. Amber after a Vest update while the copier checks itself (a few seconds).

05 GOOD HABITS

- ✓ **Start tiny.** Test one small trade across all accounts first.
- ✓ **Stay flat** between sessions and stop copying when not trading.
- ✓ **Leave headroom.** Don't run the master at 100% margin in strict 1:1.
- ✓ **Size for the worst case:** a loss on every account at once.
- ✓ **Stop copying** before any manual trade you don't want copied.
- ✓ **Something off?** Click `Download` in the log and send the file.

06 TROUBLESHOOTING

No panel? Turn on **Allow User Scripts**, then refresh Vest.

Can't tick a follower? It's a different size or type. Pick Cap-to-fit, or match accounts.

Won't start? The log names the account and the reason.

Places real orders on live accounts. One bad master trade hits every linked account at once. Trade at your own risk.
Independent tool — not affiliated with or endorsed by Vest Markets.

Docs & updates: github.com/xAmped/Vest-Copier