

Installation

Getting the plugin into your project and proving the install is good.

~10 minutes (plus one compile)

IN SHORT

Put the plugin in `YourProject/Plugins/LCMNav3D/`, open the project and let it compile, enable **Show Plugin Content** in the Content Browser, then open a demo map and press Play. If the demo map works, your install is good.

Before you start

Requirement	Detail
Unreal Engine	5.8
Platform	Windows 64-bit or Linux
Project type	C++ project for a manual install (see below)
Compiler	Visual Studio 2022 with the <i>Game development with C++</i> workload (Windows)

The plugin ships as source, so something has to compile it once. Which "something" depends on how you install it.

Method A: Installed from Fab / Epic Games Launcher

This is the simplest path and works with **Blueprint-only projects**.

1. Install the plugin from the Launcher's **Library** → **Fab Library** section. It lands in `<Engine>/Plugins/Marketplace/LCMNav3D/` and is already compiled for 5.8.
2. Open your project.
3. **Edit** → **Plugins**, search "LCM Nav3D", tick **Enabled** if it isn't already.
4. Restart the editor when prompted.

Skip to [Verify the install](#).

Method B: Manual install into your project

Use this when you have the plugin as a folder (for example from a direct purchase or a version you re-targeted yourself).

1. Close the editor.
2. Copy the `LCMNav3D` folder into your project so the layout is:

```
YourProject/  
  YourProject.uproject  
  Plugins/  
    LCMNav3D/  
      LCMNav3D.uplugin  
      Source/  
      Content/  
      Config/  
      Shaders/
```

NOTE

Create the `Plugins` folder if your project doesn't have one. The folder must be named exactly `LCMNav3D`, because the content mount `/LCMNav3D/` depends on it.

3. If your project is **Blueprint-only**, convert it to **C++** first. A Blueprint-only project has no build pipeline and cannot compile a source plugin. The easiest conversion: **Tools** → **New C++ Class** → **None** → **Create Class**. The editor generates a `Source/` folder and restarts. You never have to write any C++ afterwards.
4. Right-click `YourProject.uproject` → **Generate Visual Studio project files**.
5. Open the generated `.sln` and build **Development Editor | Win64**, or open the `.uproject` and click **Yes** when the editor offers to rebuild.
6. The plugin is `EnabledByDefault`, so it turns itself on. Confirm under **Edit** → **Plugins**.

Verify the install

Do all three of these. Each one catches a different kind of failure.

1. The plugin loaded

Edit → **Plugins** → **AI Navigation** category. You should see **LCM Nav3D**, enabled, version 2.05.

2. You can see the plugin's content

Plugin content is hidden by default in the Content Browser:

Content Browser → **Settings** (the gear icon) → tick "Show Plugin Content".

A **LCM Nav3D Content** folder appears in the tree. Without this you will not find any demo map, and it is by far the most common "the plugin didn't install" false alarm.

3. A demo map actually runs

Open **LCM Nav3D Content → Demo → BehaviourTree → Vertical_Skyscraper** and press **Play**.

You should see agents flying through the building: over floors, through gaps, not along the ground. Give it a second or two on first play: the navigation volume builds at **BeginPlay**.

If that works, **your install is correct** and you can move on to [Tutorial 02: Core Concepts](#).

The engine plugins it turns on

LCMNav3D.uplugin declares these as dependencies, so the engine enables them for you. You do not need to touch them, but it is worth knowing they are on:

Plugin	Why it's needed
StateTree , GameplayStateTree	The StateTree task/condition/evaluator set
MassGameplay , MassAI	The Mass crowd layer
SmartObjects	Smart Object behaviour definitions
DataValidation	In-editor validation of illegal Mass trait combinations

NOTE

If the plugin fails to load with **GetLastError 126** , one of the Mass plugins got disabled. **MassGameplay** in particular is required at runtime. Re-enable it and restart.

NOTE

MassEntity is not in that list on purpose. It was an engine plugin up to UE 5.2, but is now a core engine module (**Engine/Source/Runtime/MassEntity**), so there is nothing to enable. Listing it as a plugin dependency on this engine version makes plugin resolution fail outright.

Common install problems

"The following modules are missing or built with a different engine version: **LCMNav3D**" The plugin hasn't been compiled for your engine build. Click **Yes** to rebuild. If the rebuild fails, you are on a Blueprint-only project, so go back to Method B step 3.

I can't find the demo maps. You haven't enabled *Show Plugin Content*. See verification step 2.

The plugin is missing from the Plugins window entirely. The folder is in the wrong place or misnamed. It must be `YourProject/Plugins/LCMNav3D/LCMNav3D.uplugin`. Check you didn't end up with a doubled folder like `Plugins/LCMNav3D/LCMNav3D/`.

Compile errors mentioning `StateTree` or `Mass types`. An engine plugin dependency was disabled. Re-enable the table above and regenerate project files.

More in [Troubleshooting](#).

Re-targeting to a newer engine version

This copy targets 5.8. To move to a newer engine, duplicate the folder and bump four things:

File	Field	Change
<code>LCMNav3D_Sample.uproject</code>	<code>EngineAssociation</code>	<code>"5.8"</code> → the new version
<code>LCMNav3D.uplugin</code>	<code>EngineVersion</code>	<code>"5.8.0"</code> → the new version
<code>*.Target.cs</code>	<code>IncludeOrderVersion</code> and <code>DefaultBuildSettings</code>	advance both to the new engine's values
<code>LCMNav3D.Build.cs</code> , <code>LCMNav3DEditor.Build.cs</code>	<code>IncludeOrderVersion</code>	advance to match

The module-level `IncludeOrderVersion` in the two `.Build.cs` files is easy to miss and matters: a standalone `RunUAT BuildPlugin` does not inherit the value from the project's `.Target.cs`, and an include order older than the engine keeps compatibility shims alive that the engine has removed.

`DefaultBuildSettings` must match the engine exactly when building against an installed engine. The editor target shares build products with the precompiled `UnrealEditor`, so it is not permitted to modify a shared setting, and an older value is rejected rather than warned about.

Then regenerate project files and fix anything the compiler flags. Each engine version should be its own copy of the plugin.

NEXT

[Tutorial 02: Core Concepts](#). What the navigation manager is actually doing, and the three settings that decide whether it works well in your level.

Chapter 1 of the LCM Nav3D User Manual.

The complete manual is `LCM_Nav3D_Manual.pdf`, in this folder alongside every other document in the set. Start from `README.pdf`.

LCM Nav3D: True Volumetric 3D Navigation for Unreal Engine. Version 2.05 · Unreal Engine 5.8.

Copyright © 2026 L.Charitha Madhushanka. All Rights Reserved. Proprietary and confidential. Licensed, not sold; use is governed by the licence that accompanies this software. Unreal Engine is a trademark of Epic Games, Inc. All trademarks are the property of their respective owners.