NORSAGA MARITIME INTELLIGENCE

God’s Eye

Beginner User Guide



The app with **Vessels / AIS**, **Wind forecast** and **Weather imagery** enabled. AIS shows reported vessel positions; weather layers provide environmental context.

New to God’s Eye? Start with **Start Here**, then follow **First 10 Minutes** for a guided practice session.

Updated October 12, 2026 · US English

CHAPTER 01 / START HERE

Your first look at God's Eye

This guide assumes you have never used the app. Start with the short practice exercise in chapter 2. Then open the chapter for the function you need.

Before you open the app

Use a **desktop or laptop** with a mouse or trackpad and a browser window of at least **1280 × 720 pixels**. A larger window makes the controls easier to read. Phones and tablets are not suitable for this workspace. Keep an internet connection available for maps and data feeds.


Open the app address supplied by your administrator. Your exact email address must be approved first. Enter it on the login page and click **Send Login Link**. Open the email from **no-reply@norsaga.com** (sender name: **NorSaga God´s Eye Access**) within ten minutes. Click the link, then **Confirm Sign-In**. On **My Access**, choose **Open God's Eye**. Wait for the globe and **MARITIME WORKSPACE** to appear.

God's Eye puts a map, moving objects and information from different sources in one place. You choose an area, turn on the information you want, and click an object to inspect it. A **layer** is one category of information, such as vessels or wind.


> This is the NorSaga MDA Research Platform for research, training and technology evaluation. Use it to explore and learn. It is not a navigation system or a source for safety-critical decisions.

Your personal login

There is no shared password. The email link is personal, works once and expires after ten minutes. Do not forward it. The page always says a link will be sent if the address is approved; this does not mean an unregistered address has access. If no email arrives, check your spam folder and ask the administrator to check your address.




Enter your approved address and choose **Send Login Link**. If you have already set up a passkey, choose **Sign In with a Passkey**.



Choose **Confirm Sign-In** to use the email link. Opening an email preview does not sign you in.

Passkeys and My Access

A **passkey** is a login key protected by your device, usually using Touch ID, Windows Hello or a security key. Ordinary users may keep using email links or choose **Create Passkey** for quicker login. Follow your browser's instructions. A reserve passkey should be on a second device or security key.




Open God's Eye opens the workspace. **Create Passkey** sets up a key. Administrators must then choose **Verify with Passkey** before managing users.

For the administrator

After confirming with a passkey, enter each person's name and exact email under **Approved Users**. Choose **Approve User**. They can now request their own login email; an invitation is not sent automatically. **Block Access** ends their active access too. Confirm with a passkey again when administration expires after fifteen minutes. Email alone cannot reset an existing administrator passkey; contact the server operator if all keys are lost.

To check usage, scroll to **User Access Log**. It shows each successful sign-in, the user's email, whether they used an email link or passkey, their last activity and session status. Choose **Refresh Log** to see the latest records. The table shows up to 100 sign-ins from the past 90 days; times use the time zone displayed above it. **Active session** means access is still valid, not that the person is currently looking at the app. Background feed updates do not count as activity.



The simple user list opens after passkey verification. The addresses shown here are examples from an isolated test installation, not approved production users.

Use **MY ACCESS** at the top of the workspace to return to your account. **LOG OUT** ends your server session. You must sign in again after thirty minutes without activity, or after eight hours even if you have been working.

How to use this manual

Choose a chapter from the menu on the left, or use the Next button at the bottom. Click any screenshot to enlarge it. **Download PDF** saves the complete manual for offline reading. **Print / PDF** prints all chapters, including chapters you have not opened. On a narrow guide window, use the menu button at the top left.

A **bold label** such as **CAPTURE SHOT** is the exact control to look for in the app. Yellow numbers in screenshots match the explanation below each picture.



1 Choose a maritime area. **2** Turn data layers on or off. **3** Save and replay Scenes. **4** Open Display, CCTV, Street Level and Context. **5** Open this guide, Location, AI Agent and Visual Presets. **6** Clear layers, share or reset the camera.

Updated 12 October 2026. Screenshots show this version of the app with real source responses. Login and administration screenshots use an isolated test installation and example accounts. Map appearance, available objects and source status can differ on your computer. The examples use the Esri map; a configured installation may use Google 3D.

Make your first useful view

Try this exercise once. You will learn where the controls are and save a view you can reopen.

1. In **MARITIME WORKSPACE**, open the **Fly to region** list and choose **Norwegian Sea**. Wait for the camera to finish moving.
2. Open **Maritime layers** below the region list. Tick **Vessels / AIS**. AIS is the system used to report ship identities and positions.
3. Click the **+** beside **DATA LAYERS**. Find **Live Vessels** and read the small source/status line. Wait for loading to finish. If it reports a missing source or an error, you can still practise navigation and saving a view.
4. Close the large layer panel using its collapse button. Use the mouse wheel to zoom in a little. If vessel symbols are available, click one and read its name, position time and available details.
5. Open **Maritime layers** again and tick **Wind forecast** if you want weather context. Read its source status. Wind is forecast information.
6. Open **SCENES**. Click **NEW**, type **My Norwegian Sea view** in the name prompt and confirm. Then click **CAPTURE SHOT**.
7. Check that **Shot 1** appears. Move the camera somewhere else, then click **LOAD** beside Shot 1. The saved camera and configuration return.




1 Choose the operating area. **2** Tick Vessels / AIS, Wind forecast or Weather imagery. **3** Aurora has its own checkbox above Maritime layers.

You have finished when: your Scene contains Shot 1 and LOAD returns to your saved view. A Scene stores the setup; live objects can change each time you reopen it.

See the complete Scene instructions

The starting view chooser

Click **Views** in Maritime Workspace to open **Choose your maritime view**. **Global maritime**, **Baltic Sea** and **Arctic** move the camera and request vessels, wind and weather imagery. **Global overview** moves to the globe overview and keeps your current layer selection. Aurora is enabled separately.



1 Choose one of the four views, or click Close to keep exploring. **2** Do not show this at startup changes whether this chooser appears; Views lets you reopen it.

If a layer is already selected, choosing a starting view can leave it selected. Use the top **Clear selected data layers** button when you want to begin with an empty map.

Move around without getting lost

The globe is your main workspace. Start with region presets, then practise small camera movements.

To do this	Use this control
Move around the globe	Hold the left mouse button on the map and drag.
Zoom in or out	Scroll the mouse wheel or use your trackpad scroll gesture. Make small movements.
Change the angle	Hold the right mouse button and drag, or use the top **Tilt map to oblique view** button.
Put north at the top	Click the **N** button at the top: Reset map to north up.
Recover the whole Earth	Click the globe icon at the top: **Reset to full globe view**. Your layer selection is managed separately.
Jump to a maritime area	Choose an area in **Fly to region**.

Find a place by name or coordinates

1. Click **LOCATION** along the bottom to open its tray.
2. Click the magnifying glass, then click the **Search any location...** field.
3. Type a specific place, such as **Oslo, Norway**, and press **Enter**. You can also enter latitude, longitude: **59.9139, 10.7522**. Latitude comes first.
4. Wait for the camera to move. If the place is not found, add a country name or use coordinates. A region preset is another way to navigate.
5. Click LOCATION again to close the tray. The pin button keeps the tray open when you need it.



1 Type a place or coordinates and press Enter. **2** City buttons give quick shortcuts. **3** N restores north at the top. **4** The globe button restores a full globe view.

LOCATION is for places and coordinates. To find a moving object, enable its layer and select its map symbol or use the available Contacts controls. A vessel name is not a reliable place-search query.

Open, move and close panels

Click the **+** or arrow on a panel header to expand it. Click its collapse button to close it. Open only the panel you are using so the map stays visible.


CCTV and **STREET LEVEL** can be pulled out of their side rail: drag the header onto the map. Resize a floating panel by dragging its edge or corner. Double-click its header to snap it back to the rail.

> **If you lose your position:** stop dragging, click the globe icon, then choose your region again. You do not need to reload the app.

Choose what appears on the map

A layer adds a category of information. Turning a layer on requests its data; the source line tells you whether usable information has arrived.

1. Click **+** beside **DATA LAYERS**. The list is grouped by Movement, Cameras, Infrastructure, Events, Weather, Space Weather and Utilities.
2. Find the layer you want, then click its **OFF** button. The selection changes and the app begins loading it.
3. Read the source/status line below its name. Check whether it is loading, available, stale or unavailable. A selected button alone does not prove the feed is working.
4. Collapse the panel and inspect the map. Click a visible symbol to see available details. Open the panel again and click the same toggle to turn that layer off.



1 Each row has its own toggle and source line. **2** Clear selected data layers turns all selected layers off; it does not delete your saved Scenes.

> **Start with one layer.** Add another only when it helps. If the map is crowded, zoom in, disable unused layers or lower the label density in DISPLAY.

Layer / function	What to look for
Live Vessels	AIS ship positions and details. Check the reported time, identity and source. Coverage can be incomplete or empty.
Live Flights / Military Flights	Observed aircraft positions and available flight details. Military Flights is a separate selection. Select an aircraft to inspect it.
Satellites	Objects positioned using an orbital model. These are predicted positions, not a camera image from space.
Street Traffic / Transit / Bike Share	Road activity, available transit services and bike-share information. Availability depends on the location and configured source. Some traffic is visualised rather than observed vehicle by vehicle.
Cameras / Street Level / Recent Imagery	Public camera images, recorded street photographs and satellite-image dates. They have different time meanings; see their chapters.
Mapped Installations / Mapped ALPR Cameras	Mapped site or roadside-camera locations. ALPR means automatic licence-plate recognition. Mapped locations do not provide plate reads or prove a device is operating.
Data Centers / Dams / Submarine Cables	Reference locations and infrastructure. These are background datasets, not live operational status.
Space Missions (30d)	Mission and launch information; open Context → SPACE MISSIONS to inspect available missions.
Earthquakes (24h) / Active Fires / Fire Perimeters	Recent earthquake reports, detected heat/fire points and mapped fire areas. A detection and a confirmed boundary are different types of information.
Wind / Rain radar / Satellite clouds / Lightning density / Cyclone advisories	Environmental context. Wind is a forecast; the other products carry their own observation or advisory times and coverage.
Aurora Forecast	NOAA space-weather forecast. Use the separate Aurora walkthrough.
Directions / Radio / Local ADS-B	Route tools, internet radio and an optional physical aircraft receiver. These are optional functions; see Context & Tools.

Explore the aurora forecast

Aurora is available on its own. You do not need to enable vessels, wind or weather imagery first.

1. In Maritime Workspace, choose **Arctic overview** or **Svalbard** from Fly to region.
2. Tick **Aurora Forecast** directly below the region list. Alternatively, enable Aurora Forecast in DATA LAYERS. Wait for the NOAA source status.
3. Read **Forecast** and the source time. The forecast time describes the future model estimate; the source time describes the input observation.
4. Move the map so the place you want to inspect is in the centre. Click **Read map center** to read the nearest NOAA grid value.
5. Use **Subtle**, **Clear** or **Strong** to change the overlay contrast. This changes visibility of the overlay, not the forecast.
6. Untick Aurora Forecast when you have finished.



1 Read forecast time, source time, Kp when available and the colour legend. **2** Read map center inspects the nearest model cell. **3** NOAA loop opens the official image history.

> The globe legend is **relative auroral intensity from 0 to 100**. A value of 50 is not a 50% chance of seeing aurora at your location. Clouds, darkness and your surroundings affect visibility. Kp is a geomagnetic-activity index; it can be unavailable while the grid forecast still works.

Play the NOAA image history

1. Click ▶ **NOAA loop**. A separate player opens.
2. Choose **Northern hemisphere** or **Southern hemisphere**, then **Latest 30 minutes** or **Latest 24 hours**. Wait for the images to load.
3. Click **Play** to animate, then **Pause** to stop. Use **Previous**, **Next** or the timeline slider to inspect a single frame.
4. Read **Model frame** below the player. Click **Close** to return to the map.




1 Choose the hemisphere. **2** Choose the history duration. **3** Play or pause. **4** Drag the timeline to one frame. **5** Model frame gives the time of the displayed image.

> **Keep the two views separate:** the image player shows NOAA image history; the globe continues showing the latest grid forecast. Moving the player timeline does not rewind the globe.

Look at satellite images from different dates

Recent Imagery helps you compare imagery of one area. These are acquired satellite images, not a live video feed.

1. Zoom to the area you want to inspect. Use a local or regional view rather than the whole Earth.
2. Open DATA LAYERS and enable **Recent Imagery**. Open its **RECENT IMAGERY** panel if it is collapsed.
3. Click **SELECT BOX**, then drag a box around the area on the map. Or click **USE VIEW** to use the current view. Press **Esc** to cancel an unfinished box.
4. Wait for dated image cards to appear. Read the date, sensor and cloud/coverage information. Choose a usable date to preview or pin using the shown controls.
5. Choose a comparison mode: the image alone, against the basemap, or **A/B** for two image dates. For A/B, select the dates for both slots.
6. When the divider is available, drag it to compare the sides. **SWAP** trades the sides. Use opacity to adjust the image strength.
7. Open **Details** for acquisition times, source and coverage. Use **EXPORT** (or EXPORT A / EXPORT B) to download the displayed source image.
8. Click **CLEAR** to remove the box and its images.



The panel starts with area-selection controls. Select a box or use the current view before expecting image dates. Empty or cloudy dates are normal.

If you are using Google 3D, showing imagery can switch the map to **Esri** so the comparison divider works. CLEAR or disabling the layer releases that comparison. If the comparison map fails, read the notice: imagery may display without a swipe divider.

Check before comparing: date, cloud, coverage and resolution. A blank patch can mean no usable image, and a visible difference can be caused by clouds or a different sensor.

Open a camera image or a street photograph

CCTV can show a public camera still or video. Street Level shows recorded photographs. Check which product you are looking at.

CCTV: public camera images


1. Navigate to your area, then open the **CCTV** panel on the right.
2. Click **CCTV OFF** to enable Cameras. You can also enable **Cameras** in DATA LAYERS.
3. Click **NEAREST**, choose a camera from the list, use **PREV / NEXT**, or select a camera marker on the map.
4. Read the source badge and camera information. A still image refreshes according to its source; a video is available only when that camera provides it.
5. Click **FOCUS** to move the map to the camera. **COVERAGE** displays its mapped viewing area; **AUTO HOP** cycles cameras. Turn auto-hop off to keep one camera selected.
6. Use the enable button again to turn Cameras off when finished.

Oslofjord harbor cameras

The camera list includes **Oslo Harbor** (City Hall Quay, Kavringen and Vippetangen), **Drammen Harbor** (eight quay views), and **Oscarsborg Marina** (three views). Enable CCTV, then choose a view from the camera selector. The map moves to its approximate location.

These are updated still images. Read **Image updated** below the preview to see the provider's image-update time in UTC. **OUTDATED IMAGE** means the image is more than thirty minutes old. If the time is unavailable, the app says so. A failed source refresh may leave the last available image visible with a degraded status. **Open Camera Website** opens the operator's original webcam page.


The map locations are approximate. Directions and projected coverage are estimates until calibrated; use the webcam image for visual context rather than treating the drawn coverage as a surveyed camera footprint. Oscarsborg publishes new images about every ten minutes; refreshing the app does not create a newer image.



An Oslo harbor view in the CCTV panel. Read the image-update time and the source badge before interpreting what you see.



1 Enable Cameras. **2** Find the nearest camera. **3** Choose a camera. **4** FOCUS moves the map to it.




1 View the camera image. **2** Check the source badge. **3** Read the selected camera. **4** Use FOCUS to move the map to it. The selected camera and the map location can differ.

Norwegian road cameras from **Statens vegvesen** are also included when their source is available. Choose the camera by its label and check its source; the nearest available result may be far from your map centre.

PROJECTION places the camera image into the 3D view. Its alignment is an estimate. Leave **ADJUST**, **SAVE CAL** and **RESET CAL** for advanced calibration work; these controls change alignment, not the camera's original image.

Street Level: recorded photographs

1. Open **STREET LEVEL** on the right and click **OFF**, or enable **Street Level** in DATA LAYERS.
2. Check the provider chips. Choose an available provider such as **Mapillary**. If a required token is missing, ask the administrator to configure it.
3. Use **ALL**, **360°** or **FLAT** to choose the photo type. Use **SINCE** to filter by date.
4. Zoom into an area with mapped coverage and select an image marker. Read the capture date and photographer/source attribution.
5. Use the image viewer's sequence navigation to step through photos. **EXPAND** makes the image larger; **FIT** shows the whole image; **FILL** crops it to the frame.
6. Turn **FOLLOW** on if you want the globe camera to align with the image view. Use × to close the selected image. Esc shrinks an expanded viewer.



1 Provider chips show availability. **2** Choose the photo type and date filter. A missing-token message means imagery is not configured on this installation.

Move or resize the image viewer

Drag the CCTV or Street Level header onto the map to create a floating panel. Drag an edge or corner to resize it. Double-click the header to return it to its side rail. This helps when inspecting an image and the map together.

Save a view you can reopen

A Scene is a named collection of saved views. Each saved view is called a shot. A shot stores camera, visual and layer settings; it does not take a screenshot or freeze a live feed.

Create your first Scene

1. Choose your location, zoom, viewing angle and layers first.
2. Open **SCENES** on the left. Click **NEW**, enter a clear name and confirm. NEW creates the collection; it has not captured the map yet.
3. Click **CAPTURE SHOT**. Check that **Shot 1** appears in the list and the status reports it was captured.
4. Double-click the shot name to rename it, for example **Norwegian Sea overview**, and press Enter.
5. Move to another useful view and click CAPTURE SHOT again to add Shot 2.



1 NEW creates a named Scene. **2** CAPTURE SHOT saves the current setup. **3** LOAD restores a shot; click its name to select it. **4** EXPORT PRESETS makes a backup.


Control	When to use it
Scene list	Choose the named Scene you want to work on.
LOAD	Restore a saved shot's camera and configuration.
UPDATE SHOT	Select a shot by clicking its name, adjust the live view, then replace that shot's saved setup. Use CAPTURE SHOT to add a new one instead.
START / STOP / NEXT	Play the Scene as a sequence, stop it, or advance to the next shot. Esc stops Scene playback. START plays views; it does not create a video file.

Control	When to use it
EXPORT PRESETS / IMPORT	Download a JSON file containing Scene presets, or choose a saved preset file to import. Keep an export before importing or making major changes.
DEL	Remove the selected Scene, or the individual shot beside that DEL button. Read the confirmation carefully.
RUN LOG	Download playback diagnostics after a run. This is a log, not the preset backup.

> **Keep a backup.** Scenes are stored in this browser's local storage, rather than an account shared across computers. Export presets before clearing browser data or moving to another computer. A shot stores its configured view, not a historical copy of every live object or every separate tool's content.

Share a saved Scene as a file


1. Choose your Scene in the SCENES list, then click **SHARE SCENE**.
2. Read the **Share selected scene** window. It lists the shots, data packs and any unavailable layers or external-content notices.
3. For an ordinary saved Scene, click **Download scene JSON**. This downloads the selected Scene's authored settings and attribution.
4. If a supplied Scene uses extra data-pack files, choose the files or folder requested, then use **Download asset bundle**. Only the included pack files travel with that bundle; external linked media is not automatically included.
5. Close with **Cancel** or Esc. Give the downloaded file to the recipient; they use IMPORT to review it in their app.



1 Review the selected Scene, then choose Download scene JSON. The file controls and Download asset bundle are for Scenes that need additional data-pack files.

Import a Scene file without losing your work

1. Click **EXPORT PRESETS** first and keep that backup. **Applying an import replaces the current Scene project.**
2. Click **IMPORT** and choose the supplied JSON or bundle JSON file.
3. Read **Review scene import**. Check the Scene/shot counts, missing-layer notices and any file or media requirements. Selecting the file only stages it for review.
4. Click **Apply import** only when you want to replace your current project. Click Cancel or press Esc to keep the current project unchanged.
5. After applying, choose a Scene, LOAD a shot and check its source status. Bundled files are held for this browser session; reimport the bundle after reloading if those files are needed again.




1 Read the preview and replacement notice before clicking Apply import. Cancel leaves your current Scenes in place.

Advanced: EDIT DETAILS and interactive Scenes

EDIT DETAILS opens a draft editor for the selected shot's camera, timing, anchors, data packs and actions. It contains JSON fields and is intended for advanced Scene authors. Beginners can use CAPTURE SHOT and UPDATE SHOT instead. Opening the editor does not save changes; **Apply details** validates and applies the draft, while Cancel or Esc discards it.


A supplied Scene can expose a **Scene actions** panel during playback. Select a feature or choose its named action using Tab and Enter. An action can reveal a source card or move to another part of the Scene. Follow its text and read any unavailable/cancelled message.



1 The draft is separate from the saved Scene. Use Cancel to leave it. Apply details is the explicit save action after validation.

Share the current map view

1. Set up the location, camera, layers and style you want the recipient to open.
2. Click the **chain-link icon** at the top, labelled **Copy share link**. Check for the copy confirmation.
3. Paste the copied link into your chosen message or document. The recipient opens it and uses their normal app access.
4. A shared view restores supported view settings; objects and source availability can differ when it is opened. Use EXPORT PRESETS to transfer a whole Scene collection.



1 Copy share link copies the configured view. **2** N resets bearing. **3** Tilt switches between straight-down and angled views.


If the notice says **Copy failed**, wait a moment after adjusting the view, then copy the full app address from your browser's address bar, including the part after **#**. A shared view link does not sign you in or grant access to a missing data provider.

Make the map easier to read

Start with Normal and a simple display. Change one option at a time so you can see what it does.

Choose a map and a visual style

1. Click **VISUAL PRESETS** at the bottom.
2. Under **MAP SOURCE**, choose an available map. Some maps need administrator configuration. A disabled option or fallback notice explains why it is unavailable.
3. Select **Normal** for the standard appearance. CRT, NVG, FLIR, Anime, Noir and Snow apply visual effects. Click Normal to remove those effects.
4. Click the pin if you want to keep this tray open; click it again to unpin.




1 Choose the visual style. **2** Choose the map source. **3** Pin keeps the tray open.

> **NVG and FLIR are visual effects.** They do not turn a map into a night-vision or thermal sensor. Snow styling does not establish observed snow conditions.

Reduce clutter in DISPLAY

Open **DISPLAY** on the right. **HUD** controls the information overlaid on the map; the Layout list offers Tactical, Operator, Minimal and Cyber. The detection button controls object labels and detection-style graphics. Its label shows the current mode: **SPARSE**, **BALANCED** or **DENSE**; **DETECT** is shown when off. Lower Density if too many labels overlap.

3D enables close-up aircraft models; Proximity limits them to nearby views. **Scope** controls the circular mask around the workspace. **Bloom** changes glow and **Sharpen** changes image sharpness. Cyber's sonar-like display is an interface effect, not a real sonar measurement.



1 HUD changes the map information display. **2** The detection button (DENSE in this example) controls labels. **3** Scope changes the circular mask. **4** Draw opens annotation tools.


Draw a point, line or area

1. In DISPLAY, click **Draw**. Choose the available shape: Area, Line or Pin.
2. Enter an optional label and choose a colour. Click on the map to place a pin, or click successive points for a line or area.
3. Double-click or press **Enter** to finish a line or area. Press **Esc** to cancel an unfinished shape.
4. Read the resulting label or measurement. These marks are your annotations. **Clear** removes all annotations, so use it only when you want the whole board cleared.

Clean UI hides the interface for a clear view. Click **EXIT CLEAN VIEW** to return. Use your normal screenshot or screen-recording tool if you want an image or video file.

Inspect contacts and explore optional tools

Context collects information about contacts and space missions. Other optional layers provide routes, radio or local receiver input.



1 CONTACTS opens nearby-object context. **2** SPACE MISSIONS opens mission information. **3** The radio icon opens compact radio controls.

Inspect a vessel or aircraft

1. Enable **Live Vessels** or **Live Flights** in DATA LAYERS and wait for source information.
2. Click a visible object symbol. Read the available card details, including observation time and identity. Missing fields mean the source has not supplied them.
3. Open **CONTEXT** and choose **CONTACTS** for nearby-object context. Use the contact selectors offered there to narrow the type or move between contacts.
4. When a tracked aircraft exposes **COCKPIT**, click it to enter the aircraft view. Click **EXIT COCKPIT** or press Esc to return to the map. This is a visual reconstruction from available data.

Vessel speed can be shown in **knots**. Heading is the direction the vessel points; course is the direction it moves. A short displayed trail covers available received positions and is not guaranteed to be a complete voyage history.



1 Read the AIS information for the selected vessel. Compare its identity, reported position time and available details before drawing conclusions.

Optional Global Fishing Watch information

A selected vessel may show lines beginning **GFW** in its details or AIS readout. These can include identity attributes and counts of modelled activity/events when the provider is configured. **CHECKING IDENTITY + EVENTS** means enrichment is loading; **NO IDENTITY MATCH** means this lookup did not identify a match. Modelled activity is research context, not proof of a vessel's actions. Missing GFW information does not prevent the AIS view from working.

Space missions

Choose **SPACE MISSIONS** in CONTEXT and select a mission from the available roster. Read the scheduled/status information and use the offered focus controls to inspect its launch site. Times and schedules can change; simulated replays illustrate a sequence rather than confirm an actual launch.

Radio

1. Click the radio icon in the Context header and click **ENABLE**.
2. Choose a station using its map marker or the previous/next controls. The detailed Radio section adds station-tag filters and tuner controls.
3. Click **PLAY**. Adjust Volume. Click Pause or STOP in the applicable control to end playback. Audio starts only when you choose to play it.

Streaming connects to the broadcaster. AI voice and radio can compete for audio; read any takeover confirmation before continuing.

Directions and Local ADS-B

Directions: enable it in DATA LAYERS, then use its route controls to set a start and destination and inspect the returned route. Coverage and routing depend on the source. It is a planning illustration.

Local ADS-B: this requires a compatible physical RTL-SDR USB receiver. The Radio section has CONNECT and FM / ADS-B controls; follow the browser's device chooser only when the receiver is attached. The same tuner is shared by FM and aircraft reception, so it cannot perform both at once. Beginners can leave Local ADS-B off.


Give one spoken instruction at a time

The AI Agent is an optional way to use the same map functions. You can learn and use the app with the ordinary controls first.

1. Find **AI AGENT** in the bottom dock. **OFF** means no active voice session.
2. Click the microphone **ON/OFF** button. Allow microphone access if your browser asks. Wait for the agent to become ready.
3. With focus on the map rather than a text field, hold **Space** and say a short instruction, such as **“Go to Oslo, Norway.”** Release Space to send.
4. Wait for the answer and check the resulting map change. Follow with one instruction, such as **“Turn on live vessels”** or **“Reset to globe view.”**
5. Read the response card and any source/error notes. Ask another question only after the current action finishes.
6. Click ON/OFF again to end the session.

> Hold Space to speak when the map has focus. A quick Space press on a focused button activates that button. Click the map before starting a voice command so you do not accidentally trigger a control.

If voice will not connect: check microphone permission, internet access and the error message. The administrator may need to configure the AI service. Continue using the ordinary controls while it is unavailable.



1 ON/OFF starts or ends voice. **2** Status tells you whether it is ready. **3** STD selects the model tier for the next session. **4** The amount is an estimated session cost.

Good first requests include **“Show the Norwegian Sea,” “Turn off wind,”** and **“How many ships are in view?”** Data questions use loaded records from enabled layers; a count describes the available data, not every object that exists in the real world.

Know what the numbers mean

Check a source's time and coverage before interpreting what you see. Different products have different update intervals.

Status or time	What it means for you
OFF / never	This layer is off or has not loaded in this browser session. "Never" is not evidence that the source is broken.
Loading / connecting	A request or connection is in progress. Wait and read the status before assuming data has arrived.
Live / observed	The source reports observations. They can still have delay; check the position or observation timestamp.
Forecast	A model estimates conditions or positions at a stated time. Wind and Aurora are examples.
Stale / cached	Older data may still be visible. Use its original timestamp to judge age.
Empty coverage / no results	A source can answer successfully with no accepted objects in the covered area. Empty results are different from a connection error.
Unavailable / missing key / error	Usable source information could not be obtained. Read the reason and contact the administrator if configuration is needed.
UTC	A common worldwide time standard. Local time in Norway is UTC+1 in winter and UTC+2 in summer. The screenshot timestamps use UTC where labelled.

A freshly downloaded image can show an older acquisition date. A recently received position can also have an older observation time. Use the time of the underlying observation, acquisition or forecast, rather than assuming the download time describes the event.

Small glossary

Word	Plain meaning
MDA	Maritime Domain Awareness: understanding activity in the maritime area.

Word	Plain meaning
AIS / MMSI	AIS carries ship reports. MMSI is a vessel's maritime radio identity number; check it when names are similar.
ADS-B	Aircraft broadcasts used by receivers and providers to report aircraft positions.
Layer / basemap	A layer adds data. The basemap is the background map or 3D world underneath it.
Scene / shot	A Scene is a named set of saved views. A shot is one camera and configuration within it.
HUD / heading / course	HUD is information overlaid on the map. Heading is where an object points; course is where it travels.
Latitude / longitude	Coordinates: latitude measures north/south; longitude measures east/west. Search expects latitude first.
Knots / km / m	Knots measure speed at sea; one knot is 1.852 km/h. km means kilometres; m means metres.
Coverage / resolution	Coverage is where data exists. Resolution is the level of detail it can show.
Provider / token	A provider supplies data. A token is a service credential configured by the administrator.
JSON	The file format used for exported Scene presets. Keep the file for IMPORT; you do not need to edit it.

What is connected and what is not

The Arctic view provides vessels and weather when their sources are available. Its description states that **sea-ice charts are not connected yet**. The presence of a region preset does not imply all possible maritime datasets are available. Follow the actual source status in the app.

Fix common problems and practise safely

Most beginner problems can be resolved by resetting the camera, checking the source line or reopening a saved shot.

What you see	What to do next
I cannot find the controls	Make the app window at least 1280 × 720. Exit Clean View if active. Look for + or arrows on the side-panel headers.
I am lost on the map	Click N to restore north, or the globe icon to restore the whole Earth. Choose Fly to region again.
No vessels or aircraft appear	Check that the correct layer is on, read its source status, wait for loading, and try another scale or area. Empty coverage is possible.
Objects are on screen but the feed says stale	Treat the displayed positions as older information. Read their observation time and do not describe them as current.
Search finds the wrong place	Add the country or use latitude, longitude. To inspect moving objects, use their layer and Contacts rather than the location field.
My map looks different from the guide	Choose Normal in Visual Presets. Check Map Source. Google 3D may fall back to another map if its source is unavailable.
A camera is blank	Try another camera with PREV / NEXT. Read the source badge. Some cameras supply stills, some video, and some are temporarily unavailable.
Street Level says a token is missing	Ask the administrator to configure Mapillary. Other functions can still be used.
Aurora is faint or missing	Check the source status, choose an Arctic region and try Clear or Strong contrast. Low-intensity model cells can be transparent.
No recent image is usable	Select a smaller area, try another date and inspect clouds/coverage. Read the comparison-map notice if there is no divider.
My Scene has no saved view	NEW creates a Scene; CAPTURE SHOT saves a view. Look for Shot 1 before leaving the panel.

What you see	What to do next
A saved view changes after LOAD	LOAD restores its setup. Live objects update from current available sources; it is not an archived snapshot.
Scene controls are disabled	If playback is running, click STOP or press Esc before editing.
My floating panel is in the way	Double-click the CCTV or Street Level header to dock it again, or drag and resize it.
Voice does not work	Check microphone permission and the connection error. Use the normal controls and ask the administrator if service configuration is needed.
The app feels slow	Turn off unused layers, reduce labels and 3D models, close unused panels and return to Normal. Keep the practice view simple.

Three short practice exercises

1. Navigation

Go to Baltic Sea. Zoom in a little, tilt the view, then restore north. Return to the globe. You finish when you can recover your view without reloading.

2. Aurora

Choose Arctic overview. Enable Aurora, read the map centre, open NOAA loop and select one frame. Close the player and turn Aurora off.

3. Save and return

Create a practice Scene, capture one shot, move to another region and LOAD the shot. Export the presets as a backup.

When you need help

Tell your administrator which function you used, the exact source/error text and what you expected. Include a screenshot if useful. Do not include login links, passkey details or provider credentials.

Click **LOG OUT** at the top of the app to return to its personal login screen. Keep a preset export if you plan to clear this browser's stored data.