

-
-
-
-
-

Chapter 3

Processing



Drinks DRP Processing Functions

The processing options of the Drinks DRP application can be divided into the following possible tasks:

- Evaluate DC Demand.
- Run DRP for Centre.
- Run DRP for Network.
- Enter Distribution Order.
- Amend Distribution Order.
- Confirm Receipt Shipment.

Evaluate DC Demand

1... **2...** 1/DDP

This option is used to assess the supply and demand status for items handled at DCs within the selected network.

A separate schedule is produced for each DC, with supply and demand quantities, and suggested actions, for each Item.

Evaluate DC Demand Network Selection Screen

 Select the Evaluate DC Demand option.

The initial screen enables you to select the network (prompt available) for which DC demand is to be evaluated.

Fields:

Network Code

Enter a valid code, as defined to DRP via Network Maintenance.

 Press **Enter** to display the Evaluate DC Demand Processing Run Selection Screen.

Evaluate DC Demand Processing Run Selection Screen



This screen is displayed when you have entered a valid network code into the Evaluate DC Demand Processing Selection Screen.

It enables selection criteria to be entered and a Drinks DRP processing run submitted for the selected network.

```

DR002                HW - Handy Wholesalers Ltd                USER GALBRAIJ    20/10/95
                                                           13:29:15

DRP DC Run Selection

      Network..... N1    Northern region

      DRP run type... 1    1=Full regeneration
                           2=Net change
                           3=Selective

-----

Enter:   Current date..... 201095
         Overdue days..... 1
         Time fence days....
         End date..... 000000
         Include forecasts.. -    (1=Sales, 2=Stock building, 3=Both,
                                   0=Neither, Blank=As per item)

-----
F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions  F19=Print last run details

00-33    SF    HW    KS    IM    II    KENB20A    PED171S1
  
```

Fields:

Network

Code from the previous screen.

Description

From Network Details.

DRP Run Type

Specifies the type of DRP run to be processed. There are three types of DRP run as follows:

1 - Full Regeneration. All items are re-planned.

2 - Net Change. A subset of items are re-planned on the basis of changes in the supply, demand, stock or replenishment parameters of items since those items were last planned for the network or centre. Changes in supply, demand, stock or replenishment parameters set 'triggers', some or all of which may be selected for processing by pressing **F14=Review Specification** when Net Change has been specified as the run type.

3 - Selective. A subset of items are re-planned on the basis of a selection of ranges of Items, DRP Planners, Minor Item Groups, Cost/Usage Elements

and/or Preferred Suppliers. These ranges are entered by pressing **F14=Review Specification** after selective processing has been specified as the DRP run type.

Current Date

This defaults to today's date. It is used in conjunction with 'overdue days' to establish the start date for the DRP run. Start date is calculated as follows:

Start Date=Current Date - Overdue Days.

Overdue Days

Specifies the number of days prior to the current date within which the application will still include outstanding supply and demand orders (exclude any forecasts.)

Time Fence Days

Specifies the number of days forward from the current date of the DRP run during which the plan remains frozen. Any supply suggestions required within this period are set for action on the first working day after the time fence. Enter the number of time fence days to apply to all items in this DRP run. If the entry is blank or zero, time fences will be calculated at item level (defined within Distribution Item Master Maintenance), based on lead times.

End Date

Specifies the last date to be considered by the planning run. Defaults to the end date of the previous run.

Include Forecasts

Specifies the type of forecast(s) which will be considered by the planning run. Valid values are as follows:

- 1 - Include Sales Forecast only.
- 2 - Include Stock Forecast only.
- 3 - Include Both sales and Stock Forecasts.
- 0 - Exclude all forecasts - only actual demand is considered.

Blank - As per Item.

Each item is considered separately, with forecasts included or excluded on the basis of the Distribution Item Master Forecast Field Entry.

Functions:

F14

Review Specification

F16

Restrict Extractions

F19

Print last Run Details



When all details are entered and validated, submit the regeneration plan batch job by pressing **F8=Submit**.



If, however, the specified run type is Net Change or Selective, further details relating to these run types are required - press **F14=Specification**.

Evaluate DC Demand Net Trigger Selection Screen (Option 2)



This screen is accessed by choosing the Net Change option (option '2') from the Evaluate DC Demand Processing Run Selection Screen.

It displays Net Change selections for the last Net Change processing run for the selected network. Maintenance of these details for the current run is also possible.

Net Change details can be entered for each DC in the selected Network. Each time you press **Enter**, if all the details are valid, the next DC in the network is displayed. When details have been entered for all DCs in the network, the run options screen is displayed.

```

DR002          HW - Handy Wholesalers Ltd          USER GALBRAITJ  20/10/95
                                           16:44:03

DRP DC Run Selection

Network..... N1 Northern region
Net Change Trigger Selection
DC..... C1 Scotland

Sel Trigger Description          Unprocessed Quantity to
Reason          Triggers          Process
- 01 Forecast vs Actual Comparison.          0          0
- 02 Forecast Generation.                    2          0
- 03 Forecast Maintenance.                   0          0
- 04 Distribution Item Master.                2          0
- 05 Unplanned Inventory Transactions.        0          0
- 06 Requisition Maintenance.                0          0
- 07 Unplanned Issue or Receipt.             0          0
- 08 Purchase Order Maintenance.             0          0
- 09 Order Maintenance.                     0          0

1=Select All  2=Select with Limit
F3=Exit  F12=Previous  F10=Select All
11-05  S2  MW  KS  IM  II  KENB20A  PED171S1
  
```

Fields:

DC

Displays the code and description of the DC for which Net Change run details are being maintained.

Sel

Select Net Change Triggers to process for this reason code as follows:

- 1 - To select all triggers to process for this reason code, or
- 2 - To select a particular quantity of triggers to process for this reason code.

Trigger Reason

Displays the Trigger Reason Code as defined in Drinks DRP Net Change Trigger Reason Maintenance.

Description

Displays the Trigger Reason Code Description as defined in Drinks DRP Net Change Trigger Reason Maintenance.

Unprocessed Triggers

Displays the number of triggers currently set for this reason code.

Quantity to Process

Specify the number of unprocessed triggers to be processed for this reason code in the Drinks DRP Net Change run.



Note: Do not enter a value in this field if all triggers have been selected to be processed for this Reason Code.

Functions:

F18

Select All



Tip: As an alternative to individually selecting Reason Codes and quantities to process, all unprocessed triggers for all Reason Codes may be selected by pressing **F18=Select All**.



Press **Enter** to continue.

Evaluate DC Demand Selection Criteria Screen (Option 3)



This screen is accessed by choosing the Selective option (option '3') from the Evaluate DC Demand Processing Run Selection Screen.

This screen displays selections for the last selective processing run for the network and allows maintenance of these details for the current run.

Details can be entered for each DC in the selected network. Each time **Enter** is pressed, if all the details are valid, the next DC in the network is displayed. When details have been entered for all DCs in the network, the run options screen is re-displayed.

Fields:

DC

Displays the code and description of the DC for which selective run details are being maintained.

Item

Optionally enter a range of items to be selected for re-planning.

Planner

Optionally enter a range of DRP Planners. Only those items defined to DRP Planners within this range will be selected.

Item Group

Optionally enter a range of Inventory Minor Item Groups. Only those items defined to Inventory Minor Item Groups within this range will be selected.

Value / Usage Class

Optionally enter a range of Inventory Values/Usage Classes. Only those items with Value/Usage Classes within this range will be selected.

Preferred Supplier

Optionally enter a range of Preferred Suppliers. Only those items with preferred suppliers within this range will be selected. (Preferred Suppliers are defined in Item/Stockroom Maintenance in Inventory Management).

Rules for Range Selection:

- If from and to fields are left blank all selections are available.
- If from field is entered and to field is left blank, then to field defaults to from field.
- If to field is entered, from field must also be entered.
- To field must not be less than from field.

Evaluate DC Demand Restrict Order Extractions Screen (F16)



This screen is displayed when you select **F16=Restrict Extractions** on the Evaluate DC Demand Processing Run Selection Screen.

It allows selection of which purchase orders are to be extracted for DRP processing. Used to improve processing efficiency by restricting data extraction.

DR002 HW - Handy Wholesalers Ltd USER GALBRAIJ 20/10/95 17:08:30

DRP DC Run Selection

Network...

DRP run t

Restrict Order Extractions for Run

Exclude Unconfirmed Quantities on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)

Exclude Confirmed Purchase Orders (Outstanding, GI, Inspection)..... 0 (1=Yes, 0=No)

F12=Previous

Enter: Current date..... 201095
Overdue days..... 1
Time fence days.....
End date..... 311295
Include forecasts.. - (1=Sales, 2=Stock building, 3=Both, 0=Neither, Blank=As per item)

F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details

07-62 SR HW KS IM II KENB20A PED171S1

Fields:



The following exclusions may be applied:

Unconfirmed Quantities on Scheduled Purchase Orders

0 - To extract all scheduled purchase order quantities whether confirmed or not. System will assign unscheduled order quantities to the last planning period in the DRP run.

1 - To exclude unconfirmed order quantities from scheduled orders, the effect of reducing data extraction and supply processing.

Confirmed Purchase Orders - Outstanding, Goods Inwards, Inspection

0 - To include all purchase order quantities for processing.

1 - To exclude all purchase orders from processing. This applies particularly where there is no local purchasing at the DC.



Press **Enter** to update exclusion criteria and return to the Evaluate DC Demand Processing Run Selection Screen.

Run DRP For Centre

1... **2/DDP**

This option is used to assess the supply and demand for the selected supply centre, and produce the central supply plan.

The supply plan, i.e. the schedule, may contain suggested Purchase Orders and/or amendments to existing orders.

Run DRP For Centre Selection Screen



Select the Run DRP for Centre option.

The initial screen enables you to select the supply centre to be evaluated.

Fields:

Centre

A code defined as a centre to at least one network, via Drinks DRP Network Maintenance.



Press **Enter** to display the Run DRP For Centre Run Options Screen.

Run DRP For Centre Run Options Screen



This screen is displayed when you have entered a Centre code into the Run DRP For Centre Selection Screen.

It enables selection criteria to be entered and a Drinks DRP processing run submitted for the selected DRP centre.

```

DR002                HW - Handy Wholesalers Ltd                USER GALBRAIJ    24/10/95
                                                              15:01:37

DRP Centre Run Selection

      Centre..... 01 Manchester centre

      DRP run type... 1  1=Full regeneration
                       2=Net change
                       3=Selective

-----

Enter:   Current date..... 241095
         Overdue days..... 1
         Time fence days....
         End date..... 000000
         Include forecasts.. -      (1=Sales, 2=Stock building, 3=Both,
                                     0=Neither, Blank=As per item)

-----
F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions

08-33    SF      HW      KS      IM      II  PLYM400A PED171S1
  
```

Fields:

Centre

Code from previous screen.

Description

From Network Details.

DRP Run Type

Specifies the type of DRP run to be processed. There are three types of DRP run as follows:

1 - Full Regeneration. All items are re-planned.

2 - Net Change. A subset of items are re-planned on the basis of changes in the supply, demand, stock or replenishment parameters of items since those items were last planned for the network or centre. Changes in supply, demand, stock or replenishment parameters set 'triggers', some or all of which may be selected for processing by pressing **F14=Review Specification** when net change has been specified as the DRP Run Type.

3 - Selective. A subset of items are re-planned on the basis of a selection of ranges of items, DRP Planners, Minor Item Groups, Cost/Usage Elements and/or Preferred Suppliers. These ranges are entered by pressing **F14=Review**

Specification after selective processing has been specified as the DRP Run Type.

Current Date

This defaults to the current date. It is used in conjunction with 'overdue days' to establish the start date for the DRP run. Start date is calculated as follows:

Start Date=Current Date - Overdue Days.

Overdue Days

Specifies the number of days prior to the current date within which the application will still include outstanding supplies to still be valid.

Time Fence Days

Specifies the number of forward days from the current date of the DRP run during which the plan remains frozen. Any supply suggestions required within this period are set for action on the first working day after the time fence. Enter the number of time fence days to apply to all items in this DRP run. If the entry is blank or zero, time fences are calculated at item level (defined through Distribution Item Master Maintenance).

End Date

Specifies the last date to be considered by the planning run. Defaults to the end date of the previous run (if applicable).

Include Forecasts

Specifies the type of forecasts) which will be considered by the planning run. Valid values are as follows:

- 1 - Include sales forecast only.
- 2 - Include stock level forecasts only.
- 3 - Include both sales and stock level forecasts.
- 0 - Exclude all forecasts - only consider actual demand.
- Blank - As per item.

Each item is considered separately, with forecasts included or excluded on the basis of specification in Distribution Item Master Maintenance.

Functions:

F14

Review Specification

F16

Restrict Extractions



When all details are entered and validated, the regeneration plan batch job may be submitted by pressing **F8=Submit**.



If, however, the specified run type is net change or selective, further details relating to these run types should be entered. This is achieved by

pressing **F14=Review Specification**

Run DRP For Centre Net Change Trigger Selection Screen (Option 2)



This screen is displayed when you select option 2 'Net Change' on the Run DRP For Centre Run Option Screen.

It displays net change selections for the last net change processing run for the selected Drinks DRP Centre and allows maintenance of these details for the current run.

```

DR002          HW - Handy Wholesalers Ltd          USER GALBRAIJ  24/10/95
                                                    15:01:37

DRP Centre Run Selection

Centre..... 01 Manchester centre

Net Change Trigger Selection
Centre... 01 Manchester centre

Sel Trigger Description          Unprocessed Quantity to
Reason                          Triggers      Process
- 01 Forecast vs Actual Comparison.      0      0
- 02 Forecast Generation.                0      0
- 03 Forecast Maintenance.                0      0
- 04 Distribution Item Master.            1      0
- 05 Unplanned Inventory Transactions.    0      0
- 06 Requisition Maintenance.            0      0
- 07 Unplanned Issue or Receipt.         0      0
- 08 Purchase Order Maintenance.         1      0
- 09 Order Maintenance.                  0      0

1=Select All  2=Select with Limit
F3=Exit  F12=Previous  F10=Select All

11-05  SF  MW  KS  IM  II  PLYM400A PED171S1
  
```

Fields:

Centre

Displays the code and description of the Centre for which Net Change run details are being maintained.

Sel

Select Net Change Triggers to process for this reason code as follows:

- 1 - To select all triggers to process for this reason code, or
- 2 - To select a particular quantity of triggers to process for this reason code.

Trigger Reason

Displays the Trigger Reason Code as defined in DRP Net Change Trigger Reason Maintenance.

Description

Displays the Trigger Reason Code Description as defined in DRP Net Change Trigger Reason Maintenance.

Unprocessed Triggers

Displays the number of triggers currently set for this reason code.

Quantity to Process

Specify the number of unprocessed triggers to be processed for this reason code in the DRP Net Change run.



Note: Do not enter a value in this field if all triggers have been selected to be processed for this Reason Code.



Tip: As an alternative to individually selecting Reason Codes and quantities to process, all unprocessed triggers for all Reason Codes may be selected by pressing **F18=Select All**.

Functions:

F18

Select All



Press **Enter** to return to the Run DRP For Centre Run Option Screen.

Run DRP For Centre Review Specification Selection Criteria Screen (F14)



This screen is displayed when you press
F14=Review Specification on the Run DRP For
Centre Run Options Screen.

It displays selections for the last selective processing run for the centre and
allows maintenance of these details for the current run.

Item.....?..	Planner.....?..	Item Group.....?..	Value/Usage Class.....	Preferred Supplier.?..
B101	P01	SWB	-	-
C101	PC01	SWC	-	-

F4=Prompt F12=Previous

18-44 S4 HW KS IM II PLYM400A PED171S1

Fields:

DRP Centre

Displays the code and description of the DRP centre for which selective run details are being maintained.

Item

Optionally enter a range of items to be selected for re-planning.

Planner

Optionally enter a range of DRP Planners. Only those items defined to DRP Planners within this range will be selected.

Item Group

Optionally enter a range of Inventory Minor Item Groups. Only those items defined to Inventory Minor Item Groups within this range will be selected.

Value/Usage Class

Optionally enter a range of Inventory Values/Usage Classes. Only those items with Value/Usage Classes within this range will be selected.

Preferred Supplier

Optionally enter a range of Preferred Suppliers. Only those items with preferred suppliers within this range will be selected. (Preferred Suppliers are defined in Item/Stockroom Maintenance in Inventory Management).



Press Enter to return to the Run DRP for Centre
Run Option Screen.

Run DRP for Centre Restrict Order Extractions Screen (F16)



This screen is displayed when you press
F16=Restrict Extractions from the Run DRP for
Centre Run Options Screen.

It allows selection of which Purchase orders will be extracted during DRP
processing. It is used to control efficiency of DRP processing.

DR002 HW - Handy Wholesalers Ltd USER GALBRAIJ 24/10/95 15:37:55

DRP Centre Run Selection

Centre...

DRP run t

Restrict Order Extractions for Run

Exclude Unconfirmed Quantities
on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)

Exclude Confirmed Purchase Orders
(Outstanding, GI, Inspection).... 0 (1=Yes, 0=No)

F12=Previous

Enter: Current date..... 241095
Overdue days..... 1
Time fence days.....
End date..... 311095
Include forecasts.. 1 (1=Sales, 2=Stock building, 3=Both,
0=Neither, Blank=As per item)

F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions

07-62 56 HW KS IM II PLYM400A PED171S1

Fields:



The following exclusions may be applied:

Unconfirmed Quantities on Scheduled Purchase Orders

0 - To extract all scheduled purchase order quantities whether confirmed or not.
System will assign unscheduled order quantities to the last planning period in the
DRP run.

1 - To exclude unconfirmed order quantities from scheduled orders, the effect of
reducing data extraction and supply processing.

Confirmed Purchase Orders (Outstanding, GI, Inspection)

0 - To include all purchase order quantities for processing.

1 - To exclude all purchase orders from processing. This applies particularly
where there is no local purchasing at the DC.



Press **Enter** to update exclusion criteria.

Network Run

1... **2...** **3/DDP**

To access the supply and demand for the whole of the selected Network within a single run.

This includes the following automated processes:

- Evaluate DC Demand - Full Regeneration, Net Change or Selective.
- Confirm Supply Suggestions.
- Create Local Purchase Orders.
- Create Distribution Orders.
- Run Central Supply Plan - Full Regeneration only.

In effect, this removes the manual intervention stage of amending suggestions and creating orders (via Purchase Requisitioning), for the DCs.

This automated run is particularly useful where supply suggestions are unlikely to require many amendments. It enables the whole network to be assessed with a single run, which could be initiated at the end of a particular working day to execute overnight.

The resulting DC and centre schedules can be reviewed either by the schedule enquiries, or by schedule reports.



Note: Any amendments required to the generated supply orders can be effected by maintaining the Purchase Order (via Purchase Management) or Distribution Order (via Distribution Order option).

Network Run Selection Screen



Select the Network Run option.

This screen enables you to select the network to be evaluated.

```
DR042          HW - Handy Wholesalers Ltd      User GALBRAIJ  24/10/95
Network Run                                         15:40:50

Enter Network Code...?... █

This Run will do the following :-
- Evaluate DC Demand, allowing Full Regeneration,
  Net Change or Selective Run
- Create Purchase Orders
- Create Distribution Orders
- Run Full Regeneration for Centre

F3=Exit  F4=Prompt

05-36  SF  MW  KS  IM  II  PLYM400A PED171S1
```

Fields:

Network Code

A valid code, as defined to DRP via Network Maintenance.



Press **Enter** to display the Network Run Options Screen.

Network Run Options Screen



This screen is displayed when you have entered a valid Network Code into the Network Run Selection Screen.

It enables selection criteria to be entered and a DRP processing run submitted for the selected network.

```

DR002                HW - Handy Wholesalers Ltd                USER GALBRAIJ    24/10/95
                                                              15:45:19

DRP Network Run Selection

      Network..... N1    Northern region

      DRP run type...  1    1=Full regeneration
                           2=Net change
                           3=Selective

-----

Enter:   Current date..... 241095
         Overdue days.....  1
         Time fence days....  1
         End date..... 311095
         Include forecasts..  3    (1=Sales, 2=Stock building, 3=Both,
                                   0=Neither, Blank=As per item)

-----
F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions  F19=Print last run details

      08-33      SF      MW      KS      IM      II  PLYM400A PED171S1
  
```

Fields:

Network

Code from previous screen.

Description

From network details.

DRP Run Type

Specifies the type of DRP run to be processed. There are three types of DRP run as follows:

1 - Full Regeneration. All items are re-planned.

2 - Net Change. A subset of items are re-planned on the basis of unscheduled changes in the supply, demand, stock or replenishment parameters of items since those items were last planned for the network or centre. Changes in supply, demand, stock or replenishment parameters set 'triggers', some or all of which may be selected for processing by pressing **F14=Review Specification** when net change has been specified as the Run Type.

3 - Selective. A subset of items are re-planned on the basis of a selection of ranges of items, DRP Planners, Minor Item Groups, Cost/Usage Elements and/or

Preferred Suppliers. These ranges are entered by pressing **F14=Review Specification** after selective processing has been specified as the run type.

Current Date

This defaults to today's date. It is used in conjunction with 'overdue days' to establish the start date for the DRP run. Start date is calculated as follows:

Start Date=Current Date - Overdue Days.

Overdue Days

Specifies the number of days prior to the current date within which the application will still include outstanding supply and demand orders (excluding forecasts).

Time Fence Days

Specifies the number of days forward from the current date of the DRP run during which the plan remains frozen. Any supply suggestions required with this period are set for action on the first working day after the time fence. Enter the number of time fence days to apply to all items in this DRP run. If the entry is blank or zero, time fences will be calculated at item level (defined through Distribution Item Master Maintenance)

End Date

Specifies the last date to be considered by the planning run. Defaults to the end date of the previous run.

Include Forecasts

Specifies the type of forecast(s) which will be considered by the planning run. Valid values are as follows:

- 1 - Include sales forecast only.
- 2 - Include stock level forecasts only.
- 3 - Include both sales and stock level forecasts.
- 0 - Exclude all forecasts - only consider actual demand.
- Blank - As per item.

Each item is considered separately, with forecasts included or excluded on the basis of specification in Distribution Item Master Maintenance.

Functions:

F14

Review Specifications

F16

Restrict Extractions

F19

Print last Run Details



When all details are entered and validated, the regeneration plan batch job may be submitted by pressing **F8=Submit**.



If, however, the specified run type is net change or selective, further details relating to these run types should be entered. This is achieved by pressing **F14=Review Specification**.

Network Run Net Change Trigger Selection Screen (Option 2)



This screen is displayed when you enter option '2' - 'Net Change' on the Network Run Option Screen.

It displays net change selections for the last net change processing run for the selected network and allows maintenance of these details for the current run.

Net change details can be entered for each DC in the selected network. Each time you press **Enter**, if all the details are valid, the next DC in the network is displayed. When details have been entered for all DCs in the network, the run options screen is re displayed.

```

DR002                HW - Handy Wholesalers Ltd                USER GALBRAIJ    24/10/95
                                                              15:45:19

DRP Network Run Selection

      Network..... N1 Northern region
Net Change Trigger Selection
      DC..... C1 Scotland

Sel Trigger Description                Unprocessed Quantity to
Reason                               Triggers    Process
- 01 Forecast vs Actual Comparison.      0          0
- 02 Forecast Generation.                2          0
- 03 Forecast Maintenance.               0          0
- 04 Distribution Item Master.            2          0
- 05 Unplanned Inventory Transactions.    0          0
- 06 Requisition Maintenance.            0          0
- 07 Unplanned Issue or Receipt.         0          0
- 08 Purchase Order Maintenance.         0          0
- 09 Order Maintenance.                  0          0

1=Select All 2=Select with Limit
F3=Exit F12=Previous F18=Select All
11-05  S2  MW  KS  IM  II  PLYM400A PED171S1
  
```

Fields:

Network

Displays the code and description of the network for which net change run details are being maintained.

DC

Displays the code and description of each DC in the Network, one at a time.

Sel

Select Net Change Triggers to process for this reason code as follows:

- 1 - To select all triggers to process for this reason code, or
- 2 - To select a particular quantity of triggers to process for this reason code.

Trigger Reason

Displays the trigger reason code as defined in DRP Net Change Trigger Reason Maintenance.

Description

Displays the trigger reason code description as defined in DRP Net Change Trigger Reason Maintenance.

Unprocessed Triggers

Displays the number of triggers currently set for this reason code.

Quantity to Process

Specify the number of unprocessed triggers to be processed for this reason code in the DRP Net Change run. Do not enter a value in this field if all triggers have been selected to be processed for this reason code.



As an alternative to individually selecting reason codes and quantities to process, you can select all unprocessed triggers for All Reason Codes by pressing **F18=Select All**.

Functions:

F18

Select All



Press **Enter** to return to the Network Run Options Screen.

Network Run Review Specification Selection Criteria Screen (F14)



This screen is displayed when you take
F14=Review Specification on the Network Run
Options Screen.

It displays selections for the last selective processing run for the network and
allows maintenance of these details for the current run.

Selection details can be entered for each DC in the selected network. Each time
you press **Enter**, if all the details are valid, the next DC in the network is
displayed. When details have been entered for all DCs in the network, the run
options screen is re-displayed.

DR002 HW - Handy Wholesalers Ltd USER GALBRAIJ 24/10/95 16:26:34

DRP Network Run Selection

Network..... N1 Northern region

Enter Selection Criteria

DC..... C1 Scotland

Item.....?.. B101 to C101

Planner.....?.. P01 to PC01

Item Group.....?.. SWB to SWS

Value/Usage Class..... to

Preferred Supplier.?.. CD01 to

F4=Prompt F12=Previous

20-41 S2 MW KS IM II PLYM400A PED171S1

Fields:

Network

Displays the code and description of the network for which net change run details
are being maintained.

DC

Displays the code and description of each DC associated with the Network, one
at a time.

Item

Optionally enter a range of items to be selected for re-planning.

Planner

Optionally enter a range of DRP Planners. Only those items defined to DRP
Planners within this range will be selected.

Item Group

Optionally enter a range of Inventory Minor Item Groups. Only those items defined to Inventory Minor Item Groups within this range will be selected.

Value/Usage Class

Optionally enter a range of Inventory Values/Usage Classes. Only those items with Value/Usage Classes within this range will be selected.

Preferred Supplier

Optionally enter a range of Preferred Suppliers. Only those items with preferred suppliers within this range will be selected. (Preferred Suppliers are defined in Item/Stockroom Maintenance in Inventory Management).



Press **Enter** to return to the Network Run Options Screen.

Network Run Restrict Order Extractions Screen (F16)



This screen is displayed when you press
F16=Restrict Extractions from the Network Run
Options Screen.

It allows selection of which purchase orders will be extracted for Drinks DRP processing and is used to control processing efficiency of DRP runs.

```

DR002          HW - Handy Wholesalers Ltd          USER GALBRAIJ  24/10/95
                                                    16:34:45
DRP Network Run Selection
  Network...
  DRP run t

  Restrict Order Extractions for Run
  Exclude Unconfirmed Quantities
  on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)
  Exclude Confirmed Purchase Orders
  (Outstanding, GI, Inspection).... 0 (1=Yes, 0=No)
  F12=Previous

Enter:  Current date..... 241095
        Overdue days..... 1
        Time fence days... 1
        End date..... 311095
        Include forecasts.. 3 (1=Sales, 2=Stock building, 3=Both,
                               0=Neither, Blank=As per item)

F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions  F19=Print last run details

07-62  SF  HW  KS  IM  II  PLYM400A PED171S1
  
```

Fields:



The following exclusions may be applied:

Unconfirmed Quantities on Scheduled Purchase Orders

0 - To extract all scheduled purchase order quantities whether confirmed or not. The System will assign unscheduled order quantities to the last planning period in the DRP run.

1 - To exclude unconfirmed order quantities from scheduled orders, the effect of reducing data extraction and supply processing.

Confirmed Purchase Orders (Outstanding, GI, Inspection)

0 - To include all purchase order quantities for processing.

1 - To exclude all purchase orders from processing. This applies particularly where there is no local purchasing at the DC.



Press **Enter** to update exclusion criteria and
return to the Network Run Options Screen.

Distribution Order Entry



4/DDP

A Distribution Order controls the movement of goods between two stockrooms in a single company. For most of its processing cycle, a Distribution order is managed using functions in the Drinks Sales Order Processing or Drinks Warehousing applications.

Each stockroom is assigned to a particular customer, known as the internal customer, using Drinks Distribution Requirements Planning customer maintenance. The Distribution Order is created with a 'from' and a 'to' stockroom, and a sales order number is allocated. The order number and the internal customer associated with the 'to' stockroom are used to process the order through the allocate, generate pick list and confirm assembly stages.

After confirm assembly, the confirm shipment receipt procedure receives the stock into the 'to' stockroom and updates the stock balance. Order entry identifies the order as a Distribution Order and no invoice will be printed.

Manually entered Distribution Orders will be taken into account in the distribution planning runs.



Note: System 21 recognises orders created using this option as Sales Transfer Orders.

You can create Production Transfer Orders, to control the movement of goods between stockrooms in a production environment, using the System 21 Production Applications.

Third Party Bonded Stockrooms

Where DRP is to be used for transfer from an owned bonded stockroom and a third party bonded stockroom, and vice versa the correct bond movements and calculations will be made for the owned bonded stockroom.

For example, transfer from owned Bonded stockroom to a third party bond:

- Confirm Assembly will create stock movements, rotation entry and bond processing occurs for the outgoing transaction, to correctly record that goods have been despatched from a bonded stockroom. The delivery type (to other bonds) will determine that duty need not be calculated or paid as the transfer is to another bond.
- Confirm Shipment receipt is used to record the inbound transaction to the third party bond. In this case Bond processing is not invoked, because the third party is responsible for satisfying Bond requirements.

Where DRP is to be used to transfer goods from a third party bond to an owned bond:

- Confirm assembly will generate inventory movements only, but no bond processing will be carried out.

- Confirm shipment receipt to the owned bond will call bond programs to allow the input of bond details and the generation of rotation numbers for the receipt.

Where DRP is to be used to transfer goods from a Third Party Stockroom to a Duty paid stockroom, no bond processing is required and no bond movements will be made.



Note: Stock counting programs will not allow stock adjustments to be made for Bonded Stockrooms that are identified as Third Party, for stock reconciliation purposes.

Distribution Order Entry Transfer Selection Screen



Select the Distribution Order Entry option.

This screen allows selection of the despatching and receiving distribution stores and specification of the required despatch date. If a number of Distribution Orders are created sequentially the system displays details of the previous order created.

DR300	HW - Handy Wholesalers Ltd	User GALBRAIJ	24/10/95 16:40:01
Distribution Order Entry			
From Stockroom.....?.. █			
To Stockroom.....?.. _			
Despatch due date..... 24/10/95			
F3=Exit F4=Prompt			
05-32  HW KS IM II PLYM400A PED171S1			

Fields:

From Stockroom

Enter the stockroom from which the distribution order is to be sourced.

To Stockroom

Enter the stockroom in to which the distribution order is to be received.

Despatch Due Date

Enter the date on which the distribution order is due for despatch - defaults to the current date.



Press **Enter** to display the Distribution Order Entry Delivery Address Override Screen.

Distribution Order Entry Delivery Address Override Screen



This screen is displayed when you have entered valid selection details into the Transfer Selection Screen and allows an override to the delivery name and address that appears on the despatch note.

DR300	HW - Handy Wholesalers Ltd	User PGMR1	24/06/97 14:38:39
Distribution Order Entry			
From Stockroom.....	E1	Central Depot Empties	
To Stockroom.....	E2	Eastern Depot Empties	
Despatch due date.....	24/06/97		
Internal Customer.....	C004	001	
Order Reference			
Order subtype.....?	0	Domestic	
Delivery name and address:			
Royal Station Hotel (Lounge Bar)			
London Road			
Evesham			
Worcs			
WR12 7QA			
F3=Exit F4=Prompt F12=Previous F14=Additional Details			
F21=Internal Text			
10-32	SA	MW KS CL IM DM II	EDN400A KB PET087S1

Fields:

From Stockroom

From previous screen.

To Stockroom

From previous screen.

Despatch Due Date

From previous screen.

Internal Customer

The internal customer which has been set via customer maintenance for the 'to' stockroom.

Order Reference

Enter the customer's order reference or purchase order number. This is mandatory if the customer sales information condition of order reference is set to '1'.

Order Subtype

Enter the order subtype. These are user controlled and defined in the inventory descriptions file 'ORST'.



Note: The VAT code on the description file indicates whether or not it is an import order and therefore different payment terms may apply.

Delivery Name and Address Details

Enter the delivery name and address to appear on the pick/despatch notes for the distribution order. This is defaulted to the delivery address defined to the Internal customer for the order. To change the delivery address for this order, overtype the displayed details.

Functions:

F14

Additional Details.

F21

Internal Text.

F22

External Text.



Press **Enter** to display the Distribution Order
Entry Line Entry Screen.

Distribution Order Entry Additional Details Screen (F14)



This screen is displayed when you have pressed **F14=Additional Details** on the Distribution Order Entry Delivery Address Override Screen.

IN760	HW - Handy Wholesalers Ltd	User PGMR1	24/06/97 14:39:09
-------	----------------------------	------------	----------------------

Distribution Order Entry - Additional Details

Status code.....?.. **1**

Original requested ship date... 0/00/00

Latest requested ship date..... 0/00/00 [used as @ despatch pricing date]

Terms/Freight type.....?..

F.O.B. Code.....?..

Ship via/Carrier.....?..

Invoice number.....

Container type.....?..

Vessel name (main).....

Vessel name (feeder)...

Port of loading.....?..

Port of entry.....?..

Sailing date..... 0/00/00 ETA..... 0/00/00

F3=Exit F4=Prompt F8=Update F12=Previous F14=Business Entities

6-36 **SA** MW KS CL IM DM II EDN400A KB PET087S1

Fields:

Status Code

Enter the current status code for the shipment. This is validated against inventory description 'OSTS'.

Original Requested Ship Date

Enter the date the shipment was originally requested for shipment.

Latest Requested Ship Date

This date is used for invoice pricing.

If the order is 'price at despatch', and this date is entered, then it is used as the date for pricing and discounting purposes. If it is blank then the despatch date is used.

If the order is 'price at order' then the order date is used and this date is agreed.

Terms / Freight Type

Enter the terms / freight code. This is validated against inventory description 'FRTY'.

FOB Code

Enter the Free On Board code. This is validated against inventory description 'FOBC'

Ship Via Carrier

Enter the carrier code to be used for shipping. If Transport Planning is in use then this is validated against carriers defined in Transport Planning, otherwise it must be a valid supplier.

Invoice Number

Enter the invoice number.

Container Type

Enter the code for the container type used. This is validated against inventory description 'CNTD'.

Vessel Name (Main)

Enter the primary vessel name.

Vessel Type (Feeder)

Enter the vessel type.

Port Of Loading

Enter code for the loading port. This is validated against inventory description 'PORT'.

Port Of Entry

Enter the port of entry code. This is validated against inventory description 'PORT'.

Sailing Date

Enter the scheduled sailing date.

ETA

Enter the estimated time of arrival.

Function:

F14

Business Entities.



Press **Enter** to validate the entries and display
Distribution Order Entry Additional Detail Screen
2.

Distribution Order Entry Additional Detail Screen 2



This screen is displayed when you have pressed **Enter** on the Distribution Order Entry Additional Detail Screen 1.

IN760	DK - QA Drinks	User GBJBARW2	24/06/97 15:21:06
Order Amendment - Additional Details			
Container number.....			
Container seal number.....			
Commercial invoice date...	<u>0/00/00</u>		
Bill of lading number.....			
Bill of lading date.....	<u>0/00/00</u>		
Actual arrival date.....	<u>0/00/00</u>		
Ready for pickup date.....	<u>0/00/00</u>		
Freight invoice number.....			
Freight invoice date.....	<u>0/00/00</u>		
F3=Exit F8=Update F12=Previous F14=Business Entities			
6-31 SA MW KS CL IM DM II KENB20A KB PET087S1			

Fields:



Note: These are all memo fields and are not used for processing within the system.

Container Number

Enter the container number.

Container Seal Number

Enter the container seal number.

Commercial Invoice Date

The suppliers invoice date.

Bill of Lading Number

Enter the bill of lading number allocated.

Bill of Lading Date

Enter the bill of lading date.

Actual Arrival Date

Enter the actual arrival date.

Ready for Pickup Date

Enter the date the shipment is ready for collection by the customer.

Freight Invoice Number

Enter the freight invoice number.

Freight Invoice Date

Enter the freight invoice date.

Function:

F14

Business Entities.



Press **F8=Update** the save any changes you have made.

Distribution Order Entry Business Entities Screen



This screen is displayed when you have pressed **F14=Business Entities** on either of the two Distribution Order Entry Additional Details Screens.

IN760	Drinks US System Test Company (U1)	User PGMR2	9/07/97 11:50:25
-------	------------------------------------	------------	---------------------

Distribution Order Entry - Business entities attached to order

Type	Identifier	
- CB Customers broker	CB0001	Debbie O'Brien Entity Name CB0001
- FW Forwarder	FW0001	deb entity name FW0001
- NP Notify party	NP0001	deb entity name NP0001
- ST Ship to	NORTH	Northern Off licenses

1=Change, 4=Delete

☐ -

F3=Exit F4=Prompt F5=Reset to defaults F8=Update F12=Previous

21-5 **SP** MW KS CL IM DM II KENB20A KB PET087S1

Fields:

Type

Enter a code for the type of business entity. This is validated against inventory description 'ENCD'.

Identifier

Enter a code for the business entity.

Functions

F5

This resets to the defaults defined for the Supplier and order subtype.



Press **F8=Update** to save any changes to file.

Distribution Order Entry Internal and External Text Window



These screens are displayed when you press **F21=Internal Text** or **F22=External Text** on the Distribution Order Entry Customer Defaults Screen respectively.

You can attach text to an order, either for external or internal documentation. The text is limited to three lines.

Where text has been established at delivery sequence level, such text automatically becomes the external text for sales orders raised against the delivery sequence.

To add comments press **F21=Internal Text** or **F22=External Text** - a window is overlaid for entry of the required text.



*Note: The text lines do not automatically wrap text, therefore, if you wish to continue on another line, press the **Field Exit** key.*

Any existing text may be amended. Enter the external/internal text as required. While the window does not provide full text editing, lines may be added and/or deleted.

Distribution Order Entry Order Line Entry Screen



This screen is displayed when you press **Enter** on the Distribution Order Entry Delivery Address Override Screen and allows entry of Distribution Order lines.

If the despatch date is within the time fence and sufficient stock exists in inventory, the line is automatically allocated. Otherwise, the quantity will be shown in reverse image as unallocated.

DR320	HW - Handy Wholesalers Ltd	USER PGMR1	24/06/97
			14:49:25
Distribution Order Entry			
From Stockroom.... 01 Central Depot (BEERS)		Due Date.. 24/06/97	
To Stockroom..... 02 Central Depot (W&S)			
Item/			
Description	Despatch Due	Receipt Due	Quantity UOM
- B101	24/06/97	24/06/97	10 CA
Buzzard Lager 12x440ml can			Weight/
			Cube
			59.8000
			52.8000
1=Amend. 2=Int Text. 3=Ext Text. 4=Delete. 6=Avail. 8=Force Alloc. 9=Dealloc			
Item?... Qty... Dsp. 24/06/97 Rcpt. 0/00/00			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart			
F23=Control Totals			
21-11	SA	MW	KS CL IM DM II
EDN400A		KB	PET087S1

Fields:

From Stockroom

From previous screen.

To Stockroom

From previous screen.

Despatch Due Date

From previous screen.

Selection Options

The following options are available for existing order lines, by entering the option number against the appropriate line:

- 1 - Amend.
- 2 - Internal Text.
- 3 - External Text.

4 - Delete.

6 - Available.

8 - Force Allocate.

9 - Deallocate.



The following details can be entered.

Item

Enter a valid inventory item. the item must be defined to both the from and to stockrooms for the order. A prompt is available on valid inventory Items.

Quantity

Enter or amend the quantity for the order line, in the appropriate Unit of Measure.

Dsp.

This date defaults to the due date from the previous screen, but can be overridden.

Rcpt.

This date, if left blank, is calculated as the date of receipt at the 'to' stockroom - based on the item lead time for the 'to' stockroom - alternatively, a date may be entered manually.



Note: Despatch and receipt dates need not both be entered. As long as one is entered, the other can be calculated based on the lead time at the 'to' stockroom. Warning messages are issued if the despatch date is calculated as being in the past, or both dates are entered and insufficient lead time is allowed, although both can be overridden.

Functions:

F15

Restart.

F23

Control Totals. This shows the order totals for load planning purposes.



Press **F8=Update** to save any changes you have made.

Distribution Order Entry Control Totals (F23)



This screen is displayed when you have pressed **F23=Control Totals** on the Distribution Order Entry Order Line Entry Screen.

This screen displays the order totals for load planning purposes.

```

PR320          HW - Handy Wholesalers Ltd          USER PGMR1          24/06/97
                                           14:49:25

Distribution Order Entry

From Stockroom.... 01 Central Depot (BEERS)          Due Date.. 24/06/97
To Stockroom..... 02 Central Depot (W&S)

Item/
Description      Despatch Due  Receipt Due    Quantity UOM          Weight/
- B101           24/06/97    24/06/97       10        CA          Cube
  Buzzard Lager 12x440ml can                          59.8000
                                           52.8000

Total stock/issue units..      10 /      0
Total weight.....              59.8000
Total cube.....                 52.8000

1=Amend. 2=Int Text. 3=Ext Text. 4=Delete. 6=Avail. 8=Force Alloc. 9=Dealloc
Item?...      Qty...      Dsp. 24/06/97 Rcpt. 0/00/00

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart
F23=Control Totals

1-1      SA      MW      KS      CL      IM      DM      II      EDN400A      KB      PET087S1
  
```

Fields:

Total Stock / Issue Units

The total number of stock and issue units for the order.



Note: The totals add high units and low units separately, for example:

If item 1 is 12 bottles / case, item 2 is 6 bottles / case, and item 3 is 3 cases / pallet.

Order for item 1 = 3/11, item 2 = 2/5, and item 3 = 7/2.

Control total 12/18.

*If the low units add up to more than 999 then **** is displayed.*

Total Weight

The total weight of the order.

The total weight = quantity in issue units * weight per selling unit (from the item master).

Total Cube

The total cubage of the order.

Total cube = number of stock units * volume per stocking unit (from the item master). Where:

The number of stock units = high units ordered (+1 if any issue units ordered).

E.g. order 6/1 (i.e. 6 cases 1 bottle), then the cube will be 7*volume per stocking unit.



Press **F12=Previous** to return to the Distribution
Order Entry Line Entry Screen

Distribution Order Amendment



5/DDP

This function allows the entry of an existing Distribution Order number for amendment. Order header or line details can be amended depending on the option chosen. If the order number is not known, an enquiry is available on valid Distribution Orders by internal customer. A prompt is available for valid Customers.



Note: You can only use this option to amend Sales Transfer Orders created using the Distribution Order Entry option.

You must use the System 21 Production Applications to amend Production Transfer Orders.

Distribution Order Selection Screen



Select the Distribution Order Amendment option.

DR310	HW - Handy Wholesalers Ltd	User PGMR1	24/06/97 14:52:12
Distribution Order Amendment			
Order Number..... 0001269			
Amend header or lines... █ (1=Header, 2=Lines, 3=Additional Detail)			
If Order number is not known, enter an Internal Customer to enquire on Orders by Customer.			
Internal Customer....?... _____			
F3=Exit F4=Prompt			
7-29 SA MW KS CL IM DM II EDN400A KB PET087S1			

Fields:

Order Number

Enter an existing Distribution Order number to amend the details for that order.

Amend Header or Lines

Specify whether, for the Distribution Order entered, the order header or line details are to be amended.

Valid options are as follows:

- 1 - Amend Header level details.
- 2 - Amend Line level details.
- 3 - Amend Additional Details.

Internal Customer for Enquiry

If the correct order number is unknown, enter a valid internal customer to enquire on Distribution Orders by Customer. A prompt is available for valid customers.



Note: If using the Prompt facility, make sure that you only select from valid DRP (dummy) Customers.



Press **Enter** to display the Distribution Order Amendments Header or Lines Screen, depending on what you have selected.

Distribution Order Amendments Header Details Amendment Screen (Option 1)



This screen is displayed when you press **Enter** on the Distribution Order Amendments Selection Screen if you have selected option '1' on the Amend header or lines field and allows an override to the delivery name and address details that appear on the despatch note.

```

DR310          HW - Handy Wholesalers Ltd          User PGMR1          24/06/97
                                                    14:53:19

Distribution Order Amendment

From Stockroom..... 01 Central Depot (BEERS)
To Stockroom..... 02 Central Depot (W&S)

Despatch due date..... 24/06/97
Internal Customer..... DRP01 001
Order Reference ..... new
Order subtype.....?.. 0 Domestic

Delivery name and address:

Stockroom 01 DRP customer
Manchester
_____
_____
_____
M12 12Q

F3=Exit F4=Prompt F12=Previous F21=Internal Text F22=External Text

8-32  SA MW KS CL IM DM II EDN400A KB PET087S1

```

Fields:

From Stockroom

Stockroom of the order, from where the goods will be supplied.

To Stockroom

Stockroom of the order, where the goods will be received.

Despatch Due Date

Current despatch date for order lines which have not be overridden - this can be overridden with a different valid calendar date.

Internal Customer

The internal customer code which has been defined against the 'to' stockroom.

Order Reference

Enter the customer's order reference or purchase order number. This is mandatory if the customer sales information condition of order reference is set to '1'.

Order Subtype

Enter the order subtype as follows:

0 - Domestic.

1 - Direct Import.

2 - Import.

These are user controlled and defined in the inventory descriptions file 'ORST'.



Note: The VAT code on the description file indicates whether or not it is an import order and therefore different payment terms may apply.

Delivery Name and Address Details

The delivery name and address to appear on the pick/despatch notes for the distribution order. To change the delivery address for this order, type over the displayed details.

Functions:

F21

Internal Text

F22

External Text



Press **Enter** to update the altered details and re-display the Distribution Order Amendment Screen.

Distribution Order Amendment Order Line Amendment Screen (Option 2)



This screen is displayed when you press **Enter** on the Distribution Order Amendment Selection Screen if you have selected option '2' on the Amend header or lines field and allows entry, by Distribution Order Line, of an inventory item and a quantity.

If the despatch date is within the time fence and sufficient stock exists in inventory, the line is automatically allocated. Otherwise, the quantity is shown in reverse image as unallocated.

DR320	HW - Handy Wholesalers Ltd	USER PGMR1	24/06/97 14:54:27
Distribution Order Amendment			
From Stockroom.... 01 Central Depot (BEERS)		Due Date.. 24/06/97	
To Stockroom..... 02 Central Depot (W&S)			
Item/ Description	Despatch Due	Receipt Due	Quantity UOM Weight/ Cube
- B101 Buzzard Lager 12x440ml can	24/06/97	24/06/97	10 CA 59.8000 52.8000
1=Amend, 2=Int Text, 3=Ext Text, 4=Delete, 6=Avail, 8=Force Alloc, 9=Dealloc			
Item?... Qty... Dsp. 24/06/97 Rcpt. 0/00/00			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart			
F23=Control Totals			
21-11	SA	MW KS CL IM DM II	EDN400A KB PET087S1

Fields:

From Stockroom

From previous screen.

To Stockroom

From previous screen.

(Despatch) Due Date

From previous screen.

Selection Options

The following options are available for existing order lines:

1 - Order Line Amendment. This option retrieves the Order Line details for amendment.

2 - Internal Text Entry / Amendment. Text can be entered to be associated with the order line for internal use only.

3 - External Text Entry / Amendment. Text can be entered to be printed for the order line on external documentation for the order.

4 - Order line deletion. This option deletes a previously entered Line from the order. Any existing allocations will be reversed.

6 - Stock Availability Enquiry. This option calls an enquiry showing the current stock level details for the Item at the From Stockroom and details of the current supply/demand situation.

8 - Force Allocation. This option allows a partially or wholly unallocated order line to be fully allocated. Allocation will take place regardless of the available stock quantity, allocation priority or allocation time fence.

9 - Force Deallocation. This option allows a fully or partially allocated order line to be fully deallocated.



The following details can be entered:

Item

Enter a valid inventory item. The item must be defined to both the from and to stockrooms for the order. A prompt is available on valid Inventory Items.

Quantity

Enter or amend the quantity for the order line, in dual unit format.

Dsp.

This date defaults to the due date of the previous screen, but can be overridden.

Rcpt.

If left blank this date is calculated as the date of receipt at the 'to' stockroom - based on the lead time for the 'to' stockroom - alternatively, a date may be entered manually.



Note: Despatch and receipt dates need not both be entered. As long as one is entered, the other can be calculated based on the lead time at the 'to' stockroom. Warning messages are issued if the despatch date is calculated as being in the past, or if both dates are entered and insufficient lead time is allowed, although both can be overridden.

Functions:

F15

Restart



Press **F8=Update** to save any changes to file.

Distribution Order Amendment Entry Control Totals (F23)



This screen is displayed when you have pressed **F23=Control Totals** on the Distribution Order Amendment Order Line Entry Screen.

PR320	HW - Handy Wholesalers Ltd	USER PGMR1	24/06/97 14:54:27
Distribution Order Amendment			
From Stockroom.... 01 Central Depot (BEERS)		Due Date... 24/06/97	
To Stockroom..... 02 Central Depot (W&S)			
Item/ Description	Despatch Due	Receipt Due	Quantity UOM
B101	24/06/97	24/06/97	10 CA
Buzzard Lager 12x440ml can			
			Weight/ Cube
			59.8000
			52.8000
Total stock/issue units.. 10 / 0 Total weight..... 59.8000 Total cube..... 52.8000			
1=Amend. 2=Int Text. 3=Ext Text. 4=Delete. 6=Avail. 8=Force Alloc. 9=Dealloc Item?... Qty... Dsp. 24/06/97 Rcpt. 0/00/00			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart F23=Control Totals			
1-1	SA	MW KS CL IM DM II	EDN400A KB PET087S1

Fields:

Total Stock / Issue Units

The total number of stock and issue units for the order.



Note: The totals add high units and low units separately, for example:

If item 1 is 12 bottles / case, item 2 is 6 bottles / case, and item 3 is 3 cases / pallet.

Order for item 1 = 3/11, item 2 = 2/5, and item 3 = 7/2.

Control total 12/18.

*If the low units add up to more than 999 then **** is displayed.*

Total Weight

The total weight of the order.

The total weight = quantity in issue units * weight per selling unit (from the item master).

Total Cube

The total cubage of the order.

Total cube = number of stock units * volume per stocking unit (from the item master). Where:

The number of stock units = high units ordered (+1 if any issue units ordered).

E.g. order 6/1 (i.e. 6 cases 1 bottle), then the cube will be 7*volume per stocking unit.



Press **F12=Previous** to return to the Distribution
Order Amendment Line Entry Screen

Distribution Order Amendment Additional Details Screen 1



This screen is displayed when you press **Enter** on the Distribution Order Amendment Selection Screen if you have selected option '3' on the Amend header or lines field and allows amendment, by Distribution Order Line, of additional details.

IN760	HW - Handy Wholesalers Ltd	User PGMR1	24/06/97 14:55:48
-------	----------------------------	------------	----------------------

Distribution Order Amend - Additional Details

Status code.....?..

Original requested ship date... 0/00/00

Latest requested ship date..... 0/00/00 [used as @ despatch pricing date]

Terms/Freight type.....?..

F.O.B. Code.....?..

Ship via/Carrier.....?..

Invoice number.....

Container type.....?..

Vessel name (main).....

Vessel name (feeder)....

Port of loading.....?..

Port of entry.....?..

Sailing date..... 0/00/00 ETA..... 0/00/00

F3=Exit F4=Prompt F8=Update F12=Previous F14=Business Entities

6-36 SA MW KS CL IM DM II EDN400A KB PET087S1

Fields:

Status Code

Enter the current status code for the shipment. This is validated against inventory description 'OSTS'.

Original Requested Ship Date

Enter the date the shipment was originally requested for shipment.

Latest Requested Ship Date

This date is used for invoice pricing.

If the order is 'price at despatch', and this date is entered, then it is used as the date for pricing and discounting purposes. If it is blank then the despatch date is used.

If the order is 'price at order' then the order date is used and this date is agreed.

Terms / Freight Type

Enter the terms / freight code. This is validated against inventory description 'FRTY'.

FOB Code

Enter the Free On Board code. This is validated against inventory description 'FOBC'.

Ship Via Carrier

Enter the carrier code to be used for shipping. If Transport Planning is in use then this is validated against carriers defined in Transport Planning, otherwise it must be a valid supplier.

Invoice Number

Enter the invoice number.

Container Type

Enter the code for the container type used. This is validated against inventory description 'CNTD'.

Vessel Name (Main)

Enter the primary vessel name.

Vessel Type (Feeder)

Enter the vessel type.

Port Of Loading

Enter code for the loading port. This is validated against inventory description 'PORT'.

Port Of Entry

Enter the port of entry code. This is validated against inventory description 'PORT'.

Sailing Date

Enter the scheduled sailing date.

ETA

Enter the estimated time of arrival date.

Function:**F14**

Business Entities.



Press **Enter** to validate the entries and display Distribution Order Amendment Additional Detail Screen 2.

Distribution Order Amendment Additional Detail Screen 2



This screen is displayed when you have pressed **Enter** on the Distribution Order Amendment Additional Detail Screen 1.

IN760	DK - QA Drinks	User GBJBARW2	24/06/97 15:21:06
Order Amendment - Additional Details			
Container number.....			
Container seal number.....			
Commercial invoice date...	<u>0/00/00</u>		
Bill of lading number.....			
Bill of lading date.....	<u>0/00/00</u>		
Actual arrival date.....	<u>0/00/00</u>		
Ready for pickup date.....	<u>0/00/00</u>		
Freight invoice number.....			
Freight invoice date.....	<u>0/00/00</u>		
F3=Exit F8=Update F12=Previous F14=Business Entities			
6-31 SA MW KS CL IM DM II KENB20A KB PET087S1			

Fields:



Note: These are all memo fields and are not used for processing within the system.

Container Number

Enter the container number.

Container Seal Number

Enter the container seal number.

Commercial Invoice Date

The suppliers invoice date.

Bill of Lading Number

Enter the bill of lading number allocated.

Bill of Lading Date

Enter the bill of lading date.

Actual Arrival Date

Enter the actual arrival date.

Ready for Pickup Date

Enter the date the shipment is ready for collection by the customer.

Freight Invoice Number

Enter the freight invoice number.

Freight Invoice Date

Enter the freight invoice date.

Function:

F14

Business Entities.



Press **F8=Update** the save any changes you have made.

Distribution Order Amendment Business Entities Screen (F14)



This screen is displayed when you have pressed **F14=Business Entities** on either of the two Distribution Order Amendment Additional Details Screens.

IN760	Drinks US System Test Company (U1)	User PGMR2	9/07/97 11:50:25
-------	------------------------------------	------------	---------------------

Distribution Order Entry - Business entities attached to order

Type	Identifier	
- CB Customers broker	CB0001	Debbie O'Brien Entity Name CB0001
- FW Forwarder	FW0001	deb entity name FW0001
- NP Notify party	NP0001	deb entity name NP0001
- ST Ship to	NORTH	Northern Off licenses

1=Change, 4=Delete

F3=Exit F4=Prompt F5=Reset to defaults F8=Update F12=Previous

21-5 SA MW KS CL IM DM II KENB20A KB PET087S1

Fields:

Type

Enter a code for the type of business entity. This is validated against inventory description 'ENCD'.

Identifier

Enter a code for the business entity.

Functions:

F5

This resets to the defaults defined for the Supplier and order subtype.



Press **F8=Update** to save any changes to file.

Confirm Shipment Receipt



6/DDP

Once an order has been created via Drinks DRP, and it has been picked by order number and assembled via Drinks SOP, this function allows receipt of shipment to be confirmed, which maintains the in-transit balances, and updates the stock and costs at the receiving stockroom.

Confirm Shipment Receipt Selection Screen



Select the Confirm Shipment Receipt option.

This screen allows confirmation of receipt, at a stockroom, of stock in transit from another stockroom within the company. Inventory records are updated appropriately for the receiving Stockroom. If this Stockroom is defined to the Drinks Warehousing application, the appropriate details must be entered (within this option), to include the Items in the 'put-away' processing of Warehousing.

DR039	HW - Handy Wholesalers Ltd	User GALBRAIJ	24/10/95 17:24:00
Confirm Shipment Receipt			
Enter Stockrooms and/or specific Distribution Order number:			
From Stockroom.....?.. 01			
To Stockroom.....?.. 02			
Distribution Order Number... 0001246			
F3=Exit F4=Prompt			
11-39	SA	HW KS IM	II PLYM400A PED171S1

Fields:

From Stockroom

Enter the code of the stockroom from which the goods were despatched. A prompt is available on valid inventory stockrooms.

To Stockroom

Enter the code of the receiving stockroom for the goods in-transit. A prompt is available for valid inventory stockrooms.

Order Number

Optionally specify a particular Distribution Order which is to be received, or leave blank to display all Distribution Order lines for supply from the specified 'from' stockroom to the specified 'to' stockroom.



Note: If a specific order number is entered, the 'from' and 'to' stockroom combination is not required.



Note: If no items are found in the DRP In-transit file for the specified selection criteria, an error message is displayed on this screen, otherwise the Items In-Transit screen is displayed.



Note: With regard to cost of sales for duty suspended stockrooms despatching to duty paid customers, and movement values for stock transfers between duty suspended and duty paid stockrooms. Actual duty rather than notional duty may be used to uplift cost of sales and inventory movement values, providing more accurate costs, where FIFO, Average, or latest costing are used. This is controlled by a flag on the Sales Order Processing company profile.

The system will ensure that goods are not received in the target stockroom until the appropriate cost uplift has been performed upon the in-transit costs.

Where the SOP company profile indicates cost uplift by 'actual' duty paid is required and no such uplift has occurred a message will be issued. To proceed with the receipt confirmation will result in the generation of inaccurate costs at the target stockroom.



Press **Enter** to display the Confirm Shipment Receipt Items In-Transit Screen.

Confirm Shipment Receipt Items In-transit Screen



This screen is displayed when you have made valid entries and pressed **Enter** on the Confirm Shipment Receipt Selection Screen

This screen enables you to select the items within the received shipment from the list of items in-transit displayed. The items are added to this in-transit list when a Distribution Order is confirmed as despatched from a stockroom in Drinks Sales Order Processing or Drinks Warehousing, Confirmation of Assembly.

If the received quantity entered is less than the quantity despatched, the received quantity is booked-in to stock but the balances remain in-transit. The assumption is that the remainder of the item will be confirmed, via this option, once it is received.

The whole of the quantity despatched must be confirmed as received, via this screen, before it is removed from the in-transit list. As explained above, this may be done across more than one shipment receipt.

If there are any discrepancies, these must be handled by an Inventory Stock adjustment, (with an appropriate reason code) after the quantity has been fully received here.

The physical and available stocks are updated by the receiving quantity, and the in-transit quantity down dated accordingly. This is done by the batch job. Batch and FIFO cost records are maintained where appropriate. These receipts are also updated in the stock history and movement files as Transfer In quantities. These should agree with the corresponding Transfer Out details added at confirmation of despatch of the distribution order at the centre.

Drinks Warehousing Interface.

For items controlled within a stockroom defined to Warehousing, the appropriate details must be entered. By entering 1 against received lines and pressing **F13**, the Warehousing Details screen is displayed for pack and expiry date details to be entered.

DR039	DK - QA Drinks	User GBJBAIMS	4/03/98 11:46:01					
Confirm Shipment Receipt								
From Stockroom... AX DRP 1		From AX Main centre						
To Stockroom..... AY DRP 2		To... AY Southern centre						
Order..... 0001356								
Select all Lines to Update (0=No, 1=Yes) 2								
Sel	Date	Order	Lin Item	SR	Quantity	UoM	Var	Lot no.
-	4/03/98	0001356	1	BD1200	AY	10/0		
1=Select order line for receipt. 2=Additional detail. 3=Lot								
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous								

Fields:

Select All Lines To Update

0 - No.

1 - Yes.

If you set this field to 1, all lines for the selection criteria are updated. Otherwise, only the lines selected with a 1 in the Sel field, when the job is submitted, are updated.

Sel

1 - Select Order Line for receipt. Select a line to be received or to amend receipt details.

2 - Additional Details. Display the screen to Confirm Shipment Receipt Items Additional Details Screen, to enter additional details about the shipment.

3 - Lot. Display the Lot Header Maintenance Window to enter details about the lot. This is only required for items that are Lot, Batch or Serial controlled.

SR (Receiving Stockroom)

The receiving stockroom for the item. This must be defined to the item in inventory management. The receiving stockroom defaults to the 'to' stockroom for the displayed distribution order but can be overridden with any valid stockroom for the item.



Note: When Bond is in use, restrictions will apply based on the Bond status of the Stockrooms.

Quantity

Specifies the actual quantity received, in dual units. This must not exceed the quantity despatched.

Var

If receiving into a Bonded Stockroom, enter the Item Variant number.



Use **F8=Update** to update the details, after amendment by overtyping the lines.

Confirm Shipment Receipt Items Additional Details Screen 1 (Option 2)



This screen is displayed when you enter 2
against an order line in the Confirm Shipment
Receipt Items In-transit Screen and press **Enter**.

You use this screen to

IN760	DK - QA Drinks	User GBUA1MS	4/03/98 11:49:57
Confirm Shipment Receipt - Additional Details			
Status code.....?..	█		
Original requested ship date...	0/00/00		
Latest requested ship date.....	0/00/00 (used as @ despatch pricing date)		
Terms/Freight type.....?..	—		
F.O.B. Code.....?..	—		
Ship via/Carrier.....?..	_____		
Invoice number.....	_____		
Container type.....?..	—		
Vessel name (main)....	_____		
Vessel name (feeder)...	_____		
Port of loading.....?..	_____		
Port of entry.....?..	_____		
Sailing date.....	0/00/00	ETA.....	0/00/00
F3=Exit F4=Prompt F8=Update F12=Previous F14=Business Entities			

Fields:

Status Code

Enter the current status code for the shipment. This is validated against inventory description OSTs.

Original Requested Ship Date

Enter the date the shipment was originally requested for shipment.

Latest Requested Ship Date

This date is used for invoice pricing.

If the order is price at despatch, and this date is entered, then it is used as the date for pricing and discounting purposes. If it is blank then the despatch date is used.

If the order is price at order then the order date is used and this date is agreed.

Terms / Freight Type

Enter the terms / freight code. This is validated against inventory description FRTY.

FOB Code

Enter the Free On Board code. This is validated against inventory description FOBC

Ship Via Carrier

Enter the carrier code to be used for shipping. If Transport Planning is in use then this is validated against carriers defined in Transport Planning, otherwise it must be a valid supplier.

Invoice Number

Enter the invoice number.

Container Type

Enter the code for the container type used. This is validated against inventory description CNTD.

Vessel Name (Main)

Enter the primary vessel name.

Vessel Type (Feeder)

Enter the vessel type.

Port Of Loading

Enter code for the loading port. This is validated against inventory description 'PORT.

Port Of Entry

Enter the port of entry code. This is validated against inventory description 'PORT.

Sailing Date

Enter the scheduled sailing date.

ETA

Enter the estimated time of arrival date.

Function:

F14

Business Entities. Display the Business Entities Screen.



Press **Enter** to validate the entries and go to Confirm Shipment Receipt Items Additional Details Screen 2.

Confirm Shipment Receipt Items Additional Details Screen 2



This screen is displayed when you have pressed
Enter on the Confirm Shipment Receipt Items
Additional Details Screen 1.

IN760	DK - QA Drinks	User: GBJBARW2	24/06/97 15:21:06
Order Amendment - Additional Details			
Container number.....			
Container seal number.....			
Commercial invoice date...	<u>0/00/00</u>		
Bill of lading number.....			
Bill of lading date.....	<u>0/00/00</u>		
Actual arrival date.....	<u>0/00/00</u>		
Ready for pickup date.....	<u>0/00/00</u>		
Freight invoice number.....			
Freight invoice date.....	<u>0/00/00</u>		
F3=Exit F8=Update F12=Previous F14=Business Entities			
6-31 SA MW KS CL IM DM II KENB20A KB PET087S1			

Fields:



*Note: These are all memo fields and are not
used for processing within the system.*

Container Number

Enter the container number.

Container Seal Number

Enter the container seal number.

Commercial Invoice Date

The suppliers invoice date.

Bill of Lading Number

Enter the bill of lading number allocated.

Bill of Lading Date

Enter the bill of lading date.

Actual Arrival Date

Enter the actual arrival date.

Ready for Pickup Date

Enter the date the shipment is ready for collection by the customer.

Freight Invoice Number

Enter the freight invoice number.

Freight Invoice Date

Enter the freight invoice date.

Function:

F14

Business Entities. Display the Business Entities Screen.



Press **F8=Update** the save any changes you have made.

Confirm Shipment Business Entities Screen (F14)



This screen is displayed when you have pressed **F14=Business Entities** on either of the two Confirm Shipment Receipt Items Additional Details Screens.

IN760	DK - QA Drinks	User GBJBARW2	24/06/97 14:05:38
NOT BONDED To Home Use with Deferment Order Entry - Business entities attached to order			
<u>Type</u>	<u>Identifier</u>		
There are no records on file			
 			
F3=Exit F4=Prompt F5=Reset to defaults F8=Update F12=Previous			
21-5 SA MW KS CL IM DM II KENB20A KB PET087S1			

Fields:

Type

Enter a code for the type of business entity. This is validated against inventory description ENCD.

Identifier

Enter a code for the business entity.



Press **F8=Update** to save any changes to file.

Lot Header Maintenance Window (Option 3)



This window is displayed when you enter 3 against an order line in the Confirm Shipment Receipt Items In-transit Screen and press **Enter**.

You use this window to enter details about the lot you are receiving.

This window is only displayed when you are receiving lot, batch or serial controlled items.

DR039	DK - QA Drinks	User GBJBA1MS	4/03/98 13:09:06
Confirm Shipment Receipt			
Lot Header Maintenance			
From Stockn	Item.....	BD1201	
To Stocknoo	Lot reference.....	LOT001	
Order.....			
Sel Date	Production date.....	4/03/98	
2 4/03/98	Expiry date.....	4/03/99	
	First available date....	4/03/98	
	Last available date.....	4/03/99	
	Stock status.....?	—	
	Reason code.....?	—	
	Suppliers lot ref.....	_____	
F12=Previous F4=Prompt F24=More keys			
1=Select order line for receipt. 2=Additional detail. 3=Lot			
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous			

Fields:

Item

The item entered on the previous screen is displayed for information only.

Lot Reference

The lot reference entered on the previous screen is displayed for information only.

Production Date

The production date for the lot. This defaults to the current date but can be changed here.

Expiry Date

Enter the date on which the lot expires.

First Available Date

Enter the first available date for the lot. This may be later than the production date if there is a maturation period for the item.

Last Available Date

The last date on which the lot is available for use.

Stock Status

Optionally enter a status for the stock. This is taken from Inventory Description Major Type STKS.

Reason Code

Optionally enter a movement reason for the stock. This is taken from Inventory Description Major Type MOVR.



Enter the required details and press **Enter** to return to the Confirm Shipment Receipt Items In-transit Screen.

DRP Shipments Received Report Screen

This option is used to provide an audit of shipments receipts.

Fields:

Frequency

One for each shipment receipt confirmed in DRP (by the receiving to stockroom).

New Page

Overflow.

New Distribution Order Number.

Totals

None.



*Note: Reports all lines confirmed as received
within this transaction.*

This report is produced automatically by the batch program which processes the confirmed lines.