

-
-
-
-
-

Chapter 10

Sales Commissions



Sales Commissions Overview

You use System 21 Sales Commissions to calculate and report on sales commission payments based on goods invoiced.

Sales Commissions provides the ability to:

- Define sales commission schemes used to calculate commission payments.
- Define the relationships between salespeople, product groups and sales regions, used to calculate commission payments.
- Capture sales person information at invoice and credit note header and order line level.
- Calculate and report on commission payments due.

Sales Commissions reports are generated to allow commission payments to be made. In the present release, Sales Commissions does not post transactions to System 21 financial applications.

Salesperson information is recorded against the following types of order:

- Sales (Conversational Order Entry, Telesales, or EDI)
- Uplift Orders
- Tagged Goods Return

For tagged goods return orders salesperson information is held for memo purposes only on the order bank where no credit is to be created for the return i.e. a non yellow tag return.

The salesperson details recorded against a sales order, uplift or tagged goods return are available for you to override manually at any time throughout an order's life cycle, via order amendment.



Note: Where the salesperson information recorded against an order that has already resulted in the creation of a sales invoice is changed then the changes made at order level are not reflected on any pre-existing invoices for that order.

The ability to record salesperson information against a sales order line is also added to the following functions:

- Interactive Confirmation of Assembly
- Interactive Confirmation of Delivery
- Miscellaneous Invoice and Credit Note Entry

The salesperson information recorded on the order bank is replicated onto any documents that are created as a result of the despatch of an order.

When a credit note is based on a pre-existing invoice then all salesperson information for the credit note is taken, by default, from the invoice upon which it is based. Otherwise salesperson information for any new document is derived using the same rules as used in the order taking process.

Prerequisites

Before you can set up and use sales commission schemes you need to set up the following:

- In Drinks Sales Order Processing Company Profile, the following parameters that control sales commission payments:
 - The customer attribute used as the sales commission region.
 - The item attributes used to define the item product group for sales commission purposes.
 - The default time at which sales commission schemes become due for payment.



The time at which sales commission schemes become due for payment can be overridden for specific customers when you set up customer sales details in Drinks Sales Order Processing Customer Maintenance.

- In Inventory Descriptions, major type TN, sales people.
- The Sales Commissions Calendars you will use.



Note: Qualification, attainment and paid commissions are in the base currency of the Accounts Receivable company.



Note: The values of containers are not included in sales commission calculations.



Note: The system only includes a sales commission scheme in one payment run. If any qualifying documents are entered after the payment run, they are reported as exceptions but the commission payments will not be adjusted.

Setting up Sales Commission Schemes

When you have set up all of the prerequisites, you can set up sales commission schemes.

You need to set up the following:

- Sales Commission Scheme details, where you specify:
 - the item attributes to use to include items in product groups for sales commission purposes.
 - the qualification criteria and calculation basis used to calculate commission payments.
 - to which sales regions the schemes apply.
- Sales Management Details, where you associate salespeople with particular product groups within sales regions, for specified time periods. This determines which sales person is paid commission, by default, for the sales of a product group within a region over the specified time.

- Manager / Salesperson Relationships, where you set up sales teams by defining relationships between salespeople and managers.
- By not establishing any sales management details you can ensure that sales commissions are paid, by default, to the salesperson taking an order.

Calculating Commission Payments

To be able to calculate the commission due to a salesperson, information has to be recorded against every invoice and credit note, hereafter referred to as documents, that is generated within Drinks Sales Order Processing.

The values held at document header level, set up in Sales Management Details, are the default values for all lines on the document. Any values held at document line level will be specific overrides for that particular line of a document.

At sales order header level the salesperson defaults to the value specified at customer delivery point level. This value is available for override by the user.

At sales order line level salesperson information is derived from the Sales Management Details file, based on the sales region into which the selected customer delivery point falls and the product group into which the item ordered falls.

Where no default salesperson information is available for a particular customer delivery point and item combination then all sales commission information for that order line will default to blank, indicating that the sales commission for the line is to be paid to the salesperson specified on the order header. By not establishing any sales management details you can ensure that sales commissions are paid, by default, to the salesperson defined against the customer, in Customer Maintenance.

Again salesperson information held at order line level is available for you to override manually.

Sales Commission Scheme Maintenance

1... 1/DOC **2...**

You use this option to set up and maintain sales commission payment schemes.

You can set up schemes to calculate commission payments for individual salespersons or sales managers.

For individual schemes you specify:

- Which item attributes to use to include items in the scheme.
- The qualification criteria and calculation basis used to calculate commission payments for the scheme.
- Which sales regions the scheme applies to.

Before you can set up these schemes, you need to set up:

- In Drinks Sales Order Processing Company Profile, the parameters that control sales commission payments.
- The Sales Commissions Calendars.
- In Inventory Descriptions, major type TN, sales people.

Sales Commission Scheme Maintenance Screen 1



Take the Sales Commission Scheme
Maintenance option

You use this screen to enter the number of the Sales Commission Scheme. This can be a new number to create a new scheme, or an existing number to maintain an existing scheme.

You can base a new scheme on an existing one. This is useful if you want to create a new scheme by just changing one or two parameters of an existing scheme, such as the start and end dates.

```
D0008                DK - QA Drinks                User GBJBA1MS    26/01/98
                                                14:06:05

Sales Commission Scheme Maintenance

Scheme number.....?.. █
Based on.....?..

F3=Exit  F4=Prompt

5-27    SA  MW    KS  CL  IM  DM  II    STUD140  KB  ST0672S1
```

Fields:

Scheme Number

Enter the number of the sales commission scheme.

Based On

Enter the number of the sales commission scheme to base a new scheme on.
This field is optional.



Enter the required values and press **Enter** to
display Sales Commission Scheme Maintenance
Screen 2.

Sales Commission Scheme Maintenance Screen 2



This screen is displayed when you enter a scheme number in Sales Commission Scheme Maintenance Screen 1 and press **Enter**.

You use this screen to enter information about the scheme. You can specify:

- Whether or not this is a sales manager's scheme.
- Which item attributes to use to include items in the scheme.
- Which sales regions the scheme applies to.

D0008		DK - QA Drinks		User GBJBA1MS		26/01/98	
						14:08:42	
Sales Commission Scheme Maintenance							
Scheme number.....		SCH01		Sales Scheme 01			
Start date.....		26/01/98					
End date.....		0/00/00					
Managers scheme?.....		☐		0=No, 1=Yes			
Product group							
Item type.....?		-					
Item class.....?		-					
Item group major.....?		-					
Item group minor.....?		-					
Division.....?		-					
Sub division.....?		-					
Sales region:							
All sales regions?.....		-		0=No, 1=Yes			
Sales region.....?		-					
F3=Exit F4=Prompt F12=Previous							
9-27 SA MW KS CL IM DM II STUD140 KB ST0672S1							

Fields:

Scheme Number

The number of the sales commission scheme entered in the previous screen.

(Untitled)

Enter a name for the sales commission scheme.

Start Date

Enter the start date for the scheme. Qualifying documents on or after this date will be included for payment in the scheme.

End Date

Enter the end date for the scheme. Qualifying documents dated before or up to this date will be included for payment in the scheme.

Managers Scheme?

0 - No. This is not a managers scheme. Commission payments are only generated for the salesperson defined to this scheme.

1 - Yes. This is a managers scheme. Commission payments are generated for the manager defined to this scheme.

Product Group

Specify which item attributes to use to group items into a product group for this scheme. You do not have to make entries in all of these fields. If for example, you only enter a value in the Item Type field, the scheme will include sales of all items of this type in sales commission payments.



Note: Only Product Group fields defined on the Sales Order Processing Company Profile Sales Commission Parameters Window, appear in this screen.

Item Type

Enter the Item Type to include in this scheme.

Item Class

Enter the Item Class to include in this scheme.

Item Group Major

Enter the Item Group Major to include in this scheme.

Item Group Minor

Enter the Item Group Minor to include in this scheme.

Division

Enter the Division to include in this scheme.

Sub-Division

Enter the Sub-Division to include in this scheme.

Sales region

Specify the sales region to which this scheme applies.

All Sales Regions?

0 - No. This scheme only applies to the sales region entered in the Sales region field.

1 - Yes. This scheme applies to all sales regions.

Sales Region

Enter the sales region this scheme applies to. Leave this field blank if this scheme applies to all sales regions.



Enter the required information into the screen and press **Enter** to validate the data, then press **Enter** again to display Sales Commission Scheme Maintenance Screen 3.

Sales Commission Scheme Maintenance Screen 3



This screen is displayed when you enter information into Sales Commission Scheme Maintenance Screen 2 and press **Enter**.

You use this screen to define the qualification criteria and calculation basis for the scheme.

DO008	DK - QA Drinks	User GBJBA1MS	26/01/98 14:11:40
Sales Commission Scheme Maintenance			
Scheme number.....	SCH01	Sales Scheme 01	
Start date.....	26/01/98		
End date.....	28/01/98		
Qualification period....	☐ 0=None, 1=Week, 2=Period		
Qualifying break unit....	☐ 1=Sales value, 2=Item quantity		
Quantity type.....	☐ 1=Physical quantity, 2=Equivalent cases		
	☐ 3=Barrelage, 4=Literage		
Calculation basis.....	☐ 1=Sales value, 2=Pro-rata		
F3=Exit F12=Previous F17=Exclusions			
9-27	SA	MW	KS CL IM DM II STUD140 KB ST0672S1

Fields:

Scheme Number

The number of the sales commission scheme entered in Sales Commission Scheme Maintenance Screen 1.

(Untitled)

The name of the sales commission scheme entered in the previous screen.

Start Date

The start date of the scheme entered in the previous screen.

End Date

The end date of the scheme entered in the previous screen.

Qualification Period (first field)

There are two fields associated with the qualification period. If you specify a Period in the first field, you must also enter a valid Calendar Code in the (Untitled) field. Calendars are set up using the Calendar Maintenance option.

Enter the qualification period for this scheme.

0 - None. Payments for this scheme are generated once only on the end date of the scheme.

1 - Week. Payments for this scheme are generated weekly, on the week end date.

2 - Period. Payments for this scheme are generated once for each calendar period, on the period end date.

Qualification Period (second field)

Enter the Calendar Code to take date information from, for this scheme.

Leave this field blank if you enter 0 or 1 in the Qualification Period field.

Qualifying Break Unit

Specify which unit commission qualification breaks are based on.

1 - Sales Value. Commission qualification breaks are based on the value sales made.

2 - Item Quantity. Commission qualification breaks are based on the quantity of items sold.

Quantity Type

Specify the quantity type used to calculate sales commission payments.

1 - Physical Quantity. Sales commission payments are based on the physical quantity sold.

2 - Equivalent Cases. Sales commission payments are based on the equivalent cases sold.

3 - Barrelage. Sales commission payments are based on the barrelage sold.

4 - Litreage. Sales commission payments are based on the litreage sold.

5 - Gallonage. (US only) Sales commission payments are based on the gallonage sold.

Calculation Basis

Specify the basis on which sales commission payments are calculated.

1 - Sales commission payments are calculated on a percentage of the value of sales made.

If you set this field to 1, the next screen to be displayed is Qualification Limits Screen - Sales Value.

2 - Pro Rata. Sales commission payments are calculated as a fixed amount per quantity type sold. For example, if the Quantity Type is set to equivalent cases, commission could be paid at £1.00 per equivalent case.

If you set this field to 2, the next screen to be displayed is Qualification Limits Screen - Pro Rata.

Functions:

F17

Exclusions. Display the Sales Commissions - Exclusions Window. You use this to specify which types of document and document lines to exclude from qualification totals.



Enter the required information into the screen and press **Enter** to display the Qualification Limits Screen.

If you enter 1 in the Calculation Basis field, Qualification Limits Screen - Sales Value is displayed.

If you enter 2 in the Calculation Basis field, Qualification Limits Screen - Pro Rata is displayed.

Commission payments are calculated up to this value. If you enter all 9s there will be no limit on the amount of commission payable on this scheme.

Commission payments

Commission is calculated according to the values of these two fields. If, for example, the first Qualifying Break Unit is set to 10.000 Cases, Commission % is set to 5.00, then commission is calculated at the rate of 5.00% for sales quantities up to 10 cases.

You can enter a maximum of 10 qualifying breaks for commission payments.

(Qualifying Break Unit)

The title of this field defaults to the setting of the Qualifying Break Unit field on Sales Commission Scheme Maintenance Screen 3. This can be any one of the following:

- Sales Value
- Physical Quantity

You can enter up to 10 qualifying breaks for commission payments.

Commission %

Enter the percentage commission to be paid for sales totals up to the corresponding Qualifying Break Unit.

Functions:

F17

Exclusions. Display the Sales Commissions - Exclusions Window. You use this to specify which types of document and document lines to exclude from qualification totals and the values upon which commissions are calculated.



Press **F8=Update** to save the information you have entered.

Qualification Limits Screen - Pro Rata

 This screen is displayed if, on Sales Commission Scheme Maintenance Screen 3, you enter 2 in the Calculation Basis field and press **Enter**.

You use this screen to maintain a sales commission scheme whose calculation basis is set to Pro Rata. Commission qualification breaks are based on the quantity of items sold.

D0008
DK - QA Drinks
User GBJBA1MS
29/01/98
10:11:48

Sales Commission Scheme Maintenance-Qualification Limits

Scheme number..... SCH02
Scheme 02

Maximum commission..... 999999999999.99

Physical quantity	Commission value	
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000
000	00	per 00000

F3=Exit
F8=Update
F12=Previous
F17=Exclusions

9-27
SA
MW
KS
CL
IM
DM
II
STUD140
KB
ST0672S1

Fields:

Scheme Number

The number of the sales commission scheme entered in the Sales Commission Scheme Maintenance Screen 1.

(Untitled)

The name of the sales commission scheme entered in Sales Commission Scheme Maintenance Screen 2.

Start Date

The start date of the scheme entered in Sales Commission Scheme Maintenance Screen 2.

End Date

The end date of the scheme entered in Sales Commission Scheme Maintenance Screen 2.

Maximum Commission

Enter the maximum amount, in base currency, of commission that can be paid on this scheme.

Commission payments are calculated up to this value. If you enter all 9s there will be no limit on the amount of commission payable.

Commission payments

Commission is calculated according to the values of these three fields. If, for example, the first Qualifying Break Unit is set to 100.000 Cases, Commission Value is set to 5.00 and per is set to 10, then commission is calculated at the rate of £5.00 per 10 cases for sales quantities up to 100 cases.

You can enter a maximum of 10 qualifying breaks for commission payments.

(Qualifying Break Unit)

The title of this field defaults to the setting of the Qualifying Break Unit field on Sales Commission Scheme Maintenance Screen 3. This can be any one of the following:

- Sales Value
- Physical Quantity

Commission Value

Enter the commission value, in base currency, to be paid for sales totals up to the corresponding Qualifying Break Unit.

per

Enter the amount of the corresponding Qualifying Break Unit on which sales commission is paid.

Functions

F17

Exclusions. Display the Sales Commissions - Exclusions Window. You use this to specify which types of document and document lines to exclude from qualification totals and the values upon which commissions are calculated.



Press **F8=Update** to save the information you have entered.

Sales Commissions - Exclusions Window (F17)



This screen is displayed when you press **F17=Exclusions** in the Sales Commission Scheme Maintenance Screen 3 and the Qualification Limits Screen.

You use this screen to specify which types of document and document lines to exclude from sales commission qualification totals.

D0008 DK - QA Drinks User: GBJBA1MS 2/02/98

Sales Commissions-Exclusions

Specify the types of document and/or the portions of a document line sales value that are to be excluded from the qualification totals and the values upon which commissions are calculated.

The following are valid for any of the listed exclusion values:

- 0=Include in both
- 1=Exclude from qualification
- 2=Exclude from value upon which commissions are calculated
- 3=Exclude from both

Tagged goods returns.....	0	Value Added Tax.....	0
Uplift orders.....	0	Duty.....	0
Miscellaneous credit notes...	0	Cost of Sales.....	0
Managers own sales.....	0	Discounts.....	0
Split packs.....	0		

F12=Previous

F3=Exit F11=Delete F12=Previous F17=Exclusions

15-41 SA MW KS CL IM DM II STUD140 KB ST0672S1

Fields:

You can enter any of the following values against any of the listed documents and document lines.

- 0 - Include in both.
- 1 - Exclude from qualification.
- 2 - Exclude from value upon which commissions are calculated.
- 3 - Exclude from both.



Note: The default value for these fields is. This means that all of these documents will be included in commission calculations unless they are excluded here.

You can include or exclude any of the following, by entering one of these options.

Tagged Goods Returns

Uplift Orders

Miscellaneous Credit Notes

Managers Own Sales

Split Packs

Value Added Tax

Duty

State and City Taxes

Cost of Sales

Discounts



Press **F8=Update** to save the information you have entered.

Sales Management Details Maintenance



2/DOC

You use this option to associate a salesperson with a particular product group within a sales region, for a specified time period. This determines which sales person is paid commission, by default, for the sales of this product group within this region over the specified time.

Date control allows past, present and future relationships to be held on the system. There is a facility to purge expired sales management details from the system.



Note: Only a single salesperson can be associated with a particular product group and sales region over a given time period.

System 21 maintains an audit trail of changes made to the Sales Management Details.

Sales Management Details Maintenance Screen 1



Select the Sales Management Details
Maintenance option

You use this screen to:

- Enter the Sales Region for which you want to associate a salesperson with a product group.
- Purge the system of expired sales management details.

```
0E029                DK - QA Drinks                USER GBJBA1MS    29/01/98
                                                    11:21:22

Sales Management Details Maintenance

Sales region..... █
Purge expired details
  upto and including..... 0/00/00

F3=Exit

5-30  SA  MW  KS  CL  TM  DM  II  STUD140  KB  ST0672S1
```

Fields:

Sales Region

Enter the Sales Region for which you want to associate a salesperson with a product group.

Purge Expired Details Up To And Including

Enter the date up to which you want to purge the system of expired sales management details. If you do not want to purge the system, leave this field set to 0/00/00.



Enter the required information and press **Enter**
to display Sales Management Details Screen 2

Sales Management Details Screen 2



This screen is displayed when you enter information into Sales Management Details Maintenance Screen 1 and press **Enter**.

You use this screen to view and maintain existing associations between salespeople and product groups.

0E029		DK - QA Drinks		USER GBJBA1MS		29/01/98	
						11:24:24	
Sales Management Details Maintenance							
Sales region..... DIV							
Sel	Product group	Start date	End date	Sales person	Negotiator	Agent	Sub agent
1	/BB/ / /	0/00/00	99/99/99	1			
							Bottom
1=Amend. 4=Delete							
F3=Exit F6=Add F12=Previous							
9-4 SA MW KS CL IM DM II STUD140 KB ST0672S1							

Fields:

Sel

1 - Amend. Amend the details of an existing association between a salesperson and a product group.

4 - Delete. Delete an existing association between a salesperson and a product group.

Functions:

F6

Add. Displays the Sales Management Details Addition Window to add a new association between a salesperson and a product group, to the system.



Press **F3=Exit** to return to the previous screen

Sales Management Details Addition Window (F6)



This screen is displayed when you press **F6=Add** in Sales Management Details Screen 2

You use this screen to:

- Add a new association between a salesperson and a product group, to the system.
- Amend existing associations between salespeople and product groups.

```

0EQ29                      DK - QA Drinks                      USER GBJBA1MS    29/01/98
                                                                11:24:
Sa  Sales Management Details - Addition
S   Product group:
S   Item type.....?..  █
    Item class.....?..  _
    Item group major...?.. _
    Item group minor...?.. _
    Division.....?..  _
    Sub-division.....?.. _

    Salesperson.....?..  _
    Negotiator.....?..  _
    Agent.....?..  _
    Sub-agent.....?..  _

    Start date.....  0/00/00
    End date.....  99/99/99

    F4=Prompt  F8=Update                      F12=Previous  om
    1=Amend  4=Delete
    F3=Exit  F6=Add  F12=Previous

    6-33  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
  
```

Fields:

Product Group

Specify which item attributes to use to group items into a product group for this salesperson within the specified region.

Only items whose Inventory records match all of the entries in these fields will be selected for this scheme. If, for example, you leave a field blank, only item records which have this field blank will be included in this scheme.



Note: Only Product Group fields defined on the Sales Order Processing Company Profile Sales Commission Parameters Window, will appear on this screen.

For example, you might only include the Item Type field on this screen. In this case sales commissions for all items of the type you specify here will, within the specified Sales Region, be associated, by default, with the salesperson specified on this screen.

Item Type

Enter the Item Type to include.

Item Class

Enter the Item Class to include.

Item Group Major

Enter the Item Group Major to include.

Item Group Minor

Enter the Item Group Minor to.

Division

Enter the Division to include.

Sub-Division

Enter the Sub-Division to include.

Salesperson

Enter the salesperson who will receive commission payments, by default, for this product group within this region.

Negotiator

This field is reserved for future development. You can enter data here, but no commissions will be calculated for the Negotiator.

Agent

This field is reserved for future development. You can enter data here, but no commissions will be calculated for the Agent.

Sub-agent

This field is reserved for future development. You can enter data here, but no commissions will be calculated for the Sub-agent.

Start Date

Enter the start date of the time period for which these details are effective.

End Date

Enter the end date of the time period for which these details are effective.



Note: If you set this date to 99/99/99, the scheme will run indefinitely.



Press **F8=Update** to save the information you have entered.

Manager / Salesperson Relationships Maintenance

1...
2... 3/DOC

You use this option to define relationships between salespeople and managers, for sales commission purposes. In this way sales teams can be defined.

Commission payments for any salespeople defined to this manager are included in the manager's commission calculations.

You can only set up a single level of structure for these relationships for the purposes of sales commission payments.

Any one salesperson can only report to a single manager, within a given time period.

A manager may report to another manager. Where such a relationship is not established it is possible to optionally include the commission for sales made personally by the manager in the total sales for that team. You specify how commission from a manager's own sales are treated in the Sales Commission Scheme Maintenance - Exclusions Window. Any sales made by a manager who reports to another manager are automatically included in the sales commission calculations for the highest level manager, as if a single level of structure existed.

Manager / Salesperson Relationship Maintenance Screen 1



Select the Manager / Salesperson Relationship
Maintenance option

You use this screen to:

- Enter the Manager you want to establish a manager / salesperson relationship for.
- Purge the system of expired manager / salesperson relationship details.

```
D0019          DK - QA Drinks          User GBJBA1MS   29/01/98
                                     11:34:53

Manager/Salesperson Relationship

Manager.....?...  █

Purge expired relationships
  upto and including.....  0/00/00

F3=Exit  F4=Prompt

5-41  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
```

Fields:

Manager

Enter the salesperson you want to define as the manager of a manager / salesperson relationship.



*This is a salesperson ID taken from the Inventory
Description major type TN. This salesperson is
defined as a manager for the purposes of this
option.*

Purge Expired Relationships Up To And Including

Enter the date up to which you want to purge the system of expired manager / salesperson relationships. If you do not want to purge the system, leave this field set to 0/00/00.



Enter the required information and press **Enter**
to display Manager / Salesperson Relationship
Maintenance Screen 2

Manager / Salesperson Relationship Maintenance Screen 2



This screen is displayed when you enter information into Manager / Salesperson Relationship Maintenance Screen 1 and press **Enter**.

You use this screen to view and maintain existing manager / salesperson relationships.

D0019		DK - QA Drinks		User GBJBA1MS		29/01/98	
						11:38:15	
Manager/Salesperson Relationship							
Manager.....		10		D. Johns			
Sel	Salesperson			Start Date	End Date		
■	2	I. Walker		1/03/98	99/99/99		
-	6	M. Dupont		1/01/98	99/99/99		
-	8	A. Parkinson		1/03/98	99/99/99		
1=Amend, 4=Delete							
F3=Exit F6=Add F12=Previous							
9-4		SA	MW	KS	CL	IM	DM II
						STUD140	KB ST0672S1

Fields:

Sel

1 - Amend. Amend an existing manager / salesperson relationship. Only the start and end dates of an existing relationship can be amended.

4 - Delete. Delete an existing manager / salesperson relationship.

Functions:

F6

Add. Displays the Add Manager Salesperson Relationship Window, to add a new manager / salesperson relationship to the system.



Press **F3=Exit** to return to the previous screen

Add Manager / Salesperson Relationship Window (F6)



This screen is displayed when you press **F6=Add**
in Manager / Salesperson Relationship
Maintenance Screen 2

You use this screen to

- Add a new manager / salesperson relationship to the system.
- Amend the start and end dates of an existing manager / salesperson relationship.

D0019 DK - QA Drinks User GBJBA1MS 29/01/98 11:38:15

Manager/Salesperson Relationship

Manager..... 10 D, Johns

Sel

1-Add Manager/Salesperson Relationship

2-Manager..... 10 D, Johns

3-Salesperson..?..

4-Start Date..... 00/00/00

5-End Date..... 99/99/99

F4=Prompt F8=Update F12=Previous

1=Amend 4=Delete

F3=Exit F6=Add F12=Previous

10-31 SA MW KS CL IM DM II STUD140 KB ST0672S1

Fields:

Manager

The manager entered in the first Manager / Salesperson Relationship Maintenance screen.

Salesperson

Enter the salesperson for whom you want to establish a new manager / salesperson relationship, with the displayed manager.

Start Date

Enter the start date for the relationship. Sales commissions generated by this salesperson after this date will be included in commission calculations for this manager.

End Date

Enter the end date for the relationship. Sales commissions generated by this salesperson up to and including this date will be included in commission calculations for this manager.



Press **F8=Update** to save the information you have entered.

Calendar Maintenance



4/DOC

You use this procedure to define and update the calendar profiles used by Sales Commissions and Packaging Requirements.

Inventory Calendar/Year Maintenance Screen 1



Select the Calendar option

You use this screen to select the calendar you want to maintain or to enter the code for a new calendar profile.

IN850	DK - QA Drinks	User GBJBA1MS	29/01/98		
			11:48:03		
Inventory Calendar/Year Maintenance					
Sel	Code	Year	Description	Work days	Yr Start
█	AF	97	ADF 97 calendar	258	1/01/97
-	AF	98	ADF 98 calendar	258	1/01/98
-	JJ	97	1997	261	6/01/97
-	JJ	98	Jennys calendar for Sales commissions	261	5/01/98
Enter Calendar code: Year: Based on Calendar Profile:					
1=Select 6=Print					
F3=Exit					
7-4 SA MW KS CL IM DM II STUD140 KB ST0672S1					

Fields:

Sel

1 - Select, to select the calendar profile you want to maintain.

6 - Print, to print the calendar profile.

Enter Calendar Code

Enter a code for a new calendar profile.

Year

Enter the year that the new calendar profile is for.

Based on Calendar Profile

A new Calendar Profile can be based on an existing one.

Enter the code and year of the calendar profile you want to base the new profile on.



To display the Inventory Calendar/Year Maintenance Screen 2 to add a new calendar profile, enter a Calendar Code, Year and if required profile and year the calendar should be based upon.



To display the Inventory Calendar/year Maintenance Screen 2 so you can amend a calendar profile, enter 1 in the Sel field alongside the required calendar profile.

Inventory Calendar/Year Maintenance Screen 2

-  Enter 1 in the Sel field on the Inventory Calendar/Year Maintenance Screen 1 to display the Inventory Calendar/Year Maintenance Screen 2 in Amend mode.
-  Enter a Calendar Code and Year to display the Inventory Calendar/Year Maintenance Screen 2 in Add mode

You use this screen to enter details for the calendar profile you are maintaining or creating.

```

IN850                                DK - QA Drinks                User GBJBA1MS   29/01/98
                                      11:52:22

Inventory Calendar/Year Maintenance
Calendar Code/Year..... AA 98  Sales Commissions Calendar
Number of Periods per Year... 12
Normal Start Day of Week.... 1      (1=Monday ..... 7=Sunday)
Start Date of the Year..... 5/01/98

  Period Name  Days  Period Name  Days  Period Name  Days
1. January    31 23  2. February  28 20  3. March      31 22
4. April      30 21  5. May        31 23  6. June       30 21
7. July       31 22  8. August     31 23  9. Sept       30 20
10. October   31 23 11. Nov        30 22 12. December  31 21
13.           -    -

Template type to use..... 1      1=Standard Week
                                   2=Cyclic Weeks
                                   3=Period

F3=Exit  F12=Previous

4-66  SA  MW  KS  CL  TW  DM  II  STUD140  KB  ST0672S1
  
```

Fields:

Calendar Code/Year

Enter a description for the calendar profile.

Number of Periods per Year

Enter the number of periods in the year.

This can be any number in the range 1 - 13.

Normal Start Day of Week

Enter one of the following:

- 1 - Monday
- 2 - Tuesday
- 3 - Wednesday

4 - Thursday

5 - Friday

6 - Saturday

7 - Sunday.

Start Date of the Year

Enter the date that the calendar year starts.

Period Names

Enter the name of each period.

Days

Enter the number of days there are in each period.



Note: This is working and non-working days.

Template Type to Use

Enter one of the following:

1 - Standard Week, where you have the same working days each week

2 - Cyclic Week, where the working days changes over a number of weeks cycle.
You can have up to a five week cycle.

3 - Period.

Functions:

F11

Delete. Use this function to delete the selected calendar profile.



Note: This screen varies depending upon the template type you have selected.



Press **Enter** to display the Inventory
Calendar/Year Maintenance Screen 3.

Inventory Calendar/Year Maintenance

The format of this screen varies depending upon which Template Type you selected in Inventory Calendar/Year Maintenance Screen 2.

You can choose:

- 1 - Standard Week, where you have the same working days each week
- 2 - Cyclic Week, where the working days changes over a cycle of a number of weeks. You can have up to a five week cycle.
- 3 - Period, where you define a set of working days for each calendar period defined in the previous screen.

Inventory Calendar/Year Maintenance Screen 3 (Standard Week)



On the Inventory Calendar/Year Maintenance Screen 2, set the Template Type to 1 - Standard Week, then press **Enter** to display the Inventory Calendar/Year Maintenance Screen 3 (Standard Week).

You use this screen to enter the working days in a standard week. You can also enter up to five alternative week templates, with effective From and To dates.

IN850	DK - QA Drinks	User GBJBA1MS	29/01/98 11:53:29
Inventory Calendar/Year Maintenance			
Calendar Code/Year.. AA 98 Sales Commissions Calendar			
Standard Weekly Template :			
M T W T F S S			
1 1 1 1 0 0 ("0" for non working day or "1" for working day)			
Enter up to five alternative week templates with effective dates :			
M T W T F S S	From Date	To Date	
-----	_____	_____	
-----	_____	_____	
-----	_____	_____	
-----	_____	_____	
-----	_____	_____	
F3=Exit F12=Previous			
9-2 SA MW KS CL IM DM II STUD140 KB ST0672S1			

Fields:

Standard Weekly Template

Set up the Standard Weeks for 1 or more weeks.

1 - Working day

0 - Non-working day



Press **Enter** to validate the data you have entered in the Inventory calendar/Year Maintenance Screen 3. Press **Enter** again to display the Inventory Calendar/Year Maintenance Screen 4.

Inventory Calendar/Year Maintenance Screen 3 (Cyclic Week)



On the Inventory Calendar/Year Maintenance Screen 2, set the Template Type to 2 - Cyclic Week, then press **Enter** to display the Inventory Calendar/Year Maintenance Screen 3 (Cyclic Week).

You use this screen to enter the working and non-working days when the pattern varies over more than one week.

IN850	DK - QA Drinks	User GBJBA1MS	29/01/98 11:53:47
Inventory Calendar/Year Maintenance			
Calendar Code/Year.. AA 98 Sales Commissions Calendar			
Cyclic Weeks Templates :			
	M T W T F S S		
1.	0 0 0 0 0 0 0	("0" for non working day or "1" for working day)	
2.	0 0 0 0 0 0 0		
3.	0 0 0 0 0 0 0		
4.	0 0 0 0 0 0 0		
5.	0 0 0 0 0 0 0		
Number of weeks... 5			
F3=Exit F12=Previous			
11-5	SA	MW	KS CL IM DM II STUD140 KB ST0672S1

Fields:

Cyclic Weeks Template

Set up Standard Weeks for 1 or more weeks

1 - Working day

0 - Non-working day

Number of Weeks

Enter the number of weeks in the cycle.



Press **Enter** to validate the data you have entered in the Inventory Calendar/Year Maintenance Screen 3. Press **Enter** again to display the Inventory Calendar/Year Maintenance Screen 4.

Inventory Calendar/Year Maintenance Screen 3 (Period)



On the Inventory Calendar/Year Maintenance Screen 2, set the Template Type to 3 - Period, then press **Enter** to display the Inventory Calendar/Year Maintenance Screen 3 (Period).

You use this screen to enter the working and non-working days in a period.

IN850	DK - QA Drinks	User GBJBA1MS	29/01/98 11:54:03
Inventory Calendar/Year Maintenance			
Calendar Code/Year.. AA 98 Sales Commissions Calendar			
Period Template for Period : 1 January			
1 2 3 4 5 6 7 8 9 0 ("0" for non working day or "1" for working day)			
0 0 0 0 0 0 0 0 0 0			
10. 0 0 0 0 0 0 0 0 0 0			
20. 0 0 0 0 0 0 0 0 0 0			
30. 0			
F3=Exit F8=Skip to holidays F12=Previous			
12-6	SA	MW	KS CL IM DM II
STUD140		KB	ST0672S1

Fields:

Period Template

Set up Standard Weeks for 1 or more weeks

1 - Working day

0 - Non-working day



Enter all working and non-working days for the current period then press **Enter** to go to the next period. Press **F12=Previous** to return to the previous period you have entered.

Functions:

F8

Skip to Holidays. Select this function to move straight to entering holiday details without having to enter the working day pattern for the period.



Press **Enter** to validate the data you have entered for the currently displayed period and go on to the next period.



When you have entered all periods for the calendar, press **Enter** again to display the Inventory Calendar/Year Maintenance Screen 4.

Inventory Calendar/Year Maintenance Screen 4



Select **F8=Skip To Holidays** on the Inventory Calendar/Year maintenance Screen 4 (period) to display the Inventory Calendar/Year Maintenance Screen 4.



Press **Enter** to validate the data you have entered in the Inventory Calendar/Year Maintenance Screen 3. Press **Enter** again to display the Inventory Calendar/Year Maintenance Screen 4.

You use this screen to define the dates of any works holidays.

IN850		DK - QA Drinks		User GBJBA1MS		29/01/98	
						11:57:08	
Inventory Calendar/Year Maintenance							
Calendar Code AA 98 Sales Commissions Calendar							
HOLIDAYS							
From	To	From	To	From	To	From	To
☐							
F3=Exit F8=Update F12=Previous							
8-2 SA MW KS CL IM DM II STUD140 KB ST0672S1							

Fields:

Holidays From

Enter the start date of the holiday.

Holidays To

Enter the end date of the holiday.



Select **F8=Update** to save the information and display the Inventory Calendar/Year Maintenance Screen.

Sales Commission Schemes Enquiries



11/DOC

You use this option to enquire on existing sales commission payment schemes.

The following information is available from this enquiry:

- If the scheme is set up to calculate commission payments for individual salespersons or sales managers.
- The item attributes used to include items in the scheme.
- The qualification criteria and calculation basis used to calculate commission payments for the scheme.
- The sales region the scheme applies to.

Sales Commission Scheme Enquiry Screen

1



Select the Sales Commission Schemes Enquiry option

You use this screen to enter the sales commission scheme to enquire on.

```
D00008          DK - QA Drinks          User GBJBA1MS  29/01/98
Sales Commission Scheme Enquiry          12:13:58
Scheme number.....?.. █

F3=Exit  F4=Prompt

5-27  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
```

Fields:

Scheme Number

Enter the scheme you want to enquire on.



Enter a sales commission scheme number and press **Enter** to display Sales Commission Scheme Enquiry Screen 2

Sales Commission Scheme Enquiry Screen 2



This screen is displayed when you enter information in Sales Commission Scheme Enquiry Screen 1 and press **Enter**

This screen displays the following information about the scheme:

- Scheme start and end dates.
- If this scheme is a managers scheme.
- Details of the Product Group and Sales Region this scheme relates to.

D0008		DK - QA Drinks		User GBJBA1MS		29/01/98	
						12:14:04	
Sales Commission Scheme Enquiry							
Scheme number.....		SCH01		Sales Scheme 01			
Start date.....		26/01/98					
End date.....		28/02/98					
Managers scheme?.....		0		0=No, 1=Yes			
Product group							
Item type.....		B		Package Beer			
Item class.....		BB		bottles			
Item group major.....				bottles			
Item group minor.....				bottles			
Division.....				bottles			
Sub division.....				bottles			
Sales region:							
All sales regions?.....		0		0=No, 1=Yes			
Sales region.....		DIV		bottles			
F3=Exit				F12=Previous			
1-1		SA		MW		KS CL IM DM II	
						STUD140 KB ST0672S1	



Press **Enter** to display Sales Commission Scheme Enquiry Screen 3

Sales Commission Scheme Enquiry Screen 3



This screen is displayed when you press **Enter** in
Sales Commission Schemes Enquiry Screen 2

This screen displays details of the qualification criteria for this scheme.

00008	DK - QA Drinks	User GBJBA1MS	29/01/98
			12:14:08
Sales Commission Scheme Enquiry			
Scheme number.....	SCH01	Sales Scheme 01	
Start date.....	26/01/98		
End date.....	28/02/98		
Qualification period....	2 AF	0=None, 1=Week, 2=Period	
Qualifying break unit...	1	1=Sales value, 2=Item quantity	
Quantity type.....	1	1=Physical quantity, 2=Equivalent cases	
		3=Barrelage, 4=Literage	
Calculation basis.....	2	1=Sales value, 2=Pro-rata	
F3=Exit F12=Previous F17=Exclusions			
1-1	SA	MW KS CL IM DM II	STUD140 KB ST0672S1



Press **F17=Exclusions** to display the Sales
Commissions Enquiry - Exclusions Window

Sales Commissions Enquiry - Exclusions Window (F17)

 This screen is displayed when you press
F17=Exclusions in the Sales Commission
Scheme Enquiry Screen 3

This window displays details of any document exclusions that relate to this
scheme.

DO0008		DK - QA Drinks		User: GBJBA1MS 29/01/98	
Sales Commissions-Exclusions					
Sales	Specify the types of document and/or the portions of a document				
Scheme	line sales value that are to be excluded from the qualification				
Start	totals and the values upon which commissions are calculated.				
End da	The following are valid for any of the listed exclusion values:				
Qualif		0=Include in both			
Qualif		1=Exclude from qualification			
Quanti		2=Exclude from value upon which			
Calcul		commissions are calculated			
		3=Exclude from both			
Tagged goods returns.....	0	Value Added Tax.....	0		
Uplift orders.....	0	Duty.....	0		
Miscellaneous credit notes...	0	Cost of Sales.....	0		
Split packs.....	0	Discounts.....	0		
F12=Previous					
F3=Exit F12=Previous F17=Exclusions					
1-1	SA	MW	KS	CL	IM DM II STUD140 KB ST0672S1

 Press **F12=Previous** to return to Sales
Commission Scheme Enquiry Screen 3

Sales Management Details Enquiries



12/DOC

You use this option to enquire on existing sales management details.

This option displays the salespeople associated with a particular product group within a sales region and which sales person is paid commission, by default, for the sales of this product group within this region.

Sales Management Details Enquiries Screen 1



Select the Sales Management Details Enquiries option

You use this screen to enter the sales region you want to enquire on.

```
0E029                DK - QA Drinks                USER GBJBA1MS    29/01/98
Sales Management Details Enquiry
Sales region.....  █

F3=Exit

5-30  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
```

Fields:

Sales Region

Enter the sales region you want to enquire on.



Enter the sales region and press **Enter** to display Sales Management Details Enquiries Screen 2

Sales Management Details Enquiries Screen 2



This screen is displayed when you enter a sales region in Sales Management Details Enquiries Screen 1 and press **Enter**

You use this screen to select and view existing sales management details.

0E029	DK - QA Drinks	USER GBJBA1MS	29/01/98
Sales Management Details Enquiry		12:14:40	
Sales region..... DIV			
Sel	Product group	Start date	End date
1	/BB/ / / /	0/00/00	99/99/99
Sales person	Negotiator	Agent	Sub agent
1			
			Bottom
1=Select			
F3=Exit F12=Previous			
9-4	SA	MW	KS CL IM DM II
STUD140		KB	ST0672S1

Fields:

Sel

1 - Select. Select the sales management details you want to enquire on.



Enter 1 in the Sel field and press **Enter** to display the Sales Management Details Window

Sales Management Details Window

- ➔ This window is displayed when you enter 1 against a set of sales management details in the Sales Management Details Enquiries Screen 2 and press **Enter**

You use this window to view the salesperson for whom sales commission payments are calculated for the displayed product group within the displayed start and end dates. These details only relate to the region entered in Sales Management Details Enquiries Screen 1.

```

PE029          DK - QA Drinks          USER GBJBA1MS  29/01/98
                                           12:14:
Sa  Sales Management Details - Enquiry
S   Product group:
S   Item type.....
S   Item class..... BB          bottles
S   Item group major.....
S   Item group minor.....
S   Division.....
S   Sub-division.....

Salesperson..... 1          Jel frezie.....X
Negotiator.....
Agent.....
Sub-agent.....

Start date..... 0/00/00
End date..... 99/99/99

F12=Previous
1=Select
F3=Exit F12=Previous
1-1  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
  
```

- ➔ Press **F12=Previous** to return to the previous screen.

Manager / Salesperson Relationships Enquiries



13/DOC

You use this option to enquire on existing manager / salesperson relationships.

This option displays the relationships between salespeople and managers, for sales commission purposes.

Manager / Salesperson Relationships Enquiries Screen 1



Select the Manager / Salesperson Relationships option

You use this screen to enter the manager you want to enquire on.

D0019	DK - QA Drinks	User GBJBA1MS	29/01/98
Manager/Salesperson Relationship		12:15:13	
Manager.....?.. █			
F3=Exit F4=Prompt			
5-41	SA	MW	KS CL IM DM II
STUD140		KB	ST0672S1



Enter a manager and press **Enter** to display
Manager / Salesperson Relationships Enquiries
Screen 2

Manager / Salesperson Relationships Enquiries Screen 2



This screen is displayed when you enter a manager in the Manager / Salesperson Relationships Enquiries Screen 1 and press **Enter**

This screen displays a list of the salespeople who are defined to this manager and the start and end dates of the manager / salesperson relationships.

D0019		DK - QA Drinks		User GBJBA1MS		29/01/98	
						12:15:13	
Manager/Salesperson Relationship							
Manager.....		10	D. Johns				
Sel	Salesperson			Start	End		
				Date	Date		
█	2	I. Walker		1/03/98	99/99/99		
-	6	M. Dupont		1/01/98	99/99/99		
-	8	A. Parkinson		1/03/98	99/99/99		
1=Select							
F3=Exit		F12=Previous					
9-4		SA	MW	KS	CL	IM	DM II
				STUD140		KB	ST0672S1

Fields:

Sel

1 - Select. Select a salesperson you want to enquire on.



Enter a 1 against a salesperson and press **Enter**

Manager / Salesperson Relationships Enquiry Window



This window is displayed when you enter a 1
against a salesperson in Manager / Salesperson
Relationships Enquiries Screen 2 and press
Enter

This screen displays details of the Manager / Salesperson Relationship selected
in the previous screen.

DO019 DK - QA Drinks User GBJBA1MS 29/01/98 12:15:13

Manager/Salesperson Relationship

Manager..... 10 D. Johns

Sel

1

—

—

Manager/Salesperson Relationship - Enquiry

Manager..... 10 D. Johns

Salesperson..... 2 I. Walker

Start Date..... 1/03/98

End Date..... 99/99/99

F12=Previous

1=Select

F3=Exit F12=Previous

1-1 SA MW KS CL IM DM II STUD140 KB ST0672S1



Press **F12=Previous** to return to the previous
screen.

Invoice Extraction and Commission Calculations

A multiple stage process is involved in the calculation and payment of sales commissions:

- Schemes for which commissions are to be paid are selected.

You can enter the date, up to and including which, invoice lines are to be extracted to the sales commission database and the schemes for which payment of sales commissions is required. All schemes can be selected in a single payment run if required.

Salesperson and manager commission schemes can be extracted and paid in the same commission payment run.

A commission scheme can only be selected for payment in one outstanding commission payment run.

- Sales information is extracted from the invoice files.

The pricing function is called. This has two purposes.

- To calculate the correct prices for all documents flagged for at despatch pricing.
- To calculate any state and city taxes applicable to all documents.

Then where schemes have not been pre-selected for payment by the user a function is invoked to select all schemes for which the next payment date lies either before or on the data extraction date specified.

Data is then extracted from the sales invoice file to the sales commission database. All document lines that meet the rules established against the selected commission schemes up to the specified date are extracted from the invoice files to the sales commissions database.

A single document line may be eligible to both a salesperson and a manager's commission scheme. Payment for the two types of scheme does not have to be made simultaneously therefore the extraction process is capable of extracting an invoice line for a manger's scheme in a payment run requested after the payment run that extracted the document details to the appropriate salesperson commission scheme.

Quantities and values relating to specific document types excluded from a scheme are not extracted to the sales commission database.

Where split case quantities are excluded then the quantities and values extracted are those relating to the whole case portion of a document line only.

All document lines are priced prior to performing this invoice extract, thus ensuring that the correct line values are extracted and any state and city tax applicable to the documents has been calculated

- The appropriate commission rates are determined, based on the qualification totals by salesperson.

Calculation of the commission values to be paid to each salesperson is performed. This process involves the calculation of qualification and attainment values by scheme qualification period based on any sales value exclusions specified against a scheme, the determination of the sales commission rate to be used based on qualification total achieved and the calculation of the commission value to be paid.

- Commission values to be paid to individual salespeople are calculated.
- Commissions are paid to the appropriate salesperson. The time at which commission becomes due for payment is determined at company profile level, but can be overridden for individual customers.

The next scheduled payment dates are calculated, for the selected schemes and these values are updated onto the appropriate scheme headers.

Sales Commission Details Extraction Screen 1



Select the Invoice Extraction and Commission Calculations option

You use this screen to:

- Enter the extraction date for sales commission schemes. All eligible documents and document lines up to and including this date are extracted from the invoice file, to the sales commission database.
- Decide whether or not to pay all schemes eligible for payment in this run.

```
D0010          DK - QA Drinks          User GBJBA1MS  29/01/98
                                           12:15:46

Sales Commission Details Extraction

Extraction date..... 29/01/98

Pay all schemes?..... _      0=No, 1=Yes

F3=Exit  F8=Submit

5-27  SA  MW  KS  CL  IM  DM  II  STUD140  KB  ST0672S1
```

Fields:

Extraction Date

Enter the extraction date. All eligible documents and document lines up to and including this date will be extracted from the invoice file, to the sales commission database.

Pay All Schemes?

0 - No. Do not extract data for all eligible schemes. Display Sales Commission Details Extraction Screen 2 for schemes to be selected.

1 - Yes. Extract data for all schemes which the next payment date lies either before or on the specified Extraction Date.



Enter the required information and press **Enter** to display Sales Commission Details Extraction Screen 2

Sales Commission Details Extraction Screen 2



This screen is displayed when you enter No in the Pay All Schemes? field on Sales Commission Details Extraction Screen 1 and press **Enter**

You use this screen to select the schemes you want to include in this commission payment run.

This option produces two reports:

1. Details the commission payments due to each salesperson and sales manager in this payment run.
2. Details any exceptions. That is, details any documents not included in the commission calculations in this payment run.

D0011		DK - QA Drinks		User: GBJBA1MS	29/01/98 12:15:56
Sales Commission Details Extraction					
Extraction date..... 29/01/98					
Sel	Scheme	Description	Payment Due	Scheme Status	
-	ADF013		10/01/98		
-	JJB1	Jerrys test scheme #1	28/12/97		
1=Select					
F3=Exit F8=Submit F15=Select all F17=Deselect all					
9-4	SA	MW	KS CL IM DM II	STUD140	KB ST0672S1

Fields:

Sel

1 - Select. Enter a 1 against a scheme to select it for inclusion in this commission payment run.

Functions:

F15

Select All. Select all displayed commission schemes for inclusion in this commission payment run.

F17

Deselect All. Deselect all displayed commission schemes from this commission payment run.



Press **F8=Submit** to submit the batch job.