

-
-
-
-
-

Chapter 2

Processing



Configurator Processing

You have now created one of the following:

- A model item with an associated base item and route, which is ready to be preconfigured (if preconfiguration is required), and then configured during order entry.
- An item with an associated route which is defined in Inventory as an order configured item, and which will not be preconfigured, but which will be configured during order entry.


Preconfiguration

Preconfiguration enables you to incorporate selected configuration options into an item before that item is ordered. Our desk example, available in pine or PVC, is to be preconfigured so that the pine version and the PVC version exist as separate items.

The main advantage of preconfiguration is the resulting simplification of the rules and route. Leaving all configuration options to the order entry stage could result in a complex series of rules and route sequencing.

When you preconfigure, you specify the model item, which provides the Production route details, and the base item, which provides the Inventory item master and stockroom details and the Production item master details.

The process will create the item detail records for the new item. It will also create the item code itself, depending on the setting of the 'item code generation' field in the Configurator company profile.



When setting up the route in Production for the model item, you will have flagged each Configurator option as either an order entry option or not. The preconfiguration screens will now present for configuration those options which were specified as not being order entry options (in the above example, this would include the choice of material, pine or PVC).

The code of the preconfigured item generated in preconfiguration will be that used in order entry to enter a configured order line.

A preconfigured item may optionally be associated with a particular customer.

Order Configuration

Order configuration is a means of skipping the procedure of setting up a model and base item and preconfiguring items from the base. You can set up the order configured item, define a route for it, and once the rules etc. are set up you can go straight into order entry for all configuration options.

With order configuration, options are taken at order entry time. A production order will be created for the configured item, based on the configuration route, with any order entry options specified.

After Initial Selection

After initial selection, preconfiguration and order entry configuration share common processing routines and will therefore be dealt with as one option for the purposes of this product information. Any differences in processing between preconfigure and order entry modes will be pointed out in the text at the appropriate point.

Specify the model item which is to be used as the basis for the creation of a preconfigured item during preconfiguration. The model item must be defined to the configuration route for the Company. The Inventory item prompt is available.

Base Or Configured Item

If a new preconfigured item is to be created, enter the base item from which to copy Inventory details. If you enter only a model item and press Enter, a list of valid base items is displayed. If an existing preconfigured item is to be modified, enter the code of the preconfigured item. The Inventory item prompt is available.

Customer

Items may optionally be preconfigured for a specific customer. If this facility is required, enter the account code and delivery sequence of the customer to be associated with this preconfiguration. A prompt is available on valid customers.

Existing Configured Item

An existing preconfigured item rather than a model item may optionally be used to provide the route details on which to base the creation of a new preconfigured item. A valid base item must also be entered. The Inventory item prompt is available.



When you have entered the required details, press **Enter** to begin the configuration process.

Functions:

F7

Display a list of preconfigured items previously generated from a model / base item combination and allow selection of the required preconfigured item.

A valid model and base item must have been entered prior to this function key being pressed.

F9

Enter item search characteristics for a base or preconfigured item. The item must be defined to a search family.

A valid model and base item or a valid preconfigured item must have been entered prior to this function key being pressed.



Once this screen is completed, press Enter. You then begin the process of defining your configuration.

As the process of creating a preconfigured item is exactly the same as creating an order configured item in Advanced Order Entry, it is explained only once, in the section Configuration.

Order Configuration

In Advanced Order Entry, the preconfigured or order configured item is ordered on a normal sales order line. Configurator is called, allowing the line to be configured to the customer's requirements.

The following sections deal with the ordering procedures specific to configured and make-to-order processing. For full details of order capture in Advanced Order Entry, refer to the Advanced Order Entry product information, but note that all stockrooms you wish to sell from must be defined as depots.

Select the Advanced Order Entry option to display the standard order header screen. Complete the header details only, then press **Enter** to go to line entry. Do not enter your first order on the header screen. You now have a choice of the following two entries:

- Enter the code of the preconfigured or configured item together with the order quantity. Preconfigured and configured items are included in the standard Inventory item prompt.
- Enter a base item and the search type 9 if you want a prompt. A window enables you to select a customer if you wish to restrict the items listed. The prompt then lists all preconfigured and configured items for that base (and customer if specified).

When you have selected your item and have entered a quantity, press **Enter**. If you entered 1 in the Override field at the bottom of the screen, you will then go to the order line override window (if you did not, you will go into the configuration process itself and should now go to the Configuration section).

Order Line Overrides Window



Select an item and enter a quantity, then press Enter. Enter 1 in the Override field at the bottom of the screen, you go to the order line override window.

You use this window to enter the order line override details.

A0005		Z1 - Demonstration Company		User V3USER		18/10/95	
Last Five Orders Date Quantity Disc unit price				Order Line Overrides Line number... 1 Item..... DESK/0001 Calc. price... .00 Price list?... Fixed price... .00000 Disc. list?... Fixed discount .00 % Due date..... 18/10/95			
Price Structure Value Disc unit price 0.00				Enter text.... 0 (1=Yes,0=No) Configurator.. 0 (1=Yes,0=No) Order method.? 5 Configure to or Methods..... W0 Certificate... 0 Quantity/Uom.? 2.000 EA Allocated..... .000 Reserved..... 2.000 Outstanding... .000 Parent line...			
F3=Exit F4=Prompt F13=Trailer F14=Header F23=More options F24=More keys				F4=Prompt F12=Previous			
06-61 SE MW KS IM II KENB20A PET147S1							

Fields:

Calculated Price

This field displays the price of the configured item calculated according to the pricing method and order entry costing in the company profile. The calculated price is displayed as an aid to the negotiation of a fixed price for the line if required.

Price List

The price list used for the order is displayed, but can be changed. Any new price list must be in the same currency as the order.

Fixed Price

If a fixed price is to be charged enter the amount here. Leave blank to use the price list.

Discount List

The discount list used for the order is displayed, but can be changed. Any new discount list must be in the same currency as the order.

Fixed Discount

If a fixed discount percentage is required enter it here. Leave blank to use the discount list.

Due Date

The order due date is displayed. Enter the order line due date if it is different. It may not be earlier than the current date.

Enter Text

If you wish to maintain the order line text which appears on external documents, enter 1. The external order line text screen is displayed.

Configurator

Enter one of the following:

- 1 - Configure the line
- 2 - Do not configure the line

If Configurator is attached and the line is for a configured item, this flag controls entry to the options allowing operation and component selection for the configured line.

The field is preset to 1 on line entry for preconfigured items. On line amendment, the field defaults to 0.

Order Method

The default order method for the item is displayed. On line entry it may be overridden to another order method, unless it is a configured line, in which case order method is fixed. Several order methods may be used for the same line, by overriding this field when amending.

The following methods are available:

- 0 – Sell from stock (i.e. allocate normally)
- 1 – Make to order
- 2 – Purchase to order
- 3 – Direct delivery purchase to order
- 4 – Reserve against existing supply orders
- 5 – Configure to order (for configured items only)

Make to order, configure to order and reservations against production orders are only allowed if Production and Configurator are attached for the company.

Methods

Displays codes representing the ordering method or methods so far used for this order line. The codes indicate the following methods:

- WO – Production order (for make-to-order or configured lines)
- RS – Reserved against a production or purchase order
- BB – Back-to-back purchase order
- DD – Back-to-back purchase order with direct delivery.

Certificate

- 1 - You require a certificate of conformance for the order line.

Quantity

Enter the quantity ordered for delivery on the nominated delivery date. The field is mandatory.

Allocated Quantity

Displays the quantity currently allocated for the line.

Reserved Quantity

Displays the quantity currently reserved against supply orders for this line.

Outstanding Quantity

Displays the quantity currently outstanding (i.e. neither allocated nor reserved) for this line.

Unit Of Measure

Enter the unit of measure of the order line if it is different from the issue unit. The unit of measure must be any one of the purchase, stocking or issue units set up on the item record.

Parent Line

If the order line is a kit component enter the parent order line number. This may not be changed after the order line has been entered.

Kitting is not allowed for configured items.

Functions:

F13

Reserve stock against an existing supply order.

Configuration

After the initial selection of a configured item, the configuration processes in preconfiguration and order entry modes are almost identical.

The functions common to preconfiguration and order entry configuration are as follows:

- Option selection
- Characteristic display and selection
- Configuration review
- Operation selection
- Component selection
- Formatted text maintenance
- Reactive rule processing

Option Selection Window



Select the item you wish to preconfigure or configure, and then enter Configurator. If your configuration means that actual items need to be selected from mandatory generic components, the Option Selection window is displayed. Otherwise, the configuration review screen is displayed.

This window lists the actual components defined to the search family displayed at the top of the window. The format of the window depends either on the default setting of the selection method field in the company profile, or on your user ID's own selection method (set up in Inventory Descriptions).

CN021 Z1 - Demonstration Company User V3USER 17/10/95
17:01:20

Pre-configuration

Model Item.....?.. DESK

Option Selection (Direct)

Generic Component.. GNTOP Desktop - generic

Search Family..... TOP - Desktop More: -

Sel Item	Quantity	Description
- TOPPLN	1.000	Pine top without she
- TOPSHEL	1.000	Pine top with shelf

1=Select 5=Display Characteristics Item..

F8=Next Panel F15=Unprompted Selection F16=Prompted Selection

13-08 **SA** MW KS IM II KENB20A PET147S1

Fields:

Generic Component Code And Description

This field displays the generic component which will be replaced by the actual component selected from the displayed list.

Search Family Code And Description

This field displays the code and description of the search family to which the generic and actual components belong.

Item

The item code of the component in the list.

Quantity

The quantity of the component required to make one of the parent item.

Description

The item master description for the component.

Discounted Unit Price

If in order entry mode, this displays the unit price of the component, in prime currency, with any component discount accounted for. Prices are not displayed in preconfiguration mode.

Select

Enter one of the following:

- 1 - to select a component from the displayed list.
- 5 - to display the search characteristics defined to the component.

Item

As an alternative to selecting from the displayed list, the required component may be selected by directly entering its code in this field.

Functions:

F8

Next Panel. Use this function to proceed to the next screen without making a selection.

F15

Unprompted Selection. Enter search family characteristics to identify the required component.

F16

Prompted Selection. Select from prompted lists of search family characteristics to identify the required component.

Characteristic Display Window

This window displays the characteristics set up for the selected component in item master maintenance. Characteristics aid the search and selection of the appropriate component for the configuration.



Tip: If an empty window is displayed, check the following:

- The search family is set up correctly
- Each item master has had the search values set up (F18 in Inventory item master)
- The conditions set up in the rules allow a selection to be made

CN021 Z1 - Demonstration Company User V3USER 17/10/95
17:01:20

Pre-configuration

Model Item.....?.. DE

Option Selection (Direct)

Generic Component.. GNTOP

Search Family..... TOP - Deskto

Sel Item Quantity

TOPPLN 1.0

TOPSHEL 1.0

Description Code

Materials PIN

Style SHL

F12=Previous

1=Select 5=Display Characteristics Item..

F8=Next Panel F15=Unprompted Selection F16=Prompted Selection

22-53 SF MW KS IM II KENB20A PET147S1

Fields:

Description

This lists the characteristics.

Code

Enter the value you wish to select.

Characteristic Selection (Unprompted) Window

This window allows characteristics to be entered to aid the selection of component options for the configuration. By this means the list of components from which to choose can be narrowed down to those which correspond to the entered characteristics. Characteristics are entered in Inventory Item Master Maintenance for each item within the search family.

CN021 Z1 - Demonstration Company User V3USER 17/10/95
17:01:20

Pre-configuration

Model Item.....?.. DESK _____

Option Selection (Direct)

Generic Component.. GNTOP

Search Family..... TOP - Desk

Sel Item	Quant it
- TOPPLN	1
- TOPSHEL	1

Characteristic Selection (Unprompted)

Characteristic	Value (?)
Materials	_____
Style	_____

1=Select 5=Display Character

F4=Prompt F12=Previous

F8=Next Panel F15=Unprompted Selection F16=Prompted Selection

12-60 **SA** MW KS IM II KENB20A PET147S1

Fields:

Characteristic

A description of the characteristic for which a value may be selected.

Value

Enter a value for the corresponding characteristic.

- 
- Enter valid characteristic values and press **Enter**, the option selection screen is redisplayed with the list of components limited to those matching the entered characteristics. If only one component matches, this is selected automatically.

Characteristic Selection (Prompted) Window

This window allows characteristics to be selected to aid the selection of component options for the configuration. By this means the list of components from which to choose can be narrowed down to those which correspond to the entered characteristics. Characteristics are entered in Inventory Item Master Maintenance for each item within the search family.

CN021Z1 - Demonstration CompanyUser V3USER17/10/9517:01:20

Pre-configuration

Model Item.....?.. DESK

Base or Configure

Customer.....

Optionally enter for the definitio

Existing Configur

Characteristic Selection (Prompted)Char: 02

Characteristic.. Style

Code.. STYL Desktop style

Value	Description	Value	Description
■ PLN	Plain top		
■ SHL	Top with s		

1=Select

F12=Previous F14=Return

F3=Exit F4=Prompt F7=Existing Configurations F9=Characteristics

12-26S2MWKSIMIIKENB20APET147S1

Fields:

Characteristic Description

A description of the characteristic for which the list of values is displayed.

Characteristic Code

The code defined to the characteristic within the search family.

Characteristic Code Description

Text defined to the characteristic code in the Inventory Descriptions option.

Value And Description

The code and description of a characteristic value available for selection.

Select

Enter 1 to select a characteristic value from the displayed list.



After the last characteristic selection window is processed, the option selection screen is redisplayed with the list of components limited to those matching the entered characteristic values. If only one component matches, this is selected

automatically.

Functions:

F14

Return. Use this function to return to the option selection window.

Configuration Review Screen

 After you have selected all the configurable components for mandatory operations, the review screen is displayed.

You use this screen to review configuration details and make any amendments, deletions or additional selections for operations and components within the configuration.

CN030	Z1 - Demonstration Company	User V3USER	17/10/95
Configuration Review			17:11:35
Model Item.....	DESK	Desk - model	
S Oper/Component	Quantity	Description	T Cat
		FIX COMPUTER SHELF	OPN
COMSHEL	1.000	Computer shelf	
		ASSEMBLE DESK	OPN
- PINSIDE	2.000	Deskside in pine	ACT
- TOPSHEL	1.000	Pine top with shelf	ACT
- SCREW01	4.000	Screw 01	
		PAINT ASSEMBLY	OPN
- GNPNT01	1.000	Paint 01 (Generic)	GEN
1=Select 2=Text 4=Delete			
F8=Update F9=Rules Check F21=Works order text F22=Select operations			
11-02	SE	MW KS IM II	KENB20A PET147S1

The top part of the screen shows the parent items for the configuration, together with the configuration route code. If in order entry mode, a total unit price for the configuration is displayed in prime currency with any component discounts accounted for.

The middle part of the screen lists operations and components currently selected for the configuration.

Fields:

Component

Displays the item code of an actual or generic component. Highlighting is used to indicate a mandatory component.

If a generic component is shown, you cannot update the configuration until it has been replaced with an actual component.

Quantity Per

For components, displays the quantity of the component required to make one of the configured item. If quantity per is variable for the component, it may be amended within the permitted range.

Description

Displays a description of the operation or component.

Discounted Unit Price

If in order entry mode, this displays the unit price of the component, in prime currency, with any component discount accounted for. Prices are not displayed in preconfiguration mode.

Text

Formatted text indicator for operations. A value of * indicates that formatted text exists for the operation.

Category

The category of the operation or component line, according to the following codes:

OPN – Operation

GEN – Generic component

DFT – Default component within generic feature

ACT – Actual component selected for generic feature

Blank - Normal component, i.e. one not associated with a generic feature.

Select

Select a valid option for the corresponding detail line. For operations, the following options are available:

1 - Select components from within the operation

2 - Maintain formatted text

4 - Delete an optional operation

For components, the following options are available:

1 - Select an actual component from a generic feature

4 - Delete an optional component

Order entry options cannot be maintained in preconfiguration mode and vice versa.



When all the required operations and components have been selected, select **F8=Update** to update the configuration.

Functions:

F9

Rules Check. Check all Configurator rules applicable to this configuration, resetting rule actions accordingly. If any rule violations are found, a window will display detailing the errors.

F21

Works Order Text. Enter Production item text for the configured item (if in preconfigure mode) or production order text (if in order entry mode).

F22

Select Operations. Display a list of operations for this configuration, allowing the selection of optional operations.

Operation Selection Screen (F22)



On the Configuration Review Screen, select **F22** to display the Operation Selection Screen.

Use this screen to select the individual optional operations that are to be included in the configuration.

CN022	Z1 - Demonstration Company	User V3USER	17/10/95
Operation Selection			17:12:46
Model Item.....	Desk - model		
Base Item.....	Desk - base item		
Sel Op Code	Description	Text	
0030	FIX COMPUTER SHELF		
0010	ASSEMBLE DESK		
0020	PAINT ASSEMBLY		
1=Select			
F12=Previous			
01-02	SE	MW	KS IM II KENB20A PET147S1

Fields:

Operation Sequence

Displays the sequence number of the operation on the configuration route.

Operation Description

Displays a description for the operation as entered in route maintenance.

Text

Formatted text indicator for operations. A value of * indicates that formatted text exists for the operation.

Sel

1 - Select an operation for the configuration.

Component Selection Screen

- ➡ On the Configuration Review Screen, enter 1 against an operation to display the Component Selection Screen

Use this screen to select particular components to appear on the configuration for the selected operation.

CN026Z1 - Demonstration CompanyUser V3USER17/10/9517:19:17

Configurator Trailer

Configured Item..... DESK/0001

Item Description..... Desk - base item

Primary Stockroom..... 01 ?????????????????????

Customer.....

Customer Item Code.....

F3=ExitF12=PreviousF4=PromptF8=UpdateF9=Characteristic Entry

11-30SEMWKSIIMIIKENB20APET147S1

Fields:

Operation Sequence

Displays the sequence number of the operation on the configuration route.

Operation Description

Displays a description for the operation as entered in route maintenance.

Component

The item code of the component on the selection list. A highlighted code indicates that the component is mandatory.

Quantity Per

Displays the quantity of the component required to make one of the configured item. If quantity per is variable for the component, it may be amended within the permitted range.

Description

Displays a description of the component.

Discounted Unit Price

If in order entry mode, this displays the unit price of the component, in prime currency, with any component discount accounted for. Prices are not displayed in preconfiguration mode.

Category

The category of the component line, according to the following codes:

GEN - Generic component

DFT - Default component within generic feature

ACT - Actual component selected for generic feature

Blank - Normal component, i.e. one not associated with a generic feature.

Sel

1 - Select a component for the configuration.

Formatted Text Maintenance Window

You use this window to maintain the Configurator formatted text for an operation.

DB134 Z1 - Demonstration Company USER V3USER 24/10/95
15:44:16

Route Operation Maintenance UPDATE

Select Text Format

Par Position to... C

Ope 1 Seq Fmt Description 1.000

Con 1 CHK PRODUCT CHECKLIST

Formatted Text Maintenance

Number of Lines Allowable.. 4 Number of Lines Used.. More:

Key: DESK C0010 Type: OPER CHK PRODUCT CHECKLIST

Line Heading <.....1.....2.....3.....4.....5.....>

1 SERIAL NO 002274

2 LENGTH 4 Metres

3 WIDTH 2 Metres

4 FINISH Red gloss paint

Position to line number..

Insert lines after line number.. Delete lines from to

F8=Update

eration has inputs associated with it.

F4=Prompt F11=Delete this line F12=Replace line without update.

F21=Operation Text F22=Formatted Text

01-02 SF MW KS IM II KENB20A PET149S1

Fields:

Number Of Lines Allowable

The maximum number of text lines that may be entered for this format.

Number Of Lines Used

The number of lines of text so far entered for this format.

Key

The reference code of the text currently being maintained. The reference will depend on whether the text is being maintained in route maintenance, order entry or preconfiguration.

Type

The code representing the type of text being maintained.

Format

The subtype or format code and description for the text.

Line

The sequence number of the corresponding text line.

Heading

Displays or allows maintenance of a heading for the text line, depending on the option specified for the format.

Text

Enter up to the permitted number of lines of text for this format.

Position To Line Number

Specify a line number at which to position the text.

Insert Lines

Specify the number of new lines to be inserted.

Insert After Line Number

Specify the line number after which to insert new lines.



When the required formatted text has been entered, select **F8=Update** to update the details and continue.

Rule Application Messages Window

If the configuration is updated and one or more rules have been broken, a window displays listing the rule violations. This window is also displayed if a rule check is taken from the Configuration Review screen and rule violations are found.

CN030Z1 - Demonstration CompanyUser V3USER24/10/95
Configuration Review16:18:35
Model Item..... DESKDesk - Model
Configured Item.. DESKB001Desk - Base
Disc unit price.. .00 GBPLine value...

S	Oper/Component	Quantity	Description	Discount	price	T	Cat
-			FIX COMPUTER SHELF	.00			OPN
				.00			OP
							AC
							OP
							AC
							OP
							AC
							OP
							OP
							+
							-

Configurator Rule Application Messages
_ Varnish must be gloss.
_ The computer shelf requires a different desktop.

"5"-Rule Inquiry F10=Display Detail/Message Only F12=Previous
F13=Proceed

F8=Update F9=Rules Check F21=Works order text F22=Select operations

01-02 **S** MW KS IM II KENB20A PET149S1

If the violated rule was attached to a specific message, that message is displayed. Otherwise, a standard message is displayed.

If the message is highlighted, it is of a critical severity, and you must amend the configuration to conform to the rule. If no critical errors exist, amendment of the configuration is at your discretion.

Fields:

Select

5 - Enquire on rule details.

Functions:

F10

Expand or contract the amount of information displayed for each message.

Configuration End Processing

When all the details of the configuration have been selected and the configuration is updated from the configuration review screen, subsequent processing will depend on the mode of configuration, i.e. the Configurator Trailer Screen for preconfiguration, and the Sales Order Line Entry screen for order entry configuration.

Configurator Trailer Screen

 Select all the configuration details and in the Configuration Review Screen select **F8=Update**.

 *Note: The configuration mode must be Preconfiguration.*

The Configuration Trailer screen allows details to be specified for the creation or amendment of a preconfigured item. This includes the primary stockroom for the item and (optionally) the specific customer for which the preconfiguration is being created.

CN026

Z1 - Demonstration Company

User V3USER

17/10/95

17:19:17

Configurator Trailer

Configured Item.....

DESK/0001

Item Description.....

Desk - base item

Primary Stockroom.....?

01 ?????????????????????

Customer.....?

Customer Item Code.....

F3=Exit

F12=Previous

F4=Prompt

F8=Update

F9=Characteristic Entry

11-30

SF

MW

KS

IM

II

KENB20A

PET147S1

Fields:

Configured Item

Either displays or allows entry of a code for the new or modified preconfigured item, depending on the option specified on the Configurator company profile.

Item Description

Allows the entry of a description for the preconfigured item. For a new preconfigured item, this defaults to the base item description.

Primary Stockroom

Specify the Inventory stockroom where this preconfigured item will usually be stored. For a new preconfigured item, this defaults to the primary stockroom for the model item on the configuration route.

Customer

Items may optionally be preconfigured for a specific customer. If this facility is required, enter the account code and delivery sequence of the customer to be associated with this configuration. A prompt is available on valid customers.

Customer Item Code

If the preconfigured item is for a specific customer, enter a reference by which the customer refers to the preconfigured item. This reference may be used in Order Entry to aid the search of the correct preconfigured item.



Enter valid details and then press F8 to generate or amend preconfigured item details. A window displays allowing you to maintain item search details for the new preconfigured item.

Functions:

F8

Update. Update the preconfigured item details. If a new preconfigured item is being specified, item master details will be created for the preconfigured item.

F9

Characteristic Entry. Enter item search characteristics for the preconfigured item.

Sales Order Line Entry Screen



Select all the configuration details and in the Configuration Review Screen select **F8=Update**.



Note: The configuration mode must be Order Entry Configuration.

A sales order line is created for the configured item and control returns to the line entry screen in Advanced Order Entry. When you have completed the order entry, a production order is automatically created to manufacture the configured item.

A0005		Z1 - Demonstration Company		User V3USER		24/10/95	
Order Entry						16:24:35	
Second Customer		Pounds sterling					
Line Item	Str Due date	Quantity	UoM	Price/ Value	UoM	Txt	
1 DESKB001	01 24/10/95	2	EA	0.00			
Desk - Base				.00		WO	
1=Amend 2=Source 3=Alloc batches 4=Delete 5=Reserve 6=Availability							
Item.? 1		Qty..		UoM.? __		Override _	
F3=Exit F4=Prompt F9=Pricing F13=Trailer F23=More options F24=More keys							
01-02		SF		MW		KS IM II KENB20A PET149S1	

In order entry mode, when the configuration is updated from configuration review, a sales order line is updated for the configured item.

Price details are updated on the configured line, based on the pricing method in operation, and whether standard or advanced pricing is used.



Note: If a fixed price has previously been established for the configured line and the configuration details are amended such that the total price of the configured line is different to that previously calculated, control returns to the order line override window in Advanced Order Entry. This is to allow the fixed price to be reviewed against the new calculated price and any required adjustment to be made.

When sales order details are updated at the end of order entry or amend, a production order is automatically created or amended for any configured line for which configuration details have been entered or amended.



Note: If in Order Amend mode, and a production order already exists for a configured line, configuration details can only be amended up



until the time the production order is released.

Note: If in Order Amend mode, and a production order has not yet been created by the background processor, the configured line will not be available for the amendment of configuration details.

For full details of order capture in AOE, refer to the Advanced Order Entry product information.