



INVENTORY MANAGEMENT

Version 3.5.2 SP4

Product Guide

FRONTISPIECE

Copyright © 2001, Geac Enterprise Solutions Limited, Product Services Division, Eagle House, The Slough, Studley, Warwickshire, B80 7EN England.

All rights reserved.

No part of the material protected by this copyright may be reproduced or utilised in any form or by any means, stored in a retrieval system, or transmitted, in any form, or by any means, electronic, mechanical, photocopying, or otherwise, without the express prior written consent of Geac Enterprise Solutions Limited.

Although every care has been taken in the production of this manual it cannot be guaranteed that the information contained herein is without error or omission.

This product information relates to:

Inventory Management Version 3.5.2 SP4

If you have any comments please e-mail: **infobase.feedback@geac.com**

Contents

CHAPTER 1 INVENTORY MAINTENANCE.....	1-1
INVENTORY MAINTENANCE INTRODUCTION.....	1-2
DESCRIPTIONS MAINTENANCE.....	1-3
<i>Descriptions File Maintenance Selection Screen</i>	1-4
Descriptions File Major Type Codes.....	1-5
<i>Descriptions File Maintenance Screen</i>	1-24
<i>Descriptions File Maintenance Detail Screen</i>	1-26
ITEMS MAINTENANCE	1-28
<i>Item Maintenance Selection Screen</i>	1-29
<i>Item Maintenance Static Detail Screen</i>	1-30
Secondary Value Details Window	1-36
Valuation Group Window	1-38
Maintain Text Window.....	1-40
Item Text Window.....	1-42
Item Purchase Text Window	1-43
Multi-Lingual Descriptions Maintenance Window	1-44
<i>Item Maintenance Costing Details Screen</i>	1-45
Quality Item Master Window.....	1-51
Alternative Item Reference Screen.....	1-52
Item Search Characteristics Screen	1-53
Item Pricing Groups Window.....	1-54
Lot Header Parameters Maintenance Window.....	1-55
<i>Inventory Item Search Words Window</i>	1-58
<i>Item Master Scan Window</i>	1-59
ALTERNATIVE ITEMS MAINTENANCE	1-61
<i>Alternative Items Maintenance Detail Screen</i>	1-62
KIT LISTS MAINTENANCE	1-63
<i>Kit Lists Maintenance Selection Screen</i>	1-64
<i>Kit List Maintenance Detail Screen</i>	1-65
STOCKROOM DETAILS MAINTENANCE	1-66
<i>Stockroom Details Maintenance Selection Screen</i>	1-67
<i>Stockroom Details Maintenance Screen</i>	1-68
Landed Costs Entry Screen	1-73
<i>Item/Stockroom Location Control Details Window</i>	1-74
FIFO COSTS MAINTENANCE	1-76
<i>Maintain FIFO Costs Selection Screen</i>	1-77
<i>Maintain FIFO Costs Screen</i>	1-78
CALENDAR MAINTENANCE AND YEAR END UPDATE.....	1-80
<i>Maintain Calendar File Screen</i>	1-81
PERIOD END CONTROL	1-83
<i>Inventory Period End Control Maintenance Selection Screen</i>	1-84
<i>Year Total Control Window</i>	1-85
<i>Inventory Period End Control Maintenance Screen</i>	1-86
SECONDARY UOMS MAINTENANCE	1-87
<i>Maintain Unit Of Measure Selection Screen</i>	1-88
<i>Maintain Unit Of Measure Details Screen</i>	1-89
<i>Maintain Unit Of Measure Selected Details Screen</i>	1-91
LINKED ITEM MAINTENANCE	1-92
<i>Linked Item Maintenance Screen</i>	1-93
<i>Profile Selection Window</i>	1-94
COPY BASED ON ITEM CREATION.....	1-96
<i>Copy Based On Item Selection Screen</i>	1-97

Profile Options Screen	1-98
SOURCING RULES ACCESS.....	1-99
<i>Maintain Sourcing Rule Access Criteria Selection Screen</i>	1-100
<i>Maintain Sourcing Rule Access For Sales Order Screen</i>	1-101
<i>Confirm/Delete Sourcing Rule Access For Sales Order Screen</i>	1-103
SOURCING RULES	1-104
<i>Maintain Sourcing Rule Details For Sales Order Selection Screen</i>	1-105
<i>Maintain Sourcing Rule Details For Sales Order Detail Screen</i>	1-106
<i>Amend Sourcing Rule Window</i>	1-108
<i>Confirm Rule Deletion Window</i>	1-109
<i>Add Sourcing Rule Window</i>	1-110
<i>Sourcing Rule Detail Maintenance Screen</i>	1-112
<i>Sourcing Rule Detail Amendment Window</i>	1-113
<i>Confirm Rule Detail Deletion Window</i>	1-115
<i>Sourcing Rule Detail Addition Window</i>	1-116
LOCATION MAP	1-117
CHAPTER 2 INVENTORY PROCESSING	2-1
INTRODUCING INVENTORY PROCESSING	2-2
RECEIPTS, ISSUES AND ADJUSTMENTS.....	2-4
<i>Record Purchase Order</i>	2-5
Record Purchase Order Selection Screen	2-6
Record Purchase Order Detail Screen	2-8
<i>Purchase Order Receipt</i>	2-10
Record Purchase Receipt Selection Screen.....	2-11
Record Purchase Receipt Detail Screen	2-13
<i>Miscellaneous Receipt</i>	2-16
Record Miscellaneous Receipt Selection Screen	2-17
Record Miscellaneous Receipt Detail Screen.....	2-19
Enter Location Balances Window	2-22
Enter Secondary Balances Window	2-27
Secondary Value Entry Window	2-29
<i>Customer Order Issue</i>	2-31
Record Customer Order Issue Selection Screen.....	2-32
Record Customer Order Issue Detail Screen	2-34
<i>Miscellaneous Issue (Physical)</i>	2-37
Record Miscellaneous Issue (Physical) Selection Screen.....	2-38
Record Miscellaneous Issue (Physical) Details Screen	2-40
<i>Physical Stock Adjustments</i>	2-42
Record Stock Adjustment (Physical) Selection Screen	2-43
Record Stock Adjustment (Physical) Detail Screen	2-45
<i>Allocated Stock Adjustments</i>	2-48
Record Allocated Adjustment Selection Screen.....	2-49
Record Allocated Adjustment Details Screen.....	2-51
<i>Frozen Stock Adjustments</i>	2-53
Record Frozen Adjustment Selection Screen.....	2-54
Record Frozen Adjustment Details Screen	2-56
MISCELLANEOUS ISSUES	2-58
<i>Miscellaneous Issue (Available)</i>	2-59
Record Miscellaneous Issue (Available) Selection Screen.....	2-60
Record Miscellaneous Issue (Available) Detail Screen.....	2-62
<i>Frozen Stock Issues</i>	2-64
Record Miscellaneous Frozen Issue Selection Screen.....	2-65
Record Miscellaneous Frozen Issue Detail Screen	2-67
STOCK TRANSFERS	2-69
<i>Record Transfer Out</i>	2-71
Record Transfer Out Selection Screen	2-72
Record Transfer Out Detail Screen.....	2-74
Record Transfer Out Despatch Details Window.....	2-77

<i>Confirm Shipment Receipt</i>	2-79
Confirm Shipment Receipt Selection Screen	2-80
Confirm Shipments Receipt Items In Transit Screen	2-82
SINGLE STEP STOCK TRANSFERS	2-85
<i>Single Step Transfer</i>	2-86
Record Stock Transfer Selection Screen	2-87
Record Stock Transfer Detail Screen	2-89
<i>Single Step Transfer (Frozen)</i>	2-92
Record Frozen Stock Transfer Selection Screen	2-93
Record Frozen Stock Transfer Detail Screen	2-95
CHAPTER 3 INVENTORY STOCK COUNTING	3-1
STOCK COUNTING INTRODUCTION	3-2
<i>Stock Counting Steps</i>	3-3
COUNT PROFILE MAINTENANCE	3-4
<i>Count Profile Maintenance Stockroom Selection Screen</i>	3-5
<i>Count Profile Maintenance Details Screen</i>	3-6
<i>Count Profile Maintenance ABC Details Screen</i>	3-9
COUNT PROFILE ENQUIRY	3-10
REGENERATE ABC CLASSIFICATIONS	3-11
ABC RECOMMENDATIONS	3-12
<i>Create Count By Class/Date Selection Screen</i>	3-13
<i>Create Count By Class/Date Control Screen</i>	3-14
MANUAL RANGE	3-16
<i>Create Count by Manual Range Detail Screen</i>	3-17
CREATING COUNTS BY LOCATION	3-20
<i>Create Count By Warehouse Location</i>	3-21
Create Count By Warehouse Location Area Selection Screen	3-22
Create Count By Warehouse Location Detail Screen	3-23
<i>Create Count By Location Range</i>	3-26
Create Count By Location Selection Screen	3-27
MAINTAIN COUNT	3-29
<i>Maintain Count Selection Screen</i>	3-30
<i>Maintain Count Details Screen</i>	3-31
Addition Window	3-33
<i>Warehouse Location Based Maintain Count Detail Screen</i>	3-35
<i>Count Size Warning Window</i>	3-36
ENTER COUNT DETAILS	3-37
<i>Enter Count Selection Screen</i>	3-38
<i>Enter Count Details Screen</i>	3-39
<i>Enter Count Amendment Window</i>	3-41
<i>Enter Count Delete</i>	3-43
Enter Count Addition Window	3-44
<i>Update Confirmation Window</i>	3-46
COMPLETE COUNT LISTS	3-47
<i>Complete Count Lists Count Selection Screen</i>	3-48
<i>Complete Count Lists List Selection Window</i>	3-49
PRINT COUNT SHEETS	3-50
<i>Print Count Sheets Count Selection Screen</i>	3-51
REPRINT COUNT SHEETS	3-53
<i>Reprint Count Sheets Count Selection Screen</i>	3-54
COUNT RECONCILIATION	3-55
<i>Reconciliation Without Update</i>	3-57
<i>Reconciliation With Update</i>	3-59
Reconciliation History Updates	3-61
RECOMMENDED COUNTS ENQUIRY	3-62
<i>Count Enquiry Selection Screen</i>	3-63
<i>Count Enquiry Details Screen</i>	3-64

OUTSTANDING COUNTS ENQUIRY	3-65
<i>Count Enquiry Selection Screen</i>	3-66
<i>Count Enquiry Detail Screen</i>	3-67
ITEM COUNT SUMMARY ENQUIRY	3-68
<i>Item Count Summary Enquiry Selection Screen</i>	3-69
<i>Item Count Summary Enquiry Details Screen</i>	3-70
<i>Item Count Summary Enquiry Item Details Screen</i>	3-71
COUNT HISTORY ENQUIRY	3-72
<i>Count History Enquiry Selection Screen</i>	3-73
<i>Count History Enquiry Summary Screen</i>	3-74
<i>Count History Enquiry Stockroom Detail Screen</i>	3-75
CHAPTER 4 INVENTORY UPDATES	4-1
INVENTORY UPDATES INTRODUCTION	4-2
<i>Inventory Decisions</i>	4-3
WEEK END UPDATE	4-7
MONTH END UPDATE	4-8
<i>Month End Update Record Report Selection Criteria Screen</i>	4-9
<i>Month End Update Confirmation Screen</i>	4-10
YEAR END UPDATE	4-11
CALCULATE ROP, MAX STOCK, AND EOQ	4-12
CHAPTER 5 INVENTORY LOT/GRADE/POTENCY	5-1
LOT/GRADE/POTENCY INTRODUCTION	5-2
<i>Shelf Life, Grade and Potency</i>	5-4
LOT HEADER MAINTENANCE	5-6
<i>Lot Header Maintenance Selection Screen</i>	5-7
<i>Lot Header Maintenance Details Screen</i>	5-8
Adjust Active Ingredient Screen	5-12
Certificates Of Conformance Window	5-14
MANAGING GRADES	5-15
<i>Grade Maintenance</i>	5-16
Grade Maintenance Selection Screen	5-17
Grade Maintenance Detail Screen	5-18
Maintain Grade Window	5-19
STOCK STATUS RECALCULATION	5-20
<i>Stock Balance Recalculation Screen</i>	5-21
LOT TRANSFORMATION	5-22
<i>Record Lot Transformation Selection Screen</i>	5-23
<i>Record Lot Transformation Details Screen</i>	5-24
GRADE ENQUIRY	5-26
GRADE HISTORY ENQUIRY	5-27
STOCK STATUS ENQUIRY	5-28
<i>Stock Status Enquiry Screen</i>	5-29
<i>Stock Status Enquiry Available And Frozen Lots Screen</i>	5-31
STOCK STATUS HISTORY ENQUIRY	5-32
POTENCY ENQUIRY	5-33
<i>Potency History Enquiry Window</i>	5-35
LOT TRACE ENQUIRY	5-36
<i>Lot Trace Enquiry Selection Screen</i>	5-37
<i>Lot Trace Enquiry Details Screen</i>	5-38
Forward/Backward Trace Window	5-40
LOT HEADER DEFAULTS AUDIT REPORT	5-41
SHELF LIFE REPORT	5-42
CHAPTER 6 PACKAGING REQUIREMENTS	6-1
INTRODUCTION TO PACKAGING REQUIREMENTS	6-2

COUNTRY DETAILS MAINTENANCE	6-3
<i>Maintain Packaging Reporting Countries Selection Screen</i>	6-4
<i>Maintain Packaging Reporting Country Detail Screen</i>	6-5
Maintain Responsibilities Window	6-8
Packaging Codes Details Screen	6-10
<i>Add Packaging Details Window</i>	6-11
Average Packaging Details per Despatch Screen	6-13
<i>Add Average Packaging Details Window</i>	6-14
Maintain Packaging Categories Window	6-15
ITEM DETAILS MAINTENANCE	6-16
<i>Country Item Packing Details Selection Screen</i>	6-17
<i>Country Item Packaging Codes Details Screen</i>	6-18
Enter Item Packaging Details Window	6-20
Select Additional Packaging Quantity Breaks Window	6-21
Override Responsibilities Window	6-23
Packaging Reporting Country Selection Window	6-24
CUSTOMER/ITEM OVERRIDES	6-25
<i>Customer/Item Responsibility Overrides Selection Screen</i>	6-26
Selection Of Customer To Be Maintained Screen	6-27
<i>Customer/Item Responsibility Overrides Screen</i>	6-28
SALES CHANNEL OVERRIDES	6-29
<i>Sales Channel Responsibility Overrides Screen</i>	6-30
<i>Override Responsibilities Window (Sales Channels)</i>	6-31
CALENDAR MAINTENANCE	6-32
<i>Inventory Calendar/Year Maintenance Selection Screen</i>	6-33
<i>Inventory Calendar/Year Maintenance Detail Screen</i>	6-35
<i>Inventory Calendar/Year Maintenance Screen (Standard Week)</i>	6-37
<i>Inventory Calendar/Year Maintenance Screen (Cyclic Week)</i>	6-38
<i>Inventory Calendar/Year Maintenance Screen (Period)</i>	6-39
<i>Inventory Calendar/Year Maintenance Holiday Detail Screen</i>	6-40
EXTRACT DATA FROM INVENTORY	6-41
<i>Data Extract Selection Screen</i>	6-42
UPDATE PERIOD/QUARTER	6-43
<i>Update Quarter/Year Screen</i>	6-44
CORRECTIONS AND ADJUSTMENTS	6-45
<i>Corrections And Adjustments Selection Screen</i>	6-46
<i>Corrections And Adjustments Detail Screen</i>	6-47
<i>Corrections And Adjustments Screen</i>	6-48
COUNTRY DETAILS ENQUIRIES	6-49
<i>Packaging Reporting Countries Enquiry Selection Screen</i>	6-50
<i>Packaging Reporting Country Enquiry Details Screen</i>	6-51
Responsibilities Enquiry Window	6-52
Packaging Details Enquiry Screen	6-53
Average Packaging Details per Despatch Enquiry Screen	6-54
Packaging Categories Enquiry Window	6-55
ITEM DETAILS ENQUIRIES	6-56
<i>Country Item Packaging Details Enquiry Screen</i>	6-57
PACKAGING PAYMENTS REPORTS	6-58
<i>Packaging Payments Report Selection Screen</i>	6-59
PACKAGING ADJUSTMENTS REPORTS	6-60
<i>Packaging Adjustment Report Selection Screen</i>	6-61
PACKAGING USAGE REPORTS	6-62
<i>Packaging Report Selection Screen</i>	6-63
MANAGING HISTORICAL DATA	6-65
<i>Delete Historical Data</i>	6-66
Delete Historical Data Screen	6-67
<i>Create Historical Data</i>	6-68
Create Historical Data Screen	6-69

CHAPTER 7 INVENTORY VALUATION	7-1
INVENTORY VALUATION INTRODUCTION	7-2
VALUATION DESCRIPTIONS MAINTENANCE.....	7-3
COSTING ANALYSIS	7-4
<i>Costing Analysis Maintenance Selection Screen</i>	7-5
<i>Costing Analysis Maintenance Detail Screen.....</i>	7-7
STOCKROOM FISCAL CLOSE	7-9
<i>Stockroom Fiscal Close Trial Selection Screen.....</i>	7-10
<i>Stockroom Fiscal Close Screen (Stockroom Range).....</i>	7-12
<i>Stockroom Fiscal Close Screen (Stockroom List)</i>	7-13
<i>Stockroom Fiscal Close Update.....</i>	7-14
LIFO REVALUATION	7-15
LIFO REVALUATION TRIAL	7-16
<i>LIFO Revaluation Trial Screen.....</i>	7-17
<i>LIFO Revaluation Screen (Stockroom Range).....</i>	7-19
<i>LIFO Revaluation Screen (Stockroom List).....</i>	7-20
LIFO REVALUATION UPDATE	7-21
<i>LIFO Revaluation Update Screen.....</i>	7-22
<i>LIFO Revaluation Update Stockroom Range Screen.....</i>	7-24
<i>LIFO Revaluation Update Stockroom List Screen.....</i>	7-25
STOCK MOVEMENTS REPORT	7-27
<i>Stock Movements Print Selection Screen</i>	7-28
<i>Stock Movements Print Confirmation Screen.....</i>	7-30
DERIVE OPENING BALANCES.....	7-32
<i>Cost Analysis Derive Opening Balances Screen.....</i>	7-33
COSTING ANALYSIS SET UP MAINTENANCE	7-35
<i>Costing Analysis Setup Maintenance Selection Screen.....</i>	7-36
<i>Costing Analysis Setup Maintenance Opening Values Screen</i>	7-38
<i>Costing Analysis Setup Maintenance Previous Values Screen.....</i>	7-40
COSTING ANALYSIS SETUP UPDATE.....	7-42
<i>Costing Analysis Setup Update Screen.....</i>	7-43
DEFINE OPENING BALANCES	7-44
<i>LIFO Analysis Setup Selection Screen</i>	7-45
<i>LIFO Analysis Setup Detail Screen.....</i>	7-46
CHAPTER 8 INVENTORY ENQUIRIES	8-1
INVENTORY ENQUIRIES INTRODUCTION	8-2
KIT LIST ITEM WHERE USED ENQUIRY	8-3
<i>Kit List Item Where Used Screen</i>	8-4
DESCRIPTIONS ENQUIRY	8-5
<i>Descriptions File Enquiry Selection Screen.....</i>	8-6
<i>Descriptions File Enquiry Screen</i>	8-7
<i>Descriptions File Code Details Enquiry Screen</i>	8-8
ITEM/STOCKROOM ENQUIRY	8-9
<i>Item/Stockroom Enquiry Selection Screen</i>	8-10
<i>Item/Stockroom Enquiry Static Details Screen.....</i>	8-11
Movements Analysis Window	8-13
Cost Analysis Window	8-15
<i>Item/Stockroom Enquiry Costing Details Screen.....</i>	8-17
<i>Lot Header Parameters Enquiry Window.....</i>	8-18
<i>Item/Stockroom Stock Summary Enquiry Screen.....</i>	8-20
<i>Item/Stockroom Enquiry Stockroom Details Screen</i>	8-22
Item/Stockroom Lot Details Screen.....	8-26
<i>Item/Stockroom Receipts Cost Enquiry Screen.....</i>	8-29
<i>Lot Header Details Window.....</i>	8-31
Allocations Enquiry Window.....	8-34
<i>Item/Stockroom Lot By Date Details Screen</i>	8-35

Locations Enquiry Screen	8-36
Item/Stockroom Enquiry FIFO Cost Details Screen	8-37
STOCK MOVEMENTS ENQUIRY	8-38
<i>Inventory Movements Enquiry Screen</i>	8-39
<i>Inventory Movements Summary Screen</i>	8-41
<i>Inventory Movements Detail Screen</i>	8-42
ALL STOCKROOMS FOR AN ITEM ENQUIRY	8-44
<i>All Stockrooms For An Item Enquiry Screen</i>	8-45
STOCK HISTORY ENQUIRY	8-47
<i>Stock History Enquiry Selection Screen</i>	8-48
<i>Stock History Enquiry Screen</i>	8-49
STOCK IN-TRANSIT ENQUIRY	8-50
<i>Shipments In Transit Enquiry Selection Screen</i>	8-51
<i>Shipments In Transit Enquiry Screen</i>	8-52
ALTERNATIVE ITEMS ENQUIRY.....	8-54
<i>Alternative Items Enquiry Selection Screen</i>	8-55
<i>Alternative Items Enquiry Details Screen</i>	8-56
CHAPTER 9 INVENTORY REPORTS.....	9-1
ITEM/STOCKROOM REPORT	9-2
DESCRIPTIONS FILE REPORT.....	9-4
ITEMS FLAGGED FOR DELETION REPORT	9-5
ITEM AUDIT REPORT.....	9-6
STOCKROOM AUDIT REPORT	9-7
STOCK VALUATION REPORTS	9-8
<i>Stock Movements Valuation Report</i>	9-9
<i>Stock Movements Valuation Record Report Selection Criteria Screen</i>	9-10
<i>Stock Valuation Report</i>	9-12
<i>Stock Valuation Record Report Selection Criteria Screen</i>	9-13
MOVEMENTS AUDIT REPORT.....	9-15
MOVEMENT REPORTS	9-16
<i>Movements Processed By AFI Report</i>	9-17
<i>Stock Movements Report</i>	9-19
Request Stock Movements Report Selection Screen	9-20
REPORTING ON NEGATIVE STOCK	9-22
<i>Negative Stock Report</i>	9-23
<i>Negative Stock Periodic Parameters Report</i>	9-25
NON-MOVING ITEMS REPORT.....	9-26
<i>Report On Non-Moving Items Selection Screen</i>	9-27
<i>Report On Non-Moving Items By Stockroom Range Screen</i>	9-29
<i>Report On Non-Moving Items By Item Range Screen</i>	9-31
NEGATIVE LOCATIONS REPORT	9-33
Request Negative Locations Report Selection Screen.....	9-34
RE-ORDER/OVERSTOCK REPORT	9-35
<i>Re-Order/Overstock Report Screen</i>	9-36
STOCK AVAILABILITY REPORT	9-37
SUPPLY/DEMAND EXCEPTIONS REPORT	9-39
ROTATION FACTORS REPORT	9-41
<i>Stock Rotation Factor Report Selection Screen</i>	9-42
<i>Stock Rotation Factor Report By Stockroom Screen</i>	9-44
<i>Stock Rotation Factor Report By Item Screen</i>	9-45
CHAPTER 10 INVENTORY MANAGEMENT UTILITIES.....	10-1
LOCATION CONTROL INTRODUCTION	10-2
COMPANY PROFILE MAINTENANCE.....	10-7
<i>Maintain Company Profile Selection Screen</i>	10-8
<i>Maintain Company Profile Aspect Selection Screen</i>	10-9

<i>Maintain Company Profile Initial Selection Screen</i>	<i>10-10</i>
All Serial Parameter Window	10-15
Secondary UOM Window	10-19
<i>Extended Options Window</i>	<i>10-20</i>
Reference Number Entry Window	10-22
<i>Maintain Company Stockroom Profile Screen.....</i>	<i>10-23</i>
<i>Advanced Allocations Options Screen</i>	<i>10-26</i>
<i>Maintain Company Profile Stock Weeks Matrix Screen</i>	<i>10-28</i>
<i>Maintain Location Control Stockroom Profile Screen.....</i>	<i>10-31</i>
<i>Maintain Location Map Screen.....</i>	<i>10-34</i>
Location Control Number Of Locations Window	10-36
<i>Maintain Location Map Locations Screen</i>	<i>10-37</i>
<i>Select Usage Code Window</i>	<i>10-39</i>
<i>Usage Profile Screen.....</i>	<i>10-40</i>
STOCKROOM SITE MAINTENANCE	10-42
<i>Stockroom Site Maintenance Selection Screen.....</i>	<i>10-43</i>
<i>Stockroom Site Maintenance Screen.....</i>	<i>10-44</i>
Reference Number Entry Window	10-46
REFERENCE NUMBERS	10-47
<i>Maintain Reference Numbers Selection Screen.....</i>	<i>10-48</i>
<i>Maintain Reference Numbers Screen.....</i>	<i>10-49</i>
DOCUMENT TEXT PROFILES	10-50
<i>Document Text Profile Maintenance Selection Screen.....</i>	<i>10-51</i>
<i>Document Text Profile Maintenance Details Screen</i>	<i>10-52</i>
DEFAULT TEXT TYPES	10-54
<i>Default Text Maintenance Screen.....</i>	<i>10-55</i>
COPY COMPANY	10-56
REBUILD ITEM SEARCH	10-57
RENUMBER ITEM SEARCH WORDS	10-58
LOCATION BALANCE DATA TAKE ON	10-59
SET BALANCE QUANTITIES TO ZERO	10-61
BUILD ITEM DELETION LOGICAL FILES	10-62
DATABASE INTEGRITY	10-63
RECONCILING DEMAND	10-65
<i>Allocation Reconciliation</i>	<i>10-66</i>
<i>On Order Reconciliation</i>	<i>10-67</i>
AUDIT NEGATIVE FIFO	10-68
REBUILD BALANCES FROM LOCATIONS	10-69
RECALCULATE NOMINAL SEC VALUES.....	10-70
COMPANY DELETION.....	10-71
DELETE HISTORY AND MOVEMENTS	10-72
<i>Delete History And Movements Screen.....</i>	<i>10-73</i>
DELETE FIFO/LOT DETAILS	10-74
<i>Delete FIFO/Lot Details Screen</i>	<i>10-75</i>
PURGE STOCK COUNTS	10-76
<i>Purge Stock Counts Screen.....</i>	<i>10-77</i>
PURGE COUNT DETAILS/ACTION LISTS.....	10-78
<i>Count Details And Action List Purge Screen.....</i>	<i>10-79</i>
ITEM DELETION.....	10-80
<i>Item Deletion Window</i>	<i>10-81</i>
DELETE SHIPMENT RECEIPTS	10-83
AUDIT FILE PURGE MAINTENANCE.....	10-84
<i>Audit File Purge Maintenance Selection Screen.....</i>	<i>10-85</i>
<i>Audit File Purge Maintenance Details Screen</i>	<i>10-86</i>
SUBMIT AUDIT FILE PURGE.....	10-87
<i>Submit Audit File Purge Screen.....</i>	<i>10-88</i>
AUDIT PURGE MACHINE MANAGER PARAMETERS	10-89

<i>Audit Purge Machine Manager Parameters Screen</i>	10-90
PURGE LOCATION ALLOCATION DETAILS.....	10-91
PROCESSING PROFILES	10-92
<i>Inventory Processing Profile Maintenance Selection Screen</i>	10-93
<i>Inventory Processing Profile Maintenance Screen</i>	10-94
<i>Inventory Processing Profile Maintenance Detail Screen</i>	10-95
TEST.....	10-98
<i>Prompt For Inventory Trial Extract and Update Screen</i>	10-99
LIVE	10-101
INSTALL INVENTORY/AFI LINK.....	10-102
<i>AFI Data Dictionary</i>	10-104
<i>Activating The Link</i>	10-107
<i>Library List</i>	10-108
CHAPTER 11 BACKGROUND PROCESSING	11-1
START AND END STOCK MONITOR.....	11-2
START AND END RESERVATION MONITOR.....	11-3
START AND END PRICING MONITOR.....	11-4
START AND END INVOICE REFRESH MONITOR	11-5
START AND END RESTRICTIONS MONITOR	11-6
START AND END STOCK UPDATE MONITOR.....	11-7
CHAPTER 12 INVENTORY APPLICATION INTERFACE	12-1
RECEIVE PRODUCT ACTIVITY DATA	12-2
PRODUCT ACTIVITY DATA	12-3
<i>Inbound Product Activity Data Error Screen</i>	12-4
<i>Error Inbound Product Activity Header Selection Screen</i>	12-6
<i>Inbound Product Activity Header Maintenance - Error Recovery Screen</i>	12-7
<i>Untitled Line Selection Window</i>	12-8
<i>Inbound Product Activity Line Selection - Error Recovery Screen</i>	12-9
<i>Inbound Product Activity Line Detail Maintenance - Error Recovery Screen</i>	12-10
<i>Inbound Product Activity SDQ Details Maintenance - Error Recovery Screen</i>	12-11
<i>Inbound Product Activity PO Numbers Maintenance - Error Recovery Screen</i>	12-12
GLOSSARY	A
GLOSSARY	B

-
-
-
-
-

Chapter 1

Inventory Maintenance

Inventory Maintenance Introduction

You use Inventory's maintenance options to create and amend the master files and parameters that are fundamental to its operation.



Note: Use file maintenance, particularly description file maintenance, with extreme care since errors have far reaching effects. Introduce a proper procedure of authorisation and post maintenance checking.

You can use the master file enquiries to view the information you have specified in the maintenance options, and are not separately described.

Associated Applications

Inventory Management is a pre-requisite for all Customer Service, Logistic and Production applications. In a full implementation Inventory Management provides both basic data definition and transaction control for these applications.

Implementation Considerations

Before you start to use Inventory you need to consider:

- Which other applications you plan to install.
- How many companies do you need to set up within Inventory?
- How do you want Inventory to fulfil the information requirements for these applications?
- Will you use Inventory, or the other applications, to control the various stock movement transactions?
- Do you plan to interface non standard or vertical applications with Inventory?

Basic Data Setup

Once you have decided how you want to use Inventory you need to set up:

- Company profiles for each company you want to use within Inventory.
- Stockrooms and Stock weeks matrices.
- Usage profiles.
- Descriptions.
- Items.
- Stockroom Details.
- Calendars.
- Alternative items (if applicable).

Descriptions Maintenance



1/INM & 6/INUM & 1/INV & 3/SAM

Inventory Management, and many other Customer Services & Logistics applications, use the descriptions file to determine parameter values for the application.

The software uses parameter files for a number of reasons, for example, at data entry time instead of long repetitive data.

Once set up and checked, parameter files help to make sure that data input is both accurate and acceptable to the software.

An example of the use of the description file is for the usage cycle. When you set up an Inventory company profile you must set up a usage cycle code; this field determines whether the stock history records should be summarised at a weekly or monthly level.

Use this option to enter and use parameters, codes that relate to a single function are grouped together. The identifier for a group of codes is called the major type. The members of any group are the descriptions codes.

Descriptions File Maintenance Selection Screen



Select Descriptions.

Use this screen to add or maintain definitions of major types.

```
IN037              NR - Neil Radford and Co. Ltd      USER GBJBA1MS    6/13/96
                                                    10:13:44

Descriptions File Maintenance

Description type..... TYPE
Major type..... _____
Description code..... _____

Desc'n I.D.      Description                                Limit
ACDF             AC Terminology Definitions                30
ADFM             Address format                            30
AEDI             Automatic Update from EDI                  30
ALTT             Alternative Item Type                       30
AN              Agencies                                    30
ARPM             Arrears Processing Method                  30
ASAD             AS Address Type Codes                      30
ASTA             Article Status Code                        30
AUMD             Authorisation Method                       30
BCFM             Bank Code Format                            30
                                                         +

F3=Exit  F15=Description code details

06-30    SF      MW      KS      IM      II  KENB20A  PET178S2
```

Fields:

Major Type

Enter a major type to add or maintain.

Description Code

Enter a description code to add or maintain.

Functions:

F15=Description Code Details

Select to add or maintain low level codes for a major type.



Tip: Page Up and Down to display subsequent screens when appropriate.



To display details about a specific major type enter the major type and press **Enter**.

Descriptions File Major Type Codes

ADFM

Address Format. You can create address formats using up to two characters for use in World Trade.

ALTT

You can create single character item reference types. These are used in Advanced Order Entry.

AN

Five character maximum length. Agent, sub-agent. Sales order processing agents and sub agents. You can use the agents and sub-agent codes that you set up here within Sales Order Processing Commissioning processes.

BCFM

Bank Code Format. You can create bank code formats for World Trade, using up to two characters.

CALT

Calendar. You can create calendar codes for World trade, using up to three characters. As a minimum you must have the following codes:

001 - Intrastat.

002 - ESL.

CARR

Carriers. Sales and purchase order carrier codes.

CCCC

Customer Class. This is a two-character field displayed on the Customer Sales Details Screen within Customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database.

CCRQ

Certificate of Conformance required. If you are using Advanced Order Entry you can decide whether to use Certificate of Conformance. To do this you must select one of the following on the Item Maintenance Screen:

0 - Certificate cannot be entered.

1 - Certificate can be entered.

2 - Certificate must be issued.

CDSC

Cash Settlement Discount. This is a two-character code to identify the cash settlement discount given to a customer. Enter the code on the Customer Sales Details Screen in Sales Order Processing. At order entry, the code will default to the order header, but can be overridden. The percentage rate assigned to the code is included with the invoice details when posting to Accounts Receivable.

CHST

Character Set. These are two-character Character sets for use in World Trade.

CRDC

Enter one of the following:

0 - Existing credit checking only in Sales Order Processing and Advanced Order Entry.

1 - To choose additional SOP and AO credit checking methods by a credit check value and credit check by days or both. See CRLV and CRLD.

CRLV

Credit Check by Value.

Select one of the following:

0 - Your customers are not credit checked on a value entered in the Customer Master file.

1 - To perform a credit limit value check. You can then enter a value against the Credit Limit field in Customer Maintenance.

CRLD

Credit Check by Days.

Select one of the following:

0 - Do not perform credit checking by number of days for your customers.

1 - Debtor Days. So that the total debtor days do not exceed the credit limit days set up for the customer.

2 - Days Sales Outstanding. The total days outstanding do not exceed the credit limit days set up for the customer.

3 - Average Days to Pay. The average days to pay do not exceed the credit limit days set up for the customer.

4 - Average Days Slow. The average days slow do not exceed the credit limit days set up for the customer.

5 - Overdue Days. The number of days overdue of the oldest outstanding invoice does not exceed the credit limit days set up for the customer.



Note: You can only apply this policy to level 1 and level 3 accounts in customer hierarchies.



Note: CRLD options 1, 3 and 4 are calculated by the A/R debtor ratio routines. For more information see Trend Parameters in Accounts Receivable.

CRV4

For the current system date to display, you should set up CRV4 with a Description Code of 01, and Description CR Conditioning.

DEPT

Departments. In Production, if you want MRP to balance item supply and demand by stockroom rather than organisational model, then you must provide a range of Production cell codes. Codes are linked to individual stockrooms via Inventory Management, Maintain Company and Stockroom Code.

The Equivalent codes must exist on the Production Parameters file.

DFLT

These are Advanced Order Entry defaults. The only code in this major type is QTNO. You can hold the default Quotation Type code as the first character of the description of this code. Use this to produce quotations as the default order mode.

DIRE

Direction to Move in Warehousing. If you are using Item Location Rules, you must use one of two one character codes 1 (ascending) and 2 (descending) on the Maintain Location Rules - Item Screen in Warehousing module.

DIVN

Inventory Production Division.

A two character code on the Item Maintenance Screen. This is normally selected as one of the six item attributes when defining the Sales Analysis database.

DMND

Demand reference codes used in Advanced Order Entry. You must the following codes:

- 1 - Sales order.
- 2 - Purchase order.

DN

Customer Division

A two-character field on the Customer Sales Details Screen within Customer Maintenance. This is normally selected as one of the six customer attributes when defining the Sales Analysis database.

DNTE

Picking Note Print Time Fence.

This provides the default Lead Time field value on the Request Picking Notes Screen within Sales Order Processing. You must create the code T, enter the number of days lead time you want to use in the Rate field.

DOCT

Print Function in Order Entry.

Used for Forms Lengths Overrides for despatch notes and picking notes, to override the default settings for the printing areas (10 characters maximum).

EDI

EDI Application Interface.

ADEPOT - This is the default stockroom used in the batch allocation run.

ALLOCATE - Select 1 to run batch allocation from Receive Inbound prompt, after receive order processing has completed.

CATLREPT - Used in the Print Electronic Catalogues prompt. Select 0 for the report to include sent records. Select 1 for the report to include all records.

PRICETPCNT, PRICETVALU - Pricing Tolerance percentage and values allow comparison of prices sent through EDI and in System 21 database.

QUANTTPCNT, QUANTTVALU - When quantity changes occur through a purchase order, these tolerance limits define the extent of the change. If outside these limits, it will not accept the change and will print an error message.

TRANSLEAD - You decide whether the display for lead time offset is in calendar days or weekdays.

EGLR

Extended General Ledger codes for Purchase Management. When you enter Inventory items on purchase orders this retrieves extension codes to the GL account codes. Set up the subcodes:

01 - AFI rule for stock extended GL codes.

02 - AFI rule for price variance extended GL codes.

GDAR

Packaging Reporting - Adjustment Reasons.

GDRC

Packaging Reporting - Responsibility codes:

01 - Extractor.

02 - Manufacturer.

03 - Filler.

04 - Retailer.

GDRF

Packaging Reporting - Report format. Should include:

GER - German Duales Format.

Positions 6 and 7 of the parameter limit for the above descriptions have special uses:

- Set Position 6 to 1 to print a yearly report - which should only be used for the German format.
- Set Position 7 to 1 to de-activate track responsibilities. In this case you can enter responsibilities after the no tracking message, but the overrides would not be effective unless you set this parameter back to 0.

GDSC

Packaging Reporting - Sales Channels. You must have the following codes:

00 - No Sales Channel.

01 - Division.

02 - Sub-division.

03 - Region.

04 - State.

05 - Territory.

06 - Salesman.

07 - Customer Class.

08 - Corporation.

09 - Branch.

HLCO

Hierarchy Level Codes. You use these codes in Advanced Shipping to define the order in which details are printed on Advanced Shipping Notes.

I - Item

O - Order

P - Pack

S - Shipment

T - Tare

INSC

If you are using Configurator, you must enter a one-character code to define the item's Inventory source on the Item Maintenance Screen.

LGCD

Language Format. You can set up two-character language codes to use in World Trade.

LPRT

Print Code. You use these values in World Trade to validate the entries in the Intrastat/ESL print code in country maintenance. The value is concatenated with WT805PT to give the printer file used for Intrastat printing. Make sure you set up a printer description for each version of the printer file in OSLWTD3.

The following codes should already exist on the Descriptions file. You may need to add extra Minor Types.

FR - French.

DE - German.

BE - Belgian.

DK - Danish.

NL - Dutch.

IT - Italian.

SP - Spanish.

SE - Swedish.

GB - British.

MISC

Miscellaneous Company Level Descriptions.

CNFQ - Used in Advanced Shipping, Confirm Despatch Quantity Default. Set the limit to one of the following:

- 1 - To default to the quantity you need
- 2 - To default to the available quantity.
- 3 - To default to zero quantity, or any other value.

DSTL - Used in Advanced Order Entry and Sales Order Processing, Despatch over tolerance is held as the rate against this description code.

IDMP - Used in Inventory Management, Add the Item Deletion Movement Period Ago for the Item/Stockroom Deletion routines. The Rate field should state the number of periods back from the current period, during which time item stockroom deletion is

not allowed if any stock movements exist. If IDMP is not defined, all items flagged for deletion are deleted during the Item Deletion Routine.

PRCD - Used in Advanced Shipping, Set the first character of the description to one of the following:

0 - To select the invoice price from the contract.

1 - To select the invoice price from the standard price list.

MODE

Despatch method. Create a single character code. You must configure Sales and purchase order despatch methods.

You must define the following modes of transport for World Trade:

1 - Sea.

2 - Rail.

3 - Road.

4 - Air.

5 - Post.

7 - Fixed installations.

9 - Own propulsion.



Note: Take care that other Minor Types are not reported on an Intrastat.

MOVR

Movement Reason Codes.

Optional two-character field on most stock movement transactions within Inventory Management to track why a transaction is being processed. This is mandatory for stock count reconciliation where adjustments are generated.

Within Production, the following activities prompt for reason codes: scrap, hold, hold WIP, release held WIP, scrap held WIP, transfer WIP, allocate WIP, de-allocate WIP, adjust WIP, unexpected (unplanned) output and work station status.

You require codes when booking scrap and held quantity during item, order and operator booking. You can allocate the total quantity to more than one code during a session.

You can enter a default scrap order on the Production software, organisational model definition.

MVTP

Movement types.

Single character codes must exist because all Inventory transactions are created with one of the following codes and descriptions for movement types:

A - Stock Adjustment.

C - Customer Order Issue.

D - Direct Delivery.

F - Frozen Adjustment.

G - Frozen Transfer Out.

H - Frozen Transfer In.
I - Transfer In.
J - Transformation.
K - Frozen Issue.
L - Allocated Adjustment.
M - Manufacturing Issue.
N - Manufacturing Receipt.
O - Transfer Out.
P - Purchase Receipt.
Q - Back to Back.
R - Misc. Receipt.
S - Misc. Issue.
T - In-Transit Adjustment.
U - Purchase Order.
W - Manufacturing Adjustment.
X - LIFO Revaluation Adjustment.
0 - No movement to be generated.

For movement types used in Inventory Management, you can set the limit field to control whether movement reference, reason code and movement reference codes are mandatory.

You can set the limit field as follows:

Limit Field	Reference Mandatory	Reason Code Mandatory	Reference Type Mandatory
00	No	No	No
01	Yes	No	No
10	No	Yes	No
11	Yes	Yes	No
20	No	No	Yes
21	Yes	No	Yes
30	No	Yes	Yes
31	Yes	Yes	Yes

NOTN

Nature Of Transaction. You should set up the following two-character codes, for Intrastat reporting in World Trade:

10 - Standard transaction.
16 - Credit.
17 - Credit, with no goods movement.

- 20 - Replacement.
- 30 - No consideration.
- 40 - Movement before process/repair.
- 50 - Movement after process/repair.
- 58 - Process element.
- 60 - No change of ownership.
- 70 - Joint defence or government.
- 80 - General construction.
- 90 - Other.

You should set up additional codes for Intrastat and ESL reporting as follows:

- France, Germany, Spain or Denmark - Codes 11, 21, 31, 41, 42, 51, 52 and code 61.
- France, Germany or Spain - Codes 12-15, 22, 23, 32, 33, 43, 53, and code 62.
- France or Denmark - Codes 70 and 80.
- France - Code 90.
- Germany - 71, 72, 81, and 91.
- Spain - Codes 7-9 and code 34
- Italy, Belgium, Holland & Sweden - Codes 1-9.

ORDM

Ordering methods.

Used within Advanced Order Entry with or without Configurator. You must use the following codes, specified on the Item Master. You can override these codes during order entry:

- 0 - Normal Stocked item.
- 1 - Make to Order.
- 2 - Purchase to Order.
- 3 - Deliver Direct.
- 4 - Reserve.
- 5 - Configure to Order.

ORTP

Order type.

If you are using Warehousing module you must use the following codes:

- 1 - Sales Order.
- 2 - Production Order.

PCLS

Item Class. Optional two-character field on the Item Master Maintenance Screen to classify inventory items. You can request stocktake count sheets by a range of item classes. In addition, this field is normally selected as one of six item attributes when defining the Sales Analysis database.

PGMJ

Item Group Major. Optional three-character field on the Item Master Maintenance Screen to classify Inventory items. You can request stocktake count sheets and various reports by a combination of major and minor group codes. In addition, this field is normally selected as one of the six item attributes when defining the Sales Analysis database.

PGMN

Item Group Minor. Optional three-character field on the Item Master Maintenance Screen to classify Inventory items. You can request stocktake count sheets and various reports by a combination of major and minor group codes. In addition, this field is normally selected as one of the six item attributes when defining the Sales Analysis database.



Note: It is important to configure the codes appropriately for use within Production. These codes are used to group similar items into product families for use by MPS and MRP forecasting. Similarly in Forecasting and for DRP.

PGR

Discount group. Three characters maximum. Used to group items that earn the same discounts on a discount list when standard pricing is in use.

PLDL

Place Of Delivery. You can set up five-character place of delivery codes for use in World Trade.

PORT

Ports. You can set up five-character port codes for World Trade use.

PREM

Used in EDI to define Premenos User Files.

You can enter a list of document IDs and related text descriptions. This relates to the Document ID field in the Maintain Document IDs Screen.

P RTP

Pricing Functions. These price function codes are used in combination with pricing type codes in Advanced Pricing to set up pricing type profiles.

- 1 - Discount.
- 2 - Price.
- 5 - Whole Order discount.
- 6 - Retrospective discount.
- 7 - Special allowance discount.

PTYP

Item type. Optional one-character field on the Item Master Maintenance Screen to classify Inventory items. You can request stocktake count sheets by a range of item types. In addition, this field is normally selected as one of the six item attributes when defining the Sales Analysis database.

You would normally define four codes used by Service Management to determine contract charging. These, typically, are:

- Major Spares.
- Minor Spares.
- Consumables.
- Supply Items.

See System Parameters Maintenance Screen 3 in Service Management for details on how to use these codes.

QTNO

Used in Advanced Order Entry to record Quotation type codes. Set up single-character quotation type to identify the type of quote (such as 30 days, 60 days, and so on). You use this code to identify an order as a quotation in order entry. The rate is a value, added to current date, to calculate expiry date for quotations. If 1 or 2 is in the VAT field, order lines will be allocated.

REOP

Inventory Re-order Policies.

Enter one of the following five codes on the Item/Stockroom Maintenance Screen if you want to use re-order points within Inventory Management.

- 1 - Up to MAX.
- 2 - ROQ.
- 3 - Up to MIN.
- 4 - Up to ROP.
- 5 - EOQ.

RFCR

Invoice/Credit Note Reason Codes. The code identifies why you are raising an invoice or credit note and is found on the Misc. Invoice or Credit Note Header Screen.

Set the limit field within the code to 0 if you want the invoice/credit note to update Sales Analysis with quantity, sales value and cost. Set the limit field to 1 if you do not want the invoice/credit note to update Sales Analysis with sales value and cost only.



Warning: The reason code 0 must exist, otherwise the Invoice Print Program will not work.

RGME

Regime. Assign Regimes (World Trade) to Movement Transport Information and included on Intrastat and ESL reporting. Set up codes for French and Italian reporting:

- France - Codes 11, 19, 21, 22, 25, 26, 27 and 29.
- Italy - Codes 1-6.

RGNO

You can set up three-character regions of origin for use in World Trade. Regions are assigned to EC Movements and included on Intrastate and ESL reporting.

Examples: CA Catalina, NE Northern England, NI Northern Italy.

RSNC

Reason code.

RFTP

Reference Type.

SCRC

Scrap/Reject Reason Codes. This is a two-character field on the Returns/Scrap/Adjustment Enquiry Screen within Customer Returns; it identifies why you are scrapping a returned product.

Enter 1 in the VAT field against a reason code to not generate a credit for the goods scrapped/rejected.

SDIV

Item Sub division. This is a two-character field on the Item Maintenance Screen. Normally selected as one of the six item attributes when defining the Sales Analysis database.

SHLU

Shelf life units. If you are using extended Lot, Batch or Serial control you must use this code. It is found on the Item/Stockroom Maintenance Screen. You can select one of the following codes to identify how to measure shelf life:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.
- 5 - Indefinite.

SN

Customer Region.

This is a two-character field on the Customer Sales Details Screen within customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database.

SPXV

Spex version. Used to determine the installed version of SPEX.

- 00 - Default SPEX Version.
- 01 - SPEX/400 EU version.
- 02 - SPEX for Windows installed.

SRCE

Used in Advanced Order Entry to define Source/supply types. The following codes must exist:

- 1 - Batch.
- 2 - Sales order.
- 3 - Purchase order.
- 4 - Requisitions.

ST

Customer State. This is a two-character field on the Customer Sales Details Screen within Customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database.

STKF

Non Stock Item Type. If you are using Advanced Order Entry, this is a one-character field on the Item Master Maintenance Screen that identifies the type of non stock item.

STKS

Used in Inventory to define Stock status codes for items with lot, batch or serial control with shelf life.

Two character codes, used when stock is frozen or unfrozen from the Lot Maintenance options, or by the Stock Status Monitor.

You must set the Limit to 1 if you want to freeze stock, and blank or zero for codes to unfreeze stock.

FZ - Frozen.

F2 - Frozen.

RL - Released.

UN - Unfrozen.

STKU

Stockroom Usage Code. This is a two-character field on the Stockroom Maintenance Screen within the Inventory Management company profile.

STRM

Inventory Storage Method. This is a one-character field on the Item Master Maintenance Screen.

SUNC

Miscellaneous Order Charge Codes. This is a two-digit field to identify a miscellaneous charge you can add to the Order Trailer Screen during order entry, order amend or confirmation of despatch. You can only define the charge code as a value in base currency with mandatory domestic rate VAT code (or tax code in US.) Currency conversion to prime values and change of VAT code occur automatically when codes are applied to prime currency orders.

SUSP

Order Suspend Codes. A two-character field on the order header to identify why an order is suspended together with the use of the VAT field to prevent auto de-allocation. You must define at least eleven codes, for example:

CS - Customer on credit stop.

CL - Credit limit exceeded.

FP - Fixed price item.

NP - Item not priced.

You can define additional codes, however you must manually enter these against an order.

If you set the VAT field to 1, you can suspend a fixed price line in Advanced Order Entry but still allocate allocated to that line. This does not affect Conversational Order Entry.

If an order is suspended:

- You cannot raise a picking note.
- You cannot adjust the allocation using Manual Allocation.
- You cannot adjust the allocation using Manual Allocation By Item.
- You can use Advanced Order Entry, Order Amendment to de-allocate or force allocate.

If you set the VAT field to 2, you can create order lines in Advanced Order Entry with back-to-back requisitions or reserved against purchase orders.

If you set the Rate field to 1, you cannot use the code to suspend orders; for example, you could set code FP so that fixed price orders are not suspended. This only applies to the following default codes: NP, NV, FP and user defined codes.

SV

Customer Sub-Division.

This is a two-character field on the Customer Sales Details Screen within Customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database.

TAR

Tariff. Any eight-digit commodity codes should be set up for use in World Trade.

TDEL

Terms Of Delivery. Set up three character terms of delivery for World Trade as follows:

EXW - Ex Works.

FOB - Free on Board.

CIF - Carriage, Insurance & Freight.

DDU - Delivered Duty Unpaid.

DDP - Delivered Duty Paid.

XXX - Other.

TMTH

Transport method.

TN

Salesman. Required five-character field on the Customer Sales Details Screen within Customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database. You can use the salesman codes that you set up here within Sales Order Processing Commissioning processes.

TPAR

Used in Transport Planning, Adjustment Reasons - you must use these if you use carrier rating and there is a variance when authorising carrier payments.

01 - Mistake in Manual Rating.

02 - Old Rate Codes Used.

03 - One-off Deal.

TPBL

Used in Transport Planning, Bill of Lading format. You must define four codes if you want to use bills of lading when you maintain transport routes. The codes are:

01 - One document per load.

02 - Document per drop/delivery point.

03 - One document with drop details.

04 - One document details by area.

TPCC

Used in Transport Planning, Commodity code - eight characters maximum. You can use these when you define a transport centre.

TPCT

Used in Transport Planning, Carrier Type - four characters maximum. You can define these to categorise carriers.

TPCY

Used in Transport Planning, County - four characters maximum. You can define these for use when you set up Nodes.

TPDC

Used in Transport Planning, Default Capacity Type. Three codes must exist.

1 - Weight.

2 - Volume.

3 - Containers.

TPIC

Used in Transport Planning, Creation Of Requirements. The following codes must exist:

1 - Order creation.

2 - Allocation.

3 - Pick note creation.

4 – Commit (not used).

5- Confirm pick (not used).

6 - Confirmation of Despatch.

TPLS

Used in Transport Planning, Load status. The following codes must exist:

10 - Pending.

20 - A'printing.

30 – Allocated (not used).

40 – On pick (not used).

50 – Picked (not used).

- 60 - A'rating (Awaiting rating).
 - 70 - A'COD (Awaiting confirmation of load despatch).
 - 80 - A'auth. pay (Awaiting payment authorisation).
 - 90 - A'ledg. post (Awaiting posting of payment to the General Ledger).
 - 95 - A'hist (Awaiting drop to history).
 - 99 – Cancelled.
- Codes 30, 40 and 50 may exist but are not currently used.

TPPM

Used in Transport Planning, Payment Method - two characters maximum. You must define codes if you want to use carrier rating and therefore payment.

TPRM

Used in Transport Planning, Rating Method - you should create four codes if you want to use rating of loads.

- 01 - Load and rate table.
- 02 - Drop and rate table.
- 03 - Area.
- 04 - Area and rate table.

TPSE

Used in Transport Planning, Serious Errors - the following codes must exist:

- 01 - Sales order not found.
- 02 - Pick note header not found.
- 03 - Item record not found.
- 04 - Stockroom balance not found.
- 05 - Route specified not found.
- 06 - Time out for requirements update.
- 07 - Details changed after AFI post.
- 08 - Details changed after override.
- 09 - Global route change warning
- 10 - Possible capacity problems.
- 11 - Item transport prof. not found.

TR

Customer Territory. This is a two-character field on the Customer Sales Details Screen within Customer Maintenance. Normally selected as one of the six customer attributes when defining the Sales Analysis database.

TRAN

Movement Reference Type. This is a two-character field used on all Inventory transaction screens within Inventory Management. Use these codes to identify the type of source document used.

Production routines that involve Inventory movements prompt for transaction type codes.

TTYP

Text Type. This will determine the type of text entered and where on the documentation text will appear. Set up the following codes:

B - Batch reference text.

C - Customer text.

D - Certificate of Conformance text type.

I - Invoice Header text.

K - Carrier.

L - Order Line text.

O - Order Header text.

P - Item text.

T - Transport Load.

UNIT

Unit of Measure. This is a two-character field on the Item Master Screen. Unit of measure could be a purchasing UoM, stocking UoM or issuing UoM.

UOM

Units of measure codes for Catchweight - two character codes. Unit of Measure could be a purchasing, stocking or issuing UoM.



Note: You must define all secondary units of measure in both the major types UNIT and UOM.

USCY

Usage Cycle. Required, This is a one-character field on the Inventory Management Company Profile Maintenance Screen. Two codes must exist:

M - Average per Month.

W - Average per Week.

USGC

Text Usage codes. Determines where the text will appear within documentation. The codes include:

B - Batch Reference text.

C - Certificate of Conformance text.

E - External text.

I - Internal text.

P - Planner.

VAT

VAT codes. Use this if the company is not linked to the General Ledger, it is redundant if the General Ledger is linked.

Set up any new VAT codes created in the General Ledger for World Trade against major type VAT.

WAIT

Used in Transport Planning to define the wait type for temporary record locking, two six character codes must exist:

BATCH - Batch lock request. You should set the limit to five attempts to access a locked record, set the rate to 20 seconds to wait.

INTER - Interactive lock request. You should set the limit to five attempts to access a locked record, set the rate to two seconds to wait.



Note: You can use these codes to control how long a job waits for the release of a temporary record lock and how many times to try to achieve a lock for updates.

WHCS

Warehousing Commit List Sequence. If you are using Warehousing the following codes must exist:

- 1 - Order Sequence.
- 2 - Customer Sequence.
- 3 - Journey Sequence.
- 4 - Despatch Sequence.
- 6 - Consignment Sequence.

WHIS

Warehousing Item Sequence.

If you are using Warehousing, the following codes must exist:

- 1 - Item Sequence.
- 2 - Alternative Location.
- 3 - Location Sequence.

WHLS

Warehouse/List type. If you are using Warehousing, the following codes must exist:

- 01 - Put Away List.
- 02 - Pick List.
- 03 - Move List.
- 04 - Count List.

WHML

Move List by Sequence.

If you are using Warehousing, the following codes must exist:

- 1 - Warehouse.
- 2 - Area.
- 3 - Access Point for Dimension 1.

WHMS

Move List Sequence. If you are using Warehousing, the following codes must exist:

- 1 - Item.
- 2 - Arrival Time.

WHMT

Warehousing Movement Type. If you are using Warehousing, the following codes must exist:

- 1 - Put-away.
- 2 - Pick.
- 3 - Sundry Movement Planned.
- 4 - Sundry Movement Not Planned.
- 5 - Commitment Amendment.
- 6 - Count Reconciliation.
- 7 - Sundry Frozen Movement.

WHMV

Warehouse Movement Trans. If you are using Warehousing, the following codes must exist:

- AF - Frozen Stock Adjustment.
- AP - Physical Stock Adjustment.
- CI - Customer Order Issue.
- PR - Purchase Receipt.
- SI - Sundry Issue.
- SR - Sundry Receipt.
- IT - Transfer In.
- T0 - Transfer Out.
- 001 - Internal Warehouse Movement.

WHNL

No. Of Locations To Be Created. A code of MAX with a value in the limit field must exist. The entered value will default to the maximum Number Of Locations To Be Created field within Maintain Warehouse Map when creating new location codes.

WHPS

Warehousing Pick List Sequence. If you are using Warehousing, the following codes must exist:

- 1 - Warehouse Sequence.
- 2 - Area Sequence.
- 3 - Dimension 1 Sequence.

WHRS

Warehousing Reason Code. If you are using Warehousing, the following codes must exist:

- #1 - Put-Away Override.
- #2 - Commit Override.

- #3 - Replenishment Override.
- #4 - Instruction Overridden.
- #5 - Item/Pack Profile Missing.
- #6 - Item/WHSE Profile Missing.
- #7 - Planned Movement.
- #8 - Short Despatch Leave Frozen.
- #9 - Count Reconciliation.
- 99 - Short Despatch Leave Committed.



Note: Set the limit field for code 99 to 1 to leave stock committed.

WHSE

Warehouse Miscellaneous Parameters.

CDID - Confirm Despatch Session with a Rate/Value of 1 (this is system generated).

DTAQ - Data Queue Wait Time in Seconds, where the limit field sets the data queue polling delay in seconds.

EOFD - End of File Delay in Seconds, where the limit field sets the data queue polling delay in seconds.

ASPN - Produce Advanced Shipping Pick Notes, where 1 in the limit field means Yes.

Search Family Characteristic Codes

You can define Major types to act as characteristic codes, which are used in search family codes/certificates of conformance. If you want to use a major type in this way, enter V in the P/V field.

The description codes set up for each major type are the permitted values defined to the characteristic.

For example, you could have a major type (characteristic code) of COLR and descriptions (characteristic values) of Red, Pink and Blue.

Descriptions File Maintenance Screen



To display this screen enter a major type and select **F15=Description Code Details** on the Descriptions File Maintenance Selection Screen.

Or:

Select **F15=Description Code Details** on the Descriptions File Maintenance Detail Screen.

Use this screen to add or maintain Low Level Codes for a major type.

The upper part of the screen contains the details of the description code (or minor type) being maintained, the lower part, a list of the current description codes for the selected major type.

IN037	Z1 - GB Demonstration Company	USER GBJBA1MS	5/09/0
			12:03:5
Descriptions File Maintenance			
Description type.....	TYPE		
Major type.....	RFC		
Description.....	Reference Code		
Description limit.....	30	P/V... _	
Desc'n I.D.	Description	Limit	
A	aa Type	30	
ABCD	Lawrence	12	
ACD	bikram abcde3	30	
ACDF	Customer Schedule Definitions	30	
ADCD	ADCD	6	
ADFM	Address format	30	
AEDI	Automatic Update from EDI	30	
ALT	Grouter and Plasterer Monthly	100	
ALTM		30	
ALTT	Alternative Item Type	30	
F3=Exit F12=Previous F15=Description code details			
F23=Language descriptions			

Fields:

Description Type

This is your selected major type. The codes listed below this are all associated with this code. For example, if you select DIVN for sales divisions, the codes listed here would include S for sales, T for telesales and so on.

Major Type

Select a description code from those listed below to maintain one, or enter a new code and press **Enter** to create a new code.

Description

Enter the description for the description code, or minor type.

Parameter Limit

Enter up to seven numeric characters. This field is for information purposes only within Inventory Management.

Rate

Enter a rate using up to five numeric characters, two decimals. Use the rate for certain description types, such as extra charges, to define a rate associated with the major type. You define the nature of the rate by the percentage/value flag specified for this major type.

P/V

Enter one of the following:

P - Where the rate is a percentage basis.

V - Where the rate is a value basis.

VAT Code

Enter the VAT code using one character. You can use this to define VAT codes associated with extra charges.

Select (1)

Enter one of the following:

1 - To maintain the description code details.

2 - To add or amend different language text.

Functions:

F23=Language Descriptions

Use this to enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, to print any text entered in the specified language in the Maintain Text Window, on external documentation for that customer.



Note: You do not need to select Language codes to print text in the native language.



Press **Enter** to update the Description Code details.

Descriptions File Maintenance Detail Screen



To display this screen, select a specific major type for maintenance on the Descriptions File Maintenance Selection Screen and press **Enter**.

Use this screen to enter the details for the selected major type.

IN037	Z1 - GB Demonstration Company	USER GBJBA1MS	5/09/00
			12:04:48
Descriptions File Maintenance			
Description type...	RFC	Reference Code	Limit.. 30
Description code...			
1	Desc'n I.D.	Description	Limit VAT PV Rate
-	CREDITNOTE	Credit Note	.00
-	DELIVYNOTE	Delivery Note	.00
-	INTINVOICE	Internal Invoice	.00
-	INTTRANSFER	Internal Transfer	.00
-	INVOICE	Invoice	.00
1=Select 2=Language descriptions			
F3=Exit F12=Previous			

Fields:

Select (1)

Enter one of the following:

1 - Select. Use this to view the selected minor type code. This displays the Descriptions File Maintenance Selected Details Screen for your selected minor type code.

2 - Language Descriptions. Select this to view the Multi-Lingual Descriptions Maintenance Window for your selected minor type code.

Description

Enter up to 30 alphanumeric characters to describe the major type.



Tip: The value entered in the Description Limit field determines the maximum length of the description.

Description Limit

Enter up to two numeric characters to specify the length of the description associated with this major type up to a maximum value of 30.

P/V

This is percentage/value. Enter one of the following:

P - Where the rate is percentage based.

V - Where the rate is value based.



Tip: If you are defining a major type for use in perhaps a Certificate of Conformance code, then enter V in this field.

Functions:

F15=Description Code Details

Use this to add or maintain low level codes for a major type.

F23=Language Descriptions

Use this to enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, to print any text entered in the specified language in the Maintain Text window, on external documentation for that customer. (This is currently not used).



Note: You do not need to select Language codes to print text in the native language.



Press **Enter** to update the major type.

Or:

Enter a selection criterion in the 1 field and press **Enter** to display the next screen or window.

Descriptions File Maintenance Selected Details Screen



To display this screen, enter 1 next to a minor type code on the Descriptions File Maintenance Detail Screen and press **Enter**.

Use this screen to enter or amend details for the selected minor type. Any existing details are displayed.



Note: The screen is the same as the Descriptions File Maintenance Detail Screen, except that it also displays the Description, Parameter Limit, Rate, P/V and VAT code fields that relate to your selected minor type code.

IN037	Z1 - GB Demonstration Company	USER GBJBA1MS	5/09/00
			15:29:28
Descriptions File Maintenance			
Description type...	RFCD	Reference Code	Limit.. 30
Major type.....	CREDITNOTE		
Description.....	Credit Note		
Parameter limit....		Rate.. .00	P/V... _ VAT code.. _
1	Desc'n I.D.	Description	Limit VAT PV Rate
-	CREDITNOTE	Credit Note	.00
-	DELIVYNOTE	Delivery Note	.00
-	INTINVOICE	Internal Invoice	.00
-	INTTRANSFER	Internal Transfer	.00
-	INVOICE	Invoice	.00
1=Select 2=Language descriptions			
F3=Exit F11=Delete F12=Previous F23=Language descriptions			

Fields:

Description

Enter up to 30 alphanumeric characters to describe the minor type.



Tip: The value entered in the Description Limit field determines the maximum length of the description.

Description Limit

Enter up to two numeric characters to specify the length of the description associated with this minor type up to a maximum value of 30.

P/V

This is percentage/value. Enter one of the following:

P - Where the rate is percentage based.

V - Where the rate is value based.



Tip: If you are defining a minor type for use in perhaps a Certificate of Conformance code, then enter V in this field.

Functions:

F23=Language Descriptions

This is not used in this system.



Note: You do not need to select Language codes to print text in the native language.



Press **Enter** to update the minor type details and redisplay the Descriptions File Maintenance Detail Screen.

Items Maintenance




2/INM & 1/MDM & 1/SAM

Use this to create or amend the primary Item Master information. This information is primarily concerned with classifying and describing an item. The characteristics of these items are defined by the analysis codes. The use of these codes varies depending upon the needs of the company. You should note the following points:

- You use Minor product group as the main level of aggregation for the entry and maintenance of forecast data in MPS, MRP and DRP.
- You can request reports and stock counts in Inventory Management by part/style type, product class, major product group or minor product group.

Item Maintenance Selection Screen




Use this screen to specify the item code you want to create or amend.

IN002	AS - ALG Systems	USER STDFIN	3/02/00 12:30:05
Item Maintenance			
Item.....?.. _____			
F3=Exit F4=Prompt			

Fields:

Item

Enter the code of an existing item or a new code (15 characters alphanumeric) to add an item to the file. If you do not know the code for an existing item, prompt on this field to display the Item Master Scan Window.



Item Maintenance Static Detail Screen



To display this screen, select an item on the Item Maintenance Selection Screen and press **Enter**.

Use this screen to view and maintain data relating to the item. The current data for the item is displayed.



*Note: If you make an error and existing data is inadvertently overwritten, select **F12=Previous** before pressing **Enter** on the second screen to not save this data.*

IN002		Z1 - UK Demonstration Company		USER QS0	24/11/98
					14:40:29
Item Maintenance					
Item.....	5001	Suncream Factor 4 225ml			
Pallet Conv.....		Packaging Reporting Item.... (0/1)			
Volume.....					
Weight.....					
Effectivity start.....	10/08/94	Purchase pack.....			
Item type.....?	2	Medium Shelf Life			
Item class.....?	2	Medium Cost			
Item group major.....?	3	Toiletries			
Item group minor.....?	3	Sun Protection			
Division.....?	A	All Divisions			
Sub-division.....?	1	Bought In Item			
Purchase unit.....?	CA	Stock->purchase conv..... 25000			
Stock unit.....?	PL	Issue->stock conv..... 16.00000			
Issue unit.....	BX	Weight per selling unit.. 2250			
VAT code.....?	001	17.50 %			
Discount group.....?					
Inventory source.....?					
Sales analysis flag.....?	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.....	0	0=No,1=Yes	End date 0/00/00		
F3=Exit F4=Prompt F10=Val.Grp F12=Previous F21=Text entry F24=More keys					
MA		b		04/045	

Fields:

Untitled (Description)

Enter up to 36 alphanumeric characters, to describe the item. You use the description identify the item on enquiries and reports, and to build the alpha search words for the item.

(Named N)

Where Named N=1 to 3. These are the three user-defined item specification fields. Their use in the Inventory Management company is defined in the Specification N Description fields on the Maintain Company Profile Initial Selection Screen. The fields are eleven numeric characters with four decimal places.

Packaging Reporting Item

Enter one of the following:

0 - To exclude the item from the packaging report.

1 - To include the item in packaging reporting.

Effectivity Start

For a new item, enter the date from which the item can be sold, or added to the software. This field is useful if you want to find out how long the item has been used by the company.

Purchase Pack

Enter up to six alphanumeric characters to define the purchase pack for this item.

Item Type

Enter an item type chosen from those defined on the Descriptions file against major type PTYP.



Tip: Use the information held in this field to select items for stocktakes.

Item Class

Enter an item class chosen from those defined on the Descriptions file against major type PCLS.

Item Group Major

Enter a major item group chosen from those defined on the Descriptions file against major type PGMJ.

Item Group Minor

Enter a minor item group chosen from those defined on the Descriptions file against major type PGMN.

Use the above codes to classify similar items for reporting purposes and select items for the valuation of stock movements.



Note: Use Item group minor as a level of aggregation for the entry and maintenance of forecast data in MPS, MRP and DRP. Within Production, they are used to group items into product families. These product families may subsequently be used as a selection parameter on a selective MRP run.

Division

Enter a division chosen from those defined on the Descriptions file against major type DIVN.

Sub-Division

Enter a sub-division chosen from those defined on the Descriptions file against major type SDIV.



Tip: Use the above codes to define which division of the company has responsibility for this item.



Warning: You should use this code with the full knowledge of the implications to linked applications - Sales Analysis, Production and Forecasting.

If you use the Advanced Financial Integrator to maintain stock and sales values in the General Ledger, you should consider the definition of items. Appropriate coding makes the mapping to the Chart of Accounts easier.

Purchase Unit

Enter a unit chosen from those defined on the Descriptions file against major type UNIT.

The purchase unit defined here provides the default purchase ordering unit at the item stockroom level.

Stock Unit

If you only enter the stock unit, Inventory automatically enters the same unit of measure for issue and purchase units and enters 1 for the conversion factors.

Issue Unit

The issue unit defined here provides the default issue unit at item stockroom level, and is the default ordering unit for this item in Purchase Management. For example, if you raise a purchase order in crates, boxes and bottles for a single item, and the issue unit is bottles, all orders are expressed in the application in bottles only.



Note: Once you have defined the issue unit of measure for an item, you cannot change it.



Tip: The units of measure you specify in the above fields are the only valid units of measure to be used when ordering, moving, stocking and selling this Inventory item.

Stock To Purchase Conversion Factor

Enter up to nine numeric characters with five decimals to specify the relationship between the stock and purchase units. If stock and purchase units are the same, this should be 1. If, for example, stock units are Each and purchase units are Tens, this conversion factor should be 10.

Issue To Stock Conversion Factor

Enter up to nine numeric characters with five decimals to specify the relationship between the issue and stock units. If issue and stock units are the same, this conversion factor should be 1. If, for example, the issue unit is Each and the stock unit is Tens, this conversion factor should be 10.



Note: If the issue unit and the purchase unit are the same, the following condition must apply: The product of the Stock to Purchase and the Issue to Stock factors must be exactly equal to 1.

VAT Code

Enter a VAT code from those defined on the Descriptions file against major type VAT. The rate field is used to hold the appropriate VAT percentage. If you are using Sales Order Processing and Purchase Management or both this information is used to calculate the VAT payable on this item. If General Ledger is attached confirmation of the VAT code is via the General Ledger VAT code definitions.



Note: If you are using US Sales Tax then this field is not displayed and the Tax Charge Type field is displayed in its place.

Tax Charge Type

If you use US Sales Tax, then enter one of the following to determine how sales tax is applied to your selected item:

0 - Apply sales tax.

- 1 - To not apply sales tax.
- 2 - To apply sales tax depending upon the specified override rate.

Weight Per Selling Unit

Enter up to eleven numeric characters, four decimals to specify the weight of a single selling unit. If you use Transport Planning, the weight assigned to each item must be in the same unit of measure, for example, Kilograms. If this company is using Catchweight, the Secondary Value and Secondary UoM fields replace this field.

Secondary Value

If Catchweight is being used, this and the Secondary UOM field are displayed instead of the Weight Per Selling Unit field. The secondary value is the conversion between the item's issue unit and the item's secondary unit. If the item's issue unit is BOX and each box is 5KG then the secondary value and the unit of measure would equal 5.0 and KG respectively.



Note: You can use Catchweight with both standard Production items, and Production items that are attached to a Warehouse.

Secondary UOM

If you are using Catchweight, this and the Secondary Value field are displayed instead of the Weight Per Selling Unit field. This defaults to the unit of measure selected in Company Profile Maintenance. You can prompt for another unit of measure.

You can then use the secondary UoM for advanced pricing and discounting of sales orders of the item and the secondary values are passed to sales analysis.

If the item is a Catchweight item (see F9 function) then the stockroom costs are also expressed in this unit of measure.



Note: Both the Secondary Value and Secondary UOM fields must either be empty or have entries, otherwise an error message is displayed

Discount Group

You can group together items that have the same discounts on a discount list.

Enter a discount group using a three character alphanumeric code. These are defined against major type PGR in Descriptions Maintenance. Standard Pricing uses Discount groups; these are referred to in discount lists configured in Sales Order Processing.



Note: If Advanced Pricing is in use, this becomes a memo field.

Inventory Source

You can group together items that you want to update onto a price list.

Enter an Inventory source code using a one-character code, to indicate to which pricing group this item belongs. These are defined against major type INSC in Descriptions Maintenance.

Use Price List Updates to convert to a different currency, or when a percentage change in the price occurs. For more information see the Create New Price List Screen in Order Entry.

If you use Configurator, you need to define a specific and unique value for each of the following categories:

- Model items.
- Base items.
- Preconfigured items.
- Order configured items.
- Generic components.

In this case, JBA recommend that you use the M, B, P, O and G codes respectively. However, if any of these codes are already used in major type INSC, then you must use different codes.

Sales Analysis Flag

Enter one of the following to define Sales Analysis activities for kit items. These are set up under major type SAUI.



Tip: If you are creating a new item, then the value in this field defaults through from that specified in the Inventory company profile.

0 - You do not want to update Sales Analysis for this item.

1 - If this is a non kit item and should update Sales Analysis normally or this is the parent of a kit for which only the parent details should update Sales Analysis.

2 - This is the parent of a kit for which only component details should update Sales Analysis.

3 - This is the parent of a kit for which both parent and component details should update Sales Analysis.



Note: The Sales Analysis update for a kit is controlled by the flag on the parent. The flag on the kit component merely specifies the Sales Analysis update when you sell the component as an item in its own right. (For more information refer to Kit Lists.)

Flag Item For Deletion

Enter one to flag the item for deletion in the next Item Deletion run.



Note: The item is deleted after first checking that there are no outstanding transactions and that the end date entered in the End Date below has been reached.

End Date

Enter the date at which this item becomes available for deletion. Enter 1 in the Flag Item For Deletion field to delete this item using Item Deletion.

Functions:

F9=Sec Vals

If there are entries in both the Secondary Value and Secondary UOM fields, when you select **F9=Sec Vals**, the Secondary Value Details window is displayed.



Note: This function is only displayed if you are using Catchweight. For more information see Company Profile Maintenance.

F10=Val Grp

Select to display the group valuation criteria for the item you are maintaining.

F21=Text Entry

Select to display the Maintain Text window. Select a Usage Code and a Language Code for multi-lingual text entry. Press **Enter** to display the Item Text window. Enter text in the selected language to be displayed or printed on external documentation, for example despatch notes, according to the usage code selected.



Tip: You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can enter a different language to override this default language when **F16=Additional Overrides** function key is available.



Note: You do not need to select Language codes to print text in the native language.

F22=Purchase text

Use this to display the Item Text window.

F23=Language Descriptions

Use this to display the Multi-Lingual Descriptions Maintenance window, where you can enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text window will be printed on external documentation for that customer.



Note: You do not need to select Language codes to print text in the native language.

F24=More Keys

Use this toggle function to display all the available functions.



Press **Enter** to check all changed data, and to redisplay the Screen for confirmation of codes. Press **Enter** a second time with no intervening changes to display the Item Maintenance Costing Details Screen.

Secondary Value Details Window



To display this screen, enter details in both the Secondary Value and Secondary UOM fields, and select **F9=Sec Vals** on the Item Maintenance Static Detail Screen.



Note: This function is only displayed if you are using Catchweight.



Note: You can use Catchweight with both standard Production items, and Production items that are attached to a Warehouse.

Use this screen to define or amend Catchweight details for this item.

IN002		CW - Catchweight Company		USER GBJBA1MS	12/02/97
					12:06:36
Item Maintenance					
Item.....	CW1SN	Type1 Standard Not-Batch KG			
Pallet Conv					
Volume					
Area					
Effectivity start.....	24/09/96	Purchase pack.....			
Item type.....?	G	Gardening			
Item class.....?	90	Class 90			
Item group major.....?	2	Cosmetics			
Item group minor.....					
Division.....					
Sub-division.....					
Purchase unit.....					
Stock unit.....					
Issue unit.....					
VAT code.....					
Discount group...					
Inventory source....?					
Sales analysis flag.?	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.	@ 0=No,1=Yes	End date	0/00/00		
Secondary value details Catchweight item (1,2,3)..... 1 Secondary UOM..... KG Tolerance %..... 7.50 Tolerance value..... .0000 F12=Previous					
F3=Exit F4=Prompt F9=Sec vals F12=Previous F21=Text entry F24=More keys 14-S2 SP MW KS IM II KENB20A PET149S2					

Fields:

Catchweight Item (1, 2, 3)

Enter the usage category for this Catchweight item, which is either one, two or three, or leave the field blank. For more information, see the Usage Profile Screen in Inventory company profile.



Note: You can only define Production items as Catchweight items 1 or 2.

Secondary UOM

This field defaults to the unit of measure displayed in the Secondary UOM field on the Item Maintenance Static Detail Screen. This field is displayed for your information only and cannot be amended.

Tolerance %

When you capture an item's secondary value during a relevant transaction, you can enter a percentage in this field to set the default plus or minus degree of deviation from the expected nominal value. If you exceed this percentage tolerance a warning message is displayed. For example if you enter 5 in this field, any transaction that

exceeds the expected nominal value by plus or minus 5%, will cause the warning message to display.

Tolerance Value

When you capture an item's secondary value during a transaction, you can enter an absolute value in this field to set the default plus or minus degree of deviation from the expected nominal. If you exceed this fixed value tolerance a warning message is displayed. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5kg (if the UoM is kilos) will cause the warning message to display.



Note: Enter a number in either the Tolerance % field or the Tolerance Value field, you cannot enter a number in both.



Note: If both the Tolerance % or Tolerance Value fields are empty, then there is no tolerance and a warning is displayed for anything other than the default.



Select **F12=Previous** to update the details and return to the Item Maintenance Static Detail Screen.

Valuation Group Window



To display this window, select **F10=Grp Val** on Item Maintenance Static Detail Screen.

Use this window to define the group valuation criteria for the selected item. You use this information for Inventory Valuation or LIFO Revaluation purposes.

IN002	Z1 - GB Demonstration Company	USER GBJBA1MS	14/01/98 13:15:38
Item Maintenance			
Item.....	5011	Shampoo normal/dry 200ml	
Weight		Packaging Reporting Item.... (0/1)	
Volume			
Effectivity start.....	11/08/94	Purchase pack.....	
Item type.....?	3	Long Shelf Life	
Item class.....?	1	Low Cost	
Item group major.....?	3	Toiletries	
Item group minor.....?	6	Hair Care	
Division.....?	0	Domestic	
Item valuation by group..... 1 (0=No,1=Yes)			
Valuation group.....?.. 6 Hair Care			
Conversion factor (Issue to group unit).. .00000			
Group unit of measure.....			
Inventory source....?.. -			
Sales analysis flag... 1			
Flag item for deletion. 0 0=No,1=Yes			
Kit Parent Only (or Non-Kit)			
End date 0/00/00			
F3=Exit F4=Prompt F10=Val.Grp F12=Previous F21=Text entry F24=More keys			
17-50 SA MW KS CL IM DM II STUD140 KB PET087S1			

Fields

Item Valuation By Group

Enter one of the following:

0 - Do not assign this item to a valuation group.

1 - Assign this item to a valuation group.

Valuation group

Select a valuation group to which you want to assign this item. Enter a group chosen from those defined on the Descriptions file against PGMN. The group does not have to be the same as the minor item group previously assigned. It does have to have a UoM code in the VAT field, as this is the valuation group's UoM.

Conversion Factor

Enter a conversion factor using nine numeric characters, five decimals, to convert the item issue unit of measure to the assigned group unit of measure.

Group UOM

When you select a valuation group for the item, this group unit of measure information is automatically displayed.



Warning: As all items in a group are updated with the same cost using LIFO revaluation, you MUST take care when you define item groups.



Select **F8=Update** to process the details and return to Item Maintenance Static Detail Screen.

Maintain Text Window



To display this window, select **F21=Text Entry** on the Item Maintenance Static Detail Screen.



Note: This is a standard window, and is displayed in a number of different areas and applications.

Use this screen to select a Usage Code and a Language Code or both to specify where to print or display text, and in what language.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS	20/06/96
					14:33:05
Item Maintenance					
Item.....	1352_STD	1352 Standard Costed Item			
Pallet Conv	_____				
Volume	_____				
Weight	_____				
Effectivity start.....	5/07/95	Purchase pack.....	_____		
Item type.....?	C	S2/V3 : Consumables Spares			
Item class.....?	3	High Cost			
Item group major....?	Maintain Text				
Item group minor....?	Text Type..... P Item Text				
Division.....?	Text Reference.. 1352_STD				
Sub-division.....?	Usage Code...?.. _				
Purchase unit.....?	Language Code?..				
Stock unit.....?	F4=Prompt F12=Previous F13=Select existing Text				
Issue unit.....?	EA	Weight per selling unit.. _____			
VAT code.....?	2HB	%			
Discount group.....?	_____				
Inventory source.....?	_____				
Sales analysis flag.?	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.	0 0=No,1=Yes	End date	0/00/00		
F22=Purchase text F23=Language descriptions F24=More keys					
14-44	SA	MW	KS	IM	II KENB20A PET166S2

Fields:

Text Type

You can define up to ten combinations of default text.

Text Reference

This is the reference number given to a text type, which retrieves default text when no text exists for the selected usage or language code.

Usage Code

Select a usage code to specify where to display or print text.



Note: There are some standard text usage codes supplied with the Inventory application. You can define other usage codes in Inventory Descriptions Maintenance under major type USGC to suit your company's requirements.



Note: To enter text in multiple languages, enter a valid Language Code, along with the Usage Code, to display the Item Text Window.

Language Code

Select a valid language code, in addition to the usage code, if you want to enter multi-lingual text. The Item Text Window is displayed so that you can enter text in the language specified. Leave this field blank if you do not use multi-lingual text entry.



*Note: For multi-lingual text entry, you specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can, however, override this default language by entering a different language code when **F16=Additional Overrides** function key is available.*



Note: You do not need to select Language codes to print text in the native language.

Functions:

F13=Select Existing Text

Select this to list all currently defined usage and language code combinations for the entered text type text reference. You can select the combination you want to use for entering multi-lingual text.



Press **Enter** to display the Item Text Window.

Item Text Window



To display this window, enter a valid usage code in the Maintain Text Window and press **Enter**.

Or:

Select **F13=Select Existing Text** on the Maintain Text Window.

Use this window to enter, amend or delete text. Use the fields at the bottom of the window to move around the text and add or delete lines.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS	20/06/96 14:33:05
Item Maintenance					
Item.....	1352_STD	1352 Standard Costed Item			
Pallet Conv					
Volume					
Weight					
Effectivity start.....	5/07/95	Purchase pack.....			
Item type.....?	C				
Item class.....?	3				
Item group major.....?					
Item group minor.....?					
Division.....?					
Sub-division.....?					
Purchase unit.....?					
Stock unit.....?					
Issue unit.....?	EA				
VAT code.....?	3HB				
Discount group.....?					
Inventory source.....?					
Sales analysis flag.....?	1				
Flag item for deletion.	0 0=No,1=				

Maintain	
Text Typ	
Text Ref	
Usage Co	
Language	
F4=Prompt	

Lin	Batch	Reference	Text
1			
2			
3			
4			
5			
6			

Position to		Insert	after
		Delete	from

F5=Refresh F8=Update F12=Previous
F13=Change usage/language

F22=Purchase text	F23=Language descriptions	F24=More keys
12-42	SP	MW KS IM II KENB20A PET166S2

Fields:

Position To

Enter the number of the first line of text to appear at the top of the window.

Insert _ After _

Enter the number of lines you want to insert in the text as well as the number of the line after which they should appear.

Delete _ From _

Enter the number of lines you want to delete from the text as well as the first line number of the text to be deleted.

Functions:

F13=Change Usage/Language

Use this to redisplay the Maintain Text Window and enter or select a usage code and a language code for entering multi-lingual text.



Select **F8=Update** to update the text and return to the Item Maintenance Static Details Screen.

Item Purchase Text Window



To display this window, select **F22=Purchase Text** on the Item Maintenance Static Details Screen.

You can use purchase text as an alternative description for this item in Purchase Management.

You can review text entered against the item here at order entry time within the Purchase Management application. This text entry option is only available if Purchase Management is installed and is linked to this Inventory company.

The screenshot displays the 'Item Purchase Text' window. The main window title is 'IN002 Distribution V3 -> V3 Financials USER GBJBAMV1 14/11/95 14:19:06'. The main area is titled 'Item Maintenance' and contains fields for 'Item #1', 'Pallet Conv', 'Volume', 'Weight', 'Effectivity start' (18/03/95), 'Purchase pack', 'Item type', 'Item class', 'Item group major', 'Item group minor', 'Division', 'Sub-division', 'Purchase unit', 'Stock unit', 'Issue unit', 'VAT code', 'Discount group', 'Inventory source', 'Sales analysis flag', and 'Flag item for deletion'. A sub-window titled 'Item Text.' is open, showing a list of lines (1-6) for text entry. The sub-window also has fields for 'Position to', 'Insert', 'Delete', and 'After', and a 'from' field. At the bottom of the sub-window, there are function keys: F5=Refresh, F8=Update, and F12=Previous. The bottom of the main window shows a status bar with function keys: F3=Exit, F4=Prompt, F12=Previous, F21=Text entry, F22=Purchase text, 14-33, SA, MW, KS, IM, II, KENB20A, and PET129S1.

Fields:

Position To

Enter the number of the first line of text to appear at the top of the window.

Insert _ After _

Enter the number of lines you want to insert in the text as well as the number of the line after which they should appear.

Delete _ From _

Enter the number of lines you want to delete from the text as well as the first line number of the text to be deleted.



Select **F8=Update** to save new or amended details to file.

Multi-Lingual Descriptions Maintenance Window



To display this window, select **F23=Language Descriptions** from the Item Maintenance Static Details Screen.

You can enter or amend a language code and its description. You add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text window, will print on external documentation, for example despatch notes, for that customer.



Note: You do not need to select language to print text in the native language.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS	20/06/96
					14:33:05
Item Maintenance					
Item	Multi-lingual Descriptions Maintenance				
Pal	Code.....	1352 STD			Item
Vol	Description..	1352 Standard Costed Item			
Wei					
Eff	Language (?)	Description			
Ite					
Ite					
Ite					
Ite					
Div					
Sub					
Pur			1.00000		
Sto			1.00000		
Iss					
VAT					
Dis					
Inv	F4=Prompt F8=Update F12=Previous				
Sales analysis flag?... 1		Kit Parent Only (or Non-Kit)			
Flag item for deletion. @ 0=No,1=Yes		End date 0/00/00			
F22=Purchase text F23=Language descriptions F24=More keys					
09-11		SA	MM	KS	IM II KENB20A PET166S2

Fields:

Language

Enter a two-character language code, to represent a language you want to use.

Description

Enter the language name corresponding with the entered language code



Note: To delete a line, remove the language code.



Select **F8=Update** to update the file.

Item Maintenance Costing Details Screen



To display this screen, press **Enter** twice on the Item Maintenance Static Detail Screen.

Use this screen to maintain part of the data relating to the item. The current data for the item is displayed.

IN002		Z1 - GB Demonstration Company		USER GBJBA1MS		5/09/00	
						14:45:16	
Item Maintenance							
Item.....	5031	Paracetamol 100 tabs x 50 Box					
Superseded by.....?							
Supersession date.....	0/00/00	Date last changed....	5/09/00				
Costing method (S,L,A,F)	A	Purchases Account....	310000				
Standard cost.....		Sales Account.....	701100				
Latest cost.....		Cost of sales Account	601100				
Average cost.....		Price variance Acct..					
Base list price.....		Purchasing officer.?	00000				
Price regulator code.?	.00 %	Search family code.?					
Price list seq code....		C-of-C code.....?		Rqd?			
Warranty type.....?		Non-stock item type..					
Storage method.....?		Preferred supplier.?					
Shelf life unit.....?	1 Days	Ordering method....?	0 Normal Order				
Shelf life.....	24	Cust shelf life.....	18				
EEC tariff code.....?		Date..	0/00/00	Ref.	000000000000		
Duty %		Bar code.....					
Lot control (B/L/S/N)...	B	Inspection reqd.....	0 (0=No,1=Yes)				
Sub contract item....?							
F3=Exit F4=Prompt F12=Previous F17=Alias							
F18=Item search chars. F20=Lot header maint.							

Fields:

Superseded By

Enter up to 15 alphanumeric characters to specify whether this item has been, or is to be, superseded by another item. This is the superseding item reference number.

Supersession Date

If you have entered details in the Superseded By field, then you must enter the date on which the item was, or is to be, superseded.

Date Last Changed

This is a system-maintained field holding the date when you last changed the item details.

Costing Method

This indicates the method used to cost the item when received into Inventory. Although the costing method for the item remains the same in all stockrooms, each stockroom holds its own unique cost record, which may therefore vary.



Tip: Production does not use these default codes, but those associated with a specific stockroom.

Select one of the following costing methods for this item:

S - Standard. Enter the standard cost in the Standard Cost field on the second Stockroom Details Maintenance Screen.

L - Latest. Enter the cost of receipt in Miscellaneous Receipts.

A - Average. Enter the cost of receipt in Miscellaneous Receipts.

F - FIFO. Enter the cost of receipt in Miscellaneous Receipts.



Note: You only need to enter this field if you do not want the item costing method to be the same as the default costing method set up on the company profile.



Tip: You can enter information for any, or all, of the three following fields depending on the information that you want to hold for costing non stock items.

Purchases Account

Enter an account number of up to 12 characters.



Note: If you are using Purchase Management this is the account number to which the purchase invoices are posted. This defaults to the account number in the General Ledger Account field in the Maintain Company Profile Stock Weeks Matrix Screen.

Sales Account

Enter an account number of up to 12 characters. This is the account number to which stock transaction values are posted. This field defaults to the account number in the Sales GL Account field in the Maintain Company Profile Stock Weeks Matrix Screen.

Cost Of Sales Account

Enter an account number of up to 12 characters.

If you are using Sales Order Processing this is the account number to which cost of sales transaction values are posted. This field defaults to the account number in the Cost Of Sales GL Account field in the Maintain Company Profile Stock Weeks Matrix Screen.

Price Variance Acct

Enter an account number of up to 12 characters.

If you are using Purchase Management this is the account number to which accruals are posted. This field defaults to the account number in the Price Variance GL Account field in the Maintain Company Profile Stock Weeks Matrix Screen.

Purchasing Officer

Enter a purchasing officer as maintained in Purchase Management. You can prompt to display a list of valid purchasing officer codes if required.

Standard Cost

You use these costs as references for non stock items.

Latest Cost

You use these costs as references for non stock items.

Average Cost

You use these costs as references for non stock items.

Base List Price

Used in valuation of forecasts in Distribution Requirements Planning. You can use this price in Sales Analysis for kit components.

Price Regulator Code

Enter two alphanumeric characters chosen from those defined on the Descriptions file against major type PRC.

Price List Seq Code

Enter five alphanumeric characters.

Warranty Type

Enter a Warranty Type code chosen from those defined on the Descriptions file against major type WTYP.

Storage Method

Enter a storage method code chosen from those defined on the Descriptions file against major type STRM.

Search Family Code

This code, defined in Advanced Order Entry, defines up to 10 attributes of the item which are maintained using **F18=Item Search Chars**. These attributes can then be used in the item Search facility.

Configurator also uses these codes:

- To link a model product with associated base products.
- To link a generic component with its actual components.
- To search for a matching component based on the specific characteristics.

C Of C Code

This code defines the structure of the certificate of conformance that you want to attach to any batches of your selected Item. You must have already set up this code using the Certificate Of Conformance Code Maintenance option within Advanced Order Entry. These codes determine the characteristics that will appear on the Certificate of Conformance for your selected Item. This field is only displayed if you have activated Advanced Order Entry on the Inventory company profile.

Rqd?

If you have specified a Certificate of Conformance in the C Of C Code field, then enter one of the following:

- 0 - Certificate of conformance cannot be issued.
- 1 - Certificate of conformance may be issued.
- 2 - You must have a Certificate of conformance from the supplier upon receipt of the item.

These codes are set up using Inventory Description Maintenance, under major type CCRQ.

Non Stock Item Type

If you are using Advanced Order Entry, enter 5,6,7 or 8 for items that appear on sales orders, but do not have stockroom records. Leave blank to define an item as stocked. These are defined under major type STKF.

A non stock item is a saleable item that does not exist in a stockroom. For example, time charges, and items delivered directly from a supplier to a customer.



Note: You can only define an item's non stock item type when you are actually creating the item.

Preferred Supplier

If you want to use Advanced Order Entry to process back-to-back ordering of non stock items, you must nominate an existing supplier from Accounts Payable. You can also use this in Production as a selection parameter on a selective MRP run.



Note: The preferred supplier for back-to-back ordering for stock items is taken from the Stockroom Details file.

Order Method

Enter one of the following:

- 0 - Normal. This is the default.
- 1 - Made to order.
- 2 - Purchase to order. If you are using Advanced Order Entry to initiate a back-to-back requisition order at the time of order entry.
- 3 - Direct delivery. If you are using Advanced Order Entry to initiate a back-to-back requisition order at the time of order entry.
- 4 - Reservation. You can reserve stock for this sales order against outstanding purchase orders.
- 5 - Configure to order. If you are using Configurator, then this creates a production order.



Note: You define order methods on the Descriptions file against the major type ORDM

Shelf Life Unit

If you have defined your selected item as being batch, lot or serial controlled, enter a Shelf Life Unit code from those defined on the Descriptions file against major type SHLU:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.
- 5 - Unlimited.

Shelf Life

Enter up to three numeric characters. This is the shelf life of the item expressed in the item shelf life units, and is the actual life of the product.

Customer Shelf Life

This is the portion of the total shelf life after which you should take some action, for example a price reduction. For lot controlled items, subtract this value from the expiry date to give the last available date.

EEC Tariff Code

Enter an EEC tariff code chosen from those defined on the Descriptions file against major type TAR. If you enter a tariff code, then duty % is retrieved from the Descriptions file entry for the tariff code.

Tariff Date

Enter the date for the tariff classification agreement, in the format DD/MM/YY.

References

Enter up to 12 alphanumeric characters to specify the reference number of the document confirming the EEC tariff classification.

Duty %

Retrieved from the Descriptions file, if you enter an EEC tariff.

Bar Code

Enter up to 13 alphanumeric characters to specify the bar code for this item.

Lot Control

Set the control flag in Extended Lot Details within Inventory Management's company profile to determine the use of this facility. If not enabled for a type you cannot select the option.

Enter one of the following to specify the type of lot control for this item:

L - Lot: control stock by manufacturing lot number.

S - Serial Number: control stock by item serial number.

B - Batch: control stock by manufacturing batch number.

N - No batch control: control of stock by total quantity recorded only.

Batch control methods L, S and B require the entry of the appropriate control number when making a stock movement.

Within Production, there is no functional difference between lot and serial control.

Inspection Req'd

Enter one of the following:

0 - Do not inspect this item.

1 - Inspect this item before despatch.

2 - Inspect upon receipt. You can only use this option if you are running the Quality Management System for Manufacturing.



*Note: If you are running the Quality Management System for Manufacturing, and your item has already been defined to that system, then an extra function is displayed, the **F13=Quality Parameters**. If your item is not defined to the Quality Management System, then the same Quality Parameters window is displayed when you press **Enter**.*



Note: If you are using Purchase Management, any item flagged as requiring inspection upon receipt has a warning displayed when received directly into goods inwards or stores.

Sub Contract Item

If Inventory Management is linked to Purchase Management, enter up to 15 alphanumeric characters to determine whether to book the item into stock under another number. If you specify a subcontract, then any purchase receipts against the maintained item are booked into stock against the subcontract item.

Functions:

F13=Quality Parameter

Use this function to maintain the Inspection Lots for an item that has already been defined to the Quality Management System for Manufacturing.



Note: This function is only displayed if you are running the Quality Management System for Manufacturing.



Note: If you are using Advanced Order Entry, the following function keys are available:

F17=Alias

Use this to create and maintain alternative item references used for item search. You can maintain any number of alternative references for an item. These may be customer specific item numbers or the original equipment manufacturer's code.

F18=Item Search Characteristics

Use this to create and maintain item search details.

F19=Maintain Pricing Groups

Use this to maintain pricing groups.

F20=Lot Header Details

Use this to create or amend information lot controlled items.

F22=Packaging Details

Use this to display the Country Item Packaging Code Details Screen for your selected item. This is only displayed if you have specified that this item is part of packaging reporting.

F23=Language Descriptions

Use this to display the Multi-Lingual Descriptions Maintenance window, to enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text Window is printed for that customer.



Note: You do not need to select language codes to print text in the native language.



Press **Enter** to return to the Item Maintenance Selection Screen.

Quality Item Master Window



To display this window, select **F13=Quality Parameters** on the Item Maintenance Costing Detail Screen for an item that has already been defined to the Quality Management System for Manufacturing.

Or:

Press **Enter** on the Item Maintenance Costing Details Screen if you have set the Inspection Required field to 2 and want to define your selected item to the Quality Management System for Manufacturing.

Use this screen to create or maintain the Inspection Lots for your selected item.

IN002		Z1 - UK Demonstration Company		USER QSO	24/11/98
					14:40:45
Item Maintenance					
Item.....	5001	Suncream Factor 4 225ml			
Superseded by.....?					
Supersession date.....	0/00/00	Date last changed....	28/08/98		
Cost	Quality Item Master				
Stan	Item.. 5001	Issue Unit..	BX		
Late	Suncream Factor 4 225ml				
Aver					
Base	(0/1)	Transactions Requiring Quality Inspection			
Pric	0	Purchase Order Management Inspection Receipts			
Pric	0	Inventory Stock Count			
Warr	0	Warehousing Stock Count			
Stor	0	Production Order Release			
Shel	0	Production Operation Bookings			
Shel					More: +
EEC	F8=Update F12=Previous		000		
Duty %			Bar code.....		
Lot control (B/L/S/N)...	N	Inspection reqd.....	2 (0=No,1=Yes, 2=Qual.ctl)		
Sub contract item.....?					
F3=Exit F4=Prompt F12=Previous F17=Alternative item references					
F18=Item search chars. F23=Language Descriptions					
MA	b				
					12/010

Fields:

Select (0/1)

Enter one of the following to define which inspection event to use to create inspection lots for your selected item.

0 - To not create inspection lots from the inspection event.

1 - To create inspection lots from the inspection event.



Note: You can select any, or all, of the events that are displayed here. If you do not select an event, no inspection lots are created for your selected item.



Select **F8=Update** to save any changes and create an Inspection Item Master record within the Quality Management System for Manufacturing. This also redispays the Item Maintenance Costing Detail Screen.

Item Alias Maintenance Screen



To display this screen, select **F17=Alias** on the Item Maintenance Costing Detail Screen.

You can use this screen to specify any other references (or names) that you use for the selected item. For example, if you use a different reference, or name, to that of the item's manufacturer, then you could use this screen to record the manufacturer's reference for the item.

```

IN210                Z1 - GB Demonstration Company      User GBJBA1MS      5/09/00
                                                           12:27:51
Item Alias Maintenance

Item..... 5001                Suncream Factor 4 225ml

Line   Alias                                External   Alias   Delete
      agency                                type

Line   Alias                                External   Alias
      agency                                type (?)
-----
F3=Exit  F4=Prompt  F5=Refresh  F8=Update  F12=Previous

```

Fields:

Line

If there are any existing references for your selected item, enter the line number of the reference that you want to amend and press **Enter** to display the existing details in the line entry fields at the bottom section of the screen. Press **Enter** again to redisplay those details in the middle section of the screen.

Alias

Enter up to 36 alphanumeric characters to describe the item.

External Agency

Enter up to eight alphanumeric characters to indicate with which external agency, possibly the manufacturer or a customer, this alternative reference is associated.

Alias Type

Enter an alternative item type chosen from those defined on the Descriptions file against the major type ALTT. This could be the type of external agency, for example wholesaler.



Select **F8=Update** to update the information. The alternative reference you have just defined displays at the top section of the screen.

Item Search Characteristics Screen



To display this screen, select **F18=Item Search Chars** on the Item Maintenance Costing Detail Screen.

You can maintain the search characteristics for this item that are associated with the family search code specified on the Item Maintenance Costing Detail Screen. The item reference and search family code is displayed with their respective descriptions, followed by all the characteristics associated with this family code.

IN205	Z1 - GB Demonstration Company	User GBJBA1MS	5/09/00 14:48:55
Item Search Characteristics			
Item.....	5031	Paracetamol 100 tabs x 50 Box	
Search family code.....	PKL	Generic Painkillers	
Description	Code (?)		
Painkiller Group	_____		
Quantity per pack	_____		
F3=Exit F4=Prompt F5=Refresh F8=Update		F12=Previous	
F17=Update/Aliases			

Fields:

Code

Enter, or select, a code for the characteristics.



Note: The number of decimals entered must conform to the specification made for the characteristic in Search Family Maintenance in Advanced Order Entry.

Functions:

F17=Update/Aliases

Use this to create or update alternative item references. This displays the Item Alias Maintenance Screen for your selected item.



Select **F8=Update** to update the details and return to the Item Maintenance Costing Detail Screen.

Item Pricing Groups Window



To display this window, select **F19=Maintain Pricing Groups** on the Item Maintenance Costing Detail Screen.

Use this window to view, amend or delete item pricing group information.

```

IN002                NR - Neil Radford and Co. Ltd    USER GBJBA1MS    12/08/96
                                                12:30:52

Item Maintenance
Item..... 1352_STD          1352 Standard Costed Item
Superseded by.....?..
Supersession date..... 0/00/00    Date last changed.... 20/06/96
Costing method (S,L,A,F) S    Purchases Account.... 007

S  Item Pricing Groups
L  Item 1352_STD          1352 Standard Costed Item          More:
A      Seq  Prc              Itm prc
B      typ Description              Grp Description
P      -    1 MS1 MS Profile          IG1 Item Group 1
P      -    2 MS3 Pricing Type Profile 03  IG2 Item Group 2
W
S
S
S
E      1=Amend  4=Delete
D
L      Sequence      Type...?      Group...?      Position to:      Yes)
S      F4=Prompt  F5=Refresh  F8=Update  F12=Previous

F3=Exit  F4=Prompt  F12=Previous  F19=Maintain Pricing Groups

20-16    SF    MW    KS    IM    II  KENB20A  PET166S2
  
```

Fields:

Select (Untitled)

Enter one of the following:

- 1 - To amend the pricing group.
- 4 - To delete the pricing group.

Seq

Sequence. This is the sequence in which the function is searched to determine whether it applies to a particular line.

Prc Type

This is the pricing code for the individual item.

Item Prc Grp

This is the item pricing group for which the selected pricing type is effective; this is defined against major type ITMG.



Note: The description of the item pricing group is displayed next to it.



Select **F8=Update** to update the details and return to the Item Maintenance Costing Detail Screen.

Lot Header Parameters Maintenance Window



To display this window, select **F20=Lot Header Maintenance** on the Item Maintenance Costing Detail Screen against a lot controlled item.

You can maintain the Lot Header details for your selected item. Existing information will be displayed.

```

IN002                Version 3 Demonstration Company        USER STDFIN        28/01/00
                                                            15:41:46

Lot Header Parameters Maintenance
Item..... 5013                Muesli Bar Honey High Fibre 50g

Potency required..... 0  (0=No,1=Yes)
Standard potency..... %
Grade required..... 0  (0=No,1=Yes)
Default grade.....?..
Default stock status....?..
Release lead time units?... 1      Days
Release lead time..... 2
Lot dates 'to'..... 1      Actual date (no adjustment)
Display lot time..... 0  (0=No,1=Yes)

F4=Prompt  F12=Previous
Shelf life..... 12                Cust shelf life..... 8
EEC tariff code.....?..            Date.. 0/00/00  Ref. 000000000000
Duty % .....                    Bar code.....
Lot control (B/L/S/N)... B        Inspection reqd..... 0  (0=No,1=Yes)
Sub contract item....?..

F20=Lot header maint. F23=Language descriptions  F24=More keys
  
```

Fields:

Potency Required

Enter one of the following:

0 - Do not display the potency field on receipt, in this case potency is an attribute of the whole lot.

1 - Enter a potency every time you receive a new lot of this item into Inventory.

Standard Potency

If you have set the Potency Required field to 1 then you must enter a default potency value. This value is displayed in the potency field every time you receive a new lot of this item.



Note: Potency is a percentage, the potency you specify here is the number of parts of active ingredient per hundred parts.

Grade Required

Enter one of the following:

0 - Do not display the grade field on receipt, in this case grade is an attribute of the whole lot.

1 - Enter a grade every time you receive a new lot of this item into Inventory.

Default Grade

If you have set the Grade Required field to 1 you must enter a default grade value. This value is displayed in the grade field every time you receive a new lot of this item.

You must choose the grade from those defined on the Descriptions file against the major type GRAD.

Default Stock Status

Enter a stock status code chosen from those defined on the Descriptions file against the major type STKS. This stock status code defaults into the stock status field every time you receive a new lot of this item into Inventory. Stock status codes are designated as either available or unavailable and then applied to a lot make the quantity of that lot frozen or unfrozen.

A blank stock status implies that a lot is available.



Note: The seven-digit limit field of the description codes defined against STKS indicates the availability of an item. If the seventh digit of this field is 1 then the stock status code indicates an unavailable item. Any other value renders the stock status code an available code.

Release Lead Time Units

Enter one of the following alphanumeric characters to specify the release time unit used when calculating the first available date of a lot:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.

Leave this field blank if you do not want to enter the release lead time. In this case when the lot dates are calculated the first available date equals the production date.



Note: Production Date + Release Time = First Available Date.

Release Lead Time

You must enter this if you specify a release lead time unit. Enter up to three numeric characters. The release time is used in the following calculation:

For example, Available Date + Release Time = First Available Date.

If you leave this field blank when the lot dates are calculated the first available date equals the production date.

Lot Dates To

Enter one of the following alphanumeric characters to specify the method used to position lot dates once they are calculated:

- 1 - Use actual lot dates.
- 2 - Position to first day of the period.
- 3 - Position to last day of the period.

All lot dates are either entered or calculated using shelf life and release times. Once calculated, you can reposition the dates to the start or end of a period depending on the business requirements.

Display Lot Times

Enter one of the following:

0 - Do not display Lot times when you receive a new lot of this item into Inventory.

1 - Display Lot times as well as lot dates. In this case enter a time, as well as a date, upon receipt of a lot.



Press **Enter** on each screen until the item is completely updated and the Item Maintenance Costing Details Screen is redisplayed.

Inventory Item Search Words Window



This window opens automatically, if you have amended the item description, external text or created an item.

You can add or amend words relevant to the item. You can use this for item searching.

IN002		Distribution V3 -> V3 Financials		USER GBJBAMV1	14/11/95 14:47:11
Item Maintenance					
Item.....	#1	Medium Talc			
Superseded by.....?					
Supersession date.....	0/00/00	Date last changed....	14/11/95		
Costing method (S,L,A,F)		Purchases Account....	007		
Standard cost.....		Sales Account.....	1005		
Latest cost.....		Cost of sales Account	1006		
Average cost.....		Price variance Acct..	1007		
Base list price.....		Purchasing officer...	10000		
Price regulator code?..	.00 %				
Price list seq code....					
Warrant	Inventory Item Search Words				
Storage	Item Key Words:	Item Reference: #1			
Shelf 1	MEDIUM	TALC			
Shelf 1					
EEC tar					
Duty %					
Lot con					
Sub con					
		F12=Previous	F13=Rebuild		
F3=Exit F4=Prompt F12=Previous					
16-33 SA MW KS IM II KENB20A PET129S1					

Fields:

Enter up to 20 key words used in a search on Inventory's item description.

For New Items

The window displays, as separate key words, each part of the item description, and as many parts of the external text as possible.

For Existing Items

The window displays the previous versions of the keywords.

To see the latest version select **F13=Rebuild**.

Functions:

F13=Rebuild

Use this to rebuild the search engine, effectively adding new details to the search. As this is a toggle function, you can select this function key to cancel these additions and select the Old Index, or existing search engine.



Press **Enter** to update.

Item Master Scan Window



To display this window enter ? in an Item field and select **F4=Prompt**.

This is used throughout Inventory Management to assist in identifying an item. You can use the same item search function in all applications that use an item number.

Fields:

Search Type

Enter one of the following:

- 1 - Item Reference.
- 2 - Inventory Description.

If you are using Purchase Management, you can use the following search types:

- 3 - Purchasing Description.

If you are using Advanced Order Entry you can use following search types:

- 4 - Alternative Reference.
- 5 - Search Characteristics.
- 9 - Base item

? - Enter ? and press **Enter** to display another window you can use to search on up to six words that appear in the item description. The default search type is defined in the Default Item Search Option on the Inventory company profile.

Search Criteria

The content here depends on the Search Type.

- Item Reference - Displays all the items, in item number sequence, beginning with the search criterion entered. This can either be an item or the beginning characters of an item.

- **Inventory Description** - Make a selection based on the Inventory search words, which currently exist for the item. These are generated at item maintenance time based on the first 20 words from the item description and the first three lines of the external text for the item. When either the item description or external text are modified you have the opportunity to rebuild the item search index. You can add words to the search index manually.
- **Purchasing Description** - Make a selection based on the description. This can be either a whole word or the initial letters of a word appearing in the description.
- **Alternative Reference** - Make a selection based on the alternative item reference. This alternative item description may be used by a manufacturer or wholesaler and is maintained by selecting **F17=Alternative Item Desc** on the Item Maintenance Costing Detail Screen. The search criterion can be either a whole word or the initial letters of a word present in the alternative item reference. This search displays a list of all items, with the external reference and item reference, that match the criterion.
- **Search Characteristics** - Make a selection based on a single or a range of characteristics specified against a search family code. The search criterion is a search family code. You maintain this code within Advanced Order Entry.
- **Base Item** - Displays all the base items in number sequence beginning with the entry made. You can only use this if you are using Production and Configurator.
- **Prompt** - If you enter ? in the Search Type field an extra window is displayed.

You can position the display to a nominated point in the list. However, if only one reference meets the search criterion, the application returns to the maintenance screen and inserts the item reference code automatically.



Select the item you want to use.

Alternative Items Maintenance

1...
2...

3/INM



Note: This option is used for Sales Order Processing.

Use this option to define which alternative items you want to use if you are planning to phase out old stock to introduce a new product, if an item is not available or if it is currently out of stock.

Alternative Items Maintenance Detail Screen



To display this screen, select an item on the Alternative Items Maintenance Selection Screen and press **Enter**.

Use this screen to select or maintain the alternative items for this item.

IN006	Z1 - GB Demonstration Company	USER GBJBA1MS	5/09/00 14:54:54
Alternative Items Maintenance			
Item.....	5010	Shampoo frequent use large 400ml	
Alternative Item (?)	Description	Reverse (0=No,1=Yes)	
5007A	Shampoo frequent use	-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
		-	
F3=Exit F4=Prompt F12=Previous			

Fields:

Alternative Item

Enter the reference code of the item that you want to use as an alternative to the item displayed in the Item field. You can define up to 14 alternatives.

Description

This is the text description of the alternative item. This is automatically displayed.

Reverse

Enter one of the following:

0 - No. Do not use the item as an alternative for the alternative item.

1 - Yes. Use the item as an alternative for the alternative item.



If the units of measurement for the items are different, an error message is displayed. In this case, **F14=Accept UOM Mismatch** is displayed on the screen. You can either select **F14=Accept UOM Mismatch** or select **F12=Previous**.



When you have finished entering data in the fields, press **Enter** to check the details. This also defines the alternative items and redisplay the Alternative Items Maintenance Selection Screen.

Kit Lists Maintenance



4/INM

A kit list is a group of items normally sold as individual finished goods, but on occasions sold together as a unit.

The kit is known as the parent, the individual items as components.

In some industries it is more appropriate to sell a kit of items, rather than regarding the kit as a single indivisible item. You can achieve a greater level of product flexibility with a smaller investment in Inventory. Use this option to create and maintain kits. When you add a component item to a kit Inventory Management checks that there is an existing stockroom balance record in all the stockrooms that hold the parent of the kit.



Note: Stock is only held at component level.

Sales Order Processing uses this feature, where orders are raised against the kit parent as defined here in Inventory. In this case, the parent price is charged and the components' prices are ignored. However, you can use Sales Analysis to analyse the component prices.

You can call kit parent details from Advanced Order Entry and amend them during order entry, or you can define kits on line, without reference to this file.



Note: Kit components are individual items that are picked, packed and shipped. If they are items to be assembled to make a finished product, this is a Production process and not a kit list.

Kit List Maintenance Detail Screen



To display this screen, press **Enter** on the Kit List Maintenance Selection Screen.

Use this screen to add, or maintain the list of items that are defined to a kit list. Any current details of the kit are displayed, including component item numbers, descriptions and the quantity of each item you need to complete the kit.

IN007	Z1 - Demonstration Company	User SP1	23/08/94 17:27:18
Kit List Maintenance			
Item.....	5028	Luxury Eye Collection Kit	
Component Item (?)	Description	Qty.off	
5025	Black Onyx Mascara	1.00	
5026	Mahogany Eye Definer	1.00	
5029	Violet Make Up Pencils	1.00	
5030	Moisturing Eye Gel 15ml 74 Box	1.00	
5034	Silk Eye Powder 6 Colour x 50 BX	1.00	
5035	Luxury Eye Collection Bag	1.00	
F3=Exit F4=Prompt F12=Previous			

Fields:

Component Item

Enter the item number of the component item using up to 15 alphanumeric characters. The item must exist on the item file.

Qty Off

Enter the quantity of the kit component that makes up the kit using up to five characters, two decimals.



Note: Component items cannot themselves be parent items of another kit. You must define component items to all the stockrooms to which have the parent item defined.

You can delete a component from the kit by removing the item reference from the kit list.



Press **Enter** to display the item descriptions of any items that have been entered. Press **Enter** again to update the file and redisplay the Kit List Maintenance Selection Screen.

Stockroom Details Maintenance



5/INM & 2/MDM

A stockroom is a discrete area of a company where stock is recorded and controlled separately from other company stock. Some companies only need one stockroom, whilst others, perhaps with a number of distribution points, need more. The key issue is that if there is a continuous requirement to record movements in and out and know the current balance of a particular area, you should use a stockroom.

There are three stages that you need to complete:

1. Define each stockroom in the company profile.
2. Define all the items for the company in the item file.
3. Associate each item with one or more of the stockrooms.



Note: If you are using Advanced Order Entry you can define an item that does not have a stockroom record - a non stock item.

You can create more detailed definitions for items and stockrooms if, for example, you are using Warehousing, Production and DRP.

Use this option to create and maintain details related to the stocking of an item in a stockroom.

The stock management policies make sure that the levels of stock in each stockroom are correct. You can specify the Parameters defining the implementation of these policies here.

An item must have the same method of costing throughout a company, be it average, standard, FIFO, or latest but you can independently maintain the actual cost of the item at each stockroom.

Location Control

If you have created a Location Control stockroom profile for this stockroom, then you can also use this option to create Location Control details for the item. To create a Location Control stockroom profile for the stockroom use the Location Control Stockroom Profile Screen in the Inventory company profile.

You need to create details for all items that will have stock balances held in a Location Controlled stockroom. You can create these details before you activate Location Control for the stockroom. If you do not create these details, an error message is displayed during transaction processing and you will have to create them before you can complete the transaction.

Stockroom Details Maintenance Selection Screen



Select Stockroom Details.

Use this screen to specify the item and stockroom details you want to maintain or create.

```
IN003          Z1 - UK Demonstration Company    User GBJBAJSS    25/01/00
                                                    15:19:46

Stockroom Details Maintenance

Item.....?.. 5031
Stockroom.....?.. 01

F3=Exit  F4=Prompt

MA a MW 05/026
```

Fields:

Item Number

Enter the item you want to add to the stockroom, or for which you want to amend stockroom details.

Stockroom Code

Enter the stockroom code to identify the stockroom details you want to maintain.



Note: You must define the stockroom to Inventory through the company profile before you maintain the stockroom details.



Note: You must configure stockroom details for each item unless the item is being added as a non stock item.



Press **Enter** to display the Stockroom Details Maintenance Screen.

Stockroom Details Maintenance Screen



To display this screen, enter an item number and stockroom code on the Stockroom Details Maintenance Selection Screen and press **Enter**.

Use this screen to maintain the item part of the stockroom details. Any existing information is displayed.

IN003		Z1 - GB Demonstration Company		User GBJBA1MS		5/09/00	
						13:58:56	
Stockroom Details Maintenance							
Item.....	5031	Paracetamol 100 tabs x 50 Box					
Stockroom.....	01	Central Stockroom					
Purchase unit.....?	BX	Boxes of					
Issue unit.....	BX	Boxes of					
Reorder policy.....?	2	R0Q					
Profile code.....?		Vendor schedule item. _ (1=Yes)					
Lead time in weeks....	2.00	Calculate EOQ etc.... 1 (0=No,1=Yes)					
Reorder point.....	.000						
Maximum stock.....	.000						
Reorder qty.....	.000						
EOQ.....	.000	Reorder factor %.... 10%					
Over confirm.....	120.00%	ABC class override... _					
Suppliers.....?							
Material cost.....	.00000 BX						
Standard cost.....	.00000 BX						
Latest cost.....	370.00000 BX	Bins.....					
Base list price.....	.00000	Date changed..... 22/08/94					
F3=Exit F4=Prompt F11=Delete F12=Previous							

Fields:

Vendor Scheduling Item

If you are using Vendor Scheduling, enter 1 to indicate that you control item purchasing through Vendor Scheduling.

Leave this field blank if Requisitioning controls the item purchasing.

This field is for purchased items only.



Note: If you reset this field from 1 any Vendor Scheduling purchase orders remain in place.

Purchase Unit

Enter a purchase unit chosen from the units of measure defined on the descriptions file. This defaults to the purchase unit defined for the item in the Item file, major type UNIT. This unit is assumed as the default ordering unit in Inventory Management and Purchase Management if you are using it.

Issue Unit

Enter an issue unit chosen from the units of measure defined on the descriptions file. This defaults to the issue unit defined for the item in the Item file, major type UNIT. All stock balances and costs for this item in this stockroom are expressed in this unit.

In Production, when you define a route header, you use this as the default UOM.



Tip: You can only change the issue unit of measure for an existing item if there is no stock

balance or outstanding orders recorded against the item.

If you do change the UOM, then the costs and value based landed costs associated with the item are recalculated.



Note: If you are using Catchweight, and the unit of measure is a secondary UOM, this field is displayed for your information only and cannot be amended.

Reorder Policy

Enter one of the following to specify the item's normal reorder policy for this stockroom:

- 1 - Up to MAX.
- 2 - ROQ.
- 3 - Up to MIN.
- 4 - Up to ROP.
- 5 - EOQ.

The code defaults to that defined on the company profile, major type REOP, but can be changed.

Profile Code

Enter the usage profile, using up to two alphanumeric characters. This is defined in the company profile and is used in calculating the average usage for the item in this stockroom.

Lead Time

Enter the lead time, in weeks using up to five characters, two decimals. Used for stock availability calculations. Lead time is only used to calculate due dates for purchase orders if an item or supplier profile is not available in Purchase Management.

The software calculates the available date by adding the lead time to the current date.



Note: Reorder Point, Maximum stock, EOQ are calculated by the software if the Calculate EOQ and so on field is set to 1.

Reorder Point

Enter the reorder point using up to 13 numeric characters, three decimals to determine at what quantity you should reorder stock.

Do this if you do not want the software to calculate this value automatically.

Production uses this to determine the safety stock figure for the item in this stockroom when you run MRP for cellular planning.

Maximum Stock

Enter the maximum stock using up to 13 numeric characters, two decimals if you do not want the software to calculate this value automatically.



Note: If the ROP is higher than Maximum stock, a warning is given.

Reorder Qty

Specify the reorder quantity using up to 13 numeric characters, three decimals. If you leave this value as zero, the software calculates a reorder quantity based on reorder factor %. This only applies if you specify reorder policy 2 - ROP/ROQ. Otherwise, for policies 1-4, enter a figure to manually control the reorder level.

Reorder Factor %

Specify the reorder factor %, using up to three numeric characters. This defaults to the percentage defined on the company profile. This percentage is the number of lead times worth of average usage to be reordered. This only applies if you specify reorder policy as 2-ROP/ROQ.

EOQ

Enter up to 13 numeric characters, two decimals, to specify the economic order quantity. Use this if you do not want the software to calculate this value automatically.

Calculate EOQ Etc.

Enter one of the following:

0 - Manually enter these figures.

1 - The application should calculate economic order quantity, reorder point and maximum stock.



Tip: If reorder policy = 3, set this field to 0.

Material Cost

You can only enter material cost for standard cost items. For standard cost items, you enter the material cost, and any standard landed costs are applied to calculate the total standard cost. If no landed costs are defined, the standard cost equals the material cost.



Tip: The cost unit is displayed to the right of this field. This is useful if you are using Catchweight, as the cost UOM is the items secondary UOM and not the stockroom issue UOM.



Note: If you are using Catchweight, the landed costs are added to the material cost to give a total standard cost per secondary UoM. In this case, a value based landed cost relates to the secondary UoM. The Item/supplier profile and actual landed costs in Purchase Management are all based on the primary transaction quantity and never on the secondary transaction value.

Standard Cost

If you use standard costing, every issue or receipt uses the standard cost. The default costing method is defined in the Costing Method field on the Maintain Company Profile Stock Weeks Matrix Screen, and on the Item Maintenance Costing Detail Screen.

Enter up to 15 numeric characters, five decimals, to specify the standard cost of one issue unit of the item. If the item is not standard costed the field can be entered for memo purposes. For standard costed items this field is protected, the standard cost is calculated based on the material cost, with any standard costs applied.

Production updates the item cost if you transfer production costs (for manufactured items) to Inventory.



Tip: The cost unit is displayed to the right of this field. This is useful if you are using Catchweight, as the cost UOM is the items secondary UOM and not the stockroom issue UOM.

Latest Cost



Note: You only use this field when the item is first added, so that it has a value in Inventory.

If you use latest costing, all stock valuation reflects the latest cost. The default costing method is defined in the Costing Method field on the Maintain Company Profile Stock Weeks Matrix Screen, and on the Item Maintenance Costing Detail Screen.

Enter up to 15 numeric characters, five decimals, to specify the latest cost. The application maintains the latest cost as the unit cost associated with the last stock receipt recorded for an item. You specify it when the item stockroom is first set up, but is overridden during the next receipt.



Tip: The cost unit is displayed to the right of this field. This is useful if you are using Catchweight, as the cost UOM is the items secondary UOM and not the stockroom issue UOM.

Base List Price

Enter up to 15 characters, five decimals. Use this data in the valuation of forecasts in MPS, DRP and MRP. It is also used by Sales Analysis to calculate sales values for kit components.

Date Changed

This is a system maintained field indicating when you last changed this record.

ABC Class Override

The ABC classification matrix is defined for each stockroom on the company profile. The categorisation is based on the value and usage of an item, either A, B or C with associated recommended minimum and maximum stockholding levels.

Leave this field blank if you to use the default class for the item configured in the Maintain Company Profile Stock Weeks Matrix Screen.

Enter A, B or C to associate the item with a different class, so that when stock counting is requested the item is counted more or less frequently than the default.

Enter Z in this field to not include the item on a stock count request.

Over Confirm

This percentage is used in Sales Order Processing when you confirm despatch of an order or order line. This defines the maximum variance between the despatch quantity and the recorded pick quantity.

This is the default from the Descriptions file, under major type MISC and minor type DSTL.

Suppliers

Enter up to four, eight character supplier codes to specify the suppliers of this item for this stockroom. Requisitioning uses the first supplier as the preferred supplier when generating recommended purchase orders.

Bins

Enter the bins in which you store this item in the stockroom using up to two sets of six alphanumeric characters. If you require full location management, you should install Warehousing.

Functions:

F11=Delete

Use this to delete a stockroom. To do this, select this function twice, provided that the following conditions are satisfied:

- The physical stock balance must be zero.
- No movements must exist in the current month.
- No outstanding orders, either sales, production, or purchase must exist.

F14=Landed Costs

Use this to define landed costs for the item. You can only use this if the item is standard costed.



Press **Enter** to check all details and return to the Stockroom Detail Maintenance Selection Screen. If you are using Location Control, press **Enter** twice to display the Item/Stockroom Location Control Details Window.

Landed Costs Entry Screen



To display this screen, select **F14=Landed Costs** on the Stockroom Maintenance Detail Screen.

Use this screen to enter and maintain landed costs for an item.

```

IN320          Z1 - GB Demonstration Company   USER GBJBA1MS   14/01/98
                                           13:30:24

Landed Costs Entry
Item..... AB01          Standard item. No lot control
Stockroom.. 01          Central Stockroom
UoM..... EA          Single of----->

Cost
Code          Standard      Perc/
(?) Description Landed Cost  Value
              (1/0)

  01 Post & Packaging      2.50000    1
  --
  --
  --
  --
  --
  --
  --
  --
  --
  --

F3=Exit  F4=Prompt  F8=Update  F12=Previous

12-6    SA    MW    KS  CL  IM  DM  II    STUD140  KB  PET087S1
  
```



Note: You can only define landed costs for a standard costed item.

Fields:

Cost Code

Select an existing cost code. Landed Cost codes are set up in Purchase Management.

Description

The description for your chosen cost code is automatically displayed.

Standard Landed Cost

Enter a figure for the cost code using up to nine numeric characters, five decimals.

Perc/Value

Enter one of the following:

0 - For this landed cost to be value based.

1 - For this landed cost to be percentage based.



Select **F8=Update** to update the information you have added and return to the Stockroom Maintenance Details Screen.

Item/Stockroom Location Control Details Window



To display this window, press **Enter** twice on the Stockroom Details Maintenance Screen.



Note: This window is only displayed if there is a Location Control Stockroom Profile for this stockroom. To do this, use Stockroom Profile Maintenance in the Company Profile Maintenance option within Inventory.

Use this window to add Location Control defaults for your selected item and stockroom combination.

IN003		MM - Catchweight Company MM		User GBJBA1MS	17/02/00
					14:41:50
Stockroom Details Maintenance					
Item/Stockroom Location Control Details					
Item.....	Stockroom Location Control Settings:				r LLSB
Stockroom.....					
Purchase unit..	Status..... Active				
Issue unit....	Default Location..... A01				=Yes)
Reorder policy.					
Profile code...	Default Location.....?.				
Lead time.....					
Reorder point..	Multiple Locations..... 1 (0=No, 1=Yes)				
Maximum stock..	Rotate Stock..... 1 (0=No, 1=Yes)				
Reorder qty....	Collect Secondary Balances. 1 (0=No, 1=Yes)				
Reorder factor					
EOQ.....	F4=Prompt F5=Refresh F8=Update F12=Previous				0/00
Calculate EOQ e					
Material cost..					
Standard cost..					
Latest cost....					
Base list price					
F3=Exit F4=Prompt F12=Previous					F14=Landed costs

Fields:

Status

This is the Location Control status for your selected stockroom.

Default Location

This is the default location for your stockroom.

Default Location

Select the single location in which you want to stock this item. This location is then the suggested location for receipts and unplanned issues.

Multiple Locations

Enter one of the following:

0 - To only stock this item in the single default location. You can only select to store stock in a single location if there is no stock balance or if all the stock is in the default location.

1 - To stock this item in more than one location.

Rotate Stock



Tip: This field is only displayed if you have selected a lot, batch or serial controlled item.
Enter one of the following:

0 - To not use stock rotation.

1 - To use stock rotation.

Collect Secondary Balances



Tip: This field is only displayed if you select a Catchweight item.

You only need to enter secondary balances at the lowest level required, since there is no need to enter higher level transaction totals as there is for the primary balance.

Enter one of the following:

0 - To not hold secondary balances by location.

1 - To hold location level secondary balances. Specify this option if you want to stock items in multiple locations and therefore need to record secondary balances by separate location.



Tip: If you deactivate this option then all location secondary balances are cleared when you press **Enter**.



Note: If you select to stock an item in a single location then you cannot use this field because the location balance would be a duplicate of the item or lot balance.

Functions:

F5=Refresh.

Select this to restore any previous values for these fields.



Select **F8=Update** to save and update your data, and return to the Stockroom Details Maintenance Selection Screen.

Select **F3=Exit** there to exit the option.

FIFO Costs Maintenance



6/INM

FIFO (first in, first out) determines that the oldest receipted stock items are sold first. The oldest items can have different costs. The software automatically sells the oldest costed stock first and keeps detailed cost tracking.

The application generates FIFO records when you set the costing method of a product to FIFO and you receive goods into stock. If you make an error at the time of entry you can use this facility to amend the detail within a FIFO record. To audit any cost changes made, a movement is written to the transaction file. This has a zero quantity and a value equal to that of the adjustment, an audit report is then printed.



Note: If you use Catchweight, the average cost of Catchweight items for physical and in-transit FIFO items is calculated using the secondary values.



Use this screen to select the item and stockroom combination for which you want to amend FIFO costs

```
IN028          Version 3 Demonstration Company      User STDFIN      28/01/00
                                                    15:42:55

Maintain FIFO Costs

Item.....?.. _____
Stockroom.....?.. _

F3=Exit  F4=Prompt
```

Fields:

Item Number

Enter the item code. This must be an item defined to Inventory, and use the FIFO costing method.

Stockroom code

Enter the stockroom that stores your selected FIFO costed item.



To display the Maintain FIFO Costs Screen press **Enter**.

Maintain FIFO Costs Screen



To display this screen, press **Enter** on the Maintain FIFO Costs Selection Screen.

Use this screen to maintain the unit cost of a FIFO record.



Note: The cost change only affects the any items that are not issued associated with that record. Inventory Management does not track items already issued to amend their cost. If part of the receipt has been issued you must spread the total value of the adjustment over the remaining items in the receipt. This can lead to unusual short-term costs.

The upper part of the screen identifies the product and stockroom for which the amendment has been requested. The lower part lists the open FIFO records for the product/stockroom.

IN028	Z1 - GB Demonstration Company	User GBJBA1MS	5/09/00	
			13:05:19	
Maintain FIFO Costs				
Item.....	FIF01	fifo costed item 1		
Stockroom.....	01	Central Stockroom		
Issue units.....	EA	Single of		
Date / Time	Original	From supplier/	Cost per EA	Balance
received	quantity	stockroom		
4/07/00 9:09:26	100.000		12.12345	100.000
10/07/00 12:11:15	1.000	01	15.00000	1.000
F3=Exit F12=Previous				

Fields

Cost Per Unit

Enter or amend the cost for the FIFO record.



Note: Although the value of stock can have changed, this process does not update the General Ledger.

There are two options that make the creation of new items quicker:

- Linked item maintenance - you can set up profiles that other applications use by other linked applications, as well as those used by Inventory itself.
- Copy function - you can create a new item based on the details of an existing item.



Press **Enter** to change the value of the FIFO record. The value of the change is written to the movements file, as an audit of the change.

Calendar Maintenance And Year End Update

1... **7//NM & 7//NUM & 3//NC**
2...

Use this option to maintain the current week, period and year number for the Inventory company. You normally use this option once, when you first set up Inventory codes for the calendar details, after this the current calendar position is maintained automatically by the week, period, and year end batch update jobs.

You should never manually change these details during the course of the year, except under exceptional circumstances when you need to re-run the week, month, or year end update.

The Year-End Update option accesses the same details and submits a batch job which:

- Updates the number of weeks this year and last year specified on the calendar.
- Changes the number of periods specified on the calendar.
- Sets any yearly accumulators to zero.
- Increments the year number by one.
- Produces a Stock Valuation Report as part of the submission process.
- Produces a Reorder Report as part of the submission process.

Maintain Calendar File Screen



Select Calendar.

Use this screen to specify the current date information for Inventory.

IN012	Version 3 Demonstration Company	USER STDFIN	28/01/00 15:43:33
Maintain Calendar File			
Current year..... <u>00</u>			
Current week..... <u>3</u>			
Current period..... <u>1</u>			
No. of weeks this year.... <u>52</u>			
No. of weeks last year.... <u>52</u>			
No. of periods this year... <u>12</u>			
F3=Exit F11=Delete			

Fields:

Current Year

Enter the current year using up to two numeric characters.

Current Week

Enter the current week using up to two numeric characters.

Current Period

Enter the current period using up to two numeric characters.

No Of Weeks This Year

Enter the number of weeks this year using up to two numeric characters. The value must be less than or equal to 53.

No Of Weeks Last Year

Enter the number of weeks last year using up to two numeric characters. The value must be less than or equal to 53.

No Of Periods This Year

Enter the number of periods this year using up to two numeric characters. The value must be less than or equal to 13.



*Note: This information is linked to Sales Analysis
Company Profile and Forecasting's Company
Profile Periods/Backups details.*



Press **Enter**, to update the calendar with the changes.

Or:

To process a Year End Update, press **Enter** to submit a batch job to perform the year end update.

Period End Control



8/INM & 8/INUM

Use this option to maintain period and week end dates. These are used within Inventory to stamp movements and update history records with the correct year, period and week number. You normally use the procedure when you initially set up the software, and to create dates for future years.



Tip: You can define the term Period in a variety of ways but normally refers to a month.

Inventory Period End Control Maintenance Selection Screen



Select Period/End Control.

Use this screen to select the year number and period type for which end-dates are to be maintained.

IN062	ST - JBA System Test Company	USER GBJBARW2	8/11/95
Inventory Period End Control Maintenance			14:04:12
Year	00	Type	_ (1=Weekly,2=Monthly)
F3=Exit			
05-13	SA	MM	KS IM II KENB20A PET178S2

Fields:

Year

Enter the year number of the year for which end dates are to be maintained.

Type

Enter one of the following:

- 1 - To maintain Week End dates.
- 2 - To maintain Month End dates.



Press **Enter** to display Year Total Control Window.

Year Total Control Window



To display this window, press **Enter** on the Inventory Period End Control Maintenance Selection Screen.

Use this window to confirm the total number of periods or weeks for your specified year.

```
IN062          Version 3 Demonstration Company    USER STDFIN    28/01/00
                                                    15:43:51
Inventory Period End Control Maintenance
Year..... 00   Type..... 1 (1=Weekly,2=Monthly)

Enter the number of weeks for
the year you are maintaining.

      52

F12=Previous

F3=Exit
```

Fields:

Untitled

Enter the number of weeks, or periods, that you want to maintain for your selected year.

You can enter up to 53 weeks or 13 periods.



Press **Enter** to display the Inventory Period End Control Maintenance Screen.

Inventory Period End Control Maintenance Screen



To display this screen, select the year and period type on the Inventory Period End Control Maintenance Selection Screen and press **Enter**.

You can maintain end dates for a selected year and period type (week or month).



Warning: Take care when changing dates for a currently active year, as this may cause unpredictable results.

```

IN062                Z1 - GB Demonstration Company    USER GBJBA1MS    14/01/98
                                           13:38:36

Inventory Period End Control Maintenance

Year..... 97      Type..... 1 (1=Weekly,2=Monthly)

  Week  End date    Week  End date    Week  End date    Week  End date
   01  4/01/97     15  12/04/97     29  19/07/97     43  25/10/97
   02  11/01/97    16  19/04/97     30  26/07/97     44  1/11/97
   03  18/01/97    17  26/04/97     31  2/08/97     45  8/11/97
   04  25/01/97    18  3/05/97     32  9/08/97     46  15/11/97
   05  1/02/97     19  10/05/97     33  16/08/97     47  22/11/97
   06  8/02/97     20  17/05/97     34  23/08/97     48  29/11/97
   07  15/02/97    21  24/05/97     35  30/08/97     49  6/12/97
   08  22/02/97    22  31/05/97     36  6/09/97     50  13/12/97
   09  1/03/97     23  7/06/97     37  13/09/97     51  20/12/97
   10  8/03/97     24  14/06/97     38  20/09/97     52  27/12/97
   11  15/03/97    25  21/06/97     39  27/09/97
   12  22/03/97    26  28/06/97     40  4/10/97
   13  29/03/97    27  5/07/97     41  11/10/97
   14  5/04/97     28  12/07/97     42  18/10/97

ENTER=Validate
F3=Exit  F8=Update  F12=Previous

  8-10  SA  MW  KS  CL  IM  DM  II  STUD140  KB  PET087S1
  
```

Fields:

End Date

Enter dates for the week or period end dates.



Tip: Where this is the initial set up of end dates for a particular year, only enter the first date. Press **Enter**, and Inventory Management will automatically generate the rest of the dates for the year.



Press **Enter** to check any entries and then select **F8=Update** to update the database.

Secondary UOMs Maintenance



9/INM & 9/INUM

Use this option to add recently created units of measure to the software. For each unit of measure, you can configure its relationship with other units of measurement by adding a conversion table. You can also associate a unit of measure with a larger unit of measure. For example, you can associate ounces with pounds.

Maintain Unit Of Measure Selection Screen



Select Secondary UOMs.

Use this screen to select the UoM you want to maintain.

IN560 CW - Catchweight Company User GBJBA1MS 12/02/97 12:26:52

Maintain Unit Of Measure

Unit Of Measure.....?.. ?_

Units Of Measure

More: +

1 UOM	Description
- CC	cc
- CM	Centimtrs
- C3	Cubic Ins
- F0	F1 Ounces
- FT	Feet
- GL	Gallons
- GM	Grammes
- IN	Inches
- JB	fghfgh
- KG	Kilos

1=Select

F5=Refresh F12=Previous

F3=Exit F4=Prompt

11-52 SF MW KS IM II KENB20A PET149S2

Fields:

Unit Of Measure

Select the unit of measure you want to configure using a two-character code



Tip: Codes must exist for new Units of Measure in Descriptions under UOMC or GUMC before you can maintain their relationship to other units of measure.



Press **Enter** to display the Maintain Unit Of Measure Details Screen.

Maintain Unit Of Measure Details Screen



To display this screen, select a UoM on the Maintain Unit Of Measure Selection Screen and press **Enter**.

Use this screen to maintain part of the selected UoM. Existing information is displayed.

```

IN560                      CW - Catchweight Company      User GBJBA1MS   12/02/97
                                                                12:54:13

Maintain Unit Of Measure

Unit Of Measure..... OZ

Long description..... Ounces
Short description..... Ounces
Abbreviation..... oz
Larger UOM..... LB Pounds
UOM type.....?.. 1 Weight

F3=Exit  F4=Prompt  F8=Update  F12=Previous

08-34  SF  MW  KS  IM  II  KENB20A  PET149S2
  
```

Fields:

Long Description

Enter a description of the unit of measure up to 30 characters long.

Short Description

Enter a description of the unit of measure up to nine characters long. This is used elsewhere in the software to represent the unit of measure.

Abbreviation

Enter a text description of the unit of measure up to three characters long. This is used elsewhere in the software to represent the unit of measure.

Larger UOM

You can associate a unit of measure with a larger unit of measure. For example, you can associate ounces with pounds. The abbreviation and text description for the larger unit of measure are displayed in this field.

UOM Type

Enter one of the following:

- 1 - Weight.
- 2 - Volume/Fluid Capacity.
- 3 - Length.
- 4 - Area.



These UOM Types are held on the Descriptions file under major type UTP.



Select **F8=Update** to save the details on the software and display the Maintain Unit Of Measure Selected Details Screen.

Maintain Unit Of Measure Selected Details Screen



To display this screen, select **F8=Update** on the Maintain Unit Of Measure Details Screen.

Use this screen to configure the conversion factors between different units of measure.

IN560		CW - Catchweight Company		User GBJBA1MS		12/02/97 13:01:25	
Maintain Unit Of Measure							
Unit Of Measure..... OZ Ounces							
Sel	To UOM	Conv Factor	M/D	Description	Larger UOM		
█	GM	28.3496	M	Grammes			
-	KG	35.2736	D	Kilogrammes			
-	LB	16.0000	D	Pounds	1		
-	TN	35,840.0000	D	Imperial Tons			
-	TO	35,273.6000	D	Metric Tonnes			
To UOM.?. _ Conv Factor... .0000 M/D... _ Larger UOM... _ Bottom (0/1)							
F3=Exit F4=Prompt F8=Update F12=Previous							
08-02 SF MW KS IM II KENB20A PET149S2							

Fields:

Select (Sel)

Enter 1 against the conversion unit of measure you want to edit.

To UOM

Enter the abbreviation of the conversion unit of measure.

Conv Factor

Enter the value, to four decimal places, by which the unit of measure must be either multiplied or divided to result in the conversion unit of measure.

M/D

Enter one of the following to determine whether the unit of measure is multiplied or divided to result in the conversion unit of measure:

M - Multiply.

D - Divide.

Larger UOM

Enter one of the following:

0 - If it is not a larger unit of measure (or leave blank).

1 - The conversion unit of measure is a larger unit of measure.



Select **F8=Update** to save any changes.

Linked Item Maintenance



10/INM

Use this option to maintain item related profiles and details across applications. You firstly select an item, then amend any number of profiles such as item stockroom, item/supplier, DRP item profile, without having to locate the individual maintenance options on the different menus.



Note: If you are using Catchweight, the Catchweight specific functions for each of the applications work as normal.

Linked Item Maintenance Screen



Select Linked Item Maintenance.

Use this screen to enter an item number.

IN804	Z1 - GB Demonstration Company	User GBJBA1MS	5/09/00
Linked Item Maintenance			13:07:12
Item..?.. _____			
F3=Exit F4=Prompt			

Fields

Item

Enter the item reference code for which you want to maintain certain item related profiles or details.



The Profile Selection window displays automatically.

Profile Selection Window



The Profile Selection window is displayed, whether the item selected on the Linked Item Maintenance Screen exists or not.

The item code and description are displayed at the top of the screen.

You can maintain the following profiles or details for the item:

- Inventory Item Master.
- Item Stockroom Details.
- Item Supplier Profile (Purchase Management).
- Production Item Master Profile (Production Definition Management).
- Item Warehouse Profile (Warehousing).
- World Trade Item Profile (World Trade).
- DRP Item Profile (Distribution Requirements Planning).
- Forecasting Item Profile (Forecasting).
- Alternative Items.

The screenshot shows a terminal window titled 'IN804 Distribution V3 -> V3 Financials User GBJBAMV1 14/11/95 15:36:48'. The main window is 'Linked Item Maintenance' with 'Item..?... 1' entered. A sub-window 'Profile Selection' is open, showing a list of profiles and their 'Exists' status. The 'Exists' column has values 1, 1, 1, 0, 0, 1, 0, 0, 1, 0. The sub-window also shows 'F3=Exit F12=Previous' at the bottom. The main window shows 'F3=Exit F4=Prompt' at the bottom. The status bar at the bottom of the terminal shows '16-24 SA MW KS IM II KENB20A PET129S1'.

Profile	Exists (0/1)
Item..... 1	
5345 1	
— Inventory Item Master	1
— Item Stockroom Profile	1
— Item Supplier Profile	1
— Production Item Master	0
— Item Warehouse Profile	0
— World Trade Item Master	1
— DRP Item Profile	0
— Transport Planning Item Master	0
— Forecasting Item Profile	1
— Alternative Items	0

Fields:

Untitled (Sequence)

The sequence column is blank for all profiles, unless you are creating a new item.

To maintain a profile, enter 1 against the first profile you want to maintain, 2 against the second, 3 against the next and so on.



Note: If you enter an item code that does not exist, the application displays the Profile Selection window with the Inventory Item Maintenance and Item Stockroom Details already

selected for modification.

Exist 0/1

If at least one profile combination has been defined, 1 is displayed. Otherwise 0 is displayed.

For example if you have defined an item to the stockroom and to the supplier 1 is displayed in the Exists column against Inventory Item Maintenance, Item Stockroom Details and Item Supplier Maintenance and 0 is displayed against all other profiles.



*Note: The only difference when comparing those maintenance options accessed from the linked Item Maintenance option with those accessed directly from the menus, is the extra function, **F15**, which displays the Select Profiles Screen.*



Warning: For maintenance functions requiring the selection of a second parameter, that is item stockroom details, item/supplier, you must select F3=Exit from that function's selection screen to progress to the next profile chosen for amendment.



Once you have completed the Item Master, the software displays the Stockroom Details Screen. You page through other selections until you return to the Profile Selection Screen.

Copy Based On Item Creation



11/INM

Use this option to create a new item from an existing item profile. You can copy some or all of the item's attributes, depending on the setting of flags on the Profile Options Screen. This may be particularly useful when entering the details of redesigned items to replace existing stock, or when defining numerous similar items to Inventory, where only minimal changes are necessary to each item profile, thus reducing duplicate data entry.



Note: If you are using Catchweight, all the Catchweight specific information is also copied. For example, secondary UOM value, tolerance values, Catchweight item type.

Copy Based On Item Selection Screen



Select Copy Based On Item Creation.

Use this screen to select the established item from which you want to copy details and enter the item code of the new item.

INB07	Z1 - Demonstration Company	User SP1	25/08/94 17:11:29
Copy Based On Item Selection			
Item.....	5044	Muesli Bar Apricot High Fibre 50g	
Based on..?..	5013		
F3=Exit F4=Prompt F8=Submit F13=Profile options			

Fields:

Item

Enter a new and unique item code using up to 15 alphanumeric characters.



Note: If you enter an existing item a message is displayed and you should enter another item code.

Untitled (Description)

Enter the description, using up to 36 alphanumeric characters, for this item code in the field to the right of the screen.

Based On

Enter the code of an existing item, on which you would like to base this new item.



*Note: When you press **Enter** the description this existing item is displayed.*

Functions:

F13=Profile Options

Use this to select profiles before you submit the job.



Select **F8=Submit** to process the job.

Profile Options Screen



To display this screen specify the new item code, and the existing item that you want to base this new item upon, and select **F13=Profile Options** on the Copy Based On Item Selection Screen.



Note: Base item data (including item attributes, units of measure, lot, batch or serial control details and costing) is always copied to the new item. In addition, any of the following data may also be copied.

Use this screen to select the options you want to copy for the item.

IN807		Z1 - GB Demonstration Company		User GBJBA1MS		5/09/00	
						13:08:44	
Profile Options							
Item..... 5044		Muesli Bar Apricot High Fibre 50g					
Based on..... 5013		Muesli Bar Honey High Fibre 50g					
Item Details (0=No,1=Yes)							
Item text..... 1		Purchase text..... 1		Search characteristics.. 1			
Alternative Items.... 1							
Stockroom Profiles..... 1		Stockroom costs..... 0					
Location Details..... 1							
Warehouse Details 1		Pick locations..... 1		Fixed locations..... 1			
Item pack details.... 1							
Supplier Profiles..... 1		Price structure..... 1		Supplier text..... 1			
Landed costs..... 0							
World Trade Details..... 1		DRP Details..... 1		Transport Details..... 1			
Production Details..... 1		Item text..... 1		Item cost elements..... 0			
F3=Exit F8=Submit F12=Previous							

Fields:

Select (Untitled)

Enter one of the following for each field:

0 - If you do not want to copy this information for the new item.

1 - Duplicate the information held here for the new item.



Note: This will happen even if you have not defined that data for the existing item.



Note: You can use Linked Item Maintenance to amend this information.



Select **F8=Submit** to submit.

Sourcing Rules Access



12/INM

Use this option to create sourcing rules for both Production and Enterprise sales orders. You can use sourcing rules to determine the path that the software will use to supply demand orders. You can also determine whether Enterprise sales orders are delivered directly to the customer or physically delivered to the sales or supply company's stockroom before delivery to the customer. For example, if you use Production, you can create sourcing rules for Master Production Schedule runs that control the supply policy for items.

You can set up any number of sourcing rules so that, when you process a sales order, or generate a demand in Production, the sourcing program reads the rules until it finds one that can satisfy the due date for that demand line.

If you are using Enterprise sales orders and the demand line cannot be fulfilled by the due date, then a warning window is displayed; this happens again if no valid rules are found.

If you are using Production to control your Production requirements, then you can use **F14=Demand Values** to specify a default course of action if no other sourcing rules apply.



Warning: This option requires exclusive use of the system.

Maintain Sourcing Rule Access Criteria Selection Screen



To display this screen, select Sourcing Rules Access.

Use this screen to

```
IN190          AS - ALG Systems          USER STDFIN    15/02/00
                                                    15:45:52

Maintain sourcing rule access criteria

- MPS Demand
- MRP Demand
- Sales Order


1=Select
F3=Exit
```

Fields:

Select (Untitled)

Enter 1 to select the area of demand for which you want to create sourcing rules.



Select an area to automatically display the Maintain Sourcing Rule Access Detail Screen. The screen that is displayed depends on the demand area that you select.

Maintain Sourcing Rule Access For Sales Order Screen



This screen is displayed automatically when you select a demand area on the Maintain Sourcing Rule Access Criteria Selection Screen.

Use this screen to define the sourcing rule access for your selected demand area.



Warning: *JBA recommend that you carefully consider the access levels you want to use, as once they are defined they cannot be changed.*



Note: *If you opt to maintain sourcing rule access for Production demand, then the title changes to reflect this and the Customer fields are not displayed.*

```

IN190          AS - ALG Systems          User STDFIN    15/02/00
                                           15:46:03

Maintain sourcing rule access for Sales Order

Activity access level..... _      0=All,1=Activity group,2=Activity
Item access level..... _          0=All items
                                   1=Item attribute
                                   2=Item
Item attribute type.....? _
Demand Point access..... _        0=All demand points
                                   1=Warehouse/Plant
                                   2=Stockroom
Customer access level..... _      0=All customers
                                   1=Customer attribute
                                   2=Customer
Customer attribute type....? _

F3=Exit  F4=Prompt  F12=Previous
  
```

Fields:

Activity Access Level

Enter one of the following to determine what will prompt the source rules:

- 0 - All. To apply sourcing rules to all activities.
- 1 - Activity Group. To apply sourcing rules to a certain group of activities. This is currently not in use.
- 2 - Activity. To apply sourcing rules by activity.

Item Access Level

Enter one of the following to determine what will prompt the system to access the source rule:

- 0 - All. To apply sourcing rules to all items.

- 1 - Item attribute. To apply sourcing rules to certain items with the same attribute.
- 2 - Item. To apply rules to a certain item.

Item Attribute Type

If you entered 1 in the Item Access Level field, then you must enter an item attribute type. These are defined against major type ITAT in Inventory descriptions.



Note: The codes defined in ITAT list the major type codes PGMJ and PGMN; that is, they are item major and minor codes. For more information about these codes, see Inventory descriptions.

Demand Point Access

Enter one of the following to determine the demand point access:

- 0 - All demand points. If you want to define sourcing rules for all demand points. If you use Production, then this would be your normal entry.
- 1 - Warehouse/plant. If you want to define sourcing rules for a specific warehouse or Production plant. You can only use this if you want to define sourcing rules for Production demand.
- 2 - Stockroom. If you want to define sourcing rules for a specific stockroom. You can only use this if you want to define sourcing rules for Enterprise sales order demand.



Note: The next two fields are not displayed if you are creating sourcing rule access details for Production.

Customer Access Level

Enter one of the following to determine what customer level will prompt the system to access the source rule:

- 0 - All Customers. To apply a rule to all customers.
- 1 - Customer Attribute. To apply a rule to certain customers with the same attribute.
- 2 - Customer. To apply a rule to a certain customer.

Customer Attribute Type

If you entered 1 in the Customer Access Level field, then you must enter a customer attribute type. These are defined against major type CUAT in Inventory descriptions.



Note: The codes defined in CUAT are major types used in other areas of customer definition. For example, the code SN, defined to CUAT, is also the major type code for Sales Analysis Regions; code TN is the major type code for Salesman. For more information about these codes, see Inventory descriptions.



Press **Enter** to confirm your entries and display the Confirm/Delete Sourcing Rule Access For Sales Order Screen.

Confirm/Delete Sourcing Rule Access For Sales Order Screen



To display this screen, press **Enter** on the Maintain Sourcing Rule Access For Sales Order Screen.

Use this screen to confirm the sourcing access details for your selected demand area, or to delete the current sourcing access details.



Note: If you opt to maintain sourcing rule access for Production demand, then the title changes to reflect this and the Customer fields are not displayed.

IN190	AS - ALG Systems	User STDFIN	15/02/00 15:48:36
Confirm/delete sourcing rule access for Sales Order			
Activity access level..... 0		All activities	
Item access level..... 1		Item attribute	
Item access type..... PGMJ		Item Group Major	
Demand Point access..... 0		All demand points	
Customer access level..... 1		Customer attribute	
Customer attribute type..... TN		Salesman	
F3=Exit F11=Delete F12=Previous			

Functions:

F11=Delete

Select this to delete the current sourcing rule access details. This displays the Confirm Access Deletion Window. Select **F11=Delete** again to delete the current details and redisplay the Maintain Sourcing Rule Access Criteria Selection Screen.



Press **Enter** to confirm the current details and redisplay the Maintain Sourcing Rule Access Criteria Selection Screen.

Sourcing Rules



13/INM & 4/MPS

Use this option to apply sourcing rules to the sourcing rule access details that you defined using the Sourcing Rules Access option. Sourcing rules define the processing that the software follows for each demand point at the specified access level.



Warning: This option requires exclusive use of the system.

You allocate sequence numbers to each rule so that you can determine the sequence in which the software actions the various sourcing rules for a demand point. You can set effectivity dates to a set of sourcing rules or to an individual element that makes up the sourcing rule.



Note: For more information about how to apply sourcing rules for Production, see the Maintain Supply Sourcing Rules option in Production.



Note: For more information about how to apply sourcing rules for Enterprise Sales Orders, see the Maintain Supply Sourcing Rules option in Enterprise Orders.

Maintain Sourcing Rule Details For Sales Order Selection Screen



To display this screen, select Sourcing Rules.

Use this screen to select the area to which you want to apply sourcing rules.

```
IN191          AS - ALG Systems          USER STDFIN    15/02/00
                                                    15:48:59

Maintain sourcing rule details for Sales Order

- MPS Demand
- MRP Demand
- Sales Order


1=Select
F3=Exit
```

Fields:

Select (Untitled)

Enter 1 to select the area to which you want to apply sourcing rules.



The Maintain Sourcing Rule Details For Sales Order Detail Screen is displayed automatically.

Maintain Sourcing Rule Details For Sales Order Detail Screen



This screen is displayed automatically when you select an area on the Maintain Sourcing Rule Details For Sales Order Selection Screen.

Use this screen to create or maintain sourcing rules for your selected demand area. The top of the screen displays any selection criteria attached to your sourcing rule details. These are defined using the Sourcing Rules Access option. The middle of the screen displays any existing sourcing rule types, the triggers for the sourcing rule and their effectivity dates. Use the bottom of the screen to position the display to a certain rule type.

IN191	AS - ALG Systems	USER STDFIN	15/02/00
			15:53:42
Maintain sourcing rule details for Sales Order			
Item attribute type..... PGMJ		Item Group Major	
Customer attribute type..... TN		Salesman	
Sel Rule Item	Customer	<---Effectivity--->	
type attribute	attribute	Date From	Date To
- 005 E	B	15/02/00	99/99/99
- 005 G	B	15/02/00	99/99/99
Pos'n to Item att.. _____		Cust att.. _____	
1=Amend 2=Details 4=Delete			
F3=Exit F5=Refresh F10=Add F12=Previous			

Fields:

Select (Sel)

Enter one of the following:

- 1 - Amend. To amend the sourcing rule type.
- 2 - Details. To view the sourcing rule type details.
- 4 - Delete. To delete the selected sourcing rule type.

Pos'n To Item Att

Position To Item Attribute. If the list of sourcing rule sequences is too big to display on the screen, enter the item attribute that you want to display at the top of the screen and press **Enter** to change the display.

Cust Att

Customer Attribute. If the list of sourcing rule sequences is too big to display on the screen, enter the customer attribute that you want to display at the top of the screen and press **Enter** to change the display.

Functions:

F5=Refresh

Select this to redisplay the original details.

F10=Add

Select this to add sourcing rule sequences to your selected sourcing rule access detail.

Amend Sourcing Rule Window



To display this window, enter 1 against a sourcing rule type and press **Enter** on the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Use this window to amend details of an existing sourcing rule type. The fields displayed on this window depend on the criteria you set up for your sourcing rule access details using the Sourcing Rule Access option; this can include item and customer attributes, or specific item or customer reference numbers.

IN191	AS - ALG Systems	USER STDFIN	15/02/00
			16:38:04
Maintain sourcing rule details for Sales Order			
Sel Rule type		Effectivity--->	
1	005	From	Date To
-	005	1/00	14/02/00
		2/00	99/99/99
		Effective Date From... 1/01/00	
		Effective Date To..... 14/02/00	
F4=Prompt F8=Update F12=Previous			
1=Amend 2=Details 4=Delete			
F3=Exit F5=Refresh F10=Add F12=Previous			

Fields:

Sourcing Rule Type

Select the sourcing rule type you want to use.

Effective Date From

Enter the start date for your selected rule type.

Effective Date To

Enter the end date for your selected rule type.



Select **F8=Update** to save any changes and redisplay the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Confirm Rule Deletion Window



To display this window, enter 4 against a sourcing rule type and press **Enter** on the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Use this window to confirm the deletion of the selected sourcing rule type.

IN191		AS - ALG Systems		USER STDFIN		15/02/00			
						16:37:07			
Maintain sourcing rule details for Sales Order									
Sel Rule		Confirm Rule Deletion Warning: The requested function will delete all the sourcing rule data for the current sourcing process/activity, business process type and rule number. F11=Delete F12=Previous				--Effectivity-->			
type						te From		Date To	
4 005						/01/00		14/02/00	
- 005						/02/00 99/99/99			
1=Amend 2=Details 4=Delete F3=Exit F5=Refresh F10=Add F12=Previous									

Functions:

F11=Delete

Select this to confirm the deletion of your selected sourcing rule type.



Select **F11=Delete** to delete the sourcing rule type and redisplay the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Add Sourcing Rule Window



To display this window, select **F10=Add** on the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Use this window to add a sourcing rule type to your selected sourcing rule access details. The fields displayed on this window depend on the criteria you set up for your sourcing rule access details using the Sourcing Rule Access option; this can include item and customer attributes, specific item or customer reference numbers, or no reference to item and customer details at all.

IN191 AS - ALG Systems USER STDFIN 15/02/00 15:49:11

Maintain sourcing rule details for Sales Order

Item attribute type..... PGMJ Item Group Major
Customer attribute type..... TN Salesman

Sel Rule Item type attribut

Effectivity--->
From Date To

Pos'n to Item att att..

1=Amend 2=Details 4=Delete
F3=Exit F5=Refresh F10=Add F12=Previous

MA a MW 13/048

Fields:

Sourcing Rule Type

Enter the sourcing rule type you want to use. These are defined against major type SRRT in Inventory descriptions.

Item Attribute

Select the item attribute you want to use to trigger the sourcing rule.

Customer Attribute

Select the customer attribute you want to use to trigger the sourcing rule.

Effective Date From

Enter the start date for your rule type.

Effective Date To

Enter the end date for your rule type.



Tip: If the effectivity date ranges overlap an existing record, a warning message is displayed. You must alter the dates before you can update the information.



Select **F8=Update** to save any changes and redisplay the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Sourcing Rule Detail Maintenance Screen



To display this screen, select **F8=Update** on the Add Sourcing Rule Window.

Or:

Enter 2 against a sourcing rule type on the Maintain Sourcing Rule Details For Sales Order Detail Screen.

Use this screen to add sequenced source details for your selected sourcing rule type. The top half of the screen displays any trigger criteria for your selected sourcing rule type and the effectivity dates for the sourcing rule type. The middle of the screen displays any existing source sequence details. Use the entry field at the bottom of the screen to select the sequence you want to view at the top of the display.

IN192	AS - ALG Systems	USER STDFIN	15/02/00
			15:52:56
Sourcing Rules Maintenance			
Item attribute type... E		Customer attribute type... B	
Effective from..... 15/02/00 to 99/99/99			
Sel Seq.	Source type	Strm	Supplier
- 010	07		
- 015	01		SUKM002
Add Seq.	Supply Company	<---Effectivity--->	
001		Date From	Date To
		15/02/00	99/99/99
		15/02/00	99/99/99
1=Amend 4=Delete Position to Sequence: 000			
F3=Exit F5=Refresh F10=Add F12=Previous			

Fields:

Select (Sel)

Enter one of the following:

1 - Amend. To amend the details of an existing sequenced source detail.

4 - Delete. To delete a source detail.

Position To Sequence

If the list of sourcing detail sequences is too big to display on the screen, enter the sequence that you want to display at the top of the screen and press **Enter** to change the display.

Functions:

F5=Refresh

Select this to redisplay the original details.

F10=Add

Select this to add sourcing rule detail sequences to your selected sourcing rule type.

Sourcing Rule Detail Amendment Window



To display this window, enter 1 against a sequenced source detail and press **Enter** on the Sourcing Rule Detail Maintenance Screen.

Use this window to amend existing sequenced source details for your selected sourcing rule type.

IN192		AS - ALG Systems		USER STDFIN		16/02/00 15:53:18	
Sourcing Rules				Sourcing Rule Detail Amendment			
Item.....		Sequence.....	010			... CUKM001	002
Effective from.		Source type.....?	01				
Sel Seq.	Sourc	Stockroom.....?					
1	010	Supplier.....?	SUKM002	000			
	type	Supply company.....				activity--->	
	01	Override planning route..	(1=Yes,0=No)			om Date To	
		Route.....?				0	99/99/99
		Effective Date From.....	16/02/00				
		Effective Date To.....	99/99/99				
		Direct delivery	.. 0 1=Yes, 0=No				
		User confirmation	.. 0 1=Yes, 0=No				
-							
1=Amend 4=Del		F4=Prompt F8=Update F12=Previous					
F3=Exit F5=Ref							

Fields:

Sequence

This is the sequence in which the sourcing rule type will use this sourcing rule detail. This must be a three digit value. You can change the default sequence number if required.

Source Type

Enter one of the following source types to determine how the sourcing rule will source this demand:

- 01 - Purchase. To create a requisition to source this demand.
- 02 - Manufacture. To create a configure to order, or a manufacture to order document for Production to produce this item to meet this demand. You can only use this if you are using Configurator.
- 03 - Transfer. To transfer the item from another stockroom to meet this demand.
- 04 - Stock. To use items currently in stock to meet this demand.
- 05 - Enterprise. To create an Enterprise order to a specified source company to meet this demand. For more information, see the Sourcing Rule Access and Sourcing Rules options in Enterprise Orders.
- 06 - Configure. To configure to order items to meet this demand. You can only use this if you are using Configurator.

07 - Reservation. To produce a reservation against a purchase or works order to meet this demand.

Stockroom

If you specify source type 04 - Stock, or 05 - Enterprise in the Source Type field, then you must specify the stockroom that you want to use to meet this demand.

Supplier

If you specify source type 01 - Purchase or 05 - Enterprise in the Source Type field, then you must specify the supplier that you want to use to meet this demand. If you specify source type 05, then this will be the source company supplier.

Supply Company

If you specify source type 05 - Enterprise in the Source Type field, then you must specify the source company that you want to use to meet this demand.

Override Planning Route

If you enter 03 - Transfer, 04 - Stock or 05 - Enterprise in the Source Type field, then you must enter one of the following:

0 - No. Not to specify a planning route to meet this demand.

1 - Yes. To specify a planning route to meet this demand.

Route

If you entered 1 in the Override Planning Route field, select the planning route you want to use to meet this demand.

Effective Date From

Enter the start date for this sequenced source detail.

Effective Date To

Enter the end date for this sequenced source detail.

Direct Delivery

If you enter 01 - Purchase or 05 - Enterprise in the Source Type field then you must enter one of the following:

0 - No. Not to supply the demand as a direct delivery to the target customer or company.

1 - Yes. To supply the demand as a direct delivery.

User Confirmation

If you enter 01 - Purchase or 05 - Enterprise in the Source Type field then you must enter one of the following:

0 - No. The user does not have to confirm delivery of the required items.

1 - Yes. The user does have to confirm delivery.



Select **F8=Update** to save any changes and redisplay the Sourcing Rule Detail Maintenance Screen

Confirm Rule Detail Deletion Window



To display this window, enter 4 against a sequenced source detail and press **Enter** on the Sourcing Rule Detail Maintenance Screen.

Use this window to confirm the deletion of the selected sourcing rule detail.

```

IN192                AS - ALG Systems                USER STDFIN    15/02/00
                                                    15:53:04

Sourcing Rules Maintenance

Item attribute type... E                Customer attribute type... B

Effective from..... 15/02/00    to    99/99/99

Sel Seq.  Source  Strm  Supplier      Add  Supply  <---Effectivity--->
         type
  4  010      07
-   015      01

```

Confirm Rule Detail Deletion

Warning: The requested function will delete this sourcing rule detail.

F11=Delete F12=Previous

```

1=Amend  4=Delete  Position to Sequence: 000
F3=Exit  F5=Refresh F10=Add  F12=Previous

```

Functions:

F11=Delete

Select this to confirm the deletion of your selected sourcing rule detail.



Select **F11=Delete** to delete the sourcing rule details and redisplay the Sourcing Rule Detail Maintenance Screen.

Sourcing Rule Detail Addition Window



To display this window, select **F10=Add** on the Sourcing Rule Detail Maintenance Screen.

Use this window to add sequenced source details to your selected sourcing rule type. For more information about the fields on this screen, see the Sourcing Rule Detail Amendment Window.

IN192		AS - ALG Systems		USER STDFIN		15/02/00	
						16:32:00	
Sourcing Rules		Sourcing Rule Detail Addition					
		Sequence.....	000				
		Source type.....?	—				
Effective from.		Stockroom.....?	—				
		Supplier.....?	—				
Sel Seq.	Sourc	Supply company.....	—				
	type	Override planning route..	(1=Yes,0=No)	activity--->			
		Route.....?	—	om Date To			
		Effective Date From.....	1/01/00				
		Effective Date To.....	14/02/00				
		Direct delivery ..	1=Yes, 0=No				
		User confirmation ..	1=Yes, 0=No				
1=Amend 4=Del							
F3=Exit F5=Ref		F4=Prompt F8=Update F12=Previous					



Select **F8=Update** to save this sequenced source detail to your selected sourcing type rule and redisplay the Sourcing Rule Detail Maintenance Screen with this new source detail displayed.

Location Map

1... **14/INUM & 1/INUM & 1/INU**
2...

If you are using Location Control, then you can use this option to define the locations within a stockroom. Each location can be up to 12 characters long and can be created in ranges. You can also define the status of each location as being either in use or suspended.

There are two ways of accessing this option. You can access the Location Map as part of the Inventory Company Profile option, or you can use this option to access it.

For more information about this option see the Maintain Location Map Screen within the Inventory Company Profile option.

-
-
-
-
-

Chapter 2

Inventory Processing

Introducing Inventory Processing

Inventory Processing is also commonly known as stock movement transfer.

The primary functions of Inventory Management are to record stock movements and determine, at any moment, the current stock levels. To achieve this there are a number of different types of stock movements.

Whilst you can record these transactions within Inventory Management, it forms part of an integrated business system, and other applications can perform many transactions more easily. For example, Purchase Management handles the receipt of goods, and Sales Order Processing the despatch. The main transactions within Inventory Management are stock counting and housekeeping.

When you process transactions, the format of the screen is very similar for all transactions. To simplify the process, you enter common data on the first screen. The second screen records the detail of the movement.

Processing Within A Location Controlled Stockroom

If your stockroom is Location Controlled, then you need to enter Location Control data for all Inventory transactions, with the exception of the Record Purchase Order Receipt and Adjust Allocated Stock transactions.

For all other transactions, the following principles apply:

- You do not need to capture location balances for items that are defined to single locations; in this case, the balance is updated automatically with the transaction balance of the movement.
- If items are defined to more than one location, then you can capture the location balances after you have specified the item and transaction quantity (and optionally the lot reference). The total of the location balances must match the transaction quantity before you can complete the movement.
- In both cases, location balance records are recorded for each movement that is processed, and the location balances are updated immediately after the Inventory balance is updated.

Processing With Negative Stock In A Location Controlled Stockroom

For each Inventory stockroom, you can specify whether negative stock is allowed. You can still process Location Control stock transactions if negative stock is allowed.

If you are using Catchweight, then when you update the location data during the stock transactions, the software will check that stock will not go negative for primary and secondary stock balances. A warning message will appear, but if negative stock is allowed in the stockroom, you can override this warning.

The negative stock check only occurs for Location Control where there are multiple locations in the stockroom.

Processing Logic Within Inventory

Because Inventory is such a powerful application, and is the main prerequisite for other System 21 applications, there is a certain logic to the way in which it deals with processing transactions. When you press **Enter** on any of the Detail Screens Inventory will check the following:

1. If the stockroom is controlled by Inventory and you are not using Catchweight, (or the item is not an item that requires secondary balance details) then processing continues as normal and will redisplay the required Detail Screen for confirmation of the transaction.
2. If the stockroom is controlled by Inventory and you are using Catchweight, then the Secondary Value Entry Window is displayed so that you can specify the required Catchweight details before redisplaying the Detail Screen for confirmation of the transaction.
3. If the stockroom is controlled by Warehousing and you are not using Catchweight (or the item is not an item that requires secondary balance details) then the Warehouse Pack Types Window is displayed. Use this to confirm the pack details before redisplaying the required Detail Screen for confirmation of the transaction.
4. If the stockroom is controlled by Warehousing and you are using a Catchweight type 1 or 2 item, (or the item is not an item that requires secondary balance details) then the Secondary Value Entry Window is displayed. Then the Warehouse Pack Types Window is displayed before it redisplay the required Detail Screen for confirmation of the transaction.
5. If the stockroom is Location Controlled and you are processing a Location Controlled item (with or without Catchweight), then the Enter Location Balances Window is displayed so that you can specify location balance details before redisplaying the required Detail Screen so that you can confirm the transaction.

Receipts, Issues And Adjustments

You can categorise the main processes concerned with Inventory as receipts, issues or adjustments of stock.

Record Purchase Order

1...
2...

1/INP

Use this option to maintain details of the supply position held in the on order balance. Once you have recorded a purchase order using this option, you can then use the Purchase Order Receipt option to receive those goods into Inventory.



Warning: You normally record purchase orders within Purchase Management. The following applies to those companies without Purchase Management.

Record Purchase Order Selection Screen



To display this screen, select Record Purchase Order.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 9:46:46
Record Purchase Order			
Stockroom.....?..	___		
Reference.....	_____	Reference date... <u>6/09/00</u>	
Reference type.....?..	___		
Narrative.....	_____		
Reason code.....?..	___		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number for the movement using up to 14 alphanumeric characters; you can link this with the reference type.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the Reference T00type field to enter a mnemonic to describe the reference number. For example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file under major type MOVR. See Descriptions.



Press **Enter** once to confirm the details and again to display the Record Purchase Order Detail Screen.

Record Purchase Order Detail Screen



To display this screen, press **Enter** twice on the Record Purchase Order Selection Screen.

Use this screen to record the details of the purchase order.



Note: The fields at the bottom of the screen default from the information you specified on the Record Purchase Order Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00
					9:47:44
Record Purchase Order					
Stockroom.....?..	<u>01</u>	Central Stockroom			
Supplier.....	_____				
Item.....?..	_____				
Movement qty.....	_____				
Lot.....?..	_____				
Quantity units....?..	___	Stock....			
Cost/unit.....	_____	Purchase..			
		Issue....			
Reference.....		<u>heb060900-01</u>	Reference date...	<u>6/09/00</u>	
Reference type....?..		<u>IN</u> Internal			
Narrative.....		<u>Trial</u>			
Movement Reason...?..		<u>II</u> Initial Take-on of stock			
F3=Exit F4=Prompt F12=Previous F17=Lot					

Fields:

Supplier

Define the source of supply, using up to 11 alphanumeric characters.



Warning: These supplier details are not confirmed against supplier profiles in Purchase Management.

Item

Enter the item code. The software displays the description.

Movement Qty

Enter the quantity of the item.

Lot

You do not need to supply a lot number when you record a purchase order.

Quantity Units

Select one of the three units of measure defined on the item file.

The default is the purchase unit.

This transaction processes the following update for each purchase order recorded:

- Includes the quantity in the on order balance.



*Note: If you are using Catchweight, when you press **Enter**, Inventory calculates the cost of the movement and the movement balance from the nominal secondary balance for all Catchweight item types.*



Press **Enter** to check the data. Press **Enter** again to carry out the update.

Purchase Order Receipt

1...
2...

2/INP

Use this option to receive stock supplied as a result of a purchase order generated outside the Purchase Management application.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Warning: You normally record purchase orders within Purchase Management. The following applies to those companies without Purchase Management.

Record Purchase Receipt Selection Screen



To display this screen, select Purchase Order Receipt.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

```

IN009          Z1 - GB Demonstration Company   USER GBJBA1MS   6/09/00
                                           9:50:58

Record Purchase Receipt

Stockroom.....?.. 01
Reference.....?.. heb060900-01           Reference date... 6/09/00
Reference type.....?.. IN
Narrative.....?.. trial
Reason code.....?.. II Initial Take-on of stock

F3=Exit  F4=Prompt
  
```

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters. You can link this with the reference type.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Press **Enter** once to confirm the details and again to display the display the Record Purchase Receipt Detail Screen.

Record Purchase Receipt Detail Screen



To display this screen, press **Enter** twice on the Record Purchase Receipt Selection Screen.

Use this screen to record details for a receipt.



Note: The fields at the bottom of the screen default from the information you specified on the Record Purchase Receipt Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00
					9:51:35
Record Purchase Receipt					
Stockroom.....?..	01	Central Stockroom			
Supplier.....					
Item.....?..	5031	Paracetamol 100 tabs x 50 Box			
Movement qty.....	10.000				
Lot.....?..	8001				
Quantity units....?..	BX	Stock.... PL	Pallets Of		
Cost/unit.....	55.00000	Purchase.. CA	Cases of		
	Average Cost	Issue.... BX	Boxes of		
Reference.....	heb060900-01	Reference date...	6/09/00		
Reference type....?..	IN Internal				
Narrative.....	trial				
Movement Reason...?..	II	Initial Take-on of stock			
F3=Exit F4=Prompt		F12=Previous F17=Lot			

Fields:

Supplier

Define the source of supply using up to 11 alphanumeric characters.



Warning: The supplier details are not confirmed against supplier profiles in Purchase Management.

Item

Enter the item code. The description is automatically generated.

Movement Qty

Enter the quantity of the item using up to 11 alphanumeric characters.

Lot

Enter a lot number for the item you want to receive, using up to 15 alphanumeric characters.



*Note: To receive stock to a new lot number, enter the reference and press **Enter** to display the Lot Header Details Window to define your new lot reference.*

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of measure defaults to that defined as the purchase unit for this item and stockroom combination but you can change this.



Press **Enter**, to check the details for each item and to prompt for the next item number.



Note: You cannot receive more than is on order. If you do, then the following message is displayed: You cannot make a receipt for more than has been ordered. You must return to Record Purchase Order and enter a new order before you try to receive stock.

If you receive a negative stock quantity the software will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction processes the following updates:

- The movement quantity is added to the physical stock for the item stockroom combination.
- The movement quantity is subtracted from on order balance.
- The available stock is recalculated.
- The costs are recalculated (average, latest, and the creation of a FIFO record, depending on costing method).

- The date of last receipt is updated.

As costs are recalculated, if you use any form of actual costing you must enter a cost. If the item is lot controlled and a lot of the stated number does not exist, the software creates a new one.



Press **Enter** to process the receipt and return to the Record Purchase Receipt Selection Screen.

Miscellaneous Receipt

1...
2...

3/INP

Use this option to record the receipt of goods not covered by other options or applications.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Note: If you are using Catchweight, the movement cost of Catchweight items is based on the secondary value entered. When you enter a cost, it is in the item's secondary UoM.

Record Miscellaneous Receipt Selection Screen



To display this screen, select Miscellaneous Receipt.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 9:52:16
Record Miscellaneous Receipt			
Stockroom.....?..	___		
Reference.....	_____	Reference date...	<u>6/09/00</u>
Reference type.....?..	___		
Narrative.....	_____		
Reason code.....?..	___		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Miscellaneous Receipt Detail Screen.

Record Miscellaneous Receipt Detail Screen



To display this screen, press **Enter** twice on the Record Miscellaneous Receipt Selection Screen.

Use this screen to enter individual stock movements.



Note: The fields at the bottom of the screen default from the information you specified on the Record Miscellaneous Receipt Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00 9:55:28
Record Miscellaneous Receipt					
Stockroom.....?..	<u>01</u>	Central Stockroom			
Received from.....					
Item.....?..	<u>5010</u>	Shampoo frequent use large 400ml			
Movement qty.....	<u>5.000</u>				
Lot.....?..					
Quantity units....?..	<u>BX</u>	Stock.... PL	Pallets Of		
Cost/unit.....	<u>15.00000</u>	Purchase. CA	Cases of		
	<u>Latest cost</u>	Issue.... BX	Boxes of		
Reference.....		<u>heb060900-02</u>	Reference date...	<u>6/09/00</u>	
Reference type....?..		<u>IN</u> Internal			
Narrative.....		<u>Take On</u>			
Movement Reason...?..		<u>II</u> Initial Take-on of stock			
F3=Exit F4=Prompt F12=Previous F17=Lot					

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Received From

This is a free format field, enter up to 10 alphanumeric characters to describe whom you received this item from.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the quantity you want to receive, using up to 11 characters including three decimal places.

Lot Number

Enter a new lot number for the item, using up to 15 alphanumeric characters, or select an existing lot number.



*Note: To receive stock to a new lot number, enter the reference and press **Enter** to display*

the Lot Header Details Window to define your new lot reference.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This defines the unit of measure in which the movement quantity is expressed. The unit of measure defaults to that defined as the purchase unit for this item and stockroom combination but you can change this.

Cost/Unit

Enter the cost/unit using up to 15 numeric characters including five decimal places.

If the movement is a goods receipt transaction and latest, average or FIFO costing is in use, the software uses this method of costing to value the movement. Otherwise, the software values the movement according to the costing method defined for the item and stockroom combination.

Cost/unit is not used for issues. If you leave the cost per unit blank, the highlighted message: Zero unit cost has been entered is displayed at the base of the screen. You can amend the cost at this stage in the procedure.



Note: With standard costing and no batch/lot/serial control, you only need to specify the item and movement quantity.



Press **Enter** to display the three units of measure for the item. The first unit of measure, equal to the issue units of the item at this particular stockroom is highlighted in reverse image as the default units. You can still amend the screen details at this stage.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

If you specify a lot number that does not yet exist, Inventory displays the Lot Reference Maintenance Screen.



Tip: The detail screen for the transaction that you are processing will redisplay until you do not need to make any more changes, in which case press **Enter** to process the movement and prompt for the next item number.



When you have entered the entire batch of movements and processed the last movement, select **F12=Previous** to return to the previous screen.

This transaction processes the following updates:

- The movement quantity is added to physical stock for this item and stockroom combination.
- The available stock is recalculated.
- Costs are recalculated (average, latest) and a FIFO record is created, depending on costing method.
- The date of last receipt is updated.

As costs are recalculated, if you use any form of actual costing you must enter a cost. If the item is lot controlled and a lot of the stated number does not exist, Inventory creates a new one.



Press **Enter** again to carry out the update.

Enter Location Balances Window



To display this window, press **Enter** during any stock transaction processing option, if you are using Location Control.



Note: This window is not displayed if you are using the Record Purchase Order or Adjust Allocated Stock transactions to process Inventory movements.

Use this window to record the balances and quantities affected by this transaction.

The top of the window displays the item and stockroom information. If you are processing a receipt or adjustment of stock, then it displays the legend Target Location. If you are processing an issue of stock, then it displays the legend From Location in the top right hand corner of the screen for your information.

Processing Within A Location Controlled Stockroom Using Catchweight

If you are using both Location Control and Catchweight, then the existing Secondary Balance Entry Window is no longer used. There are three factors that determine how secondary balances and location balances are processed:

1. Is the secondary balance captured or calculated?
2. Is the item stocked in single or multiple locations?
3. Are secondary balances collected at the location level?

These three factors give the following combinations:

Are secondary balances captured or calculated?	Do Items have single, default, locations or multiple locations?	Are secondary balances collected by location?	Categorisation for fields displayed in the window
Calculated (or no secondary balance required)	Multiple	Yes or not applicable	Case 1
Calculated (or no secondary balance required)	Single	No, or not applicable	Case 2 (no window is displayed, normal processing occurs)
Captured	Multiple	No	Case 3
Captured	Multiple	Yes	Case 4

The fields and their descriptions define those displayed if you are processing using Case 1, that is, a Catchweight item with a single, or default, location and you do not need to capture the secondary balance by location. Any variations on this window are detailed under the relevant case section.

IN009 Enter Location Balances		9/00 3:05
Recor	Item..... MMBSNM Stockroom.. LX	Target Location
	Normal std 2/loc	
Stock	Order.....	Location... A25
Recei	Line..... 0000	
Item.		
Movem	Total 10.000 TH	
Lot..	Cumulative .000 TH	
Quant		
Cost/	S Location Quantity Uom	
Refer	2=Amend, 4=Delete	
Refer		
Narra	Location (?) Quantity Uom	
	A25 10.000 TH (?)	
Movem		
F4=Prompt F8=Update F12=Previous		
F3=Exit F4=Prompt F12=Previous F17=Lot		

Fields:

Header Section

Item

This is your selected item code; its description is displayed below the code.

Stockroom

This displays the stockroom that you are processing this transaction from.

Order

This displays the sales, production, works or purchase order that this transaction is attached to, if this is applicable.

Line

This is the associated order line for this item. If there is no sales, production, works or purchase order attached to the transaction then this field displays four zeros.

Location

This is the item's default location.

Total

This is the transaction quantity and the unit of measure that you specified during the transaction.

Cumulative

This is the current total of the location balances and is displayed in the same unit of measure as the transaction quantity.

Batch, Lot Or Serial Controlled Items And Location Control

If you are processing an item that is batch, lot or serial controlled, then the following fields are displayed:

Lot (Batch or Serial Number)

This displays the batch, lot or serial number reference for your selected item in the top section of the window.

Middle Section

Select (S)

Enter one of the following:

2 - Amend. To amend any existing details. Enter 2 against an existing line and press **Enter** to redisplay those details in the line entry fields at the bottom of the window to amend them. Press **Enter** again to redisplay those amended details in the middle of the screen.

4 - Delete. To delete existing details. Enter 4 against a line and press **Enter** to delete them.

Location

This displays the locations you have selected for use for this transaction. During Sales Order Processing Interactive Confirmation Of Despatch, the window will be pre-filled with the locations and balances printed on the pick note.

Quantity

This displays the entered location balance.

UoM (Unit Of Measure)

This displays the entered transaction's unit of measure.

Footer Section

Location

This is where you enter the location you want to use for this balance. It is initially pre-filled with the suggested, or default, location for your selected item in all circumstances except during Confirmation Of Despatch when it is blank.. You can prompt to view all active locations for your item.



Tip: If you attempt to use a location that is suspended the system displays an error message.

Quantity

This is the amount of location balance you want to process. This initially defaults to the full transaction amount in all circumstances except during Confirmation of Despatch, but you can change it if required.



Note: For more information, see Processing Within A Location Controlled Stockroom.

UoM (Unit Of Measure)

This is the default unit of measure for the transaction quantity. You can prompt to view the item's other units of measure.



Note: For more information, see Processing Within A Location Controlled Stockroom.

Case 3

If you are processing a Catchweight item with multiple locations and you do not need to capture secondary balances by location, then the following fields are displayed on the Enter Location Balances Window:

Header Section

Secondary Balance



Note: The name of this field depends on the Name of the Secondary Balance Unit Of Measure.

This field is displayed to the right of the Total and Cumulative fields. Enter the total secondary balance value in this field for all locations that are included in the transaction.

Case 4

If you are processing a Catchweight item with multiple locations and you need to capture secondary balances by location, then the following fields are displayed on the Enter Location Balances Window:

Header Section

Secondary Balance



Note: The name of this field depends on the Name of the Secondary Balance Unit Of Measure.

This field is displayed to the right of the Total and Cumulative fields. This displays the cumulative secondary balance value for all locations that are included in the transaction.

Middle Section

Secondary Balance

This displays the secondary balance value for each existing location.

UoM

This displays the unit of measure attached to the secondary balance.

Footer Section

Secondary Balance

Enter the secondary balance value for the selected item that you want to process. This initially defaults to the nominal secondary balance for the transaction quantity but you can change it if required.

UoM

This is the default unit of measure for the secondary balance value you have entered. You can change this to any valid secondary unit of measure attached to the item if required.

Case 5

If you are processing a Catchweight item with a single, default location a different window is displayed. This window performs the same function as the Secondary Value Entry Window although it displays more information about the transaction and

the location that will be processed. For more information see the Enter Secondary Balances Window.

Functions:

F4=Location Prompt

Use this to display the Location Prompt Window. If you are processing a receipt or an adjustment, then the window displays all locations that currently stock the item at the top of the list, followed by all other locations within the stockroom. If you are processing an issue of stock, then the Location Prompt Window will only display locations with stock of the selected item. Suspended locations are always excluded.



Select **F8=Update** to update the location control balances and redisplay the main processing screen for your transaction. You can only select this if your location balance quantities match the transaction quantity.

Enter Secondary Balances Window



To display this screen, press **Enter** during any stock transaction processing option if you are using Location Control and you are processing a Catchweight item with a single, default location.

Use this screen to confirm, or amend your item's secondary balance and location details.

This screen is only displayed if you are using Location Control and mirrors the functionality of the Secondary Value Entry Window. The tolerance check is performed against the transaction total.

IN009		MM - Location Control & Catchweight USER GBJBA1MS		11/05/00	
				11:39:40	
Record Miscellaneous Receipt					
Stockroom.....?..		<u>L1</u>		LC/1	
Received from.....					
Item.. Enter Kilos					
Moveme		Item..... MM1FNSNH		Stockroom.. L1	
Lot...		Type 1 fifo 1/loc			
Quanti		Order.....		Location... R52	
Cost/u		Line..... 0000			
		Total HD		Secondary Balance	
		1.000		10.0000	
				UoM KG (?)	
Ref.no F4=Prompt F12=Previous					
Narrative.....					
Movement Reason...?..					
F3=Exit F4=Prompt F12=Previous F17=Lot					

Fields:

Target Location

This is displayed in the top right hand corner of the window. For receipts and adjustment transactions it displays the title Target Location. For issues it displays the title From Location.

Item

This displays the code of the item you are processing. The item description is displayed below the item code.

Stockroom

This displays the stockroom that you are processing from.

Order

This displays the sales, production, works or purchase order that this transaction is attached to, if this is applicable.

Location

This is the item's default location.

Line

This is the associated order line for this item. If there is no sales, production, works or purchase order attached to the transaction then this field displays four zeros.

Batch, Lot Or Serial Controlled Items And Location Control

If you are processing an item that is batch, lot or serial controlled, then the following fields are displayed:

Lot (Batch or Serial Number)

This displays the batch, lot or serial number reference for your selected item in the top section of the window.

Total

This is the transaction quantity and the unit of measure that you specified during the transaction.

Secondary Balance

This is the secondary balance for this transaction, it defaults to the nominal secondary balance for the transaction quantity.

UoM

This is the unit of measure of the location balance. It defaults to the item's default unit of measure. You can prompt to display any valid codes for this item.



Press **Enter** to confirm the details and continue to process the transaction.

Secondary Value Entry Window



To display this window, press **Enter** during any stock processing transaction if you are using Catchweight, and your item is defined as a Catchweight category 1 or 2 item.

Use this window to confirm, or amend your item's secondary unit of measure and the quantity you want to process.



Note: The title of this screen will vary as it is formed from the short description of the item's secondary unit of measure and the word Details. For example if your item's secondary unit of measure was Kg, then the window's title would be Kilo Details Entry Window.

IN009	MM - Catchweight Company MM	USER GBJBA1MS	22/02/00 13:14:44
Record Miscellaneous Receipt			
Stockroom.....?..	I1	IN/1	
Received from.....			
Item.....?..	PS-C1		
Movement qty.....	1		
Lot.....?..			
Quantity units....?		Stock....	
Cost/unit.....		Purchase.	
		Kilos Details PS-C1 1.000 EA Movement Kilos 2.0000 Unit of measure....?... KG F4=Prompt F12=Cancel Held finished item	
Ref.no.date & type?..	heb01		
Narrative.....			
Movement Reason...?..	#2		
F3=Exit F4=Prompt		F12=Previous F17=Lot	

Fields:

Untitled 1

This displays the item code.

Untitled 2

This displays the primary quantity that you have just entered.

Untitled 3

This displays the unit of measure you have just entered, or the item's default stockroom issue unit of measure.

Movement Value

This is the movement quantity in the item's secondary unit of measure. You can override this value. If you enter a value that exceeds the configured tolerance, a warning message will be displayed.



Note: The title of this field changes to display the literal for the secondary unit of measure, for example, Movement Kilos, or Movement Ounces.

Unit Of Measure

This displays the item's secondary unit of measure. You can change this if required.



Press **Enter** to confirm the details and redisplay the relevant processing screen to process the transaction.

Customer Order Issue

1...
2...

11/INP

Use this option to issue stock to a customer order if you are not linked to the Sales Order Processing application.

You can only issue previously allocated stock. To do this, use Adjust Allocated Stock in Inventory Processing. There is no link with allocating stock to a customer order in the Sales Order Processing application.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Warning: You normally process sales orders through Sales Order Processing. The following applies to companies without Sales Order Processing.

Record Customer Order Issue Selection Screen



To display this screen, select Customer Order Issue.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 9:58:17
Record Customer Order Issue			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-03</u>	Reference date...	<u>6/09/00</u>
Reference type.....?	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>IT</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

You must enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

You must enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

You must enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Customer Order Issue Detail Screen.

Record Customer Order Issue Detail Screen



To display this screen, press **Enter** twice on the Record Customer Order Issue Selection Screen.

Use this screen to record the details of the customer's order issue.



Note: The fields at the bottom of the screen default from the information you specified on the Record Customer Order Issue Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00
					10:01:36
Record Customer Order Issue					
Stockroom.....?..	01	Central Stockroom			
Customer.....					
Item.....?..	5001	Suncream Factor 4 225ml			
Movement qty.....	10.000				
Lot.....?..					
Quantity units....?..	BX	Stock.... PL	Pallets Of		
Cost/unit.....	1.05525	Purchase. CA	Cases of		
	Standard Cost	Issue.... BX	Boxes of		
Reference.....	heb060900-03	Reference date...	6/09/00		
Reference type....?..	IN Internal				
Narrative.....	Order01				
Movement Reason...?..	II	Initial Take-on of stock			
F3=Exit		F4=Prompt		F12=Previous	

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Customer

Enter the customer, using up to 11 alphanumeric characters. Customer details are not checked against customer profiles in Sales Order Processing.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the quantity you want to issue using up to 11 characters including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of

measure defaults to the purchase unit for this item and stockroom combination, but you can change this.

Cost/Unit

Cost/unit is not used for issues.



Note: With standard costing and no batch/lot/serial control, you only need to specify the item and movement quantity.



Press **Enter** to display the three units of measure for the item. The first unit of measure, equal to the issue units of the item at this particular stockroom is highlighted in reverse image as the default units. You can still change the screen at this point.

If Inventory displays the error message: Cannot Issue More Than Has Been Allocated at the base of the screen, with a negative number next to the message Allocated Stock, and you want to continue with an issue, you must:

- Exit the Customer Order Issue Screen and select the Adjust Allocated Stock option.
- Enter a number of items equal to or greater than the negative allocated stock figure displayed at the same time as the error message.
- Return to the Customer Order Issue option and continue as before.

If Inventory displays the error message: Standard unit cost has not been defined in stockroom, at the base of the screen, and you want to continue with an issue you must:

- Exit the Customer Order Issue Screen.
- Select the Stockroom Details option.
- Enter a standard cost for the item in the issuing stockroom.
- Return to the Customer Order Issue option and continue as before.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry*

Window.

This transaction processes the following updates:

- The movement quantity is subtracted from the physical stock and allocated stock for the item and stockroom combination.
- Available stock for the item and stockroom combination is calculated.
- Usage figures for the item and stockroom combination are updated.
- The last issue date for the item and stockroom combination is updated.



Press **Enter** again to carry out the update.

Miscellaneous Issue (Physical)

1...
2...

12/INP

You can use this option to issue stock regardless of how much is available. If the stockroom allows you to process negative stock, then you can use this option to issue more stock that you currently have in the stockroom after a warning message.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Warning: Use this option carefully, to avoid problems with the stock levels.

Record Miscellaneous Issue (Physical) Selection Screen



To display this screen, select Miscellaneous Issue (Physical).

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:01:53
Record Miscellaneous Issue			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-04</u>	Reference date...	<u>6/09/00</u>
Reference type.....?..	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>II</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the Record Miscellaneous Issue (Physical) Detail Screen.

Record Miscellaneous Issue (Physical) Details Screen



To display this screen, press **Enter** twice on the Miscellaneous Issue (Physical) Selection Screen.

Use this screen to record the details of the miscellaneous stock issue.



Note: The fields at the bottom of the screen default from the information you specified on the Record Miscellaneous Issue (Physical) Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00 10:03:54
Record Miscellaneous Issue					
Stockroom.....?..	01	Central Stockroom			
Issued to.....?	N ELLAM				
Item.....?..	5001				
Movement qty.....	10				
Lot.....?..					
Quantity units....?..		Stock....			
Cost/unit.....		Purchase.			
		Issue....			
Reference.....		heb060900-04	Reference date...	6/09/00	
Reference type....?..		IN Internal			
Narrative.....		trial			
Movement Reason...?..		II	Initial Take-on of stock		
F3=Exit		F4=Prompt	F12=Previous		

Fields:

Stockroom

This stockroom code defaults from the selection screen; but you can change it.

Issued To

Enter a name or reference, using up to 11 alphanumeric characters.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the issue quantity using up to 11 characters including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of

measure defaults to the purchase unit for this item and stockroom combination, but you can change this.

Cost/Unit

This field is not used for issues.



Press **Enter** to check these details. This option does not check to see if the stock is available, so a negative available stock figure could result.

If you receive a negative stock quantity, the software will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction processes the following updates:

- Subtracts from the physical balance.
- Recalculates the available stock balance.
- Includes the transaction quantity in the usage details.
- Updates the date last issued.



Press **Enter** again to carry out the update.

Physical Stock Adjustments

1...
2...

31/INP

You can use this option to adjust physical stock levels without altering any other stock levels. All screens are the same as those for the Miscellaneous Receipt option, omitting any Customer/Received From fields.

This is one transaction where it would be common to have a negative movement quantity.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Record Stock Adjustment (Physical) Selection Screen



To display this screen, select Physical.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

Secondary Balance Validation And Adjusting Secondary Balances By Location

The validation rules that apply to the secondary balance value normally follow those that apply to the primary balance for all transactions with the exception of the Adjust Physical Stock option. The normal rule being that the value must not be zero and takes the sign of the transaction quantity by default (you cannot enter a sign).

If you use this option, then the transaction quantity can be zero (which is how you can adjust the secondary balances of an item without having to move stock). In this case the secondary balance must still not be zero, but you can now specify the sign of each balance. If you are processing an item with multiple locations, you can use a mix of positive and negative signs to process the adjustment.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:05:13
Record Stock Adjustment			
Stockroom.....?..	<u>01</u>		
Reference.....?..	<u>heb060900-05</u>	Reference date...	<u>6/09/00</u>
Reference type.....?..	<u>IN</u>		
Narrative.....?..	<u>trial</u>		
Reason code.....?..	<u>IT</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and

week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Stock Adjustment (Physical) Detail Screen.

Record Stock Adjustment (Physical) Detail Screen



To display this screen, press **Enter** twice on the Record Stock Adjustment (Physical) Selection Screen.

Use this screen to record the details of the physical stock adjustment.



Note: The fields at the bottom of the screen default from the information you specified on the Record Stock Adjustment (Physical) Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00 10:05:50
Record Stock Adjustment					
Stockroom.....?..		01 Central Stockroom			
Item.....?..		5001			
Movement qty.....		1			
Lot.....?..					
Quantity units....?..		— Stock....			
Cost/unit.....		Purchase.			
		Issue....			
Reference.....		heb060900-05		Reference date... 6/09/00	
Reference type....?..		IN Internal			
Narrative.....		trial			
Movement Reason...?..		II Initial Take-on of stock			
F3=Exit F4=Prompt		F12=Previous F17=Lot			

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the quantity you want to adjust using up to 11 characters including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of measure defaults to the purchase unit for this item and stockroom combination, but you can change this.

Cost/Unit

Enter the cost/unit using up to 15 numeric characters including five decimal places.

If the movement is a goods receipt transaction, and you are using latest, average or FIFO costing, this method of costing is used to value the movement. Otherwise, the movement is valued according to the costing method defined for the item and stockroom combination.

Cost/unit is not used for issues.



Press **Enter** to display the three units of measure for the item. The first unit of measure, equal to the issue units of the item at this particular stockroom, is highlighted in reverse image as the default units. You can still change the screen at this point.

If you receive a negative stock quantity, the software will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window. For non Catchweight items, if you enter zero, an error message is displayed. However, for Catchweight items, a zero primary value and a positive or negative secondary value can be entered and processed properly. This allows you to adjust the secondary balance without affecting the primary balance.*

This transaction:

- Adjusts the physical stock balance.
- Recalculates the balances for both available and frozen stock.

When Inventory adjusts the physical stock balance it updates the available or frozen stock balances, as appropriate, by the same amount.

You can use this procedure to adjust lots, if the item is lot, batch or serial controlled.



Press **Enter** again to carry out the update.

Allocated Stock Adjustments

1...
2...

32/INP

Use this option to adjust the balance between the allocated and available stock levels, without changing the physical stock level.



Warning: Using this option where Sales Order Processing is in use can have serious implications.

Record Allocated Adjustment Selection Screen



To display this screen, select Allocated.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:08:33
Record Allocated Adjustment			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-06</u>	Reference date...	<u>6/09/00</u>
Reference type.....?	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>IT</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Allocated Adjustment Details Screen.

Record Allocated Adjustment Details Screen



To display this screen, press **Enter** twice on the Record Allocated Adjustment Selection Screen.

Use this screen to record the details of the allocated adjustment.



Note: The fields at the bottom of the screen default from the information you specified on the Record Allocated Adjustment Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00
					10:09:12
Record Allocated Adjustment					
Stockroom.....?..	01	Central Stockroom			
Customer.....?	WILLS & CO				
Item.....?..	5001				
Movement qty.....	8				
Lot.....?..					
Quantity units....?		Stock....			
Cost/unit.....		Purchase.			
		Issue....			
Reference.....		heb060900-06	Reference date...		6/09/00
Reference type....?		IN Internal			
Narrative.....		trial			
Movement Reason...?		II Initial Take-on of stock			
F3=Exit F4=Prompt F12=Previous					

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Customer

Enter the customer, using up to 11 alphanumeric characters.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the quantity you want to adjust using up to 11 character including three decimal places.

Lot Number

Enter a new lot number for the item, using up to 15 alphanumeric characters, or select an existing lot number.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of

measure defaults to the purchase unit for this item and stockroom combination, but you can change this.

Cost/Unit

Enter the cost/unit using up to 15 numeric characters including five decimal places.

If the movement is a goods receipt transaction and you are using latest, average or FIFO costing, this method of costing is used to value the movement. Otherwise, the movement is valued according to the costing method defined for the item and stockroom combination.

Cost/unit is not used for issues.



Note: With standard costing and no batch/lot/serial control, you only need to specify the item and movement quantity.



Press **Enter** to display the three units of measure for the item. The first unit of measure, equal to the issue units of the item at this particular stockroom is highlighted in reverse image as the default units. You can still change the screen at this point.



*Note: If you are using Catchweight, when you press **Enter**, Inventory calculates the cost of the movement and the movement balance from the nominal secondary balance for all Catchweight item types.*

This transaction:

- Adjusts the allocated stock balance.
- Recalculates the available stock balances.

If the item is frozen or there is insufficient available stock for allocation, Inventory displays the message: You are trying to allocate more stock than you have.

You should process a receipt before continuing with the stock allocation.

If the item is lot controlled, you can display the physical and available stock balances by prompting on the Lot field. You can then continue the allocation against a lot that has sufficient available stock.



Press **Enter** to carry out the update.

Frozen Stock Adjustments

1...
2...

33/INP

Use this to alter the balance between the frozen and available stock levels, without changing the physical stock level.

You can enter details of stock that cannot be allocated or issued. You can do this as a quality assurance freeze or to reserve a lot for a particular customer. You should only use this option to adjust frozen stock for items that are not under extended lot, batch or serial control, as specified on the company profile.

The principle behind extended details is that the whole balance of a lot, batch or serial item is either frozen or unfrozen. A partially frozen balance is illogical. To freeze or unfreeze part of a lot, use the Lot Transformation option to split the original lot into its frozen and unfrozen balances.

When extended details are active, you should have the Stock Status Monitor running and use the Stock Status Recalculation option daily for items, via Machine Manager.

Therefore, adjusting the frozen balance of an item that is under extended details control is not advisable because the Stock Status Monitor will immediately reverse the adjustment.



Tip: Available Stock = Physical - Frozen – Allocated.



Note: Any stock that has not been allocated must be either available or frozen.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Record Frozen Adjustment Selection Screen



To display this screen, select Frozen.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN009	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:10:13
Record Frozen Adjustment			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-06</u>	Reference date...	<u>6/09/00</u>
Reference type.....?	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>IT</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters.

Reference

You must enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

You must enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement, using up to 20 alphanumeric characters.

Reason Code

You must enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Frozen Adjustment Details Screen.

Record Frozen Adjustment Details Screen



To display this screen, press **Enter** twice on the Record Frozen Adjustment Selection Screen.

Use this screen to record details of the adjustment of frozen stock transaction.



Note: The fields at the bottom of the screen default from the information you specified on the Record Frozen Adjustment Selection Screen.

IN009		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00
					10:10:28
Record Frozen Adjustment					
Stockroom.....?..		01 Central Stockroom			
Item.....?..		5010			
Movement qty.....		10			
Lot.....?..					
Quantity units....?..		—			
		Stock.... Purchase.. Issue....			
Reference.....		heb060900-06		Reference date...	6/09/00
Reference type....?..		IN Internal			
Narrative.....		trial			
Movement Reason...?..		II Initial Take-on of stock			
F3=Exit F4=Prompt F12=Previous F17=Lot					

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the quantity you want to adjust using up to 11 character including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of measure defaults to the purchase unit for this item and stockroom combination but you can change this.

Cost/Unit

Enter the cost/unit using up to 15 numeric characters including five decimal places.

If the movement is a goods receipt transaction and you are using latest, average or FIFO costing, this method of costing is used to value the movement. Otherwise, the movement is valued according to the costing method defined for the item and stockroom combination.

Cost/unit is not used for issues.



Note: With standard costing and no batch/lot/serial control, you only need to specify the item and movement quantity.



Press **Enter**, to display the three units of measure for the item. The first unit of measure, equal to the issue units of the item at this particular stockroom, is highlighted as the default units. You can still change the screen at this point.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight, when you press **Enter**, Inventory calculates the cost of the movement and the movement balance from the nominal secondary balance for all Catchweight item types.*

If you receive a negative stock quantity, the software will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.

This transaction:

- Adjust the frozen stock balance.
- Recalculates the available stock balance.



Press **Enter** again to carry out the update.

Or:

If you are using Location Control, press **Enter** to display the Enter Location Balances Window.

Miscellaneous Issues

If you are issuing both available and frozen stock you will need greater control on stock levels. In both cases, you cannot issue more than the actual quantity of frozen or available stock held in the stockroom.

For each option, if you try to issue more stock than the physical stock level, Inventory warns you, and prevents you from doing it.

Miscellaneous Issue (Available)

1...
2...

13/INP

You can enter details of an issue of available stock. You can amend the updates associated with this transaction type in the Inventory processing profile, to reflect the updates you need when available stock is issued.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Record Miscellaneous Issue (Available) Selection Screen



To display this screen, select Miscellaneous Issue (Available).

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN082	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:14:07
Record Miscellaneous Issue			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-07</u>	Reference date...	<u>6/09/00</u>
Reference type....?..	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>II</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Miscellaneous Issue (Available) Details Screen.

Record Miscellaneous Issue (Available) Detail Screen



To display this screen, press **Enter** twice on the Record Miscellaneous Issue (Available) Selection Screen.

Use this screen to record the details of the Miscellaneous (Available) stock issue.



Note: The fields at the bottom of the screen default from the information you specified on the Record Miscellaneous Issue (Available) Selection Screen.

IN083		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00 10:14:59
Record Miscellaneous Issue					
Stockroom.....	01	Central Stockroom			
Item.....?..	<u>5031</u>				
Movement qty.....	<u>10.000</u>				
Lot.....?..	<u>8001</u>				
Quantity units...?..	—	Stock....			
Cost/unit.....		Purchase..			
		Issue....			
Reference.....		<u>heb060900-07</u>	Reference date...	<u>6/09/00</u>	
Reference type...?..		<u>IN</u> Internal			
Narrative.....		<u>trial</u>			
Movement Reason...?..		<u>II</u> Initial Take-on of stock			
F3=Exit F4=Prompt F12=Previous					

Fields:

Stockroom

Enter the stockroom, using up to two alphanumeric characters. This defaults to the stockroom code you specified on the selection screen but you can change this.

Item

Enter the item, using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the issue quantity using up to 11 character including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of measure defaults to the purchase unit for this item and stockroom combination, you can change this.

Cost/Unit

Cost/unit is not used for issues.



Press **Enter** to check the details displayed.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight without Location Control, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction type:

- Subtracts from the physical stock balance.
- Recalculates the available stock balance.
- Includes this movement quantity in usage records for this item.
- Updates the date last issued for this item.

If you attempt to issue stock that is not available the message: Not enough stock available at this location is displayed. To continue with the issue, use the Purchase Receipt or Miscellaneous Receipt options.



Note: If the issue item uses average or FIFO costing, Inventory suggests an issue cost per item.



Select **F8=Update** to carry out the update.

Frozen Stock Issues

1...
2...

21/INP

You can enter details of an issue for stock from an item or a lot that has been frozen. You cannot issue more than is frozen. You can amend the updates associated with this transaction type in the Inventory processing profile, to reflect the updates you require when frozen stock is issued. Enter data as for other issues.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Record Miscellaneous Frozen Issue Selection Screen



To display this screen, select Miscellaneous Issue (Frozen).

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN082	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:15:39
Record Miscellaneous Frozen Issue			
Stockroom.....?..	<u>01</u>		
Reference.....?	<u>heb060900-08</u>	Reference date...	<u>6/09/00</u>
Reference type....?..	<u>IN</u>		
Narrative.....?	<u>trial</u>		
Reason code.....?..	<u>II</u>		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code that this transaction affects, using up to two alphanumeric characters. This stockroom must exist on the company profile.

Reference

Enter the reference number of the movement using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.

Narrative

Enter the narrative or description for the movement using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the descriptions file major type MOVR. See Descriptions.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.



Press **Enter** once to confirm the details and again to display the display the Record Miscellaneous Frozen Issue Detail Screen.

Record Miscellaneous Frozen Issue Detail Screen



To display this screen, press **Enter** twice on the Record Miscellaneous Frozen Issue Selection Screen.

Use this screen to record details of the miscellaneous issue of frozen stock transaction.



Note: The fields at the bottom of the screen default from the information you specified on the Record Miscellaneous Frozen Issue Selection Screen.

IN083	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:16:16
Record Miscellaneous Frozen Issue			
Stockroom.....	01	Central Stockroom	
Item.....?	5010		
Movement qty.....	10		
Lot.....?			
Quantity units....?		Stock....	
Cost/unit.....		Purchase.	
		Issue....	
Reference.....	heb060900-08	Reference date...	6/09/00
Reference type....?	IN Internal		
Narrative.....	trial		
Movement Reason...?	II Initial Take-on of stock		
F3=Exit F4=Prompt F12=Previous			

Fields:

Stockroom

This stockroom code defaults from the selection screen but you can change it.

Item

Enter the item using up to 15 alphanumeric characters. You must link existing items to the stockroom through Inventory Maintenance.

Movement Quantity

Enter the issue quantity using up to 11 character including three decimal places.

Lot Number

Select the existing lot reference number that is affected by this movement.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. The unit of measure defaults to the purchase unit for this item and stockroom combination but you can change this.

Cost/Unit

Cost/unit is not used for issues.



Press **Enter** to check the details you have entered.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction:

- Subtracts from the physical stock balances.
- Recalculates the available stock balances.
- Includes this movement quantity in usage records for this item.
- Updates the date last issued for this item.

Frozen stock includes:

- Items that have been frozen using the Adjust Frozen Stock option.
- Items where the stock status has been set to unavailable.
- Items that have not yet reached the first available date, or have passed the last available date, as indicated on the lot header, and do not have the stock status code set to released.



Note: If stock that has not yet reached the first available date and has a blank stock status code is included in the available stock, check that the stock monitor is running in the subsystem INBACK3.

If Inventory displays a warning that there is insufficient frozen stock in the stockroom for the transfer to take place, but you want to continue with the transaction you must:

- Adjust the frozen stock using the Record Frozen Adjustment option.
- Return to this option and continue as before.



Select **F8=Update** to carry out the update.

Stock Transfers

When a transfer takes place between two stockrooms, there is often not only a physical change in location, but also a change in responsibility. There are two movements to record these actions, one to transfer goods out of a stockroom and the second to transfer goods into a different stockroom.

Four options are used that relate to transferring items between stockrooms. You use:

- Record Transfer Out and Confirm Shipment Receipt together to perform the two halves of a stock transfer.
- Single Step Transfer to transfer available stock between two stockrooms, immediately. There is no change to the in transit stock balance.
- Single Step Transfer (Frozen) to transfer frozen stock between two stockrooms immediately, in a single operation.



Note: You can only transfer quantities of an item that is defined to both the transferring and receiving stockrooms.

Insufficient Frozen Or Physical Stock

If Inventory displays a message indicating that there is insufficient frozen or physical stock in the stockroom for the desired transfer to take place, and you want to continue with the transaction, you must:

- Exit the Transfer option. Select the Item/Stockroom option to view each stock balance for the item and stockroom combination.
- Then select the appropriate Stock Adjustment option (physical, available or frozen) to increase that stock balance.
- Return to the Stock Transfer option and continue as before.
- If the item is lot controlled Inventory Management automatically creates a lot with the same lot header details as the lot in the From stockroom. Until stock is transferred into this lot, both the physical and available balances are set to zero.

Costing The Transfer

The costing of your transfer depends on the costing method you specified on the item file. One of the following will apply:

- Average costing - The movement is valued at the average cost of the From stockroom, causing a recalculation of average cost at the To stockroom.
- Standard Costing - The movement out is valued at the standard cost of the From stockroom. The movement in is valued at the standard cost of the To stockroom. Any difference is written to the Inventory movement file as an A type, that is, a value only adjustment.
- FIFO - The movement out is valued at FIFO cost. The movement in creates a new FIFO record for the same value.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Record Transfer Out

1...
2...

41/INP

Use this option to record the first part of a two part transfer transaction. This option records the details related to the transfer of stock out of one stockroom before it is recorded as received in the other stockroom using the Confirm Shipment Receipt option. You would use these two options if a stock transfer is over a physical distance, for example, if you were moving stock from one area of the country to another.

The physical stock at the source stockroom will be reduced, and the in-transit stock at the destination stockroom will be increased. Once stock is transferred using this option, it will be valued as part of the stock of the destination stockroom. Cost updates at the destination stockroom will be performed once receipt is confirmed.

Record Transfer Out Selection Screen



To display this screen, select Record Transfer Out.

Use this screen to select the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN086	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:17:00
Record Transfer Out			
From stockroom....?.. <u>01</u>			
To stockroom.....?.. <u>02</u>			
Internal customer.?.. _____			
Reference..... <u>heb060900-08</u>		Reference date... <u>6/09/00</u>	
Reference type.....?.. <u>IN</u>			
Narrative..... <u>trial</u>			
Reason code.....?.. <u>IT</u>			
For domestic transactions only			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter the transferring stockroom for the item. This stockroom must exist on the company profile.

To Stockroom

Enter the receiving stockroom for the item. This stockroom must exist on the company profile.

Internal Customer

Enter the name and code of an existing customer in this field. This field depends on whether you use DRP. The customer defaults from the stockroom record held within DRP.

Reference

Enter the reference number of the movement, using up to 14 alphanumeric characters; you can link this with the reference type specified.

Reference Date

Enter a date to be used as the reference date. This field defaults to the current system date. The reference date is cross-referenced with the table of period and week end dates, to decide the week and period numbers for ageing the stock movement and history records.

Reference Type

Enter the reference type using up to three alphanumeric characters. You can define these to the descriptions file against the major type TRAN. See Descriptions.

You can use the reference type field to enter a mnemonic to describe the reference number; for example, you can use REQ to indicate that the reference number is a stores requisition note number.



Tip: This information is written to the movement history. To help you recognise, and analyse the movements, you can view and report on it.

Narrative

Enter the narrative or description associated with the movement, using up to 20 alphanumeric characters.

Reason Code

Enter a reason code chosen from those defined on the Descriptions file major type MOVR. Enter this code to indicate why the stock status code has changed.



Tip: The next two fields are only displayed when you have confirmed the movement and have redisplayed this screen so that you can exit the option.

No. Of Movements In Last Batch

This details the number of movements you have processed during this transaction. It is for information only.

Last Item Processed

This details the last item that was processed during the transaction and it is for information only.



Press **Enter** once to confirm the details and again to display the display the Record Transfer Out Detail Screen.

Record Transfer Out Detail Screen



To display this screen, press **Enter** twice on the Record Transfer Out Selection Screen.

Use this screen to record the details of the stock transfer between the selected stockrooms.



Note: The fields at the bottom of the screen default from the information you specified on the Record Transfer Out Selection Screen.

```

IN087              Z1 - GB Demonstration Company      USER GBJBA1MS      6/09/00
                                                    10:18:29

Record Transfer Out

From stockroom..... 01              Central Stockroom
To stockroom..... 02              Northern RDC Stockroom
Generated Reference..
Sel Item      Movement Qty. Lot      UOM      Cost/Unit
- 5010              10.000              BX      15.00000

1=Amend
Item.....?..
Movement qty..... Lot.....?..
Quantity units...?.. Cost/unit.....
Reference..... heb060900-08      Date.. 6/09/00
Reference type.... IN Internal
Narrative..... trial
Reason code.....?.. II Initial Take-on of stock
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F18=Despatch details
  
```

Fields:

From Stockroom

This is the code of the transferring stockroom for the item.

To Stockroom

This is the code of the receiving stockroom for the item.

Generated Reference

This is a unique code number automatically generated by the software to identify this transfer.

Select (Sel)

Enter 1 against a line you want to amend and press **Enter**. The details are then displayed at the base of the screen for modification.

Item

Enter the item, using up to 15 alphanumeric characters. You must define the item to the items file and link it to the stockroom through Inventory Maintenance. You can amend the item number displayed in this field.

Movement Qty

Enter the quantity you want to transfer, using up to 11 character including three decimal places.



*Note: If you transfer a quantity that results in a negative stock balance, Inventory will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.*

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. Only those units defined for the item are allowed. The unit of measure defaults to that defined as the issue unit for this item and stockroom combination, but you can change it here.

Narrative

Enter the item's text description.

Reference

This is the reference number that you specified on the selection screen. You can change this for each item if required.

Date

This is the movement date that you specified on the selection screen. You can change this for each item if required.

Reference Type

This is the reference type code that you specified on the selection screen. You can change this for each item if required.

Lot

Select the existing lot reference number that is affected by this movement.

Cost/Unit

Enter the cost/unit for this movement, using up to 15 numeric characters including five decimal places.

Reason Code

Enter the reason code for this movement.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Window if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction type:

- Subtracts from the physical stock in the From stockroom.
- Recalculates the available stock in the From stockroom.
- Add to in transit stock in the To stockroom.
- Updates the usage at the From stockroom.
- The date of issue is updated at the From stockroom.

Functions:

F18=Despatch Details

If you are using Centralised Document Processing, use this function to record additional despatch information associated with the movement of goods.



Once all the details for this issue are correct, press **Enter**. Press **Enter** again to transfer the movement details to the middle of the screen.

Record Transfer Out Despatch Details Window



To display this window select, **F18=Despatch Details** on Record Transfer Out Detail Screen.

Use this window to detail the document processing you want for the transfer out transaction.

```
IN087              Z1 - GB Demonstration Company    USER GBJBA1MS    6/09/00
                                                    10:18:29

Record Transfer Out
Despatch details
Document processing
Online print of despatch notes... 0 (0=No, 1=Yes)
Priced despatch note..... @ (0=No, 1=Yes)
Despatch note language..?.. _
Despatch information
Despatch method.....?.. _
Transport method.....?.. _
Reason for despatch.....?.. _
Terms of delivery.....?.. _
Carrier.....?.. _
Shipping marks..... _
Number of packs.....?.. _
Weight.....?.. _
Volume.....?.. _

F4=Prompt F5=Refresh F8=Update F12=Previous F21=Text F21=Text
Reason code.....?.. IT Initial Take-on of stock
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F18=Despatch details
```

Fields:

Document Processing

Online Print Of Despatch Notes

Enter one of the following:

0 - Print as part of a batch.

1 - Print immediately.

Priced Despatch Note

Enter one of the following:

0 - Do not show prices on despatch notes.

1 - Show prices on despatch notes.

Despatch Note Language

Indicate the language of the text that you want to print on the despatch note.

Inventory checks the chosen code against those defined in Application Manager.

Despatch Information

Despatch Method

Indicate the default despatch method. You must have already defined the method on the Inventory Descriptions file, major type MODE.

Transport Method

Indicate the default transport method. You must have already defined the code on the Inventory Descriptions file, major type TMTH.

Reason For Despatch

This defaults to blank. Any entry made is checked against the Inventory Descriptions file, major type MOVR.

Terms Of Delivery

Indicate the default terms of delivery. You must have already defined the code on the Inventory Descriptions file, major type TDEL.



Note: If you use World Trade, this field defaults to the value held on the Customer Maintenance - Trade Details Screen in Sales Order Processing.

Carrier

Indicate the default carrier. The default is blank. You must have already defined the code on the Inventory Descriptions file, major type CARR.

The confirmation of this field depends on interfaced applications. The software performs the following checks in the order specified.

- If you use Advanced Shipping, and the processing company is active with Sales Order Processing, the carrier defaults to that defined in the Shipping Customer Defaults option. If you enter a new code, it is checked against the shipping names and address file in Shipping Customer Defaults Maintenance.
- If you use Transport Planning, and the processing company is active in Sales Order Processing, the carrier defaults to the carrier defined to the Transport Planning delivery profile. If you enter a new code, it is checked against the Transport Planning carrier file.
- You define a Sales Order Processing company to a Transport Planning company via a Sales Order Processing company/stockroom combination.

Shipping Marks

This is a free format field for shipping marks.

Number Of Packs

Enter a packaging code along with a quantity and unit of measure. The confirmation depends on interfaced applications. Otherwise, codes are checked against the Inventory Descriptions file, major type TPPK.



Note: If you use Advanced Shipping, the code entered is validated against the pack types file.

Weight

Enter a UoM code along with a weight; these are checked against the Inventory Descriptions file, major type UoM.

Volume

Enter a UoM code and a volume, these are checked against the Inventory Descriptions file, major type UoM.



Select **F8=Update** to update details.

Confirm Shipment Receipt

1...
2...

42/INP 7/DRP 12/WTD

Use this option to confirm the receipt of shipment. This maintains the in transit balances and updates the stock and costs at the receiving stockroom. The acquisition movement is written at the point of internal receipt.

The transfer may have been by a transfer or distribution order, or by an Inventory transfer out transaction. If the receiving stockroom is defined to the Warehousing module, you must enter the appropriate details within this option to include items in the put-away processing within Warehousing.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.

Confirm Shipment Receipt Selection Screen



To display this screen, select Confirm Shipment Receipt.

Use this screen to confirm the receipt at a stockroom of stock in transit from another stockroom within the company. Inventory updates the records for the receiving stockroom. If you have defined this stockroom to Warehousing, you can use this option to enter details to include the items in the put-away processing of Warehousing.

IN088	Z1 - GB Demonstration Company	User GBJBA1MS	6/09/00 10:20:09
Confirm Shipment Receipt			
From Stockroom.....?.. <u>01</u>			
To Stockroom.....?.. <u>02</u>			
Distribution Order Number... _____			
Consignment Number..... _____			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter the transferring stockroom for the item. This stockroom must exist on the company profile.

To Stockroom

Enter the receiving stockroom for the item. This stockroom must exist on the company profile.



Note: If you enter a specific order or consignment number, then you do not need to specify From and To stockroom codes.

Distribution Order Number

Enter the distribution order number to transfer items between stockrooms in different locations.

Consignment Number

Enter an Advanced Shipping consignment number to display all the orders associated with this consignment.



Warning: *You cannot enter both an Advanced Shipping consignment number and a distribution order number.*



Note: *If you use DRP, and no items are found in the Distributions Requirements Planning in transit file for the specified selection criteria, then an error message is displayed.*



Press **Enter** to confirm the details to display the display the Confirm Shipment Receipt Details Screen.

Confirm Shipments Receipt Items In Transit Screen



To display this screen, press **Enter** on the Confirm Shipment Receipt Selection Screen.

Use this screen to select the items within the received shipment from the list of displayed items in transit. The items are added to this in transit list when a distribution order is confirmed as despatched from a stockroom in Sales Order Processing or Warehousing.

You must confirm the whole of the quantity despatched as received before it is removed from the in transit list. You can do this across more than one shipment receipt.

```

IN088      Z1 - GB Demonstration Company      User GBJBA1MS      6/09/00
                                           11:24:48

Confirm Shipment Receipt

From Stockroom... 01 Central Stockroom      From. C1 Birmingham Central Dep
To Stockroom..... 02 Northern RDC Stockroom  To... D1 Northern Regional DC

      Select all Lines to Update (0=No, 1=Yes)  0

Date      Item
Sel Lot number Order  Lin Consignment  SR      Quantity UoM
- 2/05/00      E    1  1535A      02      6.000 EA
- 2/05/00      E    1  1535A      02      1.000 EA
- 2/05/00      E    1  1535B      02      6.000 EA
- 2/05/00      E    1  1535C      02      6.000 EA
- 2/05/00      E    1  1535D      02      6.000 EA

More...

1=Select order line for receipt  2=Maintain lot header details
F3=Exit      F4=Prompt      F5=Refresh      F8=Update      F12=Previous
  
```

Fields:

From Stockroom

This is the stockroom code and description entered on the previous screen, or the despatching stockroom if you entered a distribution order.

To Stockroom

This is the receiving stockroom as entered on the previous screen. This is automatically displayed if you entered a distribution order.

Select All Lines To Update

Enter one of the following:

0 - No. Not to update all lines.

1 - Yes. To update all lines.

Select (Sel)

Enter one of the following:

1 - To select a line to be received or to amend receipt details.

2 - To maintain lot header details if the item is lot, batch or serial controlled. This displays the Lot Header Maintenance Window.

Reference Date

This is the date of despatch from the From Stockroom.

Lot Number

If the item is lot, batch or serial controlled, the lot reference number is displayed.

Order

This is the distribution order number allocated to the transaction.

Lin

This is the distribution order line number.

Item

This is the item reference code for the item that is in transit.

SR

This is the receiving stockroom for the item. The receiving stockroom defaults to the To stockroom as entered on the distribution order; you can override this with any valid stockroom for the item.

Quantity

You can specify the actual quantity received. This must not exceed the quantity despatched.



Note: If the received quantity is less than the quantity despatched, then the received quantity will be booked into stock but the balances will remain in transit. The assumption is that the remainder of the item will be confirmed, via this screen, once it is received.

If there are any discrepancies, you must use an Inventory stock adjustment (with an appropriate reason code) after the quantity has been fully received at the receiving stockroom.

UoM

This is the unit of measure for the item that is in transit.

If you are using Catchweight, the Secondary Value and UoM fields are also displayed. The way that these fields are displayed can be explained as follows:

- If there are no details held under either column for your item then there is no secondary value for the order line.
- If the columns display both a secondary value and a secondary unit of measure, but they are not underlined, then the secondary value of the order line is for information only.
- If the columns display both values, and they are underlined, then these values have been calculated by Catchweight and can be amended.



Note: You must confirm receipt of the entire despatch quantity before it is removed from the in transit list. You can do this across more than one shipment receipt.



Note: If you use Warehousing you must enter the appropriate location details before you can complete the receipt.

The physical and available stock balances are updated by the received quantity and the in transit quantity reduced accordingly. This also updates the batch and FIFO cost records if appropriate.

These receipts are also updated in the stock history and movement files as transfer in quantities. These should match with the corresponding transfer out details added at confirmation of despatch of the distribution order and the centre.



Select **F8=Update** to save any details. This submits the batch program to update selected lines. It also displays Warehousing details if applicable. A Shipments Received Report is produced as part of the batch job, to provide printed proof of shipments receipts.

Or:

If you are using Location Control, press **Enter** to display the Enter Location Balances Window.

Single Step Stock Transfers

You can record the transfer of stock from one stockroom to another as a single process. Use these options to transfer between stockrooms held within the same physical location; for example, between goods inwards and your stockroom.

Single Step Transfer

1...
2...

43/INP

Use this option to record a simultaneous transfer out of one stockroom and receipt into another. The updates that result from this transaction depend on the Inventory processing profile.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Note: If you use Location Control, then the Enter Location Balances Window is displayed twice, once to record details at the From Stockroom, and a second time to record details at the Target Stockroom.

Record Stock Transfer Selection Screen



To display this screen, select Single Step Transfer

Use this screen to specify the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN079	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:22:21
Record Stock Transfer			
From stockroom....?.. <u>01</u>			
To stockroom.....?.. <u>02</u>			
Reference..... <u>heb060900-09</u>		Reference date... <u>6/09/00</u>	
Reference type.....?.. <u>IN</u>			
Narrative..... <u>trial</u>			
Reason code.....?.. <u>IT</u>			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter the transferring stockroom for the item. This stockroom must exist on the company profile.

To Stockroom

Enter the receiving stockroom for the item. This stockroom must exist on the company profile.



Note: If you are using Location Control, you can enter the same stockroom in both the From Stockroom and To Stockroom fields so that you can record a move from one location to another within the same stockroom.



Tip: These values that you enter in the next three fields will be used for subsequent movements. If you use Document Processing, the reference is generated automatically.

Reference

Enter the reference number for the movement.

Reference Date

This date defaults to today's date, but you can change it if required.

Reference Type

Enter the reference type code for the movement.

Narrative

You can enter text to be used as the default for the subsequent movement.

Reason Code

Enter a reason code to explain the move.



Press **Enter** once to confirm the details and again to display the display the Record Stock Transfer Detail Screen.

Record Stock Transfer Detail Screen



To display this screen, press **Enter** twice on the Record Stock Transfer Selection Screen.

Use this screen to record the details of the stock transfer.



Note: The fields at the bottom of the screen default from the information you specified on the Record Stock Transfer Selection Screen.

```

IN081                Z1 - GB Demonstration Company      USER GBJBA1MS      6/09/00
                                                           10:23:36

Record Stock Transfer

From stockroom....?.. 01                Central Stockroom
To stockroom.....?.. 02                Northern RDC Stockroom

Sel Item          Movement Qty. Lot          UOM      Cost/Unit
- 5010              3.000                      BX        15.00000

1=Amend
Item.....?.. _____
Movement qty..... _____ Lot.....?.. _____
Quantity units....?.. _____ Cost/unit..... _____
Reference.....?.. heb060900-09      Date.. 6/09/00
Reference type....?.. IN Internal
Narrative.....?.. trial
Reason code.....?.. IT Initial Take-on of stock
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous
  
```

Fields:

From Stockroom

This is the name of the transferring stockroom for the item.

To Stockroom

This is the name of the receiving stockroom for the item.

Select (Sel)

Enter 1 against a line to amend it and press **Enter**. The details are then displayed at the base of the screen for modification.

Item

Enter the item using up to 15 alphanumeric characters. You must link the item to the stockroom through Inventory Maintenance. You can amend the item number displayed in this field.



*Note: You can enter an item that is defined as a Kit Parent as long as that item is also defined as a stock item and both the Kit Parent and any corresponding Component items are defined to both stockrooms.
In this case, the processing logic explodes the*

kit a component at a time. Because the quantity of each component is defined to the Kit Parent, the Movement Quantity field is protected, but you can enter lot and any location details if required.

Movement Qty.

Enter the quantity you want to transfer, using up to 11 character including three decimal places.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. Only those units defined for the item are allowed. Unless you change it, this unit of measure defaults to that defined as the issue unit for this item and stockroom combination.

Narrative

You can override the existing narrative.

Reference

This is the reference number that you specified on the selection screen. You can change this for each item if required.

Date

This is the movement date that you specified on the selection screen. You can change this for each item if required.

Reference Type

This is the reference type code that you specified on the selection screen. You can change this for each item if required.

Lot Number

Select the existing lot reference number that is affected by this movement.

Cost/Unit

Enter the cost/unit for this movement, using up to 15 numeric characters including five decimal places.

Reason Code

Enter the reason code for this movement.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Windows if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*



*Note: If you transfer a quantity that results in a negative stock balance Inventory will display a warning. You can continue with the transaction if you have decided to accept a negative stock balance in this stockroom. This is set on the stockroom record of the Inventory company profile. In this case, select **F8=Continue** to override the warning message.*

This transaction:

- Subtracts from the physical balance in the From stockroom.
- Recalculates the available stock in both the From and To stockrooms.
- Adds to the physical balance in the To stockroom.
- Updates the usage and date of issue at the From stockroom.
- Updates the date of receipt in the To stockroom.
- Updates the item costs in the To stockroom.

See Transfer Out for an explanation of the costing methods for transfers.



Once all the details for this issue are correct, press **Enter**. Press **Enter** again to transfer the movement details to the middle of the screen. Select **F8=Update** to carry out the update.

Single Step Transfer (Frozen)

1...
2...

51/INP

Use this option to transfer already frozen stock from one stockroom to another, preserving the frozen status.

You cannot choose to transfer a greater quantity than the actual amount of frozen stock held in the From stockroom.



Note: If you are using Location Control or Location Control and Catchweight, please see Processing Within A Location Controlled Stockroom for more information.



Note: If you use Location Control, then the Enter Location Balances Window is displayed twice, once to record details at the From Stockroom, and a second time to record details at the Target Stockroom.

Record Frozen Stock Transfer Selection Screen



To display this screen, select Single Step Transfer (Frozen).

Use this screen to specify the stockroom that this transaction affects, and the date, reference information and reason code for the transaction.

IN079	Z1 - GB Demonstration Company	USER GBJBA1MS	6/09/00 10:23:56
Record Frozen Stock Transfer			
From stockroom....?.. <u>01</u>			
To stockroom.....?.. <u>02</u>			
Reference..... <u>heb060900-10</u>		Reference date... <u>6/09/00</u>	
Reference type.....?.. <u>IN</u>			
Narrative..... <u>trial</u>			
Reason code.....?.. <u>IT</u>			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter the transferring stockroom for the items. This stockroom must exist on the company profile.

To Stockroom

Enter the receiving stockroom for the items. This stockroom must exist on the company profile.



Note: If you are using Location Control, you can enter the same stockroom in both the From Stockroom and To Stockroom fields so that you can record a move from one location to another within the same stockroom.



Tip: These values that you enter in the next three fields will be used for subsequent movements. If you use Document Processing, the reference is generated automatically.

Reference

Enter the reference number for the movement.

Reference Date

This date defaults to today's date, but you can change it if required.

Reference Type

Enter the reference type code for the movement.

Narrative

You can enter text to be used as the default for the subsequent movement.

Reason Code

Enter a reason code to explain the move.



Press **Enter** once to confirm the details and again to display the Record Frozen Stock Transfer Detail Screen.

Record Frozen Stock Transfer Detail Screen



To display this screen, press **Enter** twice on the Record Frozen Stock Transfer Selection Screen.

Use this screen to record the details of the frozen stock transfer.



Note: The fields at the bottom of the screen default from the information you specified on the Record Frozen Stock Transfer Selection Screen.

IN081		Z1 - GB Demonstration Company		USER GBJBA1MS	6/09/00 10:25:08
Record Frozen Stock Transfer					
From stockroom....?.. 01		Central Stockroom			
To stockroom.....?.. 02		Northern RDC Stockroom			
Sel Item	Movement Qty.	Lot	UOM	Cost/Unit	
- 5010	4.000		BX	15.00000	
1=Amend					
Item.....?..		Lot.....?..			
Movement qty.....		Cost/unit.....			
Quantity units....?..		Date.. 6/09/00			
Reference.....		heb060900-10			
Reference type....?..		IN Internal			
Narrative.....		trial			
Reason code.....?..		IT Initial Take-on of stock			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous					

Fields:

From Stockroom

This is the transferring stockroom for the item.

To Stockroom

This is the receiving stockroom for the item.

Select (Sel)

Enter 1 against a line to amend it and press **Enter**. The details are then displayed at the bottom of the screen for modification.

Item

Enter the item, using up to 15 alphanumeric characters. You must link the item to the stockroom through Inventory Maintenance. You can amend the item number displayed in this field.



*Note: You can enter an item that is defined as a Kit Parent as long as that item is also defined as a stock item and both the Kit Parent and any corresponding Component items are defined to both stockrooms.
In this case, the processing logic explodes the*

kit a component at a time. Because the quantity of each component is defined to the Kit Parent, the Movement Quantity field is protected, but you can enter lot and any location details if required.

Movement Qty

Enter the quantity you want to transfer, using up to 11 character including three decimal places.

Quantity Units

Enter the unit of measure code, as defined on the descriptions file major type UNIT. This is the unit of measure in which the movement quantity is expressed. Only those units defined for the item are allowed. Unless you change it, this unit of measure defaults to that defined as the issue unit for this item and stockroom combination.

Narrative

You can override the existing narrative.

Reference

This is the reference number that you specified on the selection screen. You can change this for each item if required.

Date

This is the movement date that you specified on the selection screen. You can change this for each item if required.

Reference Type

This is the reference type code that you specified on the selection screen. You can change this for each item if required.

Lot

Select the existing lot reference number that is affected by this movement.

Cost/Unit

Enter the cost/unit for this movement using up to 15 numeric characters, including five decimal places.

Reason Code

Enter the reason code for this movement.



*Note: If you are using Location Control, press **Enter** to display the Enter Location Balances Windows if these are required for this item/stockroom combination. The window that is displayed depends on whether you need to capture details about location balances, and (if you are using Catchweight) the levels of secondary balance details required. If you are using Catchweight, for items that are Catchweight category 1 or 2, when you first press **Enter** the [Secondary Value Entry] Window is displayed. The title of this window varies, as it is formed from the short description of the item's secondary UoM, plus the literal Details, for example Kilos Details Entry Window. For more information, see the Secondary Value Entry Window.*

This transaction:

- Subtracts from the physical balance in the From Stockroom.
- Recalculates the frozen balance in both the From and To Stockrooms.
- Adds to the physical balance in the To Stockroom.
- Updates the usage and date of issue at the From stockroom.
- Updates the date of receipt in the To Stockroom.
- Updates the item costs in the To Stockroom.

See Transfer Out for an explanation of the costing methods for transfers.



Once all the details for this issue are correct, press **Enter**. Press **Enter** again to transfer the movement details to the middle of the screen. Select **F8=Update** to carry out the update.

-
-
-
-
-

Chapter 3

Inventory Stock Counting

Stock Counting Introduction

You can use Inventory Management for stock counting. You can produce counts that are:

- Time based.
- Manually requested.

Time Based

Use this for cycle counting or perpetual inventory. The software uses item classification to suggest WHAT to count and WHEN. Items are classified using the Stock Weeks Matrix Maintenance within the Company profile as follows:

- A - High value and high usage or both.
- B - Medium value and medium usage or both.
- C - Low value and low usage both.
- Z - Ignore these items in a class/date control count.

Stockrooms have a count objective per year, per ABC classification. With the definition of a number of working days, the software calculates time intervals so that you can meet the count objectives.

Manual Request

You can use group ranges to select items for counting at any time (for example Major, Minor, and so on).

Warehousing Stock Counting

The primary options of Warehousing are to record item locations and quantities and item movements. This incorporates a stock counting option that provides assistance with the control, documentation, reconciliation and adjustment of stock counting.

The Warehousing Stock Count options apply to the default warehouse only. You can use Authorise Users To Warehouse to change a user's default warehouse.

Physical Warehouse Areas/Locations

You can request stock counts by a range of locations within a given area. In addition, you can select specific location types with the omission of void locations.

Stock Taking And Location Control

Location Controlled stockrooms can also be counted by a range of locations. This will correct the location balances within the selected range of locations, but you will have to verify discrepancies by looking at the item's other location balances before you make an adjustment.

Stock Counting Steps

Count Creation

You can use ABC classification or Manual range to create a count. For either method, the software provides a series of recommendations of what to count, but does not record details (lot/batch/serial). You can print count sheets at this stage but this will bypass the review stage and the count has an immediate status of outstanding.

Review Recommendations

If you have created a stock count then you can review those recommendations.

Maintain the count

Once you have created a count, you can add to, or delete items from, the count list.

Print Count Sheets

The software records the computer stock figure. The count is now of outstanding status. The produced count sheets can cover a number of action lists. You can also use the reprint option to reprint the count sheets.

Count Entry

You can record actual count figures. You can add new items to the count at that time.

Reconciliation With Or Without Update

Without Update - You can compare your counted figure with the recorded computer stock figure. If you use this option, you can report any variances by quantity and value. If these variances fall outside your defined tolerance limits they are designated as errors.

With Update - You can automatically adjustment the computer recorded figures to reflect you're counted figures.



Note: If you use either DRP or MRP, these options write net change triggers.

Count Profile Maintenance



1/INS & 1/WH

Use this option to set up profiles that control the range of items you want to count, and when.

For more information, see the Company Profile - Stock Weeks Matrix Maintenance and Stockroom Details within Inventory Management to see how to define the ABC classifications.

Count Profile Maintenance Stockroom Selection Screen



To display this screen, select Maintenance.

Use this screen to enter the selection criteria of Count Profile Maintenance.

IN106	Z1 - Demonstration Company	User SP1	26/08/94 9:23:46
Stock Count Profile Maintenance			
Stockroom?.. <u>01</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code using up to two alphanumeric characters. You must define the stockroom to the Inventory company profile.



Press **Enter** to display the Count Profile Maintenance Details Screen

Count Profile Maintenance Details Screen



To display this screen, select a stockroom on the Count Profile Maintenance Selection Screen and press **Enter**.

Use this screen to enter counting criteria for the stockroom or warehouse.

IN106		NR - Neil Radford and Co. Ltd		User GBJBA1MS		22/07/96	
						11:37:49	
Stock Count Profile Maintenance							
Stockroom		W1		Neil's Warehouse 1			
Last count number							
Overdue days		1					
Time fence days		1					
View quantity on count ..		0		0=No 1=Print 2=Panel 3=Both			
Count by class		0		0=No,1=Yes			
Tolerances:							
Percentage (-ve)							
Percentage (+ve)							
Value (-ve)							
Value (+ve)							
F3=Exit F8=Update F12=Previous							
00-27		SF		MW		KS IM II KENB20A PET007S1	

Fields:

Last Count Number

This is the last count number used within the stockroom or warehouse. This is automatically assigned during count creation.

Overdue Days

Enter the number of days you want after the due date of a count before the software will consider it overdue. When the count becomes overdue, the count initialisation date on the Recommended Count Selection Screen is highlighted in red rather than yellow.

Time Fence Days

Enter the number of days of ABC cycle counting you want to produce counts for. When you set the time fence days to zero then the count will only include items that are due to be counted on or before that day. When you set it to greater than zero then the software creates extra counts, one for each day into the future. These counts only include items that are due to be counted on that day.

View Quantity On Count

Use this to define whether recorded or computer stock figures are visible to the user after printing of count sheets. Enter one of the following:

0 - No visibility. The user cannot view the computer stock figures at all.

1 - Printed. The user can view computer stocks on count sheets only.

2 - Screens. The user can view computer stocks on count entry screens only.

3 - Both. The user can view computer stocks on both count sheets and screens.

Count By Class

Use this to define whether you can count by class for the stockroom. Enter 1 to activate this, you *must* define tolerances for each class, that is A, B and C.

If you have outstanding counts for your stockroom, you cannot de-activate Count By Class.

Tolerances:

Only shortfalls or excesses greater than the figures specified here are considered as count errors.

Percentage (-ve)

Enter the acceptable maximum percentage tolerance for stock shortage. During reconciliation, any shortfall between your actual count and the computer recorded count that is greater than this tolerance is a count error.

The software calculates percentage errors as follows:

Counted Quantity - Computer Quantity X 100

Computer Quantity

Percentage (+ve)

Enter the acceptable maximum percentage tolerance for stock excess. During reconciliation, any excess between your actual count and the computer recorded count that is greater than this tolerance is a count error.

The software calculates percentage error as follows:

Counted Quantity - Computer Quantity X 100

Computer Quantity

Value (-ve)

Enter the acceptable maximum value tolerance for stock shortage. During reconciliation, any shortfall between your actual count and the computer recorded count that is greater than this tolerance is a count error.

The software calculates value errors according to the costing method of the item as follows:

(Counted Quantity - Computer Quantity) X COST

Where COST = Standard or Latest or Average according to costing method of item.

The software using latest cost to value any discrepancies for FIFO costing items.

Value (+ve)

Enter the acceptable maximum value tolerance for stock excess. During reconciliation, any excess between your actual count and the computer recorded count that is greater than this tolerance is a count error.

The software calculates value errors according to the costing method of the item as follows:

$(\text{Counted Quantity} - \text{Computer Quantity}) \times \text{COST}$

Where COST = Standard or Latest or Average according to costing method of item.

Discrepancies for FIFO costing items are valued at latest cost.



Press **Enter** to refresh the screen and display
the Count Profile Maintenance ABC Details
Screen.

Count Profile Maintenance ABC Details Screen



To display this screen, enter 1 in the Count By Class field on the Count Profile Maintenance Details Screen and press **Enter**.

Use this screen to view the details for the Count Profile Maintenance selection criteria previously specified.



Note: This screen is the same as the first Count Profile Maintenance Screen, except that it displays information for counts by item class.

IN106		NR - Neil Radford and Co. Ltd		User GBJBA1MS		22/07/96	
						11:45:44	
Stock Count Profile Maintenance							
Stockroom		W1		Neil's Warehouse 1			
Last count number							
Overdue days		2					
Time fence days		1					
View quantity on count ..		3					
Count by class		1					
Number of days/year		365					
		Class A		Class B		Class C	
Number of counts/year ..		_____		_____		_____	
Maximum items/count		_____		_____		_____	
Tolerances:							
Percentage (-ve)		_____		_____		_____	
Percentage (+ve)		_____		_____		_____	
Value (-ve)		.00		.00		.00	
Value (+ve)		.00		.00		.00	
F3=Exit		F8=Update		F12=Previous			
08-27		SF		MW		KS IM II KENB20A PET087S1	

Fields:

Number Of Days/Year

You use the number of days per year together with the count objective per class to calculate the next due count date for each item within the stockroom (based on the class of the item and the last counted date).

For example, if working days/year is 200 and the count objective for A class items is 20 (each item needs a stock check 20 times per working year) then you should count each A class item every 200/20 - 10 working days.

Number Of Counts/Year

This is the total number of counts that you want to perform for A, B and C class items during a working year.

Maximum Items Count

Use this to indicate the maximum number of A, B and C class items you want to include on an individual count sheet.

Count Profile Enquiry



2/INS & 2/WHs



To display this screen, select Enquiry.

Use this option to view the stockroom count profile.

Count Profile Enquiry Selection Screen



To display this screen, select Count Profile Enquiry.

Use this screen to select the stockroom whose count profile you want to view.

IN107	MM - Catchweight Company MM	User GBJBA1MS	6/09/00 12:04:22
Stock Count Profile Enquiry			
Stockroom?.. <u>LX</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code of the stockroom that you want to enquire upon.



Press **Enter** to display the Count Profile Enquiry Details Screen.

Count Profile Enquiry Details Screen



To display this screen, press **Enter** on the Count Profile Enquiry Selection Screen.

This window displays the same information as that specified on the Count Profile Maintenance ABC Details Screen. You cannot change anything at this point.

IN107	MM - Catchweight Company MM	User GBJBA1MS	6/09/00 12:04:24
Stock Count Profile Enquiry			
Stockroom LX		LC, Neg.Stck=1	
Last count number 12			
Overdue days 1			
Time fence days 1			
View quantity on count . 2		0=No 1=Print 2=Panel 3=Both	
Count by class 0		0=No,1=Yes	
Tolerances:			
Percentage (-ve)		2.00	
Percentage (+ve)		2.00	
Value (-ve)		10.00	
Value (+ve)		10.00	
F3=Exit F12=Previous			



Select **F3=Exit** to leave the enquiry.

Regenerate ABC Classifications



11/INS & 11/WHS

Use this option to reclassify items within a stockroom based on their average usage and cost in relation to the stockroom cost/usage matrix. Once reclassified, the software recalculates the next count date for each item in the stockroom based on the last count date and the criteria defined for the stockroom count profile.

This option is prompted at Period End processing within Inventory when average usage for item/stockroom profiles are recalculated. This could be a Week or Month End depending on the usage cycle you have selected for your Inventory company).

You can, however, use this option at any time to reassign classifications and next count dates to items. You would need to do this if you have changed a stockroom matrix or stockroom count profile.

You can view the ABC classification of items in the item/stockroom enquiry.

Regenerate ABC Classifications Screen



To display this screen, select Regenerate ABC Recommendations.

Use this screen to select the stockroom whose items you want to reclassify.

```
IN933          MM - Catchweight Company MM      User GBJBA1MS      6/09/00
                                                    12:04:45
ABC Regeneration
Stockroom .....?.. __

```

Fields:

Stockroom

Enter the code for the stockroom that you want to reclassify items for.



Note: If you are using Warehousing, you do not need to enter a stockroom code. The software assumes that you want to process within your default warehouse.



Press **Enter** to confirm your selection, then select **F8=Submit** to start the process.

Or:

If you use Warehousing, just select **F8=Submit**. The software assumes that you want to process within your default warehouse.

ABC Recommendations



21/INS & 21/WHS

Use this option to create counts based on the next due for count date defined for each item within the stockroom or warehouse.

The software produces counts for all items due for count before or on the count recommendation date specified on the screen.

You can choose to produce additional counts for each day after the specified date up to the number of time fence days specified. These counts contain items that are due for count on those days only and provide a forward looking view of future work loads.

The software also selects items based on the maximum number of items to count per class. You can specify this on the stockroom count profile.

You can print count sheets immediately, as a result they go straight to a status of outstanding. You can also choose include a review stage.

The count sheet contains a list of items, the quantity of the items and the type. The type can be as follows:

- Type 1 - Class/Date Control. For more information see Create Count By Class/Date Control Screen.
- Type 2 - Manual Range. For more information see Manual Range.
- Type 3 - Warehouse Location. For more information see Create Count BY Warehouse Location.
- Type 4 - Catchweight. This means the item has a zero primary value and a non-zero secondary value. You investigate this item to find out if any of this item is still available. As you can receive more of the item between printing of the count sheet and completing the stock take, JBA strongly recommend that you investigate and correct these type 4 items first.



Note: Before you create an ABC count you should use the option to regenerate ABC classifications.

Create Count By Class/Date Selection Screen



To display this screen, select ABC Recommendations.



Note: If you using Warehousing, this screen is not displayed.

Use this screen to specify the stockroom that you want to create a count for.

```
IN116A          MM - Catchweight Company MM          User GBJBA1MS          6/09/00
                                                    12:06:26
Create Count by Class/Date Control

Stockroom .....?.. __

F3=Exit          F4=Prompt
```

Fields:

Stockroom

Enter a stockroom code.



Press **Enter** to display the Create Count By Class/Date Control Screen.

Create Count By Class/Date Control Screen



To display this screen, select a stockroom on the Create Count By Class/Date Selection Screen and press **Enter**.



Note: If you are using Warehousing, this is the first screen displayed when you select ABC Recommendations (Create Count).

IN116B	MM - Catchweight Company MM	User GBJBA1MS	0/09/06 12:06:38
Create Count by Class/Date Control			
Stockroom	HL	LC Stockroom	
Time fence days	<u>1</u>	from	<u>6/09/00</u>
Print count sheets	<u>0</u>	0=No,1=Yes	
No of instructions/list	<u>0</u>		
Sequence count by.	<u>1</u>	1=Item 2=Location	
F3=Exit F8=Submit F12=Previous			

Fields:

Time Fence Days

Enter the number of days after the date of recommendation (displayed as the From date), to be reviewed separately for count creation. Where possible the software produces a daily count detailing the items that are due for count on the specific day, thus giving a view of future counts and workloads.

From...Date

Enter the start date from which count creation begins. The default is today's date.

Print Count Sheets

Enter one of the following:

0 - Review recommendations using Maintain Count Recommendations before printing.

1 - Print immediately after generating the recommendations.



Note: If you enter 1 here, the count is outstanding immediately. This action bypasses the option to review before printing.

Number Of Instructions Per List

Enter the maximum number of items or location you want to print on an action list. If you use Warehousing then the value defaults to the value defined for the Warehouse List Profile for count lists. If you enter zero then all instructions for the count appear on one list only.



Note: If you use Warehousing, the next two fields are displayed.

Organise Count By

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example if you set up Aisle to be the first dimension in the warehouse, then the software produces one Action list per Aisle.

For example, if you set Organise Count By to 2 (Area) then the software creates a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for Number Of Instructions/List.

Sequence Count By



*Note: If you are using Location Control, this field is displayed when you press **Enter**.*

Enter one of the following:

1 - Item. Order the actions on the list by item. This is the default.

2 - Location. Order the actions on the list by location code.

There are two reasons why the software does not produce a count after you have run the Create Count By ABC Recommendation option:

First, if you have set the Number Of Counts Per Year to count items relatively infrequently and you have recently counted all items, then no items may be due to be counted, and hence no count recommendations are produced on the Count Profile.

Second, the software cannot include items that are currently being counted on other count lists, whether active or recommended. So, any items that appear on manually requested counts lists, at either a summary or detail level, do not appear on a count list created by ABC Recommendation.



Select **F8=Submit** to submit count creation.

Manual Range



22/INS & 22/WHS

You can select items for counting at any time. These are flagged as unplanned counts.

You can create counts for one or more stockrooms based on item range selection or item attribute selection.

You can enter a single stockroom or range of stockrooms in addition to a single selection or range of one of the following item attributes:

- Item number.
- Item group (major and minor).
- Item type.
- Item class.
- Count class (A, B, C or Z).

You can print counts immediately, or review them before printing.

Create Count by Manual Range Detail Screen



To display this screen, select Manual Range.

Use this screen to select the items you want to count. You can use some or all the selection criteria.

For each search criterion, if you only enter a value in the From field, or if both the From and the To fields are the same, entries must exist on the item master file. However if you define a range, the From and To entries need not exist on the item master file. If you only enter the From value and leave the To value blank, the To fields default to the From field.

IN120	Z1 - GB Demonstration Company	User GJBAMS	15/01/96 17:13:06
Create Count by Item Selection			
Selection criteria	Range from	Range to	
Stockroom?..	___	___	
AND			
Item?..	_____	_____	
OR			
Item group major/minor..?..	___	___	
OR			
Item type?..	___	___	
OR			
Item class?..	___	___	
OR			
Count class	___	___	
Count date	15/01/96		
Print count sheets	@ 0=No,1=Yes	No of instructions/list.... @	
F3=Exit F4=Prompt F5=Refresh F8=Submit			
07-30	SP	MM	KS IM II KENB20A PET166S2

Fields:

Stockroom

Enter the stockroom code for which you want to create a count.

If you enter a single stockroom, it must exist as a stockroom defined to the company. If, however, you enter a range, the From and To stockrooms you use to define the range need not exist on the stockrooms master file, except when they are the same value.

If you are creating a stock count for Warehousing, this field does not display.

Item

Enter the item reference code of the item, or items, that you want to include on your stock count.

If you enter a single item, then it must exist on the item master file. If, however, you enter a range, the From and To items you use to define the range need not exist on the item master file, except when they are the same value.

Item Group Major

Enter an item group major code as defined to the descriptions file against the major type PGMJ.

If you enter a single major or minor combination, it must exist on the item master file. However, if you enter a range, the From and To major or minor groups you use to define the range need not exist on the item master file, except when they are the same value.

Item Group Minor

Enter the item group minor as defined to the descriptions file against the major type PGMN.

If you enter a single major or minor combination, it must exist on the item master file.

However, if you enter a range, the From and To major or minor groups you use to define the range need not exist on the item master file, except when they are the same value.

Item Type

Enter the item type as defined to the descriptions file against the major type PTYP.

If you enter a single item type, then it must exist on the item master file. However, if you enter a range, the From and To item types you use to define the range need not exist on the item master file, except when they are the same value.

Item Class

Enter the item class as defined to the descriptions file against the major type PCLS.

If you enter a single item type, then it must exist on the item master file. However, if you enter a range, the From and To item classes you use to define the range need not exist on the item master file, except when they are the same value.

Count Class

Enter the item classification code for this stockroom. The software categorises items into classes A, B and C. Items with a classification of A normally have the highest usage and value, and so on.

Valid classes are A, B, C and Z. The Z class excludes items From count requests by ABC classification.

Count Date

This is the date you want to process the count. This defaults to today's date.

Print Count Sheets

Enter one of the following:

0 - Review recommendations through Maintain Count Recommendations before printing.

1 - Print immediately after generating recommendations.



Note: If you enter 1 here, the count is outstanding immediately. This action bypasses the option to review before printing.

Number Of Instructions Per List

Use this to determine the maximum number of item or location details you want to print on an action list.

If you use Warehousing then the value defaults to the value defined for the Warehouse List Profile for count lists.

If you enter zero, all instructions for the count appear on one list only.



Note: If you use Warehousing, the next two fields are displayed.

Organise Count By

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example Aisle is set up to be the first dimension in the warehouse, then one Action list per Aisle is produced.

For example, if Organise count by is set to 2, Area, then create a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for No of instructions/list.

Sequence Count By



*Note: This field is only displayed if you are using Location Control and you press **Enter**.*

Enter one of the following:

1 - Item. The actions on the list are ordered by item.

2 - Location. The actions on the list are ordered by location code.



Note: A blank range selection for stockrooms defaults to all stockrooms.



Note: If you do not specify other selection criteria, the software selects all items within the specified stockroom range.

The count follows exactly the same steps as the class/date count.



Select **F8=Submit** to submit the process.

Creating Counts By Location

There are two options that you can use to create counts by location, these are the Create Count By Warehouse Location and the Create Count By Location Range.

Create Count By Warehouse Location

1...
2...

23/WHS



Note: You can only use this option if you use Warehousing.

You can create count for the default warehouse by location within a defined area.

You can choose to use a range of criteria to select the locations within the area:

- By range selected by dimension.
- By status, so that you only count within active locations or all locations.
- By location type.

You can select a maximum number of locations so that count lists do not become too large.

You can print counts or create recommended counts to review before printing them.

Create Count By Warehouse Location Area Selection Screen



To display this screen, select Create Count By Warehouse

Use this screen to select the area containing the locations you want to count, and specify the date associated with the count.

IN125	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Create Count by Warehouse Location			
Area	MS		
Count date	010994		
F3=Exit F4=Prompt			

Fields:

Area

Enter the area within your warehouse you want to target for the count.

Count Date

Enter the date associated with the count recommendation.



Press **Enter** to display the Create Count by Warehouse Location Detail Screen

Create Count By Warehouse Location Detail Screen



To display this screen, select an area and count date on the Create Count by Warehouse Location Selection Screen and press **Enter**.

Use this screen to select the locations within the chosen area for stock counting.

IN125	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Create Count by Warehouse Location			
Area		MS	
Count date		1/09/94	
Location Ranges :		From (?)	To (?)
Aisle		A	B
Bay			
Row			
Location status 1 0=All 1=Active only			
Location type ?.. RA			
Maximum number of locns .. 300			
Print count sheets 0 0=No.1=Yes			
No of instructions/list .. 0			
Organise count by 1 1=Warehouse 2=Area 3=Access to dimension 1			
Sequence count by 2 1=Item 2=Location			
F3=Exit F4=Prompt F5=Refresh F8=Submit F12=Previous			
F16=No. of locns			

Fields:

Location Ranges

You can leave both the From and To entry fields blank to select the entire range of dimension codes for the particular dimension.

Aisle

Enter the target range of dimension codes for count creation within the area.

Bay

Enter the target range of dimension codes for count creation within the area.

Row

Enter the target range of dimension codes for count creation within the area.

Location Status

Enter the location status:

0 - All. Select all locations defined by the dimension range.

1 - Active only. Ignore void locations (generated via the warehouse map), and select those locations defined as active from the dimension range.

Location Type

You can restrict the target locations for count by type. You must define the location type you enter to warehouse Location types.

If left blank, the software selects all location types found for the dimension range.

Maximum Number Of Locns

This is the maximum number of target locations for the count.

This defaults to the entry held on the Inventory descriptions file under major type WHNL, minor type MAX.

JBA strongly recommend that you maintain this value so that you can guard against the entry of dimension ranges that targets a large number of locations.

Print Count Sheets

Enter one of the following:

0 - Review recommendations through Maintain Count Recommendations before printing.

1 - Print immediately after generating recommendations.



Note: If you enter 1 here, the count is outstanding immediately. This action bypasses the option to review before printing.

No Of Instructions/List

If you set Print count sheets to 1 use this to determine the maximum number of item or location details you want to print on an action list. This value defaults to the value defined in the Warehouse list profile for count lists.

Enter 0 to indicate that a new list should not be initiated based the number of item or location details. New lists can however be initiated by the Organise count by option.

Organise Count By

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example if you set up Aisle to be the first dimension in the warehouse, then the software produces one Action list per Aisle.

For example, if you set Organise Count By to 2 (Area) then the software creates a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for Number Of Instructions/List.

Sequence Count By

Enter one of the following:

1 - Item. Order the actions on the list by item.

2 - Location. Order the actions on the list by location code.

Functions:

F16=No. Of Locns.

Use this to review the number of locations targeted for count based on the specified dimension range.



*Note: JBA recommend that you use **F16=No of Locations** to guard against producing counts over a large number of locations.*



Select **F8=Submit** to submit the count request.

Create Count By Location Range

1...
2...

23/INS



*Note: You can only use this option if you use
Location Control.*

You can create count for a stockroom by location. You can choose whether to print count sheets immediately; the number of instructions that you want to include on a count list; and whether to sequence the count by item or location.

Create Count By Location Selection Screen



To display this screen, select Location Range.

Use this screen to select the stockroom and locations that you want to produce a stock count for.

IN625	MM - Catchweight Company MM	User GBJBA1MS	23/02/00 13:58:28
Create Count by Location Selection			
Selection criteria	Range from	Range to	
Stockroom?..	__		
Location.....?..	_____	_____	
Count date	23/02/00		
Print count sheets	0 0=No,1=Yes		
No of instructions/list....	0		
Sequence count by.	2 1=Item 2=Location		
F3=Exit F4=Prompt F5=Refresh F8=Submit			

Fields:

Stockroom

Enter the stockroom upon which you want to produce a count.

Location From

Enter the start of the range of locations you want to include on the count.

Location To

Enter the end of the range of locations you want to include on the count.



Tip: To include a single location, enter that code in both the From and To fields.

Count Date

This defaults to today's date, but can be changed if required.

Print Count Sheets

Enter one of the following:

0 - No. To not print the count sheets immediately. If you select this, you can produce the count sheets after reviewing their contents using the Maintain Counts option.

1 - Yes. To print count sheets immediately. If you select this, you cannot review the results and the count is considered to be recommended.

No. Of Instructions/List

Enter the number of instructions that you want to print on each count list.

If you set the Print Count Sheets field to 1 use this to determine the maximum number of item or location details you want to print on an action list.

Sequence Count By

Enter one of the following:

- 1 - Item. Order the actions on the list by item.
- 2 - Location. Order the actions on the list by location code.



Select **F8=Submit** to process the count request.

Maintain Count



31/INS & 31/WHS

You can review recommended counts before you print them if you have not selected to print count sheets when you requested the count.

Item Based Counts

You can add or delete summary recommendations, that is, a request to count all balances for an item. In addition, you can request detail recommendations, that is, specific lots, batches or serial numbers for count. You can delete counts entirely and all associated items taken off count.

If you add any items to the count, the software considers them Unplanned requests, and you must enter a reason code for these.

Location Based Counts In A Location Controlled Stockroom

You can add active locations if they are not already on another count.

You can delete locations from the count.

You can delete the entire count and unset the Stocktake In Progress flag for all locations.

Maintain Count Selection Screen



To display this screen, select Maintain Count.

Use this screen to select the stockroom and stock count that you want to maintain.

IN129A Z1 - Demonstration Company User SP1 5/09/94
12:30:26

Maintain Count

Stockroom?.. 01

Count number?.. 0

Recommended Count Selection

	Central Warehouse			
Sel	Count number	Date	Time	Items to count
	3	26/08/94	10:40:56	1
<u>1</u>	4	5/09/94	12:28:01	9

1=Select Position to

F12=Previous

F3=Exit F4=Prompt

Fields:

Stockroom Code

Enter the stockroom code.



Note: If you use Warehousing, this field does not display.

Count Number

Enter the count number.



Press **Enter** to display the Maintain Count Details Screen.

Or:

If you use Warehousing, press **Enter** to display the Location Based Maintain Count Detail Screen.

Maintain Count Details Screen



To display this screen, select a stockroom and count on the Maintain Count Selection Screen and press **Enter**.

Use this screen to add or delete summary or detail item recommendations.



Note: Summary recommendations are recommendations at item level. Detail recommendations are recommendations at lot, batch or serial number level. You cannot add a lot for an item that is already on the count, but you can add a single lot for an item that is not already on the count.

The stockroom, count number and the number of items or lots to count are displayed at the top of the screen. Detail recommendations are a request to count specific lot, batch or serial numbers. You can only review recommended counts.



Note: If you use Location Control, the Location column is also displayed on this screen.

IN129B	Z1 - Demonstration Company	User SP1	5/09/94 12:32:06
Maintain Count			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	
- 5011		Planned Count	
- 5013	B002	Unplanned Request	
- 5014		Planned Count	
- 5015		Planned Count	
- 5016		Planned Count	
- 5017		Planned Count	
- 5018		Planned Count	
- 5019		Planned Count	
- 5020		Planned Count	
		Position to item ..	_____
4=Delete			
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete			
F12=Previous			

Fields:

Select (Untitled)

Enter 4 to delete the count recommendation for a particular line. When you select **F8=Update**, the count recommendation is not included in the count and you immediately return to the count selection screen.

Position To Item

If the list of recommendations extend over a single screen, you can use this to enter the item reference number, or the first few characters of that reference, to view the count recommendation for that item.

Functions:

F9=Add

Use this to add new items to the count.



Select **F8=Update** to save any changes.

Addition Window



To display this window, select **F9=Add** on the Maintain Count Details Screen.

Use this window to add a new item to your selected count.

IN129B		Z1 - Demonstration Company		User SP1		5/09/94 12:31:54	
Maintain Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		0	
Create date/time		5/09/94 12:28:01		Item summaries cancelled		1	
More:							
Item	Lot	Reason					
- 5011		Planned Count					
- 5014		Planned Count					
- 5015		Planned Count					
- 5016		Planned Count					
- 5017		Planned Count					
- 5018		P					
- 5019		P					
- 5020		P					
		Addition					
		Item?.. 5013					
		Lot?.. B002					
		Reason code ?.. UN					
		F4=Prompt F12=Previous					
		Position to item ..					
4=Delete							
F3=Exit		F5=Refresh		F8=Update		F9=Add	
F12=Previous						F11=Delete	

Fields:

Item

Enter the reference code for the Item you want to add. The item must exist on the Inventory item master file.

Location

This is only displayed if you want to process a Warehouse stock count. The location must exist within the current warehouse.



Note: You only need to enter the location (and any other detail for the item balance) if you want to request the count of a specific warehouse balance for that item.

Lot

Enter the lot, batch or serial number associated with a lot controlled item.

Rotation

This is only displayed for Warehouse stock count. Enter the rotation date associated with a balance for a date controlled item.

Pack

This is only displayed for Warehouse stock count. Enter the pack type associated with an item.

Label

This is only displayed for Warehouse stock count. The label number associated with a label-controlled pack type.

Reason Code

Enter the reason for adding this item to the count list. You must define the reason code to the descriptions file against the major type CTRE and must be of an unplanned nature



Note: You cannot use the reserved code of #1 representing a Planned request for an item originating from an initial count request.



To delete the entire count, select **F11=Delete** twice.



Warning: You must delete summary recommendations before you can add a detail recommendation for an item.



Warning: Lot controlled items are only shown at summary level. You can specify individual lots by pressing F9=Add.



Select **F8=Update** to update all item additions and deletions.

Warehouse Location Based Maintain Count Detail Screen



To display this screen, select a warehouse and date on the Location Based Maintain Count Selection Screen and press **Enter**.



Note: You can only use this if you are processing a Warehousing stock count.

Use this screen to add location summary or detail recommendations to the count.

IN131	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
Maintain Count			
Count number	4	Location summaries to count .	15
Create date/time	01/09/94 11:00:00	Location details to count ...	0
		Location summaries cancelled.	0
		More: +	
Location	Item	Lot	Rotation Pack Reason
- AA1			#1
- AA2			#1
- AA3			#1
- AA4			#1
- AA5			#1
- AB1			#1
- AB2			#1
- AB3			#1
- AB4			#1
- AB5			#1
Position to location ... _____			
4=Delete			
F3=Exit	F5=Refresh	F8=Update	F9=Add
F12=Previous	F15=Labels	F11=Delete	

Fields:

Select (Untitled)

Enter 4 to delete a location recommendation.

This takes effect when you select **F8=Update**.

Position To Location

Position to location. Enter the first few characters of a location code to position the details to the point you want to view.



Note: You must delete summary recommendations before you can add detailed recommendations for a location.

Functions:

F9=Add

Use this to add recommendations.

F15=Labels

Use this to display label numbers for label controlled pack types.

Count Size Warning Window



This screen automatically displays when the number of items specified for any of the classifications exceeds the maximum number of items per count sheet that you specified on the stockroom count profile when you select to update a count request by ABC classification.

This situation can arise where you have added unplanned counts to the count list.

INI29B	Z1 - Demonstration Company	User SP1	05/09/94 12:36:13
Maintain Count			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	Class
- 5011		Planned Count	B
- 5013	B002	Unplanned Request	B
- 5014			
- 5015			
- 5016			
- 5017			
- 5018			
- 5019			
- 5020			

Count Size Warning

Number of class A items in count	2
Maximum class A items specified	10
Number of class B items in count	6
Maximum class B items specified	5
Number of class C items in count	1
Maximum class C items specified	20

F12=Previous

4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous



Select **F12=Previous** to amend the current count.

Or:

Press **Enter** to accept the count with the excess items.

Enter Count Details



32/INS & 32/WHS

You can enter counted details on a list by list basis. You can amend those details until you record the list as complete. You can delete lists entirely and take all associated items off count (unless item details span a number of lists). You can only add item details if the item already exists as on count in this particular count. The software considers any additions Override details so you must enter an appropriate reason code.

JBA recommend that you do not complete the list until you have reviewed the reconciled details, as you cannot maintain a completed list.

If you are using Location Control, then you can use this option to:

- Display stocked item/lot/location combinations with a primary balance that is not equal to zero. That is, any primary balances with a value greater or less than zero (if you have specified that your stockroom can have negative balances).
- Add an item or lot in any active location provided that the combination is not included on another count, and the item is not restricted to a different single location.
- Remove individual entries from the count.
- Delete the entire count.
- You cannot enter a balance at a location that is not a single location item's default location.
- You cannot view inactive locations when you use the Location Prompt.
- You cannot select or add inactive or duplicate locations.

Enter Count Selection Screen



To display this screen, select Enter Count Details.

Use this screen to select the Stockroom, Count number and List number you want to enter the count details for.

```
IN133A      Version 3 Demonstration Company      User STDFIN      2/02/00
                                                    15:49:28

Enter Count

Stockroom .....?.. 01
Count number .....?.. 
List number .....?.. 

Outstanding Count Selection
      Stockroom .....01
      Central Stockroom
      Count   Lists   Date and time   Items to
      Sel    number  comp   count printed   count
      -      -      -      -      -
      -      4      -      5/09/94  12:33:17      8
      -      5      -      5/05/98  11:45:55     10
      -      6      1      5/05/98  11:50:07     13
      -      7      -      2/02/00  15:36:54      5

      1=Select   Position to .....
      F12=Previous

F3=Exit      F4=Prompt
```

Fields:

Stockroom

Enter the stockroom code. This field is not displayed if you are using Warehousing.

Count Number

Enter the count number.

List Number

Enter the list number.



Press **Enter** to display the Enter Count Details Screen.

Enter Count Details Screen



To display this screen, select a stockroom, stock count and list and press **Enter** on the Maintain Count Selection Screen.

Use this screen to enter the item quantities you have counted.



Note: If you are using Location Control, the Location column is displayed on this screen.

IN133B		Z1 - Demonstration Company		User SP1	5/09/94 12:33:59
Enter Count					
Stockroom		01	Item summaries to count		8
Count number		4	Item details to count		1
List number		4	Item summaries cancelled		1
Create date/time		5/09/94 12:28:01		More:	
Item	Lot	Reason	Recorded qty	Entered qty	
- 5011		#1	512.000	512.000	
- 5013	B002	UN	719.000	.000	
- 5014	LP004	#1	138.000	138.000	
- 5014	L001	#1	575.000	575.000	
I 5015	LP054	#1	159.000	.000	
- 5015	L002	#1	625.000	.000	
			Position to item ..		
1=Select 2=Lot header 4=Delete					
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete					
F12=Previous					

Fields:

Select (Untitled)

Enter one of the following

1 - To enter or amend detail item count quantities. Press **Enter**, to display the Enter Count Amendment Window and view current information available for amendment.

2 - To display the Lot Header Window for a detail count line that is displayed on this Enter Count Screen.

4 - Delete. To display the Enter Count Delete Screen.

Entered Qty

Enter the quantity you have counted for each item in the defined issue unit of measure.

Position To Item

Enter an item code you want displayed first.

Functions:

F9=Add

Use this to add item details. You can only do this if the item already exists on this particular count. You can use this if you have discovered different lots of an item that were not recorded on the original count sheets. If the item is lot controlled, the Lot Reference Maintenance window is automatically displayed for completion.



Select an option and press **Enter**.

Enter Count Amendment Window



To display this window, enter 1 to select an item on the Enter Count Details Screen and press **Enter**.

Use this window to amend current information for your selected item.



Note: You can also enter the quantity directly into the column marked Entered Qty beside the appropriate item count line.

IN133B		Z1 - Demonstration Company		User SP1	5/09/94 12:33:59
Enter Count					
Stockroom	01	Item summaries to count		8	
Count number	4	Item details to count		1	
List number	4	Item summaries cancelled		1	
Create date/time	5/09/94 12:28:01	More:			
Item	Lot	Reason	Recorded qty	Entered qty	
- 5011		#1	512.000	512.000	
- 5013	B0 02	UN	719.000	.000	
- 5014	LP004	#1	138.000	138.000	
- 5014	L0 01				
- 5015	LP054				
- 5015	L0 02				

Amendment

Item 5015

Lot LP054

Reason #1

Recorded qty ... 159.000

Entered qty 160

F12=Previous

1=Select 2=Lot header 4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous

Position to item ..

Fields:

Item

This is the item code.

Location

This displays the location for the item. This is only displayed if your stockroom is Location Controlled.

Lot

This is the associated lot number.

Reason

Enter a reason code for the amendment.

Recorded Quantity

Enter the quantity recorded by the system when you initiated the count.

Entered Quantity

Enter the actual quantity for the item. This is your manually counted item quantity.



Select **F12=Previous** to redisplay the Enter Count Details Screen and save the amended details.

Enter Count Delete



To display this screen, enter 4 to select an item on the Enter Count Details Screen and press **Enter**.

Use this screen to delete a selected item from the count.

IN133B		Distribution V3 -> V3 Financials		User GBJBAMV1	16/11/95
					15:43:59
Enter Count					
Stockroom	#P	Item summaries to count	1		
Count number	5	Item details to count	0		
List number	4	Item summaries cancelled	0		
Create date/time	23/10/95 14:59:42	More:			
Item	Lot	Reason	Recorded qty	Entered qty	
4 ROB		#1	25000.000	.000	
Position to item ..					
1=Select 2=Lot header 4=Delete					
F3=Exit		F5=Refresh		F8=Update	
F12=Previous		F9=Add		F11=Delete	
10-02		SA		MM KS IM II KENB20A PET129S1	

Fields:

Entered Quantity

Enter the counted quantity for the item record, this must be in the item's issue unit of measure.



Select **F11=Delete** to confirm the deletion.

Enter Count Addition Window



To display this window, select **F9=Add** on the Enter Count Details Screen.

Use this window to add an item to the count.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:34:11	
Enter Count							
Stockroom 01				Item summaries to count 8			
Count number 4				Item details to count 1			
List number 4				Item summaries cancelled 1			
Create date/time 5/09/94 12:28:01				More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B002	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L001			00			
- 5015	LP054			00			
- 5015	L002			00			

Addition

Item?.. 5013

Lot?.. B009

Reason code .?.. UN

Entered qty 325

F4=Prompt F12=Previous

Position to item ..

1=Select 2=Lot header 4=Delete

F3=Exit F5=Refresh F8=Update F9=Add F11=Delete

F12=Previous

Fields:

Item

Enter an item number, this must be already on count in this count.

Location

This is displayed if you are using Warehousing. Enter the location where you counted the additional stock.

Lot

Enter a lot, batch or serial number.

Rotation

This is displayed if you are using Warehousing. If the stock counted is rotation date controlled enter the appropriate rotation date.

Pack

This is displayed if you are using Warehousing. Enter the pack type associated with the stock counted.

Label

This is displayed if you are using Warehousing. If the pack type associated with the stock is label controlled enter the appropriate label number.

Reason Code

Enter the reason for adding this item to the count list. You must define the reason code to the descriptions file against the major type CTRE and must be of an override nature.



Note: You cannot select the reserved code of #1 for a Planned request for an item originating from an initial count request.

Quantity

Enter the counted quantity in the item's issue unit of measure.

When you press **Enter**, you return to the details screen, the software does not calculate stock balance for the additional item, and is not displayed in the Recorded Qty column. You can delete the complete list with **F11=Delete**, and all associated items taken off count (unless the item details span a number of lists).



Select **F8=Update** to update the list. If there are no errors, the Update Confirmation window is displayed.

Update Confirmation Window



To display this window, select **F8=Updates** to update the specified quantities.

Use this screen to confirm a completed list. You must complete all lists associated with a count before you can process a reconciliation with update.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:36:16	
Enter Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		1	
List number		4		Item summaries cancelled		1	
Create date/time		5/09/94 12:28:01		More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B002	UN	719.000	720.000			
- 5014	LP004	#1	138.000	.000			
- 5014	L001	#1	575.000	.000			
- 5015	LP054	#1	159.000	.000			
- 5015							
- 5013							
Update Confirmation							
Complete list ?					0 1=Yes 0=No		
F12=Previous							
1=Select 2=Lot header 4=Delete				Position to item ..			
F3=Exit		F5=Refresh		F8=Update		F9=Add	
F12=Previous						F11=Delete	

Fields:

Complete List

Enter one of the following:

0 - To not complete the list. This is the default.

1 - To complete the list.



Tip: Once you have completed a list you cannot maintain it.



Note: JBA recommend that you do not complete a list until after reconciliation, as a completed list can no longer be maintained.

Complete Count Lists



33/INS & 33/WHS

You can use this option to complete all lists associated with a count en masse, after you have specified details, reviewed the results of reconciliation, and before the final update.

You cannot complete lists if they contain detail records with lots referring to the special case of * Lot Error *. These are generated during the printing of count sheets if no lots exist for a batch, lot or serial controlled item.

Complete Count Lists Count Selection Screen



To display this screen, select Complete Count Lists.

Use this screen to select the count number you want to complete.

IN181A	Version 3 Demonstration Company	User STDFIN	2/02/00 16:01:29
Count Completion			
Stockroom?.. _			
Count number?.. ____@			
F3=Exit F4=Prompt			

Fields:

Count Number

Enter the count number you want to complete. This count must be of an outstanding status, that is, the count has been printed and maintained.



Press **Enter** to display the Complete Count Lists List Selection Window.

Complete Count Lists List Selection Window



To display this window, select a stockroom and count number and press **Enter**.

Use this window to select an action list associated with a chosen count for completion.

IN181A		Z1 - Demonstration Company		User SP1		5/09/94	
						12:38:07	
Count Completion							
Stockroom		01					
Count number		4					
				Select List Number			
				Central Warehouse			
				Count No..... 4			
				More:			
				S Number			
				1 4			
				- 5			
				- 6			
				- 7			
				1=Select			
				Position to....			
				F3=Exit F8=Update F12=Previous			
F3=Exit				F4=Prompt			

Fields:

Select (S)

Enter 1 to select a list number associated with this count.



Select **F8=Update** to update.

Print Count Sheets



41/INS & 41/WHS

Use this option to record the computer stock figure for your count and produce summary recommendations. These are expanded to include lot/batch/serial level detail where relevant.

If a lot controlled item has no recorded lots or each lot is empty the software writes a record with the reference Lot error. You must delete this reference during count entry and count and add the actual lots of the item (if they exist), or you can delete the item from the count.

In addition, when you print, you can split the workload for the count across a number of lists based on the number of instructions on the count and the number of instructions you want per list.

When you print the count sheet, it contains a list of items, the quantity of the items and the type. These can be as follows:

- Type 1 - Class/Date Control. For more information see Create Count By Class/Date Control Screen.
- Type 2 - Manual Range. For more information see Manual Range.
- Type 3 - Warehouse Location. For more information see Warehousing.
- Type 4 - Catchweight. In this case, the item has a zero primary value and a non-zero secondary value. You need to investigate this item to find out if any of this item is still available. As you can receive more of the item between printing off the count sheet and completing the stock take, JBA strongly recommended that you investigate and correct these type 4 items first.

If you are using Location Control, then you can select a single stockroom, a range of counts and a sequence (item or location, whichever is the default) on which to produce the count sheets.

Print Count Sheets Count Selection Screen



To display this screen, select Print Count Sheets.

Use this screen to enter the selection criteria for Print Count Sheets.

IN152	Z1 - Demonstration Company Central Warehouse	User SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Print count sheets

Count number from?.. 4 to?.. 6

No of instructions/list 15

Organise count by 2 1=Warehouse 2=Area
3=Access to dimension 1

Sequence count by 2 1=Item 2=Location

F3=Exit F4=Prompt F8=Submit

Fields:

Stockroom

This field is not displayed if you are using Warehousing.

Enter the stockroom code.

Count Number From/To

If you enter a single count, it must be outstanding. You can enter a range, to act as limiters. If you leave these fields blank, the software includes all recommendations.

No Of Instructions/List

Enter a number to create multiple lists. If you enter zero, all counts appear on one list.



Note: If you use Warehousing, the next two fields are displayed.

Organise Count By

Enter one of the following:

1 - Warehouse. As the count only relates to your default warehouse, create a new list when the number of location or item details exceeds the value set for No of instructions/list.

2 - Area. Create a separate count list for each change of area code within the warehouse.

3 - Access to dimension 1. Create a separate count list for each change of access to dimension 1. If for example Aisle is set up to be the first dimension in the warehouse, then one Action list per Aisle is produced.

For example, if Organise count by is set to 2, Area, then create a new list for each change in area code. There may be several lists per area if the number of location or item details to be checked exceeds the value set for No of instructions/list.

Sequence Count By



*Note: This field is also displayed if you are using Location Control when you press **Enter**.*

Enter one of the following:

- 1 - Item. The actions on the list are ordered by item.
- 2 - Location. The actions on the list are ordered by location code.



Select **F8=Submit** to submit count sheets to print.

Reprint Count Sheets



42/INS & 42/WHS

Use this option to select count sheets you want to reprint.



Note: If you are using Location Control, then, for counts that are in location sequence, the sort sequence is lot within item within location, and the column sequence (from left to right) is location, item and lot. For counts by item sequence, the sort sequence is lot within location within item and the column sequence is item, location and lot.

Reprint Count Sheets Count Selection Screen



To display this screen, select Reprint Count Sheets.

Use this screen to reprint count sheets. You can print all, or selected lists for a count.

IN161	Z1 - Demonstration Company	User SP1	5/09/94 12:36:59
Reprint count sheets			
Stockroom?.. <u>01</u>			
Count number from.....?.. <u>4</u>		List number from...?.. <u>4</u>	
Count number to.....?.. <u>4</u>		List number to.....?.. <u>5</u>	
F3=Exit		F4=Prompt	F8=Submit

Fields:

Stockroom

Enter the stockroom code. This field is not displayed if you use Warehousing.

Count Number From/To

If you enter a single count, it must be outstanding. You can enter a range, to act as limiters. If you leave these fields blank, the software includes all recommendations.

List Number From/To

If you enter a single list number it must incomplete or outstanding. You can enter a range, to act as limiters. If you leave these fields blank, the software includes all recommendations.



Select **F8=Submit** to action the batch job.

Count Reconciliation

You use Reconciliation to compare counted stock quantities with recorded computer stock quantities and assess stock count errors.

The software assesses stock errors on both a percentage quantity variance and a value variance basis. You can define these tolerances on the stockroom count profile.

If you have defined count profiles as count by classification, the software uses classification tolerances for each item detail record, that is, A, B or C.

If you have not specified count by classification for the stockroom, the software uses the single default set of quantity percentage and value tolerance figures to assess count errors.

You can restrict Reconciliation (Without Update) to completed lists within the count, or to additionally include Open lists that are still available for modification. You can also restrict the report content such that it only includes items with quantity/value variances.

You can print full detail or summary information by item with selection by item range.

The software highlights detail or item summaries that in error with an * at the right hand side of the report.

If an item summary is found to be in error but no errors have occurred for the detail lines, the summary is highlighted with a **. This situation normally arises due to a number of small positive (or negative) variances that in total constitute an error.

A similar situation happens in reconciliation (with update) where detail lines exist that are in error; however the summary is not flagged as in error. This normally happens when you have a number of positive and negative variance errors at detail level that cancel each other out. If this happens, the software assesses whether the item summary is placed in error or the adjusted detail lines are ignored for the summary totals. If they are in error, the software processes forced adjustments for all detail variances regardless of the extent of the variance, and the summary is highlighted with a **.

If you want to assess whether variances are true count errors, you can print inventory movements that have occurred since the count sheets were printed, (and the computer stocks recorded), for those items that are in error.

You can use Reconciliation (With Update) to make adjustments involving the update of the inventory stockroom balances according to the variances specified. Full movement audit and history updates are reflected in Inventory for any adjustments that take place.

Additionally, item count summaries are updated to reflect the type of count carried out for the item, together with the last count date and a recalculated next due count date. The stockroom period count history is updated to reflect the number and type of counts carried out for the stockroom.

If you use DRP and Production Planning, or both, the software writes net change triggers for any adjusted items. The software uses net change triggers to replace the items.

If you use Catchweight, then the following occurs when reconciliation takes place.

For Catchweight items or non-Catchweight items with secondary units of measure, if the primary value is zero then the secondary value is also made zero. If the primary value is adjusted, the secondary value is automatically adjusted. The nominal secondary value of the quantity is also adjusted.

Reconciliation Without Update

1...
2...

51/INS & 51/WHS

Use this option to process a reconciliation between the system recorded stock balances and the manually counted stock figures without updating the system.

Request Count Reconciliation (Without Update) Selection Screen



To display this screen, select Without Update.

Use this screen to select the stockroom and count number that you want to use.



Note: If you use Warehousing. You only need to enter a count number as the software assumes that you want to process within your default warehouse.

IN136A	MM - Catchweight Company MM	User GBJBA1MS	6/09/00 12:17:34
Request Count Reconciliation (without update)			
Stockroom.....?.. __			
Count number.....?.. ____0			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the code of the stockroom that you want to use.

Count Number

Enter the count number that you want to try to process a reconciliation for.



Press **Enter** to display the Request Count Reconciliation (Without Update) Details Screen.

Request Count Reconciliation (Without Update) Details Screen



To display this screen, press **Enter** on the Request Count Reconciliation (Without Update) Selection Screen.

Use this screen to specify the details you want to reconcile.

IN136B	Z1 - Demonstration Company	User SP1	5/09/94 12:37:32
Request Count Reconciliation (without update)			
Stockroom.....	01	Central Stockroom	
Count number.....	4		
Count lists.....	2	1=Completed 2=All	
Report content.....	1	1=Detail 2=Summary	
Print movements.....	1	0=No,1=Yes	
Items to be included....	2	0=None 1=Variance 2=All	
Range of items:			
From.....?	_____	To.....?	_____
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Count Lists

Enter one of the following:

- 1 - Completed. Include completed lists on the report.
- 2 - All. Include both open and completed lists on the report.

Report Content

Enter one of the following:

- 1 - Detail. Include item detail, that is, lots, batches and serial numbers on the report.
- 2 - Summary. Include item totals on the report.



Note: If you are using Location Control, then the Detail report content includes location details. The Summary report content includes item level balances in item sequence or location level balances in location sequence.

Print Movements

Enter one of the following:

1 - To print the movements: counted quantity, value of the count and recorded quantity of items. The items printed on the report depend on the entry in the field Items to be included.

0 - To exclude movements.

Items To Be Included

Enter one of the following:

0 - None. Do not include details on the report.

1 - Variance. Include those details with either a quantity or value variance on the report.

2 - All. Include all detail regardless of variance on the report.

Range Of Items From.. To..

Enter the valid item reference number.

If you enter a single item it must exist on the item master file. If you enter a range, the From and To items used to define the range need not exist on the item master file except when they are the same value. If you leave the To item blank, it defaults to the From item. You can use range restriction to investigate specific item discrepancies.



Tip: If you are using Location Control, then the name of this field changes to Range Of Locations From.. To.., and you can define the range of locations that you want to use.



Note: If you are using Location Control, then this option sequences item based counts by item, whereas location based counts are always sequenced by location, regardless of the sequence they were created in.



Note: A blank range selection for items defaults to all items on the count.



Select **F8=Submit** to action batch job.

Reconciliation With Update

1...
2...

52/INS & 52/WHS

Use this option to process a reconciliation between system recorded and manually counted stock figures. If you use this option, then you can update the inventory stockroom balances according to the variances specified on the Count Profile.

Request Count Reconciliation (With Update) Selection Screen



To display this screen, select With Update.

Use this screen to select the stockroom and count number that you want to use.



Note: If you use Warehousing. You only need to enter a count number as the software assumes that you want to process within your default warehouse.

IN136A	Z1 - GB Demonstration Company	User GBJBA1MS	6/09/00 13:56:01
Request Count Reconciliation (with update)			
Stockroom.....?.. __			
Count number.....?.. ____0			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the code of the stockroom that you want to use.

Count Number

Enter the count number that you want to try to process a reconciliation for.



Press **Enter** to display the Request Count Reconciliation (With Update) Details Screen.

Request Count Reconciliation (With Update) Details Screen



To display this screen, press **Enter** on the Request Count Reconciliation (With Update) Selection Screen.

Use this screen to specify the details that you want to reconcile.

IN136B	Z1 - Demonstration Company	User SP1	5/09/94 12:41:32
Request Count Reconciliation (With update)			
Stockroom.....	01	Central Stockroom	
Count number.....	4		
Report content.....	1	1=Detail 2=Summary	
Print movements.....	1	0=No, 1=Yes	
Items to be included....	2	0=None 1=Variance 2=All	
Generate adjustments....	0	0=No 1=All 2=Outside tolerances	
Reason code.....?	__		
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Report Content

Enter one of the following:

- 1 - Detail. Include item detail, that is, lots, batches and serial numbers on the report.
- 2 - Summary. Include item totals on the report.

Print Movements

Enter one of the following:

- 0 - No. Do not print movements.
- 1 - Yes. Print movements for all items that are in error.
- 2 - Warehousing. Print Warehousing movements for all items that are in error.
- 3 - Both. Print both Inventory and Warehousing movements for all items that are in error.

You can only use options 2 and 3 if you use Warehousing.

Items To Be Included

Enter one of the following:

- 0 - None. Do not include details are on the report.

- 1 - Variance. Include details with either a quantity or value variance on the report.
- 2 - All. Include all detail regardless of variance on the report.

Generate Adjustments

Enter one of the following:

- 0 - None. Do not make stock adjustments.
- 1 - All. Adjust all quantity variances regardless of size within inventory.
- 2 - Outside tolerances. Adjust those variances which are flagged as errors (those with *) within Inventory.

Reason Code

If you need to make adjustments, you must enter a movement reason. Reason codes are defined to the descriptions file against the major type MOVR.



Select **F8=Update** to submit the batch job.

Reconciliation History Updates

If you request count reconciliation with update, the software performs the following count history updates:

Item Count History

- Count by Class. If the item was a planned summary recommendation then the number of recommended counts is incremented. Similarly, if the item was part of an unplanned recommendation, that is, originating from an addition via recommendations maintenance, then the number of unplanned counts is incremented.
- Count by Manual Range. The number of unplanned counts is incremented.

Stockroom Count History

- Count by Class. The software increments all numbers of A, B and C items counted for all planned item counts. In addition the software increments the numbers of A, B and C items that are in error for planned summary recommendations.
- Count by Manual Range. The software increments the number of other counts. In addition software increments the numbers of other counts that are in error.



Note: If you use Warehousing and you select to count by Warehouse location, the software performs other updates associated with these counts.

Recommended Counts Enquiry



61/INS & 61/WH

Use this option to view the details of the Maintain Count option. You cannot maintain details using this option.

Count Enquiry Selection Screen



To display this screen, select Recommended Counts.

Use this screen to select the stockroom and count number that you want to enquire upon.

```
IN142A          Z1 - UK Demonstration Company    User GBJBAMSA    1/06/98
                                                    13:38:44

Count Enquiry

Stockroom .....?.. 01
Count number .....?.. 0

Recommended Count Selection
Stockroom .....01
Central Stockroom
      Count      Date and time      Items to
Sel number    count initialised    count
-           7    21/01/98   18:33:16      1

1=Select      Position to .....
F12=Previous

F3=Exit      F4=Prompt
```

Fields:

Stockroom

Enter a stockroom code using up to two characters.

Count Number

Enter a count number associated with the stockroom you have chosen.



Press **Enter** to display the Count Enquiry Details Screen.

Count Enquiry Details Screen



To display this screen, select a stockroom and count list on the Count Enquiry Selection Screen and press **Enter**.

This screen displays the count details for your previously selected stockroom and count list combination. This includes the stockroom, the selected count number and list, the date (and time) that the list was created, and the item count details. The middle of the screen displays the information about the items included on the count including the lot reference, if applicable, any reason codes for amendments to the count quantities, and both of those count quantities.



Note: If you are using Location Control, the Location column is displayed on this screen.

IN142B	MM - Catchweight Company MM	User GBJBA1MS	6/09/00 12:26:13
Count Inquiry			
Stockroom	LX	Item summaries to count	0
Count number		Item details to count	0
Create date/time	6/09/00 12:08:11	Item summaries cancelled	0
Item	Location	Lot	Reason
More:			
F3=Exit F12=Previous			

Fields:

Position To Item

To view specific item details, enter the item reference number and press **Enter**, the details are then displayed at the top of the columns.



Select **F3=Exit** to exit the enquiry.

Outstanding Counts Enquiry



62/INS & 62/WH

Use this option to enquire on outstanding counts for a stockroom. You can review open or complete lists for a count.

Count Enquiry Selection Screen



To display this screen, select Outstanding Counts.

Use this screen to select the count details that you want to enquire on.

IN146A	MM - Catchweight Company MM	User GBJBA1MS	6/09/00 12:25:54
Count Details Enquiry			
Stockroom?.. _			
Count number?.. _____			
List number?.. _____			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Count Number

Enter a count number.

List Number

Enter a list number.



Press **Enter** to display the Count Enquiry Detail Screen.

Count Enquiry Detail Screen



To display this screen, select a count on the Count Enquiry Selection Screen and press **Enter**.

Use this screen to view the details of the count that you have selected to enquire on. The top of the screen displays the stockroom and count number details, together with the item count information and the creation date.

The middle of the screen displays all items associated with this count, any lot reference numbers if applicable, and the reason why the item is associated with the count.



Note: If you are using Location Control, the Location column is displayed on this screen.

```

IN146B      MM - Catchweight Company MM      User GBJBA1MS      6/09/00
                                           12:25:42

Count Inquiry

Stockroom ..... LX      Item summaries to count ..... 7
Count number .....      Item details to count ..... 0
List number ..... 23     Item summaries cancelled .... 0
Create date/time ..... 2/08/00 16:23:09      More: +

Item/Lot      Location      Reason      Recorded qty      Entered qty
MNBSBMF              #1              .000              .000
  * Lot error *
PS-C1              #1              .000              .000
  * Lot error *
PS-C1-LC           #1              .000              .000
  * Lot error *
TBBSB              #1              .000              .000
  * Lot error *
TBLQT              #1              .000              .000
  * Lot error *

                                           Position to item .. _____

F3=Exit      F12=Previous
  
```

Fields:

Position To Item

Enter an item code to start the display.



Note: If you are using Location Control, the following field is displayed instead of the Position To Item field:

Position To Location

Enter the location code to start the display.



Select **F3=Exit** to exit the enquiry.

Item Count Summary Enquiry



63/INS & 63/WHS

Use this option to view yearly summary count information by item; that is, the number and type of counts carried out to date, with dates of the last count and the next count due.

Item Count Summary Enquiry Selection Screen



To display this screen, select Item Count Summary.

Use this screen to select the stockroom and item for the count summary information that you want to view.

IN174A	Z1 - Demonstration Company	User SP1	5/09/94 12:37:51
Item Count Summary Enquiry			
Stockroom?.. <u>01</u>			
Item?.. <u>5013</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Item

Enter an item code to display count details for a single item. Leave the field blank to display all item summaries associated with the specified stockroom.



Tip: If you enter a stockroom and leave the item field blank, the software displays summary count information for all items in the specified stockroom.



Press **Enter** to display the Item Count Summary Enquiry Details Screen.

Item Count Summary Enquiry Details Screen



To display this screen, select the stockroom on the Item Count Summary Enquiry Details Screen and press **Enter**.

Use this screen to view the count summary information for the selected stockroom and to select the item that you want to view in more detail.

The top of the screen displays your selected stockroom. The middle of the screen displays a list of items held in the stockroom, the year and the number of recommended counts and unplanned counts that have been performed for each item. You can also view the date and the time of the last count and next count for each item.

IN174C	Z1 - Demonstration Company	User SPI	21/09/94				
			9:48:03				
Item Count Summary Enquiry							
Stockroom 01 Central Stockroom							
Item	Year	Counts recommended	Counts unplanned	Last count date	time	Next count date	time
- 5001	94	0	0	11/08/94		17/12/94	
- 5002	94	0	0	11/08/94		17/12/94	
- 5003	94	1	0	16/08/94		22/12/94	
- 5004	94	0	1	5/09/94		12/01/95	
- 5005	94	0	0	11/08/94		17/12/94	
- 5006	94	1	0	16/08/94		22/12/94	
- 5007	94	1	0	16/08/94		22/12/94	
- 5008	94	0	0	11/08/94		17/12/94	
- 5009	94	0	0	11/08/94		17/12/94	
- 5010	94	0	0	11/08/94		17/12/94	
- 5011	94	0	0	11/08/94		17/12/94	
- 5012	94	0	2	5/09/94		12/01/95	
				Position to item			
F3=Exit		F12=Previous					

Fields:

Select (Untitled)

Enter 1 to display count details for this item. This displays the Item Count Summary Enquiry Item Details Screen.

Position To Item

If the list extends over a single screen, enter the item reference number or the first few characters of an item to reposition the count list.



Select an item and press **Enter** to view the Item Count Summary Enquiry Item Details Screen

Item Count Summary Enquiry Item Details Screen



To display this screen, select an item to view and press **Enter** on the Item Count Summary Enquiry Details Screen

Use this screen to view summary information for the selected item and stockroom. The top of the screen displays the stockroom and item you have selected. The middle of the screen displays the year, the date and time of the last and next count for your selected item.

IN174B	Z1 - Demonstration Company	User SP1	5/09/94 12:37:56
Item Count Summary Enquiry			
Stockroom	01	Central Stockroom	
Item	5013		
Year	94		
Date/time of last count	5/09/94	0:00:00	
Date/time of next count	12/01/95	0:00:00	
Recommended counts	0		
Unplanned counts	2		
Negative stock counts	0		
Low stock counts	0		
Zero stock counts	0		
Transaction frequency counts	0		
F3=Exit F12=Previous			

Fields:

Recommended Counts

This is the number of recommended counts carried out this year.

Unplanned Counts

This is the number of unplanned, or manually requested, counts carried out this year.

Negative Stock Counts

This is the number of counts that have occurred with a negative balance for this year.



Note: Low Stock Counts, Zero Stock Counts, Transaction Frequency Counts are provided for recommending counts in the future.



Select **F3=Exit** to exit the enquiry.

Count History Enquiry



64/INS & 64/WHS

Use this option to view stockroom summary count information by period. You can only view counts for which you have run a reconciliation with update, even if no stock adjustments were actually generated.

At summary level the total number of counts is displayed, with information on the number of each ABC classified item counted with the number of items in error.

The number of other counts (those where you manually select the range) and other counts in error are displayed only at a detail level on an individual period basis.

Count History Enquiry Selection Screen



To display this screen, select Count History.

Use this screen to select the stockroom and period for the count history information that you require to view.

IN177A	Z1 - Demonstration Company	User SP1	5/09/94 12:39:06
Count History Enquiry			
Stockroom?.. <u>01</u>			
Period ____			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code.

Week/Period

Enter the week or period you want to review. Leave this field blank to display all summaries associated with stockroom. These are displayed in descending period sequence by year.

If you want to view a specific period, you must use the following format:

YYMM for a Monthly usage cycle.

YYWW for a Weekly usage cycle.

Where YY is the current year, MM is the current period and WW is the current week.



Tip: You define the usage cycle on the Inventory company profile maintenance.



Press **Enter** to display the Count History Enquiry Summary Screen.

Count History Enquiry Summary Screen



To display this screen, select a stockroom and period on the Count History Enquiry Selection Screen and press **Enter**.

Use this screen to view the count history information for the selected stockroom and period combination. The top of the screen displays your selected stockroom. The middle of the screen displays the periods in which a count occurred for this stockroom, the total number of counts, the number of A, B and C class counts carried out, and the number of errors that occurred.

IN177C	Z1 - Demonstration Company	User SP1	5/09/94 12:39:09				
Count History Enquiry							
Stockroom 01 Central Stockroom							
Period	Counts	Class A counts	Class B counts	Class C counts	Count A errors	Class B errors	Class C errors
_ 08	2	0	0	0	0	0	0
Position to ____							
F3=Exit		F12=Previous					

Fields:

Select (Untitled)

Enter 1 to display a more detailed count history. This displays the Count History Enquiry Stockroom Detail Screen.

Position To

If the summary count history extends over more than a single screen then enter the period you want to view in the position to field.



Press **Enter** to display the Count History Enquiry Stockroom Detail Screen.

Count History Enquiry Stockroom Detail Screen



To display this screen, select a period on the Count History Enquiry Summary Screen and press **Enter**.

Use this screen to view the summary period information for the stockroom, including the number of ABC classified items counted and the number of items with errors.

IN177B	Z1 - Demonstration Company	User SP1	5/09/94 12:44:20
Count History Enquiry			
Stockroom 01 Central Stockroom			
Period 9408			
Number of counts		3	
Number of class A items counted ...		0	
Number of class B items counted ...		0	
Number of class C items counted ...		0	
Number of class A item errors		0	
Number of class B item errors		0	
Number of class C item errors		0	
Number of other counts		3	
Number of other count errors		1	
F3=Exit F12=Previous			



Select **F3=Exit** to exit the enquiry.

-
-
-
-
-

Chapter 4

Inventory Updates

Inventory Updates Introduction

The investment in Inventory typically represents one of the largest single areas of investment in a business, often as high as 25% of total assets. It is vital that you plan and control its acquisition and disposition.

There are a number of techniques to help with this control. In the sphere of a Production operation where demand is dependent on an agreed production schedule, the most common forms of control are Material Requirements Planning (MRP), or Just In Time (JIT).

However, there are a number of factors which are independent of company decisions that influence the demand for end-product items. These external factors include a certain amount of random variation in the demand for such items. As a result, forecasts of demand for these items are typically projections of historical demand patterns to determine average usage.

You must consider the concepts of independent and dependent demand when you select the appropriate Inventory Management techniques.

There are two types of Inventory: Movement and Organisational.

Inventory Holding

- Work In Progress - in a Production organisation.
- Stock In Transit - in a Distribution environment.
- Cycle Stock is a result of buying or making more than is needed immediately.
- To determine the Economic Order Quantity, you must set the one-time costs of raising an order and perhaps the cost of setting machines or transport against the costs of holding stock.
- You would hold anticipation stock to deal with times when demand exceeds the rate of economic supply for an item. Seasonal products, for example lawn mowers, are a good example of where it is sensible to have a fairly steady rate of production throughout the year. You could build high levels of stock over the winter so that the depletion rate of stock plus the production rate equals demand during high summer.

Inventory Decisions

You need to make two types of routine decisions when managing inventories, how much and when to order. Four main factors influence these decisions:

- Forecast demand.
- Replenishment lead time.
- Inventory related cost.
- Management policies.

There are two important parameters to assist inventory controllers in making these decisions, they are:

- Economic Order Quantity - EOQ.
- Economic Time Between Orders - ETBO.

The standard calculation of EOQs:

$$EOQ = \sqrt{(2 * CP * AU) / CH}$$

Where:

CP = Cost of order placement.

AU = Average usage per annum.

CH = Inventory holding cost per year.

$$CH = \text{Item Cost} * \text{Carrying Rate}/100$$

Once the software has calculated the EOQ then:

$$ETBO = EOQ/WU.$$

Where WU = Weekly Usage.

The resulting Economic Time Between Orders (ETBO) is in weeks.



Note: You specify the cost of order placement and carrying rate on the Inventory company profile.

Demand Management

Inventory Management has a range of facilities to help you manage independent demand items, traditionally controlled by reorder point techniques.

- You can use the value/usage matrix to help you implement a stock investment policy at each stockroom.
- You can use usage profiles to provide a range of calculations for forecast usage.
- The software calculates the EOQ. You can use this as the basis of reorder quantity and time between orders.
- You can factor lead time within the reorder calculation to modify order review periods.

You can use Inventory Management to make re-order level calculations.

You can use many different criteria within the calculations to reflect differing item usages, values and stock control requirements.

The culmination of the process is the production of the Reorder/Overstock report that details all recommendations.

Included in the set up before this are:

- The calculation of an Average Usage figure.
- The calculation of Reorder Point (ROP), Maximum Stock and Economic Order Quantity (EOQ).
- The selection of one of 5 Reorder Policies appropriate to each item.

Selection Of The Reorder Policy

The software uses the following data for each of the Reorder Recommendations:

Physical/Available	= 0
Expected	= -90
Max weeks = 8 Average Usage	= 10
Min weeks = 6 Lead Time	= 4 weeks
Reorder Factor	= 200%
ROP = (Min. Weeks) 6 + (Lt) 4 * (av. usage) 10	= 100
Maximum stock = (Max. Weeks) 8 * (av. usage) 10	= 80

The Maximum stock level is below the ROP because the lead time (4) is greater than the difference between Maximum (8) and Minimum (6) weeks, in other words 2.

Reorder Policy 1 (Up To Max)

ROQ = Maximum stock - Expected + (average usage * lead time).

If you do not specify maximum stock on the item/stockroom record the software obtains the appropriate value from the stock weeks grid. This is expressed in weeks and is multiplied by average usage to give a maximum stock value.

Example

$$\begin{array}{rccccccccc} 80 & - & -90 & + & 40 & = & 210 \\ \text{Maximum} & - & \text{Expected} & + & (\text{av. usage} * \text{lt}) & & \\ \text{stock} & & & & & & \end{array}$$

Reorder Policy 2 (ROQ)

ROQ = Average Usage * lead time * FACTOR percentage.

Example

$$\begin{array}{rccccccccc} 10 & * & 4 & * & 200\% & = & 80 \\ \text{Av. usage} & * & (\text{lt}) & * & \text{Factor} & & \end{array}$$

Reorder Policy 3 (Up To Min)

To use this you must set the Calculate EOQ, etc. field to 0.

You can manually enter a ROP.

$ROQ = ROP - \text{Expected}$.

Example

$$0 - 90 = 90$$

Reorder Point - Expected

As you have set Calculate EOQ, etc. field to 0 for this policy, the software does not calculate ROP, it remains as 0 on the item/stockroom record.

Reorder Policy 4 (Up To ROP)

$ROQ = ROP - \text{Expected} + (\text{average usage} * \text{lead time})$.

Example

$$100 - 90 + 40 = 230$$

Reorder Point - Expected + (lt)

Reorder Policy 5 (EOQ)

$ROQ = EOQ$.

If you use Policies 1 to 4 you can manually enter a Reorder Quantity. You can use Policy 3 if you want to reorder to demand. The software reviews the stock position as follows for all items:

1. You can calculate Available stock as: Physical - Frozen - Allocated = Available.
2. You can calculate Expected stock as: Available + Order + In Transit - Back Order - Reserved = Expected.
3. If expected stock is greater than maximum stock the item is reported as in Excess.
4. If expected stock is less than reorder point, the item is reported for Order action.
5. If you need an order action, you can manually specify the reorder quantity. If you do not, the software determines the reorder quantity for each policy as follows:
 - If the policy is Up to MAX, the software will recommend reorder up to the maximum stock holding.
 - If the policy is ROP, the software calculates a reorder quantity based on the reorder quantity factor, the average usage and the lead time or the difference between Expected and ROP if greater.
 - If the policy is Up to MIN, the software will recommend reorder up to the minimum stock holding.
 - If the policy is Up to ROP the software will recommend that you order enough to bring expected back to ROP.
 - If the policy is EOQ, the software will recommend reorder of the calculated or maintained economic order quantity.

Example

If the Maximum Stock is:

*Maximum Stock Weeks * Average Usage.*

The Reorder Point is:

*(Minimum Stock Weeks + Lead Time (in weeks)) * Average Usage.*

The Expected Stock is:

Available + On Order + In Transit - Back Orders - Reserved.

The EOQ depends on Cost of Order placement, Average Usage per annum and Inventory Holding Cost per year.

Regular Updates

To improve the speed and quality of information displayed within Inventory, a series of weekly and periodic balances are maintained. These balances need to be updated at week, month and year end.

At month end you should run both the week end and month end updates consecutively. The month end run normally includes a valuation of stock movements and this, therefore, is prompted.

At year end, you should run the week end, month end and year end consecutively.

Week End Update



1/INC

This batch option performs the following tasks:

- If you have set the usage cycle on the company profile to W, for weekly, then the software recalculates the average weekly usage for each product/stockroom.
- Both the physical and in transit stock at the end of the week are stored in a separate field Stock At Start Of Week for each product/stockroom.
- The software re-sets the usage this week to zero for each product/stockroom.
- The current week number on the calendar file is incremented by 1. If you are updating the last week of the year, then week number is set to 1.

If you are processing the last week of the year, you should follow this update immediately by month and year end processing since the year number on the Calendar file is only incremented by the year-end update.



Note: If you use Catchweight then, for items with a secondary unit of measure, the secondary stock at the start of the week is updated. The stock at the start of the week is equal to the total physical stock and the stock in-transit, minus all movements in future weeks.

If an item does not have a secondary unit of measure, the secondary stock at the start of the week is zero.

Week End Update Confirmation Screen



To display this screen, select Week End Update.

Use this screen to confirm the Inventory week end.

IN105	MM - Catchweight Company MM	User GBJBA1MS	2/10/00 14:40:54
Week End Update Confirmation			
Regenerate ABC classifications <u>1</u>			
-			
F3=Exit F8=Submit			

Fields:

Regenerate ABC Classifications

Enter one of the following:

0 - No. To not automatically regenerate the ABC classifications of your items during the week end processing.

1 - To automatically regenerate the ABC classifications of your items during the week end processing.



Select **Submit=F8** to submit the update.

Month End Update



2/INC

This batch option performs the following tasks for each product/stockroom.

- If you have set the usage cycle on the company profile to M, for monthly, then Inventory recalculates the average monthly usage.
- The software sets the usage this period to zero.
- The software sets the number of sales orders this period to zero.
- The software sets the number of substitutions this period to zero.
- Current physical stock is stored in a separate field Stock at start of period.
- Inventory calculates the stock value using the appropriate costing method and stored the value in a field called Stock value at start of period.

The option will also:

- Increment the current period number by 1. It also sets the period number to 1 when you reach the end of the year.
- Produce a stock movements valuation report if you have requested this as part of the submission process. This report is produced based on parameters specified at that time.
- Produce a reorder report as part of the submission process.



Warning: Run Inventory Month End before you run any updates within the Accounts module. Inventory's Calendar dictates the posting of invoices to Accounts Receivable. You must Close Inventory Period to post to a future period, otherwise, postings will continue for the previous period and be incorrect.



Note: If you use Catchweight then, for items with a secondary unit of measure, the secondary stock at the start of the period is updated. The stock at the start of the period is equal to the total physical stock and the stock in-transit minus all movements in future periods. If an item does not have a secondary unit of measure, the secondary stock at the start of the period is zero.

Month End Update Record Report Selection Criteria Screen



To display this screen, select Month End Update.

Use this screen to specify the criteria that you want to use to produce the month end update report and process your month end update.

- To action the month end update and print a report, enter a range of parameters and press **Enter**.
- To action the month end update without printing a report, leave all fields blank and press **Enter**.

IN056	Z1 - GB Demonstration Company	User GBJBA1MS	2/10/00 15:10:11
Record Report Selection Criteria			
	From	To	
Stockroom code.....?..	—	—	
Item.....?..	—	—	
OR			
Item group major/minor.....?..	— —	— —	
OR			
Item type.....?..	—	—	
OR			
Item class.....?..	—	—	
Include kits..... 1 (1=components, 2=headers, 3=both)			
F3=Exit F4=Prompt			

Fields:

Stockroom Code

Item

Enter a single item, or range of items that you want to produce the month end report upon.

Item Group Major/Minor

Enter a single item group, or range of item groups that you want to produce the month end report upon.

Item Type

Enter a single item type, or range of item types that you want to produce the month end report upon.

Item Class

Enter a single item class, or range of item classes that you want to produce the month end report upon.

Include Kits

Enter one of the following:

- 1 - Components. To include kit components in the report.
- 2 - Headers. To include kit headers in the report.
- 3 - Both. To include both kit components and headers in the report.



Press **Enter** to display the Month End Update Confirmation Screen.

Month End Update Confirmation Screen



To display this screen, press **Enter** on the Month End Update Record Report Selection Criteria screen.

Use this screen to specify whether ABC classifications are regenerated.

IN105	Z1 - GB Demonstration Company	User GBJBA1MS	6/09/00
			14:29:37
Month End Update Confirmation			
Regenerate ABC classifications <u>1</u>			
Stockroom Fiscal Close:			
Primary sequence	<u>1</u>	Item	
Secondary sequence	<u>2</u>	Movement date	
Report content.....	<u>1</u>	0=None,1=Detail,2=Summary,3=Both	
F3=Exit F4=Prompt F8=Submit			

Fields:

Regenerate ABC Classifications

Enter one of the following:

0 - Do not generate ABC classifications.

1 - Generate ABC classifications.

Stockroom Fiscal Close

Use the next three fields to determine how you want to process a stockroom fiscal close for your selected stockroom.



Tip: These fields are only displayed if you have set the Stockroom Fiscal Close field to 1 on the Inventory Company Profile so that you can automatically produce a stockroom fiscal close at Month End



Note: Use the Primary Sequence and Secondary Sequence codes to control the fiscal close. For example, if you specify that your primary sequence is by Item and your secondary sequence is by Movement Date, then the system will close the fiscal period by item and movement date order.

Primary Sequence

Select the primary sequence that you want to use to process a fiscal close. These codes are setup in Inventory descriptions under major type SJSQ.

Secondary Sequence

Select the secondary sequence that you want to use to process a fiscal close. These codes are setup in Inventory descriptions under major type SJSQ.

Report Content

Enter one of the following:

- 0 - None. To not produce a report of the fiscal close.
- 1 - Detail. To produce a detailed report of the fiscal close.
- 0 - Summary. To produce a summarised report of the fiscal close.
- 0 - Both. To produce both a detailed and summarised report of the fiscal close.



Select **F8=Submit** to action the update and print a report if you have specified to do so.

Year End Update



3/INC

Use this option to

- Update the number of weeks this year and last year specified on the calendar.
- Change the number of periods specified on the calendar.
- Set any yearly accumulators to zero.
- Increment the year number by one.
- Produce a Stock Valuation Report as part of the submission process.
- Produce a Reorder Report as part of the submission process.



Tip: This option is the same as the Calendar
Maintenance And Year End Update option.

Maintain Calendar File Screen



To display this screen, select Year End Update.

Use this screen to specify the current date information for Inventory.

IN012	Version 3 Demonstration Company	USER STDFIN	28/01/00
			15:43:33
Maintain Calendar File			
Current year..... <u>00</u>			
Current week..... <u>3</u>			
Current period..... <u>1</u>			
No. of weeks this year.... <u>52</u>			
No. of weeks last year.... <u>52</u>			
No. of periods this year... <u>12</u>			
F3=Exit F11=Delete			

Fields:

Current Year

Enter the current year using up to two numeric characters.

Current Week

Enter the current week using up to two numeric characters.

Current Period

Enter the current period using up to two numeric characters.

No Of Weeks This Year

Enter the number of weeks this year using up to two numeric characters. The value must be less than or equal to 53.

No Of Weeks Last Year

Enter the number of weeks last year using up to two numeric characters. The value must be less than or equal to 53.

No Of Periods This Year

Enter the number of periods this year using up to two numeric characters. The value must be less than or equal to 13.



*Note: This information is linked to Sales Analysis
Company Profile and Forecasting's Company
Profile Periods/Backups details.*



Press **Enter** to process a Year End Update. This submits a batch job to perform the year end update.

Calculate ROP, Max Stock, And EOQ



4/INC

You can use this option to calculate the ROP, Maximum Stock and EOQ. These calculations are performed during the Ad-Hoc Update for all items that have 1 in the Calculate EOQ, etc. field on the second Stockroom Details Maintenance screen.

Select the Ad-Hoc Update option.



*Note: Run the **Ad-hoc Update** after the week/month end update to pick up the latest average usage figures.*

You can see information about the basis of these calculations on the fifth Maintain Company Profile screen, and the second Stockroom Details Maintenance screen.



There are no selection criteria for this option, Select **F8=Confirm Submit** to process the batch job.

-
-
-
-
-

Chapter 5

Inventory Lot/Grade/Potency

Lot/Grade/Potency Introduction

You can use Batch or Lot control on items that need more detailed identification of the stock, for example, drugs, wallpaper, wool, date controlled items. It is the same *item*, but you can manufacture quantities of the item at different times, or the item could be of varying colour/shade or need greater traceability through the supply chain.

Serial control is much more specific. This is where each *individual* item carries a unique number, for example, a PC, a television, and so on.

You indicate on the Item Master file if the item is to be batch, lot or serial controlled. However, you must first indicate on the company profile whether you need to use if extended Lot details.

Are Extended Lot Details Required?

If you do not need to use extended lot details, Inventory functions as follows:

1. When you receive these items you *must* enter a lot number.
2. Inventory holds stock balances at lot number level.
3. You must also specify a valid lot number when you issue these items.
4. All Inventory enquiries will include lot number information.

If you do require extended lot details, Inventory supplies support for the Production application but also provides extra controls:

- Stock status.
- Dates.
- Shelf life.
- Potency.
- Grade.
- Lot traceability.

Lot Movements

You can trace the location of a lot over both time and locations. For example, you can trace Lots back to Production - to both component and parent items - and to both Sales Order Processing and Purchase Management Order enquiries. You can hold a single lot of an item in a number of stockrooms, where all parts of it retain the same lot header details. However, you can transform a lot and amend the lot details for each part.

You can enquire on all these aspects of lot control.



Note: You can hold a single lot of an item in more than one stockroom.

Stock Status

This is one of the functions that you can use to control stock availability. It covers the requirement to classify stock as being unavailable for processing, for example,

for allocation, picking and despatch. For example, you can use stock status to cater for quarantine stock, stock within inspection or QA, stock for internal sales or for key customers.

If you leave the stock status blank then dates will control availability.

If you specify a stock status then this code will determine availability.

If you use a stock status code with 1 in the seventh digit of the Limit field of a description code recorded against STKS in the Descriptions file, you will make sure that all receipts of that item are automatically frozen.

The stock status applies to a complete lot regardless of how many holding stockrooms there are for that lot. You can specify a default stock status on the Item Master. Any changes made to the stock status are written to an audit file.

Shelf Life, Grade and Potency

All lots have four dates associated with them, used by Production and Sales Order Processing, Order Entry to control release and allocation of stock.

You can maintain a shelf life for all lot controlled items and, in conjunction with the production or receiving dates, the stock status monitor can calculate the availability of the lot. A status flag, also on the lot header, provides extra function for lot control. You can use this to override the availability dates for the whole lot.

You can maintain the grade and potency level of the lot; you can make these details mandatory for certain items. Production uses Lot potency to process actual potent units of a product where the strength of an active ingredient is important, rather than physical units.

Dates

You need to maintain Shelf Life Units (for example, days), and possibly numbers for shelf life and customer shelf life.

You also need to maintain release lead time units and numbers, if you require an inspection or QA period.

Production date = Current date (if finished goods received from Production or Purchasing).

Expiry date = Production date + Shelf life.

First available date = Production date + Release lead time.

Last available date = Expiry date - Customer shelf life.

An Inventory Stock Status Monitor constantly reviews all controlled items with extended details and automatically freezes/unfreezes stock according to stock status codes or availability dates if there is a transaction involving the batch, lot or serial reference number.

If you are using Warehousing, the commit routine will ignore frozen stock beyond last available date.



Warning: JBA recommend that you run the Stock Status Recalculation option regularly to make sure that any controlled item balances are frozen when they are past their last available date. Otherwise the Warehousing commit routine will use this stock, regardless of the date because it would still consider it to be available for use.

If you are using Advanced Order Entry then allocation against batches will give a warning message if stock is beyond Last Available date or Expiry date.

If you are using Sales Order Processing/Warehousing then the software warns you during confirm pick/despatch if the lot is beyond dates.

Grade

You use this for products that have a wide range of quality specifications and require multiple grades, for example, eggs.

You can use this to control allocation and issues - with specific grades only being issued to production, received into stock or issued to customers.

You can also use this if you need to downgrade or upgrade stock.

Potency

Again, you use this to hold potency details at lot level. You can update lot potency - if mixtures or blending of potency occur.

Lot Traceability

You use this to provide full forward/backward traceability for all lots.

Forward = Customer Orders, Production Orders, Transfer Orders.

Backward = Purchase Orders, Production Orders, Transfer Orders.

Lot Header Maintenance



1/INL & 2/AOM

Use this option to record basic information about a product lot, irrespective of the holding stockrooms for this lot within Inventory Management.

You normally enter this information when you receive a batch, lot or serial controlled item into Inventory Management by any route. These routes include Inventory Receipts, Purchase Management Receipts, Production Finished Goods Receipts, and so on. However you can maintain the lot header directly.



Note: You can also access these screens using the Lot Reference option in Advanced Order Entry.

Lot Header Maintenance Selection Screen

 To display this screen, select Lot Header.

Use this screen to select the item and lot reference whose header details you want to maintain.

IN215

Z1 - GB Demonstration Company

USER GBJBA1MS

7/09/00
09:49:34

Lot Header Maintenance

Item.....?..

Lot reference.....?..

F3=Exit F4=Prompt

Fields:

Item

You must enter the item reference number of the item you want to amend; or enter a unique number to create a new lot reference for that item.

Lot Reference

Enter a lot reference. This can be a new reference number or an existing one.

 *Note: You must enter the item number to prompt on associated lot reference numbers.*

 Press **Enter** to display the Lot Header Maintenance Detail Screen.

Lot Header Maintenance Details Screen



To display this screen, select an item and lot number on the Lot Header Maintenance Selection Screen and press **Enter**.

Use this screen to maintain the header details for the requested lot. The lot header details are valid for all items included in the lot regardless to the physical location of parts of that lot.

To modify the details for a subset of the lot, see Lot Transformation.



Note: In some circumstances other external flags or applications control the visibility and maintenance of some of these fields. (This is particularly relevant if you use Production.)

Inventory holds the lot header information until the lot number itself is purged when you use the Delete FIFO/Lot Utility.

The upper part of the screen identifies the item and lot number that you want to maintain. The lower part lists the lot header details specifically detailed for this item.

The screen displays any current data for the lot.

IN215	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	26/06/96 10:51:34
Lot Header Maintenance			
Item.....	1352_LOT		
Lot reference.....	LOT02		
Production date.....	26/06/96	Time.....	10:37
Expiry date.....	26/02/08	Time.....	0:00
First available date....	26/06/96	Time.....	0:00
Last available date.....	26/02/98	Time.....	0:00
Stock status.....?	—		
Reason code.....?	—		
Potency.....	80.00000 %		
Grade.....	AVE Average Quality		
C-of-C reference.....	NER		
Suppliers Lot ref.....	_____		
F3=Exit	F4=Prompt	F12=Previous	F13=Grades
F16=Adjust active ingredient			F14=Status
10-27	SA	MW	KS
			IM
			II
			KENB20A
			PET166S2

Fields:

Production Date

This is the date that of manufacture, or receipt, for this lot. The field will default to the current date but can be any previous date. If you do not enter this date, Inventory calculates it back from the expiry date using the shelf life of the item.

If you receive the lot into either Purchase Management or Production then you must enter either a production data or expiry date. If you receive the lot into Inventory the fields are not mandatory.

This only applies when you receive the item lot for the first time. Once the lot exists you cannot maintain either the production or expiry date.



Warning: The software displays the production, expiry and first and last available times if you have set the Display Lot Time field on the Lot Header Parameters Screen, in Item Maintenance to 1.

Production Time

Once you have created the lot, you cannot change this information.

Expiry Date

This is the date on which the shelf life of the item expires.

If you do not enter this information the software calculates this date by adding the shelf life to the production date. If you receive the lot in Purchase Management or Production then you must enter either a production or expiry date. If you receive via Inventory the fields are not mandatory.

Once the lot exists, the production and expiry dates are not maintainable. Enter a date not less than today's date. If you enter this you can calculate the production date by subtracting the shelf life from the expiry date.

Expiry Time

The time at which the shelf life of the item expires.

First Available Date

Enter a date, which must be greater than or equal to the production date.

Inventory will normally freeze all lots with the first available date greater than the current date. If you do not enter a date Inventory generates it by adding the release time to the production date.

First Available Time

Enter a time for memo purposes only. If the production date is equal to the first available date then the first available time must be equal to, or greater than, the production time.

Last Available Date

Enter a date, which must be greater than the first available date but less than or equal to the expiry date.

The Inventory freezes all lots with a last available date less than the current date if there is no stock status. Inventory will generate the date if you do not enter one.



Tip: For more information, see the Lot/Grade/Potency Introduction.

Last Available Time

Enter a time. If expiry date is equal to the last available date then last available time must be less than or equal to expiry time.

Status Code

Select a stock status code from those defined on the Inventory Descriptions file against major type STKS.

The stock status code is used as an override to the availability dates to determine if a lot quantity is available or classed as frozen stock.

If you leave the stock status blank, the availability dates are used to move stock in and out of the frozen stock.

You can divide stock statuses into available or unavailable using the 7 digit limit field held against the stock status description codes on the Inventory Descriptions file. If you set the seventh digit to 1, the stock status indicates that the lot is unavailable. If this last digit is set to any other value then the lot is available.

Reason Code

Enter a reason code from those defined on the Inventory Descriptions file against major type SSRC.

You must select a code, if you change the stock status code, or if it is blank initially, to indicate why you have changed the status of the lot.

Potency

This is the potency of the whole lot irrespective of which stockroom the lot is located in.



Note: This field is displayed if the Potency Required flag on the Lot Header Parameters Maintenance Screen is set to 1.



Note: Potency is a percentage, so the potency you specify here is the number of parts of active ingredient per hundred parts.

Grade

Select a grade code from those defined on the Inventory Descriptions file against the major type GRAD. This is the grade of the whole lot irrespective of which stockroom the lot is located in.



Note: This field is displayed if the Grade Required flag on the Lot Header Parameters Maintenance Screen is set to 1.

C-Of-C Reference

Enter a Certificate of Conformance reference, associated with a C-of-C defined in Advanced Order Entry, to be assigned to this lot. You enter the values for this C-of-C when you first receive the lot into Inventory.



Note: If you are using Advanced Order Entry, and you have specified that this item requires a Certificate of Conformance on the second Item Maintenance Screen, then Inventory displays a Certificates of Conformance field on the Lot Header Maintenance Screen. (See Advanced Order Entry for an explanation of Certificates of Conformance.)

Suppliers Lot Reference

Enter up to 36 alphanumeric characters to specify the lot reference allocated by the supplier.

Function:

F13=Grades

Use this to display lot Grade History Enquiry for this lot.

F14=Status

Use this to display the Stock Status History Enquiry for an existing lot.

F15=Potency

Use this to display lot Potency History Enquiry for this lot.

F16=Adjust Active Ingredient

Use this to display the Adjust Active Ingredient Screen.

F17=Certificate of Conformance

Use this to display certificate of conformance details.

F21=Text Entry

Use this to display the Maintain Text window to enter or select a Usage Code and a Language Code for multi-lingual text entry. Press **Enter** to display the Item Text window. Use this window to enter text in your selected language, this text is displayed or printed on external documentation, for example, despatch notes, according to the usage code selected.



Tip: You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is available.



Note: Language codes do not need to be selected in order to print text in the native language.



Press **Enter** to validate your entries and select a function key to continue.

Or:

Press **Enter** again to redisplay the Lot Header Maintenance Selection Screen.

Adjust Active Ingredient Screen



To display this screen, select **F16=Adjust Active Ingredient** on the Lot Header Maintenance Details Screen.

Use this screen to modify the current potency level for a lot of the selected item. This change applies to the whole lot irrespective of its location.

The top of the screen displays the item number, item description and lot number of the selected lot.

IN231	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	26/06/96
			11:42:44
Adjust Active Ingredient			
Item.....	1352_LOT	Mitchelson Compound	
Lot number.....	LOT02		
Potency.....	80.00000 %		
Quantity.....	657.000		
Total potent units.....	525.600		
New potency.....	75.00000 %		
New potency units.....	492.750		
Potency change.....	32.850-		
Reason code.....	01 Blended with high grade		
F3=Exit	F8=Update	F12=Previous	
01-02	SP	MW	KS IM II KENB20A PET166S2

Fields:

Potency

This is the current potency of the lot.

Quantity

The current quantity of items attached to your selected lot; this figure is displayed in the item's issue unit.

Total Potent Units

This displays the total potent units for your selected lot. Inventory calculates this as:
 $\text{Quantity} \times \text{Current Potency \%} = \text{Total Potent Units}$.

New Potency

Specify the new potency using up to nine characters, five decimal places. Negative values are not allowed.



Note: Potency is a percentage, so the potency you specify here is the number of parts of active ingredient per hundred parts.

Reason Code

Enter a two alphanumeric character reason code from those defined in the Inventory Descriptions file against the major type PRSC.



*Note: When you press **Enter**, Inventory will calculate and display the following information:*

New Potent Units

This is the total potent unit for your selected lot using the new potency level in the Quantity x Potency % calculation.

Potency Change

The difference between the original total potent units and the new potent units. This field can be positive or negative.



Select **F8=Update** to update the lot header details and potency history file.

Certificates Of Conformance Window



To display this window, enter a new Certificate of Conformance and select **F17=Cert of Conformance** on the Lot Header Maintenance Details Screen.

Use this window to complete the Certificate of Conformance criteria before the lot is received into Inventory.

See the Advanced Order Entry application for details on creating Certificates of Conformance.

IN215		NR - Neil Radford and Co. Ltd		USER GBJA1MS		13/08/96									
						16:45:42									
Lot Header Maintenance															
Item.....		1352_LOT													
Lot reference.....		LOT02													
Production date.....		26/06/96													
Expiry date.....		26/02/00													
First available date....		26/06/96													
Last available date....		26/02/98													
Stock status.....?		—													
Reason code.....?		—													
Potency.....		75.000													
Grade.....		AVE A													
C-of-C reference.....		NER													
Suppliers Lot ref.....		—													
Maintain C-of-C reference AMENDMENT <table><tr><td>Description</td><td>Code (?)</td></tr><tr><td>piece of wood</td><td>S</td></tr><tr><td>length</td><td></td></tr><tr><td>width</td><td></td></tr></table>								Description	Code (?)	piece of wood	S	length		width	
Description	Code (?)														
piece of wood	S														
length															
width															
F5=Refresh F4=Prompt F8=Update F12=Previous F21=Text															
F3=Exit		F4=Prompt		F12=Previous		F13=Grades									
F16=Adjust active ingredient						F14=Status									
11-63		SF		MW		KS IM II KENB20A PET166S2									
						F15=Potency									
						F17=Cert of conformance									
						F21=Text									

Fields:

Code

Enter, or select, a relevant code for the criteria you need for this Certificate of Conformance.

Functions:

F21=Text Entry

Use this to display the Maintain Text window where you enter or select a Usage Code and a Language Code for multi-lingual text entry. For more information, see the Maintain Text Window in Inventory Maintenance.



Select **F8=Update** to save these details and redisplay the Lot Header Maintenance Details Screen.

Managing Grades

Use these options to maintain and enquire on grades for an item.



Note: You can use this option if you have specified that your item requires grade details recorded against it.

Grade Maintenance

1...
2... **2/INL**

Use this option to alter the grade of a lot. The change in grade applies to the whole lot, irrespective of where the lot is located.



Use this screen to select the item whose current grade details you want to maintain.

```
IN234                Z1 - GB Demonstration Company    User GBJBA1MS      7/09/00
                                                           09:55:26
Grade Maintenance
Item.....?.. HEB01
```

```
F3=Exit      F4=Prompt
```

Fields:

Item



Note: The item must be lot, batch or serial number controlled.



Press **Enter** to display the Grade Maintenance Detail Screen.

Grade Maintenance Detail Screen



To display this screen, enter an item code on the Grade Maintenance Selection Screen and press **Enter**.

Use this screen to view a list of all the lots associated with the selected item.

IN234	NR - Neil Radford and Co. Ltd	User GBJBA1MS	26/06/96 13:10:57
Grade Maintenance			
Item..... 1352_LOT		Mitchelson Compound	
Lot number	Grade	Description	
- LOT01	AVE	Average Quality	
- LOT02	AVE	Average Quality	
- LOT03	AVE	Average Quality	
1=Maintain grade 2=Grade history 3=Lot header 4=Lot trace enquiry			
F3=Exit F12=Previous			
08-02	SF	MW	KS IM II KENB20A PET166S2

Fields:

Select (Untitled)

Enter one of the following selections for each lot:

- 1 - Maintain Grade. To change the grade for this lot.
- 2 - Grade History. To view the Grade History Enquiry for the selected lot.
- 3 - Lot Header. To view the Lot Header Details Window for the selected lot.
- 4 - Lot Trace Enquiry. To view the Lot Trace Enquiry for the selected item.



Select an option to automatically display the next screen.

Or:

Select **F3=Exit** to exit the option.

Maintain Grade Window



To automatically display this window, enter 1 next to the lot you want to maintain on the Grade Maintenance Detail Screen.

Use this window to maintain the grade for the selected lot. Existing information is displayed.

IN234		NR - Neil Radford and Co. Ltd		User GBJBA1MS	26/06/96 13:10:57
Grade Maintenance					
Item.....		1352_LOT		Mitchelson Compound	
	Lot number	Grade	Description		
1	LOT01	AVE	Average Quality		
-	LOT02	AVE	Average Quality		
-	LOT03	AVE	Average Quality		

Grade.....?	AVE	Average Quality
Reason.....?	RI	Re-inspected
F4=Prompt F12=Previous		

1=Maintain grade 2=Grade history 3=Lot header 4=Lot trace enquiry			
F3=Exit		F12=Previous	

16-38	SF	MW	KS	IM	II	KENB20A	PET166S2
-------	----	----	----	----	----	---------	----------

Fields:

Grade

Select a grade from those defined in the Inventory Descriptions file against the major type GRAD

Reason Code

Select a code describing why the grade is amended. These are defined in Inventory Descriptions against the major type RSCD.



Press **Enter** to update the details and return to the Grade Maintenance Detail Screen.


Grade Enquiry



21/INL

Use this option to view the grades defined to a particular item.

Grade Enquiry Selection Screen




Use this screen to select the item

```
IN234          Z1 - GB Demonstration Company    User GBJBA1MS    7/09/00
                                                    11:36:13
Grade Enquiry
Item.....?.. HEB01
```

Fields:

Item

Enter the item reference code of the item whose grade details you want to view.



Grade Enquiry Details Screen



To display this screen, specify an item and press **Enter** on the Grade Enquiry Selection Screen.

Use this screen to view the selected item number and item description, and a list of valid lots, with associated grades and grade descriptions.

IN234	Z1 - Demonstration Company	User SP1	26/08/94 11:47:55
Grade Enquiry			
Item..... 5020		Carton Fresh Orange Juice 1/2 Litre	
Lot number	Grade	Description	
- B006	GOOD	Good Quality	
1=Grade history 2=Lot header 3=Lot trace enquiry			
F3=Exit F12=Previous			

Fields:

Select (Sel)

Enter one of the following:

- 1 - To display the Grade History Enquiry for this lot.
- 2 - To display the Lot Header Details Window for this lot.
- 3 - To display the Lot Trace Enquiry for this lot.



Select the option to view the enquiry you want and press **Enter** to continue.

Stock Status Recalculation



11/INL

Use this option to process all lots currently with physical stock. It uses the current date and the first and last available dates of each lot to determine whether the lot quantity should be available or frozen. This option checks all lots regardless of status. Any change in stock status applies to the whole lot across all stockrooms.

This option affects two stock balance values: available and frozen. The actual quantity of the lot does not change and the equation is not affected by this procedure: $\text{Physical} = \text{Available} + \text{Allocated} + \text{Frozen}$. The procedure reviews dates and stock status if the stock monitor is not running.



Note: JBA recommend that you include this option as part of your Day Start Up Procedure. For more information, contact your System Manager.

Stock Balance Recalculation Screen



To display this screen, select Stock Status Recalculation.

Use this screen to select the stock balance you want to recalculate.

```

IN242                Distribution V3 -> V3 Financials    User GBJBAMV1    17/11/95
                                                           14:46:32

Stock Balance Recalculation

Item.....?.. █
Lot.....?.. 
Stockroom.....?.. 

F3=Exit      F4=Prompt      F8=Submit

05-27      SA      MW      KS      IM      II  KENB20A  PET129S1

```

Fields:

Item

Enter an item number.

Lot

Enter a lot reference.

Stockroom

Enter a stockroom code.



Note: You can leave each of these fields blank to recalculate all lots of all items in all stockrooms that have a blank status code.



Press **Enter** to confirm your selection, then select **F8=Submit** to submit the recalculation.

Lot Transformation



12/INL

Use this to enter the details of lots to be split or transformed. The status of each original lot remains constant while you maintain target lot header details.

You can use this if part of a lot has failed QA and you need to freeze it, whilst the remainder of the lot was of a good quality and should remain in an available status.

For Catchweight items, you can also transfer the secondary values. There are three different processes:

- When the entire balance is transformed and the entire secondary is also assigned to the new lot, batch or serial number, so it does not need to be specified.
- For partial transformations of Catchweight type 1 and 2 items, the actual secondary value must be captured.
- For Catchweight type 3 items and items with a secondary unit of measure, the nominal secondary value is always calculated for partial and full transformations.

Record Lot Transformation Selection Screen



To display this screen, select Lot Transformation.

Use this screen to select and enter a stockroom, date, references and reason codes for transforming lots.

IN260	Z1 - GB Demonstration Company	USER GBJBA1MS	7/09/00 11:53:49
Record Lot Transformation			
Stockroom.....?..	01	Central Stockroom	
Reference type....?..	___		Date.. 7/09/00
Narrative.....	_____		
Reason code.....?..	___		
F3=Exit F4=Prompt			

Fields:

Stockroom

You must enter the code of an existing stockroom.

Reference Type

Specify the transformation type using up to three alphanumeric characters. These are defined on the Inventory descriptions file against the major type TRAN.

Date

Specify the date of the lot transformation, this defaults to today's date.

Narrative

Specify the narrative, or description, using up to twenty alphanumeric characters, associated with this lot transformation.

Reason Code

Select a reason code from those defined on the Inventory Descriptions file against the major type MOVR.



Press **Enter** to confirm the details, and again to display the Record Lot Transformation Details Screen.

Record Lot Transformation Details Screen



To display this screen, enter your selection criteria on the Record Lot Transformation Selection Screen and press **Enter** twice.

Use this screen to enter details of multiple lots you want to split or transform. The status of the original lots will remain constant, while you maintain the target lot header details.

IN262		Z1 - GB Demonstration Company		USER GBJBA1MS	7/09/00 11:53:55
Record Lot Transformation					
Stockroom..... 01		Central Stockroom			
Sel Item	Movement Qty.	From Lot	UOM	Cost/Unit	
1=Amend 3=Lot header details					
Item.....?..	_____	From lot....?..	_____	_____	
Movement qty.....	_____	To lot.....?..	_____	_____	
Quantity units....?..	_____	Cost/unit.....	_____	_____	
Narrative.....	_____	Date..	7/09/00	_____	
Reference type....?..	_____	_____			
Reason code.....?..	_____	_____			
F3=Exit F4=Prompt		F12=Previous F13=To lot details			

Fields:

Select (Sel)

Enter one of the following:

- 1 - Amend, to return details to the entry fields at the base of the screen. Modify any details and press **Enter** to accept the changes.
- 3 - Display lot header details, to display the lot header details of the lot displayed in the From/To lot column.

Movement Qty

Specify the quantity you want to subtract from the first lot and transfer to the second lot using up to eleven characters, three decimals.

From Lot

Enter the originating lot using up to fifteen alphanumeric characters. This lot must exist in your selected stockroom.

To Lot

Enter the lot to receive the transferred items using up to fifteen alphanumeric characters. This can be an existing lot or a new lot. In the case of an existing lot, the items are added to the total physical stock for that lot and the frozen or available balance as appropriate.



Press **Enter** to display the Lot Header Details Window.



*Note: If you use Catchweight, for items which are Catchweight category 1 or 2, when you first press **Enter** the Secondary Value Entry window is displayed.*

Functions:

F13=From/To Lot Details

Use this to toggle between the two lots.



Once you have completed the lot header details for this transaction, press **Enter** to validate your selection, then select **F8=Update** to process the transformation.

Lot Header Details Window



To display this window, press **Enter** on the Record Lot Transformation Details Screen.

Use this screen to view any current or default lot header details for the To Lot, so that you can amend them. The values specified here are valid for the whole lot, even if parts of the lot are located in different stockrooms.

You must complete these details to process the lot transformation.

IN262	Z1 - GB Demonstration Company	USER GBJBA1MS	7/09/00 11:54:47
Record Lot Transformation			
Stockroom..			
Sel Item			
Lot Header Maintenance Item..... HEB02 Lot reference..... HEB012 Production date..... 7/09/00 Time..... 11:52 Expiry date..... 7/09/01 Time..... 0:00 First available date.... 7/10/00 Time..... 0:00 Last available date.... 7/12/00 Time..... 0:00 Stock status.....?.. RL Released Reason code.....?.. Potency..... 60.000000 % Grade.....?.. GOOD Good Quality Suppliers lot ref..... F12=Previous F4=Prompt F21=Text			
1=Amend 3 Item..... Movement qt Quantity un Narrative.. Reference t Reason code			
F3=Exit F4=Prompt		F12=Previous F13=To lot details	

Fields:

Production Date

This is the date that of manufacture, or receipt, for this lot. The field will default to the current date but can be any previous date. If you do not enter this date, Inventory calculates it back from the expiry date using the shelf life of the item.

If you receive the lot into either Purchase Management or Production then you must enter either a production data or expiry date. If you receive the lot into Inventory the fields are not mandatory.

This only applies when you receive the item lot for the first time. Once the lot exists you cannot maintain either the production or expiry date.



Warning: The software displays the production, expiry and first and last available times if you have set the Display Lot Time field on the Lot Header Parameters Screen, in Item Maintenance to 1.

Production Time

Once you have created the lot, you cannot change this information.



Note: This field is only displayed if you selected to have time stamps for this item when you first created the lot header details.

Expiry Date

This is the date on which the shelf life of the item expires.

If you do not enter this information the software calculates this date by adding the shelf life to the production date. If you receive the lot in Purchase Management or Production then you must enter either a production or expiry date. If you receive via Inventory the fields are not mandatory.

Once the lot exists, the production and expiry dates are not maintainable. Enter a date not less than today's date. If you enter this you can calculate the production date by subtracting the shelf life from the expiry date.

Expiry Time

The time at which the shelf life of the item expires.



Note: This field is only displayed if you selected to have time stamps for this item when you first created the lot header details.

First Available Date

Enter a date, which must be greater than or equal to the production date.

Inventory will normally freeze all lots with the first available date greater than the current date. If you do not enter a date Inventory generates it by adding the release time to the production date.

First Available Time

Enter a time for memo purposes only. If the production date is equal to the first available date then the first available time must be equal to, or greater than, the production time.



Note: This field is only displayed if you selected to have time stamps for this item when you first created the lot header details.

Last Available Date

Enter a date, which must be greater than the first available date but less than or equal to the expiry date.

The Inventory freezes all lots with a last available date less than the current date if there is no stock status. Inventory will generate the date if you do not enter one.



Tip: For more information, see the Lot/Grade/Potency Introduction.

Last Available Time

Enter a time. If expiry date is equal to the last available date then last available time must be less than or equal to expiry time.



Note: This field is only displayed if you selected to have time stamps for this item when you first created the lot header details.

Status Code

Select a stock status code from those defined on the Inventory Descriptions file against major type STKS.

The stock status code is used as an override to the availability dates to determine if a lot quantity is available or classed as frozen stock.

If you leave the stock status blank, the availability dates are used to move stock in and out of the frozen stock.

You can divide stock statuses into available or unavailable using the 7 digit limit field held against the stock status description codes on the Inventory Descriptions file. If you set the seventh digit to 1, the stock status indicates that the lot is unavailable. If this last digit is set to any other value then the lot is available.

Reason Code

Enter a reason code from those defined on the Inventory Descriptions file against major type SSRC.

You must select a code, if you change the stock status code, or if it is blank initially, to indicate why you have changed the status of the lot.

Potency

This is the potency of the whole lot irrespective of which stockroom the lot is located in.



Note: This field is displayed if the Potency Required flag on the Lot Header Parameters Maintenance Screen is set to 1.



Note: Potency is a percentage, so the potency you specify here is the number of parts of active ingredient per hundred parts.

Grade

Select a grade code from those defined on the Inventory Descriptions file against the major type GRAD. This is the grade of the whole lot irrespective of which stockroom the lot is located in.



Note: This field is displayed if the Grade Required flag on the Lot Header Parameters Maintenance Screen is set to 1.

C-Of-C Reference

Enter a Certificate of Conformance reference, associated with a C-of-C defined in Advanced Order Entry, to be assigned to this lot. You enter the values for this C-of-C when you first receive the lot into Inventory.



Note: If you are using Advanced Order Entry, and you have specified that this item requires a Certificate of Conformance on the second Item Maintenance Screen, then Inventory displays a Certificates of Conformance field on the Lot Header Maintenance Screen. (See Advanced Order Entry for an explanation of Certificates of Conformance.)

Suppliers Lot Reference

Enter up to 36 alphanumeric characters to specify the lot reference allocated by the supplier.

Functions:

F21=Text

Use this function to view any existing item text. For more information, see the Item Text Window in the Inventory Management Product Guide.



*Note: When you press **Enter** to confirm these details, Inventory will redisplay the Record Lot Transformation Details Screen, with the new line displayed in the top part of the screen. The quantity units and cost per unit default from the From lot. To toggle between the From lot and the To lot select **F13=From/To Lot Details**.*



Press **Enter** to confirm these details and redisplay the Record Lot Transformation Details Screen.

Grade History Enquiry



22/INL

Use this option to view any changes to the grade details recorded against a lot, batch or serial reference for an item.

Grade History Enquiry Selection Screen



To display this screen, select Grade History.

Use this screen to select the item and lot reference numbers for which you want to view grade history details.

```
IN237                Z1 - GB Demonstration Company      User GBJBA1MS      7/09/00
                                                           11:55:49
Grade History Enquiry

Item.....?.. HEB02
Lot number.....?.. HEB012

F3=Exit            F4=Prompt
```

Fields:

Item

Enter the item reference number for the item whose grade details you want to view.

Lot Number

Enter the specific lot, batch or serial reference number of the item.



Press **Enter** to display the Grade History Enquiry Details Screen.

Grade History Enquiry Details Screen



To display this screen, enter the item code and lot number on the Grade History Enquiry Selection Screen and press **Enter**.

Use this screen to view the grade history of the lot, in date order. To modify the grade associated with this lot, use the Grade Maintenance option.

IN237	Z1 - Demonstration Company	User SP1	26/08/94 11:47:02
Grade History Enquiry			
Item.....	5020	Carton Fresh Orange Juice 1/2 Litre	
Lot number.....	B006		
Grade	Description	Date changed	User Reason
GOOD	Good Quality	26/08/94	SP1 RI
AVE	Average Quality	26/08/94	SP1 DG
GOOD	Good Quality	26/08/94	SP1 RI
F3=Exit F12=Previous F13=Lot header F14=Lot trace			

Fields:

Grade

This displays all valid grades that have been recorded against your particular item and lot reference number combinations. These codes are set up against major type GRAD in the Inventory descriptions file.

Description

This is the description of the grade codes.

Date Changed

This is the date upon which the grade change took place.

User

This is the user name of the person who last updated the lot grade.

Reason

This is the reason code attached to the grade change.

Functions:

F13=Lot Header

Use this to display the Lot Header Details Window.

F14=Lot Trace

Use this to view the Lot Trace Enquiry.



Select **F3=Exit** to exit the enquiry.

Stock Status Enquiry



23/INL

Use this enquiry to view the status of all lots associated with a particular item or stockroom. You can to select frozen or available lots, or all lots with a specific stock status code.

Stock Status Enquiry Screen



To display this screen, select Stock Status.

Use this screen to select all lots associated with an item, stockroom or subset of items.

IN244	Z1 - Demonstration Company	USER SP1	26/08/94 11:01:55
Stock Status Enquiry			
Date..... 26/08/94			
Enter any one of the following mandatory fields:			
Available.....	-	(Blank or 1)	
Frozen.....	-	(Blank or 1)	
All.....	I	(Blank or 1)	
Stock status.....?	-		
The following are optional:			
Item.....?	5013		
Lot.....			
OR			
Stockroom.....?	-		
Item FROM.....?			
Item TO.....?			
F3=Exit F4=Prompt			

Fields:

Date

The date defaults to today's date.



Note: Select one of the following four fields:

Available

Enter 1 to view stock balances and current stock status of only available stock, otherwise leave this field blank.

Frozen

Enter 1 to view stock balances and current stock status of only frozen stock, otherwise leave this field blank.

All

Enter 1 to view stock balances and current stock status of all lot controlled stock, otherwise leave this field blank.

Stock Status

Enter a stock status code using up to two alphanumeric characters to view stock balances for stock that has that stock status code. These are defined in Inventory Descriptions against the major type STKS.



Note: You can select any of these fields to restrict the scope of the enquiry.

Item

Enter a lot controlled item reference number to restrict the enquiry to this item only.

Lot

Enter a lot number, associated with the specified item. You cannot specify a lot number without first specifying the item.

Stockroom

Enter the stockroom you wish to restrict the enquiry to using a two alphanumeric character code. If left blank all stockrooms will be included in the enquiry.

Item From

Enter an item using up to fifteen alphanumeric characters. This will be the start of the range of items. If you leave the no Item To field blank, then the application will select all lot controlled items ordered alphanumerically after this item.

Item To

Enter an item using up to fifteen alphanumeric characters. This will specify the last item in the range.

If you specify a stockroom and a range of items then the enquiry will be restricted to those items within the range, in the stockroom. If you leave the stockroom blank then all stockrooms will be checked for items within the range.



Press **Enter** to display the Stock Status Enquiry
Available And Frozen Lots Screen.

Stock Status Enquiry Available And Frozen Lots Screen



To display this screen, select your enquiry criteria on the Stock Status Enquiry Screen and press **Enter**.

Use this screen to view the available and frozen stock balances and stock status codes for all lots located that fulfil the selections made on the previous screen.

IN244		NR - Neil Radford and Co. Ltd		USER GBJBA1MS		26/06/96	
						13:15:59	
Stock Status Enquiry - Available and Frozen Lots							
Stockroom.....		All Stockrooms					
Date.....		26/06/96					
Item	SR	Lot number	Available	Frozen	Status		
■ 1352_LOT	01	LOT01	233.000	.000			
- 1352_LOT	01	LOT02	645.000	12.000			
1=Lot Header details 2=Lot trace details 3=Allocations							
F3=Exit F12=Previous							
09-02 SF MW KS IM II KENB20A PET166S2							

Fields:

Select (Sel)

Enter one of the following:

- 1 - To view the Lot Header Details Window.
- 2 - To view the Lot Trace Enquiry.
- 3 - To display any allocations made against the selected lot. This option is only available if you are using Advanced Order Entry. Frozen Lots with existing allocations are marked with an * for lot header, to view the lot header details. This displays the Allocations Enquiry.



Note: The lot quantity will display in reverse image if its status is not derived from the availability date range for the lot. This can occur when the stock status is manually adjusted.



To continue, enter an option and press **Enter**.
Or:
Select **F3=Exit** to leave the enquiry.

Stock Status History Enquiry



24/INL

Use this option to view the past status of stock for a specific item and lot reference number combination.

Stock Status History Enquiry Selection Screen



To display this screen, select Stock Status History.

Use this screen to select the item and lot number combination you want to enquire upon.

IN238	Z1 - GB Demonstration Company	USER GBJBA1MS	7/09/00 11:58:25
Stock Status History Enquiry			
Item.....?.. <u>HEB02</u>			
Lot number.....?.. <u>HEB012</u>			
F3=Exit F4=Prompt			

Fields:

Item

Enter the item code for the item you want to enquire upon.

Lot Number

Enter the item's specific lot, batch or serial reference number you want to enquire upon.



Press **Enter** to display the Stock Status History Enquiry Details Screen.

Stock Status History Enquiry Details Screen



To display this screen, and enter the item and lot number on the Stock Status History Enquiry Selection Screen and press **Enter**.

The item reference number, item description and lot number specified on the previous screen are displayed at the top of this screen. When you enter the stock status enquiry, summary information is displayed. This includes

- Stock status and description.
- Stockroom where the lot is located.
- Stock balances that are affected by changes in the stock status.
- Available stock, frozen stock and the net change in the two balances.

IN238	Z1 - Demonstration Company	USER SP1	26/08/94 12:19:44
Stock Status History Enquiry			
Item.....	5013	Muesli Bar Honey High Fibre	50g
Lot number.....	B009		
----- Affected Stock Balance -----			
Stock		Available	Frozen
Stat. Description	SR	Stock	Stock
FZ Frozen	01	.000	25.000
RL Released	01	10.000	.000
F3=Exit F12=Previous F13=Detail/Summary F14=Lot Detail F15=Lot Trace			

Functions:

F13=Detail/Summary

Use this to toggle between detail and summary information.

F14=Lot Detail

Use this to Lot Header Details Window for this lot.

F15=Lot Trace

Use this to view the Lot Trace Enquiry for this lot.




Select **F3=Exit** to leave the enquiry.

Potency Enquiry



25/INL

Use this option to view any potency details recorded against a specific item and stockroom combination.



```
IN232                Z1 - GB Demonstration Company        USER GBJBA1MS        7/09/00
                                                                12:12:47

Potency Enquiry

Item.....?.. HEB02
Stockroom.....?.. 01

F3=Exit            F4=Prompt
```

Press **Enter** to display the Potency Enquiry Details Screen.

Potency Enquiry Details Screen



To display this screen, enter a stockroom and item on the Potency Enquiry Selection Screen and press **Enter**.

Use this screen to view the actual and previous level of potency for the selected lot. Both the item and lot number are displayed at the top of the window, with the associated information displayed in date order, by stockroom, underneath.

IN232	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	26/06/96
			13:17:20
Potency Enquiry			
Item.....	1352_LOT	Mitchelson Compound	
Stockroom.....	01	Neil's Stockroom 01	
Lot number	Potency %	Quantity	Total potent units
- LOT01	95.00000	233.000	221.350
- LOT02	75.00000	657.000	492.750
1=Potency history 2=Lot header details 3=Lot trace enquiry			
F3=Exit F12=Previous			
09-02	SP	MW	KS
IM	II	KENB20A	PET166S2

Fields:

Select (Untitled)

Enter one of the following:

- 1 - To display the Potency History Enquiry Window for this lot.
- 2 - To view the Lot Header Details Window for the selected lot.
- 3 - To view the Lot Trace Enquiry for the selected lot.

Lot Number

This displays the lot number references associated with your selected item

Potency %

This displays the current potency of the lot.

Quantity

The quantity of the item in the lot.

Total Potent Units

This displays the total potent units for your selected lot. Inventory calculates this as:
Quantity x Current Potency % = Total Potent Units.



Note: Potency is a percentage, so the potency displayed here is the number of parts of active ingredient per hundred parts.



Select your enquiry criteria, and press **Enter** to continue.

Potency History Enquiry Window



To display this screen, enter 1 against a Lot and press **Enter** on the Potency Enquiry Screen.

The item reference number, item description and lot number are displayed at the top of the screen, with the following information in date order:

- Date of change in the level of potency for the batch.
- New potency.
- The quantity affected by the change in potency.
- Resulting potent units (Quantity Affected x Potency %= Resulting Potent Units).
- The Reason code for the change in potency. This is defined in Inventory Descriptions against the major type MOVR.

If you want to amend the potency of part of a batch, select Lot Transformation.

```
IN232                NR - Neil Radford and Co. Ltd      USER GBJBA1MS    26/06/96
                                      13:17:20

Potency Enquiry

Item..... 1352_LOT          Mitchelson Compound
Stockroom..... 01          Neil's Stockroom 01

  Lot
  1 LOT0
  1 LOT0

    Potency History Enquiry

    Item..... 1352_LOT          Lot number..... LOT02
    New
    Date          Potency %      Quantity      Resulting
    26/06/96      75.00000      657.000      Potent units
    26/06/96      80.00000      671.000      492.750
                                      536.800
                                      Reason
                                      01

                                      Bottom
    F12=Previous

1=Potency history  2=Lot header details  3=Lot trace enquiry
F3=Exit           F12=Previous

09-02    SF    MW    KS    IM    II  KENB20A  PET166S2
```



Select **F12=Previous** to redisplay the previous screen.

Lot Trace Enquiry



26/INL

Use this option to follow the receipt and issue of items associated with a particular lot, as well as identifying where a lot has been moved between stockrooms.

Lot Trace Enquiry Selection Screen



To display this screen, select Lot Trace.

Use this screen to select the Item and the Lot you want to trace.

```
IN800          NR - Neil Radford and Co. Ltd   User GBJBA1MS   26/06/96
                                                    13:19:50

Lot Trace Enquiry

Item.....?.. █
Lot.....?..
Stockroom.....?..
From date..... 0/00/00
To date..... 0/00/00
Movement type....?.. _

F3=Exit      F4=Prompt

05-23      SF      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Item

Enter the item whose lot you want to trace using up to 15 alphanumeric characters.

Lot

Enter the lot number for the item using up to 15 alphanumeric characters.

Stockroom

Enter the stockroom you want to view using up to two alphanumeric characters.

Date Range

Enter a range of dates to restrict the display of movements.



Note: If you specify a date range, then the From date must be less than the To date. If you do not specify a To date, then it will default to the From date.

Movement Type

Enter a single alphanumeric character code from those defined on the Inventory Descriptions file against the major type MVTP.



Press **Enter** to display the Lot Trace Enquiry Details Screen.

Lot Trace Enquiry Details Screen



To display this screen, select an item, lot and Movement combination on the Lot Trace Enquiry Selection Screen and press **Enter**.

Or:

Enter 3 in the Select field on the Item/Stockroom Lot Details Screen and press **Enter**.

Use this screen to view the receipts and issues of the selected item and lot combination. The item and lot details are displayed at the top of the screen.

IN801	Z1 - GB Demonstration Company	User GBJBA1MS	7/09/00
			12:14:05
Lot Trace Enquiry			
Item/Lot.. HEB02		HEB012	Batch Controlled Item
Stockroom.. 01 Central Stockroom			
Sel	Date	Type	Order/Reference
-	7/09/00	Trans.	HEB012
		Customer/	Supplier Issue Units BX
			10.000
1=Movement details 2=Order enquiry 3=Forward/Backward			
F3=Exit F12=Previous F13=Lot header details F15=Potency history			

Fields:

Select (Sel)

Enter one of the following:

- 1 - To display the Inventory Movements - Summary. For more information see Inventory Movements - Summary Screen.
- 2 - To display the Order Enquiry Screen. For more information, see Order Enquiries.
- 3 - To display the Forward/Backward lot trace.

Date

This is the date of the receipt or issue for each lot.

Type

This is the type of transaction carried out for this item.

Order/Reference and Sub-Reference

This is the reference recorded for a transaction.



Note: You can use up to 33 characters to create the reference for works order-less production transactions (codes M, N and W). In this case the reference is made up as follows:

I = Item reference of up to 15 characters

R = Route code of 1 character (with a space either side)

F = Work-in-Progress Lot Number of up to 15 characters

Customer/Supplier

This is the customer or supplier associated with the transaction. This information is taken from the Sales Order for a customer and the Purchase Order for a supplier.

Quantity

The amount of items associated with this lot/transaction, displayed in the primary unit of measure.

If you are using Catchweight, select **F9=Quantity (or Short Description)** to display the amount of items in either the primary unit of measure or the secondary unit of measure.

Functions:

F9=Quantity/(Short Description)

This is a toggle function that is only displayed when Catchweight is used for this company.

Select **F9=Quantity** to display the quantity of the item in the Quantity fields in the primary unit of measure.

Select **F9=(Short Description)**, where (Short Description) is the 9 character description of the secondary unit of measure, to display the quantity of the item in the (Short Description) secondary unit of measure.

F13=Lot Header Details

Use this to toggle between lot details.

F15=Potency History

Use this to view the Potency History Enquiry.



Select an item with a 1, 2 or 3 to enquire on further details for your chosen item and press **Enter** to continue.

Forward/Backward Trace Window



To display this window, enter 3 against an item on the Lot Trace Enquiry Details Screen and press **Enter**.

Use this window to display production orders and receipts for your chosen item. Use **F13=Transformations From** or **F13=Transformations To** to toggle between both depending on which details are displayed at the time. Use the Backwards trace to display component issues associated with a works order receipt, and the Forwards trace to display finished goods receipts associated with a works order issue.

```

IN801          Version 3 Demonstration Company   User STDFIN      2/02/00
                                           16:43:11

Lot Trace Enquiry

Item/Lot.. 50311          WBPC01          Paracetamol 250 tabs/box
Stockroom. 01 Central Stockroom

Sel Date  Type  Order/Reference  Sub-Reference  Customer/
Supplier Quantity
- 27/01/00 Receipt                10.000
- 27/01/00 Receipt                1.000
- 27/01/00 Iss
- 2/02/00 Iss
- 2/02/00 Iss
3 2/02/00 Tra

Lot Transformations "To"
New Lot..... WBPC02
Item          Lot          Date    Quantity
- 50311       WBPC02       2/02/00  1.000

1=Select
1=Movement det  F12=Previous F13=Transformations "From"
F3=Exit  F12=Previous F13=Lot header details F15=Potency history
  
```

Fields:

Select (Untitled)

Enter 1 to display the receipt or order you want to view.

Functions:

F13=Transformations From/To

Use this to toggle between issues and receipts recorded for this item.



Select **F3=Exit** to exit the enquiry.

Lot Header Defaults Audit Report



31/INL



Select Lot Header Defaults Audit.

This report provides a hard copy print of the header defaults for each lot controlled inventory item.

The information printed is the current default header details for each item, with additional entries of any changes made to the header details since this audit report was last run.



There are no selection criteria involved in this option, select **F8=Submit** to submit the report.

Shelf Life Report



32/INL



To display this screen, select Shelf Life.

Use this report to print details of lots in a stockroom that are frozen or available on a specified date.

```
IN250          Version 3 Demonstration Company    USER STDFIN    2/02/00
                                                    16:45:04

Shelf Life Report

Date..... 2/02/00

Enter any one of the following mandatory fields:

Available..... _ (Blank or 1)
Frozen..... _ (Blank or 1)
All..... _ (Blank or 1)   Include zero lots..... @ (0/1)
Stock status.....?.. _

The following are optional:

Item.....?.. _____
Lot..... _____
      OR
Stockroom.....?.. _
Item FROM.....?.. _____
Item TO.....?.. _____

F3=Exit      F4=Prompt      F8=Submit
```

Fields:

Date

The date defaults to today's date.

Available

Enter 1 to print stock balances and current stock status of only available stock, otherwise leave this field blank.

Frozen

Enter 1 to print stock balances and current stock status of only frozen stock, otherwise leave this field blank.

All

Enter 1 to print stock balances and current stock status of all lot controlled stock, otherwise leave this field blank.

Include Zero Lots

Enter 1 to print zero lot balances, otherwise leave this field blank.

Stock Status

Enter a two alphanumeric character code from those defined in Inventory Descriptions against the major type STKS if you want to print stock balances for stock that has the particular stock status code specified.

You can then select some of these additional fields to restrict the scope of the report.

Item

Enter a lot controlled item reference number to restrict the report to this item only.

Lot

Enter a lot number, associated with the item specified above. The lot field cannot be specified independently of the item field. An entry in this field will restrict the enquiry to that lot only.

Alternatively you can use some of the following fields.

Stockroom

Enter the stockroom you wish to restrict the report to using up to two alphanumeric characters. If left blank all stockrooms will be included in the report.

To restrict the scope of the report you may select a range of items.

Item From

Enter an item using up to fifteen alphanumeric characters. This will be the item from which items will be selected. If no Item To field is specified, then the application will select all lot controlled items ordered alphanumerically after this item.

Item To

Enter an item using up to fifteen alphanumeric characters to specify the last lot controlled item in the range.

If a stockroom is specified and a range of items specified the report will be restricted to those items within the range, in the stockroom. If the stockroom is left blank then all stockrooms will be checked for items within the range.



Select **F8=Submit** to submit the report to print.

-
-
-
-
-

Chapter 6

Packaging Requirements

Introduction To Packaging Requirements

You can use Packaging Requirements to both analyse and report on packaging information. This information will help you to produce the packaging statistics that you need to submit to the appropriate authority. You can use the information produced to complete the standard documentation provided by these authorities.

You use Packaging Requirements to enter information about the quantity of each type of packaging that you use when you ship a product to a domestic customer over a specific period.

Setting Up Packaging Requirements

Before you can track the packaging used you need to set up the following:

For each Style Inventory Company you must:

- Set the Packaging Reporting Flag on the Maintain Company Profile Screen.
- Set up the Packaging Reporting Country.
- Set the Packaging Reporting Flag on each item you need to track the packaging details.

For each Packaging Reporting Country you must create:

- Packaging categories.
- Packaging codes.
- Average packaging details per despatch.
- Default responsibilities.

You also need to set up the packaging details for each item that you want to track.

Country Details Maintenance



1/INK

Use this to maintain the data and reporting parameters for each country which needs to submit a packaging report. The information you can enter includes:

- Packaging Responsibilities. To apportion the responsibility for each member of the supply chain.
- Default Responsibilities. To define percentage responsibilities when you are tracking responsibilities.



Note: You can define default responsibilities, but they do not become effective until you switch on Track Responsibilities Processing.

- Packaging Categories. To define summary groups for the packaging used so that you can provide totals by surface area, weight, volume or any other classification.
- Packaging Codes. These could relate to packaging materials, for example, glass, cardboard, wood, or to individual packaging, for example, glass bottle (25cl), glass bottle (33cl).



Note: Before you set up any of the reporting parameters, you must set the Packing Reporting Flag on the Maintain Company Profile Screen.

Maintain Packaging Reporting Countries Selection Screen



Select Country Details (Maintenance).

Use this window to select the Packaging Reporting Country you want to maintain.

IN345	Z1 - GB Demonstration Company	User GBJBA1MS	2/10/00
			16:16:53
Maintain Packaging Reporting Countries			
Country	Description	Format	Year
Period			
_ GB	United Kingdom		98
			01 of 12
2=Amend 4=Delete			
F3=Exit F10=Add country F19=Position to			

Fields:

Select (Untitled)

Enter one of the following:

2 - Amend. To alter the details for the reporting country.

4 - Delete. To delete the details for the country.

Functions:

F10=Add Country

Use this to define a new reporting country for the current Inventory Company.

F19=Position To

Use this to position the screen display to the country selected.



Select **F3=Exit** to leave the screen without making any changes.

Maintain Packaging Reporting Country Detail Screen



To display this screen, enter 2 in the untitled field on the Maintain Packaging Reporting Countries Selection Screen.

Or:

Select **F10=Add Country** on the Maintain Packaging Reporting Countries Selection Screen.

Use this screen to enter new details and change existing details for the selected packaging reporting country.

IN345	Z1 - UK Demonstration Company	User GBJBA1MS	7/10/97 10:37:25
Maintain Packaging Reporting Country			
Country.....	DE	Germany	
Reporting Frequency.....	1	(1=Monthly, 2=Quarterly)	
Reporting Format.....?		Blank, Valid format	
Track Responsibilities.....	1	(0/1)	
Calendar Code.....?	P1		
Current Year.....	97		
Current Period.....	01	of 12	
Reporting Currency.....?	GBP	Pounds Sterling	
Reporting VAT Code.....?	000		
Reporting Address.....	Address		
Target Recovery.....	20.00	%	
Target Recycling.....	40.00	%	
F3=Exit F4=Prompt F8=Update F11=Delete Country F12=Previous			
F13=Responsibilities F14=Packaging Codes F24=More keys			
6-31	SA	MW	KS CL IM DM II STUD140 KB PKH318S1

Fields:

Country

Enter the country code.

If you select to amend existing country details then this field is for your information only, you cannot change it.



Note: You can only set up one set of packaging reporting details for each country.

Reporting Frequency

Enter one of the following to define how often you need to produce the report:

1 - Monthly. This is the default value for this field.

2 - Quarterly.

Reporting Format

Enter a valid report format or leave this field blank to use the standard report format.



Note: You can define a report format using the descriptions file code GDFT.

Track Responsibilities

Enter one of the following:

- 0 - If you have total responsibility for the packaging.
- 1 - To track responsibilities throughout the supply chain.



Note: If you are using the German Duales report format, you must set the Track Responsibilities to 0.

Calendar Code

Enter the code for the calendar used by this reporting country.

Current Year

Enter the current year. This defaults to the current year for the Inventory company.
When you amend existing country details this field is for information only.

Current Period

Enter the current period. This defaults to the first period of the current year.
When you amend existing country details this field is for information only.

Reporting Currency

You must enter a reporting currency that is valid within General Ledger.
If you use World Trade, this field defaults to the reporting currency specified for this country.

Reporting VAT Code

You must enter a valid VAT Code.

Reporting Address

You must enter the address where you need to submit your packaging data.

Target Recovery and Target Recycling

Enter the Target Recovery and Target Recycling Percentage.
You use these fields when tracking responsibilities to compound with the derived responsibility. For example, if the amount of packaging you must recover is 25Kg, and you have set Recovery to 40% with Recycling set to 8%, you must recover 10Kg of packaging and recycle 2Kg of packaging during this period.

Functions:

F13=Responsibilities

Use this to maintain the packaging responsibilities incurred by the members of the supply chain.



Note: Responsibilities are only effective if you have set Track Responsibilities to 1.

F14=Packaging Codes

Use this to define the packaging codes applicable in this country.

F15=Average Packaging

Use this to maintain the average packaging details to be included on each despatch line.

F16=Packaging Categories

Use this to maintain the packaging categories used by the countries to which you need to submit the report.



Tip: If all the functions are not available, select **F8=Update** to save the information. The rest of the functions will then be available.



Select **F8=Update** to validate and save the information entered. Then select **F12=Previous** to return to the Maintain Packaging Reporting Country Selection Screen.

Maintain Responsibilities Window



To display this window, select **F13=Responsibilities** on the Maintain Packaging Reporting Country Detail Screen.

Use this window to change the packaging responsibilities for the members of the supply chain. You can do this if you have selected to Track Responsibilities through the supply chain on the Maintain Packaging Reporting Screen.

```

IN345                Z1 - UK Demonstration Company      User GBJBA1MS      7/10/97
                                                           11:32:18
Maintain Packaging Reporting Country

Maintain Responsibilities
Country      GB      United Kingdom

Country      GB      United Kingdom
Rep          1      Extractor      .00      1
Rep          2      Manufacturer    .00      1
Rep          3      Filler          .00      1
Rep          4      Retailer        .00      1
Rep          5      Consumer        .00      1
Rep

1=Select  4=Delete
? _      _      .00      _

Tar F4=Prompt F8=Update F12=Previous
Target Recycling..... 40.00 %

F3=Exit F4=Prompt F8=Update F11=Delete Country F12=Previous
F13=Responsibilities F14=Packaging Codes F24=More keys

```

Fields:

Select (Untitled)

Enter one of the following:

- 1 - Select, to select the item. The item details transfer to the fields at the bottom of the window so you can change the Responsibility % and Default.
- 4 - Delete, to remove the current item. You cannot delete the item if you have set responsibility overrides.

Responsibility %

Enter the percentage responsibility for each member of the supply chain.

The total responsibility for the supply chain cannot exceed 100% for either recycling or recovery.



*Note: If the total responsibility does not equal 100%, you get a warning message when you select **F8=Update**. Clear the message and then select **F8=Update** again to validate and save the changes.*

DFT

Enter one of the following:

0 - To exclude this responsibility code from calculations.

1 - To include this responsibility code in calculations.



Select **F8=Update** to validate and save the information. Then select **F12=Previous** to return to the Maintain Packaging Reporting Country Detail Screen.

Packaging Codes Details Screen



To display this screen, select **F14=Packaging Codes** on the Maintain Packaging Reporting Country Detail Screen.

Use this screen to define the packaging codes used for the current country.

IN351	Z1 - UK Demonstration Company	User GBJBAIMS	7/10/97 11:47:58
Packaging Details			
Country DE Germany			
Pack	Packaging	UoM	Fees
Code	Description	Category	VAT
A1	CARDBOARD BOXES	VOLUME BASED	M3 000
A2	SHRINKWRAP	SURFACE AREA	CM 000
			1.500000
			.250000
2=Amend 4=Delete			
F3=Exit F6=Add F12=Previous			

Fields:

Select (Untitled)

Enter one of the following:

- 2 - Amend, to alter the packaging code definition.
- 4 - Delete, to remove the packaging code definition.

Functions:

F6=Add

Use this to add new packaging code definitions.



Select an option and press **Enter**.

Add Packaging Details Window



To display this window, enter 2 in the Untitled field on the Packaging Codes Details Screen.

Or:

Select **F6=Add** on the Packaging Codes Details Screen.

Use this window to alter the details of the selected packaging details.



Note: If you amend an existing packaging detail, the title of the window changes to Amend Packaging Details.

IN351	Z1 - UK Demonstration Company	User GBUBAIMS	7/10/97 10:41:14
Packaging Details			
Country	DE	Germany	
Pack Code	Packaging Description	Category	UoM VAT Fees
No packaging details have been defined for this country.			
Add Packaging Details Packaging Code..... 01 CARDBOARD BOXES Category.....?.. 3 VOLUME BASED M3 VAT Code.....?.. 000 Fee..... 1.500000 F4=Prompt F8=Update F12=Previous			
F3=Exit F6=Add F12=Previous			

Fields:

Packaging Code

Enter a packaging code that is unique within this country. Enter a description for the packaging code.



Note: If you amend the packaging code definition you cannot change the packaging code but you can change the description.

Category

Enter the category of the packaging. The categories can be user defined, see Maintain Packaging Categories for more information.

VAT Code

Enter the VAT Code for the packaging. You only need to do this in Germany.

Fee

Enter the fee for the packaging. You only need to do this in Germany.



Press **Enter** and then select **F8=Update** to validate and save the information. Then select **F12=Previous** to return to the Packaging Codes Details Screen.

Average Packaging Details per Despatch Screen



To display this screen, select **F15=Average Packaging** on the Maintain Packaging Reporting Country Detail Screen.

Use this screen to select average packaging details per despatch.



Tip: You can use this panel to represent packaging used in small quantities on every despatch, for example, Shrink-wrap.

IN344		Z1 - UK Demonstration Company		User: GBJBA1MS	7/10/97
					12:21:11
Average Packaging Details per Despatch					
Country DE Germany					
Pack Code	Packaging Description	Category	UoM	Units Per Despatch	M
A1	CARDBOARD BOXES	VOLUME BASED	M3	3.000000	1
A2	SHRINKWRAP	SURFACE AREA	CM	2.000000	0
2=Amend 4=Delete F3=Exit F6=Add F12=Previous					

Fields:

Select (Untitled)

Enter one of the following:

2 - Amend. To alter the average packaging details for the packaging code.

4 - Delete. To delete the average packaging details for the packaging code.

Functions:

F6=Add

Use this to add average despatch packaging details.



Select **F12=Previous** to return to the Maintain Packaging Reporting Country Detail Screen.

Add Average Packaging Details Window



To display this window, enter 2 in the Untitled field on the Average Packaging Details per Despatch Screen.

Or:

Select **F6=Add** on the Add Average Packaging Details Per Despatch Screen.

Use this window to amend the selected average packaging details per despatch.

IN344	Z1 - UK Demonstration Company	User GBJBA1MS	7/10/97
			12:20:16
Average Packaging Details per Despatch			
Country	DE	Germany	
Pack Packaging			
Code Description	Category	UoM	Units Per Despatch
_ A1 CARDBOARD BOXES	VOLUME BASED	M3	3.000000
			M
			D
			1

Add Average Packaging Details

Packaging Code.....?..

Category.....

Units per Despatch..... .000000

Multiply or Divide..... 0 Multiply

F4=Prompt F12=Previous

2=Amend 4=Delete

F3=Exit F6=Add F12=Previous

Fields:

Packaging Code

Enter the packaging code.

Units Per Despatch

Enter the average number of units of packaging that you use for each despatch.

Multiply Or Divide

Enter one of the following:

0 - To multiply the despatch quantity by the units per despatch to get the total units used.

1 - To divide the despatch quantity by the units per despatch to get the total units used.



Press **Enter** to validate the information, then select **F8=Update** to save. Select **F12=Previous** to display the Packaging Codes Details Screen.

Maintain Packaging Categories Window



To display this window, select **F16=Packaging Category** on the Maintain Packaging Country Screen.

Use this window to maintain the packaging categories for the selected packaging reporting country.

IN345 Z1 - UK Demonstration Company User GBUBAIMS 7/10/97 10:37:58

Maintain Packaging Reporting Country

Country. DE Germany

Country	Category	Description	Unit
1		WEIGHT BASED	KG

1=Select, 4=Delete

2 SURFACE AREA ? PC

F4=Prompt 12=Previous

Target Recovery..... 20.00 %

Target Recycling..... 40.00 %

F15=Average Packaging F16=Packaging Categories F24=More keys

9-15 SA MW KS CL IM DM II STUD140 KB PKH318S1

Fields:

Select (Untitled)

Enter one of the following:

1 - Select, to select the packaging category. It is transferred to the fields at the bottom of the screen so you can amend the details.

4 - Delete, to remove the packaging category.

Description

Enter a description for the packaging category.

Unit

Optionally, enter the unit of measure for the selected packaging category.

Add Packaging Categories

Use the line entry fields at the bottom of the window to add a new packaging category. Enter a new unique Category Code at the bottom left of the window, then enter a Description and Unit. To accept and validate the information press **Enter**.



Press **Enter** to validate the data, then select **F12=Previous** to display the Maintain Packaging Country Detail Screen.

Item Details Maintenance



2/INK

Use this to define country specific information about the packaging that you need for each item. You can condition the packaging definition for an item dependent on the quantity despatched. For example:

Beer:

Per litre = 50 grams aluminium.

Per 10 litres = 500 grams aluminium + 2 grams plastic + 4 grams cardboard.

Per 100 litres = 5000 grams aluminium + 20 grams plastic + 40 grams cardboard + 1 kg wood pallet.



Note: Before you can define the packaging information you need to set the Packaging Reporting Flag in the Item Maintenance screen.

Country Item Packing Details Selection Screen



Select Item Details (Maintenance).

Use this screen to select the item whose packing details you want to maintain.

IN352	Z1 - UK Demonstration Company	User GBJBA1MS	8/10/97 9:10:38
Country Item Packaging Details			
Item...?. AHIGDI			
Country.?. ____		(leave blank for all)	
F3=Exit F4=Prompt			

Fields:

Item

Enter the Item code.

Country

Enter the country you are defining the packaging for.



Tip: If you leave this field blank and press **Enter**, the software displays a list of all the available packaging countries. Select the country you require.



Note: If you have not defined packaging details, select **F6=Add** to display the Enter Item Packaging Window, then select the country. For more information, see Enter Item Packaging Details Window.



Enter an Item Code and a Country Code, and then press **Enter** to display the Country Item Packaging Codes Details Screen.

Country Item Packaging Codes Details Screen



To display this screen, enter an Item Code and Country Code on the Country Item Packaging Details Selection Screen, and press **Enter**.

Use this screen to enter or amend the Item Packaging details.

IN352	Z1 - UK Demonstration Company	User GBJBA1MS	8/10/97
			9:11:45
Country Item Packaging Details			
Item.....	AHIGDI	GDI	
Country.....	DE	Germany	
Issue Unit.....	EA	Single of	
Packaging Details per Issue Unit			
Pack Code	Packaging Description	Category	Packing Units M
A1	CARDBOARD BOXES	VOLUME BASED	1.500000 0
A2	SHRINKWRAP	SURFACE AREA	2.300000 1
2=Amend 4=Delete			
F3=Exit F6=Add F8=Update F12=Previous F16=Quantity Breaks			
F17=Responsibilities F18=Select Country			

Fields:

Select (Untitled)

Enter one of the following:

- 2 - Amend, to alter the packaging details.
- 4 - Delete, to delete the packaging details.

Functions:

F6=Add

Use this to add new packaging details.

F16=Quantity Breaks

Use this to add new despatch quantity breaks.

F17=Responsibilities

Use this to define the recycling and recovery responsibilities of each member of the supply chain.

F18=Select Country

Use this to select a new country to define packaging information for this item.



Tip: If this function is not available, select **F21=Issue Units** to return to the issue units display.

F21=Issue Units

Use this to display the Packaging Details per Issue Unit. You can only use this when the packaging details per quantity breaks are displayed.



Select **F8=Update** to validate the information.
Then select **F12=Previous** to display the Country Item Packaging Details Selection Screen.

Select Additional Packaging Quantity Breaks Window



To display this window, select **F16=Quantity Breaks** on the Country Item Packaging Codes Details Screen.

Use this window to select quantity breaks you want to display the packaging details for. You can also:

- Add packaging details for a new quantity break.
- Display the packaging details for existing quantity breaks.

For example, if you have defined the issue unit for a bottled beer as cases. But the item can also be packaged in cardboard cases, with twelve bottles per case. It can also be stocked in pallets with ten cases per pallet, shrink wrapped in polythene.

In this instance, you would need to create packaging quantity breaks for:

- One issue unit, in this example, one case. The packaging details would be twelve bottles and one case.
- Ten issue units or one pallet. The packaging details would be ten cases, one pallet and one unit of polythene shrink wrap.

IN352	Z1 - UK Demonstration Company	User GBUBAIMS	8/10/97 9:14:19
Country Item Packaging Details			
Item.....	AHIGDI	GDI	
Country.....	DE	Germany	
Issue Unit.....	EA	Single of	
Packaging Details per Issue Unit			
Pack Code	Packaging Description	Quantity (EA)	More:
- A1	CARDBOARD BOXES	- 1	
- A2	SHRINKWRAP	- 20	
			New Break
			F6=Add F12=Previous

2=Amend 4=Delete
F3=Exit F6=Add F8=Update F12=Previous F16=Quantity Breaks
F17=Responsibilities F18=Select Country

Fields:

Select (Untitled)

Enter 1 to select the quantity break you want to display the item packaging details for. The Country Item Packaging Codes Details Screen is displayed showing the packaging details for the specified quantity break.



*Note: Select **F21=Issue Units** to display the Country Item Packaging Codes Details Screen for the Issue Unit.*

Functions:

F6=Add

Use this to add the packaging details for a new quantity break.



To display the Enter Item Packaging Details Window, select **F6=Add**, then enter a quantity break figure in the New Break field and press **Enter**.

Override Responsibilities Window



To display this window, select
F17=Responsibilities on the Country Item
Packaging Codes Details Screen.

Use this window to override the country default packaging responsibilities at the item level.

```

IN352                Z1 - UK Demonstration Company    User GBJBAIMS    8/10/97
                                           9:16:27

Country Item Packaging Details

Item..... AHIGDI      GDI
Country..... DE        Germany

Issue Unit..... EA      Single of

P Override Responsibilities
  Item..... AHIGDI      GDI
  Country.... DE        Germany
  More:
  Resp      Responsibility
  1 Extractor          1
  2 Manufacturer       1
  3 Filler             1
  4 Retailer           1
  5 Consumer           1

2 F8=Update F12=Previous
F3=Exit F6=Add F8=Update F12=Previous F16=Quantity Breaks
F17=Responsibilities F18=Select Country
  
```

Fields:

Responsibility

Enter one of the following:

- 0 - To exclude the item from the responsibility calculations.
- 1 - To include the item in the responsibility calculations.



Select **F8=Update** to display the Country Item
Packaging Codes Details Screen.

Packaging Reporting Country Selection Window



To display this window, select **F18=Select Country** on the Country Item Packaging Codes Details Screen.

Use this window to select a new packaging reporting country.

IN352 Z1 - UK Demonstration Company User GBJBA1MS 8/10/97
10:30:31

Country Item Packaging Details

Item..... AHIGDI GDI
Country..... DE Germany
Issue Unit..... EA

Packaging Details per Iss

Pack	Packaging Code	Description
- A1	CARDBOARD	BOXES
- A2	SHRINKWRAP	

2=Amend 4=Delete
F3=Exit F6=Add F8=Updat
F17=Responsibilities F18=Select Country

Packaging Reporting Country Selection

1	Country	Description	More:
☒	DE	Germany	
☐	GB	United Kingdom	

Position to: ____

F5=Refresh F12=Cancel

Fields:

Select (Untitled)

Enter 1 to select the country you want to define.



Note: If you have no Item Packaging details set up for the country selected, the Enter Item Packaging Details Window is displayed.



To display the Country Item Packaging Codes Details Screen, select the country.

Customer/Item Overrides



3/INK

Use this to override responsibilities for packaging on the customer item. You should use this if a specific customer varies from the norm for the sales channel to which it belongs.

You can specify the delivery sequence that the responsibility override relates to. If you do not specify the delivery sequence then the responsibility override is applied to all delivery points for the customer.



Note: Inventory uses customer item responsibility overrides regardless of the responsibility settings for Sales Channels, Country and Item.

Customer/Item Responsibility Overrides Selection Screen



Select Customer/Item Overrides.

Use this screen to select the customer and item for which you want to enter packaging overrides.

IN354	Z1 - UK Demonstration Company	User GBJBA1MS	10/10/97 11:25:12
-------	-------------------------------	---------------	----------------------

Customer/Item responsibility overrides

Country..... GB United Kingdom
Item.....?.. ALATCH
Customer.....?.. _____

F3=Exit F4=Prompt F6=Customer scan by item F12=Previous

Fields:

Country

Enter the code for the country.

Item

Enter the item code.

Customer

Enter the customer code and delivery sequence.

Functions:

F6=Customer Scan By Item

Use this to display a list of all the customers and delivery sequences that apply to the item.



To display the Override Responsibilities Window, enter a Country, Item, Customer Code and Delivery Sequence and then press **Enter**.

Selection Of Customer To Be Maintained Screen



To display this screen, select **F6=Customer Scan By Item** on the Customer/Item Responsibility Overrides Selection Screen.

Use this screen to select the customer overrides you want to maintain.

IN354		Z1 - UK Demonstration Company		User: GBJBA1MS	10/10/97
					11:26:17
Selection of Customer to be Maintained					
Item.....		AHIGDI		GDI	
Sel	Customer	Del Seq	Description		
☒	C01	000	Rover Dealership - London		
☐	MJB1	001	MARK B		
Position to.....					
1=Select					
F3=Exit F12=Cancel					

Fields:

Select (Sel)

Enter 1 to select the customer and delivery sequence you want to enter responsibility overrides for.

Position To

Use this to position the display to the specified field.



To display the Customer/Item Responsibility Overrides Screen, enter 1 in the Untitled field on the Selection Of Customer To Be Maintained Screen.

Customer/Item Responsibility Overrides Screen



To display this window, enter a Country, Item, Customer Code and Delivery Sequence on the Customer/Item Responsibility Overrides Selection Screen and then press **Enter**.

Or:

Enter 1 in the Untitled field on the Selection Of Customer To Be Maintained Screen.

Use this window to enter packaging responsibilities for the customer and item. These responsibilities override the default responsibilities set up for the packaging country.

IN354	Z1 - UK Demonstration Company	User GBJBANB4	27/12/99 16:13:32
Customer/Item responsibility overrides			
Item.....	5001	Suncream Factor 4 225ml	
Customer.....	GC01	000	Reeves Chemist's
Country.....	GB	United Kingdom	
Resp	Description	Responsibility	
1	Extractor	<u>0</u>	
2	Manufacturer	<u>1</u>	
3	Filler	<u>1</u>	
4	Retailer	<u>1</u>	
F3=Exit F8=Update F11=Delete F12=Previous			

Fields:

Responsibility

Enter one of the following:

0 - To exclude this item from the responsibility calculations.

1 - To include this item in the responsibility calculations.



Select **F8=Update** to validate the data and display the Customer/Item Responsibilities Override Selection Screen.

Sales Channel Overrides



4/INK

Use this to define packaging responsibilities for a sales channel when they vary from the default for a particular country.



Note: Inventory uses Sales Channel responsibility overrides regardless of the responsibility settings for Country and Item, but are overridden by any responsibility overrides defined for the customer.

Sales Channel Responsibility Overrides Screen



Select Sales Channel Overrides.

Use this screen to select the sales channel for which you want to enter responsibility overrides.



Note: If the company does not have sales channels defined then you cannot define Sales Channel Responsibilities overrides.

IN346	Z1 - UK Demonstration Company	User: GBJBAIMS	8/10/97 11:10:01
Sales Channel Responsibility Overrides			
Sales Channel....?..			
Country.....?..			
F3=Exit F4=Prompt			

Fields:

Sales Channel

Enter the code for the sales channel.

Country

Enter the country.

For more information, see Override Responsibilities Window (Sales Channels).



To display the Override Responsibilities Window, complete the Sales Channel and Country fields and then press **Enter**.

Override Responsibilities Window (Sales Channels)



To display this window complete the Sales Channel and Country fields on the Sales Channel Responsibility Overrides Screen and then press **Enter**.

Use this screen to enter the packaging responsibilities for the selected sales channel.

```

IN346                Z1 - GB Demonstration Company    User GBJBA1MS    3/02/98
                                      13:01:47

Sales Channel Responsibility Overrides

Sales Channel....?..  2_          Europe
Country.....?..    GB_        United Kingdom ok.

Channel.... 2          Europe
Country.... GB        United Kingdom ok.

Resp          Responsibility
1  Extractor          1
2  Manufacturer        0
3  Filler              0
4  Retailer            0

More:

F3=Exit F4=Prompt

16-46  SA  MW  KS CL IM DM II  MARVIN  KB  PET087S1
  
```

Fields:

Responsibility

Enter one of the following:

- 0 - To exclude this item from the responsibility calculations.
- 1 - To include this item in the responsibility calculations.



Select **F8=Update** to validate the data and display the Sales Channel Responsibility Overrides Screen.

Calendar Maintenance



5/INK

Use this to define and update the calendar profiles used by Packaging Requirements.

Inventory Calendar/Year Maintenance Selection Screen



Select Calendar.

Use this screen to select the calendar you want to maintain or to enter the code for a new calendar profile.

IN850	Z1 - UK Demonstration Company	User GBJBA1MS	8/10/97		
			11:15:20		
Inventory Calendar/Year Maintenance					
Sel	Code	Year	Description	Work days	Yr Start
█	C1	00		200	1/01/97
-	C1	00		200	1/01/98
-	C1	00		200	1/01/99
-	P1	97	Period Calendar for 97	261	1/01/97
Enter Calendar code: Year: Based on Calendar Profile:					
1=Select 6=Print					
F3=Exit					

Fields:

Select (Sel)

Enter one of the following:

1 - Select, to select the calendar profile you want to change.

6 - Print, to print the calendar profile.

Enter Calendar Code

Enter a code for a new calendar profile.

Year

Enter the year for the new calendar profile.

Based on Calendar Profile

You can enter the code and year of the calendar profile that you want to base the new profile upon.



To display the Inventory Calendar/Year Maintenance Detail Screen so you can add a new calendar profile, enter a Calendar Code, Year and, if you want, the profile and year the calendar should be based upon.

Or:

Enter 1 to select an existing calendar for amendment, which also displays the Inventory Calendar/Year Maintenance Detail Screen.

Inventory Calendar/Year Maintenance Detail Screen



To display this screen in Amend mode, enter 1 in the Sel field on the Inventory Calendar/Year Maintenance Selection Screen.

Or:

To display this screen in Add mode, enter a Calendar Code and Year on the Inventory Calendar/Year Maintenance Selection Screen.

Use this screen to enter details for the calendar profile you are maintaining or creating.

IN850		Z1 - UK Demonstration Company		User GBJBA1MS		8/10/97 11:20:25		
Inventory Calendar/Year Maintenance								
Calendar Code/Year.....		C1 00						
Number of Periods per Year...		12						
Normal Start Day of Week.....		1 (1=Monday 7=Sunday)						
Start Date of the Year.....		1/01/97						
Period Name		Days	Period Name		Days	Period Name		Days
1. jan	31	23	2. feb	28	20	3. mar	31	21
4. apr	30	22	5. may	31	22	6. jun	30	21
7. jul	31	23	8. aug	31	21	9. sep	30	22
10. oct	31	23	11. nov	30	20	12. dec	31	23
13.								
Template type to use.....		1 1=Standard Week 2=Cyclic Weeks 3=Period						
F3=Exit F11=Delete F12=Previous								

Fields:

Calendar Code/Year

Enter a description for the calendar profile.

Number of Periods per Year

Enter the number of periods in the year, you can enter either 12 or 13 periods.

Normal Start Day of Week

Enter one of the following:

- 1 - Monday
- 2 - Tuesday
- 3 - Wednesday
- 4 - Thursday
- 5 - Friday

6 - Saturday

7 - Sunday.

Start Date of the Year

Enter the date that the calendar year starts.

Period Names

Enter the name of each period.

Days

Enter the number of days there are in each period.



Note: This includes working and non-working days.

Template Type To Use

Enter one of the following:

- 1 - Standard Week, where you have the same working days each week
- 2 - Cyclic Week, where the working days changes over a number of weeks cycle. You can have up to a five week cycle.
- 3 - Period.



Note: This screen varies depending upon the template type you have selected.

Functions:

F11=Delete

Use this to delete the selected calendar profile.



Press **Enter** to display the second Inventory Calendar/Year Maintenance Screen. The screen that displays depends on the template type you specify here

Inventory Calendar/Year Maintenance Screen (Standard Week)



To display this screen, set the Template Type to 1 - Standard Week, then press **Enter** on the Inventory Calendar/Year Maintenance Detail Screen.

Use this screen to enter the working days in a standard week.

IN850	Z1 - UK Demonstration Company	User: GBJBA1MS	10/10/97 11:58:05
Inventory Calendar/Year Maintenance			
Calendar Code/Year.. C3 98 Calenday for 1998			
Standard Weekly Template :			
M T W T F S S			
0 0 0 0 0 0 ("0" for non working day or "1" for working day)			
Enter up to five alternative week templates with effective dates :			
M T W T F S S	From Date	To Date	
- - - - -	_____	_____	
- - - - -	_____	_____	
- - - - -	_____	_____	
- - - - -	_____	_____	
- - - - -	_____	_____	
F3=Exit F12=Previous			

Fields:

Standard Weekly Template

Enter one of the following to set up the Standard Weeks for one or more weeks.

0 - Non-working day.

1 - Working day.



Note: Use the fields at the bottom of the screen to define five alternative weekly templates if required.



Press **Enter** to validate the data you have specified, press **Enter** again to display the Inventory Calendar/Year Maintenance Holiday Detail Screen.

Inventory Calendar/Year Maintenance Screen (Cyclic Week)



To display this screen set the Template Type to 2 - Cyclic Week, then press **Enter** on the Inventory Calendar/Year Maintenance Detail Screen.

Use this screen to enter the working and non-working days when the pattern varies over more than one week.

IN850	Z1 - UK Demonstration Company	User: GBJBAIMS	10/10/97 11:58:24				
Inventory Calendar/Year Maintenance							
Calendar Code/Year.. C3 98 Calendar for 1998							
Cyclic Weeks Templates :							
M T W T F S S							
1.	1	1	1	1	0	0	("0" for non working day or "1" for working day)
2.	1	1	1	1	0	0	
3.	-	-	-	-	-	-	
4.	-	-	-	-	-	-	
5.	-	-	-	-	-	-	
Number of weeks... 2							
F3=Exit F12=Previous							

Fields:

Cyclic Weeks Templates

Set up cyclic week templates for one or more weeks.

0 - Non-working day.

1 - Working day.

Number of Weeks

Enter a value between one and five to determine the number of weeks that are in your cycle.



Press **Enter** to validate the data you have specified, press **Enter** again to display the Inventory Calendar/Year Maintenance Holiday Detail Screen.

Inventory Calendar/Year Maintenance Screen (Period)



To display this screen set the Template Type to 3 - Period, then press **Enter** on the Inventory Calendar/Year Maintenance Detail Screen.

Use this screen to enter the working and non-working days for either the 12 or 13 periods you have specified for this calendar year.

```

IN850              Z1 - UK Demonstration Company   User GBJBA1MS   10/10/97
                                                    11:57:52

Inventory Calendar/Year Maintenance

Calendar Code/Year.. C3 98 Calendaray for 1998

Period Template for Period : 1 J

      1 2 3 4 5 6 7 8 9 0      ("0" for non working day or "1" for working day)
      1 1 1 1 1 0 0 0 0 0
10. 0 0 0 0 0 0 0 0 0 0
20. 0 0 0 0 0 0 0 0 0 0
30. 0

F3=Exit F8=Skip to holidays F12=Previous
  
```

Fields:

Period Template for Period:

Set up the working day pattern for the specified period; enter one of the following:

0 - Non-working day.

1 - Working day.

Functions:

F8=Skip To Holidays

Select this to display the Inventory Calendar/Year Maintenance Holiday Detail Screen without having to enter the working day pattern for the period.



Press **Enter** to validate the data you have specified, press **Enter** again to display the Inventory Calendar/Year Maintenance Holiday Detail Screen.

Inventory Calendar/Year Maintenance Holiday Detail Screen



To display this screen either select **F8=Skip To Holidays** on the Inventory Calendar/Year Maintenance Screen (Standard Week), Inventory Calendar/Year Maintenance Screen (Cyclic Week), or Inventory Calendar/Year Maintenance Screen (Period) without maintaining the details.

Or:

Press **Enter** to validate the data you have specified on the Inventory Calendar/Year Maintenance Screen (Standard Week), Inventory Calendar/Year Maintenance Screen (Cyclic Week), or Inventory Calendar/Year Maintenance Screen (Period) and press **Enter** again.

Use this screen to define the dates of any works holidays.

IN850		Z1 - UK Demonstration Company		User GBJBA1MS		10/10/97	
						11:57:43	
Inventory Calendar/Year Maintenance							
Calendar Code C3 98 Calendar for 1998							
HOLIDAYS							
From		To		From		To	
■							
F3=Exit F8=Update F12=Previous							

Fields:

Holidays From

Enter the start date of the holiday.

Holidays To

Enter the end date of the holiday.



Select **F8=Update** to save the information and display the Inventory Calendar/Year Maintenance Screen.

Extract Data From Inventory



11/INK

Use this to extract from the Inventory Movements file the details of all issues for the selected period. The information saved to the packaging extract file and then used to create the Packaging Usage Report.



Note: You cannot extract data from closed packaging reporting periods.

Data Extract Selection Screen



Select Extract Data From Inventory.

Use this screen to select the country and period whose packaging data you want to extract.

IN355	Z1 - UK Demonstration Company	User GBJBA1MS	8/10/97 11:54:10
Data Extract Selection			
Country for Extract.....?. <u>GB</u> United Kingdom			
Period to be extracted..... <u>97</u> <u>01</u>			
F3=Exit F4=Prompt F8=Submit			

Fields:

Country for Extract

Enter the country for which you want to extract the packaging data.

Period/Quarter To Be Extracted

Enter the period/quarter for which you want to extract the packaging data.



Note: you can only extract data for the current or future periods or quarters.



Select **F8=Submit** to start the extraction process.

Update Period/Quarter



12/INK

Use this to change the current packaging reporting period or quarter and year.



Note: You should perform data extract for the current period before you change the reporting period.

Update Quarter/Year Screen



Select Update Period/Quarter.

Use this screen to select the quarter, period and year that you want to update.

IN358	Version 3 Demonstration Company	User STDFIN	3/02/00
			09:44:59
Update Period			
Country.....	GB	Great Britain	
Current Period...	06		
Current Year.....	98		
F3=Exit F8=Update F12=Previous			

Fields:

Country

Select the country whose details you want to update and press **Enter** to display the next two fields.

Current Quarter/Period

Enter the quarter/period you want to update. This defaults to the current reporting quarter/period.

Current Year

Enter the year. This defaults to the current reporting year.



Select **F8=Update**, to update the quarter or period.

Corrections And Adjustments



13/INK

Use this to enter adjustments related to the periods contained in the packaging report summary. These adjustments are shown on the German Duales Report as period 13 figures.

Corrections And Adjustments Selection Screen



Select Corrections And Adjustments.

Use this screen to select the country and period that you want to enter packaging adjustments for.

```
IN359                Z1 - UK Demonstration Company    User: GBJBA1MS    8/10/97
                                                         12:00:52

Corrections & Adjustments

Country.....?.. GB United Kingdom
Period..... 01

F3=Exit F4=Prompt
```

Fields:

Country

Enter the packaging reporting country for which there are adjustments.

Period

Enter the period for the adjustments.



Enter a Country and Period on the Corrections And Adjustments Selection Screen and press **Enter** to display the Corrections And Adjustments Detail Screen.

Corrections And Adjustments Detail Screen



To display this screen, enter a Country and Period on the Corrections And Adjustments Selection Screen and press **Enter**.

Use this screen to select the adjustment details you want to amend or add.

IN359	Z1 - UK Demonstration Company	User GBJBAIMS	10/10/97 12:20:46
Corrections & Adjustments			
Country..... DE Germany			
Period..... 01			
Packing Code	Responsibility	Category	Adjustment Quantity
■ A1 CARDBOARD BOXES	2 Manufacturer	3 VOLUME BASED	12.000000
2=Amend 4=Delete			
F3=Exit F6=Add F12=Previous			

Fields:

Select (Untitled)

Enter one of the following:

2 - Amend to select the correction you want to amend.

4 - Delete to remove the correction.

Functions:

F6=Add

Use this to add a new correction or adjustment.



Select **F6=Add** to display the Corrections And Adjustments Screen in Add mode.

Or:

Enter 2 in the untitled field, to display the Corrections And Adjustments Screen in Amend mode.

Corrections And Adjustments Screen



To display this screen in Add mode select **F6=Add** on the Corrections And Adjustments Detail Screen.

Or:

To display this screen in Amend mode enter 2 in the untitled field on the Corrections And Adjustments Detail Screen.

Use this screen to enter the adjustment details.

IN359	Z1 - UK Demonstration Company	User GBJBA1MS	8/10/97 12:01:51
Corrections & Adjustments			
Packaging Code.....?	█		
Category.....			
Responsibility.....?	█		
Quantity.....	.000000		
Adjustment Reason.....?	█		
F4=Prompt F12=Previous			

Fields:

Packaging Code

Enter the packaging code for the adjustment.

If you amending the adjustment this field is for information only.

Responsibility

Enter who has responsibility for the adjustment.

If you amending the adjustment this field is for information only.

Quantity

Enter the quantity of packaging this adjustment applies to, either a positive or negative value.

Adjustment Reason

Enter the reason for the adjustment.



Select **F12=Previous** to return to the Corrections And Adjustments Detail Screen.

Country Details Enquiries



21/INK

Use this to view the details for the packaging reporting countries.

Packaging Reporting Countries Enquiry Selection Screen



Select Country Details (Enquiries).

Use this screen to select the packaging reporting country whose details you want to display.

IN362	Z1 - UK Demonstration Company	User: GBJBA1MS	9/10/97
			10:55:52
Packaging Reporting Countries Enquiry			
Country	Description	Format	Year
DE	Germany		97
GB	United Kingdom		97
Period			
			01 of 12
			01 of 12
1=Select			
F3=Exit F19=Position to			

Fields:

Select (Untitled 1)

Enter 1 to select the country whose packaging reporting details you want to view.

Position To (Untitled 2)

Enter the country you want to display and select **F19=Position To**, to position the cursor to that line.

Functions:

F19=Position To

Use this to position the cursor at the country code you want to select.



Select the country code you want to enquire upon to automatically display the Packaging Reporting Country Enquiry Details Screen.

Packaging Reporting Country Enquiry Details Screen



To automatically display this screen, select the country you wish to view on the Packaging Reporting Countries Enquiry Selection Screen and press **Enter**.

Use this screen to view the details for the packaging reporting country. The fields in this screen are the same as in the Maintain Packaging Reporting Country Detail Screen.

N362	Z1 - UK Demonstration Company	User: GBJBA1MS	10/10/97 12:24:12
------	-------------------------------	----------------	----------------------

Packaging Reporting Country Enquiry

Country..... DE Germany
Reporting Frequency..... 1 (1=Monthly, 2=Quarterly, 3=Annually)
Reporting Format.....
Track Responsibilities..... 1 (1=Yes, 0=No)
Calendar Code..... P1
Current Year..... 97
Current Period..... 01 of 12
Reporting Currency..... GBP Pounds Sterling
Reporting VAT Code..... 000
Reporting Address..... Address

Target Recovery..... 20.00 %
Target Recycling..... 40.00 %

F3=Exit F12=Previous F13=Responsibilities F14=Packaging Codes
F15=Average Packaging F16=Packaging Categories

Functions:

F13=Responsibilities

Use this to display the packaging responsibilities for each section of the supply chain.

F14=Packaging Codes

Use this to display the defined packaging codes.

F15=Average Packaging

Use this to display the average packaging used per despatch.

F16=Packaging Categories

Use this key to display the defined packaging categories.



Select **F3=Exit** to exit the enquiry.

Responsibilities Enquiry Window



To view this window, select
F13=Responsibilities on the Packaging
Reporting Enquiry Details Screen.

Use this window to view the responsibilities set up for this packaging reporting
country.

N362		Z1 - UK Demonstration Company		User: GBJBA1MS	10/10/97
					12:24:12
Packaging Reporting Country Enquiry					
Responsibilities Enquiry					
Cou	Country	DE	Germany		
Rep					
Rep					
Tra	Resp			Responsibility %	Dft
Cal	1	Extractor		10.00	1
Cur	2	Manufacturer		70.00	1
Cur	3	Filler		20.00	1
Rep	4	Retailer		.00	1
Rep	5	Consumer		.00	1
Rep					
Tar: F12=Previous					
Target Recycling..... 40.00 %					
F3=Exit F12=Previous F13=Responsibilities F14=Packaging Codes					
F15=Average Packaging F16=Packaging Categories					



Select **F3=Exit** to exit the enquiry.

Packaging Details Enquiry Screen



To display this screen, select **F14=Packaging Codes** on the Packaging Reporting Enquiry Details Screen.

Use this window to view the packaging codes set up for this packaging reporting country.

N351	Z1 - UK Demonstration Company	User GBJBATMS	10/10/97
			12:25:21
Packaging Details			
Country	DE	Germany	
Pack Code	Packaging Description	Category	UoM VAT Fees
A1	CARDBOARD BOXES	VOLUME BASED	M3 000 1.500000
A2	SHRINKWRAP	SURFACE AREA	CM 000 .250000
F3=Exit F12=Previous			



Select **F3=Exit** to exit the enquiry.

Average Packaging Details per Despatch Enquiry Screen



To display this screen, select **F15=Average Packaging** on the Packaging Reporting Enquiry Details Screen.

Use this window to view the responsibilities set up for this packaging reporting country.

N344	Z1 - UK Demonstration Company	User GBJBA1MS	10/10/97
			12:25:39
Average Packaging Details per Despatch			
Country	DE	Germany	
Pack	Packaging		
Code	Description	Category	UoM
A1	CARDBOARD BOXES	VOLUME BASED	M3
A2	SHRINKWRAP	SURFACE AREA	CM
		Units Per	M
		Despatch	D
		3.000000	1
		2.000000	0

F3=Exit F12=Previous



Select **F3=Exit** to exit the enquiry.

Packaging Categories Enquiry Window



To display this window, select **F16=Packaging Categories** on the Packaging Reporting Enquiry Details Screen.

Use this window to view the packaging categories set up for this packaging reporting country.

N362		Z1 - UK Demonstration Company		User: GBJBA1MS	9/10/97 10:58:45
Packaging Reporting Country Enquiry					
Packaging Categories Enquiry					
Country.	Country	DE	Germany		
Reportin					
Reportin	Category	Description		Unit	
Track Re	Code				
Calendar	1	WEIGHT BASED		T0	
Current	2	SURFACE AREA		CM	
Current	3	VOLUME BASED		M3	
Reportin	4	WEIGHT BASED		KG	
Reportin					
Reportin					
F12=Previous					
Target Recovery.....		20.00 %			
Target Recycling.....		40.00 %			
F3=Exit F12=Previous F13=Responsibilities F14=Packaging Codes					
F15=Average Packaging F16=Packaging Categories					



Select **F3=Exit** to exit the enquiry.

Item Details Enquiries



22/INK

Use this to look at the packaging details for the item.

Country Item Packaging Details Enquiry Selection Screen

 To display this screen, select Item Details (Enquiry).

Use this screen to select the item and country whose details you want to view.

IN360	Z1 - GB Demonstration Company	User GBJBA1MS	2/10/00 16:28:43
Country Item Packaging Details - Enquiry			
Item.....?..	<u>HEB01</u>	Lot, Grade, Potency, CoFC etc	
Country.....?..	<u>GB</u>	United Kingdom	
F3=Exit F4=Prompt			

Fields:

Item

Enter the item code for the item whose packaging details you want to view.

Country

Enter the code for the country.

 Press **Enter** to display the Country Item Packaging Details Enquiry Screen.

Country Item Packaging Details Enquiry Screen



To display this screen, specify both the item and packaging reporting country combination on the Country Item Packaging Details Enquiry Selection Screen and press **Enter**.

Use this screen to view the packaging details for the item displayed. You can view the details for one issue unit or for the defined quantity breaks.

N360	Z1 - UK Demonstration Company	User GBJBA1MS	9/10/97
			11:00:21
Country Item Packaging Details - Enquiry			
Item.....	ALATCH	Latch Assembly for Car Boot	
Country.....	DE	Germany	
Issue Unit.....	EA	Single of	
Packaging Details per Issue Unit			
Pack Code	Packaging Description	Category	Packing Units
A1	CARDBOARD BOXES	VOLUME BASED	12.000000
A2	SHRINKWRAP	SURFACE AREA	2.000000
			M D
			1 0
F3=Exit F12=Previous F16=Quantity Breaks F18=Select Country			

Functions:

F16=Quantity Breaks

Use this to display the packaging quantity breaks.

F18=Select Country

Use this to display the packaging details for a different packaging reporting country.



Select the function you want to view, or select **F3=Exit** to leave the enquiry.

Packaging Payments Reports



31/INK

Use this report to detail the recommended packaging payments totalled by period, quarter or year. There are also sub-totals for each category and each responsibility.

Packaging Payments Report Selection Screen



To display this screen, select Packaging Payments.

Use this screen to specify the country, and period range that you want to produce this report upon.

IN364	Z1 - UK Demonstration Company	User GBJBATMS	9/10/97 11:01:48
-------	-------------------------------	---------------	---------------------

Packaging Payments Report Selection

Reporting country.....?. 81 United Kingdom
From Period..... 97 01
To Period..... 97 01

F3=Exit F4=Prompt F8=Submit

Fields:

Reporting Country

Enter the country for the payment report.

From Period/Quarter

Enter the starting period or quarter for the payment report.

To Period

Enter the finishing period or quarter for the payment report.



Select **F8=Submit** to start the report printing.

Packaging Adjustments Reports



32/INK

Use this report to show all the packaging adjustments made for the specified period or quarter.

Packaging Adjustment Report Selection Screen



To display this screen, select Packaging Adjustments.

Use this screen to specify the country and period you want to produce the report upon.

```
IN363                Z1 - UK Demonstration Company    User: GBJBA1MS    9/10/97
                                     11:02:28

Packaging Adjustments Report

Reporting Country.....?.. GB - United Kingdom
Period..... 27 01

F3=Exit  F4=Prompt  F8=Submit
```

Fields:

Reporting Country

Enter the country you want to produce the adjustment report for.

Period/Quarter

Enter the period or quarter you require the adjustment report for.



Select **F8=Submit** to start the report printing.

Packaging Usage Reports



33/INK

Use this report to print the Packaging Extract file. For more information, see Extract Data From Inventory. You can produce the Packaging Usage Report for a period, quarter or year.

Packaging Report Selection Screen



To display this screen, select Packaging Usage.

Use this screen to select the country and periods that you want to produce this report upon.

```
IN366          Z1 - GB Demonstration Company    User GBJBA1MS    3/02/98
                                     13:16:43
Packaging Report

  Reporting Country.....?.. GB United Kingdom ok.
  Current Period..... 97 03
  Advance Period..... 0 (0 or 1)
  Yearly report required.... 0 (0 or 1)

F3=Exit F8=Submit job

5-43  SA  MM  KS  CL  IM  DM  II  MARVIN  KB  PET087S1
```

Fields:

Reporting Country

Enter the packaging reporting country.

Current Period

This is the current period.

Advance Period

Enter either:

- 0 - Keep the current period open.
- 1 - Close the current period and open a new period.

Yearly Report Required

Enter either:

- 1 - To produce the yearly report.
- 2 - To not produce the yearly report.



Note: If you are producing the yearly report and you set the Advance Period flag, the year is also advanced, as long as an Inventory Data Extract has been run for every period of the year.



Select **F8=Submit Job** to run the report, and where relevant advance the period.

Managing Historical Data.

Use these options to create and delete historical data for the Packaging Extract file.

Delete Historical Data

1...
2...

42/INK

Use this to delete the historical data from the Packaging Extract file. The Packaging Extract file is produced when you run Extract Data From Inventory. For more information, see Extract Data From Inventory.

Delete Historical Data Screen



Select Delete Historical Data.

Use this screen to select the country and period of the data you are deleting.

IN368	Z1 - UK Demonstration Company	User: GBJBA1MS	9/10/97 11:03:08
Delete Historical Data			
Country.....?.. <u>83</u> United Kingdom			
Last period's data to be cleared.. <u>10</u> <u>95</u>			
Period End Date.....			
F3=Exit F4=Prompt			

Fields:

Country

Enter the packaging reporting country.

Last Periods/Quarter Data To Be Erased

Enter the last period or quarter whose data you want to erase.

Period End Date

Enter the end date of the last period you want to erase.



Press **Enter** to remove the historical data.

Create Historical Data

1...
2...

43/INK

Use this to create historical data for the specified country and quarter or period.

Create Historical Data Screen



Select Create Historical Data.

Use this screen to specify the packaging country and period or quarter of the data you are creating.

IN368	Z1 - UK Demonstration Company	User GBJBA1MS	9/10/97 11:03:35
Create Historical Data			
Country.....?.. <u>83</u> United Kingdom			
Last Quarters Data to be Created.. <u>01</u> <u>96</u>			
Period End Date.....			
F3=Exit F4=Prompt			

Fields:

Country

Enter the packaging reporting country you want to create data for.

Last Periods/Quarter Data To Be Created

Enter the last period or quarter that you want to create data for.

Period End Date

Enter the end date of the last period or quarter.



Select **F3=Exit** to exit the enquiry.

-
-
-
-
-

Chapter 7

Inventory Valuation

Inventory Valuation Introduction

There are three main features in the Inventory Valuation. These are:

- Stockroom fiscal close. Use this to close a stockroom period and open the next. You can then process all movements within a stockroom period together.
- Stock Journal report. Use this to produce a report for each stockroom at each inventory period end. You can choose to produce the report automatically as part of the Stockroom Fiscal Close.
- LIFO revaluation. Use this function to revalue stock on a Last In First Out (LIFO) basis. You would normally only run this at the year end.

You can activate Inventory Valuation company by company.

You can also enter an override cost for selected items or item groups. These costs will override all other costs for that item and group.

Valuation Descriptions Maintenance



1/INV

Use this option to create and maintain description codes for Inventory Management valuation. This option is the same as the Descriptions Maintenance option, for more information, see the Maintenance section of the Inventory Management product guide.

Costing Analysis



2/INV

Use this to manually enter an override cost for selected items or item groups. The latest or average cost to be overridden is displayed as are the start and close dates for the period or the year to date.

You can override the costs for a selected period or for the year to date for both stockroom items and stockroom valuation groups.

Costing Analysis Maintenance Selection Screen



Select the Costing Analysis (Maintenance).

Use this screen to select the stockroom, item or valuation group and period you want to enter an override cost for.

```

IN065          NR - Neil Radford's Test Company   User GBJBANER   13/12/96
                                                    15:31:47

Costing Analysis Maintenance

Stockroom.....?.. 01          Stockroom One
Item valuation group.?..      Aspirin Dispersible tablets BP 300m
Item.....?.. A1

Year..... 96
Period..... 12
Summary Level..... 1          1=Period,2=Year to date

F3=Exit F4=Prompt

12-27  SF  MW  KS  IM  II  KENB20A  PET165S2
  
```

Fields:

Stockroom

Enter the stockroom code where the item or item group is situated.



Note: You must enter a stockroom in combination with either an item or an item group.

Item Valuation Group

Enter the Item Valuation Group. Leave this field blank if you have entered an Item Code.



*Note: You can set up Item Valuation Groups in Item Maintenance by selecting **F19=Maintain Pricing Groups**.*

Item

Enter the item code. The item must be a stockroom item for the selected stockroom. Leave this field blank if you have entered an item valuation group code.

Year

Select the year in which the fiscal period to be maintained falls. This defaults to the current year.

Period

Enter the period number for the stock movement of the item that you want to enter or amend.

Summary Level

Enter one of the following:

- 1 - To override the cost for the period selected.
- 2 - To override the cost for the year to date.



Press **Enter** to accept the screen details and to display the Costing Analysis Maintenance Detail Screen.

Costing Analysis Maintenance Detail Screen



To display this screen, enter the required details on the Costing Analysis Maintenance Selection Screen 1, and press **Enter**.

Use this screen to enter the costing analysis details for the item or group, stockroom and period selected.

IN865		NR - Neil Radford's Test Company		User GJBANER		17/12/96	
						9:05:28	
Costing Analysis Maintenance							
Item.....	A1	Aspirin Dispersible tablets BP 300m					
Stockroom.....	01	Stockroom One					
Issue unit.....	BT	Bottles of					
Year/Period.....	96/10	Period					
Start date.....	1/10/96						
Close date.....	0/00/00						
Latest cost.....		.00000	0/00/00				
Average cost.....		.90000					
Average cost (last 3 periods)...		.89615					
Average cost (Period-1).....		.00000					
Average cost (Period-2).....		.00000					
Manual Cost override.....		.00000					
F3=Exit F12=Previous							
19-34	SA	MW	KS	IM	II	EDN400A	PET16SS2

Fields:

Start Date

This is the first date of the selected period.

Close Date

If you have run a period end update, then this is the end date of the period.

Latest Cost

This is the calculated latest cost.

Average Costs

The first average cost shows the average calculated for the selected period. An average over the last three periods, previous period and previous but one period are also displayed.



Note: The cost calculations may or may not include miscellaneous receipts - this depends on the setting of your company profile flag Include Miscellaneous Receipts.

Manual Cost Override

Enter a new average cost value to override the calculated average cost for the period selected.



Note: This is the value used when you select Manual Cost as the valuation method in the LIFO Revaluation Screens.



Press **Enter** to accept the new cost. This updates the manual cost and redisplay the selection screen.

Stockroom Fiscal Close



11/INV (TRIAL)

12/INV (UPDATE)

You can run the stockroom fiscal close either manually or automatically. When you are running the fiscal close in manual mode you can run either a trial or an update close.



Note: You cannot select either Stockroom Fiscal Close option unless you have defined your Inventory Company Method of Close as manual.

The two stockroom fiscal close options operate in the same way. The difference between the two is:

- Trial. Use this option to accumulate values, up to the cut-off date selected, for analysis purposes, before the final update close. This also produces a report of items selected for the trial close. You can select the level of detail of the report and the sorting order for the details.
- Update. Use this option to close either a site or selected stockrooms at the existing stock levels. The final summary stock movements are accumulated up to the entered cut-off date and the period is closed. You can choose to produce a report of the closed stock movements.



Note: You must close all stockrooms associated with the site for the previous period.

Stockroom Fiscal Close Trial Selection Screen



Select the Stockroom Fiscal Close - Trial option.

Use this to accumulate values, up to the cut-off date selected, before the final update close. This also produces a report of items selected for the trial close. You can select the level of detail of the report and the sorting order for the details.

IN855		NR - Neil Radford's Test Company		User GJBANER		19/12/96	
						8:24:59	
Stockroom Fiscal Close - Trial							
Year.....		96					
Period.....		10					
Cut-Off date.....		1/10/96					
Site.....?		SITE01		SITE01 ----->			
OR							
Stockroom.....		_		1=Range,2=List			
Primary sequence.....?		1		Item			
Secondary sequence.....?		2		Movement Date			
Report content.....		3		1=Detail,2=Summary,3=Both			
F3=Exit F4=Prompt F8=Submit							
06-33		SF		MW		KS IM II EDN400A PET16SS2	

Fields:

Year

Select the year in which the fiscal period to be closed falls. This defaults to the current year.

Period

Enter the period number for the stockroom period being closed. This defaults to the current period.

Cut-Off Date

Enter the last date for the collection of the data. This defaults to the current date.



Tip: The summary movement details are accumulated from the last time a stockroom fiscal close was run (trial or update) to the specified Cut-Off Date.

Site

If you want to include all the stockrooms in a site, enter a site code. Leave this field blank if you want to produce the report for a list or range of stockrooms.

Stockroom

Enter one of the following:

1 - Range. Use this option if you want to close a range of stockrooms.

2 - List. Use this option if you want to close a list of stockrooms.

Leave this field blank if you have entered a site.



Note: If you want to close a range of stockrooms, you must perform a fiscal close for every stockroom in the range for the previous period.

Primary Sequence

Select the primary sequence by entering one of the following:

1 - Item details.

2 - Movement date.

3 - Movement type.

Secondary Sequence

Select the secondary sequence by entering one of the following:

1 - Item details.

2 - Movement date.

3 - Movement type.

Report Content

Enter one of the following:

1 - To produce a report with stock movement transaction details.

2 - To produce a summary report giving transaction quantities and values posted for the period.

3 - To produce both reports.

If you selected a site, the batch processes are submitted and the report produced.

If you enter 1 in the Stockroom field the Stockroom Fiscal Close Screen (Stockroom Range) is displayed.

If you enter 2 in the Stockroom field, the Stockroom Fiscal Close Screen (Stockroom List) is displayed.



Press **Enter** to validate your entries then select **F8=Submit**.

Stockroom Fiscal Close Screen (Stockroom Range)



To display this screen, enter 1 in the Stockroom field, enter the rest of the required information. Press **Enter** to validate your entries then select **F8=Submit** on the Stockroom Fiscal Close Trial Selection Screen.

Use this screen to enter the range of stockrooms you want to run a fiscal close on.

IN855	NR - Neil Radford's Test Company	User GBJBANER	19/12/96
			10:43:44
Stockroom Fiscal Close - Trial			
Year.....	96		
Period.....	10		
Cut-Off date.....	1/10/96		
Primary sequence.....	Item		
Secondary sequence.....	Movement Date		
Report content.....	Both		
Stockroom.....?	01	10	
F3=Exit F4=Prompt F8=Submit F12=Previous			
15-51	SF	MW	KS IM II EDN400A PET16SS2

Stockroom

Enter a From - To range of stockroom codes.



Note: You must close all the stockrooms in the range for the previous period.



Press **Enter** to validate your entries. Then select **F8=Submit** to submit the batch process and produce the report.

Stockroom Fiscal Close Update



Select the Stockroom Fiscal Close Update
(Processing).

Use this option to close either a site or selected stockrooms at the existing stock levels. The final summary stock movements are accumulated up to the entered cut-off date and the period is closed.

The Stockroom Fiscal Close - Update Screen is the same as the Stockroom Fiscal Close - Trial Screen. For more information, see Stockroom Fiscal Close - Trial Selection Screen.

LIFO Revaluation

You can run Last In/First Out (LIFO) revaluation as a trial or as a live update option. Stock is revalued on your selected average costs of either:

- Average annual receipt unit cost.
- Average cost of receipt over the last three periods.
- Documented (manually entered) unit cost.

You normally run the revaluation at the year-end. You can run revaluation for a selected site or stockroom for a specified period. You can only perform a LIFO revaluation on stockrooms that are under fiscal control.



Note: You can run the trial LIFO Revaluation at any time.

The revaluation can be accumulative. The net gain at the year end is recalculated and includes previous years' closing stock values. The result can be a levelling out of current stock values affecting overall profit levels. The closing stock value is defined by the cost of any net gains plus the accumulated value of any remaining stock, based on a last in first out view of the remaining cost summaries from previous years.

Generated adjustments and LIFO cost summaries are generated at item or stockroom level. A report is produced giving the new closing stock value.

If you run a trial LIFO revaluation a report is printed but the Inventory data is not adjusted. If you run an update LIFO revaluation, the Inventory data is adjusted. You can also purge LIFO balances and print the report.



Note: During a LIFO revaluation all items in a group are updated with the same cost. Therefore when you define an item group, make sure you only include items of the same or similar values.

LIFO Revaluation Trial



13/INV

Use this option to submit a revaluation on the basis of last in first out stock, for a selected site or stockrooms for a chosen period. You can include the previous years' LIFO revalued stock in the trial revaluation.

You select the valuation method for calculating the average cost for the period. You can generate a trial revaluation at any time.

LIFO Revaluation Trial Screen



Select the LIFO Revaluation Trial (Processing).

Use this screen to enter the details for the Trial LIFO Revaluation.

```

IN000          NR - Neil Radford's Test Company   User GBJBANER   2/01/97
                                                    15:46:10

LIFO Revaluation - Trial

Year..... 86
Period..... 11

Site.....?..
OR
Stockroom..... 2          1=Range,2=List

Valuation Method..... 1      1=Annual average
                               2=Last 3 months average
                               3=Manual cost

Purge existing LIFO records..... 0      (0=No,1=Yes)

-----
F3=Exit  F4=Prompt  F8=Submit

05-37  SF  MW  KS  IM  II  EDN400A  PET16SS2
  
```

Fields:

Year

Enter the year in which the fiscal period to be revalued falls. This defaults to the current year.

Period

Enter the period number for the stockroom period being closed. This defaults to the current period.

Site

Enter a site for the LIFO revaluation. Leave this field blank if you want to revalue by stockroom.

Stockroom

Enter one of the following:

1 - Range. Use this option if you want to revalue the stock for a range of stockrooms.

2 - List. Use this option if you want to revalue the stock for a list of stockrooms.

Leave this field blank if you have entered a site.



Note: The stockrooms you select for trial revaluation must be either open for the current period or closed for the previous period.

Valuation Method

Enter the revaluation method for the closing stock:

- 1 - Annual Average. To revalue any net gain in stock on the average cost of receipts over the year to date
- 2 - Last 3 months average. To revalue any net gain in stock on the average cost of receipts over the previous three months.
- 3 - Manual Cost. To revalue any net gain in stock using the manual override entered on the Costing Analysis Maintenance Detail Screen.



Note: If you want to do a LIFO revaluation by Manual Cost, all of the items in all of the stockrooms selected must have a manual cost override. If only a few items need a manual cost, transfer all the stock to a temporary stockroom, update the manual costs, define the opening balances, fiscally close the stockroom, revalue the stock and then transfer the stock back to the original stockroom. When there is a net reduction in stock, the stock is revalued at an earlier year's costs and the LIFO stock balances for the previous years' are reduced.

Purge Existing LIFO records

Enter one of the following:

- 0 - To keep all previous LIFO summary records.
- 1 - To remove all previous LIFO summary records.



Note: If the LIFO revaluation produces a higher stock valuation then the costs, in general, are falling. In this situation purging the previous years' LIFO summary balances produces a lower stock valuation.

If you select a site, the batch processes are submitted and the report is printed.

If you enter 1 in the Stockroom field the LIFO Revaluation Screen (Stockroom Range) is displayed.

If you enter 2 in the Stockroom field, the LIFO Revaluation Screen (Stockroom List) is displayed.



Press **Enter** to validate your entries. Then select **F8=Submit**.

LIFO Revaluation Screen (Stockroom Range)



To display this screen, enter 1 in the Stockroom field, then enter the rest of the required information. Press **Enter** to validate your entries then select **F8=Submit** on the LIFO Revaluation Trial Screen.

Use this screen to enter the range of stockrooms for which you want to do a LIFO revaluation.

```

IN000          NR - Neil Radford's Test Company   User GBJBANER   2/01/97
                                           16:13:21

LIFO Revaluation - Trial

Year..... 96
Period..... 12
Valuation method..... Manual cost

Stockroom.....?.. 01                02

F3=Exit  F4=Prompt  F8=Submit  F12=Previous

09-37    SF      MW      KS      IM      II  EDN400A  PET16SS2
  
```

Fields:

Stockroom

Enter a From - To range of stockroom codes you want to select for the period close. The selected stockrooms must be open for the current period or closed for the previous period.



When you have completed the selection screen press **Enter** to validate or accept your entries. Then select **F8=Submit** to start the batch processes and print the report.

LIFO Revaluation Update



14/INV

Use this option to submit a revaluation on the basis of last in first out stock, for a selected site or stockrooms for a chosen period. You can include the previous years' LIFO revalued stock in the trial revaluation.

You select the valuation method for calculating the average cost for the period. You can also specify whether a report is printed and previous LIFO records are purged.

The LIFO Revaluation Update option adjusts the inventory LIFO summary data. You can also choose to use this option to update the costs and generates value-only stock movements whereas the LIFO Revaluation Trial option only produces a report.

LIFO Revaluation Update Screen



Select the LIFO Revaluation Update.

Use this screen to enter the details for the LIFO Revaluation.

IN000		NR - Neil Radford's Test Company		User	GBJBANER	3/01/97
						11:49:59
LIFO Revaluation - Update						
Year.....	96					
Period.....	12					
Site.....	SITE01		SITE01 -----			
OR						
Stockroom.....	_		1=Range,2=List			
Valuation Method.....	1		1=Annual average 2=Last 3 months average 3=Manual cost			
Print valuation report.....	1		(0=No,1=Yes)			
Generate inventory adjustments....	0		(0=No,1=Yes)			
Purge existing LIFO records.....	0		(0=No,1=Yes)			
F3=Exit F4=Prompt F8=Submit						
05-37 SF MW KS IM II EDN400A PET16SS2						

Fields:

Year

Defaults to the current year. Select the year in which the fiscal period you want to enter falls.

Period

Enter the period number for the stockroom period being closed.

Site

Enter a site for the revaluation update or leave blank if one or more stockrooms are to be selected.

Stockroom

Enter one of the following:

1 - Range. Use this option if you want to revalue the stock for a range of stockrooms.

2 - List. Use this option if you want to revalue the stock for a list of stockrooms.

Leave this field blank if you have entered a site.



Note: The stockrooms you select for revaluation must be fiscally closed.

Valuation Method

Enter the revaluation method for the closing stock:

- 1 - Annual Average. To revalue any net gain in stock on the average cost of receipts over the year to date.
- 2 - Last 3 months average. To revalue any net gain in stock on the average cost of receipts over the previous three months.
- 3 - Manual Cost. To revalue any net gain in stock using the manual override entered on the Costing Analysis Maintenance Detail Screen.



Note: If you want to do a LIFO revaluation by Manual Cost, all of the items in all of the stockrooms selected must have a manual cost override. If only a few items need a manual cost, transfer all the stock to a temporary stockroom, update the manual costs, define the opening balances, fiscally close the stockroom, revalue the stock and then transfer the stock back to the original stockroom.

Print Valuation Report

Enter one of the following:

- 0 - Do not print a valuation report.
- 1 - Produce a valuation report listing summary records for the period or year to date. The report includes opening quantities and values, receipts, issues and the average units costs for your selected valuation method. It also includes LIFO valuation details for remaining quantity, unit cost, extended value and closing stock quantities, unit costs and values for the year whether for a net gain or net loss.

Generate Inventory Adjustments

Enter one of the following:

- 0 - Do not adjust inventory item costs with revalued costs.
- 1 - To update unit costs and generate value-only stock movements as specified on the Inventory Adjustment Criteria section of the LIFO Revaluation Screen 2.

Purge Existing LIFO records

Enter one of the following:

- 0 - To keep all previous LIFO summary records.
- 1 - To remove all previous LIFO summary records.

If you selected a site and are not updating costs, the batch processes are submitted and the report is printed.

If you selected a site and are updating the costs, or selected a stockroom list or range, the LIFO Revaluation Screen 2 is displayed.



Press **Enter** to validate your entries. Then select **F8=Submit**.

LIFO Revaluation Update Stockroom Range Screen



To display this screen, enter 1 (for range) in the Stockroom field on the LIFO Revaluation Update Screen and select **F8=Submit**.

Use this screen to select the range of stockrooms that you want to include in the revaluation update, or to enter the Inventory Adjustment Criteria if you have specified that you want to update the costs.

IN585	Version 3 Demonstration Company	User STDFIN	3/02/00
			10:08:59
LIFO Revaluation - Update			
Year.....	00		
Period.....	01		
Valuation method.....	Annual average		
Print valuation report.....	Yes		
Generate inventory adjustments....	No		
Purge existing LIFO records.....	No		
Stockroom.....?	—	—	
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Year

This is the current year this information cannot be changed.

Period

This is the current period this information cannot be changed.



Note: The information held in the next four fields is defaulted through from the values entered on the LIFO Revaluation Update Screen

Stockroom

Enter a range of stockrooms that you want to update. You can enter a single stockroom, or leave these fields blank to include all stockrooms.

These fields are not displayed if you entered a site code on the LIFO Revaluation Update Screen.



Select **F8=Submit** to process the revaluation.

LIFO Revaluation Update Stockroom List Screen



To display this screen, enter either 2 in the Stockroom field, enter the rest of the required information. Press **Enter** to validate your entries then select **F8=Submit** on the LIFO Revaluation Update Screen.

Or:

Enter 1 in the Generate Inventory Adjustments field, enter the rest of the required information. Press **Enter** to validate your entries then select **F8=Submit** on the LIFO Revaluation Update Screen.

Use this screen to enter the list of stockrooms for which you want to do a LIFO revaluation or to enter the Inventory Adjustment Criteria if you have specified that you want to update the costs.

```

IN585                    Version 3 Demonstration Company      User STDFIN      3/02/00
                                                                10:10:40
LIFO Revaluation - Update

Year..... 00
Period..... 01
Valuation method..... Annual average
Print valuation report..... Yes
Generate inventory adjustments.... No
Purge existing LIFO records..... No
Stockroom?
-----

F3=Exit  F4=Prompt  F8=Submit  F12=Previous
  
```

Fields:

Year

This is the current year, the information cannot be changed.

Period

This is the current period, the information cannot be changed.



Note: The information held in the next four fields is defaulted through from the values entered on the LIFO Revaluation Update Screen

Stockroom

Enter a list of stockroom codes.

These fields are not displayed if you entered a site code on the LIFO Revaluation Update Screen.



Note: You must close the selected stockrooms for the previous period

Inventory adjustment criteria:



Note: The inventory adjustment criteria are only displayed if you entered 1 in the General Inventory Adjustments field on the LIFO Revaluation Update Screen.

Standard Cost Items

Enter one of the following:

- 1 - To update the standard costs with the revalued unit costs.
- 2 - To update the standard, latest and average costs with revalued unit costs.

Actual Costed Items (L/A/F)

Enter one of the following:

- 1 - To update the actual costs (latest, average and FIFO) with the revalued costs.
- 2 - To update the standard and actual costs with the revalued unit costs.

Ref. No Date & Type

Enter a reference number for the adjustment transaction.

Enter a date, this defaults to the current date.

Enter a valid reference type to identify the revaluation adjustment.

Narrative

Enter a brief note of up to 20 characters on the adjustment.

Reason Code

Enter a valid reason code to be reported with the cost adjustment item.



When you have completed the selection screen press **Enter** to validate or accept your entries. Then select **F8=Submit** to start the batch processes and print the report, if you have chosen to produce one.

Stock Movements Report



21/INV

Use this option to print a stock valuation report. You can choose from a range of dates, from a site, a range of stockrooms or individual stockrooms. You can also select the order of the report and the level of detail. You can produce either a full list of stock journal movements for a selected period or an ad hoc selection. You can produce the ad hoc report for a list, or range, of items, movement types and dates.

Stock Movements Print Selection Screen



Select Stock Movements.

Use this screen to enter the selection criteria for the Stock Movements Report.

IN850		NR - Neil Radford's Test Company		User GBJBANER		8/01/97	
						15:56:08	
Stock Movements Print Selection							
Selection criteria:							
Site.....?.. _____							
or							
Stockroom.....		1		1=Range,2=List			
Report type.....		1		1=Adhoc movements 2=Stock Journal Print			
Primary sequence.....?		1		Item			
Primary selection.....		1		1=Range,2=List			
Secondary sequence.....?		2		Movement Date			
Report content.....		1		1=Detail,2=Summary,3=Both			
F3=Exit F4=prompt							
07-33		SF		MK		KS IM II KENB20A PET16SS2	

Fields:

Site

Enter the site if you want to report on all the stockrooms at a specific site. Leave this field blank if you want to report on a range or list of stockrooms.

Stockroom

Enter one of the following:

1 - Range. Use this option if you want to report on the stock movements for a range of stockrooms.

2 - List. Use this option if you want to report on the stock movements for a list of stockrooms.

Leave this field blank if you have entered a site.

Report Type

Enter one of the following:

1 - Adhoc movements. Use this option to produce a report for a list, or range, of items, movement types and dates specified on the following screens.

2 - Stock Journal Print. Use this option to produce a full stock movements report from the last closed date, up to the cut off date specified on the following screen.

Primary Sequence

Specify the first sort order of the report by entering one of the following:

- 1 - Item details.
- 2 - Movement date.
- 3 - Movement type.

Primary Selection

Enter one of the following to determine which primary items are displayed:

- 1 - Range. Use this option if you want to report on the stock movements for a range of the specified primary sequence.
- 2 - List. Use this option if you want to report on the stock movements for a list of the specified primary sequence.



Note: If you are producing the Stock Journal Report, you must enter 1 - Range for the primary selection.

Secondary Sequence

Specify the second sort order of the report by entering one of the following:

- 1 - Item details.
- 2 - Movement date.
- 3 - Movement type.



Note: The Primary and Secondary Sequence cannot be the same

Report Content

Enter one of the following:

- 1 - To report on stock movement transaction details.
- 2 - To produce a summary report giving transaction quantities and values posted for the period.
- 3 - To produce a report combining stock movement transaction details, transaction quantities and values posted for the period.



Note: The exact format of the next report selection screen depends upon the information you have specified on this screen.



When you have completed the selection screen press **Enter** to validate your entries and to display the Stock Movements Print Selection Screen.

Stock Movements Print Confirmation Screen



To display this screen complete the Stock Movements Print Selection Screen, and press **Enter** (which also validates your entries).

Use this screen to enter the selection criteria for the Stock Movements Report.



Note: The format of the Stock Movements Print Selection Screen 2 depends upon the information you have specified on the Stock Movements Print Selection Screen.

IN850	NR - Neil Radford's Test Company	User GBJBANER	9/01/97 8:46:16
Stock Movements Print Selection			
Primary sequence.....	Item		
Secondary sequence.....	Movement Date		
Report content.....	Detail		
Stockroom.....?			
Movement date.....	<u>1/12/96</u>	<u>31/12/96</u>	
Item.....?			
F3=Exit F4=Prompt F8=Submit F12=Previous			
08-32	SF	MW	KS IM II KENB20A PET16SS2

Fields:

Year

Enter the year in which the fiscal period selected falls.

This field is only displayed if you entered 2 in the Report Type Field on the Stock Movements Print Selection Screen.

Period

Enter the period for the opening balance figures to take effect.

This field is only displayed if you entered 2 in the Report Type Field on the Stock Movements Print Selection Screen.

Cut-Off Date

Enter the last date to include stock movements for.

This field is only displayed if you entered 2 in the Report Type Field on the Stock Movements Print Selection Screen.

Stockroom

Enter either a From - To range of stockroom codes or a list of stockroom codes.

This field is not displayed if you entered a site code on the Stock Movements Print Selection Screen.



Note: You should close selected Stockrooms for previous periods.

Item

Enter either a From - To range of items codes or a list of item codes.

This field is only displayed if you enter 1 in the Primary Sequence field on the Stock Movements Print Selection Screen. This field is not displayed if you have selected 2-Stock journal Report for the Report Type.

Movement Date

Enter either a From and To date or a list of dates to select movement transactions from.

This field is only displayed if you enter 2 in the Primary Sequence field on the Stock Movements Print Selection Screen.

Movement Type

Enter either a From and To movement type or a list of movement types.

This field is only displayed if you enter 3 in the Primary Sequence field on the Stock Movements Print Selection Screen.



Press **Enter** to validate your selection and then select **F8=Submit** to submit the print.

Derive Opening Balances



31/INV

Use this option to set the opening balances for a specified starting period. You need to specify the year and period you want to derive the opening balances for.

You only need to run this option once, when you are setting up the inventory valuation.



Note: When you run a Stockroom Fiscal Close, the software assumes that the opening balances have already been defined during the previous period close. This is one method of defining the initial opening balances. You cannot use this with the other; Cost Analysis Setup Maintenance option combined with the Cost Analysis Setup Update.

Cost Analysis Derive Opening Balances Screen



Select Derive Opening Balances (Cost Analysis Setup).

Use this screen to select the period, year and stockroom for which you want to derive the opening balances.

IN579	Z1 - UK Demonstration Company	User GBJBA1MS	23/10/98 9:11:45
-------	-------------------------------	---------------	---------------------

Costing Analysis Setup - Derive Opening Balances	
Year.....	97
Period.....	06
Stockroom...?	
Start Date.....	23/10/98

F3=Exit	F4=Prompt	F8=Submit
---------	-----------	-----------

Fields:

Year

Enter the year you want to create the opening stock balances for. This defaults to the current year.

Period

Enter the period you want to create the opening stock balances for. This defaults to the current period.



Note: If the year and period selected are prior to the current year then stock movements must exist from this point onwards. Once the opening balances have been derived, perform a series of manual fiscal closes for each of the intervening periods until the previous period is closed. From this point onwards you can perform fiscal closes automatically.

Enter the stockroom for which you want to derive the current balances.



Note: The period and stockroom combination cannot be closed or open.

Start Date

Enter the date on which you want to start the opening balances.



Enter the Year, Period, Start Date and Stockroom, then select **F8=Update** to create the Opening Balances.

Costing Analysis Set Up Maintenance



32/INV

Use this facility to define initial opening balances before you run a Stockroom Close Function. Use this option combined with the Cost Analysis Setup Update option to set up the inventory historical data.



Note: When you run a Stockroom Fiscal Close, the software assumes that the opening balances have already been defined during the previous period close. This is one method of defining the initial opening balances. You cannot use this with the other, Derive Opening Balances.

You can define item period summaries so you can then manually close the stockroom. Once you have manually closed the first period the initial details are available for the following period so you can use the normal close function.

If you have purged stock movements, you can use this option to define the movement details for the purged periods until an appropriate position has been reached and you can use the manual close function again.



Note: Once the opening balances have been derived for the purged periods, perform a series of manual fiscal closes for each of the intervening periods until the previous period is closed. From this point onwards you can perform fiscal closes automatically.

Costing Analysis Setup Maintenance Selection Screen



Select Maintenance (Costing Analysis Setup).

Use this screen to enter the Year, Period, Stockroom and Item that you want to enter initial opening balances for.

IN872	NR - Neil Radford's Test Company	User GBJBANER	17/12/96 14:46:35
Costing Analysis Setup - Maintenance			
Year.....	96		
Period.....	12		
Stockroom.....	01	Stockroom One	
Start date.....	1/12/96		
Item.....?			
F3=Exit F4=Prompt F12=Previous			
10-21	SP	MW	KS IM II EDN400A PET165S2

Fields:

Year

Select the year in which the fiscal period to be entered falls. This defaults to the current year.

Period

Enter the period number.

Stockroom

Enter the stockroom code where the item is situated.

Start Date

Enter the date the costing analysis is to take place. This must be within the period selected. If you leave the field blank it defaults to the first day of the period selected.



*Note: Press **Enter** to display the Item field.*

Item

Enter the item code. The item must already exist on the Item Master file and must have been entered as a stockroom item for the selected stockroom.



Press **Enter** to accept the period control details and to display the Costing Analysis Setup Maintenance Opening Values Screen.

Costing Analysis Setup Maintenance Opening Values Screen



To display this screen press **Enter** to accept the period control details on the Costing Analysis Setup Maintenance Selection Screen.

Use this screen to enter the opening quantity and value of stock, the receipts, issues, adjustments and transfers of stock in the selected period.

IN872	NR - Neil Radford's Test Company	User GBJBANER	18/12/96
			8:51:49
Costing Analysis Setup - Maintenance			
Item.....	A1	Aspirin Dispersible tablets BP 300mg	
Stockroom.....	01	Stockroom One	
Issue unit.....	BT	Bottles of	
Year/period.....	96/12	Start date..	1/12/96

		Quantity	Value
Opening.....		5000.000	4500.00000

Receipts.(All).....		3500.000	3210.00000
Receipts.(Excluding misc.).....		.000	.00000
Issues.....		1300.000	1100.00000
Adjustments.....		.000	.00000
Transfers.....		100.000	85.00000

Closing.....		9900.000	8895.00000

F3=Exit F12=Previous			
11-41 SF MW KS IM II EDN400A PET16SS2			

Fields:

Opening

Enter or amend the opening quantity and value for the period to date.

Receipts (All)

Enter or amend the quantity and value for all receipts for the period to date.

Receipts (Excluding Misc.)

Enter or amend the quantity and value for all receipts posted as miscellaneous for the period to date.



Note: Data is only displayed in this field if you have set your company profile flag to Include Miscellaneous Receipts.

Issues

Enter or amend the quantity and value for all issues for the period to date.

Adjustments

Enter or amend the quantity and value for all adjustments for the period to date.

Transfers

Enter or amend the quantity and value for all transfers for the period to date.



Press **Enter**. The software calculates the closing balances for the period. Then press **Enter** again to display the Costing Analysis Setup Maintenance Previous Values Screen.

Costing Analysis Setup Maintenance Previous Values Screen



To display this screen press **Enter**, so that the software calculates the closing balances for the period, then press **Enter** again on the Costing Analysis Setup Maintenance Opening Values Screen.

Use this screen to enter the previous two periods receipts and costs.

IN872	NR - Neil Radford's Test Company	User GBJBANER	18/12/96
			12:14:28
Costing Analysis Setup - Maintenance			
Item.....	A1	Aspirin Dispersible tablets BP 300mg	
Stockroom.....	01	Stockroom One	
Issue unit.....	BT	Bottles of	
Year/period.....	96/10	Start date..	1/10/96

		Quantity	Value
Receipts.(All)(Period-1).....		150.000	85.00000
Receipts.(All)(Period-2).....		100.000	75.00000
Receipts.(Excluding misc.)(Period-1)..		50.000	40.00000
Receipts.(Excluding misc.)(Period-2)..		50.000	35.00000

Latest cost.(All).....		.000	0/00/00
Latest cost.(Excluding misc.).....		.000	0/00/00

F3=Exit F8=Update F12=Previous			
11-41 SF MW KS IM II EDN400A PET16SS2			

Fields:

Receipts (All)(Period-1)

Enter the quantity and value of receipts for the previous period.

Receipts (All)(Period-2)

Enter the quantity and value of receipts for the period before last.

Receipts (Excluding misc.)(Period-1)

Enter the quantity and value of receipts, excluding miscellaneous receipts in the previous period.

Receipts (Excluding misc.)(Period-2)

Enter the quantity and value of receipts, excluding miscellaneous receipts in the period before last.

Latest cost (All)

Enter the latest cost of all stock.

Enter a date to show when the latest cost was entered.

Latest cost (Excluding misc.)

Enter the latest cost of all stock excluding the miscellaneous receipts.

Enter a date to show when the latest cost was entered.



Note: The latest and average cost calculations only include miscellaneous receipts if you have set your company profile flag to Include Miscellaneous Receipts.



Select **F8=Update** to perform the cost update.
The Costing Analysis Setup Maintenance
Selection Screen is redisplayed.

Costing Analysis Setup Update



33/INV

Use this option to manually close stockrooms. This option differs from the Maintenance option in that it closes the stockroom at the existing stock levels. You cannot change any stock quantities or values.

You use this option combined with the Cost Analysis Setup Maintenance option to set up the Inventory historical data.



Note: When you are doing the initial set up of the Inventory data you either use the Cost Analysis Setup Derive Opening Balances Option or use the Cost Analysis Setup Maintenance option combined with the Cost Analysis Setup Update option to create historical data.

Costing Analysis Setup Update Screen



Select the Update option (Costing Analysis Setup).

Use this screen to enter the details of the stockroom and period that you want to perform a manual close on.

```

IN873          NR - Neil Radford's Test Company   User GBJBANER   18/12/96
                                                    14:40:19

Costing Analysis Setup - Update

Year..... 86
Period..... 10
Stockroom..... 01   Stockroom One
Cut-Off date..... 31/10/96

F3=Exit  F4=Prompt  F8=Submit

05-21   SF   MW   KS   IM   II  EDN400A  PET165S2
  
```

Fields:

Year

Select the year in which the fiscal period to be entered falls. This defaults to the current year.

Period

Enter the period number for the stockroom period being closed.

Stockroom

Enter the code of the stockroom you want to close.

Cut off Date

Enter the last date on which posting will be allowed to the stockroom.



Close the stockroom by selecting **F8=Submit**.

Define Opening Balances



41/INV

Use this option when you begin to use LIFO Revaluation for the first time, or if an item is to be included in LIFO revaluation for the first time.

For each stockroom item you need to enter the original quantity, current quantity and the unit cost.

Once you have created the historical LIFO Summary records you can maintain them using the Derive Opening Balances option.



Note: The amendment function is achieved by deleting and rewriting the LIFO summary balance records. No indication is given that an existing LIFO summary record is about to be overwritten.

LIFO Analysis Setup Selection Screen



Select the Define Opening Balances option,
(Costing Analysis Setup).

Use this screen to enter the year and stockroom whose opening stock balances you want to enter.

```
IN587          Inventory Valuation test company..# User GBJBA1MS  17/10/98
                                           13:39:04

LIFO Analysis Setup

Year..... 92
Stockroom....?.. 11 Stockroom 11

F3=Exit  F4=Prompt
```

Fields:

Year

Enter the year you want to create stock details for.

Stockroom

Enter the code of the stockroom that you are setting up with the opening balance.



Press **Enter** to validate the data and display the
LIFO Analysis Setup Detail Screen.

-
-
-
-
-

Chapter 8

Inventory Enquiries

Inventory Enquiries Introduction

The enquiries included in Inventory Management are designed to help you achieve a layered approach to the review of an item. This includes:

- Balances, usage and cost at stockrooms.
- Movements.
- History.
- Descriptions and codes from the Descriptions File.

Kit List Item Where Used Enquiry



1/INE

Use this option to view the parent items of the selected kit component.

Kit List Item Where Used Selection Screen



To display this screen, select Kit List Item Where Used.

Use this screen to select the item code of the kit component that you want to enquire upon.

The screenshot shows a terminal window with the following text:

```
IN008                MM - Catchweight Company MM      USER GBJBA1MS      3/10/00
                                                           14:57:02
Kit List Item Where Used Enquiry
Item.....?.. _____
F3=Exit  F4=Prompt
```

Fields:

Item

Enter the item code of the kit component whose details you want to view.



Press **Enter** to display the Kit List Item Where Used Screen.

Kit List Item Where Used Screen



To display this screen, enter the item code of a kit component on the Kit List Item Where Used Selection Screen and press **Enter**.

This screen displays the selected component item, the kit parent that it is used in, the description of the kit, and the quantity of the component item used to make up the kit.

IN008	Distribution V3 -> V3 Financials		USER GBJBAMV1	14/11/95
				15:01:02
Kit List Item Where Used Enquiry				
Item	ANDYKIT2/2	andys kit item 2/2		
Used on	Description	Qty. off		
ANDYPARENT2	andys parent item 2	5.00		
F3=Exit F12=Previous				
01-02	SA	MW	KS	IM II KENB20A PET129S1



Select **F3=Exit** to return to the menu.

Descriptions Enquiry



2/INE

Use this option to view entries on the Descriptions File. The screens are the same as those used for maintenance, but you cannot amend any fields.

Descriptions File Enquiry Selection Screen



To display this screen, select Descriptions (Enquiries).

Use this screen to specify the major or minor description codes that you want to enquire upon.

```

IN038                AS - ALG Systems                User STDFIN        3/02/00
                                                    14:58:36
Descriptions File Enquiry

Description type..... TYPE
Major type.....
Description code.....

Desc'n. I.D.   Description                               Limit
ACDF          AC Terminology Definitions              30
ADFM          Address format                          30
AEDI          Automatic Update from EDI                30
ALTT          Alternative Item Type                    30
AN            Agent                                    30
ANTP          Article Number Type                     30
ARPM          Arrears Processing Method                30
ASAD          AS Address Type Codes                   30
ASTA          Article Status Code                     30
AUMD          Authorisation Method                    30

F3=Exit  F15=Description code details
  
```

Fields:

Major Type

Enter the major type that you want to enquire upon. Press **Enter** to display the Descriptions File Enquiry Screen.

Description Code

This field is for future development.

Functions:

F15=Description Code Details

Select this to display the Descriptions File Enquiry Details Screen for your selected major type.

Descriptions File Enquiry Screen



To display this screen, enter a major type code on the Descriptions File Enquiry Selection Screen and press **Enter**.

Use this screen to view records in the Descriptions file, but not to maintain them.

IN038	MM - Catchweight Company MM	User GBJBA1MS	3/10/00 14:59:07
Descriptions File Enquiry			
Description type.....	TYPE		
Major type.....	DIYN		
Description.....	Inventory Product Division		
Description limit.....	30		
Desc'n I.D.	Description	Limit	
?		44444	
A	aa	30	
ABCD	Lawrence	12	
ACD	bikram abcde3	30	
ACDF	Customer Schedule Definitions	30	
ADCD	ADCD	6	
ADFM	Address format	30	
AEDI	Automatic Update from EDI	30	
ALT	Grouter and Plasterer Monthly	100	
ALTM		30	
F3=Exit F12=Previous F15=Description code details F23=Language descriptions			

Fields:

Major Type

Select a major type. Specify a major type and press **Enter**, to display its description.

Description Code

Enter the description code if you only want to view the details of that single description code. Leave this field blank if you want to display the description of the major type.

Use page up and page down to display the major types.

Functions:

F15=Description Code Details

Use this to display the Descriptions File Enquiry Details Screen.

F23=Language Descriptions

Use this to display the Multi-Lingual Descriptions Enquiry Window.



To display all description codes for a major type, enter the major type and select one of the function keys to continue.

Descriptions File Enquiry Details Screen



To display this screen select **F15=Description Code Details** on the Descriptions File Enquiry Screen.

Or:

Select **F15=Description Code Details** on the Descriptions File Enquiry Selection Screen.

You can view all the descriptions and the associated codes and rates, if appropriate.

```

IN038                MM - Catchweight Company MM        User GBJBA1MS    3/10/00
                                                14:59:38

Descriptions File Enquiry

  Description type... DIVN      Inventory Product Division      Limit      30
  Description code... _____

1 Desc'n I.D. Description                      Limit      Vat PV Rate
- A      All Divisions                          .00
- D      Domestic                              .00
- E      Export                                .00
- ED     Export/Domestic                        .00
- I      Import                                .00
- ID     Import/Domestic                        .00

1=Select  2=Language descriptions
F3=Exit  F12=Previous
  
```

Fields:

Select (1)

Enter one of the following:

1 - Select. To display the Description File Enquiry Minor Type Details Screen for your selected minor type code.

2 - Language Descriptions. To display the Multi-Lingual Descriptions Enquiry Window for your selected minor type code.



Enter an option in the 1 field and press **Enter** to continue.

Or:

Select **F3=Exit** to exit the enquiry.

Description File Enquiry Minor Type Details Screen



To display this screen, enter 1 next to a minor type on the Descriptions File Enquiry Details Screen and press **Enter**.

This screen displays the description, parameter limit, rate, percentage or value and VAT codes assigned to your selected minor type code.

IN038	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00
			9:58:33
Descriptions File Enquiry			
Description type...	DIVN	Inventory Product Division	Limit 30
Major type.....	A		
Description.....	All Divisions		
Parameter limit....	0	Rate.. .00	P/V... VAT code..
1 Desc'n I.D.	Description	Limit	Vat PV Rate
- A	All Divisions		.00
- D	Domestic		.00
- E	Export		.00
- ED	Export/Domestic		.00
- I	Import		.00
- ID	Import/Domestic		.00
1=Select 2=Language descriptions			
F3=Exit F12=Previous			



Select **F12=Previous** to redisplay the Descriptions File Code Details Enquiry Screen.

Multi-Lingual Descriptions Enquiry Window



To display this screen select **F23=Language Descriptions** on the Descriptions File Enquiry Screen.
Or:
Enter 2 in the 1 field on the Descriptions File Enquiry Details Screen and press **Enter**.

You can view all of the different languages and their descriptions associated with your selected code.

```
IN038                MM - Catchweight Company MM      User GBJBA1MS    3/10/00
                                                15:00:00
Descriptions File Enquiry
Multi-lingual Descriptions Enquiry
Code..... DIYN
Description.. Inventory Product Division

Language      Description
              No descriptions found.

F12=Previous
ALTM                      30

F3=Exit  F12=Previous  F15=Description code details  F23=Language descriptions
```



Select **F12=Previous** to redisplay the previous screen.
Or:
Select **F3=Exit** to exit the enquiry.

Item/Stockroom Enquiry



3/INE

Use this option to view all of the data from the item master and the stockroom balance. You can view static data for the item, a summary of the company stock position for the item, or the individual stockroom balances. You can also view both batch and FIFO cost record details for stockrooms where this level of information is available.



Note: The function keys you can use to view aspects of your Item/Stockroom Enquiry depend on how you have set up your item in Item Maintenance.

Item/Stockroom Enquiry Selection Screen



Select Item/Stockroom.

Use this screen to select the item and the level of information you want to view.

IN018	Version 3 Demonstration Company	USER STDFIN	3/02/00 10:19:58
Item / Stockroom Enquiry			
Item.....?.. _____			
Stockroom.....?.. _			
F3=Exit F4=Prompt F13=Stock summary			

Fields:

Item

To view the static information associated with the item, enter the item number only and press **Enter**. For more information, see the Item/Stockroom Enquiry Static Details Screen.

Stockroom

To view the stockholding of an item in a single stockroom, enter the item and stockroom code and press **Enter**. This displays the Item/Stockroom Enquiry Stockroom Details Screen.

Functions:

F13=Stock Summary

Use this to display Item/Stockroom Stock Summary Enquiry Screen.



Select an item and press **Enter** to display
Item/Stockroom Enquiry Static Details Screen.

Item/Stockroom Enquiry Static Details Screen



To display this screen, specify an item and press **Enter** on Item/Stockroom Enquiry Selection Screen.

Use this screen to view the static descriptive information for the item. The fields on this screen are the same as the fields in the Item Maintenance Static Details Screen. For more information about the fields on this screen, see the Item Maintenance Static Details Screen.

IN018		Version 3 Demonstration Company		USER STDFIN	3/02/00
					10:19:58
Item / Stockroom Enquiry					
Item.....	50311	Paracetamol 250 tabs/box			
Pallet Conv					
Volume					
Weight		Packaging reporting.... 1			
Effectivity start.....	27/01/00	Purchase pack.....			
Item type.....	2	Medium Shelf Life			
Item class.....	2	Medium Cost			
Item group major.....	4				
Item group minor.....	7	Painkilling Drugs			
Division.....	ED	Export/Domestic			
Sub-division.....	1	Bought In Item			
Purchase unit.....	CA	Stock->purchase conv... .50000			
Stock unit.....	PL	Issue->stock conv..... 16.00000			
Issue unit.....	BX	Weight per selling unit .2000			
VAT code.....	001	17.50 %			
Discount group.....					
Inventory source.....					
Sales analysis update..	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.	0	0=No,1=Yes	End date 0/00/00		
F3=Exit F10=Group valuation criteria F12=Previous F21=Text F24=More keys					

Functions:

If there are entries in both the Secondary Value and Secondary UOM fields, select **F9=Sec Vals**, to display the Secondary Value Details Window. You cannot change any of the information displayed here.



Note: This function is only displayed if you use Catchweight, and the item has a secondary value. For more information, see the Inventory Company Profile Maintenance section.

F10=Group Valuation

Use this to view the group valuation for the selected item.

F20=Movement And Cost Analysis

Use this to view the movement and cost analysis for the selected item. You can only use this function if you use stockroom fiscal close. For more information, see the Inventory Company Profile Maintenance section.

F21=Text Entry

Use this to view the Maintain Text Window where you have previously specified a usage code and a language code for multi-lingual text entry. Press **Enter** to display the Item Text Window. This is where you can view text in the selected language to

be displayed or printed on external documentation, for example, despatch notes, according to the usage code selected.



Tip: You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** is available.



Note: You do not need to select language codes to print text in the native language.

F22=Item Packaging Details

Use this to view the Country Item Packaging Details Enquiry, if you are using Packaging Requirements. You can only use this function if your selected item has been set up for packaging reporting.



Press **Enter** to display Item/Stockroom Enquiry Costing Details Screen.

Movements Analysis Window



To display this window, select **F20=Movement & Cost Analysis** on Item/Stockroom Enquiry Static Details Screen.

Use this window to view movement and cost analysis information for your selected item in both year and period to date formats.

```
IN018      Version 3 Demonstration Company      USER STDFIN      3/02/00
                                                10:21:22

Movements Analysis - Period
Period..... 0001
Start date..... 3/02/00
Close date..... 5/02/00
Item..... 50311      Paracetamol 250 tabs/box
Issue unit.. BX      Boxes of

Opening.....      Quantity      Value
-----
Receipts.....
Issues.....
Adjustments.....
Transfers.....
-----
Closing.....      .000      .00000

Latest receipt... 0/00/00
Latest issue..... 0/00/00

F12=Previous F13=Year to date details F14=Cost analysis
F3=Exit F10=Group valuation criteria F12=Previous F21=Text F24=More keys
```

Fields:

Period

This is the current period.

Start Date

This is the start date for this period.

Close Date

This is the end date for this period, for the purposes of this enquiry.

Stockroom

This is the stockroom for your selected item.

Item

This is your selected item.

Issue Unit

This is the issue unit for your selected item; this is defined in Item Maintenance.



Note: The following fields display both the quantity and value for the item for this period.

Opening

This is the stock balance for this item/stockroom combination and the associated value at the start of the period.

Receipts

This is the total stock of this item you have received and the associated value for those receipts for this period.

Issues

This is the total stock of this item you have issued and the associated value for those issues for this period.

Adjustments

This is the total stock of this item you have adjusted and the associated value for those adjustments for this period.

Transfers

This is the total stock of this item you have transferred and the associated value for those transfers for this period.

Closing

This is the stock balance for this item/stockroom combination and the associated value at the end of the period

Latest Receipt

This is the date of the latest receipt of this item in this stockroom.

Latest Issue

This is the date of the latest issue of this item in this stockroom.

Functions:

F13=Year To Date Details

Use this to toggle between period and year to date details for this item and stockroom combination.

F14=Cost Analysis

Use this to toggle between the cost or movement analysis details.

F15=Previous Period

Use this to view the details recorded against the previous period, where applicable.

F16=Next Period

Use this to view the details recorded against the next period, where applicable.

F17=Item Group

Use this to view the details recorded against an item group, if your item is part of an item group.



Select **F12=Previous** to redisplay the Item/Stockroom Enquiry Static Details Screen.

Cost Analysis Window



To display this screen select **F14=Cost Analysis** on the Movements Analysis Window.

Use this window to view cost analysis details for your selected item in both period and year to date format. The software displays the reference number and description, issue unit and current period details for your selected item.

IN018		Version 3 Demonstration Company		USER STDFIN		3/02/00	
						10:21:22	
Cost Analysis							
Item..... 50311		Paracetamol 250 tabs/box					
Issue unit.. BX		Boxes of					
Year/period. 0001							

		Period		Year			
Start date.....		3/02/00		3/02/00			
Close date.....		5/02/00		5/02/00			
Latest cost.....		.00000		0/00/00			

Average cost.....		.00000		.00000			
Average cost (last 3 periods).		.00000		.00000			

Average cost (Period-1).....		.00000		.00000		00	
Average cost (Period-2).....		.00000		.00000		00	

Manual cost override.....		.00000		.00000		2000	

F12=Previous F14=Movement analysis							
F3=Exit F10=Group valuation criteria F12=Previous F21=Text F24=More keys							

Fields:

Start and Close Date

This is the date range for the current period, for the purposes of this enquiry.

Latest Cost

This is the latest cost for this item, and the date upon which the cost was calculated.

Average Cost

This is the average cost of the item for this period, and the year to date.

Average Cost (Last 3 Periods)

This is the average cost of the item for the period three months ago, and the year to date.

Average Cost (Period-1)

This is the average cost of the item for the previous period, and the year to date.

Average Cost (Period-2)

This is the average cost of the item for the period two months ago, and the year to date.

Manual Cost Override.

This is the value of any manual cost overrides you have performed for the current period and the year to date.

Functions:

F14=Movement Analysis

Use this to toggle between this screen and the details held on the Movement Analysis Window.



Select **F12=Previous** to redisplay the Movement Analysis Window.

Item/Stockroom Enquiry Costing Details Screen



To display this screen press **Enter** on
Item/Stockroom Enquiry Static Details Screen.

Use this screen to display the static descriptive information for the item. The fields in this screen are the same as the fields in the Item Maintenance Costing Details Screen. For more information about the fields on this screen, see the Item Maintenance Costing Details Screen.

IN018		Version 3 Demonstration Company		USER STDFIN	3/02/00
					10:21:22
Item / Stockroom Enquiry					
Item.....	50311	Paracetamol 250 tabs/box			
Superseded by.....					
Supersession date.....	0/00/00				
Costing Meth.(S,L,A,F)..	A	GL A/C.....	310000		
Standard cost.....		Sales GL A/C.....	701100		
Latest cost.....		Cost of sales GL A/C..	601100		
Average cost.....		Price variance A/C...			
Base list price...		Purchase Officer.....	1		
Price regulator code....		Search family code...	PKL		
Price list seq code....		C-of-C code.....	PKL Rqd		
Warranty type.....		Non-stock item type..			
Storage method.....		Preferred supplier...			
Shelf life unit.....	1 Days	Ordering method.....	0 Normal Orde		
Shelf life.....	24	Cust shelf life.....	18		
EEC tariff code.....		Date..	0/00/00	Ref.	000000000000
Duty %.....	.00	Bar code.....			
Lot control (B,L,S,N)...	B	Inspection reqd.(1/0).	0		
Sub contract Item.....					
F3=Exit F12=Previous F20=Lot Header details F22=Grade					

Functions:

F20=Lot Header Details

Use this to display the Lot Header Parameters Enquiry Window for the selected item, if it is subject to lot, batch or serial control.

F22=Grade

Use this to display the Grade Enquiry Screen for the selected item, if you have chosen to use grades for the item.



Press **Enter** to display the Item/Stockroom Stock
Summary Enquiry Screen.

Lot Header Parameters Enquiry Window



To display this window, select **F20=Lot Header Details** on the Item/Stockroom Enquiry Costing Details Screen.

Use this window to view the lot header details for your selected batch, lot or serial controlled item. The fields displayed on this screen are for information only.

```

IN018          Version 3 Demonstration Company      USER STDFIN      3/02/00
                                                    10:21:22

Lot Header Parameters Enquiry
Item..... 50311          Paracetamol 250 tabs/box

Potency required..... 1  (0=No,1=Yes)
Standard Potency..... .34000 %
Grade required..... 1  (0=No,1=Yes)
Default grade..... GOOD   Good Quality
Default stock status..... FZ   Frozen
Release lead time units....
Release lead time.....
Lot dates 'to'..... 1      Actual date (no adjustment)
Display lot time..... 0  (0=No,1=Yes)

F12=Previous
Shelf life unit..... 1    Days      Ordering method..... 0 Normal Orde
Shelf life..... 24          Cust shelf life..... 18
EEC tariff code.....      Date.. 0/00/00 Ref. 000000000000
Duty %..... .00          Bar code.....
Lot control (B,L,S,N)... B      Inspection reqd.(1/0). 0
Sub contract Item.....

F3=Exit F12=Previous F20=Lot Header details F22=Grade
  
```

Fields:

Potency Required

This indicates whether you want to display the default potency value upon receipt or not.

Standard Potency

If you have set the Potency Required field to 1, then this is the default potency value that is displayed in the Potency field every time you receive a new lot of this item.



Note: Potency is a percentage; the potency you specify here is the number of parts of active ingredient per hundred parts.

Grade Required

This specifies whether you want to display the default grade value upon receipt or not.

Default Grade

If you have set the Grade Required field to 1, then this is the default grade value that is displayed in the Grade field every time you receive a new lot of this item.

Default Stock Status

This is the stock status code chosen from those defined on the Descriptions file against the major type STKS. This stock status code defaults into the Stock Status field every time you receive a new lot of this item into Inventory. Stock status codes are designated as either available or unavailable and then applied to a lot to make the quantity of that lot frozen or unfrozen.

A blank stock status implies that a lot is available.



Note: The seven-digit limit field of the description codes defined against STKS indicates the availability of an item. If the seventh digit of this field is 1 then the stock status code indicates an unavailable item. Any other value renders the stock status code an available code.

Release Lead Time Units

This is the release time unit used when calculating the first available date of a lot; it can be 1, for days, 2 for weeks, 3 for months, 4 for years or left blank if there is no specified release lead time. In this case, when the lot dates are calculated the first available date is the same as the production date.



Note: Production Date + Release Time = First Available Date.

Release Lead Time

If you specified a release lead time unit, then this is the release lead time. If this field is blank when the lot dates are calculated, the first available date is the same as the production date.

Lot Dates To

This specifies the method used to position lot dates once they are calculated; all lot dates are either entered or calculated using shelf life and release times.

Display Lot Times

This specifies whether to display lot times or not.



Select **F12=Previous** to redisplay the Item/Stockroom Enquiry Costing Details Screen.

Item/Stockroom Stock Summary Enquiry Screen



To display this screen press **Enter** on Item/Stockroom Enquiry Costing Details Screen.



*Note: If you enter an item on Item/Stockroom Enquiry Selection Screen and select **F13=Stock Summary**, then you can view this information for each item/stockroom combination.*

Use this screen to view simple control figures for the total company stock of the item.

IN018	Version 3 Demonstration Company	USER STDFIN	3/02/00
			10:21:22
Item / Stockroom Enquiry			
Item.....	50311	Paracetamol 250 tabs/box	
	Boxes of		
Usage this week.....	2.000		
Usage this month.....	2.000		
Usage this year.....	2.000		
Total physical stock..	9.000		
Total physical stock stored in stock units.	.563	Pallets Of	
F3=Exit F12=Previous			

Fields:

Usage

These are the usage figures for the company, in issue units of measure.

Total Physical Stock

This is the physical stock figure for the company, in issue units of measure.



*Note: If you are using Catchweight for this company and the item has a secondary value, select **F9=Quantity/[Short Description]** to display the quantity of the item in this field in either primary or secondary units of measure.*

Total Physical Stock In Stock Units

This is the physical stock figure for the company, in issue units of measure.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which you can only use when you use Catchweight for this company and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select it to display the quantity of the item in the Total Physical Stock field in the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select it to display the quantity of the item in the Total Physical Stock field in the secondary unit of measure. The abbreviation of the secondary unit of measure is displayed on the screen by the appropriate fields.



Press **Enter** to display Item/Stockroom Enquiry
Stockroom Details Screen.

Item/Stockroom Enquiry Stockroom Details Screen



To display this screen press **Enter** on Item/Stockroom Stock Summary Enquiry Screen.
Or:
Enter both the item code and stockroom code on Item/Stockroom Enquiry Selection Screen and press **Enter**.



*Note: If you stock the selected item in more than one stockroom then the stock balances will be displayed sequentially. Press **Enter** to display the details for the next stockroom.*

This screen displays stockroom information for your selected item.

The item and stockroom codes, with their associated descriptions are displayed at the top of the screen.

All the balances displayed are in the issue units of the item and stockroom combination. Stock is valued using the item's costing method indicated in the right-hand Costs column.

IN018	MM - Catchweight Company MM	USER GBJBAHEH	9/11/00
			14:03:50
Item / Stockroom Enquiry			
Item.....	HEB01	Standard Item, (no LC/CW)	
Stockroom.....	W2	WH/2	
<-STOCK BALANCES (EA)-> <-USAGE/REORDER DATA(EA)-> <-----COSTS (EA)----->			
Physical	100.000	This week..	.000 Standard 3.50000
On order	.000	This month..	.000 Latest.. 3.50000
Alloc...	10.000	This year..	.000 Average.. 3.50000
Frozen..	.000	Average.....	.000 Value... 350.00
Avail...	90.000	ROP.....	.000 Cost at. STANDARD
Transit.	.000	Maximum....	.000 Price... .00000
Back Ord	.000	EOQ.....	.000 <----- DATES ----->
POD.....	.000	Reorder....	.000 Last changed... 9/11/00
		Reorder factor.%.	10 Last receipt... 9/11/00
<--- MISCELLANEOUS --->		Lead time in weeks	.00 Last issue.... 0/00/00
Stocktake in progress		No. weeks cover...	.00 Last stk check. 0/00/00
Packaging reporting..		Max stock weeks....	.0 Next stk check. 0/00/00
		Min stock weeks....	.0 <---- SUPPLIERS ---->
Purchase units.....	EA	ABC classification....	...
Bin 1.	2.	ABC class override....	...
F3=Exit F12=Previous F18=Stock availability F21=Text			

Fields:



Note: (XX) indicates the Unit of Measure code, for example, Stock Balances could be in Boxes, Each, Pallets, and so on.

Stock Balances (XX)

This section of the screen displays the following:

The physical stock held at this stockroom.

The stock currently on purchase and works (production) orders.

The stock currently allocated to demand orders.

Stock currently frozen, that is, unavailable for allocation to demand orders.

Stock currently in transit between stockrooms.

Stock currently available for movement, allocation.

Back Order, which is the stock on sales back order.

POD, which is the stock currently awaiting POD (Proof Of Delivery).



Note: If you are using Catchweight, then the secondary balance for your selected Catchweight item is also displayed in this section.

Miscellaneous

This section displays the following:

Whether there is a stocktake in progress for your selected item and stockroom combination.

Whether your selected item is defined to Packaging Reporting.

The unit of measure that is used to purchase this item from this stockroom.

The stockroom bins where this item is located, if these are defined.

Usage/Reorder Data (XX)

This section displays the following:

The amount of this item that has been issued from this stockroom over a weekly, monthly and annual basis.

The average usage for this item, which is calculated by Inventory.

The ROP, or reorder point, for this item stockroom combination.

The maximum holding stock level for this stockroom. Inventory uses this quantity for the reorder policy Up To Max.

The EOQ, or the Economic Order Quantity for this item stockroom combination.

The quantity you need to reorder.

The Reorder Factor for your selected item. This is the number of lead times worth of average usage that you should reorder.



Note: Inventory only uses the information held within the Reorder and Reorder Factor fields if you have selected to use Reorder Policy 2 - ROP/ROQ.

The Lead Time In Weeks. This shows the time in weeks, between placing an order for a particular item and receiving it at the stockroom.

Immediately below this are the details from the stock weeks matrix. You can view the following:

The number of weeks stock cover for this item held in this stockroom.

The minimum and maximum weeks of stock held on the company profile for this item stockroom combination.

The current system assigned ABC Classification, again from the stock weeks matrix. Or, if you have specified one, the ABC classification override from the item master file.

Costs (XX)

This section of the screen displays the following:

The Standard, Latest and Average cost recorded for this item stockroom combination. The most recent item cost according to the method of costing displayed next to the heading Cost At.



Note: If there is a base list price for the item this will be displayed under the costing method in the Price field.



Note: If you are using Proof Of Delivery (POD) then the value awaiting POD is included in the Value field. The value includes the value of the physical stock at the current costing method, the value of the stock in-transit and the value of stock awaiting POD.

Dates

This section details the date that you last changed this item stockroom combination. It also displays the most recent receipt and issue of this item from this stockroom, and the dates of the last and next stock count.

Suppliers

This final section displays the preferred suppliers for this item. It displays four supplier references, but only the supplier reference displayed first is used in processing.

Functions:

F13=Lot Details

If the item is batch, lot or serial controlled, use this function to provide a further breakdown of stock balances by batch number. A list of lots is displayed showing lot balance information. For more information see the Item/Stockroom Lot Details Screen.

F14=Lot By Date

If the item is batch, lot or serial controlled, use this function to provide a further breakdown of stock balances by creation date. A list of lots is displayed showing lot balance information. For more information see the Item/Stockroom Lot By Date Details Screen.

F15=Locations

If your item is defined to a Location Controlled stockroom, then you can use this function to view the locations that this item is held in. For more information, see the Locations Enquiry Screen.

F18=Stock Availability

Use this to view the Stock Availability Enquiry Details Screen within Sales Order Processing.

F19=FIFO Cost Details

Use this to view FIFO costs for the selected item if applicable.

F20=Movement Cost Analysis

Use this to view the movement and cost analysis details for the selected item. See Movement Analysis Window for more details.

F21=Text Entry

Use this to view the Maintain Text Window where you have previously selected a usage code and a language code for multi-lingual text entry. Press **Enter** to display the Item Text Window. This is where you can view text in the selected language to be displayed or printed on external documentation, for example, despatch notes, according to the usage code selected.

F22=Potency

Use this to view potency details for items that are subject to lot, serial or batch control. This displays the Potency Enquiry for your selected item.



Press **Enter** to view a series of similar screens for each stockroom that stocks this item, in stockroom code order.

Item/Stockroom Lot Details Screen



To display this screen select **F13=Lot Details** on Item/Stockroom Enquiry Stockroom Details Screen, if the item is batch, lot or serial controlled.

Use this screen to view a further break down of stock balances by batch number. A list of lots is displayed showing lot balance information.

IN018	Version 3 Demonstration Company	USER STDFIN	3/02/00
			10:21:22
Item / Stockroom Enquiry			
Item.....	50311	Paracetamol 250 tabs/box	
Stockroom.....	FG	Finished Goods	
Issue units.....	BX	Boxes of	
1	Lot	Physical/ frozen	Allocated/ on order
-	WBPC01	1.000 .000	.000 .000
			Available 1.000
1=Receipt costs 2=Lot header 3=Lot trace 4=Potency history 5=Grade history			
F3=Exit F12=Previous F13=Include zero lots F23=More Options			

Fields:

Item

This is the reference code of the item.

Stockroom

This is the reference code of the stockroom.

Issue Units

This is the code for the primary unit of measure.



*Note: If this company uses Catchweight, and the item has a secondary value, when you select **F9=[Short Description]**, the Issue Units field is not displayed.*

Select (1)

For each lot balance, you can enter one of the following:



Note: The options available depend on whether you have made changes to the grade or potency profile of the lot, or both.

1 - Receipt Costs. To view the cost of the items either transferred from a stockroom or received from a supplier. For more information see the Item/Stockroom Receipts Cost Enquiry Screen.

2 - Lot Header. To display the lot header details for this lot. For more information see the Lot Header Details Window.

3 - Lot Trace. To perform a lot trace enquiry. For more information see Lot Trace Enquiry Details Screen.

4 - Potency History. To display the potency history of a particular lot. For more information see Potency History Enquiry Window.

5 - Grade History. To view the grade history of this lot. For more information see Grade History Enquiry.

6 - Allocations. To view any allocations made against this lot. This displays the Allocations Enquiry Window.

Lot

This is the reference code of each lot balance.

Physical/Frozen

These are the physical and frozen quantities of the item for each lot balance.



*Note: If this company uses Catchweight and the item has a secondary value, when you select **F9=[Short Description]**, this field is removed from the screen.*

Physical

If you use Catchweight in this company, and you select **F9=[Short Description]**, this field is displayed. For each lot balance, the physical quantity of the item is displayed in the secondary unit of measure.

Allocated/On Order

These are the allocated and on order quantities of the item for each lot balance.

Available

This is the available quantity of the item for each lot balance.

Secondary UOM

If you use Catchweight in this company and the item has a secondary value, when you select **F9=[Short Description]**, this is the abbreviation of the secondary unit of measure.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is only available when you use Catchweight and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select it to remove the Secondary UOM field from the screen and to display the Issue Units field. Also, the Physical is quantity of the item in the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select it to remove the Issue Units field from the screen and display the Secondary UOM field. Also, the Physical balance displayed is the quantity of the item in the secondary unit of measure.

F13=Include Zero Lots

Use this to include zero lots for this item - and to return to the original details.



Specify an option or select a function key to continue.

Or:

Select **F12=Previous** to redisplay the Item/Stockroom Enquiry Stockroom Details Screen.

Item/Stockroom Receipts Cost Enquiry Screen



To display this screen, enter 1 in the 1 field on the Item/Stockroom Lot Details Screen.

Use this screen to view receipt or transfer cost history for your selected item, lot and stockroom combination.

IN018	Version 3 Demonstration Company	USER STDFIN	3/02/00
			10:21:22
Item / Stockroom Enquiry			
Item.....	50311	Paracetamol 250 tabs/box	
Stockroom.....	FG	Finished Goods	
Issue units.....	BX	Boxes of	
Lot.....	WBPC01		
Date / time received	Original quantity	From supplier/ stockroom	Cost/unit
2/02/00 15:20:36	1.000	01	55.00000
			Balance
			1.000
F3=Exit F12=Previous			

Fields:

Item

This is the item.

Stockroom

This is the stockroom.

Issue Units

This is the primary unit of measure.



*Note: If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]**, the Issue Units field is not displayed.*

Secondary UOM

If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]** this field is displayed instead of the Issue Units field containing the abbreviation of the secondary unit of measure.

Lot

This is your selected lot reference for this item.

Date/Time Received

This is the receipt date and time for each lot balance.

Original Quantity

This is the quantity of the item received, expressed in the primary unit of measure for each lot balance.



*Note: If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]**, this field is replaced by the Original [Short Description] field.*

Original [Short Description]

This field is displayed if you are using Catchweight and you select **F9=[Short Description]**. For each lot balance, the quantity of the item received, expressed in the secondary unit of measure, is displayed in this field.

From Supplier/Stockroom

This is the reference of the supplier or stockroom for each lot balance.

Cost/Unit

This is the cost per unit for each lot balance.

Balance

This is the total balance of each lot balance.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is only available when you use Catchweight and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select it to display the quantity of the item in the Original Quantity field in the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select it to display the quantity of the item in the Original [Short Description] field in the secondary unit of measure.



When you have finished displaying the receipt costs, select **F12=Previous** to display the Item/Stockroom Enquiry Stockroom Details Screen.

Lot Header Details Window



To display this screen, enter 2 in the 1 field on the Item/Stockroom Lot Details Screen.

Use this window to view lot header details for your selected item and lot reference.

IN018		Version 3 Demonstration Company		USER STDFIN	3/02/00
					10:21:22
Item / Stockroom Enquiry					
Item.....	503	Lot Header Details Item number..... 50311 Lot number..... WBPC01 Stockroom..... FG Finished Goods Physical..... 1.000 Allocated..... .000 Available..... 1.000 Actual potency... .35000 % Potent units..... .003 Issue units..... BX Receipt date..... 27/01/00 First avail date. 27/01/00 Last avail date.. 2/02/00 Expiry date..... 20/02/00 Stock status..... FZ Frozen Grade..... GOOD Good Quality Supplier Lot Ref. F12=Previous F21=Text			
Stockroom.....	FG				
Issue units.....	BX				
1 Lot					
2 WBPC01					
1=Receipt costs 2=Lot header 3=Lot trace 4=Potency history 5=Grade history F3=Exit F12=Previous F13=Include zero lots F23=More Options					

Fields:

Item Number

This is the item.

Lot Number

This is your selected lot reference.

Stockroom

This is the stockroom.

Physical

This is the physical stock balance for items with your selected lot reference in your selected stockroom.

If Catchweight is used for this company and the item has a secondary value, the number of items can be displayed in either the primary unit of measure by selecting **F9=Quantity**, or the secondary unit of measure by selecting **F9=[Short Description]**.

Allocated

This is the allocated stock balance for items with your selected lot reference in your selected stockroom.

If you use Catchweight, and you select **F9=[Short Description]**, this field is replaced by the Available field.

Available

This is the available stock balance for items with your selected lot reference in your selected stockroom.

If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]** this field is removed from the screen.

Issue Units

This is the issue unit of measure for this item.



*Note: If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]**, this field is removed from the screen.*

Secondary UOM

If you use Catchweight and the item has a secondary value, when you select **F9=[Short Description]** this field is displayed instead of the Issue Units field, containing the abbreviation of the secondary unit of measure.

Receipt Date

This is the receipt date for the item.

First Avail Date

This is the first date that the items are available to leave the stockroom.

Last Avail Date

This is the last date that the items are available to leave the stockroom.

Expiry Date

This is the expiry date of the items.

Stock Status

This is the current status of the items in the stockroom.

Grade

This is the current grade for lots of this item in the stockroom.

Supplier Lot Ref

This is a specific reference name that is usually provided by your supplier.

Functions:

F9=Quantity/[Short Description]

This toggle function is available only when you use Catchweight and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select it to remove the Physical and Secondary UOM fields for the secondary unit of measure, and display the Physical, Allocated, Available and Issue Units fields for the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of

measure, you can select it to remove the Physical, Allocated, Available and Issue Units fields for the primary unit of measure. This will redisplay the Physical and Secondary UOM fields for the secondary unit of measure.

F17=C-Of-C Reference

Use this to display the Enquire: C-Of-C Reference Window. This window displays all of the valid certificate of conformance details attached to your selected item.



When you have finished displaying the lot header details, select **F12=Previous** to redisplay the Item/Stockroom Lot Details Screen.

Allocations Enquiry Window



To display this window, enter 6 in the 1 field on the Item/Stockroom Lot Details Screen.

Use this window to display any allocated orders linked to this item and stockroom combination.

```

IN018          Version 3 Demonstration Company    USER STDFIN    3/02/00
                                           10:21:22

Item / Stockroom Enquiry

Item..... 50311          Paracetamol 250 tabs/box
Stockroom..... FG        Finished Goods
Issue units..... BX      Boxes of

1  Lot                Physical/    Allocated/    Available
   WBPC01             frozen       on order

6  WBPC01             Allocations Enquiry
                        WBPC01      Batch      More:
                        Sel Reference  Type Due date  Allocated
                        No details exist

                        1=Demand order enquiry
                        F12=Previous

6=Allocations
F3=Exit F12=Previous F13=Include zero lots F23=More Options
  
```

Fields:

Select (Sel)

Enter 1 to display details of the demand order linked to this item and stockroom combination.

Reference

This is the order reference number; this includes the order line number that this item appears on.

Type

This code indicates the type of demand order that this item is allocated to; these are set up within Inventory Descriptions under major type ORTP.

Due Date

This is the date that the customer expects delivery of this stock.

Allocated

This is the quantity of this item, held in this stockroom that is allocated to this demand order.



Select **F12=Previous** to redisplay the Item/Stockroom Lot Details Screen.

Item/Stockroom Lot By Date Details Screen



To display this screen select **F14=Lot By Date** on Item/Stockroom Enquiry Stockroom Details Screen, if the item is batch, lot or serial controlled.

Use this screen to view a further break down of stock balances by date. A list of lots is displayed showing lot balance information. The information this screen displays is very similar to that shown on the Item/Stockroom Lot Details Screen.

IN018	CW - Mitsubishi Fuso Truck (CW)	USER GBJBA1MS	16/02/99
			11:45:34
Item / Stockroom Enquiry			
Item.....	HEB01	Lot Controlled Item 1	
Stockroom.....	01	Stockroom 01	
Issue units.....	BT	Bottles of	
1	Lot	Physical/ frozen	Allocated/ on order
-	LT01	1000.000	.000
		.000	.000
			1000.000
1=Receipt costs 2=Lot header 3=Lot trace 4=Potency history 5=Grade history			
F3=Exit F12=Previous F13=Include zero lots F23=More Options			



Select **F12=Previous** to redisplay the Item/Stockroom Enquiry Stockroom Details Screen

Locations Enquiry Screen



To display this screen, select **F15=Locations** on the Item/Stockroom Enquiry Stockroom Details Screen, if your item is defined to a location controlled stockroom.

Use this screen to view the locations that hold stock of your selected item. The top of the screen displays the item and its description, the selected stockroom, the default location allocated to this item, whether the item has multiple locations associated against it and whether you have chosen stock rotation for your selected item.

The middle of the screen displays the current location, or locations, of the item and any stock balances (in issue units of measure) held against it.

```

IN617              MM - Catchweight Company MM      USER GBJBAHEH  18/10/00
                                           14:43:06
Location Enquiry

Item..... MMBSNM          Normal std 2/loc
Stockroom..... HL          LC Stockroom
Default Location... D06      Multiple Locations... 1 Rotate Stock... 1

S Location              Physical (EA)    Frozen (EA)    Allocated (EA)
- D06                   5.000           .000           .000

1=Rotation Date Balances
F3=Exit F12=Previous F13=Include zero locations
  
```

Fields:

Select (S)

Enter 1 to view rotation date balances for your selected item/location combination.



Note: This field is only displayed if the item is not batch, lot or serial controlled.

Functions:

F9=Quantity/[Secondary Value]

Select this function to view the location level secondary balances if they exist.



Note: You can only use this function if your company is set up as a Catchweight company.

F13=Include Zero Locations

Select this function to view any locations defined to this item in this stockroom, that do not have stock balances. This is a toggle function, if you have selected the

F13=Include Zero Locations to display the locations without stock balances, then the name of the function changes to **F13=Exlude Zero Locations**. If you select this, the zero locations are removed.



Select **F12=Previous** to redisplay the
Item/Stockroom Enquiry Stockroom Details
Screen

Rotation Date Balances Screen



To display this screen, enter 1 against an item's location and press **Enter** on the Locations Enquiry Screen.

Use this screen to view the physical balances for your selected item.

The top of the screen displays details of the selected item code and description, the stockroom and location, and the affected balance in issue units. It displays the location balance from the Locations Enquiry Screen and the sum of the rotation date balances. These two balances should be the same. If they are not, then you can use the Rebuild Balances From Locations option or the Adjust Rotation Date Balances option to reconcile them.

The middle of the screen displays the receipt (or creation) date and the time of that transaction along with the unique reference allocated to that transaction, and the quantity affected by that transaction.

IN614	MM - Catchweight Company MM	USER GBJBAHEH	18/10/00
			14:43:13
Rotation date balance enquiry			
Item.....	MMBSNM	Normal std 2/loc	
Stockroom.....	HL	LC Stockroom	
Location.....	D06	Balance.....	5.000 EA
		Cumulative..	5.000
	Date	Time	Unique Id
	26/09/00	14:07:55	000000000001228
		Quantity	5.000
F3=Exit F12=Previous			



Select **F12=Previous** to redisplay the Locations Enquiry Screen.

Item/Stockroom Enquiry FIFO Cost Details Screen



To display this screen select **F19=FIFO Cost Details** on Item/Stockroom Enquiry Stockroom Details Screen, if the item is FIFO costed.

This screen displays the opening and current position of the unused FIFO batches for an item/stockroom. You can view both date and time details. The list of batches is displayed.

You can view the quantity received from another stockroom or supplier, and the balance of this batch remaining in the stockroom, with the associated cost per unit.



Note: To adjust FIFO records use the FIFO Costs option.

If the chosen item is lot, batch or serial controlled, then you can select the **F19=FIFO Cost Details** function, on the Item/Stockroom Enquiry Stockroom Details Screen, to view this screen, even if the item is not FIFO costed. You can then view the received costs, calculated according to the costing method specified on the Item Maintenance Costing Details Screen.

You can use this screen for lot, batch, and serial controlled items. To do this, enter 1 against a lot for receipt costs from the Lot Details Screen. In this case the costs displayed will only refer to the selected lot.

IN018	Z1 - GB Demonstration Company	USER GBJBA1MS	3/10/00
			15:02:44
Item / Stockroom Enquiry			
Item.....	HEB01	Lot, Grade, Potency, CofC etc	
Stockroom.....	01	Central Stockroom	
Issue units.....	EA	Single of	
Date / time	Original	From supplier/	
received	quantity	stockroom	Cost per EA
_3/10/00 10:26:41	100.000		15.00000
			Balance
			100.000
F3=Exit F12=Previous			



Select **F3=Exit** to exit from the enquiry.

Stock Movements Enquiry



4/INE & 11/DRE

Use this option to view stock movements for an item either in summary or detailed form. You can use the other selection criteria to restrict the number of movements displayed.

Inventory Movements Enquiry Screen



Select Stock Movements.

Use the top section of the screen to enter selection criteria and the lower to choose from a list of permitted movement types.



Note: Page up and down to view more valid movement type codes.

```
IN019          Version 3 Demonstration Company    User STDFIN    3/02/00
                                                    10:34:22

Inventory Movements Enquiry

Item.....?.. _____
Stockroom.....?.. _____
Lot.....?.. _____
From date..... 0/00/00
To date..... 0/00/00
Movement type.....
Summary/detail.... 1    (1=Summary,2=Detail)

                        Valid Movement Types

      A - Stock Adjustment      I - Transfer In
      B - Tfr out of bond      J - Transformation
      C - Customer Order Issue K - Frozen Issue
      D - Direct delivery      L - Allocated Adjustment
      F - Frozen Adjustment     M - Manufacturing Issue
      G - Frozen transfer out   N - Manufacturing Receipt
      H - Frozen transfer in    O - Transfer Out

F3=Exit F4=Prompt
```

Fields:

Item

Enter the item you want to enquire upon.

You can then use any of the following selection criteria to reduce the scope of the subsequent display:

Stockroom

Select a stockroom or leave blank to include all stockrooms in the enquiry.

Lot

Select a lot or leave blank for all lots.

From Date/To Date

Specify a range of dates or leave blank for all dates.

Movement Type

Specify a particular movement type or leave blank for all. You can select a movement type code from the list displayed in the lower half of the screen. Use page up and page down to display more valid movement types.

Summary/Detail

Enter one of the following:

- 1 - To display a summary list with many movements on one screen.
- 2 - To display a detailed enquiry with one movement per screen.



Press **Enter** to confirm the selections and display the screen selected in the Summary/Detail field.

Inventory Movements Summary Screen



To display this screen, enter 1 on the Summary/Detail field on the Inventory Movements Enquiry Screen.

Use this screen to view a summarised list of the selected movements. The most recent movement is displayed first. Use page up and page down to display more movements.

IN019	Z1 - Demonstration Company	User SP1	26/08/94 9:12:00		
Inventory Movements - Summary					
Item.....	5013	Muesli Bar Honey High Fibre 50g			
Reference	Mvt date	Mvt type	Stockroom	Quantity	Units
-	25/08/94	Transfer Out	Central Stockroom	1.000-	BX
-	25/08/94	Transfer Out	Central Stockroom	1.000-	BX
-	25/08/94	Frozen Issue	Central Stockroom	1.000-	BX
-	25/08/94	Frozen Adjustme	Central Stockroom	5.000	BX
-	25/08/94	Allocated Adjus	Central Stockroom	5.000	BX
- Rubik 25a4	25/08/94	Purchase Order	Central Stockroom	1.000	BX
- Init Receipt3	23/08/94	Miscellaneous R	Central Stockroom	450.000	BX
1=Select					
F3=Exit F12=Previous					

Fields:

Select (Untitled)

Enter 1 against the movement you want to view.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is available only when you use Catchweight, and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select **F9** to remove the [Short Description] field for the secondary unit of measure, and display the Quantity field for the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen (where [Short Description] is the nine character description of the secondary unit of measure) you can select **F9** to remove the Quantity field for the primary unit of measure, and display the [Short Description] field for the secondary unit of measure.



Select a movement to continue.

Inventory Movements Detail Screen



To display this screen, enter 2 on the Summary/Detail field on the Inventory Movements Enquiry Screen.

Or:

Enter 1 in the Untitled field on the Inventory Movements Summary Screen.

Use this screen to view the full details of an individual stock movement. There are three groups of data:

- Identification of the movement: Item, stockroom, references and date.
- Movement quantity, the resulting balance after recording the movement, and the movement value.
- Further control information: Lot number, third party (supplier, customer and so on), date, time, terminal, user and the full display of production and lot transformation references, and so on.



Tip: Use page up and page down to view other movements.

IN019	Z1 - GB Demonstration Company	User GBJBAJFW	13/02/98 15:46:11
Inventory Movements - Detail			
Item.....	RPD672C1	Component	
Stockroom.....	AM		
Movement type.....	Manufacturing I		
Movement ref.....	W001597		
Ref. type.....			
Ref. date.....	17/10/97		
Movement Qty.....	5000.000-	Single of----->	
Movement value.....	.00		
Resulting Qty Bal	5000.000-	Single of----->	
To/from.....	W0015970010		
Lot.....			
Reason.....			
Narrative.....	W001597	0010	Route: WIP Lot:
Date.....	17/10/97	Week... 21	Period... 05
Time.....	17:59:49		
Screen.....	ST0396S1		
User.....	GBJBARRC		
F3=Exit F12=Previous			
6-2 SA MW KS CL IM DM II EDN400A KB PET165S2			

Fields:

Narrative

This varies according to the source of the transaction.

For example, if you are processing a Physical Stock Adjustment, you can use the narrative to add key narrative text to the transaction. Other system-generated transactions, for example, Production Issues, use the narrative to store additional information relating to the transaction. So production movements relating to works orders would include the works order, operation, route and work in progress lot number. For repetitive production movements the narrative would contain the parent

item operation, route and work in progress lot number. If the transaction is not related to the works order, then it splits into the item and route.

Movement Qty/(Abbreviation)

This is the amount of the item moved and the unit of measure.

If you use Catchweight and the item has a secondary value, you can select **F9=Quantity/[Short Description]** to toggle between the Movement Qty field for the primary unit of measure and the Movement (Abbreviation) field for the secondary unit of measure.

Resulting Balance/(Abbreviation) Bal

This is the amount of the item left after the movement and the unit of measure.

If you use Catchweight and the item has a secondary value, you can select **F9=Quantity/[Short Description]** to toggle between the Resulting Balance field for the primary unit of measure and the Resulting (Abbreviation) Bal field for the secondary unit of measure.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is available only when you use Catchweight, and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select **F9** to remove the Movement (Abbreviation) and Resulting (Abbreviation) Bal fields for the secondary unit of measure, and display the Movement Qty and Resulting Balance fields for the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select **F9** to remove the Movement Qty and Resulting Balance fields for the primary unit of measure, and display the Movement (Abbreviation) and Resulting (Abbreviation) Bal fields for the secondary unit of measure.



Select **F3=Exit** to exit from the enquiry.

All Stockrooms For An Item Enquiry



5/INE

Use this to view the stock of an item throughout the company at summary level, and then access the standard stockroom enquiry.

All Stockrooms For An Item Enquiry Selection Screen



Select All Stockrooms For An Item.

Use this screen to specify the item whose details you want to view.

IN004	Z1 - GB Demonstration Company	USER GBJBA1MS	3/10/00
All Stockrooms For An Item Enquiry			15:31:45
Item.....?.. _____			
F3=Exit F4=Prompt F14=Enterprise			

Fields:

Item

Enter the item code of the item whose details you want to view.

Functions:

F14=Enterprise

This function is only displayed if you are using Enterprise Orders. You can use this to view the stock position for your selected item over all companies that are defined to your Enterprise.



Enter an item and press **Enter** to display the All Stockrooms For An Item Enquiry Screen.

All Stockrooms For An Item Enquiry Enterprise Wide Screen



To display this screen, enter an item and select **F14=Enterprise** on the All Stockrooms For An Item Enquiry Selection Screen.

Use this screen to view the stock position of your selected item over all companies.

IN004	Z1 - GB Demonstration Company	USER GBJBA1MS	4/10/00
			10:16:37
All Stockrooms For An Item Enquiry - Enterprise Wide			
Item.....?.. 5001 Suncream Factor 4 225ml			
Company/ Stockroom/ units	Frozen/ allocated	On order/ In transit	Physical/ Available
- Catchweight Company MM			
Simple SR Defaults (AL)	.000	.000	100.000
Boxes of	.000	.000	100.000
- GB Demonstration Company			
Cambridge	.000	.000	3994.000
Boxes of	.000	.000	3994.000
- GB Demonstration Company			
D1 General stockroom	.000	.000	19.000
Boxes of	.000	.000	19.000
- GB Demonstration Company			
Finished Goods	.000	869907.000	676.000
Boxes of	32.000	.000	644.00 +
1=Select			
F3=Exit F12=Previous			

Fields:

Select (Untitled)

Enter 1 to display the Item/Stockroom Enquiry Stockroom Details Screen for your selected company and stockroom combination.

Company/Stockroom/Units

This displays the Enterprise company and stockroom combination and the stock unit of measure.

Frozen/Allocated

This displays the quantity of stock that is frozen or allocated, or both, in the stock unit displayed in the Company/Stockroom/Units column.

On Order/In Transit

This displays the quantity of stock that is on order or in transit, or both, in the stock unit displayed in the Company/Stockroom/Units column.

Physical/Available

This displays the quantity of stock that is physically stocked or available, or both, in the stock unit displayed in the Company/Stockroom/Units column.



Select the item, company and stockroom combination that you want to enquire upon and press Enter to display the Item/Stockroom Enquiry Stockroom Details Screen.

Or:

Select **F12=Previous** to redisplay the All Stockrooms For An Item Enquiry Selection Screen.

All Stockrooms For An Item Enquiry Screen



To display this screen, select an item on the All Stockrooms For An Item Enquiry Selection Screen and press **Enter**.

Use this screen to view the summary balance data for each stockroom where the item is stocked. It includes frozen, allocated, on order, in transit, physical and available stock balances.

IN004	Version 3 Demonstration Company	USER STDFIN	3/02/00
			10:38:59
All Stockrooms For An Item Enquiry			
Item.....?.. 50311		Paracetamol 250 tabs/box	
Stockroom/ units	Frozen/ allocated	On order/ In transit	Physical/ Available
- Finished Goods	.000	.000	1.000
- Boxes of	.000	1.000	1.000
- Paris Central Stockroom	.000	.000	.000
- Boxes of	.000	.000	.000
- Central Warehouse	.000	.000	.000
- Boxes of	.000	.000	.000
- Central Stockroom	1.000	10.000	8.000
- Boxes of	.000	.000	7.000
- Northern RDC Stockroom	.000	.000	.000
- Boxes of	.000	.000	.000
- Southern RDC Stockroom	.000	.000	.000
- Boxes of	.000	.000	.000
1=Select			
F3=Exit F12=Previous			

Fields:

Select (Untitled)

Enter 1 against the stockroom to display the Item/Stockroom Enquiry Stockroom Details Screen for your selected item stockroom combination.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is available only when you use Catchweight, and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select **F9** to remove the Physical/In Transit fields for the secondary unit of measure, and display the Frozen/Allocated, On Order/In Transit and Physical/Available fields for the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select **F9** to remove the Frozen/Allocated, On Order/In Transit and Physical/Available fields for the primary unit of measure, and display the Physical/In Transit fields for the secondary unit of measure.



Select **F3=Exit** to exit from the enquiry.

Stock History Enquiry



6/INE

Use this to view stock movement summaries (Stock History) by week or period depending on the usage cycle you have specified on the Inventory Company Profile.

Stock History Enquiry Selection Screen



Select Stock History.

Use this screen to select the item and stockroom combination that you want to view.

IN061	Z1 - Demonstration Company	USER SP1	26/08/94 9:13:25
Stock History Enquiry			
Item.....?.. 5013			
Stockroom.....?.. 01			
F3=Exit F4=Prompt			

Fields:

Item

Enter the item reference number upon which you want to enquire.

Stockroom

Enter a two-character stockroom code where the item is located.



Press **Enter** to display the Stock History Enquiry Screen.

Stock History Enquiry Screen



To display this screen, select an item and stockroom on the Stock History Enquiry Selection Screen and press **Enter**.

The top of the screen displays the average usage of the item in this stockroom.

This is followed by a list of the activity of the item for each week or period that has a movement recorded against it.

IN061	Z1 - Demonstration Company	USER SP1	26/08/94 9:13:30
Stock History Enquiry			
Item.....?	5013	Muesli Bar Honey High Fibre 50g	
Stockroom.....?	01	Central Stockroom	
Units.....	BX	Boxes of	
Period Average....	.000	This Week..	3.000
This Period.....	3.000	This Year..	3.000
Period	Receipts/ P.Orders	Issues/ Adjustments	Transfers
94 08	450.000		2.000-
	1.000	11.000	
F3=Exit F12=Previous			



Note: Use page up and page down to view more movements.



Select **F3=Exit** to exit from the enquiry.

Stock In-Transit Enquiry



7/INE

Use this option to carry out enquiries on Distribution Order lines in-transit between a selected Centre and DC.

These items have been confirmed as despatched from the Centre (via Sales Order Processing or Warehousing), but not yet confirmed as received at the DC (via Distribution Requirements Planning).

Shipments In Transit Enquiry Selection Screen



Select Stock In-Transit.

Use this screen to select all the Distribution Order lines in-transit between a supply Centre and a selected DC, or to display details of lines for one specific order in-transit.

You can select a list of all DCs and a list of all Centres.

IN270	Z1 - GB Demonstration Company	User GJBAMS	15/01/96
			16:57:17
Shipments In-Transit Enquiry			
Enter Stockrooms and/or specific Distribution Order number:			
From Stockroom.....?.. _			
To Stockroom.....?.. _			
Distribution Order Number... _			
F3=Exit F4=Prompt			
07-33 SF MW KS IM II KENB20A PET166S2			

Fields:

From Stockroom

Enter a DC code, you must define this, to at least one Network within DRP.

To Stockroom

Enter a Centre Code, you must define this to at least one Network within DRP.

Distribution Order Number

Enter a valid distribution order, in other words, one confirmed as despatched at the Centre and not yet confirmed as fully received at the DC.



Note: You can select an order without specifying its relevant Centre or DC.



Enter a valid DC/Centre combination or order number, or both, to display the Shipments In Transit Enquiry Screen.

Shipments In Transit Enquiry Screen



To automatically display this screen enter a valid DC/Centre combination or order number, or both, on the Shipments In Transit Selection Enquiry Screen.

The screen displays the Distribution Order line details.

IN270	Version 3 Demonstration Company	User STDFIN	3/02/00
			10:41:21
Shipment In-Transit Enquiry			
From Stockroom... 01 Central Stockroom		From. C1 Central	
To Stockroom..... FG Finished Goods			
Date	Order	Lin Item	SR
2/02/00		1 50311	FG
		Quantity	UoM Lot Number
		1.000	BX WBPC01
F3=Exit F12=Previous			

Fields:

From/To Stockroom

These are default entries from previous screen.

Date

This is the date of despatch from Centre.

Order

This is the Distribution Order Number.

Lin

This is the Distribution Order Line Number.

Item

This is the code for the Item within Inventory Management.

SR

This is the local stockroom for the Item at the DC.

Quantity

This is the amount of the item in-transit between the selected stockrooms. This amount is expressed using the primary unit of measure.

Secondary Val

This is the amount of the item in-transit between the selected stockrooms. This amount is expressed using the secondary unit of measure.

If you use Catchweight and the item has a secondary value, you can select **F9=Quantity/[Short Description]** to remove the Quantity field and display the Secondary Val field.

UOM

This is the unit of measure. If you use Catchweight and the item has a secondary value, you can select **F9=Quantity/[Short Description]** to toggle between the primary and secondary unit of measure.

Lot Number

This is the lot, batch or serial number for a lot, batch or serial controlled Item.

You can amend the stockroom, pack, lot number and rotation date when you confirm receipt of the shipment (via the DRP Processing Option) where appropriate.

Use page up and page down to view any further pages of lines meeting the selection criteria.

Functions:

F9=Quantity/[Short Description]

This is a toggle function, which is available only when you use Catchweight, and the item has a secondary value.

When **F9=Quantity** is displayed at the bottom of the screen, select **F9** to remove the Secondary Val field for the secondary unit of measure, and display the Quantity field for the primary unit of measure.

When **F9=[Short Description]** is displayed at the bottom of the screen, where [Short Description] is the nine character description of the secondary unit of measure, select **F9** to remove the Quantity field for the primary unit of measure, and display the Secondary Val field for the secondary unit of measure.



Select **F3=Exit** to exit from the enquiry.

Alternative Items Enquiry





8/INE

Use this option to view any alternative items that you have set up.



Note: Although you can create alternative items within Inventory Management, they are used during Order Entry.



Alternative Items Enquiry Details Screen



To display this screen, select an item on the Alternative Items Enquiry Selection Screen and press **Enter**.

Use this screen to view details of any alternative items attached to your selected item.

IN006	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99 16:30:43
Alternative Items Enquiry			
Item.....	5001	Suncream Factor 4	225ml
Alternative Item (?)	Description	Reverse (0=No,1=Yes)	
5005	Suncream Factor 4	300ml	1
F3=Exit F12=Previous			

Fields:

Item

This is your selected item and its description code.

Alternative Item

This is the item that you can use as an alternative item during order processing if there is insufficient stock of your selected item.

Description

This is the alternative item's description.

Reverse

If this field displays 1, then you can reverse the relationship between your selected item and its alternative item. For example, if you wanted to sell your alternative item, but there was insufficient stock, then you could use your base item as an alternative.

If this field is blank, then you cannot reverse the relationship.



Select **F3=Exit** to leave the enquiry.

-
-
-
-
-

Chapter 9

Inventory Reports

Item/Stockroom Report



1/INR



Select Item/Stockroom.

Use this to produce a hard copy listing of Items and Stockroom balances. You can select ranges of items, item types, classes or groups to tailor the report. The following specifications are appropriate for this report:

- Frequency - On request.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Overflow.
- Totals - None.



Note: If you use Catchweight, the secondary value, unit of measure, Catchweight type and tolerances are displayed for each item. Also, the secondary unit of measure and description, physical and in-transit stock values and descriptions for each stockroom are displayed.

IN056	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00 11:15:48
Record Report Selection Criteria			
Item summary/detail ? 1 (1=Summary, 2=Detail)			
Stockroom summary/detail ? 1 (1=Summary, 2=Detail)			
	From	To	
Stockroom code.....?	__	__	
Item.....?	_____	_____	
OR			
Item group major/minor.....?	__ __	__ __	
OR			
Item type.....?	_	-	
OR			
Item class.....?	__	__	
Include kits..... 1 (1=components, 2=headers, 3=both)			
F3=Exit F4=Prompt			

Fields:

Item Summary/Detail

Enter one of the following:

- 1 - To produce a summary listing by items on your specific report.
- 2 - To produce a detailed listing by items on your specific report.

Stockroom Summary/Detail

Enter one of the following:

- 1 - To produce a summary listing by stockrooms on your specific report.
- 2 - To produce a detailed listing by stockrooms on your specific report.

You can use one of the following ranges to tailor your report, leave these fields blank to report on all criteria.

Stockroom

Enter a stockroom or a range of stockrooms for inclusion on in this report.

Item

Enter an item or item range for inclusion on in this report.

Item Group Major/Minor

Enter the item group or range of item groups for inclusion on in this report.

Item Type

Enter the item type or range of item types for inclusion on in this report.

Item Class

Enter the item class or range of item classes for inclusion on in this report.

Include Kit

Enter one of the following:

- 1 - Components. To display kit components on the report. This is the default for this field.
- 2 - Headers. To display kit headers on the report.
- 3 - Both. To display both kit components and headers on this report.



Note: This final setting may produce misleading results on the report due to the duplicate representation of each kit in the stockroom.



Press **Enter** to produce the report.

Descriptions File Report



2/INR



Select Descriptions File.

This report lists the details included in the descriptions file. The following specifications are appropriate for this report:

- Frequency - On request.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Overflow.
- Totals - None.



There are no selection criteria needed to produce this report, select **F8=Confirm Submit** to print the report.

Items Flagged For Deletion Report



3/INR



Select Items Flagged For Deletion.

This report lists all items currently flagged for deletion. The report prints the effectivity end date for each item in the list. The following specifications are appropriate for this report:

- Frequency - On request.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Overflow.
- Totals - Total number of items flagged for deletion.



There are no selection criteria needed to produce this report, select **F8=Confirm Submit** to print the report.

Item Audit Report



11/INR



Select Item Audit.

This option prints out of all the changes made to the item file since this was last run. The following specifications are appropriate for this report:

- Frequency - On request. Typically as part of a day or weekend run.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Change of part number.
- Totals - None.



Note: If you use Catchweight, the secondary value, unit of measure, Catchweight type and tolerances are displayed for each item. Also, the secondary unit of measure and description, physical and in-transit stock values and descriptions for each stockroom are displayed.



There are no selection criteria needed to produce this report, select **F8=Confirm Submit** to print the report.

Stockroom Audit Report



12/INR



Select Stockroom Audit.

This option prints out of all the changes made to the stockroom since this was last run. The following specifications are appropriate for this report:

- Frequency - On request - typically part of a day or weekend run.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Overflow.
- Totals - None.



There are no selection criteria needed to produce this report, select **F8=Confirm Submit** to print the report.

Stock Valuation Reports

You can use two reports to produce information about Stock Valuation.

- Stock Movements Valuation Report, which lists stock availability, opening stock levels, movements and closing levels for all items that have moved during the period.
- Stock Valuation Report, which values the physical stock of items or stockrooms.

Stock Movements Valuation Report

1...
2...

21/INR

This report lists the stock availability of an item, or range of items, over a period of time, taking into account both demand and supply orders. Inventory calculates two running totals of stock availability; the first only takes into account demand orders, the second takes into account both demand and supply (in other words a worst and best case).

Proof Of Delivery

If you are using Proof Of Delivery (POD) then the Inventory value includes the value of the physical stock, in-transit stock and that stock awaiting POD (even though the last two balances are not physically present in the stockroom).

When you request a Period End Update the software prompts you to run this report.

Stock Movements Valuation Record Report Selection Criteria Screen



Select Stock Movements Valuation.

Use this screen to select the criteria you want to use to produce the stock movements valuation report.

IN056	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00
			11:17:51
Record Report Selection Criteria			
	From	To	
Stockroom code.....?..	__	__	
Item.....?..	_____	_____	
OR			
Item group major/minor.....?..	__ __	__ __	
OR			
Item type.....?..	_	_	
OR			
Item class.....?..	__	__	
Include kits.....	1	(1=components, 2=headers, 3=both)	
Items with zero balances.....	0	(0=exclude, 1=include)	
F3=Exit F4=Prompt			

Fields:

Stockroom From/To

Enter a range of stockrooms or leave blank to include all stockrooms.

Item From/To

Enter a range of items or leave blank to select all items.

Item Group Major/Minor

Enter a range of major or minor item codes or leave blank to include all major or minor item codes.

Item Type

Enter a range of item type codes or leave blank to include all item type codes.

Item Class

Enter a range of item class codes or leave blank to include all item class codes.

Include Kit

Enter one of the following:

1 - Components. To display kit components on the report. This is the default for this field.

2 - Headers. To display kit headers on the report.

3 - Both. To display both kit components and headers on this report.

Items With Zero Balances

Enter one of the following:

0 - Exclude. To exclude items with zero balances from the report.

1 - Include. To include items with zero balances in the report.



Note: If you use Catchweight, the secondary values and unit of measure are displayed.



Press **Enter** to submit the report.

Stock Valuation Report



22/INR

Use this report to value the physical stock of the requested items or stockrooms.
The following specifications are appropriate for this report:

- Frequency - On request. Typically as part of the month end processing stock taking problems.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Change of part number.

Totals - At change of stockroom and at the end of the report, the report prints a total stock value.

Stock Valuation Record Report Selection Criteria Screen



Select Stock Valuation.

Use this screen to specify the selection criteria you want to use to produce the stock valuation report.

IN056	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00 11:18:30
Record Report Selection Criteria			
	From	To	
Stockroom code.....?..	—	—	
Item.....?..	—	—	
OR			
Item group major/minor.....?..	— —	— —	
OR			
Item type.....?..	—	—	
OR			
Item class.....?..	—	—	
Include kits.....	1 (1=components, 2=headers, 3=both)		
Items with zero balances.....	0 (0=exclude, 1=include)		
F3=Exit F4=Prompt			

Fields:

Stockroom From/To

Enter a range of stockrooms or leave blank to include all stockrooms.

Item From/To

Enter a range of items or leave blank to select all items.

Item Group Major/Minor

Enter a range of major or minor item codes or leave blank to include all major or minor item codes.

Item Type

Enter a range of item type codes or leave blank to include all item type codes.

Item Class

Enter a range of item class codes or leave blank to include all item class codes.

Include Kit

Enter one of the following:

1 - Components. To display kit components on the report. This is the default for this field.

2 - Headers. To display kit headers on the report.

3 - Both. To display both kit components and headers on this report.

Items With Zero Balances

Enter one of the following:

0 - Exclude. To exclude items with zero balances from the report.

1 - Include. To include items with zero balances in the report.



Tip: You can choose to include kit components, headers or both on the report.



Note: If you use Catchweight, the secondary values and unit of measure are displayed.



Press **Enter** to process the report.

Movements Audit Report



31/INR



Select Movements Audit.



Note: As this report details all movements since the report was last run, it is important to run this report at regular intervals regardless to whether you print it or not.

Use this report to detail all movements of all items since the report was last run. The software then purges the file. The following specifications are appropriate for this report:

- Frequency - As required, but you should normally run it as part of a day or weekend run.
- Stationery - Standard listing paper.
- Print positions - 132.
- New Page - Change of part number.
- Totals - Movement value by transaction type, for each stockroom.

You can run this option straight from the menu.



Note: If you use Catchweight, the secondary values and unit of measure are displayed.



There are no selection criteria needed to produce this report, select **F8=Confirm Submit** to print the report.

Movement Reports

You can use two reports to produce information about Stock Movement.

- Movements Processed By AFI Report, which lists stock movements processed via Advanced Financial Integrator.
- Stock Movements Report, which can produce a number of user defined stock movement lists.

Movements Processed By AFI Report

1...
2...

32/INR



Select Movements Processed By AFI.

Use this option to provide a hard copy print of a selection of stock movements that processed via the Advanced Financial Integrator (AFI) in a number of different sequences.

IN050	Version 3 Demonstration Company	User STDFIN	3/02/00 10:44:23
Request Movements Processed via AFI Report - Selection			
Stockroom.....?..	___		
Item.....?..	_____		
Item group major....?..	___		
Item group minor....?..	___		
Reference date.....	_____	_____	
Movement date.....	_____	_____	
Movement type.....?..	___		
Week no.(YYWW).....	0000		
Period no.(YYPP).....	0000		
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom on which you want to produce the report, using up to two alphanumeric characters. To print all stockrooms leave blank.

Item Number

Specify the item you want to include on the report using up to fifteen alphanumeric characters. To print all items leave blank.

Item Group Major

Enter the major item group you want to produce the report on.

For a report of movements for all major item groups, leave blank.

Item Group Minor

Enter the minor item group you want to produce the report on.

For a report of movements for all minor item groups, leave blank.

Reference Date

To print a report of movements for a particular reference date, enter a single date. Leave blank to print a report for all reference dates.

Movement Date

Enter up to two valid dates to specify the movements you want to include. This will print any movements made between the dates specified. To print movements for a particular day enter just one date. Leave both fields blank to print all movements.

Movement Type

Specify the movement type to print on the report using a one-character code, or leave blank to print all movement types.

Week Number

Specify the week number of the movements you want to print using four numeric characters, format WWYY. If this field is blank the report will detail all movements that satisfy previous selection criteria regardless of week number.

Period Number

Specify the period number of the movements you want to print using four numeric characters, format PPYY. If this field is blank the report will detail all movements that satisfy any of the above selection criteria regardless of period number.



Press **Enter** and then select **F8=Submit** to send the report to print.

Stock Movements Report

1...
2...

33/INR

Use this option to produce a hard copy print of a selection of stock movements in a number of different sequences.

Request Stock Movements Report Selection Screen



Select Stock Movements.

Use this screen to specify the stock movements criteria that you want to report on.

IN050	Z1 - Demonstration Company	User SP1	26/08/94 9:16:12
-------	----------------------------	----------	---------------------

Request Stock Movements Report - Selection			
Stockroom.....?..	01	Central Stockroom	
Item.....?..	5013	Muesli Bar Honey High Fibre 50g	
Item group major....?..	—		
Item group minor....?..	—		
Reference date.....	200804	260894	
Movement date.....	—	—	
Movement type.....?..	—		
Week no.(WWYY).....	—		
Period no.(PPYY).....	—		

F3=Exit	F4=Prompt	F8=Submit
---------	-----------	-----------

Fields:

Stockroom

Enter the stockroom on which you want to produce the report, using up to two alphanumeric characters. To print all stockrooms leave blank.

Item Number

Specify the item you want to include on the report using up to fifteen alphanumeric characters. To print all items leave blank.

Item Group Major

Enter the major item group you want to produce the report on.

For a report of movements for all major item groups, leave blank.

Item Group Minor

Enter the minor item group you want to produce the report on.

For a report of movements for all minor item groups, leave blank.

Reference Date

To print a report of movements for a particular reference date, enter a single date. Leave blank to print a report for all reference dates.

Movement Date

Enter up to two valid dates to specify the movements you want to include. This will print any movements made between the dates specified. To print movements for a particular day enter just one date. Leave both fields blank to print all movements.

Movement Type

Specify the movement type to print on the report using a one-character code, or leave blank to print all movement types.

Week Number

Specify the week number of the movements you want to print using four numeric characters, format WWYY. If this field is blank the report will detail all movements that satisfy previous selection criteria regardless of week number.

Period Number

Specify the period number of the movements you want to print using four numeric characters, format PPYY. If this field is blank the report will detail all movements that satisfy any of the above selection criteria regardless of period number.



Press **Enter** and then select **F8=Submit** to send the report to print.

Reporting On Negative Stock

You can use two reports to produce information about Negative Stock:

- The Negative Stock Report, which lists any stock that has become negative as a result of an inventory transaction.
- The Negative Stock Periodic Parameters Report, which you can use to set the parameters when you run the Negative Stock Report automatically using Machine Manager.

Negative Stock Report

1...
2...

34/INR



Select Negative Stock.

Use this option to highlight stock that has been allowed to go negative for any transaction that reduces stock levels.

IN274	NR - Neil's Test Company	User GJBANER	21/05/96 10:45:29
Request Negative Stock Report - Selection			
Stockroom	?	—	
Item	?	—	
From date		21/05/96	
To date		21/05/96	
Control flag	@	0=Report only 1=Report & delete 2>Delete only 3=Report,delete and adjust FIFO items	
F3=Exit F4=Prompt F8=Submit			
05-25	SA	MW	KS IM II KENB20A PET178S1

Fields:

Stockroom

Enter a valid stockroom code.

Item

Enter the item code that you want to produce the report upon.

From Date/To Date

Specify the period that you want to produce the report upon.

Control Flag

Enter one of the following:

- 0 - To only produce a report. This writes the record to the negative stock data file.
- 1 - To produce a report and deletes the any negative stock movements that have been previously written to the negative stock data file.
- 2 - To delete the negative stock movement data only.
- 3 - To produce a report, delete the stock movements and adjust negative FIFO records produced by value only adjustments.



Note: GEAC recommend that you use this option to produce the report first, then use the option again to process any deletions and so on.



Select **F8=Submit** to send the report to print.

Negative Stock Periodic Parameters Report

1...
2...

35/INR



Select Negative Stock Periodic Parameters.

You use this screen to amend the periodic parameters.

IN274	NR - Neil's Test Company	User GBJBANER	21/05/96
			10:51:41
Negative Stock Report Periodic Parameter Maintenance			
Stockroom?.. █			
Item.....?.. _____			
Control flag..... @ 0=Report only 1=Report & delete 2=Delete only 3=Report,delete and adjust FIFO items			
F3=Exit F4=Prompt F8=Update			
05-25 SA MW KS IM II KENB20A PET178S1			

Fields:

Stockroom

Enter a valid stockroom code.

Item

Enter the item code that you want to produce the report upon.

Control Flag

Enter one of the following:

- 0 - To produce the report only.
- 1 - To produce the report and delete the item(s).
- 2 - To delete the item(s) only.
- 3 - To produce a report, delete and adjust FIFO items.



Press **F8=Update**.

Non-Moving Items Report



36/INR

This report lists the last movements of both items that have no movements recorded against them since the selected last movement date, and items that have no movements at all.

You should run this report as part of the period end routines.

The report excludes the following:

- New items whether they have movements in the current period or not. This is because the software does not create a Movement Analysis record for the current period unless the stockroom had undergone a trial fiscal close.
- All items in stockrooms not under fiscal open and close control.

The report includes the following:

- Slow moving items that have moved during the current period, but whose previous movement was before the selected last movement date. Again, the items' inclusion in the report is due to the Movement Analysis record for the current period not being created.

You can also include Miscellaneous Receipts within this report, depending on how you have set up your Inventory Management's Company Profile.

Movement Analysis records holds two dates of last receipt, one includes miscellaneous receipts, the other does not, so this report can include items that have a recent miscellaneous receipt.

Report On Non-Moving Items Selection Screen



Select Non-Moving Items.

Use this screen to select report criteria.

```

IN591                Z1 - GB Demonstration Company    User GBJBA1MS    3/02/98
                                      17:01:00

Report on Non-Moving Items

Report criteria..... 1  1=by stockroom, 2=by item

Item..... 1  1=Range,2=List
Movement Type..... 3  1=Issues, 2=Receipts, 3=Both
Last Movement Date.... 1/01/96

Site.....?.. _____
or
Stockroom..... 2  1=Range,2=List

-----
F3=Exit  F4=Prompt

-----
5-25  SA  MW  KS  CL  IM  DM  II  MARVIN  KB  PET087S1
  
```

Fields:

Report Criteria

Enter one of the following:

- 1 - To produce the report by stockroom.
- 2 - To produce the report by item.

Item

Select to produce the report on one of the following:

- 1 - A range of items.
- 2 - A list of items.

Movement Type

Select one of the following:

- 1 - Report on Issues.
- 2 - Report on Receipts.
- 3 - Report on Both.

Last Movement Date

Enter the date of the last movement on which to base the report. The format for the date is DDMMYY.



Note: If you select to produce the report by stockroom you must either enter a site to produce the report on, or elect to produce the report on a range or list of stockrooms

Site

Enter the site on which to produce the report.

Stockrooms

Or select to produce the report on one of the following:

1 - A range of stockrooms.

2 - A list of stockrooms.



Note: The choice of criteria selected on this screen will determine the appearance of the second selection screen.



Press **Enter** to display the Report On Non-Moving Items By Stockroom Screen.

Report On Non-Moving Items By Stockroom Range Screen



To display this screen, enter 1 in report criteria, 1 in both the Item and Stockroom fields, select other report requirements on Report On Non-Moving Items Selection Screen and press **Enter**.

Use this screen to determine the item/stockroom ranges on which you want to process the report.



Note: If you enter 2 in the Stockroom field you can use this screen to select a list of stockrooms rather than a range. In this case, the title of the screen changes to Report On Non-Moving Items By Stockroom List Screen.

IN591	Version 3 Demonstration Company	User STDFIN	3/02/00 10:46:27
Report on Non-moving Items - by stockroom			
Movement Type..... Both			
Last Movement Date.... 2/02/00			
Item From.....?.. _____		To..?. _____	
Stockroom From.....?.. _		To..?. _	
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Movement Type

This is the movement type on which you have chosen to base the report.

Last Movement Date

This is the last movement date on which you have chosen to base the report.

Item From And To

Enter the range of items on which you want to base the report.

Stockroom From And To

Enter the range of stockroom codes on which you want to base the report.



Note: If you selected to produce a report on a list of stockrooms, then there would be a number of entry fields on this screen so that you could specify the exact stockrooms on which you want to produce the report.



Select **F8=Submit** to process the report using a batch job.



Use this screen to determine the item range on which you want to process the report.



```
IN591                Z1 - GB Demonstration Company      User GBJBA1MS      4/10/00
                                                           11:20:45

Report on Non-moving Items - by stockroom

Movement Type..... Both
Last Movement Date... 1/01/00

Item From.....?.. _____ To..?. _____
Stockroom?
-----

F3=Exit  F4=Prompt  F8=Submit  F12=Previous
```

Enter a list of stockroom codes on which you want to base the report.



Note: If you selected to produce a report on a list of items, then there would be a number of entry fields on this screen so that you could specify the exact items on which you want to produce the report.



Select **F8=Submit** to print the report.

Report On Non-Moving Items By Site Screen



To display this screen, enter 1 in report criteria, 1 in the Item field and a site code in the Site field select other report requirements on the Report On Non-Moving Items Selection Screen and press **Enter**.

Use this screen to determine the item range on which you want to process the report.



Note: If you enter 2 in the Item field you can use this screen to select a list of items rather than a range. In this case, the title of the screen changes to Report On Non-Moving Items By Item List Screen.

```
IN591                Z1 - GB Demonstration Company    User GBJBA1MS    4/10/00
                                                           11:21:36
Report on Non-moving Items - by stockroom

Movement Type..... Both
Last Movement Date.... 1/01/00
Site..... DFW          David
Item From.....?.. _____ To..?.. _____

F3=Exit F4=Prompt F8=Submit F12=Previous
```

Fields:

Movement Type

This is the movement type on which you have chosen to base the report.

Last Movement Date

This is the last movement date on which you have chosen to base the report.

Site

This displays your selected site code and its associated description.

Item From And To

Enter the range of items on which you want to base the report.



Note: If you selected to produce a report on a list of items, then there would be a number of entry fields on this screen so that you could specify the exact items on which you want to produce the report.



Select **F8=Submit** to print the report.

Negative Locations Report



37/INR

Use this report to list locations where the physical balance is negative, the frozen balance is negative or the physical balance is less than the frozen balance. You can select to produce the report on one, or all location controlled stockrooms, and a range of locations within those stockrooms.



Note: If you use Catchweight, then this report will also include any locations where the secondary balance is negative.

Request Negative Locations Report Selection Screen



To display this screen, select Negative Locations.

Use this screen to determine the selection criteria on which you want to produce the report.

IN628	MM - Catchweight Company MM	USER GBJBA1MS	17/02/00 16:05:52
Request Negative Locations Report - Selection			
Stockroom.....?..	__	(Leave blank for all stockrooms)	
Location Range From.?..	_____	(Leave From/To Blank for all	
To...?..	_____	locations)	
F3=Exit F4=Prompt F8=Submit Job			

Fields:

Stockroom

Enter the stockroom code for the stockroom that you want to produce this report on. This must be a location controlled stockroom.

Leave this field blank to produce a report on all location controlled stockrooms.

Location Range From..

Enter the starting value of the range of locations that you want to include in this report.

To..

Enter the closing value of the range of locations that you want to include in this report.



Note: If you have not specified a stockroom code in the Stockroom field, then the range of location codes specified in these fields will apply over all location controlled stockrooms.



Select **F8=Submit Job** to produce the report.

Re-Order/Overstock Report



41/INR

Use this option to produce a report on stock levels compared to maximum stock levels and re-ordering points. This also reports on the recommended order quantity or if there is a stock excess.

You can select to produce the report in either item within stockroom or stockroom within item bias. You can choose to have all items in the report, or only those with movements since the report was last run.

Re-Order/Overstock Report Screen



Select Re-Order/Overstock.

Use this screen to select the report you want to produce, in either *item within* stockroom, or *stockroom within item* sequence.

```
IN034                Z1 - UK Demonstration Company    USER GBJBALTW    3/06/98
                                                           12:32:56
Request Reorder/Overstock Report

Sequence..... 2    (1=Item/Stockroom, 2=Stockroom/Item)
All items..... 2    (1=All items, 2=Just those items that have moved
                       and not yet been reported)

F3=Exit
```

Fields:

Sequence

Enter one of the following:

- 1 - To produce a report in item then stockroom sequence.
- 2 - To produce a report in stockroom then item sequence.

All Items

Enter one of the following:

- 1 - All Items.
- 2 - Just those items that have moved and not yet been reported.

If you use Requisitioning, you can use a similar option to produce additional reports, and you can subdivide this report by Requisition, Purchasing Officer and Supplier.



Select **Enter** to process the report.

Stock Availability Report



42/INR



Select Stock Availability.

Use this option to provide information on stock levels, current customer orders and other demands for all the selected items.

```
IN063          Z1 - UK Demonstration Company  USER GBJBAJSS  26/01/00
                                                    10:07:40
Stock Availability Report

Please enter selection criteria for the Stock availability report:-

Item FROM.....?.. _____ (Leave blank for all items)
Item TO.....?.. _____
Stockroom FROM.....?.. _____ (Leave blank for all Stockrooms)
Stockroom TO.....?.. _____

Do you require Allocations to be printed... 0 (0=No, 1=Yes)
Do you require Reservations to be printed.. 0 (0=No, 1=Yes)

F3=Exit F4=Prompt
MA a MW 10/029
```

Fields:

Item From and To

Enter a range of item codes, or leave blank to produce a report on all items.

Stockroom From and To

Enter a range of stockroom codes, or leave blank to produce a report on all stockrooms.



Tip: Leave both the Item and Stockroom fields blank to produce a report on all items in all stockrooms.

Do You Require Allocations To Be Printed

Enter one of the following:

- 0 - To not print current stock allocations.
- 1 - To print current stock allocations.

Do You Require Reservations To Be Printed

Enter one of the following:

- 0 - To not print current stock reservations.

1 - To print current stock reservations.



Press **Enter** to run the report.

Supply/Demand Exceptions Report



43/INR & 1/AOR



Select Supply/Demand Exceptions.

Use this option to detail any changes affecting sales orders reserved against supply orders, for example purchase to order, make to order or direct delivery orders created in Advanced Order Entry.

The report shows the following sales order details, you can also report on the supply order details, for each purchase to order and direct delivery order where changes have occurred. It shows all incidents since the report was last run.

- Supply order type.
- Demand order type.
- Supply reference number.
- Demand reference number, supplier code and name.
- Customer code and name.
- Item code and description.
- Stockroom code and description.
- Original quantity.
- Action quantity.
- Order Due date.

You can also view the reason for the amendment this can include:

- Sales order amended.
- Production items master missing.
- Standard planning route not found.
- Sales order suspended, cancelled or a quotation.
- Production order quantity too small.
- Production order completion too late.
- Production order excess quantity.

IN068	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00 11:22:45
Exception Report Prompt			
Report to be sequenced by <u>3</u>		1 = Purchasing sequence 2 = Sales order sequence 3 = Both	
Include purchase orders... <u>1</u>		(1=Yes, 0=No)	
Include works orders..... <u>0</u>		(1=Yes, 0=No)	
F3=Exit F8=Submit			

Fields:

Report To Be Sequenced By

Enter one of the following to determine the order sequence for your report:

1 - Purchasing sequence.



Note: If you select this option, you must take the option to include purchase orders.

2 - Sales order sequence.

3 - Both.

Include Purchase Orders

If you have selected to sequence your report by purchase orders you *must* enter 1 to include details of the supply orders corresponding to the sales orders included in the report, otherwise enter 0.

Include Works Orders

Enter 1 to include details of the works orders corresponding to the sales orders included in the report, otherwise enter 0.



Select **F8=Submit** to produce the report.

Rotation Factors Report



44/INR

Inventory calculates stock rotation factors for items based on their recent usage. The factor is defined as the total usage across a selected number of periods (which you select), divided by the average stock level.

You can calculate an items' average stock level as the sum of the closing balances divided by the number of periods.

Inventory processes this calculation each time you run the report. The latest rotation factor and the number of periods used in the calculation are held on the file. You can view them using the Movement Analysis Enquiry. Inventory excludes details for the current period as the period is incomplete.



Note: The software calculates rotation factors from the Movement Analysis records, these are created for items in stockrooms with fiscal control.

Stock Rotation Factor Report Selection Screen



Select Rotation Factors.

Use this screen to select report criteria.

```
IN589          Z1 - GB Demonstration Company   User GBJBA1MS   3/02/98
                                           17:06:07

Stock Rotation Factor Report

Report criteria..... 1 1=by stockroom, 2=by item

Item..... _ 1=Range,2=List
No. of Periods..... 6

Site.....?.. _____
or
Stockroom..... _ 1=Range,2=List

-----
F3=Exit F4=Prompt

-----
5-25  SA  MW  KS  CL  IM  DM  II  MARVIN  KB  PET087S1
```

Fields:

Report Criteria

Enter one of the following:

- 1 - To produce the report by stockroom.
- 2 - To produce the report by item.

Item

Select to produce the report on one of the following:

- 1 - A range of items.
- 2 - A list of items.

No. Of Periods

Define the number of periods' usage on which to base the calculations.



Note: You can produce the report by stockroom and either enter a site or a range or list of stockrooms to produce the report on.

Site

Select a site on which to produce the report.

Stockrooms

Or select to produce the report on one of the following:

1 - A range of stockrooms.

2 - A list of stockrooms.



Note: The criteria you select on this screen will determine the appearance of the second selection screen.



Press **Enter** to display the Stock Rotation Factor Report By Stockroom Screen.

Stock Rotation Factor Report By Stockroom Screen



To display this screen, enter 1 in the Report Criteria, Item and Stockroom fields on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item/stockroom ranges on which you want to process the report.

IN589	Z1 - GB Demonstration Company	User GBJBA1MS	3/02/98 17:07:07
Stock Rotation Factor Report - by Stockroom			
No. of Periods..... 06			
Item From.....?.. █		To..?. _____	
Stockroom From.....?.. _		To..?. _____	
F3=Exit F4=Prompt F8=Submit F12=Previous			
7-25 SA MW KS CL IM DM II MARVIN KB PET087S1			

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Item From And To

Enter the range of items on which you want to base the report.

Stockroom From And To

Enter the range of stockrooms on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

Stock Rotation Factor Report By Item Screen



To display this screen, enter 2 in the Report Criteria field and 1 in the Item field on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item range on which you want to process the report.

IN589

Z1 - GB Demonstration Company

User GBJBA1MS

3/02/98
17:07:31

Stock Rotation Factor Report - by item

No. of Periods..... 06

Item From.....?.. To...?.

F3=Exit F4=Prompt F8=Submit F12=Previous

7-25 SA MW KS CL IM DM II MARVIN KB PET087S1

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Item From And To

Enter the range of items on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

Stock Rotation Factor Report By Stockroom And Item List Screen



To display this screen, enter 1 in the Report Criteria field, 2 in the Item field and 1 in the Stockroom field on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item range on which you want to process the report.

IN589	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00 11:24:34
Stock Rotation Factor Report - by Stockroom			
No. of Periods..... 06			
Item?			
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
Stockroom From.....?.. __		To..?.. __	
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Item

Enter a list of the items on which you want to base the report.

Stockroom From.. To..

Enter a range of the stockrooms on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

Stock Rotation Factor Report By Stockroom List And Item List Screen



To display this screen, enter 1 in the Report Criteria field, 2 in the Item field and 2 in the Stockroom field on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item range on which you want to process the report.

IN589 Z1 - GB Demonstration Company User GBJBA1MS 4/10/00
11:33:40

Stock Rotation Factor Report - by Stockroom

No. of Periods..... 06

Item?

_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____

Stockroom?

F3=Exit F4=Prompt F8=Submit F12=Previous

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Item

Enter a list of the items on which you want to base the report.

Stockroom

Enter a list of the stockrooms on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

Stock Rotation Factor Report By Site And Item Range Screen



To display this screen, enter 1 in the Report Criteria field, 1 in the Item field and a site code on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item range on which you want to process the report.

IN589	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00
			11:34:35
Stock Rotation Factor Report - by Stockroom			
No. of Periods..... 06			
Site..... DFW David			
Item From.....?.. To..?..			
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Site

This is the site that you selected on the Stock Rotation Factor Report Selection Screen.

Item From.. To..

Enter a range of the items on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

Stock Rotation Factor Report By Site And Item List Screen



To display this screen, enter 1 in the Report Criteria field, 2 in the Item field and a site code on the Stock Rotation Factor Report Selection Screen and press **Enter**

Use this screen to determine the item range on which you want to process the report.

IN589	Z1 - GB Demonstration Company	User GBJBA1MS	4/10/00
			11:35:04
Stock Rotation Factor Report - by Stockroom			
No. of Periods..... 06			
Site..... DFW		David	
Item?			
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

No Of Periods

This is the number of periods on which you have chosen to base the report calculations.

Site

This is the site that you selected on the Stock Rotation Factor Report Selection Screen.

Item

Enter a list of the items on which you want to base the report.



Select **F8=Submit** to process the report using a batch job.

-
-
-
-
-

Chapter 10

Inventory Management Utilities

Location Control Introduction

You use Location Control as an alternative to Warehousing as it provides location control without the full disciplines required within Warehousing. Location Control also delivers more stock control features than Inventory Management.

Another name for Location Control is Stock Locator.

Before you can install and activate Location Control, you must install Inventory Management. Although Location Control is a separate application, it does not have software of its own, it is integrated throughout System 21 to process stock movements. The applications most affected by Location Control are:

- Inventory Management.
- Catchweight.
- Order Entry.
- Purchase Management.
- Customer Returns.
- Production.

Implementing Location Control

Before you can start to use Location Control, you must:

- Create the Location Control application in Application Manager and apply the authorisation codes. For more information, see your Systems Manager.
- Set up the Stockroom Profile in Inventory Company Maintenance.
- Create the Location Control Stockroom Profile details.
- Create the Location Control Location Map.
- Create as many of the Location Control Item/Stockroom profiles as required. The Data Take-On Maintenance option will create any missing Location Control item/stockroom profiles from the stockroom's default values.
- Complete or cancel as many outstanding pick notes and pull lists as possible.
- Activate Location Control for the stockroom.
- Use the Location Data Take-On Maintenance option to populate the item's default location.
- Perform a stocktake, or location to location transfers, to make sure that you correctly distribute the stock across the locations.



Note: Although the location to location transfer is a simple operation, GEAC recommend that you process a full stocktake as you can use it to test your implementation. Inaccurate location balances substantially reduce the benefits of Location Control.

If you are going to use Location Control within Production, you must create Location Control details within Routes/Structures Maintenance, Text Type and Additional Text Maintenance.

Location Control – Key Points

Although Location Control is integrated with existing applications, you must create the Location Control application so that you can apply an authorisation code to it, and so activate it. If you do not activate Location Control, then System 21 Inventory, Order Entry, Purchase Management, Customer Returns and the Production applications are not affected.

The main features of Location Control are:

- Stockroom Specific
 - Location Control is applied at stockroom level. You can also set Location Control defaults at item/stockroom level
 - You can use Location Control in a company which has stockrooms that are controlled by both Inventory and Warehousing. Stockrooms can be controlled by Inventory, Warehousing or Location Control
 - You can set up all details required by Location Control before you activate it
 - You can use a new data take-on option to convert an existing stockroom to a location controlled stockroom.
- Locations
 - Each Location Control activated stockroom has two subdivisions, which are called In Use and Suspended. These subdivisions have no capacity or proximity limitations
 - You can create locations in ranges to make the creation process quicker.
- Location Balances
 - Physical and frozen balances are maintained by location
 - If you activate both Location Control and Catchweight, then you can choose to maintain secondary balances by location.
- Stock Rotation

Stock rotation is an important requirement for many organisations. You can choose to record stock rotation for both lot, batch and serial controlled items and non-lot controlled items. If you use either form of stock rotation you do not need to enter or select stock by rotation date.

- For non-lot controlled items, the stock rotation date is the date that the stock was received into the location. The system maintains a set of rotation date balances for each item by location. Receipts create new balances and receipt reversals consume these balances in LIFO sequence. Other transactions (issues, transfers and adjustments) consume the balances in FIFO sequence when the transaction reduces the stock balance, and increases the stock of the oldest balance when the transaction increases the stock balance.

- For lot controlled items, the stock rotation date is the lot's last available date. The date is calculated and maintained by the existing extended lot header options within System 21
 - If you do currently use extended lot header details, then you can use a new option to activate them for existing lots, batches or serial controlled items. For more information, see the Advanced Allocations Options Screen.
- Event Allocation
This is the batch process that selects which location balances are to be used on a picking note or pull list. It also allocates the lot balances.
- Planned Issues
 - When you produce picking notes for sales orders and shop documentation for production issues, they will list the lots or the locations, or both, to pick from
 - These details are displayed during confirmation so that you can confirm the despatch or issue without any other data entry, apart from any overrides that are necessary. You can therefore, confirm sales orders in batch
 - The picking logic takes into account any stock that is committed to outstanding issues when selecting the lot or location balances, or both, that Inventory can pick stock from. You can now automatically allocate lot balances in Production
 - If lot balances are manually allocated, these are honoured.
- Other Stock Movements
 - Each item has a default location in a Location Controlled stockroom. If you process an unplanned transaction, then the default location is presented as the suggested location for the item
 - You can spread a single transaction over several locations
 - You can use the Single Step Transfer option to transfer stock from location to location.
- Single Location Items
 - You can restrict an item to its default location. This means that you do not need to capture the location balances during transactions.
- Location Prompts
 - When you process a receipt, the locations where the item is currently stocked are displayed at the top of the list, with their current balances
 - When you process an issue, only locations with stock for the item are displayed, with their current balances.
- Processing Stocktaking

When you activate Location Control, you can process stocktakes by:

- Range of locations
- Range of items
- ABC classification.

- Enquiries and Reports
 - You can use the Item/Stockroom Enquiry and the Stock Enquiry in Sales Order Processing to view the location balances by item. You can also use the same Location Balances By Item enquiry to view item balances by rotation date.
 - You can produce a report to list negative location balances.

Constraints

- Integrated Applications

Location Controlled stockrooms can be used by all stock balance affecting applications, with the following exceptions:

- Advanced Receiving
- Advanced Shipping
- Service Management
- Workshop Management.



Warning: These applications do not recognise Location Controlled stockrooms and so do not issue a warning if you are about to use one. This means that the location balances are not updated. The Rebuild Balance options Reconciliation report will identify the stock imbalance, but there is no easy method of rectifying the discrepancy as it works from location balances upwards. Some options may terminate abnormally if they attempt to update the location balances with missing Location Control data.

- Stock Rotation - For lot, batch and serial controlled items, the prerequisites are extended lot, batch and serial header details. This is because the Location Control program uses the last available date on the lot header as the stock rotation date.
- Automatic Lower Level Allocation - This is mandatory for Location Controlled stockrooms. This means that the Sales Order Processing picking program can allocate lots, batches and serial numbers.
- Manual Allocation Of Stock By Locations is not supported. Location balances are only committed with the pick note or production pull list is raised.
- Locations cannot be assigned to customers, suppliers, vans and so on. They cannot be designated as consignment stock, inspection, quarantine or marshalling locations. A location is simply a sub-division of a stockroom.
- Missing Location Control Item/Stockroom profiles cannot be created during a transaction. You must end the transaction and create the required profiles before you can complete the transaction. As these are now created by the Location Balance Data Take-On option or the Rebuild Balances For Locations option, this situation should not arise. Once a stockroom has been activated as

Location Controlled, you cannot add a new item/stockroom profile without also adding the corresponding Location Control item/stockroom profile.

- The Negative Stock Window is displayed after the location balances have been entered. This is because the negative stock processing also checks for the Catchweight balances and these are captured at the same time as the location balances. You will only view this window if negative stock is allowed for a stockroom, as the negative location stock error will have already occurred when negative stock is not allowed. When negative stock is allowed warning messages are displayed at location level and another warning is displayed at stockroom level.
- Location Balance Movement records are written for each movement, but they are audit records, so you cannot enquire or report on them.
- Kit parents are best defined for non stock items for a variety of reasons. If then have been defined as stocked items, then the system will expect a Location Control Item/Stockroom profile to exist for each parent. When you raise a picking note the location will be Unspecified because there is no stock of a kit parent, but the subsequent confirmation will ignore this.
- During a Single Step Transfer you can select a line for amendment, if you do this, the previously entered location details for this item are lost.



Warning: Warehousing and Location Control are mutually exclusive for the same stockroom. You cannot place an active location controlled stockroom under warehouse control. Warehousing and Location Control profiles can exist for the same stockroom as long as one or neither is active.

To convert a Warehousing Controlled stockroom to a Location Controlled stockroom you must:

1. Set up Location Control.
2. Deactivate Warehousing for your selected stockroom; to do this select **F14=Activate/Deactivate** in the Warehouse Profile Maintenance option.
3. Activate Location Control for your selected stockroom and process a Data Take-On or Stock Count as required.

Company Profile Maintenance



1/INU & 1/INUM

You use this option to:

- Maintain company details and defaults for the Inventory Management application. (If you use Advanced Order Entry, then you need to maintain these parameters within Inventory Management too.)
- Create and maintain stockrooms for a company.
- Create and maintain usage profiles for a company.



Warning: If there is a Copy Company option within Utilities, GEAC strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.

Maintain Company Profile Selection Screen



Select Maintain Company.

Use this screen to select the company that you want to maintain.

```
IN010                                User GBJBARW2    8/11/95
                                      12:24:57

Maintain Company Profile
Sel  Company
-   AC  Acceptance test - Process
-   BJ  BJ
-   CP  Z1 QA company V3.2
-   JW  JW - Jeffs Company
-   JW  JW - Jeffs Company
-   MA  Mathews Company
-   MD  Repetitive Production
-   PM  Process Manufacturing Test Com
-   RP  JBA Production Company
-   RW  ROBS COMPANY
-   SF  Simon Fishers Test Company
-   SH  Steves Manufacturing Company
-   SS  Steve Hughes Test Company
-   ST  Style
-   S1  System Test One
-   TE  TE Base Test Company
-   TS  TESTPRO - TEST COMPANY
1=Select
F3=Exit

14-03  SF  MK  KS  IM  II  KENB20A  PET178S2
```

Fields:

Select (Sel)

Enter 1 against the company you want to maintain. This automatically displays the Maintain Company Profile Aspect Selection Screen.



Select a company to automatically display the Maintain Company Profile Aspect Selection Screen

Maintain Company Profile Aspect Selection Screen



To display this screen, enter 1 against the company you want to maintain on the Maintain Company Profile Selection Screen.

Use this screen to select the aspect of the company profile you want to maintain.

IN010	Neil Radford and Co. Ltd	User GBJBA1MS	6/13/96 9:23:19
Maintain Company Profile			
Press ENTER to process Company OR enter			
Stockroom code.....?..		OR enter	
Usage profile code...?..			
F3=Exit F4=Prompt F12=Previous			
07-27	SA	MW	KS IM II KENB20A PET178S2

Fields:

Stockroom Code

Enter a stockroom code, either an existing code for amendment or a new code for addition, and press **Enter** to display the Maintain Company Profile Stockroom Profile Screen and maintain the stockroom profile.

Usage Profile Code

Enter the code of the usage profile you want to maintain, or enter a new code for addition. Press **Enter** to display the Usage Profile Screen to maintain the usage profile.

Inventory Management uses the Usage Profile to nominate historical data, by week or month that is used to calculate average usage. Inventory Management uses this code to make reorder recommendations. You can define different usage profiles to reflect different usage trends.



Leave the stockroom and usage profile codes blank and press **Enter** to display the Maintain Company Profile Initial Selection Screen.

Maintain Company Profile Initial Selection Screen



To display this screen, leave the stockroom and usage profile codes blank and press **Enter** on the Maintain Company Profile Selection Screen.

Use this screen to maintain the default company parameters. Any current information is displayed. The company name is displayed. You cannot change this within Inventory Management.

IN010	Catchweight Company MM	User GBJBA1MS	5/10/00 10:27:18
Maintain Company Profile			
Company name..... Catchweight Company MM			
Costing method (S,L,A,F)..... S		Extended Lot Details	
Specification 1 description... Pallet Conv		Batch controlled..... 0 (0/1)	
Specification 2 description... Volume		Lot controlled..... 1 (0/1)	
Specification 3 description...		Serial controlled.... 1 (0/1)	
General ledger account..... 310000			
Sales GL account..... 701100		Packaging reporting.... 0 (0/1)	
Cost of sales GL account..... 601100			
Price variance GL account.... 310000			
Usage cycle..... W			
Default reorder policy..... 1 Upto MAX		Sales Analysis	
Reorder quantity factor %.... 10		Default Flag.....? 3	
Stock carrying rate %..... 20.00			
Order placement cost..... 3.00000			
Purchasing in use..... 1 (0=No,1=Yes)			
SOP in use..... 2 (0=No,1=SOP attached,2=AOE attached)			
Date last changed..... 3/10/00			
F3=Exit F4=Prompt F9=Sec.UOM F10=Extras F12=Previous F15=Reference numbers			

Fields:

Costing Method

Enter one of the following to specify your company's default costing method:

- L - Latest costing.
- A - Average costing.
- S - Standard costing.
- F - FIFO costing.

You can change the costing method for each individual product, for more information, see the Item Maintenance Costing Details Screen.

Specification N Description

Where N is 1 to 3. You can define three numeric specifications for each product, using up to 15 characters.

The description for each specification appears alongside the specification on the product maintenance screen. You use these specifications to define some dimension of a product not provided in the standard data. Standard Processing makes no use of the specifications.

General Ledger Account

Enter the default account number in the General Ledger to which purchase invoices are posted, if you use Purchase Management.

Sales GL Account

Enter the default account number in the General Ledger to which stock transaction values are posted.

Cost Of Sales GL Account

Enter the default account number in the General Ledger to which cost of sales transaction values are posted, if you use Sales Order Processing.

Price Variance GL Account

Enter the default account number in the General Ledger to which accruals are posted, if you use Purchase Management.

Usage Cycle

Enter one of the following to define the basis for Inventory Management to calculate average usage.

M - To maintain usage figures by month, and to express average usage as average usage/month.

W - To maintain usage figures by week, and to express average usage as average usage/week.

The software automatically records usage of all items at stockroom and company level.



Note: The usage figure is based on all types of Issue movements and Transfers Out. Four of the Reorder Policies use an average usage figure. To set the software to calculate this, you need to define usage profile codes.

Default Reorder Policy

Enter one of the following to specify the company's normal reorder policy:

1 - Up To Max. When expected stock drops below the reorder point the software suggests that an order be placed of sufficient size to take the stock level up to the maximum.

2 - Reorder Quantity (ROQ). When expected stock drops below the reorder point the application suggests that the reorder quantity be ordered.

You can set this quantity yourself, or the software can determine it for you. You can hold a Reorder Quantity Factor at stockroom level or as a default on the company profile.

To explain, if you have set the reorder quantity factor to 30%, Inventory recommends that you reorder enough stock to last through 30% of the lead time. If you set the factor at 200% Inventory recommends that you reorder enough stock to last through twice the lead time.

3 - Up To ROP. When expected stock drops below the reorder point the application suggests that you order enough to take the level up to the reorder point again. For example, if you set the reorder point to zero, this rule would reorder goods when there is demand for them, for example, from a customer or manufacturing order.

4 - Up To Min. When expected stock drops below the reorder point the software suggests that you order enough stock to take the balance back up to the minimum level.

5 - EOQ. When expected stock drops below the reorder point the software suggests that you place an order for the calculated or maintained economic order quantity.

This reorder policy is then the default for all products in all stockrooms. You can change it for a particular product or stockroom if required.

Reorder Quantity Factor %

Define, as a percentage, the number of lead times worth of average usage you want to reorder, for example, 100% is 1 lead times worth, 150% is 1.5 lead times worth.

Inventory Management uses this factor to calculate the reorder quantity for those item stockroom combinations that use the reorder policy ROP but you have not specified a reorder quantity.

Stock Carrying Rate %

Enter the percentage cost of carrying a stock item for a year using up to five numeric characters with two decimals. This is the cost as a percentage of the item cost. Inventory Management uses this in the economic order quantity calculations.

Order Placement Cost

Enter the cost in base currency of placing and processing a purchase order using up to five numeric characters with two decimals. Inventory Management uses this in economic order quantity calculations.

Purchasing In Use

Enter one of the following:

- 0 - Purchase Management not in use.
- 1 - Purchase Management application is in use

SOP In Use

Enter one of the following:

- 0 - Sales Order Processing application is not in use.
- 1 - SOP Attached. Sales Order Processing is in use.
- 2 - AOE Attached. Advanced Order Entry is in use.

Extended Lot Details

Enter one of the following to activate or deactivate extended detail control for batch, lot or serial controlled items:

- 0 - To deactivate extended details for batch, lot or serial controlled items.
- 1 - To activate extended details for batch, lot or serial controlled items.

If you enter 1 to activate extended details, then the Header Parameter Window is activated for the appropriate area, for example, for batch, lot or serial controlled items, or a combination of these if appropriate.

You would normally activate, or deactivate, this option during system implementation. If you deactivate this option after implementation then all of the function that used this information is disabled.

If you activate this option after implementation, then you will be prompted to enter the missing information for all batch, lot or serial controlled items that do not have extended details and shelf life parameters. For more information, see the All Serial Header Parameter Window.



Tip: If you have activated Location Control for your company, you need to make sure that you have activated lower level allocation details for all lot, batch or serial controlled items. This is because Location Control cannot commit location balances to a pick note for these items unless the lots, batches or serial numbers are already allocated.

Packaging Reporting

You use this field to determine whether you want to use Packaging Usage reporting for your company. If you use Packaging Usage, the software compiles packaging statistics for submission to the appropriate authority.

Enter one of the following:

0 - To deactivate packaging usage for your company.

1 - To activate packaging usage for this company.



Note: The next two fields appear if you have chosen to activate Packaging Reporting for your company. For more information about these fields, see Packaging Reporting.

Default Country

Enter the default reporting country for packaging reporting.

Sales Channel

Enter the sales channel you want to use for packaging reporting.

Sales Analysis Default Flag

Use this to determine how you want to update Sales Analysis for this company. These codes are defined in Inventory Descriptions under major type SAUI.

Functions:

F9=Sec UOM

Use this to display the Secondary UOM window.



Note: This function is displayed if you use Catchweight. To use Catchweight, you must have a valid authorisation code.

F10=Extras

Use this to display the Extended Options Window.

F15=Reference Numbers

Use this to display the Reference Number Entry Window.

F20=Packaging Countries

This function key is displayed if you have set the Packaging Reporting flag to 1. Use this function to access the screens used to set up the packaging reporting information; for more information see Country Details Maintenance in Packaging Requirements.



Once you have made the required amendments, press **Enter** twice to update the company profile. If you have selected to activate extended details for batch, lot or serial controlled items, or both, then the All Serial Parameter Window is displayed. The title of the window changes to reflect the items whose extended details you have chosen to activate.

All Serial Parameter Window



To display this window, enter 1 in the Serial Controlled field on the Maintain Company Profile Initial Selection Screen and press **Enter**.



Note: The title of the window changes to reflect the items whose extended details you have chosen to activate. For example, if you select to activate extended details for batch controlled items, the title of the window is All Batch Parameter Window and so on. If you select to activate more than one area of extended details, then this window is displayed for each of your selected areas in turn.

There are three conditions when this option is used:

- If you have not yet defined items with the selected type of control; that is batch, lot or serial. In this case, any values entered on this window will have no effect but they still need to be entered for future use.
- If you have defined items with the selected type of control, but they have no stock balances recorded against them. In this case, the shelf life parameters are used to update any item that does not have shelf life details recorded against them. Items with existing shelf life parameters are not affected.
- If your controlled items have stock balances. In this case, those with missing shelf life parameters are updated and any extended batch, lot or serial header details are created.

These missing values are either entered using this window, derived from existing data, calculated or set to a default value.

The derived values are: the item, lot reference and production date. The production date is calculated from the earliest remaining receipt in any stockroom.

The calculated values are: the first available date, the last available date and the expiry date.

The default values are: the potency and grade details, as these are set as being not required.

When you use this window, only missing values are created, existing values are retained. If you use Advanced Order Entry, then the supplier's reference is retained for batch controlled items.

Once you have created these details you can amend them using Item Lot Header Maintenance.

```
IN010          GB Demonstration Company          User GBJBA1MS   23/02/00
                                                    11:30:28

All Serial Header Parameters Maintenance

Shelf life unit.....?..
Shelf life..... 000
Customer shelf life..... 000

Default stock status....?.. _
Release lead time units.?.. _
Release lead time..... _
Lot dates 'to'.....?.. _
Display lot time..... _ (0=No,1=Yes)

F4=Prompt F12=Previous
Stock carrying rate %..... 20.00
Order placement cost..... 3.00000
Purchasing in use..... 1 (0=No,1=Yes)
SOP in use..... 2 (0=No,1=SOP attached,2=A0E attached)
Date last changed..... 23/02/00

F3=Exit F4=Prompt F9=Sec.UOM F10=Extras F12=Previous
F15=Reference numbers F20=Packaging Countries
```

Fields:



Note: You can use the Item Maintenance option to define the details held in the next three fields for individual items. For more information, see the Item Maintenance Costing Details Screen.

Shelf Life Unit

Enter one of the following shelf life unit codes to specify the default from those defined on the Inventory descriptions file against major type SHLU:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.
- 5 - Unlimited.

Shelf Life

Enter up to three numeric characters to specify the default shelf life of the item expressed in the shelf life units. This is the actual life of the product.

For example, if you entered 1 for days in the Shelf Life Units field, and enter 7 in this field, then the total shelf life is 7 days.

Customer Shelf Life

For batch, lot or serial controlled items, this value is subtracted from the expiry date to give the last available date. The stock status recalculation option will freeze the stock in all stockrooms when a batch, lot or serial controlled item has passed its last available date. This option should be run regularly.

For example, if you enter 5 in this field, having entered a total shelf life of 7 days, 2 days are stock shelf life days and 5 are customer shelf life days.



Note: You can use the Item Maintenance option to define the details held in the next three fields for individual items. For more information, see the Lot Header Parameters Maintenance Window. You can also use this option to define Potency and Grade details for individual items if they are required.

Default Stock Status

Enter a stock status code chosen from those defined on the Descriptions file against the major type STKS. This stock status code defaults into the Stock Status field every time you receive a new lot of this item into Inventory. Stock status codes are designated as either available or unavailable, and then applied to a lot to make the quantity of that lot frozen or unfrozen. Receipts are frozen by the stock status monitor.

You can leave this field blank if you want to specify the lot as available.



Note: The seven-digit limit field of the description codes defined against STKS indicates the availability of an item. If the seventh digit of this field is 1 then the stock status code indicates an unavailable item. Any other value renders the stock status code an available code.

Release Lead Time Units

Enter one of the following alphanumeric characters to specify the release time unit used when calculating the first available date of a lot:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.

Leave this field blank if you do not want to enter the release lead time. In this case, when the lot dates are calculated, the first available date equals the production date.



Note: Production Date + Release Time = First Available Date. The Stock Status Monitor will freeze receipts, and the Stock Status Recalculation option will unfreeze them once the release date has passed.

Release Lead Time

You must enter this if you specified a release lead time unit. Enter up to three numeric characters. The release time is used in the following calculation:

For example, Available Date + Release Time = First Available Date.

If you leave this field blank then, when the lot dates are calculated, the first available date equals the production date.

Lot Dates To

Enter one of the following alphanumeric characters to specify the method used to position lot dates once they are calculated:

- 1 - Use actual lot dates.
- 2 - Position to first day of the period.
- 3 - Position to last day of the period.

All lot dates are either entered or calculated using shelf life and release times. Once calculated, this field can reposition the first available, last available and expiry dates to the start or end of a week depending on the business requirements. The first available date is set to the production date when the start of week date precedes the production date. In this case, the last, available and expiry dates are still calculated from this start of week date.

Display Lot Times

Enter one of the following:

- 0 - Do not display lot times when you receive a new lot of this item into Inventory.
- 1 - Display lot times as well as lot dates. In this case, you need to enter a time, as well as a date, upon receipt of a lot.



*Note: If you select **F12=Cancel**, then these details are not saved, and the Extended Details field is set back to 0.*



*Note: When you press **Enter** the item and extended details are updated interactively.*



Press **Enter** to save these details and redisplay the Maintain Company Profile Initial Selection Screen.

Secondary UOM Window



To display this window, select **F9=Sec UOM** on the Company Profile Maintenance Initial Selection Screen.



Note: This function is displayed if you use Catchweight. To use Catchweight, you must have a valid authorisation code.

Use this window to define the default secondary unit of measure, and the default percentage tolerance and tolerance value limits for your company. You use these tolerance limits during any transactions that involve a change to an item's stockroom balance.

IN010		Catchweight Company MM	User GBJBA1MS	5/10/00
				10:28:57
Maintain Company Profile				
Company name.....	Catchweight Company MM			
Costing method (S,L,A,F).....	S	Extended Lot Details		
Specification 1 description...	Pallet Conv	Batch controlled.....	0 (0/1)	
Specification 2 description...	Volume	Lot controlled.....	1 (0/1)	
Specification 3 description...		Serial controlled....	1 (0/1)	
General ledger account.....	310000	Secondary UOM		
Sales GL account.....	701100	Secondary UOM...?.. KG		
Cost of sales GL account.....	601100	Tolerance %..... 5.00		
Price variance GL account....	310000	Tolerance Value... ..		
Usage cycle.....	W	F4=Prompt F8=Update F12=Previous		
Default reorder policy.....?	1 Up			
Reorder quantity factor %....	10			
Stock carrying rate %.....	20.00			
Order placement cost.....	3.00000			
Purchasing in use.....	1 (0=No,1=Yes)			
SOP in use.....	2 (0=No,1=SOP attached,2=A0E attached)			
Date last changed.....	5/10/00			
F3=Exit F4=Prompt F9=Sec.UOM F10=Extras F12=Previous				
F15=Reference numbers F20=Packaging Countries				

Fields:

Secondary UOM

Enter an existing unit of measure. You can prompt the field and display the Units Of Measure window containing a list of configured units of measure. You can use the Secondary UOM Maintenance option to create these.

Tolerance %

When an item's secondary value is captured during a relevant transaction, entering a percentage number in this field can set the default plus or minus degree of deviation from the expected nominal value. If you exceed this percentage tolerance during a transaction, Inventory Management displays warning message. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5%, will cause the warning message to display.

Tolerance Value

When an item's secondary value is captured during a relevant transaction, entering an absolute value in this field can set the default plus or minus degree of deviation from the expected nominal value. If you exceed this fixed value tolerance during a

transaction, Inventory Management displays a warning message. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5kg (if the UOM is kilos) will cause the warning message to display.



Note: Tolerance percentages or values are defined only for Catchweight item types 1 and 2. You can display and amend default values during Catchweight item creation.

Note: If both the Tolerance Percentage or Tolerance Value fields are empty, then there is no tolerance and a warning is displayed for anything other than the default.



Note: You can enter a number in either the Tolerance percentage field or the Tolerance Value field, but you cannot enter a number in both.



Select **F8=Update** to save the selected entries in the Secondary UOM window, and display the Maintain Company Profile Initial Selection Screen.

Extended Options Window



To display this window select **F10=Extras** on the Company Profile Maintenance Initial Selection Screen.

Use this window to define the centralised processing of delivery documentation and designation of the default item search. If you are using Advanced Order Entry you can determine whether you can enter decimal quantities on orders.

```

IN010          Catchweight Company MM          User GBJBA1MS    5/10/00
                                                10:28:57

Maintain Company Profile

Company name..... Catchweight Company MM
Costing method (S,L,A,F)..... S          Extended Lot Details
Specification 1 description... Pallet Conv    Batch controlled..... 0 (0/1)
Specif          Extended options
Specif
Genera          Inventory Revaluation Parameters
Sales          Stockroom fiscal close..... 0      0=No,1=Month End,
Cost o          2=Manual
Price          Latest and average cost calculation. 1  1=Exclusive of misc.rec.
Usage          2=Inclusive of misc.rec.
Default        Centralised delivery documents..... 0  0=No,1=Optional
Reorde          2=Mandatory
Stock          Default item search option..... 1      1=Item reference
Order          2=Inventory description
Purcha          3=Purchasing description
SOP in          4=Alias
Date l          5=Search characteristics
                Integer quantities..... 1      (0=No,1=Yes)
F3=Exi          F5=Refresh F12=Previous
F15=Reference numbers F20=Packaging Countries
  
```

Fields:

Integer Quantities

This field is reserved for future development. You use this field to determine whether you want to display item quantities with decimals, or just as integers. Enter one of the following:

- 0 - To enter decimal quantities.
- 1 - Item quantities on orders can only be integers.

Stockroom Fiscal Close

This is used in Inventory Revaluation and determines how you want to perform your stockroom fiscal close process. For more information see Stockroom Fiscal Close in Inventory Valuation.

Enter one of the following:

- 0 - To not perform a stockroom fiscal close.
- 1 - To perform a stockroom fiscal close as part of Inventory Management's Period End process.
- 2 - To perform stockroom fiscal close manually.

Latest And Average Cost Calculation

This is used in Inventory Revaluation. Enter one of the following:

0 - To exclude miscellaneous receipts of stock from latest and average cost calculations.

1 - To include miscellaneous receipts of stock from latest and average cost calculations.

Centralised Delivery Documents

Enter one of the following:

0 - To generate separate despatch/delivery documentation by each function.

1 - To generate centralised delivery documentation where additional details have been specifically entered for the transaction.

2 - To generate centralised delivery documentation for all movement of goods.

Default Item Search Option

Enter one of the following to specify the search criteria on the item search facility:

1 - Item reference.

2 - Inventory Management description.

3 - Purchasing description.

4 - Alternative reference (only available if you are using Advanced Order Entry).

5 - Search characteristics (only available if you are using Advanced Order Entry).

9 - Search by base item (only available if you are using Production and Configurator).

Integer Quantities

Enter one of the following:

0 - No. If you do not want integer quantities.

1 - Yes. If you do want integer quantities.



Select **F12=Previous** to redisplay the Company Profile Maintenance Initial Selection Screen.

Reference Number Entry Window



To display this window select **F15=Reference Numbers** on the Company Profile Maintenance Initial Selection Screen.

Use this window to enter document processing reference numbers.

```

IN010          Neil Radford and Co. Ltd          User GBJBA1MS          6/13/96
                                                9:25:23

Maintain Company Profile

Com  Reference Number Entry  S
Cos
Spe  Code..... NR          . 1 (0/1)
Spe  Description.. Neil Radford and Co. Ltd . 1 (0/1)
Spe                                     . 1 (0/1)
Gen
Sal  Reference type          Reference   Last number
Cos  Internal Transfer        Code(?)   Used
Pri                                     1450 NRA
Usa
Def
Reo
Sto
Ord  F4=Prompt F8=Update F12=Previous
Purchasing in use..... 1 (0=No,1=Yes)
SOP in use..... 1 (0=No,1=SOP attached,2=A0E attached)
Date last changed..... 6/12/96

F3=Exit F4=Prompt F10=Extras F12=Previous F15=Reference numbers

12-48  SF  MW  KS  IM  I1  KENB20A  PET178S2
  
```

Fields:

Code

This is the Company profile code and cannot be changed.

Description

This is the Company description and also cannot be changed.

Reference Type

This is the document processing option: invoice or credit notes.

Reference Code

You can choose to enter a new reference number or select a default one.

Last Number Used

This is the reference number last used for the document processing option currently selected.



Select **F8=Update** to save any changes and redisplay the Maintain Company Profile Initial Selection Screen.

Maintain Company Stockroom Profile Screen



To display this screen select the stockroom whose profile you want to maintain on the Maintain Company Profile Selection Screen and press **Enter**.

Use this screen to create and maintain stockroom profiles.

IN010		Catchweight Company MM		User GBJBA1MS		4/04/00	
						13:56:31	
Maintain Company Profile							
Stockroom..... HL		LC Stockroom					
Include in valuation..... 0		(0=No,1=Yes)					
Stockroom usage code..... ?..		-					
Department..... ?..		-					
Stockroom site..... ?..		-					
Transaction allowed (0=No,1=Yes)				Consignment Stock			
Receipts..... 1				EDI Updates (1/0)			
Issues..... 1				0			
Adjustments..... 1				0			
Consignment stock consumption. 0				0			
Inventory balance updates				0			
Transfers..... 1							
Supplier orders..... 1							
Sales orders..... 1							
Negative stock allowed..... 1 (0=No,1=Yes)							
F3=Exit F4=Prompt							

Fields:

Stockroom

Enter the stockroom name using up to 25 alphanumeric characters.

Include In Valuation

You can use this field to decide whether you want to include this stockroom in Inventory Management valuation or not. Enter one of the following:

0 - To exclude the stockroom from valuation.

1 - To include the stockroom in valuation.

Stockroom Usage Code

Enter the usage code associated with this stockroom. Inventory Management uses this code for information only. You can define Stockroom usage codes within Inventory Management Descriptions against major type STKU. For more information, see the Descriptions File Maintenance Selection Screen.

Department

Enter a department code associated with this stockroom. Inventory Management uses this data for information only. You can define Department codes within Inventory Management Descriptions against major type DEPT. For more information, see the Descriptions File Maintenance Selection Screen.

If you use Productions MRP Cellular Planning function, then you must enter a three character cell code to indicate the cell manager responsible for the supply and demand requirements of this stockroom. For each cell code defined, you should define an equivalent department code on the Production Parameters file.

Stockroom Site

Use this to determine the output print queue of the delivery documentation

Transaction Allowed:

Use the following fields to determine the transactions you want to process within this stockroom.

Receipts

Enter one of the following:

- 0 - To exclude the stockroom from goods receiving activities.
- 1 - To receive goods at this stockroom.

Issues

Enter one of the following:

- 0 - To exclude the stockroom from goods issuing activities.
- 1 - To issue goods from this stockroom.

Adjustments

Enter one of the following:

- 0 - You cannot make adjustments in this stockroom.
- 1 - You can make adjustments in this stockroom.

Consignment Stock Consumption

Enter one of the following:

- 0 - To allow consignment stock consumption in this stockroom.
- 1 - To not allow consignment stock consumption in this stockroom.

Transfers

Enter one of the following:

- 0 - To not initiate transfers from this stockroom.
- 1 - To initiate transfers from this stockroom.

Supplier Orders

Enter one of the following:

- 0 - To not initiate supplier orders from this stockroom.
- 1 - To initiate supplier orders from this stockroom.

Sales Orders

Enter one of the following:

- 0 - To not take sales orders against this stockroom.

1 - To take sales orders against this stockroom.

Negative Stock Allowed

Enter one of the following:

0 - Transactions that produce negative item balances for this stockroom are not allowed.

1 - To process transactions that produce negative item balances for this stockroom.

Functions:



Press **Enter** to update the stockroom profile and to display the Advanced Allocations Options Screen.

Advanced Allocations Options Screen



To display this screen, press **Enter** on the Maintain Company Stockroom Profile Screen.

Use this screen to enter the Advanced Allocation options for your selected company and stockroom.

```

IN010          Catchweight Company MM          User GBJBA1MS  17/02/00
                                                13:56:20
Maintain Company Profile
Stockroom..... HL    LC Stockroom

Advanced Allocation Options:

Automatic lower level allocation... 0  (0=No, 1=Yes)
Manual lower level allocation..... 0  (0=No, 1=Yes)
Allocation at batch level..... 0  (0=No, 1=Yes)
Allocation at serial level..... 0  (0=No, 1=Yes)
Allocation at lot level..... 0  (0=No, 1=Yes)
Alternative kit allocation..... 0  (0=No, 1=Yes)

F3=Exit  F5=Refresh F12=Previous
  
```

Fields:

Automatic Lower Level Allocation

Enter one of the following:

0 - Not required.

1 - To automatically allocate orders against specific lots, batches and/or serial numbers when you produce pick notes.

Manual Lower Level Allocation

Enter one of the following:

0 - Not required.

1 - To allocate against specific lots, batches or serial numbers at the time of order entry or when you amend an order. The ability to allocate against lot numbers depends on the settings of the allocate at flags described below.



Tip: If you set either the Automatic Lower level Allocation field or the Manual Lower Level Allocation field to 1, then you must set at least one of the next three Allocation At fields to 1. If you have set both of these fields to 0, then you must make sure that the next three Allocation At fields are also set to 0.

The next three fields activate each type of lower level allocation:



Tip: If you want to define a Location Controlled stockroom, then you must set the Automatic Lower Level Allocation field to 1, and you must set one of the next three fields to 1. You cannot activate Location Control without activating Automatic Lower Level Allocation.



Note: GEAC recommend that you set each of the Allocation At fields to 1 if Location Control is active.

Allocation At Batch Level

Enter one of the following:

- 0 - Not required.
- 1 - If you want lower level allocations to be valid for batches.

Allocation At Serial Level

Enter one of the following:

- 0 - Not required.
- 1 - If you want lower level allocations to be valid for items controlled at serial number level.

Allocation At Lot Level

Enter one of the following:

- 0 - Not required.
- 1 - If you want lower level allocations to be valid for lot controlled items.

Alternative Kit Allocation

Enter one of the following.

- 0 - To only allocate component items if you can allocate the whole kit.
- 1 - To allocate component items whether you can allocate the whole kit, or not.



Press **Enter** to display the Maintain Company Profile Stock Weeks Matrix Screen.

Maintain Company Profile Stock Weeks Matrix Screen



To display this screen, press **Enter** on the Advanced Allocations Options Screen.

Or:

Select Regenerate ABC Classification in Stock Counting.

Use this screen to determine the parameters that govern stock usage.

During the update routines (weekly or monthly) you can run the regenerate ABC classification, which reviews and re-classifies items and calculates next count dates.

A three by three matrix is displayed. The Y axis, labelled value, is the unit cost of the item held in the selected stockroom. The X axis, labelled usage, is the most recently calculated average usage for any item in the stockroom. This means each square relates to a value/usage category.

By specifying low/medium and medium/high boundaries you can define nine cells that represent the value/usage categories for items in this stockroom.

The minimum and maximum stock holdings for each category are expressed in number of weeks of average usage. The date the matrix was last changed is displayed.

```

IN010          Catchweight Company MM          User GBJBA1MS  17/02/00
                                                    13:56:20
Maintain Company Profile

Stockroom..... HL   LC Stockroom
Y
A 0.000          +--- 1 ---+--- 2 ---+--- 3 ---+   Stock weeks code
L                | Class A | Class A | Class A |   1 Low val/low usg.
U   to           | Min  .0 | Min  .0 | Min  .0 |   2      /med usg.
E                | Max  .0 | Max  .0 | Max  .0 |   3      /hi usg.
                +--- 4 ---+--- 5 ---+--- 6 ---+
.00000          | Class A | Class A | Class A |   4 Med val/low usg.
                | Min  .0 | Min  .0 | Min  .0 |   5      /med usg.
to              | Max  .0 | Max  .0 | Max  .0 |   6      /hi usg.
.00000          +--- 7 ---+--- 8 ---+--- 9 ---+
                | Class A | Class A | Class A |   7 Hi val /low usg.
                | Min  .0 | Min  .0 | Min  .0 |   8      /med usg.
                | Max  .0 | Max  .0 | Max  .0 |   9      /hi usg.
                +---+---+---+
                0.0 to .000 to .000 USAGE Last change 17/02/00

F3=Exit F8=Update Complete F11=Delete F12=Previous
  
```

Fields:

Enter the following details for each cell:

Class

Enter A, B or C to assign a classification to all items within this value/usage category. Historically, A class items are high value/high usage, whereas C class items are low value/low usage. You can enter Z to exclude a value and usage combination from the matrix.

You can stock count by ABC classification and define a profile so that you count higher value items more frequently than lower value items.

To exclude single items from your stock counting mechanisms enter Z in the item classification field during Item Maintenance.

Min

Enter three numeric characters, one decimal, to specify the minimum weeks stock to hold for the category.

Max

Enter three numeric characters, one decimal, to specify the maximum weeks stock to hold for the category.

Value 1

Enter fifteen numeric characters, five decimals, to specify the first value de-limiter. Any items with a unit cost less than or equal to this value are in categories 1, 2 or 3.

Value 2

Enter fifteen numeric characters, five decimals, to specify the second value de-limiter. Any item with a unit cost between this value and value 1 are in category 4, 5 or 6. Items with a unit cost over this value are in category 7, 8 or 9.

Usage Qty 1

Enter eleven numeric characters, three decimals, to specify the first usage de-limiter. Items with an average usage up to this quantity are in category 1, 4 or 7.

Usage Qty 2

Enter eleven numeric characters, three decimals, to specify the second usage de-limiter. Items with an average usage between quantity 1 and this quantity are in category 2, 5 or 8. Items with an average usage over this quantity are in category 3, 6 or 9.

During the Ad-hoc Update, for each included item, the software reviews the item's cost and average usage, thus identifying an appropriate square and then selecting the number of minimum and maximum weeks.

The software then calculates:

Reorder Point $(\text{Minimum Stock Weeks} + \text{Lead Time in Weeks}) \times \text{Average Usage}$

Maximum Stock $\text{Minimum Stock Weeks} \times \text{Average Usage}$

Economic Order Quantity $\sqrt{\frac{(2 \times \text{order placement cost} \times \text{annual usage})}{\text{inventory holding cost per year}}}$



Note: Any stockroom balance records found without an associated item master or stockroom detail record are written to an exception report.

The Stockroom details record would now include the calculated figures.



Press **Enter** to update the stockroom weeks matrix and display the Maintain Location Control Stockroom Profile Screen.

Or:

Select **F8=Update Complete** to update the stockroom weeks matrix and display the Maintain Company Profile Aspect Selection Screen if you are using Location Control. This function is only displayed if Location Control is active.

Maintain Location Control Stockroom Profile Screen



To display this screen, press **Enter** on the Maintain Company Profile Stock Weeks Matrix Screen.

Use this screen to create or maintain the Location Control stockroom profile details.

IN610	Catchweight Company MM	USER GBJBA1MS	17/02/00
			14:10:36
Maintain Location Control Stockroom Profile		*UPDATE	
Stockroom.....?. HL LC Stockroom			
Default Location:.....?. _____			
Multiple Locations..... 1 (0=no, 1=yes)			
Rotate Stock..... 1 (0=no, 1=yes)			
Collect Secondary Balances. 1 (0=no, 1=yes)			
Location Control Status.... 0 (0=Inactive, 1=Active)			
Warehouse Control Status... Inactive			
F3=Exit F4=Prompt F8=Update Complete F11=Delete F12=Previous			

Fields:

Stockroom

This is your selected stockroom.



Note: The details that you specify in the Default Location, Multiple Locations, Rotate Stock and Collect Secondary Balances fields are defaults. They are used when you create the Location Control Item/Stockroom Profile. They are also used to create missing item/stockroom profiles during the Data Take-ON and Reconciliation programmes.

Default Location

You can enter a default location if required.



*Note: If you enter a default location and press **Enter**, or select **F8=Update** to save these details, then the location is created and is recorded on the Location Map.*

Multiple Locations

Enter one of the following:

0 - If you want some or all of your stock to have single location references within your selected stockroom at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.

1 - If you want some or all of your stock to have multiple location references within your selected stockroom at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.

Rotate Stock

Enter one of the following:

0 - To deactivate stock rotation for this stockroom at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.

1 - To activate stock rotation for this stockroom at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.

Collect Secondary Balances

Enter one of the following:

0 - To not hold secondary balances by location for this stockroom at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.

1 - To hold location level secondary balances at item/stockroom level. This is a default value and can be changed at in the Item/Stockroom Profile if required.



Note: This field is only displayed if you are using Catchweight.

Location Control Status

Enter one of the following:

0 - To deactivate Location Control within your selected stockroom.

1 - To activate Location Control within your selected stockroom.



*Note: If you make a Location Controlled stockroom inactive, then the action clears the location balances and rotation balances and any outstanding event balances.
You cannot make a stockroom active if it is an active warehouse, or if you have not activated lower level allocation.*



Warning: GEAC recommend that you do not deactivate an active Location Controlled stockroom.

Warehouse Control Status

This displays whether or not Warehousing is active for your selected stockroom.



Note: You cannot use Warehousing and Location Control for the same stockroom, they are mutually exclusive.

Functions:

F8=Update Complete

Select this function to update the profile without maintaining the Location Map for your selected stockroom.

F11=Delete

Select this function to delete Location Control details for your selected stockroom.



Note: This deletes Location Control data; the location balances, event allocations, location control data within the item/stockroom profile, the location map and location control stockroom profile for your selected stockroom.



Press **Enter** to display the Maintain Location Map Screen.

Or:

Select **F8=Update Complete** to display the Maintain Company Profile Aspect Selection Screen.

Maintain Location Map Screen



To display this screen, press **Enter** on the Maintain Location Control Stockroom Profile Screen.

Or:

Select the Location Map option.

Use this screen to create location codes for a location controlled stockroom, or to maintain location codes for an existing location controlled stockroom.

You can also use this screen to define the range of location codes that you want to create for your selected stockroom.



Note: You must make sure that your selected stockroom is defined to Inventory Management.

IN611	Catchweight Company MM	User GBJBA1MS	17/02/00
			14:10:45
Maintain Location Map			
Stockroom.... HL			
Start display at..?. _____ (Blank for first location)			
OR			
Enter location range to create		From..?. _____	
		To...?. _____	
		Status. @ (0=active, 1=suspended)	
Restrict Number of Locations Created To: <u>9999</u>			
F3=Exit F4=Prompt F8=Create Range F16=Number of Locations			

Fields:

Stockroom

Select the stockroom whose location map you want to create or amend. This stockroom must be defined to Inventory.



Note: If you access this screen from Inventory Company Maintenance, then this field displays your selected stockroom.

Stockroom Description

This field is only displayed if you access this screen from Stockroom Profile Maintenance within the Inventory company profile. It displays the name, or description, of your selected stockroom.

Start Display At

Enter the location code that you want to display at the top of the screen. You can only use this if you want to view existing locations. If you enter information in this field, you cannot use the next two fields. Press **Enter** to redisplay the next screen with the correct location code at the top of the screen.

Enter Location Range To Create From

Enter the first code in the range of locations that you want to create. This code can be up to 12 alphanumeric characters long.

To

Enter the last code in the range of locations that you want to create.

Enter a single location code here, if required.



Tip: When you select **F8=Create Range**, Inventory checks each character position in turn and searches for the same type of character in each position. It also checks that the To Location code is not less than the From Location code.

If you enter the range A01 to A99, Inventory will create 99 locations. If you enter A01 to C50, Inventory will create 250 locations. That is, 99 A locations, 100 B locations and 51 C locations.



Tip: GEAC recommend that you carefully consider the naming convention you use to create your location codes so that the resulting codes best reflect the layout of the stockroom.

Status

Enter one of the following:

0 - To activate the location.

1 - To deactivate the location.

Restrict Number Of Locations To Be Created To

If you have entered a range of locations for creation, enter the maximum number of locations that you want to create.

The default is 9999, which is the maximum value you can enter.

Functions:

F8=Create Range

Select this function to create the locations you have defined in the Location Range To Create fields. Any location codes within that range that have already been created are not duplicated. The creation process stops once the number of locations to be created has been exceeded or once the range is complete.

F16=Number Of Locations

Select this to check that your specified range will produce the number of locations that you are expecting. This displays the Location Control Number Of Locations Window.



Press **Enter** to display the Maintain Location
Map Locations Screen.

Location Control Number Of Locations Window



To display this window, select **F16=Number of Locations** on the Maintain Location Map Screen.

Use this window to check the number of locations that you are going to create from your selected range.

IN611 Catchweight Company MM User GBJBA1MS 4/04/00 14:37:35

Maintain Location Map

Stockroom.... HL

Start display at..?. _____ (B

OR

Enter location range to create From.? E01
To...?. E05
Status. 1 (0=active, 1=suspended)

Restrict Number of Locations Created To: 9999

F3=Exit F4=Prompt F8=Create Range F16=Number of Locations

Fields:

Number Of Locations

This is the number of locations that you are planning to create using your specified range.



Press **Enter** to return to the Maintain Location Map Screen.

Maintain Location Map Locations Screen



To display this screen, press **Enter** on the Maintain Location Map Screen.

Use this screen to view or amend any existing location codes for your selected stockroom. The stockroom and its description are displayed at the top of the screen. There are up to three columns of location information displayed in the middle of the screen, up to a maximum of 39 locations.

Location		Status	Location		Status	Location		Status
01 A01	In use	14 B04	In use	27 C07	In use			
02 A02	In use	15 B05	In use	28 C08	In use			
03 A03	In use	16 B06	In use	29 C09	In use			
04 A04	In use	17 B07	In use	30 C10	In use			
05 A05	In use	18 B08	In use	31 D01	In use			
06 A06	In use	19 B09	In use	32 D02	In use			
07 A07	In use	20 B10	In use	33 D03	In use			
08 A08	In use	21 C01	In use	34 D04	In use			
09 A09	In use	22 C02	In use	35 D05	In use			
10 A10	In use	23 C03	In use	36 D06	In use			
11 B01	In use	24 C04	In use	37 D07	In use			
12 B02	In use	25 C05	In use	38 D08	In use			
13 B03	Suspended	26 C06	In use	39 D09	In use		+	

Line: __ Location: _____ Action: _ (0=activate, 1=suspend, 4=delete)
Position To: _____
F3=Exit F12=Previous

MA a 21/008

Fields:

Stockroom

This displays your selected stockroom.

Line Number (Untitled)

This displays the line number that you can use to select a line for amendment or deletion. The numbers are always between one and 39.

Location

This is the location code.

Status

This displays the current status of the location code.



Tip: Page up and down to display more location codes if required.

Line

Enter the number of the line that corresponds to the location code you want to amend. The location details are displayed in the entry fields when you press **Enter**.

Location

This is your selected location code.



Tip: You can enter a location code to select a location for amendment or deletion rather than entering a line number if required.

Action

Enter one of the following:

0 - To activate the location code. You can activate a suspended location at any time.

1 - To suspend a location code. You can only suspend an active location if it is empty and not defined as the default location for an item, or for the stockroom.

4 - To delete a location code. You can only delete a location if it is empty and it is not a default location for an item or stockroom.



Note: If you delete location codes by mistake, then you can redefine them.

Position To

Enter the location code that you want to display at the top of the screen. Press **Enter** to display your selected location code.



Press **Enter** to confirm the changes that you have made.

Then select **F3=Exit** to exit the Location Map and redisplay the Maintain Location Control Stockroom Profile Screen. Select **F8=Update Complete** to save the changes and redisplay the Maintain Company Profile Aspect Selection Screen.

Select Usage Code Window



To display this window select **F4=Prompt** in the Usage Profile Code field on the Maintain Company Profile Aspect Selection Screen.

Use this window to select the usage code you require.

IN010	UK Demonstration Company	User GBJBAHEH	10/02/99 11:25:56
Maintain Company Profile			
Press ENTER to process Company OR enter			
Stockroom code.....?.. _ OR enter			
Usage profile code...?.. ?			
F3=Exit F4=Prompt F12=Previous			

Select Usage Code		
Code	Code	Code
_ 01		
1=Select Usage Code		
F5=Refresh F12=Previous		

Fields:

Select (Untitled)

Enter 1 to select the Usage Profile code that you want to view or amend.



Select the Usage Profile code you require and press **Enter** to display the Usage Profile Screen.

Usage Profile Screen



To display this screen, select the Usage Profile Code you require using the Select Usage Code Window and press **Enter**.



Note: This screen is displayed if you select to amend an existing Usage Profile code, or create a new one.

Use this screen to add and edit a set of profiles that define the historical periods used in the calculation of average weekly or monthly usage. You can use these for items with significant seasonal variations in sales.

Select the profile to display the weekly or monthly periods, depending on the usage cycle defined on the Inventory Management Company profile. You can define the usage pattern for the current and previous 59 periods, so, depending on the period definition, the history can go back one and a quarter or five years.

The calculations are based on the last 3 weeks/months usage figures.

An appropriate usage profile code is then assigned to each item in the Stockroom details file.

IN010	Catchweight Company MM	User GBJBA1MS	5/10/00 10:34:15												
Maintain Company Profile															
Usage profile code... 01 Usage cycle... Weekly															
Average usage is calculated each weekend & only closed weeks are considered. '1' = Include in calculation. '0' = Exclude from calculation.															
Week -1 = The last week closed.															
Weeks	-1	-2	-3	-4	-5	-6	-7	-8	-9	-10	-11	-12	-13	-14	-15
	1	1	1	1	0	0	0	0	0	0	0	0	0	0	0
Weeks	-16	-17	-18	-19	-20	-21	-22	-23	-24	-25	-26	-27	-28	-29	-30
	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
Weeks	-31	-32	-33	-34	-35	-36	-37	-38	-39	-40	-41	-42	-43	-44	-45
	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
Weeks	-46	-47	-48	-49	-50	-51	-52	-53	-54	-55	-56	-57	-58	-59	-60
	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
Date last changed... 12/10/99															
F3=Exit F11=Delete F12=Previous															

Usage Profile Code

This is the Usage Profile Code that you selected using the Select Usage Code Window, or entered on the Maintain Company Profile Aspect Selection Screen.

This Week/Month

Enter one of the following:

0 - To not include the current week or month in the calculations.

1 - To include the current week or month in the calculations.

Select (Untitled)

To include a period in the average usage calculation enter 1 under it. The default, 0, omits the period from the calculation.

Date Last Changed

This is the date that an existing usage profile was last changed.



Press **Enter** to save any changes and redisplay the Maintain Company Profile Aspect Selection Screen.

Stockroom Site Maintenance



2/INU & 2/INUM

Use this option to maintain stockroom sites. Inventory Management uses this to define the output queue appropriate to the printing of delivery documentation.

Stockroom Site Maintenance Selection Screen



Select Stockroom site from the menu.

Use this screen to select the stockroom that you want to maintain.

IN975 NR - Neil's Test Company User GBJBANER 21/05/96 11:32:20

Stockroom Site Maintenance

Stockroom site....?..

F3=Exit F4=Prompt

05-24 SA MW KS IM II KENB20A PET178S1

Fields:

Stockroom Site

Enter a stockroom site to create or maintain. You can enter a maximum of 10 characters.



Press **Enter** to display the Stockroom Site Maintenance Screen.

Stockroom Site Maintenance Screen



To display this screen, enter a stockroom site and press **Enter** on the Stockroom Site Maintenance Selection Screen.

Use this screen to maintain the stockroom site details. Inventory Management displays any information for an existing stockroom site for amendment.



Tip: Once you have defined sites, you must assign them to Inventory Management stockrooms if you want to use centralised document processing.

```
IN975                Z1 - UK Demonstration Company    User GBJBAHEH    10/02/99
                                                           11:51:58

Stockroom Site Maintenance

Stockroom site..... STUDLEY

Site name..... Studley

Documentation output queues:

Delivery Notes
Output queue..... QPRINT
Library..... QGPL

Combined Delivery Note/Invoice
Output queue..... QPRINT
Library..... QGPL

F3=Exit  F8=Update  F12=Previous  F15=Reference numbers
```

Fields:

Site Name

Enter a description or name for the stockroom site.

Delivery Note

Enter a valid output queue and library for delivery note, to determine where you want delivery notes to print.

Combined Delivery Note/Invoice

Enter a valid output queue for combined delivery notes/invoices, to determine where you want combined delivery notes/invoices to print. If left blank the fields default to the queue/library defined for delivery notes when you press **Enter**.



Tip: You cannot update a stockroom site until you have defined reference numbers for it. For further details see Document Processing.

Functions:

F15=Reference Numbers

Use this to define reference code for the stockroom site.



Select **F8=Update** to save the details you have entered.

Reference Number Entry Window



To display this window select **F15=Reference Numbers** on the Stockroom Site Maintenance Screen.

Use this window to view reference numbers for amendment/information purposes. You can also view the type of documentation to which the reference number refers, for more information, see Reference Numbers.

IN975		Z1 - UK Demonstration Company		User GBJBANB4		4/02/98	
						12:04:48	
Stockroom Site Maintenance							
Sto							
Sit	Code..... CENTRAL						
Doc	Description.. central site						
Del	Reference type		Reference	Last number			
Ou	Container References		Code(?)	Used			
Li	Container References						
Com	Delivery Notes			B000210			
Ou							
Li							
F3=Exit F8=Update F12=Previous F15=Reference numbers							
12-40		SA	MW	KS	CL	IM	DM II
				MARVIN	KB	PET087S1	

Fields:

Reference Code

Enter a defined reference code. You can define these within Inventory Management descriptions under major type RFCD. Reference codes are linked to reference types, which are defined under major type RFTP. For more information, see the Descriptions File Maintenance Selection Screen.

Last Number Used

This is the last number the software has recorded against each reference type displayed.



Select **F8=Update** to save any changes.

Reference Numbers



3/INU & 3/INUM

Use this option to maintain reference numbers. You use reference numbers to define separate sequences of despatch note references for each stockroom site.

Maintain Reference Numbers Selection Screen



Select Reference Numbers.

Use this screen to select the reference type and reference code that you want to maintain.

IN977	NR - Neil's Test Company	User GJBANER	21/05/96
			11:38:04
Maintain Reference Numbers			
Reference type...?.. _____			
Reference code...?.. _____			
F3=Exit F4=Prompt			
05-23 SA MW KS IM II KENB20A PET178S1			

Fields:

Reference Type

This is defined within Inventory Management Descriptions as a minor type, for example CREDITNOTE, under major type RFTP. For more information, see the Descriptions File Maintenance Selection Screen.

Reference Code

This is a major type code as defined to the descriptions file RFCD. For more information, see the Descriptions File Maintenance Selection Screen.



Enter the details and press **Enter** to display the Maintain Reference Numbers Screen.

Maintain Reference Numbers Screen



To display this screen, enter the details and press **Enter** on the Maintain Reference Numbers Selection Screen.

Use this screen to maintain the reference number information for amendment.



Tip: You can choose to prefix numbers with a single alpha character leaving up to seven numeric characters free.



Tip: If you want to prefix the reference number to an alpha character, then the leftmost numeric character must be zero.

IN977	NR - Neil's Test Company	User GJBANER	21/05/96 11:40:08
Maintain Reference Numbers			
Reference type..... CREDITNOTE Credit Note			
Reference code.....			
Last number used.... 0 _____ 1			
Next number to use.. 0 _____ 2			
From reference:			
Prefix.. 0 Number.. _____ 1			
To reference:			
Prefix.. 0 Number.. _____ 99			
F3=Exit F8=Update F12=Previous			
10-23 SA MW KS IM II KENB20A PET178S1			

Fields:

Last Number Used

This is the number used for the last transaction for the displayed type of documentation.

Next Number To Use

This is the next sequential number.

From Reference

You can define a start number range for your sequence.

To Reference

You can also define an end number range for your sequence.



Select **F8=Update** to save any details you have entered.

Document Text Profiles



4/INU & 4/INUM

Use this option to maintain document text profiles. These are used to help you specify the type of text you want to use and how you want to use that text. These are defined in the Default Text Types option. Use this option to specify where you want the text types to display in your documentation. For example, you could specify which text appears in the header, line and footer areas of your invoice, order acknowledgement, pick notes and so on.

Document Text Profile Maintenance Selection Screen



Select Document Text Profiles.

Use this screen to select the text profile you want to maintain.

IN046	NR - Neil's Test Company	User GBJBANER	21/05/96 11:41:33
Document Text Profile Maintenance			
Sel	Document Class		
■	Acknowledgements		
-	Pick Notes		
-	Delivery Notes		
-	Invoices		
1=Select F3=Exit			
06-03	SA	MW	KS IM II KENB20A PET178S1

Fields:

Select (Sel)

Enter 1 to select the type of documentation you want to define.

Document Class

You can maintain:

- Acknowledgements.
- Pick Notes.
- Delivery Notes.
- Invoices.



When you have selected a type of documentation press **Enter** to display the Document Text Profile Maintenance Details Screen.

Document Text Profile Maintenance Details Screen



To display this screen select a type of documentation and press **Enter** on the Document Text Profile Maintenance Selection Screen.

Use this screen to enter the text details for your selected document type.

IN046	NR - Neil's Test Company	User GBJBANER	21/05/96 11:43:58
Document Text Profile Maintenance			
Document Class.. Pick Notes			
Sel	Text Type/Usage	Position	Seq.
_ 0 S	Order Header Text / Sales Office Memos	Header	1
Text type..?.. █			
Text usage..?.. _			
Position..... _ 1=Header, 2=Detail, 3=Trailer			
Sequence..... _			
1=Select 4=Delete			
F3=Exit F4=Prompt F12=Previous			
17-18 SA MW KS IM II KENB20A PET178S1			

Fields:

Select (Sel)

Enter one of the following:

- 1 - To select for amendment.
- 4 - To select for deletion.

Text Type

Enter the type of text you want to use on the documentation, for example Order Header.

Text Usage

Enter the code to define where you can use this text. You can define these codes within Inventory Management Descriptions under major type USGC. For more information, see the Descriptions File Maintenance Selection Screen.

Position

Enter one of the following to define the position of the text on the document:

- 1 - Header.
- 2 - Detail.
- 3 - Trailer.

Sequence

Use this to determine where you want to print the text on the documentation.



Press **Enter** to save any details.

Default Text Types



5/INU & 5/INUM

Use this to link the primary text type/usage code and the default or secondary text type/usage code. These text types are used in the Document Text Profiles option to define how you want to display information on your documentation.

Default Text Maintenance Screen



Select Default Text Types.

Use this screen to view or amend default text.

IN052 NR - Neil's Test Company User GJBANER 21/05/96 11:45:36

Default text maintenance

Sel	Text type/usage	Default text type/usage
- 0 E	Order Header Text	C E Customer Text
	External Text	External Text

Text type.....?.. -
Text usage.....?.. -
Default text type..?.. -
Default text usage.?.. -

1=Select 4=Delete
F3=Exit F4=Prompt

06-03 SA MW KS IM II KENB20A PET178S1

Fields:

Select (Sel)

Enter one of the following:

1 - To amend.

4 - To delete.



Note: When you select amend, the current details are displayed in the fields at the bottom of the Screen.

Text Type

Select the type of text you want to use on the documentation, for example, Order Header.

Text Usage

Select the code to use this field as a memo field available for user defined records.

Default Text Type/Usage

These are the default values for the text type and usage; you can define them within Inventory Management Descriptions file under major type USGC.



Press **Enter** to save any details you have entered.

Copy Company



11/INU & 1/INUD

Use this to create a new company within Inventory Management. The option copies the company profile and descriptions file. You can then complete the new company information using the company maintenance option.

```
IN005                                     User STDFIN          3/02/00
                                           11:21:28

Copy Companies

From Company.....?..  _
To Company.....      _

F3=Exit  F4=Prompt
```

Fields:

From Company

Enter the company code of the company from which you want to copy data.

To Company

Enter the new company code of the company to which you want data copied.



Note: The new company code should not exist already within the application.



Press **Enter** to copy the company details.

Rebuild Item Search

1... 12/INU & 2/INUD
2...

Use this option to refresh the Item Master Scan.

You should run this option if:

- You have converted files from another system and therefore need the scan redefining.
- You have made changes to the item description and/or text and need to re-build the text.

```
IN049          Version 3 Demonstration Company      User  STDFIN          3/02/00
                                                    11:21:56

*** WARNING ***

The rebuild facility uses the basic item description
and the item external text to rebuild the search index.
NOTE that there is no facility to preserve search word
overrides.

F3=Exit          F8=Submit
```

 Select **F8=Submit** to rebuild the item search words.

Renumber Item Search Words



13/INU & 3/INUD

Use this option to renumber the search words associated with each item.

This is submitted directly from the menu, with no selections or parameters required.



There are no selection criteria for this option,
select **F8=Confirm Submit** to process the batch
job.

Location Balance Data Take On



5/INUD

Use this option when you implement Location Control. You use this option to add the item's (or item and lot's) current Inventory balance to its default location.

You must run this option for each active Location Controlled stockroom.

If the item's location control item/stockroom profile has not been created then this option will create it, based on the stockroom's defaults, and the location balance if placed in the stockroom's default location.

This option produces a report of all of the balances transferred and any profiles that have been created. There should be no need to re-run this option for a stockroom. If you do re-run this option, it can only update those items with no location balances, and these should not exist. All items and item/lot combinations that have an existing location balance are not updated, these will appear on the report with the Already Transferred error text.

You need to process a stocktake for all items that use multiple locations, so that you correctly populate the location balances before you start to use Location Control.



Note: This, optionally, runs the Rebuild Balances From Locations report in report only mode. The report should show that the sum of the location balances by item/lot match the item/lot balances by stockroom.

Considerations Before Using This Option To Create Location Control Item/Stockroom Profiles

If you are going to use this option to create the Location Control Item/Stockroom profiles then you need to consider the following issues:

- Whether you set the stockroom profile value to single or multiple locations:
 - GEAC strongly recommend that you use the multiple locations setting. If you do not select this then you will have to reset this value for each item that uses a different location to the stockroom's default location before you can start to perform a stocktake and redistribute the stock around the stockroom.
- Items that only require a single location that is different from the stockroom's default location:
 - If the item/stockroom profile is created before you use this option then the take-on will place the stock into the correct location. If the profile is created as part of this option then the single location status will have to be set after the stocktake has been processed.

Rebuild Balances From Locations Screen

To display this screen, select the Rebuild Balances From Locations option.

Use this screen to select the stockroom, or stockrooms, whose balances you want to validate or update, and start the process.

IN635P	MM - Catchweight Company MM	USER GBJBAHEH	7/11/00 11:19:32
Location Detail Data Take-on			
Stockroom..?.. __			
Run Reconciliation Report <u>1</u> (1-Yes, 0-No)			
F3=Exit F4=Prompt F8=Submit Job			

Fields:

Stockroom

Enter the stockroom whose location balance details you want to take on. This must be a stockroom that has Location Control activated.

Run Reconciliation Report

Enter one of the following:

0 - To produce the Rebuild Balances From Locations Report and not update the balances.

1 - To produce the Rebuild Balances From Locations Report and update the balances. For more information, see the Rebuild Balances From Locations option.



Select **F8=Submit Job** to process the Rebuild Balances From Locations and produce the required reports.

Adjust Rotation Date Balances



You can only use this option if your company is using Location Control.

Use this option to adjust the rotation balances so that they match the actual stock balances' rotation dates in a location.

There are a number of reasons why these two balances might not match:

- The picker does not pick the oldest stock every time they are requested to issue stock.
- The newest stock is not returned when a receipt is returned.
- Stock has been transferred between locations or stockrooms.
- Stock has been returned from a customer.



Note: These kinds of discrepancies are normal if you use this form of stock rotation to control your stockroom balances. GEAC recommend that you use this option whenever you consider the discrepancies are beginning to affect the quality of the stock rotation you are achieving.

Adjust Rotation Date Balances Selection Screen



To display this screen, select the Adjust Rotation Date Balances option.

Use this screen to select the item, stockroom and location whose rotation date balances you want to adjust.

```
IN614                MM - Catchweight Company MM      USER GBJBAHEH    18/10/00
                                                    15:11:59

Adjust Rotation date balances

Item.....?.. _____
Stockroom.....?.. _
Location.....?.. _____

F3=Exit  F4=Prompt
```

Fields:

Item

Enter the item code for the item you want to maintain. This item must be stocked in a Location Controlled stockroom, it must not be lot controlled, and must not be a Kit parent item.

Stockroom

Enter the stockroom code for the stockroom you want to maintain. This stockroom must be Location Controlled.

Location

Enter the location that you want to maintain.



Note: If your item has only a single, default, location defined against it, you do not need to enter the location code.



Press **Enter** to display the Adjust Rotation Date Balances Details Screen.

Adjust Rotation Date Balances Details Screen



To display this screen, press **Enter** on the Adjust Rotation Date Balances Selection Screen.

Use this screen to add, amend or delete rotation date balances for your selected item/stockroom/location combination.



Note: When you add, amend or delete a rotation balance, the same window is displayed, but the title of that window reflects the action that you have chosen.

The top of the screen displays details of the selected item code and description, the stockroom and location, and the location balance in issue units, and the sum of the rotation date balances.

The middle of the screen displays the receipt (or creation) date and the time of that transaction, along with the unique reference allocated to that transaction, and the quantity affected by that transaction.

IN614		MM - Catchweight Company MM		USER GBJBAHEH		18/10/00	
						15:12:18	
Adjust Rotation date balances							
Item.....	MMBSNM		Normal std 2/loc				
Stockroom.....	HL		LC Stockroom				
Location.....	D06		Balance....		5.000	EA	
			Cumulative..		5.000		
Sel	Date	Time	Unique Id		Quantity		
-	26/09/00	14:07:55	0000000000001228		5.000		
2=Amend 4=Delete							
F3=Exit F6=Add F12=Previous							

Fields:

Select (S)

Enter one of the following:

- 2 - Amend. To select the balance whose details you want to amend.
- 4 - Delete. To select the balance whose details you want to delete.

Functions:

F6=Add

Select this function to create a new rotation data balance.



*Note: If the balance and the cumulative balance do not match, then you cannot use **F3=Exit** or **F12=Previous** to exit the option.*



Press **Enter** to save any changes that you have made and exit the option.

Amend Rotation Date Balances Window



To display this window, enter 2 next to the balance that you want to amend and press **Enter** on the Adjust Rotation Date Balances Details Screen.

Or:

Enter 4 next to the balance that you want to delete and press **Enter** on the Adjust Rotation Date Balances Details Screen.

Or:

Select **F6=Add** on the Adjust Rotation Date Balances Details Screen.

Use this window to amend your selected rotation date balance.



Note: When you add, amend or delete a rotation balance, the same window is displayed, but the title of that window reflects the action that you have chosen.

IN614		MM - Catchweight Company MM		USER GBJBAHEH		18/10/00	
						15:12:18	
Adjust Rotation date balances							
Item.....	MMBSNM	Normal std 2/loc					
Stockroom.....	HL	LC Stockroom					
Location.....	D06	Balance....	5.000	EA			
		Cumulative..	5.000				
Sel	Date	Time	Unique Id	Quantity			
2	26/09/00	14:07:55	0000000000001228	5.000			

Amend rotation date balance			
Date.....	26/09/00		
Time.....	14:07:55		
Quantity...	5.000		
F12=Previous			

2=Amend 4=Delete
F3=Exit F6=Add F12=Previous

Fields:

Date

This is the date of the selected rotation date balance. You can change it to any date up to the current system date if required.

If you are adding a new rotation date balance then this value defaults to the current system date.

If you are deleting a balance you cannot change this information.

Time

This is the time associated with the transaction. You cannot enter a date and time combination that is in the future.

If you are adding a new rotation date balance then this value defaults to the current system time.

If you are deleting a balance you cannot change this information.

Quantity

This is the rotation date balance.

If you are entering a new rotation date then this value must be greater than zero.

If you are deleting a balance you cannot change this information.

Functions:

F11=Delete

This function is only displayed if you have selected to delete a rotation date balance. Select this function to confirm your intention to delete the selected balance.



Press **Enter** to add, or amend, the rotation date as required and redisplay the Adjust Rotation Date Balances Details Screen.

Set Balance Quantities To Zero



14/INU & 27/INUD

This option sets the Inventory primary and secondary balances for the stockroom, lot, FIFO and location to zero.

This option does not zeroise the corresponding warehouse location balances.



Warning: GEAC strongly recommend that you use this option within a test environment as it does not generate any adjustment records.



There are no selection criteria for this option, select **F8=Confirm Submit** to process the batch job.

Build Item Deletion Logical Files



15/INU & 28/INUD

You can use this option as part of the item deletion routine, see Item Deletion for more details.



There are no selection criteria for this option, select **F8=Confirm Submit** to process the batch job.

Database Integrity



16/INU & 1/INUI

Use this option to check the integrity of the item data across several files. These are:

- Item Master - INP35.
- Stockroom Balance - INP60.
- Stockroom Profile - INP20.
- Stock Location - INP80.
- FIFO Costs - INP83.

This does not make any automatic adjustments but produces a report highlighting any errors for manual amendment.



Note: You should run this on a weekly basis initially, then run monthly, quarterly, and finally on an ad hoc basis. GEAC suggest that you run this option in the Bottom-Up Validation format.

IN900CLP	User STDFIN	0/00/00
		11:22:33
Inventory Integrity Menu		
1. Top-down validation.		
2. Bottom-up validation.		
Company code.... #		
Enter option.... 01		
Message type.... 2	1 = warning and serious messages will print,	
	2 = serious messages only will print (default)	
F3=Exit F6=Messages		

Fields:

Company Code

Enter the company code of the company that you want to perform integrity processing upon.

Enter Option

Enter one of the following:

- 1 - Validate using Top-Down Validation.

2 - Validate using Bottom-Up Validation.

Message Type

Enter one of the following:

- 1 - To print warning and serious messages.
- 2 - To only print serious messages. This is the default.

The routine processes as follows:

Top-Down Validation

This function reads the Item Master Records and performs the following integrity checks:

1. That each item has at least one item stockroom record associated with it. A warning message is printed if this is not the case.
2. That a stockroom profile record exists for each stockroom defined on a stockroom balance record. A serious error message is printed if this is not the case.
3. That at least one FIFO cost record exists for stockroom balances associated with items for which FIFO costing is specified. A warning message is printed if this is not the case.
4. That for FIFO costed items, the sum of the FIFO balance quantities is equal to the stockroom balance physical stock. A serious error message is printed if this is not the case.
5. The presence of FIFO records for items that are not FIFO costed. If any such records are found, a serious error message is printed.
6. That for lot controlled items the sum of the balance is equal to the stockroom balance physical stock. A serious error message is printed if this is not the case.
7. The presence of lot records for items that are not defined as lot controlled. If any such records are found, a serious error message is printed.

Bottom-Up Validation

This function is processed as above, but in reverse and a similar report is produced.

Functions:

F6=Messages

Use this to display Messages.



Press **Enter** to start the validation process.

Reconciling Demand

You can use two options to reconcile demand.

- Allocation Reconciliation - which reconciles stockroom balance record allocation totals to Sales, Transfer and Production orders.
- On Order Reconciliation - which reconciles stockroom balance record on order totals to Purchase and Production orders.



Note: You should run these on a weekly basis initially, then run monthly, quarterly, and finally on an ad hoc basis.

Allocation Reconciliation

1...
2...

17/INU & 2/INUI



Select Allocation Reconciliation.

Use this option to update the Stockroom Balance File (INP60).

```
IN916P          Z1 - UK Demonstration Company      User GBJBALW      3/06/98
                                                    13:05:26
Allocation Reconciliation

Company..... Z1

Do you wish the Reconciled quantity Allocated to be updated? 0 (0=No,1=Yes)

Press Enter to submit report.

F3=Exit
```

Fields:

Do You Wish The Reconciled Quantity Allocated To Be Updated?

Enter one of the following:

0 - To report the differences with no update to the stockroom balance.

1 - To use the software calculated allocated quantity to update the stockroom balance record where differences are found.



Press **Enter** to confirm your selection and submit the job.

On Order Reconciliation

1...
2...

18/INU & 3/INUI



Select On Order Reconciliation.

Use this option to update the Stockroom Balance Record (INP60).

```
IN917P          Z1 - UK Demonstration Company      User GBJBALTW      3/06/98
                                                    13:05:54

On Order Reconciliation.

Company..... Z1

Do you wish the Reconciled quantity On Order to be updated?  0  (0=No,1=Yes)

Press Enter to submit report.

F3=Exit
```

Fields:

Do You Wish The Reconciled Quantity On Order To Be Updated?

Enter one of the following:

0 - To report on the differences without updating the stockroom balances.

1 - To use the application calculated order quantity to update the stockroom balance record where differences are found.



Press **Enter** to confirm your selection and submit the job.

Audit Negative FIFO



19/INU & 4/INUI

If you process an issue before making the appropriate receipt, this can result in a negative figure in the FIFO record. Use this option to print a list of any records that have been created with negative costs.



There are no selection criteria for this option, select **F8=Confirm Submit** to process the batch job.

Rebuild Balances From Locations



5/INUI

If you are using Location Control then you can use this option to re-align Inventory balances and rotation balances with the location balances if they do not match.

You can run this option in report only or report and update modes for one or all Location Controlled stockrooms. There are two stages to the rebuild balances process:

- Rebuild from the location balances:
 - Compares the location balance to the sum of the rotation date balances (for non lot controlled items). If the sum of the rotation date balances exceeds the location balance, it consumes the rotation date balances in FIFO (First In First Out) sequence. If the sum of the rotation date balances is less than the location balance, it adds the difference to the oldest balance or writes a new balance record with the current system date.
 - Compares the lot or item balances to the sum of the location balances. If the sum of location balances differs from the lot or item balance, it adjusts the lot or item balance accordingly.
 - Deletes any empty location balance records. An empty location balance has zero physical and frozen stock.
- Create missing location and rotation balances:
 - The rebuild stage relies on the presence of a location balance. This creation stage caters for situations where there is an Inventory balance without a corresponding location balance. This situation should not occur after the initial data take-on process. This stage uses the same logic as the Location Balances Data Take-On option and will create any missing item/stockroom profiles if required.

Each stage will produce a report. If you run this option in report mode only then no balances are updated or deleted.



Warning: This option does not check that the sum of the lot balances matches the items stockroom balance. To do this, use the Data Integrity option. This option does not detect items or lot balances with no corresponding location balance as this situation should not occur.



Note: This screen is the same as that used in the Location Balance Data Take On option.

```
IN634P          Z1 - GB Demonstration Company    USER GBJBA1MS    5/10/00
                                                    11:31:41
Rebuild Balances from locations
Stockroom..?... _ (Blank for all stockrooms)
Update..... @ (0=Report, 1=Report and Update)

In report mode this option will: -
* Recalculate the nominal secondary balances (catchweight only)
* Report differences between location, rotation date & lot/stockroom balances
* Report lot/stockroom balances with no location balance

In Update mode this option will also: -
* Recalculate the nominal secondary balances (catchweight only)
* Report differences between location, rotation date & lot/stockroom balances
  * Adjust the lot/stockroom & rotation date balances to the location balances
* Delete empty location balances
* Report lot/stockroom balances with no location balances
  * Create missing item/stockroom profiles from the default values
  * Create missing location & rotation date balances in the default location

F3=Exit F4=Prompt F8=Submit
```

Fields:

Stockroom

Enter the stockroom whose location balances you want to rebuild. Leave this field blank to rebuild location balances for all location controlled stockrooms within your company.

Update

Enter one of the following:

0 - Report. To just produce a report.

1 - Report And Update. To produce the report and update the location balances.



Select **F8=Submit** to process the report and, optionally, update the balances.

Recalculate Nominal Sec Values



20/INU & 4/INUD

Use this option to recalculate the nominal secondary stock levels for Non-Catchweight items, or for Catchweight type 3 items that have a secondary value when transactions have occurred. You can use it to reset existing values, but is intended to create secondary stock levels for Non-Catchweight items that have just had a secondary value assigned to them.



Note: If you are using Location Control, then this option is also run as part of the Rebuild Balances From Locations option.

If no transactions have occurred, then the secondary values are zero.

The software calculates the secondary stock balance from the primary stock balance for the stockroom, lot, FIFO or lot trace, or both and location balances held within Inventory.



Tip: If you hold a lot of Catchweight type 3 items GEAC recommend that you run a stock valuation before and after you use this option.



Warning: *This option does not produce stock movements or an audit trail.*



There are no selection criteria for this option, select **F8=Confirm Submit** to process the batch job.

Company Deletion



21/INU & 21/INUD

Use this option to delete all the data for specified companies. You would normally use this option in a test environment. The purpose of this option is to remove all data from Inventory Management for one or more selected companies. This occurs in three steps:

1. Copy to a temporary library, the data for the companies that you want to retain.
2. Clear the physical files in the live library.
3. Copy back the data from the temporary library to the live library.

Enter the libraries that contain the relevant data for the deletion. If bespoke libraries are present then you should run this option separately for each library.



Select Company Deletion.

Use this screen to select the company that you want to delete.

IN903	User GBJBA1MS	16/02/99
		14:36:03
Company Deletion		
This utility will delete records within all inventory files		
for Company CW CW - Mitsubishi Fuso Truck (CW)		
Press ENTER to submit the deletion routine.		
Press function key F3 to cancel the deletion routine.		
F3=Exit		

Fields:

This Utility Will Delete Records Within All Inventory Files For Company

Enter the code for company you want to delete and press **Enter**. The company you are currently using is the default.



Press **Enter** to confirm the deletion and submit a batch job to delete the requested companies.

Delete History And Movements



22/INU & 22/INUD

Use this option to purge data from the Stock Movement and Stock History files. Inventory deletes a record from the appropriate file when its week number is before the current week being processed, modified by the number of weeks entered as a parameter.



Warning: Take care to control history deletion, as the Stock History Records are used to determine average usage.

Delete History And Movements Screen



Select Delete History And Movements.

Use this screen to select the information that you want to retain after the purge has occurred.

IN039	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:06:41
Remove Obsolete Movement And/Or History Details			
No. of weeks movements to retain.... 060 (999 - Retain all)			
No. of weeks history to retain..... 060 (999 - Retain all)			
F3=Exit			

Fields:

No Of Weeks Movement To Retain

Enter up to three numeric characters to specify the number of weeks of Stock Movements you want to retain. The default is 60 weeks. Enter 999 to retain all movements.

No Of Weeks History To Retain

Enter up to three numeric characters to specify the number of weeks of Stock History records you want to retain. The default is 60 weeks. Enter 999 to retain all history records.



Press **Enter** to confirm the input parameters, and submit the job to remove movement and history records.

Delete FIFO/Lot Details



23/INU & 23/INUD

Use this option to purge data from the FIFO Details file (INP83). You can also purge details from the batch/lot file (INP80).

This deletes any FIFO records with zero balances, and batch/lot records with zero balances and no stock movements.

Delete FIFO/Lot Details Screen



Select Delete FIFO/Lot Details.

Use this screen to specify the selection criteria to base your purge upon.

IN910	Z1 - UK Demonstration Company	USER GBJBALTW	3/06/98
			13:07:11
FIFO and lot			
Cut-off Date..... <u>3/06/98</u>			
Only FIFO cost records up to and including the cut-off date with a zero balance will be deleted			
Location.(0=no,1=yes)..... <u>0</u>			
Cut-off Date for location. <u>3/06/98</u>			
F3=Exit			

Fields:

Cut-Off Date

Enter the cut-off date for the FIFO details deletion. You can only delete records up to and including the cut-off dates.

Location

Enter one of the following:

1 - To delete batch/lot details.

0 - To retain batch/lot details.

Cut-Off Date For Location

Enter the cut-off date for the batch/lot details deletion. Again, you can only delete records up to and including the cut-off dates.



Press **Enter** to confirm the selection criteria and submit the job to remove FIFO details and batch/lot records.

Purge Stock Counts



24/INU & 24/INUD

Use this option to purge completed counts by individual count or by a count range basis.

The count headers and their associated count recommendations are deleted with full auditing to system standards. In addition the associated count lists and their details are deleted.

You can choose to purge incomplete outstanding counts, so associated items are taken off count (for item based counts) and associated locations are taken off count (for location based counts).

Purge Stock Counts Screen



Select Purge Stock Counts.

Use this screen to specify the selection criteria to base your purge upon.

IN921	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:07:24
Purge stock count			
Stockroom.....?.. _			
Count number from.....?.. _____ to.....?.. _____			
Purge incomplete count..... 0 0=No 1=Yes			
F3=Exit F4=Prompt F8=Submit			

Fields:

Stockroom

Enter the stockroom for which at least one count has been requested.

Count Number From To

Enter a range of count numbers. If you define a range, then the From and To count numbers need not exist.

If you leave the To count number blank, it defaults to the From count number.

Enter a single count number. If you select a single count number then it must exist, be complete (reconciled) and the purge incomplete counts field should be set to 0.



Tip: You must enter 1 in Purge Incomplete Counts if you want to purge incomplete counts.

Purge Incomplete Counts

Enter one of the following:

0 - Do not purge incomplete counts as well as reconciled counts.

1 - Purge incomplete outstanding counts as well as reconciled counts.



Select **F8=Submit** to send the report to print.

Purge Count Details/Action Lists



25/INU & 25/INUD

Use this option to purge completed count list details, by date.

The count lists and all associated details are deleted when their date of creation is less than or equal to the date entered.

Count Details And Action List Purge Screen



Select Purge Count Details/Action Lists.

Use this screen to select the stockroom on which you want to process the purge, and the cut off date for the purge itself.



Tip: The date entered defaults to the period end date for the current period minus two.

IN927	Z1 - UK Demonstration Company	User GBJBALTW	3/06/98 13:07:38
Count Details and Action List Purge			
Stockroom.....?.. _			
Purge upto..... <u>28/02/98</u>			
F3=Exit F4=Prompt F8=Submit			

Fields:

Stockroom

Enter the stockroom code for which purge has been requested.

Purge Date

Enter the date up to which you want to delete completed details.



Select **F8=Submit** to start the process.

Item Deletion



26/INU & 29/INUD

Use this option to delete from the database those items previously flagged for deletion in Item Master Maintenance, using a batch job.

If you want to delete a large number of items this option can take a considerable time to run. So you can split this process into two separate stages:

1. Take the Build Item Deletion Logical Files option to create the necessary technical requirements to allow the software to process the item deletion.
2. Take this option (Item Deletion) to physically remove the items from the database.



Note: You can use this option to perform the item deletion as a single task.



Note: The overall performances of the two methods are approximately the same.

Item Deletion Window



Select Item Deletion.

Use this window to specify the cut off date for the deletion, and whether you want to delete items and produce a report or just to produce the report. The report lists all items flagged for deletion using the Item Maintenance option.

INU	Version 3 Demonstration Company	User STDFIN	03/02/00
			11:25:30
Inventory Utilities Menu			
Maintenance		Integrity/Reconciliation	
1. Company		16. Database integrity	
Remove inventory items flagged for deletion			
Do you wish to delete the items from the database.. 1 1=Report Only			
2=Report & Delete			
Delete items with effectivity end date up to..... 0/00/00			
F3=Exit F8=Submit			
14. Set balance quantities to zero		24. Purge stock counts	
15. Build item deletion logical files		25. Purge count details/action lists	
		26. Item deletion	
89. Processing profiles and AFI		27. Delete shipment receipts	
90. Signoff		28. Audit file purge maintenance	
Option 26		29. Submit audit file purge	
Search		30. Audit purge-machine mgr parms	
F3=Exit F4=Prompt F6=Messages F12=Previous F16=Change company F18=Prints			

Fields:

Delete Items From Database

Enter one of the following:

- 1 - To produce a report of items for deletion.
- 2 - To physically delete the items from the database and produce a report of the items deleted.

Effectivity End Date

Specify an effectivity end date for the deletion. All items flagged for deletion with an effectivity end date on or before the entered date are deleted.



*Note: To prevent deletion of an item stockroom with any existing stock movement, you should set up the code IDMP in the Descriptions file under Major Type MISC. The IDMP **Rate** field should specify the number of periods back from the current period, during which time you do not want deletions to occur. If you have not defined IDMP in the Descriptions file, all items flagged for deletion will be deleted during the Item Deletion Routine.*



Select **F8=Submit** to process the report or delete the items and process the report, depending on your selection criteria.

Delete Shipment Receipts



27/INU & 26/INUD

Use this option to delete all confirmed shipment reports from the database.



Note: This function requires exclusive use of the application.



There are no selection criteria, select
F8=Confirm Submit to process the batch job.

Audit File Purge Maintenance



28/INU & 28/INUD

Use this housekeeping option to select audit files you want to include in the purge routine to free unnecessarily occupied space on your system.

Audit File Purge Maintenance Selection Screen



Select Audit File Purge Maintenance.

Use this screen to select the application to purge.

IN527 Distribution V3 -> V3 Financials 3F User GBJBA1MS 5/12/96
16:10:59

Audit File Purge Maintenance

Application.....?.. ?_ (Leave blank for all)

Select application

MORE: +

Sel	Application	Description
■	AC	AC Fix environment V3.0
-	CN	Configurator fix
-	CR	Customer returns V3 Fix
-	DR	DRP Version 3 FIX
-	FC	Forecasting V3 fix
-	IN	Inventory V3 fix environ
-	OE	Sales order processing V
-	PM	Purchase Management V3 F
-	TP	Transport Planning V3 FI
-	WH	warehousing V3 fix

1=Select
F12=Previous

F3=Exit F4=Prompt

10-35 SF MW KS IM II EDN400A PET149S1

Fields:

Application

You can select to submit audit files to the purge routine in two ways:

- Enter a specific Application Code to display only audit files corresponding with a required Application.
- Leave the Application field blank to display all audit files corresponding with all applications.



Press **Enter** to display the Audit File Purge Maintenance Details Screen.

Audit File Purge Maintenance Details Screen



To display this screen, select the required Application and press **Enter** on the Audit File Purge Maintenance Selection Screen.

Use this screen to select the audit files you want to submit to the purge routine. The files are displayed in numerical order. For each file the audit file number, description and date of the last purge is displayed.

IN527		Distribution V3 -> V3 Financials 3F User GBJBA1MS			6/12/96
					10:40:14
Audit File Purge Maintenance					
<u>Include(0/1)</u>	<u>File</u>	<u>Description</u>	<u>Purge Date</u>	<u>Number of Days</u>	
1	INP01A	Product transaction control au	6/12/96	_____	
0	INP35A	Item maintenance audit log	0/00/00	_____	
0	INP36A	Item attributed audit	0/00/00	_____	
1	INP37A	Item/customer profile	6/12/96	_____	
0	INP38A	Alternative item reference aud	0/00/00	_____	
0	INP45A	Alternative parts- Amendment 1	0/00/00	_____	
0	INP46A	Supersessions	0/00/00	_____	
0	INP47A	Multi-sourcing rule header aud	0/00/00	_____	
0	INP48A	Multi-sourcing rule details au	0/00/00	_____	
0	INP50A	Search family attributes audit	0/00/00	_____	
0	INP51A	Count profile audit	0/00/00	_____	
0	INP52A	ABC class profile audit	0/00/00	_____	
0	INP54A	Count details audit	0/00/00	_____	
0	INP58A	Count header audit	0/00/00	_____ +	
F3=Exit F8=Update F12=Previous					
00-05		SP	MW	KS	IM II EDN400A PET149S2

Fields:

Include 0/1

Enter one of the following:

- 0 - To exclude it in the next purge routine.
- 1 - To include an audit file in the next purge routine.

Number of days

Enter the number of days before a run date that you want to keep audit file records. You can enter a maximum of 999 days.



Select **F8=Update** to update any changes and update the appropriate records to Inventory Management. To run the purge routine, select Submit Audit File Purge.

Submit Audit File Purge



29/INU & 12/INUD

Before you use this option, select the audit files you want to include in the purge routine using the Audit File Purge Maintenance option.

Use this housekeeping option to start the audit file purge routine.



Note: This option also purges Location Control audit files if you are using Location Control.



Tip: You should run this option regularly using Machine Manager.

Submit Audit File Purge Screen



Select Submit Audit File Purge.

Use this screen to select the application you require.

```
IN529          Distribution V3 -> V3 Financials 3F User GBJBA1MS    6/12/96
                                                    11:25:04
Audit File Purge
Application.....?.. __

F3=Exit  F4=Prompt  F8=Submit

05-22    SF      MW      KS      IM      II  EDN400A  PET149S2
```

Fields:

Application

Enter an application code to submit the selected audit files for one application or leave this blank to submit all audit files selected in the Audit File Purge Maintenance option.

The software calculates the purge date for each audit file by subtracting the entered number of days from the current system date. It purges any audit records created on or before the calculated purge date.



Tip: After the routine is complete, the submitted audit files remain selected with 1. This is so you can keep a fixed number of days' records and run the purge routine without using the Audit File Purge Maintenance option.



Select **F8=Submit** to process the purge.

Audit Purge Machine Manager Parameters

1...
2...

30/INU & 13/INUD

- Select the audit files you want to include in the purge routine using the Audit File Purge Maintenance option.




Note: This option also purges Location Control audit files if you are using Location Control.



Tip: You should run this option regularly using Machine Manager.

Audit Purge Machine Manager Parameters Screen



Use this housekeeping option to routinely purge audit files via Application Manager. This is useful if your system does not have a space problem, as you only need to access the Audit File Purge Maintenance option once.

[illegible]

Fields:

Application

Either enter an application code to submit audit files for specific applications or leave this blank to submit all audit files selected in the Audit File Purge Maintenance option.

The software will purge the files selected in the Maintenance option, with the same number of days audit records preserved each time the routine is run.



Purge Location Allocation Details



30/INUD

Use this option to delete completed event allocation details.



Tip: You should run this option regularly using Machine Manager.



There are no selection criteria for this option, select **F8=Confirm Submit** to process the purge.

Processing Profiles



1/INW & 13/INUM

Use this option to provide profile information for the Inventory Management interface program. These profiles provide both user defined Inventory Management updates as well as standard updates dictated via other Distribution products.



Note: For more information about how POD works, see the Introduction To Proof Of Delivery in the Utilities Section of the Sales Order Processing Product Guide.

Inventory Processing Profile Maintenance Selection Screen



Select Processing Profiles.

Use this screen to specify the profile that you want to process.

IN085	Z1 - GB Demonstration Company	User GBJBA1MS	5/10/00
Inventory Processing Profile Maintenance			10:43:52
Profile code...?.. ____			
F3=Exit F4=Prompt			

Fields:

Profile Code

Enter the profile code that you want to process.



Press **Enter** to display the Inventory Processing
Profile Maintenance Screen.

Inventory Processing Profile Maintenance Screen



To display this screen, enter a profile code that defines an instruction set on the Inventory Processing Profile Maintenance Selection Screen and press **Enter**.

Use this screen to view existing sequences within the profile, showing movement type and description.

IN085	Z1 - Demonstration Company	User SP1	21/09/94 9:54:43
Inventory Processing Profile Maintenance			
Profile code..... 001		<u>Adjust Physical Stock</u>	
1	Sequence	Type	Description
<u>1</u>	1	A	Stock Adjustment
1=Select			
F3=Exit F8=Addition F11=Delete F12=Previous			

Fields:

Profile Code

The Screen displays the profile code, you can enter or amend the description.
Press **Enter** to display the next detail fields on the screen.

Select (1)

Enter 1 to select the sequence you want to maintain.

Sequence

The sequence number allocated to use in the profile.

Type

The movement type that you want to generate for a given item.

Description

A description of the movement type.



Select a sequence to maintain and press **Enter** to display the Inventory Processing Profile Maintenance Detail Screen.

Inventory Processing Profile Maintenance Detail Screen



To display this screen, select to maintain a profile or sequence on the Inventory Management Processing Profile Maintenance Screen and press **Enter**.

Use this screen to maintain part of the profile code you have selected.

IN085	MM - Catchweight Company MM	User GBJBAHEH	9/11/00 10:10:14
Inventory Processing Profile Maintenance			
Profile code.....	004	Transfer In	
Sequence.....	1		
Movement type..?	1	Transfer In	
Stockroom.....	1	(1=From,2=To)	
Sign of quantity..	+		
Cost value calc.?			
Update for balance Fields:			
Physical.....?	1	On order.....?	0
Allocated.....?	0	On back order..?	0
Frozen.....?	0	Bonded.....?	0
In-transit....?	0	Forward.....?	0
Reserved.....?	0		
Other updates: (0=No,1=Yes)			
Available.....	1	Costs.....	0
FIFO balances...	1	Date of issue....	0
Update history..?	6	Usage.....?	0
		Date of receipt...	1
Additional movement details:			
Reference type.?	___		
Reason Code....?	___		
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous			

Fields:

Sequence

Define the sequence of Inventory Management updates within the profile.

Movement Type

The movement type that you want to generate for a given item.

Stockroom

Enter one of the following:

1 - For the From stockroom.

2 - Use the To stockroom when two stockrooms are affected by the instruction set in this profile.

Sign Of Quantity

This specifies the sign that the quantity would normally be expressed in on the movement record.

Cost Value Calc

Any entry made is validated against the Inventory Management Descriptions file, against type CVLR

Update For Balance Fields

This specifies which of the balance fields are to be updated as a result of this transaction:

- Physical.
- On order.
- Allocated.
- On back order.
- Frozen.
- Bonded.
- In-transit.
- Forward
- Reserved

Enter one of the following:

- 0 - Update not required.
- 1 - Add actual quantity.
- 2 - Subtract actual quantity.
- 3 - Add planned quantity.
- 4 - Subtract planned quantity.

Recalculate Available

Enter one of the following:

- 0 - Available stock is not to be recalculated.
- 1 - Available Stock to be recalculated.

Update Costs

Enter one of the following:

- 0 - Latest, Average and FIFO costs are not to be updated.
- 1 - Latest, Average and FIFO costs to be updated.

Update Usage

Enter one of the following:

- 0 - Update not required.
- 1 - Add actual quantity.
- 2 - Subtract actual quantity.
- 3 - Add planned quantity.
- 4 - Subtract planned quantity.

FIFO Balances

Enter one of the following:

0 - FIFO cost/lot trace balances are not to be updated.

1 - FIFO cost/lot trace balances are to be updated.

Date Of Issue

Enter one of the following:

0 - Date of last issue is not to be updated.

1 - Date of last issue to be updated.

Date Of Receipt

Enter one of the following:

0 - Date of last receipt is not to be updated.

1 - Date of last receipt to be updated.

Update For History

Enter one of the following to specify the balance to be updated for stock history:

0 - Update not required.

1 - Receipt.

2 - Issue.

3 - Adjustment.

4 - Transfer out.

5 - Supplier orders.

6 - Transfer in.

Additional Movement Details

Reference Type

Enter an additional movement type code for this item. These are defined in Inventory Descriptions under major type TRAN.

Reason Code

Enter a reason code for the movement. These are defined in Inventory Descriptions under major type MOVR.

Functions:

F11=Delete

Select this to delete the processing profile.



Select **F8=Update** to save any changes.

Test



2/INW & 2/INUA

Use this option to run test extracts of data from Inventory Management and create a General Ledger journal.



Note: No actual updating of data takes place, either within Inventory Management or General Ledger. This is simply a simulation of the effect of creating the specified journals for the nominated company.

You can generate three reports:

- General Ledger Postings - A list of the postings generated.
- Exceptions Report - Displaying, for example, any balancing postings automatically created for an unbalanced journal.
- Error Report - Displayed error conditions encountered.

Prompt For Inventory Trial Extract and Update Screen



Select Test.

Use this screen to select the source company and type of extract you want to process.

```
FI510                      Advanced Financial Integrator  User GBJBA1MS  30/07/96
                             Prompt for Inventory Trial Extract and Update  13:04:05

Source company . . . . . ? 01
EITHER: work with inventory movements not yet processed 1 (1/0)

OR   : work with inventory movements from . ? _____ to _____

Type of Journal definition to use: 1  1=Under Test
                                   2=LIVE
                                   3=Both

Consolidate postings? . . . . . 0 (1/0)

-----
F3=Exit  F4=Prompt  F8=Proceed  F12=Previous

07-39    SP      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Source Company

Enter the source company whose data you want to use for this trial extraction.

Work With Inventory Movements Not Yet Processed

Enter one of the following:

- 0 - To specify a range of transaction numbers on which you want to base the trial.
- 1 - To use data that has not been extracted in live operation mode by AFI.

Work With Inventory Movements From And To

This is only relevant if the previous response was 0. Specify here the range of transaction dates in the source application you want to use in this trial. If you want to use only the Inventory movements that occurred on a single day, specify the same date in the From and To entries.

Transactions within the source application that can be used for this trial are displayed in a pop up window.

Type Of Journal Definition To Use

Enter one of the following:

- 1 - Use journal definitions that are specified as being under test.

2 - Use journal definitions that are specified as being live.

3 - Use both test and live journal definitions.

Consolidate Postings

Enter one of the following:

0 - For no consolidation to take place, even though you may have postings defined as consolidatable.

1 - For consolidation to take place on those postings defined as consolidatable.



Press **Enter** to validate the entries, then
F8=Proceed to process the trial extraction.

Live



3//NW & 3//NUA



Select Live.

Use this option to initiate the extract of Inventory Management transactions from the Inventory movements file, for processing by AFI to create General Ledger journals.



Note: If you have not activated the link between Inventory Management and Advanced Financial Integrator, then a warning message is displayed.

Use this screen to select the company whose transactions you want to extract.

```
INW          NR - Neil Radford and Co. Ltd      User GBJBA1MS      30/07/96
                                                    13:04:29

Inventory Processing Profile/AFI

Processing Definition
  1. Processing profiles
    AFI Stock Move
    2. Test
    3. Live
    4. Install In

Advanced Financial Integrator
Inventory to General Ledger update

Please nominate the company from which
you wish to extract data to update the
General Ledger:

Z1 Demonstration Company

F4=Prompt F8=Proceed F12=Previous

90. Signoff

Option 3
Search

F3=Exit F4=Prompt F6=Messages F12=Previous F16=Change company F18=Prints
14-20   SF        MW        KS        IM        II KENB20A PET166S2
```

Fields:

Company

Specify the company code of the company for which you want Inventory Management transactions extracted.

Transactions are extracted according to the selection criteria set up on your journal condition.



Select **F8=Proceed** to continue with the extraction.

Install Inventory/AFI Link



4/INW & 1/INUA

Where you have linked AFI to Inventory Management, the software extracts inventory movements when the operator selects Install Inventory/AFI Link. AFI creates transactions for the Inventory movement types as defined on the journal conditions set up for Inventory Management. When the operator selects the AFI to General Ledger Update option, these are posted to the General Ledger as journals.

There is no facility to automatically extract transactions and post to the General Ledger without operator intervention within Inventory Management, unlike Sales Invoicing. It is more appropriate to control the extract of Inventory movement transactions on a manual basis, because of the wide range of Inventory movement types, and the likely number of transactions.

If you have not linked AFI to Inventory Management, purchase receipts made within Purchase Management update General Ledger stock accounts when supplier invoices are matched to goods received notes and the logged invoices are confirmed in the Accounts Payable application.



Note: When you receive goods into Inventory Management AFI automatically posts details to the General Ledger Goods Purchased Account.

As well as the AFI link status being set to active, there must also be one or more live journals. The facility to set up a journal as live is part of the Journal Conditions Maintenance facility.



Note: You must set the Journal Condition field to test for a valid value when you want to read date from the source application. For example, you must set up the Journal Condition field to test for a specific Inventory movement type or range of types.

FI940	Version 3 Demonstration Company	USER STDFIN	3/02/00 11:29:35
Install AFI Control Data - APPLICATION: Inventory			
This option causes AFI Control Data to be copied from the install files in the application library into the control files in the AFI Library. AFI will then be aware that this application is installed, and be able to extract data from it.			
Copy From Library . . <u>OSLINP3</u>		Only amend this, if you have renamed your Application displays library.	
Copy To Library . . . <u>OSLFIF3</u>		Amend this library to match your Financial Integrator files library, or the Consolidated Financials files library.	
Please note that records will be added to the file if they do not already exist. If they do exist, they will be overwritten by the new records.			
F3=Exit F8=Submit Job			

Fields:

Copy From Library

Enter the application library that you want to use as the source library.

Copy To Library

Enter the application library that you want to use as the target library.



Select **F8=Submit** to process the link.

AFI Data Dictionary

The following files, and their associated fields, are available for defining how selection and consolidation or both are to take place.

Item Master

- Company Number.
- Item Code.
- Item Type.
- Item Class.
- Division.
- Sub-Division.
- Item Group Major.
- Item Group Minor.
- VAT Code.
- Discount Group.
- Stock Source.
- General Ledger Stock Account.
- General Ledger Cost of Sales Account.
- General Ledger Sales Account.
- General Ledger Price Variance Account.
- Warranty Type.
- Storage Method.
- Costing Method.
- Sub-Contracted Item.
- Resource Code.

Inventory Movement

- Company Number.
- Item Code.
- Stockroom Code.
- Transaction Type.
- Reference Number.
- Movement Type.
- Movement Reason Code.
- Movement Source.

- To/From.

Stock Balance

- Item Type.
- Item Class.
- ABC Override.
- ABC Class.

Stockroom

- Stockroom Usage Code.
- Department Code.

The following fields are defined as quantities that are available to post, (refer to Quantity field to post within posting definitions).

Daily Movements

- Movement Quantity (Movement UOM).
- Movement Quantity (Item Master Issue UOM).

The following fields are available on the Inventory Movement file for posting as a value to the General Ledger.

- Total Movement cost (Good Cost plus Landed Cost).
- Secondary Cost (Landed Cost).
- Net Cost (Good Cost).

Customer Order Issue, has an Inventory Movement Type of C you can use it to perform a negative adjustment.

Sundry Issue, has an Inventory Movement Type of S you can use it to perform a negative adjustment.

Purchase Order Receipt, has an Inventory Movement Type of P you can use it to perform a positive adjustment.

Sundry Receipt, has an Inventory Movement Type of R you can use it to perform a positive adjustment.

Adjust Physical Stock, has an Inventory Movement Type of A, you can use it to perform both a positive and negative adjustment.

Adjust Allocated Stock, has an Inventory Movement Type of L and is both a positive and negative adjustment.

Adjust Frozen Stock, has an Inventory Movement Type of F you can use it to perform both a positive and negative adjustment.

Transfer Out, has an Inventory Movement Type of O you can use it to perform a negative adjustment.

Transfer In has an Inventory Movement Type of I you can use it to perform a positive adjustment.

Purchase Order has an Inventory Movement Type of U you can use it to perform a positive adjustment.

Production Issue, has an Inventory Movement Type of M you can use it to perform a negative adjustment.

Production Receipt, has an Inventory Movement Type of N you can use it to perform a positive adjustment.

Production Adjustment, has an Inventory Movement Type of W you can use it to perform both a positive and negative adjustment.

Adjust In-Transit, has an Inventory Movement Type of T if you process a Transfer Out this is a positive adjustment, if you process a Transfer In this is a negative adjustment.

Direct Delivery, has an Inventory Movement Type of D you can use it to perform a negative adjustment.

Frozen Transfer Out, has an Inventory Movement Type of G you can use it to perform a negative adjustment.

Frozen Transfer In, has an Inventory Movement Type of H you can use it to perform a positive adjustment.

Transformation, has an Inventory Movement Type of J you can use it to perform both a positive and negative adjustment.

Frozen Issue, has an Inventory Movement Type of K you can use it to perform a negative adjustment.

Back-to-back, has an Inventory Movement Type of Q you can use it to perform a positive adjustment.

Activating The Link

GEAC recommend that you set Journal Conditions to test, and use the AFI Test option to prove them before you activate AFI and set Journal Conditions to Live.

Inventory movements are not posted to the General Ledger until you activate AFI. When AFI is active, posting to the General Ledger are made each time Inventory movements are extracted.

You must take the following steps to activate AFI:

1. AFI Maintenance menu. Use the Maintain Journal Condition option to change the status of your journal conditions from inactive (0) or under test (1) to a status of live (2). You do not need to do this for all journal conditions - only those which you are ready to activate.
2. AFI Utilities menu. Use the Maintain Application option to change the status of the AFI link from inactive to active using **F8**. At the same time check the validity of your consolidation settings on this display.

You can now use AFI to process Inventory movements to create General Ledger journals, according to your rules and definitions, from the point when you next create movements within the Inventory Management application and extract them.

Library List

A separate task level library list has been created within AFI to include all the Inventory files necessary to undertake a data extract of Inventory movements from Inventory Management into AFI.

Besides containing the necessary Inventory Management libraries, this includes the following AFI libraries:

OSLFIF3	AFI Data files
OSLFID3	AFI Printer and Display files
OSLFIP3	AFI Programs

Inventory Management also contains a task level library list for the stock movements audit report that includes the necessary Inventory Management and AFI libraries. A check is made to make sure that Inventory movements have been processed by AFI before these are cleared from the daily stock movements file (where clearance of data has been requested).

-
-
-
-
-

Chapter 11

Background Processing

Start And End Stock Monitor



1/INB & 2/INB



***Warning: You must start the subsystem
INBACK3 in library OSLINP3 first.***

Use these options to start and stop the stock monitor. The start stock monitor checks for any lot, batch or serial controlled item with an exceeded expiry date. If this is the case, then the monitor freezes the quantity of that item that has that lot reference recorded against it.

The stock monitor is a background job that establishes the stock status from the production, expiry and availability times and dates that are held on the lot header details. It also updates the frozen and available stock balances, as appropriate, on a daily basis.

You can start and end these monitors directly from the menu.

If you try to restart the stock monitor once you have started it, Inventory will display a window indicating when the monitor was started, and who started it. If this happens, press **Enter** to continue.



There are no selection criteria, select
F8=Submit to start or end the monitor.

Start And End Reservation Monitor



3/INB & 4/INB



***Warning: You must start the subsystem
INBACK3 in library OSLINP3 first.***

Use these options to start and stop the stock reservation monitor. The start reservation monitor updates sales orders when you have chosen to create a back to back (or direct delivery) purchase receipt to supply the items detailed on them.

You can only use this option if you are using Advanced Order Entry and Purchase Management.

If you cannot supply stock from your stockroom for an order, you can use Advanced Order Entry to automatically raise a purchase order which is then reserved against the outstanding sales order.

If you have started the reservation monitor then, when you receive the goods, that receipt is automatically reserved against the sales order. The received goods are then allocated to that sales order for despatch to your customer.

You can start and end these monitors directly from the menu.

If you try to restart the reservation monitor once you have started it, Inventory will display a window indicating when the monitor was started, and who started it. If this happens, press **Enter** to continue.



There are no selection criteria, select
F8=Submit to start or end the monitor.

Start And End Pricing Monitor



5/INB & 6/INB

Use these options to start and stop the advanced pricing monitor. The start pricing monitor performs the relevant calculations and updates when you specify background pricing for the company.

Start And End Invoice Refresh Monitor



7/INB & 8/INB

These options start and stop the invoice refresh monitor. The Start Invoice Refresh Monitor updates the Invoice Monitor.

The start invoice refresh monitor refreshes the database of invoice references with the generated references at the time of invoice print.

You can start and end these monitors directly from the menu.

Start And End Restrictions Monitor



9/INB & 10/INB

You use these options to start and stop the restrictions monitor. When you add and edit price types, you can add and edit the restrictions associated with them. For example you could add special prices and discounts as restrictions. You can apply restrictions when adding and editing price types, or as a background process later.

For more information see Sales Details within Customer Maintenance in Sales Order Processing.

You can start and end these monitors directly from the menu.

In each case, Inventory displays a window for confirmation.



There are no selection criteria, select
F8=Submit to start or end the monitor.

Start And End Stock Update Monitor



11/INB & 12/INB

You use these options to start and stop the stock update monitor. You can use this monitor to perform a stock update if your supplier is using third party software, that is, not System 21. The third party software populates a trigger file that is processed when you start this monitor, and regularly once it is activated.

Once the data has been accessed, System 21 uses simple validation criteria to check if the data is valid. If the data is valid then the Inventory Interface automatically creates the relevant stock movements to update the stock balance and the stock history files. Once this is complete, the original trigger file is deleted. If the data is not valid then the trigger file is updated to include the validation error conditions so that your supplier can report and resolve these errors.

You can start and end these monitors directly from the menu, or as part of the Inventory subsystem (INBACK3).

If you start these monitors from the menu then for each option, Inventory displays a window for confirmation.



There are no selection criteria, select
F8=Submit to start or end the monitor.

-
-
-
-
-

Chapter 12

Inventory Application Interface

Receive Product Activity Data



1/INAI



Select Product Activity Data (Receive).

Use this option to process inbound product activity data transactions, for example stock movements from a remote site, typically your customer's, via EDI.

INI350	Z1 - UK Demonstration Company	User GBJBANB4	9/04/98 13:49:03
Receive Product Activity Data			
Print Product Activity control list. . <u>1</u> (1=All activity,2=Exceptions only)			
F3=Exit F8=Submit			

Fields:

Print Product Activity Control List

Use this to determine the information you want to print.

Enter one of the following:

- 1 - To print all activity.
- 2 - To print exceptions.



Select **F8=Submit** to print the control list.

Product Activity Data



11/INAI

Use this option to recover inbound product activity data errors. Product activity provides information on customers' sales activity and inventory status.

Inbound Product Activity Data Error Screen



Select Product Activity Data (Maintenance).

Use this screen to select a customer for the data recovery.

INI353	Z1 - UK Demonstration Company	User GBJBANB4	9/04/98 13:49:49
Inbound Product Activity Data Error Recovery			
Customer.....?.. <u>GC01</u> <u>000</u> Unique... _____			
Mailbox ID..... _____			
Include..... <u>1</u> (1=Errors not updated, 2=All Errors)			
Maintain..... <u>1</u> (1=Headers, 2=Lines, 3=PO Numbers)			
F3=Exit F4=Prompt			

Fields:

Customer

You must enter the customer whose data you want to recover.



*Note: Select a customer and press **Enter** to display the Error Inbound Product Activity Header Selection Screen.*

Mailbox ID

You can also enter the mailbox ID. Each translator has a special identification address, called the mailbox ID. You can view this on the exception report.

Include

Use this to decide the level of information you want to display.

Enter one of the following:

1 - Errors not updated. To include information about product activity transmissions that have failed.

2 - All errors. To include information for failed transmissions and those that have already been maintained after failing validation.

Maintain

Enter one of the following:

1 - Headers. To display the Inbound Product Activity Header Maintenance - Error Recovery Screen.

2 - Lines. To display the Untitled Line Selection Window.

3 - Purchase Orders. To display the Inbound Product Activity PO Numbers Maintenance - Error Recovery Screen.



Press **Enter**. The screen displayed depends on what you enter on this screen.

Error Inbound Product Activity Header Selection Screen



To display this screen select a customer on the Inbound Product Activity Data Error Screen and press **Enter**.

Use this screen to select the required customer details. If more than one record has failed validation, then the screen displays a list of them for you to choose from.

INI353	Z1 - UK Demonstration Company	USER GBJBANB4	9/04/98
			13:51:18
Error Inbound Product Activity Header Selection			
Customer Seq	Unique	Mailbox	Customer Location
Customer Name			
GC01	000	NGH 3.1BB	1010101010
- GC01	000	NGH 3.1BB1	1010101010
			Bottom
1=Header 2=Line 3=PO Number			
F3=Exit F5=Refresh F12=Previous F13=Toggle Name			

Fields:

Untitled

Select. Enter one of the following:

- 1 - Headers. To display the Inbound Product Activity Header Maintenance - Error Recovery Screen.
- 2 - Lines. To display the Untitled Line Selection Window.
- 3 - Purchase Orders. To display the Inbound Product Activity PO Numbers Maintenance - Error Recovery Screen.:

Functions:

F13=Toggle Name

Use this function to toggle between displaying customer names and customer reference codes.



Press **Enter**, the screen that is displayed depends on what you enter on this screen.

Inbound Product Activity Header Maintenance - Error Recovery Screen



To display this screen enter 1 in the Untitled field on the Error Inbound Product Activity Header Selection Screen and press **Enter**.

Or: Enter 1 in the Maintain field on the Inbound Product Activity Data Error Screen and press **Enter**.

Use this screen to view and maintain details before you resubmit them to batch validation.

INI354	Z1 - UK Demonstration Company	User GBJBANB4	9/04/98 13:51:51
Inbound Product Activity Header Maintenance - Error Recovery			
Action. <u>1</u>		Reporting Date <u>24/09/97</u>	
Customer.?. <u>GC01</u> <u>000</u> Reeves Chemist's			
Unique..... <u>NGH 3.1BB</u>			
Mailbox.... 1010101010			
Location _____			
Number of Lines 00000			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F14=Line Sel F15=PO Numbers Sel			

Fields:

Location

Enter the location details for the customer.

Functions:

F14= Line Selection

Use this to display the Untitled Line Selection Window.

F15=Purchase Order Number Selection

Use this to display the Inbound Product Activity PO Numbers Maintenance - Error Recovery Screen.

Untitled Line Selection Window



To display this window enter 2 in the Untitled field on the Error Inbound Product Activity Header Selection Screen and press **Enter**.
Or: Enter 2 in the Maintain field on the Inbound Product Activity Data Error Screen and press **Enter**.
Or: Select **F14=Line Select** on the Inbound Product Activity Header Maintenance - Error Recovery Screen.

Use this screen to select the line number you wish to maintain.

INI353		Z1 - GB Demonstration Company		USER GBJBA1MS	24/06/98 09:41:36
Error Inbound Product Activity Header Selection					
Customer Seq	Unique	Mailbox	Customer Location		
Customer Name					
2 GC01	000		AD		
- GC01	000	Enter line number: _____			
- GC01	000	(blank = all lines)			
- GC01	000	F12=Previous			
					Bottom
1=Header 2=Line 3=PO Number					
F3=Exit F5=Refresh F12=Previous F13=Toggle Name					

Fields:

Enter Line Number

Enter the line number you want to maintain. Leave this field blank to display all lines that need maintenance.



Press **Enter** to display the Inbound Product Activity Line Selection - Error Recovery Screen.

Inbound Product Activity Line Selection - Error Recovery Screen



To display this screen leave the Enter Line Number field blank and press **Enter** on the Untitled Line Selection Window.

Use this screen to view and maintain all the lines for a record.

INI356	Z1 - GB Demonstration Company	USER GBJBA1MS	24/06/98
			09:42:13
Inbound Product Activity Line Selection - Error Recovery			
Customer.	GC01	000	Reeves Chemist's
Unique...	NER 001		Mailbox ID..
Line	Supplier Item	Bar Code	Customer Item
-	2 AI02		
-	3 P1		
		Qty	Quantity
		31	12.000
		31	12.000
			Bottom
1=Select Line Details 2=Select SDQ Details			
F3=Exit F12=Previous			

Fields:

Untitled

Enter one of the following:

- 1 - To Select Line Details. To display the Inbound Product Activity Line Detail Maintenance - Error Recovery Screen.
- 2 - To Select SDQ Details. To display the Inbound Product Activity SDQ Details Maintenance - Error Recovery Screen.



Tip: An asterisk indicates that you have already updated details for a line.



Select an option and press **Enter**, the screen that is displayed depends on what you enter on this screen.

Inbound Product Activity Line Detail Maintenance - Error Recovery Screen



To display this screen enter 1 in the Untitled field on the Inbound Product Activity Line Selection - Error Recovery Screen and press **Enter**.

Use this screen to maintain order line details for your selected customer before resubmission to the validation process.

INI356		Z1 - GB Demonstration Company		User GBJBA1MS		24/06/98 09:42:32	
Inbound Product Activity Line Detail Maintenance - Error Recovery							
Customer.... GC01 000 Reeves Chemist's							
Unique..... NER 001 Mailbox ID..							
Ord Line.... 00002 Customer Location.. 000							
Supplier's Item...?. <u>AI02</u>							
Barcode.....				Customer's Item.....			
Quantity Modifier. <u>-</u>				Movement Date..... <u>23/09/97</u>			
Process Control... <u>31</u>				Reason.....?			
Processing Prof.?. <u>-</u>				Type.....?			
Add Item Bal Ctl.. <u>1</u>				Source.....?			
Kit Control.....				From Stockroom.....? To			
Actual Quantity... <u>12.000</u> UOM <u>PK</u>				Reference Number.... <u>EDISAL3</u>			
Planned Quantity.. <u>.000</u> UOM <u>EA</u>				To/From Reference...			
Lot Number.....				Prod Line.....			
Narrative.....				Pack Type.....?			
Unit Cost..... <u>10.00000</u>				Expiration Date..... <u>0/00/00</u>			
Unit Price..... <u>150.00000</u>				Workstation ID..... <u>ST0451</u>			
Consign Ref.....				User ID..... <u>GBJBAPJC</u>			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F16=SDQ Details							

Functions:

F16=SDQ Details

Select this to display the Inbound Product Activity SDQ Details Maintenance - Error Recovery Screen.

Inbound Product Activity SDQ Details Maintenance - Error Recovery Screen



To display this screen Enter 2 in the Untitled field on the Inbound Product Activity Line Selection - Error Recovery Screen and press **Enter**.

Or: Select **F16= SDQ Details** on the Inbound Product Activity Line Detail Maintenance - Error Recovery Screen.

Use this screen to view the SDQ details for the record you have selected.

INI357	Z1 - GB Demonstration Company	USER GBJBA1MS	24/06/98 09:42:54
Inbound Product Activity SDQ Details Maintenance - Error Recovery			
Customer: GC01	000 Reeves Chemist's		
Unique: NER 001	Mailbox: 0000000001	Ord Line: 00002	
Location Detail: 8			
Line Quantity...	12.000	SDQ Total Qty...	
1 SDQ Location	SDQ Quantity	UOM	Deleted
1=Select 4=Delete			
F3=Exit F10=Add F12=Previous			

Fields:

Untitled

Enter one of the following:

1 - To select a line for amendment.

4 - To delete a line.

Functions:

F10=Add

Use this to add a line to the product activity data recovery.



Select **F8=Update** to return to the Inbound Product Activity Line Detail Maintenance - Error Recovery Screen.

Inbound Product Activity PO Numbers Maintenance - Error Recovery Screen



To display this screen enter 3 in the (untitled) field on the Error Inbound Product Activity Header Selection Screen.

Or: Enter 3 in the Maintain field on the Inbound Product Activity Data Error Screen

Or: Select **F15=Purchase Order numbers** on the Inbound Product Activity Header Maintenance - Error Recovery Screen.

Use this screen to select the purchase order number you wish to maintain for your selected customer.

```

INI358                Z1 - UK Demonstration Company          USER GBJBANB4      9/04/98
                                                                13:52:16
Inbound Product Activity PO Numbers Maintenance - Error Recovery

Customer: GC01      000    Reeves Chemist's
Unique:   NGH 3.1BB      Mailbox: 1010101010

   Customer      Starting      Ending
1  Location      Order Number  Order Number      Status
-  NEEDLES      POBBB0000000000002800  POBBB0000000000002899

                                                                Bottom

F3=Exit  F8=Update  F10=Add  F12=Previous

```

Fields:

1

Select. Enter 1 against a customer to select the purchase order.

Customer Location

This is the customer location code.

Starting/Ending Order Number

This is the range of purchase orders for your selected customer and customer location.

Status

This is the status of the selected customer purchase order range.

Functions:

F10=Add

Use this to add customer purchase order numbers to the product activity data recovery.



Glossary

Glossary

Access Point

This is normally used in Warehousing to define a point of reference in the dimension of a key element. For example there is an access point between aisles A and B.

Action List

A list of instructions to perform a number of warehouse moves including picks, putaways and transfers.

Allocated (Stock)

The quantity of a part which has been allocated to customer or works orders. It is usually expressed as a balance at part/stockroom level.

Alternative (Part)

A part which can be used as an alternative to another.

Area

The part of a warehouse, the definition of which corresponds to the Location code. The area has a two character code.

Area Dimension

A Location code is made up of four elements. Each element is called an area dimension. For example you could interpret the area A01C as located at aisle A, bay 01, Row C.

Area Rules

See **Rules**.

Available (Stock)

The quantity of a part which is available for issue. It is usually expressed as a balance at part/stockroom level.

Average Cost

The average cost of a part in a stockroom. This is recalculated every time a receipt is made.

Average Usage

The average usage per week/period of a part in a stockroom. The weeks or periods which are included in this calculation are defined by the usage profile.

Back Order

The quantity of a part which is required for customer orders which cannot currently be satisfied from stock. It is usually expressed as a balance at part/stockroom level.

Back To Back Order

This is a purchase order raised to meet the requirements of a sales order.

Balance

This may be used either to signify a database record holding summary information, such as a stockroom balance, or a single summary quantity field on such a record, such as allocated stock.

Batch Control

This is a level of stock control at a more detailed level than part/stockroom. See also lot control.

Batch/Lot Traceability

Where stock control is specified at batch or lot level, this refers to the ability to trace the movement of stock at this detailed level.

Carton

An item code which describes a collection of piece items. The stock can be moved (in other words, purchased, stocked, issued) as a carton or as individual pieces.

Catchweight

For most businesses, an item is bought, stocked, ordered, discounted, picked, priced and sold by the quantity of the item. This is known as the primary unit of

measure and is available to all companies. However, some businesses price and sell by another unit of measure for example, a weight. This is known as the secondary unit of measure. A company which uses catchweight can use both primary and secondary units of measure.

Check Digits

Check digits or return codes can be used within the application to make sure that warehouse staff have visited the defined location. Check Digits consist of a pair of characters, displayed on the location, which must be entered to confirm an action. Check Digits are user defined.

Committing

The Sales Order Processing, Invoicing and Production Control applications allocate stock against the four wall inventory for the warehouse. When the picking decisions have been made, the inventory at a location is then committed.

Cost

A value associated with a part in a stockroom, or a movement. It is usually a value related to a single part (a unit cost), but may refer to a quantity of parts (a movement cost or value).

Costing Method

This refers to the method used to establish a cost for movements or stock balances. The methods available are latest, average, standard and FIFO.

Count Error

This is an error condition when one or more of the items associated with a count are found to be in error. In other words, there is a discrepancy between the recorded computer stock figure and the actual physical stock figure as specified by the allowed tolerances for the stockroom.

Count Objective

Associated with stockrooms defined for counting by class/date control. A count objective is specified for each class A, B and C and defines the number of times per working year that each item (defined to the appropriate class) should be counted.

Count Reconciliation

This is the comparison of counted stock quantities in order to assess a stock error or discrepancy, as defined by the tolerance criteria specified for a stockroom.

Cycle Counting

This is the term given to the methodology associated with performing physical stock checks on an automated time based, or cyclic process defined by the class of each item and the number of times each class should be counted per working year.

Descriptions File

This is a file maintained within Inventory Management which defines a number of parameter codes and their descriptions.

Detail Recommendation

A manual request to count a specific lot, batch or serial number. Detail recommendations are entered via count recommendations maintenance after the count has been generated and may be a modified summary recommendation or may be a request to count an item or location that was not originally requested on the count.

Depot

A depot is a stockroom which has been set up in Inventory Management and authorised for making despatches for sales orders.

Economic Order Quantity

This is an optimum quantity of a part to be ordered on a single occasion. Its calculation is based on the usage of the part, the cost of order placement and the cost of carrying the part in stock.

Expected (Stock)

The quantity of a part which is expected will be available for issues on a given date. This is usually expressed as a quantity for a part/stockroom.

Fast Batch

This is the name given to the data entry style of confirmation of despatch. Data is entered in a batch and submitted to a batch queue for subsequent processing. This is to limit operator screen time.

FIFO

This is an acronym for First In First Out - one of the costing methods available in the Inventory Management application. By this method, each stock receipt is valued at actual cost, and issues are valued using these receipt batch costs on a First In First Out basis.

First Available Date

The system calculates the first available date as being the lot production date plus the first release lead time. The first release lead time is the time the lot is held in Inventory before being released. This may be used for produce which is kept for maturing - for example, wines and spirits, cheese, and so on.

First Available Time

If the production date is equal to the first available date then this time must be equal to or greater than the production time. The time is only displayed if the Display Time field on the lot header parameters file is set to 1.

Frozen (Stock)

The quantity of a part which is not available for issue (and not allocated). It is usually expressed as a balance quantity at part/stockroom level.

In Transit

The quantity of a part which is currently in transit between two stockrooms. It is usually expressed as a balance quantity at the target part/stockroom.

Item Characteristics

The attributes relating to an item (for example, shape grade, length, section and so on).

Item Class, Item Group, Item Type

These are the main analysis categories in which you can group items together. Selection and sequencing on many reports is provided by these categories.

Item Stockroom

This is the main level at which costs and balances are held within the application. The item stockroom record also defines stock management rules for an item within a particular stockroom.

Latest Cost

The last cost at which a part was received into a **stockroom**. One of the costs maintained at **part/stockroom** level.

Last Available Date

The system calculates the last available date as being the expiry date minus the customer shelf life. All lots with a last available date less than the current date will be frozen if there is no stock status code entered.

Last Available Time

Enter the latest time that this lot will be available on the last available date. If the last available date equals the expiry date then the last available time must be equal to or less than the expiry time.

Lead Time

The standard amount of time, in weeks, from a decision to order a part for a stockroom, to the part being received in the stockroom.

LIFO Revaluation

The revaluing of stock on a Last In First Out Basis. When stock levels are falling, LIFO revaluation consumes the most recent stock first leaving the remaining balance to be valued at the earlier year's cost. When stock levels are rising, only the net gain in stock is valued at the current cost, the remaining balance is valued at the previous year's values.

Lot Control

This refers to a level of stock control lower than part/stockroom. May also be known as batch control.

Lot Error

Special lot reference generated for an Inventory stock count, when a summary request for a lot, batch, or serial controlled item is printed and no lot balances exist for the item.

Maximum Stock

The maximum quantity of a part in a stockroom preferred by the user. This may be set manually, or automatically calculated by the system.

Movement Type

This refers to the classification of movements by type of transaction, in other words, miscellaneous receipts, customer order issues.

On Order

The quantity of a part for which outstanding purchase or work orders exist. It is usually expressed as a balance quantity at part/stockroom level.

Order Placement Cost

The cost in base currency of placing and processing a purchase order. This is used in the calculation of economic order quantity.

Overdue Days

This represents the number of days at which counts become overdue for printing, based on the date of count recommendation as entered at count request time.

Physical (Stock)

The total quantity of a part in a stockroom. It is usually expressed as a balance quantity at part/stockroom level.

Pick List

This contains a number of lists, one per order/schedule. Within all the lists are all the warehouse controlled components required, their quantities, locations within the warehouse and if appropriate the lot details.

Planned Request

Items that are targeted for count in summary form (in other words, count all item balances), via the initial count creation, are considered planned requests. Item summary and/or detail requests that are entered via count.

Potency

The potent value of the entire lot is displayed irrespective of which stockroom it is held in.

Reason Code

This is entered whenever the stock status of a lot is changed. valid codes are held on the descriptions file against major type SSRC.

Reorder Point

The quantity of a part in a stockroom which, when reached, should trigger a reorder action. This may be set manually or calculated by the application.

Reorder Policy

The policy adopted to control the reorder of parts - may be either ROP/MAX, ROP/ROQ, or Up to ROP.

Reorder Quantity

The quantity of a part recommended for reorder when reorder point is reached for the part in a stockroom.

Reorder Quantity Factor %

The number of lead times worth of average usage to be reordered, expressed as a percentage.

Rotation Date

The date the stock should be rotated. Stock may be rotated using the expiry date, the date of receipt to the warehouse or to the location.

Serial Number Control

A form of **batch** or **lot control**, but exercised at a single, unique element level.

Standard Cost

This unit **cost** of a part in a stockroom, specified as a standard by the user for a defined period. Standard costing is one of the available costing methods within the application.

Stock Carrying Rate %

The percentage cost of carrying a stock part for a year. This rate is used in Economic Order Quantity calculations.

Stock Count

A periodic verification of the accuracy of computer-held stock figures by a physical count of stock.

Stock History

A summarised view of stock movements per week or period.

Stock Management/Stock Movement

A movement of a quantity of an item into or out of a stockroom. This refers more particularly to the recording of such a movement in the application, and the transaction record created as a result.

Stockroom

A discrete area of a company where stock is recorded and controlled separately from other company stocks.

Stockroom Balance

See balance and part/stockroom.

Summary Recommendation

A request to count an item or location in its entirety (in other words, all lots, balances or serial numbers for a lot controlled item in an inventory stockroom, or all low level warehouse balances for an item or location as defined within a warehouse). All item or location recommendations that are targeted via the initial count creation are summary recommendations by default.

Suppliers Lot Reference

This is the specific lot reference allocated by the supplier.

Time Fence

You can define a time fence to control the date on which stock processing happens, for example stock allocation and printing acknowledgements. To do this, you specify the number of days that you want the system to add to the

current date to calculate a date in the future that the system will use control stock processing.

Tolerance

Tolerances are defined against the stockroom and define the upper and lower variances (by quantity percentage and value), that will be allowed for stock discrepancies for items counted within the stockroom. Percentage variances for a balance are defined as follows:

Value variances are defined by valuing the quantity variance according to the unit cost of the associated item:

$(\text{Counted Quantity} - \text{Computer Quantity}) \times \text{Cost}$.

Cost=costing method applied to the item.

Discrepancies for FIFO costed items are valued at latest cost.

Transaction Type

Identifies whether the document is either an invoice or a credit note.

Type (Stock Availability Enquiry)

Type of Order for example, purchase order or sales order.

Unit Of Measure (UOM)

The unit in which a quantity or unit cost is expressed.

Usage

The quantity of an item issued from a stockroom in a given period.

Usage Profile

A user defined profile which specifies the pattern of periods to be included in the calculation of average usage.

Variance

The calculated quantity % or value discrepancy between the counted stock balances and the associated computer stock balance for an item. Variances outside the defined tolerances for a stockroom are considered to be a count error for the item.

VAT Code

Refers to the VAT rate that should be used to calculate the VAT charge for a specific order.

Warehouse

This is a stockroom that has been set up and authorised for location recording in the Warehousing applications. It may also be authorised as a depot (see Depot).