

-
-
-
-
-

Chapter 1

Inventory Maintenance



Inventory Maintenance Introduction

You use the maintenance functions to create and amend master files, and parameters, that are fundamental to the application's operation.



Note: Use file maintenance, particularly description file maintenance, with extreme care since errors have far reaching effects. Introduce a proper procedure of authorisation and post maintenance checking .

The master file enquiries are output only versions of the maintenance transactions and are not separately described.

Descriptions Maintenance



1/INM

The Descriptions file is used by Inventory Management, and many other Customer Services & Logistics applications, to determine parameter values for the application.

The system uses parameter files for a number of reasons, for example, at data entry time instead of long repetitive data.

Once set up and checked, parameter files help to ensure that data input is both accurate and acceptable to the system.

An example of the use of the description file is for the usage cycle. When you set up an Inventory company profile you must set up a usage cycle code; this field establishes whether the stock history records should be summarised at a weekly or monthly level.

Use this function to enter and use parameters, codes that relate to a single function are grouped together. The identifier for a group of codes is called the major type. The members of any group are the descriptions codes.

Descriptions File Maintenance Selection Screen



Select Descriptions.

Use this screen to add or maintain definitions of Major Types.

IN037	NR - Neil Radford and Co. Ltd	USER GBJBA1MS	6/13/96 10:13:44
Descriptions File Maintenance			
Description type..... TYPE			
Major type.....			
Description code.....			
Desc'n I.D.	Description	Limit	
ACDF	AC Terminology Definitions	30	
ADFM	Address format	30	
AEDI	Automatic Update from EDI	30	
ALTT	Alternative Item Type	30	
AN	Agencies	30	
ARPM	Arrears Processing Method	30	
ASAD	AS Address Type Codes	30	
ASTA	Article Status Code	30	
AUMD	Authorisation Method	30	
BCFM	Bank Code Format	30	+
F3=Exit F15=Description code details			
06-30 SF MW KS IM II KENB20A PET178S2			

Fields:

Major Type

Enter a major type to add or maintain.

Description Code

Enter a description code to add or maintain.



Tip: Use the page up/down keys to display subsequent screens when appropriate.



To display details about a specific Major Type enter the Major Type and press **Enter**.

Descriptions File Major Type Codes

ADFM

Address Format. You can create address formats using up to two characters for use in World Trade.

ALTT

(AOE) You can create single character item reference types.

AN

Five character maximum length. Agent, sub-agent. Sales order processing agents and sub agents.

BCFM

Bank Code Format. You can create bank code formats using up to two characters for World Trade use.

CALT

Calendar. You can create calendar codes using up to three characters for World Trade use. As a minimum codes must exist for the following:

001 - Intrastat.

002 - ESL.

CARR

Carriers. Sales and purchase order carrier codes.

CCCC

Customer Class. Required. A two character (maximum) field displayed on the Customer Sales Details screen within Customer Maintenance. Normally selected as one of the six customer attributes in defining the sales analysis database.

CCRQ

Certificate of Conformance required. If you have installed AOE and are using Certificate of Conformance, this is a required single character field on the Item Maintenance screen.

Select one of the following:

0 - Certificate cannot be entered.

1 - Certificate may be entered.

2 - Certificate must be issued.

CDSC

Cash Settlement Discount. Required two character field that identifies the cash settlement discount given to a customer. Code is a required field on the Customer Sales Details screen. At order entry, the code will default to the order header, but can be overridden. The percentage rate assigned to the code will be included with the invoice details when posting to Accounts Receivable.

CHST

Character Set. Create two character character sets for World Trade use.

CRDC

0 - Existing credit checking only in Sales Order Processing and Advanced Order Entry.

1 - Allows you to choose additional SOP and AO credit checking methods by a credit check value and credit check by days or both. See CRLV and CRLD.

CRLV

Credit Check by Value.

Select one of the following:

0 - Your customers will not be credit checked on a value entered in the customer master file.

1 - You can perform a credit limit value check . You can then enter a value against the Credit Limit field in Customer Maintenance.

CRLD

Credit Check by Days.

Select one of the following:

0 - You will not perform credit checking by number of days for your customers.

1 - Debtor Days. The total debtor days does not exceed the credit limit days set up for the customer.

2 - Days Sales Outstanding. The total days outstanding does not exceed the credit limit days set up for the customer.

3 - Average Days to Pay. The average days to pay does not exceed the credit limit days set up for the customer.

4 - Average Days Slow. The average days slow does not exceed the credit limit days set up for the customer.

5 - Overdue Days. The number of days overdue of the oldest outstanding invoice does not exceed the credit limit days set up for the customer.



Note: This policy can only be applied to level 1 and level 3 accounts in customer hierarchies.



Note: CRLD options 1, 3 and 4 are calculated by the A/R debtor ratio routines. See more information in Trend Parameters in Accounts Receivable product information.

CRV4

For the current system date to display, you should set up CRV4 with a Description Code of 01, and Description CR Conditioning.

DEPT

Departments. In Production, if MRP is to balance item supply and demand by stockroom rather than organisational model, then you must provide a range of Production cell codes. Codes are linked to individual stockrooms via the Inventory

Management, maintain company, stockroom code facility and defined against the major type DEPT.

The Equivalent codes must exist on the Production Parameters file.

DFLT

Advanced Order Entry (AOE) defaults. The only code in this major type is QTNO. You can hold the default Quotation Type code as the first character of the description of this code. This puts AOE into default quotation mode. If blank, AOE defaults to order mode.

DIRE

Direction to Move in Warehousing. Two one character codes 1 (ascending) and 2 (descending) on the Maintain Location Rules - Item screen within the Warehousing module if you are using Item Location Rules.

DIVN

Inventory Production Division.

Optional, two character field on the Item Maintenance screen. Normally selected as one of the six item attributes in defining the sales analysis database.

DMND

(AOE) Demand reference codes. You must set up single character Demand Reference codes against this major type as follows:

- 1 - Sales order.
- 2 - Purchase order.

DN

Customer Division.

Optional, two character field on the Customer Sales Details screen within customer Maintenance. Normally selected as one of the six customer attributes in defining the sales analysis database.

DNTF

Picking Note Print Time Fence.

Provides default Lead Time field value on the Request Picking Notes screen within Sales Order Processing module. The code T must exist; enter the number of days in the Rate field of description file.

DOCT

Print Function in Order Entry.

Used for Forms Lengths Overrides for despatch notes and picking notes, to override the default settings for the printing areas (10 characters maximum).

EDI

EDI Application Interface.

ADEPOT - This is the default stockroom used in the batch allocation run.

ALLOCATE - Select 1 to run batch allocation from Receive Inbound prompt, after receive order processing has completed.

CATLREPT - Used in the Print Electronic Catalogues prompt. Select 0 for the report to include Sent records. Select 1 for the report to include all records.

PRICETPCNT, PRICETVALU - Pricing Tolerance percentage and values allow comparison of prices sent through EDI and in System 21 database.

QUANTTPCNT, QUANTTVALU - When quantity changes occur through a purchase order, these tolerance limits define the extent of the change. If outside these limits, it will not accept the change and will print an error message.

TRANSLPAD - You decide whether the display for lead time offset is in calendar days or weekdays.

EGLR

Extended General Ledger codes for Purchase Management. When you enter Inventory items on purchase orders this retrieves extension codes to the GL account codes. Set up the subcodes:

01 - AFI rule for stock extended GL codes.

02 - AFI rule for price variance extended GL codes.

GDAR

Packaging Reporting - Adjustment Reasons.

GDRC

Packaging Reporting - Responsibility codes:

01 - Extractor.

02 - Manufacturer.

03 - Filler.

04 - Retailer.

GDRF

Packaging Reporting - Report format. Should include:

GER - German Duales Format.

Positions 6 and 7 of the parameter limit for the above descriptions have special uses:

- Position 6 set to 1 would cause a yearly report to be printed - which should only be used for the German format.
- Position 7 set to 1 sets track responsibilities to No. In this case you can enter responsibilities after the no tracking message, but the overrides would not be effective unless you set this parameter back to 0.

GDSC

Packaging Reporting - Sales Channels. The following are required and should not be changed:

00 - No Sales Channel.

01 - Division.

02 - Sub-division.

03 - Region.

- 04 - State.
- 05 - Territory.
- 06 - Salesman.
- 07 - Customer Class.
- 08 - Corporation.
- 09 - Branch.

INSC

Inventory source.

Required, one-character field on the Item Maintenance screen - if Configurator is in use see IN V3 product guide.

LGCD

Language Format. You can set up two-character language codes for World Trade use.

LPRT

Print Code. You use the values entered against Major Type LPRT(in World Trade) to validate the entries in the Intrastat/ESL print code in country maintenance. The value is concatenated with WT805PT to give the printer file used for Intrastat printing. Ensure you set up a printer description for each version of the printer file in OSLWTD3.

The following codes should already exist on the descriptions file. You may need to add extra Minor Types.

- FR - French.
- DE - German.
- BE - Belgian.
- DK - Danish.
- NL - Dutch.
- IT - Italian.
- SP - Spanish.
- SE - Swedish.
- GB - British.

MISC

Miscellaneous Company Level Descriptions.

(AS) CNFQ - Confirm Despatch Quantity Default. Set the limit to one of the following:

- 1 - To default to the required quantity.
- 2 - To default to the available quantity.
- 3 - To default to zero quantity, or any other value.

(AO and OE) DSTL - Despatch over tolerance is held as the rate against this description code.

(IN) IDMP - Add the Item Deletion Movement Period Ago for the Item/Stockroom Deletion routines. The Rate field should state the number of periods back from the current period, during which time item/stockroom deletion is not allowed if any stock movements exist. If IDMP is not defined, all items flagged for deletion are deleted during the Item Deletion Routine.

(AS) PRCD - Set the first character of the description to one of the following:

0 - To select the invoice price from the contract.

1 - To select the invoice price from the standard price list.

MODE

Despatch method. Create a single character code. You must configure Sales and purchase order despatch methods.

You must define the following modes of transport for World Trade:

1 - Sea.

2 - Rail.

3 - Road.

4 - Air.

5 - Post.

7 - Fixed installations.

9 - Own propulsion.



Note: Care should be taken that other Minor Types are not reported on an Intrastat.

MOVR

Movement Reason Codes.

Optional two character field on most stock movement transactions within Inventory Management to track why a transaction is being processed. This is mandatory for stock count reconciliation where adjustments are generated.

Within Production, the following activities prompt for reason codes: scrap, hold, hold WIP, release held WIP, scrap held WIP, transfer WIP, allocate WIP, de-allocate WIP, adjust WIP, unexpected (unplanned) output and work station status.

You require codes when booking scrap and held quantity during item, order and operator booking. You can allocate the total quantity to more than one code during a session.

A default scrap order may be entered on the Production system, organisational model definition.

MVTP

Movement types.

Single character codes must exist because all Inventory transactions will be created with one of the following codes and descriptions for movement types:

A - Stock Adjustment.

C - Customer Order Issue.

D - Direct Delivery.
 F - Frozen Adjustment.
 I - Transfer In.
 J - Transformation.
 K - Frozen Issue.
 L - Allocated Adjustment.
 M - Manufacturing Issue.
 N - Manufacturing Receipt.
 O - Transfer Out.
 P - Purchase Receipt.
 Q - Back to Back.
 R - Misc. Receipt.
 S - Misc. Issue.
 T - In-Transit Adjustment.
 U - Purchase Order.
 W - Manufacturing Adjustment.
 0 - No movement to be generated.
 1 - Single Shot Transfer.
 2 - Multi Shot Transfer.

For movement types used in Inventory Management, the limit field can be set to control whether movement reference, reason code and movement reference codes are mandatory.

The limit field can be set as follows:

Limit Field	Reference Mandatory	Reason Code Mandatory	Reference Type Mandatory
00	No	No	No
01	Yes	No	No
10	No	Yes	No
11	Yes	Yes	No
20	No	No	Yes
21	Yes	No	Yes
30	No	Yes	Yes
31	Yes	Yes	Yes

NOTN

Nature Of Transaction. The following two-character codes, should be set up for Intrastat reporting in World Trade:

- 10 - Standard transaction.
- 16 - Credit.
- 17 - Credit, no goods movement.
- 20 - Replacement.
- 30 - No consideration.
- 40 - Movement before process/repair.
- 50 - Movement after process/repair.
- 58 - Process element.
- 60 - No change of ownership.
- 70 - Joint defence or government.
- 80 - General construction.
- 90 - Other.

You should set up additional codes for Intrastat and ESL reporting as follows:

- France, Germany, Spain or Denmark - Codes 11, 21, 31, 41, 42, 51, 52 and code 61.
- France, Germany or Spain - Codes 12-15, 22, 23, 32, 33, 43, 53, and code 62.
- France or Denmark - Codes 70 and 80.
- France - Code 90.
- Germany - 71, 72, 81, and 91.
- Spain - Codes 7-9 and code 34
- Italy, Belgium, Holland & Sweden - Codes 1-9.

ORDM

Ordering methods.

For AOE with or without Configurator. You must use the following codes, specified on the Item Master. These may be over-ridden during AOE:

- 0 - Normal Stocked item.
- 1 - Make to Order.
- 2 - Purchase to Order.
- 3 - Deliver Direct.
- 4 - Reserve.
- 5 - Configure to Order.

ORTP

Order type.

If Warehousing module is installed, the following codes are required:

1 - Sales Order.

2 - Production Order.

PCLS

Item Class. Optional two-character field on the Item Master maintenance screen to classify Inventory items. Stocktake count sheets may be requested by a range of item classes. In addition, this field is normally selected as one of six item attributes in defining the sales analysis database.

PGMJ

Item Group Major. Optional three-character field on the Item Master Maintenance screen to classify Inventory items. Stocktake count sheets and various reports may be requested by a combination of major and minor group codes. In addition, this field is normally selected as one of the six item attributes in defining the sales analysis database.

PGMN

Item Group Minor. Optional three-character field on the Item Master Maintenance screen to classify Inventory items. Stocktake count sheets and various reports may be requested by a combination of major and minor group codes. In addition, this field is normally selected as one of the six item attributes in defining the sales analysis database.



Note: It is important to configure the codes appropriately for use within Production. These codes are used to group similar items into product families for use by MPS and MRP forecasting. Similarly in Forecasting and for DRP.

PGR

Discount group. Three characters maximum. Used to group items which earn the same discounts on a discount list when standard pricing is in use.

PLDL

Place Of Delivery. You can set up five-character place of delivery codes for use in World Trade.

PORT

Ports. You can set up five-character port codes for World Trade use.

PREM

(EDI) Premenos User File Definitions.

You can enter a list of document IDs and related text descriptions. This relates to the Document ID field in the Maintain Document IDs screen.

P RTP

Pricing Functions. These price function codes are used in combination with pricing type codes in Advanced Pricing to set up pricing type profiles.

1 - Discount.

2 - Price.

5 - Whole Order discount.

6 - Retrospective discount.

7 - Special allowance discount.

PTYP

Item type. Optional one-character field on the Item Master Maintenance screen to classify Inventory items. You can request Stocktake count sheets by a range of item types. In addition, this field is normally selected as one of the six item attributes in defining the sales analysis database.

You would normally define four codes which are used by Service Management to determine contract charging. These, typically, are:

- Major Spares.
- Minor Spares.
- Consumables.
- Supply Items.

See System Parameters Maintenance Screen 3 in Service Management for details on how to use these codes.

QTNO

(AOE) Quotation type codes. Set up single-character quotation type to identify the type of quote (such as 30 days, 60 days, etc) being entered. The code is used to identify an order as a quotation in AOE. The rate is a value, added to current date, to calculate expiry date for quotations. If 1 or 2 is in the VAT field, order lines will be allocated.

REOP

Inventory Re-order Policies.

Enter one of the following five codes on the Item/Stockroom maintenance screen if the user is going to utilise the re-order point feature within Inventory Management.

1 - Up to MAX.

2 - ROQ.

3 - Up to MIN.

4 - Up to ROP.

5 - EOQ.

RFCR

Invoice/Credit Note Reason Codes. The code identifies why the invoice or credit note is being raised and is found on the Misc. Invoice or Credit Note header screen.

Set the limit field within the code to 0 if the invoice/credit note will update Sales Analysis with quantity, sales value and cost. Set the limit field to 1 if the invoice/credit note will not update Sales Analysis with sales value and cost only.



***Warning: Reason code 0 must exist
otherwise the Invoice Print Program will not
work.***

RGME

Regime. Assign Regimes (World Trade) to Movement Transport Information and included on Intrastat and ESL reporting. Set up codes for French and Italian reporting:

- France - Codes 11, 19, 21, 22, 25, 26, 27 and 29.
- Italy - Codes 1-6.

RGNO

You can set up three-character regions of origin for World Trade use. Regions are assigned to EC Movements and included on Intrastat and ESL reporting.

Examples: CA Catalonia, NE Northern England, NI Northern Italy.

SCRC

Scrap/Reject Reason Codes. Required two-character field on the Returns/Scrap/adjustment enquiry screen within Customer Returns that identifies why returned product is being scrapped.

Enter 1 in the VAT field against a reason code to not generate a credit for the goods scrapped/rejected.

SDIV

Item Sub division. Optional two-character field on the Item Maintenance screen. Normally selected as one of the six item attributes in defining the sales analysis database.

SHLU

Shelf life units. This is mandatory if extended Lot, Batch or Serial control is being used and is found on the Item/Stockroom maintenance screen. You can select one of the following codes to identify how to measure shelf life:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.
- 5 - Indefinite.

SN

Customer Region.

Optional two-character field on the Customer Sales Details screen within customer Maintenance. Normally selected as one of the six customer attributes in defining the sales analysis database.

SPXV

Spex version. Which version of SPEX is installed.

- 00 - Default SPEX Version.
- 01 - SPEX/400 EU version.
- 02 - SPEX for Windows installed.

SRCE

(AOE) Source/supply types. Set up single-character supply type codes against this major type must exist as follows:

- 1 - Batch.
- 2 - Sales order.
- 3 - Purchase order.
- 4 - Requisitions.

ST

Customer State. Required two-character field on the customer Sales Details screen within customer maintenance. Normally selected as one of the six customer attributes in defining the sales analysis database.

STKF

Non-Stock Item Type. If AOE is installed, this is a required one-character field on the Item Master maintenance screen that identifies the type of non-stock item.

STKS

(IN) Stock status codes for items with lot, batch or serial control with shelf life.

Two character codes, used when stock is frozen or unfrozen from the Lot Maintenance options, or by the Stock Status Monitor.

The Limit must be set to 1 for codes which will freeze stock, and blank or zero for codes which will unfreeze stock.

FZ - Frozen.

F2 - Frozen.

RL - Released.

UN - Unfrozen.

STKU

Stockroom Usage Code. Optional two-character field on the Stockroom maintenance screen within the Inventory Management company profile (memorandum field only).

STRM

Inventory Storage Method. Optional one-character field on the Item Master Maintenance screen (memorandum field only).

SUNC

Miscellaneous Order Charge Codes. Optional two-digit field identifying a miscellaneous charge that can be added to the Order Trailer screen during order entry, order amend or confirmation of despatch. The charge code can only be defined as a value in base currency with mandatory domestic rate VAT code (or tax code in US.) Currency conversion to prime values and change of VAT code occur automatically when codes are applied to prime currency orders.

SUSP

Order Suspend Codes. two-character field on the order header that identifies why an order is suspended together with the use of the VAT field to prevent auto de-allocation. System 21 requires the definition of at least eleven codes. For example:

CS - Customer on credit stop.

CL - Credit limit exceeded.

FP - Fixed price item.

NP - Item not priced.

Additional codes may be defined if required, however they will be manually entered against an order.

The VAT field on a code can be set to 1. This will cause a fixed price line in Advanced Order Entry to be suspended, but stock will be allocated to it. (Conversational Order Entry remains unchanged, that is with no allocation.)

While the order remains suspended:

- No picking note can be raised for it.
- You cannot adjust the allocation using Manual Allocation.
- You cannot adjust the allocation using Manual Allocation By Item.
- You can use Advanced Order Entry, Order Amendment to de-allocate or force allocate.

If the VAT field is set to 2, order lines in Advanced Order Entry can be created with back to back requisitions or reserved against purchase orders.

If the Rate field on a code is set to 1, the code will not be used to suspend orders, for example, FP could be set so that fixed price orders are not suspended.

SV

Customer Sub-Division.

Optional two character field on the Customer Sales Details screen within Customer Maintenance. Normally selected as one of the six customer attributes in defining the Sales Analysis Database.

TAR

Tariff. Any required eight-digit commodity codes should be set up for use in World Trade.

TDEL

Terms Of Delivery. Set up three character terms of delivery for World Trade as follows:

EXW - Ex Works.

FOB - Free on Board.

CIF - Carriage, Insurance & Freight.

DDU - Delivered Duty Unpaid.

DDP - Delivered Duty Paid.

XXX - Other.

TMTH

Transport method.

TN

Salesman. Required five-character field on the customer Sales Details screen with Customer Maintenance. Normally selected as one of the six customer attributes in defining the Sales Analysis database.

TPAR

TP Adjustment Reasons - required if carrier rating is being used and there is a variance when authorising carrier payments.

01 - Mistake in Manual Rating.

02 - Old Rate Codes Used.

03 - One-off Deal.

TBBL

TP Bill of Lading format - four codes must exist if bills of lading are required when maintaining transport routes in TP. The codes are:

01 - One document per load.

02 - Document per drop/delivery point.

03 - One document with drop details.

04 - One document details by area.

TPCC

TP Commodity code - eight characters maximum. Optionally used in TP when defining a transport centre.

TPCT

TP Carrier Type - four characters maximum. User defined codes optionally used in TP to categorise carriers.

TPCY

TP County - four characters maximum. User defined codes required when setting up Nodes in TP.

TPDC

TP default capacity type. Three codes must exist.

1 - Weight.

2 - Volume.

3 - Containers.

TPIC

TP Creation of requirements. The following codes must exist:

1 - Order creation.

2 - Allocation.

3 - Pick note creation.

6 - Confirmation of Despatch.

Codes 4 and 5 may exist, but are not currently used.

TPLS

TP Load status. The following codes must exist:

10 - Pending.

20 - A'printing.

60 - A'rating.

70 - A'COD.

80 - A'auth.pay.

90 - A'ledg.post.

95 - A'hist.

99 - Cancelled.

Codes 30, 40 and 50 may exist but are not currently used.

TPPM

TP Payment Method - two characters maximum. User defined codes must exist if carrier rating and therefore payment is being used.

TPRM

TP Rating Method - four codes should exist to be used if TP rating of loads is to be used.

01 - Load and rate table.

02 - Drop and rate table.

03 - Area.

04 - Area and rate table.

TPSE

TP Serious Errors - the following codes must exist:

01 - Sales order not found.

02 - Pick note header not found.

03 - Item record not found.

04 - Stockroom balance not found.

05 - Route specified not found.

06 - Time out for updates.

07 - Details changed after AFI post.

08 - Details changed after override.

09 - Global route change warning

10 - Possible capacity problems.

11 - Item transport prof. not found.

TR

Customer Territory. Required, two-character field on the Customer Sales Details screen within Customer Maintenance. Normally selected as one of the six customer attributes in defining the Sales Analysis database.

TRAN

Movement Reference Type. Optional, two-character field on all Inventory transactions screens within Inventory Management. Identify what type of source document is being used.

Production routines that involve Inventory movements prompt for transaction type codes.

TTYP

Text Type. This will determine the type of text entered and where on the documentation text will appear. Set up the following codes:

B - Batch reference text.

C - Customer text.

D - Certificate of Conformance text type.

I - Invoice Header text.

K - Carrier.

L - Order Line text.

O - Order Header text.

P - Item text.

T - Transport Load.

UNIT

Unit of Measure. Required, two-character field on the Item Master screen. Unit of measure could be a purchasing UoM, stocking UoM or issuing UoM.

UOM

Units of measure codes for Catchweight - two character codes. Unit of Measure could be a purchasing, stocking or issuing UoM.

All secondary units of measure must be defined in both the major types UNIT and UOM.

USCY

Usage Cycle. Required, one-character field on the Inventory Management Company Profile Maintenance screen. Two codes must exist:

M - Average per Month.

W - Average per Week.

USGC

Text Usage codes. Determines where the text will appear within documentation. The codes required include:

B - Batch Reference text.

C - Certificate of Conformance text.

E - External text.

I - Internal text.

P - Planner.

VAT

VAT codes. Configure this if the company is not linked to the General Ledger, it is redundant if the General Ledger is linked.

Set up any new VAT codes created in the General Ledger For World Trade against Major Type VAT.

WAIT

TP wait type for temporary record locking, two six character codes must exist:

BATCH - Batch lock request. The limit should be set to five attempts to access a locked record, and the rate should be set to 20 seconds to wait.

INTER - Interactive lock request. The limit should be set to five attempts to access a locked record, and the rate should be set to two seconds to wait.

WHCS

Warehousing Commit List Sequence. If Warehousing module is installed, define the following codes must exist:

- 1 - Order Sequence.
- 2 - Customer Sequence.
- 3 - Journey Sequence.
- 4 - Despatch Sequence.
- 6 - Consignment Sequence.

WHIS

Warehousing Item Sequence.

If Warehousing is installed, the following codes must exist:

- 1 - Item Sequence.
- 2 - Alternative Location.
- 3 - Location Sequence.

WHLS

Warehouse/List type. If Warehousing module is installed the following codes must exist:

- 01 - Put Away List.
- 02 - Pick List.
- 03 - Move List.
- 04 - Count List.

WHML

Move List by Sequence.

If Warehousing module is installed the following codes must exist:

- 1 - Warehouse.
- 2 - Area.
- 3 - Access Point for Dimension 1.

WHMS

Move List Sequence. If Warehousing module is installed the following codes must exist:

- 1 - Item.
- 2 - Arrival Time.

WHMT

Warehousing Movement Type. If Warehousing module is installed the following codes must exist:

- 1 - Putaway.
- 2 - Pick.
- 3 - Sundry Movement Planned.
- 4 - Sundry Movement Not Planned.
- 5 - Commitment Amendment.
- 6 - Count Reconciliation.
- 7 - Sundry Frozen Movement.

WHMV

Warehouse Movement Trans. If Warehousing module is installed the following codes must exist:

- AF - Frozen Stock Adjustment.
- AP - Physical Stock Adjustment.
- CI - Customer Order Issue.
- PR - Purchase Receipt.
- SI - Sundry Issue.
- SR - Sundry Receipt.
- IT - Transfer In.
- T0 - Transfer Out.
- 001 - Internal Warehouse Movement.

WHNL

No Of Locations To Be Created. A code of MAX with a value in the limit field must exist. The entered value will default to the maximum Number Of Locations To Be Created field within Maintain Warehouse Map when creating new location codes.

WHPS

Warehousing Pick List Sequence. If Warehousing module is installed the following code must exist:

- 1 - Warehouse Sequence.
- 2 - Area Sequence.
- 3 - Dimension 1 Sequence.

WHRS

Warehousing Reason Code. If Warehousing module is installed the following codes must exist:

- #1 - Put-Away Override.
- #2 - Commit Override.
- #3 - Replenishment Override.
- #4 - Instruction Overridden.
- #5 - Item/Pack Profile Missing.
- #6 - Item/WHSE Profile Missing.
- #7 - Planned Movement.
- #8 - Short Despatch Leave Frozen.
- #9 - Count Reconciliation.
- 99 - Short Despatch Leave Ccommitted.



Note: Set the limit field for code 99 to 1 to leave stock committed.

WHSE

Warehouse Miscellaneous Parameters.

CDID - Confirm Despatch Session with a Rate/Value of 1 (this is system generated).

DTAQ - Data Queue Wait Time in Seconds, where the limit field sets the data queue polling delay in seconds.

EOFD - End of File Delay in Seconds, where the limit field sets the data queue polling delay in seconds.

ASPN - Produce Advanced Shipping Pick Notes, where 1 in the limit field means Yes.

Search Family Characteristic Codes

You can define Major types to act as characteristic codes, which are used in search family codes/certificates of conformance. In order for a major type to be used in this way, a put a V in the P/V field.

The description codes set up for each major type are the permitted values defined to the characteristic.

For example, you could have a major type (characteristic code) of COLR and descriptions (characteristic values) of Red, Pink and Blue.

Descriptions File Maintenance Screen (F15)



To display this screen enter a major type and select **F15=Description code details** on either the Descriptions File Maintenance Selection screen or the Descriptions File Maintenance Details screen.

Use this screen to add or maintain Low Level Codes for a Major Type.

The upper part of the screen contains the details of the Description Code being maintained, the lower part, a list of the current Description Codes for the selected Major Type.

```

IN037              Z1 - GB Demonstration Company    USER GBJBA1MS    14/01/98
                                           12:53:06

Descriptions File Maintenance

Description type... RFCD      Reference Code          Limit..    30
Major type..... A
Description..... ALL Divisions
Parameter limit...      Rate.. .00 P/V...    VAT code..   

1 Desc'n I.D. Description          Limit    VAT PV Rate
- AOUS      Aosta Valley Service NDC          .00
- DANSREF    Dans Reference Code              .00
- DELIVNOTE  .007                          .00
- INVOICE    .007                          .00
- JIMS       Jims test reference code          .00
- JKGREF     Juliet Keg Reference              .00
- LK         Lk ref type                      3    .00
- NEWREF     JKG Copy Cat Ref                  .00
- RFC        Rob's                            .00      +

1=Select 2=Language descriptions
F3=Exit F11=Delete F12=Previous F23=Language descriptions

8-25  SA  MW  KS CL IM DM II  STUD140  KB  PET087S1
  
```

Fields:

Description Code

Select a description code.



Tip: To add a new description enter the code and press **Enter**

Description

Enter the description for the Low Level Code.

Parameter Limit

Enter up to seven numeric characters. This field is for information purposes only within Inventory Management.

Rate

Enter a rate using up to five numeric characters, two decimals. Use the rate for certain description types, such as extra charges, to define a rate associated with the

Major Type. You define the nature of the rate by the percentage/value flag specified for this Major Type.

P/V

P - Where the rate is a percentage basis.

V - Where the rate is a value basis.

VAT Code

Enter the VAT code using one character. This would typically be used to define VAT codes associated with extra charges.

Sel

Select. Enter one of the following:

1 - To maintain the description code details.

2 - To add or amend different language text.



Press **Enter** to update the Description Code details.

Descriptions File Maintenance Detail Screen



To display this screen select a specific Major Type for maintenance on the first Descriptions File Maintenance screen and press **Enter**.

Use this screen to enter the details for the selected Major Type.

IN037	NR - Neil's Test Company	USER GBJBANER	21/05/96 11:09:39
-------	--------------------------	---------------	----------------------

Descriptions File Maintenance

Description type..... TYPE
Major type..... RFCD
Description..... Reference codes
Description limit..... 30 P/V... _

Desc'n I.D.	Description	Limit
ACDF	AC Terminology Definitions	30
ADFM	Address format	30
AEDI	Automatic Update from EDI	30
ALIT	Alternative Item Type	30
AN	Agencies	30
ARPM	Arrears Processing Method	30
ASAD	AS Address Type Codes	30
ASTA	Article Status Code	30
AUMD	Authorisation Method	30
BCFM	Bank Code Format	30

F3=Exit F12=Previous F15=Description code details
F23=Language descriptions
07-30 SA MW KS IM II KENB20A PET178S1

Fields:

Description

Enter up to 30 alphanumeric characters to describe the Major Type.



Tip: The limit field determines the maximum length.

Limit

Enter up to two numeric characters to specify the length of the description associated with this Major Type (maximum value 30).

P/V

This is percentage/value.



Tip: If you are defining a major type for use in perhaps a Certificate of Conformance code, then enter V in this field.

Functions:

F15

Description Code Details. Select to add or maintain low level codes for a major type. See Descriptions File Maintenance Screen (F15).

F23

Language Descriptions. This displays the Multi-Lingual Descriptions Maintenance window, where you can enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, to print any text entered in the specified language in the Maintain Text window (F21), on external documentation for that customer.



Note: You do not need to select Language codes to print text in the native language.



Press **Enter** to update the major type.

Items Maintenance

1... **2/INM**

This procedure creates and maintains the primary Item Master information. This information is primarily concerned with classifying and describing an item. The characteristics of these items are defined by the analysis codes. The use of these codes varies depending upon the needs of the company. The following points should, however, be noted.

- Minor product group is used as the main level of aggregation for the entry and maintenance of forecast data in MPS, MRP and DRP.
- Reports and stock counts in Inventory Management can be requested by part/style type, product class, major product group or minor product group.

Item Maintenance Selection Screen



Select Items.

Enter the code of an existing item or a new code (15 characters alphanumeric) to add an item to the file. If you do not know the code for an existing item, prompt on this field to display the Item Master Scan Window.

Item Maintenance Detail Screen 1



To display this screen select an item on the Item Maintenance Selection screen and press **Enter**.

Use this screen to view and maintain data relating to the item. The current data for the item is displayed.



*Note: If you make an error and existing data is inadvertently overwritten, select **F12=Previous** before pressing **Enter** on the second screen and the data on the file is not updated.*

IN002		Z1 - GB Demonstration Company		USER GBJBA1MS	14/01/98 13:15:38
Item Maintenance					
Item.....	5011	Shampoo normal/dry 200ml			
Weight		Packaging Reporting Item.... (0/1)			
Volume					
Effectivity start.....	11/08/94	Purchase pack.....			
Item type.....?	3	Long Shelf Life			
Item class.....?	1	Low Cost			
Item group major.....?	3	Toiletries			
Item group minor.....?	6	Hair Care			
Division.....?	0	Domestic			
Sub-division.....?	1	Bought In Item			
Purchase unit.....?	CA	Stock->purchase conv..... .25000			
Stock unit.....?	PL	Issue->stock conv..... 16.00000			
Issue unit.....?	BX	Weight per selling unit.. .2000			
VAT code.....?	001	17.50 %			
Discount group.....?					
Inventory source.....?					
Sales analysis flag.....?	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.	0	0=No,1=Yes End date 0/00/00			
F3=Exit F4=Prompt F10=Val.Grp F12=Previous F21=Text entry F24=More keys					
4-45 SA MW KS CL IM DM II STUD140 KB PET087S1					

Fields:

Untitled

Description. Enter up to 36 alphanumeric characters, which describe the item. You use the description identify the item on enquiries and reports, and to build the alpha search words for the item.

(Named N)

Where Named N=1 to 3. These are the three user-defined item specification fields. Their use in the Inventory Management company is defined in the Specification N Description fields on the third Company Profile Maintenance screen. The fields are eleven numeric characters with four decimal places.

Packaging Reporting Item

Enter one of the following:

0 - To exclude the item from the packaging report.

1 - To include the item in packaging reporting.

Effectivity Start

For a new item, enter the date from which the item can be sold, or added to the system. This field is useful if you want to find out how long the item has been used by the company.

Purchase Pack

Enter up to six alphanumeric characters to define the purchase pack for this item.

Item Type

Enter an item type chosen from those defined on the descriptions file against major type PTYP.



Tip: Use this field to select items for stocktakes.

Item Class

Enter an item class chosen from those defined on the descriptions file against major type PCLS.

Item Group Major

Enter a major item group chosen from those defined on the descriptions file against major type PGMJ.

Item Group Minor

Enter a minor item group chosen from those defined on the descriptions file against major type PGMN.

Use the above codes to classify similar items for reporting purposes and select items for the valuation of stocks movements.



Note: Use Item group minor as a level of aggregation for the entry and maintenance of forecast data in MPS, MRP and DRP. Within Production, they are used to group items into product families. These product families may subsequently be used as a selection parameter on a selective MRP run.

Division

Enter a division chosen from those defined on the descriptions file against major type DIVN.

Sub-Division

Enter a sub-division chosen from those defined on the descriptions file against major type SDIV.



Tip: Use the above codes to define which division of the company has responsibility for this item.



Warning: You should code with the full knowledge of the implications to linked applications - Sales Analysis, Production and Forecasting.

If you use the Advanced Financial Integrator (AFI) to maintain stock and sales values in the General Ledger. You should consider the definition of items. Appropriate coding makes the mapping to the required Chart of Accounts easier.

Purchase Unit

Enter a unit chosen from those defined on the descriptions file against major type UNIT.

The purchase unit defined here provides the default purchase ordering unit at the item/stockroom level.

Stock Unit

If you only enter the stock unit, the application automatically enters the same unit of measure for issue and purchase units and enter 1 for the conversion factors.

Issue Unit

The issue unit defined here provides the default issue unit at item/stockroom level, and is the default ordering unit for this item in Purchase Management. For example, if you raise a purchase order in crates, boxes and bottles for a single item, and the issue unit is bottles, all orders are expressed in the application in bottles only.



Tip: The units of measure you specify in the above fields are the only valid units of measure to be used when ordering, moving, stocking and selling this Inventory item.

Stock To Purchase Conversion Factor

Enter up to nine numeric characters with five decimals to specify the relationship between the stock and purchase units. If stock and purchase units are the same, this should be 1. If, for example, stock units are Each and purchase units are Tens, this conversion factor should be 10.

Issue To Stock Conversion Factor

Enter up to nine numeric characters with five decimals to specify the relationship between the issue and stock units. If issue and stock units are the same, this conversion factor should be 1. If, for example, the issue unit is Each and the stock unit is Tens, this conversion factor should be 10.



*Note: If the issue unit and the purchase unit are the same, the following condition must apply:
The product of the Stock to Purchase and the Issue to Stock factors must be exactly equal to 1.*

VAT Code

Enter a VAT code from those defined on the descriptions file against major type VAT. The rate field is used to hold the appropriate VAT percentage. If you are using Sales Order Processing and Purchase Management or both this information is used to calculate the VAT payable on this item. If General Ledger is attached confirmation of the VAT code is via the General Ledger VAT code definitions.

Weight Per Selling Unit

Enter up to eleven numeric characters, four decimals to specify the weight of a single selling unit. If Transport Planning is attached, the weight assigned to each item must be in the same unit of measure, for example, Kilogrammes. If Catchweight is being

used by this company, this field is replaced by the Secondary Value and Secondary UOM fields.

Secondary Value

If Catchweight is being used, this and the Secondary UOM field are displayed instead of the Weight Per Selling Unit field. The secondary value is the conversion between the item's issue unit and the item's secondary unit. If the item's issue unit is BOX and each box is 5KG then the secondary value and the unit of measure would equal 5.0 and KG respectively.

Secondary UOM

If Catchweight is being used by this company, this and the Secondary Value field are displayed instead of the Weight Per Selling Unit field. This defaults to the unit of measure selected in Company Profile Maintenance. You can prompt for another unit of measure.

The secondary UoM may then be used for advanced pricing and discounting of sales orders of the item and the secondary values are passed to sales analysis.

If the item is a Catchweight item (see F9 function) then the stockroom costs are also expressed in this unit of measure.



Note: Both the Secondary Value and Secondary UOM fields must either be empty or have entries, otherwise an error message is displayed

Discount Group

You can group items together which have the same discounts on a discount list.

Enter a discount group using a three character alphanumeric code. These are defined against major type PGR in Descriptions Maintenance. Discount groups are used by Standard Pricing, and are referred to in discount lists configured in Sales Order Processing.



Note: If Advanced Pricing is in use, this becomes a memo field.

Inventory Source

You can group items that are to be updated together on a price list.

Enter an Inventory source code using a one character code, to indicate to which pricing group this item belongs. These are defined against major type INSC in Descriptions Maintenance.

Use Price List Updates to convert to a different currency, or when a percentage change in the price occurs. For more information see the Create New Price List screen in Order Entry.

If you use Configurator, define a specific and unique value for each of the following categories:

- Model items.
- Base items.
- Preconfigured items.
- Order configured items.

- Generic components.

In this case, it is suggested that you use the M, B, P, O and G codes respectively. However, if any of these codes are already used in major type INSC, then you must use different codes.

Sales Analysis Flag

Enter one of the following to define Sales Analysis activities for kit items.

0 - No Sales Analysis update is to take place for this item.

1 - Either this is a non-kit item and should update Sales Analysis normally or this is the parent of a kit for which only the parent details should update Sales Analysis.

2 - This is the parent of a kit for which only component details should update Sales Analysis.

3 - This the parent of a kit for which both parent and component details should update Sales Analysis.



Note: The Sales Analysis update for a kit is controlled by the flag on the parent. The flag on the kit component merely specifies the Sales Analysis update when you sell the component as an item in its own right. (For more information refer to Kit Lists.)

Flag Item For Deletion

Enter one to flag the item for deletion in the next Item Deletion run.



Note: The item is deleted after first checking that there are no outstanding transactions and that the end date entered in the End Date below has been reached.

End Date

Enter the date at which this item becomes available for deletion. Enter 1 in the Flag Item For Deletion field to delete this item using Item Deletion.

Functions:

F9

Sec Vals. If there are entries in both the Secondary Value and Secondary UOM fields, when you select **F9=Sec Vals**, the Secondary Value Details window is displayed.



Note: This function is only displayed if Catchweight can be used. For more information see Company Profile Maintenance.

F10

Val Grp. Select to display the group valuation criteria for the item you are maintaining.

F21

Text Entry. Select to display the Maintain Text window. Select a Usage Code and a Language Code for multi-lingual text entry. Press **Enter** to display the Item Text window. Enter text in the selected language to be displayed or printed on external documentation, for example despatch notes, according to the usage code selected.



Tip: You specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can override this default language by entering a different language code when **F16=Additional Overrides** function key is available.



Note: You do not need to select Language codes to print text in the native language.

F22

Purchase text. Select to display the Item Text window.

F23

Language Descriptions. This displays the Multi-Lingual Descriptions Maintenance window, where you can enter or amend a language code and its description. You can add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text window (F21), will be printed on external documentation for that customer.



Note: You do not need to select Language codes to print text in the native language.

F24

More Keys. This is a toggle function to display all the available functions.



Press **Enter** to check all changed data, and to redisplay the screen for confirmation of codes.



Press **Enter** a second time with no intervening changes to display the second screen.

Secondary Value Details Window (F9)



If there are entries in both the Secondary Value and Secondary UOM fields, when **F9=Sec Vals** is selected on the Item Maintenance screen, the Secondary Value Details window is displayed.



Note: This function is only displayed if Catchweight can be used in this company.

IN002		CW - Catchweight Company		USER GBJBA1MS	12/02/97
					12:06:36
Item Maintenance					
Item.....	CW1SN	Type1 Standard Not-Batch KG			
Pallet Conv					
Volume					
Area					
Effectivity start.....	24/09/96	Purchase pack.....			
Item type.....?	G	Gardening			
Item class.....?	98	Class 98			
Item group major....?	2	Cosmetics			
Item group minor.					
Division.....					
Sub-division....					
Purchase unit....					
Stock unit.....					
Issue unit.....					
VAT code.....					
Discount group...					
Inventory source....?					
Sales analysis flag.?	1	Kit Parent Only (or Non-Kit)			
Flag item for deletion.	0	0=No,1=Yes	End date	0/00/00	
Secondary value details Catchweight item (1,2,3)..... 1 Secondary UOM..... KG 00000 Tolerance %..... 7.50 00000 Tolerance value..... .0000 11.0000 F12=Previous					
F3=Exit F4=Prompt F9=Sec vals F12=Previous F21=Text entry F24=More keys 14-52 SF MW KS IM II KENB20A PET149S2					

Fields:

Catchweight Item (1, 2, 3)

Enter the usage category for this Catchweight item, which is either one, two or three, or leave the field blank. For more information see the fifth Company Profile Maintenance screen.

Secondary UOM

This field defaults to the unit of measure displayed in the Secondary UOM field on the Item Maintenance screen. This field is displayed for your information only and cannot be amended.

Tolerance %

When you capture an item's secondary value during a relevant transaction, you can set the default plus or minus degree of deviation from the expected nominal value by entering a percentage number in this field. If you exceed this percentage tolerance a warning message is displayed. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5%, will cause the warning message to display.

Tolerance Value

When you capture an item's secondary value during a transaction, you can set the default plus or minus degree of deviation from the expected nominal by entering an

absolute value. If you exceed this fixed value tolerance a warning message is displayed. For example if you enter 5 in this field, any transaction that exceeds the expected nominal value by plus or minus 5kg (if the UoM is kilos) will cause the warning message to display.



Note: Enter a number in either the Tolerance % field or the Tolerance Value field, you cannot enter a number in both.



Note: If both the Tolerance % or Tolerance Value fields are empty, then there is no tolerance and a warning is displayed for anything other than the default.



Select **F12=Previous** to update and return to the Item Maintenance window.

Group Valuation Window (F10)



To display the Group Valuation window, select
F10=Grp Val on the first Item Maintenance
Details screen

Use this window to define the group valuation criteria for the selected item.

IN002		Z1 - GB Demonstration Company		USER GBJBA1MS	14/01/98 13:15:38
Item Maintenance					
Item.....	5011	Shampoo normal/dry 200ml			
Weight		Packaging Reporting Item.... (0/1)			
Volume					
Effectivity start.....	11/08/94	Purchase pack.....			
Item type.....?	3	Long Shelf Life			
Item class.....?	1	Low Cost			
Item group major.....?	3	Toiletries			
Item group minor.....?	6	Hair Care			
Division.....?	0	Domestic			
Item valuation by group..... 1 (0=No,1=Yes) Valuation group.....?.. 6 Hair Care Conversion factor (Issue to group unit).. .00000 Group unit of measure.....					
Inventory source.....?					
Sales analysis flag... 1					
Flag item for deletion. 0 0=No,1=Yes					
Kit Parent Only (or Non-Kit)					
End date 0/00/00					
F3=Exit F4=Prompt F10=Val.Grp F12=Previous F21=Text entry F24=More keys					
17-50 SA MW KS CL IM DM II STUD140 KB PET087S1					

Fields

Item Valuation By Group

Enter one of the following:

0 - Do not assign this item to a valuation group.

1 - Assign this item to a valuation group.

Valuation group

Select a valuation group to which you wish to assign this item. Enter a group chosen from those defined on the descriptions file against PGMN. The group does not have to be the same as the minor item group previously assigned. It does have to have a UoM code in the VAT field, as this is the valuation group's UoM.

Conversion Factor

Enter a conversion factor using nine numeric characters, five decimals, to convert the item issue unit of measure to the assigned group unit of measure.

Group UOM

When you select a valuation group for the item, this group unit of measure information is automatically displayed.



Warning: As all items in a group are updated with the same cost using LIFO revaluation, You MUST take care when you define item

groups.



Select **F8=Update** to process the details and return to the first Item Maintenance Details screen.

Maintain Text Window (F21)



To display the text maintenance select **F21=Text Entry** on the first Item Maintenance Details screen.

Use this screen to select a Usage Code and a Language Code or both to specify where to print or display text.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS		20/06/96	
						14:33:05	
Item Maintenance							
Item.....	1352_STD	1352 Standard Costed Item					
Pallet Conv							
Volume							
Weight							
Effectivity start.....	5/07/95	Purchase pack.....					
Item type.....?	C	S2/V3 : Consumables Spares					
Item class.....?	3	High Cost					
Item group major....?		Maintain Text					
Item group minor....?		Text Type.....	P	Item Text			
Division.....?		Text Reference..	1352_STD				
Sub-division.....?		Usage Code....?	-				
Purchase unit.....?		Language Code?..					
Stock unit.....?		F4=Prompt F12=Previous F13=Select existing Text					
Issue unit.....?	EA	Weight per selling unit..					
VAT code.....?	3HB	%					
Discount group.....?							
Inventory source....?							
Sales analysis flag.?	1	Kit Parent Only (or Non-Kit)					
Flag item for deletion.	0	0=No,1=Yes	End date	0/00/00			
F22=Purchase text F23=Language descriptions F24=More keys							
14-44	SR	MW	KS	IM	II	KENB20A	PET166S2

Fields:

Text Type

You can define up to ten combinations of default text/default.

Text Reference

This is the reference number given to a text type, which retrieves default text when no text exists for the selected usage or language code.

Usage Code

Select a Usage Code to specify where to display or print text.



Note: There are some standard text usage codes supplied with the Inventory application. Define other usage codes in Inventory Descriptions Maintenance under major type USGC.



Note: To enter text in multiple languages enter a valid Language Code, along with the Usage Code, to display the Item Text window.

Language Code

Select a valid language code, in addition to the Usage Code, if you want to enter multi-lingual text. The Item Text entry window is displayed where you can enter text

in the language specified. This field may be left blank if you do not use multi-lingual text entry.



*Note: For multi-lingual text entry, you specify your customer's default language in Customer Details Maintenance in Sales Order Processing. You can, however, override this default language by entering a different language code when **F16=Additional Overrides** function key is available.*



Note: You do not need to select Language codes to print text in the native language.

Functions:

F13

Select existing text. This lists all currently defined Usage/Language code combinations for the entered text type/text reference. You can select the combination you want to use for entering multi-lingual text.



Press **Enter** to display the Item Text Window.

Item Text Window (F13)



To display this window, enter a valid usage code in the Maintain Text Window and press **Enter**.

Or: Select **F13=Select Existing Text** on the Maintain Text Window (F21).

You can enter, amend or delete text in this window. Use the fields at the bottom of the window to move around the text and add or delete lines.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS	20/06/96
					14:33:05
Item Maintenance					
Item.....	1352_STD	1352 Standard Costed Item			
Pallet Conv					
Volume					
Weight					
Effectivity start.....	5/07/95	Purchase pack.....			
Item type.....?	C				
Item class.....?	3				
Item group major....?	Maintain				
Item group minor....?	Text Typ				
Division.....?	Text Ref				
Sub-division.....?	Usage Co				
Purchase unit.....?	Language				
Stock unit.....?	F4=Prompt				
Issue unit.....?	EA				
VAT code.....?	3HB				
Discount group.....?					
Inventory source....?					
Sales analysis flag.?	1				
Flag item for deletion.	@ 0=No,1=				

Item Text					
Lin	Batch	Reference	Text		
1					
2					
3					
4					
5					
6					
Position to ___ Insert ___ after ___					
Delete from					
F5=Refresh F8=Update F12=Previous					
F13=Change usage/language					

F22=Purchase text	F23=Language descriptions	F24=More keys
12-42	MM KS IM II	KENB20A PET166S2

Fields:

Position To

Enter the number of the first line of text to appear at the top of the window.

Insert _ After _

Enter the number of lines you want to insert in the text as well as the number of the line after which they should appear.

Delete _ From _

Enter the number of lines you want to delete from the text as well as the first line number of the text to be deleted.

Functions:

F13

Change usage/language. To redisplay the Maintain Text window and enter or select a Usage Code and a Language Code for entering multi-lingual text.



Select **F8=Update** to update the text and return to the Item Maintenance screen.

Item Text Window (F22)

 To display this screen select **F22=Purchase Text** on the first Item Maintenance screen.

You can use Purchase text as an alternative description for this item in Purchase Management.

You can review text entered against the item here at order entry time within the Purchase Management application. This text entry option is only available if Purchase Management is installed and is linked to this Inventory company.

IN002		Distribution V3 -> V3 Financials		USER GBJBAMV1	14/11/95
					14:19:06
Item Maintenance					
Item.....	#1	784			
Pallet Conv					
Volume					
Weight					
Effectivity start.....	18/03/95	Purchase pack.....			
Item type.....?					
Item class.....?					
Item group major....?					
Item group minor....?					
Division.....?					
Sub-division.....?					
Purchase unit.....?					
Stock unit.....?					
Issue unit.....?					
VAT code.....?					
Discount group.....?					
Inventory source....?					
Sales analysis flag.?					
Flag item for deletion.					

Item Text.

	#1
1	
2	
3	
4	
5	
6	

Position to ____ Insert ____ after ____
Delete ____ from ____

F5=Refresh F8=Update F12=Previous

F3=Exit	F4=Prompt	F12=Previous	F21=Text entry	F22=Purchase text
14-33	SA	MW	KS	IM
			II	KENB20A
				PET129S1

 Select **F8=Update** to save new or amended details to file.

Multi-Lingual Descriptions Maintenance Window (F23)



To display this window, select **F23=Language Descriptions** from the Item Maintenance screen.

You can enter or amend a language code and its description. You add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text window (F21), will print on external documentation, for example despatch notes, for that customer.



Note: You do not need to select Language to print text in the native language.

IN002		NR - Neil Radford and Co. Ltd		USER GBJBA1MS	20/06/96
					14:33:05
Item Maintenance					
Multi-lingual Descriptions Maintenance					
Pal	Code.....	1352 STD	Item		
Vol	Description..	1352 Standard Costed Item			
Wei					
Eff	Language (?)	Description			
Ite			s		
Ite					
Ite					
Ite					
Div					
Sub					
Pur			1.00000		
Sto			1.00000		
Iss					
VAT					
Dis					
Inv	F4=Prompt F8=Update F12=Previous				
Sales analysis flag?... 1 Kit Parent Only (or Non-Kit)					
Flag item for deletion. @ 0=No,1=Yes End date 0/00/00					
F22=Purchase text F23=Language descriptions F24=More keys					
09-11 SF MW KS IM II KENB20A PET166S2					

Fields:

Language

Enter a two character language code, to represent a language you want to use.

Description

Enter the language name corresponding with the entered language code



Note: To delete a line, remove the language code.



Select **F8=Update** to update the file.

Item Maintenance Details Screen 2



To display this screen press **Enter** twice on the Item Maintenance Selection screen.

Use this screen to maintain of part of the data relating to the item. The current data for the item is displayed.

IN002		NR - Neil Radford's Test Company		USER GBJBANER	19/12/96
					16:17:58
Item Maintenance					
Item.....	A1	Aspirin Dispersible tablets BP 300mg			
Superseded by.....?					
Supersession date.....	0/00/00	Date last changed....	13/12/96		
Costing method (S,L,A,F) S		Purchases Account....	310000		
Standard cost.....	.95000	Sales Account.....			
Latest cost.....	1.05000	Cost of sales Account			
Average cost.....	1.00000	Price variance Acct..	310000		
Base list price.....	1.95000	Purchasing officer...	00000		
Price regulator code.?	.00 %	Search family code.?			
Price list seq code....		C-of-C code.....?	Rqd? _		
Warranty type.....?		Non-stock item type..			
Storage method.....?		Preferred supplier.?			
Shelf life unit.....?	4 Years	Ordering method....?	0 Normal Orde		
Shelf life.....		Cust shelf life.....			
EEC tariff code.....?		Date.. 0/00/00	Ref.	000000000000	
Duty %		Bar code.....			
Lot control (B/L/S/N)... N		Inspection reqd.....	0 (0=No,1=Yes)		
Sub contract item.....?					
F3=Exit F4=Prompt F12=Previous F14=Group valuation criteria					
F17=Alternative item references F18=Item search chars. F24=More keys					
05-27	SR	MM	KS	IV	II EDN400A PET16SS2

Fields:

Superseded By

Enter up to fifteen alphanumeric characters to specify if the item on display has been or is to be superseded by another item. If the item has been superseded then enter the new item number and the supersession date.

Supersession Date

If you have entered details in Superseded By then you must enter the date on which the item was or is to be superseded.

Date Last Changed

This is a system maintained field holding the date when you last changed the item details.

Purchases Account

Enter an account number of up to 12 characters.



Note: If Purchase Management is being used this is the account number to which the purchase invoices are posted. This defaults to the account number in the General Ledger Account field in the third Maintain Company Profile screen.

Sales Account

Enter an account number of up to 12 characters. This is the account number to which stock transaction values are posted. This field defaults to the account number in the Sales GL Account field in the third Maintain Company Profile screen.

Cost Of Sales Account

Enter an account number of up to 12 characters.

If Sales Order Processing is being used this is the account number to which cost of sales transaction values are posted. This field defaults to the account number in the Cost Of Sales GL Account field in the third Maintain Company Profile screen.

Price Variance Acct

Enter an account number of up to 12 characters.

If Purchase Management is being used this is the account number to which accruals are posted. This field defaults to the account number in the Price Variance GL Account field in the third Maintain Company Profile screen.

Purchasing Officer

Enter a purchasing officer as maintained in Purchase Management.

Costing Method

This indicates the method used to cost the item when received into Inventory. Although the costing method for the item remains the same in all stockrooms, each stockroom holds its own unique cost record which may therefore vary.



Tip: Production does not use these default codes, but those associated with a specific stockroom.

Select one of the following costing methods for this item:

S - Standard. Enter the standard cost in the Standard Cost field on the second Stockroom Details Maintenance screen.

L - Latest. Enter the cost of receipt in Miscellaneous Receipts.

A - Average. Enter the cost of receipt in Miscellaneous Receipts.

F - FIFO. Enter the cost of receipt in Miscellaneous Receipts.



Note: You only need to enter this field need if you do not want the item costing method to be the same as the default costing method set up on the company profile.

Standard Cost

You use these costs as references for non-stock items.

Latest Cost

You use these costs as references for non-stock items.

Average Cost

You use these costs as references for non-stock items.

Base List Price

Used in valuation of forecasts in Distribution Requirements Planning. You can use this price in Sales Analysis for kit components.

Price Regulator Code

Enter two alphanumeric characters chosen from those defined on the descriptions file against major type PRC.

Price List Seq Code

Enter five alphanumeric characters.

Warranty Type

Enter a warranty type code chosen from those defined on the descriptions file against major type WTYP.

Storage Method

Enter a storage method code chosen from those defined on the descriptions file against major type STRM.

Search Family Code

This code, defined in Advanced Order Entry, defines up to 10 attributes of the item which are maintained using **F18=Item Search Chars**. These attributes can then be used in the item search facility.

These codes are also used by Configurator:

- To link a model product with associated base products.
- To link a generic component with its actual components.
- To search for a matching component based on the specific characteristics.

C Of C Code

Define the structure of the Certificate of Conformance that is to be associated with any batches of this item. The certificate codes are defined in Advanced Order Entry (AOE) Maintenance.

Rqd?

Enter one of the following:

0 - Certificate of conformance cannot be issued.

1 - Certificate of conformance may be issued.

2 - Certificate of conformance is required from the supplier upon receipt of the item. This field requires a certificate of conformance code.

Non-Stock Item

(AOE) Enter 5,6,7 or 8 for items to appear on sales orders, but that does not have stockroom records. Leave blank to define an item as stocked.

A non-stock item is a saleable item that does not exist in a stockroom. For example, time charges, and items delivered directly from a supplier to a customer.



Note: You can only define an item's non-stock item type when you are actually creating the item.

Preferred Supplier

(AOE) - For back-to-back ordering of non-stock items. You must nominate an existing supplier from Accounts Payable. This can also be used in Production as a selection parameter on a selective MRP run.



Note: The preferred supplier for back-to-back ordering for stock items is taken from the Stockroom Details file.

Order Method

Enter one of the following:

0 - Normal. This is the default.

1 - Made to order.

2 - Purchase to order. If Advanced Order Entry is installed a back to back requisition order is initiated at the time of order entry.

3 - Direct delivery. If Advanced Order Entry is installed a back to back requisition order is initiated at the time of order entry.

4 - Reservation. You can reserve stock for this sales order against outstanding purchase orders.

5 - Configure to order. You can only use this if the Configurator is being used. This creates a production order.



Note: You define order methods on the descriptions file against the major type ORDM

Shelf Life Unit

Enter a shelf Life Unit code from those defined on the Descriptions file against Major Type SHLU:

1 - Days.

2 - Weeks.

3 - Months.

4 - Years.

5 - Unlimited.

Use this field if an item is batch, lot or serial controlled.

Shelf Life

Enter up to three numeric characters. This is the shelf life of the item expressed in the item shelf life units. The actual life of the product.

Customer Shelf Life

This is the portion of the total shelf life after which you should take some action, for example a price reduction. For lot controlled items subtract this value from the expiry date to give the last available date.

EEC Tariff Code

Enter an EEC tariff code chosen from those defined on the descriptions file against major type TAR. If you enter a tariff code then duty % is retrieved from the descriptions file entry for the tariff code.

Tariff Date

Enter the date for the tariff classification agreement, in the format DD/MM/YY.

References

Enter up to 12 alphanumeric characters to specify the reference number of the document confirming the EEC tariff classification.

Duty %

Retrieved from the descriptions file if you enter an EEC tariff.

Bar Code

Enter up to thirteen alphanumeric characters to specify the bar code for this item.

Lot Control

Set the control flag in Extended Lot Details within Inventory Management's company profile to determine the use of this facility. If not enabled for a type you cannot select the option.

Enter one of the following to specify the type of lot control for this item:

L - Lot: control stock by manufacturing lot number.

S - Serial Number: control stock by item serial number.

B - Batch: control stock by manufacturing batch number.

N - No batch control: control of stock by total quantity recorded only.

Batch control methods L, S and B require the entry of the appropriate control number when making a stock movement.

Within Production, there is no functional difference between lot and serial control.

Inspection Req'd

Enter one of the following:

0 - Do not inspect this item.

1 - Inspect this item before despatch.



Note: If Purchase Management is installed, any item flagged as requiring inspection upon receipt has a warning displayed when received directly into goods inward or stores.

Sub Contract Item

If Inventory Management is linked to Purchase Management, enter up to fifteen alphanumeric characters to determine whether to book the item into stock under another number. If you specify a sub contract, then any purchase receipts against the maintained item are booked into stock against the sub contract item.

Functions:



Note: If AOE is active, the following function keys are available:

F17

Alternative Item References. To create and maintain alternative item references used for item search. You can maintain any number of alternative references for an item. These may be customer specific item numbers or the original equipment manufacturer's code.

F18

Item search characteristics. To create and maintain item search details.

F19

Price Groups. To maintain pricing groups.

F20

Lot Header Details. Only displayed for lot controlled items.

F23

Language Descriptions. To display the Multi-Lingual Descriptions Maintenance window, to enter or amend a Language Code and it's Description. You can add these defined language codes to a customer's profile, in Sales Order Processing, so that any text entered in the specified language in the Maintain Text window (F21), is printed for that customer.



Note: You do not need to select Language codes to print text in the native language.



Press **Enter** to return to the Item Maintenance Selection screen.

Alternative Item Reference Screen (F17)



To display this screen select **F17=Alternative Item References** on the second Item Maintenance Details screen.

You can specify alternative references for the selected item.

IN210	Z1 - Demonstration Company	User SP1	25/08/94 16:55:00
Alternative Item Reference Maintenance			
Item.....	5013	Muesli Bar Honey High Fibre	50g
Line	Alternative reference	External agency	Alt.item type Delete
1	HONEY MUESLI BAR - SMALL	RUBIK	M
Line	Alternative reference	External agency	Alt.item type (?)
_____	_____	_____	_____
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous			

Fields:

Alternative Reference

Enter up to 36 alphanumeric characters to describe the item.

External Agency

Enter up to eight alphanumeric characters to indicate with which external agency, possibly the manufacturer or a customer, this alternative reference is associated.

Alt Item Type

Enter an alternative item type chosen from those defined on the descriptions file against the major type ALTT. This could be the type of external agency, for example wholesaler.



Select **F8=Update** to update the information. The alternative reference you have just defined displays at the top section of the screen.

Item Search Characteristics Screen (F18)



To display this screen select **F18=Item Search Chars** on the second Item Maintenance Details screen.

You can maintain the search characteristics for this item that are associated with the family search code specified on the second Item Maintenance screen. The item reference and search family code is displayed with their respective descriptions, followed by all the characteristics associated with this family code.

IN205	Z1 - Demonstration Company	User SP1	25/08/94 16:56:07
Item Search Characteristics			
Item.....	5013	Muesli Bar Honey High Fibre	50g
Search family code.....	CRT	Lab Certificate - Food Content	
Description	Code (?)		
Fat Content g/100g	_____	.00	
Salt Contentg/100g	_____	.00	
Carbohydrateg/100g	_____	.00	
Protein g/100g	_____	.00	
Preservative (Y/N)	Y	_____	
Sweetener (Y/N)	Y	_____	
Added Colour (Y/N)	N	_____	
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous F17=Update/Alternative item references			

Fields:

Code

Enter, or select, a code for the characteristics.



Note: The number of decimals entered must conform to the specification made for the characteristic in Search Family Maintenance in Advanced Order Entry.

Functions:

F17

Update Alternative Item References. To create or update alternative item references.



Select **F8=Update** to update the details and return to the second Item Maintenance screen.

Item Pricing Groups Window (F19)



To display this window select **F19=Price Groups** on the second Item Maintenance Details screen.

You can display or amend item pricing group information.

```

IN002                NR - Neil Radford and Co. Ltd      USER GBJBA1MS   12/08/96
                                                           12:30:52

Item Maintenance
Item..... 1352_STD          1352 Standard Costed Item
Superseded by.....?..
Supersession date..... 0/00/00      Date last changed.... 20/06/96
Costing method (S,L,A,F) S      Purchases Account.... 007

S  Item Pricing Groups
L  Item 1352_STD          1352 Standard Costed Item      More:
A  Seq  Proc              Itm proc
B      typ Description          Grp Description
P  -    1 MS1 MS Profile          IG1 Item Group 1
P  -    2 MS3 Pricing Type Profile 03  IG2 Item Group 2
W
S
S
S
E  1=Amend  4=Delete
D
L  Sequence      Type...?      Group...?      Position to:
S  F4=Prompt  F5=Refresh  F8=Update  F12=Previous

F3=Exit  F4=Prompt  F12=Previous  F19=Maintain Pricing Groups

20-16  SF  MW  KS  IM  II  KENB20A  PET166S2
  
```

Fields:

Untitled

Select. Enter one of the following:

- 1 - To amend the pricing group.
- 4 - To delete the pricing group.

Seq

Sequence. This is the sequence in which the function is searched to determine whether it applies to a particular line.

Type

The pricing code for the individual item.

Group

This is the item pricing group for which the selected type is effective, this is defined against major type ITMG.



Select **F8=Update** to update the details and return to the second Item Maintenance screen.

Lot Header Parameters Maintenance Window (F20)



To display this window select **F20=Lot Header Maintenance** on the second Item Maintenance Details screen against a lot controlled item.

You can maintain the Lot Header. Existing information will be displayed.

IN002		Z1 - Demonstration Company		USER SP1	25/08/94 16:56:28
Lot Header Parameters Maintenance					
Item..... 5013		Muesli Bar Honey High Fibre 50g			
Potency required.....	0	(0=No,1=Yes)			
Standard potency.....	%				
Grade required.....	0	(0=No,1=Yes)			
Default grade.....?					
Default stock status.....?					
Release lead time units.?	1	Days			
Release lead time.....	2				
Lot dates 'to'.....?	1	Actual date			
Display lot time.....	0	(0=No,1=Yes)			
F4=Prompt F12=Previous					
Shelf life.....	12	Cust shelf life.....	8		
EEC tariff code.....?		Date..	0/00/00	Ref.	000000000000
Duty %		Bar code.....			
Lot control (B/L/S/N)...	B	Inspection reqd.....	0 (0=No,1=Yes)		
Sub contract item....?					
F3=Exit F4=Prompt F12=Previous F17=Alternative item references					
F18=Item search characteristics F20=Lot header maintenance					

Fields:

Potency Required

Enter one of the following:

0 - Do not display the potency field on receipt, potency is an attribute of the whole lot.

1 - Enter a potency every time you receive a new lot of this item into Inventory.

Standard Potency

If you have set Potency Required to 1 then enter a value, this defaults into the potency field every time you receive a new lot of this item.



Note: Potency is a percentage, the potency you specify here is the number of parts of active ingredient per hundred parts.

Grade Required

Enter one of the following:

0 - Do not display the grade field on receipt, grade is an attribute of the whole lot.

1 - Enter a grade every time you receive a new lot of this item into Inventory.

Default Grade

If you have set Grade Required to 1 enter a value, this defaults into the grade field every time you receive a new lot of this item.

You must choose the grade from those defined on the descriptions file against the major type GRAD.

Default Stock Status

Enter a stock status code chosen from those defined on the descriptions file against the major type STKS. This stock status code defaults into the stock status field every time you receive a new lot of this item into Inventory. Stock status codes are designated as either available or unavailable and when applied to a lot make the quantity of that lot frozen or unfrozen.

A blank stock status implies that a lot is available.



Note: The seven digit limit field of the description codes defined against STKS indicates the availability of an item. If the seventh digit of this field is 1 then the stock status code indicates an unavailable item. Any other value renders the stock status code an available code.

Release Lead Time Units

Enter one of the following alphanumeric characters to specify the release time unit used when calculating the first available date of a lot:

- 1 - Days.
- 2 - Weeks.
- 3 - Months.
- 4 - Years.

Leave this field blank if the release lead time cannot be entered. In this case when the lot dates are calculated the first available date equals the production date.



Note: Production Date + Release Time = First Available Date.

Release Lead Time

You must enter this if you specify a release lead time unit. Enter up to three numeric characters. The release time is used in the following calculation:

For example, Available Date + Release Time = First Available Date.

If you leave this field blank when the lot dates are calculated the first available date equals the production date.

Lot Dates To

Enter one of the following alphanumeric character to specify the method used to position lot dates once they are calculated:

- 1 - Use actual lot dates.
- 2 - Position to first day of the period.
- 3 - Position to last day of the period.

All lot dates are either entered or calculated using shelf life and release times. Once calculated, you can reposition the dates to the start or end of a period depending on the business requirements.

Display Lot Times

Enter one of the following:

0 - Do not display Lot times when you receive a new lot of this item into Inventory.

1 - Display Lot times as well as lot dates. In this case enter a time, as well as a date, upon receipt of a lot.



Press **Enter** on each screen until the item is completely updated.

Inventory Item Search Words Window

 The Item Search Words Window opens automatically, if you have amended the item description, external text or created an item.

You can add or amend words relevant to the item. This is used for item searching.

IN002		Distribution V3 -> V3 Financials		USER GBJBAMV1	14/11/95 14:47:11
Item Maintenance					
Item.....	#1	Medium Talc			
Superseded by.....?					
Supersession date.....	0/00/00	Date last changed....	14/11/95		
Costing method (S,L,A,F)	-	Purchases Account....	007		
Standard cost.....		Sales Account.....	1005		
Latest cost.....		Cost of sales Account	1006		
Average cost.....		Price variance Acct..	1007		
Base list price.....		Purchasing officer...	10000		
Price regulator code.?	.00 %				
Price list seq code....					
Warrant					
Storage					
Shelf 1					
Shelf 1					
EEC tar					
Duty %					
Lot con					
Sub con					
Inventory Item Search Words Item Key Words: Item Reference: #1 MEDIUM TALC _____ _____ _____ _____ F12=Previous F13=Rebuild					
F3=Exit F4=Prompt F12=Previous					
16-33 SA MW KS IM II KENB20A PET129S1					

Fields:

Define up to 20 key words used in a search on Inventory's item description.

For New Items

The window displays, as separate key words, each part of the item description, and as many parts of the external text as possible.

For Existing Items

The window displays the previous versions of the keywords.

To see the latest versions select **F13=Rebuild**.

Functions:

F13

Rebuild. Use to rebuild the search engine.

 Press **Enter** to update.

Item Master Scan Window



To display this window enter ? in an Item field and select **F4=Prompt**.

This is used throughout Inventory Management to assist in identifying a required item. The same item search function is used in maintenance, enquiry and processing, as well as being used in all applications where an item number is used.

```
IN002                Z1 - Demonstration Company      USER SP1      23/08/94
                  17:17:53

Item Maintenance
Item.....?.. ?

Item Master Scan
Search Type  1 ('1' - Item Reference,      '2' - Inventory Description,
              '3' - Purchasing Description, '4' - Alternate Reference,
              '5' - Search Characteristics, '?' - Prompt
Search Criteria _____
F4=Prompt  F12=Previous
```

Fields:

Search Type

Enter one of the following:

1 - Item Reference.

2 - Inventory Description.

If Purchase Management is installed the following search types are available:

3 - Purchasing Description.

If Advanced Order Entry is installed, the following search types are available:

4 - Alternative Reference.

5 - Search Characteristics.

9 - Base item

? - Enter ? and press **Enter** to display another window you can use to search on up to six words that appear in the item description. The default search type is defined in the Default Item Search Option on the company profile maintenance.

Search Criteria

What is keyed here depends on the Search Type.

- Item Reference - Displays all the items, in item number sequence, beginning with the search criterion entered. The search criterion can either be an item or the beginning characters of an item.
- Inventory Description - Make a selection based on the Inventory search words which currently exists for the item. These are generated at item maintenance time based on the first 20 words from the item description and the first three lines of the external text for the item. When either the item description or external text are modified you have the opportunity to rebuild the item search index. You can add words to the search index manually.
- Purchasing Description - Make a selection based on the description. The search criterion can be either a whole word or the initial letters of a word appearing in the description.
- Alternative Reference - Make a selection based on the alternative item reference. This alternative item description may be used by a manufacturer or wholesaler and is maintained by pressing **F17=Alternative Item Desc** from the second Item Maintenance screen. The search criterion can be either a whole word or the initial letters of a word present in the alternative item reference. This search displays a list of all items, with the external reference and item reference, that match the criterion.
- Search Characteristics - Make a selection based on a single or a range of characteristics specified against a search family code. The search criterion is a search family code. This code is maintained from the Advanced Order Entry application.
- Base Item - Displays all the base items in number sequence beginning with the entry made. This is only possible when Production and Configurator are attached.
- Prompt - If ? is keyed in the Search Type field an extra window is displayed.

You can position the display to a nominated point in the list. However, if only one reference meets the search criterion, the application returns to the maintenance screen and insert the item reference code automatically.



Select the item you wish to use.

Alternative Items Maintenance




3/INM



Note: This option is used for Sales Order Processing.

You can define which alternative items can be used. You would normally use an alternative item if an item is not available, out of stock, or you are phasing out old stock to introduce a new product.



```
IN006                Z1 - GB Demonstration Company      USER GBJBA1MS   14/01/98
                                                           13:25:51
```

Alternative Items Maintenance

Item..... 5013 Muesli Bar Honey High Fibre 50g

Alternative Item (?)	Description	Reverse (0=No,1=Yes)
APPLEJACK	APPLEJACK SNACKPACK	1
		-
		-
		-
		-
		-
		-
		-
		-
		-
		-
		-
		-
		-
		-

F3=Exit F4=Prompt F12=Previous

10-3 SA MW KS CL IM DM II STUD140 KB PET087S1



Alternative Item

Description

Reverse

0 - No. Do not use the Item as an alternative for the Alternative Item.

1 - Yes. Use the Item as an alternative for the Alternative Item.



defines the alternative items and displays the first Alternative Items Maintenance screen.

Kit Lists Maintenance

4/INM

A kit list is a group of items normally sold as individual finished goods, but on occasions sold together as a unit.

The kit is known as the parent, the individual items as components.

In some industries it is more appropriate to sell a kit of items, rather than regarding the kit as a single indivisible item. You can achieve a greater level of product flexibility with a smaller investment in Inventory. Use this option to create and maintain kits. When you add a component item to a kit Inventory Management checks that there is an existing stockroom balance record in all the stockrooms that hold the parent of the kit.



Note: Stock is only held at component level.

This feature is used by Sales Order Processing where orders are raised against the kit parent as defined here in Inventory. In this case, the parent price is charged and the components' prices are ignored. However, you can use Sales Analysis to analyse the component prices.

You can call kit parent details from Advanced Order Entry and amend them there, or you can define kits on line, without reference to this file.



Note: Kit components are individual items that are picked, packed and shipped. If they are items to be assembled to make a finished product, this is a Production process and not a kit list.

Kit Lists Maintenance Selection Screen



Select Kit List.



Note: If Catchweight is used in this company, then a Catchweight item cannot be the parent of a kit list. In this case, when you select Kit List, an error message is displayed.

Also, if a non-Catchweight item is the parent of a kit list, you can add Catchweight type three items as components. Also, you can add non-Catchweight items with or without a secondary UOM as components.



Enter the Item code to act as the kit parent, and press **Enter** to display the Kit List Maintenance Detail screen.

Kit List Maintenance Detail Screen



To display this screen select an item number that defines the kit parent, on the Kit List Maintenance Selection screen and press **Enter**

You can create and maintain a kit of items, once you have selected the parent item.

The current kit is displayed showing component item numbers, descriptions and the quantity of each item required to complete the kit.

IN007	Z1 - Demonstration Company	User SP1	23/08/94 17:27:18
Kit List Maintenance			
Item.....	5028	Luxury Eye Collection Kit	
Component Item (?)	Description	Qty.off	
5025	Black Onyx Mascara	1.00	
5026	Mahogany Eye Definer	1.00	
5029	Violet Make Up Pencils	1.00	
5030	Moisturing Eye Gel 15ml 74 Box	1.00	
5034	Silk Eye Powder 6 Colour x 50 BX	1.00	
5035	Luxury Eye Collection Bag	1.00	
F3=Exit F4=Prompt F12=Previous			

Fields:

Component Item

Enter the item number of the component item using up to fifteen alphanumeric characters. The item must exist on the item file.

Qty Off

Enter the quantity of the kit component that makes up the kit using up to five characters, two decimals.



Note: Component items cannot themselves be parent items of another kit. You must define component items to all the stockrooms to which have the parent item defined.

You can delete a component from the kit by removing the item reference from the kit list.



Press **Enter** to display the item descriptions of any items that have been entered. Press **Enter** again to update the file and return to the selection screen.

Stockroom Details Maintenance



A stockroom is a discrete area of a company where stock is recorded and controlled separately from other company stock. Some companies may require only one stockroom, whilst others, perhaps with a number of distribution points, require more. The key issue is that if there is a continuous requirement to record movements in and out and know the current balance of a particular area, you should use a stockroom.

Firstly you define each stockroom in the company profile. Secondly you define all the items for the company in the item file. The next stage is to associate each item with one or more of the stockrooms.

There is an exception. With AOE, you can define an item that does not have a stockroom record - a non-stock item.

You can create more detailed definitions for items and stockrooms if, for example, Warehousing, Production and DRP are in use.

Use this option to create and maintain details related to the stocking of an item in a stockroom.

The stock management policies ensure that the levels of stock in each stockroom are correct. You can specify the Parameters defining the implementation of these policies here.

An item must have the same method of costing throughout a company, be it average, standard, FIFO, or latest but you can independently maintain the actual cost of the item at each stockroom.

Stockroom Details Maintenance Selection Screen



Select Stockroom Details.

Use this screen to specify the item and stockroom details you wish to maintain or create.

Fields:

Item Number

Enter the item number.

Stockroom Code

Enter the stockroom code to identify the stockroom details you wish to maintain.



Note: You must define the stockroom to Inventory through the company profile section before you maintain the stockroom details.



Note: You must configure stockroom details for each item unless the item is being added as a non-stock item.



Press **Enter** to display the Stockroom Details Maintenance screen.

Stockroom Details Maintenance Screen



To display this screen enter an item number and stockroom code on the Stockroom Details Maintenance Selection screen, and press **Enter**.

Use this screen to maintain the item part of the stockroom details. Any existing information will be displayed.

IN003		Z1 - GB Demonstration Company		User GBJBA1MS		14/01/98	
						13:29:59	
Stockroom Details Maintenance							
Item.....	AB01	Standard item. No lot control					
Stockroom.....	01	Central Stockroom					
Purchase unit.....?	SA	Cases of					
Issue unit.....?	EA	Single of----->					
Reorder policy.....?	1	Upto MAX					
Profile code.....?	—	Vendor schedule item... _ (1=Yes)					
Lead time.....	.00						
Reorder point.....	.000						
Maximum stock.....	.000						
Reorder qty.....	.000						
Reorder factor %.....	10%						
EOQ.....	.000	ABC class override..... _					
Calculate EOQ etc.....	1 (0=No,1=Yes)	Over confirm. 120.00%					
Material cost.....	.00000	Suppliers?... _					
Standard cost.....	.00000	_					
Latest cost.....	.03285	Bins..... _					
Base list price.....	40.00000	Date changed..... 12/01/98					
F3=Exit F4=Prompt F11=Delete F12=Previous F14=Landed costs							
7-26 SA MW KS CL IM DM II STUD140 KB PET087S1							

Fields:

Vendor Scheduling Item

Enter 1 to indicate that you control item purchasing through Vendor Scheduling - if Vendor Scheduling has been installed.

Leave this field blank if the item purchasing is controlled by Requisitioning.

This field is for purchased items only.



Note: If you reset this field from 1 any Vendor Scheduling purchase orders remain in place.

Purchase Unit

Enter a purchase unit chosen from the units of measure defined on the descriptions file. This defaults to the purchase unit defined for the item. This unit is assumed as the default ordering unit in Inventory Management and Purchase Management if it is installed.

Issue Unit

Enter an issue unit chosen from the units of measure defined on the descriptions file. This defaults to the issue unit defined for the item. All stock balances and costs for this item in this stockroom are expressed in this unit.

In Production, when you define a route header, you use this as the default UOM.



Note: If Catchweight is used in this company, and the unit of measure is a secondary UOM, this field is displayed for your information only and cannot be amended.

Reorder Policy

Enter one of the following to specify the item's normal reorder policy in this stockroom:

- 1 - Up to MAX.
- 2 - ROQ.
- 3 - Up to MIN.
- 4 - Up to ROP.
- 5 - EOQ.

The code defaults to that defined on the company profile but can be changed.

Profile Code

Enter the usage profile, using up to two alphanumeric characters. This is previously defined in the company profile and is used in calculating the average usage for the item in this stockroom.

Lead Time

Enter the lead time, in weeks using up to five characters, two decimals. Used for stock availability calculations.

The system calculates the available date by adding the lead time to the current date.



Note: Reorder Point, Maximum stock, EOQ are calculated by the system if the Calculate EOQ and so on field is set to 1.

Reorder Point

Enter the reorder point using up to thirteen numeric characters, three decimals to determine at what quantity you should reorder stock.

Do this if you do not want the system to calculate this value automatically.

Production uses this to determine the safety stock figure for the item in this stockroom when you run MRP in cell mode.

Maximum Stock

Enter the maximum stock using up to thirteen numeric characters, two decimals if you do not want the system to calculate this value automatically.



Note: If the ROP is higher than Maximum stock, a warning is given.

Reorder Qty

Specify the reorder quantity using up to 13 numeric characters, three decimals. If you leave this value as zero, the system calculates a reorder quantity based on reorder factor %. This only applies if you specify reorder policy 2 - ROP/ROQ. Otherwise, for policies 1-4, enter a figure to manually control the reorder level.

Reorder Factor %

Specify the reorder factor %, using up to three numeric characters. This defaults to the percentage defined on the company profile. This percentage is the number of lead times worth of average usage to be reordered. This only applies if you specify reorder policy 2-ROP/ROQ.

EOQ

Enter up to thirteen numeric characters, two decimals, to specify the economic order quantity. Use this if you do not want the system to calculate this value automatically.

Calculate EOQ Etc.

Enter one of the following:

0 - Manually enter these figures.

1 - The application should calculate economic order quantity, reorder point and maximum stock.



Tip: If reorder policy = 3, set this field to 0.

Material Cost

You can only enter material cost for standard cost items. For standard cost items, you enter the material cost, and any standard landed costs are applied to calculate the total standard cost. If no landed costs are defined, then the standard cost equals the material cost.



Note: If Catchweight is active for this company, the landed costs are added to the material cost to give a total standard cost per secondary UoM. In this case, a value based landed cost relates to the secondary UoM. The Item/supplier profile and actual landed costs in Purchase Management are all based on the primary transaction quantity and never on the secondary transaction value.

Standard Cost

If standard costing is being used, every issue or receipt uses the standard cost. The default costing method is defined in the Costing Method field on the third Maintain Company Profile screen, and on the second Item Maintenance screen.

Enter up to 15 numeric characters, five decimals, to specify the standard cost of one issue unit of the item. If the item is not standard costed the field can be entered for memo purposes. For standard costed items this field is protected, the standard cost is calculated based on the material cost, with any standard costs applied.

Production updates the item cost if you transfer production costs (for manufactured items) to Inventory.

Latest Cost



Note: You only use this field when the item is first added, so that it has a value in Inventory.

If you use latest costing, all stock valuation reflects the latest cost. The default costing method is defined in the Costing Method field on the third Maintain Company Profile screen, and on the second Item Maintenance screen.

Enter up to fifteen numeric characters, five decimals, to specify the latest cost. The application maintains the latest cost as the unit cost associated with the last stock receipt recorded for an item. You specify it when the item/stockroom is first set up, but is overridden during the next receipt.

Base List Price

Enter up to fifteen characters, five decimals. Use this data in the valuation of forecasts in MPS, DRP and MRP. It is also used by Sales Analysis to calculate sales values for kit components.

Date Changed

This is a system maintained field indicating when you last changed this record.

ABC Class Override

The ABC classification matrix is defined for each stockroom on the company profile. The categorisation is based on the value and usage of an item, either A, B or C with associated recommended minimum and maximum stockholding levels.

Leave this field blank if you want the system to use the default class for the item configured in the fifth Maintain Company Profile screen.

Enter A, B or C to associate the item with a different class, so that when stock counting is requested the item is counted more or less frequently than the default.

Enter Z in this field to not include the item on a stock count request.

Over Confirm

This is the default from the descriptions file. Entering a value in this field alters the acceptable tolerances for over despatching an item from this stockroom.

Suppliers

Enter up to four, eight character supplier codes to specify the suppliers of this item for this stockroom. Requisitioning uses the first supplier as the preferred supplier when generating recommended purchase orders.

Bins

Enter the bins in which you store this item in the stockroom using up to two sets of six alphanumeric characters. If you require full location management, you should install Warehousing.

Functions:

F11

Delete. To delete a stockroom select this function twice, after satisfying the following conditions:

- The physical stock balance must be zero.
- No movements must exist in the current month.
- No outstanding orders, either sales, Production, or purchase must exist.

F14

Landed Costs. To define landed costs for the item. This function key is available when the item is standard costed.



Press **Enter** to check all details and return to the Stockroom Detail Maintenance Selection screen.

Landed Costs Entry Screen (F14)



To display this screen select **F14=Landed Costs** on the second Stockroom Maintenance Detail screen

Use this screen to enter and maintain landed costs for an item.

```

IN320                Z1 - GB Demonstration Company    USER GBJBA1MS    14/01/98
                                      13:30:24

Landed Costs Entry
Item..... AB01                Standard item. No lot control
Stockroom.. 01                Central Stockroom
UoM..... EA                Single of----->

Cost Code      Description      Standard Landed Cost      Perc/Value (1/0)
(?)

01 Post & Packaging      2.50000      1
-
-
-
-
-
-
-
-
-
-

F3=Exit F4=Prompt F8=Update F12=Previous

12-6      SA      MW      KS CL IM DM II      STUD140      KB      PET087S1
  
```



Note: Landed Costs can only be defined for a standard costed item.

Fields:

Cost Code

Select an existing cost code. Landed Cost codes are usually set up in Purchase Management.

Description

The description for your chosen cost code is automatically displayed.

Standard Landed Cost

Enter a figure for the cost code using nine numeric characters, five decimals.

Perc/Value

Enter one of the following:

0 - For this landed cost to be value based.

1 - For this landed cost to be percentage based.



Select **F8=Update** to update the information you have added and return to the second Stockroom Maintenance Details screen.

FIFO Costs Maintenance



6/INM

FIFO (first in, first out) determines that the oldest receipted stock items are sold first. The oldest items can have different costs. The system automatically sells the oldest costed stock first and keeps detailed cost tracking.

The application generates FIFO records when you set the costing method of a product to FIFO and you receive goods into stock. If you make an error at the time of entry you can use this facility to amend the detail within a FIFO record. To audit any cost changes made, a movement is written to the transaction file. This has a zero quantity and a value equal to that of the adjustment, an audit report is then printed.



Note: If Catchweight is used for this company, the average cost of Catchweight items for physical and in-transit FIFO items is calculated using the secondary values.

Maintain FIFO Costs Selection Screen



Select FIFO Costs.

Use this screen to select the item and stockroom combination for which you wish to amend FIFO costs

Fields:

Item Number

Enter the item code.

Stockroom code

Enter the stockroom for which you want to amend FIFO costs.



To display the Maintain FIFO Costs screen press
Enter.

Maintain FIFO Costs Screen



To display this screen select the item and stockroom combination on the Maintain FIFO Costs Selection screen and press **Enter**.

Use this screen to maintain the unit cost of a FIFO record.



Note: The cost change only affects the unissued items associated with that record. Inventory Management does not track items already issued to amend their cost. If part of the receipt has been issued it is necessary to spread the total value of the adjustment over the remaining items in the receipt. This may lead to unusual short term costs.

The upper part of the screen identifies the product and stockroom for which the amendment has been requested. The lower part lists the open FIFO records for the product/stockroom.

IN028		Z1 - GB Demonstration Company		User: GBJBA1MS	14/01/98 13:35:27
Maintain FIFO Costs					
Item.....	ALFIFO	Fifo Item			
Stockroom.....	01	Central Stockroom			
Issue Units.....	EA	Single of----->			
Date / time Received	Original qty	From supplier/ stockroom	Cost per unit	Balance	
9/12/97 10:30:27	10.000		10.0000	10.000	
9/12/97 10:31:24	10.000		10.0000	10.000	
12/01/98 11:47:52	20.000		10.0000	20.000	
F3=Exit F12=Previous					
11-49 SA MW KS CL IM DM II STUD140 KB PET087S1					

Fields

Cost Per Unit

Enter or amend the cost for the required FIFO record.



Note: Although the value of stock may have changed, the General Ledger is not updated by this process.

There are two options which make the creation of new items quicker:

- Linked item maintenance - you can set up profiles required by other linked applications, as well as those required by Inventory itself.

- Copy function - you can create a new item based on the details of an existing item.



Press **Enter** to change the value of the FIFO record. The value of the change is written to the movements file, as an audit of the change.

Calendar Maintenance



7/INM & 3/INC

Use this option to maintain the current week, period and year number for the Inventory company.

Codes must exist for the calendar details when you set up the system, but after this the current calendar position is maintained automatically by the week, period, and year end batch update jobs. You should never manually change it during the course of the year, except under exceptional circumstances where a re-run of the week, month, or year end update is necessary.

The Year End Update option accesses the same details and submits a batch job which:

- Updates the number of weeks this year and last year specified on the calendar.
- Changes the number of periods specified on the calendar.
- Sets any yearly accumulators to zero.
- Increments the year number by one.
- Produces a Stock Valuation Report as part of the submission process.
- Produces a Reorder Report as part of the submission process.

Maintain Calendar File Screen



Select Calendar.

IN012	ST - JBA System Test Company	USER GBJBARW2	8/11/95
			14:03:26
Maintain Calendar File			
Current year.....	<u>87</u>		
Current week.....	<u>18</u>		
Current period.....	<u>6</u>		
No. of weeks this year.....	<u>52</u>		
No. of weeks last year.....	<u>52</u>		
No. of periods this year...	<u>12</u>		
F3=Exit F11=Delete			
06-30	SA	MM	KS IM II KENB20A PET178S2

Fields:

Current Year

Enter the current year using up to two numeric characters.

Current Week

Enter the current week using up to two numeric characters.

Current Period

Enter the current period using up to two numeric characters.

No Of Weeks This Year

Enter the number of weeks this year using up to two numeric characters. The value must be less than or equal to 53.

No Of Weeks Last Year

Enter the number of weeks last year using up to two numeric characters. The value must be less than or equal to 53.

No Of Periods This Year

Enter the number of periods this year using up to two numeric characters. The value must be less than or equal to 13.



Note: This information is linked to Sales Analysis Company Profile and Forecasting's Company Profile Periods/Backups details.



Press **Enter**, to update the calendar with the changes.

Or, if you are processing a Year End Update, press **Enter** to submit a batch job to perform the year end update.

Period End Control



8/INM

Use this option to maintain period and week end dates. These are used within the application to stamp movements and update history records with the correct year, period and week number. The procedure is normally used only when you initially set up the system, and to create dates for future years.



Tip: Period can be defined in a variety of ways but normally refers to a month.

Inventory Period End Control Maintenance Selection Screen



Select Period/End Control.

Select the year number and period type for which end-dates are to be maintained.

```

IN062                ST - JBA System Test Company      USER GBJBARW2      8/11/95
                                                           14:04:12
Inventory Period End Control Maintenance

Year   00          Type   _   (1=Weekly,2=Monthly)

F3=Exit
05-13   SA      MW      KS      IM      II   KENB20A   PET178S2

```

Fields:

Year

Enter the year number of the year for which end dates are to be maintained.

Type

Enter one of the following:

- 1 - To maintain Week End dates.
- 2 - To maintain Month End dates.



Press **Enter** to display the Inventory Period End Control Maintenance screen.

Inventory Period End Control Maintenance Screen



To display this screen select the year and period type on the Inventory Period End Control Maintenance Selection screen and press **Enter**.

You can maintain end dates for a selected year and period type (week or month).



Warning: Take care when changing dates for a currently active year, as this may cause unpredictable results.

```

IN062                Z1 - GB Demonstration Company    USER GBJBA1MS    14/01/98
                                      13:38:36

Inventory Period End Control Maintenance

Year..... 97      Type..... 1 (1=Weekly,2=Monthly)

  Week  End date    Week  End date    Week  End date    Week  End date
   01  4/01/97     15  12/04/97     29  19/07/97     43  25/10/97
   02  11/01/97    16  19/04/97     30  26/07/97     44  1/11/97
   03  18/01/97    17  26/04/97     31  2/08/97     45  8/11/97
   04  25/01/97    18  3/05/97     32  9/08/97     46  15/11/97
   05  1/02/97     19  10/05/97     33  16/08/97     47  22/11/97
   06  8/02/97     20  17/05/97     34  23/08/97     48  29/11/97
   07  15/02/97    21  24/05/97     35  30/08/97     49  6/12/97
   08  22/02/97    22  31/05/97     36  6/09/97     50  13/12/97
   09  1/03/97     23  7/06/97     37  13/09/97     51  20/12/97
   10  8/03/97     24  14/06/97     38  20/09/97     52  27/12/97
   11  15/03/97    25  21/06/97     39  27/09/97
   12  22/03/97    26  28/06/97     40  4/10/97
   13  29/03/97    27  5/07/97     41  11/10/97
   14  5/04/97     28  12/07/97     42  18/10/97

ENTER=Validate
F3=Exit  F8=Update  F12=Previous

-----
8-10  SA  MW  KS  CL  IM  DM  IT  STUD140  KB  PET087S1
  
```

Fields:

End Date

Enter dates for the week or period end dates.



Tip: Where this is the initial set up of end dates for a particular year, only enter the first date. Press **Enter**, and Inventory Management will automatically generate the rest of the dates for the year.



Press **Enter** to check any entries and then select **F8=Update** to update the database.

Secondary UOMs Maintenance




9/INM

You can add recently created units of measure to the system. For each unit of measure, you can configure its relationship with other units of measurement by adding a conversion table. You can also associate a unit of measure with a larger unit of measure. For example, you can associate ounces with pounds.

Maintain Unit Of Measure Selection Screen

 Select Secondary UOMs.

You can select the required UoM.



Fields:

Unit Of Measure

Select the unit of measure you want to configure using a two character code

 Tip: Codes must exist for new Units of Measure in Descriptions under UoMC or GUMC before you can maintain their relationship to other units of measure.

 Press **Enter** to display the Maintain Unit Of Measure Details screen.

Maintain Unit Of Measure Details Screen



To display this screen select a UoM on the Maintain Unit Of Measure Selection screen and press **Enter**.

Use this screen to maintain part of the selected UoM. Existing information will be displayed.

IN560	CW - Catchweight Company	User GBJBA1MS	12/02/97 12:54:13
Maintain Unit Of Measure			
Unit Of Measure..... OZ			
Long description..... <u>Ounces</u>			
Short description..... <u>Ounces</u>			
Abbreviation..... <u>oz</u>			
Larger UOM..... LB Pounds			
UOM type.....?.. 1 Weight			
F3=Exit F4=Prompt F8=Update F12=Previous			
00-34 SF MW KS IM II KENB20A PET149S2			

Fields:

Long Description

Enter a description of the unit of measure up to 30 characters long.

Short Description

Enter a description of the unit of measure up to nine characters long. This is used elsewhere in the system to represent the unit of measure.

Abbreviation

Enter a text description of the unit of measure up to three characters long. This is used elsewhere in the system to represent the unit of measure.

Larger UOM

You can associate a unit of measure with a larger unit of measure. For example, you can associate ounces with pounds. The abbreviation and text description for the larger unit of measure are displayed in this field.

UOM Type

Enter one of the following:

- 1 - Weight.
- 2 - Volume/Fluid Capacity.

3 - Length.

4 - Area.



These UOM Types are held on the Descriptions file under Major Type UTYP, and can be maintained.



Select **F8=Update** to save the details on the system and display the third Maintain Unit Of Measure screen.

Maintain Unit Of Measure Screen 3



To display this screen select **F8=Update** on the Maintain Unit Of Measure Details screen.

Use this screen to configure the conversion factors between different units of measure.

IN560		CW - Catchweight Company		User GBJBA1MS		12/02/97 13:01:25	
Maintain Unit Of Measure							
Unit Of Measure..... OZ Ounces							
Sel	To UOM	Conv Factor	M/D	Description	Larger UOM		
█	GM	28.3496	M	Grammes			
-	KG	35.2736	D	Kilogrammes			
-	LB	16.0000	D	Pounds	1		
-	TN	35,840.0000	D	Imperial Tons			
-	TO	35,273.6000	D	Metric Tonnes			
To UOM.?. _ Conv Factor... .0000 M/D... _ Larger UOM... _					Bottom (0/1)		
F3=Exit F4=Prompt F8=Update F12=Previous							
00-02 SF MW KS IM II KENB20A PET149S2							

Fields:

Sel

Select. Enter 1 against the conversion unit of measure you want to edit.

To UOM

Enter the abbreviation of the conversion unit of measure.

Conv Factor

Enter the value, to four decimal places, by which the unit of measure must be either multiplied or divided to result in the conversion unit of measure.

M/D

Enter one of the following to determine whether the unit of measure is multiplied or divided to result in the conversion unit of measure:

M - Multiply.

D - Divide.

Larger UOM

Enter one of the following:

0 - If it is not a larger unit of measure (or leave blank).

1 - The conversion unit of measure is a larger unit of measure.



Select **F8=Update** to save the details on the system.

Linked Item Maintenance



10/INM

You can cross application maintain item related profiles and details. You firstly select an item, then amend any number of profiles such as item/stockroom, item/supplier, DRP item profile, without having to locate the individual maintenance options on the different menus.



Note: If Catchweight is used in this company, the Catchweight specific functions for each of the applications work as normal.

Linked Item Maintenance Screen



Select Linked Item Maintenance.

Use this screen to enter an item number.

Fields

Item

Enter an item for which you wish to maintain certain item related profiles or details.



The Profile Selection window displays automatically.


Profile Selection Window

-  The Profile Selection window is displayed, whether the item selected on the Linked Item Maintenance screen exists or not.

The item code and description are displayed at the top of the screen.

You can maintain the following profiles or details for the item:

- Inventory Item Master.
- Item Stockroom Details.
- Item Supplier Profile (Purchase Management).
- Production Item Master Profile (Production Definition Management).
- Item Warehouse Profile (Warehousing).
- World Trade Item Profile (World Trade).
- DRP Item Profile (Distribution Requirements Planning).
- Forecasting Item Profile (Forecasting).
- Alternative Items.



Profile Selection	Exists [0/1]
Item..... 1	
5345 1	
— Inventory Item Master	1
— Item Stockroom Profile	1
— Item Supplier Profile	1
— Production Item Master	0
— Item Warehouse Profile	0
— World Trade Item Master	1
— DRP Item Profile	0
— Transport Planning Item Master	0
— Forecasting Item Profile	1
— Alternative Items	0

F3=Exit F12=Previous

F3=Exit F4=Prompt

16-24 SA MW KS IM II KENB20A PET129S1

Fields:

Untitled

Sequence. The sequence column is blank for all profiles, unless you are creating a new item.

To maintain a profile, enter 1 against the first profile you want to maintain, 2 against the second, 3 against the next and so on.



Note: If you enter an item code that does not exist, the application displays the Profile Selection window with the Inventory Item Maintenance and Item Stockroom Details already selected for modification.

Exist 0/1

If at least one profile combination has been defined, 1 appears. Otherwise 0 is displayed.

For example if you have defined an item to the stockroom and to the supplier 1 appears in the Exists column against Inventory Item Maintenance, Item Stockroom Details and Item Supplier Maintenance. 0 appears against all other profiles.



*Note: The only difference when comparing those maintenance options accessed from the linked Item Maintenance function with those accessed directly from the menus, is the addition of the function key **F15**, which displays the Select Profiles screen.*



Warning: For maintenance functions requiring the selection of a second parameter, that is item/stockroom details, item/supplier, you must select F3=Exit from that function's selection screen to progress to the next profile chosen for amendment.



Once you have completed the Item Master, the system displays the Stockroom Details screen. You scroll through other selections until you return to the Profile Selection screen.

Copy Based On Item Creation



11/INM

You can create a new item from an existing item profile. You can copy some or all of the item's attributes, depending on the setting of flags on the Profile Options screen. This may be particularly useful when entering the details of redesigned items to replace existing stock, or when defining numerous similar items to Inventory, where only minimal changes are necessary to each item profile, thus reducing duplicate data entry.



Note: If Catchweight is used in this company, all the Catchweight specific information is also copied. For example, secondary UOM value, tolerance values, Catchweight item type.

Copy Based On Item Selection Screen



Select Copy Based On Item Creation.

Use this screen to select the established item from which you wish to copy details and enter the item code of the new item.

IN807	Z1 - Demonstration Company	User SP1	25/08/94 17:11:29
Copy Based On Item Selection			
Item.....	5044	Muesli Bar Apricot High Fibre 50g	
Based on..?..	5013		
F3=Exit F4=Prompt F8=Submit F13=Profile options			

Fields:

Item

Enter a unique item code, up to 15 alphanumeric characters.



If you enter an existing item a message is displayed and you should enter another item code.

Untitled

Description. Enter the description, using up to 36 alphanumeric characters, for this item code in the field to the right of the screen.

Based On

Enter the code of an existing item, on which you would like to base this new item.

Functions:

F13

Profile Options. To select profiles before you submit the job.



Select **F8=Submit** to process the job.

Profile Options Screen (F13)



To display this screen select **F13=Profile Options** on the Copy Based On Item Selection screen.



Note: Base item data (including item attributes, units of measure, lot, batch or serial control details and costing) is always copied to the new item. In addition, any of the following data may also be copied.

Use this screen to select the required options for copying the item.

IN807	Z1 - Demonstration Company	User SP1	25/08/94 17:11:42
Profile Options			
Item..... 5044	Muesli Bar Honey High Fibre 50g		
Based on..... 5013	Muesli Bar Apricot High Fibre 50g		
Item Details (0=No,1=Yes)	Warehouse Details.....	1	
Item text..... 1	Pick location details...	1	
Purchase text..... 1	Fixed locations.....	1	
Search characteristics.. 1	Item pack details.....	1	
Stockroom Profiles..... 1	World Trade Details.....	1	
Supplier Profiles..... 1	DRP Details.....	1	
Price structure..... 1	Alternative Item Details...	1	
Supplier text..... 1	Transport Details.....	1	
Production Details..... 1			
Item text..... 1			
Item Cost Elements..... 1			
F3=Exit	F8=Submit	F12=Previous	

Fields:

Enter one of the following for each field:

0 - This information is not required for this item.

1 - Duplicate the information held here for the new item.



Note: This will happen even if you have not defined that data for the existing item.



Note: You can amend this information using the Linked Item Maintenance option.



Select **F8=Submit** to submit.