

-
-
-
-
-

Chapter 2

Processing



Introduction to Fixed Assets Processing

Asset maintenance consists of a number of steps, the use of which depends on:

- Whether you have the basic or advanced version of Fixed Assets.
- The number of maintenance elements you wish to undertake.

For any asset, new or existing, you can maintain:

Base details:

Basic information about the asset.

Analysis codes:

Detailed analysis codes for as many classifications as have been set up in the systems reference code ANTY.

Notepad:

This consists of free-form narrative information which can be dated and classified. It is available only in the advanced version.

Financial details:

These contain the acquisition data for an asset, plus the expected life and residual value.

External funding details:

Information entered in this section can affect the valuation and the depreciation of the asset. The effect of external funding may differ for each financial view or book that is used. This is a facility only available in the advanced version.

Lease details:

This holds details relating to leased assets. This includes periodic payments, number of payments and to whom payment is made. This is a facility only available in the advanced version.

Depreciation details:

An asset can have none or one or several books. The basic version allows only one depreciation book. Financial control is exercised through the way in which a book is linked to an asset.

For any existing asset, you can also use:

Asset revaluation

This feature is only available in the advanced version.

Depreciation journal

This facility allows you to adjust calculated depreciation of an asset.

Asset journal

This transaction allows calculated depreciation or lease postings to be adjusted

Asset disposal

You can at any time dispose of an asset using this transaction

An additional feature of asset maintenance is the concept and practice of skip procedures.

General Ledger Link

General Ledger accounts to which asset financial transactions are posted are generated from the analysis codes set up in the structured General Ledger accounts procedure.

Transactions are posted at the end of a maintenance section, when you return to the menu. The transactions generated during that session are posted as a batch.

Rules:

- Transactions are only posted for a given book if the book profile specifies a link with the General Ledger.
- A book must be linked either to fiscal or to memorandum accounts
- Where an asset is being maintained individually, data is posted to the ledger for each transaction
- Where batch procedures are invoked, (depreciation) transactions are posted either in summary by General Ledger account or in detail by asset, if so specified in the book profile
- The GL account number must be valid when the transaction is created. If not, none of the transactions in that document is posted. An exceptions report is produced of the invalid transactions
- Corrections can be made to the invalid postings or you can choose to post to the suspense accounts, if set up, attached to the relevant book.

Transactions Header Information

Every maintenance procedure carries the same header information, contained within the first two lines on each maintenance screen.

Doc Date

Document date, which defaults to today's date.

Period

This defaults to the current Fixed Assets period in the format YYPP.

Transactions can be posted to an earlier period but transactions generated will be posted, in the General Ledger, to the Fixed Assets current period or the GL current period, whichever is the later.

Period numbers can be different in each system.

Ref

Transaction reference. The number must be unique within each item type. If the appropriate indicator is set in the company profile the reference number is automatically generated.

Reason

This is an optional field. If a reason code is used and entered ,it is validated against the reason codes set up in the systems reference codes.

Desc

Reason code description is displayed if the reason code is entered. If no reason code is entered, the description can optionally be entered. If a reason code has been entered, the description can be entered to overwrite the generated description.

Transaction Details Information

Financial transactions are generated for every maintenance procedure except analysis codes and notepad. All transactions are held on a transaction file and are available for on-line enquiries and for inclusion within reports.

Transaction data is held at three levels.

- Session
- Item
- Transaction value

Session records are started as soon as an asset is selected. If the maintenance process is abandoned, the session remains on the session audit file with a message.

Transaction records are generated for each maintenance procedure. General Ledger postings will result from the creation of financial transaction records only if:

- The book being used is linked to the General Ledger.
- Valid structured General Ledger accounts have been set up in the book being used.

Skip Procedures

Every maintenance screen has the same collection of function keys. If you press **F15** the Skip Procedures window displays.

FA101	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 9:50:13
Asset Base Details Maintenance			
Doc.Date 27/10/95	Period 9511	Ref..... 00000134	Reason? ____
Asset..... A1001		Desc.....	
Parent Asset..		Desc.....	Saab 900i
Reference.....		Desc.....	
Supplier No..?	Cmpy ____	Supplier Name.	
Model.....		Serial No.....	
Manufacturer..		Quantity.....	
Location.....	Customer Services, Birmingham	U.O.M.....?	
Date Acquired. 1/11/95	Commissioned 1/11/95	Warranty Expires.....	0/00/00
Prim Notepad.?		Retired Date.....	0/00/00
Text.....			0/00/00
Anal.? ATP Asset Type	VEH1	Company Cars	
Types COS Cost Centre	010	Sales Department	
Select Skip to Maint./Enq.			
Type.? 201	Asset.? C1001	Book.? ____	Notepad.? ____
F4=Prompt F12=Previous			
21-30	S*	MW	KS IM II EDN400A PED169S1

By this means you can skip out of the current maintenance procedure and enquire on any aspect of another or indeed the same asset.

Fields:

Type

The asset maintenance skip code which identifies the enquiry required. These codes are maintained in the system reference codes under code SKIP. They are identical to the equivalent codes NXTE - next enquiry type, used in the enquiry environment. Select the desired enquiry with a 1.

Asset

Enter the asset number from which the other information is sought.

Book

Enter the book number, if required.

Notepad

Enter the notepad type, if required.



Press **Enter** to display the selected enquiry.

Summary of Procedures and Financial Transactions

The matrices below show, for each type of asset maintenance procedure, the financial transactions that will result if the procedure is satisfactorily completed. Note that postings to the General Ledger will result only if the structured General Ledger accounts option has been correctly used.

ASSET MAINTENANCE PROCEDURES & FINANCIAL TRANSACTIONS

Procedure (Table 1)		COST BOOK									
		Asset Cost						Disposal			
No.	Description	001	002	003	005	006	009	101	105	109	200
101	Base Details										
105	Analysis Codes										
106	Notepad										
110	Financial		*				*				
112	External Funding				*	*					
115	Depr. Book							*			
120	Revaluation										
135	Disposal							*	*	*	*
416	Period Depr.										
419	Year End	*		*							

Procedure (Table 1)		DEPRECIATION BOOK								Other	
		Depreciation				Disposal					
No.	Description	300	310	323	325	400	410	421	422	905	909
101	Base Details	*									
105	Analysis Codes										
106	Notepad										
110	Financial	*	*							*	*
112	External Funding	*									
115	Depr. Book	*									
120	Revaluation	*	*								
135	Disposal					*	*	*	*		
416	Period Depr.				*						
419	Year End			*							

The matrix above illustrates the financial transactions that are generated from the main asset maintenance procedures. It does not include leased assets or asset journal (both depreciation and leased) procedures. These are shown on the following diagram.

ASSET MAINTENANCE PROCEDURES & FINANCIAL TRANSACTIONS																			
Procedure (Table 2)		LEASED ASSETS from COST BOOK																Deprec. Journal	
		Leasing Transactions												Disposal					
No.	Description	030	031	032	033	034	035	036	037	038	039	040	131	132	133	134	321	322	
113	Leasing Details	*							*	*									
127	Leasing Journal		*	*	*	*													
135	Disposal (leasing)												*	*	*	*			
418	Lease posting						*	*											
419	Year End (leasing)										*	*							
125	Depreciation Journal																	*	*
126	Depreciation Journal																	*	*

What Transactions are Generated?

Financial transactions are Generated By your maintaining different aspects of an asset. A pair of postings (debit and credit) are created and posted to the General Ledger.

All possible types of postings to the General Ledger are included in the transaction list. In practice only a few of the financial transactions will be used by companies with relatively simple requirements. However, transactions are available for companies using the advanced facilities of leasing or revaluation or external funding.

The complete financial transaction list is shown below:

001 Historical Asset Cost

Definition

Adds changes in asset value for the year to the historic cumulative asset cost.

Generated By

Year-end roll-over procedure when the system detects that the first period of the year is about to be opened.

General Ledger Posting

Debit: Asset historic cost account as at year-end (B/S)

Credit: Asset additions account for current year (B/S).

002 Asset Additions

Definition

Cost of asset additions and amendments for the current year.

Generated By

The system detecting that a new asset is being entered, or when an existing asset's value is changed.

General Ledger Posting

Debit: Asset additions account for the current year (B/S).

Credit: Asset control account (B/S).



Note: The creditors control account cannot be accessed directly because this is done by the purchase invoice posting. Thus a suspense account should be credited, then cleared by a purchase invoice debit posting.

003 Asset Disposal Year End Transfer

Definition

Carries the total of asset disposal postings at the year end to the credit side of the historic asset cost account.

Generated By

The year end roll-over procedure, when the system detects that the first period of the new year is about to be opened.

General Ledger Posting

Debit: Asset disposals account for the current year (B/S).

Credit: Asset historic cost account (B/S).

005 External Funding - Capital

Definition

The value of external funding to be offset against the capital value of the asset.

Generated By

External funding details being added to an asset record.

General Ledger Posting

This transaction and the following 006 transaction are rarely linked to the General Ledger. If it is linked, then it will depend on how the transaction is to be used, for example:

- To reduce the capital value of the asset and increase the value of grants received.
- To increase the value of grants and credit the 'source of finance' side of the balance sheet.

006 External Funding - Revenue

Definition

Value of external funding which remains after capital value of grant has been deducted.

Generated By

Adding external funding details to an asset record.

General Ledger Posting

If linked to the General Ledger, this transaction could be used to increase revenue in the P&L and debit B/S cash.

009 Replenishment Reserve

Definition

Value by which the replacement cost of the asset varies from the historic cost.

Generated By

Altering the historic cost of the asset while leaving the replacement cost unaltered, or vice versa.

General Ledger Posting

If linked to the General Ledger it would add to / subtract from a replacement cost reserve account (B/S) and credit a P&L account holding income due to replenishment reserve value.

Compare this to a revaluation reserve posting.

012 Asset Value Transfer Out

Definition

Book value of asset at transfer out. Cost book.

Generated By

Changing any asset analysis code that is linked to a General Ledger posting for which this transactions has been set up in the Structured GL Accounts option.

General Ledger Posting

Debit: Asset control account (B/S).

Credit: Original additions posting (B/S).

013 Asset Value Transfer Out Year End Roll

Definition

Asset at transfer out - year end value. Cost book.

Generated By

The year end roll over when the system detects that the first period in the new year is about to be opened.

General Ledger Posting

Debit: Asset additions account in respect of transfers out during the year.

Credit: Asset historic cost account with value of transfers out during the year.

022 Asset Value Transfer In

Definition

Book value of asset at transfer in. Cost book.

Generated By

Changing any asset analysis code that is linked to a GL posting for which this transaction has been set up in the Structured GL Accounts option.

General Ledger Posting

Debit: New additions posting (B/S).

Credit: Asset control account (B/S).

023 Asset Value Transfer In Year End Roll

Definition

Asset at transfer in - year end transaction. Cost book.

Generated By

The year end roll over when the system detects that the first period in the new year is about to be opened.

General Ledger Posting

Debit: Asset historic cost account with value of transfers in during the year.

Credit: Asset additions account in respect of transfers in during the year.

030 Leased Asset Periodic Payments

Definition

The value of the payment to be made in each period for which payments are generated.

Generated By

The creation or amendment of the Periodic Payments field in the Asset Lease Details screen.

General Ledger Posting

It would be very unusual if this financial transaction were to be linked to a General Ledger posting account. The most you might want to do would be to pass the periodic payment value to a GL memorandum account.

031 Lease Interest Previous Year

Definition

The value, or amended value, of lease contract interest charges, deemed by you to have been paid in previous years.

Generated By

A leased asset journal in which the Amend Values By or the Amend Values To field has been filled in for the interest previous year line.

General Ledger Posting

Under no circumstances should this transaction be linked to a General Ledger account.

032 Lease Interest Year To Date

Definition

The value, or amended value, of lease contract interest charges which you determine as paid in the current year.

Generated By

A leased asset journal in which the Amend Values By or the Amend Values To field has been filled in for the interest year to date line.

General Ledger Posting

Debit: Lease interest charges account (P&L).

Credit: Lease interest payments account (B/S).

033 Lease Capital Previous Year

Definition

The value, or amended value, of lease contract capital charges, which you deem to have been paid in previous years.

Generated By

A leased asset journal in which the Amend Values By or the Amend Values to field has been filled in for the capital previous year line.

General Ledger Posting

Under no circumstances should this transaction be linked to a General Ledger account.

034 Lease Capital Year To Date

Definition

The value, or amended value, of lease contract capital charges determined by you to have been paid in the current year.

Generated By

A leased asset journal in which the Amend Values By or the Amend Values To field has been filled in for the capital year to date line.

General Ledger Posting

Debit: Lease assets capital payments account (P&L).

Credit: Lease capital payments account (B/S).

035 Lease Interest Payments

Definition

The value of periodic interest payments calculated by using the leased asset calculation parameters and the 'sum of digits' method.

Generated By

The period lease postings option.

General Ledger Posting

Debit: Lease interest charges account (P&L).

Credit: Lease interest payments account (B/S).

036 Lease Capital Payments

Definition

The value of periodic capital payments calculated by using the leased asset calculation parameters and the 'sum of digits' method.

Generated By

The period lease postings option.

General Ledger Posting

Debit: Lease assets capital payments account (P&L).

Credit: Lease capital payments account (B/S).

037 Lease Total Interest Payable

Definition

The value of interest payments to be made under the agreed lease contract.

Generated By

Updating the leasing details screen for a leased asset.

General Ledger Posting

It is unlikely that this transaction would be linked to a General Ledger posting except as a posting to a memorandum account or possibly as a provision against which periodic interest payments may be accumulated.

038 Lease Total Capital Payable

Definition

The value of capital payments to be made under the agreed lease contract.

Generated By

Updating the leasing details screen for a leased asset.

General Ledger Posting

It is unlikely that this transaction would be linked to a General ledger posting except as a memorandum account posting, or possibly, as a provision against which periodic capital payments might be accumulated.

039 Lease Interest Year End Transfer

Definition

The value of lease contract capital payments made during the current year transferred to prior year lease interest account.

Generated By

The year end roll over when the system detects that the first period of the new year is about to be opened.

General Ledger Posting

Debit: Lease interest payments account (B/S).

Credit: Accumulated lease interest account (B/S).

040 Lease Capital Year End Transfer

Definition

The value of base contract interest payments made during the current year transferred to the Prior Year Lease Interest account.

Generated By

The year end roll over when the system detects that the first period of the new year is about to be opened.

General Ledger Posting

Debit: Lease capital payments account (B/S)

Credit: Accumulated lease capital account (B/S)

090 Job Management Postings

Definition

The value of any asset or part of an asset which is being capitalised from data in Job Management.

Generated By

Job Management Fixed Assets Transfer.

General Ledger Posting

Debit: Asset additions account (B/S).

Credit: Asset WIP stock account (B/S).

101 Asset Disposal Cost

Definition

The cost of the asset at the time of disposal.

Generated By

Disposal action. See also transactions 200, 421 and 422.

General Ledger Posting

Debit: Sale of assets account (P&L).

Credit: Assets disposal account (B/S).

105 Disposal External Funding

Definition

The value of external funding capital allocated to an asset as held in the system at the time of disposal.

Generated By

Disposal action.

General Ledger Posting

It is unlikely that the transaction would be linked to the General Ledger. It would need to be linked only in circumstances where the grant has to be repaid if the asset is disposed of within a given timescale.

109 Disposal Replenishment Reserve

Definition

The value by which the replacement cost of the asset varies from the historic cost at the time of disposal.

Generated By

Disposal action.

General Ledger Posting

The transaction allows you to include, if desired, the difference between the historic cost and the replacement cost of the asset in the calculation of the profit or loss on the sale of the asset. In this respect the postings would follow the same pattern as transaction 101 Asset Disposal Cost.

131 Disposal Previous Year Lease Interest

Definition

The value of interest paid on the lease contract in previous years.

Generated By

Disposal action.

General Ledger Posting

It is unlikely that leased assets would feature in the Balance sheet but the transaction is available should you wish to calculate a notional profit or loss and, possibly, hold this information in memorandum accounts.

132 Disposal Year To Date Lease Interest

Definition

The value of interest paid on the lease contract in the current year.

Generated By

Disposal action.

General Ledger Posting

It is unlikely that leased assets would feature in the balance sheet but the transaction is available should you wish to calculate a notional profit or loss and, possibly, hold this information in memorandum accounts.

133 Disposal Previous Year Lease Capital

Definition

The value of payments made in previous years against the capital element of a lease contract.

Generated By

Disposal action.

General Ledger Posting

It is unlikely that leased assets would feature in the Balance sheet but the transaction is available should you wish to calculate a notional profit or loss and, possibly, hold this information in memorandum accounts.

134 Disposal Year To Date Lease Capital

Definition

The value of payments made against the capital element of a lease contract in the current year.

Generated By

Disposal action.

General Ledger Posting

It is unlikely that leased assets would feature in the Balance sheet but the transaction is available should you wish to calculate a notional profit or loss and maybe hold this information in memorandum accounts.

200 Asset Disposal Sales Value

Definition

Sale value of asset.

Generated By

Asset disposal.

General Ledger Posting

Debit: Asset control account (B/S).

Credit: Sales of assets account (P&L).



Note: The debtors control account cannot be accessed directly by these transactions, because this is done by the sales invoice posting. Thus a suspense account should be debited, to be cleared by a sales invoice credit posting.

300 Book Value

Definition

The original value of the asset as defined by the parameters in the depreciation book profile.



Note: This may be based on replacement or re-valued value, or may include the value of dependent assets.

Generated By

The entry of a new asset or change in financial details provided that a depreciation book is attached.

General Ledger Posting

If 002 asset additions transaction is used, this transaction would not normally be required to be linked to the General Ledger. However, if an asset value other than historic cost is used to represent the asset value in the balance sheet, then you may wish to link this transaction in the same way as defined for transaction 002.



Note: Only the one or the other should be used.

310 Revaluation Reserve

Definition

The change in asset value arising out of the formal revaluing of the asset.

Generated By

Revaluation, within standard Asset Maintenance.

General Ledger Posting

Debit: Revaluation reserve account (B/S).

Credit: Income due to revaluation account (P&L).

321 Depreciation This Year

Definition

Depreciation adjustment journal for current year values.

Generated By

Depreciation journal, either from standard Asset Maintenance or from the Asset Journals option.

General Ledger Posting

Debit: Depreciation charges account (P&L).

Credit: Depreciation this year account (B/S).

322 Depreciation Prior Year

Definition

Depreciation adjustment journal for prior year values

Generated By

Depreciation journal, either from standard Asset Maintenance or from the Asset Journals option.

General Ledger Posting



Note: This transaction should never be linked to a General Ledger account.

323 Depreciation Year End Transfer

Definition

Depreciation adjustment journal for prior year values.

Generated By

Depreciation journal, either from standard Asset Maintenance or from the Asset Journals option.

General Ledger Posting

Debit: This year depreciation account (B/S).

Credit: Accumulated depreciation account (B/S).

325 Period Depreciation

Definition

Monthly depreciation posting

Generated By

The monthly depreciation posting task.

General Ledger Posting

Debit: Depreciation charges account (P&L).

Credit: Depreciation this year account (B/S).

400 Disposal Book Value

Definition

The book value of the asset, as defined by the original transaction 300, at the time of disposal.

Generated By

Disposal action.

General Ledger Posting

If the book value (transaction 300) is linked to General Ledger posting, then this transaction would be set up in the same way as defined for Asset Disposal Cost (Transaction 101).



Note: If Asset Disposal Cost (Transaction 101) is used then this transaction (400 disposal book value) is not required.

410 Disposal Revaluation Reserve

Definition

The changed part of the asset value that is due to formal revaluation as recorded at the time of disposal.

Generated By

Disposal action.

General Ledger Posting

Debit: Sale of assets account (P&L).

Credit: Assets disposal account (B/S).

421 Depreciation Disposal - Current

Definition

The value of depreciation charged this year in assets disposed of in the current year.

Generated By

Asset disposal

General Ledger Posting

Debit: Depreciation in assets disposed of this year (B/S).

Credit: Sale of assets account (P&L).

422 Depreciation Disposal - Prior

Definition

The value of depreciation charged in prior years in assets disposed of in the current year.

Generated By

Asset disposal.

General Ledger Posting

Debit: Depreciation in assets disposed of this year (B/S).

Credit: Sale of assets account (P&L).

511 Depreciation This Year Transfer Out

Definition

The value of depreciation for the current year, accumulated in an asset being transferred from one analysis code to another.

Generated By

Change of any analysis code that is linked to a General Ledger posting.

General Ledger Posting

Debit: Asset control account (P&L).

Credit: Old code depreciation balance for this year (P&L).

512 Depreciation Prior Years Transfer Out

Definition

The value of depreciation accumulated in prior years in an asset being transferred from one analysis code to another.

Generated By

Change to any analysis code that is linked to a General Ledger posting for which this transaction has been set up in the Structured GL Account option.

General Ledger Posting

This transaction should not be linked to a General Ledger posting.

513 Depreciation This Year Transfer Out Year-End.

Definition

The value of depreciation associated with a transferred asset that is to be transferred from this year accounts to prior year accumulated depreciation.

Generated By

Year end roll over when the system detects that the first period of the new year is about to be opened.

General Ledger Posting

Debit: This year depreciation account (B/S).

Credit: Prior year (accumulated) depreciation account (B/S).

514 Depreciation Prior Year Transfer Out Year-End

Definition

The value of depreciation from prior years associated with a transferred asset.

Generated By

Year-end roll over.

General Ledger Posting

The transaction should not be linked to a General Ledger posting.

521 Depreciation This Year Transfer In

Definition

The value of depreciation for the current year accumulated in an asset being transferred from one analysis code to another.

Generated By

Change to any asset analysis code that is linked to a GL posting for which this transaction has been set up in the Structured GL Accounts option.

General Ledger Posting

Debit: New code depreciation balance for this year (P&L).

Credit: Asset control account (P&L).

522 Depreciation Prior Years Transfer In

Definition

The value of depreciation for prior years in an asset being transferred from one analysis code to another.

Generated By

Change to any analysis code that is linked to a GL posting for which this transaction is set up in Structured GL Accounts.

General Ledger Posting

This transaction would not be linked to a General Ledger posting.

523 Transferred In Depreciation Year End Roll

Definition

The value of depreciation associated with a transferred asset that is to be transferred from this year's account to prior year accumulated depreciation.

Generated By

Year-end roll over when the system detects that the first period of the new year is about to be opened.

General Ledger Posting

Debit: This year depreciation account (B/S).

Credit: Accumulated depreciation account (B/S).

524 Depreciation Prior Years Transfer In Year-End

Definition

The value of depreciation from prior years associated with a transferred asset.

Generated By

Year-end roll over.

General Ledger Posting

This transaction would not be linked to a General Ledger posting.

Asset Maintenance

The facilities for selecting assets for maintenance processing are similar to those provided for enquiries.

Having selected an asset or a group of assets, you can choose up to seven categories of maintenance activity.



Select Asset Maintenance to see the first Asset Maintenance Selection screen.

```

FA100          F8 - Fixed Assets V3 Company - F8          User FAF8          27/10/95
                                                    9:59:17

Asset Maintenance Selection

Enter : Asset .....? A1001          Maintain Dependents ... @
      Based on .....?                In Company .....

or : Select from :
      Analysis Type .? 
      Code .....?                to 
                                   to 
      and from
      Analysis Type .? 
      Code .....?                to 
                                   to 

F3=Exit  F4=Prompt

05-33    S2    MW    KS    IM    II    EDN400A    PED169S1
  
```

Fields:

Asset

Type in asset number.

Maintain Dependents

1 - the chosen asset is a parent asset and its dependants are also to be maintained.

Based On

If the asset to be maintained is a new asset, it may be based on another asset in another company.



Tip: Where skeleton assets have been set up in company '##', all you have to do is base the new asset on the skeleton asset and change or add a few fields.

In Company

Enter the based on assets company code.

Analysis Type

Enter a valid analysis type.

You can use a 'From' and 'To' code to select a range of codes which may be supplemented with another range. A second analysis type code with up to two more ranges of analysis detail codes can be used in conjunction with the first set.



Note that in defining a range of detail codes, if the 'From' position is left blank, the selection will be made of all codes up to the 'To' code.

If the 'To' position is left blank, the selection will be of all codes from the first to the end of the list.

Code

Enter an analysis detail code.



Press **Enter**. Assets which satisfy the selection criteria are displayed on the second Asset Maintenance Selection screen.

Asset Maintenance Selection Screen 2

Assets which satisfy the selection criteria you entered on the first Asset Maintenance Selection screen are displayed here.

FA100	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 10:00:09
Asset Maintenance Selection			
Selected from : Analysis Type ATP			
Code VEH1	to VEH1	&	to
Code	and : Analysis Type	&	to
Sel Asset Description Type Code Type Code			
1 A1001	Saab 900i	ATP VEH1	
1 C1001	Vauxhall Vectra 2.0	ATP VEH1	
1 C1002	Vauxhall Omega 2.0	ATP VEH1	
- C1002X	Car Radio (Panasonic	ATP VEH1	
- C1003	Ford Mondeo	ATP VEH1	
- C1004	BMW 3.18i saloon	ATP VEH1	
- C1004X	Blaupunkt radio	ATP VEH1	
F3=Exit F12=Previous			
12-02	SA	MW KS IM II	EDN400A PED169S1

Fields:

Sele(ect)

From the list displayed, select assets for amendment by typing 1 against each required asset. If several are selected, the system will work through the list in sequence before returning to this screen.



Note: When selecting from a list, dependants must be selected individually.



When you have made your selection, press **Enter** to see the third Asset Maintenance Selection screen.

Asset Maintenance Selection Screen 3

This screen displays the first of the assets you chose on the second selection screen. Below the asset name are listed the various elements available for maintenance for that particular asset.

If you are amending an asset, all books held against this asset are displayed. Roll to see more. For a new asset, the books required must be entered.

No maintenance is allowed on assets that have already been disposed of.

FA100	F0 - Fixed Assets V3 Company - F0	User FAF0	27/10/95
Asset Maintenance Selection		15:10:20	
Asset ... A1001		Vauxhall Vectra 2.0	
Parent ..			
Maintenance Requirements :			
Base details	1	(0/1)	
Analysis types	1	(0/1)	
Notepads	0	(0/1)	Types...? A01
Financial details ..	1	(0/1)	
External funding ...	0	(0/1)	
Lease details	0	(0/1)	
Dep'n Books...?	Value	Reval'n	Journal
D01	1	0	0
---	0	0	0
---	0	0	0
Next Maint...?		Book...?	Note...?
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip			
11-29	SE	MW	KS IM II EDN400A PED169S1

Fields:

Maintenance Requirements

Enter 1 against each element you wish to maintain. The choice of what is offered is determined by settings in the company profile and, to a certain extent, settings in the various book profiles. It also depends on whether you are working in the advanced or base version of Fixed Assets.



Warning: If a setting has 0 beside it on the company profile, it will not appear at all.

If this is a new asset, base details must be entered first.

List any notepad types which you want to amend.

The depreciation book must exist if revaluation or depreciation journals are to be used.

Next Maint

The sequence originally selected in the maintenance procedure selection screen can be interrupted at any time from any maintenance screen by inserting an alternative maintenance procedure number in the 'Next Maint' field. Type in any valid maintenance procedure number.

Book

Type in a valid book code if required.

Note

Type in a valid notepad type, if required.



The procedures are displayed on the procedure selection screen in the sequence in which they are carried out. This of course corresponds with the sequence of next maintenance types (NXTM) which are those codes identifying these procedures.

The procedures are:

- Base asset details
- Analysis codes
- Notepad records (if there are several, each is processed in turn)
- Financial details
- External funding
- Lease details
- Depreciation books. If there are several books, the data elements for each book are processed in turn, followed by the elements for the next book
 - value
 - revaluation
 - journal



Press **Enter** to see the Basic Details screen.

Base Details Screen

This screen is displayed if:

- You have selected this screen for the asset you are amending.
- You are setting up a new asset. This screen is compulsory in this case, as all assets must have some basic details.

FA101	F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 10:17:56
Asset Base Details Maintenance				
Doc.Date	27/10/95	Period	9511	Ref..... 00000135 Reason?
Asset.....	A1001	Desc.....		
Parent Asset..		Desc.....	Saab 900i	
Reference.....		Desc.....		
Supplier No..?		Cmpy	Supplier Name. FLEETCARS, WORCESTER	
Model.....	SAAB 900I	Serial No.....	123/789/A/2FA	
Manufacturer..	SAAB	Quantity.....		
Location.....	Customer Services, Birmingham		U.O.M.....?	
Date Acquired.	1/11/95	Commissioned	1/11/95	Warranty Expires..... 0/00/00
Prim Notepad..?	A01	Retired Date.....	0/00/00	
Text.....	This vehicle was acquired after use as a demonstrator. 0/00/00			
	A thorough service was promised. Check! 0/00/00			
Anal.? ATP Asset Type	VEH1	Company Cars		
Types COS Cost Centre	010	Sales Department		
LOC Location	BHAM	Birmingham		
Next Maint..?	105	Analysis Codes	Book..?	Note..?
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip				
16-51	SA	MW	KS	IM II EDN400A PED169S1

Fields:

Doc Date

Document date, which defaults to today's date.

Period

This defaults to the current Fixed Assets period in the format YYP.

Transactions can be posted to an earlier period but transactions generated will be posted, in the General Ledger, to the Fixed Assets current period or the GL current period, whichever is the later.

Period numbers can be different in each system.

Reason

This is an optional field. If a reason code is used and entered, it is validated against the reason codes set up in the system reference codes under 'REAS'.

Desc

The description is displayed if the reason code is entered. If no reason code is entered, the description can optionally be entered. If a reason code has been entered, the description can be entered to overwrite the generated description.

Asset

The number of the asset being maintained.

Desc

The description of the asset in free-form text.

Parent Asset

Enter the parent asset number for the dependent asset you are maintaining.

The parent asset must already exist and not itself be a dependant.

The asset being maintained must not be a parent.

This asset's books must also exist for the parent asset. None of this asset's books must "Include Dependants".

If the asset being maintained is a dependant of another asset, that other asset's number is displayed here.

Desc

If a parent asset is quoted, upon pressing Enter the system will display the description of the parent asset.

Reference

As required.

Supplier No.

If the application is linked to Accounts Payable, a supplier can be entered here, otherwise leave blank.

Cmpy

Enter the Accounts Payable company of the supplier entered.

Supplier Name

If Accounts Payable is linked and you have entered a supplier and company, then on pressing Enter the supplier name is displayed. If Accounts Payable is not linked, the supplier name can be entered.

Model

As required

Serial No

As required

Manufacturer

As required

Quantity

An optional field. Decimal quantities are possible.

Location

Enter as required.

UOM

Unit of measure. This field is optional, but if entered, must have been set up on the system reference code file under analysis type 'AUOM' - asset unit of measure.

Date Acquired

The field defaults to document date. An earlier or later date can be entered. The format of the date is DDPYY.

Commissioned

The date commissioned is an optional field. It defaults to the date acquired and must not be earlier than this date. It is keyed in the format DDPYY.

Warranty Expires

An optional field of the format DDMMYY, which if used, must not be before the date commissioned.

Prim Notepad

Primary notepad. The notepad type against which additional text is held.

Retired Date

Enter as required.

Text

Up to two lines of additional text can be entered. For each line the date it was created or amended, is displayed.

Anal Types

Analysis types. Up to three analysis type codes can be entered. The prompts are set up on the company profile, and can be changed depending on the setting there. The analysis codes themselves must be already set up on the systems reference codes under the code 'ANTY' - analysis code list.

If you wish to transfer an asset, you can change any of the codes here. The appropriate transactions will be posted to the General Ledger, taking the asset value from the former location and adding it to the current one.

Next Maint

The sequence originally selected in the maintenance procedure selection screen can be interrupted at any time from any maintenance screen by inserting an alternative maintenance procedure number in the 'Next Maint' field. Type in any valid maintenance procedure number.

Book

Type in a valid book code if required.

Note

Type in a valid notepad type, if required.

Transactions

300 Book value transactions can be generated if a parent asset number is removed or added and if the parent book value includes dependants.



Press **Enter**. The system proceeds to the next maintenance procedure as defined by your entries to the third selection screen.

Asset Analysis Codes Maintenance Screen

This screen is displayed if you selected it on the third selection screen.

Although analysis types and analysis detail codes can be maintained on the Basic Details screen, they can only be changed. This screen allows addition and deletion. The existing analysis codes are highlighted.

FA105		F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 10:24:00
Asset Analysis Codes Maintenance					
Doc.Date 27/10/95		Period 9511		Reference.... 00000136	Reason? ____
Asset..... A1001		Desc.....		Saab 900i	
Parent Asset...		Desc.....			
<-----Analysis Type----->			<-----Analysis Code----->		
ATP Asset Type			VEH1 Company Cars		
COS Cost Centre			010 Sales Department		
LOC Location			BHAM Birmingham		
MGR Manager			PER Jim Hardison - Perso		
Amendment Type.. 0 (0=Add, 1=Change, 2=Remove)					
Analysis Type..? ____			Analysis Code..? ____		
Next Maint..? 110 Financial Details			Book..? ____		Note..? ____
F3=Exit F4=Prompt F5=Refresh F8=Update			F12=Previous F15=Skip		
04-11			MW KS IM II EDN400A PED169S1		

Fields:

Amendment Type

0 - A new analysis type code is to be added.

1 - An analysis type is to be changed.

2 - An analysis type is to be deleted.

Analysis Type

Select the code required.

Analysis Code

Select the detail code required.

Next Maint

The sequence originally selected in the maintenance procedure selection screen can be interrupted at any time from any maintenance screen by inserting an alternative maintenance procedure number in the 'Next Maint' field. Enter any valid maintenance procedure number.

Book

Type in a valid book code if required.

Note

Type in a valid notepad type, if required.



Press **F8** to update.

Asset Notepad Maintenance Screen

This screen is displayed if you selected it on the third selection screen.

Space for the entry of free format text is provided only within the advanced version of Fixed Assets. The text can be managed and scanned by means of change dates which are activated each time a line is created or changed.

FA106		F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 10:50:57
Asset Notepad Maintenance					
Doc.Date	27/10/95	Period	9511	Ref.....	00000130 Reason.....? ____
		Desc.....			
Asset.....	A1001	Desc.....		Saab 900i	
Notepad type. A01 Acquisition Notes					
Line	Text....	Chg Date			
1	This vehicle was acquired after use as a demonstrator.	27/10/95			
2	A thorough service was promised. Check!	27/10/95			
3		0/00/00			
4		0/00/00			
5		0/00/00			
6		0/00/00			
7		0/00/00			
8		0/00/00 +			
Position to Line No.. ____@		Insert.. ____@ lines after line.. ____@			
		Delete.. ____@ lines from line... ____@			
Scan Date.. 0/00/00		& Operand. (>, <, =)			
Next Maint...? 110 Financial Details		Book...? ____		Note...? ____	
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous F15=Skip F16=Scan					
09-07 SA MW KS IM II EDN400A PED169S1					

Fields:

Doc. Date

The document date of the transaction header is shown.

Period

The period of the transaction header is shown.

Ref

The reference code of the transaction header is shown.

Reason

The reason code entered for the transaction header is shown.

Desc

The description of the transaction header is shown.

Notepad Type

The code shown is the code entered into the asset maintenance selection screen. Text lines created under this type code are displayed.

Narrative Lines

Up to 9999 lines are allowed. Roll keys can be used to display the next or previous pages. Further maintenance facilities are provided by the F16=Scan functions.

Position Line No

Enter a line number. On pressing Enter the narrative display starts at the nominated line number.

Insert

You can insert any number of lines after line number. If x is 0 then any lines inserted will be positioned at the front of the text.

Delete

You can delete any number of lines starting from (and including) the 'from' line quoted.

Scan Date

The scan date is a marker date which when used with the operators > < = (greater than, less then, equal to) finds the next line to the date.



Press **Enter** then press **F8** to update.

Asset Financial Detail Maintenance Screen

This screen is displayed if you selected it on the third selection screen.

Financial details contain the acquisition data, expected life and residual value information.

Basic details must already exist for the asset.

The top two lines contain the header information, the third and fourth lines contain the asset number, its description and the parent asset reference, if relevant.

FA110	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 10:51:37
Asset Financial Detail Maintenance			
Doc.Date . 27/10/95	Period ... 9511	Ref 00000139	Reason? ____
Asset A1001		Desc	
Parent Asset		Desc Saab 900i	
Cost Book? CST		Cost Book	
Asset Cost	15550.00	Historic Cost	.00
Currency cost (memo)	.00	Currency Code (memo)	____
Capitalisation Date. 1/11/95	Or Capitalisation Period. 9511		
Life (periods) 0	Or Retirement Period 0000		
Residual Value	6000	Or Residual Percentage	.00 %
Replacement Value ..	15550.00	Valuation Date	26/10/95
Disposal Date	311098 (Planned)		
Next Maint...? 115 Depreciation Book		Book...? 001	Note...? ____
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip			
21-16	SA	MW	KS IM II EDN400A PED169S1

Fields:

Cost Book

Enter the book number used to generate asset acquisition transactions. If the field is left blank, no postings are made to the General Ledger.



Note: Even if the field is entered, the structured General Ledger accounts must have been set up.

Asset Cost

The cost of the asset.

Historic Cost

This field displays the asset cost as at the end of the previous year. It cannot be amended.

Currency Cost

The cost of the asset in the currency in which it was (memo) purchased can be recorded here as a memorandum value.

Currency Code

The code of the currency used in the currency cost (memo) field. The code is not validated.

Capitalisation Period

This date defaults to the commissioned date on the base period details record but can be changed. If the date is not entered, it is calculated by the system from the capitalisation period. The date can be left blank. If used it should be covered by the calendar.

Life (Periods)

The expected useful life in periods (months) from the capitalisation period.

Retirement Period

Provided the asset life is entered, the retirement period is calculated and displayed. If you change this, the 'Life (Periods)' value is recalculated accordingly. The period is in the form YYPP.

Residual Value

The expected value of the asset at the end of its useful life. This value can be used in the depreciation calculation to reduce the asset cost to be depreciated, if the book being used for depreciation has the 'Depreciate on net' indicator set to 1.

Residual %

The percentage can be entered if the residual value is not entered. The system then calculates and displays the residual value. If either field is entered the system calculates and displays the other field.

Replacement Value

The expected cost of replacing the asset. It defaults to the initial asset cost, but is not changed if the asset cost is changed.

Valuation Date

This is the date on which the replacement value was assessed. If the replacement value takes in the initial cost, the replacement date is set to the document date. If another date is required, it must be entered.

Disposal Date

The date on which it is expected or planned to dispose of the asset. It must be greater than the capitalisation date.



Note: Dates need to be within the period financial calendar. This should be set up to cover a reasonable period of time. It can be set up for company '###' so that it is available to all companies.

Transactions

If the asset has a parent, the parent values are automatically updated by the value of this amendment. If the asset cost or replacement value has been amended, the book value for each book for this asset may be recalculated.

Revaluation records are not affected by a change in asset cost, but the revaluation reserve may be.

Cost book transactions:

- 002 Asset additions. If this is a changed asset cost, only the net change value is posted.
- 909 Replacement cost. For a new asset, this will be the same as transaction 002.
- 905 Residual value. If a residual value has been entered, this transaction is generated.

Depreciation book transactions:

See Asset Depreciation Book Screen topic to see more details of these transactions.

For a new asset without a residual value with a depreciation book, the following transactions are created:

- 002 Asset additions.
- 909 Replacement cost.

For an asset whose value is changed, the following transactions are created:

- 002 Asset additions.
- 009 Replenishment reserve
- 909 Replacement cost.

Asset External Funding Maintenance Screen

Funding can reduce the value to be depreciated. It can also affect the valuation of the asset.

Funding can also apply to a group of assets and thus be difficult to apportion to each one. If funding, in the form of a grant does not affect the book value of an asset nor its depreciation, it can be created as an asset in its own right.

If funding does affect depreciation and value for a group of assets, it must be applied to the whole project, to the parent asset. The effect of an external grant must be incorporated in the parent valuation. The depreciation book used must be one that includes dependants.

External Funding is selected from the maintenance procedures as part of asset maintenance selection



Select Asset Maintenance, enter the asset number and press **Enter**.

Select the maintenance procedure external funding by typing 1 against it, and press **Enter**. The screen displays the transaction header, the asset and its description.

FA112	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:02:57
Asset External Funding Maintenance			
Doc.Date 27/10/95	Period ... 9511	Ref 00000142	Reason? ____
Asset B101	Desc Godiva Tower and Warehouse		
Parent Asset	Desc		
Total Funding 150000.00			
of this 120000.00		reduces the value of the asset	
leaving 30000.00		not capitalised (revenue)	
Next Maint.? ____		Book? ____ Note? ____	
F3=Exit	F4=Prompt	F5=Refresh	F12=Previous
F15=Skip			
04-11	SF	MW	KS
		IM	II
		EDN400A	PED169S1

Fields:

Total Funding

The value of the grant. Type in the capital portion of the grant by which the value of the asset is reduced.

Of This...

The balancing portion of the grant which is not included in the reduction of capital value shown here.

Leaving

The difference between the above two values.



Note: The capital portion of the grant must not be larger than the grant itself, nor larger than the asset cost.

Transactions



Note that before completing the external funding maintenance procedure you may need to check the depreciation book to see if it includes an indicator to incorporate grants before depreciation.

After returning to the menu, the system will recalculate balance values and recalculate book values for each book attached to this asset.

Transactions from the cost book will be:

- 005 External funding. Asset capital value offset.
- 006 External funding. Revenue contribution only.

Also:

- 300 Book value. This value is reduced by external funding and takes the same value as 005.

Lease Details Screen

Leased assets, while not subject to depreciation charges, are nevertheless part of the Fixed Assets Register and incur periodic charges in a similar manner to owned assets. The system allows you to record monthly payments, number of payments to make and other details relating to the lessor.

Maintenance Prerequisites

This facility is only available in the advanced version of the system. The base asset record and the financial details record must already exist. The procedure is selected from the asset maintenance procedure selection screen.

The transaction header, asset and description and, if relevant, parent asset details, are displayed at the top of the screen.

FA113	F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 11:03:35
Lease Details				
Doc.date 27/10/95	Period.. 9511	Reference... 00000142	Reason? ____	
		Description. _____		
Asset code..... B003	Description. Guardian House Offices, M'ter			
Parent asset....	Description. _____			
Leaser reference AB/00098	Leaser..... MC Developments			
Postings required? 1 (0=No/1=Yes)				
Periodic payment..	24000.00	Periods between payments..... 1		
Interest payable..	240000.00	First payment period..... 9510		
Number of payments to make....	60	Last payment period..... 9510		
Number of payments made.....	1			
Interest Payments:-		Capital Payments:-		
Year to date.....	7868.85	Year to date....	16131.15	
Previous year....	.00	Previous year...	.00	
Next maint.? ____		Book? ____ Note? ____		
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip				
04-11 82 MW KS IM II EDN400A PED169S1				

Fields:

Leaser Reference

The field can be filled as required with the contract reference number, or other identifying data for the person or company who is granting the lease.

Leaser

The name of the person / company who is granting the lease.

Postings Required

1 - lease postings are to be calculated for this asset.

0 - postings are not required.

Periodic Payments

Enter the value of the periodic payments to be made.

Interest Payable

Enter the total amount of interest payable over the life of the asset.

Periods Between Payments

Enter the number of periods between each payment e.g. quarterly payments would therefore require a 3 in this field.

Number Of Payments To Make

Enter the total number of payments that are to be made over the life of the lease.

First Payment Period

Type in the first period on which a payment needs to be made. The period must not be in a prior year.



The following fields display information which cannot be modified.

Number Of Payments Made

The system maintains this figure.

Last Payment Period

This is calculated by the system.

Interest Payments And Capital Payments

These figures are maintained by the system for both the current year to date and if sufficient information has accumulated, for the previous year.

Transactions

A complete set of transactions exists for leased assets. These can, if required, be linked through the cost book to General Ledger accounts.



Note: Only the cost book is involved in leased asset processing.

- 030 Periodic payment. Created if there is a change in the periodic payment value.

- 037 Total interest payable. This is defined as the periodic payment multiplied by the number of payments to be made, minus the total interest. Where the figure has changed this transaction will reflect the difference.

Asset Revaluation Screen

Assets can be revalued at any time, either by management decision or by using index linking.

Like other maintenance facilities, the procedure is accessed from the asset maintenance procedure selection screen and from a financial book which must already exist.



Note: If the book value 'includes dependants' then the original cost includes dependent costs and subsequent revaluations must apply at parent level.

The screen displays mostly the background data to the revaluation, which cannot be amended.

The top two lines are the transaction header. The next three lines contain the asset and its description, the parent asset and its description (if relevant), and the book and its description.



Note: The book is selected from the asset maintenance procedure selection screen.

FA120	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:04:34
Asset Revaluation			
Doc. Date.....	27/10/95	Period 9511	Ref..... 00000143 Reason.....? ____
Asset.....	B001	Desc.....	JBA House, Birmingham
Parent Asset..		Desc.....	
Book.....	D01	Desc.....	Deprecn. Str.line Annual %
Valn Method...	100 Valuation at asset cost	Total cost	1000000.00
Valn Index....		Book value	1000000.00
Current Index.		Book includes depnts(0/1)	0
No. of Revals.	0		
Original Cost.		Date	Period
Last Used.....		Date	Period
Current.....	1500000		
Next Maint..?	____	Book..?	____ Note..?
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip			
21-16	SE	MW	KS IM II EDN400A PED169S1

Fields:

Valn Method

The valuation method is set up within the chosen book profile.

Valn Index

The index is displayed from the book profile. This field is not displayed if the book concerned has no valuation index.

Current Index

This is the index for the current period from the valuation index file.

Total Cost

The asset cost from the financial details record.

Book Value

This figure is displayed from the asset depreciation Book record

Book Includes Depnts (0/1)

This is defined on the book profile. A 1 indicates that the book includes dependants.

No Of Revals

The number of revaluations is displayed and is automatically incremented by 1 for each accepted transaction.

Original Cost

The original cost at the time of the first revaluation. A change in the cost will not affect this value.

Date

The date of the first revaluation.



Note: If this is the first revaluation, the original and latest date are blank.

Period

The period of the first revaluation.

Index No

The index number of the first revaluation (if indexed).

Last Used

The most recent valuation.

Date

The date of the most recent valuation.



Note: If this is the first revaluation, the original and latest date are blank.

Period

The period of the most recent valuation.

Index No

The index number of the most recent valuation (if indexed).

New Calculated

If the valuation method is indexed, the current indexed value is calculated and displayed. If not, this field is not displayed.

Current

Type in the new management valuation for this asset.

This is the only field relating to revaluation on this screen that can be maintained.

Indexed Revaluation

If the asset is revalued according to a revaluation index, the newly calculated field is displayed. You can override the calculated value.

Override Value

Enter the override value required.

Override Period

Alternatively you may choose another period from the index on which recalculation of the indexed value is to be based.

If this is entered as well as a value, the override value is ignored.



Note: If this is the first revaluation, the original and latest date are blank.

If the period number is outside the period range of the index and the required period is:

- before the first period; the first period in the index is used
- after the last period; the last period is used.

Transactions

Upon successful completion of maintenance, the last used date is set to the document date, the period is set to the transaction or override period, the number of revaluations is increased by 1 and in the case of indexed revaluations, the period's index is added into the record.

Transaction values are created for each book for which there has been a change in asset value.

300 Book value. Change in asset value.

310 Revaluation reserve. New revaluation minus previous revaluation.



Press **Enter** to display the recalculated, indexed value. The value and period can be re-amended if necessary. Press **F8** to update the transaction.

Asset Depreciation Book Screen

A financial book determines how an asset is to be valued and how it is to be depreciated. Each book profile describes one of these views.

An asset may have attached to it

- No book
- One book (which is all that is allowed in the basic version of the system)
- Several books (advanced version)

For most users of the advanced version, each asset will have just the one depreciation book which will probably be for valuation at asset cost and depreciation on a straight line annual %. If however an asset is revalued, you may want to continue the previous depreciation but may also want to post depreciation by a different method based on the revalued value even though such transactions that are generated from it are posted to memorandum accounts.

For the convenience of use, a number of book profiles can be established from which you will select one, at this stage of asset maintenance, to attach to the asset and from which the correct depreciation calculations will be made. The act of attaching a book to an asset fixes the following data:

- the valuation method
- whether depreciation is to be on the gross value of the asset or on the value net of estimated sales value.
- whether the value of any external funding is to be deducted from the asset cost
- the valuation index to be used for revaluation calculations

You, however, can still change from what is held on the book profile

- the depreciation method
- the depreciation rate

If the asset being maintained has a parent, the depreciation book must have previously been created for the parent. If the depreciation book used for the parent includes dependent assets, the system will not allow the book to be attached to the dependant.

The transaction / document header details are displayed followed by the asset and its description, the parent reference (if any) and its description, and book number and its description. The asset book value and "include dependants" indicator are shown. None of the above fields (apart from the header details) can be amended.

FA115		F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 10:52:36
Asset Depreciation Book					
Doc.Date .. 27/10/95		Period ... 9511	Ref 00000140	Reason? ____	
Asset A1001		Desc ... Saab 900i			
Parent Asset		Desc ...			
Book 001		Desc ... Deprecn. Str.line Annual %			
Book Value 15550.00		Include Dependents .. 0 0/1			
Depreciate 1 0/1		Initial Deprn 1500		Max. Per Period 15550.00	
Minimum Asset Value. 3000		OR Start Date 1/11/95		Period Count 0	
Start Period 9511		OR End Date 0/00/00		Latest Period Deprn . 0	
Depreciation Life .. 0		1st Year Dep Method? & Rate		& Rate 20.00	
End Period 0000		Deprecn Method 001 Str.Line Annual Percentage			
Next Period 0000		Next Maint..? ____ Book..? ____ Note..? ____			
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Skip					
18-23 SF MW KS IM II EDN400A PED169S1					

Fields:**Depreciate**

0 - The asset is not to be included in the period depreciation calculations.

1 - It is to be depreciated.

Initial Deprn

The value to be charged to depreciation in the first period. If left blank, the system will calculate the value in accordance with the chosen method and rate.

This field can only be used before the first calculated depreciation. The field cannot be negative.

Minimum Asset Value

The written down or depreciated value below which no further depreciation is allowed in any period. This defaults to the initial asset book value and should not be greater than this.

Start Period

The start period is related to the start date, and either one or both can be entered. If one is entered, the other is calculated. The period is in the form YYPP.

If the start date is used and is not the beginning of a period, the initial depreciation field can also be used to input the appropriate value for the first part period. Once a period's depreciation has taken place these fields cannot be amended.

If the start period is less than the current Fixed Assets period, but in the current financial year, depreciation is calculated up to the current Fixed Assets period. This causes a financial period depreciation transaction to be created for each prior period.

If the start period is in a previous year an error message is produced and no depreciation is calculated.

Start Date

If the start date (which may have originally been calculated from the start period) is not the first of the month and a date elsewhere in the month has been inserted, the calculated value for the first period is reduced proportionately to the balance of days left in the period.

Depreciation Life

The number of periods over which depreciation is calculated. This field can be left blank if depreciation is continuous. If entered, the end period and end date are calculated from the depreciation life field. This field must be entered if the depreciation method chosen is 004.

Period Count

The number of periods for which depreciation calculations have been made. This field cannot be amended.

End Period End Date

Either one or both or neither may be entered. The entry of one allows the system to calculate the other from the financial calendar. If entered, period depreciation ceases when this period is reached. The period format is YYPP, the date format DDMMYY.

Next Period

The field (format YYPP) specifies the next period to be used for period depreciation. It is normally automatically maintained by the period depreciation procedure but can be amended to a later period. It can be used only after period depreciation has started.

Latest Period

This is a non-maintainable field which displays the latest period for which depreciation has been calculated.

1st Year Dep Method & Rate

A different depreciation method and / or rate can be used for the first year compared with that used thereafter. If it is not required, leave the fields blank.

Deprn Method

The depreciation method and / or rate that initially appear in these & rate fields are those from the book profile. They can be changed by selecting any valid method from the application defined list found under the system reference code DEPM. Rate can be a % or a value depending on the method chosen.



Press **Enter**.

From any screen press **F3** to complete the session. It is at this point that transactions are generated and General Ledger postings are made.

Depreciation Calculation

A depreciation calculation is made for each asset selected, based on the depreciation method and rate or other depreciation data.

There are conditions:

- Any change affecting depreciation, such as method; rate; revaluation, takes place at the next calculation. It cannot be retrospective.
- An asset cannot be depreciated if:
 - its written down value is below the 'minimum' value
 - the current period is beyond its 'End Period' or 'End Date'. If the 'End Date' is in the middle of a period, the final depreciation calculation is reduced proportionately.
- No adjustment is made for a disposal month.

After calculations have been made, the cycle count is increased by 1 and the 'Latest Period Deprn' is set equal to the current period.

The depreciation year-to-date figure is increased by the depreciation calculated and the cycle count is increased by 1.

Depreciation Methods

Straight Line Depreciation

The key characteristic of these methods is that, unless any of the factors affecting depreciation is changed, the same depreciation value is charged throughout the asset's life. Depreciation is based on book value alone - depreciation to date is not taken into account.

- 001 Straight line annual percentage divided by number of periods in year.
- 002 Straight line period value
- 003 Straight line annual value where the value for the period is the annual value divided by the number of periods in the year.

Equal Periods over Asset Life

The asset is written down to its minimum value over its depreciation life. Its main feature is that if the book value or depreciation life changes, the depreciation charge is adjusted.

- 004 Straight line asset life where the book value or value to be depreciated is divided by the number of periods of asset life to obtain the period value.

Straight Line Depreciation Proportionate to Days in Period

These methods calculate the annual 'straight line' depreciation value, and spread it across the year proportionately to the days in the period.

- 011 Straight line annual percentage of the book value or value to be depreciated where the percentage is proportionate to the working days (or calendar days) in the period.

For example: $\text{Period Value} = \text{Asset Value} \times \text{Annual \%} \times \frac{\text{Days in Period}}{\text{Days in Year}}$

- 012 Straight line annual value as a proportion of the working days in the period.

e.g.: $\text{Period Value} = \text{Annual Deprn. Value} \times \frac{\text{Days in Period}}{\text{Days in year}}$

The number of days in the period could be working days or even calendar days. This is controlled by the data keyed into the Financial Calendar.

Reducing Balance Depreciation

These methods apply an annual percentage to the book value of the asset, less depreciation to date (total or prior year only). The 'straight' method uses the annual percentage divided by the accounting periods in the year. The compound method reflects the changing values during the year.

- 101 Reducing balance with a simple annual percentage
- e.g.: $\text{Period Value} = \text{Current Written Down Asset Value} \times \text{Annual \% Rate} / \text{Periods per year}$
- 102 Reducing Balance with compound annual percentage.
- e.g.: $\text{Period Value} = \text{Current Written Down Asset Value} \times \text{Compound \% Rate} / \text{Periods per year}$

Reducing Balance Proportionate to Days in Period

These methods calculate 'reducing balance' depreciation, and then apportion it to periods proportionately to days in the period.

- 111 Reducing balance annual percentage proportionate to working days in year, (of method 011).
- 112 Reducing balance annual percentage compound proportionate to working days in year, (of method 012).

Reducing Balance Method with a Return to Straight Line

This depreciation method is a variant of the double declining method, the variance being that it changes to the straight line method in the final two years of the asset's life.

The asset's life is based on whole years, so if an asset is acquired part way through a year, with a useful life of 5 years, the asset must be written off by the end of the 5th year. Normally the asset would be written off part way through the 6th year, taking into account the fact that the asset started being depreciated part way through the first year.

- 433 The standard 200% (double declining) depreciation rate.
- 444 150% depreciation rate.
- 544 250% depreciation rate.
- 644 300% depreciation rate.

Straight Line Annual Percentage by Actual Days

- 933 This method will charge depreciation from the implementation date to the end of the current period.

Dérogatoire Depreciation

It is sometimes a legal requirement in France to post the difference between straight line depreciation charge and the double declining depreciation charge to a specific account, which varies depending on whether the posting is a credit or a

debit. This depreciation method is therefore the net of the straight line depreciation charge and the double declining depreciation charge method.

935 Dérogatoire depreciation at 200%.

936 Dérogatoire depreciation at 150%.

937 Dérogatoire depreciation at 250%.

938 Dérogatoire depreciation at 300%.



The depreciation methods listed above can be grouped in other ways.

- 1 Straight line using an equal number of periods in the year subdivided into methods with:
 - annual percentage
 - period percentage
 - annual value
 - period value
- 2 Straight line depreciation proportionate to working days in period subdivided into methods with:
 - annual percentage
 - annual value
- 3 Reducing balance with equal periods subdivided into:
 - annual percentage, straight
 - annual percentage, compound
- 4 Reducing balance proportionate to working days in period subdivided into:
 - annual percentage, straight
 - annual percentage, compound

Transactions

The book value is calculated based on the first digit of the valuation method code:

- 1 - Asset cost from financial details record
- 2 - Replacement value from financial details record
- 3 - Revaluation value.



Note: For a new asset, which has no revaluation value, the asset cost is used.

The procedure generates the following:

300 Book value.

Review the matrix in the topic 'What Transactions are Generated?' to see the combinations of financial transactions resulting from maintenance procedures, and in particular those resulting from financial details maintenance.

Elementary Asset Maintenance

This procedure provides a means for quickly entering basic asset details, analysis codes, financial details and depreciation details using just one screen.

Additional details relating to those assets can be entered subsequently using the full maintenance facilities (the processing option - Asset Maintenance).

Whether a company makes any or much use of elementary asset maintenance may depend on a number of factors, such as:

- time available for the creation of the asset database
- number of maintenance features required



Select Elementary Asset Maintenance, and press **Enter** to see the first Elementary Asset Maintenance screen with the following selection fields:

Fields:

Asset

Key the asset number.

Book

Key the book number if depreciation book is to be maintained as well as base and financial details.

Based On Asset

Only permissible if a new asset is being entered. The system will search for the asset in the nominated company, provided that the company profile parameters allow the company in question to be used for 'based on' activities.

In Company

Enter nominated company. If this field is left blank, it defaults to the current company.



Press **Enter** to see the second Elementary Asset Maintenance screen.

Elementary Asset Maintenance Screen 2

If the asset cost is amended, the book value for each book for this asset may be recalculated if the book value is based on asset cost.

When the depreciation book is created, the book value is calculated based on the first digit of the valuation method code (BVAL).

- 1 - asset cost, from the financial details
- 2 - replacement value, the financial details
- 3 - valuation



Note: It is not possible to enter a new dependent asset using the Elementary Asset Maintenance option. Amendments, however, are allowed.



Note: As the valuation record has not yet been created, asset cost is used.

Any replacement cost is set to asset cost on creation. It cannot afterwards be changed by the Elementary Asset Maintenance procedure. The financial details from the full Asset Maintenance procedure must be used.

If transactions are to generate postings to the General Ledger, accounts must have been set up in the structured General Ledger accounts facility.

FA140	F8 - Fixed Assets V3 Company - F8	User FAF8	26/10/95
Elementary Asset Maintenance			16:45:22
Transaction Details			
Reference....	00000132	Date..	26/10/95
		Posting Period..	9511
Reason Code.?		Description..	
Asset			
Code.....	A1001	Description..	Saab 900i
Cost.....	15550	Cost Book...?	CST
Date Acquired.....	011195	Location....	Customer Services, Birmingham
Capitalisation Date..			
Depreciation		Required.....	1 (0=No/1=Yes)
Book.....	001 Deprecn. Str.line Annual %	Life in Periods..	0
Method.....?	001 Str.Line Annual Percentage	Start Period.....	9511
Rate.....	20.00	Start Date	
Analysis Types...?			
ATP Asset Type	VEH1		
LOC Location	BHAM		
COS Cost Centre	010		
F3=Exit F4=Prompt F5=Refresh F12=Previous			
21-40	SA	MW	KS IM II EDN400A PED169S1

Fields:

Date

Document date, which defaults to today's date.

Posting Period

This defaults to the current Fixed Assets period in the format YYPP.

Transactions can be posted to an earlier period but transactions generated will be posted, in the General Ledger, to the Fixed Assets current period or the GL current period, whichever is the later.

Period numbers can be different in each system.

Reason Code

This is an optional field. If a reason code is used and entered, it is validated against the reason codes set up in the systems reference codes.

Description

Reason code description is displayed if the reason code is entered. If no reason code is entered, the description can optionally be entered. If a reason code has been entered, the description can be entered to overwrite the generated description.

Code

Enter the asset code.

Description

Enter the description of the asset. The description is free-format.

Cost

Enter the cost of the asset.

Cost Book

Enter the book used to generate the General Ledger asset cost accounts. If the cost book is not entered no values are posted to the General Ledger.

Date Acquired

The date defaults to the document date but can be earlier.

Location

A free-format text field.

Capitalisation Date

This date defaults to the acquisition date, but can be changed. The date must be included within the scope of calendar file.

Required

0 - Period depreciation calculations are not required.

1 - Period depreciation calculations are required.

Book

The depreciation book selected on the Asset Selection screen.

Life In Periods

If the depreciation method entered is 004, this field must be completed with the number of periods (usually months) over which the asset is to be depreciated.

Period depreciation stops when the 'period count' equals depreciation life.

Method

The depreciation method defaults to that set up in the book profile. It can be changed.

The field must contain one of the depreciation methods contained in the systems reference code DEPM.

If the depreciation methods chosen is 004 - asset life, then the 'Life in Periods' field must be completed and the default rate must be deleted.

Start Period

If either this or the start date is entered, the other is calculated.

If both are entered, the date must be within the start period. This enables initial depreciation to be for part of a period. These fields cannot be amended once initial depreciation has taken place.

Rate

The rate to be applied for the method chosen. If a percentage depreciation method is chosen, this is a percentage figure, otherwise enter an amount.

Start Date

If either this or the start period is entered, the other is calculated.

If both are entered, the date must be within the start period. This enables initial depreciation to be for part of a period. These fields cannot be amended once initial depreciation has taken place.

Analysis Types

Up to 3 analysis types can be requested.

The first is mandatory and will normally be the asset type code. This arises out of the analysis code (ANTY) entered into the company profile.

The second and third codes may or may not be mandatory depending on the indicator settings in the company profile.

Transactions

If the asset has a parent, the parent values are amended by the value of this amendment.

The full complement of financial transactions is created as it would be for full asset maintenance.

These are the financial transactions:

- 002 Asset cost
- 009 Replenishment reserve
- 905 Residual value (not on elementary posting)
- 909 Replacement cost
- 300 Book value from the depreciation book



Note: If transaction 009 is posted to the General Ledger, the full asset maintenance procedure should be used to amend the cost of

the asset.

Transactions are posted to the General Ledger only for those financial transactions for which General Ledger accounts have been set up in the Structured GL Accounts option for each book used.



Press **Enter** to validate any entries. The system creates financial records and posts to the system files only when **F3** is pressed.



Once you have completed this procedure, four enquiries enable you to review all aspects of the asset creation process you have undertaken:

- Sessions Enquiry
- Transactions Enquiry
- Elementary Assets Enquiry
- General Ledger Enquiry

Asset Disposal

Asset disposal is achieved by use of this procedure. Once disposed of, an asset cannot be reinstated. The disposal record, however, can be amended.

The disposal of a parent asset also involves the disposal of all the dependent assets. A dependent asset cannot be disposed of by itself. Its parent asset number must first be removed from its record.

The disposal of a proportion of an asset, such as 50% of a collection of VDUs, cannot be achieved unless the asset is first split into multiple records.



Select Asset Disposal and press **Enter**. You will see the first Asset Disposal screen.

Asset Disposal Screen 1

FA136	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:07:22
Asset Disposal			
Enter : Asset? CM002			
Based on? _____		In Company _____	
F3=Exit F4=Prompt			
05-33	SA	MW	KS IM II EDN400A PED169S1

Fields:

Asset

Enter the asset number.

Based On

The asset to be disposed of can be based on another known asset.

In Company

Enter the company in which the based on asset can be found.



Press **Enter** to see the second Asset Disposal screen.

Asset Disposal Screen 2

The transaction header and asset number and description are displayed at the top of the screen. The asset cost, dependent cost total cost together with residual value, deprn residual value and total residual value fields are displayed with their current data. These fields cannot be amended.

FA136	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:09:24
Asset Disposal			
Doc.Date.. 27/10/95	Period.. 9511	Ref 00000147	Reason? ____
Asset Number CM002		Desc Ford Transit Van	
Asset Cost	16750.00	Residual Value	.00
Dependent Cost ..	.00	Deprn Residual Value.	.00
Total Cost	16750.00	Total Residual Value.	.00
Sales Value	12500.00	Currency Value (memo)	.00
Sales Ledger Co..	__	Currency Code (memo).	__
Customer Code ..?	__	Cust. Name	COMMERCIAL AUCTIONS LTD.
Analysis Types .?	__		
ATP Asset Type	VEH2	Commercial Vehicles	
COS Cost Centre	020	Buying Department	
LOC Location	MANC	Manchester	
Disposal Notepad? A99	__		
Text....	Almost new van, surplus to requirements		0/00/00 0/00/00
F3=Exit F4=Prompt F5=Refresh F8=Update F12=Previous Press F8 to confirm disposal, press enter to ignore 19-50 S MW KS IM II EDN400A PED169S1			

Fields:

Doc Date

Enter the document date.

Period

Enter the period.

Reason

Enter the appropriate reason code.

Desc

Enter a description for the document.

Sales Value

Enter the disposal value of the asset. This can be zero.

Currency Value (Memo)

If the sale has been made abroad and you need a memorandum of the sales value in a foreign currency, this can be entered here.

Sales Ledger Co

If Accounts Receivable is linked to Fixed Assets, then enter the linked company here.

Currency Code (Memo)

If the sale has been made abroad and you need a memorandum of the sale in another currency, enter that currency here.

Customer Code

If Accounts Receivable is linked to Fixed Assets then enter the appropriate customer here.

Cust. Name

If you enter the Accounts Receivable company and customer, the system will enter this customer name automatically.

If Accounts Receivable is not linked, leave the company blank, and enter, if required, the customer name into the name field.

Analysis Types

Analysis detail codes corresponding to the analysis types originally set up, are displayed. These can be amended. It is possible that analysis codes on dependent assets may need to be changed before disposing of the asset.

Disposal Notepad

The value of the field defaults to the primary notepad type. It can be changed at this point when a disposal record is created. It may not be changed thereafter.

Text

Up to two lines of additional text can be created and added to the end of the chosen notepad record.

Transactions

Upon completion of the disposal, the asset is updated and a disposal record created.

In the asset base details record, the disposal date is set to the document date for the asset and all its dependants.

An asset disposal record is created for this asset.

A set of transactions is created for the disposed of asset, which, if it is a parent, includes the value of the parent and its dependants.

From the cost book, the following transactions can be created.

- 101 Asset disposal cost. From the GL accounts structure set this would debit the Accounts Payable sale of asset account and credit the balance sheet asset disposals account.
- 105 Capital-external funding. This transaction is created if external funding is involved.
- 109 Replenishment reserve. This transaction negates the replenishment cost.
- 131 Disposal, previous years lease interest. These transactions are initiated only if a lease asset is

disposed of.

- 132 Disposal YTD lease interest. These transactions are initiated only if a lease asset is disposed of.
- 133 Disposal previous years lease capital. These transactions are initiated only if a lease asset is disposed of.
- 134 Disposal YTD lease capital. These transactions are initiated only if a lease asset is disposed of.
- 200 Sales value. This transaction should be linked to the General Ledger so that it debits the balance sheet suspense account and credits the Accounts Payable sale of assets account.

From each depreciation book, the following transactions are created:

- 400 Book value.
- 410 Revaluation reserve. Asset cost-revaluation (if any).
- 421 Depreciation the year for disposed of assets. This transaction would debit the balance sheet depreciation-disposed-of-this-year account, and credit the Accounts Payable sale of assets account.
- 422 Depreciation prior year.

In the context of the structured General Ledger accounts set up for this course, the transactions that will cause postings to be made to the General Ledger are:

- 101 Asset disposal cost.
- 200 Sales value.
- 421 Disposal of depreciation this year.



Press **Enter**, and press **F8** to confirm the disposal.

Asset Journals

This option is used to:

- Adjust depreciation values. This procedure allows you to adjust calculated depreciation. It can be used to fully depreciate the asset. It can be used even if the period depreciation flag is set to 0.
- Lease postings.

The journal can be initiated in two ways:

- Through Asset Maintenance, the selection of a depreciation journal for a particular book.
- By selecting Asset Journals (processing option). Within this option, on the first screen, you can either create a depreciation journal or leased asset journal.

The first screen you see is the Asset Journals screen.

Asset Journals Screen



Select Asset Journals to see the Asset Journals selection screen.

FA150	F8 - Fixed Assets V3 Company - F8	User: FAF8	27/10/95 11:05:25
Asset Journals			
Asset Code....? <u>B002</u>		Book....? <u>D01</u>	
Journal Type... <u>1</u> (0=Leased Asset Journal) (1=Depreciation Journal)			
F3=Exit F4=Prompt 08-18 S MW KS IM II EDN400A PED169S1			

Fields:

Asset Code

Enter the asset as required.

Book

Enter the book as required.

Journal Type

1 - Maintain a depreciation journal.

0 - Maintain a leased asset journal.



Press **Enter**. The Assets Depreciation Journal screen is now displayed.

Assets Depreciation Journal Screen (Option 1)

If you entered 1 in the 'Journal Type' field, then you will see the Assets Depreciation Journal screen.

The transaction header, asset and asset description are displayed at the top of the screen. The depreciation book, its description, together with the latest depreciation period and the minimum asset value are also displayed.

FA126	F8 - Fixed Assets V3 Company - F8	User FAF8	27/10/95 11:05:48
Assets Depreciation Journal			
Doc.Date . 27/10/95	Period 9511	Reference.... 00000144	Reason.....? ____
Asset..... B002	Description.. Kensington House, Birmingham		
Book..... 001	Description.. Deprecn. Str.line Annual %		
Latest Period... 9510	Minimum value .00		
Fully depreciate @ 0 = No, 1 = To minimum value, 2 = To zero			
	Present Values	Amend values to	Amend values by
Book Value.....	120000.00		
Deprn this YTD.....	50000.00	60000	
Deprn previous year.....	600000.00		
Written down value.....	550000.00		
	(Debit)	(Credit)	
General Ledger Accounts..? _____			
F3=Exit F4=Prompt F5=Refresh F12=Previous			
16-63	SE	MW	KS IM II EDN400A PED169S1

Fields:

Fully Depreciate

0 - Not to be fully depreciated. This is the default value.

1 - Depreciate down to minimum value.

2 - Depreciate to zero written down value.



Note: If this indicator is set to 1 or 2 values should not be entered in the Amend Values fields.

Present Values

The present values of the following are displayed:

- Book
- Value
- Depreciation this year to date
- Depreciation previous year
- Written down value

Amend Values To

The depreciation values can be replaced by an absolute alternative value.

Amend Values By

The depreciation values can be increased or decreased by an amount.

- Total depreciation cannot be greater than book value minus minimum value.
- You cannot depreciate below zero or minimum value.
- Depreciation cannot be negative, therefore a negative adjustment cannot be greater than the current value to be depreciated.



Warning: If prior year depreciation is adjusted, a warning message is displayed. No postings should be made to General Ledger accounts for this routine.



Note: An increase in depreciation is entered as a positive value.

General Ledger Accounts

The accounts to be debited and credited may be nominated in these fields if the accounts Generated By the procedure are not to be used. The GL accounts nominated apply only to this one transaction.

Transactions

- 321 This year's depreciation. Created if there is a change in depreciation.
- 322 Prior year depreciation. Created if there is a change in the prior year depreciation.



Press **Enter** .

If you entered this procedure from the Asset Maintenance Selection screen, the system will return you to this screen. If you entered the system from the Asset Journal the system returns you to the Asset Journal Selection screen.

Lease Journals Screen (Option 0)



Select Asset Journals and press **Enter**. You will see the Asset Journals screen. Enter the asset code, and leave the 'Book' field blank. Enter 0 in the 'Journal Type' field.



Note: When creating a lease asset journal, the book must be a cost book.

You will then see the Lease Journals screen. The header, asset and, if relevant, parent asset information is shown at the top of the screen.

FA127		F8 - Fixed Assets V3 Company - F8		User FAF8	27/10/95 11:06:45
Lease Journals					
Doc.date	27/10/95	Period..	9511	Reference....	00000145 Reason.....? ____
		Description...			
Asset.....	B003	Description...		Guardian House Offices, M'ter	
Parent asset....		Description...			
		Present values	Amend values by	Amend values to	
Interest previous year...		.00	.00	.00	
Interest year to date....		7868.85	.00	.00	
Capital previous year....		.00	.00	.00	
Capital year to date.....		16131.15	.00	.00	
General Ledger Accounts		(Debit)	(Credit)		
Interest previous.....?					
Interest year to date...?					
Capital previous year...?					
Capital year to date....?					
F3=Exit F4=Prompt F5=Refresh F12=Previous					
05-11	SR	MW	KS	IM	II EDN400A PED169S1

Fields:

Present Values

The present values for interest and capital for both the year to date and previous year are displayed in the left hand column.

Amend Values By

Any of the four values can be increased or decreased by an amount.

Amend Values To

Any of the four values can be changed to an absolute alternative value.



Note: A negative adjustment cannot be greater than the current values i.e. values cannot be negative.

General Ledger Accounts

Specific General Ledger debit and credit accounts can be entered for each of the four values if required.

These replace the generated accounts. The GL accounts apply only to this one off transaction.

Transactions

Unless the entry of GL accounts has overridden the GL account creation, the following transactions are created.

031 Previous year's interest

032 Lease interest for the year to date

033 Previous year's capital

034 Capital for the year to date



In each transaction the system calculates the value as the new value minus the old value, thus posting the net change in value.



Press **Enter**.