

-
-
-
-
-

Chapter 1

Maintenance



Introduction to Accounts Receivable Maintenance

You can add and edit a company profile in the Accounts Receivable application. The system also provides you with the facility to produce a printout of configured company profiles.

Company Profile Maintenance

Each application requires the configuration of control parameters and master files in order for you to operate it. The most important control information that any application requires is the company profile. Accounts Receivable supports multiple companies. For every company that you want to use you must create a company profile which holds the rules which govern the operation of Accounts Receivable for that company.



Warning: In order to configure the Accounts Receivable module you must ensure that a General Ledger application is installed with a complete Chart of Accounts. The company or companies that you want to use with Accounts Receivable must have corresponding company profiles in the General Ledger.



Note: You cannot maintain a company profile when other users are using the application.



Warning: You should avoid changing existing company profiles once the application is live, as this may corrupt your data. If a change is essential it must be strictly controlled.

Other Maintenance

Before invoices can be sent or payments logged in Accounts Receivable it is first necessary to set up the basic information about customers. This can be done using maintenance options - once the company profile has been set up.

One record is created for each customer, using the Names and Addresses option from the menu. Each record is identified by a unique, user-defined customer account number, and holds such information as the customer address, payment terms, VAT codes, credit limit and General Ledger accounts.

The system also allows the defining of delivery addresses for each customer, and is particularly flexible with regard to the entry of text at customer or item level. Reason codes may also need defining - see the relevant section for more details.

Reports are available on most of the maintenance options.

Creating or Maintaining a Company Profile

1... **2/ASCO**
2...

This procedure is used for both creating and maintaining a company profile.

If you wish to base a new company on an existing company, use the AR utility option Create.

Maintain Company Profile Screen

This screen contains basic company details and defines defaults which are used throughout the application.



Select the company profile option for Accounts Receivable. Enter the code of the company you wish to set up or maintain. Press **Enter** to display the first maintenance screen.

SL005	User ED3	4/03/94 17:30:02
Maintain Company Profile		
Company Code E1		
Company Name E1 Demonstration Company		
General Ledger Active? : 1 (0/1)	General Ledger Company . : E1	
Cash Mgmt Active? . . . : 1 (0/1)	Cash Mgmt Company : E1	
Multi currency? : 1 (0/1)	Default Currency Rate Code PERD ?	
Periods Per Year : 12	Currency Code : GBP	
Posting Period : 0311	Country Code ? GB	
Next Cash Reference . . : 1	Generate Cash Refs? . . . : 1 (0/1)	
Next Adjustment Ref . . : 32	Generate Adjustment Refs? : 1 (0/1)	
Next Invoice Number . . : 1	Overdue analysis periods 1 to 5:	
Next Credit Memo . . . : 1	30 , 60 , 90 , 120 and 150 Days	
Next Transfer Ref . . . : 1 000002	Generate Dunning Ltr Ref?: 1 (0/1)	
Next statement run no. : 5	Prt items on Dunning ltr?: 1 (0/1)	
Revaluation? : 0 (0/1)	Due date o'ride allowed? : 1 (0/1)	
Batch Controls Active?: 1 (0/1)	Maximum adjustments value: 1000.00	
Default Payment Terms : D 30	Default Payment Method . ? CHO	
Purge: No.of Months . . : 6	Purge: No.of Transactions: 0	
Statement print queue : QPRINT	In library : QGPL	
Display Cash First? . . : 1 (0/1)	Immediate/Delayed Updates 1 (1/D)	
Extended Terms ?	Inhibit postings? : 0 (0/1)	
F3=Exit	F4=Prompt	F12=Previous

Fields:

Company Name

If this is the first time this company has been set up in any application, enter the name of the company. (This name will then be given to all other applications for this company).

If a name has previously been given for this company, it is displayed but cannot be changed.

If the Company Name has been changed in Application Manager, you should "maintain" the Accounts Receivable company profile in order to get the amended description onto this application.

General Ledger Active?

Determines whether this ledger is to post transactions automatically to your General Ledger.

- 1 - The link is active
- 2 - The link is not active

General Ledger Company

If the link is active, you must also enter the Company Code of the General Ledger company to which this ledger is to be linked.

Cash Mgmt Active?

This field allows you to activate a link with the Cash Management application. You must activate this link if you are going to operate multiple currencies within Accounts Receivable.

0 - The link is not active.

1 - The link is active.



Note: If '1' the General Ledger link must also be active.

Cash Mgmt Company

If the link is active, enter here the Cash Management company to which you are linked. This need not be the same as the General Ledger company to which you are linked.

If you are linked to both General Ledger and Cash Management, then Accounts Receivable and its linked Cash Management application must link to the same General Ledger.

Multi-Currency?

0 - Postings to be made in base only.

1 - Postings allowed in prime.

Both General Ledger and Cash Management links are mandatory for multi-currency Accounts Receivable.

Default Currency Rate Code

For a multi-currency ledger, enter the rate code most often used to convert transaction currency values into base currency values.

If the code has not previously been created, a window is displayed enabling you to set it up now.

Periods Per Year

The number of periods in the financial year, from 1 to 99. This must be the same as for the General Ledger if the two applications are linked.

Currency Code

If this company is linked to a General Ledger you must enter a currency code which is the same as the base currency of the General Ledger to which you are linked.

If you have not activated the link with a General Ledger then this is a memorandum field only, and you can leave it blank. If you intend to link to a General Ledger at some future date, enter the General Ledger base currency code.



Warning: Once you have used Accounts Receivable, this field cannot be amended.

Posting Period

When adding a new company, enter the opening period for the ledger, using the format YYPP. This is subsequently maintained by the normal period close and open functions.

Once set up, therefore, it should not be necessary to change it, nor is this recommended.

Country Code

Enter the country code for the country in which this application is being used. If you are not sure of the codes you can use the prompt facility.

Next Cash Reference

Each cash transaction posted to Accounts Receivable has a unique reference code for access (enquiry) and audit purposes. These unique references may be entered at the time the transaction is entered, or they may be automatically generated by the application when cash is posted to the customer's account (replaced by Cash Management if it is installed and linked to the company).

If Cash Management is limited, this application will generate the cash reference numbers for each transaction.

Generate Cash Refs

0 - If you want to enter transaction references manually.

1 - The system will automatically generate transaction reference codes starting with the number in the Next Cash Reference field.

Next Adjustment Ref

Each adjustment transaction posted to Accounts Receivable has a unique reference code for access (enquiry) and audit purposes. These unique references may be entered at the time the transaction is entered, or they may be automatically generated by adjustments resulting from cash allocation.

Generate Adjustment Refs

0 - If you want to enter transaction references manually.

1 - The system will automatically generate transaction reference codes starting with the number in the Next Adjustment Ref field.

Next Invoice Number

Each invoice must have a unique reference number for enquiry and audit purposes.

When you post manually to the ledger you must assign a number manually. When Sales Order Processing is linked to the ledger the numbers are automatically assigned.

Next Credit Memo

Each credit note must have a unique reference number for enquiry and audit purposes.

When you post manually to the ledger you must assign a number manually. When Sales Order Processing is linked to the ledger the numbers are automatically assigned.

Overdue Analysis Periods

The ledger allows you to set up 5 overdue periods which are used for enquiry and reporting purposes.

Enter up to 3 digits in each field to indicate the 'number of days overdue' for each of the 5 columns on the overdue payments report. Period 1 is the 'least overdue' and period 5 is the 'most overdue'.

Next Transfer Ref

Each transfer between customer accounts must have a unique reference number for enquiry and audit purposes.

When you transfer a transaction from one customer account to another an audit record is written from account and this is assigned the next transfer reference number available

Generate Dunning Ltr Ref?

0 - Dunning Letter references will not be generated by general ledger.

1 - The system assigns the next sequentially numbered Dunning letter to customers already in receipt of a Dunning letter and whose overdue debt remains uncleared at the time of the next letter run.

Next Statement Run No.

This is usually set to 1, when the application is set up, and is subsequently maintained by the statement print procedure.

The last statement run number is recorded against each account.

Prt Items On Dunning Ltr?

0 - To suppress the printing of item details on Dunning letters.

1 - To include item details for overdue customer accounts on the Dunning letters.

Revaluation

Determines whether or not debtor balances in this company can be revalued by the General Ledger revaluation procedure.

0 - Revaluation not required.

1 - Revaluation is allowed.

Due Date O'ride Allowed ?

Your options are:

0 - and the payment due date calculated for a transaction cannot be changed.

1 - The payment due date derived from the customer's terms can be overridden for a specific invoice and also maintained by the 'Due dates' procedure.

Batch Controls Active?

0 - Accounts Receivable has mandatory session control which automatically sets up traceability of input batches of items. This should not be confused with the optional batch control which will insist that batch values are entered prior to entry of a batch of transactions. On completion of the batch, the batch total will be checked against the value of the items entered and a warning message.

1 - If you wish to use batch controls.

Maximum Adjustments Value

When allocating cash, adjustments may be entered. Enter the maximum value allowed (in Base currency) for one allocation.

This is used when writing off differences using adjustment code AJ. However this may be specified at user level using the GL utility option Field Level Security.

Default Payment Terms

This field is split into three smaller fields which together define default payment terms. Set up your standard payment terms to display as a default at the Customer Name and Address option. You can then change payment terms for individual customers.

First field

This contains a single character code which defines the type of terms to be used. The following codes are valid:

D - Number of days from invoice date.

M - Number of months before payment.

P - Periodic range.

For the D and M codes, leave the second field blank.

For code D you must enter the number of days in the third field in the format DDD. For example, for a payment of 30 days from the receipt of invoice, enter 030.

For codes P and M, the third field contains the month and the day within that month (MDD). For example:

A code of M ____ 210 will generate a payment date of the 10th of the 2nd month following the date of invoice. In this example, an invoice date of 22.04.98 would generate a payment date of 10.06.98.

Second field (for Periodic Range only)

The second field is used with the code P to indicate your periodic range. You are, in effect, redefining the period in which due dates are to be calculated.

Example: Periodic Range

Terms	Payment Method	Spread Factor
P 2019 106	DD	

This example can be explained as:

P = Periodic payments.

20 = the first day of your redefined period.

19 = the last day of your redefined period.

1 = add one month to the end of the redefined period.

06 = make the due date fall on the 6th of the added month.

This table shows 4 example invoices (using the example terms) with calculated due dates.

Invoice Date	Invoice falls in the redefined	Due Date (Add 1 calendar
--------------	--------------------------------	-----------------------------

	current period:	month to the end of the redefined current period)
13.05.98	20.04.98 -19.05.98	06.06.98
20.05.98	20.05.98 -19.06.98	06.07.98
19.06.98	20.05.98 - 19.06.98	06.07.98
20.06.98	20.06.98 - 19.07.98	06.08.98

Third field (Payment date)

Depends on what is entered in the first field:

If D this holds the number of days in the format DDD.

If P or M holds the month and the date in the format MDD.

Examples:

A code of D ____ 030 means that the payment date is 30 days from the invoice date.

A code of M ____ 210 means a payment will be made on the 10th of the second month after the month in which the invoice was sent.

See also periodic range example.

Default Payment Method

Enter a value which will become the default payment method when setting up a new customer.

Purge: No. Of Months

When transactions are completed they are eligible to be purged from the computer system. Enter in this field the minimum number of periods for which transactions are to be retained for each customer.

Purge: No. Of Transactions

Enter the minimum number of transactions which are to be retained for each customer. Zero transactions may be entered.

Statement Print Queue

This field establishes the print queue to be used for customer statements. It overrides the value set up in Application Manager. (See Application Manager).

In Library

This field establishes the library to be used for customer statements. It overrides the value set up in Application Manager. (See Application Manager).

Display Cash First?

You can enter the following options:

0 - During cash allocation, outstanding items will be displayed in the order of the posting period.

1 - During cash allocation, the display of all outstanding items is to present unallocated cash items first irrespective of the posting period.

Immediate/Delayed Updates

You can opt for an immediate or batch update of Accounts Receivable. If batch is chosen, an update job is submitted at the end of each session. You can enter the following options:

I - Immediate update of ledger.

D - Deferred update.

(General Ledger update is always submitted as a batch job, although in practice this may be almost instantaneous - see General Ledger).

Extended Terms?

Enter a default extended terms code as required.

The **F4=Prompt** is available.

Inhibit Posting?

0 - Resetting the flag to 0 will allow processing to restart.

1 - When this flag is set to 1, no processing is allowed in this Accounts Receivable company. It is used by the application during period close to prevent processing until the next period is opened. The flag can also be set manually if you wish to prevent processing.



Press **Enter** to accept all your entries. If the General Ledger interface is not active for the company that you are configuring then the system returns you to the menu.

Adding a Rate Window

If the rate code you select on the maintenance screen has not yet been defined to the application, a window will be displayed to tell you to press **F4** for a list of available rate codes, or to press **Enter** to add a rate code. If you press **Enter** you will see the following fields:

Fields:

Rate Code Description

Up to 35 characters defining the rate code (e.g. Standard Trading Rate).

Effectivity Type

An effectivity date may be applied to each rate code. This may be entered as a calendar date or accounting period.

P - accounting period

D - calendar date

Effectivity dates are entered when you set up the exchange rates themselves.

Adding A Currency Window

If the currency code you select on the maintenance screen has not yet been defined to the application, a window will be displayed to tell you to press **F4** for a list of available currency codes, or to press **Enter** to add a currency code. If you press **Enter** you will see the following fields:

Fields:

Description

Enter the currency description.

Short Description

The description entered here will appear on many screens and reports.

Smallest Unit

This field contains the value of the smallest unit of the specified currency (e.g. in US dollars the smallest unit is one cent, shown as 0.01, whereas the smallest unit of the Japanese yen is one yen - 1.00).

Movement Tolerance

Some currency exchange rates fluctuate wildly whereas others vary within a much smaller band. The movement tolerance field allows you to specify a single plus/minus percentage for the exchange rate variation. Movements outside this range will cause a warning to be issued when exchange rate information is entered.

Maintain Company Profile General Ledger Details Screen

Add your General Ledger control accounts, VAT details and exclude Collection Documents.



The General Ledger Details screen displays when you are creating a new company or amending an existing Company Profile for which the General Ledger interface is active.

SL005	UK Demonstration Company	User GBJBA1MS	29/05/98
Maintain Company Profile....General Ledger Details			
Company Code Z1 UK Demonstration Company			
G/L Company Code . . . Z1 UK Demonstration Company			
Control Account . . . : 411100			
Bank Account : <u>888888</u> ?			
Sales Account : <u>701100</u> ?			
Discount Account . . . : <u>665100</u> ?			
Default VAT Code . . ? <u>001</u>			
VAT on cash date . . : <u>0</u> (1/0)			
VAT address code . . : <u> </u>			
Suppress Coll Docs . : <u>0</u> (1/0)			
F3=Exit F4=Prompt F12=Previous			
MA	a	MW	24/033

Fields:

Control Account

The General Ledger control account for this Accounts Receivable company. This cannot be changed once transactions have been posted.

Bank Account

The default Bank Account General Ledger code into which cash receipts will be paid.

Sales Account

If a default analysis of invoices to a General Ledger sales account is selected, enter the sales account code to be used.

Discount Account

The General Ledger account to be debited with discount allowed.

Default VAT Code

Default tax code to be used when posting invoices and credit notes.

For a full explanation of the code see General Ledger.

VAT On Cash Date

Whether VAT liability is incurred on the transaction date or on receipt of cash, this condition applies to all Accounts Receivable transactions for this company.

0 - VAT based on transaction tax date.

1 - VAT based on receipt of cash.

VAT Address Code

If VAT communications are sent to an address other than the normal customer address, enter the delivery address code that will be used for each such customer.

Suppress Coll Docs

0 - The default value for a new company.

1 - Defaults to collection documents being included within open item enquiries.



Press **Enter** to validate the details and to display the Maintain Company Profile Alpha Search Details screen. If you are using extensions to your account codes the Extension Code Window(s) displays.

Maintain Company Profile Alpha Search Details Screen

Select two fields from the Customer File to be used as additional search criteria. You may then search for the customer on the fields entered (as well as the customer name). The Alpha Search is available at all screens in the system where the customer is selected.



Note: The GL Parameters SRC1 and SRC2 will hold the search descriptions selected here. The system will create the sub-codes for SRC1 and SRC2.



To display this screen, press **Enter** at the Maintain Company Profile General Ledger Details Screen.

SL005	UK Demonstration Company	User GBJBA1MS	29/05/98
Maintain Company Profile....Alpha Search Details			
Choose the 2 fields to be used in the alpha search facility in addition to customer name. Current search fields are..			
and..			
Sel	Field Name	Length	Text
-	RSTS05	1	Record Status Code
-	CUSN05	8	Customer Account Number
-	DSEQ05	3	Delivery Address Sequence Number
-	CON005	2	Company Number
-	CNAM05	35	Customer Name
-	CAD105	35	Customer Address Line 1
-	CAD205	35	Customer Address Line 2
-	CAD305	35	Customer Address Line 3
-	CAD405	25	Customer Address Line 4
-	CAD505	25	Customer Address Line 5
-	PCD105	5	Customer Address Post Code 1
-	PCD205	5	Customer Address Post Code 2
			More...
1=Select			
F3=Exit(without update)		F12=Previous	
MA	a	MW	09/004

Fields:

Sel

1 - Select a line to be used as an additional customer search field. Up to two lines can be selected.



Note: After subsequent changes to the search fields, at this screen, you must update by running the AR Verification/Rebuild option Name Scan Index.



Press **F8=Update** to save changes made to the Company Profile.

Creating a Control Account

When you specify a General Ledger account as an Accounts Receivable control account for a new company, the system displays a message telling you to press **F8=Update** to make this account a General Ledger control account. You will then be returned to the General Ledger details screen.

Printing The Company Profile

The system provides you with the facility to print a report of company profile details. To print the company profile details for an Accounts Receivable company use the following procedure:



1 - From the menu select the Company Profiles option.



2 - Select Accounts Receivable from the Reports option, press **Enter**, and the system displays the Company Select Screen.



3 - Enter the Company Code for which the report is to be printed.



A report is generated of all the company profile data for this company. The menu then displays.

Names And Addresses



1/ARM

This option enables you to create a new customer account record for the customer database. The procedure is the same whether adding new customer details or amending an existing one. Certain information must be entered for every customer and may be used by the Sales Order Processing application.

You can produce reports of all or any selected customer details stored on the system.



Select the maintenance option Names And Addresses to display the company selection screen.

Fields:

Customer Code

Your options are:

- Enter an existing code to change the details of a customer already on the system. See also Customer Selection: By Account Code.
- Enter a new customer code to add a new customer. Press **F6=Base On** to base the new customer on an existing customer. Instead of showing blank fields, the maintenance screen will be displayed showing the details of the customer on which the new customer is to be based.

Customer Selection: By Account Code

The customer search facility is available in Accounts Receivable Maintenance, Processing, Report, Enquiry and other options that are selected on a customer or range of customers.

You can select a customer by Bank Account, by entering the first character or first few characters of the Alpha Sequence Code, or by entering a known Account Code.

Your alpha search facility can be customised by the inclusion of two additional fields from the customer details as search items. For example, you may want to select on Company Name or Customer Group Code or both.



Note: The additional alpha search fields are selected at the Maintain Company Profile Alpha Search Details screen.

```

SL015                Z2 - US Demonstration Company    User GBJBA1MS    1/06/98
                                                15:20:17

Customer Maintenance
Customer Selection: by alpha sequence code
Search argument ..... FR                               More: - +
Customer Name .....
Customer Address Line 3 ..... BIRM

1 Account Name & Address                               Alpha seq.
- FM1      Franck Hierarchy supplier 1|Needles House|Main Stree FR
- FM1/1    Franck Hierarchy Other supplier 1|Kensington House|S FR
- FM2      Franck Hierarchy suppl 2|Hierarchy House|Green Lane| FR
- FM3      Franck hierarchy supplier 3|Needles| FR
- FM4      Franck Hierarchy supplier 4|43 Calthorpe Road|Edgbas FR
- FRANCK2  Franck supplier|Needles| FR
- GBJBARE0 Rob Elliott's Z1 test customer|Strata House,|Bath Ro GBJBARE0
- GBJBARE1 Rob Elliott's Z1 test customer|Strata House,|Bath Ro GBJBARE0
- GSK122   gurmej singh kalsi z2 account|have|not|got|one|yet| GSK122
- COMET15  COMET Studley HCY02| H

1=Select
F12=Previous F15=Search on Bank account F17=Alpha search
F19=Position to...alpha sequence F21=Position to...account code

F3=Exit F4=Prompt F6=Base on
MA a MW A 07/039
  
```

Fields:

Search Argument

Enter the first character or first few characters of the Alpha Sequence item. Then, press **F17=Alpha Search** to select all customers that meet the criteria. Select **F19=Position To Alpha Search** and the screen will display from the position of the selected item.

Customised Fields

Two fields can display after the Search Argument Field. These fields from the Customer File will display as selected at the Maintain Company Profile Alpha Search Details screen. For example, you could select on the Customer Name and town if you use your Address Line 3 to hold the town or city part of the address.

Enter search characters and select **F17=Alpha Search** to run the search. You may search on all three fields:

- the Search Argument and your two additional fields, or
- on any one of these, or
- any combination of these.

Select

1 - Select the customer.

Functions:

F15

Search On Bank Account. The Bank Detail window displays for you to select by bank details.

F17

Alpha Search. Selects and displays all items that match the search criteria.

F19

Position To Alpha Search. Use with the Search Argument field and the screen will display from the position of the first selected customer.

F21

Position to Account Code. Select to position the screen display from a particular customer by entering the Customer Account Code.



Select the customer with 1 to display the first Customer Maintenance screen.

Customer Maintenance Base On Window

Fields:

Customer Code

Enter the existing customer code on which the new customer is to be based.

Company

Enter the company to which the base customer is defined. This field defaults to the current company.

Copy Delivery Addresses

0 - Delivery addresses for the new customer will be different from the existing customer.

1 - If you want the delivery addresses defined to the base customer to be copied to the new customer.



Press **Enter** to see the first maintenance screen.

Customer Maintenance Screen 1



Press **Enter** on the Company Selection screen to display the first maintenance screen.

SL015	Z1 - GB Demonstration Company	User GBJBA1MS	6/06/97 9:18:40
Customer Maintenance			
Account . . :	FC03	AMENDMENT	
Name . . . :	Dumas et Fils		Alpha seq DUMAS
Address . . :	2 Rue de la Victoire		
	Paris 48029		
	France		
Phone 1 . . :	010 331 4891 7733		Post Code
Phone 2 . . :			Fax 1 . . : 010 331 4891 9821
Country . ? :	F		Fax 2 . . :
Contact 1 . :	Francine Waterman		Language? FR
Contact 2 . :			Salesman? LH
Salutation . :			Region ? NW
Remarks . . :			Bal B/F . -
Currency? :	1		Currency Code . ? FRF Francs
Payment Terms :	M 210		Payment Method . ? LCC
Calendar :	0001		Credit Limit . . . 800000.00
Credit Limit Days . . :			Insured Limit . . . 800000.00
F3=Exit F4=Prompt F12=Previous			
06-13 SF MW KS IM II EDN400A PET16S2			

Fields:

Name

Up to 35 characters are available for the customer's name as it is to appear on records and statements.

Alpha Seq

This is used for selected report sequencing and enquiries. For example, the customer W.H.Smith would sensibly be entered as: SMITHWH.

If an alphabetical report sequence is not required you may wish to use some other detail for search purposes, e.g. Post code to find stockists of your goods in a certain area.

Address

Up to 35 characters for each of the first three lines of the customer's address, and up to 25 characters for the fourth and fifth lines.

Post Code

Enter the customer post code.



Note: If you use the Service Management module, you must enter the 10-character postcode in two equal parts - separated by a space. Example: Enter postcode B13 9DP as B13 space space 9DP. This allows the customer postcode to match customers with the nearest

available engineer.

Phone 1

Enter the customer telephone number.

Fax 1

Enter the customer fax number.

Phone 2

Enter a second telephone number for the customer.

Fax 2

Enter a second fax number for the customer.

Country

The country code entered will decide the format of the bank details window to be displayed. Enter the code which will allow you to enter your customer's banking details in the correct format.

Language

The language in which letters for this customer will be sent. (See the Customer Letters section.) Leave blank to send letters in the local language.

Contact 1

Enter the name of your contact at the customer address. This name will appear on enquiries and reports.

Salesman

Enter the salesman, representative or territory code for this account. This may be used for sequencing reports (such as Aged Debt, Name & Address) within Accounts Receivable.



*Note: Salesman codes should be predefined on the General Ledger parameter file **Option 32/GLA** code SLMN.*

Contact 2

Enter the name of any second contact at the customer address.

Region

Up to three characters may be used to provide a regional coding structure for customers. This may be used for sequencing Accounts Receivable reports.



*Note: Region codes should be predefined on the General Ledger parameter file **Option 3/GLA** code REGN.*

Salutation

Enter here, if required, a default salutation for customer letters - for example, 'Dear Sir/Madam'. This default may be overridden when performing a letter run.

Bal B/F

You can enter the following options:

Blank - To operate the account as an open item account.

B - To operate the account as a balance forward account.

Remarks

Up to 50 characters are available to store any remarks to be held on this customer's record.

Currency

0 - If this customer trades only in the base currency of Accounts Receivable. You will not be able to post transactions in other currencies to this account.

1 - If you wish to be able to post currency transactions to this account.

Currency Code

Enter the three character currency code which is the normal trading currency of this customer. Leaving the field blank denotes that this customer normally trades in the base currency of the General Ledger.

Payment Terms

Payment terms default to the values established in the company profile if these fields are left blank, but enter different terms here to define rules for this particular customer.

There are four parts to the definition of payment terms.

1 - A single character code which defines the types of terms to be used. The following codes are allowed: D - Number of days from invoice date. M - Number of months before payment. P - Periodic range. T - Extended payment terms.

2 - This field is used with the above code P, to indicate the period range in number form. See further explanation see the example for the field Default Payment Terms in the Maintain Company Profile Screen.

3 - This field holds the number of days in the format DDD for the above code D, or holds the month and the date in the format MDD for the above codes P and M. For example, a code of D ____ 030 means that the payment date is 30 days from the invoice date. A code of M ____ 210 means a payment will be made on the 10th of the second month after the month in which the invoice was sent.

4 - If the above code T was specified, then this field must hold the extended terms code. This is a code set up in the Cash Management application which defines a more or less complex pattern of payments.

Payment Method

Enter a default payment method for the customer.

Calendar

If you are using the Accounts Receivable due date calculation function, which is specified in the General Ledger country-specific parameters, then you should enter here the calendar to be used for this customer. If none is entered, the system default 0001 will be used.

If you are not using the AR due date function, you may wish to enter a customer calendar anyway, as it can be used for calculating delivery dates.

Credit Limit

Enter the commercial credit limit value, which is used by the Sales Order Processing application. The value is expressed in the General Ledger base currency.

The value of outstanding items and orders not suspended should be less than the Credit Limit otherwise the orders will be suspended in Sales Order Processing.

The credit limit can now be secured separately using the GL utilities option Field Level Security facilities.



Note: The value of the credit limit will only be effective if (Inventory Description) Code CRDC is set up with minor code CRLV (Credit Check by Value) is set to 1.

Credit Limit Days

Enter a value of 0 days if the customer is not to be subject to a credit check by days.

The number of days entered will be used to credit check invoices posted through Sales Order Processing / Advanced Order Processing. Up to five methods of credit checking by days may be in use.



Note: The number of days will only be effective if Inventory Description Code CRDC is set up with minor code CRLD Credit Check by Days set up with a value of 1 - 5. For more information on credit checking calculation methods see Inventory Management Product information.



Note: You may enter a credit limit value and / or credit limit days. An order will be suspended if either check fails.

Insured Limit

The insured credit limit value. This is a memorandum field only, and is not used by any application.



Press **Enter** to validate the contents of the screen. Any errors will be highlighted, otherwise the customer bank details window is displayed (where appropriate) to enable you to enter the bank address, etc.

Bank Detail Maintenance Window

The bank window to display depends on the country you are operating in and the payment method used. This window enables you to enter your bank details, particularly important if payment is by an electronic method.



This window displays automatically at completion of the first customer maintenance screen when the payment method entered is electronic.

SL015	Z1 - GB Demonstration Company	User GBJBA1MS	29/08/97 9:57:37
Customer Maintenance			
Account . . .	MB06		
Name . . .	Reeves Chemicals		
Address . . .	Lenton Boulevard		
	Lenton		
	Nottingham		
	England		
Phone 1 . . .	0602 2		
Phone 2 . . .			
Country . ?	GB		
Contact 1 .	Bob Cr		
Contact 2 .			
Salutation .			
Remarks . .			
Currency?			
Payment Terms . .			
Calendar	? 0001		
Credit Limit Days .	60		
	Bank Sort Code.....	222222	
	Account Number.....	45115465	
	Account name.....	Cooper Banks	
	Bank Name.....	Cooper Banks Corp	
	Address.....	Cupar, Fife.	
	User Reference.....		
	Type of Account.....	3	
	First direct debit..	0 (0/1)	
	Credit Limit . . .	15000.00	
	Insured Limit . .	100000.00	
F3=Exit F4=Prompt F12=Previous			
12-43 SA MW KS CL IM DM II EDN400A KB PKH312S1			



Enter the customer's bank details and press **Enter**.

Unpaid Bills Counter Screen

If you are using Italian statutory reports (That is, Italian Statutory Reports is active in Maintain Country-Specific Parameters) the Unpaid Bills counter screen displays.

Errors

Adjust the count of unpaid bills displayed for cambiale, riba and recalled documents.
Enter amended number or errors as required.

Customer Maintenance Screen 2



Enter the bank details and press **Enter** to display the second Customer Maintenance screen.

SL015		Z1 - GB Demonstration Company		User GBJBA1MS		4/06/97	
						10:25:17	
Customer Maintenance							
Account . : FC03		AMENDMENT					
Name . : Dumas et Fils		Alpha Seq		DUMAS			
Controller . ? EW		Credit Agency Code ? A					
Discount Code ?		Group Code 1/2/3/4 ? FF1		QTX EUR BAC			
Account Status		Account Stop? . . . -					
Parent A/C . ? FC03		Invoice Address . . .					
Consolidate? . 0		Statement Copies . . 1					
Statement Grp . L		Statement Message ? 002					
VAT Code . . ? 002		Cash Basis VAT? . . 0					
VAT ID FR-71 237700022		Fiscal Code					
VAT Calc Basis 1		Tax Classification . 0					
Alloc Method. . 1		Letter Category . . A					
Letter Code . ?		Exempt / Days Grace 0					
Interest % . .		Control Acct . . . 411300					
G/L Company . : Z1		Contra Co/Account . .					
Bank Acct . . . 512400							
F3=Exit F4=Prompt F10=Additional Details F12=Previous F23=External 06-60 SF MW KS IM II EDN400A PET16SS2							

Fields:

Controller?

Enter the code of the controller responsible for this account.



*Note: Controller codes should be predefined on the General Ledger parameter file **Option 32/GLA** code CRSP.*

Credit Agency Code?

If a third party company is being used to monitor and collect debts, enter the code for that company here.



*Note: Credit Agency codes should be predefined on the General Ledger parameter file **Option 32/GLA** code CRLC.*

Discount Code

Enter a default settlement discount code, if multiple settlement discounts are to be offered to this customer.

Group Code 1/2/3/4

These fields can be used for the user-defined coding of customers for sales analysis, and for the sequencing of certain reports.

Customer Group codes should be predefined on the General Ledger parameter file **Option 32/GLA** codes CPG1-4 e.g. Use Customer Group 1 to identify Home/Export and International customers.

Account Status

Under certain circumstances, you may wish to flag an account as being of a certain status. The following status types are available:

D - Recommend for deletion.

S - Suspend trading.

U - Uncertain debt (the customer's debt may not be paid. This status may eventually be changed to L).

L - Legal status (where the customer's affairs are in legal hands and any debt is unlikely to be collected).

These status codes relate to the Doubtful Debtors processing options.

Account Stop?

0 - For customers previously stopped reinstates order processing and integrated invoicing processing.

1 - Enter 1 to indicate a stopped customer. This does not inhibit any action in Accounts Receivable, but is used in Sales Order Processing to prevent the despatch of goods. It is also available for use by integrated sales invoicing applications.

Parent A/C

If the statement for this customer account is to be sent to an address different from that which is contained within this record, enter the account of the required customer.

Invoice Address

If this customer data is being used by a sales invoicing application, this field may be used to hold the account code of an alternative invoice address.

Consolidate?

0 - You wish to be able to enquire and report upon individual transactions current for the customer.

1 - To consolidate transactions for this customer with the account indicated by the statement address code.

This means that although transactions are raised against this account the updates will go to the parent account. If you enquire on this account you will not see any transactions. All items will appear on the enquiry of the parent account, the originating account can be seen from the Item Detail Screen.



Note: An alternative to consolidation is to use Customer Hierarchies.

Statement Copies

You can enter the following options:

Leave blank - To default to one copy.

0 - To suppress statement printing for a customer.

1 to 9 - Enter a number from 1 - 9 for the number of statement copies required.

Statement Grp

When you print statements (from the Accounts Receivable Period Close option), you can select a number of statement groups to be included in the statement run. Any customer defined here as a member of one of the groups will have a statement printed.

Enter here the group to which you want this customer to belong. The code is not set up elsewhere, but is defined here, so any character or number can be entered.

Statement Message

Enter the message code to identify the message which is to be printed on the customer's statements. This will override statement messages specified when you print statements. See Assign Statement Messages.

VAT Reg Req'd

0 - VAT Registers not used.

1 - If VAT registers are to be used, enter 1 here.



Note: VAT Registers are used in Italy.

VAT Register

If you are using the additional VAT register analysis facility provided by the General Ledger, then you must enter the code for the register that is to be used for this customer.

VAT Code

Enter the default VAT code to be used for this customer. This field allows you to use the prompt facility to select from the available VAT codes on the system as shown. You must enter a valid code to complete the customer details.

Extra Rate

0 - If extra VAT is not to be applied to this customer.

1 - If this customer is to be charged extra VAT (the VAT code should have been defined with extra rate VAT on the General Ledger).

Cash Basis VAT

This field enables you to define whether VAT liability for this customer is incurred on the transaction date or on receipt of cash. You can here override the default setting on the company profile.

0 - VAT based on transaction tax date.

1 - VAT based on cash receipt date.

VAT ID

Enter the customer's VAT registration number.

Fiscal Code

Enter the classification code assigned by the government to this customer.

This is a reference field displayed on some reports. The fiscal code may be overwritten when a sales order is entered.

VAT Calc Basis

This field is used by Sales Order Processing to indicate the customer's VAT status for sales invoicing. Valid values are:

- 1 - VAT exempt (for export customers outside the European Community).
- 2 - Use the VAT code entered in the VAT Code field above.
- 3 - Use the VAT code set up against each invoice item from the Inventory item records. It is essential that if world Trade is in use, this indicator is set to 3 for domestic and EC customers



Note: The default for a new customer is 3.

Tax Classification

Enter the appropriate code from the following:

- 0 - Legal entity.
- 1 - Male.
- 2 - Female.

Alloc Method

Select the default method of cash allocation for the customer.

- 1 - Items. All outstanding items for the customer display for selection.
- 2 - References. Select items by entering references.
- 3 - Filter. Select items for allocation by eliminating unwanted items. Selection includes customers, item types, references, external references, periods, outstanding values, due dates.

Value Date Type

- 1 - In place. Your bank and customer's bank are close to each other - normally in the same town.
- 2 - The banks are in different towns.
- 3 - The banks are in different countries.

The value is used with the value date table in Cash Management to calculate the date on which the bank account is updated with a payment. It is an estimate of the number of days a payment takes to clear.



Note: This field is only displayed if Value Date Active field in Country-Specific Parameters (GL Utilities) is set to 1.

Letter Code

Enter the code of the Dunning letter which you normally wish to use for this customer.

The codes are set up using the procedures provided by the Accounts Receivable Letters options. If the default letter code is left blank, the application will use the standard letter code specified when the letters are created. Otherwise the default only is received.

Letter Category

The letter category is used to select customers for letter runs. If it is left blank, no letters will be produced.

In order to invoke the debtor control letter system, any non-blank character may be used. See Customer Letters for further details.

Interest %

Enter here the percentage interest to be charged on this customer's overdue debt.

Exempt/Days Grace

0 (or blank) - If the customer is liable for interest charges.

1 - If the customer is exempt from interest charges.

2 - If the interest is to be calculated and recorded as a memo invoice, but the customer is not to be charged.



Note: You may only input to this field if the Interest Charges Active? field is set to 1. This is selected from the Defaults option in the Accounts Receivable Interest Charges options.

Days Grace

Enter the number of days grace before the customer is liable for interest charges.



Note: Not relevant if Exempt is set to 1.

G/L Company

The General Ledger company code is displayed.



Note: This field is for your information only and cannot be amended.

Control Acct

Enter the General Ledger Debtors control account, if different from that set up on the company profile. Once postings have been made to the customer's account the account cannot be changed.

Bank Acct

Enter the General Ledger bank account for the customer, if different from that set up on the company profile.

Contra Co/Account

If you intend to use contra accounting, enter the Accounts Payable ledger company which is attached to the same General Ledger company as the Accounts Receivable ledger company.

The second part of this field enter the supplier account code in the Accounts Payable ledger with which this customer is related for contra accounting purposes.

Functions:

F10

Additional Details. Displays the Extra Rate field after the VAT code.



Press **Enter** when you have completed the fields. If there are any errors these will be highlighted for you to amend, otherwise the customer details will be updated and you will be returned to the first selection screen.

F23

External. Allows you to access your customised program option. The function of such a program will have been designed by your company to suit your customer maintenance records' requirements.



*Note: The appearance of the **F23=External** function key on this screen depends on GL Country Specific Parameter External Function 042 being set to 1 and a suitable program being linked.*



Press **Enter** and then **F8=Update** to update amended country specific parameters.

Collection Document Window

The Collection Document window displays if the payment method field on the first maintenance screen is not blank.

The window enables you to set up defaults to be used when creating collection documents for this customer.



Press Enter on the second Customer Maintenance screen to display the Collection Documents window.

SL015	E1 - Demonstration Company	User ED3	15/03/94 10:32:03
Customer Maintenance			
Account . . : FC01	AMENDMENT		
Name . . . : La Perfumerie Agnes		Alpha Seq AGNES	
Controller . . ? EW		Credit Agency Code ? A	
Discount Code ?		Group Code 1/2/3/4 ? FFI STD EUR CHO	
Account Status			
Parent A/C . . ? FC01			
Consolidate? . 0			
Statement Grp . I			
VAT Reg Reqd . 0			
VAT Code . . . ? 002			
VAT ID			
VAT Calc Basis I			
Letter Code . . ?			
Interest % . .			
G/L Company . . : Z1			
Bank Acct . . . ? 512400			
		Control Acct . . . ? 411300	
		Contra Co/Account . Z1 GS03	
F3=Exit	F4=Prompt	F12=Previous	

Collection Documents

Consolidate Items	2
Create in SOP ?	0
Creation Group	-
Review Code	?
Apply Linked Credits ? . .	0
Cash Collection Letter ? .	0
Suppress Attached Items ? .	0

F4=Prompt F12=Previous

Fields:

Consolidate Items

This field allows you to define whether items are consolidated into one collection document. Enter one of the following:

0 - No consolidation.

1 - Items will be consolidated based on the posting account (Level 1 of a hierarchy).

2 - Items will be consolidated based on the statement address (Level 3 of a hierarchy).



Note: If the customer is not in a hierarchy there is no difference between 1 and 2.

Create In SOP?

0 - To produce collection documents from Cash Management.

1 - To produce documents from Sales Order Processing.

Creation Group

Enter a single character code which you can use to group customers together for statements and for the production of collection documents.

Review Code

Individual documents are flagged with a review code to signify that authority and reviews are needed before processing. Enter a default code here.

Apply Linked Credits

0 - Linked credit notes will not be applied to replacement collection document.

1 - When a credit note from Sales Order Processing is created, the system will check whether the associated invoice is still on an outstanding collection document. If it is, the system will replace the document with a new one including the credit note.

Cash Collection Letter

0 - Collection letters not produced automatically.

1 - The system will produce a letter for the customer to warn that a collection document is about to mature.

Suppress Attached Items

0 - Invoices on an unaccepted document will be listed for inclusion on the new document.

1 - Normally, when you enter the manual collection document creation option, invoices on an unaccepted document will be listed for inclusion on the new document. If you do not want such invoices to be listed, enter 1 here.



Press **Enter** to update and return to the first selection screen.

Delivery Addresses



2/ARM

The delivery address maintenance facility allows you to create or maintain additional delivery address records which are associated with a customer account. They may then be used by any linked Sales Order Processing application.

The customer account record for which you want to create additional delivery address records must already be configured before any delivery name and address records can be added.



Note: If a VAT account code is specified on the company profile, you need to set up a VAT address with this code for each customer requiring separate VAT communications



Select the maintenance option Delivery Addresses to see the selection screen, and enter the customer for which you want to create delivery addresses.

Delivery Address Maintenance Selection Screen

-  Press **Enter**, and the name and address of the entered customer is displayed.
-  To confirm that this is the customer whose addresses you want to maintain, press **Enter** and a blank delivery code field will be displayed.

SL025	E1 - Demonstration Company	User ED3	14/03/94 10:18:52
Delivery Address Maintenance			
Account Code...? FC01			
Account Name... La Parfumerie Agnes			
Address..... 17A Rue de Rivoli			
Lyons 69018			
France			
Post Code.....			
...press ENTER to accept this account, or key in another customer.			
F3=Exit F4=Prompt			

Fields:

Delivery Code

Enter a 3-character code to identify the delivery address. (Do not use the code 000, as this has a reserved meaning in the system).

If the customer code is C00, for example, you might call the first delivery address C01.

Leave this field blank to select from a list of addresses already defined to this customer.

Delivery Address Maintenance Screen

Enter full delivery address details.



Press **Enter** when you have entered or selected a delivery address code.

SL025	Z1 - UK Demonstration Company	User GBJBA1MS	2/06/98
Delivery Address Maintenance			
Account Code....	A101	Mitchells	
Delivery Code...	001	ADDITION	
Name.....	Mitchells		
Address 1.....	274 Capon Street		
Address 2.....			
Address 3.....	Dublin 2		
Address 4.....			
Address 5.....			Post Code...
Contact.....			
Phone Number....			
FAX Number.....			
Group.....?..	1	2	3 4
Remarks.....			
Salesman.....?..	Region?		
F4=Prompt F12=Previous			
MA	a	MW	14/020

Fields:

Name

Enter the delivery address name that is to appear upon delivery documentation.

Address

Enter the delivery address.

Post Code

Enter the post code.

Contact

Enter the contact name for this address.

Phone Number

Enter the telephone number of this address.

Fax Number

Enter the fax number for this address.

Groups

These three character group codes enable the user to define coding of accounts for use within Sales Analysis. The codes may also be used to sequence Accounts Receivable reports.



*Note: Customer Groups should be defined on the General Ledger parameter file **Option 32/GLA** code CGP1-4.*

Remarks

Up to 50 characters may be entered for remarks to be held against this delivery address.

Salesman

The salesman, representative or territory code for this account. This may be used for sequencing reports (such as aged debt or name & address reports) within Accounts Receivable.



*Note: Salesman codes should be defined on the General Ledger parameter file **Option 32/GLA** code SLMN.*

Region

This field is used to provide a regional coding structure for customers. This may be used for sequencing Accounts Receivable reports.



*Note: Region codes should be defined on the General Ledger parameter file **Option 32/GLA** code REGN.*

Activity

For normal live records this field should be left blank.

D - To delete an account. The account will be purged from the database when the month end utilities are run - the delete will NOT be performed immediately.

S - To suspend an account.



Note: Your settings selected here have no effect upon processing within the Accounts Receivable application, but are used by other applications, such as Sales Order Processing .



Press **Enter** to update.

Reason Codes



3/ARM

The system provides you with the facility to create a set of standard reason codes which you can allocate to credit notes, journals and adjustments. Associated with each code is a description GL code extension code which will be used to code postings to the General Ledger.

It is recommended that in addition to each credit note, journal and write off adjustment that a full range of cash allocation adjustment reason codes are created to make cash allocations easier. The reason codes for this are BX, CA, DN, NA, NT, OP, PT, RG, UP. See the Cash Allocation section for more details.

The credit note analysis report is in reason code sequence.

Reason Codes Maintenance Screen



Select the AR maintenance Reason Codes option to see the list of existing reason codes.

Fields:

4

Enter 4 beside a code to be deleted.

Reason Code

Two character code identifying the reason. 0 - 9 and A - Z are valid characters.

Reason Code Description

Up to 15 characters of description may be entered to identify the reason code.

General Ledger Account Code

The General Ledger account code to which journals for this reason code are analysed or, if the General Ledger is interfaced to this ledger, postings are made.

Cash Allocation adjustments (except for Write off AJ) do not post to the General Ledger but a General Ledger code will need to be entered here.



Note: Maintenance of these codes is not strictly speaking possible. You must first delete a code and then re-enter it in order to amend it.

Select Extension Code Window

If you are entering General Ledger accounts, and are using extension codes, the extension code window will be displayed for confirmation or maintenance.



Press **Enter** to update.

Statement Messages

1...
2...

4/ARM

You can print a seven line message on each statement. This procedure maintains messages which may be printed on either all or selected statements.

These can be assigned manually to each customer or globally by the Assign Statement Messages period close procedure. In this you define the age of overdue accounts, and assign the pre-set messages for printing on statements. The Statement message held in Customer Account Screen is updated.

Statement Message Text Maintenance Screen



Select the maintenance option Statement Messages to see the selection screen. Enter a code for the message and press **Enter** to proceed to the next screen.

SL320	E1 - Demonstration Company	User ED3	14/03/94 10:23:37
Statement Message Text Maintenance			
Message reference selected is: 001			
Line	Text		
1	*** We Have A New Product Range Due Soon ***		
2			
3			
4			
5			
6			
7			
F3=Exit F11=Delete statement message F12=Previous			

Fields:

Statement Message Text

A maximum of seven lines of text may be entered to form the message exactly as it is to be printed on the statement.



Press **Enter** to update.

Disputed Invoice Codes



5/ARM

This procedure enables you to create, change and delete reason codes used for defining the nature of a dispute on an invoice. Up to three lines of text may be attached to a reason code. The text is available in subsequent enquiries and reports

Invoices with dispute codes may be excluded during Cash Allocation and omitted from certain reports. A report is also available to list those invoices with codes.

Disputed Invoices Reason Codes Maintenance Screen



Select the maintenance option Disputed Invoice Codes to see a list of existing codes.

Fields:

Disputed Invoice Reason Code

To enter a new reason code, enter the required two-character code.

Text

Enter the text to be used for this reason code.



To create a new code, enter the two-character code at the bottom of the screen, and enter up to three lines of code description. Press **Enter** to update.

To amend an existing code, enter 1 beside the code displayed, and it will be brought down to be displayed in the maintenance fields at the bottom of the screen. Amend as required, and press **Enter** to update.

Functions:

F11

Select the code to delete with 1. When it is displayed at the bottom of the screen, press **F11** twice to delete.

Customer Hierarchies

1...
2...


6/ARM

Hierarchies are set up so that you can allocate cash from a controlling customer account to sub-accounts - often branches - belonging to that customer, which are linked in lower levels of the hierarchy structure.

They can also perform a comprehensive credit check, so the value of orders can be checked against the customer's credit at order entry level (level 1). If a credit check fails, the order will be suspended. Enquires can also be made at controlling customer and sub account customer level.

Structure Of A Hierarchy

First design your proposed hierarchy, and define the customers within the hierarchy.



Resulting balances are updated upwards through the hierarchy.

The ledger balance figures are taken from the level 3 customers by Accounts Receivable, which means that you can only define one level 3 customer in any one branch of the hierarchy.

Similarly, orders entered for a level 1 customer cannot be linked to another level 1 customer.

However, customers at levels 2 and 4 are used to produce summary information only, and you may therefore link as many of these as you want on one hierarchy branch.

Level 2 and level 4 customers are defined by setting the cash allocation flag to 0 (although cash can be allocated at level 2).

Level 2 and level 4 accounts are not essential to the hierarchy, so a level 1 account can be linked directly to a level 3 account. However if a level 2 account is specified it must link into a level 3 account. A level 3 customer is defined by setting its cash allocation flag to 1.

Postings

Postings to the different levels are restricted by the following rules:

- Level 1: Invoices, credit notes, adjustment journals and cash may be posted and allocated, SOP orders are entered at this level.
- Level 2: Cash entry and allocation.
- Level 3: Cash entry and allocation.
- Level 4: No postings may be made and no Cash Allocation.
- Adjustments : Cash Allocation adjustments made at level 3 need to be assigned a level 1 account. If the adjustment is not attributable to a specific account, a dummy level 1 account may be specified to hold these miscellaneous adjustments.

Maintenance

1. Hierarchies can only be created and maintained using accounts without postings.

You cannot move a level 1 account to another level once postings have been made (see 2. below).

2. Should you wish to create or maintain hierarchies when postings have been made then two maintenance options are available.

- Hierarchy Maintenance (utilities option).
- Advanced Hierarchy Maintenance

(see table below) use the Hierarchy Maintenance utility option. When you have made changes, balances for the accounts involved are rebuilt.

When you add a customer to a hierarchy select only:

- A hierarchy customer at the top of its hierarchy (any child accounts will follow), or
- A non hierarchy customer (add into level 1, 2 or 3 only).
- A customer not in an active interest charges run.

Effects Of Changing/Adding A Hierarchy Level:

Add customer of level	To customer of level	Added customer becomes level	Customer added to
4	4	no change	no change
4	3	2	no change
4	2	2	no change
4	1	2	2
3	4	no change	no change
3	2	2	no change
3	1	2	2
non hierarchy	3	1	no change
non hierarchy	2	1	no change
non hierarchy	1	1	2

When you remove a customer from a hierarchy:

- Select a customer not in an active interest charges run
- Ensure that no unconfirmed collection documents exist which involve items for this customer/other customers in the hierarchy.

Effects Of Removing A Customer From A Hierarchy:

Remove customer of level	From customer of level	Removed customer becomes level	Customer removed from
4	4	no change	no change (see note)
3	4	no change	no change (see note)
2	3	3	no change (see note)
2	2	3	1
1	3	non hierarchy	no change (see note)
1	2	non hierarchy	1 (see note)



Note: If a removed customer has no remaining child accounts and no parent account then it becomes a non-hierarchy account.



Note: Dunning letters can only be produced for level 3 accounts.

Customer Hierarchy Maintenance Selection Screen



Select the maintenance option Customer Hierarchy to see the selection screen.

Fields:

Account

Enter the account to be added to the hierarchy. The next screen will then enable you to specify the accounts which are to form the level below this account.

If you are setting up a new hierarchy then the system will assume that the accounts below this account are level 1 accounts.



When you are entering a new hierarchy, the account you enter in the selection screen must be an account on a level immediately above a level 1 account. It must therefore be either a level 2 or level 3 account.

This is because when you go to the next screen, you will have to enter the level 1 accounts which are linked to the account you have just entered.

In the diagram above, for example, the account you enter on the initial screen to start defining the hierarchy will be either area office C (to define branches 1 and 2), Regional Head Office 1 (to define branch 3), or Area Office B (to define branch 4).

Assume you have entered Area Office B and defined branch 4. Your next step might be to enter Regional Head Office 2 and define Area Office B to that. Continue in this way until the whole hierarchy is defined.



When you have entered the account to which you want to define lower levels, press **Enter** to display the Customer Hierarchy Maintenance screen.

SL014	E1 - Demonstration Company	User ED3	15/04/94 11:46:30
-------	----------------------------	----------	----------------------

Customer Hierarchy Maintenance

Account AOC Area Office C

Cash Allocation Level . . . : 0 (0/1)
Produce statements : 0 (0/1)
Enter NEW account ?
Interest Charges Level . . : 0 (0/1)

4 Account Name
- BR01 Branch Office 1
- BR02 Branch Office 2

F3=Exit F4=Prompt F11=Delete hierarchy F12=Previous
F7=Amend Details

Fields:

Enter New Account

Enter here any account you wish to define as a lower level account. As long as the account is valid, it will be displayed in the list lower down the screen when you press **Enter**.

4

If you wish to delete an account from the hierarchy, enter 4 against it and press **Enter**.

Functions:

F7

To amend or add data to Cash Allocation Level, Produce Statements, and Interest Charges level fields.

F11

Delete the whole hierarchy definition. Start hierarchy deletion at the highest level.

Customer Hierarchy Maintenance Screen New Account (F7)



When you press **F7**, the screen changes from allowing you to input new accounts in the hierarchy to allowing you to change certain fields governing the parent account.

SL014	E1 - Demonstration Company	User ED3	15/04/94 11:46:53
-------	----------------------------	----------	----------------------

Customer Hierarchy Maintenance

Account AOC Area Office C

Cash Allocation Level . . : 0 (0/1)
Produce statements. . . : 0 (0/1)
Enter NEW account . . . : ?
Interest Charges Level. . : 0 (0/1)

4	Account	Name
-	BR01	Branch Office 1
-	BR02	Branch Office 2

4=Remove from hierarchy

F3=Exit F4=Prompt F11=Delete hierarchy F12=Previous
F7=Enter New Account

Fields:

Cash Allocation Level

1 - If you want this account to be a level 3 account.

0 - Identifies this account as either level 4 or level 2. Cash can be entered and allocated at level 1 or level 2.



Note: When you create a level 3 account, it automatically becomes the parent account of those customers beneath it.

Produce Statements

If you want to produce statements at this level, enter 1 here.

Interest Charges Level

0 - to apply interest charges to the level 1 accounts.

1 - to apply the charges to a level 3 account.

This field is maintainable only if this is the cash allocation level account. A figure must exist in the Interest % field on the customer maintenance file.

Functions:

F7

This function key toggles between enabling the addition of new accounts and enabling the maintenance of the account parameters.

F11

Press **F11** to delete the hierarchy.

Customer and Item Text



7/ARM

In addition to the normal financial details which are held for each customer you also have the facility to record free-format text. This free-format text would typically be used for keeping records of accounts in query, payment promises, records of telephone conversations, and so on. This procedure provides the facility to add or change this customer narrative

This option can be used in conjunction with the text diary report to produce daily telephone chase lists on promised payments etc.

This text can be reviewed and updated at various points throughout the system i.e. processing and enquiries.

Customer and Item Text Selection Screen



Select the maintenance option Customer and Item Text, and enter the customer for whom text is to be maintained.



Press **Enter** to see the next fields:

Fields:

Item Type

If text is to be associated with a particular transaction item within the ledger, enter the item type code of two characters. Valid item type codes usable within Accounts Receivable are as follows:-

IN - Invoice

CR - Credit Note

CA - Cash on Account

AJ - Adjustment Journal

UC - Unallocated Cash

Item Reference

Enter the reference number of the item that is to have text attached. This item reference may be obtained by use of the enquiry facilities examining items attached to the customer account specified.

Diary Facility (Action date sequence) Customer Text Screen



Leave both of the fields blank if you wish to enter customer text rather than item text. Press **Enter** to display the Diary Facility (Action Date Sequence) - Customer Text screen.

SL270	Z1 - Z1 TSS	USER GBJBANB1	23/08/94 11:45:01
Diary Facility (Action date sequence) Changes by GBJBANB1			
Account GC01 Reeves Chemist's		Controller NJR	
X Action S Customer account level text			
-	250894	5	Customer has close links with La Parfumerie Agnes, in France. Inform our French agents of the link.
1	190894		Get authority before sending letters.
Position to action date <u>23/08/94</u> Status . . . ?			
Options 1=Select 4=Delete Recorded by . ? <u>ED3</u>			
F3=Exit F4=Prompt F6=Add new F12=Previous F15=Change seq.			

Fields:

X

Enter 1 to amend the text, or 4 to delete the text.

Position To Date

Enter the date at which you want the list to display.

Status

To display only text of a certain status, select a status code. The following are suggested code descriptions as set up at the GL audit option Parameters.

- 1 - Item cleared.
- 2 - Text cleared.
- 3 - Open text.
- 4 - Action required.
- 5 - Reviewed/actioned.

Recorded By

Enter the name or code to be associated with the text entered. This defaults to the current user code.

Functions:

F6

Add new text.

F15

Toggles between displaying text in action date order and in change date order.

Diary Facility Text Maintenance Screen



Select the text you wish to review or amend by entering 1 against it. The Diary Facility - Text Maintenance screen will be displayed.

SL271	E1 - Demonstration Company	USER ED3	23/08/94 11:48:10
-------	----------------------------	----------	----------------------

Diary Facility - Text Maintenance	
Account GC01	Reeves Chemist's
Status Code. . ? _	Action Date . . . 19/08/94
	Controller NJR
	Changed 23/08/94

Line	Customer account level text
01	Get authority before sending letters.
02	
03	
04	
05	
06	
07	
08	
09	
10	
11	
12	

+

Insert	_	lines after line	_
Delete	_	lines from line	_

F3=Exit F4=Prompt F8=Update F12=Previous

Fields:

Status Code

You can if you wish assign a status to the text. Suggested codes are as follows, but the codes can be user defined using the GL audit option Parameters.

- 1 - Item cleared.
- 2 - Text cleared.
- 3 - Open text.
- 4 - Action required.
- 5 - Reviewed/actioned.

Action Date

If this text requires action to be taken, enter the action deadline here.

Line Text

Enter text as required, Use the insert and delete fields at the bottom of the screen to edit the text.



Press **F8** to update the text.

Trend Parameters

1...
2...

8/ARM

The statistics available for the credit manager enquiries are calculated by a batch job (the AR processing option Update Statistics) which should be run frequently, possibly as part of the auto day end routine.

This option enables you to specify the values of certain parameters which affect the calculations mentioned above, in particular the number of periods to be used in calculating trends.

Before using this option you should define a performance code (type PFMC), using the GL audit option Parameters.

Credit Manager Maintenance Screen



Select the maintenance option Trend Parameters to display the Credit Manager Maintenance screen.

SL240	E1 - Demonstration Company	User ED3	15/04/94 11:55:50
Credit manager maintenance			
Batch update last run		13/04/94 17:30:59	
Period last updated		9311	
Trend period interval		3	
Exclude disputed invoices from ratios? . . .		1	
Ratio for indicator		1	1=DD 2=DSO 3=ADP 4=SDP
Default text status for enquiries		?	-
Performance indicator		T0	
A	Performance Indicator A	30	
B	Performance Indicator B	60	
C	Performance Indicator C	90	
D	Performance Indicator D	999	
E	Performance Indicator E	999	
F	Performance Indicator F		+
F3=Exit			

Fields:

Trend Period Interval

Enter here the number of periods to be integrated in the calculation of the amalgamated trends figures. These figures are:

Total sales.

Total credits

Debtor days

Day's sales outstanding.

Average days to pay

Average days slow.

Exclude Disputed Invoices

Enter 0 to include disputed invoices in the calculations, enter 1 to exclude them.

Ratio For Indicator

Each customer can be assigned a performance code which gives a general indication of their payment performance. This field specifies which of four credit manager statistics is to be used to produce the performance code:

1 - Debtor days

2 - Days' sales outstanding

3 - Average days to pay

4 - Average days slow

26 codes are available for grading performance.

These codes are defined on the General Ledger audits and other maintenance option Parameters (32/GLA) under the parameter code PFMC.

Default Text Status

Enter the text status which you want to appear as the default when you select text by enquiry.

Debtor Days

The figure shown here represents the weighted average number of days outstanding for the customer's outstanding debt.

Select all open items for the customer. For each item, multiply the number of days between document and current date by the outstanding balance.

Divide the resulting total by the total of the outstanding balances. The result is the number of debtor days:

Open Items Value	X	Days Outstanding	=	Result
500	X	30	=	15000
200	X	60	=	12000
700				27000
$\frac{27000}{700} = 38.5 \text{ debtor days}$				

Days Sales Outstanding

This figure shows the number of days sales that the outstanding debtor value represents.

Assume that the outstanding sales value is 10,000. Follow the steps numbered below and relate them to this table:

1 - Compare the outstanding sales value (OSV) with the total sales value (TSV) for the most recent (or current) period. The OSV > TSV, so enter the total number of days elapsed so far in that period into the days outstanding column.

2 - OSV - TSV=Working value.

3 - Compare the working value with TSV of the next period down. The working value is greater than the TSV, so put the total number of days in the period into the days outstanding column.

4 - Repeat operations 2 and 3 until you reach the final period, when the working value is only 50% of the TSV. In this case, take the same percentage of days in the period, 50%, which is about 15 days, and put this in the days outstanding column.

5 - The sum of the figures in the days outstanding column, 108, is therefore the days sales outstanding figure.

Period	No. of Days	Sales Value	Days Outstanding
9405	31	2000	4*
9404	30	3000	30
9493	31	1000	31
9402	28	2000	28
9401	31	4000	15
			108

* Assume a current date of 4/5/94

Average Days To Pay

This figure shows the average number of days a customer takes to pay an invoice, from document date to payment date, with appropriate weighting depending upon the size of the invoice.

Take all paid items for the customer. For each item, multiply the number of days between document and payment date by the invoice value.

Divide the resulting total by the invoice value total. The result is the average number of days taken to pay:

Paid Items Value	X	Payment Date minus Document Date	=	Result
100	X	30	=	3000
300	X	60	=	12000
400				15000
	$\frac{15000}{300}$	=	50 days slow	

Average Days Slow

This figure shows the average number of days late a customer pays an invoice, from due date to payment date, with appropriate weighting depending upon the size of the invoice.

Take all paid items for the customer. For each item, multiply the number of days between due date and payment date by the invoice value.

Divide the resulting total by the invoice value total. The result is the average number of days payment is late:

Paid Items Value	X	Payment Date minus Due Date	=	Result
200	X	30	=	6000
100	X	60	=	6000
300				12000
	<u>12000</u>	=	40 days slow	
	300			

Debtor Provision Accounts



9/ARM

This option enables you to specify the General Ledger accounts to which provision for bad debts is to be posted.

GL Provision Accounts Maintenance Screen



Select the audit option Debtor Provision
Accounts to see the following fields:

Fields:

General Provision Accounts:

Debit

Enter the account which is to hold the general provision for bad debt. This should be a Profit and Loss account.

Credit

Enter the account to be associated with the debtor account. This should be a Balance Sheet account.

Specific Provision Accounts:

Debit

Enter the account which is to hold the specific provision for bad debt. This should be a profit and loss account.

Credit

Enter the account to be associated with the debtor account. This should be a balance sheet account.



Press **F8** to update.

Cash Allocation Preferences

10/ARM

This option allows you to customise your cash posting and allocation sessions:

- You may select which initial control windows you wish to use. Up to three windows may be selected - batch control, session control and allocation control.
- Define up to a maximum of 9 views for which you may
 - select which fields should display at the cash allocation screen.
 - Select the order the fields should be presented on the cash allocation screen



Note: The first view defined will become the default view at the Advanced Cash Posting and Allocation options. F7 will allow you to switch between your defined views.



Note: To use the system-defined view do not set up any defined views.

SL1119SI	User GBJBA1MS	4/09/97 9:59:27
Customise User Preferences for Cash Allocation		
User.....	GBJBA1MS	(Leave blank for default user)
Base on.....		
Customise what?..	2	(1=Initial route, 2=Item views)
F3=Exit		
5-21	SR	MW KS CL IM DM II EDN400A KB PKH312SI

Fields:

User

Enter the signon name of the Cash Posting and Allocation options user.

Base On

Enter the signon of a user already set up with user preferences - to be amended and updated as required for the present user.

Customise What?

- 1 - Initial Route. Allows you to select up to three windows to display first when your user selects the posting option.
- 2 - Item Views. Select the fields to be included at the cash allocation screen and sequence fields as required.

Customise User Preferences for Cash Allocation Initial Route Screen



Note: Control options suppressed here may still be selected with function keys at the Cash Posting and Allocation screens. See also Fields.

SL1119SI	User GBJBA1MS	4/09/97 10:34:06
Customise User Preferences for Cash Allocation		
User..... GBJBA1MS		
Display batch controls?..... 1 (0/1)		
Display session defaults?..... 1 (0/1)		
Display allocation defaults?... 1 (0/1)		
F3=Exit F8=Update F12=Previous		
7-34	SR	MW KS CL IM DM II EDN400A KB PKH312S1

Fields:

Display Batch Controls?

0 - Omit Batch Control options for the user. Batch controls may not be selected at all at the Allocation only option.

1 - Batch Control option will display at cash posting and allocation.



Note: This field is only effective if Batch Controls Active is set to 1 in the AR company profile.

Display Session Defaults?

0 - Omit Session defaults for the user.

1 - Session Defaults will display at cash posting and allocation. Your user will then be given the option of accepting or amending the posting and discount dates and the GL bank account - a bank reference may be added for the session.



Note: If a session default bank reference is not added at the posting option then cash transactions will report as blank.

Display Allocation Defaults?

0 - Omit allocation defaults for the user. Allocation Default Controls may not be selected at the Cash Posting only option.

1 - The Allocation Defaults window will display with the option to change the company, customer, allocation currency and payment methods for the posting.

If the customer selected has no default allocation method the user will be prompted to select one of the 3 allocation methods - 1 by individual Items, 2 by invoice / item references, or 3 by filtering from a range of dates, codes, item types, values etc.



Press **F8** to update the Preferences selected.

Customise User Preferences for Cash Allocation Item Views

- Select 2 at the Customise What? field on the first selection screen.

SL1119SIUser GBJBA1MS 4/09/97
11:34:21

Customise User Preferences for Cash AllocationUser... GBJBA1MS

1	Due Date Item	Value (Prime)	Pay (Prime)	Discount(Prime)
2	99/99/99 00 00000000	99999999999999.99-	99999999999999.99-	99999999999999.99-
3	00 00 99999999999999.99-	99999999999999.99-	99999999999999.99-	
4				
5				
6				
7				
8				
9				

F12=Previous

F17=Fields

F18=What is

F24=More

7-4

SR

ML

KS

CL

IM

DM

II

EDN400A

KB

PKH312S1

Each numbered line displays the views available at cash allocation. Select a view to display for the user by rolling up or down (Page Up or Page Down keys).

- You may add a new view by highlighting a blank line and pressing **Enter**.
- Once the line is highlighted (in blue) press **Enter** to display the window which will allow you to select the column headings.

Customise User Preferences for Cash Allocation (Add / Amend View)

The window allows you to select all possible fields to position and access on the cash allocation screen.

SL1119SI User GBJBA1MS 4/09/97 11:34:21

Customise User Preferences for Cash Allocation User... GBJBA1MS

1	Due Date Item	Value (Prime)	Pay (Prime)	Discount(Prime)
2	99/99/99 00 00000000	99999999999999.99-	99999999999999.99-	99999999999999.99-

Seq.	Field	Type
10	Due date	7,0
20	Item type	2
30	Item reference	8
40	Balance due (prime)	15,2
50	Value to be allocated (prime)	15,2
60	Discount to be taken (prime)	15,2
		More...

F12=Previous

F12=Previous F18=What is F24=More

12-13 SR MW KS CL IM DM II EDN400A KB PKH312S1

Fields:

Seq.

The number displayed shows the column position on screen.

- ➡ To reposition the field, overwrite with a new number and press **Enter**. The item will be positioned within the window.
- ➡ Roll down (Page Down) to display all possible fields to be included on the allocations screen for the user. Select as before by entering the column position number and press **Enter**.

If blank then the field will not be included on the allocation posting screen.

Field

Displays the fields which may be included on the allocation posting screen. You must add your column heading name for the field.

Type

Displays the field length for information.

- ➡ Press **Enter** to accept the new or amended view. You will be returned to the previous screen where the updated lines will be included.

Functions:

F11

Delete. When the cursor is on a field, deletes (on a further prompt).

F18

What Is? When the cursor is on a field, displays the field name.



Press **F8=Update** to save the view and be returned to the first screen.

Reports

The system enables you to print reports of the reference data on the system. In addition, you can produce a customer audit report showing all the changes made to the customer file. The customer audit report should be run on a regular basis to clear down the audit file but also to identify any unauthorised changes to a customers details, preferably as part of the auto day end routine.

Account Names and Addresses Listing



31/ARM



Select the maintenance reports option Names and Addresses to see the following selection fields:

Fields:

Account Code Sequence.

To produce a report in ascending account code sequence, enter a 1 in this entry field.

Account Code Range Select.

To allow the selection of a range of accounts for which the report is to be produced, enter a 1 in this field.

Sales Region Code Select.

To sequence the Name and Addresses report by the contents of the sales region code, enter a 1 in this field.

Sales Representative Code Select.

To sequence the Name & Addresses report by the contents of the sales representative code, enter a 1 in this field.

Customer Groups

To sequence the report by the contents of a customer group, enter 1 in the relevant field.

Credit Responsibility Code Select

To sequence the Name & Address report by the credit responsibility code entered against each account, enter a 1 in this field.

Alpha Sequence Select.

To sequence the Name & Address report by the contents of the Customer alpha sequence field, enter a 1 in this field.

Detailed Listing

1 - To print full customer address details,

0 - To print only the customer name and the first line of the address.



You can select only one of the options. If you leave the Range of Account Codes field blank, the report will pick up all accounts. If you enter 1 in the field, the following fields will enable you to enter your selection of accounts:

Starting Account Code

Enter the start point for the name and address list. The account code entered here need not be an existing account, and can be just the first characters of a code.

Ending Account Code

Enter the end point for the name and address list. The account code entered here need not be an existing account, and can be just the first characters of a code.



Press **Enter** to submit a job to generate the report.

Delivery Addresses Listing



32/ARM



Select the maintenance report option Delivery Addresses to see the following selection fields.

Account Code Sequence.

To produce a report in ascending account code sequence, enter a 1 in this entry field.

Account Code Range Select.

1 - To allow the selection of a range of accounts for which the report is to be produced.

Sales Region Code Select.

1 - To sequence the Delivery Addresses report by the contents of the sales region code.

Sales Representative Code Select.

1 - To sequence the Delivery Addresses report by the contents of the sales representative code.

Customer Groups

1 - To sequence the report by the contents of a customer group, enter 1 in the relevant field.

Detailed Listing

0 - To print only the customer name and the first line of the address.

1 - To print full customer address details.

Delivery Name & Address Only

1 - To print delivery addresses only, 0 to print the customer address as well as delivery addresses.



You can select only one of the options. If you leave the Range of Account Codes field blank, the report will pick up all accounts.



Enter 1 in the field and the following fields will enable you to enter your selection by a range of accounts:

Starting Account Code

Enter the start point for the name and address list. The account code entered here need not be an existing account, and can be just the first characters of a code.

Ending Account Code

Enter the end point for the name and address list. The account code entered here need not be an existing account, and can be just the first characters of a code.



Press **Enter** to submit a job to generate the report.

Reason Codes Listing



33/ARM

Select the maintenance report option Reason to see a window asking you to press **F8=Confirm** to confirm your request. A report of all the company's reason codes will be produced.

Statement Messages Listing

1...
2...

34/ARM

Select the maintenance reports option Statement Messages to see a window asking you to press **F8=Confirm** to confirm your request. A report of all the company's statement messages will be produced

Disputed Invoice Codes Listing



35/ARM

Select the maintenance reports option Disputed Invoice Codes to see a window asking you to press **F8** to confirm your request. A report of all the company's disputed invoice reason codes will be produced.

Customer Hierarchy Listing



36/ARM



Select the maintenance reports option Customer Hierarchies to see a window asking you to press **F8=Confirm** to confirm your request. A report of all the company's customer hierarchies will be produced.

Customer Audit Listing



41/ARM

It is recommended that this option is run frequently, perhaps as part of an auto day-end routine to check for unauthorised changes to the customer file.



Select the maintenance audit reports option
Customer Audit to see the following fields:

Fields:

Customer

Enter the customer account code to produce an audit list for a specific customer. Leave the account code blank to print an audit report for all customers.

Date From Which To Start

Enter a start date from which changes are to be printed. (This includes any previously printed changes). Leave the date blank to print all changes which have not previously been printed.



Press **Enter** to produce the report.