

-
-
-
-
-

Chapter 1

Maintenance



Country Maintenance



1/WTM

Use this option to maintain the country details.

In World Trade, you attach countries to customers, suppliers and stockrooms. By comparing countries it is possible to determine if a particular movement of goods is a home transaction, EC movement, export or import.

The country details contains different types of information:

- General information about a country, such as default currency or date format.
- Intrastat Mask. That is which reporting elements this country requires.
- Country Name Information. Redefining country names for Intrastat and ESL reporting in different countries.
- Information about this company in the country; for example, VAT registration.

Country Parameters Maintenance Selection Screen



To display this screen, select the Country Maintenance option.

Use this screen to select the country you want to maintain.

WT050	Z1 - Demonstration Company	User SP1	22/09/94 14:13:57
Country Parameters Maintenance			
Select	Country	Description	EC Member Collect INTRASTAT data
-	BE	Belgium	0 0
-	DE	Germany	0 0
-	DK	Denmark	0 0
-	EL	Greece	0 0
-	ES	Spain	1 0
-	FR	France	1 0
<u>I</u>	GB	United Kingdom	1 1
-	IE	Ireland	0 0
-	IT	Italy	1 0
-	LU	Luxemburg	0 0
-	NL	Netherlands	0 0
-	PT	Portugal	0 0
			+
1=Amend, 2=Reporting country codes, 4=Delete F3=Exit F10=Add country F19=Position to			

Fields:

Select

Enter one of the following:

- 1 - Amend. To select the country you want to maintain.
- 2 - Reporting Country Codes. To maintain the country codes for this country, using the Intrastat Reporting Countries Window.
- 4 - Delete. To delete the country from World Trade. You must select **F11=Delete** to confirm the deletion.

Functions:

F10

Add Country. Use this function to add a new World Trade country.

F19

Position To: Use this function to move the cursor to a specific country on the list.



Select a country with option 1 - Amend and press **Enter** to display the Country Parameters Maintenance Details Screen.

Country Parameters Maintenance Details Screen



To display this screen, select a country with option 1, or select **F10=Add Country**, on the Country Parameters Maintenance Selection Screen.

Use this screen to enter the VAT, currency and basic reporting details for the selected country.

WT050	W2 - W2 World trade test	User GBJBA1MS	16/10/97 10:59:20
Country Parameters Maintenance			
Country code.....	DE	Germany	
EC Member.....	1	(0=No, 1=Yes)	
Over dist sell threshold....	0	(0=No, 1=Yes)	
Currency code.....?	GBP	Pounds sterling	
VAT Registration.....	44444444444444444444	444	
VAT Registration address....	German VAT registration		
UK nature of transaction....	0	(0=No, 1=Yes)	
Intrastat/ESL print code.?	DE		
Simplify triangulation.....	0	(0=No, 1=Yes)	
SOP declaration.....?			
WT Spex declaration.....?			
F3=Exit F4=Prompt F8=Update F10=More details F12=Previous F14=Reporting country codes F15=Zero-rated VAT codes			
5-35	SA	MW	K5 CL IM DM II STUD140 KB PKH31251

Fields:

(Untitled)

Enter a description for this country.

EC Member

Enter one of the following:

0 - No. If this country is not a member of the EC.

1 - Yes. If this country is a member of the EC.

Over Distance Selling Threshold

Enter one of the following:

0 - No. If this company is not over the threshold for EC distance sales in this country.

1 - Yes. If this company is over the threshold for EC distance sales in this country.

The threshold is a cumulative sales limit to non VAT registered customers in a country, for a twelve month period. You set this flag on historic data or forecasts,

whether or not sales will exceed this limit. If you will exceed the threshold the VAT charge is determined by the country's VAT routine. If you will not exceed the threshold, the VAT charge is determined by the company's VAT routine.



Note: If a company exceeds the limit, you must set the flag to 1 for the following two years, regardless of the sales performance over that two year period.

Currency Code

Enter the default currency for this country. This currency is used for ESL and Intrastat reporting to this country's authorities.

VAT Registration

Enter the VAT registration number of this company in this country.

VAT Registration Address

Enter the address where this company is registered for VAT in this country.

UK Nature Of Transaction

Enter one of the following:

0 - No. Not to print transaction codes on the Intrastat report.

1 - Yes. To print the 2 digit nature of transaction codes on the Intrastat report.



Note: This generates a UK format for reporting, so use this for any country requiring a report in the UK format.

Intrastat/ESL Print Code

Select the printer file to use when sending reports to this countries authorities. You define the valid values on the descriptions file.



Note: The entered value is concatenated with WT805PT to define the Intrastat printer file and with WT815PT to define the ESL printer file.

Simplify Triangulation

Enter one of the following:

0 - No. Not to use the simplified triangulation procedure with this country.

1 - Yes. To use the simplified triangulation procedure with this country when it is the intermediary for a direct delivery, where the customer, supplier and intermediary are all based in different EC countries. In this case no movements are recorded on the intrastat for the intermediary country and this country does not need to register for VAT or intrastat reporting in either the acquiring or disposing country.

SOP Declaration

Enter the additional text to print on an invoice when the simplified triangulation procedure applies and the invoice is printed in SOP invoicing.

WT SPEX Declaration

Enter the additional text to print on an invoice when the simplified triangulation procedure applies and the invoice is printed in SPEX invoicing.

Functions:

F10

More Details. Use this function to display the More Details Screen for this country. All the information you enter on this screen are memo only, and used for reporting purposes.

F11

Delete. Use this function to delete the country details. You must then select **F11=Delete** again to confirm the deletion. This function is only available when you are maintaining a country with no other details, such as customer or supplier details, set up.

F14

Reporting Country Codes. Use this function to display the Intrastat Reporting Countries Window so you can maintain the country codes used on the EC reports. This function is only available when you maintain a country with the Collect Intrastat Data flag to 1 - Yes.

F15

Zero-rated VAT Codes. Use this function to display the Zero-rated VAT Codes Window where you enter the details that distinguish the selling country for items where there is zero VAT.



Press **Enter**. If you set EC Member to 1 - Yes, the Intrastat Reporting Selection Window displays.

Otherwise select **F8=Update** to save the country details.

Intrastat Reporting Selection Window

-  This window displays automatically when you press **Enter** on the Country Parameters Maintenance Details Screen, and the EC Member Flag is set to 1 - Yes.

Use this screen to specify whether or not you require EC reporting.

WT050	Z1 - Demonstration Company	User SP1	22/09/94 14:14:10
Coun	INTRASTAT reporting		
Coun	Country code..... GB United Kingdom		
EC M	Collect INTRASTAT data..... <u>1</u> (0=No, 1=Yes)		
Over	F12=Previous		
Curr	F12=Previous		
VAT Registration.....	456123678	001	
VAT Registration address....	Eagle House		
	The Slough		
	Studley		
	Warwickshire		
	BB0	7 EN	
UK nature of transaction....	<u>1</u>	(0=No, 1=Yes)	
Intrastat/ESL print code?..	<u>GB</u>		
F3=Exit F4=Prompt F8=Update F10=More details F12=Previous F14=Reporting country codes			

Fields:

Collect Intrastat Data

Enter one of the following:

- 0 - No. If you do not require EC reporting.
- 1 - Yes. If you do require EC reporting.

-  Press **Enter** to save changes. If you set the Collect Intrastat Data field to 1 the Intrastat Reporting Details Windows is displayed. If set to 0, the previous screen is redisplayed.

Intrastat Reporting Details Window



To display this window, on the Intrastat Reporting Selection window, set the Collect Intrastat Data filed to 1 and press **Enter**.

Use this screen to define the format of the EC reports.

WT050		Z1 - Demonstration Company		User SP1		22/09/94 14:14:10	
Coun INTRASTAT reporting							
Coun	Country code..... GB United Kingdom						
EC M	Select optional elements :						
Over							
Curr	Intrastat periods..... 12						
VAT	ESL periods..... 4						
VAT	Ancillary value..... 0 (0=No, 1=Yes)						
	Region of origin..... 0 (0=No, 1=Yes)						
	Country of origin..... 1 (0=No, 1=Yes)						
	Port of arrival/despatch..... 0 (0=No, 1=Yes)						
	Port of transshipment..... 0 (0=No, 1=Yes)						
	Statistical procedure..... 0 (0=No, 1=Yes)						
	Commodity code description... 0 (0=No, 1=Yes)						
UK n	Siret number..... 0 (0=No, 1=Yes)						
Intr	Acquisition letter..... A						
	Disposal letter..... D						
F8=Update F12=Previous							
F3=Exit F4=Prompt F8=Update F10=More details							
F12=Previous F14=Reporting country codes							

Fields:

Intrastat Periods

Enter the number of Intrastat reports required per year in this country.

ESL Periods

Enter the number of ESL reports required per year in this country.



Note: The following group of fields are collectively known as the Intrastat mask. The Intrastat mask defines which data is included on the on the Intrastat report for this country.

Ancillary Value

Enter one of the following:

0 - No. If you do not need to include the ancillary value.

1 - Yes. To include the ancillary value on the Intrastat returns.

Region Of Origin

Enter one of the following:

0 - No. If you do not need to include the region.

1 - Yes. To include the region on the Intrastat returns.

Country Of Origin

Enter one of the following:

0 - No. If you do not need to include the country of origin.

1 - Yes. To include the country of origin on the Intrastat returns.

Port Of Arrival/Despatch

Enter one of the following:

0 - No. If you do not need to include the port of arrival or despatch.

1 - Yes. To include the port of arrival or despatch on the Intrastat returns.

Port Of Transshipment

Enter one of the following:

0 - No. If you do not need to include the port of transshipment.

1 - Yes. To include the port of transshipment on the Intrastat returns.

Statistical Procedure

Enter one of the following:

0 - No. If you do not need to include the statistical procedure.

1 - Yes. To include the statistical procedure on the Intrastat returns.

Commodity Code Description

Enter one of the following:

0 - No. If you do not need to include the commodity code description.

1 - Yes. To include the commodity code description on the Intrastat returns.

Siret Number

Enter one of the following:

0 - No. If you do not need to include the Siret Number.

1 - Yes. To include the Siret Number on the Intrastat returns.

Acquisition Letter

Enter the letter to define acquisitions for this country.

Disposal Letter

Enter the letter to define disposals for this country.



Tip: To display the Intrastat Reporting More Details Window, press **Enter** before selecting **F8=Update**.



Select **F8=Update** to check for empty mandatory fields and save changes. The Country Parameters Maintenance Details Screen is displayed.

Intrastat Reporting More Details Window



To display this additional window, press **Enter** on the Intrastat Reporting Details Window.



Note: This window only displays if you set Non-UK Reporting to 1 in the Company Profile.

Use this window to enter the Intrastat and ESL non-UK reporting header information.

WT050 W2 - W2 World trade test User GBJBA1MS 16/10/97 11:12:11

Coun INTRASTAT reporting
INTRASTAT Reporting - More Details

Co Country code..... SE Sweden

EC Nature of Transaction length 1 (1/2)

Ov Contact Name.....

Cu Telephone Number.....

VA FAX number.....

VA Name of signatory.....

Place of signatory.....

Third party name..... THIRD PARTY

Third party address..... THIRD PARTY ADDRESS

UK LINE 2

In LINE 3

Si LINE 4

LINE 5

P1 P2

INTRASTAT Office code.....

F3 F8=Update F12=Previous F14=Statistical Value Rules

F12=Previous F14=Reporting country codes F15=Zero-rated VAT codes

8-40 SA MW K5 CL IM DM II STUD140 KB PKH31251

Fields:

Nature of Transaction Length

Enter the transaction length, either 1 or 2 characters, for this country.

Contact Name

Enter the name of your contact on Intrastat and ESL reporting.

Telephone Number

Enter the telephone number of your contact.

Fax Number

Enter the contact's fax number.

Name of Signatory

Enter the name of the person responsible for the EC reports.

Place of Signatory

Enter the location of the person responsible.

Third Party Name

If applicable, enter the third party name.

Third Party Address

Enter the address and postcode of the third party, using up to six lines.

Intrastat Office Code

Enter the Intrastat code for your office.

Functions:

F14

Statistical Value Rules. Use this function to specify value percentages at different levels of cost detail.



Press **Enter** then select **F8=Update** to save the details and return to the Country Parameters Maintenance Screen.

Statistical Value Rules Window (F14)



To display this screen, select **F14=Statistical Value Rules** in the Intrastat Reporting More Details Window.

Use this to add or amend statistical percentages for each of your terms of delivery. For acquisitions and disposals the statistical value is recalculated in the verification routine.

If you do not add statistical rules then the invoice value is used as the statistical value, unless an ancillary value exists on the purchase or sales order override, in which case that is used.

WT026		W2 - W2 World trade test		User GBJBAIMS		16/10/97	
						11:27:05	
Statistical Value Rules							
Reporting Country SE Sweden							
Select	Terms	A/D	Qty of origin	Region of origin	Customer/Supplier	Percentage	
■	FOB	1			DES01 000	80	
-	FOB	2			DEC01 000	70	
1=Amend 4=Delete							
F10=Add rule F12=Previous F19=Position to							
9-4 SA MW K5 CL IM DM II STUD140 KB PKH31251							

Fields:

Select

Enter one of the following:

- 1 - Amend. To select the delivery term item to amend the percentage displayed.
- 4 - Delete. To exclude the delivery term item from the statistical calculation.



Select a rule with option 1, and press **Enter** to display the Statistical Value Rules Details Screen.



```

WT026                      W2 - W2 World trade test      User GBJBA1MS    16/10/97
                                           11:40:47

Statistical Value Rules

Reporting Country ..... SE  Sweden

Terms of delivery ..?... 1
Acquisition/Disposal .. 1 (1=Acq,2=Dis)
Country of origin ..?...     
Region of origin ..?...     
Customer/Supplier ..?...     
Percentage ..... 00.00

-----
F3=Exit      F4=Prompt      F8=Update      F12=Previous
-----
7-27      SA      MW      K5  CL  IM  DM  II      STU0140      KB      PKH31251

```

1-13

Country of Origin

Select a country to apply the statistical percentage to a country. Leave blank for all countries.

Region of Origin

Select a region to apply the statistical percentage calculation to a region. Leave blank for all regions.

Customer/Supplier

If you set Acquisition/disposal to 1, enter a supplier to apply the statistical percentage calculation at individual supplier level.

If you set Acquisition/Disposal to 2, enter a customer to apply the statistical percentage calculation at individual customer level.

Percentage

Enter the percentage of the value for the displayed level. The percentage is used in the verification routine as follows:

Ancillary Price x Movement Quantity x Percentage = Statistical Value



Press **Enter** to check the information, then select **F8=Update** to save.

More Details Window (F10)



To display this screen, select **F10=More Details** on the Country Parameters Maintenance Details Screen.

Use this screen to enter the memo details used for reporting.

WT050	Z1 - Demonstration Company	User SP1	16 /01 /95 15 :42:07
Country Parameters Maintenance			
More details			
Co	Country code..... GB United Kingdom		
EC	Date format.....	—	
Ov	Address format.....?	—	
Cu	Bank code format.....?	—	
VA	Primary language.....?	—	
VA	Character set.....?	—	
	Numbers as words.....	0	(0=No, 1=Yes)
	Bank code check digit....	0	(0=No, 1=Yes)
	Tax code check digit....	0	(0=No, 1=Yes)
	Main/other form length...	66	66
UK	Analysis code.....	—	
In	F4=Prompt F12=Previous		
F3=Exit F4=Prompt F8=Update F10=More details F12=Previous F14=Reporting country codes			

Fields:

Date Format

Enter one of the following:

- 1 - To display the date as Day, Month, Year (DD/MM/YY).
- 2 - To display the date as Month, Day, Year (MM/DD/YY).
- 3 - To display the date as Year, Month, Day (YY/MM/DD).

Address Format

Select the format to use for the address.

Bank Code Format

Select the bank code format to use for this country.

Primary Language

Select the primary language for this country. This is the language in which the Intrastat and ESL reports are printed.

Character Set

Select the character set for this country.

Numbers As Words

Enter one of the following:

0 - No. To print the numbers as numbers on external documentation.

1 - Yes. To print the numbers as words on external documentation.

Bank Code Check Digit

Enter one of the following:

0 - No. If the bank code does not include a check digit.

1 - Yes. If the bank code includes a check digit.

Tax Code Check Digit

Enter one of the following:

0 - No. If the tax code does not include a check digit.

1 - Yes. If the tax code includes a check digit.

Main/Other Form Length

Enter the length of the main and secondary forms, in number of lines.

Analysis Codes

These fields are memo and user defined.



Press **Enter** to save changes to the screen and return to the Country Parameters Maintenance Details Screen.

Intrastat Reporting Country Codes Window (F14)

 To display this screen, either select a country with option 2 on the Country Parameters Maintenance Selection Screen, or select **F14=Reporting Country Codes** from the Country Parameters Maintenance Details Screen.

Use this screen to create a table of the country codes to use on the EC reports produced for this country. You must enter the codes defined by the government of the country being maintained. The codes can be different for the Intrastat and the ESL. The list of countries is set up in Application Manager.

WT050 Z1 - Demonstration Company User SP1 22/09/94 4:45

INTRASTAT reporting More: +

Coun Country code..... GB United Kingdom

Coun Define reporting country codes :

Country	INTRASTAT	ESL
BE Belgium	BL	BE
DE Germany	DE	DE
DK Denmark	DK	DK
EL Greece	GR	EL
ES Spain	ES	ES
FR France	FR	FR
GB United Kingdom	GB	GB
IE Ireland	IE	IE
IT Italy	IT	IT
LU Luxemburg	BL	LU

Intr F8=Update F12=Previous

F3=Exit F4=Prompt F8=Update F10=More details
F12=Previous F14=Reporting country codes

Fields:

Intrastat

Enter the code to use for this country on the Intrastat for the country being maintained.

ESL

Enter the code to use for this country on the ESL for the country being maintained.



Tip: These codes are specific to the country being maintained and only appear on reports submitted to the authorities of this country.



Select **F8=Update** to save changes and return to the previous screen.

Zero-Rated VAT Codes Window (F15)



To display this windows, select **F15=Zero-Rated VAT Codes** on the Country Parameters Maintenance Basic Details screen.

Use this screen to enter the details for updates used for zero-rated VAT movements.

The screenshot shows the 'Zero-rated VAT Codes' window (F15) overlaid on the 'Country Parameters Maintenance' screen. The background screen displays information for 'Z1 - UK Demonstration Company' with user 'GBJBANB4' on '7/04/98' at '10:29:47'. The 'Country code' is 'FN Finland'. Other fields include 'EC Member' (1), 'Over dist sell threshold' (0), 'Currency code', 'VAT Registration', 'UK nature of trade', 'Intrastat/ESL p', 'Simplify triang', 'SOP declaration', and 'WT Spex declaration'. The 'Zero-rated VAT Codes' window contains the following fields:

- Accounts Payable VAT Updates
 - Purchase triangulation VAT code...?.. ___
 - Import VAT code.....?.. ___
- Accounts Receivable VAT Updates
 - EU Zero-rated VAT code.....?.. ___
 - Export VAT code.....?.. ___

Navigation keys at the bottom of the window: F4=Prompt F12=Previous. At the bottom of the background screen: F3=Exit F4=Prompt F8=Update F10=More details F12=Previous F14=Reporting country codes F15=Zero-rated VAT codes. The status bar at the bottom shows '12/058'.

Fields:

Accounts Payable VAT Updates

Purchase Triangulation VAT Code

Enter the VAT code to use for all purchases in this country where you use simplified triangulation for Zero-rated VAT goods.

Import VAT Codes

Enter the VAT code used to update Accounts Payable for zero-rated goods imported into this country.

Accounts Receivable VAT Updates

EU Zero-Rated VAT Code

Enter the VAT code to use for all goods bought within the EU which have zero-rated VAT.

Export VAT Code

Enter the VAT code to use in Accounts Receivable for all goods with zero-rated VAT exported from this country.



Press **Enter** to save the information. This displays the Intrastat Reporting Window.

Period Maintenance

1... **2...** 2/WTM

Use the Period Maintenance option to define the time span covered by the Intrastat and ESL reports.

You define these periods for calendars previously defined on the Inventory descriptions file.

Period Maintenance Selection Screen



To display this screen, select the Period (Maintenance) option.

Use this screen to select the calendar and country for which you want to maintain period details.

WT070	Z1 - Demonstration Company	USER SP1	22/09/94 13:29:35
Period Maintenance			
Calendar code?.. <u>001</u>		Country code?.. <u>GB</u>	
F3=Exit F4=Prompt			

Fields:

Calendar Code

Enter a calendar code defined on the Inventory descriptions file, under major type CALT.

Country Code

This field may only be specified if the percentage/value field on the description of the calendar is set to P, that is to identify that this calendar varies by country.

The entered value must be a valid country code.



Press **Enter** to check for empty mandatory fields, if none exist, the Period Maintenance screen is displayed.

Period Maintenance Screen



To display this screen, enter the details and press Enter on the Period Maintenance Selection Screen.

The period numbers are automatically generated according to the following rules:

- Calendars 001 and 002: The number of periods each year is determined from the values entered on the country profiles for Intrastat and ESL periods.
- Other calendars: The number of periods each year is determined from the value entered in the rate field on the calendar description. If no value is specified the default is 12.

WT070	Z1 - Demonstration Company	USER SP1	22/09/94 13:29:47
Period Maintenance			
Calendar code 001		Country code GB	
Period	End date		
93-01	310193		
93-02	280293		
93-03	310393		
93-04	300493		
93-05	310593		
93-06	300693		
93-07	300793		
93-08	310893		
93-09	300993		
93-10	311093		
93-11	301193		
93-12	311293		
94-01	310194	+	
F3=Exit F8=Update F12=Previous			

Fields:

End Date

Enter the end date for the period using DDMMYY date format. Start dates are automatically calculated.



Select **F8=Update** to save any changes and return to the previous screen.

Stockroom Maintenance



3/WTM

Use this option to define the stockroom, country and the customer code for distribution orders.



Note: you define the stockrooms using Inventory Management.

Define Stockroom Details Selection Screen

 To display this screen, select the Stockroom (Maintenance) option.

Use this screen to select the stockroom you want to maintain.

WT020 Z1 - Demonstration Company User SP1 22/09/94
12:26:32

Define Stockroom Details

Select	Stockroom
-	F1 Paris Central Stockroom
-	WH Central Warehouse
<u>1</u>	01 Central Stockroom
-	02 Northern RDC Stockroom
-	03 Southern RDC Stockroom

1=Select
F3=Exit

Fields:

Select

Enter 1 to select the stockroom you want to maintain.

 Select a stockroom with option 1 and press **Enter**. The Define Stockroom Details Screen is displayed.

Define Stockroom Details Screen



To display this screen, select a stockroom with option 1 and press **Enter** on the Define Stockroom Details Selection Screen.

Use this screen to enter the stockroom details.

WT020	Z1 - Demonstration Company	User SP1	22/09/94 12:26:32
Define Stockroom Details			
Stockroom.....	01	Central Stockroom	
Country.....?	<u>GB</u>	United Kingdom	
Region.....?	<u> </u>		
Internal Customer.....?	<u>C1</u>	Internal Customer (Supply	
F3=Exit F4=Prompt F12=Previous			

Fields:

Country

Enter the country in which the stockroom is located.

Region

Enter the region in which this stockroom is located.

Internal Customer

Enter the customer to use for a distribution order with this stockroom as the destination.



Note: The internal customer must be a Sales Order Processing customer with a delivery sequence of 001.



Press **Enter** to save changes and return to the previous screen.

Item Maintenance



4/WTM

Use this option to enter extra details about an item for EC reporting and export documentation.



Note: All items used must already exist in Inventory Management, in the Inventory Item Master file.

Item Trade Details Screen



To display this screen, enter an item and press **Enter** on the Item Trade Details Selection Screen.

Use this screen to enter the details for the selected item.

WT035		Z1 - UK Demonstration Company		User GBJBANB4	7/04/98
					10:54:16
Item Trade Details					
Item	5001	Suncream Factor 4 225ml			
Commodity code	71022900	Other class 2			
Other class 1					
Commodity type	1				
Country of origin					
Issue UoM to net kilos	1.00000				
Issue UoM to gross kilos ..	1.00000				
2nd quantity UoM					
Issue UoM to 2nd quantity ..	1.00000				
Issue UoM cubic metres	1.00000				
Customs and excise price ..	50.00000				
Ancillary price					
Packing instructions					
F3=Exit F4=Prompt F12=Previous F13=Country VAT codes					
MA a					07/030

Fields:

Commodity Code

Enter the harmonised commodity code for the selected item. The first 8 digits are included on the Intrastat report. The remaining digits are for the full information for exports outside the EC and CAP details.



Note: You must have defined these codes to the major type TAR in the Inventory descriptions file.

Other Class 1

Enter the other class 1 for this product. Other class 1 is concatenated with other class 2 to form the key to the goods file when performing allocation in the export documentation software.

For hazardous goods enter UN concatenated with the UN number.

Other Class 2

Enter the other class 2 for this product. Other class 2 is concatenated with other class 1 to form the key to the goods file when performing allocation in the export documentation software.

For hazardous goods enter the flashpoint.



Warning: Do not put spaces within the data in the other classification fields.

Commodity Type

Enter the commodity type for this item:

This type determines for each type of transaction whether reporting occurs on the ESL and Intrastat, and what VAT accruals occur.

If an item has no World Trade details, the default is 1 - Standard item.

Country Of Origin

Enter the country of origin for this item. This does not need to be the supplier's country.

Issue UOM To Net Kilos

Enter the net mass of the goods, that is the mass without packaging, in kilograms per item master issue unit. This is required for the Intrastat.

Issue UOM To Gross Kilos

Enter the gross mass of the goods, that is the mass with packaging, in kilograms, per item master issue unit. This may be used in export documentation.

Second Quantity UOM

Enter a second unit of measure for the goods, if one is required for the specified commodity code . If entered, you must complete the Issue UoM To 2nd Quantity UOM field.

Issue UOM To 2nd Quantity UOM

Enter the number by which the issue unit is multiplied to give the quantity in the second unit of measure.

Issue UOM To Cubic Metres

Enter the volume of the goods, in cubic metres, per inventory item issue unit. This may be used in export documentation.

Customs And Excise Price

Enter the value of the goods to use for VAT and Intrastat purposes, if no invoice or order value is available. The value should be in the currency of the Inventory Management company. If this is blank, the inventory cost is used.

Ancillary Price

Enter the ancillary price to use when calculating the ancillary value for some EC countries. This is used with the statistical value percentage entered for the Country.



*Note: This field displays if you use Intrastat and
ESL Requirements for Additional EEC Countries.*

Packing Instructions

Enter the packing instructions to print on any export documentation.

Functions:

F13

Country Vat Codes. Use this function to enter the VAT codes for selected countries using the Item/Country VAT Code Maintenance Window.



Press **Enter** to check for empty mandatory fields, and then save changes. This selection screen is then redisplayed.

Item/Country VAT Code Maintenance Window (F13)



To display this screen, select **F13=Country VAT Codes** on the Item Trade Details Screen.

Use this window to enter the VAT codes that apply if an item is sold domestically in the selected country. This information is used to determine the correct VAT code in Sales Order Processing Invoicing and Purchase Management Invoice Matching routines.

WT035		Z1 - Demonstration Company		User SP1	22/09/94 12:55:49
Item Trade Details					
Item					
Commodity code ...					
Other class 1					
Commodity type ...					
Country of origin					
Issue UoM to net k					
Issue UoM to gross					
2nd quantity UoM .					
Issue UoM to 2nd q					
Issue UoM cubic me					
Customs and excise					
Packing instructio					
F3=Exit F4=Prompt F12=Previous F13=Country VAT codes					

Item/Country VAT code maintenance		
More : +		
Sel	Country(?)	VAT(?)
-	FR France	0
-	IE Ireland	1
-	GB United Kingdom	1
1=Amend 4=Delete		
F4=Prompt F8=Update F12=Previous		

Fields:

Sel

Selection field. Enter one of the following:

1 - Amend. To maintain the country VAT code in the fields at the bottom of the window.

4 - Delete. To delete a country VAT code, select **F11=Delete** to confirm deletion.

Country

To define a new country, enter the country.

VAT

Enter the VAT code to apply to this item in the selected country.



Press **Enter** to save changes to a line, then select **F8=Update** to save all the information and return to the previous screen.

Customer Maintenance



5/WTM

Use this option to define the customer attributes required for EC reporting and Export Documentation.

These attributes centre on gathering extra information about each customer delivery point. You can maintain this either from World Trade or Customer Maintenance in Sales Order Processing or Accounts Receivable.

World Trade uses this information to identify whether the transaction is a domestic, EC or non-EC movement.

Customer Trade Details Screen

 To display this screen, select Customer (Maintenance).

Use this screen to select the customer you want to maintain.




WT009	Z1 - Demonstration Company	User SP1	22/09/94 12:28:08
Customer Trade Details			
Customer?.. <u>G001</u> <u>000</u>			
F3=Exit F4=Prompt			

Fields:

Customer

Enter the customer account and delivery sequence numbers.

 Press **Enter** to display the Maintain Customer Trade Details Window.



Enter the terms of delivery. This defaults from the customer master file.

Enter 1 or 2 in the fourth digit if you use Intrastat and ESL Requirements for Additional EEC Countries. That is, Non-UK Reporting in your company profile is set to 1.

Port Of Despatch

Enter the default port of despatch for this customer.

Port Of Transshipment

Enter the default port of transshipment for this customer.

Statistical Procedure

Enter the default statistical procedure for this customer.

Siret Number

Enter the Siret number for this customer. This is a requirement for the French authorities.

Functions:

F13

Export Details. Use this function to maintain the export details, if you need export documentation for this address.



Press **Enter** to save any changes and return to the previous screen.

Export Details Maintenance Window (F13)

 To display this window, select **F13=Export Details** on the Maintain Customer Trade Details Window.

Use this screen to enter the information required for export documentation. The prompt fields display information set up in World Trade SPEG.

WT009

Z1 - Demonstration Company

User SP1

22 /09/94
12:31:36

Customer Trade Details

Customer?.. GC01 000

Maintain Customer Trade Details
Reeves Chemist's
Country?.. GB
VAT country?.. GB
VAT re
Terms
Port o
Port o
Statis
Siret
F4=Prom

Export Details Maintenance
Place of delivery?..
Marks
F4=Prompt F12=Previous F13=Export address details

F3=Exit F4=Prompt

Fields:

Place Of Delivery

Enter the default place of delivery for this customer. This must be defined on the Inventory descriptions file.

Marks

Enter the default marks for this customer. This is free format text used to describe the contents of the goods being exported.

Functions:

F13

Export Address Details. Use this function to maintain further details for the export documentation.

 Press **Enter** to save changes and return to the previous screen.

Export Address Details Maintenance Window (F13)



To display this window, select **F13=Export Address Details** on the Export Details Maintenance Window.

Use this screen to enter further information for export documentation. This information can be automatically included on the relevant shipping screens using the autoload facility within World Trade SPEX.

WT009 NR - Neil Radford and Co. Ltd User G8JBA1MS 28/06/96 15:22:58

Customer Trade Details

Customer?.. 1352_003 000

Maintain Customer Trade Details

1352_003 Customer Name ----->

Export Address Details Maintenance

Exporter ..?.. _____	Export cargo shipping instructions ..?.. _____
Bank?.. _____	Bill of exchange information?.. _____
Other?.. _____	Notify party 1: letter of credit ...?.. _____
Forwarder ..?.. _____	Notify party 2: letter of credit ...?.. _____
Declarant ..?.. _____	Invoice text 1?.. _____
Principal ..?.. _____	Invoice text 2?.. _____
Carrier ...?.. _____	Transit point?.. _____
Signatory ..?.. _____	Terms of payment?.. _____
Autorun ...?.. _____	Country of despatch.....?.. _____

F4=Prompt F12=Previous

F3=Exit F4=Prompt

12-20 SA MW KS IM II KENB20A PET087S1

Fields:



Note: The data you enter here must be set up in the World Trade SPEX master files.

Exporter

Enter the default exporter for this customer.

Export Cargo Shipping Instructions

Enter the default Export Cargo Shipping Instructions for this customer.

Bank

Enter the default bank for this customer.

Bill Of Exchange Information

Enter the default bill of exchange information for this customer.

Other Address

Enter another address required for this customer.

Notify Party 1

Enter the first person to notify party when paying by letter of credit.

Forwarder

Enter the default forwarder for this customer.

Notify Party 2

Enter the second person to notify when paying by letter of credit.

Declarant

Enter the default declarant for this customer.

Invoice Text 1

Enter the first piece of default invoice text for this customer.

Principal

Enter the default principal for this customer.

Invoice Text 2

Enter the second piece of default invoice text for this customer.

Carrier

Enter the default carrier for this customer.

Transit Point

Enter the default transit point for this customer.

Signatory

Enter the default signatory for this customer.

Terms Of Payment

Enter the default terms of payment for this customer.

Autorun

If you your version of SPEX supports documentation prior to despatch (For example, SPEX V3.00), you can assign autorun codes at customer level. The autorun code assigned to the customer is carried onto each shipment when you create it.

Country Of Despatch

Enter the default country of despatch for this customer. These details are maintained within World Trade itself.



Note: This value is not used when determining From and To countries for EC reporting, or, determining whether or not to create a shipment.



Press **Enter** to save changes to the screen and return to the previous screen.

Supplier Maintenance



6/WTM

Use this option to define the supplier attributes required for EC reporting.

You can also maintain these details in Supplier Maintenance in Accounts Payable.

World Trade uses this information to determine whether the transaction is a domestic, EC, or non-EC movement.

Supplier Trade Details Screen

 To display this screen, select Supplier (Maintenance).

Use this screen to select the supplier you want to maintain.

WT014 Z1 - Demonstration Company User SP1 22/09/94
12:37:55

Supplier Trade Details

Supplier?.. FS01 000

F3=Exit F4=Prompt

Fields:

Supplier

Enter the supplier name and address.

 Press **Enter** display the Maintain Supplier Trade Details Window.

Enter 1 or 2 in the fourth digit if you use Intrastat and ESL Requirements for Additional EEC Countries.

Port Of Arrival

Enter the default port of arrival for this supplier.

Port Of Transhipment

Enter the default port of transhipment for this supplier.

Statistical Procedure

Enter the default statistical procedure for this supplier.

Siret Number

Enter the Siret number for this supplier. This is a requirement for the French authorities.



Press **Enter** to save changes to the screen and return to the previous screen.

Charge Codes Maintenance



7/WTM

Use this option to enter the VAT code that applies if you add a charge to a domestic despatch in the selected country. This information is used to determine the correct VAT code in Sales Order Processing invoicing.

Charge Codes/Country VAT Code Maintenance Screen



To display this screen, select Charge Codes
(Maintenance).

Use this screen to select the Charge Code for the Charge Code/Country VAT
Code Maintenance.

WT040	Z1 - Demonstration Company	User SP1	22/09/94 13:30:11
Charge Code / Country VAT Code Maintenance			
Charge code.....?.. <u>01</u>			
F3=Exit F4=Prompt			

Fields:

Charge Code

Enter the charge code to maintain.



Press **Enter** to check for a valid charge code.
The Charge Codes VAT Code Maintenance
window is displayed.

Charge Codes VAT Code Maintenance Window



To display this window, enter a charge code and press **Enter** on the Charge Codes/Country VAT Code Maintenance Screen.

Use this window to select and maintain the country VAT code.

WT040 Z1 - Demonstration Company User SP1 22/09/94 13:30:57

Charge Code / Country VAT Code Maintenance

Charge code.....?.. 01 Carriage Charge

Sel	Country(?)	More :	VAT(?)
-	FR France		002
-	GB United Kingdom		000
-	IT Italy		003
-	US United States		004

F1=Amend F4=Delete
F4=Prompt F8=Update F12=Previous
F3=Exit F4=Prompt

Fields:

Sel

Selection field. Enter one of the following:

1 - Amend. To select a country VAT code to maintain. The selected country and VAT code is displayed in the lower part of the window for you to amend.

4 - Delete. To delete a country VAT code.

Country

Enter a country for which VAT codes must be defined.

VAT Code

Enter the VAT code to apply for this country.



Press **Enter** to save changes made to individual lines. Then select **F8=Update** to save all changes and return to the menu.

Item Mass Maintenance



11/WTM

Use this option to update Item Trade Details across a range of items.

Item Mass Maintenance is a two phase process. You define the items to maintain by entering ranges of various attributes. Then set the defaults for the selected items. A batch job performs the updates.

The selections are all mutually inclusive. For example, if you enter a range of item numbers and item types, then the selected items satisfy both the item number and item type restrictions.

Item Mass Maintenance Selection Criteria Screen



To display this screen, select Item (Mass Maintenance).

Use this screen to select the item and attribute range to maintain.

WT065	Z1 - Demonstration Company	User SP1	22/09/94 13:25:42
Item Mass Maintenance : Selection Criteria			
Item.....	From 5001	To 5004	
OR item mask....			
Item type.....?..	—	—	
Item class.....?..	—	—	
Major group.....?..	—	—	
Minor group.....?..	—	—	
Division.....?..	—	—	
Sub division....?..	—	—	
Issue unit.....?..	—	—	
F3=Exit F4=Prompt			

Fields:

Item

Enter the start and end of a range of items to process.

This option is mutually exclusive with entering an item mask.

Item Mask

This option is mutually exclusive with entering an Item range.

Enter a mask to use to select items by specifying either the required character or _ and * as wildcards. You must enter all 15 characters. For example, '_ _ A _ B _ _ _ _ _ _ _ _ _ _ _ _ _' selects any item with A as the third character and a B as the sixth character, 1* selects any item with a 1 in it, and 1 _ _ _ _ _ _ _ _ _ _ _ _ _ selects only those that begin with a 1.



Tip: You can also enter ranges of item classification to further define the selection.



Note: Specify a From field, but not To field, to maintain a range of items starting from, and including, the From through to the last item. If you specify a To field without a From field, the job maintains a range of items from the start through to, and including, the specified To item.



Note: Example; if you set up items AA to AZ, and item classes A to E, a selection of From item AQ and T' item class B, maintains all items from AQ to AZ which had an item class A or B.

Item Type

Enter a range of item types.

Item Class

Enter a range of item classes.

Major Group

Enter a range of item major groups.

Minor Group

Enter a range of item minor groups.

Division

Enter a range of divisions.

Sub Division

Enter a range of sub divisions.

Issue Unit

Enter a range of issue units.



Note: An Item Mass Maintenance Audit Report is available once the job completes. Use this to confirm the selection criteria and the requested field changes submitted.



Press **Enter** to display the Item Mass Maintenance Map To Fields Screen.

Item Mass Maintenance Map To Fields Screen



To display this screen, enter the selection criteria and press **Enter** on the Item Mass Maintenance Selection Criteria Screen.

Use this screen to enter default field contents for the items selected on the first screen.

WT065	W2 - W2 World trade test	User GBJBA1MS	16/10/97
Item Mass Maintenance : Map to Fields			12:37:20
Commodity code.....?	71022900		
Other class 1		Other class 2	
Commodity type.....?			
Country of origin.....?	SE		
Issue VoM to net kilos....	00000		
Issue VoM to gross kilos..	00000		
2nd quantity VoM.....?			
Issue VoM to 2nd quantity..	00000		
Issue VoM cubic metres....	00000		
Customs and excise price..	00000		
Ancillary price	90000		
Packing Instructions.....			
F3=Exit F4=Prompt F8=Submit job F12=Previous F13=Country VAT codes			
5-29	SA	MW	KS CL IM DM II
STUD140		KB	PKH31251



Note: If you leave a field blank, then it is not changed in the records to be updated.

Fields:

Commodity Code

Enter the harmonised commodity code for the selected items. The first 8 digits are included on the Intrastat report. Use the remaining digits to enter the full information for exports outside the EC and CAP details.

Other Class 1

Enter the other class 1 for this product. Other class 1 is concatenated with other class 2 to form the key to the goods file when performing allocation in the export documentation software.

For hazardous goods enter UN concatenated with the UN number.

Other Class 2

Enter the other class 2 for this product. Other class 2 is concatenated with other class 1 to form the key to the goods file when performing allocation in the export documentation software.

For hazardous goods enter the flashpoint.



Warning: Do not put spaces within the data in the other classification fields.

Commodity Type

Enter the commodity type for this item.

This type determines for each type of transaction whether or not reporting occurs on the ESL and Intrastat, and what VAT accruals occur.

Country Of Origin

Enter the country of origin, or original manufacturer, for this item. It does not need to be the same as the supplier's country.

Issue UOM To Net Kilos

Enter the net mass of the goods, that is the mass without packaging, in kilograms, for the issue unit.

Enter 0 to make sure fields are not changed on current records but set the value to 1 on new records.

Issue UOM To Gross Kilos

Enter the gross mass of the goods, that is the mass with packaging, in kilograms, for the issue unit.

Enter 0 to make sure fields are not changed on current records but set the value to 1 on new records.

Second Quantity UOM

If required for the specified commodity code, enter a second unit of measure for the goods. If you complete this field, you must complete the Issue UoM to 2nd Quantity field.

Issue UOM To 2nd Quantity

Enter the number by which the issue unit, as defined on the inventory item, is multiplied to give the quantity in the second unit of measure.

Enter 0 to make sure fields are not changed on current records but set the value to 1 on new records.

Issue UOM Cubic Metres

Enter the volume of the goods, in cubic metres per inventory item issue unit.

Enter 0 to make sure fields are not changed on current records but set the value to 1 on new records.

Customs And Excise Price

Enter the price per issue unit of the goods for VAT and Intrastat purposes, if no invoice or order value is available. The value should be in the currency of the Inventory Management company. If no value is entered then the inventory cost is used.

Enter 0 to make sure fields are not changed on current records.

Ancillary Price

Enter the ancillary price used to calculate the ancillary value for some EEC countries. It is used in conjunction with the statistical value percentage entered for the Country.



*Note: This field displays if you use Intrastat and
ESL Requirements for Additional EEC Countries.*

Packing Instructions

Enter the packing instructions to print on any export documentation. This field is for reference only.

Functions:

F13

Country VAT Codes. Use this function to specify the VAT codes for specified countries for this range of items.



Select **F8=Update** to submit the batch job to
update the details against the selected items.

Item Mass Country VAT Window (F13)



To display this window, select **F13=Country Vat Codes** on the Item Mass Maintenance Map To Fields Screen.

Use this window to select the VAT code for the items being maintained.

WT065 Z1 - Demonstration Company User SP1 22/09/94
13:26:41

Item Mass Maintenance : Map to Fields

Commodity code.....?.. 71022900 - _____
Other class 1 Other class 2
Commodity type..... 1
Country of origin.....?.. -

Issue UoM to net kilos.... -
Issue UoM to gross kilos.. -
2nd quantity UoM.....?.. B
Issue UoM to 2nd quantity. -
Issue UoM cubic metres.... -
Customs and excise price.. -

Packing Instructions..... -
-
-

Country VAT Codes

Country	VAT(?)
BE Belgium	___
DE Germany	___
DK Denmark	___
EL Greece	___
ES Spain	___
FR France	___
GB United Kingdom	___
IE Ireland	___
IT Italy	___
LU Luxemburg	___

More: +

F4=Prompt F8=Update F12=Previous
F3=Exit F4=Prompt F8=Submit job F12=Previous F13=Country VAT codes

Fields:

VAT Code

Enter the VAT code for the items if they are sold domestically in the selected country. This information is used to determine the correct VAT code in Sales Order Processing Invoicing and Purchase Management Invoice Matching routines.



Select **F8=Update** to save changes and return to the previous screen.

Customer Mass Maintenance



12/WTM

Use this option to maintain a range of customer delivery addresses in the same session.

World Trade Customer Quick Entry is a two stage process.

- First you define which fields you want to maintain in the session and set up default values for certain fields.
- Then define the customers you want to maintain and specify if you want to override any defaults entered.



Use this screen to define the fields you want to maintain and to set up certain default values.

```

WT060                                W2 - W2 World trade test      User GBJBAIMS    16/10/97
                                           11:57:46

Customer Details - Quick Entry Session Defaults

                                Dsp Default
Country .....?.. *
Region .....?.. *
Terms of delivery .....?.. * *
Port of despatch .....?.. 0 *
Port of transhipment .....?.. 0 *
Statistical procedure .....?.. 0 *
Siret number .....?.. 0 *

F3=Exit      F4=Prompt

7-31  SA  MW  K5  CL  IM  DM  II  STUD140  KB  PKH31251

```


If you use Intrastat and ESL Requirements for Additional EEC Countries, you can enter a fourth digit of either 1 or 2 depending on your country's requirements on terms of delivery.

Dsp

Enter one of the following alongside each option:

0 - Not to display this field on the next screen.

1 - To display this field on the next screen so you can maintain it. You must then enter the default value.

Port Of Despatch

Enter the default port of despatch for customers.

Port Of Transhipment

Enter the default port of transhipment for customers.

Statistical Procedure

Enter the default statistical procedure for customers.

Siret Number

This is a requirement for the French authorities and is unique to each customer.

If the details of a customer with a number of delivery addresses require maintenance, enter the default siret number for the customer.



Press **Enter** to display the Customer Mass
Maintenance Customer Detail Screen.

Customer Mass Maintenance Customer Detail Screen



To display this screen, press **Enter** on the Customer Mass Maintenance Defaults Screen.

Use this screen to define the customers requiring maintenance and enter any defaults to override.

W0006	GB Demonstration Company	USER GBJBANB1	9/04/98 14:59:31
Company Profile Maintenance			
Time interval:	0:30	(HH:MM)	
Service window - Start:	8:00 a	(HH:MM a/p/n)	
Service window - Finish:	5:30 p		
Display diary from:	8:00 a	(defaults to system time)	
Reserved time buffer:			
Day	From	To	
Mon	8:00 a	5:30 p	
Tue	8:00 a	5:30 p	
Wed	8:00 a	5:30 p	
Thu	8:00 a	5:30 p	
Fri	8:00 a	5:30 p	
Sat	0:00 a	0:00 a	
Sun	0:00 a	0:00 a	
Display reserve time as available time (0=No, 1=Yes) 0			
F3=Exit F12=Previous			

Fields:

Customer

Enter the customer account number.

Seq

Enter the delivery sequence number.



Tip: Enter * in any of the following fields to specify that the current value of this field should not be changed for any existing World Trade customer master records.



Note: If this is a delivery address, and is in the same country as the statement address, then there is no need to re-enter the following fields.

Cty

Enter the country of this customer address. You do not need to enter this for a delivery address.

VAT Cty

Enter the country in which this customer is registered for VAT purposes.

VAT Registration

Enter the customer's VAT registration in the specified country.

Trm Del

Enter the default terms of delivery for this customer.

If you use Intrastat and ESL Requirements for Additional EEC Countries, you can enter a fourth digit of either 1 or 2 depending on your country's requirements on terms of delivery.

Port Of Despatch

Enter the default port of despatch for this customer.

Port Of Transhipment

Enter the default port of transhipment for this customer.

Statistical Procedure

Enter the default statistical procedure for this customer.

Siret Number

Enter the customer's Siret number. This is a requirement for the French authorities.

Functions:

F15

Restart. Use this function to return to the first screen to totally restart the customer mass maintenance procedure.



Select **F8=Delete** to save the changes and exit to the menu.

Supplier Mass Maintenance



13/WTM

Use this option to maintain a range of suppliers in the same session.

World Trade Supplier Quick Entry is a two stage process.

- First screen define which fields you want to maintain and set up default values for certain fields.
- Then define the suppliers and enter any defaults to override.

Supplier Details Quick Entry Session Defaults Screen



To display this screen, select Supplier (Mass Maintenance).

Use this screen to select the fields to maintain and set up certain default values.

WT065		Z1 - UK Demonstration Company		User GBJBANB4		7/04/98	
						10:49:53	
Supplier Details - Quick Entry Session Defaults							
				Dsp Default			
Country	?			*			
Region	?			*			
Terms of delivery	?			*	*		
Port of arrival	?	0		*			
Port of transhipment	?	0		*			
Statistical procedure	?	0		*			
Siret number	?	0		*			
F3=Exit F4=Prompt							
MA		a				07/031	

Fields:



Tip: Enter * in any of the following fields to specify that the current value of this field should not be changed for any existing World Trade supplier master records.

Country

Enter the default country in which the suppliers are located.

Region

Select a region associated with the suppliers.



Note: You set up regions against Inventory Descriptions Type RGNO.



Note: This field displays if you use Intrastat and ESL Requirements for Additional EEC Countries. That is, Non-UK Reporting in your company profile is set to 1.

Terms Of Delivery

Enter the default terms of delivery for suppliers to be maintained.

If you use Intrastat and ESL Requirements for Additional EEC Countries, you can enter a fourth digit of either 1 or 2 depending on your country's requirements on terms of delivery.



Note: For each of the following fields, you specify whether the field displays on the Supplier Details Quick Entry Screen using the Dsp field. Enter 1 to display the field, 0 Not to display the field.

Only complete the fields, if you set Dsp to 1.

Port Of Arrival

Enter the default port of arrival for suppliers maintained in this session.

Port Of Transshipment

Enter the default port of transshipment for suppliers maintained in this session.

Statistical Procedure

Enter the default statistical procedure for suppliers maintained in this session.

Siret Number

This is a company number, unique to each supplier, used by the French authorities. To maintain one supplier with a number of despatch addresses, enter the default siret number for that supplier.



Press **Enter** to display the Supplier Details Quick Entry Screen.

Supplier Details Quick Entry Screen



To display this screen, press **Enter** on the Supplier Details Quick Entry Session Defaults Screen.

Use this screen to define the suppliers requiring maintenance and enter any defaults to override.

WT055		W2 - W2 World trade test				User GBJBA1MS		16/10/97 12:22:30	
Supplier Details - Quick Entry									
Supplier	Seq	Cty	Rgn	VAT	VAT	registration	Trm	Del?	
?		?	?	Cty?					
■		*	*	*	*		*	*	
		*	*	*	*		*	*	
		*	*	*	*		*	*	
		*	*	*	*		*	*	
		*	*	*	*		*	*	
		*	*	*	*		*	*	
		*	*	*	*		*	*	
+									
F3=Exit		F4=Prompt		F8=Update		F15=Restart			
8-2		SA	MW	K5	CL	IM	DM	II	STUD140 KB PKH31251

Fields:

Supplier

Enter the supplier account code.

Seq

Enter the despatch sequence number code.



Tip: Enter * in any of the following fields to specify that the current value of this field should not be changed for any existing World Trade supplier master records.

Cty

Enter the country in which this supplier address is located.

Trm Del

Enter the default terms of delivery for the suppliers, for example, Ex Works.

If you use Intrastat and ESL Requirements for Additional EEC Countries, you can enter a fourth digit of either 1 or 2 depending on your country's requirements on terms of delivery.

Port Arr

Enter the default port of arrival for this supplier.

Port Tran

Enter the default port of transhipment for this supplier.

Statistical Procedure

Enter the default statistical procedure for this supplier.

Siret Number

This is a requirement for the French authorities. Enter the supplier's Siret number.

Functions:

F15

Restart. Use this function to return to the previous screen, so you can complete re-specification of the fields to maintain and the default field values.



Select **F8=Update** to save the changes and exit to the menu.

Item File Listing



21/WTM

This report lists the World Trade details for selected items. The report attributes are:

- Frequency - As required.
- Stationery - Standard listing paper.
- Print Positions - 132.
- New Page - Page overflow.
- Totals - None.
- Sequence - Item number.

World Trade Item Reporting Screen



To display this screen, select Item (File Listing).

Use this screen to define the items listed on the report.

WT900	Z1 - Demonstration Company	User SP1	23/09/94 11:34:54
World Trade Item Reporting			
Item.....	From 5001	To 5004	
OR item mask....			
Item type.....?	-	-	
Item class.....?	-	-	
Major group.....?	-	-	
Minor group.....?	-	-	
Division.....?	01	03	
Sub division.....?	-	-	
Issue unit.....?	-	-	
F3=Exit F4=Prompt F8=Submit			

Fields:

Item Range

Enter the range of item numbers to process.



Note: You cannot enter an Item Range and an Item Mask.

Item Mask

Enter a mask used to select the items by specifying either the required character or _ and * as wildcards. You must enter all 15 characters. For example, _A_B_____ selects any item with an A as the third character and a B as the sixth character of the item number, 1* selects any item with 1 in it, and 1_____ selects only items that begin with 1.

Item Type Range

Enter the range of item types.

Item Class Range

Enter the range of item classes.

Major Group Range

Enter the range of major groups.

Minor Group Range

Enter the range of minor groups.

Division Range

Enter the range of divisions.

Sub Division Range

Enter the range of sub divisions.

Issue Unit Range

Enter the range of issue units.



Note: Specify a From value but not To to maintain items starting from, and including, the From value through to the last item. Specify a To value without From to maintain the items from the first item through to, and including, the specified To selection.

Example; if you set up items AA to AZ, and item classes A to E, then enter a selection of From item AQ and To item class B, all items from AQ to AZ which had item class A or B are selected.



Note: If you do not enter any selection criteria, the report lists all items maintained within World Trade.



Select **F8=Submit** to submit the report.

Customer File Listing



22/WTM

This report lists the World Trade details for selected customers. The report attributes are:

- Frequency - As required.
- Stationery - Standard listing paper.
- Print Positions - 132.
- New Page - Page overflow.
- Totals - None.
- Sequence - Customer number/delivery sequence.

World Trade Customer Reporting Screen



To display this screen, select Customer (File Listing).

Use this screen to enter customer and group ranges for the Customer Listing.

WT905	Z1 - Demonstration Company	User SP1	23/09/94 11:36:46
World Trade Customer Reporting			
	From	To	
Customer?..	<u>GC01</u>	<u>GC06</u>	
Customer group 1...	___	___	
Customer group 2...	___	___	
Customer group 3...	___	___	
Customer group 4...	___	___	
F3=Exit F4=Prompt F8=Submit			

Fields:

Customer Range

Enter the range of customer account codes.

Customer Group 1 Range

Enter the range of customer group 1 codes.

Customer Group 2 Range

Enter the range of customer group 2 codes.

Customer Group 3 Range

Enter the range of customer group 3 codes.

Customer Group 4 Range

Enter the range of customer group 4 codes.



Note: You can define the customer group codes for each customer using Sales Order Processing Customer Maintenance.



Note: Enter no selection criteria, to list all customers maintained within World Trade.



Select **F8=Submit** to submit the report.

Supplier File Listing



23/WTM

This report lists the World Trade details for selected suppliers. The report attributes are:

- Frequency - As required.
- Stationery - Standard listing paper.
- Print Positions - 132.
- New Page - Page overflow.
- Totals - None.
- Sequence - Supplier number/delivery sequence.

World Trade Supplier Reporting Screen



To display this screen, select Supplier (File Listing).

Use this screen to select supplier and group ranges for the Supplier Listing.

WT910	Z1 - Demonstration Company	User SP1	23/09/94 11:38:40
World Trade Supplier Reporting			
	From	To	
Supplier?...	<u>FS01</u>	<u>FS05</u>	
Supplier group 1...	___	___	
Supplier group 2...	___	___	
Supplier group 3...	___	___	
Supplier group 4...	___	___	
F3=Exit	F4=Prompt	F8=Submit	

Fields:

Supplier Range

Enter the range of supplier account codes.

Supplier Group 1 Range

Enter the range of supplier group 1 codes.

Supplier Group 2 Range

Enter the range of supplier group 2 codes.

Supplier Group 3 Range

Enter the range of supplier group 3 codes.

Supplier Group 4 Range

Enter the range of supplier group 4 codes.



Note: Define the supplier group codes for each supplier through Accounts Payable Supplier Maintenance.



Note: Enter no selection criteria to print all the suppliers maintained within World Trade.



Select **F8=Submit** to submit the report.