



DISTRIBUTION REQUIREMENTS PLANNING

Version 3.5.2 SP4

Product Guide

FRONTISPIECE

Copyright © 2001, Geac Enterprise Solutions Limited, Product Services Division, Eagle House, The Slough, Studley, Warwickshire, B80 7EN England.

All rights reserved.

No part of the material protected by this copyright may be reproduced or utilised in any form or by any means, stored in a retrieval system, or transmitted, in any form, or by any means, electronic, mechanical, photocopying, or otherwise, without the express prior written consent of Geac Enterprise Solutions Limited.

Although every care has been taken in the production of this manual it cannot be guaranteed that the information contained herein is without error or omission.

This product information relates to:

Distribution Requirements Planning Version 3.5.2 SP4

If you have any comments please e-mail: **infobase.feedback@geac.com**

Contents

Chapter 1 Maintenance	1-1
Introduction	1-2
Calendar Maintenance	1-4
Calendar Maintenance Selection Screen	1-5
Calendar Maintenance Holidays Screen	1-6
Calendar Maintenance Week Templates Screen	1-7
Period Maintenance	1-9
Maintain Periods Selection Screen	1-10
Maintain Periods Details Screen	1-11
Stockroom Maintenance	1-13
Maintain DRP Stockrooms Selection Screen	1-14
Maintain DRP Stockrooms Details Screen	1-15
Customer Maintenance	1-16
DRP Stockroom/Customer Maintenance Selection Screen	1-17
DRP Stockroom/Customer Maintenance Details Screen	1-18
Network Maintenance	1-19
Maintain DRP Networks Selection Screen	1-20
Maintain DRP Networks Centre Detail Screen	1-21
Maintain DRP Networks DC Detail Screen	1-22
Distribution Item Master Maintenance	1-23
Distribution Item Master Maintenance Screen	1-24
Distribution Item Master File Maintenance Screen	1-25
Planner Maintenance	1-29
DRP Planners Selection Screen	1-30
DRP Planners Details Screen	1-31
Net Change Reason Codes Maintenance	1-32
Net Change Reason Codes Maintenance Screen	1-33
Supplier Schedule Profile Maintenance	1-34
Supplier Schedule Period Maintenance Selection Screen	1-35
Supplier Schedule Period Maintenance Detail Screen	1-36
Chapter 2 Forecasting	2-1
DRP Forecasting Introduction	2-2
Maintain Item Group Profiles	2-3
Maintain Item Group Profile Selection Screen	2-4
Maintain Item Group Profile Group List Screen	2-5
Maintain Item Group Profile Details Screen	2-6
Maintain Seasonal Profiles	2-7
Maintain Seasonal Profiles Screen	2-8

Maintain Seasonal Profiles Indices Screen	2-10
Sales Forecast Maintain Item Group Forecasts	2-12
Maintain Item Group Forecasts Selection Screen.....	2-13
Maintain Item Group Forecasts Interval Screen	2-15
Maintain Item Group Forecasts Spread Forecast Screen	2-17
Maintain Item Group Forecast Weekly Spread Window	2-20
Maintain Item Group Forecast Daily Spread Window	2-22
Maintain Item Group Forecasts Update Item Forecasts Screen.	2-24
Forecast Barchart Screen	2-25
Sales Forecast Generate Item Forecast	2-26
Generate Item Forecast Selection Screen	2-27
Generate Item Forecast Group Selection Screen	2-28
Sales Forecast Maintain Item Forecast	2-29
Maintain Item Sales Forecast Selection Screen	2-30
Maintain Item Sales Forecast Interval Selection Screen	2-32
Maintain Product Forecast Spread Forecast Screen	2-34
Sales Forecast Spread Item Forecast	2-37
Spread Item Sales Forecast Selection Screen	2-38
Spread Item Sales Forecast Detail Screen	2-40
Stock Forecast Maintain Item Group Forecast	2-41
Maintain Item Group Stock Forecasts Selection Screen.....	2-42
Maintain Item Group Stock Forecasts Intervals Selection Screen.....	2-44
Maintain Item Group Stock Forecasts Period Stock Levels Screen	2-46
Maintain Item Group Stock Forecasts Create/Item Forecasts Window	2-49
Maintain Item Group Stock Forecasts Stock Profile Window.....	2-50
Stock Forecast Generate Item Forecast	2-52
Generate Item Stock Forecast Item Group Selection Screen.....	2-53
Generate Item Stock Confirm Selection Screen.....	2-54
Stock Forecast Maintain Item Forecast	2-55
Maintain Item Stock Forecast Selection Screen.....	2-56
Maintain Item Stock Forecast Period Targets Screen	2-58
Stock Forecast Spread Item Forecast	2-60
Spread Item Stock Forecast Selection Screen.....	2-61
Stock Spread Item Forecast Detail Screen	2-62
Chapter 3 Processing	3-1
The DRP Cycle	3-2
DRP Run Processing Options	3-5
Evaluate DC Demand	3-7
Evaluate DC Demand Screen	3-8
DC Run Selection Screen	3-9
DC Run Net Change Trigger Selection Window	3-11
DC Run Selection Criteria Window	3-12

DC Run Restrict Order Extractions For Run Window	3-14
Run DRP For Centre	3-15
Run DRP For Centre Screen	3-16
Centre Run Selection Screen	3-17
Network Run	3-19
Network Run Screen	3-20
Network Run Selection Screen	3-21
Distribution Order Entry	3-23
Distribution Order Entry Selection Screen	3-24
Distribution Order Entry Delivery Address Override Screen	3-25
Distribution Order Entry Lines Screen	3-26
Distribution Order Amendment	3-28
Distribution Order Amendment Selection Screen	3-29
Chapter 4 Enquiries	4-1
Enquiries Introduction	4-2
View Schedule For DC Enquiry	4-3
DRP DC Schedule Enquiry Selection Screen	4-4
DRP Schedule Enquiry Detail Selection Screen	4-5
Schedule Enquiry Summary Screen	4-6
Item Supply and Demand Details Screen	4-8
Header Details Window	4-10
Schedule Enquiry Detail Line Screen	4-11
View Schedule For Centre Enquiry	4-13
DRP Centre Schedule Enquiry Selection Screen	4-14
Distribution Item Master Enquiry	4-15
Distribution Item Master Enquiry Selection Screen	4-16
Distribution Item Master Enquiry Item Details Screen	4-17
Stock In Transit Enquiry	4-18
Shipments In Transit Enquiry Selection Screen	4-19
Shipments In Transit Enquiry Order Line Details Screen	4-20
Chapter 5 Reports	5-1
Introduction	5-2
Print Run Details Report	5-3
DRP Run Details Report Selection Screen	5-4
Schedule Report	5-5
Request Schedule Report Selection Screen	5-6
Request Schedule Report Details Screen	5-7
Enter Selection Criteria Window	5-9
Planner Action Report	5-11
Request Planner Action Report Selection Screen	5-12
Request Planner Action Report Detail Screen	5-13
Valuation Report	5-14

PRODUCT
GUIDE

Request Valuation Report Selection Screen	5-15
Distribution Item Master Report	5-17
Distribution Item Master Report Selection Screen	5-18
Supplier Schedule Reports	5-19
Supplier Schedule Report Selection Screen	5-20
Chapter 6 Utilities	6-1
Maintain Company Profile	6-2
Maintain Profile Records Screen	6-3
Maintain DRP Company Profile Screen	6-4
Copy Company	6-7
Copy Company Select Libraries Screen	6-8
Copy/Replace Company Details Screens	6-9
Glossary	A



Chapter 1

Maintenance

Introduction

Distribution Requirements Planning provides the necessary data for matching customer demand with the supply of products at various stages in the physical distribution system.

DRP helps to anticipate future requirements, effectively deploy Inventory to meet customer requirements, and more rapidly adjust to a constantly changing market place.

DRP is one of the advanced application modules that extend the functionality of the base application modules.

The modules that are pre-requisite for DRP are:

- Inventory Management.
- Sales Order Processing.
- Purchase Management.
- Requisitioning.
- General Ledger.
- Accounts Receivable.
- Accounts Payable.

DRP also interfaces with, and enhances, Warehousing, World Trade, Forecasting and the Production modules.

Before you use DRP you must plan carefully. You need to consider your supply chain network and the flow of products between sites, particularly the relationship between distribution centres (DC's) and stockrooms.

Preparing To Use DRP

As this is an advanced application module, you set up most of the primary data through the base modules. However to get maximum benefit from the module you must define additional reference data specific to DRP.

After installation, the recommended implementation steps for DRP are in brief:

1. Within Sales Order Processing, create customer records for each stockroom, with a delivery address number of 001.
2. Make sure the necessary processing profile records are in Inventory. Refer to the Utilities section of the Inventory Management product information for further details.
3. Create the DRP company profile record, using the same company code as the one defined to Inventory Management.
4. Create the DRP calendars for this year, and any subsequent years.
5. Create the DRP networks, and define how and when they are processed.
6. Create the DRP period records for each centre and DC.

7. Create the DRP stockroom records for each centre and DC.
8. Assign the internal customer number to the stockroom within DRP Customer Maintenance.
9. Create the DRP network and planner records.
10. Define the item to all stockrooms at centres and DCs via Inventory Management.
11. Create the distribution item master records for every centre or DC that handles the item.
12. Create item group profiles and forecasts.
13. Create seasonal profiles.
14. Generate item sales forecasts.
15. Maintain the generated sales forecasts, where appropriate.
16. If you require stock building, enter the item group stock level parameters and create item stock levels.
17. Maintain the generated item stock level forecast, where appropriate.
18. If you are using net change DRP, set up net change reason codes.
19. If you require the supplier schedule report, define supplier schedule profiles.



Tip: Only steps 1 – 11 are mandatory.



Note: If you create sales forecasts in Forecasting, you do not need to do steps 12 to 14. However, if you maintain seasonal profiles then Forecasting applies them when you transfer the DRP forecasts.



Note: You can run DRP based on actual demand only, that is, excluding forecasts.

Calendar Maintenance



1/DRM

You use this option to maintain the calendars for all sites within the company.

You can create a single calendar for a whole company or different calendars for each centre or DC.

For each calendar you can maintain up to five weekly templates specifying periods when the working week is not the same as usual, and the working days and the dates to which it applies.

You can define the calendar codes here and assign them to individual sites via the Period Maintenance option.



Note: Before you generate a new calendar year, review the calendar details on the company profile, that is, the working days, to make sure that they are accurate for this particular year.

Calendar Maintenance Selection Screen



Select the Calendars option.

You use this screen to select a calendar to maintain or enter a new calendar.

DR017		Z1 - UK Demonstration Company		USER GBJBANB4		28/12/99 15:06:00	
Calendar Maintenance							
Sel	Code	Year	Days	Working Days	Year Start		
-	AC	99	364	260	4/01/99		
-	AC	00	364	260	3/01/00		
-	C1	94	364	257	3/01/94		
-	C1	95	364	260	2/01/95		
-	C1	96	364	260	1/01/96		
-	C1	97	364	260	30/12/96		
-	C1	98	364	260	29/12/97		
-	C1	99	364	260	28/12/98		
-	C1	00	364	260	27/12/99		
-	C1	01	364	260	25/12/00		
1=Select 4=Delete 6=Print							
Enter Calendar code: __ and Year: __ Based on Calendar __							
F3=Exit							

Fields:

Select (Sel)

Enter one of the following:

- 1 - To maintain the calendar.
- 4 - To delete the calendar.
- 6 - To print the details of the calendar.

Enter Calendar Code

To maintain an existing calendar, enter the calendar code.

To add a calendar, enter a new code.

Year

Enter the calendar year (in YY format).

Based On Calendar

You can choose to enter an existing calendar, to base the new calendar on. This saves entering information again and you can make any adjustments on the Calendar Maintenance Holidays Screen.



Press **Enter** to display the Calendar Maintenance Holidays Screen.

Calendar Maintenance Holidays Screen



To display this screen, either enter a new calendar, or select an existing calendar on the Calendar Maintenance Selection Screen, and press **Enter**.

You use this screen to maintain the calendar start date and all the company wide holidays for this calendar, such as bank holidays.

DR017		Z1 - UK Demonstration Company		USER GBJBANB4	28/12/99
					15:08:41
Calendar Maintenance					
Calendar Code C1					
Year 99	Start Date <u>281298</u>		Standard Week: M T W T F S S		
Holidays			N N		
From	To				
<u>010199</u>	<u>010199</u>				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
_____	_____				
F3=Exit F8=Update F12=Previous F13=Maintain Week Templates					

Fields:

Start Date

Enter the date of the first Monday of the year.

Holidays From

Enter the start date for the holiday in the format DDMMYY.

To

Enter the end date for the holiday.



Note: Holidays must not overlap.

Functions:

F13=Maintain Week Templates

Use this function to display the Week Templates Screen.



Select **F8=Update** to update the calendar holiday records. DRP audits all updates.

Calendar Maintenance Week Templates Screen



To display this screen, select **F13=Maintain Week Templates** on the Calendar Maintenance Holidays Screen.

You use this screen to maintain up to five weekly templates for the calendar. This is optional, but it can be useful for time periods when the calendar will operate differently, for instance when there will be less working days than usual.

This displays any existing week templates. Each template indicates which days of the week are working days. The top right-hand corner of the screen shows the default Week Template.



Note: If there is no weekly template defined for a particular date, DRP uses the company level default template.

DR017	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99 15:08:41
Calendar Maintenance			
Calendar Code C1			
Year 99	Start Date <u>281298</u>	Standard Week: M T W T F S S N N	
Enter up to five week templates for this year with effective dates.			
MTWTFSS	From Date	To Date	
_____	_____	_____	
_____	_____	_____	
_____	_____	_____	
_____	_____	_____	
F8=Update week templates F12=Previous			

Fields:

Start Date

Enter the start date.

MTWTFSS

These represent Monday through to Sunday.

Enter N beneath any non working day. Leave working days blank.

From Date

Enter the effective start date for this template.

To Date

Enter the effective end date for this template.



Note: Effectivity dates must not overlap.



Select **F8=Update Week Templates** to update the calendar template records. DRP audits all updates.

Period Maintenance



2/DRM

You use this option to define the time slots over which you want to assess the supply and demand.

You set up time slots for each centre or DC individually, but you can amend them before any processing run. You define the periods in terms of calendar days and associate them with a particular calendar code.

This is the first stage in defining a new centre or DC. Conversely, it is the last stage in deleting one.

Maintain Periods Selection Screen



Select the Periods option.

You use this screen to select the centre or DC you want to set up periods for.

DR031	Z1 - UK Demonstration Company	USER GBJBANB4	6/02/98 13:19:51
Maintain Periods			
Enter Centre/DC.....?.. _			
F3=Exit F4=Prompt			

Fields:

Enter Centre/DC

Enter the centre or DC you want to create or amend periods for.



Enter the centre or DC code and press **Enter** to display the Maintain Periods Details Screen.

Maintain Periods Details Screen



To display this screen, enter a centre or DC code on the Maintain Periods Selection Screen, and press **Enter**.

You use this screen to associate a calendar with a centre or DC, and define the periods to be analysed by DRP, for this site.

DR031		Z1 - UK Demonstration Company				USER GBJBANB4		6/02/98		13:20:56	
Maintain Periods (in Calendar days)						Centre/DC..... D1					
Calendar Code...?..						01					
1	2	3	4	5	6	7	8	9	10	11	12
2	2	2	2	2	2	2	2	7	7	7	7
13	14	15	16	17	18	19	20	21	22	23	24
28	28	28	28	28	28	28	28	28	28	28	28
25	26	27	28	29	30	31	32	33	34	35	36
37	38	39	40	41	42	43	44	45	46		
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous											

Fields:

Calendar Code

Enter a calendar code.

1 - 46

You can specify up to 46 different periods, defined in calendar days. The periods represent the time slots over which supply and demand will be assessed. Typically, they will be short to begin with, followed by longer periods and then longer periods again. The earlier periods represent the very near future and the later periods the more distant future.

The assumption is that less detail is required in the more distant future, where requirements may be more tentative.

For example, the initial four periods are short, just two days; the next four periods will be slightly longer, seven days, and the periods get a little longer as you move through the 46 fields.

Enter the length of each period in the appropriate field.



Tip: Remember, these periods are not related to Inventory or Financial periods, they are specifically DRP planning periods.



Select **F8=Update** to update the period details. DRP audits all updates. The Maintain Periods Selection Screen is redisplayed. Select **F3=Exit** to exit the option.

Stockroom Maintenance



3/DRM

You use this option to define Inventory stockrooms to centres or DCs.

This defines the stockrooms associated with a site and controls which stock balances, demands and supply orders DRP considers during a planning run. You can define any number of stockrooms to a centre or DC. If a centre or DC only includes a single stockroom, you can use the same code for the centre or DC as for the stockroom.



Note: You must have already defined the stockrooms to Inventory Management and specified periods for the centre or DC. You must also have assigned each stockroom a SOP dummy internal customer number to reflect distribution orders raised for that stockroom.

For planning purposes, you can associate multiple stockrooms with a distribution centre yet for any item, you can only define only one stockroom as the primary receiving and issuing store.

Maintain DRP Stockrooms Selection Screen



Select the Stockrooms option.

You use this screen to select the centre or DC and to indicate whether to include all stockrooms.

```
DR015                Z1 - UK Demonstration Company    USER GBJBANB4    6/02/98
                                     13:21:09
Maintain DRP Stockrooms.
Centre/DC...?...  Include all Stockrooms 0 (0=No 1=Yes)

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter a centre or DC code with defined periods.

Include All Stockrooms

Enter one of the following:

0 - Not to include all Inventory stockrooms.

1 - To add all Inventory stockrooms to a centre or DC.



*Note: If the stockroom you select does not exist, select **F8=Create** to create the stockroom.*



Press **Enter** to display the Maintain DRP Stockroom Details Screen.

Maintain DRP Stockrooms Details Screen

 To display this screen, enter a Centre or DC code on the Maintain DRP Stockrooms Selection Screen and press **Enter**.

You use this screen to enter the stockrooms to define to the centre or DC.

DR015

Z1 - UK Demonstration Company

USER GBJBANB4

6/02/98
13:21:24

Maintain DRP Stockrooms.

Centre/DC...?... D1 Include all Stockrooms 0 (0=No 1=Yes)

..... Stockrooms to be included

02	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—
—	—	—	—	—	—	—	—

F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous

Fields:

Stockrooms To Be Included

If you have already defined stockrooms to this centre or DC, they are displayed here. If you are defining stockrooms to a new centre or DC, enter the codes here.

 *Note: Select **F11=Delete** to remove the centre or DC and all its associated stockrooms permanently.*

 Select **F8=Update** to update the displayed stockrooms. Then select **F3=Exit** to exit the option.

Customer Maintenance



4/DRM

Use this option to maintain the internal customers who will be able to raise distribution orders in DRP and production transfer orders, and receive transferred supply.

You process distribution orders, created through DRP, through the Sales Order Processing module in a similar way to normal sales orders.



Note: Distribution orders are also called transfer orders. Transfer orders are used in the production applications to transfer stock between production units if you are using multi-plant, multi-sourcing or cellular production.

Therefore, you must set up an internal customer account, in Sales Order Processing, for each stockroom that is to supply DCs in the DRP network. The internal customer must have a delivery address sequence number of 001.

This option defines internal customer codes to stockrooms for DCs to generate order details and despatch documentation that support stock transfer between centres and DCs.

DRP Stockroom/Customer Maintenance Selection Screen



Select the Customers option.

This screen displays the various stockrooms from and to which goods can be transferred. It also shows any customers who are attached to these transfer stockrooms.

You use this screen to select the DRP stockroom and customer you want to maintain. All Inventory stockrooms used by DRP are displayed.

```

DR340          Z1 - UK Demonstration Company   User GJBANB4   28/12/99
                                           15:14:22

DRP Stockroom/Customer Maintenance

  SR  Description                      Customer
  --  -
  AS  A Sales Stockroom                ACDUMMY
  A1  A1 Stockroom
  BG  BG2 Test Stockroom 1
  B2  BG2 DC Test                      BG2C3
  CS  Component Stock
  FG  Finished Goods                  DRP-N2
  FS  Floor Stock
  F1  Paris Central Stockroom
  GP  Dept C...Group Parents
  G1  Dept C..Group Co-Products
  IT  Integration Test W/house
  I1  Integration Test S/Room 1
  I2  Integration Test S/Room 2
  I3  Integration Test S/Room 3
  I4  Dept D ..Intermediates          +

1=Select
F3=Exit
  
```

Fields:

Select (Untitled)

Enter 1 alongside the stockroom you want to maintain.



Press **Enter** to display the DRP
Stockroom/Customer Maintenance Details
Screen.

DRP Stockroom/Customer Maintenance Details Screen



To display this screen, enter 1 alongside a stockroom on the **DRP Stockroom/Customer Maintenance Selection Screen**, and press **Enter**.

You use this screen to enter the dummy internal customer code, which holds distribution orders for receipt at this stockroom.

DR340	Z1 - UK Demonstration Company	User GBJBANB4	28/12/99 15:22:11
DRP Stockroom/Customer Maintenance			
Stockroom.....	FG	Finished Goods	
Internal Customer.....?	.. <u>DRP-N2</u>	Dummy for DRP only	
F3=Exit F4=Prompt F12=Previous			

Fields:

Internal Customer

Enter the customer code to use when you enter a distribution order with this stockroom as its destination.



Note: You must have already set up the internal customer code in Sales Order Processing with a delivery sequence of 001.



Press **Enter** to save the details then select **F3=Exit** to exit the option.

Network Maintenance



5/DRM

This defines the overall supply chain relationship. Use this option to define DRP networks and the relationships between centres and DCs within those networks. A DRP network consists of one centre and any number of distribution centres supplied by that centre. You can define a centre or DC to more than one network.

You can define multiple networks for a company and include sites in more than one network, normally as a centre on one level and as a DC on another.



Note: You must have previously defined periods and stockrooms for each centre and DC you use here.

Maintain DRP Networks Selection Screen



Select the Networks option.

You use this screen to enter the network to maintain.

DR016	Z1 - UK Demonstration Company	USER GJBANB4	28/12/99 15:24:55
Maintain DRP Networks			
Enter Network Code...?.. __			
F3=Exit F4=Prompt			

Fields:

Enter Network Code

Enter an existing network code or enter a new code to add a network.



Press **Enter** to display the Maintain DRP
Networks Detail Screen.

Maintain DRP Networks Centre Detail Screen



To display this screen, enter a network code on the Maintain DRP Networks Selection Screen, and press **Enter**.

You use this screen to maintain the centre code and descriptions for this network.

DR016	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99 15:26:07
Maintain DRP Networks			
Network Code.....	N1	Description	UK Supply Network
Centre for Network..?..	C1	Description	Birmingham Central Depot
F3=Exit F4=Prompt F12=Previous			

Fields:

Description

Enter a description for the network code you have entered.

Centre For Network

Enter a centre code. This is the network centre.

Description (Centre)

Enter a description of the network centre.



Press **Enter** to update the DRP network file with the centre code and descriptions. DRP audits updates to the network file. The Maintain DRP Networks DC Detail Screen is displayed.

Maintain DRP Networks DC Detail Screen



To display this screen, press **Enter** on the
Maintain DRP Networks Centre Detail Screen.

You use this screen to maintain the DC details for the selected network.

DR016	Z1 - UK Demonstration Company	USER GJBANB4	28/12/99
Maintain DRP Networks			15:27:42
Network Code..... N1 UK Supply Network			
Centre for Network.. C1 Birmingham Central Depot			
DCs Supplied By Centre			
Line	DC	Description	
1	D1	Northern Regional DC	
2	D2	Southern Regional DC	
Line: ____ DC.?..: __ Desc.: _____			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Line

If you are maintaining an existing network, enter the line number of the DC you want to amend.

DC

Enter a DC or centre to add to this network.

Desc.

Enter a description for the DC or centre.

Functions:

F11=Delete

To delete a centre or DC from the network, enter the relevant line number and select **F11=Delete**.

If you do not enter a line number and select delete, you delete details for the whole network. Select **F11=Delete** a second time to confirm the update.



Select **F8=Update** to save the network details
and then select **F3=Exit** to exit the option.

Distribution Item Master Maintenance



6/DRM

You use this option to maintain additional, specific distribution details, in order to use Inventory items effectively within DRP.

You must maintain this information for each site; this means each centre or DC handling the item. The site can be a distribution or a retail outlet for the item.



Note: If you manufacture the item, you only need to define it to DRP at its retail DCs. Define the manufacturing centre, and its items in Production. The MPS or MRP modules then treat the centre as a model.

Distribution Item Master Maintenance Screen



Select the Distribution Item Master option.

You use this screen to enter the item you want to maintain.



Tip: To use the standard Inventory item prompt, select **F16=Inventory Search Item**.

DR007	Z1 - UK Demonstration Company	User GBJBANB4	28/12/99
Distribution Item Master Maintenance			15:29:12
Centre/DC....?.. __			
Item.....?.. _____			
F3=Exit F4=Prompt F16=Inventory item search			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Item

Enter an Inventory item code.

Functions:

F16=Inventory Item Search

Use this function to select the standard Inventory item search facility for all items within the company.



Press **Enter** to display the Distribution Item Master File Maintenance Screen.

Distribution Item Master File Maintenance Screen



To display this screen, enter an item code and a centre or DC on the Distribution Item Master Maintenance Screen and press **Enter**.

You use this screen to maintain the re-supply rules used for planning this item.

DR007		Z1 - UK Demonstration Company		USER GBJBANB4	28/12/99
Distribution Item Master File Maintenance					15:30:51
Item.....	5002	Suncream Factor 8 225ml			
Centre/DC.....	C1	Birmingham Central Depot			
		Date Last Planned.... 15/09/94			
Source of Supply...	2	(1=Local, 2=Central)			
Planner.....?	SGM				
DRP Forecast.....	3	(0=None, 1=Sales, 2=Stock, 3=Both)			
Forecast Error Tolerance% Absolute..	.00				
Forecast Profile.?					
Order Policy.....	B	(A,B,D,G,H) Min Order Qty.....			
		OR			
Max Order Qty.....		Use Inventory Order Qty... 2			
Fixed Order Qty....		(1=Economic Order Qty., 2=Reorder Qty.)			
Mult Order Qty.....					
Safety Stock.....		Stockroom Details			
Days supply.....	0	Local Stockroom.....?.. 01			
Time fence days....	0	Centre.....?..			
Safety stock weeks..	2	Central Stockroom.....?..			
Safety stock days..	3				
F3=Exit F4=Prompt F11=Delete F12=Previous					

Fields:

Source Of Supply

Enter one of the following:

- 1 - If you purchase the item locally, that is, as a DC you purchase the item directly, rather than it being supplied by a supply centre.
- 2 - If the item is supplied centrally, that is, it is purchased, or manufactured, or supplied by a centre defined to DRP or Production.

Planner

Enter the planner responsible for this item on this site.

DRP Forecast

Forecasts are not mandatory in DRP.

Enter one of the following:

- 0 - To not use forecasts at all. In this case, DRP only considers actual orders.
- 1 - To use sales forecasts only for this item.
- 2 - To use stock level forecasts only for this item.
- 3 - To use both sales forecasts and stock levels for this item.

Forecast Error Tolerance % Absolute

Enter the percentage difference between sales forecast quantities and actual sales quantities before DRP writes a net change trigger for the item concerned. If you do not enter a value, this defaults to the value set up on the company profile.

Forecast Profile

If you use forecasts in DRP, enter the default seasonal profile used as a template to break down sales forecasts, and maintain stock levels, from period, to weekly and daily level. You can override this default during forecast processing.

Order Policy

Enter one of the following order policy codes:

Cod e	Description	Mandatory Quantities
A	Discrete. DRP suggests an order for the actual quantity required, regardless of other factors.	None.
B	Discrete above minimum. DRP suggests an order for the actual quantity required, if greater than the supplier's minimum order quantity.	Minimum order quantity.
D	Fixed quantity. DRP suggests a fixed order quantity of this item, regardless of other factors, for example, forecasts or stock levels.	Fixed order quantity.
G	Number of days supply. DRP accumulates the requirements over the specified days and suggests an order quantity to satisfy this demand.	Number of day's supply.
H	Fixed quantity above minimum. The suggested order quantity must be greater than minimum and divisible by the multiple quantity.	Minimum order quantity. Multiple order quantity.



Note: You can enter either Minimum Order Quantity or Use Inventory Order Quantity. You must specify a minimum order quantity for order policies B and H.

Min Order Qty

Enter the minimum quantity that DRP suggests for replenishment of this item. If the reorder quantity calculated by DRP is less than this minimum, DRP uses the latter. This applies only to order policies B and H.

Inventory Order Quantity

Enter one of the following:

- 1 - To use the economic order quantity as the DRP minimum order quantity.
- 2 - To use the Inventory reorder quantity as the DRP minimum.

Leave blank to use neither.

Max Order Qty

Enter the maximum quantity that DRP suggests for replenishment of this item. If DRP calculates the re-order quantity as greater than this maximum, the DRP planner action report highlights it.

If specified, DRP uses this maximum order quantity regardless of the order policy specified for the item.

Fixed Order Qty

Enter the fixed re-order quantity DRP should suggest for this item.

If the required quantity is greater than the fixed order quantity then DRP suggests multiples of the fixed order quantity to satisfy the demand.



Note: If you have specified order policy D, you must enter a fixed order quantity greater than zero.

Mult Order Qty

Multiple Order Quantity. Enter a quantity. DRP suggests multiples of this quantity for the re-order quantity.



Note: If you have specified order policy H, you must enter a multiple order quantity greater than zero.

Safety Stock

If you do not need to calculate the safety stock during DRP processing, enter the fixed quantity of safety stock.

Days Supply

Enter the number of days for which DRP totals the requirements, and raises a single order.



Note: If you have specified order policy G, you must enter a number of days.

Local Stockroom

Enter a stockroom code. You must have defined the stockroom to the item in Inventory Management and to the centre or DC in DRP. DRP updates on-order and in-transit quantities against this stockroom for the item. This is the primary stockroom for the item at this centre or DC.

Time Fence Days

Enter the number of days forward from the current date of a DRP processing run, during which DRP schedules no new supply suggestions for forecasted demand, only for actual demand.

You can override this, when you submit a DRP run, with a blanket time fence that applies to all items in the run.

Leave this field blank to calculate the item level time fences:

- For centrally supplied items from the item/stockroom lead time.
- For locally purchased items from the lead time for the item/preferred supplier.

Safety Stock Weeks & Days

Enter the required safety stock cover, in weeks and days. This defaults from the company profile but you can vary it at item or DC level. DRP calculates safety stock from the forecast demand for the item.

You must enter sales forecasts for items if you want to create safety stocks. You can override this when you submit a DRP run by a blanket value that applies to all items for that run.

Centre

This field is only displayed if you entered 2 in the Source Of Supply field, Central. Enter a centre code (defined as a centre within at least one DRP network). Use this to include or exclude items when processing a particular centre.

Central Stockroom

This is only displayed if you entered 2 in the Source Of Supply field, Central. Enter a stockroom code defined to the item within Inventory Management, and to a centre within DRP.

You create distribution order lines for this item against this stockroom.



Press **Enter** to update. DRP records all updates in the DRP Item master audit file. Then select **F3=Exit** to exit the option.

Planner Maintenance



7/DRM

Planners are responsible for planning items or a range of items at each centre or DC.

You use this option to maintain details of all planners, at each centre or DC. Each planner must be cross-referenced to a purchase officer within Purchase Management.



Note: You assign this planner code to all items the planner is responsible for via the Distribution Item Master.

DRP Planners Selection Screen



Select the Planners option.

You use this screen to select the Centre or DC and the planner code you want to maintain.

DR043	Z1 - UK Demonstration Company	USER GJBANB4	28/12/99
			15:36:28
DRP Planners - Selection			
Centre/DC.....?.. _			
Planner Code....?.. ____			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter any centre or DC code which has periods defined to it.

Planner Code

Enter an existing planner to maintain, or enter a new planner code.



Note: If you specify a centre or DC, this restricts the list of planners to this centre or DC. If you leave the field blank, all planners for the company are displayed.



Press **Enter** to display the DRP Planners Details screen.

DRP Planners Details Screen



To display this screen, enter a planner code on the **DRP Planners Selection Screen**, and press **Enter**.

You use this screen to maintain information relating to the planner and specify a purchase officer number to reference the planner to. Purchase Management requires the purchase officer number when purchase orders are created from **DRP suggestions** (for items controlled by the planner).

DR043	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99 15:37:55
DRP Planners - Details			
Centre/DC.....		C1	
Planner.....		SGM	
Name.....		Simon G. Merral	
Department.....		Planning	
Telephone.....		2436	
Purchase Officer No...?..		00002 Simon G. Merral	
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Name

Enter the name of the planner.

Department

Enter the planner's department.

Telephone

Enter the planner's telephone or extension number.

Purchase Officer No

Enter the Purchase Officer number as defined in Purchase Management.



Select **F8=Update** to update the details displayed in the **DRP Planners** file.

Net Change Reason Codes Maintenance

1... **8/DRM**
2...

You use this option to maintain up to 20 reason codes for DRP net change processing. Each reason code corresponds to a type of transaction that could potentially affect the supply, demand, stock, or replenishment parameters of DRP items. For instance, unplanned Inventory issues or receipts could change demand at a centre.

Transactions that affect DRP items set off net change triggers in DRP grouped by reason code. This allows a flexible approach to DRP planning runs, whereby a subset of DRP items can be replanned based on an analysis of triggers, set for particular reason codes.

Net Change Reason Codes Maintenance Screen



Select the Net Change Reason Codes option.

You use this screen to activate net change triggers in DRP processing.

Code	Description	Active (1=Yes,0=No)
01	Forecast vs Actual Comparison.	1
02	Forecast Generation.	1
03	Forecast Maintenance.	1
04	Distribution Item Master.	1
05	Unplanned Inventory Transactions.	1
06	Requisition Maintenance.	1
07	Unplanned Issue or Receipt.	1
08	Purchase Order Maintenance.	1
09	Distribution Order Maintenance.	1
10		0

F3=Exit F5=Refresh F8=Update

Fields:

Code

This displays the net change reason codes. There are currently nine, predefined reason codes set up. There are 11 more reason codes reserved for possible future development.

Description

Each reason code description is displayed. Each reason describes a type of transaction that potentially affects the planning of DRP items. You can change the reason code description, but it will not affect the code.

Active

Enter one of the following:

0 - To deactivate the reason code.

1 - To activate the reason code.



Note: DRP only processes net change triggers with activated reason codes.



Select **F8=Update** to update the details.

Supplier Schedule Profile Maintenance



9/DRM

Supplier schedule reports are of particular use to companies who have a close working relationship with their suppliers and want to keep them notified with details of future commitments, by providing forward schedules. The suppliers can use these reports to buy in materials, manufacture and plan to meet the schedule demand.

You use this option to control the format and scope of supplier schedules, at individual supplier, or supplier and minor item group level.

The supplier schedule profile is set up on the assumption that you will know what orders need to be placed immediately, but will become less sure of requirements for the more distant future.

Supplier Schedule Period Maintenance Selection Screen



Select the Supplier Schedule Profile option.

You use this screen to specify the supplier, and if required, the minor item group to maintain schedule formats for.

DR400	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99 15:41:49
-------	-------------------------------	---------------	----------------------

Supplier Schedule Period Maintenance

Enter a Supplier and optionally a Minor Item Group

Supplier.....?.. GS02____

Minor Item Group...?.. 3__

F3=Exit F4=Prompt

Fields:

Supplier

Enter a supplier defined within Purchase Management.



Note: To maintain schedule formats at supplier level, enter a Purchase Management supplier. To maintain schedule formats at supplier and item group level, enter a supplier and a minor item group.

Minor Item Group

Enter a minor item group defined in the Inventory descriptions file. This is optional. Building a schedule profile using minor item groups makes sure that the supplier receives even more detailed reports.



To display the Supplier Schedule Period Maintenance Detail Screen, enter a supplier, and if required, minor item group, and press **Enter**.

Supplier Schedule Period Maintenance Detail Screen



To display this screen, enter a supplier, and if required, a minor item group on the Supplier Schedule Period Maintenance Selection Screen, and press **Enter**.

You use this screen to define the supplier schedule report column headings, reporting intervals, and inclusion and exclusion rules.

DR400	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99
			15:43:19
Supplier Schedule Period Maintenance			
Supplier..... GS02		Coles Commercial Chemicals Ltd	
Minor Item Group..... 3		Sun Protection	
Time Period	Weekly Report (Max. 16 Weeks)	Monthly Report (Max. 15 Periods)	Supply Records (1=Include, 0=Exclude)
			PO RQ SG
<u>FIXED</u>	—		<u>1</u> <u>1</u> <u>1</u>
<u>FIRM</u>	—		<u>1</u> <u>1</u> <u>1</u>
<u>PROBABLE</u>		—	<u>1</u> <u>1</u> <u>1</u>
<u>TENTATIVE</u>		—	<u>1</u> <u>1</u> <u>1</u>
F3=Exit F8=Update F12=Previous			

Fields:

Time Period

The weekly and monthly reports are each split into two sections, representing shorter term and longer term scheduling. You define each section to consist of a number of weeks and periods. You can change the default column headings for each section, by overtyping the defaults with your own headings.

Weekly Report

Specify how many weeks, from the start date of the report, to include in the fixed and firm sections of the weekly report. The maximum is 16 weeks.

Monthly Report

Specify how many periods from the start of the report to be included in the probable and tentative sections of the period report. The maximum is 15 periods.

The schedules are built this way because your advance order for a point in time might be tentative, becoming probable a few weeks later, then firm as time moves on, and finally fixed when you are sure of demand.

Supply Records

PO

Purchase Orders. Enter one of the following to specify whether to include purchase orders in the short-term section of the weekly report:

- 1 - To include.
- 2 - To exclude.

RQ

Requisitions. Enter one of the following to specify whether to include requisitions created from DRP supply suggestions, in the short-term section of the weekly report:

- 1 - To include.
- 2 - To exclude.

SG

Suggested Purchase Orders. Enter one of the following to specify whether to include suggested purchase orders in the short-term section of the weekly report.

- 1 - To include.
- 2 - To exclude.



Note: This does not include changes to suggested quantity or dates.



Select **F8=Update** to save the record and then select **F3=Exit**.

-
-
-
-
-

Chapter 2 Forecasting

DRP Forecasting Introduction

Forecasts are not essential within DRP but they can be very useful for forward planning. You can generate sales forecasts and stock level forecasts.

You can also transfer sales forecasts into DRP from the Forecasting module; this avoids entering manual forecasts and takes into account the last three years sales history.

You can generate forecasts for minor item groups and spread them down to item level using spread profiles.

You can maintain forecasts at period, weekly and daily level. You can spread forecasts from period to weekly to daily level by defining seasonal indices, invoking automatic spreading or direct entry and manipulation of forecasts and spread indices.

Use stock level forecasts to build stock up to a planned level according to specified target quantities and dates.

Maintain Item Group Profiles



1/DRF

Use this option to assign percentages to products within minor item groups to reflect their relative demand, in either quantity or value. You can then spread the overall sales forecasts, or stock level targets, according to these percentages.

DRP uses the minor item group codes specified for items in Inventory Management to identify product families. DRP treats all items with the same minor item group code as members of a family.

Maintain Item Group Profile Selection Screen



Select Maintain Item Group Profiles.

Use this screen to select the centre or DC to maintain.

```
DR010          Z1 - GB Demonstration Company    USER GBJBA1MS    5/02/98
                                           14:44:52

Maintain Item Group Profile

      Enter Centre/DC....?... █

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.



Enter a centre or DC and press **Enter** to display
Maintain Item Group Profile List Screen.

Maintain Item Group Profile Group List Screen



To display this screen, enter a centre or DC on the Maintain Item Group Profile Selection Screen and press **Enter**.

You use this screen to select the minor item group to maintain.

This screen displays a list of all minor item groups at the specified centre. If 1 is displayed alongside a group, it already has a profile defined; you can still maintain that profile.

DRP sources these groups from the Inventory descriptions file.

DR010	Z1 - GB Demonstration Company	USER GBJBA1MS	5/02/98
			14:52:33
Maintain Item Group Profile		Centre/DC.. C1	
Select	Group	Description	Profile (1=Defined)
-	ZA	Automotive Assemblies	
-	1	Food	1
-	2	Drinks	1
-	3	Sun Protection	1
-	4	Make-up	1
-	5	Lipsticks	
-	6	Hair Care	1
-	7	Painkilling Drugs	1
-	8	Other Pharmaceutical	1
-	9	Gardening Products	

i=Select Item Group
F3=Exit F12=Previous

Fields:

Select

Enter 1 against the required item group to select it.



Tip: When you select an item group, the item profiles are displayed on the next screen. However, the selected item group must have at least one item defined to it (via Inventory Management Item Details).



Press **Enter** to display the Maintain Item Group Profile Details Screen.

Maintain Item Group Profile Details Screen



To display this screen, enter 1 alongside an item and press **Enter**, on the Maintain Item Group Profile Group List Screen.

You use this screen to assign a percentage quantity or value to each item in the selected minor item group.

DR010	Z1 - GB Demonstration Company	USER GBJBA1MS	5/02/98
Maintain Item Group Profile		Centre/DC.. C1	14:54:29
Item Group... M	Manufactured	Seasonal Profile?... __	
Item	Description	Source	Percentage
TL01	Trevor Lewis DRP Item	Local	100.000
		Total percentage entered 100.000	
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			

Fields:

Seasonal Profile

You can enter a seasonal profile code for the DC or centre and product group; otherwise it will default to the last code entered.

Percentage

Enter the projected percentage sale for each item within the item group. DRP interprets blank fields as zero sales.



Note: The total percentage for the item group must equal 100%.



*Note: When you select **F11=Delete**, DRP sets all the percentages to zero but does not delete the items themselves.*



Select **F8=Update** to immediately update these percentages in the DRP Item Group Profile file.

Maintain Seasonal Profiles

1...
2... **2/DRF**

Use this function to maintain seasonal profiles. You can use these profiles as a template to break down sales forecasts on a time phased basis by period, week and day. This facility is not mandatory for forecast maintenance, but it is useful if you want to take into account seasonal fluctuations.

Similarly, you can use this to define time phased stock building and consumption planning profiles.

Maintain Seasonal Profiles Screen



Select Maintain Seasonal Profiles.

You use this screen to create and maintain seasonal profiles.

```
DR700          Z1 - GB Demonstration Company  USER GBJBA1MS  5/02/98
                                         14:41:36

Maintain Seasonal Profiles

      Centre/DC.....?.. █
      Profile code....?.. _
      Year..... 98
      Entry Level..... 1  1=Period 2=Weekly
      Base on Profile.?.. _

_____
F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter a centre or DC that has a calendar, time phased planning periods and stockrooms defined.

Profile Code

Enter the profile code. The profile code itself is not unique; you can use common seasonal profile codes across different years and different centres or DCs.

Year

Enter the year, in YY format. You must set up the centre or DC and year combination using Calendar Maintenance. This defaults to the current year.

Entry Level

Enter one of the following to specify how to build the seasonal profile:

1 - On a period basis up to 13 periods.



Note: If you have set the Period Forecast option on the company profile to 0, this option is not available.

2 - On a weekly basis, up to 53 weeks.

Based On Profile

You can create a new profile using an existing profile as a template. The calendar code, year and entry level for the based on profile must match those for the profile you create.



Press **Enter** to display the Maintain Profiles
Indices Screen.

Maintain Seasonal Profiles Indices Screen



To display this screen, enter the details on the Maintain Seasonal Profiles Screen, and press **Enter**.

Use this screen to maintain the profile description and individual period, weekly and daily indices. The screen displayed depends on the entries you made on the previous screen.

DR700		Z1 - GB Demonstration Company		USER GBJBA1MS		17/11/97	
						10:21:18	
Maintain Seasonal Profiles							
Profile A1 Trial Seasonal Profile				Calendar C1		Year 97	
Daily Indices		1	0	2	0	3	0
		4	0	5	0	6	0
		7	0				

Period Indices		Weekly Indices	
Period	Index	Period	Index
1	2	1	1
2	1	2	
3	2	3	
4		4	
5	1		
6	2	2	5
7	2	6	
8	3	7	
9	4	8	
10	3		
11	1	3	9
12	1	10	
13	1		

More: +

F3=Exit F8=Add F12=Previous F16=Period F18=Distribution



Note: If you select Entry Level 1 on the previous screen, you do not need to enter the weekly indices.

Fields:

Profile

Enter a description of the profile.

Daily Indices

Daily indices are not mandatory; they can be useful for forecast maintenance to take fluctuations within a normal working week into account.

Enter the daily indices: these values cannot be negative or greater than 999. DRP breaks weekly forecasts down, based on the daily indices relative to the sum of all daily indices for the week. Day 1 is Monday. If you do not enter daily figures, DRP spreads weekly forecasts uniformly based on the working days defined in the weekly templates for the calendar.



Warning: If you enter daily indices, DRP disregards weekly templates.

Period Indices

Enter the period indices: these values cannot be negative or greater than 999. DRP breaks forecasts down by period, using the period index relative to the sum of index values for all periods.

Weekly Indices

If you selected Entry Level 1 on the previous screen, enter the weekly indices. These values cannot be negative or greater than 999. DRP breaks period forecasts down based on the weekly indices.

If you select Entry Level 2 on the previous screen, enter the weekly indices. These values cannot be negative or greater than 999. DRP breaks annual forecasts down based on the weekly indices relative to the sum of all weekly indices for the year.

Functions:

F16=Period.

Use this function to maintain the period indices.

F17=Weekly

Use this function to maintain the weekly indices within a period.

F18=Distribution

Use this function to calculate the percentage spread for the entered indices.



Select **F8=Update** to add the new profile, or update the existing one.



Tip: When you select an item group, the item profiles are displayed on the next screen. However, the selected item group must have at least one item defined to it (which is done via Inventory Management Item Details).

Sales Forecast Maintain Item Group Forecasts

1...
2...

3/DRF

The Maintain Item Group Forecasts option generates a forecast for a minor item group. It will not include information on specific items. However, you can vary the time bands you generate forecasts for and you can break forecasts right down to a daily level, if you want.

You can generate forecasts on a quantity or value basis.

Maintain Item Group Forecasts Selection Screen



Select Maintain Item Group Forecasts.

Use this screen to enter the details of the forecast you want to generate.

DR710	Z1 - GB Demonstration Company	USER GBJBA1MS	5/02/98 14:56:44
Maintain Group Forecasts			
Centre/DC.....?.. █			
Year..... 98			
Item Group.....?.. ____			
Forecast Basis..... 1 (1=Quantity 2=Value)			
Seasonal Profile..?.. ____			
Maintain Intervals... _ (1=Yes)			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with defined time phased planning periods and stockrooms and at least one valid minor item group profile defined.

Year

Enter the year, in YY format. The default is the current year. You can change to a subsequent year, but it must be defined to the calendar for the selected DC or centre.

Item Group

Enter a minor item group with a profile set up for the centre or DC you have chosen.

Forecast Basis

You can generate forecasts by quantity or by value. Enter one of the following:

- 1 - To maintain forecasts by quantity.
- 2 - To maintain forecasts by value.



Tip: If you have previously maintained this forecast using the other forecast basis, DRP displays a warning. Select **F8=Update** to proceed.

Seasonal Profile

Enter a seasonal profile, which has a profile, year and centre or DC combination previously set up through the Seasonal Profile Maintenance function. The profile you select determines the levels at which you can maintain the forecast. If you set up the seasonal profile with Entry Level 2, you can only maintain daily and weekly forecasts.

To spread product group sales forecast quantities, or values, evenly across the forecast periods, weeks or days, or both, leave this field blank.

Maintain Intervals

Enter 1 to access the Maintain Group Forecast Intervals Screen. You use this to define the time bands, or intervals over which DRP spreads an input quantity or value forecasts.



To display the Maintain Item Group Forecasts Interval Screen, press **Enter**.

Maintain Item Group Forecasts Interval Screen



To display this screen, enter 1 in the Maintain Intervals field on the Maintain Item Group Forecasts Selection Screen, and press **Enter**.

You use this screen to enter forecast quantities or values, by item group and centre or DC, and to define time intervals to spread this forecast over.

If you select no profile, DRP assumes an equal distribution; otherwise, the indices associated with the selected seasonal profile control the distribution of the forecast.

The resulting forecast replaces any existing forecasts for the periods concerned.

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:04:25
Maintain Group Forecasts			
Centre/DC.....	C1 AS	Year 98	Calendar C1
Item Group.....	3 Sun Protection		
Total Forecast....	Value	.00	
Seasonal Profile..			
Control Details			
Daily Forecasts to Week..	4		
Weekly Forecasts to Week..			
Last Week of Forecast.....			
Spread Details			
Forecast Value	to Spread 100	.00	
Daily Forecasts from Week	1 to Week		
Weekly Forecasts from Week	to Week		
F3=Exit F12=Previous			

Fields:

Calendar

The calendar used in the forecasting routines. This is either the code for the selected centre or DC and year, or the default company profile calendar code

Item Group

This is the item group that you are generating forecasts for.

Total Forecast

The previously maintained total forecast quantity or value for the minor item group and year.

Seasonal profile

If you selected a seasonal profile, it is displayed here.

Control Details

Daily Forecasts To Week

The number of the last week for which the automatic forecast spread function created daily forecasts.



Note: This does not update when you interactively spread forecasts.

Weekly Forecast To Week

This is the number of the last week for which the automatic forecast spread function created weekly forecasts.



Note: This does not update when you spread forecasts interactively.

Last Week Of Forecast

This is the number of the last week of the forecast that has a non zero quantity or value. If this is a period forecast the last week is the end week of the period.

Spread Details

Forecast Value To Spread

The title of this field depends on whether you have selected to generate forecasts by quantity or value. In this example the forecast is by value. Enter the forecast value to spread over the selected intervals. DRP breaks this down according to the seasonal profile previously selected. Leave blank, to spread the forecast evenly across the intervals.

Daily Forecast From and To Week

Weekly Forecast From and To Week

Enter the range for which you want to generate period, weekly or daily forecasts over the specified time bands, or intervals. The intervals must not overlap and must be in correct date order, that is, the From date must not be after the To date. The From and To weeks should correspond to the period start and end weeks in the calendar structure.



Press **Enter** to display the Maintain Item Group Forecasts Spread Forecast Screen.

Maintain Item Group Forecasts Spread Forecast Screen



To display this screen, enter the forecast details on the Maintain Item Group Forecasts Interval Selection Screen, then press **Enter**.
Or, enter the forecast details on the Maintain Item Forecasts Selection Screen and press **Enter**.

You use this screen to:

- Maintain the total sales forecast quantity or value for the year.
- Maintain the time phased spread indices.
- Maintain the forecast quantities or values.
- Spread the total forecast.

DR712		Z1 - GB Demonstration Company		USER GBJBA1MS	5/02/98 15:00:51
Maintain Group Forecasts					
Centre/DC.....	D1	Northern Regional DC		Year 97	Calendar C1
Item Group.....	B	Bottled water			
Total Forecast Quantity...	█		Seasonal Profile...?... AL		
Position to Period.....	█	Index	Quantity		
Period	Start	Total...			
- 05	28/04/97				
- 06	26/05/97				
- 07	23/06/97				
- 08	21/07/97				
- 09	18/08/97				
- 10	15/09/97				
- 11	13/10/97				
- 12	10/11/97				
- 13	8/12/97				
1=Select to spread					
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F14=Barchart					
F17=Apply Index F20=Update/Item Forecasts					

Fields:

Total Forecast Quantity

The default value is the previously maintained total forecast quantity or value. Enter a new total forecast quantity. If you enter a different total forecast from DRP total, a warning message displays. You can override this by selecting **F8=Update**.

Seasonal Profile

You can enter a different seasonal profile from the one chosen on the initial screen. This is the profile used if you select a period to week, or week to day, forecast break down. You must have set up the Profile, Year and DC or centre combination using the Seasonal Profile Maintenance function. If this field is

blank, DRP spreads the quantity or value evenly across the selected forecast periods.

Select (Untitled)

Enter 1 against a period to break down period or weekly forecasts.

DRP breaks period forecast records down to weekly forecasts; and weekly forecast records down to daily forecasts. You cannot select daily records, as they cannot be broken down any further.

Position To Period

The default for the start of the period list is the current period. Enter a period number to reposition the list.

Period

There are three forecast levels: period, weekly and daily.

Period records have a number in the format PP, where PP is the defined period number.

Weekly records have a number in the format PPWW, where PP is the period number and WW is the week number.

Daily records display a weekly period number and the actual date as the Start Date.

Start

This column shows the start date for the forecast period, whether it is a period, a week or a day.

For period records the start date is always the first Monday in the period.

For weekly records the start date is always the Monday of the week.

For daily records the actual date is the start date.

Index and Quantity Total

These fields are maintained by the software. To recalculate these figures press **Enter**.

If DRP retrieves the indices from a seasonal profile code, the total is initially 100 and DRP expresses individual forecast period indices proportionally.

DRP reconciles the quantity with the total forecast quantity or Value you have already entered.

Index

Enter the period index value used to spread forecasts. You can retrieve this from the seasonal profile. DRP uses this index to apportion the total forecast.

Quantity

Enter a quantity or value for the respective period, week or day.

You can generate this by interactively breaking down period, or weekly, forecasts or by applying period indices to forecast quantities or values by selecting

Functions:

F14=Barchart

Use this function to display a bar chart showing the forecast quantity or value distribution by period throughout the forecast year.

F17=Apply Index

Use this function to break down the total forecast quantity or value over the forecast periods, in proportion to the period indices, compared to the sum of all period index values.

F20=Update/Item Forecasts

Use this function to update the item minor group forecasts, as for **F8=Update**, and display a window, which you can use to create and maintain multiple item sales forecasts.



Warning: You should apply any indices you have amended, before updating with F8=Update or F20=Update/Item Forecasts.



Select **F8=Update**. This updates the forecasts and indices for the selected DC or centre, year and item group. If DRP maintained total forecast quantity or value is different from the entered forecast quantity, a warning is displayed. You can override this and then update the entered forecast quantity or value.

Maintain Item Group Forecast Weekly Spread Window



To display this window, select a period record on the Maintain Item Group Forecasts Spread Forecast Screen.

You use this window to break down period forecasts into weekly forecasts.



*Note: To update the records, press **Enter** without altering any of the fields.*

DR712	Z1 - GB Demonstration Company	USER GBUA1MS	5/02/98 15:00:51
Maintain Group Forecasts			
Centre/DC..... D1	Northern Regional DC	Year 97	Calendar C1
Item Group..... B	Bottled water		
Total Forecast Quantity...		Seasonal Profile...?..	B1
Position to Period.....	Index	Quantity	
Period	Start	Total...	
1 05	28/04/97		

Weekly Spread			
Period.... 5	Total Quantity....	Seasonal Profile...?..	B1
		Index	Quantity
Week	Start Date	Entered....	
- 17	28/04/97	4.000	
- 18	5/05/97	1.000	
- 19	12/05/97	1.000	
- 20	19/05/97	1.000	
1=Select To Spread			
F4=Prompt F12=Previous F17=Apply Index			

Fields:

Period

The period for which DRP breaks the forecasts down to weekly level.

Total Quantity

Enter the total quantity or value for the period. This defaults from the previous screen.

Seasonal Profile

Enter the seasonal profile used to break down the period forecast to weekly forecasts. This defaults from the previous screen. Leave the profile blank to spread the forecast quantity or value evenly across the weekly forecast periods specified as working weeks on the calendar.

Select (Untitled)

Enter 1 to select a weekly forecast to break down to daily forecasts. Leave the seasonal profile blank, to spread the forecast evenly using the working days on the calendar week template.

Index

Enter the weekly index. The default is from the seasonal profile. Leave the profile code blank on the previous screen, to spread the quantities evenly for all working weeks.

Quantity or Value

Enter the forecast quantity or value for each week. You can generate this by applying the weekly indices to the entered total quantity or value.

Functions:

F17=Apply Index

Use this function to spread the entered total quantity or value over the weeks in the period, in proportion to the weekly indices.



Press **Enter** to continue.

Maintain Item Group Forecast Daily Spread Window



To display this window, select a weekly record on the Maintain Item Group Forecast Weekly Spread Window and press **Enter**.

You use this window to break down weekly forecasts into daily forecasts. Press **Enter** without altering any of the fields, to update the records.

DR712 Z1 - GB Demonstration Company USER GBJBA1MS 5/02/98
15:00:51

Maintain Group Forecasts
Centre/DC..... D1 Northern Regional DC Year 97 Calendar C1
Item Group..... B Bottled water
Total Forecast Quantity...
Position to Period..... Index Seasonal Profile...?... A1
Quantity
Period Start Total...
1 05 28/04/97

S Daily Spread

Period.	Week	Week Total....	Start Date	Entered....	Index	Quantity
1	17		28/04/97		5.000	
-	18		29/04/97		1.000	
-	19		30/04/97		1.000	
-	20		1/05/97		1.000	
			2/05/97		1.000	
			3/05/97			
			4/05/97			

1=Select
F4=Prompt F12=Previous F17=Apply Index

12-32 SR MW KS CL IM DM II EDN400A KB PKH318S1

Fields:

Week Total

Enter the total quantity or value for the week and select **F17=Apply Index** to adjust the forecast.

Index

The top figure in the Index column is always the entered index total. To recalculate the sum of all the daily indices, press **Enter**.

Enter the daily index values and select **F17=Apply Index** to adjust the quantities. This defaults from the seasonal profile. If you leave the profile code blank, DRP sets the indices to 1 for each working day on the weekly template.

Quantity

The top figure in the Quantity column is always the entered quantity total. To recalculate the sum of all daily forecast quantities or values, press **Enter**. DRP checks this against the entered week total quantity or value. If different, DRP issues a warning; select **F8=Update** to override.

Enter the forecast quantity or value for each day. To generate this, apply the daily indices to the total quantity or values and press **Enter**.

Functions:

F17=Apply Index

Use this function to spread the total quantity or value over the days, in proportion to the daily indices.



Press **Enter** to continue.

Maintain Item Group Forecasts Update Item Forecasts Screen.



To display this screen, select **F20=Update Item Forecasts** from the Item Group Forecast Spread Forecast Screen.

Use this screen to select one or more items from the item group to apply the group forecasts to.

```
DR712          Z1 - GB Demonstration Company      USER GBJBA1MS    5/02/98
                                           15:18:32

Maintain Group Forecasts
Centre/DC..... D1   Northern Regional DC          Year 97  Calendar C1
Item Group..... B    Bottled water
Total Forecast Quantity... _____ Seasonal Profile...?... 01
Position to Period..... _      Index      Quantity
Period      Start      Total...

Select Item
-----
Item          Description                      % of Group
_ LTS/N/001    latest costed item 1                  100.000

1=Select      Position to: _____
F12=Previous
F8=Exit F4=Prompt F8=Update F11=Delete F12=Previous F14=Barchart
F17=Apply Index F20=Update/Item Forecasts
```

Fields:

Select (Untitled)

Enter 1 to select the item, or items, and access Item Sales Forecast Maintenance functions.



Press **Enter** to continue.

Forecast Barchart Screen




To display this screen, select **F14=Barchart** on the Spread Forecast Screen.

This screen displays a bar chart of the forecast quantity or value distribution throughout the forecast year, by week.

If the forecast is for periods, DRP divides the total by the number of weeks within the period. For example, a period forecast of 200 units for a 4 week period displays as 50 units per week.

If the forecast is for days, DRP accumulates the forecasts throughout the week and displays the resulting weekly total.

DRP calculates the Y axis from the maximum forecast quantity or value in the year, so that it all fits on screen. You can change this by entering a maximum figure in the Alter Scale field. If this field is blank the display reverts to the default.



Tip: Page up and down to display further weeks.



Press **Enter** to exit the screen.

Sales Forecast Generate Item Forecast



4/DRF

Use this function to break item group forecasts down into item forecasts, in proportion to the percentages defined for the items within the item group profiles.

This function regenerates all item forecasts for items within the selected item groups.

Generate Item Forecast Selection Screen



Select Generate Item Forecast.

You use this screen to select the centre or DC, year and range of item groups to generate item level forecasts for.

DR732	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Generate Item Forecast		10:12:14	
Enter Centre/DC.....?.. █			
Year..... 98			
Item Group.....?.. ____ to ____			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined and at least one item group profile defined for the DC or centre.

Year

Enter the year, in YY format, that you want to generate forecasts for.

Item Group From and To

Enter the minor item group range.



Note: Leave both fields blank to display all item groups that have item group forecasts assigned for the DC or centre.



Press **Enter** to display the Generate Item Forecast Group Selection Screen.

Generate Item Forecast Group Selection Screen



To display this screen, press **Enter** on the
Generate Item Forecast Selection Screen.

You use this screen to select one or more item groups in order to generate item level sales forecasts. DRP recalculates all forecasts for the items within the item group according to the percentages defined in the item group profile.

DR732	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:12:43
Generate Item Forecast			
Centre/DC..... C1 AS		Year	Calendar C1
WARNING - This Program will recalculate all Items Forecasts within the selected Item Groups.....			
Sel	Item Group	Description	
1	10	Alcohol	
-	3	Sun Protection	
<u>1=Select</u>			
F3=Exit F8=Submit Job F12=Previous			

Fields:

Sel

Enter 1 to select an item group for processing.



Tip: You can maintain the item forecast using
the Item Sales Forecast option.



Select **F8=Submit Job**

Sales Forecast Maintain Item Forecast



5/DRF

Use this function to create and maintain item level sales forecasts. You can generate these forecasts by:

- Profiling item group forecasts, using facilities within the DRP module.
- Transferring forecasts directly from the Forecasting module using facilities within that module.
- Direct entry through this function without prior set-up of Item Group Profiles.

Maintain Item Sales Forecast Selection Screen



Select Maintain Item Forecast.

You use this screen to select the item for which you want to create or maintain sales forecasts.

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
10:13:38			
Maintain Product Forecast			
Centre/DC.....?.. ☐			
Year..... 98			
Item.....?.. _____			
Forecast Basis..... 1 (1=Quantity 2=Value)			
Seasonal Profile..?.. __			
Maintain Intervals... _ (1=Yes)			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Year

Enter the year for which the forecast is being created, in YY format. You can change to a subsequent year defined to the calendar for the DC or centre.

Item

Enter an item defined to the centre or DC.

Forecast Basis

Enter one of the following:

- 1 - To forecast by quantity.
- 2 - To forecast by value.

If you previously maintained the forecast using the alternative forecasting basis, a warning is displayed; select **F8=Update** to proceed.

Seasonal Profile

Enter a seasonal profile. The profile, year and DC or centre combination must already exist. The seasonal profile you select here determines the level at which you can maintain targets. If you enter a seasonal profile which has been set up

using weekly levels, you cannot maintain period targets. If you don't enter a profile, DRP spreads item level quantity or value forecasts across the forecast periods.

Maintain Intervals

Enter 1 to access the Maintain Intervals Screen. You use this to define the time bands (intervals) to spread the quantity or value forecasts over. The default is blank.



Press **Enter** to continue.

Maintain Item Sales Forecast Interval Selection Screen



To display this screen, press **Enter** on the Maintain Item Sales Forecast Selection Screen.

You use this screen to enter forecast quantities, or values, by item and centre or DC and define time intervals over which to automatically spread this forecast, using a selected seasonal profile. The resulting forecast replaces any existing forecasts for the time bands involved. You can display the calendar structure for the DC to help when specifying the time bands, or intervals.

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:13:38
-------	-------------------------------	---------------	----------------------

Maintain Product Forecast

Centre/DC..... C1	AS	Year 98	Calendar C1
Forecast Item..... 5012	Crisps low fat/salt 30g x 144 Box		
Total Forecast....	Quantity	.000	
Seasonal Profile..			

Control Details

Daily Forecasts to Week..	
Weekly Forecasts to Week..	
Last Week of Forecast.....	

Spread Details

Forecast Quantity to Spread	☐ .000
-----------------------------	-------------------------------

Daily Forecasts from Week __ to Week __
Weekly Forecasts from Week __ to Week __

F3=Exit F12=Previous

Fields:

Calendar

The calendar used in the forecasting routines. This is either the code for the selected centre or DC and year, or the default company profile calendar code

Forecast Item

This is the item that you are generating forecasts for.

Total Forecast

The previously maintained total forecast quantity or value for this item and year.

Seasonal profile

If you selected a seasonal profile, it is displayed here.

Control Details

Daily Forecasts To Week

The number of the last week for which the automatic forecast spread function created daily forecasts.



Note: This does not update when you interactively spread forecasts.

Weekly Forecast To Week

This is the number of the last week for which the automatic forecast spread function created weekly forecasts.



Note: This does not update when you spread forecasts interactively.

Last Week Of Forecast

This is the number of the last week of the forecast that has a non zero quantity or value. If this is a period forecast the last week is the end week of the period.

Spread Details

Forecast Quantity To Spread

The title of this field depends on whether you have selected to generate forecasts by quantity or value. In this example the forecast is by quantity. Enter the forecast value to spread over the selected intervals. DRP breaks this down according to the seasonal profile previously selected. Leave blank, to spread the forecast evenly across the intervals.

Daily Forecast From and To Week

Weekly Forecast From and To Week

Enter the range for which you want to generate period, weekly or daily forecasts over the specified time bands, or intervals. The intervals must not overlap and must be in correct date order, that is, the From date must not be after the To date. The From and To weeks should correspond to the period start and end weeks in the calendar structure.



Press **Enter** to display the Maintain Product Forecast Spread Forecast Screen .

Maintain Product Forecast Spread Forecast Screen



To display this screen, press **Enter** on the Maintain Item Sales Forecast Interval Selection Screen.

You use screen this to maintain the total and period forecast quantities or values and seasonal indices. You can break down the forecasts to daily, period and weekly forecasts.

DR714	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:18:31
Maintain Product Forecast			
Centre/DC..... C1	AS	Year 98	Calendar C1
Item Group..... 1	Food	% of Group...	.000
Forecast Item.... 5012	Crisps low fat/salt	30g x 144 Box	
Total Forecast Quantity...		Seasonal Profile...?	—
Position to Period.....	Index	Quantity	
Period	Start	Total..	
- 0310	9/03/98		
- 0311	16/03/98		
- 0312	23/03/98		
- 0413	30/03/98		
- 0414	6/04/98		
- 0415	13/04/98		
- 0416	20/04/98		
- 0517	27/04/98		
- 0518	4/05/98		+
1=Select to spread			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F14=Barchant			
F17=Apply Index F18=Display Values			

Fields:

Total Forecast Quantity

The default value is the previously maintained total forecast quantity or value. Enter a new total forecast quantity or value. If you enter a different total forecast from DRP total, a warning message displays. You can override this by selecting **F8=Update**.

Seasonal Profile

You can enter a different seasonal profile from the one chosen on the initial screen. This is the profile used if you select a period to week, or week to day, forecast break down. You must have set up the Profile, Year and DC or centre combination using the Seasonal Profile Maintenance function. If this field is blank, DRP spreads the quantity or value evenly across the selected forecast periods.

Position To Period

The default for the start of the period list is the current period. Enter a period number to reposition the list.

Period

There are three forecast levels: period, weekly and daily.

Period records have a number in the format PP, where PP is the defined period number.

Weekly Records have a number in the format PPWW, where PP is the period number and WW is the week number.

Daily records display a weekly period number and the actual date as the Start Date.

Start

This column shows the start date for the forecast period, whether it is a period, a week or a day.

For period records the start date is always the first Monday in the period.

For weekly records the start date is always the Monday of the week.

For daily records the actual date is the start date.

Index and Quantity Total

These fields are maintained by the software. To recalculate these figures press **Enter**.

If DRP retrieves the indices from a seasonal profile code, the total is initially 100 and DRP expresses individual forecast period indices proportionally.

DRP reconciles the quantity with the total forecast quantity or Value you have already entered.

Select (Untitled)

Enter 1 against a period to breakdown period or weekly forecasts.

DRP breaks period forecast records down to weekly forecasts; and weekly forecast records down to daily forecasts. You cannot select daily records, as they cannot be broken down any further.

Index

Enter the period index value used to spread forecasts. You can retrieve this from the seasonal profile. DRP uses this index to apportion the total forecast.

Quantity

Enter a quantity or value for the respective period, week or day.

You can generate this by interactively breaking down period, or weekly, forecasts or by applying period indices to forecast quantities or values by selecting

Functions:

F14=Barchart

Use this function to display a bar chart showing the forecast quantity or value distribution by period throughout the forecast year.

F17=Apply Index

Use this function to break down the total forecast quantity or value over the forecast periods, in proportion to the period indices, compared to the sum of all period index values.

F18=Display Values

Display Values or Quantities. Use this function to alternate between the quantity and value displays. You cannot maintain the alternative view.



Warning: You should apply any indices you have amended, before updating with F8=Update.



Select **F8=Update**. This updates the forecasts and indices for the selected DC or centre, year and item group. If DRP maintained total forecast quantity or value is different from the entered forecast quantity, a warning is displayed. You can override this and then update the entered forecast quantity or value.

Sales Forecast Spread Item Forecast



6/DRF

You use this option to quickly spread sales forecasts down to period, weekly and daily levels by batch processing. This avoids having to individually spread forecasts in the Maintain Item Forecast option.

If you have set up a seasonal profile on the DRP item master record, it appears as the default profile on the Spread item Sales Forecast Detail Screen. You can change to an alternative profile or leave blank, in which case DRP evenly spreads the forecasts across the intervals.



Note: DRP does not update any forecast with planning intervals that are inconsistent with the interval parameters and it also includes the forecast in an exception report.

Spread Item Sales Forecast Selection Screen



To display this screen, select the Spread Item Forecast option.

You use this screen to enter the selection criteria for the Spread Item Sales Forecast.

DR726	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Spread Item Sales Forecast			10:28:47
Centre/DC.....?.. █			
Year 98			
Item Group.....?.. ____			
From Item?.. _____			
To Item?.. _____			
Forecast Basis 1 (1=Quantity 2=Value)			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Year

Enter the year, in YY format. You must have set up the year and centre or DC combination already.

Item Group

Enter a minor item group. If you leave the field blank, all item groups with existing item forecasts display.

From Item and To Item

Enter the required item range.



Note: If you leave both the From and To fields blank, all existing item forecasts within the item group display.

Forecast Basis

Enter one of the following:

- 1 - To maintain quantity forecasts.
- 2 - To maintain value forecasts.

If you previously maintained the forecast using the other option, a warning displays.



Press **Enter** to display the detail screen.

Spread Item Sales Forecast Detail Screen



To display this screen, on the Spread Item Sales Forecast Selection Screen, enter the required details and press **Enter**.

Use this screen to select one or more items for spreading over the specified intervals, or time bands. These intervals must be in correct date order, that is the From date must be before the To date, and you must enter at least one set.

DR726	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Spread Item Sales Forecast			10:30:59
Centre/DC..... C1	AS	Year 98	Calendar C1
Item Group..... 3	Sun Protection		
Item	Description	Total Forecast	Seasonal
		Quantity	PRF.(?)
- 5001	Suncream Factor 4 225ml	99.000	
- 5002	Suncream Factor 8 225ml B0B		
- 5005	Suncream Factor 4 300ml		
Intervals: Daily forecasts from week <u>1</u> to week <u>4</u>			
Weekly forecasts from week <u> </u> to week <u> </u>			
<u>1=Select</u>			
F3=Exit F4=Prompt F8=Submit job F12=Previous F15=Select all			
F18=Display Values			

Fields:

Select (Untitled)

Enter 1 to select an item forecast for profiling over the selected intervals.

Functions:

F15=Select All

Use this function to set all selection fields to 1. Then manually de-select items for which you do not require a forecast.

F18=Display Values

Display values or quantities. Use this function to alternate the basis of display.



Select **F8=Submit Job** to submit the job.

Stock Forecast Maintain Item Group Forecast

1... **7/DRP**
2...

You use this function to interactively maintain stock level targets at item group and centre or DC level. You can build stocks, in excess of safety stocks, to meet periods of demand when the supply rate is unable to satisfy that demand.

You can express requirements in terms of quantity or value and you can specify dates during which and by which, you must build and consume the target.

Maintain Item Group Stock Forecasts Selection Screen



Select Maintain Item Group Forecast.

You use this screen to select which stock level targets to maintain and on what basis, by centre or DC, year and item group.

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:32:40
Maintain Item Group Stock Forecasts			
Centre/DC.....?.. C1			
Year..... 98			
Item Group.....?.. █			
Forecast Basis..... 1 (1=Quantity 2=Value)			
Seasonal Profile..?.. _			
Maintain Intervals... _ (1=Yes)			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined. It must also have at least one valid minor item group profile, defined through Item Group Profile Maintenance.

Year

Enter the year, in YY format. This defaults to the current year. You can change this to a subsequent year defined to the calendar for the selected DC or centre.

Item Group

Enter a minor item group with a profile set up for the centre or DC.

Forecast Basis

Enter one of the following:

- 1 - To maintain stock level targets by quantity.
- 2 - To maintain stock level targets by value.

If you previously maintained the stock level using the other option, a warning is displayed.

Seasonal Profile

Enter a seasonal profile code. The profile determines at which level, period or week, you can maintain stock level targets. For example, if you have set up the seasonal profile using entry level 2, you cannot maintain the period targets.

If you leave this field blank, and do not select the stock level profiling option, the stock level targets are at maximum for the initial forecasting period and reduce on a straight line basis for subsequent periods.

Maintain Intervals

Enter a 1 to access the Maintain Intervals Screen. You can then define time bands (intervals) over which to automatically maintain stock level targets. The default is blank.



Press **Enter** to continue.

Maintain Item Group Stock Forecasts Intervals Selection Screen



To display this screen, enter a 1 in the Maintain Intervals field on the Maintain Item Group Stock Forecasts Selection Screen and press **Enter**.

You use this screen to maintain stock level targets and to define the time bands (intervals) over which you build or consume the targets, or both.

The indices, associated with the selected seasonal profile, control the build and consumption of the stock levels. If you do not select a profile, DRP applies the stock target to the first period selected and reduces it, on a straight line basis, to zero by the end period.

You can display the calendar structure for the DC/centre and year to assist in specifying time bands (intervals).

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98 10:33:33
-------	-------------------------------	---------------	----------------------

Maintain Item Group Stock Forecasts

Centre/DC..... C1	AS	Year 98	Calendar C1
Item Group..... 3	Sun Protection		
Stock Target.....	Quantity	.000	
Seasonal Profile.. A1	Fred		

Control Details

Daily Forecasts to Week..	4
Weekly Forecasts to Week..	
Last Week of Forecast.....	

Spread Details

Stock Target over Intervals	☐ .000
-----------------------------	-------------------------------

Daily Forecasts from Week	__	to Week	__
Weekly Forecasts from Week	__	to Week	__
Period Forecasts from Week	__	to Week	__

F3=Exit F12=Previous F20=Display Structure

Fields:

Calendar

The calendar used in the forecasting routines. This is either the code for the selected centre or DC and year, or the default company profile calendar code

Item Group

This is the item group that you have selected.

Stock Target

This is the last maintained stock target.

Seasonal profile

If you selected a seasonal profile, it is displayed here.

Control Details

Daily Forecasts To Week

The number of the last week for which the automatic forecast spread function created daily forecasts.



Note: This does not update when you interactively spread forecasts.

Weekly Forecast To Week

This is the number of the last week for which the automatic forecast spread function created weekly forecasts.



Note: This does not update when you spread forecasts interactively.

Last Week Of Forecast

This is the number of the last week of the forecast that has a non zero quantity or value. If this is a period forecast the last week is the end week of the period.

Spread Details

Stock Target Over Intervals

Enter the maximum stock level target for the selected intervals. DRP assigns this according to the selected seasonal profile, in proportion to the maximum period index. If you do not select a seasonal profile, DRP sets the period indices to 100.

Daily Forecast From and To Week

Weekly Forecast From and To Week

Period Forecasts From and To Week

Enter the range for which you want to generate period, weekly or daily forecasts over the specified time bands, or intervals. The intervals must not overlap and must be in correct date order, that is, the From date must not be after the To date. The From and To weeks should correspond to the period start and end weeks in the calendar structure.

Functions:

F20=Display Structure

Use this function to show the details for the selected year, calendar and centre or DC combination.



Press **Enter** to display the Maintain Item Group Stock Period Stock Levels Screen.

Maintain Item Group Stock Forecasts Period Stock Levels Screen



To display this screen, enter details on the
Maintain Item Group Stock Forecasts Intervals
Selection Screen and press **Enter**.

Use this screen to maintain a stock level target, the time phased spread indices
and stock level target quantities or values, for periods, weeks and days.

DR712		Z1 - UK Demonstration Company		USER GBJBANB4	10/03/98 10:34:21
Maintain Item Group Stock Forecasts					
Centre/DC..... C1		AS		Year 98 Calendar C1	
Item Group..... 3		Sun Protection			
Stock Target Quantity.....		Seasonal Profile...?... 01			
Position to Period.....		Quantity			
Period	Start	Index			
- 01	5/01/98	1.000			
- 02	2/02/98	1.000			
- 03	2/03/98	1.000			
- 04	30/03/98	1.000			
- 05	27/04/98	1.000			
- 06	25/05/98	1.000			
- 07	22/06/98	1.000			
- 08	20/07/98	1.000			
- 09	17/08/98	1.000			
+					
1=Select to spread					
F3=Exit F4=Prompt F8=Create F12=Previous F14=Barchant					
F17=Apply Index F20=Create/Item Forecasts F22=Stock Profile					

Fields:

Stock Target Quantity

Enter the new target. The default is the previously entered stock level target.

Seasonal Profile

Enter a different seasonal profile to profile stock levels. If this field is blank, DRP assigns the target to the initial period and reduces it, on a straight line basis, to zero at the last period.

Position To Period

Enter the period number to reset the list start from the current period.

Period

There are three forecast levels: period, weekly and daily.

Period records have a number in the format PP, where PP is the defined period number.

Weekly Records have a number in the format PPWW, where PP is the period number and WW is the week number.

Daily records display a weekly period number and the actual date as the Start Date.

Start

This column shows the start date for the forecast period, whether it is a period, a week or a day.

For period records the start date is always the first Monday in the period.

For weekly records the start date is always the Monday of the week.

For daily records the actual date is the start date.

Index and Quantity Total

These fields are maintained by the software. To recalculate these figures press **Enter**.

If DRP retrieves the indices from a seasonal profile code, the total is initially 100 and DRP expresses individual forecast period indices proportionally.

DRP reconciles the quantity with the total forecast quantity or Value you have already entered.

Select (Untitled)

Enter 1 to select a stock level target. Select a period target to spread to weekly level. Select a weekly target to spread to daily level. You cannot select a daily target.

Quantity or Value

Enter a period quantity or value. DRP checks the period quantity or value against the maximum stock level target. If period forecasts exceed the maximum target, a warning displays.

You can also apportion the value by applying period indices to maximum stock level target quantities or values, or adjust the value by profiling period targets down to week targets and weeks down to days.

If applying seasonal indices, DRP calculates the period stock level from the maximum stock level target, based on the ratio of the period index to the maximum period index. If you do not select a seasonal profile, DRP sets the period indices to 100.

Functions

F14=Barchart

Use this function to display a bar chart showing the stock build quantity (or value) distribution, by period, throughout the forecast year.

F17=Apply Index

Use this function to profile the total stock over the forecasting periods, in proportion to the period indices relative to maximum period index.

F20=Create/Item Forecasts

Use this function to update the item minor group stock targets and display a window showing all items within the family, so you can create and maintain item stock level targets.

F22=Stock Profile

Use this function to maintain target (maximum) stock levels (value or quantity) and dates to build and consume stocks by.



Warning: Make sure you apply indices before you select F8=Create or F20=Create/Item Forecasts.



Press **Enter** to continue.

Maintain Item Group Stock Forecasts Create/Item Forecasts Window



To display this window, select **F20=Create/Item Forecasts** on the Maintain Item Group Stock Forecasts Period Stock Levels Screen.

This window displays all the items within the product item group and the percentage splits for items within the item group profiles. You can select one or more items sequentially, to apply the updated time-phased stock level targets at item level.

```
DR712          Z1 - UK Demonstration Company      USER GBJBANB4  10/03/98
                                                    10:42:03
Maintain Item Group Stock Forecasts
Centre/DC..... C1  AS                          Year 98  Calendar C1
Item Group..... 3   Sun Protection
Stock Target Quantity..... 1000.000             Seasonal Profile...?... AL
Position to Period.....  _   Index              Quantity
    Period      Start
Select Item
+-----+
| Item      | Description                               | % of Group |
|-----|-----|-----|
| - 5001    | Suncream Factor 4 225ml                   | 10.000     |
| - 5002    | Suncream Factor 8 225ml B0B               | 50.000     |
| - 5005    | Suncream Factor 4 300ml                   | 20.000     |
+-----+
1=Select    Position to:  _
F12=Previous
F9=Exit F4=Prompt F8=Create          F12=Previous F14=Barchart
F17=Apply Index F20=Create/Item Forecasts F22=Stock Profile
```

Fields:

Select (Untitled)

Enter 1 to select item(s) and access Item Stock Forecast Maintenance functions.

Position to:

If you want to position the list to a certain point, enter an item code here.



Press **Enter**.

Maintain Item Group Stock Forecasts Stock Profile Window



To display this window, select **F22=Stock Profile** from the Maintain Item Group Stock Forecasts Period Stock Levels Screen.

Use this window to define stock building targets so DRP can automatically create a time phased stock level plan.

DR712	Z1 - UK Demonstration Company	USER GBJBAHEH	25/08/99 14:38:10
Maintain Item Group Stock Forecasts			
Centre/DC.....	C1 Birmingham Central Depot	Year 99	Calendar C1
Item Group.....	3 Sun Protection		
Stock Target Quantity.....		Seasonal Profile...?..	___
Position to Period.....	___	Index	Quantity
Period	Start		
- 0728	12/07/99		
- 0829	19/07/99		
- 0830	26/07/99		
- 0831	2/08/99		
- 0832	9/08/99		
- 0933	16/08/99		
- 0934	23/08/99		
- 0935	30/08/99		
- 0936	6/09/99		

Stock Level Profile

From date..... 4/01/99

To date..... 27/12/99

Target date..... 31/03/99

Target Quantity..... 100000

F12=Previous

1=Select to spread
F3=Exit F4=Prompt F8=Create F12=Previous F14=Barchart
F17=Apply Index F20=Create/Item Forecasts F22=Stock Profile

Fields:

From Date and To Date

Enter the date to start the stock build and the date by which the stock should be back to the safety stock level.

Target Date

Enter the date by which the stock should reach the maximum quantity. This must be between the To and From date range.

Target Quantity or Value

Enter a target or maximum quantity, or value, to build by the specified target date. This should be a quantity above the safety stock level.

Example

You must build stocks from 04/01/99, to a maximum stock position of 100,000 units by 31/03/99. You must consume this stock by 27/12/99

The date range is 04/01/99 to 27/12/99.

The target quantity is 100,000 units.

The target date is 31/03/99.

DRP generates time phased stock level targets, building from the safety stock level, on a straight line basis from 04/01/99 to a peak of 100,000 on 31/03/99. DRP reduces the stock back down to safety stock, on a straight line basis, by 27/12/99, assuming there is sufficient demand to consume it.

Functions:

F13=Generate Stock Targets

Use this function to generate stock targets for the items within the selected item group.

Select **F12=Previous** to abandon the transaction without updates; select **F8=Create Entry** to proceed with the creation.



Press **Enter** to generate the stock level indices and targets within the date range.

Stock Forecast Generate Item Forecast



8/DRF

You use this function to profile item group stock level targets to item stock level targets, in proportion to the percentages defined for the items within the item group profile.

This function regenerates all item stock targets for the items in the selected item groups.

Generate Item Stock Forecast Item Group Selection Screen



To display this screen, select Generate Item Forecast.

You use this screen to select the centre/DC, year and range of item groups for which you want to generate stock level targets.

DR732	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
			10:44:01
Generate Item Stock Forecast			
Enter Centre/DC.....?.. Q1			
Year..... 98			
Item Group.....?.. ___ to ___			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined and at least one item group profile defined for the DC or centre.

Year

Enter the year, in YY format.

Item Group

Enter the required minor item group range. Leave both fields blank to display all item groups for the DC or centre, which have item group forecasts assigned.



Press **Enter** to continue.

Generate Item Stock Confirm Selection Screen



To display this screen, complete the Generate Item Stock Forecast Item Group Selection Screen and press **Enter**.

You use this screen to select one or more item groups in order to generate item level stock targets. DRP recalculates the targets for all items within the selected item group, according to the percentages defined for the item in the Item Group Profile.

DR732	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Generate Item Stock Forecast			10:44:22
Centre/DC.....	C1 AS	Year	Calendar C1
WARNING - This Program will recalculate all Items Forecasts within the selected Item Groups.....			
Sel	Item Group	Description	
☒	10	Alcohol	
☐	3	Sun Protection	
_1=Select			
F3=Exit F8=Submit job F12=Previous			

Fields:

Sel

Select. Enter 1 to select an item group for processing.

This converts an item group stock level target from a value target to a quantity target. DRP divides the value target by the base list price to obtain the quantity requirement.



Select **F8=Submit Job** to submit the job. This recalculates stock level targets for all items within selected item groups.

Stock Forecast Maintain Item Forecast



9/DRF

You use this option to create and maintain stock level targets, by item and DC or centre. DRP generates these targets by:

- Profiling item group stock level targets using previously described functions within DRP.
- Direct entry through this function without prior set-up of Item Group Profiles.

Maintain Item Stock Forecast Selection Screen



To display this screen, select Maintain Item Forecast.

You use this screen to select the item for which you want to create or maintain stock level targets.

DR710	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Maintain Item Stock Forecast			10:44:44
Centre/DC.....?.. Q1			
Year..... 98			
Item.....?.. _____			
Forecast Basis..... 1 (1=Quantity 2=Value)			
Seasonal Profile..?.. _			
Maintain Intervals... _ (1=Yes)			
F3=Exit F4=Prompt			

Fields:

DC/Centre

Enter a centre or DC with periods and stockrooms defined.

Year

Enter the year, in YY format. You can change to a subsequent year defined to the calendar for the DC or centre item.

Item

Enter an item defined in DRP for the centre or DC.

Forecast Basis

Enter one of the following:

- 1 - To generate stock building schedules by quantity.
- 2 - To generate stock building schedules by value.

If the forecasting basis is different to that previously used, a warning is displayed. You can override this.

Seasonal Profile

Enter a seasonal profile. The seasonal profile you select here determines the level at which you can maintain targets. If you enter a seasonal profile which has been set up using weekly levels, you cannot maintain period targets.

Maintain Intervals

Enter 1 to access the Maintain Intervals Screen. You use this screen to define time bands (intervals) used to automatically maintain quantity or value stock level targets. The default is blank.



Press **Enter** to continue.

Maintain Item Stock Forecast Period Targets Screen



To display this screen, complete the Maintain Item Stock Forecast Intervals Selection Screen and press **Enter**.

You use this screen to maintain maximum and period stock level targets and seasonal indices. You can profile, by stages, period stock level targets to daily and weekly targets, using different seasonal profiles for each stage.

DR714	Z1 - UK Demonstration Company		USER GBJBANB4	10/03/98 10:45:57
Maintain Item Stock Forecast				
Centre/DC..... C1	AS	Year 98 Calendar C1		
Item Group..... 3	Sun Protection	% of Group.. 10.000		
Forecast Item.... 5001	Suncream Factor 4 225ml			
Stock Target Quantity.....		Seasonal Profile...?... AL		
Position to Period.....		Index	Quantity	
Period	Start	Total..		
- 01	5/01/98	1.000		
- 02	2/02/98	1.000		
- 03	2/03/98	1.000		
- 04	30/03/98	1.000		
- 05	27/04/98	1.000		
- 06	25/05/98	1.000		
- 07	22/06/98	1.000		
- 08	20/07/98	1.000		
- 09	17/08/98	1.000		+
1=Select to spread				
F3=Exit F4=Prompt F8=Create F12=Previous F14=Barchart				
F17=Apply Index F18=Display Values F22=Stock Profile				

Fields:

% Of Group

The percentage stock level requirement for this item, within the item group profile. This does not display if you created the stock build using this function but did not include the item in the item group profile.

Stock Target Quantity or Value

Enter the stock level target quantity or value.



Note: You can use **F18=Display Values/Quantities** to switch between quantity and values; however you cannot maintain the alternative display. You base conversion on item stockroom base sales price.

Seasonal Profile

You can enter a different seasonal profile from that chosen on the Maintain Item Stock Forecast Selection Screen. This is the profile used if you selected period to week or week to day stock level profiling.

Position To Period

Enter a period number to set the initial start position for display of period forecast. The default is the current period.

Select (Untitled)

Enter 1 to select a period schedule to break down to weekly level or a weekly schedule to break down to daily level. You cannot select a daily record.

Period and Start Dates

Period records have a number in format PP, where PP is the period number defined in the DC or centre calendar for the year. The start date is the first Monday in the period.

Weekly records have a number in the format PPWW, where PP is the period number and WW is the week number within the year defined in the calendar. The start date is the Monday of the week.

Daily records have the weekly number and the actual date as the start date.

Index

Enter the period index. DRP can retrieve this from the database or the seasonal profile. DRP uses this to calculate the individual period stock level target quantity, or value, from the maximum target quantity or value in proportion to maximum period index.

Quantity or Value

Enter the quantity or value for each forecasting period. You can generate this figure by applying seasonal indices.

Functions:

F14=Barchart

Use this function to display a bar chart showing the stock build quantity or value distribution throughout the forecast year.

F17=Apply Index

Use this function to profile the entered stock level target over the planning periods, according to the indices in each period relative to maximum period index.

F18=Display Values/Quantities

Use this function to alternate between the quantity and value displays. If you originally selected quantity, you cannot maintain the value. It is not possible to change the indices or values or stock level targets.

F22=Stock Profile

This displays the Stock Profile Window. Use this function to maintain target stock levels and dates to build and consume stocks by.



Press **Enter** to continue.

Stock Forecast Spread Item Forecast



10/DRF

Use this function to automatically profile stock level targets by period, week and day, using a seasonal profile selective within defined time intervals.

The seasonal profile set up on the DRP item master records appears as the default profile on the item selection screen. You can change to an alternative profile or leave it blank.



Note: An exception report highlights any existing stock level targets inconsistent with the interval parameters report. DRP does not update the targets.

Spread Item Stock Forecast Selection Screen



Select Spread Item Forecast.

Use this screen to enter the criteria for the spread item stock forecast.

DR726	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Spread Item Stock Forecast			10:49:40
Centre/DC.....?.. Q1			
Year 98			
Item Group.....?.. █			
From Item?.. _____			
To Item?.. _____			
Forecast Basis 1 (1=Quantity 2=Value)			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Year

Enter the year, in YY format, for which you require the stock level targets.

Item Group

Enter a minor item group. If you leave the field blank, all item groups with existing item stock level targets are displayed.

From Item and To Item

Enter the required item range. Leave both the From and To fields blank to display all existing item stock level targets within the selected item group.

Forecast Basis

Enter one of the following:

- 1 - To maintain stock level plans by quantity.
- 2 - To maintain stock level plans by value.



Press **Enter** to display the Stock Spread Item Forecast Detail Screen. .

Stock Spread Item Forecast Detail Screen



To display this screen, complete the Spread Item Stock Forecast Selection Screen, and press **Enter**.

You use this screen to specify one or more items for spreading over the specified intervals or time bands.

DR726	Z1 - Demonstration Company	USER SP1	23/09/94 11:23:29
Spread Item Stock Forecast			
Center/DC.....	C1 Birmingham Central Depot	Year 94 Calendar C1	
Item Group.....	3 Sun Protection		
Item	Description	Stock Target Quantity	Seasonal Profile
1 5005	Suncream Factor 4 300ml	2500.000	—
Intervals: Daily forecasts from week __ to week __			
Weekly forecasts from week __ to week __			
1=Select			
F3=Exit F4=Prompt F8=Submit job F12=Previous F15=Select all			
F18=Display Values			

Fields:

Select (Untitled)

This field is untitled on screen. Enter 1 to select an item stock level target for profiling over the selected intervals or time bands.

Stock Target Quantity

You can change whether the stock target quantity or value displays, using **F18=Display Quantity or Values**. This defaults to the previously maintained item group profiles and item group or item level stock targets.

Seasonal Profile

Enter a new seasonal profile. This defaults to the seasonal profile for the item. This determines how to profile the stock level targets over time. If blank, DRP spreads the requirements evenly.

Intervals

Enter the intervals (time bands) over which to profile the stock targets. The intervals must be in correct date order, that is the From date must be before the To date, and you must enter at least one set. If the intervals are inconsistent with existing item stock level targets, DRP produces an exception report. For example, where a selection attempts to break down an existing daily forecast down into weeks.

Functions:

F15=Select All

Use this function to select all the items. You can then manually deselect items for which you do not require a stock build plan.

F18= Display Quantity and Value

Use this function to alternate the basis of display; if displaying quantities this displays the values and vice versa.



Note: You must select at least one item from the list.



Select **F8=Submit Job** to submit the job.

-
-
-
-
-

Chapter 3 Processing


The DRP Cycle

The following diagram represents the DRP cycle.

This description represents a one-level DRP cycle run. You can repeat or partially repeat this cycle for each network.



Note: You can define a supply centre in one network as a DC (Distribution Centre) in another network.



Review DC Forecasts

If you use forecasts, you review and update the stock and sales forecasts for each item at the DC. Forecasts are not mandatory in DRP.

Evaluate DC Demand

Assess the supply and demand figures for all DCs within a specified network. Supply plans are generated at item level for each centre. The supply plans suggest new supply orders, from the centre or from external suppliers, and amend existing supply orders. Evaluate DC demand also deletes all previous suggestions.

The plans provide planners with the information to match supply and demand, check the feasibility of suggestions, monitor data integrity and assess the impact of new situations at each DC.

Confirm Suggestions

Once you have reviewed and accepted the DC run suggestions, you can convert the suggestions to requisitions in the Requisitioning module. You can amend the requisitions if you want.



Note: DRP deletes all outstanding requisitions for the stockrooms, and adds new ones from the latest DRP suggested orders.

Create Local Purchase Orders

Use Requisitioning to convert the purchase requisitions, created from DRP, to purchase orders on external suppliers. DRP transfers purchase orders into Purchase Management.

Create Distribution Orders

Use Requisitioning to convert the distribution requisitions, for supply from a centre, into distribution orders. DRP transfers distribution orders into Sales Order Processing and places the order lines against the centre stockroom defined to the item in DRP.

You can enter distribution orders directly into Sales Order Processing, by using the Distribution Order Entry or Amend options. Specify the From and To stockrooms, to automatically create a link between them. DRP creates an internal sales order against the customer defined for the to stockroom.

Note the following:

- DRP treats the distribution order as an internal sales order, and raises no invoice details. The customer is defined to the stockroom to receive the supply.
- On confirmation of despatch, DRP adds the distribution order lines to the DRP Shipments In-Transit File. If you have World Trade attached, and the transfer is across an EC border, DRP writes a movement record for processing within the World Trade module. DRP uses this to produce Intrastat and ESL reports, and to post the acquisition VAT due on receipt of the goods.
- When the stockroom receives the distribution order lines, you need to confirm the goods as received within DRP.

Run Central Purchasing Plan

Assess the supply and demand figures for the supply centre. Suggest new purchase orders from external suppliers and recommend amendments to existing purchase orders.



Note: If the centre is a Manufacturing site, you must define the Items at the centre to Manufacturing not DRP, and the centre run should be an MPS run not a DRP run.

Create Purchase/Production Orders

Create the requisitions from DRP suggestions and then convert them to purchase orders, in Purchase Management.

You can create manufacturing orders from MPS suggestions within the Master Production Scheduling module. Refer to Requisitioning or Manufacturing product information for further details.



Note: You can automate the Evaluate DC Demand, Confirm Suggestions, Create Local Purchase Order, Create Distribution Orders and Run Central Supply Plan steps by using the Network Run option. It performs the tasks of the DRP cycle in a one step batch job.

DRP Run Processing Options

In each of the DRP run options there are a number of ways you can select the items for replanning.

There are three distinct DRP run types:

1 - Full Regeneration

This replans all DRP items for the selected network or centre.

2 - Net Change

Net Change selects a number of items for replanning on the basis of changes in the supply, demand, stock or replenishment factors since they were last planned. This is achieved using net change triggers.

The triggers are predefined and use a set of reason codes.

A net change reason is a type of business transaction that potentially affects the supply, demand, and stock or replenishment parameters of a particular item.

For instance, if you raise a purchase order for replenishment of item B005 at stockroom H1, and stockroom H1 is attached to a centre or DC in DRP, and item B001 is defined as an item at that centre or DC, then a net change trigger is written for that particular location, item and reason code combination, (provided that this trigger has not already been set).

When you review net change triggers for a centre or DC before submitting a net change planning run, the number of triggers set for each reason code is displayed. Use this information to select whether you process some or all of the items that have set triggers under any of the reason codes.



Note: When a particular item is replanned at a particular DRP location, all net change triggers are deleted for that location/item combination. This is irrespective of the DRP run type chosen for processing.

3 - Selective Processing

This selects a subset of items for replanning on the basis of the selection of ranges of DRP items, planners, minor item groups, Inventory cost or usage elements, or preferred suppliers.

You can make these selections before submitting any of the DRP planning runs, that is, DC, centre or network.

An item will only be replanned at a particular centre or DC under the following conditions:

- It is within the range of items selected. And
- the DRP planner assigned to the item is within the range of DRP planners selected. And
- the Inventory minor item group to which the item belongs is within the range of Inventory minor item groups selected. And

- the Inventory cost or usage element calculated for that item is within the range of cost or usage elements selected. And
- the preferred supplier defined on the Inventory item/stockroom details is within the range of preferred suppliers selected.

Evaluate DC Demand



1/DRP

Use Evaluate DC Demand to assess the supply and demand status for items handled at the DCs within a selected network.

DRP produces a separate schedule for each DC, with supply and demand quantities, and suggested actions, for each item.

Evaluate DC Demand Screen



Select Evaluate DC Demand.

You use this screen to select the network that you want to evaluate DC demand for.

DR025	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99
Evaluate DC Demand			15:51:22
Enter Network Code...?.. __			
F3=Exit F4=Prompt			

Fields:

Enter Network Code

Enter a network code.



Press **Enter** to display the DC Run Selection Screen.



You use this screen to enter the criteria for a DRP processing run and submit the run.

```

DR002                Z1 - UK Demonstration Company                USER GBJBANB4                28/12/99
                                                                15:54:01

DRP DC Run Selection

      Network..... N1    UK Supply Network

      DRP run type..... 1    1=Full regeneration
                              2=Net change
                              3=Selective

```

```

Enter:  Current date..... 281299
        Overdue days..... 7
        Time fence days..... 7
        Calculate safety stock.... 1          (0=No, 1=Yes)
        Safety stock cover weeks.. 1
                                      Days... 0
        End date..... 311299
        Include forecasts..... 3          (1=Sales, 2=Stock building, 3=Both,
                                                0=Neither, Blank=As per item)

```

```

F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions  F19=Print last run details

```

Fields:

DRP Run Type

Enter the type of DRP run you want to generate:

- 1 - Full regeneration. This replans all items.
- 2 - Net change. This replans a subset of items on the basis of changes in the supply, demand, stock or replenishment parameters of items. Select **F14=Review Specification** to select the triggers you want to use.
- 3 - Selective. This replans a subset of items on the basis of a selection of ranges of items, planners, minor item groups, Inventory cost or usage elements and preferred suppliers. Select **F14=Review Specification** to enter the ranges.

Current Date

The date defaults to the current date. DRP uses this in conjunction with Overdue Days to establish the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Specify the number of days prior to the current date within which the module still includes outstanding supply and demand orders (excluding any forecasts).

Time Fence Days

Specify the number of days, forward from the current date of the DRP run, during which the plan remains frozen. DRP sets any supply suggestions required within this period, for action on the first working day after the time fence. If this is blank or zero, DRP calculates the time fence at item level (defined within Distribution Item Master), based on lead times.

Calculate Safety Stock

Enter one of the following:

0 - To only consider fixed safety stocks, as defined on the Distribution Item Master.

1 - To calculate safety stock cover for DRP items based on forecasted demand.

Safety Stock Cover Weeks and Days

Specify the number of weeks and days safety cover to use, as a blanket value for all items in this run. DRP calculates this from forecast demand for each item; you must therefore enter sales forecasts for all items requiring safety stock cover.

If this field is blank or zero and you require safety stock calculations, the number of weeks or days safety cover defaults to that entered on the Distribution Item Master.

End Date

Specify the last date for the planning run to consider. The field defaults to the end date of the previous run.

Include Forecasts

Enter the type of forecasts for the planning run to consider:

0 or blank - To exclude all forecasts and only consider the actual demand. DRP considers each item separately, with forecasts included or excluded on the basis of the Distribution Item Master and DRP Forecast field entry.

1 - To include sales forecast only.

2 - To include stock level forecasts only.

3 - To include both sales and stock level forecasts.

Functions:

F14=Review Specification

Use this function to enter further net change or selective processing details.

F16=Restrict Extractions

Use this function to exclude certain purchase orders.

F19=Print Last Run Details

Use this function to print the report of the last run.



Select **F8=Submit**. This validates all details and submits the regeneration plan batch job.

DC Run Net Change Trigger Selection Window



To display this window set the DRP Run Type to 2 on the DC Run Selection Screen, and select **F14=Review Specification**.

Use this window to maintain the net change selections for the current run. Each time you press **Enter**, the next DC in the network is displayed.

```

DR002                Z1 - UK Demonstration Company        USER GBJBANB4    28/12/99
                                                           15:55:55
DRP DC Run Selection

Network..... N1 UK Supply Network
Net Change Trigger Selection
DC..... D1 Northern Regional DC
Sel Trigger Description      Unprocessed Quantity to
Reason                      Triggers      Process
01 Forecast vs Actual Comparison.      0      0
02 Forecast Generation.                0      0
03 Forecast Maintenance.                0      0
04 Distribution Item Master.            4      0
05 Unplanned Inventory Transactions.    1      0
06 Requisition Maintenance.            0      0
07 Unplanned Issue or Receipt.          0      0
08 Purchase Order Maintenance.         0      0
09 Distribution Order Maintenance.      0      0
1=Select All  2=Select with Limit
F3=Exit  F18=Select All
  
```

Fields:

Sel

Enter one of the following:

- 1 - To select all triggers to process for this reason code.
- 2 - To select a particular quantity of triggers to process for this reason code.

Quantity To Process

Enter the number of unprocessed triggers to process for this reason code. If you want to process all triggers, do not enter a value in this field

Functions:

F18=Select All

Use this function to select all unprocessed triggers for all reason codes.



Press **Enter** to return to the DC Run Selection Screen.

DC Run Selection Criteria Window



To display this window, set the DRP Run Type to 3 and select **F14=Review Specification** on the DC Run Selection Screen.

You use this window to enter the details you want to be included in a selective processing run. The selections for the last selective processing run for the network display. You can enter selection details for each DC in the selected network. Each time you press **Enter**, the next DC in the network displays.

Item.....?..	to	
Planner.....?..	to	
Item Group.....?..	to	
Value/Usage Class.....	to	
Preferred Supplier.?..	to	

F4=Prompt F12=Previous

Fields:

You do not have to enter information in all of the fields, just the ranges that you want to include in the DC run.

Leave the From and To fields blank to select all items.

If you enter a From value and leave the To field blank, then the To field defaults to the From field.

If you enter a To value, you must enter a From value.

The To field must not be less than the From field.

Item

Enter a range of items to be replanned.

Planner

Enter a range of DRP planners.

Item Group

Enter a range of Inventory minor item groups.

Value/Usage Class

Enter a range of Inventory values or usage classes.

Preferred Supplier

Enter a range of preferred suppliers. You define preferred suppliers in Stockroom Details in Inventory Management.)



Press **Enter** to return to the DRP DC Run Selection Screen.

DC Run Restrict Order Extractions For Run Window



To display this window, select **F16=Restrict Extractions** on the DC Run Selection Screen.

Use this window to select the purchase orders to extract for the DRP processing run. This improves processing efficiency by restricting unnecessary data extraction.

DR002 Z1 - UK Demonstration Company USER GBJBANB4 28/12/99
15:59:47

DRP DC Run Selection

Network.. Restrict Order Extractions for Run

DRP run t Exclude Unconfirmed Quantities
on Scheduled Purchase Orders..... 0 (1=Yes, 0=No)

Exclude Confirmed Purchase Orders
(Outstanding, GI, Inspection).... @ (1=Yes, 0=No)

Enter: Current date.. F12=Previous

Overdue days..... 7

Time fence days..... 7

Calculate safety stock.... 1 (0=No, 1=Yes)

Safety stock cover weeks.. 1

Days... 0

End date..... 311299

Include forecasts..... 3 (1=Sales, 2=Stock building, 3=Both,
0=Neither, Blank=As per item)

F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details

Fields:

Exclude Unconfirmed Quantities On Scheduled Purchase Orders

Enter one of the following:

0 - To include all scheduled purchase order quantities whether confirmed or not. DRP assigns the unscheduled order quantities to the last planning period in the DRP run.

1 - To exclude unconfirmed order quantities from scheduled orders.

Exclude Confirmed Purchase Orders (Outstanding, GI, Inspection)

This is concerned with purchase orders not yet accepted into stock. Enter one of the following:

0 - To include all purchase order quantities for processing.

1 - To exclude all purchase orders from processing. This is particularly useful where there is no local purchasing at the DC.



Press **Enter** to update exclusion criteria.

Run DRP For Centre



2/DRP

You use this function to assess the supply and demand at the selected supply centre, and to produce a central supply plan.

The supply plan may contain suggested purchase orders, amendments to existing orders, or both.

Run DRP For Centre Screen



Select Run DRP For Centre.

You use this screen to select the supply centre to evaluate.

DR029	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
Run DRP for Centre		10:53:15	
Enter Centre Code...?... █			
F3=Exit F4=Prompt			

Fields:

Enter Centre Code

Enter the code of a centre defined to at least one network.



Press **Enter** to continue.

Centre Run Selection Screen



To display this screen, enter a centre code and press **Enter** on the Run DRP For Centre Screen,

You use this screen to specify the criteria for, and submit, a DRP processing run.

```

DR002          Z1 - UK Demonstration Company      USER GBJBANB4  10/03/98
                                                    10:53:44

DRP Centre Run Selection

      Centre..... C1  AS

      DRP run type..... 1  1=Full regeneration
                           2=Net change
                           3=Selective

-----

Enter:  Current date..... 100398
        Overdue days..... 10
        Time fence days..... 5
        Calculate safety stock... 1      (0=No, 1=Yes)
        Safety stock cover weeks.. 25
        Days... 0
        End date..... 280398
        Include forecasts..... -      (1=Sales, 2=Stock building, 3=Both,
                                         0=Neither, Blank=As per item)

-----
F3=Exit F5=Refresh F8=Submit F12=Previous F14=Review specification
F16=Restrict extractions F19=Print last run details
  
```

Fields:

DRP Run Type

Enter the type of DRP run you want to process:

1 - Full Regeneration. This replans all items.

2 - Net Change. This replans a subset of items on the basis of changes in the supply, demand, stock or replenishment parameters, since you last planned them. To select which triggers you want to process, select **F14=Review Specification**.

3 - Selective. This replans specified ranges of items, DRP planners, minor item groups, cost or usage elements, or preferred suppliers. To enter these ranges, select **F14=Review Specification**.

Current Date

Enter the current date. DRP uses this in conjunction with overdue days to calculate the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Enter the number of days prior to the current date within which the module still includes outstanding supply and demand orders (excluding any forecasts).

Time Fence Days

Enter the number of days, forward from the date of the DRP run, during which the plan remains frozen. DRP actions any supply suggestions within this period on the first working day after the time fence. If this is blank or zero, DRP calculates time fences at item level which are defined in the Distribution Item Master.

Calculate Safety Stock

Enter one of the following:

0 - To only consider the fixed safety stocks defined within Distribution Item Master.

1 - To calculate safety stock cover for DRP items based on forecasted demand.

Safety Stock Cover Weeks and Days

Enter the number of weeks and days safety stock cover required as a blanket value applicable to all items in this run. DRP calculates this from the sales forecast for each item; you must therefore enter sales forecasts for all items requiring safety stock cover.

If the safety weeks and days cover for this run is blank or zero, the number of weeks and days cover defaults to that entered at Distribution Item Master level.

End Date

Specify the last date the planning run considers. This defaults to the end date of the previous run.

Include Forecasts

Enter one of the following:

0 or blank - To exclude all forecasts. Only consider actual demand. DRP considers each item separately, with forecasts included or excluded on the basis of specification in Distribution Item Master.

1 - To include sales forecasts only.

2 - To include stock level forecasts only.

3 - To include both sales and stock level forecasts.

Functions:

F14=Review Specification

This will display the Run Net Change Trigger Selection Window or the Selective DC Run Criteria Window depending on what you entered in the DRP Run Type field.

F16=Restrict Extractions

This will display the Restrict Order Extractions For Run Window. You can use this window to exclude certain purchase orders from the DRP run.

F19=Print Last Run Details

Use this function to print a report of the last run.



Select **F8=Submit**, to validate all information and submit the regeneration plan batch job.

Network Run



3/DRP

You use this function to access the supply and demand for the whole of the selected network within a single run.

The Network Run will carry out the following automated processes:

- Evaluate DC Demand - full regeneration, net change or selective.
- Confirm supply suggestions.
- Create local purchase orders.
- Create distribution orders.
- Run a central supply plan - full regeneration only.

This removes the user intervention stage of amending suggestions and creating orders (via Requisitioning) for the DCs.

The automated run is particularly useful where supply suggestions are unlikely to require many amendments. You can assess the whole network with a single overnight run. You can review the resulting DC and centre schedules using schedule enquiries or reports.



Note: You can make any amendments to the generated supply orders by maintaining the purchase order (via Purchase Management) or distribution order (via the Distribution Order Amend option).

This procedure generates the following reports:

- The New Requisitions Report.
- The Requisitions Deleted Report.

Network Run Screen



Select Network Run.

You use this screen to select the network to evaluate.

DR042	Z1 - UK Demonstration Company	User GBJBANB4	28/12/99 16:03:26
Network Run			
Enter Network Code...?.. _			
This Run will do the following :-			
- Evaluate DC Demand, allowing Full Regeneration, Net Change or Selective Run			
- Create Purchase Orders			
- Create Distribution Orders			
- Run Full Regeneration for Centre			
F3=Exit F4=Prompt			

Fields:

Enter Network Code

Enter a network code, as defined to DRP via Network Maintenance.



Press **Enter** to display the Network Run
Selection Screen.

Network Run Selection Screen



To display this screen, enter a network code and press **Enter** on the Network Run screen.

You use this screen to specify the criteria for and submit a DRP processing run.

```

DR002                Z1 - UK Demonstration Company          USER GBJBANB4    28/12/99
                                                           16:07:03

DRP Network Run Selection

      Network..... N1  UK Supply Network

      DRP run type..... 1      1=Full regeneration
                               2=Net change
                               3=Selective

-----
Enter:  Current date..... 281299
        Overdue days..... 7
        Time fence days..... 7
        Calculate safety stock.... 1      (0=No, 1=Yes)
        Safety stock cover weeks.. 1
        Days... 0
        End date..... 311299
        Include forecasts..... 3      (1=Sales, 2=Stock building, 3=Both,
                                         0=Neither, Blank=As per item)

-----
F3=Exit  F5=Refresh  F8=Submit  F12=Previous  F14=Review specification
F16=Restrict extractions  F19=Print last run details
  
```

Fields:

DRP Run Type

Enter the type of DRP run to process:

1 - Full Regeneration. Replans all items.

2 - Net Change. Replans a subset of items on the basis of changes in the supply, demand, stock or replenishment parameters, since you last planned them. To select which triggers you want to process, select **F14=Review Specification**.

3 - Selective. This replans items within specified ranges of items, DRP planners, minor item groups, cost or usage elements or preferred suppliers, or all of these. To enter these ranges, select **F14=Review Specification**.

Current Date

Enter the current date. DRP uses this with Overdue Days to calculate the start date for the DRP run as follows:

Start Date = Current Date - Overdue Days.

Overdue Days

Enter the number of days prior to the current date within which outstanding supplies are still valid.

Time Fence Days

Enter the number days, forward from the date of the DRP run the plan remains frozen. DRP sets any supply suggestions within this period for action on the first working day after the time fence. If this is blank or zero, DRP calculates the time fences at item level (as defined on the Distribution Item Master).

Calculate Safety Stock

Enter one of the following:

0 - To only consider the fixed safety stocks defined within Distribution Item Master Maintenance.

1 - To calculate safety stock cover for DRP items based on forecasted demand.

Safety Stock Cover Weeks & Days

Enter the number of weeks and days safety stock cover required as a blanket value applicable to all items in this run. DRP calculates this from the sales forecast for each item. You must therefore enter sales forecasts for all items requiring safety stock cover.

If the safety weeks and days cover for this run is blank or zero the number of weeks and days cover defaults to that entered at DRP Distribution Item Master level.

End Date

Specify the last date the planning run considers. This defaults to the end date of the previous run.

Include Forecasts

Enter one of the following:

0 or Blank - To exclude all forecasts and only consider actual demand. DRP considers each item separately, with forecasts included or excluded on the basis of the entries on the Distribution Item Master.

1 - To include sales forecast only.

2 - To include stock level forecasts only.

3 - To include both sales and stock level forecasts.

Functions:

F14=Review Specification

This will display the Run Net Change Trigger Selection Window or the DC Run Selection Criteria Window depending on what you entered in the DRP Run Type field.

F16=Restrict Extractions

This displays the Restrict Order Extractions For Run Window. You can use this window to exclude certain purchase orders from the DRP run.

F19=Print Last Run Details

Use this function to print a report of the last run details.



Select **F8=Update** to validate the entries and submit the regeneration batch job.

Distribution Order Entry



4/DRP
1/WTB

Distribution orders are internal orders placed on supply centres in a network to satisfy demand for items at the DCs, that is, a movement of stock between two stockrooms in a single company. They are basically a formal request for a transfer of stock.

You must set up a dummy customer in the Customer Maintenance option in Sales Order Processing. You then need to assign each DRP stockroom to a dummy customer, known as the internal customer, using the DRP Customer option (or, if using World Trade, the World Trade Stockroom option). The distribution order can then be processed through Sales Order Processing, as a normal sales order would be, except the customer will be a dummy customer - a DRP stockroom.

Distribution orders are created in different ways, they can be created automatically, for instance by the network planning run, or you can use the Distribution Order Entry option to enter the orders.

You create the distribution order with a From and a To stockroom, and the software allocates a sales order number. DRP uses the order number and the internal customer associated with the To stockroom to process the order through the allocation, pick and confirm despatch stages. The dummy address can be a particular stockroom to supply DCs, or you can override the delivery address each time you enter a distribution order.

After confirm despatch, the confirm receipt procedure receives the stock into the To stockroom and updates the stock balance. Sales Order Processing identifies the order as a distribution order and so does not generate an invoice.

Therefore, for most of its processing cycle, you manage a distribution order using functions in the Sales Order Processing or Warehousing modules.

If the From and To stockrooms are in different EC countries, confirm despatch creates World Trade movements. DRP uses these movements to produce Intrastat and ESL reports, and to post the acquisition VAT due on receipt of the goods.



Note: DRP takes into account manually entered distribution orders in the distribution planning runs.

Catchweight

The Distribution Order Entry options calculate secondary values and UoMs. You can enquire upon orders for catchweight items using the Distribution Enquiry options.

About Transfer Order Control In Production

If you are using the Production applications, distribution orders are known as transfer orders.

Transfer Orders (or Inter-Plant Supply Requests) are requests to move stock between production units. You can only have transfer order control if you are using one, two or all three of multi-plant, multi-sourcing or cellular network.

Transfer orders authorise the movement of stock from one planning unit to another, in order to satisfy a demand in the requesting planning unit. The planning unit receiving the transfer order will process the transfer request as a source of demand.

You can create transfer orders in two ways:

- Manually.
- Via MPS, which recommends transfer orders that you then confirm using the Requisitions module. Multi-sourcing must be active for the MPS run to recommend transfer orders.

You can set the maximum number of lines allowed for each transfer order. You do this as part of Company Profile Maintenance.

The transfer lead time is obtained from the item's To Stockroom lead time (defined in weeks). You can override the lead time at transfer order line level.

Distribution Order Entry Selection Screen



Select Distribution Order Entry.

You use this screen to select the despatching and receiving distribution stockrooms, and to specify the required despatch date for the distribution order. If you create a number of distribution orders sequentially, the previously created order details are displayed.

DR300	Z1 - UK Demonstration Company	User GBJBANB4	28/12/99 16:09:30
Distribution Order Entry			
From Stockroom.....?.. __			
To Stockroom.....?.. __			
Despatch due date..... <u>28/12/99</u>			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter the stockroom to source the distribution order.



Tip: The From stockroom must be defined as a depot in Sales Order Processing.

To Stockroom

Enter the stockroom to receive the distribution order. This stockroom must have an internal customer code attached to it in Sales Order Processing.

Despatch Due Date

Enter the date on which the distribution order is due for despatch.



Press **Enter** to display the Delivery Address Override Screen.

Distribution Order Entry Delivery Address Override Screen



To display this screen, enter the required details and press **Enter** on the Distribution Entry Selection Screen.

You can use this screen to override the delivery name and address that appear on the despatch note.

DR300	Z1 - UK Demonstration Company	User GJBANB4	28/12/99 16:10:59
Distribution Order Entry			
From Stockroom..... FG Finished Goods			
To Stockroom..... AS A Sales Stockroom			
Despatch due date..... 28/12/99			
Internal Customer..... ACDUMMY 001			
Delivery name and address:			
<u>DRP TRANSFER DFROM AC TO A1</u>			
<u>INTERNAL STOCK TRANSFER ORDERS ONLY</u>			

F3=Exit F12=Previous F21=Text			

Fields:

Delivery Name And Address

Enter the delivery name and address to appear on the pick and despatch notes for the distribution order. This defaults to the delivery address defined to the internal customer for the receiving stockroom.



Press **Enter** to display the Distribution Order Line Entry Screen.

Distribution Order Entry Lines Screen



To display this screen, press **Enter** on the Order Entry Delivery Address Overrides Screen.

You use this screen to enter distribution order lines. If the despatch date is within the time fence and sufficient stock exists in Inventory, DRP automatically allocates the line. Otherwise the quantity shows in reverse image as unallocated.

DR320	Z1 - UK Demonstration Company	USER GBJBANB4	28/12/99
			16:20:03
Distribution Order Entry			
From Stockroom.... 01 Central Stockroom		Due Date.. 28/12/99	
To Stockroom..... 02 Northern RDC Stockroom			
Item/Description	Despatch Due	Receipt Due	Quantity UOM
- 5002	28/12/99	28/12/99	10.000 BX
Suncream Factor 8 225ml			
1=Amend 2=Text 4=Delete 6=Avail 8=Force Alloc 9=Dealloc			
Item?... _____	Qty.. _____	.000	Dsp. 28/12/99 Rcpt. 0/00/00
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous F15=Restart			

Fields:

Select (Untitled)

Enter one of the following:

- 1 - To amend the order line details.
- 2 - To enter internal text for the order line.
- 3 - To enter external text for the order line.
- 4 - To delete the line from the order. This reverses any existing allocations.
- 6 - To enquire on the current stock availability for the item at the From stockroom and the current supply and demand situation.
- 8 - To fully allocate a partially or wholly unallocated order line. Allocation takes place regardless of the available stock quantity, allocation priority or allocation time fence.
- 9 - To deallocate a fully or partially allocated order line.

To add a new order line or amend an existing order line, enter the following:

Item

Enter an item. The item must be defined to both the From and To stockrooms for the order.

Qty

Quantity. Enter the quantity required.

Dsp

Despatch. Enter the despatch date. This defaults to the due date from the previous screen.

Rcpt

Receipt. Enter the receipt date. If you leave this blank, DRP calculates the receipt date by the item lead time.



Note: You do not need to enter both despatch and receipt dates. If you enter one, DRP calculates the other based on the lead time at the To stockroom.

Functions:

F11=Delete

Use this function to delete the whole order.

F15=Restart

Use this function to abandon all changes made since the last update and return to the Distribution Order Entry Selection Screen.



Press **Enter** to validate the order line details.



Select **F8=Update** to update the distribution order details and display distribution order numbers.

Distribution Order Amendment

1...
2...

5/DRP
2/WTB

You use this function to amend an existing distribution order. You can amend the order header or order line details. If you do not know the order number, you can enquire on all distribution orders by internal customer.

Distribution Order Amendment Selection Screen



Select Distribution Order Amend.

You use this screen to select the distribution order you want to amend.

DR310	Z1 - UK Demonstration Company	User GBJBANB4	28/12/99 16:23:53
Distribution Order Amendment			
Order Number..... _____			
Amend header or lines... _ (1=Header, 2=Lines).			
If Order number is not known, enter an Internal Customer to enquire on Orders by Customer.			
Internal Customer....?.. _____			
F3=Exit F4=Prompt			

Fields:

Order Number

Enter an existing distribution order number.

Amend Header Or Lines

Enter one of the following:

1 - To amend header level details. This displays the Distribution Order Delivery Address Screen. For more details on this screen, refer to the Distribution Order Entry section.

2 - To amend line level details. This displays the Distribution Order Lines Screen. For more details on how to use this screen, please refer to the Distribution Order Entry section.

Internal Customer

If you do not know the correct order number, you can enter an internal customer to list all the distribution orders for that customer.



Press **Enter** to continue.

-
-
-
-
-

Chapter 4 Enquiries

Enquiries Introduction

There is three categories of DRP enquiry:

- Planning details.
- Static information.
- Status information.

The enquiries in each group are:

- DC and Centre Schedule Enquiries - planning.
- Distribution Item Master Enquiry - static information.
- Shipments In transit Enquiry - status.

View Schedule For DC Enquiry



1/DRE

You can use this enquiry to view the time phased plan, by item, created when you last evaluated the DC demand within a supply network.

The enquiry also provides details of actions suggested by DRP for the item.

DRP DC Schedule Enquiry Selection Screen



Select View Schedule For DC.

You use this screen to select the DC for which you want to display the schedule.

```
DR036          Z1 - UK Demonstration Company    USER GBJBANB4    10/03/98
DRP DC Schedule Enquiry                        11:09:16

Enter DC.....?... █

F3=Exit  F4=Prompt
```

Fields:

Enter DC

Enter a DC that has periods and stockrooms defined, and is assigned to least one network.



Press **Enter** to display the Schedule Enquiry
Detail Selection Screen.

DRP Schedule Enquiry Detail Selection Screen



To display this screen, enter a DC or centre code and press **Enter** on the DRP DC Schedule Enquiry Selection Screen.

You use this screen to define the enquiry, by item, planner or a range of plan dates. You can only select one criterion for a particular enquiry.

```
DR080          Z1 - UK Demonstration Company      USER GBJBANB4  10/03/98
DRP DC Schedule Enquiry                          11:09:40

DC..... D1 - 1

Optionally select one of the following:

  Item.....?..
OR
  Planner.....?..
OR
  Date last planned from... to ...

F3=Exit  F4=Prompt  F12=Previous
```

Fields:

Enter one of the following:

Item

Specify any item code. This does not need to be a valid item because the enquiry starts from the first item found after the value entered.

Planner

Specify any DRP planner code. This does not need to be a valid planner because the enquiry starts from the first item found after the value entered.

Date Last Planned From and To

Specify a range of calendar dates. The enquiry begins at the first item with a last planned date on or after the from date.



Note: Leave all the selection fields blank to begin the enquiry at the first valid item.



Press **Enter** to display the Schedule Summary Enquiry Screen.

Schedule Enquiry Summary Screen



To display this screen, press **Enter** on the
Schedule Enquiry Detail Selection Screen.

This displays the supply, demand and requirement quantities for each selected item or time period. This gives an overall picture of the supply and demand pattern and indicates where shortfalls of supply will occur.

The dates displayed are the start dates for each period. All figures are in terms of quantity rather than value. The overdue column includes orders with outstanding demand or supply. This does not include forecasts.

The system calculates the actual available stock as:

Previous available+Supply-Demand.

The net requirement is the difference between supply and demand:

Demand+stock level forecast+safety stock-previous planned available-supply.

If the result is positive, there is a shortfall. If there is sufficient or excess stock, the output is blank.

The system calculates the planned available stock as:

Previous planned available+plan orders-demand.

PR080	Z1 - UK Demonstration Company	USER GBJBANB4	10/03/98
			11:10:13
Enquiry - Summary DC..... D1 Last Run Date: Start.. 14/02/98 End.. 28/03/98			
Item..... 5009	Shampoo/conditioner 2 in 1 300ml		
Start.. 8/02/98	End.. 28/03/98	Time fence.. 23/02/98	
Planner..... JFB	Minor item group.. 6	Last planned	18/02/98
Purchase UoM. CA	Physical stk. 788.000	Fixed qty...	
Order policy. B	Safety stock. 125.000	Min. qty....	
Item type.... 3	Lead time.... days.	Max. qty....	
Supplier.....	Value/usage class.. 1	Multiples...	
Enquiry UoM.. BX			
	<u>OVERDUE</u>	<u>240298</u>	<u>260298</u>
Actual....			
Forecast...			
Dist.Order.			
Demand....			
Available..	788	788	788
Supply....			
Net Reqment			
Plan orders			
Plan avail.	788	788	788
			788 +
F3=Exit F12=Previous F17=Detail F19=Next item			



Tip: Page up and down to view all the period
summaries.

Functions:

F17=Detail

Use this function to display the Item Supply And Demand Details Screen.

F19=Next Item

Use this function to display the next item.

F20= Next Planner

Use this function to display the first item for the next planner.



Note: This is only available if you sequence the enquiry by planner.



Select **F3=Exit**.

Item Supply and Demand Details Screen



To display this screen, select **F17=Detail** on the Schedule Enquiry Summary Screen.

This displays details of supply and demand for a specific item. Details include the required date, order number, quantity and status of both the supply and the demand. It also displays the action DRP suggests you should take on this supply line.

```

PR080                Z1 - GB Demonstration Company          USER GBJBA1MS    13/03/98
                                                              11:33:59
Enquiry - Detail      DC..... D1          Start.. 15/01/97  End.. 10/02/97
                                                              Time fence.. 10/01/97
Item.... LTS/N/001          latest costed item 1

<---- Demand -----> <----- Supply ----->
Date Order  SR Quantity  St Order  Quantity  St Action  Available
13MAY                               1852  SC                               20
20MAY                               4667  SC                               20
27MAY                               4759  SC                               20
3JUN                                4852  SC                               20
10JUN                                315  SC                               20
17JUN                                278  SC                               20
24JUN                                185  SC                               20
1JUL                                 93  SC                               20
3JAN                                5000  SC                               20
10JAN                                4990  SD                               5010
                                0007707

F3=Exit  F12=Previous  F17=Summary  F18=Header details  F19=Next item
F20=Next Planner  F22=Detail line

```

The demand status can be:

SO - Sales order line

SX - Sales order line excluded

DO - Distribution order line

DX - Distribution order line excluded

FC - Sales forecast

FX - Sales forecast excluded.



Note: This excludes order lines if the forecast is greater than the demand and vice-versa. There are no exclusions if you use consumption of forecast.

The supply status can be:

SP - Suggested purchase order line

CP - Confirmed purchase order line

SD - Suggested distribution order line

DO - Distribution order line

TI - In transit

GI - Received at goods inwards

IS - Received at inspection

UP - Unconfirmed purchase order line

FS - Stock level forecast.

The action suggested by DRP can be:

SP - Suggested purchase order line

SD - Suggested distribution order line

RI - Reschedule in (Expedite)

RO - Reschedule out (Defer)

CQ - Change quantity

CA - Cancel order line

RICQ - Reschedule in and change quantity

ROCQ - Reschedule out and change quantity.



*Note: To display the dates or quantities, or both, associated with these actions, select **F22=Detail Line**.*



Tip: Page up and down to move through the supply and demand details.

Functions:

F17=Summary

Use this function to return to the Schedule Enquiry Summary Screen.

F18=Header Details

Use this function to display the Header Details Window.

F19=Next Item

Use this function to display the next item, on the Schedule Enquiry Summary Screen.

F20=Next Planner

Use this function to display the first item for the next planner, on the Schedule Enquiry Summary Screen.



Note: This is only available if you sequence the enquiry by planner.

F22=Detail Line

Use this function to display the action details for this item.



Select **F3=Exit** to leave the enquiry.

Header Details Window



To display this window, select **F18=Header Details** on the Item Supply and Demand Details8 Screen.

Use this window to view the basic information about the item. These details include the planner, unit of measure, order policy, supplier, stock levels, lead time, and order quantities.

PR000		Z1 - GB Demonstration Company		USER GBJBA1MS		13/03/98	
						11:33:59	
Enquiry - Detail		DC..... D1		Start.. 15/01/97		End.. 10/02/97	
						Time fence.. 10/01/97	
Item.... LTS/N/001		latest costed item 1					
<---- Demand ----->		<----- Supply ----->					
Date	Order	SR	Quantity	St	Order	Quantity	St Action
13MAY						1852	SC
						Available	
						20	
Header Details							
Planner..... JFB		Item group B		Last planned...		3/01/97	
Purchase UoM EA		Phys. stk.		20.000		Fixed qty..	
						10.000	
Order policy H		Safety stk		10.000		Min. qty...	
						10.000	
Item type...		Lead time.		14 Days.		Max. qty...	
						10.000	
Supplier....		Value/usage class.. 9		Multiples..		10.000	
F12=Previous							
3JAN				5000		SC	
						20	
10JAN		0007707		4990		SD	
						5010	
F3=Exit F12=Previous F17=Summary F18=Header details F19=Next item							
F20=Next Planner F22=Detail line							



Select **F12=Previous** to return to the Item Supply and Demand Details Screen.

Schedule Enquiry Detail Line Screen



To display this screen, select **F22=Detail Line** on the Schedule Enquiry Detail Screen.

This screen displays the actions suggested by DRP. These include the start date for suggested orders, new due dates for rescheduled orders, and new quantity.



Tip: Page up and down to move through the action details.

DR080	Z1 - Demonstration Company		USER SP1		23/09/94 12:00:39				
Inquiry - Detail		DC..... D1	Start.. 7/09/94		End.. 31/12/94				
			Time fence.. 14/09/94						
Item... 5009		Shampoo/conditioner 2 in 1 300ml							
<---- Demand -----> <----- Supply ----->									
Date	Order	SR	Quantity	St	Order	Quantity	St	Process	Available
14SEP						21		SC	788
94									
15SEP	0000099		800	SO	0000046	158		SP	146
94								15/09/94	
19SEP			11	FC		32		SC	146
94									
19SEP					0000047	11		SP	157
94								19/09/94	
22SEP	0000099		200	SO		200		SP	157
94								22/09/94	
26SEP			11	FC		32		SC	157
94									+
F3=Exit F12=Previous F17=Summary F18=Header details F19=Next item F22=Detail line									

Functions:

F17=Summary

Use this function to return to the Schedule Enquiry Summary Screen.

F18=Header Details

Use this function to display the Header Details Window.

F19=Next Item

Use this function to display the next item, on the Schedule Enquiry Summary Screen.

F20=Next Planner

Use this function to display the first item for the next planner.



Note: This is only available if you sequence the enquiry by planner.

F22=Detail Line

Use this function to display the action details for this item.



Press **Enter** to return to the Supply and Demand
Details Screen.

View Schedule For Centre Enquiry



2/DRE

You use this enquiry to view the time phased plan, per item, created when you last evaluated the centre within DRP.

This enquiry also provides details of actions suggested by DRP for the item.

DRP Centre Schedule Enquiry Selection Screen



Select View Schedule For Centre.

You use this screen to specify the centre you want to view the schedule for.

```
DR037          Z1 - UK Demonstration Company    USER GBJBANB4    10/03/98
DRP Centre Schedule Enquiry                    11:36:56

Enter Centre.....?... L

F3=Exit  F4=Prompt
```

Fields:

Enter Centre

Enter a centre code that has periods and stockrooms defined and is defined as a centre within at least one network.



Press **Enter** to display the **DRP Centre Schedule Enquiry Item Planner Selection Screen**. For further information, see the **View Schedule for DC Enquiry Item/Planner Selection Screen**, as this works in exactly the same way.

Distribution Item Master Enquiry



3/DRE

You use this enquiry to view the fixed DRP details for a selected item, held on the distribution item master, for a centre or DC.

These are the parameters that control how you plan the item and where to source from as a default.

Distribution Item Master Enquiry Selection Screen



Select Distribution Item Master.

You use this screen to enter the centre or DC and item for enquiry.

DR008	Z1 - GB Demonstration Company	USER GBJBA1MS	13/03/98 10:40:33
Distribution Item Master Enquiry			
Centre/DC.....?.. █			
Item.....?.. _____			
F3=Exit F4=Prompt F16=Inventory Item Search			

Fields:

Centre/DC

Enter a centre or DC with periods and stockrooms defined.

Item

Enter an item defined to the Inventory Management and DRP modules.

Functions:

F16= Inventory Item Search

Use this function to search on Inventory items.



Press **Enter** to display the Distribution Item Master Enquiry Item Details Screen.

Distribution Item Master Enquiry Item Details Screen



To display this screen, enter a centre or DC and item code and press **Enter** on the Distribution Item Master Enquiry Selection Screen.

This screen shows details of the Distribution Item Master Enquiry, such as supply source, planner, forecast details, order policy codes, order quantity details, stock levels, and stockrooms. You cannot change any of the information here, it is for enquiry only.

```

DR008          Z1 - GB Demonstration Company      USER GBJBA1MS    13/03/98
Distribution Item Master Enquiry                    10:40:57

Item..... 5002          Suncream Factor 8 225ml
Centre/DC..... C1          Birmingham Central Depot
                               Date Last Planned.... 7/03/97

Source of Supply... 1      (1=Local, 2=Central)
Planner..... SGM
DRP Forecast..... 3      (0=None, 1=Sales, 2=Stock, 3=Both)
Forecast Error Tolerance% Absolute... .00
Forecast Profile...
Order Policy..... B (A,B,D,G,H)  Min Order Qty..... .000
                               OR
Max Order Qty..... .000          Use Inventory Order Qty... 2
Fixed Order Qty.... .000          (1=Economic Order Qty., 2=Reorder Qty.)
Mult Order Qty..... .000
Safety Stock..... .000
Days Supply..... 0
Time fence days.... 0
Safety stock weeks.. 2
Safety stock days.. 3

Stockroom Details
Local Stockroom..... 01

F3=Exit  F12=Previous
  
```



Select **F3=Exit**.

Stock In Transit Enquiry



11/DRE

You use this enquiry to view distribution order lines in transit between two selected stockrooms.

Items in transit have been confirmed as despatched from the From stockroom, this could be in Sales Order Processing, Warehousing, or DRP, but have not yet been received at the To stockroom in Distribution Requirements Planning.

Shipments In Transit Enquiry Selection Screen



Select Stock In Transit.

Use this screen to select the distribution order lines that you want to enquire upon. You can select all distribution lines in transit between two stockrooms or display one specific distribution order.

IN270	Z1 - GB Demonstration Company	User: GBJBA1MS	13/03/98 10:41:45
Shipments In-Transit Enquiry			
Enter Stockrooms and/or specific Distribution Order number:			
From Stockroom.....?.. █			
To Stockroom.....?.. _			
Distribution Order Number... _____			
F3=Exit F4=Prompt			

Fields:

From Stockroom

Enter an Inventory stockroom defined as a Sales Order Processing depot and defined to a DC or centre within DRP.

To Stockroom

Enter an Inventory stockroom defined as a Sales Order Processing depot and defined to a DC or centre within DRP.

Distribution Order Number

You can enter a distribution order number, confirmed as despatched at the From stockroom and not confirmed as received at the To stockroom. This is optional. Leave blank to display all stock in transit between the two stockrooms you have specified.



Note: You can enter an order number without specifying From and To stockrooms.



Press **Enter** to display the Shipments InTransit Enquiry Order Line Details Screen.

Shipments In Transit Enquiry Order Line Details Screen



To display this screen, enter the required details on the Shipments In Transit Enquiry Screen, and press **Enter**.

This screen displays the distribution order line details. These details include:

- Originating and destination stockroom and DC or centres.
- Due date.
- Distribution order number and line number.
- Inventory item code.
- Local stockroom at the DC.
- Despatched quantity and unit of measure.
- Lot number, if the item is batch, lot or serial controlled.

IN270	Z1 - GB Demonstration Company	User GBJBA1MS	13/03/98			
Shipment In-Transit Enquiry		10:42:06				
From Stockroom... 01 Central Stockroom		From R1 Rob's DC1				
To Stockroom..... 02 Northern RDC Stockroom		To... R2 Rob's DC2				
Date	Order	Lin Item	SR	Quantity	UoM	Lot Number
17/09/97	A000218	1 SSMCD1	02	2.000	EA	
25/11/97	A000246	1 5001	02	1.000	EA	
30/01/98	A000267	1 5001	02	5.000	EA	
30/01/98	A000271	1 5001	02	10.000	EA	
30/01/98	A000273	1 5001	02	2.000	EA	
25/11/97	0004770	1 MARK/S/N	02	2.000	EA	
25/11/97	0004770	1 MARK/S/N	02	1.000	EA	
9/03/98	0005317	1 DANS-COMP-1	02	10.000	EA	
9/03/98	0005320	1 DANS-COMP-1	02	3.000	EA	
9/03/98	0005320	1 DANS-COMP-1	02	7.000	EA	
F3=Exit		F12=Previous				



Note: Where appropriate you can amend the stockroom, pack type, lot number and rotation date when you confirm receipt.



Tip: Page up and down to view more order lines.



Select **F3=Exit**.

-
-
-
-
-

Chapter 5

Reports

Introduction

You can enter selection and sequencing parameters before running any of the reports.

Standard reports print on standard listing paper with 132 print positions and 6 lines to the inch. The reports print the procedure or program number on the top left and the page number on the top right of the report.



Note: The Schedule and Valuation Reports both have 198 print positions.

As with the enquiries, you can group the reports into Planning, Static Information and Status.

Print Run Details Report



1/DRR

This report outputs the control details of the last processing run for a selected centre or network.

The output consists of run parameters and period details.

Frequency - For each network, and for each centre, this report is included automatically in a processing run. You can also request reprints.

Totals - None.

DRP Run Details Report Selection Screen



Select Print Run Details.

You use this screen to select the centre or network for the **DRP Run Details Report**.

```
DR003P          Z1 - GB Demonstration Company      USER GBJBA1MS   13/03/98
                                           10:42:57

DRP Run Details Report

      Enter Centre....?... █
      OR
      Enter Network....?... _

_____
F3=Exit  F4=Prompt  F8=Print run details report
```

Fields:

You can enter either a centre or a network:

Centre

Enter a centre code to print details of the last **DRP** run for this centre.

Network

Enter a network code to print details of the last **DRP** run for the network specified.



To print the report, select **F8=Print Run Details Report**.

Schedule Report



2/DRR

This report produces a time phased plan, or schedule, for controlling item stock levels within the selected centre or DC. You can select a range of dates and the level of detail required in your report.

It is a printed version of the details that you can view, per item, using the Schedule Enquiries.

Refer to the DC Schedule Enquiry section for a detailed content description.

Frequency – You can run this report as required.

New Page – A new page is used for each item, and, or planner.

Totals - For item.

Request Schedule Report Selection Screen



Select Schedule Report.

You use this screen to select the centre or DC to produce the Schedule Report for.

DR021P	Z1 - GB Demonstration Company	User GBJBA1MS	13/03/98
			10:43:26
Request Schedule Report			
Centre/DC.....?. _			
F3=Exit F4=Prompt			

Fields:

Centre/DC

Enter a DRP centre or DC.



Press **Enter** to continue.

Request Schedule Report Details Screen



To display this screen, enter a centre or DC on the Request Schedule Report Selection Screen, and press **Enter**.

You use this screen to select a range of plan dates and the level of detail you require for the report.

DR021P	Z1 - GB Demonstration Company	User GBJBAIMS	13/03/98
Request Schedule Report			10:43:40
Centre..... C1 Birmingham Central Depot			
Date last planned from: 27/11/97 to: 27/11/97			
Print Supply/Demand detail... 1 (0=No 1=Yes)			
Print Items with no details.. 0 (0=No 1=Yes)			
F3=Exit F8=Submit report F12=Previous F14=Additional selection			

Fields:

Date Last Planned From and To

Specify a range of plan dates to include in the report. Only items last planned within this range of dates appear on the report. This defaults to the date of the last planning run for the centre or DC.

Print Supply/Demand Detail

Enter one of the following:

0 - To display totals only.

1 - To include details of the supply and demand orders.

Print Items With No Details

Enter one of the following:

0 - To exclude the codes and description of items with no supply or demand details.

1 - To include codes with no supply or demand details.

Functions:

F14=Additional Selection

Use this function to maintain additional selection and sequencing criteria for the report, on the Enter Selection Criteria Window.



To submit the report to a batch job, select
F8=Submit.

Enter Selection Criteria Window



To display this window, select **F14=Additional Selection** on the Request Schedule Report Details Screen.
Or, On the Request Planner Action Report Details Screen, select **F14=Additional Selection**.

You use this window to specify additional select and sequencing information for the report.

Enter Selection Criteria				
DC..... C1 Birmingham Central Depot				Report
Item.....?..		to		Sequence
Planner.....?..		to		-
Item Group.....?..		to		-
Value/Usage Class.....		to		-
Preferred Supplier.?..		to		-

F4=Prompt F12=Previous

Fields:

Item

Enter a range of items to select for the report.

Planner

Enter a range of DRP planners. Only items defined to DRP planners within this range are included in the report.

Item Group

Enter a range of Inventory minor item groups. This only selects those items defined to Inventory minor items groups within this range.

Value/Usage Class

Enter a range of Inventory value or usage classes. This only selects those items with value or usage classes within this range.

Preferred Supplier

Enter a range of preferred suppliers. This only selects those items with preferred suppliers within this range.



Tip: You define preferred suppliers in the Item stockroom profile, within the Stockroom Detail option in Inventory Management.

Rules for Range Selection

Leave the From and To fields blank to select all items.

If you enter the From field and leave the To field blank, then the To field defaults to the From field.

If you enter a To field, you must enter a From field.

The To field must not be less than the From field.

Sequencing

Select the order in which the selection criteria are to appear on the report. You can select up to three sequencing criteria.

If you do not enter a sequence, the report sequences by item.



To confirm the selection and return to the previous screen, press **Enter**.

Planner Action Report



3/DRR

You use this report to print the suggested actions for the planner, resulting from processing runs for the selected centre or DC.

These actions include:

- Reorder suggestions.
- Order amendments - quantities or due dates, or both.
- Order cancellations.



Note: Orders are purchase orders for items supplied externally to the company, and distribution orders for items supplied by centres within the company.

Frequency – You can run this report as required.

New Page – A new page is used for each new item or planner.

Totals - None.

Request Planner Action Report Selection Screen



Select Planner Action Report.

You use this screen to specify the centre or DC you want the Planner Action Report to cover.

```
DR034P          Z1 - GB Demonstration Company      USER GBJBA1MS  13/03/98
                                     10:44:42
Request Planner Action Report

Centre/DC.....?.. █

F3=Exit  F4=Prompt
```

Fields:

Centre/DC

Enter a DRP centre or DC.



Press **Enter** to continue.

Request Planner Action Report Detail Screen



To display this screen, enter a centre or DC and press **Enter** on the Request Planner Action Report Selection Screen,

You use this screen to select a range of dates for planner actions and specify whether to include or exclude overdue orders.

DR034P	Z1 - GB Demonstration Company	USER GBJBAIMS	13/03/98
			10:45:02
Request Planner Action Report			
Centre..... C1 Birmingham Central Depot			
Planner Action start from: 27/11/97 to: 27/11/97			
Include overdue orders.... 1 (0=No, 1=Yes)			
F3=Exit F8=Submit report F12=Previous F14=Additional selection			

Fields:

Planner Process Starts From:

Specify a range of plan dates to include in the report. Only items last planned within this range of dates show on the report. This defaults to the date of the last planning run for the selected centre or DC.

Include Overdue Orders

Enter one of the following:

0 - To exclude all overdue orders.

1 - To include all overdue orders.

Functions:

F14= Additional Selection

Use this function to maintain additional selection and sequencing criteria for the report. More information on this function can be found in the Schedule Report section.



To submit the report, select **F8=Submit**.

Valuation Report



4/DRR

You use this report to produce a time phased costing for the plan produced for a selected centre or DC.

Frequency - As required.

New Page – A new page is used for each new supply source, new item or new planner.

Totals - For item, for centre or DC.

Request Valuation Report Selection Screen



Select Valuation Report.

You use this screen to specify the criteria for the Valuation Report.

DR023P	Z1 - GB Demonstration Company	User GBJBA1MS	13/03/98 10:45:52
Request Valuation Report			
Enter Centre/DC.....?...?.. _			

Supply source..... _	1=Locally purchased items only 2=Centrally supplied items only 3=All items		
Level of detail required..... _	1=Summary only 2=Full detail		
Costing method..... _	1=Standard cost 2=Latest cost		
Factor..... _	1=One thousands 2=Ten thousands 3=Hundred thousands 4=Millions		

F3=Exit F4=Prompt F8=Submit report			

Fields:

Enter Centre/DC

Enter a DRP centre or DC.

Supply Source

Enter one of the following:

- 1 - To include only those items not supplied by a DRP supply centre, that is, locally purchased items.
- 2 - To include only those items supplied from a DRP supply centre to the selected centre or DC, that is, centrally supplied items.
- 3 - To include both centrally supplied and locally purchased items.

Level Of Detail Required

Enter one of the following:

- 1 - To display a summary costing only. The totals for each included item are summed for the centre or DC.
- 2 - To display individual costing details for each included item.

Costing Method

Enter one of the following:

- 1 - To use the standard cost at the Inventory stockroom assigned to the item at the selected centre or DC.

2 - To use the latest (current) cost of the item at the Inventory stockroom assigned to the item at the selected centre or DC.

Factor

Enter one of the following:

- 1 - To display costings in units of one thousand.
- 2 - To display costings in units of ten thousand.
- 3 - To display costings in units of one hundred thousand.
- 4 - To display costings in units of one million.



To submit the report, select **F8=Submit Report**.

Distribution Item Master Report



5/DRR

You use this report to print DRP Distribution Item Master file information, for a range of items within the centre or DC.

Frequency – You can run this report as required.

New Page – A new page is used for each new item.

Totals - None.

Distribution Item Master Report Selection Screen



Select Distribution Item Master.

You use this screen to enter the selection details for the Distribution Item Master Report.

The screenshot shows a terminal-style interface for the 'Distribution Item Master Report Selection' screen. At the top, it displays session information: 'DR028P', 'Z1 - GB Demonstration Company', 'USER GBJBA1MS', and the date/time '13/03/98 10:46:23'. Below this is the title 'Distribution Item Master Report Selection.'. There are two main input fields: 'Centre/DC...?' followed by a cursor, and 'Select....?..' followed by two blank lines. Between these fields are the labels 'From' and 'To'. Below the input fields, there are three lines of instructions: 'To produce a report showing a range of Items, key in Both fields.', 'To produce a report for a specific Item, key in the From field.', and 'To produce a report for all Items, leave Both fields blank.'. At the bottom, a horizontal line separates the instructions from the function key definitions: 'F3=Exit F4=Prompt F8=Submit report'.

Fields:

Centre/DC

Enter a centre or DC.

Select From and To

Enter a range of item codes defined to this centre or DC.

Enter values in both the From and To fields to only include items within this range.

If you only enter a value in the From field, the report runs for the item specified only.

If you leave both fields blank, the report includes all items defined to this DC or centre.



To submit the report, select **F8=Submit Report**.

Supplier Schedule Reports



6/DRR

You use this report to produce a supplier schedule, either weekly or for each period or both. You can specify the following:

- A range of Purchase Management suppliers.
- A range of minor item groups.
- A range of DRP supply and distribution centres.
- The start date for the report.
- If the report produces weekly schedules, periodic schedules or both.
- Whether you sequence the report by item, within minor item group, within supplier, or item within supplier, irrespective of minor item group.



Note: The period report is a summary of the supplier schedule showing only total quantities per item per period.



Note: The weekly report provides all the information that the period report does, but also specific details of the purchase orders, requisitions and suggestions behind these total quantities (for the fixed part of the Schedule).

Supplier Schedule Report Selection Screen



Select Supplier Schedule Reports.

You use this screen to enter the selection details for the Supplier Schedule Report.

DR401	Z1 - GB Demonstration Company	USER GBJBA1MS	13/03/98 10:46:44
Supplier Schedule Report - Selection			
Supplier.....?..	█	to	
Minor Item Group....?..		to	
Centre/DC.....?..		to	
Start Date.....	13/03/98		
Weekly/Period Report... 1		(1=Weekly, 2=Period, 3=Both).	
Report Sequencing..... 1		(1=Minor Item Group, 2=Item).	
F3=Exit F4=Prompt F8=Submit			

Fields:

Supplier

Enter a range of suppliers. These do not need to be valid codes; the system selects the next or previous valid code.



Note: Supplier details only print on the report if you have entered supplier schedule details for that supplier in the DRP Supplier Schedule Profile option.

Minor Item Group

Enter a range of minor item groups. These do not need to be valid codes; the software selects the next or previous valid code.

Centre/DC

Enter a range of DRP centres or DCs. These do not need to be valid codes; the software selects the next or previous valid code.

Rules for Range Selection

Leave the From and To fields blank to select all items.

If you enter the From field and leave the To field blank, then the To field defaults to the From field.

If you enter a To field, you must enter a From field.

The To field must not be less than the From field.

Start Date

Specify the date from which to start detailing supplier schedule details on the report. This defaults to the Monday prior to the current date on the software. On the weekly report, any supply due before the start date, appears in the Past Due Date column. The Period Report does not show supply due prior to the report start date.

You must ensure that you define the default DRP calendar for the company for all the time periods that are to appear on the report.



Note: Please note that the period report can range over three calendar years.

Weekly/Period Report

Enter one of the following:

- 1 - To produce a weekly report.
- 2 - To produce a period report.
- 3 - To produce both weekly and period reports.

Report Sequencing

Enter one of the following:

- 1 - To sequence the report by item, within minor item group, within supplier. There is a page break when there is an overflow, change of minor item group, or change of supplier. The report uses the formats defined at minor item group level. When items do not have a defined minor item group or supplier/minor item group combinations, the report uses supplier level formats.
- 2 - To sequence the report by item within supplier. There is a page break when there is an overflow or change of supplier. The system ignores the minor item group and the report uses the format specified in the supplier definition within DRP Supplier Schedule maintenance.



To submit the report for printing, select
F8=Submit.

-
-
-
-
-

Chapter 6

Utilities

Maintain Company Profile




1/DRU

You use this procedure to define new companies to DRP and to maintain existing companies. The company code must correspond to the code defined to Inventory Management for this company.



Note: You maintain period details in this company profile. You must review these before you create a new calendar year using the Calendar Maintenance option.



```

DR019                      DRP Company Profile                      User SP1                      22/09/94
                                                                    11:52:04


Maintain Profile Records
Sel  Company
  1   Z1 Demonstration Company

Enter new company  __

1=Select
F3=Exit

```

Note: This code must not already exist in DRP. However, it should exist in Inventory Management.



Maintain DRP Company Profile Screen



To display the Maintain DRP Company Profile Screen, select a company, or enter a new company code on the Maintain Profile Records Screen.

You use this screen to specify the company defaults, including how you consume forecasts by actual demand, and the maximum number of lines on a distribution order.

DR019		USER SP1		22/09/94 11:52:41																																					
Maintain DRP Company Profile.																																									
Company code..... Z1 Company name... Demonstration Company																																									
Consume forecast.... 1 (0=No) Lines per Distribution Order... 999																																									
(1=Run level, 2=Week level, 3=Period level) Forecast Error Tolerance%																																									
Calc. safety stock.. 1 (0=No, 1=Yes) Absolute..... 30.00																																									
Safety stock weeks... 2 Include Quotations Percentage.. 100																																									
Safety stock days... 3 Period Forecasts.. 1 (0=No, 1=Yes)																																									
Calendar Parameters.																																									
Calendar code..... C1 Number of periods per year..... 13																																									
<table border="0" style="width: 100%;"><thead><tr><th>Period name</th><th>Days</th><th>Period name</th><th>Days</th><th>Period name</th><th>Days</th></tr></thead><tbody><tr><td>1. 1</td><td>28</td><td>2. 2</td><td>28</td><td>3. 3</td><td>28</td></tr><tr><td>4. 4</td><td>28</td><td>5. 5</td><td>28</td><td>6. 6</td><td>28</td></tr><tr><td>7. 7</td><td>28</td><td>8. 8</td><td>28</td><td>9. 9</td><td>28</td></tr><tr><td>10. 10</td><td>28</td><td>11. 11</td><td>28</td><td>12. 12</td><td>28</td></tr><tr><td>13. 13</td><td>28</td><td></td><td></td><td></td><td></td></tr></tbody></table>						Period name	Days	Period name	Days	Period name	Days	1. 1	28	2. 2	28	3. 3	28	4. 4	28	5. 5	28	6. 6	28	7. 7	28	8. 8	28	9. 9	28	10. 10	28	11. 11	28	12. 12	28	13. 13	28				
Period name	Days	Period name	Days	Period name	Days																																				
1. 1	28	2. 2	28	3. 3	28																																				
4. 4	28	5. 5	28	6. 6	28																																				
7. 7	28	8. 8	28	9. 9	28																																				
10. 10	28	11. 11	28	12. 12	28																																				
13. 13	28																																								
Standard week template.																																									
M T W T F S S																																									
N N (Blank for working day or 'N' for non-working day)																																									
F3=Exit																																									

Fields:

Consume Forecast

Enter one of the following:

0 - Forecast consumption is not used. Demand for a particular period is the greater of the forecast or actual sales for that period.

1 - To use consumption of forecast with no period control. The software bases demand for a particular period on cumulative consumption of forecast and actual demand, without reference to period ends, between the start and end dates specified for a DRP run.

2 - To use consumption of forecast by week. The system bases demand on cumulative consumption of forecast and actual demand within each week defined in the calendar for the DC or centre. At week ends, the system resets accumulations to zero.

3 - To use consumption of forecast by period. The system bases the forecast on cumulative consumption of forecast and actual demand within each period defined in the calendar for DC or centre. At period ends the system resets accumulations to zero.

Lines Per Distribution Order

Enter the maximum number of lines you want to appear on any distribution order. You can enter any number in the range 0 to 999.

Calc. Safety Stock

Enter one of the following:

0 - Not to calculate safety stock during DRP processing. The software uses the fixed safety stocks maintained at item or DC level.

1 - To calculate variable safety stock. The software calculates the safety stock on the basis of sales forecasts and the minimum safety stock cover (weeks and days) specified.

Forecast Error Tolerance % Absolute

Specify the default percentage by which sales forecast quantities and actual sales quantities can differ without the system writing a net change trigger for the item. The software uses this percentage if you do not enter a tolerance percentage at item level.

Safety Stock Weeks and Days

If you want to calculate safety stock, enter the minimum cover required, in weeks and days. You can override this at item or DC level or at DRP run time.

The software calculates the sales forecast for the specified time and uses this as the safety stock quantity. However, it excludes the forecast in the current column, as the calculation of demand includes this.

The system does not calculate safety stocks at daily level.

Include Quotations Percentage

Specify a percentage of the quantities of sales quotations, set up in Advanced Order Entry, to be included as demand in the DRP processing runs.

For example: 100% = Include full quantities of all quotations.

20% = Assume demand to be 20% of quantities of all quotations.

0% = Exclude all quotations from DRP demand.

Period Forecasts

Enter one of the following:

0 - Not to calculate period forecasts.

1 - To calculate period forecasts. You can then maintain both seasonal profiles at period level and Item Group or Item level period forecasts, or both.

Calendar Code

Enter the default calendar code for the company. Any DC or centre without a calendar code assigned to it via Period Maintenance uses this calendar (defined via Calendar Maintenance).

Number Of Periods Per Year

Enter the number of periods per year, in the range 1 to 13 inclusive.

Period Name

Enter a description for each period, up to the number of periods specified.

Days

Enter the number of days for each period.

Standard Week Template

Enter N against non working days in your normal working week. Leave blank for working days.

For example: 1994 Period 12:

Set the number of days to 32. This ensures that the year ends on a Sunday (01/01/95) rather than a Saturday (31/12/94). The total number of days in the year is then 364.

This is necessary because you maintain forecasts on a weekly basis, with the week always beginning on a Monday.



Note: The total number of days must equal 364 or 371. Also, you must make sure that the next year starts on a Monday.



Press **Enter** to update the company profile record and return to the Maintain Profile Records Screen.

Copy Company



2/DRU

You use this function to copy the data relating to one company across libraries and companies. You can therefore create backup libraries and create or update company data from a master company.

Copy Company Select Libraries Screen



Select Copy Company.

You use this screen to enter details for the Copy Company Select Libraries facility.

DR902CLP	DRP Copy Company Utility	User SP1	27/09/94 13:13:46
----------	--------------------------	----------	----------------------

Copy Company - Select Libraries

Library to copy from.....?.. OSLDEM3
Library to copy to.....

Regenerate file list..... (0=No, 1=Yes)

Company number field default
start position on files..... 0000

F3=Exit F4=Prompt F12=Previous

Fields:

Library to Copy From

Enter the name of the AS400 library which holds the source DRP data. This defaults to the standard DRP files library.

Library to Copy To

Enter the name of the AS400 library to copy the source DRP data to.

Regenerate File List

Enter one of the following:

0 - Not to regenerate the file list.

1 - To regenerate the file list.

Company Number Field Default Start Position On Files

Enter the company code from which to copy the information.



Press **Enter** to continue.



Glossary

Glossary

Calendar	To generate a calendar you specify the start date, holidays, and non-working days.
Centre	A central distribution point, supplying one or more DCs within the company.
Central Stockroom	The inventory stockroom, defined at the Centre, which normally supplies the Item.
Customer	The customer code allocated to a stockroom within Distribution Requirements Planning.
Distribution Centre or DC	A regional distribution or retail outlet for the company.
Demand	The outstanding sales and distribution orders and sales forecasts against an item.
Distribution Item	A valid inventory item which has been defined to DRP.
Distribution Order	An internal sales order placed on a centre to meet the demand of one of the DCs it supplies, this is a formal request to transfer stock.
Forecasts	A sales forecast is the anticipated value, or quantity, to be sold within a given period. A stock forecast is the required level of stock to be planned as being available within a given period, that is as part of a stock build action (to typically meet a seasonal demand with a potential lack of supplier capacity).
Forecast/Seasonal Profiles	Time-phased spread patterns which can be applied to item group and item sales forecasts or stock building requirements to break them down by period, week and day.
Item Master	Details for each item which are specific to its control within DRP.
Local Stockroom	The primary inventory stockroom for the item at the centre or DC, that is where it is normally stocked.
Net Change	A method of planning by which items may be selected for re-planning on the basis of unplanned changes in supply, demand, stock levels or replenishment

parameters that have occurred since last planning.

Network	The relationship between a centre and all the DCs it can supply.
Overdue Days	The number of calendar days, prior to the current date, that DRP considers overdue orders in the planning runs.
Order Policy	This defines how an item is to be replenished when a supply requirement has been identified.
Pack Type Code	The code for the pack in which the item is being despatched, from centre to DC. Applies to System 21 Warehousing interface.
Planner	The person responsible for controlling the supply of a number of items within DRP.
Planner Actions	Actions suggested by DRP to be taken against supply orders (in attempting to match supply to demand).
Reason Codes (Net Change)	A code defined in DRP and referring to a type of transaction within the Business 400 applications which potentially affects the supply, demand, stock levels or replenishment parameters of DRP items. Net change triggers are set under particular reason codes.
Safety Stock	The fixed level of stock you plan to be permanently available.
Safety Stock Weeks and Days Cover	The level of safety stock cover calculated during DRP, expressed in terms of weeks and days demand. This is calculated from the sales forecast, at item level.
Schedule	The time-phased plan generated by DRP for each item showing supply, demand and suggested actions.
Selective Actioning	A method of planning by which a range of DRP items, DRP planners, inventory minor item groups, inventory cost/usage elements and/or preferred suppliers are used to select certain DRP items for re-planning.
Shipments	Items in-transit between supply centres and DCs, that is confirmed as despatched from the centre but not confirmed as fully received at the DC.
Supply	The stock of an item to be replenished, that is purchase order lines, distribution order lines, and stock in-transit to a DC.
Time Fence Days	The number of calendar days, from the current date, that DRP freezes the schedule, that is it does not suggest any new supply orders.
Triggers	In net change DRP, triggers are used to highlight changes which potentially affect the planning of DRP items.

Triggers are set by transactions and maintenance options throughout distribution management applications under the control of a set of defined reason codes.

Valuation	An assessment of the cost involved in following the supply suggestions shown on the schedule.
Week Templates	A representation of the working and non-working days in a week, that is Monday to Sunday (these are associated with a range of dates).

PRODUCT
GUIDE