

-
-
-
-
-

Chapter 2

Processing



Forecasting Processing Introduction

You can divide forecast processing into three distinct stages:

1. Extracting groups of items and their sales for each forecasting model.
2. Applying Forecasting techniques.
3. Downloading forecasts.

Extraction

For each forecasting model, you must extract the Inventory Management profiles and Sales Analysis sales history for selected groups of items.

You can either select items by Inventory minor item group, or transfer all the items together.

You can execute this function as required. During this process new items are added to the forecasting model, and existing item details are updated on the Forecasting database.



Note: You cannot maintain Group/item profiles in a forecasting model until you have extracted this combination.

From Sales Analysis, you can select full sales history, or last period sales only. You should extract the last period sales immediately after you have run a Sales Analysis period-end, and before you run the Forecast period-end. Full sales history attempts to extract three years of sales demand.

These sales quantities are extracted for every item with a profile defined in the selected forecasting model.

Item sales quantities are aggregated to minor item group level and also stored in Forecasting.

You can transfer values from Service Management (the Transfer Full Service Demand option) either before or after extracting from Sales Analysis (Transfer Full Sales History).



Warning: When you run the second of the two options, make sure that you specify that you do not want to overwrite existing data, otherwise the system will clear the data you have just transferred.

Applying Forecasting Techniques

The Forecast Period-end job calculates forecasts for the next twelve or thirteen periods for all forecasting models.

Groups or items with a locked in forecast method immediately use the corresponding formula to create forecasts. Items with a locked in manual forecast are ignored.

Otherwise, the process of simulation is used. The application goes back in time evaluating each forecast method for each item and group of items. This period of time, that is, the simulation period, is defined for each group/item on its profile record, in each forecasting model.

The application projects these simulated periods, using each of the methods, pretending they did not happen. Whichever method best projects these periods that have already happened is the one used to project the future for this item or group of items.

Thus, the Forecasting application decides which is the best method by calculating forecast errors for each method. The error is expressed in terms of percentage.

The absolute value of this error percentage is used to compare methods and is known as the MAPE (Mean Absolute Percentage Error).

There are seven forecasting methods supplied and all are used in this Period-end processing.



Note: You can manually change a forecast created by the period-end run using the Forecast Manipulation option. This is identical to the Forecast Enquiry but with update facilities.



Note: Item forecasts may be optionally aggregated up to group level using the Forecast Aggregation option.

Downloading Forecasts

You can download forecasts into:

- The DRP and/or Production applications. This may be done at minor item group or item level.
- A specified DRP Centre or DC, or MPS/MRP model. This applies the DRP/Production Spread Profiles setup within Forecasting Maintenance, to distribute the forecasts over working weeks/days.
- DRP and/or Production applications employing seasonal profiles defined and maintained within the DRP or Production application. These Seasonal Profiles are a set of indices defining the spreading of forecasts from annual to period, period to weekly, and weekly to daily forecasts. You can assign a seasonal profile to any forecasted item or minor item group.
- A requirements file. You can load this into your own applications for further evaluation. Software programs must be written to achieve this.

Transfer Product Details



1/FCP

Use this procedure to transfer item details from Inventory Management into forecasting models, using the Inventory company code defined on the Forecasting company profile.

For new items a group/item profile record is created in the selected forecasting model, using the minor item group/item code from Inventory. For items already having a group/item profile these details are updated.

A profile record is also created/updated for each minor item group.

You must select this option before maintaining an item/group profile or using a forecasting model. Thereafter, it is used to transfer new items and this can be done at any time.



Note: If an Inventory item has had its minor item group reassigned, then this option copies it to the new group, with its existing demand and forecast quantities, and deletes the old records.

Transfer Product Details Selection Screen



Select Transfer Product Details.

Use this screen to select the forecasting model you want to update, and the group of items you want to transfer.

FC031	Z1 - Demonstration Company	USER SP1	14/09/94 13:53:14
Transfer Item Details - Select			
Model to transfer.....?.. <u>C1</u> Midlands DRP Centre			
Group to transfer.....?.. <u>3</u> Sun Protection			
F3=Exit F4=Prompt F8=Submit			

Fields:

Model To Transfer

Enter a model code to specify the forecasting model to which the Item details are to be transferred. Leave blank to select all models.

Group To Transfer

Enter the minor item group to be transferred. If you leave this blank, all minor item groups in the Inventory Management application are transferred.



Note: If you select all groups, items with no minor item group assigned to them in the Inventory application are also transferred. These are defined to a default group code 999 within this application.



Select **F8=Submit** to submit a job to perform the transfer.

Transfer Full Sales History



2/FCP

Use this procedure to transfer the last 36 or 39 sales history periods from the Sales Analysis application into each forecasting model. This is done for all items having a group/item profile within this application.

Sales history quantities are accumulated for each item within each group, and a group sales history quantity is then transferred, for each group within the forecasting model.



Warning: You normally run this option once (when you set up the company for the first time).



Note: The current Forecasting year and period must match the corresponding year and period in the Sales Analysis application. Any quantities for the current period are not extracted. If the year and period do not match, an error message is displayed and the batch job to perform the transfer cannot be submitted.

When transferring details from Sales Analysis, the option exists in Sales Analysis to hold quantities in the Inventory issue unit from the item master file (see Sales Analysis company profile maintenance for details). If the generated forecasts are to be transferred to Distribution Requirements Planning, this must be the case, as DRP deals in the Inventory issue unit from the item master file and expects quantities to arrive in that unit.



Note: This also applies when transferring forecasts to MPS or MRP.

Transfer Full Sales History Selection Screen



Select Transfer Full Sales History.

Use this screen to submit the job to update this application with the last 3 years' Sales History for all groups and Items defined to each forecasting model in this application.

You specify whether or not you wish to keep any Forecasting data already in the transfer files.

```
FC023          Z1 - GB Demonstration Company      LOAN          22/01/97
                                                16:15:54

Transfer Full Sales History - Select

Warning: If you have previously transferred demand history from Service
Management and wish to add Sales demand history, then do not
select to delete existing history.
If you have previously transferred Sales demand history, then
you must select to delete existing history, or double counting
will occur. N.B. any existing demand history from Service Management
will also be deleted.

Delete existing Forecasting demand history..... 1 (1=Yes,0=No)

Press F8 to confirm and submit batch job to transfer sales history

F3=Exit

15-51  SF  MW  KS  IM  II  EDN400A  PET179S2
```

Fields:

Delete Existing Forecasting Demand History

Enter one of the following:

0 - If you do not want to overwrite any Forecasting demand that exists in the files, but want to accumulate it with the new data when you update.

1 - If you do not wish to keep any Forecasting demand that may already exist in the files when you update.



Select **F8=Update**, to submit a job to create/update records in the demand history and current forecasts file.

Transfer Last Period History



3/FCP

You use this option to transfer the last period sales/demand quantities from Sales Analysis and Service Management (if Service Management is installed) into each forecasting model. This is done for all items having a group/item profile.

The last period demand quantities are accumulated for each item within a group and also transferred.

You should select this option before invoking the period-end run, and just after processing the current period in Sales Analysis.



Note: The current Forecasting year and period must be one period behind the Sales Analysis period.



Note: If Service Management is attached, the current Inventory period must match the current Forecasting period.

Transfer Last Period History Selection Screen



Select Transfer Last Period History

Use this screen to view the period to transfer, and submit the job to perform the updates for this transfer.

FC026	Z1 - Demonstration Company	SP1	14/09/94 14:14:02
Transfer Last Period Sales - Select			
Last period transferred.... 94 08			
Period to transfer this session... 94 09			
F3=Exit F8=Submit Job			

Fields:

Last Period Transferred

Displays the last period.

Period To Transfer This Session

Displays the period to be transferred this time.



Select **F8=Submit** to submit a job to perform the updates. The Last Period Sales quantities for all items and groups defined to each forecasting model are written to the demand history file in this application.

Transfer Full Service Demand



4/FCP

You use this option to transfer any item demand raised within Service Management into the same file that holds the sales history transferred from Sales Analysis.



Warning: If you have already transferred from Sales Analysis, then make sure you do not overwrite that information. You can choose not to clear down information already in the sales history file.

If you have not already done the transfer from Sales Analysis, then you can do so after selecting this option.



Note: You can only use this option if Service Management is attached for the interface company defined on the Forecasting company profile.

Transfer Full Service Management Demand Selection Screen



Select Transfer Full Service Demand.

Use this screen to execute the Transfer Full Service Management Demand option and to select whether you want to delete the existing Forecast in demand history.

FC710	Z1 - GB Demonstration Company	LOAN	22/01/97
Transfer Full Service Management Demand - Select			16:16:23
Warning: If you have previously transferred demand history from Sales Analysis and wish to add Service demand history, then do not select to delete existing history. If you have previously transferred Service Management demand history, then you must select to delete existing history, or double counting will occur. N.B. any existing demand history from Sales Analysis will also be deleted.			
Delete existing Forecasting demand history..... ☒ (1=Yes,0=No)			
Press F8 to confirm and submit batch job to transfer demand history			
F3=Exit F8=Submit Job			
15-51	SF	MW	KS IM II EDN400A PET179S2

Delete Existing Forecasting Demand History

Enter one of the following:

0 - To accumulate any existing Forecasting demand with the new data.

1 - To remove any Forecasting demand that may already exist in the files. Any such data is overwritten when you select to transfer the new forecasting history.

The submitted job extracts the usage of parts reported on the engineer's technical report. The job only extracts data from closed technical reports, and excludes any returns from the extract. The demand is assigned to those forecasting models that include the engineer's stockroom. The demand is deemed to fall on the date of the engineer's visit.



Select **F8=Submit Job** to submit a job to create/update records in the demand history and current forecasts file within this application.

Forecast Period End



11/FCP

You use this procedure to generate forecasts for the next year in each forecasting model. Forecasts are generated for all groups of items, and individual items, having profiles in this application.

This is achieved by evaluating the performance of each forecast method over a simulation period. This program selects the best method, and uses this to project the forecast quantities for the coming 12 or 13 periods.



Note: Select this option at the end of each period, after the last period sales have been transferred from Sales Analysis. If the latter has not been done, an error message is displayed. However, you can still run the period-end (as you may have manually entered the last period's demand quantities) by selecting the submit key.

Forecast Period End Selection Screen



Select Forecast Period End.

Use this screen to submit the period-end run. This screen is for confirmation only.

FC015	Z1 - Demonstration Company	USER SP1	14/09/94 14:14:07
-------	----------------------------	----------	----------------------

Forecast Period End - Select

Forecast Current Period..... 9

Forecast Current Year 94

Period To Forecast 10

Year To Forecast 94

F3=Exit F8=Submit

Fields:

Forecast Current Period

The current period, that is the last period for which forecasts were generated (by this option).

Forecast Current Year

The current year, that is the last year for which forecasts were generated (by this option).

Period To Forecast

The starting periods for the forecasts from this run.

Year To Forecast

The starting year for the forecasts from this run.

This process does the following:

1. Starts a backup of the Forecasting files library, if this option is selected on the Company Profile. A message is displayed on the screen requesting that a tape or cartridge be mounted on the relevant device.
2. Increments the period number and description forward one period on the company profile. For each profile record (group or item) found in each forecasting model the process performs the steps 3 to 9.
3. Increments the marketing masks back one period, with the last one being reset to

zero.

4. Establishes the simulation period. The period for an item is retrieved from the item profile, unless it is zero, in which case the period from the group profile is used.
5. Increments the demand history quantities back one period, losing the oldest period. The last period sales figure is moved into the most recent period's figure, and the last period zeroised.
6. Applies each of the forecast methods over the simulation period, calculating a forecast error for each. The method with the error closest to zero is selected. This step is not executed for group or items where a manual or locked in forecast is specified on the profile.
7. Applies the selected forecast method and writes the forecast quantities to the demand history and current forecast file. These are the forecast quantities before applying marketing masks. This step is not executed if forecasts are flagged as Manual in the profile record.
8. Applies conversion factors to these forecast quantities, if this is selected as required on the company profile.
9. Writes the forecasts to the Forecast History Files, after incrementing the forecast back one period and losing the oldest one. You specify on the company profile the number of periods forecast history you want retained before purging. The forecast history files are used for reporting and evaluating forecast performance
10. After processing all profile records for the company, produces a report. This gives a summary of the number of times each Forecast Method code was selected within each group of items.



Note: If this processing run fails for any reason, contact your software support organisation. The likelihood is that you will need to perform a restore from your initial security copy.



Select **F8=Submit** to submit a job to perform the Forecast Period-end run.

Forecast Manipulation



12/FCP

You use this procedure to maintain the current forecasts for any item, or group of items, in any Forecasting Model. You can select an alternative forecast method that recalculates the forecasts or manually enter the forecast quantities.

The last 3 years sales demand is shown for comparison.

The sales and forecast quantities may also be displayed in the form of a Bar Chart.

Forecast Manipulation Selection Screen



Select Forecast Manipulation.

Use this screen to select the forecasting model and the item or group of items to be maintained.

FC053	Z1 - Demonstration Company	USER SP1	14/09/94 13:55:37
Forecast Manipulation - Select			
Model....?.. <u>C1</u>	Midlands DRP Centre		
Group....?.. <u>3</u>	Sun Protection		
Item.....?.. <u>5002</u>	Suncream Factor 8 225ml		
F3=Exit F4=Prompt			

Fields:

Model

Enter a model code to specify the forecasting model you wish to manipulate.

Group

Enter a group code.

Item

Optionally, enter an item code. The item must have a profile record for this group within the application.



Note: If you enter a group, with item blank, the details the system displays the screen for this group of items.



To display the Forecast Manipulation Details screen, select an item, and press **Enter**.

Forecast Manipulation Details Screen



To display this screen select an item and press **Enter** on the Forecast Manipulation Selection screen.

Use this screen to display the sales history, and maintain forecasted quantities, for the selected item or group in the selected Forecasting Model.

FC053	Z1 - Demonstration Company	USER SP1	14/09/94 13:55:39
Forecast Manipulation - Details			
Model... C1	Group... 3	Item... 5002	Forecast code?... C
Suncream Factor 8	225ml		Error %..... 16.67
History of Demand			
Period	91/92	92/93	93/94
10	4	4	5
11	3	4	4
12	2	3	1
13	1	1	2
1	1	1	1
2	1	1	1
3	1	1	1
4	12	12	12
5	15	19	21
6	18	22	25
7	21	18	19
8	10	9	11
9	6	7	12
+++	95	102	115
Forecast			
			94/95
			5
			4
			2
			3
			1
			1
			1
			12
			20
			24
			19
			10
			16
			118
F3=Exit F4=Prompt F8=Update F12=Previous F15=Text F18=Graph			

Fields:

Description

This field is not named on the screen, but contains the description for item, or group of items, from the profile record.

Locked In Forecast

The Forecast Method locked into this item or group. If specified on the profile record, then this is the one used in the Period-end run for generating forecasts.



Note: This field and title only display if the record is selected as locked into.

Forecast Code

The selected forecast method code.

You can overtype the displayed code with a different code; if you enter *, you can change the quantity fields for the forecasts. Press **Enter** to display the details for the specified Forecast Code.

Error %

The percentage error calculated for the forecast method selected by the forecast code.

In the main body of the screen, quantities are shown for the last 3 years sales

demand and the next 12 or 13 period forecasts.



Note: The mechanics of this calculation error are explained in the Applying Forecasting Techniques section at the beginning of this section.

The periods are retrieved from the descriptions on the Company Profile.

The forecast quantities shown are those calculated before the Marketing Masks are applied, in other words the initial forecasts. The Marketing Masks in the final column are those for the selected item or group, as specified on the profile record. If the masks for an item are all zero, the masks for the group are used. If the group masks are all zero, then all masks default to 1.



*Note: The manual forecasts entered are overwritten by the Forecast Period-end unless the locked in Forecast Code is set to * in the profile record.*

If the Forecast Code is amended to another valid method code, the forecasts are immediately recalculated (as is the forecast error).

Functions:

F15


Text. Use this to maintain text for an item or group of items.

F18

Graph. Use this to display graph screen.



Select **F8=Update** to write the current forecasts to the Sales Demand and Current Forecasts file.



The graph itself splits into two. The left-hand side shows the Demand History, and the right shows the Forecast Quantities.

The scale on the Y axis is calculated so that the highest peak just fits on the screen.



Note: The quantities used for the forecasts in the graph are the final forecasts shown down the right hand side of the screen, that is with any marketing masks applied.



Select **F8=Update** to update the revised masks in the Forecasting Model Group/Item Profile record.

Forecast Aggregation



13/FCP

You use this procedure to select Forecasting Model Groups for forecast recalculation. This is done by aggregating all forecasts for items in each selected group, and updating the Group forecast record with the totals. The previous group forecast is then lost.

You use this when you feel that the aggregated item forecasts are more accurate than the forecast generated from the demand history for the group.

Forecast Aggregation Selection Screen



Select Forecast Aggregation.

Use this screen to select the Forecasting Model groups you want to process and update.

FC054	Z1 - Demonstration Company	User SP1	14/09/94 13:56:16
Forecast Aggregation - Select			
Model.....?.. <u>C1</u> Midlands DRP Centre			
Group From..?.. ____			
Group To....?.. ____			
Warning: This job will replace any existing forecasts for the selected group with the aggregated item forecast.			
F3=Exit F4=Prompt F8=Submit			

Fields:

Model

Enter the Forecasting Model in which forecasts are to be aggregated. Leave this field blank to select all Models.

Group From/To

Select the range of Groups to be updated.



Note: If From is entered and To left blank, only the Group From is processed. If you leave both blank, all groups are processed.

This sums the forecasts for the items in the group, and updates the group record in the Sales Demand and Current Forecasts file. The previous Group forecast is lost.

Conversion factor and marketing masks are applied to each item as part of the aggregation. You can maintain this forecast using the forecast manipulation function.



Select **F8=Submit** to submit a job to perform the forecast aggregation for each selected group.

Generate Requirements File



21/FCP

Use this procedure to create a file of forecast requirements for Type 4 forecasts that need to be transferred to another destination or held internally. The system submits a batch job that transfers the forecast quantities for the next 12 or 13 periods to the file. You can then remove the file from this application and transfer it to your own application.



Note: Software programs must be written to achieve this.

You can select single or all Forecasting Type 4 Models. The transfer may be for a single Group or for all Groups and may be at either Group or Item level.

Conversion factors and Marketing Masks are applied before the requirements record is written.



Note: This option is not required for Forecasting Models Types 1–3 as forecasts are transferred directly from Forecasting into the DRP and/or Production applications.

Generate Requirements File Selection Screen



Select Generate Requirements File.

Use this screen to select the Forecasting Model to be transferred, and to select the level of forecast to transfer, that is those for individual items, or for groups of items as a whole.

A description for any selected group is displayed.

FC032	Z1 - Demonstration Company	User SP1	14/09/94 13:56:30
Generate Requirements File - Select			
Model.....?.. __			
Group to transfer..?.. __			
Level to Transfer.... <u>1</u> (1=Item 2=Group)			
F3=Exit F4=Prompt F8=Submit			

Fields:

Model

Select the Type 4 Forecasting Model that is to have forecasts transferred to the requirements file.

Leave blank for all Type 4 Model Codes.

Group To Transfer

Enter the group to be transferred.

Leave blank to transfer all groups.

Level To Transfer

Enter one of the following

- 1 - To transfer item forecasts only.
- 2 - To transfer group forecasts only.



Note: Before running this procedure you must transfer the forecasts already in the Requirements File into their respective destination applications.



Note: The relevant Marketing Masks are applied to the forecasts before writing them to the file.



Select **F8=Submit** to submit a job to transfer the requirements selected. This job writes the relevant final forecasts to the Requirements File.

Transfer Forecast To DRP



22/FCP

You use this procedure to transfer forecasts from Forecasting Models into the Distribution Requirements Planning application.

A Forecasting To DRP Exceptions Report is produced automatically. This shows all items, or groups, which have failed to transfer forecasts into DRP together with a description of the reason.



Note: If the Exceptions Report is blank all forecasts have transferred successfully into the DRP Forecast files.

In the Company Profile Maintenance - Forecast Options screen, specify whether the forecasts are transferred using the spread profiles defined in the Forecasting application or those defined in the DRP application.

Transfer Forecasts To DRP Selection Screen



Select Transfer Forecasts To DRP.

You use this screen to select the Forecasting Model, Group and Transfer Period Range, from which forecasts are transferred to DRP.



Note: Only forecasts from Forecasting Models defined with DRP Centres or Distribution Centres as Target Models are eligible for transfer. Each Type 1 forecasting model has a DRP Distribution Centre as its Target Model. Each Type 2 forecasting model has a DRP Centre as its Target Model.

FC042	Z1 - Demonstration Company	User SP1	28/09/94 12:19:47
Transfer Forecasts to DRP - Select			
Model.....?.. <u>C1</u> Midlands DRP Centre			
Group to transfer....?.. <u> </u>			
Level to transfer..... <u>1</u> (1=Item 2=Group)			
Period to transfer from <u>9409</u> (YYP) to <u>9508</u> (YYP)			
F3=Exit F4=Prompt F8=Submit			

Fields:

Model

Select either a Type 1 or 2 Forecasting Model from which forecasts are transferred to DRP. Leave blank to select all Type 1 and 2 Models.

Group

Enter the Group that is to have forecasts transferred.

Level To Transfer

Enter one of the following:

- 1 - To transfer Item Forecasts.
- 2 - To transfer Group Forecasts

Period To Transfer

Enter the range of periods to be transferred to DRP. The forecasting application

suggests a range of forecasts to be transferred. Enter periods in the format YYPP

In doing this, the application applies the Spread Profiles maintained in Forecasting, to convert the period forecasts into the weekly or daily DRP forecasts.

Any existing forecasts found within DRP for the selected Minor Item Groups are deleted, before adding this new data.



Select **F8=Submit** to submit a job to transfer all selected forecasts into DRP.

Transfer Forecasts To DRP Using DRP Spread Profiles



22/FCP

This method of forecast transfer uses Seasonal Profiles, which are a set of indices defining the spreading of forecasts from annual to period, period to weekly, and weekly to daily forecasts.

These Seasonal Profiles are maintained within DRP and a particular Seasonal Profile can be assigned to any forecasted Item or Minor Item Group.



Tip: You choose to use DRP Spread Profiles in your Company Profile.

If a Seasonal Profile is not entered for a particular Item or Group, then forecasts are spread evenly over the time intervals required.

The application produces a Forecasting to DRP Exceptions that shows all items, or groups, which have failed to be transferred into DRP together with an appropriate description of the reason.



Note: If the Exceptions Report is blank all forecasts have transferred successfully into the DRP Forecast files.

Transfer Forecasts To DRP Using Seasonal Profiles Selection Screen



Select Transfer Forecasts To DRP.

Use this screen to select the procedure to use when transferring forecasts to DRP.

Only forecasts from Forecasting Models defined with DRP Centres or Distribution Centres as Target Models are eligible for transfer. Where each Type 1 forecasting model has a DRP Distribution Centre as its Target Model. and each Type 2 forecasting model has a DRP Centre as its Target Model.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:17:57
Transfer Forecasts to DRP using Seasonal Profiles			
Enter a specific Model or leave blank to transfer all Models:			
Model.....?.. <u>C1</u> Midlands DRP Centre			
Level to transfer..... <u>1</u> (1=Item, 2=Group)			
Period to transfer from <u>9409</u> (YYPP) to <u>9508</u> (YYPP)			
F3=Exit F4=Prompt			

Fields:

Model

Select either a Type 1 or a 2 Forecasting Model from which forecasts are transferred to DRP. Leave blank to select all Type 1 and 2 Models.

Level To Transfer

Enter one of the following:

- 1 - To transfer Item forecasts.
- 2 - To transfer Group forecasts.

Period To Transfer

Enter the range of periods to be transferred to DRP. The forecasting application suggests a range of forecasts to be transferred. Enter periods in the format YYPP.



Press **Enter** to display the Transfer Forecasts To DRP Using Seasonal Profiles Transfer All Models screen. The format of this screen depends on which values were entered.

Transfer Forecasts To DRP Using Seasonal Profiles Transfer All Models Screen



To display this screen press **Enter** on the Transfer Forecasts To DRP Using Seasonal Profiles Selection screen. The format of this screen depends on which values were entered.



Note: This screen is displayed when the Model field on the initial screen is left blank.

Use this screen to select the daily and weekly transfer periods for this transfer method.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:17:32
Transfer Forecasts to DRP using Seasonal Profiles - All Models			
Transfer is at Item level from period 9409 to period 9508			
All Items in all Models will be transferred.			
First forecast week is 33 in year 94 Last forecast week is 32 in year 95			
Intervals: Daily forecasts from week __ to week __			
Weekly forecasts from week __ to week __			
F3=Exit F4=Prompt F8=Submit F12=Previous			

Fields:

Daily Forecast From/To Week

Select the interval for the Daily forecast.

Leave blank to select the whole transfer period defined on the initial screen.

Weekly Forecast From/To Week

Select the interval for the Weekly forecast.

Leave blank to select the whole transfer period defined on the initial screen.



Press **Enter** to check the entries.



Select **F8=Submit** to submit the job to transfer the forecasts into DRP using the DRP spread profiles.

Transfer Forecasts To DRP Using Seasonal Profiles Group Selection Screen



To display this screen press **Enter** on the Transfer Forecasts To DRP Using Seasonal Profiles Selection screen. The format of this screen depends on which values were entered.



Note: This screen is displayed when the Model field on the initial screen is completed, and the Level to Transfer field is set to 2=Group.

Use this screen to select a single group or a range of groups. Further, you have the option of specifying the time intervals for the daily and weekly forecasts.

The screen displays the Forecasting Model and transfer periods specified.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:19:12
Transfer Forecasts to DRP using Seasonal Profiles - Select Groups			
Model..... C1 Midlands DRP Centre		Calendar C1	
Transfer is at Group level from period 9409 to period 9508			
Enter a range of Groups to transfer or leave blank to transfer all:			
From Group.....?.. 1 Food			
To Group.....?.. 5 Lipsticks			
First forecast week is 33 in year 94 Last forecast week is 32 in year 95			
Intervals: Daily forecasts from week __ to week __			
Weekly forecasts from week __ to week __			
F3=Exit F4=Prompt F8=Submit F12=Previous F16=Select Group/Seasonal Profiles			

Fields:

From/To Group

Enter the Group Range to which you want to restrict the transfer.

Leave both fields blank to transfer all Groups.

Daily Forecasts From/To Week

Select the interval for the Daily forecast.

Leave blank to select the whole transfer period defined on the initial screen.

Weekly Forecast From/To Week

Select the interval for the Weekly forecast.

Leave blank to select the whole transfer period defined on the initial screen.

 Press **Enter** to validate the entries.

Functions:

F16

Select Group/Seasonal Profiles. Display Group/Seasonal Profile Selection screen.

 Select **F8=Submit** to submit the job to transfer the selected forecasts into DRP using the DRP spread profiles.

Transfer Forecasts To DRP Using Seasonal Profiles Select Profile Screen (F16)



To display this screen select **F16=Select Groups/Seasonal Profiles** on the Transfer Forecasts To DRP Using Seasonal Profiles Group Selection screen.

Use this screen to assign any seasonal profile to the selected group range. These seasonal profiles are maintained within DRP.

The screen displays the model code and description, the list of Group codes and descriptions selected and the transfer periods.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:19:17
-------	----------------------------	----------	----------------------

Transfer Forecasts to DRP using Seasonal Profiles - Select Profiles

Model..... C1 Midlands DRP Centre Calendar C1

Transfer is at Group level from period 9409 to period 9508

Group	Description	Seasonal Profile(?)
1	Food	—
2	Drinks	—
3	Sun Protection	—
4	Make-up	—
5	Lipsticks	—

1=Select
F3=Exit F4=Prompt F8=Submit F12=Previous F15=Select all

Fields:

Select

This field is not named on the screen. Enter 1 to select a spread profile for this group.

Seasonal Profile

Enter a seasonal profile code that is to be associated with the selected group.

Functions:

F15

Select all. Use this function to select all groups for transfer.



Select **F8=Submit** to submit the job.

Transfer Forecasts To DRP Using DRP Spread Profiles Select Item Screen



To display this screen press **Enter** on the Transfer Forecasts To DRP Using Seasonal Profiles Selection screen. The format of this screen depends on which values were entered.



Note: This screen is displayed when the Model field on the initial screen is completed, and the Level to Transfer field is set to 1=Item.

Use this screen to select a single item or a range of items if required. You also have the option of specifying the time intervals for the daily and weekly forecasts.

The screen displays the Forecasting Model and transfer periods specified.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:18:30
Transfer Forecasts to DRP using Seasonal Profiles - Select Items			
Model..... C1 Midlands DRP Centre		Calendar C1	
Transfer is at Item level from period 9409 to period 9508			
Enter a range of Items to transfer or leave blank to transfer all:			
From Item.....?.. 5001		Suncream Factor 4 225ml	
To Item.....?.. 5005		Suncream Factor 4 300ml	
First forecast week is 33 in year 94 Last forecast week is 32 in year 95			
Intervals: Daily forecasts from week __ to week __			
Weekly forecasts from week __ to week __			
F3=Exit F4=Prompt F8=Submit F12=Previous F16=Select Items/Seasonal Profiles			

Fields:

Item Range

Enter the range of Items to which you want to restrict the transfer.

Leave both fields blank to transfer all Items.

Daily Forecasts From/To Week

Select the interval for the Daily forecast.

Leave blank to select the whole transfer period defined on the Transfer Forecasts to DRP using DRP Spread Profiles initial screen.

Weekly Forecasts From/To Week

Select the interval for the Weekly forecast.

Leave blank to select the whole transfer period defined on the Transfer Forecasts to

DRP using DRP Spread Profiles initial screen.



Press **Enter** to validate the entries.

Functions:

F16

Select Items/Seasonal Profiles.



Select **F8=Submit** to submit the job to transfer the selected forecasts into DRP.

Transfer Forecasts To DRP Using DRP Spread Profiles Item Profile Selection Screen (F16)



To display this screen select **F16=Select Items/Seasonal Profiles** on the Transfer Forecasts To DRP Using Seasonal Profiles Group Selection screen.

Use this screen to assign any seasonal profile to the selected item range. These seasonal profiles are maintained within DRP.

The screen displays the model code and description, the list of Item codes and descriptions selected and the transfer periods.

FC142	Z1 - Demonstration Company	User SP1	28/09/94 12:18:38
Transfer Forecasts to DRP using Seasonal Profiles - Select Profiles			
Model..... C1 Midlands DRP Centre		Calendar C1	
Transfer is at Item level from period 9409 to period 9508			
Item	Description	Seasonal Profile(?)	
- 5001	Suncream Factor 4 225ml	—	
- 5002	Suncream Factor 8 225ml	—	
- 5005	Suncream Factor 4 300ml	—	
1=Select			
F3=Exit F4=Prompt F8=Submit F12=Previous F15=Select all			

Fields:

Select

Enter 1 to select a spread profile for this Item.

Seasonal Profile

Enter a seasonal profile code that is to be associated with the selected Item.

Functions:

F15

Select all. Use this function to select all the spread profiles.



Select **F8=Submit** to submit the job.

Transfer Forecasts To MPS/MRP



23/FCP

Use this procedure to transfer forecasts from Forecasting Models into the MPS/MRP runs.

A Forecasting to MPS/MRP Exceptions Report is produced. This shows all items, or groups, which have failed to transfer forecasts into Production together with a description of the reason.



Note: If the Exceptions Report is blank all forecasts have transferred successfully into the Production Forecast files.

Transfer Forecasts To MPS/MRP Selection Screen



Select Transfer Forecasts to MPS/MRP.

Use this screen to select the Forecasting Model, Group and Transfer to Period from which forecasts are transferred to MPS/MRP.



Note: Only Forecasting Models defined with MPS/MRP Target Models are eligible for transfer to MPS/MRP. These Models are defined as Model Type 3.

FC043	Z1 - UK Demonstration Company	User GBJBANB4	9/04/98 10:57:11
Transfer Forecasts to MPS/MRP - Select			
Model Number.....?..... _			
MPS/MRP Forecast Group...?.. _			
Level to transfer..... 1 (1=Item 2=Group)			
Period to transfer from 9705 (YYPP) to 9804 (YYPP)			
F3=Exit F4=Prompt F8=Submit			

Fields:

Model Number

Select the Type 3 Forecasting Model from which forecasts are transferred to MPS/MRP. Leave blank to select all Type 3 Models.

MPS/MRP Forecast Group

Select the Group that is to have forecasts transferred.

Level To Transfer

Enter one of the following:

- 1 - To transfer Item forecasts.
- 2 - To transfer Group forecasts.

Period To Transfer From and To

Enter the range of periods you want to transfer to MPS/MRP using the format YYPP.

When you do this the Spread Profiles maintained in this application are used to

convert the period forecasts into the weekly MPS/MRP forecasts.

Alternatively, if you have configured Forecasting to use the MPS/MRP application seasonal spread profiles, these spread profiles (which are maintained within the MPS/MRP application) are used.

Any existing forecasts found within MPS/MRP for the selected Minor Item Group(s) are deleted before the new data is added.



Select **F8=Submit** to submit a job to transfer all selected forecasts into Production for use by the MPS/MRP runs.