

-
-
-
-
-

Chapter 9

Cost To Complete

Cost To Complete Initiation



1/JCI

This option sets off a batch job that updates all the standard commitment values, and clears all existing data from the cost to complete files. It also clears all existing budget values from the budget you specify on the selection screen. Every job included in the cost to complete calculations then has its job details and expense type data copied into the cost to complete files.



Take the Initiation option to see the Cost To Complete Initiation Screen.

Cost To Complete Initiation Screen



Take the Initiation option to see the Cost To Complete Initiation Screen.

```

JM360          Z1 - GB Demonstration Company  USER GBJBAAP1  6/02/98
                                           16:42:13

Cost To Complete Initiation

Budget to be used for standard cost calculations.....?.. BUD 1

Budget to be used to record cost to complete calculations..?..    _

To run CTC initiation for a single job, type the job.....?..        _

To run CTC initiation for a single CTC code, type the code.?..    _

F3=Exit  F4=Prompt
  
```

Fields:

Budget For Standard Cost Calculations

Enter the budget to hold the output of the standard cost calculations.

Budget For Recording Cost To Complete Calculations

Enter the budget you wish to hold the output of the cost to complete calculations. You will be warned if you choose a budget which has already been used for recording variations. This budget will be closed during initiation.

To Run CTC Initiation For A Single Job

If you want to run cost to complete initiation for a single job, enter that job here.

If you leave this field and the To Run CTC Initiation For A Single CTC Code field blank, then all those jobs which have a cost to complete code against them will be included in the cost to complete initiation.

To Run CTC Initiation For A Single CTC Code

If you want to run cost to complete initiation for all jobs with a certain cost to complete code, enter that code here.

If you leave this field and the To Run CTC Initiation For A Single Job field blank, then all those jobs which have a cost to complete code against them will be included in the cost to complete initiation.



Press **Enter** to submit the job.

Cost To Complete Maintenance



2/JCI

Use this option to record cost to complete calculation information. This is stored in the files which are prepared when you run Cost To Complete Initiation, and the information can then be used in cost to complete reporting.



Take the cost to complete Maintenance option to see the Cost To Complete Maintenance Selection Screen.

Cost To Complete Maintenance Selection Screen



Take the cost to complete Maintenance option to see the Cost To Complete Maintenance Selection Screen.

```

JM361                Z1 - GB Demonstration Company    User GBJBATD0    16/10/97
                                           13:51:02

Cost to Complete Maintenance

Job/sub-job/task...?.. 00MP21  ____  ____

All Levels..... 1  (0=No, 1=Yes)

By expense type..... 1  (0=No, 1=Yes)

-----
F3=Exit  F4=Prompt  F15=Labour  F16=Materials  F17=Other Direct
-----

5-24  SA  MW  KS  CL  IM  DM  II  STUD140  KB  PKH317S1
  
```

Fields:

Job/Sub-job/Task

Enter the job detail to which the cost to complete calculations are to apply.

If you set the All Levels field to '0', then the job detail you enter here must not be closed.

All Levels

0 - Entries made at this level are not to be applied to all lower levels.

1 - Entries made at this level are to be applied to all lower levels.

By Expense Type

0 - Maintenance for material and other direct costs is to be entered at job detail level.

1 - Maintenance for material and other direct costs is to be entered at expense type level.

Functions:

F15

Labour. This displays the Cost To Complete Labour Screen.

F16

Materials. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F16=Materials** you see the Material By Job Detail Screen. If it is '1', you see the Material By Expense Type Screen.

F17

Other Direct. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F17=Other Direct** you see the Other Direct By Job Detail Screen. If it is '1', you see the Other Direct By Expense Type Screen.



Tip: All three of these screens at first display the values in the cost to complete files. When you enter new values and calculations are performed, the original values on the screen are replaced by new ones, but the actual files are not updated until you select **F8=Update**.

Cost To Complete Labour Screen (F15)

This screen is displayed whether you selected expense types or not on the Cost To Complete Maintenance Selection Screen.



Select **F15=Labour** from any screen within the cost to complete Maintenance option to see the Cost To Complete Labour Screen.

```

JM361                Z1 - GB Demonstration Company      User GJBATD0      16/10/97
                                           13:51:18

Cost to Complete Maintenance - Labour

All levels..... 1 (0=No, 1=Yes)

Job/sub-job/task..... COMP21          CTC test

Method.....?.. 1

          This Level          Rolled Up
Estimated hours.....          .00          1480.00
Actual Hours.....          .00          200.00
Percentage inefficient..          .00          .00
Percentage efficient...          100.00          100.00
Standard hours achieved..          .00          200.00
Hours to complete.....          .00          1280.00
Cost to complete.....          .00          10240.00
Percentage complete.....          100.00          13.51

-----
F3=Exit F4=Prompt F8=Update F12=Previous F16=Materials F17=Other Direct
-----

9-27      SP      MW      KS CL IM DM II      STUD140      KB      PKH317S1
  
```

Fields:

Method

Enter the method you wish to use to calculate the cost to complete. Select from the following:

1 - Finish budget on time. Apply this method when the labour hours already recorded are a true representation of the actual work achieved, and you expect the job to continue at the same level of efficiency.

Hours to complete = estimated hours - actual hours.

2 - Continue at same level of efficiency. Apply this method when the standard hours achieved are different to the actual hours recorded, and you expect the efficiency achieved so far to continue at the same rate. You will have to enter by hand the standard hours achieved.

Hours to complete = ((estimated hours * actual hours)/standard hours achieved) - actual hours.

3 - Complete at standard rate. Apply this method when the standard hours achieved are different to the actual hours recorded, but you expect the level of efficiency to return to normal for the rest of the job. You will have to enter by hand the standard hours achieved.

Hours to complete = estimated hours - standard hours achieved.

4 - Input degree of inefficiency to apply to rest of job. Apply this method when you cannot calculate from history the degree of inefficiency to apply to the rest of the job. Instead, manual input is required. You must enter the standard hours achieved and the degree of inefficiency.

Hours to complete = (estimated hours - standard hours achieved) * percent inefficient.

5 - Input degree of efficiency to apply to rest of job. Apply this method when you cannot calculate from history the degree of efficiency to apply to the rest of the job. Instead, manual input is required. You must enter the standard hours achieved and the degree of efficiency.

Hours to complete = (estimated hours - standard hours achieved) * percent efficient.

6 - Enter hours to complete manually. Apply this method if you wish to enter hours to complete manually.



Note: Whether a field is input-capable or input-inhibited depends on the method you select here.



Note: Levels 2, 3, 4, 5 and 6 are not allowed if you set the All Levels field to '1' on the selection screen.

Estimated Hours

The current estimated hours are displayed.

Actual Hours

The actual hours input so far are displayed.

Percentage Inefficient

This is used in calculations for method 4. Enter the level of inefficiency to be applied to the rest of the job. This value cannot be negative.

Percentage Efficient

This is used in calculations for method 5. Enter the level of efficiency to be applied to the rest of the job. This cannot be negative.

Standard Hours Achieved

Enter the number of standard hours achieved so far. For example, if you have recorded 30 actual hours, it could be that only 25 hours' worth of output has been achieved, and in this case the standard hours would be 25.

This value cannot be negative, and must be greater than zero for method 2.

Hours To Complete

Enter manually the number of hours required to complete the job.

Cost To Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new cost to complete.

Percentage Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new percentage complete.

Functions:

F16

Materials. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F16=Materials** you see the Material By Job Detail Screen. If it is '1', you see the Material By Expense Type Screen.

F17

Other Direct. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F17=Other Direct** you see the Other Direct By Job Detail Screen. If it is '1', you see the Other Direct By Expense Type Screen.



When you have entered new values, press **Enter**. The fields are all refreshed, and display the new cost to complete details.

When you are sure the values are accurate, press **F8=Update** to record them.

Material By Job Detail Screen (F16)



Select **F16=Materials** from any screen within the cost to complete Maintenance option. As long as you set the By Expense Type field to '0' on the selection screen, you will see to see the Material By Job Detail Screen.

JM361	Z1 - GB Demonstration Company	User GBJBAAP1	11/02/98 12:20:12
Cost to Complete Maintenance - Materials			
Job/sub-job/task.....?.. <u>COMP21</u> ____ CTC test			
Cost to complete code... <u>1</u>			
All levels..... <u>1</u> (0=No, 1=Yes)			
Method.....?.. <u>1</u>			
	This Level	Rolled Up	
Budget.....	.00	10001.00	
Commitments.....	.00	800.00	
Actual cost.....	.00	230.00	
Standard cost achieved..	.00	.00	
Variance value.....	.00	.00	
Variance percentage....	.00	.00	
Cost to complete.....	.00	.00	-
F3=Exit F4=Prompt F8=Update F12=Previous F15=Labour F17=Other Direct			

Fields:

Method

Enter the method you wish to use to calculate the cost to complete. Select from the following:

1 - Based on commitment. Apply this method when the cost to complete is the outstanding value of job commitments. This can be applied at all lower levels.

Cost to complete = purchase commitments + inventory commitments.

2 - Based on original estimate. Apply this method when the cost to complete should be based on the original budgets. You will have to enter manually a variance percentage, a variance value, or a standard cost achieved. This can be applied at all lower levels.

3 - Enter revised estimate. This is for when you want to enter the revised estimate by hand. Apply this method when the materials already recorded are a true representation of the actual work achieved, and you expect the job to continue at the same level of efficiency.

Material costs to complete = estimated material costs - actual material costs.

Budget

This field displays the accumulation of all expense type budgets for the job detail that are categorised as material.

Commitments

This field displays the accumulation of all expense type commitments for the job detail that are categorised as material.

Actual Cost

This field displays the accumulation of all expense type actual costs for the job detail that are categorised as material.

Standard Cost Achieved

Enter the standard material costs achieved so far. For example, if you have recorded actual costs of 30 pounds, it could be that only 25 pounds' worth of output has been achieved, and in this case the standard costs would be 25.

This value cannot be negative, and must be greater than zero for method 2.

Variance Value

Enter the value variance of material cost against standard cost achieved. This value cannot be negative.

Variance Percentage

Enter the percentage variance of material cost against standard cost achieved. This value cannot be negative.

Cost To Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new cost to complete.

Functions:

F15

Labour. This displays the Cost To Complete Labour Screen.

F17

Other Direct. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F17=Other Direct** you see the Other Direct By Job Detail Screen. If it is '1', you see the Other Direct By Expense Type Screen.

Other Direct By Job Detail Screen (F17)



Select **F17=Other Direct** from any screen within the cost to complete Maintenance option. As long as you set the By Expense Type field to '0' on the selection screen, you will see the Other Direct By Job Detail Screen.

JM361	Z1 - GB Demonstration Company	User GBJBAP1	11/02/98 12:22:16
Cost to Complete Maintenance - Other Direct			
Job/sub-job/task.....?.. <u>COMP21</u> ____ CTC test			
Cost to complete code... <u>1</u>			
All levels..... <u>1</u> (0=No, 1=Yes)			
Method.....?.. <u>1</u>			
	This Level	Rolled Up	
Budget.....	.00	16000.00	
Commitments.....	.00	800.00	
Actual cost.....	.00	230.00	
Standard cost achieved..	.00	.00	
Variance value.....	.00	.00	
Variance percentage....	.00	.00	
Cost to complete.....	.00	.00	
F3=Exit F4=Prompt F8=Update F12=Previous F15=Labour F16=Materials			

Fields:

Method

Method. Enter the method you wish to use to calculate the cost to complete. Select from the following:

1 - Based on commitment. Apply this method when the cost to complete is the outstanding value of job commitments. This can be applied at all lower levels.

Cost to complete = purchase commitments + inventory commitments.

2 - Based on original estimate. Apply this method when the cost to complete should be based on the original budgets. You will have to enter manually a variance percentage, a variance value, or a standard cost achieved. This can be applied at all lower levels.

3 - Enter revised estimate. This is for when you want to enter the revised estimate by hand. Apply this method when the other direct costs already recorded are a true representation of the actual work achieved, and you expect the job to continue at the same level of efficiency.

Other direct costs to complete = estimated other direct costs - actual other direct costs.

Budget

This field displays the accumulation of all expense type budgets for the job detail that are categorised as other direct.

Commitments

This field displays the accumulation of all expense type commitments for the job detail that are categorised as other direct.

Actual Cost

This field displays the accumulation of all expense type actual costs for the job detail that are categorised as other direct.

Standard Cost Achieved

Enter the standard other direct costs achieved so far. For example, if you have recorded actual costs of 30 pounds, it could be that only 25 pounds' worth of output has been achieved, and in this case the standard costs would be 25.

This value cannot be negative, and must be greater than zero for method 2.

Variance Value

Enter the value variance of other direct cost against standard cost achieved. This value cannot be negative.

Variance Percentage

Enter the percentage variance of other direct cost against standard cost achieved. This value cannot be negative.

Cost To Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new cost to complete.

Functions:

F15

Labour. This displays the Cost To Complete Labour Screen.

F16

Materials. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F16=Materials** you see the Material By Job Detail Screen. If it is '1', you see the Material By Expense Type Screen.

Material By Expense Type Screen (F16)



Select **F16=Materials** from any screen within the cost to complete Maintenance option. As long as you set the By Expense Type field to '1' on the selection screen, you will see the Material By Expense Type Screen.

```

JM361                Z1 - GB Demonstration Company    User GBJBATD0    16/10/97
                                      13:51:29

Cost to Complete Maintenance - Material

All levels..... 1 (0=No, 1=Yes)

Job/sub-job/task..... COMP21                CTC test

      Variance      Variance      Standard cost
      Mth?      %      value      achieved      Cost to complete      All
      INV      █      .00      .00      .00      .00      levels
      MAT      1      .00      .00      .00      .00      (0/1)
                                      1
                                      1

-----
F3=Exit  F4=Prompt  F8=Update  F12=Previous  F15=Labour  F17=Other Direct
-----

11-8      SP      MW      KS  CL  IM  DM  II      STUD140  KB  PKH317S1
  
```

Mth

Enter the method you wish to use to calculate the cost to complete. Select from the following:

1 - Based on commitment. Apply this method when the cost to complete is the outstanding value of job commitments. This can be applied at all lower levels.

Cost to complete = purchase commitments + inventory commitments.

2 - Based on original estimate. Apply this method when the cost to complete should be based on the original budgets. You will have to enter manually a variance percentage, a variance value, or a standard cost achieved. This can be applied at all lower levels.

3 - Enter revised estimate. This is for when you want to enter the revised estimate by hand. Apply this method when the materials already recorded are a true representation of the actual work achieved, and you expect the job to continue at the same level of efficiency.

Material costs to complete = estimated material costs - actual material costs.

Variance Percentage

Enter the percentage variance of material cost against standard cost achieved. This value cannot be negative.

Variance Value

Enter the value variance of material cost against standard cost achieved. This value cannot be negative.

Standard Cost Achieved

Enter the standard costs achieved so far. For example, if you have recorded actual costs of 30 pounds, it could be that only 25 pounds' worth of output has been achieved, and in this case the standard costs would be 25.

This value cannot be negative, and must be greater than zero for method 2.

Cost To Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new cost to complete.

All Levels

0 - Do not apply to lower levels.

1 - Apply to all levels.

Functions:

F15

Labour. This displays the Cost To Complete Labour Screen.

F17

Other Direct. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F17=Other Direct** you see the Other Direct By Job Detail Screen. If it is '1', you see the Other Direct By Expense Type Screen.

Other Direct By Expense Type Screen (F17)



Select **F17=Other Direct** from any screen within the cost to complete Maintenance option. As long as you set the By Expense Type field to '1' on the selection screen, you will see to see the Other Direct By Expense Type Screen.

```

JM361                Z1 - GB Demonstration Company    User GBJBATD0    16/10/97
                                      13:51:37

Cost to Complete Maintenance - Other Direct

All levels..... 1 (0=No, 1=Yes)

Job/sub-job/task..... COMP21                CTC test

      Variance      Variance      Standard cost
      Mth?      %      value      achieved      Cost to      All
      CON      |      .00      .00      .00      .00      levels
      EXP      -      .00      .00      .00      .00      (0/1)
      MAN      -      .00      .00      .00      .00      1
      P/H      -      .00      .00      .00      .00      1

-----
F3=Exit F4=Prompt F8=Update F12=Previous F15=Labour F16=Materials

-----
11-8      SP      MW      KS CL IM DM II      STU0140      KB      PKH317S1
  
```

Mth

Method. Enter the method you wish to use to calculate the cost to complete. Select from the following:

1 - Based on commitment. Apply this method when the cost to complete is the outstanding value of job commitments. This can be applied at all lower levels.

Cost to complete = purchase commitments + inventory commitments.

2 - Based on original estimate. Apply this method when the cost to complete should be based on the original budgets. You will have to enter manually a variance percentage, a variance value, or a standard cost achieved. This can be applied at all lower levels.

3 - Enter revised estimate. This is for when you want to enter the revised estimate by hand. Apply this method when the other direct costs already recorded are a true representation of the actual work achieved, and you expect the job to continue at the same level of efficiency.

Other direct costs to complete = estimated other direct costs - actual other direct costs.

Variance %

Enter the percentage variance of other direct cost against standard cost achieved. This value cannot be negative.

Variance Value

Enter the value variance of other direct cost against standard cost achieved. This value cannot be negative.

Standard Cost Achieved

Enter the number of standard direct costs achieved so far. For example, if you have recorded actual costs of 30 pounds, it could be that only 25 pounds' worth of output has been achieved, and in this case the standard costs would be 25.

This value cannot be negative, and must be greater than zero for method 2.

Cost To Complete

When you have entered new values and press **Enter**, the fields are all refreshed, and this field displays the new cost to complete.

All Levels

0 - This level only.

1 - All levels.

Functions:

F15

Labour. This displays the Cost To Complete Labour Screen.

F16

Materials. The screen displayed here depends on the setting of the By Expense Type field on the selection screen. If it is '0', then when you select **F16=Materials** you see the Material By Job Detail Screen. If it is '1', you see the Material By Expense Type Screen.