

-
-
-
-
-

Chapter 3

Contracts Database



Contracts Maintenance



1/SSC

Use this option to set up and maintain the details of all service contracts and quotations for contracts.

You can use this option on a regular basis to add, amend or delete contracts and quotations.

Concepts

A contract describes the terms of maintenance for one or more pieces of equipment installed at one or more of a customer's sites.

A contract has a start date, and normally an end date, although it can be a never-ending contract. Each piece of equipment covered by a contract has an inclusion date (which can be later than the contract start date), and may have a removal date (if it is removed from the contract before the contract end date).

A contract is always associated with a single customer account, although it can be multi-site, that is, can cover pieces of equipment which are installed at several sites for that account.

Description

A contract is uniquely identified by the combination of the contract number, contract type, and start date.

A contract consists of a number of components:

- Contract header: the terms for the contract.
- Contract equipment: the pieces of equipment covered.
- Maintenance visit schedule: the schedule by service period of planned maintenance visits.

For each piece of equipment on the contract, the maintenance visit schedule can be defined. You can either set this up manually, or enter a scheduled visit profile for the contract, the model itself, or the model group. This profile enables the system to generate visits automatically.

A special price can be defined for any piece of equipment on a contract, this price overriding the standard price calculated within contract invoicing.

New contracts will have a status of pending start date. This status is changed to active by the day end or the contract updating procedure, provided that the contract start date has been reached.

Contract quotations are created in exactly the same way as true contracts, but are given quotation status by means of a special function key. The same function key is used to convert the quotation into a true contract when the customer accepts the quotation.

Implications

The data set up within this function is used:

- To maintain a complete contract's database, enabling identification of a piece of equipment's contract status when a service call is placed.
- To facilitate automatic invoicing of contracts for rental, meterage or service, in advance, in arrears, or by maintenance visit.
- To determine the pricing and invoicing procedure for engineer visits to pieces of equipment.

Contract Maintenance Initial Screen



Select Contracts Maintenance.

SS024	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		17:05:47
Contract Maintenance			
Contract Number..... _____			
Contract Type.....?.. _____			
Account Number...?.. G001 _____			
Account Address..... 000 _____			
F3=Exit F4=Prompt			
6-24 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Contract Number

If the account code and address codes are not entered this must already exist.

If entered by itself, a list of all contracts with this contract number will be displayed, in contract type and start date sequence.

Contract Type

Enter an existing contract type file.

Must be entered in conjunction with a contract number. This combination must already exist on the contract file, if account and address codes are not entered.

If only contract number and type are entered, all relevant contracts will be displayed in start date sequence.

Account Number

Must exist on the customer master file.

If entered alone, a list of all address codes for this account number will be displayed.

If an address code is selected, a list of all contracts for this account number and address code will be displayed in contract type and start date sequence.

Account Address

Must be entered in conjunction with an account number. This combination must exist on the additional details file.

If only account number and address code are entered, all contracts will be displayed in contract type and start date sequence.



Note: To enter a new contract directly from this screen, all four input fields must be entered.



Press **Enter** to display the first Contract Selection screen.

Contract Selection Screen



To display this screen do not specify a contract and press **Enter** on the Contract Maintenance Initial screen.

Use this screen to select any contract from a list for that customer.

```
SS614          Z1 - GB Demonstration Company    USER GBJBATD0  24/09/97
               "BRUM" TRAINING & SERVICE BRANCH  17:06:14
Contract Selection

Account Number..... GC01          Account Address..... 000
Account Name..... Reeves Chemist's

n  Contract.. Contract Type.....      Contract Start Date.
  0000101    B01          S&A Adv: Basic cover    24/09/97

Enter a selection or new Contract No./Type/Dt  _____ 0/00/00
1=Select
F8=Exit F4=Prompt F12=Previous

9-3      SA      MW      KS      CL      IM      DM      II      EDN400A      KB      PKH317S1
```

Fields:

N

Select. Enter 1 against the contract to be selected for maintenance.

Contract No

To maintain an existing contract, enter the number of the contract.

To set up a new contract, leave the contract number blank and only enter the contract type and date, and the system will generate a new contract number.

Contract Type

Enter the contract type of the contract to be maintained or set up.

Contract Dt

Enter the contract start date of the contract to be maintained or set up.



Press **Enter**.

Contract Header Maintenance Screen



In addition mode, this screen is displayed after the Contracts Maintenance Initial Screen, or the Contract Selection Screen.

In update mode, this screen is displayed when you press **F12=Previous** from the Contract Equipment Maintenance Screen (which follows from the Contract Maintenance Selection Screen).

SS035		Z1 - GB Demonstration Company		USER GBJBATD0	24/09/97
		"BRUM" TRAINING & SERVICE BRANCH			17:09:04
Contract Header Maintenance		UPDATE			
Account Number.....	GC01	000	Reeves Chemist's		
Contract Number.....	0000101	Alt. Cont. No.		Version.	
Contract Type.....?	B01	S&R Adv: Basic cover	Status. Pending start date		
Contract Start Date..	24/09/97	End Date. 23/09/98	Invoice Start. 0/00/00		
Tot. Contract Value...		Header price...	120.00		
Duration.....	12	Mantle Code...?			
Customer Order Ref 1..		Order Ref Date..	0/00/00		
Customer Contact.....	Michael Wello	Telephone No....	0121 448 5273		
Renew Contract (1/0)..	1	Region....	WM West Midlands		
Non-posting Invoices..	0	Header level pricing (1/0)..	1		
Salesman Code.....?		Invoice Summ/Det Form (1/0)...	0		
Invoice Destination...		Direct Debit (1/0).....	0		
Contract Inv. Bill to...		Header currency (1/0).....	1		
Job Invoice Bill to...					
F3=Exit F4=Prompt F5=Re-Value	F12=Previous F14=Service				
F16=Billing maint. F18=Conditions maint					
F21=Text F22=Quotation only	F23=Invoice enquiry				
6-51	SR	MW	KS	CL	IM DM II EDN400A KB PKH317S1

Fields:

Alt Cont No

Alternative contract number. Enter up to seven alphanumeric characters for an alternative contract number.

Version

Enter up to five alphanumeric characters for a version number.

Contract Type

Enter an existing contract type. You can only amend this when the contract has a status of pending start.

Status

This field displays the contract's status. This field is maintained by the system. Status descriptions are retrieved from the Codes/Parameter File Maintenance option, parameter type CHST.

The status can be:

P - Pending start.

Q - Quotation.

A - Active.

E - Expired.

D - Deleted.

Contract Start Date

Enter the start date for the contract. You can only maintain this when the contract status is pending start. The contract will be made active by the Day End Routines option when the start date is reached.

The contract can be backdated.

End Date

Enter the date on which the contract is to end. If you leave the field blank, then the system will calculate it as the start date plus the contract duration.

If the contract duration is zero, the system will make this a rolling contract with an end date of 99/99/99.

If you overwrite the original end date with an earlier date, the system assumes the contract is ending early.

This date is used by the options Contract Updating and Contract Credit Selection as the basis for calculating any credits that may be due.

Invoice Start

This field displays the date on which the first invoice for the contract was raised.

Tot Contract Value

This field displays the total value of the fixed service charges, entered in the Contract Equipment Maintenance Contract Conditions Window for each contract equipment line. It is the annualised, or term's, nominal value of the service elements of a contract.

No value can be displayed in advance of the contract start date, or of the effective date(s) for the equipment prices.

The total does not necessarily reflect the invoice value of the contract, if equipment is added or deleted during the course of the billing term, and this field is not used for pricing or invoicing the contract if header pricing applies.



Tip: Note that **F5=Re-value** updates this field's value.

Header Price

This displays the header, or block, price for the contract, as entered in the Contract Header Maintenance Contract Conditions Window (**F18=Conditions Maintenance**). This is the price that will be invoiced for the contract term.

The field is only displayed if the Header Level Pricing field (further down this screen) is set to 1.

Duration

Enter the contract duration, in months, up to a maximum of 120.

The initial value defaults from the contract type. This field can only be changed if the contract status is pending start.

If the duration is zero, the system assumes it is a rolling, or never-ending contract, with an end date of 99/99/99.

Mantle Code

Enter an existing mantle code of up to five alphanumerics.

Codes are validated against the parameter type MANT on the Inventory Descriptions file.

The mantle code is used in the Global Price Update option, to identify a group of contracts for a percentage price change.

Customer Order Ref 1

This field, and the Order Ref Date, are mandatory if the Customer Ref. For Contracts field in the Customer Additional Service Details Maintenance option is set to 1.

Enter up to 20 alphanumerics as the customer's order reference.

Order Ref Date

This field, and the Customer Order Ref 1, are mandatory if the Customer Ref. For Contracts field in the Customer Additional Service Details Maintenance option is set to 1.

Enter a valid date (DDMMYY) for the customer's order.

Customer Contact

Enter the name of the contact to whom enquiries relating to this contract should be addressed. The contact entered in the Contact field in the Customer Additional Service Details option is the default for this field.

Telephone No

Enter the telephone number to which enquiries relating to this contract should be directed. The telephone number entered in the Service Telephone Number field in the Customer Additional Service Details option is the default for this field.

Renew Contract

Enter one of the following:

0 - The contract will never be renewed.

1 - The contract will be renewed with effect from the end date on the contract header.



Note: This indicator has no effect if the contract end date is set to 99/99/99: a rolling or never-ending contract.

Region

The customer's region is displayed, as set up in the Region field in the Customer Additional Service Details Maintenance option.

Non-Posting Invoices

Enter one of the following:

0 - Invoices produced for the contract will be posted to the ledgers.

1 - The contract will function as normal, but invoices produced will stay within the Service Management system and will not post to the ledgers.

Header Level Pricing

Enter one of the following:

0 - If no price has been entered into the Contract Header Maintenance Contract Conditions Window, the contract is priced from the contract rates file, for each of the contract equipment lines.

If a price has been entered into the Contract Header Maintenance Contract Conditions Window, that price is defaulted to each Contract Equipment Maintenance Contract Conditions Window for equipment added to the contract.

1 - The Contract Header Maintenance Contract Conditions Window must be completed before you can update the contract header: enter only a fixed service charge. The contract will be priced based on the price in the Contract Header Maintenance Contract Conditions Window.

Any prices entered into the Contract Equipment Maintenance Contract Conditions Window are ignored by the pricing program. They are used for comparison purposes: their total is displayed in the Tot Contract Value field.

Estimates Allowed

The default comes from the System Parameters File Maintenance option.

0 - No metered charges will be made.

1 - Invoices based on estimated meter readings will be produced.

Number Of Estimates

Enter the number of consecutive estimates which are allowed for billing. Valid entries are from 1 to 999.

Pool Contracts

This is only valid for contracts which have meterage billing parameters defined on the contract type.

0 - Non-Pooled. Non-pooled contracts are assessed for invoicing on the basis of the individual machine. If the number of copies/vends is less than minimum, then minimum is charged; if the number exceeds the minimum, then the additional copies/vends are charged.

1 - Pooled. Pooled contracts are assessed for invoicing on the basis of the aggregated minima of all the machines on the contract. That is, machines which have an excess of copies/vends can offset the total excess against those machines which have actual usage which is less than the minimum.

Tiled Contracts

This is only valid for contracts which have meterage billing parameters defined on the contract type.

0 - Non-tiled.

1 - Tiled. Tiled contracts are a special form of pooled contract. They can only be used if pooled contracts are being used. Unlike pool contracts, which have a

defined termination date, tiled contracts allow the termination date to be extended for each new item of equipment added to the contract. The new termination date is calculated by adding the contract term to the inclusion date of the machine which has been added.

Salesman Code

Enter an existing salesman.

Codes are set up as parameter type SN on the Inventory Descriptions file.

The salesman is used for memo purposes only.

Invoice Summ/Det Form

For future development.

Invoice Destination

Enter the customer's account. This defaults in, but can be changed to any existing account.

Untitle)

Address code. Enter a valid address code for the corresponding customer.

This is the address that will be printed on all invoices and credit notes for the contract.

Direct Debit

This field is for future development.

Contract Inv Bill To

If you wish contract invoices to go to a different customer, enter the customer here and the relevant address in the next field.

Untitled

Contract Invoice Bill Address. If you wish contract invoices to go to a different customer or address, enter the customer in the previous field and the relevant address here.

Header Currency

Enter one of the following:

0 - Equipment on the contract will be invoiced in the currency of the site where the equipment is installed.

1 - All equipment on the contract will be invoiced in the currency of the account on the contract header.



Note: Some of the fields on the header screen are only displayed if the function they relate to has been selected for the contract type.

Job Invoice Bill To

If you wish job invoices to go to a different customer, enter the customer here and the relevant address in the next field.

Untitled

Job Invoice Bill Address. If you wish job invoices to go to a different customer or address, enter the customer in the previous field and the relevant address here.

Functions:

F5

Re-value. Totals the nominal value of the fixed service charges for all the contract lines and displays the new value in the Tot. Contract Value field on the contract header.

F8

Update. (This key is only displayed when billing/conditions maintenance has been completed.)

F14

Service parameters window.

F16

Billing parameters window.

F18

Contract conditions window.

F21

Text entry/update.

F22

Quotations Only/Accept Contract. This toggles between changing pending start contracts to quotations and vice versa.

F23

Invoice enquiry screen.

Service Parameters Window (F14)



To display this window select **F14=Service** on the Contract Header Maintenance screen.

SS035	Z1 - GB Demonstration Company	USER GBJBAT00	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		17:09:04
Contract Header Maintenance		UPDATE	
Account Number.....	GC01	000	Reeves Chemist's
Contract Number.....	0000101	Alt. Cont. No.	Version.
Contract Type.....?	B01	S&R Adv: Basic cover	Status. Pending start date
Contract Start Date..	24/09/97	End Date. 23/09/98	Invoice Start. 0/00/00
Tot. Contract Value...		Header price..	120.00
Duration.....	12	Mantle Code..?	
Customer Order Ref 1..		Order Ref Date..	0/00/00
Customer Contact.....	Michael Wello	Telephone No....	0121 448 5273
Renew Contract (1/0)..	1	Region....	WM West Midlands
Service Parameters			
Response hours..... 16			
Schedule visit profile..			
Allow service cover when contract pending (1/0). 1			
Use start date rates.... 1 On,Until.... 0/00/00			
Global Price Code..?....			
F4=Prompt F8=Update F12=Previous			
F16=Billing maint. F18=Conditions maint			
F21=Text F22=Quotation only F23=Invoice enquiry			
16-30 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Response Hours

The value defaults from the contract type, but may be overwritten. Enter up to five numerics (hhh:mm) to set the response time for the contract. The response will apply to all contract lines, unless a line is given its own special response time.

Scheduled Visit Profile

Leave blank, or Enter a valid scheduled visit profile (SVP) code of up to three alphanumeric; or prompt for the code selection window.

The profile generates the visits to each piece of equipment on a contract. The system selects the profile according to the following hierarchy:

1. Use the SVP on the contract header.
2. If there is none, use the SVP for the model.
3. If there is none, use the SVP for the model group.
4. If there is none, use the SVP from the company profile.
5. If there is none, do not generate visits.

As long as an SVP is found, the system generates visits for the equipment line on the contract, using the first SVP found, when you take option 8 on the Contract Equipment Maintenance Screen.

When an SVP is entered in the Service Parameters Window, the **F14=Schedule Override** key appears, to enable you to edit the SVP details.

Use Scheduled Visit Override at Renewal

Enter one of the following:

0 - At contract renewal, the SVP field will be blank. A valid SVP may be entered, but if left blank, the SVP hierarchy will determine the equipment visits to be generated on the renewed contract.

1 - The *OV amendments to the SVP will be used when the contract is renewed and equipment visits are generated.

Allow Service Cover When Contract Pending

This defaults from the System Parameters File Maintenance (screen 1 of 5), but may be overwritten. Enter one of the following:

0 - Contract cover will only be effective on and after the contract start date.

1 - All calls to the equipment to be included on the contract, logged prior to the contract start date (while the contract has the status pending), will be treated as though the contract cover was effective; this will be reflected on the call detail screen.

Use Start Date Rates

Defaults from the contract type but may be overwritten. Enter one of the following:

1 - The labour rates and parts prices effective on the contract start date will be used to price any chargeable work carried out on the equipment covered by the contract.

0 - The price lists used for chargeable work will be those effective at the date the work is carried out.

Or, Until

If the Use Start Date Rates field is 1, this field must be 0/00/00.

If the Use Start Date Rates field is 0, enter a valid date (DDMMYY): the labour and parts price lists used for chargeable work, effective at the contract start date, will only be used until the date entered. After this date, the price lists used will be those effective on the date the work was carried out.

Global Price Code

Enter an existing global price. The code is used in the Global Price Update option, to select contracts for inclusion in the price revision then being applied.

These codes are set up under the parameter type GLPR, in the Codes/Parameter File Maintenance option.

Functions:

F14

Schedule Override. This enables the scheduled visit profile to be changed for the contract. The Scheduled Visit Profile Maintenance Detail Screen is displayed.



If you update the SVP, select **F8=Update**. Then regenerate equipment visits using the revised SVP, by taking option 8 for each record on the Contract Equipment Maintenance Detail Screen.

The SVP code, for a contract where the SVP has been edited, will now be displayed as *OV: to indicate that a standard SVP code has been overridden.

Billing Parameters Window (F16)



To display this window select **F16=Billing Maintenance** on the Contract Header Maintenance screen.

```
SS035          Z1 - GB Demonstration Company    USER GBJBATD0  24/09/97
               "BAUM" TRAINING & SERVICE BRANCH  17:09:40
Contract Header Maintenance      UPDATE

Account Number..... GC01      000 Reeves Chemist's
Contract Number..... 0000101    Alt. Cont. No.      Version.
Contract Type.....?.. 001 S&R Adv: Basic cover    Status. Pending start date
Contract Start Date.. 24/09/97  End Date. 23/09/98  Invoice Start. 0/00/00
Billing Parameters
Set all Next pricing cycle to dates to: 0/00/00
Set all Next pricing cycle from start days to: 0

Billing type:      Term  Freq  Adv/Visit/Ann  Next pricing cycle
                  (mths) (mths) (0/1/2)      From      To
Fixed Service Chrg.: 12   3    0 (0/1/2)    24/09/97  23/09/98
Rental Charge.....: 12   3    0 (0/1/2)    24/09/97  23/09/98

F8=Update  F12=Previous
F3=Exit  F4=Prompt  F5=Re-Value  F8=Update  F12=Previous  F14=Service
F16=Billing maint.  F18=Conditions maint

10-46  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
```

Fields:

Set All Next Pricing Cycle To Dates To

The system will use the end date of the first contract term, as standard.

Only enter a valid date (DDMMYY) if the first term of the contract is to be shorter than the standard term. This might occur where a contract has to meet the user requirement for it to coincide with the start of the user's financial year.

Set All Next Pricing Cycle From Start Days To

The pricing cycle start day - the day on which the contract first invoices - defaults either to the day on which the contract starts, or to the first of the following month, if defined in System Parameters maintenance (see screen 4 of 5).

The entry of a start day allows the invoice day to be changed to any day following the contract start day for up to one month. If the day entered is less than the contract start day it will be assumed to be the following month.

Line 1 Fixed Service Charge - Term

The term is expressed in months; it defaults to a value of 12; valid entries are from one to 120 (10 years).

The term is the number of months within the contract's duration for which the contract price is protected from change, and the number of periods covered by the Fixed Service Charge.

Frequency

The frequency of invoicing expressed in months. Valid entries are between 0 and the maximum number in the term, and must be equally divisible into the term. For example:

1 - Monthly

3 - Quarterly

12 - Annual invoicing in a 12 month term.

Enter 0 if Adv/Visit/Arr is 1.

Adv/Visit/Arr

Advance, visit or arrears billing. This defaults to the value in the Invoice Schedule field on the contract type. Enter one of the following:

0 - Invoice in Advance; release date is the start of the invoice period: the invoice for each invoice term is issued before the term starts.

1 - Invoice each scheduled PM visit; this is a Job Invoice, raised as the result of the engineer's Technical Report for the visit. Invoice Freq must be 0.

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes, but should have been priced in advance of the contract start date.

Next Pricing Cycle From..(Date)

Display only. This value is maintained by the system.

Next Pricing Cycle To..(Date)

This defaults to the Next Pricing Cycle From date, plus the billing term. It can be changed when the contract is first entered.

The To date is the end of the contract term and can therefore cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term will not take effect until after the Next Pricing Cycle To date has been passed.

Line 2 Rental Charge - Term

The term is expressed in months, and defaults to a value of 12. Acceptable entries are from one to 120 (10 years).

The term is the number of months within the contract duration for which the rental price is protected from change and the number of periods covered by the Rental Charge.

Frequency

The frequency of invoicing expressed in months. Valid entries are between 0 and the maximum number in the term, and must be equally divisible into the term. For example:

1 - Monthly

3 - Quarterly

12 - Annual invoicing in a 12 month term.

Adv/Visit/Arr

Advance, visit or arrears billing. Defaults to the value in the Invoice Schedule field on the contract type. Enter one of the following:

0 - Invoice in advance; release date is the start of the invoice period: the invoice for each invoice term is issued before the term starts.

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Next Pricing Cycle To

This date defaults to the Next Pricing Cycle From date plus the billing term. It can be changed when the contract is first entered.

The To date is the end of the contract term and can therefore cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term will not take effect until after the Next Pricing Cycle To date has been passed.

Line 3 Pre-Billing Charge - Frequency

The frequency of invoicing expressed in months. Valid entries are between 0 and the maximum number in the term, and must be equally divisible into the term. For example:

1 - Monthly

3 - Quarterly

12 - Annual invoicing in a 12 month term.

Adv/Visit/Arr

Advance, visit or arrears billing. The initial value defaults to that set up on the contract type file. Enter one of the following:

0 - Invoice release date is the start of the invoice period.

2 - Invoice release date is the end of the invoice period.

Next Pricing Cycle To

This date defaults to the Next Pricing Cycle From date, plus the billing term. It can be changed when the contract is first entered.

The To date is the end of the contract term and can therefore cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term will not take effect until after the Next Pricing Cycle To date has been passed.

Line 4 Interim Charge - Frequency

The frequency of invoicing expressed in months: 1 equals monthly invoices, 12 equals annual invoicing in a 12 month term.

Acceptable entries are between one and the maximum number in the term, and must be equally divisible into the term.

Next Pricing Cycle To

This date defaults to the Next Pricing Cycle From date, plus the billing term. It can be changed when the contract is first entered.

The To date is the end of the contract term and can therefore cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term will not take effect until after the Next Pricing Cycle To date has been passed.

Line 5 Reconciliation Charge - Term

The term is expressed in months and defaults to a value of 12. Acceptable entries are from one to 120 (10 years).

The term is the number of months after which a reconciliation of the number of machine cycles (for example, copies or vends) will be verified against the cycles which have been billed in advance; or, at an interim stage, as a result of an estimated or customer advised meter reading.

Next Pricing Cycle To

This date defaults to the Next Pricing Cycle From date, plus the billing term. It can be changed when the contract is first entered.

The To date is the end of the contract term and can therefore cover one or more invoices, depending on the invoice frequency within the term.

Contract price increases during the term will not take effect until after the Next Pricing Cycle To date has been passed.



Note: Only the billing parameters selected for the contract type are displayed.

Contract Header Maintenance Contract Conditions (F18)



To display this window select **F18=Conditions Maintenance** on the Contract Header Maintenance Screen For a header priced contract, only the fixed service charge is displayed.

```
SS035          Z1 - GB Demonstration Company   USER GBJBATD0  24/09/97
               "BAUM" TRAINING & SERVICE BRANCH 17:10:08
Contract Header Maintenance      UPDATE

Account Number..... GC01      000 Reeves Chemist's
Contract Number..... 0000101    Alt. Cont. No.      Version.
Contract Type.....?.. B01 S&R Adv: Basic cover  Status. Pending start date
Contract Start Date.. 24/09/97   End Date. 23/09/98 Invoice Start. 0/00/00
Contract Conditions
Cover type.?.  B01 Eff.Date: 24/09/97   GBP
Fixed Service Charge... 120.00000

F8=Update F10=Add F12=Previous

11-20 SA MW KS CL IM DM II EDN400A KB PKH317S1
```

Fields:

Cover Type

Enter a header level cover type as required.

Eff Date

This defaults to the contract start date, but may be overwritten with a later, valid date (DDMMYY).

Fixed Service Charge

Enter the value to be charged; it will be applied for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option (see screen 1 of 5).

Charges entered at Header level will be applied to all machine lines, unless a special machine line condition is set up. If the Header details are subsequently amended, the conditions for each machine should be checked, and amended if necessary.



Note: Month/term processing must not be changed after initial system set up.

Fixed Visit Charge

Enter the value to be charged, for each visit made.

Charges entered at Header level will be applied to all machine lines, unless a special machine line condition is set up. If the Header details are subsequently amended, the conditions for each machine should be checked and amended, if necessary.

Fixed Rental Charge

Enter the value to be charged; it will be applied for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option (see screen 1 of 5).

Charges entered at Header level will be applied to all machine lines, unless a special machine line condition is set up. If the Header details are subsequently amended, the conditions for each machine should be checked, and amended if necessary.



Note: Month/term processing must not be changed after initial system set up.

Pre-Billing Value/Volume

The contract type determines whether this entry is for a monetary value or for a number of copies or vends.

Enter the value or quantity which has been agreed as the predetermined monthly value for copies or vends.

This field can only be used if the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option is set to month.

The header level charge will be applied to all machines on the contract and cannot be changed on the conditions for individual machine lines.



Note: Month/term processing must not be changed after initial system set up.

Minimum Volume

Enter a numeric value for the agreed minimum number of copies/vends which will be invoiced each month.

This field can only be used if the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option is set to month.

The minimum, entered at Header level, will be applied to all machine lines unless changed in the contract Conditions on a machine line.



Note: Month/term processing must not be changed after initial system set up.

Copies in Rental

Enter a numeric value, for the number of copies per month which are to be included in the rental charge.

Free Copies

Enter the number of free copies allowed on each monthly billing.

Meter 1 - Band Volume To

Enter a numeric value for the maximum number of copies to which the price for the band applies.

The volume for band 1 must not be less than the minimum volume.

Meter 1 - Band Price Per Copy

Enter the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence/cents by setting the currency multiplier on the system parameter file.

Meter 2 - Band Volume To

Enter a numeric value for the maximum number of copies to which the price for the band applies.

Meter 2 - Band Price Per Copy

Enter the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence/cents by setting the currency multiplier on the system parameter file.

If meterage is specified, at least one price band must be entered for meter 2 even if not used in this contract.

Functions:

F10

Add record.



Note: Only the contract conditions selected for the contract type will be displayed.



Page up and down to display more screens of differently dated contract conditions.



To display this screen select **F23=Invoice Enquiry** on the Contract Header Maintenance Screen.

```

SS645                      Demonstration Company          USER BRERETM          18/11/93
                           CENTRAL BRANCH                  13:32:40

Contract Maint Invoice Enquiry

Account Number..... C03          000 Jones and Crossland Ltd.
Contract Number..... 0000115     Alt. Cont. No:          Version:
Contract Type..... B01 Basic cover      Status: Active
Contract Start Date. 6/04/93      End Date: 99/99/99      Invoice Start: 6/04/93

Total Revenue.....:          179.19
Volume after last Interim/Reconciliation...

Invoice
Number Type          Value          Period
                    From          To
1500641 01          150.00          6/04/93  5/04/94
1500641 02           4.17          6/04/93  5/05/93

```

Fields:

All Fields

Display only: Total Revenue for the Contract, with Invoice records (that is, Inv No, Type, Value, Period from, Period to) to provide the detail.

Contract Equipment Maintenance Detail Screen



To display this screen select **F8=Update** once the Contract Header Maintenance screen is set up.

The equipment you can select can be listed in the lower half of the screen. If highlighted, the equipment is already included in a pending or active contract.

SS025	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		17:07:42
Contract Equipment Maintenance			
Account Number..... GC01	Contract Start Date.. 0000101 B01	24/09/97	
Position to Serial Number...	000 Reeves Chemist's		
Inst.Adr Loc Model	Serial	Stat Inc. Dt. Remov dt R.Hrs Ust	
GC01 000 WA10	WAN0001	Pen 24/09/97 0/00/00	0
Select by Account No...?.. GC01 Addr. 000 Model..?. WA10			
Loc Model	Serial	Loc Model	Serial
_ 000 WA10	WAN0002		
_ 000 WA10	WAN0003		
1=Add 2=Conditions 3=Peripherals 4=Invoice history 5=Meter history			
F3=Exit F4=Prompt F12=Previous F21=Text F23=More options			
8-2 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Position to Serial Number

Enter a valid serial number of up to 15 alphanumerics.

If there are more machines on the contract than can be displayed on the screen, entry of a known serial number for the contract will enable the cursor to be quickly displayed on that machine for selection.

Untitled

Select. This screen is divided into two, the top half lists machines selected to be on the contract, and the lower half lists those machines available for selection. Both halves have select fields.

The select fields in the lower half of the screen only accepts the option 1, and selects a machine to be added to the top half of the screen.

The select fields in the top half of the screen accept the following options:

2 - Conditions: displays a window for the entry of charges to be applied to the machine, which will override the contract header conditions. If Header Level Pricing applies to the contract, any values keyed in will be ignored by the Pricing program.

3 - Peripherals: displays a screen showing the peripherals attached to the machine, and allows selection for entry of additional charges for the peripheral.

4 - Invoice history: displays a screen showing the invoice history.

5 - Meter history: displays a screen showing all the previous meter readings from all sources for the machine.

6 - Statistics: displays a statistics screen showing average copies/vends and total usage where meterage is used.

7 - Visits: displays a screen showing the service visits scheduled for the machine, for enquiry or amendment. Visits may be added, but beware if the contract has already been priced/invoiced. If Load PM Jobs has already been taken for the other/existing visits on the contract, run it again to convert the added visits.

8 - Generate visits: generates a schedule of planned visits by period for the machine; this depends on the application of the schedule visit profile (SVP) hierarchy to generate visits using the first SVP found:

1. Use the SVP on the contract header.
2. If there is none, use the model file SVP.
3. If there is none, use the model group file SVP.
4. If there is none, use the company profile SVP.
5. If there is none, no visits will be generated.

If visits exist for the machine, the Vst column displays 1; if no visits have been generated, 0.



Note: Make sure the Daily Calendar file is set up far enough ahead to handle the visits to be generated; otherwise, the last column will continue to display Vst - 0.

9 - Delete: displays a window for the entry of a date and a cancellation reason code to remove the equipment line from the contract. Cancellation reason codes are set up under parameter type CCRC in the Codes/Parameter File Maintenance option.

Loc

This displays the site address for the selected machine.

Model

This displays the model of the selected machine.

Serial

This shows the serial number for the selected machine.

Stat

This displays the status of the selected machine line.

Inc Dt

This is the inclusion date, and it defaults to the contract start date, but may be changed if a different inclusion date (DDMMYY) is required.

The machine line will remain with a status of pending until the inclusion date is reached and the contracts are updated (either by running the Contract Updating option, or the Day End Routines option).

Remov Dt

This is a removal date. Enter the date on which the machine is to be removed from contract. Outstanding visits will be deleted by the system.

The expiry of the machine from the contract will occur when the contracts are updated (either by running the Contract Updating option, or the Day End Routines option). This will cancel all outstanding visits.

Rsp Hrs

Enter hours and minutes (hhh:mm), to define the response time for this machine on the contract.

The machine's response time overrides the contract header response time, and is used at call logging, to calculate the target time for the call.

Vst

This field is system maintained.

0 - No visits have been generated.

1 - Scheduled visits exist.

Select By Account Address

Enter a valid installation site and press **Enter** to display all equipment at the site.

Equipment already on a contract is displayed with the model and serial number highlighted. If this equipment is added to another contract, it will appear on the Contract Updating error report, and its status on the new/active contract will remain pending. You must resolve such duplication issues: a machine can only be active on one contract at any one time.

Leave this field blank and enter a model in the next field to display all equipment of that model belonging to the customer account, regardless of installation site.

Model

To display a list of all equipment for a model for any site within the customer account, leave the Select By Account Address field blank and enter a valid model here.

To display a list of all equipment for a model for a particular site within the customer account, enter an address in the Select By Account Address field and enter a valid model here.

Select

Enter 1 against a machine to add it to the contract. Machines which are already on a contract (this is indicated by highlighting) can be added to a new contract, but can only be active on one contract at a time, they will be pending on any other contracts.

Adding a machine will automatically display the Equipment Conditions Window for acceptance or amendment and update (see option 2 - Conditions, above). If header level pricing applies to the contract, the header price is attached to the first machine added to the contract; the machine is always displayed first on the

list of equipment. For this reason, the dummy machine may be added for use with header pricing.

Functions:

F21

Text entry/update.

F23

More Options.



Once the equipment is added and displayed in the top half of the screen, you can select options 2 to 8 using the Select option on lines 8 - 13.

Contract Conditions Window (Option 2)



To display this window select option 2 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

Conditions initially entered by **F18=Conditions Maintenance** at header level will be defaulted to the equipment conditions. Any subsequent changes to the **F18=Conditions Maintenance** detail will not be carried through to the existing equipment conditions: take option 2 to check these conditions and amend if necessary.

SS025		Z1 - GB Demonstration Company		USER GBJBATD0	24/09/97
		"BRUM" TRAINING & SERVICE BRANCH			17:08:22
Contract Equipment Maintenance					
Account Number..... GC01		000	Contract Start Date.. 0000101 B01	24/09/97	
Position to Serial Number...		Reeves Chemist's			
Inst.Adr Loc Model	Serial	Stat Inc.	Dt.	Remov dt	R.Hrs Vst
2 GC01 000 WA10	WAN0001	Pen	24/09/97	0/00/00	0
Contract Conditions					
Model.: WA10		WAN0001			
Cover Type..?..: 301	Eff.Date.: 24/09/97	GBP			
Fixed Service Charge...		.00000			
F8=Update F10=Add F12=Previous					
11-20 SA MW KS CL IM DM II EDN400A KB PKH317S1					

Fields:

Cover Type

This defaults from the contract, but you can change it.

Eff Date

Defaults to the contract start date, but may be overwritten with a later, valid date (DDMMYY).

Untitled

The currency is displayed. It defaults from the Additional Service Details for the customer.

Fixed Service Charge

Enter the value to be charged for fixed service for this piece of equipment.

This value will be applied either for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field in the System Parameters File Maintenance option (screen 1 of 5).

If a header charge was set up in the Billing Parameters Window, it is displayed for change or acceptance.

If you enter zero, the equipment will be priced at zero.

If you leave the value blank and press **Enter**, the appropriate charge for the division, model group, model sub-group and model for the contract type and term is retrieved from the contract rate for the specified currency.

If header level pricing applies to the contract, any fixed service charge will be ignored by the pricing program. Entries would be for memo purposes only; the sum of them all is shown in the Total Contract Value field on the header screen.



Note: Month/term processing must not be changed after initial system setup.

Fixed Visit Charge

The value to be charged for each service visit to the machine.

It will be applied, per visit, for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term in the System Parameters File Maintenance option (screen 1 of 5).

For contracts billed in advance or in arrears, the fixed visit charge is multiplied by the number of visits in the term.

For visit type contracts, which are invoiced after each visit, the fixed visit charge is included on a job invoice. This follows the completion of a technical report for the planned service call.

If a visit charge was set up in the Contract Header Conditions Window, it is displayed for change or acceptance.

If you enter a value of zero, the visit will be priced at zero.

If you leave the value blank and press **Enter**, the appropriate charge for the division, model group, model sub-group and model for the contract type and term will be retrieved from the contract rates file for the specified currency.



Note: Month/term processing must not be changed after initial system setup.

Fixed Rental Charge

Enter the value to be charged for rental.

This value will be applied for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term on the System Parameters File Maintenance option (screen 1 of 5).

If a charge was set up in the Contract Header Conditions Window, it is displayed for change or acceptance.

If a value of 0 is entered, the visit will be priced at zero.

If the value is left blank and **Enter** is keyed, the appropriate charge for the division, model group, model sub-group and model for the contract type and term will be retrieved from the contract rates file for the specified currency.



Note: Month/term processing must not be changed after initial system setup.

Pre-Billing Value/Volume

The contract type determines whether this entry is for a monetary value or for a number of copies or vends.

The entry defaults from the header conditions and cannot be overwritten at equipment line level.

Minimum Volume

Enter a numeric value for the agreed minimum number of copies/vends which will be invoiced each month.

This value can only be used if the setting of Processing By Month Or Term on the System Parameters File Maintenance option (screen 1 of 5) is equal to month.

Minima entered at machine level will override those defaulted from the contract header conditions.



Note: Month/term processing must not be changed after initial system set up.

Copies in Rental

Enter a numeric value for the number of copies per month which are to be included in the rental charge.

Free Copies

Enter the number of free copies or vends allowed on each monthly billing.

Meter 1 - Band Volume To

Enter a numeric value for the maximum number of copies to which the price for the band applies.

The volume for band 1 must not be less than the minimum volume.

Copy bands entered for the machine line override the values defaulted from the contract header conditions.

Band Price Per Copy

Enter the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence by setting the currency multiplier on the system parameter file.

For pool contracts, copy charges can only be defined on the contract header conditions: all machines must use the same copy price.

Meter 2 - Band Volume To

Enter a numeric value for the maximum number of copies to which the price for the band applies.

Copy bands entered for the machine line override the values defaulted from the contract header conditions.

Meter 2 - Band Price Per Copy

Enter the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence by setting the currency multiplier on the system parameter file.

For pool contracts, copy charges can only be defined on the contract header conditions: all machines must use the same copy price.

Functions:

F10

Add new conditions.



Page up and down to display further screens of differently dated contract conditions.



Note: Only the contract conditions selected for the contract type will be displayed.



Select **F8=Update** to update. If this contract type was set up with the Automatically Generate Service Schedule field set to 1, you will be able to select a scheduled visit profile for the new piece of equipment before the update takes place.

Contract Equipment Peripherals Screen (Option 3)



To display this screen take option 3 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

SS648	Demonstration Company	USER BRERETM	10/03/94	
	CENTRAL BRANCH		11:12:38	
Contract Equipment - Peripherals				
Account Number.....	C03	000 Jones and Crossland Ltd.		
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600	
Model number.....	WA10	Serial number.....	W920100	
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93	
Sel	Model number	Serial number	Date Inc.	Date Removed
1	SP100	W920100/P	6/04/93	0/00/00
1=Select				
F12=Previous				

Fields:

Select Option

Enter 1 to display a window to allow the entry of additional charges, which may be applied to the peripheral.

Peripheral Removal Date

Enter the date on which the Peripheral is to be removed from the contract.

The expiry of the equipment from the contract will occur during Contract Updating, which is run as part of the Day End procedures on the removal date.



Select a particular peripheral to see the Peripheral Conditions Window.

Peripheral Conditions Window

 To display this window select a particular peripheral on the Contract Equipment Peripherals screen.

SS648		Demonstration Company		USER BRERETM	10/03/94
		CENTRAL BRANCH			11:12:38
Contract Equipment - Peripherals					
Account Number.....	C03	000 Jones and Crossland Ltd.			
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600		
Model number.....	WA10	Serial number.....: W920100			
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93		
Peripheral Conditions					
Sel	Model number	Serial	Effective date....	6/04/93	d
1	SP100	W9201	Service charge....	25.50	
			Rental charge....	15.02	
			F8=Update F10=Add F12=Previous		
1=Select					
F12=Previous					

Fields:

Effective Date

The date of the price list, for the additional peripheral charges, defaults to the contract start date; it can be changed, if required, to another valid date (DDMMYY).

Service Charge

Enter the value required as an additional service charge for the peripheral. This charge will be added to the charge for the main machine according to the pricing rules applied to that machine when the contract is invoiced.

Rental Charge

Enter the value required as an additional rental charge for the peripheral. This charge will be added to the charge for the main machine according to the pricing rules applied to that machine when the contract is invoiced.

Additional Minimum Volume

The additional volume, entered for the peripheral, is added to the minimum for the main machine when calculating copy/vending charges.

Additional Copy Price

The additional price per copy is added to the price per copy of the main machine, to calculate the total copy price to be applied, when copy/vending charges are invoiced.



Note: Only the peripheral conditions selected for the contract type will be displayed.

Functions:

F10

Add peripheral conditions.

Contract Line Invoice Enquiry Screen (Option 4)



To display this screen take option 4 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

```

SS649          Demonstration Company          USER BRERETM  18/11/93
                  CENTRAL BRANCH                               13:36:17

Contract line invoice enquiry

Account Number..... C03          000 Jones and Crossland Ltd.
Contract Number..... 0000115      Contact: DAVID FEATHER      Tel: 0926 500600
Model number.....:   WA10          Serial number.....: 101000
Contract Start Date.  6/04/93      End Date: 99/99/99  Invoice Start: 6/04/93

Total Revenue.....:                179.19
Volume after last Interim/Reconciliation...

Invoice
Number Type          Value  Period
                        From    To
1500641 02           4.17    6/10/93  5/11/93
1500641 02           4.17    6/09/93  5/10/93
1500641 02           4.17    6/08/93  5/09/93
1500641 02           4.17    6/07/93  5/08/93
1500641 02           4.17    6/06/93  5/07/93
1500641 02           4.17    6/05/93  5/06/93
+

F12=Previous
  
```

Fields:

All Fields

Display only: details for the equipment line selected at option 4.

Functions:

F14

Prime/Base Currency. Use this to toggle between prime and base currency details.

Meter Reading History Screen (Option 5)



To display this screen take option 5 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

SS651	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		13:36:38
Meter Reading History			
Account Number.....	C03	000 Jones and Crossland Ltd.	
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600
Model number.....	WA10	Serial number.....	101000
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93
Reading date	Reading type	Meter 1	Meter 2
17/11/93	03	2125601	25456
F12=Previous			

Fields:

All Fields

Display only: details are for the equipment line selected at Option 5.

Meter Statistics Screen (Option 6)



To display this screen take option 6 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

SS650	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 13:37:01
Meter Statistics			
Account Number.....	C03	000 Jones and Crossland Ltd.	
Contract Number.....	0000115	Contact: DAVID FEATHER	Tel: 0926 500600
Model number.....	WA10	Serial number....	101000
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93
Copy Volumes...	Months.....	3	6
	Produced...	0	0
	Invoiced...	0	0
Invoice Code	Period	Copies Produced	
	From To		
	THERE ARE NO CONTRACTING STATISTICS AT PRESENT FOR THIS CONTRACT		
F12=Previous			

Fields:

All Fields

Display only: details are for the equipment line selected at option 6.

Scheduled Visits Maintenance Screen (Option 7)



To display this screen take option 7 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract, take option 7.

If option 8 - Generate Visits has already been taken, the screen will display the visits set up for the particular equipment record.

You can amend or delete existing visits or add further visits..

You must take care if you add new visits after the contract has been priced/invoiced. The new visit(s) will have to be charged separately on a Job Invoice. If Load PM Jobs has been run, the new visit(s) will only be converted to a Job after the next run of that program.

SS026	Demonstration Company	BRERETM	9/04/93
	CENTRAL BRANCH		15:27:58
Scheduled Visits Maintenance			
Contract No./Type/Dt		0000115 B01 Basic cover	6/04/93
Model.....	WA10	Serial....	101000
		Quantity	1
n	Period	No.Vis	Job Category.....
-	9304	1	CM Service visit
-	9307	1	CM Service visit
-	9310	1	CM Service visit
-	9401	1	CAL Calibration
-	9404	1	CM Service visit
-	9407	1	CM Service visit
			Hours
			1:30
			2:00
			1:45
			2:00
			1:30
			2:00
			+
Srv. Period (YYP)		No. of Visits	Job Cat. Est. Hours
Total Visits 7		Use these visits on renewal? (1/0)	0
Start next profit load from (YYP) 9999 (9999 = never, 0 = re-start)			
Special Price .00000 Engineer			
1=Amend 4=Delete			
F3=Exit F4=Prompt F8=Update F11=Delete F12=Previous			
F21=Text			

Fields:

N

Select. Enter one of the following:

1 - Select the line for amendment. The line will be redisplayed in the fields in the lower half of the screen, where you can make changes.

4 - Delete the line. The line is marked **** DELETED ****; and will be removed after you update. If the machine is to be removed from the contract, an entry in the Equipment Maintenance Screen Remov Dt field is all that is required. After running the Day End Routines option on this date, the records will be deleted, including the visit records.



Once Load PM Jobs' has been run, and jobs created, no visit lines may be deleted.

Service Period

To add a visit, enter valid detail in this and the next six fields.

If amend or delete is selected, the record's data will be displayed in these fields.

This is the service period in which the visit is scheduled. It must be a valid period entered in YYPP format and must fall between the contract start and end dates.

Number of Visits

This is the number of scheduled visits to be made to the piece of equipment within this service period.

It must be greater than 0.

Job Category

This is the type of job to be done on this scheduled visit. It must exist on the Job Category file.

Estimated Hours

This is the estimated hours to carry out the scheduled job. Enter up to five numerics, in the format hhh:mm.

Total Visits

Must be greater than 0. This is the total number of scheduled visits to be made to this piece of equipment during the contract term.

Use These Visits on Renewal

Enter one of the following:

0 - Visits will be generated according to the contract header scheduled visit profile.

1 - If the contract is renewed, the scheduled service visits on the new contract will be based on the revised scheduled service visits shown here. This setting cannot be used unless amending or adding a visit.

Start Next Profile Load from (YYPP)

Must be a valid service period in YYPP format or 9999.

Cannot be less than the current period.

Can be manually entered, or updated by the application referring to the last scheduled visit generated.

Functions:

F21

Text entry/update.



Select **F8=Update** to save changes you have made.

Delete Record Window (Option 9)



To display this screen take option 9 on the Contract Equipment Maintenance Detail screen once equipment has been added to a contract.

SS025	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		13:37:31
Contract Equipment Maintenance			
Contract No./Type/Dt 0000115 B01		6/04/93	
Account Number..... C03	000	Jones and Crossland Ltd.	
Position to Serial Number..			
Loc Model.....	Serial....	Stat Inc. Dt.	Remov dt
9 000 WA10	101000	Act 6/04/93	0/00/00
		Rsp.Hrs	Vst
			1

DELETE RECORD			
Loc: 000	Model: WA10	Serial: 101000	Status: Act
Removal date: 17/11/93	Cancel Reas Code A Poor Service		
Inclusion date: 6/04/93	Response Hours		
F4=Prompt F11=Delete F12=Previous			
6=Statistics 7=Visits 8=Generate visits 9=Delete			
F3=Exit F4=Prompt F12=Previous F21=Text F23=More options			

Fields:

Removal Date

Enter a valid date (DDMMYY).

Cancellation Reason Code

Enter a valid reason code, or prompt for the code selection window. The codes are set up under parameter type CCRC on the Codes/Parameter File Maintenance.

Inclusion Date

Display only, from the equipment line record; will usually default to the contract start date.

Response Hours

Display only, from the equipment line record; if blank, the contract header response hours will be used.

Functions:

F21

Text entry/update.

Contract Type Maintenance

1... **2...** 2/SSC

Use this option to maintain the details of all contract types.

You can use this option during setup, and whenever a contract type code requires addition, amendment or deletion.

Contract types describe the different types of contract and their associated terms and billing parameters.

Implications

You must set up at least one contract type before you can create any contracts.

A contract type cannot be deleted if it has been used in a contract.

The data associated with a contract type is used:

- To provide default data (contract duration, invoice schedule, invoice at start date flag) for each contract of a given type as it is created. The default data can be amended if required.
- To provide call escalation monitoring, using the guaranteed response time to calculate the target arrival time for the engineer.

Contract Type Maintenance Initial Screen



Select Contract Type.

SS032	Demonstration Company	BRERETM	16/09/93
	CENTRAL BRANCH		15:12:37
Contract Type Maintenance			
Contract Type..... <u>B01</u>			
F3=Exit F4=Prompt			

Fields:

Contract Type

Enter a new or existing contract type.

If the type exists, it will be displayed for update, otherwise a new contract type can be added.

One contract type with the code *NO must be set up, with a fixed service charge, for visit-only contracts. These are not invoiced or priced by the contract routines, only in job pricing and invoicing.



Press **Enter** to display the Contract Type Maintenance Screen.

Contract Type Maintenance Screen

 To display this screen select your contract type on the Contract Type Maintenance Initial Screen and press **Enter**.

SS032	Demonstration Company CENTRAL BRANCH	BRERETM	16/09/93 15:13:24
Contract Type Maintenance ADD			
Contract Type..... B01 Basic cover			
Automatically generate service schedule?	1	(1=yes 0=no)	
Quotation required on renewal?	0	(1=yes 0=no)	
Use Contract Start Date Rates?:	0	(1=yes 0=no)	
Response hours guarantee: (hhh:mm)	0800		
Contract duration (months)	0		
Termination notice in days:			
Invoice Schedule.....	0	(0=Advance, 1=Visit, 2=Arrears)	
Contract Type to Include Following Parameters? (1=yes 0=no)			
Fixed Service Charge.....	1	Interim Charges.....	0
Fixed Rental Charge.....	1	Reconciliation Charges.....	0
Fixed Visit Charge.....	0	Copies Incl. Rental.....	0
Minimum Volume.....	0	Copy Charges 1.....	0
Pre Billing Value.....	0	Copy Charges 2.....	0
Pre Billing Volume.....	0	Free Copies.....	0
		Free Visits.....	0
F3=Exit F8=Update F12=Previous			

Fields:

Contract Type Description

Enter a description of up to 20 alphanumerics, to identify the type of contract.

Automatically Generate Service Schedule

Enter one of the following:

0 - You will not be able to select a scheduled visit profile when adding equipment to contracts which have this contract type.

1 - When you add a piece of equipment to a contract of this contract type, a window will enable you to select a scheduled visit profile.

Quotation Required on Renewal

Enter one of the following:

0 - This type of contract will renew as a pending contract.

1 - This type of contract will renew as a quotation.

Use Contract Start Date Rates

Enter one of the following:

0 - Labour rates and parts prices used in job pricing, for any jobs on equipment covered by this contract, will be those effective on the date of call out or date of engineer's visit.

1 - Labour rates and parts prices used in job pricing, for any jobs on equipment covered by this contract, will be those effective at the contract start date.

Response Hours Guarantee

This is the normal response time guaranteed for equipment covered by this type of contract.

Used in job escalation routines.

Contract Duration (Months)

This is the standard contract duration, used to calculate contract termination. Set this duration to zero (blank) to indicate a contract which runs indefinitely. The field works in calendar months, not periods.

Termination Notice in Days

Enter here the number of days to be used by the contract credit calculation as the default penalty days for contract cancellation. For example, if you wish to charge a customer for 10 days' cover when they ask to cancel a contract, then enter 10.

Invoice Schedule

Enter one of the following:

0 - Invoice in advance.

1 - Invoice after each scheduled visit.

2 - Invoice in arrears. The invoice cannot be printed until after the end of any instalment period.

Fixed Service Charge

Enter one of the following:

0 - Fixed service charges cannot be applied to this contract type.

1 - Fixed service charges may be applied to this contract type.

The input fields for these charges will be displayed in the contract conditions window.

Interim Charges

Enter one of the following:

0 - Interim charges cannot be applied to this contract type.

1 - Interim charges may be applied to this contract type, and the input fields for these charge cycles will be displayed in the contract billing window.

Interim charges allow for actual or estimated copies, in excess of the minimum, to be invoiced periodically.

Fixed Rental Charge

Enter one of the following:

0 - Fixed rental charges cannot be applied to this contract type.

1 - Fixed rental charges may be applied to this contract type.

The input fields for these charges will be displayed in the contract conditions window.

Reconciliation Charges

Enter one of the following:

0 - Reconciliation charges cannot be applied to the contract type.

1 - Reconciliation charges may be applied to the contract type.

The input fields for these charge cycles will be displayed in the contract billing window.

Reconciliation charges allow for actual copies in excess of the minimum to be invoiced, or excess estimated copies which have been invoiced, to be credited at the end of the period.

Fixed Visit Charge

Enter one of the following:

0 - Fixed visit charges cannot be applied to this contract type.

1 - Fixed visit charges may be applied to this contract type.

The input fields for these charges will be displayed in the contract conditions window.

Copies in Rental

Enter one of the following:

0 - No copies are to be included in the rental charge.

1 - A value may be keyed in for the number of copies per month, which are included in the rental charge.

The input field for this allowance will be displayed in the contract conditions window.

Minimum Volume

Enter one of the following:

0 - Minimum copy volumes cannot be applied to this contract type.

1 - Minimum copy volumes may be applied to this contract type.

The input fields for these copies will be displayed in the contract conditions window.

Copy Charges 1

Enter one of the following:

0 - Copy charge bands cannot be applied to this contract type.

1 - Copy charge bands will be applied to this contract type.

The input fields for these copy bands will be displayed in the contract conditions window.

Pre-Billing Value

Enter one of the following:

0 - A predetermined value cannot be applied to this contract type.

1 - A predetermined value may be applied to this contract type.

The input fields for this value will be displayed in the contract conditions window.

Copy Charges 2

Enter one of the following:

0 - Copy charge bands cannot be applied to this contract type.

1 - Copy charge bands will be applied to this contract type.

The input fields for these copy bands will be displayed in the contract conditions window.

Pre-Billing Volume

Enter one of the following:

0 - A predetermined volume cannot be applied to this contract type.

1 - A predetermined volume may be applied to this contract type.

The input fields for this volume will be displayed in the contract conditions window.

Free Copies

Enter one of the following:

0 - No free copies allowed.

1 - Yes, the number of free copies specified in the contract conditions will be allowed on each monthly billing.

Free Visits

For future development.



Select **F8=Update** to save any changes.

Scheduled Visit Profile Maintenance

1... 3/SSC
2...

Use this option to maintain the schedule of planned maintenance visits for each visit profile.

Concepts

A scheduled visit profile defines the number, type and frequency of scheduled maintenance visits. Each visit has an associated job category, to indicate the kind of work to be done, and the period in which it are scheduled to be carried out.

Once set up, a visit profile can be linked to a model, a model group, or an individual contract, to define the schedule of visits for that model, model group or contract.

Implications

Although not essential to the system, visit profiles are used to save time within Contracts Maintenance. When defining the service visit schedule for the pieces of equipment on the contract, the visit profiles generate the schedule automatically, so you do not have to key it in manually.

The scheduled visit profile description is held on the Codes/Parameter file under parameter type VSTP.

Scheduled Visit Profile Maintenance Initial Screen



Select Scheduled Visit Profile.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 16:04:04
-------	---	--------------	----------------------

Scheduled Visit Profile Maint.

Enter profile to be maintained..?. 4PA

F3=Exit F4=Prompt

Fields:

Enter Profile To Be Maintained

Enter a valid scheduled visit profile.

A visit profile is a recommended pattern of planned maintenance visits which can be applied at contract, model, model group, or company level. The profile indicates both the service periods and job categories of the intended visits.

When a piece of equipment is added to a contract, visits can be generated, based on the pattern of the visit profile.



Press **Enter** to display the Scheduled Visit Profile Maintenance Selection Screen.

Scheduled Visit Profile Maintenance Selection Screen



To display this screen select a profile on the
Scheduled Visit Profile Maintenance Initial
Screen and press **Enter**.

SS036	Demonstration Company	USER BRERETM	18/11/93
	CENTRAL BRANCH		16:04:10
Scheduled Visit Profile Maint.			
Profile		Profile	
1	4PA 4 visits per annum	6PA	6 visits per annum
2	2PA 2 visits per annum		
F3=Exit F12=Previous			

Fields:

Select Option

Enter 1 - Select against the required visit profile record; the profile Detail Screen will be displayed immediately.

Scheduled Visit Profile Maintenance Detail Screen



To display this screen select the profile you want to maintain on the Scheduled Visit Profile Maintenance Selection screen.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	18/11/93 16:04:20
Scheduled Visit Profile Maint.			
Profile: 4PA 4 visits per annum			
Relative Period	Job Category.....	Est. Hours	
1	PSV Planned service visit	1:00	
3	PSV Planned service visit	1:00	
6	PSV Planned service visit	1:00	
9	CAL calibration	1:30	
12	*RP	0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	
0		0:00	+
F3=Exit F4=Prompt F7=Resequence F8=Update F11=Delete F12=Previous			

Fields:

Profile

Enter a description, of up to 30 alphanumeric, for the visit profile code.

Relative Period

Enter up to two numerics, to represent the number of service periods, after the period in which a contract starts, in which a scheduled service visit will be generated.

0 is valid, if the first visit is to be made in the contract's start period.

The relative period used in this context is the service period relative to the period in which the contract start date falls. For example, if a profile for three visits per annum is required, the application is using monthly service periods, and the relative periods are defined as 02, 06 and 10, then for a contract which starts in period 07/98 (July 1998), this would result in the application generating a schedule of three visits, in periods 09/98, 01/99 and 05/99.

Job Category

Enter an existing job category. This indicates the type of job which the engineer will perform on the planned maintenance visit.

If the contract covers several years, for example, and you wish to generate the same pattern of visits year after year, you do not have to enter these repeated visits.

Instead, enter the special job category of *RP to introduce a cyclic aspect to the profile. This means that when the visit schedule is being generated the system will generate visits as far ahead as the contract end date, or as the number of service periods to be loaded (as specified on the company profile), whichever is the sooner. So, even if you only enter one year's visits here, they will be generated for subsequent years automatically.

Load PM Jobs will, in fact, load any job category found here, not just a job category code set up as PM.

Est Hours

Enter up to five numerics (hhh:mm), for the estimated job duration.

The value is not used directly in the current system.



*Note: If a relative period is keyed in, and *RP is entered in the job category column, a repeat cycle of visits will be generated using the existing visit profile, starting from the relative period entered.*

Functions:

F7

Re-sequence. Use this to re-sequence the relative periods numerically.



Select **F8=Update** to save details.

Recommended Service Visits Maintenance

1... 4/SSC **2...**

Use this option to maintain the scheduled visit profile which applies to each model group, by effectivity date.

Concepts

This option defines the number, type and frequency of scheduled maintenance visits normally associated with a model group, by linking the model group with a scheduled visit profile code. Additionally, there is an effective date which enables the same model group to be linked to different profiles for different time windows. The concept of scheduled visit profiles is explained in Scheduled Visit Profile Maintenance.

Implications

The profile code detail is accessed within Contract Maintenance, when generating the service visit schedule for the pieces of equipment on the contract, where there is no visit profile defined for the contract or the model. If the recommended visit profile is not defined for the model group, the visit profile defined on the Company Profile is used; if this is absent, no visit schedule is generated.

Recommended Visits Maintenance Initial Screen

 Select Recommended Service Visits .

SS028	Demonstration Company CENTRAL BRANCH	USER BRERETM	11/03/94 2:15:14						
Recommended Visits Maintenance									
Division.....?.. <u>10</u>									
Model Group.....?.. <u>?</u>									
		Model Group Selection							
		<table border="1"><thead><tr><th>1</th><th>Code</th><th>Desc.</th></tr></thead><tbody><tr><td><u>1</u></td><td>100</td><td>Analysers</td></tr></tbody></table>		1	Code	Desc.	<u>1</u>	100	Analysers
1	Code	Desc.							
<u>1</u>	100	Analysers							
F3=Exit F4=Prompt		F12=Previous							

Fields:

Division Code

Enter a valid division code of up to two alphanumerics; or, prompt for the code selection window.

Model Group Code

Enter a valid model group code of up to three alphanumerics; or, prompt for the code selection window.

 Select the valid division and model group codes to display the Recommended Visits Maintenance Detail Screen.

Recommended Visits Maintenance Detail Screen



To display this screen select a valid division and model group code on the Recommended Visits Maintenance Initial Screen.

SS028	Demonstration Company CENTRAL BRANCH	USER BRERETM	11/03/94 2:16:48
-------	---	--------------	---------------------

Recommended Visits Maintenance

Division..... 10 Environmental Monitoring
Model Group..... 100 Analysers

Effective date..... 0/00/00
Visit Profile Code.?. ____

	Date	Visit Profile Code
-	1/01/94	4PA 4 Visits per annum
-	1/01/93	4PA 4 Visits per annum

4=Delete
F3=Exit F4=Prompt F12=Previous

Fields:

Effective Date

Enter a valid date (DDMMYY); this allows the same Model Group to be linked to different profiles for different time windows.

Scheduled Visit Profile Code

Enter a valid Scheduled Visit Profile code.

A Visit Profile, qualified by its Effective Date, will be used in the generation of scheduled service visits for each piece of this Model Group's equipment on a Contract. What code to apply depends on the following hierarchy:

- Use the SVP on the contract header.
- If there is none, use the model SVP.
- If there is none, use the model group SVP.
- If there is none, use the company profile SVP.
- If there is none, no visits will be generated.

else, generate visits for the equipment line on the contract, using the first SVP code found, when Option 8 on the Equipment Screen (SS025) is taken.

Select Option

Enter 4 to delete the Visit Profile Code.

Cover Type Maintenance



5/SSC

A cover type defines the charge conditions under which jobs are priced, and to which a service visit profile can be attached.

A minimum of one cover type must be defined: *NO, for no contract.

Cover Type Maintenance Selection Screen

 Select Cover Type Maintenance.

SS050	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		10:33:08
Cover Type Maintenance			
Cover Type?.. 01			
F3=Exit F4=Prompt			
5-29	SA	MW	KS CL IM DM II EDN400A KB PKH317S1

Fields:

Cover Type

Enter a new or existing cover type.

 Press **Enter** to display the Cover Type Maintenance Screen.

Cover Type Maintenance Screen



To display this screen press **Enter** on the Cover Type Maintenance Selection screen.

SS050	Z1 - GB DEMO, SERVICE COMPANY	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		10:34:13
Cover Type Maintenance		ADDITION	
Cover Type.....	N01	TYPE 01	
Service Visit Profile..?	1AA	1Vis : 6 AAI	
F3=Exit F8=Update F12=Previous			
5-35	SA	MW KS CL IM DM II	EDN400A KB PKH317S1

Fields:

Untitled

Cover Type Description. Enter the description of a new cover type.

Service Visit Profile

Enter a service visit profile to the cover type if required.



Select **F8=Update** to save the cover type and details.

Contract Rates Maintenance



6/SSC

Use this option to maintain the term contract rates for each model group/sub-group/model/contract type combination, by effectivity date and currency.

You can use this during setup, and whenever the contract rates for a model group/sub-group/model/contract type/effective date require addition, amendment or deletion.

Concepts

Contract rates are used by term processing to calculate the price for each piece of equipment on a contract. For each contract type and contract term, the rates can be defined for each model group or sub-group or model, so that the rates for any given model on any given type of contract can be derived.

Contract rates are of three types:

- A visit charge, which is the price to be charged for each scheduled maintenance visit to a piece of equipment.
- A rental charge, which is the price to be charged for the equipment rental for the term.
- A service charge, which is the price to be charged for the piece of equipment's fixed service for the term.

Any of these rates may be zero. The contract charge for a piece of equipment can comprise one or more of these rates.

Contract rates are held by effectivity dates; this enables different rates to be held for different time windows.

Contract rates are held for different currencies.

Implications

Contract rates data is accessed by contract maintenance when setting up the conditions for the contract equipment.

If contract rates data is completely absent, the contract line will require a special price, or zero, to be entered in the conditions window.



Note: When using monthly rather than term pricing, these contract prices cannot be used; the rate per month must be set within the contract.

Contract Rates Maintenance Initial Screen



Select Contract Rates.

SS030	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		11:40:55
Contract Rates Maintenance			
Division.....?..	HW		
Model Group.....?..	A-C		
Term.....?..	12		
Currency Code.....?..	GBP		
Based on :-			
Division.....?..	█		
Model Group.....?..	---		
Term.....?..	---		
Currency Code.....?..	---		
F3=Exit F4=Prompt			
14-27 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Division

Enter a valid division.

Model Group

Enter a valid model group.

Each model group can have contract rates attached, with effective dates.

The current rate will be used, at Contract Pricing, to price a piece of equipment belonging to a particular model group.

Term

Enter the billing term. Valid mandatory entries are from one to 120 calendar months; the default value is 12.

Term defines the price protection period for the contract and the number of periods for which contract pricing will generate pending invoice and actual invoice records.

The contract rate selected for the contract header will be for the same term as that entered in the contract billing parameters.

Currency Code

Enter a valid currency using three characters.

Based On Fields

If you want to create a contract rate based on an existing one, then enter the existing rate details here.

The system will set up the structure of the new rate based on the existing one, but the actual detail lines cannot be amended. If you need to change them you have to delete them and enter new ones.

This means that the based on facility is of limited use.



Press **Enter** to view the Contract Rates
Maintenance Screen.

Contract Rates Maintenance Screen



To display this screen select valid division and model group codes on the Contract Rates Maintenance Initial Screen and press **Enter**.

```

SS030          Z1 - GB Demonstration Company      USER GBJBATD0      24/09/97
               "BRUM" TRAINING & SERVICE BRANCH    11:41:13
Contract Rates Maintenance

Division..... HV   Heat and Ventilate
Model Group..... A-C Air-Conditioning
Term..... 12
Model Sub-group...?..
Model.....?..
Effective Date..... 0/00/00  <----- Changes ----->
Cover Type.....?..          Visit      Rental      Service
Currency Code..... GBP
MG MSG Model      Typ Eff.Date
- A-C             B01 1/11/95          480.00      1120.00
- A-C             B02 1/11/95          600.00
- A-C             B05 31/12/96      40.00      1900.00
- A-C             B05 1/12/96      35.00      1850.00
- A-C             B05 1/11/95      30.00      1800.00
- A-C             B05 1/06/94      32.00      1400.00
- A-C             B05 1/01/93      20.00      1200.00
- A-C             B10 1/11/95      36.00      480.00      1344. +
4=Delete
F3=Exit F4=Prompt F12=Previous

8-27  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
  
```

Fields:

Model Sub-Group

Enter a valid model sub-group or leave blank.

If entered, the contract rates will apply to all models belonging to this model sub-group, within the model group and division.

Model

Enter a valid model code of up to 15 alphanumeric; or, prompt for the code selection window or leave blank.

A model code is linked to model sub-group, model group and division. If a contract rate record is set up at model level, at contract pricing, this rate will override any rates set up at model sub-group or model group levels.

Effective Date

Enter a valid date (DDMMYY), on which the contract rate becomes active.

All existing contract rates, for the new model group/model sub-group/model combination, which have earlier effective dates, will be superseded.

Cover Type

Enter a valid contract type code of up to three alphanumeric.

The specified service, rental or visit charge(s) will be applied to this contract type, for the product combination selected, at contract pricing.

Currency Code

Display only: as selected on the previous screen.

Visit

Enter the charge per visit made during the contract, if term processing is set on the System Parameter file (screen 1 of 5).

The visit charge will be overridden by any charges which have been set up in the Contract Conditions windows.

The price for a contract line is calculated by multiplying the charge per visit by the number of visits in the term and adding the rental and service charges for the term.

Rental

Enter the rental to be charged for the contract term, if term processing is set on the System Parameters file (screen 1 of 5).

The rental charge will be overridden by any charges which have been set up in the Contract Conditions Windows.

The price for a contract line is calculated by multiplying the charge per visit by the number of visits in the term and adding the rental and service charges for the term.

Service

Enter the charge to be made for fixed service for the contract term, if term processing is set on the System Parameters file (screen 1 of 5).

The service charge is overridden by any fixed service charge set up in the Contract Conditions Windows.

The price for a contract line is calculated by multiplying the charge per visit by the number of visits in the term and adding the rental and service charges for the term.

Untitled (Option)

4 - Delete the contract rates for this model group/model sub-group/model combination.



Press **Enter** to update.

Contracts Enquiry



11/SSC

Use this option to enquire on the details of service contracts, and quotations for contracts, on an ad hoc basis.

Description

To access a contract for enquiry, the contract number (and optionally, the contract type), or customer account (and optionally, the address code), or alpha search can be used. Depending on the entries made, lists are presented of customer sites or contracts matching the selection parameters, to allow further selection.

The details of the selected contract (or contract quotation) are displayed, enabling you to enquire on the header, the equipment covered and any override details affecting service, invoicing, conditions and visits scheduled.

Contract Enquiry Initial Screen



Select Contracts Enquiry.

SS524	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBATD0	25/09/97
	"BAUM" TRAINING & SERVICE BRANCH		10:44:59
Contract Enquiry			
Contract Number..... _____			
Contract Type.....?.. _____			
Account Number...?.. G001 _____			
Account Address..... 000 _____			
F3=Exit F4=Prompt			
6-24 SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Contract Number

Enter a valid contract number.

The contract number must exist already, if the account number. and address code are not entered.

If entered by itself, a list of all contracts with this number will be displayed in contract type and start date sequence.

Contract Type Code

Linked to Contract Number, this must exist on the contract type file.

The combination must exist on the contract file, if account number and address code are not entered.

If only contract number and contract type are entered, a list of all contracts with these numbers/types is displayed in start date sequence.

Account Number

Enter a valid customer account code of up to eight alphanumerics.

If you enter the account number without an address code, it displays a list of all address codes for this account.

If an address code is selected, a list of all contracts with this account number/address code combination will be displayed.

Account Address Code

Must be entered in conjunction with an account number; the account number/address code combination must exist on the Additional (Service) Details file, so that the customer is defined to Service Management.

If only the account number and address code are entered, a list is displayed of all of that site's contracts, in contract number, contract type and start date sequence.



Select a valid contract to display the Contract Header Enquiry Detail Screen.

Contract Header Enquiry Detail Screen



To display this screen select a valid contract has been selected from the Contract Enquiry Initial screen.

SS535	Z1 - GB DEMO. SERVICE COMPANY	USER GBJBATD0	25/09/97
	"BAUM" TRAINING & SERVICE BRANCH		11:00:19
Contract Header Enquiry			
Account Number.....	GC01	000 Reeves Chemist's	
Contract Number.....	0000101	Alt. Cont. No.	Version.
Contract Type.....	B01	S&R Adv: Basic cover	Status. Pending start date
Contract Start Date..	24/09/97	End Date. 23/09/98	Invoice Start. 0/00/00
Tot. Contract value..		Header price..	
Duration.....	12	Mantle Code.....	
Customer Order Ref 1..		Order Ref Date..	0/00/00
Customer Contact.....	Michael Wello	Telephone No....	0121 448 5273
Renew Contract (1/0)..	1	Region....	WM West Midlands
Non-posting Invoices..	0	Header level pricing (1/0)..	1
Salesman Code.....		Invoice Summ/Det Form (1/0)...	0
Invoice Destination...		Direct Debit (1/0).....	0
Contract Inv. Bill to..		Header currency (1/0).....	1
Job Invoice Bill to...			
F3=Exit	F8=Detail	F12=Previous	F14=Service
F18=Conditions enq.			F21=Text
			F16=Billing enquiry
			F23=Invoice enquiry
1-1	SA	MW	KS CL IM DM II
			EDN400A KB PKH317S1

Fields:

Alt Cont No

This field displays up to seven alphanumerics for an alternative contract number.

Version

This field displays up to five-alphanumerics for the version number.

Contract Type

This field displays the contract type.

Status

Display only: retrieved from the Codes/Parameter File Maintenance option, parameter type CHST, dependent on the contract header status.

The status may be:

P - Pending.

Q - Quotation.

A - Active.

E - Expired.

D - Deleted.

Contract Start Date

Display only: the contract will be made active by the Day End Routines option when the start date is reached.

Contract End Date

This is calculated using contract start date + contract duration.

If the contract duration is 0, the contract will be assumed to be rolling, with an end date displayed as 99/99/99.

The contract will be expired by the Day End Routines option when its contract end date is reached.

Invoice Start Date

Display only: This is system-maintained as the date on which the first invoice for the contract was raised.

Total Contract Value

This is the total value of the fixed service charges, entered in the Contract Conditions Window of each contract equipment line. It is the annualised, or term's, nominal value of the service elements of a contract, but is not used for invoicing.

No value can be displayed in advance of the contract start date; or of the effective date(s) for the equipment prices.

The total does not necessarily reflect the invoice value of the contract, if equipment is added or deleted during the course of the billing term.

Header Price

The header or block price to be invoiced for the contract, as entered in the Contract Header Conditions (F18). This can be compared to the total contract value, the nominal price displayed from the total of the contract lines.

The field literals are only displayed if Header Level Pricing is set to 1 - Yes in the field five lines lower down the screen.

The literals are not displayed if Header Level Pricing is set to 0 - No.

Contract Duration

Displays the contract duration in months up to a maximum of 120.

If the contract duration is 0, the contract is assumed to be never-ending, or rolling, with an end date of 99/99/99.

Mantle Code

This field displays a user-defined mantle code of up to five alphanumerics, set up under the parameter type MANT in Inventory Descriptions.

The mantle code is used in the Global Price Update routine, to identify a group of contracts for a percentage price change.

Customer Order Ref 1

This field, and the Order Ref Date, are mandatory if the Customer Ref. for Contracts field in the customer's additional service details is set on.

Order Ref Date

Display only: the field is mandatory if the if the Customer Ref. for Contracts field in the customer's additional service details is set on, otherwise, it is left as 0/00/00.

Customer Contact

This defaults from the site additional details Contact field, but may have been overwritten. The field holds the name of the contact to whom enquiries relating to this contract should be addressed.

Telephone No

This defaults from the site additional details, but may have been overwritten.

Renew Contract

0 - The contract will never be renewed.

1 - The contract will be renewed with effect from the end date on the contract header.



Note: This indicator has no effect if the contract end date is set to 99/99/99, and is therefore a never-ending contract.

Region

This displays the service region from the additional service details file for the site.

Non-Posting Invoices

0 - Invoices are posted to the ledgers.

1 - The contract functions as normal, but invoices produced stay within Service Management and are not posted to the ledgers.

Header Level Pricing

0 - If no price is keyed into the contract header conditions window, the contract is priced from the contract rates file, for each of the contract equipment lines.

0 - If a price is keyed into the contract header conditions window, that price is defaulted to each equipment conditions window for equipment added to the contract.

1 - The **F18=Conditions** window requires a fixed service charge before the contract header can be updated. The contract is priced based on the value in the contract header conditions window.



Note: If 1 - Yes, any prices keyed into contract equipment conditions windows will be ignored by the pricing program. They may be used for comparison purposes: their total is displayed in the Total Contract Value field.

Estimates Allowed

0 - No metered charges will be made.

1 - Invoices based on estimated meter readings will be produced.

Pool Contracts

This is only valid for contracts which have meterage billing parameters defined on their contract type.

0 - Non-pooled contracts are assessed for invoicing on the basis of the individual machine: if the number of copies/vends is less than minimum, then minimum is charged; if the number of copies exceed the minimum, then the additional copies/vends are charged.

1 - Pooled contracts are assessed for invoicing on the basis of the aggregated minima of all the machines on the contract: machines which have an excess of copies/vends can offset the total excess against those machines which have actual usage which is less than the minimum.

Salesman Code

This displays the salesman from the customer account. These are set up under parameter type SN in the Inventory Descriptions.

The salesman is used for memo purposes only.

Invoice Summ/Det Form

This field is for future use.

Invoice Destination

The customer and address are displayed, from the site's additional details.

The narrative address is retrieved for printing on all invoices and credit notes for the contract.

Direct Debit

This field is for future development.

Contract Inv Bill To

Contract invoices are sent to the customer entered here.

Untitled (Contract Invoice Bill Address)

Contract invoices are sent to the address entered here.

Header Currency

0 - Equipment on the contract will be invoiced in the currency of the site where the equipment is installed.

1 - All equipment on the contract will be invoiced in the currency of the account header.



Note: Some of the fields on the header screen are only displayed if the function they relate to has been selected for the contract type.

Job Invoice Bill To

Job invoices are sent to the customer entered here.

Untitled (Job Invoice Bill Address)

Job invoices are sent to the address entered here.

Functions:

F8

Detail. Detail (equipment lines).

F14

Service. Service parameters enquiry window.

F16

Billing Enquiry. Billing parameters enquiry window.

F18

Conditions Enq. Contract conditions enquiry window.

F21

Text. Text enquiry.

F23

Invoice Enquiry.



Select **F8=Detail** to display the detail screen.

Service Parameters Window (F14)



To display this window select **F14=Service** on the Contract Header Enquiry Detail screen.

```
SS535          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBATD0  25/09/97
               "BRUM" TRAINING & SERVICE BRANCH    11:00:19
Contract Header Enquiry

Account Number..... GC01          000 Reeves Chemist's
Contract Number..... 0000101        Alt. Cont. No.      Version.
Contract Type..... B01 S&R Adv: Basic cover  Status. Pending start date
Contract Start Date.. 24/09/97      End Date. 23/09/98  Invoice Start. 0/00/00
Tot. Contract value..                Header price...
Duration..... 12                    Mantle Code....
Customer Order Ref 1..                Order Ref Date.. 0/00/00
Customer Contact..... Michael Wello   Telephone No.... 0121 448 5273
Renew Contract (1/0).. 1              Region.... WM West Midlands

Service Parameters
Response hours..... 16
Schedule visit profile..
Allow service cover when contract pending (1/0). 1
Use start date rates.... 1    Or,Until.... 0/00/00
Global Price Code.....

F12=Previous
F18=Conditions enq.          F21=Text          F23=Invoice enquiry

1-1  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
```

Fields:

Response Hours

Up to five numerics (hhh:mm), the field sets the response time for the contract; it applies to all contract lines, unless a line is given its own special response time.

Scheduled Visit Profile Code

The code is used in generating the visits to each piece of equipment on a contract. What code to apply depends on the following hierarchy:

- Use the SVP on the contract header.
- If there is none, use the model SVP.
- If there is none, use the model group SVP.
- If there is none, use the company profile SVP.
- If there is none, no visits will be generated.

As long as an SVP is found, the system generates visits for the equipment line on the contract, using the first SVP found, when you take option 8 on the Contract Equipment Maintenance Screen.

The SVP code, for a contract where the SVP has been edited, will be displayed as *OV: to indicate that a standard SVP code has been overridden.

Use Scheduled Visit Override At Renewal

0 - At contract renewal the SVP hierarchy will determine the equipment visits to be generated on the renewed contract.

1 - The *OV amendments to the SVP will be used when the contract is renewed and equipment visits are generated.

Allow Service Cover on Pending Contract

Display only: defaults from the System Parameters File Maintenance option (screen 1 of 5), but can be overwritten.

0 - Contract cover is effective from the contract start date.

1 - All calls to the equipment to be included on the contract, logged prior to the contract start date (while the contract has the status pending), will be treated as though the contract cover was effective; this will be reflected on the call detail screen.

Use Contract Start Date Rates

0 - Labour rates and parts prices will be those effective on either the date the call was placed or the date of the engineer's visit.

1 - Labour rates and parts prices will be those effective at the contract start date.

Or, Until (Date)

If Use Start Date Rates is 1, this field is displayed as 0/00/00.

If Use Start Date Rates is 0, a valid date (DDMMYY) is displayed. The labour and parts price lists used for chargeable work, effective at the contract start date, will only be used until the date entered.

After this date, the price lists used will be those effective on the date the work was carried out.

Global Price Update Code

Display only: a valid global price update code of up to two alphanumerics, or blank is displayed. Any code entered will be validated against the parameter type GLPR, on the Codes/Parameter File Maintenance option.

The code is used in the Global Price Update option, to select contracts for inclusion in the price revision then being applied.



Select **F12=Previous**.

Billing Parameters Window (F16)



To display this window select **F16=Billing Enquiry** on the Contract Header Enquiry Detail screen.

```
SS535          Z1 - GB DEMO. SERVICE COMPANY      USER GBJBATD0  25/09/97
                "BAUM" TRAINING & SERVICE BRANCH    11:01:16
Contract Header Enquiry

Account Number..... GC01          000 Reeves Chemist's
Contract Number..... 0000101      Alt. Cont. No.      Version.
Contract Type..... B01 S&R Adv: Basic cover  Status. Pending start date
Contract Start Date.. 24/09/97      End Date. 23/09/98  Invoice Start. 0/00/00
Tot. Contract value..              Header price...
Duration..... 12                  Mantle Code.....

Billing Parameters
-----
Billing type:      Term  Freq  Adv/Visit/Arr  Next pricing cycle
                  (mths) (mths) (0/1/2)      From      To
Fixed Service Chrg.: 12    3    0 (0/1/2)      24/09/97  23/09/98
Rental Charge.....: 12    3    0 (0/1/2)      24/09/97  23/09/98

F12=Previous
F3=Exit  F8=Detail  F12=Previous  F14=Service  F16=Billing enquiry
F18=Conditions enq.  F21=Text      F23=Invoice enquiry

1-1  SA  MW  KS  CL  IM  DM  II  EDN400A  KB  PKH317S1
```

Fields:

Fixed Service Chrg: Term

Display only, from the time the contract is invoiced.

The term is expressed in months; it defaults to a value of 12, but may be set to one to 120 months (that is, a 10 year maximum).

The term is the number of months within the contract's duration for which the contract price is protected from change and the number of periods covered by the fixed service charge.

Fixed Service Chrg: Freq

This is display only, from the time the contract is invoiced.

It is the frequency of invoicing expressed in months: 1 is monthly, 3 is quarterly, 12 is annual invoicing in a 12 month term.

Entries will be between 0 and the maximum number in the term, and equally divisible into the term.

Fixed Service Chrg: Adv/Visit/Arr

Display only, from the time the contract is invoiced.

Defaults to the value in the invoice schedule field on the contract type file:

0 - Invoice in advance; release date is the start of the invoice period, the invoice for each invoice term is issued before the term starts.

1 - Invoice each scheduled PM visit; this is a job invoice, raised as the result of the engineer's technical report for the visit. Invoice freq must be 0.

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Fixed Service Chrg: Next Pricing Cycle From

Display only, from the time the contract is invoiced.

It is the anniversary date of the first invoice; it will be the date on which the next pricing cycle will start.

Fixed Service Chrg: Next Pricing Cycle To

Display only, from the time the contract is invoiced.

It is the end date of the next contract term.

Rental Charge: Term

Display only, from the time the contract is invoiced.

The term is expressed in months; it defaults to a value of 12, but may be set to one to 120 months (that is, a 10 year maximum).

The term is the number of months within the contract's duration for which the rental price is protected from change and the number of periods covered by the rental charge.

Rental Charge: Freq

Display only, from the time the contract is invoiced.

It is the frequency of invoicing expressed in months: 1 is monthly, 3 is quarterly, 12 is annual invoicing in a 12 month term.

Entries will be between 0 and the maximum number in the term, and equally divisible into the term.

Rental Charge: Adv/Visit/Arr

Display only, from the time the contract is invoiced.

Defaults to the value in the invoice schedule field on the contract type file:

0 - Invoice in advance; release date is the start of the invoice period: the invoice for each invoice term is issued before the term starts.

1 - Invoice each scheduled PM visit; this is a job invoice, raised as the result of the engineer's technical report for the visit. Invoice frequency must be 0.

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Rental Charge: Next Pricing Cycle From

Display only, from the time the contract is invoiced.

It is the anniversary date of the first invoice; it will be the date on which the next pricing cycle will start.

Rental Charge: Next Pricing Cycle To

Display only, from the time the contract is invoiced.

It is the end date of the next contract term.

Pre-Billing Charge: Term

Not applicable: always blank.

Pre-Billing Charge: Invoice Frequency

Display only, from the time the contract is invoiced.

It is the frequency of invoicing expressed in months: 1 is monthly, 3 is quarterly, 12 is annual invoicing in a 12 month term.

Entries will be between 0 and the maximum number in the term, and equally divisible into the term.

Pre-Billing Charge: Adv/Arr

Display only, from the time the contract is invoiced.

Defaults to the value in the invoice schedule field on the contract type file:

0 - Invoice in advance; release date is the start of the invoice period: the invoice for each invoice term is issued before the term starts.

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Pre-Billing Chrg: Next Pricing Cycle From

Display only, from the time the contract is invoiced.

It is the anniversary date of the first invoice; it will be the date on which the next pricing cycle will start.

Pre-Billing Chrg: Next Pricing Cycle To

Display only, from the time the contract is invoiced.

It is the end date of the next contract term.

Interim Charge: Term

Not applicable: always blank.

Interim Charge: Freq

Display only, from the time the contract is invoiced.

It is the frequency of invoicing expressed in months: 1 is monthly, 3 is quarterly, 12 is annual invoicing in a 12 month term.

Entries will be between 0 and the maximum number in the term, and equally divisible into the term.

Interim Charge: Arr

Display only, from the time the contract is invoiced.

Defaults to the value in the invoice schedule field on the contract type file:

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Interim Charge: Next Pricing Cycle From

Display only, from the time the contract is invoiced.

It is the anniversary date of the first invoice; it will be the date on which the next pricing cycle will start.

Interim Charge: Next Pricing Cycle To

Display only, from the time the contract is invoiced.

It is the end date of the next arrears invoicing period, which is set by the interim charge invoice frequency; it may only be for a three month period, for example.

Reconciliation Charge: Term

Display only, from the time the contract is invoiced.

The term is expressed in months; it defaults to a value of 12, but may be set to one to 120 months (that is, a 10 year maximum).

The term is the number of months within the contract's duration, for which the contract price is protected from change.

Reconciliation Charge: Freq

Display only, from the time the contract is invoiced.

It is the frequency of invoicing expressed in months: 1 is monthly, 3 is quarterly, 12 is annual invoicing in a 12 month term.

Entries will be between 0 and the maximum number in the term, and equally divisible into the term.

Reconciliation Charge: Arr

Display only, from the time the contract is invoiced.

Defaults to the value in the invoice schedule field on the contract type file:

2 - Invoice in arrears; release date is the end of the invoice period: the invoice for each invoice term is issued after the term finishes.

Reconciliation Chrg: Next Pricing Cycle From

Display only, from the time the contract is invoiced.

It is the anniversary date of the first invoice; it will be the date on which the next pricing cycle will start.

Reconciliation Chrg: Next Pricing Cycle To

Display only, from the time the contract is invoiced.

It is the end date of the next arrears invoicing period, which is set by the reconciliation charge invoice frequency; it may only be for a three month period, for example.



Note: Only the billing parameters selected for the contract type will be displayed.



Select **F12=Previous**.

Contract Conditions Window (F18)



To display this window select **F18=Conditions Enq** on the Contract Header Enquiry Detail screen.

<pre>SS535 Z1 - GB DEMO. S "BRUM" TRAININ Contract Header Enquiry Account Number..... GC01 Contract Number..... 0000101 Contract Type..... B01 S&R Ad Contract Start Date.. 24/09/97 Tot. Contract value.. Duration..... 12 Customer Order Ref 1.. Customer Contact..... Michael We Renew Contract (1/0).. 1 Non-posting Invoices.. 0 Salesman Code..... Invoice Destination... Contract Inv. Bill to.. Job Invoice Bill to... F3=Exit F8=Detail F12=Previo F18=Conditions enq.</pre>	<pre>Cover type... B01 Eff.Date: 25/09/97 GBP Fixed Service Charge... .00000</pre>
---	--

1-1 **SR** MW KS CL IM DM II STUD140 KB PKH317S1

Fields:

Cover Type

The cover type for the header is displayed.

Effective Date

This defaults to the contract start date, but may have been overwritten with a later, valid date (DDMMYY).

Currency Code

This defaults from the customer additional service details for the site, or the account on the contract header.

Fixed Service Charge

This is the value to be charged; it will be applied for the term of the contract, or for a month, depending on the setting of the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option.

Charges entered at header level will be applied to all machine lines, unless a special machine line condition is set up.



Note: Month/term processing must not be changed after initial system set up.

Fixed Visit Charge

This is the value to be charged for each visit made.

The charge entered at header level will be applied to all machine lines, unless a special machine line condition is set up.

Fixed Rental Charge

This is the rental to be charged; it will be applied for the term of the contract, or for a month, depending on the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option.

The charge entered at header level will be applied to all machine lines, unless a special machine line condition is set up.



Note: Month/term processing must not be changed after initial system set up.

Pre-Billing Value/Volume

The contract type determines whether this is a monetary value or a number of copies or vends.

The value or quantity which has been agreed as the pre-determined monthly minimum value for copies or vends is displayed.

This field can only be used if the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option is set to month.

The header level charge is applied to all machines on the contract and could not be changed on the conditions for individual machine lines.



Note: Month/term processing must not be changed after initial system set up.

Minimum Volume

The numeric value for the agreed minimum number of copies or vends which will be invoiced each month is displayed.

This field can only be used if the Processing By Month Or Term field on the first screen of the System Parameters Maintenance option is set to month.

The minimum, entered at header level, is applied to all machine lines unless it was changed in the contract conditions on a machine line.



Note: Month/term processing must not be changed after initial system set up.

Copies In Rental

This is the number of copies per month which are to be included in the rental charge.

Free Copies

The number of free copies allowed on each monthly billing is displayed.

Meter 1 - Band Volume To

This is the maximum number of copies to which the price for the band applies.

The volume for band 1 must not be less than the minimum volume.

Meter 1 - Band Price Per Copy

This is the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence/cents by setting the currency multiplier on the system parameter file.

Meter 2 - Band Volume To

This is the maximum number of copies to which the price for the band applies.

Meter 2 - Band Price Per Copy

This is the price per copy to be charged up to the band maximum.

The copy price can be expressed in pence/cents by setting the currency multiplier on the system parameter file.

If meterage is specified, at least one price band must be entered for meter 2 even if not used in the contract.



Page up or down, to display further screens of differently dated contract conditions.



Note: Only the contract conditions selected for the contract type will be displayed.



Select **F12=Previous**.

Contract Maintenance Invoice Enquiry Screen (F23)



To display this screen select **F23=Invoice Enquiry** on the Contract Header Enquiry Detail screen.

SS645	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 10:53:15
Contract Maint Invoice Enquiry			
Account Number.....	C03	000 Jones and Crossland Ltd.	
Contract Number.....	0000115	Alt. Cont. No:	Version:
Contract Type.....	B01 Basic cover	Status: Active	
Contract Start Date.	6/04/93	End Date: 99/99/99	Invoice Start: 6/04/93
Total Revenue.....:	179.19		
Volume after last Interim/Reconciliation..:			
Invoice Number	Type	Value	Period From To
1500641	02	4.17	6/10/93 5/11/93
1500641	02	4.17	6/09/93 5/10/93
1500641	02	4.17	6/08/93 5/09/93
1500641	02	4.17	6/07/93 5/08/93
1500641	02	4.17	6/06/93 5/07/93
1500641	02	4.17	6/05/93 5/06/93
			+
F12=Previous			

Fields:

All Fields

The total revenue for the contract is displayed, with all invoices listed.



Select **F12=Previous**.

Contract Equipment Enquiry Detail Screen (F8)



To display this screen select **F8=Detail** on the Contract Header Enquiry Detail screen.

SS525	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		10:53:56
Contract Equipment Enquiry			
Contract No./Type/Dt 0000115 B01		6/04/93	
Account Number.....	C03	000 Jones and Crossland Ltd.	
Loc	Model	Serial	Stat Inc. Dt. Rem date Rsp.Hrs Yst
- 000	WA10	W920100	Act 6/04/93 0/00/00 4:30 1
- 000	WA10	101000	Act 6/04/93 0/00/00 1
2=Conditions 3=Peripherals 4=Inv hist. 5=Meter hist. 6=Stats. 7=Visits			
F3=Exit F12=Previous F13=Fold/Truncate F21=Text			

Fields:

Untitled

Enter one of the following:

- 2 - See the Contract Conditions Window.
- 3 - See the Peripherals Screen; from which the Peripheral Conditions Screen can be accessed.
- 4 - See the invoice history.
- 5 - See any meter history.
- 6 - See meter reading statistics.
- 7 - See the scheduled visits.

Loc

The site, or installation address, code for the equipment; this need not be the same code as on the contract header.

Model

The model code for the equipment.

Serial

The serial number of the piece of equipment.

Stat

The status of the equipment on the contract:

Pen - Pending.

Act - Active.

Exp - Expired.

Del - Deleted.

Inc Dt

The date when the equipment was/will be included on the contract.

This date must lie between the contract start date and end date.

Rem Dt

The date when the equipment was/will be removed from the contract.

Resp Hrs

The contracted response time for the piece of equipment.

If a time is displayed, it will override the response time on the contract header.

Vst

0 - No visits have been generated.

1 - Scheduled visits exist.

Functions:**F13**

Fold/Truncate.

F21

Text.

Contract Type Enquiry



12/SSC

Use this option to enquire on the details of service contract types.

Contract Type Enquiry Initial Screen



Select Contract Type Enquiry.

SS532	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:19:23
Contract Type Enquiry			
Contract Type..... <u>B01</u>			
F3=Exit F4=Prompt			

Fields:

Contract Type

Enter a valid contract type.



Select a contract type and press **Enter** to display the Contract Type Enquiry Detail screen.

Contract Type Enquiry Detail Screen



To display this screen select a contract type on the Contract Type Enquiry Initial Screen and press **Enter**.

SS532	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:19:41
Contract Type Enquiry			
Contract Type..... B01 Basic cover			
Automatically Generate Service Schedule 1 (1=yes 0=no)			
Quotation required on renewal 0 (1=yes 0=no)			
Use Contract Start Date Rates 0 (1=yes 0=no)			
Response Hours Guarantee: (hhh:mm) 8:00			
Contract Duration (months)			
Termination notice in days			
Invoice Schedule..... 0 (0=Advance, 1=Visit, 2=Arrears)			
Contract Type Includes the following parameters (1=yes 0=no)			
Fixed Service Charge..... 1 Interim Charges..... 0			
Fixed Rental Charge..... 1 Reconciliation Charges. 0			
Fixed Visit Charge..... 0 Copies Incl. Rental.... 0			
Minimum Volume..... 0 Copy Charges 1..... 0			
Pre Billing Value..... 0 Copy Charges 2..... 0			
Pre Billing Volume..... 0 Free Copies..... 0			
Free Visits..... 0			
F3=Exit F12=Previous			

Fields:

Automatically Generate Service Schedule

This field is for future development.

Quotation Required on Renewal

0 - This type of contract is renewed as a pending contract.

1 - This type of contract is renewed as a quotation.

Use Contract Start Date Rates

0 - The labour rates and parts prices used in job pricing, for any jobs on equipment covered by this contract, are those effective on the date of call out, or the date of the engineer's visit.

1 - The labour rates and parts prices used in job pricing, for any jobs on equipment covered by this contract, are those effective at the contract start date.

Response Hours Guarantee

This is the normal response time guaranteed for equipment covered by this type of contract.

Used in job escalation routines.

Contract Duration

This is the standard contract duration, used to calculate contract termination.

If duration is set to 0 (zero), it indicates a contract which runs indefinitely.

Termination Notice in Days

The number of days entered is used by the contract credit program as the default penalty days for contract cancellation.

Invoice Schedule

- 0 - Contracts of this type are invoiced in advance.
- 1 - Contracts are invoiced after each scheduled visit.
- 2 - Contracts are invoiced in arrears. The invoice cannot be printed until after the end of any instalment period.

Fixed Service Charge

- 0 - No, fixed service charges may not be applied to this contract type.
- 1 - Yes, fixed service charges may be applied to this contract type.

The input fields for these charges will be displayed in the contract conditions window.

Interim Charges

- 0 - No, interim charges may not be applied to this contract type.
- 1 - Yes, interim charges may be applied to this contract type, and the input fields for these charge cycles will be displayed in the contract billing window.

Interim charges allow for actual or estimated copies, in excess of the minimum, to be invoiced periodically.

Fixed Rental Charge

- 0 - No, fixed rental charges may not be applied to this contract type.
- 1 - Yes, fixed rental charges may be applied to this contract type.

The input fields for these charges will be displayed in the contract conditions window.

Reconciliation Charges

- 0 - No, reconciliation charges may not be applied to the contract type.
- 1 - Yes, reconciliation charges may be applied to the contract type.

The input fields for these charge cycles will be displayed in the contract billing window.

Reconciliation charges allow for actual copies in excess of the minimum to be invoiced, or excess estimated copies which have been invoiced, to be credited at the end of the month.

Fixed Visit Charge

- 0 - No, fixed charge visits may not be applied to this contract type.
- 1 - Yes, fixed charge visits may be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Copies in Rental

- 0 - No, a value may not be keyed in for the number of copies per month.

1 - Yes, a value may be keyed in for the number of copies per month, which are included in the rental charge.

The input fields for these charge cycles will be displayed in the contract conditions window.

Minimum Volume

0 - No, minimum copy volumes may not be applied to this contract type.

1 - Yes, minimum copy volumes may be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Copy Charges 1

0 - No, copy charge bands will not be applied to this contract type.

1 - Yes, copy charge bands will be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Pre-Billing Value

0 - No, a predetermined value may not be applied to this contract type.

1 - Yes, a predetermined value may be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Copy Charges 2

0 - No, copy charge bands will not be applied to this contract type.

1 - Yes, copy charge bands will be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Pre-Billing Volume

0 - No, a predetermined volume may not be applied to this contract type

1 - Yes, a predetermined volume may be applied to this contract type.

The input fields for these charge cycles will be displayed in the contract conditions window.

Free Copies

0 - No, the number of free copies specified in the contract conditions will not be allowed on each monthly billing.

1 - Yes, the number of free copies specified in the contract conditions will be allowed on each monthly billing.

Free visits

Not currently used by the system.

Schedule Visit Profile Enquiry



13/SSC

Use this option to enquire on the details of scheduled service visit profiles on an ad hoc basis.

Scheduled Visit Profile Enquiry Initial Screen



Select Schedule Visit Profile Enquiry.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:21:48
Scheduled Visit Profile Enq'y			
Enter profile to enquire on.....?. ?__			
F3=Exit F4=Prompt			

Fields:

Scheduled Visit Profile Code

Enter a scheduled visit profile of up to three-alphanumerics.

A visit profile is a recommended pattern of planned maintenance visits which can be applied at contract, model, model group, or company level. The profile indicates both the service periods and job categories of the intended visits.

When a piece of equipment is added to a contract, visits can be generated, based on the pattern of the visit profile.



Select your profile and press **Enter** to display the Scheduled Visit Profile Enquiry Detail Screen.

Scheduled Visit Profile Enquiry Selection Screen



To display this screen select **F4=Prompt** on the Scheduled Visit Profile Enquiry Initial Screen.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:21:54
Scheduled Visit Profile Enq'y			
Profile		Profile	
_ 4PA 4 visits per annum			
F3=Exit			

Fields:

Untitled

Select. Enter 1 to select the required visit profile record; the profile Detail Screen will be displayed immediately.

Scheduled Visit Profile Code

A display of all current visit profile codes.

Profile Description

Descriptions for the current profile codes.



Select your profile and press **Enter** to display the Scheduled Visit Profile Enquiry Detail Screen.

Scheduled Visit Profile Enquiry Detail Screen



To display this screen select a profile and press **Enter**.

SS036	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:20:51
Scheduled Visit Profile Enq'y			
Profile: 4PA 4 visits per annum			
Relative Period	Job Category.....	Est. Hours	
1	PSV Planned service visit	1:00	
3	PSV Planned service visit	1:00	
6	PSV Planned service visit	1:00	
9	CAL calibration	1:30	
12	*RP	0:00	
F3=Exit		F12=Previous	

Fields:

Relative Period

This is the number of service periods, after the period in which a contract starts, in which a scheduled service visit will be generated. The relative period 0 would indicate a visit in the period in which the contract started.

Job Category code

This is the job category indicates the type of job which the engineer is going to do on the scheduled visit.



*Note: If *RP is displayed in the job category column, a repeat cycle of visits will be generated, using the visit profile, starting from the relative period shown to the left of *RP.*

Job Category Description

This is for the preceding code, the detail comes from the Job Category file.

Estimated Hours

This is an estimate of how long this type of job normally takes.



Press **Enter** to save any changes you have made.

Recommended Service Visits Enquiry



14/SSC

Use this option to enquire on the details of recommended visits per model group, on an ad hoc basis.

Recommended Visits Enquiry Initial Screen



Select Recommended Service Visits Enquiry .

SS528	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 17:37:13
Recommended Visits Enquiry			
Division.....?... 10			
Model Group.....?... 100			
F3=Exit F4=Prompt			

Fields:

Division

Enter a valid division code of up to two alphanumerics.

Model Group

Enter an existing model group for the selected division.

Each model group can have a scheduled visit profile attached, with an effective date. This will be used in the generation of scheduled service visits, if there is no visit profile specified at contract or model level.



Select a division and model group and press **Enter** to display the Recommended Service Visits Enquiry Detail Screen.

Recommended Visits Enquiry Detail Screen



To display this screen select a division and model group on the Recommended Visits Enquiry Initial screen and press **Enter**.

SS528	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		17:18:40
Recommended Visits Enquiry			
Division.....	10	Environmental Monitoring	
Model Group.....	100	Analysers	
Date	Visit Profile Code..		
1/01/94	4PA 4 Visits per annum		
1/01/93	2PA 2 Visits per annum		
F3=Exit F12=Previous			

Fields:

Effective Date

This is the date when a model group/visit profile association becomes active.

Scheduled Visit Profile Code

Must be a valid visit profile on the scheduled visit profile file.

The visit profile, with the correct effective date, will be used in the generation of scheduled service visits, if there is no visit profile specified at contract or model level.

Cover Type Enquiry



15/SSC

A cover type defines the charge conditions under which jobs are priced, and to which a service visit profile can be attached.

Use this option to enquire on cover types that already exist on the system.

Cover Type Enquiry Selection Screen



Select Cover Type Enquiry.

SS050	Z1 - GB Demonstration Company	USER GBJBATD0	24/09/97
	"BRUM" TRAINING & SERVICE BRANCH		12:16:52
Cover Type Enquiry			
Cover Type?.. ☐ NO			
F3=Exit F4=Prompt			
5-29 ☐ SA MW KS CL IM DM II EDN400A KB PKH317S1			

Fields:

Cover Type

Enter a cover type.



Press **Enter** to display the Cover Type Enquiry screen.

Cover Type Enquiry Screen



To display this screen press **Enter** on the Cover
Type Enquiry Selection screen.

```

SS050                Z1 - GB Demonstration Company      USER GBJBATD0      24/09/97
                    "BAUM" TRAINING & SERVICE BRANCH    12:17:06

Cover Type Enquiry

Cover Type..... *NO   No user contract

Service Visit Profile..?. ____

F3=Exit                F12=Previous

1-1    SA    MW    KS    CL    IM    DM    II    EDN400A    KB    PKH317S1

```

Contract Rates Enquiry



16/SSC

Use this option to enquire on the details of contract rates for a model group and term, by currency, on an ad hoc basis.

Contract Rates Enquiry Initial Screen



Select Contract Rates Enquiry.

SS030	Z1 - C&T TEST COMPANY	USER GBJBAJKG	28/02/96
	BIRMINGHAM BRANCH		16:34:58
Contract Rates Enquiry			
Division.....?	D1		
Model Group.....?	MG1		
Term.....?	12		
Currency Code.....?	GBP		
F3=Exit F4=Prompt			
05-27	SA	MW	KS IM II KENB20A PED129S1

Fields:

Division

Enter a valid division code of up to two alphanumerics; or, prompt for the code selection window.

Model Group

Enter a valid model group code of up to three alphanumerics; or, prompt for the code selection window.

Each model group can have contract rates attached, with effective dates. The current rate will be used, at Contract Pricing, to price a piece of equipment belonging to a particular model group.

Billing Term

Enter from 1 to 120 calendar months; the default value is 12.

Term defines the price protection period for the contract and the number of periods for which contract pricing will generate pending invoice and actual invoice records.

The contract rate selected for the contract header will be for the same term as that entered in the contract billing parameters.

Currency Code

Enter a valid three alphanumeric code, or prompt for the Code Selection Window.



Press **Enter** to display the Contract Rates

Enquiry Detail screen.

Contract Rates Enquiry Detail Screen



To display this screen press Enter on the Contract Rates Enquiry Initial screen.

SS030	Z1 - C&T TEST COMPANY	USER GBJBAJKG	28/02/96
	BIRMINGHAM BRANCH		16:37:10
Contract Rates Enquiry			
Division.....	D1	Division 1	
Model Group.....	MG1	Model Group 1	
Term.....	12		
Currency Code.....	GBP	<..... Charges>	
MG MSG Model	Typ	Eff.Date	Visit
MG1 MSG MODEL1	B10	31/01/96	50.00
			Rental
			3000.00
			Service
			2000.00

F3=Exit F12=Previous

01-02 **SF** MW KS IM II KENB20A PED129S1

Fields:

MG

The contract rates record will apply to this model group within the product division.

MSG

If shown, the contract rates will only apply to models which belong to this model sub-group within the model group.

Any contract rates for the model group will be overridden by the rates for the model sub-group.

Model

Must exist on the model file and be for the correct model group and model sub-group.

If a model number is shown these rates will override those for the model group or model sub-group in contract pricing.

Typ

Must exist on the Contract Type file.

Indicates the contract rates to be used in contract pricing depending on the contract type of the contract being priced.

Eff Date

This is the date on which the contract rates become active. All contract rates with earlier dates will be obsolete.

Visit

The charge per visit. This value is used in contract pricing. It is applied per visit.

Rental

Annual rental. This value is used in contract pricing. It is applied per contract term.

Service

Annual service charge. This value, also known as the fixed service charge, is used in contract pricing and is applied per contract term.

Contract Quotation Print



20/SSC

Use this option to print quotations for all contracts which have a status of Quote.

Use this option whenever contract quotations need to be sent out.

When you select this option from the menu, a batch job is submitted. The job will generate a printer file of quotations on the output queue.

The account address printed at the top of the report will be the contract invoice bill to account, if one exists.

After a quotation has been printed, it is flagged in order to prevent a repeat print when this option is next run.

Contract Renewal



21/SSC

Use this option to renew all contracts which are due to expire, and which are flagged as being renewable. This option should be used on a regular basis (for example, monthly).

Which Contracts Will Be Renewed?



Note: This procedure requires exclusive use of the company.

Contracts will only be renewed if the Renew Contract field on the contract header is Yes.

Contracts to be renewed must be Active; they must not be Pending or Expired, otherwise renewal will fail.

The contract termination date must be less than or equal to the date selected on the Contract Renewal Selection Screen.

How is the Renewed Contract Created?

The new contract will have a start date one day after the termination date of the original, and an end date of the start date plus the contract duration for the contract type.

The contract type will remain the same.

The contract number will depend on the setting of the company profile field New Contract No At Renewal. If this is set to No then the same number is retained, if it is set to Yes a new number is generated by the system, from the sequence on the company profile.

The status of the new contract is Pending start date, unless the contract type indicates that a quotation is required on renewal, in which case the status is set to Quotation. In the latter case, this will cause a quotation to be printed in the next run of the Print Contract Quotations option, and the quotation can subsequently be changed to a true contract through Contract Maintenance.

The renewal procedure will also renew the service schedule for each piece of equipment on the contract. This will depend on the following:

- If the existing schedule has the Use These Visits On Renewal field set on, the new schedule will mirror the existing one.
- If the existing contract header has a non-standard visit profile held against it, and is flagged to say Use The Non-Standard Profile On Renewal, the new schedule will be generated using the non-standard profile (and this profile will be attached to the new contract).
- If the existing contract header has a standard visit profile held against it, this will be used to generate the new schedule.
- If the model number for the piece of equipment has a standard visit profile, this will be used to generate the new schedule.

- If the model group for this piece of equipment has a standard visit profile, this will be used to generate the new schedule.
- If the company profile has a standard visit profile, this will be used to generate the new schedule. If not, then this procedure will not be able to generate a new schedule.

What Should Be Done After Renewal?

After contracts are renewed, check the equipment contract conditions (option 2 from the Contract Equipment Maintenance Screen in the Contracts Maintenance option). It is these conditions which will be applied when the contract is priced, not the conditions at header level.

Contract Renewal Selection Screen



Select Contract Renewal.

SS480P	Demonstration Company	USER BRERETM	24/11/93
	CENTRAL BRANCH		16:27:58
Contract Renewal			
Renew those which will expire on or before DDMMYY: <u>24/11/93</u>			
F3=Exit F8=Submit job			

Fields:

Expiry Date

Enter an appropriate, valid date in the format DDMMYY.



Select **F8=Submit** to submit the job for processing.

Contract Updating



22/SSC

Use this option to perform various housekeeping procedures on the contracts for a branch.

Note that the procedures included in this option are also included in the Day End Routines option, when they apply to the whole company.



Note: This procedure requires exclusive use of the company.

Description

When you take this option, a batch job performs the following processing on contracts owned by the requesting service branch:

- Any active contracts which have reached their termination date are identified and their status is set to expired. The installation is also updated, so it shows that the equipment is no longer covered.
- Any pending start contracts which have reached their start date have their status set to active. The installation is also updated, so it shows that the equipment is now covered.
- Pieces of equipment which are supposed to become active on a contract but are already covered by a different active contract are included on an error report.
- Contracts which have had a termination date entered before the end of their current term are selected for credit processing. The contracts will appear on the report of contracts selected for credit.



Tip: Because this processing is always performed as part of the Day End Routines option, this option would normally only be run if there was an urgent requirement to update a contract status during the day.

Request Quotes From Contract



23/SSC

Use this option to create contract quotations from existing service contracts.

Use this option if your customer already has a contract, and wants a quote for a different type of contract to cover the same equipment.

The new quotation can either be generated immediately, or the request can be stored and the new quotation generated later, by running the Generate Deferred Request Quotes from Contracts option.

Request Quotes From Contract Detail Screen



Select Request Quotes from Contract.

SS930	Demonstration Company CENTRAL BRANCH	USER BRERETM	24/11/93 16:33:04
-------	---	--------------	----------------------

Request Quote from Contract

New contract..... 9400115 ...?. B01 060494

Based-on contract..... 0000115 ...?. B01 060493

Service visits - copy(1)/generate(2)/none(3) 2

Service visit profile...?. 4PA

F3=Exit F4=Prompt F13=Process later F22=Process now

Fields:

New Contract

Enter an exclusive new contract number of up to seven alphanumerics.

Untitled

New Contract Type. Enter a valid contract type code of up to three alphanumerics; or prompt for the Code Selection window. If you are basing this new contract on an existing one, then both must have the same contract type.

Untitled

New Contract Start Date. Enter the date (DDMMYY) on which the new contract will start.

Based-On Contract

If you wish to base the new contract on an existing one, enter that existing contract here.

Untitled

Based-On Contract Type. If you wish to base the new contract on an existing one, enter the contract type of the existing contract here. This must be the same as the contract type of the new contract.

Untitled

Based-On Contract Start Date. If you wish to base the new contract on an existing one, enter the actual start date (DDMMYY) of the based-on contract here.

Service Visits

Enter one of the following:

1 - Copy. Only the existing, or remaining/outstanding, visits for each piece of equipment on the old contract will be copied to the new; leave Service Visit Profile blank;

2 - Generate. New visits will be generated for each piece of equipment on the new contract, for the contract's duration: this may be a more extensive series of visits than that set up by 1 - Copy; requires a valid entry in the service visit profile field;

3 - None. No visits will be set up; leave service visit profile blank.

Service Visit Profile Code

May be blank if 1 - Copy, or 3 - None, in Service Visits field. If 2 - Generate, Enter a valid scheduled visit profile code; or, prompt to display the code selection window. The profile code will be used to generate scheduled service visits for each piece of equipment on the new contract.

Functions:

F13

Process Request Later. Generate the new quotes at a later time by running the batch job Generate Deferred Request Quotes From Contract.

F22

Process Request Now. Generate the new quote now.

Generate Deferred Request Quotes From Contracts



24/SSC

Use this option to generate quotations from existing service contracts, using stored requests.

Description

A batch job is submitted to perform the processing. This takes outstanding requests for quotes from contracts (made through the Request Quotes from Contracts option) and generates contract quotation records. It copies the contract header and contract equipment records from the based-on contract to the new contract, and either copies or generates the service schedule records for the new contract.

Global Price Update



25/SSC

Use this option to apply percentage price increases, or decreases, to selected groups of product families, customers or contracts.

Description

Contracts can be coded by price code and/or by mantle code to allow selective price changes to be applied.

The choice of one or more criteria will select only those contract records to which the price change is to be applied, and then generate a new dated price list for those contracts.

The price change program is, by default, run as a model; that is, it will only update a work file and produce a report showing the current and new prices.

Once the model is confirmed as correct, the pricing program can be run to update the files directly.

Implications

Contracts are price protected by their term. The application of a global price change may generate a new dated price list for a contract, but it will not become effective until the end of the term even if the price list has an effective date prior to the end of the term.



Note: There is no provision for updating contract visit charges. Only service, rental and copy charges can be updated.

Global Price Update Detail Screen



Select the Global Price Update.

You must complete at least one of the seven selection fields (three contract selections and four price change selections).

SS905P	Demonstration Company CENTRAL BRANCH	USER BRERETM	21/12/93 11:54:13
--------	---	--------------	----------------------

Effective from date.....:	<u>1/01/94</u>		
Contract selection:	Mantle code...?..:		
	Price code....?..:	<u>MA</u>	Major Account Groups' Code
	Contract type.?..:	<u>B01</u>	Basic cover
Price change selection:			
	Division.....?..:		
	Model group...?..:		
	Model sub-grp.?..:		
	Model.....?..:		
	Service charge...:	<u>8.50</u>	%
	Rental charge...:	<u>2.50</u>	%
	Price per copy...:	<u>.00</u>	%
Update conditions file.....:	<u>0</u> (1=Yes/0=No)		

F3=Exit	F4=Prompt	F8=Submit Job
---------	-----------	---------------

Fields:

Effective From Date

Enter the date (DDMMYY) on which the update is to come into force.

Mantle Code

Enter a valid mantle code of up to five alphanumeric; or, prompt for the code selection window.

If entered, the code is validated against parameter type MANT on the Inventory Descriptions file. The mantle code determines which contracts are to be selected for the price update, by matching the entered code with that set up on the contract header.

Price Code

Enter a valid price code of up to two alphanumeric; or, prompt for the code selection window.

Code 00 is a system code, not for general use.

If entered, the price code will be validated against parameter type GLPR on the Codes/Parameter file.

The price code determines which contracts are to be selected for the price update. The entered code is matched against the global price code set up on the Contract Header Conditions (Service Parameters) Window.

Contract Type

May be blank (but one of the seven parameters must hold a positive value), else enter a valid contract type of up to three alphanumerics; or, prompt for the code selection window.

If a contract type is specified, the price update selection is limited to that type; if blank, all contract types within the other selection criteria will be included.

Division

May be blank (but one of the seven parameters must hold a positive value), else enter a valid division code of up to two alphanumerics; or, prompt for the code selection window.

If a division code is specified, the price update selection is limited to that division; if blank, all divisions within the other selection criteria will be included.

Model Group

May be blank (but one of the seven parameters must hold a positive value), else enter a valid model group code of up to three alphanumerics; or, prompt for the code selection window.

If a model group code is specified, the price update selection is limited to that model group; if blank, all model groups within the other selection criteria will be included.

Model Sub-Grp

May be blank (but one of the seven parameters must hold a positive value), else enter a valid model sub-group code of up to three alphanumerics; or, prompt for the code selection window.

If a model sub-group code is specified, the price update selection is limited to that model sub-group; if blank, all model sub-groups within the other selection criteria will be included.

Model

May be blank (but one of the seven parameters must hold a positive value), else enter a valid model code of up to 15 alphanumerics; or, prompt for the code selection window.

If a model code is specified, the price update selection is limited to that model code; if blank, all models within the other selection criteria will be included.

Service Charge

May be blank (but one of three percentage parameters must hold a value other than .00), else enter a percentage in the range 0.01 to 999.99, positive or negative.

Rental Charge

May be blank (but one of three percentage parameters must hold a value other than .00), else enter a percentage in the range 0.01 to 999.99, positive or negative.

Price Per Copy

May be blank (but one of three percentage parameters must hold a value other than .00), else enter a percentage in the range 0.01 to 999.99, positive or negative.

Update Contract Conditions

Default is 0; valid entries are 1 - Yes, or 0 - No. 1 - Yes will update the service, rental and price per copy charges on the Contract Conditions, to take account of the percentage changes specified above.



Select **F8=Submit Job** to submit the job for processing.

Copy Kit Batch Job



26/SSC

Use this option to report details of contracts based on copy volume, which will expire when an agreed volume of copies has been used.

Copy Kit contracts are based on providing service and materials (for example, paper, toner and so on) for either a predefined period of time, or a predefined number of copies, whichever runs out first.

Description

This function is only available if copies are selected on the contract type file: a Copy Kit select flag will be displayed on the contract header.

If copy kit is selected, the Minimum Copies, entered in the conditions window for the contract, become the number of copies for the termination of the contract.

Submitting the Copy Kit Batch Job reads the contract file and the meterage file, and produces a report of contracts which have reached the number of copies for termination.

Implications

The report enables you to decide whether to cancel or renew the contract.

The contract end date is the normal termination date for the contract. Contracts reaching this date are handled by the standard contract updating program; no report is produced.

Contract Credit Selection



27/SSC

Use this option to identify any contracts which have been terminated prior to their contracted expiry date, and may therefore require a credit.

It will also select expired contracts which need a retrospective credit.

This presupposes that Contract Maintenance has already been used to reset the Contract End Date on the Header Screen, particularly if it is a header priced contract; alternatively, Remov dt on the equipment records may be reset if the contract is not header priced, and only certain machines are to be omitted and credited.

Description

Contracts must be selected for credit before Contract Credits Maintenance can be accessed. Contract Credits Maintenance is described in another section of this product information.

The selection process does the following:

1. Selects records for both pending and actual invoices. Pending invoice records will not produce a credit, but the value will be recalculated to ensure the correct value is used when the invoice is produced;



Note: If there are pending invoice records on SSP44, but no invoice recalculation is involved, remove the equipment via contract maintenance. Generate and Print (Contract) Invoices will clear the records from SSP44 on the removal date specified.



Note: Do not attempt to use contract credit functionality, as no invoice amount will need to be credited.

2. Puts the selected records in a work file, together with the expected credit and re-invoice values; these are based on the termination date plus the penalty days defaulted from the Termination Days on the contract type file;
3. Produces a report of all the records which are in the work file, which require editing or acceptance. The section Contract Credit Maintenance, provides details of the processing required after the report, Contracts Awaiting Edit and Acceptance of Credits/Re-Invoices, has been run.

Selection Of Contracts For Credit Screen



Select Contract Credit Selection.

```
SS423P          Z1 - GB Demonstration Company   User GJBABL T   8/03/96
                  "BRUM" TRAINING & SERVICE BRANCH 9:46:52
Selection of contracts for credit:

Branch.....?..: BT      (*A for all)
Contract number.....: _____ (Blank for all)
Contract type.....?..: _____
Contract date.....: 0/00/00
Invoice number.....: _____

Contracts terminating on or before.....: 8/03/96

F3=Exit  F4=Prompt

06-47  SF  MW  KS  IM  II  KENB20A  PED129S1
```

Fields:

Branch

The branch will default to the current branch. You can change it to any branch you are authorised to, or to all branches if you have blanket branch authority.

If you only enter the branches and the termination date, then all contracts terminating on or before this date will be selected.

Contract Number

Enter a contract number to select a specific contract for credit, or blank to select all contracts. Pending, active, deleted and expired contracts which have been priced and/or invoiced will be accepted. The contract number (if used) needs to be entered in conjunction with the contract type and date (below).

Contract Type

Enter a contract type.

Contract Date

Enter the start date of the contract number and type which have been entered above.

When selecting an expired or deleted contract for credit, only the number, type and date need to be entered.

Invoice Number

Enter the invoice number in the format Innnnnnn to select a contract which has been invoiced and requires credit, or leave blank to select all invoices for the contract entered above.

Contracts Terminating On Or Before

Defaults to the current date, on or before which credits for terminating contracts are to be processed. A later, but not an earlier, date may be substituted.



Select **F8=Submit Job** to submit job for processing. This function key will only be displayed after the selection screen has been validated and contains no errors.

Contract Credit Selection Report Layout

After the batch run has completed successfully, a report is available entitled Contracts Awaiting Edit And Acceptance Of Credits/Re-Invoices.