

-
-
-
-
-

Chapter 1

Production Order Control



Production Order Control Introduction

This section reviews order creation, maintenance and release procedures.

Production Order Control is the Production module which controls and directs the movement of production orders through all the production processes from the transfer of raw materials and components into work-in-progress to the delivery of finished goods into Inventory.



Note: Controlling and directing the movements of purchase orders is undertaken by the Purchase Management application

Production Order Control provides facilities to control and monitor actual shop floor line activities.

Production orders can be automatically created from:

- Master Production Schedule, (MPS) runs
- Material Requirements Planning, (MRP) runs
- Manual Entry

Each item to be produced has a unique order number against which materials may be issued and operational bookings made.

Production orders have a different status according to which stage they have reached in the production process.

Works planning facilities provide methods for determining the priority of production orders at each work station, shortage reporting and extensive on-screen enquiries.

The system can be used to provide production documentation:

- Material pick lists
- Work instructions

Material movements are controlled in two ways:

- Raw materials from Inventory into work-in-progress
- Finished items from work-in-progress to Inventory

Extensive operational recording facilities are provided.

Production Order Status Control

A production order is a document which sets out the details of the production of a specific item in specific quantities and which is used as an authority to carry out the production processes required.

Each production order passes through a number of stages in its life cycle. Each stage is referred to as an order status. Abbreviations are used for each order status for enquiries. They are:

DESCRIPTION	ALPHA CODE	NUMERIC CODE
SUGGESTED	SUG	not used

PLANNED	PLN	1
CONFIRMED	CON	2
RELEASED	REL	3
ACTIVE	ACT	4
COMPLETE	FIN	8
CANCELLED	CNL	9

The following tables compare and contrast production orders of different status.

Production Order Status: SUGGESTED		SUG	
CREATED BY			
• MPS runs • MRP runs			
CHARACTERISTICS			
• The orders only appear in MPS or MRP • Enquiries cannot be made on these orders in Production Control • The orders are for a specific item and stockroom • They have a planning route code, a due date and a quantity			
POSSIBLE ACTIONS			
• Firm up into a CONFIRMED order by taking the appropriate action in MPS and/or MRP • Take no action, in which case any remaining suggested orders are deleted by the next run			

Production Order Status: PLANNED	PLN	1
CREATED BY		
• Direct entry into Production Order Control		
CHARACTERISTICS		
• These orders represent a planned supply but there is (as yet) no demand for materials or resources • The orders are for a specific item and stockroom • They have a planning route, a due date and a quantity • Planned orders can be created with non-standard routes, the route details being entered when the order is raised. This then becomes an amended standard route for this order only • They are shown as on order in the Inventory system		
POSSIBLE ACTIONS		
• Convert into a CONFIRMED order by using the <i>Order Maintenance</i> facility in Production Control • Maintain the route details, due dates and quantities • Convert into a CANCELLED order by using the order <i>Maintenance</i> routine		

Production Order Status: CONFIRMED	CON	2
CREATED BY		
- Firm up of SUGGESTED orders in MPS and MRP - Conversion of PLANNED orders in Production Control		
CHARACTERISTICS		
- These orders establish a demand for materials and resources - The orders have the same characteristics as SUGGESTED orders, but with the full route details listing materials required and resources to be used - They are shown as on order in the Inventory Management application		
POSSIBLE ACTIONS		
- Convert into a RELEASED order - Maintain route details, due dates and quantities - Convert into a CANCELLED order by using the <i>Order Maintenance</i> facility		

Production Order Status: RELEASED	REL	3
CREATED BY Release of single or multiple CONFIRMED orders in Production Control		
CHARACTERISTICS - Materials may be issued to this order and operational details may be booked - On release several tasks are available: - change the order priority - print the order document - issue materials for the first operation only, or for all operations - allocate materials (if already issued and allowed in the company profile)		
POSSIBLE ACTIONS - Make operational bookings - Issue further materials - Maintain route details and due dates - Convert into a COMPLETE order by: booking finished goods into Inventory, within Production Control; using the manual <i>Order Completion</i> facility - Convert into a CANCELLED order by using the <i>Order Completion</i> facility		

Production Order Status: ACTIVE	ACT	4
CREATED BY		
Material issues and/or bookings being made against a RELEASED order		
CHARACTERISTICS		
The orders have the same characteristics as RELEASED orders		
POSSIBLE ACTIONS		
- Make operational bookings - Issue further materials - Maintain route details and due dates - Convert into a COMPLETE order by: booking finished goods into Inventory, within Production Control; using the manual <i>Order Completion</i> facility - Convert into a CANCELLED order by using the <i>Order Completion</i> facility		

Production Order Status: COMPLETE	FIN	8
CREATED BY		
- Transfer of finished goods on a RELEASED or ACTIVE order to Inventory - Manual completion of RELEASED or ACTIVE order		
CHARACTERISTICS		
No material issues or bookings are allowed to these orders		
POSSIBLE ACTIONS		
- Re-open and make further bookings - Delete all COMPLETED orders by using the <i>Order Archiving</i> routine		
Production Order Status: CANCELLED	CNL	9
CREATED BY		
Use of the <i>Order Deletion</i> facility within the <i>Order Completion</i> task on PLANNED, CONFIRMED, RELEASED, or ACTIVE orders		
CHARACTERISTICS		
These orders are not accessible and so cannot be maintained in any way		
POSSIBLE ACTIONS		
None, except enquiries are possible		

Order Processing

Order Processing contains:

- Order entry
- Order maintenance
- Order release
- Material issue
- Documentation issue
- Production planning
- Order completion
- Receipt of finished goods
- Monitoring progress by means of enquiries and reports
- Measurement and evaluation of performance

These are explained in the remaining sections of this product information.

Potency

The Inventory Management application has facilities for supporting lot control and for the definition of potency, if it is required for an item.

Potency is used when the strength or the effectiveness of an input must be measured to ensure that the final product is of acceptable quality.

There are a variety of industries and processes which are able to make use of the potency control in their production. The brewing industry is one example where some of the raw materials are natural ingredients and are therefore not all exactly the same. The strength and quality of the hops may vary, not only from year to year, but also from farm to farm.

To use a recipe which calls for a given physical quantity of hops each time a brew is made, takes no account of the actual hops used.

Not all inputs require potency control. For those that do, the standard potency (that is, the normally expected potency) is set on the Lot Header Details. This can then be used when creating or maintaining routes to ensure that the route details produce the correct quality for the finished item.

In order to do this calculations are made to determine the number of potency units required to make the finished item to the standard required.

Potency is expressed in the form of a percentage. If for example we had 100 physical units with a potency of 80%, then we would calculate that there would be 80 potency units available from this material.

In order for the potency calculations to be effective the items MUST be lot controlled.

Shelf Life

Shelf life is a feature of the Inventory Management application which limits the availability of specific lots and/or batches of material to a fixed period.

This period is normally expressed in days, weeks, months or even years from the date it is first received. The goods receiving procedures recognises that the material is subject to a limited shelf life and prompt for expiry dates and if selected an expiry time.

Items subject to potency control may well have a limited shelf life.

Production Order Processing

Potency control must be carried out by creating a production order. This is done in the normal way by either:

1. Conversion of suggested order in MPS/MRP, or
2. Manually using Maintain Orders on the menu.

When the order has been created, it may then be released. The normal procedure when processing a production order subject to lot control is:

1. Raise the order (Maintain Orders) or from MPS/MRP
2. Release and batch balance the order (Release Orders)
3. Enquire on batch balance (Production Batch Balancing) if required

4. Issue material

Calculation of Equivalent Physical Quantities Example

The standard potency of a finished product is 50% using 1000 physical units.

We have a stock lot of 2000 physical units at an actual potency of 40%. How many physical units of this lot must be issued to make the standard potency ?
The finished product must have 500 potency units because this is the standard.
To calculate the physical units required the calculation is:

Potency Units Required

Actual Potency %

This is: $500 \times 100 / 40$

= 1250 physical units

This can also be expressed as:-

Physical Units X Potency = Standard Potency Units

Physical Units X 40% = 500. Therefore Physical Units = $500 / 40\% = 1250$

Normally we would have used 1000 physical units at a standard potency of 50% to make the finished item but because the actual potency is only 40% we have had to use 1250 to achieve the final result.

This is the figure which is used by MPS/MRP in planning.

Order Release

Order release contains the option to allocate materials from specific lots. If these lots contain different levels of potency, then selections must be made to ensure that the correct number of potency units are used. This process is called Lot Balancing and is undertaken as part of the order release option.

Maintain Orders



1/PCM

The main purpose of this task is to maintain production orders. Order Maintenance covers:

- Order review.
- Operation and input selection.
- Operation maintenance.
- Input maintenance.
- Text maintenance.
- Inclusion of operations and inputs from another order or route

The task can also be used to enter new orders, but this is more likely to be done automatically via MRP and MPS.



When Maintain Orders is selected on the menu, the first Production Order Maintenance screen is displayed.

Production Order Maintenance Screen 1



When Maintain Orders is selected on the menu, the first Production Order Maintenance screen is displayed.

The following fields and functions are displayed:

PC130	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95
Production Order Maintenance			15:23:04
Production Order...?:			Week: 49 95
OR Select by:			
Item.....?:	_____		
Route.....?:	_ or 1 (1=All routes)		
Reference.....?:	_____		
Order Type.....:	_ (1=Standard 0=Non-standard)		
Orders Due from.....:	_8/12/95 to: 8/12/95		
F3=Exit F4=Prompt F8=Create new order F16=Review orders			
05-26	SA	MW	KS IM II KENB20A PET166S2

Fields:

Production Order

Enter an order number and select **F8=Create New Order**. The second Production Order Maintenance screen is displayed.

Or Select By

You can display all the orders that meet your criteria on the Production Order Selection window, and then select one to edit. The order is then displayed on the second Production Order Maintenance screen.

Item

If you enter an item code you see all orders for this finished item, subject to the next three selection criteria. If you leave blank you see all orders for all finished items, again subject to the next three selection criteria.

Route

For a single route enter its code in the first field. For all routes enter 1 in the second field.



Note: Do not enter details in both fields.

Reference

Use this to select orders based on the entries made in the Reference 1 field on the order header.

Order Type

You can enter one of the following options:

0 - Non-Standard. For orders based on non-standard routes.

1 - Standard. For orders based on standard routes (including amended standard).

Orders Due From/To

Enter dates required.

Functions:

F16

Review Orders. When you select this option, the selection criteria you entered above is used to display a list of orders in the Production Order Selection window, explained below.



*Note: When **F16=Review Orders** is selected, the Orders Due From and Orders Due To fields default to the current date.*



When you select an order to edit, the order is displayed on the second Production Order Maintenance screen.

Production Order Selection Window (F16)

The window contains a list of orders meeting the selection criteria/dates set on the first Production Order Maintenance screen.



When **F16=Review Orders** is selected on the first Production Order Maintenance screen, the Production Order Selection window is displayed.

The following fields and functions are displayed:

```

PC130              Z1 - GB Demonstration Company    USER GBJBAMS    8/12/95
Production Order Maintenance                        15:29:08
                                                    Week: 49 95
Production Order...?..: _____

Production Order Selection
-----
S T Order  Item/Group  Sts  Order Qty UOM St Due Date R Reference
-   W000182 MS001      2      5.000 EA FG 11/12/95 1
-   W000183 MS001      2     48.000 EA FG 27/12/95 1
-   W000184 MS001      2     12.000 EA FG 31/01/96 1
-   W000185 MS001      2     30.891 EA FG 26/01/96 1
-   W000186 MS001      2     21.517 EA FG 27/02/96 1

1=Select  2=Text
Position to:
F12=Previous  F22=Expand/Contract

22-32  S2  MW  KS  IM  II  KENB20A  PET166S2
  
```

Fields:

S

You can enter one of the following options:

1 - Select. You can edit an existing order. When you enter this option in this field, the second Production Order Maintenance screen is displayed, containing the details of the selected order.

2 - Text.

Functions:

F22

Expand/Contract. This is a toggle key which displays more or less information about all the orders listed in the window.

Production Order Maintenance Screen 2

For an existing order, the following fields are displayed for your information only and cannot be amended:

- Order Number.
- Status.
- Order Type.
- Item.
- Process Group.
- Route Code.
- UOM.
- Stockroom.
- Shelf Life Val.



Note: For process groups, enter a process group in the Item field. Process groups containing co-products cannot be non-standard, and must have a status of Confirmed (they cannot have a status of Planned).



When an order number is entered in the Production Order field on the first Production Order Maintenance screen, or 1 is entered in the S field on the Production Order Selection window, the second Production Order Maintenance screen is displayed.

The following fields and functions are displayed:

PC151	E3 - Enterprise-Adv-with MPL	USER GBJBAJFW	29/01/98
Production Order Maintenance			11:24:07
			Week: 04 98
Order Number.....	W000001	* Existing order maintenance.	
Status.....	Released		
Order Type.....	1 Standard		
Item.....	CAR	A-Car	
Process Group....			
Route Code.....	1		
Quantity.....	10.000	UOM.....	EA
		Stockroom:	G2
Due Date.....	10897	Due Week.....	3097
Start Date.....	10797 OR	Start Week.....	2697
Latest Start Date:	10897	Latest Start Week:	3097
Calendar Code...?	01	Reference 1.....	
Planning Filter.?	-	Reference 2.....	
Output Validation.	0	Shelf Life Val....	0
Firm Planned Order	- (1=Yes)		
F3=Exit F4=Prompt		F8=Update order	F12=Previous
		F18=Amend details	F21=Text
14-22	SA	MW	KS CL IM DM II
STUD140		KB	PET165S1

Fields:

Order Number

This field displays your order number if this was entered on the order selection screen, or you can enter an order number now.

Leave blank for the system-generated number.

For an existing order, this field is displayed for your information only and * Existing Order Maintenance is displayed to the right of the order number.

Status

This field is displayed for your information only.

Order Type

The following can be displayed:

0 - Non-Standard. All the operations and inputs needed to define the order must be entered manually.

1 - Standard. The system generates all the operations and inputs from the route as defined in the database.



Note: Non-standard orders cannot be created for a Process Group with lot balanced items. It can however be amended after it has been created.

For an existing order, this field is displayed for your information only.

Item

Enter the finished item code.

For an existing order, this field is displayed for your information only.

Process Group

This field is displayed for your information only.

Route Code

For a standard order enter the code of the required route.

For an existing order, this field is displayed for your information only.

UOM

Units Of Measure. This field is displayed for your information only.

Quantity

Order Quantity. For standard orders, if left blank, the quantity defaults to the economic order quantity defined on the associated route.



Note: Quantity cannot be altered once an order is released.

If the order item is a process group, the quantity is used to calculate equivalent quantities of output items that are produced by the order, by using the output item standard quantity relationships defined on the selected process group route.

If the order item is a co-product on a process group, the associated co-products, by-products and waste products defined on the route are calculated in the appropriate ratio defined on the route.

Stockroom

Receiving Stockroom. This field is displayed for your information only.

Due Date

This field contains the date by which the order must be completed. It may be derived in one of three ways:

- Directly enter a date.
- Let the system calculate the due date from the Start Date by forward scheduling.
- Leave this, the Start Date and Start Week blank, and the due date defaults to the Friday of the specified Due Week.

Due Week

This field contains the number of the week when the order is to be finished.

- Leave blank and the system calculates a value from the Due Date using the associated week in the calendar.
- Enter a value and the Due Date is calculated from it as described in Due Date above.

Start Date

This field contains the earliest start date on which work can begin, or the date upon which you wish to begin the order. It may be derived in one of several ways:

- Entered directly.
- Calculated from the due date by backward scheduling.
- It defaults to the current date if neither the start date and start week are specified.
- It defaults to the first working date of the start week if the start day is blank, but the start week contains a value.

Start Week

This field contains the number of the week when the order is to be started.

If the start date field has been left blank, it defaults to be the last working date of the specified start week.

If the start date has been entered without a start week, the latter is calculated using the associated week number on the calendar code field, or the default calendar set on the company profile.

The week is displayed on the format NNYT where NN is the week number, and YY the year.

Earliest Start Date

This field is shown after update of the order. It normally displays the same date as the start date; where back scheduling is used, it displays the latest date the

job must start - which may be before the start date. In this case, it is advisable to enter this earliest start date as the start date, to determine what effect this has on the due date of the order.

Latest Start Date

This is calculated from the due date by backward scheduling using the lead time of the order. It is the latest possible date at which the order can be started and just meet the due date of the order. It is of course possible that the date is in the past, if the available time is less than the lead time. An error message to this effect is displayed.

Latest Start Week

This is calculated from the latest start date using the associated week number from the calendar.



Note: When amending existing dates don't forget to blank out Start Date/Start Week/Due Date/Due Week as appropriate, so that the above choices work properly.

Calendar Code

Enter the code of the calendar to be associated with this order.

Leave blank if you want to use the default code specified in the company profile.

Planning Filter

This entry specifies the rescheduling policy for this order in MPS/MRP planning routines.

Reference 1

This optional field can be used to provide a reference for identification or grouping purposes. There is an on screen enquiry facility which can use this field to select an order or group of orders.

Reference 2

This optional field can be used to provide a reference for identification or grouping purposes. There is an on screen enquiry facility which can use this field to select an order or group of orders.

Output Validation

On making production bookings against this order, for process items, a check can be made to ensure that the quantity of all the co-products agree.



Note: For process groups, the output validation field defaults to 0 and overrides the route setting. Other details are entered normally.

Shelf Life Value

This flag is only effective for lot controlled items and allows the order to have a different shelf life validation policy from that normally associated with the item.

This flag may only be maintained for a standard order at Planned order status; once the order has been Confirmed, it cannot be changed. For non-standard orders, the flag may be maintained at Confirmed status.

The following can be displayed:

0 - For no check to be performed when issuing lots.

1 - When issuing lots to a production order, a check is performed and a warning displayed if the selected lots become unavailable (that is, past their last available date) before the parent item itself becomes unavailable. This is calculated from the order due date and the parent's shelf life. No check is carried out for automatic allocation and issuing.

For existing orders, this field is displayed for your information only.

Firm Planned Order

1 - Yes. When the order is processed the following actions will occur :

- Netting will take place after normal supply has been considered.
- Filter settings will be ignored.
- Cancellation, re-schedule in/out are prohibited.
- Suggested quantity change is allowed, but is non-executable (only an indication of the suggested supply requirement).
- Dependent demand is always generated from the firm supply quantity.
- The production lead time is calculated from the firm supply quantity.
- The available stock figure displayed via the planning reviews will only consider the firm quantity.



If a new order is displayed, press **Enter** to display the Output Quantity Maintenance window.

Functions:

F8

Update Order. Select this function to add an order with a status of Planned.

Press **Enter** to validate your entries; this allows the system to automatically enter the item Economic Order Quantity (EOQ) as the order quantity and the current date as the start date/start week and the due date/due week.

Select **F19=Create Details** to create an order with a status of Confirmed and:

- Increment the on order quantity on the Inventory Stock balance.
- Create the operation and input records from the specified route if this is a standard order.

Taking this function key against an existing Planned order changes its status to Confirmed.



*Note: For process groups, **F8=Update Order** adds a Confirmed order immediately, because the status of Planned is not allowed.*

F15

Redistribute Qty. This function is only displayed when editing an existing order. When you select this function, the Output Quantity Maintenance window is displayed. This allows maintenance of the output quantities.

F18

Amend Details. When you select this function, the Production Order Maintenance - Inputs screen is displayed.

F21

Text. When you select this function, the second Text Maintenance screen is displayed. This enables you to add, change and delete text. For more information see Production Definition Maintenance.

F24

Display Outputs. This function is only displayed when editing an existing order. When you select this function, the Output Quantity Maintenance window is displayed. This contains the existing outputs, and is displayed for your information only.

Output Quantity Maintenance Window (F15/F24)

- ➔ If editing an existing order, when **F15=Redistribute Qty** is selected on the second Production Order Maintenance screen, the Output Quantity Maintenance window is displayed. This window allows maintenance of the output quantities.
- ➔ If editing an existing order, when **F24=Display Outputs** is selected on the second Production Order Maintenance screen, the Output Quantity Maintenance window is displayed. This window is displayed for your information only.
- ➔ When **Enter** is pressed on the second Production Order Maintenance screen, the Output Quantity Maintenance window is displayed. This window displays all the respective outputs from the standard route for a standard order based on the order quantity of the process group entered on the header screen.

The following fields and functions are displayed:

PC151		Z1 - GB Demonstration Company		USER GBJBAMS	13/12/95
					16:06:24
Production Order Maintenance					Week: 50 95
Order Number.....: _____		* Enter new order details.			
Order Type.....: 1 (0=Non-Standard)					
Item.....?..: MS003		Co-product process group			
Process Group...?: MS003		Co-product process group			
Route Code....?..: 1					
Output Quantity Maintenance					
Output Item	Output Type	Quantity	Prmy	UOM	Stkrn
COP01	1 Co-product	300.000	1	EA	FG
COP02	1 Co-product	100.000	-	EA	FG
BYP01	2 By-product	500.000	-	EA	FG
WAS01	3 Waste	400.000	-	EA	FG
F8=Update F12=Previous					
F3=Exit F4=Prompt		F8=Add new order		F12=Previous	
F16=Item search		F19=Create details			
13-41		SA	MW	KS	IM II KENB20A PET166S2

Fields:

Output Item

This field displays the name of the output item.

Output Type

This field displays the output type, for example:

- 1 - Co-Product.
- 2 - By-Product.
- 3 - Waste.

Quantity

For each output item, you can enter the quantity.

Prmy

Primary. You can decide which item is the primary by entering 1 in this field.

UOM

Unit Of Measure. This field displays the unit of measure.

Stkrm

Stockroom. This field displays the name of the stockroom.



If you can maintain the output quantities, when **F8=Update** is selected the database is updated and the second Production Order Maintenance screen is displayed.



If the output quantities can only be displayed, when **F12=Previous** is selected the second Production Order Maintenance screen is displayed.

Production Order Maintenance Inputs Screen (F18)

This screen allows you to:

- Maintain operations.
- Maintain inputs.
- Copy operations and inputs from another order.
- Copy operations and inputs from another route.
- Re-sequence the operations and inputs.



When **F18=Amend Details** is selected on the second Production Order Maintenance screen, the Production Order Maintenance - Inputs screen is displayed.

The following fields and functions are displayed:

PC152	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95		
Production Order Maintenance - Inputs			15:31:05		
Order Number: W000182 Item: MS001		Quantity: 5.000	UOM: EA		
Stockroom: FG		Product A			
0 Opsq	Insq	Input	ST UM Description	Quantity	Shr%
-			Operation 10		.0
-	10	RAM01	RM EA Raw material 1	11.700	.0
-	20	RAM02	RM EA Raw material 2	25.000	.0
-	30	RAM03	RM EA Raw material 3	10.000	.0
-	40	RAM04	RM EA Raw material 4	7.500	.0
-	20		Operation 20		.0
-	30		Operation 30		.0
1=Maintain 2=Add Input Item					
Enter Sequence to maintain Or Position to Operation					
F3=Exit F8=Update F12=Cancel F17=Copy Order/Route F19=Re-sequence					
F20=Maintain Outputs F21=Maintain Inputs & Outputs					
20-30 SF MW KS IM II KENB20A PET166S2					



To add/edit an input, enter *both* an Operation Sequence number and an Input Sequence number in the second Production Order Maintenance -Inputs screen, then press **Enter**. The Input Item Maintenance window is displayed.

This screen allows:

- A new operation to be added
- An existing operation to be amended
- An existing operation to be deleted



Press **Enter** to save an amended/new operation.

The next operation details are displayed. Use **F12=Cancel** without update to return to the second Production Order Detail Maintenance screen.



Note: An amendment or deletion of an operation is not allowed if this or subsequent operations are active or complete.

Considerations on amending production orders:

- If the shrinkage factor is changed you must manually change the times and the input quantities to take account of the change.
- The times displayed are the total duration time for this operation.
- If you make any amendments to the order details, the Order Type shown on the order header is changed to Amended Standard.
- Having made changes to the details or header date, the start date is compared with the current date. If there is insufficient time to complete the order a message latest start date is before today's date is displayed.

Functions:

F17

Copy Order/Route.

F19

Re-Sequence. Re-sequence the operation and input sequence numbers in steps of 10. It is worth doing after inserting/deleting operations and inputs.

F20

Maintain Outputs. Allow outputs to be maintained.

The Output Item Maintenance window is similar in operation to Input Item maintenance. In addition, when booking production information, you do not necessarily have to enter amounts against the main item of the process in order to reflect that quantities of co-products, waste products and by-products exist. Outputs defined with zero quantities are highlighted as warnings but do not prevent the entry of other output type detail.

F21

Maintain Inputs & Outputs. Allows inputs and outputs to be maintained.

Input Item Maintenance Window

This screen allows:

- A new input to be added
- Or, an existing input to be amended
- Or, an existing input to be deleted - select **F11=Delete** twice



Note: Deleting an input is not allowed if an issue has taken place.



To add/edit an input, enter *both* an Operation Sequence number and an Input Sequence number in the second Production Order Maintenance -Inputs screen, then press **Enter**.
The Input Item Maintenance window is displayed.

The following fields and functions are displayed:

PC152		Z1 - GB Demo		Input Item Maintenance	
Production Order Maintenance - In				Operation	10 Input Seq. 10 UPDATE
Order Number: W000182 Item: MS00				Input Item.....	RAM01
Stockroom: FG Prod				Input Type.....	0 Material
				Issuing Stockroom ..?	RM
0 Opsq Insq Input ST UM				Quantity	11.700
-				Fixed Quantity Per....	(1=Yes)
-				Shrinkage %	.0
-				Change Reference	
-				Effective From Date ...	
-				Effective To Date	999999
-				UOM Conversion Factor..	
-				Substitution Allowed... 1	(1=Yes)
1=Maintain 2=Add Input Item				F4=Prompt F11=Delete F12=Cancel	
Enter Sequence to maintain 10					
F3=Exit F8=Update F12=Cancel F					
F20=Maintain Outputs F21=Maintain Inputs & Outputs					
06-62 Sf MW KS IM II KENB20A PET166S2					

Fields:

Operation

The operation is displayed for your information only.

Input Seq

The input sequence is displayed for your information only.

Input Item

The input item is displayed for your information only.

Input Type

The input type is displayed for your information only.

Issuing Stockroom

You can enter the stockroom in this field.

Quantity

You can enter the quantity in this field.

Fixed Quantity Per

You can enter one of the following options:

0 - No.

1 - Yes.

Shrinkage %

You can enter the shrinkage percentage in this field.

Change Reference

You can enter the change reference in this field.

Effective From Date

You can enter the effective from date in this field.

Effective To Date

You can enter the effective to date in this field.

Uom Conversion Factor

You can enter the unit of measure conversion factor in this field.

Substitution Allowed

You can enter one of the following options:

0 - No.

1 - Yes.



Press **Enter** to save an added/edited input. The next operation details are displayed. When **F12=Cancel** is selected without update, the second Production Order Detail Maintenance screen is displayed.

Copy Order/Route (F17)

This screen is used to select either a route or an order, from which to copy details.



When **F17=Copy Order/Route** is selected on the Production Order Maintenance - Inputs screen, additional fields are displayed.

The following fields and functions are displayed:

PC152	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95
Production Order Maintenance - Inputs			15:32:03
Order Number: W000182	Item: MS001	Quantity: 5.000	UOM: EA
Stockroom: FG	Product A		
0 Opsq	Insq	Input	ST UM Description
-			Operation 10
-	10	RAM01	RM EA Raw material 1
-	20	RAM02	RM EA Raw material 2
-	30	RAM03	RM EA Raw material 3
-	40	RAM04	RM EA Raw material 4
-	20		Operation 20
-	30		Operation 30
			Quantity Shr%
			11.700 .0
			25.000 .0
			10.000 .0
			7.500 .0
			.0
			.0
Include at Sequence No.. 0000			
Copy from Item/Route...?		Explode Phantoms.. 1 (1=Yes)	
OR Order Number..?			
F4=Prompt F12=Cancel Copy F16=Item search			
19-29	SF	MW	KS IM II KENB20A PET166S2

Fields:

Include At Sequence No

Enter the operation sequence number at which the new details are to be added/inserted.

For route:

Copy From Item/Route

This contains two fields. You can enter an item code in the first field.

You can also enter an existing route for the item selected in the second field.

Or Order Number

Alternatively, you can enter the order number.

Explode Phantoms

You can enter one of the following options:

0 - No.

1 - Yes. When you enter this option, you can copy the inputs from phantom items. (With production routes copy only).



When **Enter** is pressed, the Production Order Maintenance - Copy From Another Route screen is displayed.

Functions:

F16

Item Search.

Production Order Maintenance Copy From Another Route Screen



When **Enter** is pressed on the Copy Order/Route screen, the Production Order Maintenance - Copy From Another Route screen is displayed.

The following fields and functions are displayed:

PC158	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:33:46
Production Order Maintenance - Copy From Another Route			
Order Number W000182		Item MS001	Product A
Copy details from:-			
Route Code	1	Item MS001	Product A
Op.Sq	Cp.Sq	Component	St Description Quantity
10			Operation 10
10	10	RAM01	RM Raw material 1 11.700
10	20	RAM02	RM Raw material 2 25.000
10	30	RAM03	RM Raw material 3 10.000
10	40	RAM04	RM Raw material 4 7.500
20			Operation 20
30			Operation 30
Copy details from operation sequence: _____ to operation sequence: _____			
OR position display at operation seq: _____			
F12=Previous			
20-43		MW	KS IM II KENB20A PET166S2

Fields:

Copy Details From/To Operation Sequence

You can enter the range of operations to be copied. Both the from and to operations and their inputs are included.

Or Position Display At Operation Seq

You can enter the operation that you want at the top of the display. (Then enter the range of operations to be copied.)



Press **Enter**, then select **F8** to copy the operation sequence from one place to another.

Production Batch Balancing

1... 2/PCM

This option allows enquiries to be made to orders that have already been balanced on release but not yet issued. This window is the same window displayed in Order Release. Amendments can be made to the lots using this option, but no updates.



When Production Batch Balancing is selected on the menu, the Lot Balancing Maintenance screen is displayed.

The following fields and functions are displayed:

```

PC320                Z1 - GB Demonstration Company    USER GBJBAMS    13/12/95
                                      15:55:45

Lot Balancing Maintenance

Production Order number..?.: W0000195

Potent Lot Window
Item number      Std Potency      Potency Range      UOM      O/S Pot Un
RAM03           50.00000      50.00000      50.00000      EA           .000
X Lot Number      Act Potency      Phy Qty Req      Allocated      Avl Pot Un      St
- LOT01           50.00000           .000           2.000      819.000      RM
- LOT02           25.00000           .000           .000      112.500      RM
- LOT04           75.00000           .000           .000      150.000      RM

1=Select 2=Lot Maintenance 3=Lot Header Enquiry
F8=Update F12=Previous F14=All stockrooms F15=Issuing Stockroom
F16=Existing Allocations F18=Clear Allocations

12-03      S2      MK      KS      IM      II      KENB20A      PET166S2
  
```

Fields:

Item Number

The item number is displayed for your information.

Std Potency

The standard potency number is displayed for your information.

Potency Range

The potency range is displayed for your information.

UOM

The unit of measure is displayed for your information.

O/S Pot Un

The outstanding potency unallocated is displayed for your information.

X

For each lot, you can enter one of the following options:

- 1 - Select.
- 2 - Lot Maintenance
- 3 - Lot Header Enquiry.

Lot Number

For each lot, the lot number is displayed for your information.

Act Potency

For each lot, the active potency is displayed for your information.

Phy Qty Req

For each lot, the physical quantity required is displayed for your information.

Allocated

For each lot, the allocated quantity is displayed for your information.

Avl Pot Un

For each lot, the available potency unallocated is displayed for your information.

St

For each lot, the stockroom is displayed for your information.

Functions:

F14

All Stockrooms. Displays all stockrooms for the item.

F15

Issuing Stockroom. Displays only the issuing stockroom for the item.

F16

Existing Allocations. Displays any existing allocations for the item.

F18

Clear Allocations. Clears any reservations made in this session, allowing a fresh start to be made.

Release Orders



This option:

- Releases confirmed orders to the shop floor; this may allocate (depending on the company profile setting) material to the order and allows transactions to be processed against it
- Optionally prints order documentation
- Assigns default order priority
- Optionally issues materials to the first or all operations
- Invokes lot balancing where appropriate
- Optionally, creates warehouse requirements

From within the task it is possible to:

- Carry out order maintenance
- Check on material availability of inputs for a single order or for a number of orders in a session



Note: If you request order documentation to be printed, it is done either interactively or in batch, depending upon what is set in the company profile.



Note: An audit report is automatically produced when an order is released.



When Release Orders is selected on the menu, the first Production Order Release screen is displayed.

Production Order Release Screen 1

On the first Production Order Release screen:

- To release/amend/trial kit a single confirmed order enter the order number in the Production Order field and press **Enter**. The second Production Order Release screen is displayed.
- To release/maintain text/trial kit for several confirmed orders specify Item/Group, reference and/or a date range if required and select **F16=Review Orders**. The third Production Order Release screen is displayed.



When Release Orders is selected on the menu, the first Production Order Release screen is displayed.

The following fields and functions are displayed:

PC003	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:34:49
Production Order Release			
Production Order.....?..: █			
OR Select by:			
Item/Group.....?..: _____			
Reference.....?..: _____			
Orders Due from.....: <u>8/12/95</u> to: <u>8/12/95</u>			
F3=Exit F4=Prompt F16=Review orders			
07-30 S MW KS IM II KENB20A PET166S2			

Fields:

Production Order

You can enter the production order number.

Item/Group

You can enter the item/group number.

Reference

You can enter the reference number.

Orders Due From

You can enter the first date in a range of dates. This field defaults to the current system date.

To

You can enter the last date in a range of dates. This field defaults to the current system date.



When the order number is entered in the Production Order field on the first Production Order Release screen, and **Enter** is pressed, the second Production Order Release screen is displayed.



When details are entered in the Item/Group, Reference and/or Orders Due From field on the first Production Order Release screen, and select **F16=Review Orders** is pressed, the third Production Order Release screen is displayed.

Production Order Release Screen 2

You can release/amend/trial kit a single confirmed order.



When the order number is entered in the Production Order field on the first Production Order Release screen, and **Enter** is pressed, the second Production Order Release screen is displayed.

The following fields and functions are displayed:

PC003	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:42:54
Production Order Release			
Order Number	W000190		
Order Type	Standard	No Order Text Exists	
Finished Item	MS004	Product C	
Route	1		
Order Quantity	14.345		
Order Date	8/12/95		
Start Date	1/03/96 / 9/96		
Latest Start Date	1/03/96 / 9/96		
Due Date	1/03/96 / 9/96		
Reference 1		Reference 2	
Order Priority	5		
Print Shop Documentation	0 (0=No 1=Yes)		
Issue Materials - First Operation Only	0 - All Operations 0 (0=No 1=Yes)		
Create Warehouse Requirements	1 (0=No 1=Yes)		
F3=Exit F8=Release Order F12=Previous F17=Amend Order F18=Trial Allocate			
F21=Text F22=Lot Balancing			
18-42 SF MW KS IM II KENB20A PET166S2			

Fields:

Order Priority

This field is used to set the priority of the order. This priority is passed down to the operations and is used to sequence production at work stations.

The value must be in the range 0 to 9 inclusive, with 0 having the highest priority, i.e. it is processed first.

The default value for this field is set on the company profile via the Order Priority Default Value flag.

Create QS Inspect Ord



Note: This field is only displayed if either 1 or 2 are entered in the Inspection Policy Default field on the Database Options screen.

Create QS Inspection Orders. A QS inspection order for this item can be generated when a production order is released. However, to do this, one of the following two conditions must be met:

- The Inspection Policy field on the Production Details screen is 1.

- The Inspection Policy field on the Production Details screen is 0 or blank, and the Inspection Policy Default field on the Database Options screen is 1.

You can decide whether or not to generate a QS inspection lot when this production order is released. To do this, you can enter one of the following options:

0 - No. The QS inspection lot is not created when the production order is released. If 0 is entered in the Issue Materials field, i.e. no materials are issued for this production order, the inspection lot can be generated using the Generate Inspection Orders option on the menu.

1 - Yes. If 1 is entered in the Issue Materials field, i.e. materials are issued for this production order, inspection lot is automatically generated when the production order is released, and sent to the QS software. If 0 is entered in the Issue Materials field, i.e. no materials are issued for this production order, the inspection lot can be generated using the Generate Inspection Orders option on the menu.

When the QS software receives an inspection lot from the system, an inspection order can be generated either manually or automatically, and this inspection order can be printed either manually or automatically. This is configured in the QS software.

Print Order Documentation

Order documentation can be printed as a separate task. The default from the company profile is displayed. You can amend the default. You can enter one of the following options:

0 - No. Do not print work instructions and pick lists.

1 - Yes. Print work instructions and pick lists.

Issue Material - First/All Operations

This field determines whether stock is issued to the first operation only on the order. The default from the company profile is displayed. You can amend the default. You can enter one of the following options:

0 - No. For no automatic issue.

1 - Yes. To issue the required quantity of material automatically, providing that it is not bulk issue.

If material is not to be issued automatically it must be done as a separate task - either formally issued to the order or to floor stock or consumed by backflushing from primary or floor stock during bookings.

Create Warehouse Requirements

If the materials are warehouse controlled, this setting allows the stock to be allocated in the warehouse stockroom if required. You can enter one of the following options:

0 - No. No generation required.

1 - Yes. Generate requirements.



F8=Release Order can now be used to confirm release of the selected orders.

Functions:

F17

Amend Order. Allows you to amend the order. This option takes you to the order header screen from which all the order amend options are available. To release a single order select **F8=Release Order**.

F18

Trial Allocation. Allows Trial Allocation if materials can be issued to the order. Several orders may be trial kitted during the release option. When **F3=Exit** is selected the menu the trial kitting simulation is ended. No materials are issued by the trial kitting.

F21

Text. Allows you to maintain order header text.

F22

Lot Balancing. Allows Lot Balancing for lot controlled items. When you select this function, the Lot Balancing window is displayed.

Lot Balancing Window (F22)

Lot Balancing Example:

Lot Size=100

Balancing Quantity=110

Input A - 100 kgs with std potency of 50%

Input B - 10 kgs (filler) Production Order raised for 100 kgs

The following lots of item A are available:

- Lot L714 With a potency of 40%
- Lot L715 With a potency of 75%

To make the order of 100 kgs with a potency of 50% requires 50 potency units:

One way this may be done is to:

Use Lot L714: 50 kgs at 40%=20 potency units

Use Lot L715: 40 kgs at 75%=30 potency units

Total of 90 kgs=50 potency units

Filler needed: 20 kgs to make up quantity to batch balancing total of 110 kgs.

Lot balancing can be undertaken directly without releasing the order.



When **F22=Lot Balancing** is selected on the second Production Order Release screen, the Lot Balancing window is displayed.

The following fields and functions are displayed:

PC003	Z1 - GB Demonstration Company	USER GBJBAMS	13/12/95										
Production Order Release			15:40:00										
Order Number	W000195												
Lot Balancing Window <table border="1"> <thead> <tr> <th>Sel</th> <th>Item number</th> <th>Std Potency</th> <th>Potency Range</th> <th>Outstand Qty.</th> </tr> </thead> <tbody> <tr> <td>☒</td> <td>RAM03</td> <td>50.00000</td> <td>50.00000</td> <td>4.00000</td> </tr> </tbody> </table> 1=Lot Selection 2=Existing Allocations F8=Update F12=Previous				Sel	Item number	Std Potency	Potency Range	Outstand Qty.	☒	RAM03	50.00000	50.00000	4.00000
Sel	Item number	Std Potency	Potency Range	Outstand Qty.									
☒	RAM03	50.00000	50.00000	4.00000									
F3 F21=Text F22=Lot Balancing 11-08 SA ML KS IM II KENB20A PET166S2													

Fields:

Sel

Select. You can enter one of the following options:

1 - Lot Selection. When this option is entered, the Potent Lot window is displayed.

2 - Existing Allocation. To enquire on any existing lot reservations. Allocations can be cleared and re-selected.

Item Number

The item number is displayed. This field is for your information only and cannot be amended.

Std Potency

As specified in the Inventory Item File. This field is for your information only and cannot be amended.

Potency Range

As specified on the route. This field is for your information only and cannot be amended.

Outstand Qty

This is calculated from the order. This field is for your information only and cannot be amended.



When 1 is entered in the Sel field on the Lot Balancing window, the Potent Lot window is displayed.



When **F8=Update** is selected on the Lot Balancing window, the item is updated and the second Production Order Release screen is displayed.

Potent Lot Window (Option 1)

Lots with available potency units (Avl Pot Un) shown as zero have been used and are not available. In the top right corner of the window, the system displays the outstanding potency units (O/S Pot Un) required.



Note: Only lots available on the start date of the order are displayed



When 1 is entered in the Sel field on the Lot Balancing window, the Potent Lot window is displayed.

The following fields and functions are displayed:

PC003		Z1 - GB Demonstration Company		USER GBJBAMS		13/12/95	
						15:40:00	
Production Order Release							
Order Number		W000195					

Potent Lot Window							
Item number	Std Potency	Potency Range		UOM	O/S Pot Un		
RAM03	50.00000	50.00000	50.00000	EA	2.000		
X Lot Number	Act Potency	Phy Qty Req	Allocated	Avl Pot Un	St		
LOT01	50.00000	4.000	.000	823.000	RM		
LOT02	25.00000	8.000	.000	112.500	RM		
LOT04	75.00000	2.667	.000	150.000	RM		

1=Select 2=Lot Maintenance 3=Lot Header Enquiry
 F8=Update F12=Previous F14=All stockrooms F15=Issuing Stockroom
 F16=Existing Allocations F10=Clear Allocations

F21=Text F22=Lot Balancing
 12-03 SF MK KS IM II KENB20A PET166S2

Fields:

X

You can enter one of the following options:

1 - Select. Allocates the remaining outstanding quantity from the selected lot. The available potent units are decreased; physical quantity required set to zero; and the allocated quantity updated to reflect the original required quantity. If invoked before any allocations have been made, the entire outstanding quantity is allocated. If selected following partial allocation, the remaining quantity only is allocated.

2 - Lot Maintenance. Carries out lot maintenance. This enables you to manually enter or allocate quantities if allocations are to be made from more than one lot. Lots may be selected alternately.

3 - Lot Header Enquiry.

Lot Number

The assigned lot number. This field is for your information only and cannot be amended.

Act Potency

Actual potency of this lot. This field is for your information only and cannot be amended.

Phy Qty Req

The physical quantity required is calculated as:

$(\text{Pot Units Req/Act. Potency \%}) \times 100$

This field is for your information only and cannot be amended.

Allocated

This is blank initially. After selection, this field displays the allocated number of potency units. This field is for your information only and cannot be amended.

Avl Pot Un

Available potency units in this lot. This field is for your information only and cannot be amended.

St

System maintained field; displays the issuing stockroom. This field is for your information only and cannot be amended.



When **F8=Update** is selected on the Potent Lot window, the item is updated and the Lot Balancing window is displayed.



If a filler has been defined on the route, when **F8=Update** is selected on the Potent Lot window, the Filler Requirements window is displayed.



Note: When allocations have been made, screen details are updated. The Allocated column is updated and the O/S Pot UN figure in the top right of the window is down dated. When this happens, the Phy Qty Req column for the remaining lots is recalculated for the new outstanding potency unit requirements, if any.

If any lot selected is passed its Last Available Date, a warning is displayed. The lot may still be selected by using F8=Update to override the warning.

If the quantity contained in the lot is greater than the quantity required, then only the quantity required is selected, leaving the balance as available.

A further **F8=Update** is required to complete the process. This displays the Filler Requirements window if a filler is specified on the route.

The following fields and functions are displayed:

PC003	Z1 - GB Demonstration Company	USER GBJBAMS	13/12/95
Production Order Release			15:40:00
Order Number	W000195		

Potent Lot Window							
Item number	Std Potency	Potency Range	UOM	O/S Pot	Un		
RAM03	50.00000	50.00000	EA		.000		
X Lot Number	Act Potency	Phy Qty Req	Allocated	Avl Pot	Un	St	
- LOT01	50.00000	.000	2.000	821.000		RM	
- LOT02	25.00000	.000	.000	112.500		RM	
- LOT04	75.00000	.000	.000	150.000		RM	

1=Select 2=Lot Maintenance 3=Lot Header Enquiry
 F8=Update F12=Previous F14=All stockrooms F15=Issuing Stockroom
 F16=Existing Allocations F18=Clear Allocations

F21=Text F22=Lot Balancing
 12-03 SF MK KS IM II KENB20A PET166S2

Functions:

F14

All Stockrooms. Toggles between displaying all stockrooms for this item or only the issuing stockroom.

F15

Issuing Stockroom. Only displays the issuing stockroom.

F16

Existing Allocations. Displays any existing allocations.

F18

Clear Allocations. Clears any reservations made in this session, allowing a fresh start to be made.

Filler Requirements Window (F8)

This window enables you to confirm the amount of filler required by the order to attain the batch balancing quantity. A filler is necessary when the physical quantity of lot balanced items falls short of the target physical quantity required to meet the batch balancing quantity.

The filler must be defined on the route and be a standard constituent of the route. That is, it must be required in at least a minimal quantity as a standard input to the parent item. Flagging as a filler indicates that the quantity required may be increased in order to meet a physical demand. This increase is unrelated to the quantity per requirement.



If a filler has been defined on the route, when **F8=Update** is selected on the Potent Lot window, the Filler Requirements window is displayed.

The following fields and functions are displayed:

PC003	Z1 - GB Demonstration Company	USER GBJBAMS	13/12/95
Production Order Release			15:40:00
Order Number	W000195		
0	Lot Balancing Window		
F			
R	Sel Item number	Std Potency	Potency Range
0	RAM03	50.00000	50.00000
O			Outstand Qty.
S			.00000
L			
D			
R			
O			
P			
I	1=Lot Selection 2=Existi		
C	F8=Update F12=Previous		
F3			
F21=Text F22=Lot Balancing			
17-57 Sa Mk KS IM II KENB20A PET166S2			

Filler Requirements

Filler Item.: RAM01

Operation Seq: 010

Component Seq: 010

Required Qty.: 6.000

F8=Confirm F12=Previous

Fields:

Required Quantity

Enter the quantity of filler required or accept the default calculated as the production order equivalent balancing quantity less the sum of the quantity allocated and issued for all potent items, and the quantity of filler issued to-date.



When **F8=Confirm** is selected, the transactions are completed and the Potent Lot window is displayed.



Note: If the Allocation of Materials at Order Release flag on the company profile flag is set to 1 (yes), allocation takes place when completing

release.



Note: If the item being balanced is a key ingredient, this causes an allocation to take place in floor stock

Production Order Release Screen 3 (F16)

To release/maintain text/trial kit for several confirmed orders first specify Item/Group, reference and/or a date range if required on the first Production Order Release screen.

This screen displays all orders within the defined selection parameters, and all confirmed orders within the selected dates.



When **F16=Review Orders** is selected on the first Production Order Release screen, the third Production Order Release screen is displayed.

The following fields and functions are displayed:

Opt	Order	Type	Item	Route	Start Dt	Due Date	Quantity
—	W000182	1	MS001	1	11/12/95	12/12/95	5.000
—	W000183	1	MS001	1	21/12/95	5/01/96	48.000
—	W000187	1	MS004	1	23/01/96	26/01/96	77.000
—	W000185	1	MS001	1	25/01/96	2/02/96	30.891
—	W000184	1	MS001	1	31/01/96	2/02/96	12.000
—	W000188	1	MS004	1	2/02/96	2/02/96	23.000
—	W000189	1	MS004	1	2/02/96	2/02/96	20.594
—	W000186	1	MS001	1	26/02/96	1/03/96	21.517
—	W000190	1	MS004	1	1/03/96	1/03/96	14.345

Order priority..... 5
 Print shop documentation..... 0 (0=No 1=Yes)
 Issue materials - first operation 0 - all operations 0 (0=No 1=Yes)
 Create warehouse requirements.... 1 (0=No 1=Yes)

1=Select for release 2=Text 3=Trial kit
 F3=Exit F8=Release order(s) F12=Previous

06-02 SF MW KS IM II KENB20A PET166S2

Fields:

Opt

You can enter one of the following options:

1 - Select For Release. When this option is entered, and **F8=Release Order(s)** is selected, the order is released.

2 - Text. When this option is entered, and **Enter** is pressed, you can maintain order header text.

3 - Trial Kit. When this option is entered, and **Enter** is pressed, you can have limited access to the material availability enquiry. This simulates the issue of materials to the order and highlights potential shortages (which would result in negative stocks if the order was released with the Issue Materials flag set to 1 (Yes).

Order Priority

This field is used to set the priority of the order. This priority is passed down to the operations and is used to sequence production at work stations. The value

must be in the range 0 to 9 inclusive, with 0 having the highest priority, that is, is processed first. The default value for this field is set on the company profile via the Order Priority Default Value flag.

Create QS Inspection Orders



Note: This field is only displayed if either 1 or 2 are entered in the QS Inspection Policy field on the Database Options screen.

A QS inspection lot for this item can be created when a production order is released. However, to do this, one of the following two conditions must be met:

The Inspection Policy field on the Production Details screen is 1.

The Inspection Policy field on the Production Details screen is 0 or blank, and the QS Inspection Policy field on the Database Options screen is 1.

You can decide whether or not to create a QS inspection lot when this production order is released. To do this, you can enter one of the following options:

0 - No. The QS inspection lot is not created when the production order is released.

1 - Yes. The QS inspection lot is created when the production order is released.

Issue Material - First/All Operations

This field determines whether stock is issued to the first operation only on the order. The default from the company profile is displayed. You can enter one of the following options:

0 - No. For no automatic issue.

1 - Yes. To issue the required quantity of material automatically, providing that it is not bulk issue.

If material is not to be issued automatically it must be done as a separate task - either formally issued to the order or to floor stock or consumed by backflushing from primary or floor stock during bookings.

Create Warehouse Requirements

If the materials are warehouse controlled, this setting allows the stock to be allocated in the warehouse stockroom if required. You can enter one of the following options:

0 - No. No generation required.

1 - Yes. Generate requirements.



When 1 is entered in the S field, and **F8=Release Order(s)** is selected, the selected order is released.

Generate Warehouse Requirements



There are two methods of generating warehouse requirements for production orders, through Release Orders or a dedicated option Generate Warehouse Requirements.

Order Release

Production Order Release can be used in the normal manner when there are Warehouse Controlled items, with the addition of the extra field at the foot of the screen which generates warehouse requirements if set to 1.

Generate Warehouse Requirements

Only those production orders with warehouse controlled items having outstanding quantities that are not currently being processed by Warehousing are displayed, (subject to selection parameters).

Once accepted no further extraction for an order line can be carried out until stock has been issued to this line from the Warehousing system.

This is also where the quantity recommended can be altered to reflect the real issue units from the warehouse. i.e. require 3 caps, issue a box of 200, return 197 to the warehouse.

Warehouse controlled items cannot be manually issued to a production order using Issue Materials, the above procedure should be used instead.

Generating warehouse requirements creates a stock allocation in the warehouse stockroom.



When Generate Warehouse Requirement is selected on the menu, the Generate Warehouse Requirements screen is displayed.

The following fields and functions are displayed:

PC201	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:53:56
Generate Warehouse Requirements			
From warehouse.....?.. █	To warehouse.....?.. █		
From finished item..?.. █	To finished item..?.. █		
From reference.....?.. █	To reference.....?.. █		
From op. start date.... 0/00/00	To op. start date.... 0/00/00		
From order.....?.. █	To order.....?.. █		
From operation..... █	To operation..... █		
(Blank or zero implies from start)		(Blank or zero implies to end)	
Include zero balances.. 0 (0=No 1=Yes)			
F3=Exit F4=Prompt			
06-27	SE	MW	KS IM II KENB20A PET166S2

Fields:

From/To Warehouse

The From Warehouse and To Warehouse fields are used to select a range of warehouses for material issue. The lower limit is assumed if the From Warehouse field is left blank.

From/To Finished Item

The From Finished Item and To Finished Item fields are used to select a range of finished items whose input requirements are displayed on the next screen. The lower limit is assumed if the From Finished Item field is left blank.

From/To Reference

The From Reference and To Reference fields are used to select a range of orders whose references fall in the range. The input items requirements for these orders are displayed on the next screen. The lower limit is assumed if the From Reference field is left blank.

From/To Op Start Date

The From Op Start Date and To Op Start Date fields are used to review requirements for items required for operations starting between the range of dates specified. No lower limit is assumed if the From Op Start Date field is left blank.

From/To Order

The From Order and To Order fields are used to select a range of orders whose input requirements are displayed on the next screen. The lower limit is assumed if the From Order field is left blank.

From/To Operation

The From Operation and To Operation fields are used to select a limited range of operations whose input requirements you wish to view. The lower limit is assumed if the From Operation field is left blank.

Include Zero Balances

Input items with no outstanding balance are not normally displayed on the material requirements screen which is displayed next. Choosing to display items with a zero balance allows the entry of unplanned requirements for the item. You can enter one of the following options:

0 - No. Do not display zero balance items.

1 - Yes. Display all items regardless of the outstanding requirement.



Press **Enter** to display a list of orders with warehouse controlled materials/quantities awaiting allocation in warehousing. Select required items and **F8** to submit job.

Print Order Documentation



Order documentation consists of:

- Pick lists - providing printed details of all inputs needed for each operation on each released production order.
- Work instructions - providing printed details of each operation, including a description on each production order and may include operational text (instructions) if required.

The use of Order Documentation is controlled by the settings made on the company profile. The actual printing is controlled in three ways:

- Automatically, by setting the company profile field Print Order Documentation at Order Release to 1.
- Manually, by setting the company profile field Print Order Documentation at Order Release to 0 and making use of the facility to print the documentation in the order release task.
- Manually, by setting the company profile field Print Order Documentation at Order Release to 0 and using the print order documentation task to select orders for documentation printing.

The last of these three methods is considered on the following pages.

If the company profile flag has been set to print in batch then on leaving these options the documents are sent to the job queue and are printed when the batch job has been processed.

If the flag is set to print interactively then the documents are processed immediately. If large numbers of documents are selected, then there may be a delay before the screen can be used again.



When Print Order Documentation is selected on the menu, the first Print Order Documentation screen is displayed.

Print Order Documentation Screen 1



When Print Order Documentation is selected on the menu, the first Print Order Documentation screen is displayed.

The following fields and functions are displayed:

PC042	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95
			15:54:49
Print Order Documentation		Print in batch.	
Option.....	1 {1=Select from unprinted orders}		
	{2=Select from all orders}		
	{3=Print all unprinted released/active orders}		
	{4=Print all released/active orders}		
F3=Exit			
06-22	SA	MW	KS
		IM	II
		KENB20A	PET166S2

Fields:

Option

You can enter one of the following options:

- 1 - Select From Unprinted Orders. When this option is entered, the second Print Order Documentation screen is displayed.
- 2 - Select From All Orders. When this option is entered, the third Print Order Documentation screen is displayed.
- 3 - Print All Unprinted Released/Active Orders. Automatically prints all the previously unprinted, released orders. Note this option submits a job which runs either interactively or in batch, depending on the setting in the company profile.
- 4 - Print All Released/Active Orders. Automatically prints or reprints all released and active orders, regardless of their print status. This option also submits a job.



When 1 is entered in the Option field in the first Print Order Documentation screen, the second Print Order Documentation screen is displayed.



When 2 is entered in the Option field in the first Print Order Documentation screen, the third Print Order Documentation screen is displayed.

Print Order Documentation Screen 2 (Option 1)



When 1 is entered in the Option field in the first Print Order Documentation screen, the second Print Order Documentation screen is displayed.

The following fields and functions are displayed:

PC042	Z1 - GB Demonstration Company	USER	GBJBAMS	8/12/95
				15:54:49
Print Order Documentation				Print in batch.
				Print
0	Order	Item	Reference1	Reference2
	NT10/01	NT10		
-	W000015	MPSPAR		
-	W000017	PRCGRP1		
-	W000018	REP01		
-	W000020	ASV1		
-	W000025	TESTPOT1		
-	W000027	TESTPOT1		
-	W000028	TESTPOT1		
-	W000029	TESTPOT1		
-	W000033	TSTPOT1		
-	W000034	TSTHLD1		
-	W000035	TSTHLD1		
-	W000045	PIE3		
-	W000046	PIE3		
			Order Qty.	Status
			10.000	
			1000.000	
			100.000	
			10.000	
			100.000	
			123.000	
			101.000	
			100.000	
			100.000	
			100.000	
			100.000	
			100.000	
			3.000	
			2.000	+
1=Print as original 2=Print as outstanding * - Already awaiting printing				
F3=Exit F12=Previous F8=Print all released orders F22=Expand detail				
06-02	SE	MW	KS	IM
			II	KENB20A PET166S2

Fields:

0

Option. You can select which details are printed on the documentation. You can enter one of the following options:

1 - Print As Original. Duplicates the documentation originally produced for the order selected.

2 - Print As Outstanding. Adjust the documentation to represent the current state of the order.



*Note: When * is displayed, this means the order is already selected and is waiting to be printed.*

Print Status

This field displays the printing status for the order. The following can be displayed:

Blank - Documentation has not yet been printed for the order.

Printed - Documentation has already been printed for the order, however, the order may be selected for re-printing.

Selected - The order has been selected, but the documentation has not yet been printed. This situation can arise when printing is submitted as a batch job.

Functions:

F8

Print All Released Orders. Prints order documentation for all released orders



Note: This includes all, not just previously unprinted.

F22

Expand Detail. Provides expanded details for each order: Order Type, Based On Route Start Date, Due Date and Schedule Order Quantity

Print Order Documentation Screen 3 (Option 2)

This screen displays all orders, so that any order which has already been printed, can be reprinted, if required.



When 2 is entered in the Option field in the first Print Order Documentation screen, the third Print Order Documentation screen is displayed.

The following fields and functions are displayed:

PC042	Z1 - GB Demonstration Company	USER	GBJBAMS	8/12/95
				15:54:49
Print Order Documentation				Print in batch.
0	Order	Item	Reference1	Reference2
■	W000083	LIPSTK		Order Qty.
-	W000092	DMLASSY-FS		100.000
-	W000093	DMLASSY-FS		30.000
-	W000094	SUBCA		25.000
-	W000099	MJ0125PW		100.000
-	W000114	PIE3		1.000
-	W000118	PIE3		10.000
-	W000120	PIE3		30.000
-	W000121	PIE3		35.000
-	W000123	PIE3		50.000
-	W000134	UNDERWORLD		35.000
-	W000140	CAKE		1.000
-	W000143	P82P		10.000
-	W000147	AL1		5.000
				100.000
				Printe +
1=Print as original 2=Print as outstanding * - Already awaiting printing				
F3=Exit F12=Previous F8=Print all released orders F22=Expand detail				
06-02	SA	MW	KS	IM
				II
				KENB20A
				PET166S2

Fields:

O

Option. You can enter the following options:

- 1 - Print As Original. Reprint with original quantities.
- 2 - Print As Outstanding. Reprint with current quantities



*Note: When * is displayed, this means the order is already selected and is waiting to be printed.*



*Note: Reprinted documents have ***REPRINT shown in the top right hand corner.*



When all the required orders have been selected, and **Enter** is pressed, the first Print Order Documentation screen is displayed.

Functions:

F8

Print All Released Orders. Prints order documentation for all released orders



*Note: This includes all, not just previously
unprinted.*

F22

Expand Detail. Provides expanded details for each order: Order Type, Based On Route Start Date, Due Date and Schedule Order Quantity

Order Completion



6/PCM



When Order Completion is selected on the menu, the first Production Order Completion screen is displayed.

Orders can be completed in two ways:

- By booking at the last operation and indicating that the order is complete. The effect of this action is to reduce the value of work-in-progress and to increase the inventory stock level. This should therefore be considered as the normal method of completing orders.
- By selecting the Order Completion option on the menu. The effect of this action is to close down the order, either completely or operation by operation, in production order control only. This task does not update the physical stock in Inventory Management and therefore, the goods remain in work-in-progress. The order can then be re-opened, either entirely or for selected operations or cancelled via the same facility.

The file updates affected by carrying out order completion by either method are as follows:

Action	Production Orders	Inventory
On completion of an Individual Operation.	Operation status changed to <i>Completed</i>. <i>Completion Date</i> is recorded. Inputs' status changed to <i>Complete</i>.	Inputs' <i>allocated</i> stock is reduced by any outstanding amount (quantity required less quantity issued) and therefore available stock is increased. The company profile must be set to allow allocation on release for this to happen.
On completion of an Order.	Header status changes to <i>Complete</i>. Completion Date is recorded. Status of all operations and inputs is changed to <i>complete</i>.	Parent Item <i>on-order</i> balance is reduced by order quantity. Inputs' allocated stock is updated as above for all operations.

Re-opening an order reverses the transactions made on the original completion. The effects of cancelling an order are similar to completion except that:

- The status is set to be cancelled
- The completion date is not recorded
- The order cannot be re-opened

The remainder of this section is concerned with the use of the Order Completion option.

Production Order Completion Screen 1



When Order Completion is selected on the menu, the first Production Order Completion screen is displayed.

The following fields and functions are displayed:

PC005	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 16:48:17
Production Order Completion			
Production Order...?:			
OR Select by:			
Item/Group.....?:			
Reference.....?:			
Orders Due from.....: <u>8/12/95</u> to: <u>8/12/95</u>			
F3=Exit F4=Prompt F16=Review Orders			
06-26	S	MW	KS IM II KENB20A PET166S2

Fields:

Production Order

Enter the number of the order required for completion. Only orders that are released or active can be selected. Alternatively a list of orders can be displayed using **F16=Review Orders**. The list can be reduced by entering selection criteria in Select By fields on this screen.

Item/Group

This and the following fields constitute the search criteria for an order review. The fields may be used independently. The required order may be selected from a list presented by selecting **F16=Review Orders**. Enter the item or process group code.

Reference

An entry limits the orders shown in the selection window to those with the same entry in the reference 1 field on the order header.

Orders Due From

Limits the orders shown in the selection window to those with a due date after the date entered. This may be used in conjunction with the Orders Due To field to select orders with due dates spanning a range of dates.



Note: The Orders Due From and Orders Due To fields default to the current system date.

Orders Due To

Limits the orders shown in the selection window to those with a due date before the date entered. This may be used in conjunction with the Orders Due From field to select orders with due dates spanning a range of dates.

Functions:

F16

Review Orders. When you select this function the second Production Order Completion screen is displayed.



When **F16=Review Orders** is selected on the first Production Order Completion screen, the second Production Order Completion screen is displayed.

Production Order Completion Screen 2 (F16)

This screen displays a list of all released, active and completed orders and allows you to select any of them for processing.



When **F16=Review Orders** is selected on the first Production Order Completion screen, the second Production Order Completion screen is displayed.

The following fields and functions are displayed:

PC005		Z1 - GB Demonstration Company			USER GBJBAMS		8/12/95	
							16:48:17	
Production Order Completion								
O/T	Order	Stat	Type	Item	Rte	Due	Order Qty	Qty O/S
-	W000183	Rel	1	MS001	1	5/01/96	48.000	48.000
-	W000187	Rel	1	MS004	1	26/01/96	77.000	77.000
-	W000184	Rel	1	MS001	1	2/02/96	12.000	12.000
-	W000189	Rel	1	MS004	1	2/02/96	20.594	20.594
-	W000182	Act	1	MS001	1	12/12/95	5.000	4.000
1=Select order 3=Text								
F3=Exit F12=Previous								
06-02		SF		MW	KS	IM	II	KENB20A PET166S2

Fields:

O/T

You can enter one of the following options:

1 - Select Order. You can select an order for completion. When this option is entered, the third Production Order Completion screen is displayed.

3 - Text. You can display or edit the order header text for an order.

Stat

Status. The following can be displayed:

REL - Released Orders.

ACT - Active Orders.

FIN - Completed Orders.

Type

The following can be displayed:

0 - Non-Standard Orders.

1- Standard Orders.

Due

Route Due Date. Displays the order route for production.

Order Qty

Displays the original order quantity of the finished product.

Qty O/S

Quantity Outstanding. Displays the original order quantity less receipts into stock.



When 1 is entered in the O/T field on the second Production Order Completion screen, the third Production Order Completion screen is displayed.

Production Order Completion Screen 3 (Option 1)

This screen displays the header details and all operations for the selected order.



When 1 is entered in the O/T field on the second Production Order Completion screen, the third Production Order Completion screen is displayed.

The following fields and functions are displayed:

PC005	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95
Production Order Completion			16:48:17
Order Number	W000182	Status	Active
Order Type	Standard	No Order Text Exists	
Item	MS001	Product A	
Route	1		
Order Quantity	5.000	Complete	1.000 Outstanding 4.000
Start Date	11/12/95 - 50/95	Due Date	12/12/95 - 50/95
* 3=Released, 4=Active, 8=Complete			
0 S Oper Description	Start	Due	Scheduled Completed Outstanding
4 10 Operation 10	111295	121295	5.000 1.000 2.000
4 20 Operation 20	111295	121295	5.000 1.000 4.000
4 30 Operation 30	121295	121295	5.000 1.000 2.000
1=Complete Operation 2=Re-open Operation 3=Text			
F3=Exit	F8=Complete Order	F12=Re-select Order	
	F21=Header Text	F19=+/- Additional Balances	
15-02	82 MW KS	IM	II KENB20A PET166S2

Fields:

O

Option. You can enter one of the following options:

- 1 - Complete Operation.
- 2 - Re-Open Operation.
- 3 - Text.

S

Status. The following can be displayed:

- 3 - Released Operation.
- 4 - Active Operation.
- 8 - Complete Operation.
- 9 - Cancelled Operation.

Oper

The operation sequence number is displayed for your information and cannot be amended.

Description

The operation description is displayed for your information and cannot be amended.

Start

The recorded start date for this operation is displayed for your information and cannot be amended.

Due

The due date for completion of this operation is displayed for your information and cannot be amended.

Scheduled

The scheduled quantity for this operation is displayed for your information and cannot be amended.

Completed

The quantity recorded as completed via operation bookings is displayed for your information and cannot be amended.

Outstanding

The difference between the scheduled quantity and the quantity completed is displayed for your information and cannot be amended.

Functions:

F8

Complete Order. When this function is selected, the order is completed regardless of the status of the individual operations. The Status fields of all the order operations are amended to 8 (Complete).

F11

Cancel. When this function is selected, the order is cancelled. The order remains on the file but cannot be updated in any way. The Status fields of the order operations are amended to 9 (Cancelled).



Note: This facility should be used with care as the order cannot be re-opened.

F12

Re-Select Order. When this function is selected, a completed order is re-opened. The Status fields of the order operations are amended to 4 (Active).

F19

+/- Additional Balances. When this function is selected, additional fields are displayed. These fields display the quantities of rework, held and scrap.

F21

Header Text.



Tip: When a particular action is carried out the screen is re-displayed with the appropriate status detail.

Generate Inspection Orders



Note: These screens are only available if either 1 or 2 are entered in the Inspection Policy Default field on the Database Options screen.

You can generate inspection lots for selected released production orders. The inspection lots are sent to the QS software.

For more information about releasing production orders see Release Orders.

When the QS software receives an inspection lot from the system, an inspection order can be generated either manually or automatically, and this inspection order can be printed either manually or automatically. This is configured in the QS software. For more information see the QS manuals.



7/PCM



When Generate Inspection Orders is selected on the menu, the first Create Inspection Orders screen is displayed.

Create Inspection Orders Screen 1



When Generate Inspection Orders is selected on the menu, the first Create Inspection Orders screen is displayed.

The following fields and functions are displayed:

Fields:

Option

You can enter one of the following options:

1 - Select From Unflagged Orders. This option displays all the released production orders for which inspection lots have not been generated. When this option is entered, the second Create Inspection Orders screen is displayed.

2 - Select From All Orders. This option displays all the released production orders. When this option is entered, the third Create Inspection Orders screen is displayed.

3 - Create For All Unflagged Released/Active Orders. This option generates inspection lots for all released and active production orders. When this is complete, the first Create Inspection Orders screen is removed from the screen.



When 1 is entered in the Option field on the first Create Inspection Orders screen, the second Create Inspection Orders screen is displayed.



When 2 is entered in the Option field on the first Create Inspection Orders screen, the third Create Inspection Orders screen is displayed.

Create Inspection Orders Screen 2 (Option 1)

This screen contains all the released production orders for which inspection lots have not been generated.



When 1 is entered in the Option field on the first Create Inspection Orders screen, the second Create Inspection Orders screen is displayed.

The following fields and functions are displayed:

Fields:

O

Option. You can enter one of the following options:

1 - Select. When this option is entered, the released order is selected to generate an inspection lot. This has a blank in the Inspect Status field.

Order

This field displays the number of the production order and is for your information only.

Item

This field displays the name of the item associated with the production order and is for your information only.

Reference 1

This field displays descriptive text about the production order and is for your information only.

Reference 2

This field displays descriptive text about the production order and is for your information only.

Order Qty

This field displays the amount of the item required for this production order and is for your information only.

Inspect Status

This field displays the inspection status for the production order and is for your information only. The following can be displayed:

Blank - An inspection lot has not been generated for this production order.

Created - Inspection lot generated for this production order.

Functions:

F8

Generate All Released Orders. This function generates inspection lots for all the released orders with 1 in the O field, which are sent to the QS software.

When the QS software receives an inspection lot from the system, an inspection order can be generated either manually or automatically, and this inspection order can be printed either manually or automatically. This is configured in the QS software.

F22

Expand Detail. This function displays additional information about each of the orders.

Create Inspection Orders Screen 3 (Option 2)

This screen contained all the released production orders.



When 2 is entered in the Option field on the first Create Inspection Orders screen, the third Create Inspection Orders screen is displayed.

The following fields and functions are displayed:

Fields:

O

Option. You can enter one of the following options:

1 - Select. When this option is entered, the released order is selected to generate an inspection lot. This has a blank in the Inspect Status field.



*Note: When * is displayed, this means the released order already has a generated inspection lot. Created is displayed in the Inspect Status field.*

Order

This field displays the number of the production order and is for your information only.

Item

This field displays the name of the item associated with the production order and is for your information only.

Reference 1

This field displays descriptive text about the production order and is for your information only.

Reference 2

This field displays descriptive text about the production order and is for your information only.

Order Qty

This field displays the amount of the item required for this production order and is for your information only.

Inspect Status

This field displays the inspection status for the production order and is for your information only. The following can be displayed:

Blank - No inspection lot generated for this production order.

Created - Inspection lot generated for this production order.

Functions:

F8

Generate All Released Orders. This function generates inspection lots for all the released orders with 1 in the O field, which are sent to the QS software.

When the QS software receives an inspection lot from the system, an inspection order can be generated either manually or automatically, and this inspection order can be printed either manually or automatically. This is configured in the QS software.

F22

Expand Detail. This function displays additional information about each of the orders.

Issue Materials



11/PCM



When Issue Materials is selected on the menu, the Issue Materials screen is displayed.



Note: If the Warehousing application is in use, the material issues for the order are controlled by that application, and it is NOT necessary to use this option.

There are four methods of issuing materials:

- Automatically on order release, for the first operation only or for all operations. This method is quick and easy but may result in negative stocks - however, a warning message is given if this would happen, and the issuing request can be overridden. Order shortage reports can be run to find out if this has happened. Items subject to batch control require the selection of the batch number as part of Order Release. If the Warehouse application is in use, this option is not available.
- By manually issuing the items in Inventory Management. However, if this method is used there is no record of actual material issues in Production Control and therefore, no actual material costs recorded in production.
- By the backflushing of items flagged as bulk issue on the item master file during item booking.
- By manually issuing the items in Production Control. This method records issues to the order or shop floor, costs the actual issues and reduces the inventory issuing stockroom balances.

The last of these four methods is described in detail in the following pages.

Floor Stock

The use of the floor stock option enables specified items to be individually reserved (controlled) before using in WIP. Items may be issued to floor stock to track lot controlled items in a scheduled environment; although non lot controlled items may also be issued from a floor stock stockroom. Any lot controlled key ingredient item MUST have a Material Policy code 3 (floor stock issue).

It allows the use of controlled items in less rigidly controlled environments.

Each item to be controlled in this way must have a Material Control Policy code of 3 set in Production Details.

The stockroom to be used for holding floor stock is designated as such and linked to a single or several work station(s) using Maintain W/Station WIP Location on the menu.

The Issue Material options for either production orders or schedules are used to issue these materials from a raw material stockroom to a floor stock stockroom (Issue Materials on the menu or Issue Material on the menu). This action causes the Inventory Management material stock to be reduced and the floor stock to be increased. The floor stock is shown as fully allocated because there is not

normally any freely available stock in the floor stock stockroom. However, it is possible to over or bulk issue items to the shop floor stockroom. Any excess (free stock) is netted by the Daily Requirements Pull List routines against new scheduled requirements.

On booking the next count point operation, (if items are not formally manually issued), the reservation/allocation is backflushed out of the floor stock stockroom. Scheduled requirements are de-allocated in FIFO sequence when shop floor stock is consumed.

Issue Materials Screen



When Issue Materials is selected on the menu, the Issue Materials screen is displayed.

The following fields and functions are displayed:

PC220	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:49:18
Issue Materials			
Production Order....?: _____			
Operation Sequence....: _____ (Blank for All Inputs)			
Date.....: <u>8/12/95</u>			
Workstation.....?: _____			
Shift.....: <u>00</u>			
OR			
Item/Group.....?: _____			
Reference.....?: _____			
Orders Due From.....: <u>8/12/95</u> to: <u>8/12/95</u>			
F3=Exit F4=Prompt F16=Review Orders			
05-27 S2 MW KS IM II KENB20A PET166S2			

Fields:

Production Order

Enter the order against which issues are to be recorded. Only orders with a status of Released or Active can be selected.

Operation Sequence

You can enter the number of the operation for which you wish to issue inputs. If this field is left blank all operations and inputs for the selected order are displayed.

Date

Enter the date on which issues are to be made.

Work Station

This field enables you to record material issues to work stations other than those defined on a route; or specified during order and/or operator booking. If a work station is not entered, yield analysis assumes the work station defined on the route for the operation. If a work station is entered, it overrides that held on the route.

Shift

Enter a specific shift within the shift profile for the work station on the route during which the issues are to be made; or the override work station entered on this screen.

Item/Group

Enter the item/group.

Reference

Enter the reference.

Orders Due From/To

Enter the dates.



If you enter details in the Production Order, Operation Sequence, Date, Work Station and Shift fields, then press **Enter**, the Record Issues And Adjustments screen is displayed containing the selected order.

Functions:**F16**

Review Orders. Select this function to display a list of all orders on the system, defined by the entries in the Item/Group, Reference and Orders Due From/To fields. Note that the default date is current date, you may need to change this. When **F16=Review Orders** is selected on the Issue Materials screen, the Production Order Selection window is displayed.

Production Order Selection Window (F16)



When **F16=Review Orders** is selected on the Issue Materials screen, the Production Order Selection window is displayed.

The following fields and functions are displayed:

PC220		Z1 - GB Demonstration Company		USER GBJBAMS	8/12/95 15:49:18	
Issue Materials						
Production Order....?: _____						
Operation Sequence.....: _____ (Blank for All Inputs)						
Date.....: 8/12/95						
Production Order Selection						
S	T	Order	Item/Group	Sts	Order Qty	UOM St Due Date R Reference
■		W000183	MS001	3	48.000	EA FG 5/01/96 1
-		W000184	MS001	3	12.000	EA FG 2/02/96 1
-		W000187	MS004	3	77.000	EA FG 26/01/96 1
-		W000189	MS004	3	20.594	EA FG 2/02/96 1
1=Select						
F12=Previous F22=Expand/Contract						
11-04 S MW KS IM II KENB20A PET166S2						

Fields:

S

You can enter the following option:

1- Select. When this option is entered, the Record Issues And Adjustments screen is displayed for the selected order.

T

Text. For each order, an asterisk is displayed in this field if text has been entered against the order.

Sts

Status. The current status of the order. The following can be displayed:

- 1 - Planned Order.
- 2 - Confirmed Order.
- 3 - Released Order.
- 4 - Active Order.

Order Qty

The original order quantity.

UOM

Unit of measurement defined for this item.

St

Primary stockroom.

Due Date

Due date of the order.

R

Route code.

Reference

Reference field number 1.



When 1 is entered in the S field on the Production Order Selection window, the Record Issues And Adjustments screen for the selected order is displayed.

Functions:

F22

Expand/Contract. Toggles between displaying basic and full details of the orders.

Record Issues And Adjustments Screen (Option 1)

When completing this screen consideration should be given to the following:

- Any of the pre-set fields may be changed.
- The Type and Reference fields are optional but note that there may be defaults set for these and other fields lower down the screen. These may be changed if required.
- If the input is subject to lot batch or serial control, a valid lot number or serial number is required. If this is not known, then **F4=Prompt** may be used.
- If an asterisk (*) is shown against the Issue Qty of an input then there is insufficient stock in the displayed stockroom. Issues can be made from another stockroom or an override can be taken which sets the stock negative.
- If a less than (<) symbol is shown against the Issue Qty of an input then this item is designated as backflushed. Under normal circumstances this item should not be issued.



When 1 is entered in the S field on the Production Order Selection window, the Record Issues And Adjustments screen for the selected order is displayed.

The following fields and functions are displayed:

PC221	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:51:05		
Record Issues and Adjustments					
Production Order...: W000182		Operation...:	Date...: 8/12/95		
Workstation.....:		Shift.....: 00			
Process Group/Item: MS001		Product A			
Order Quantity....:		5.000	UOM: EA Quantity Complete:		
S Input	Issue Qty	UOM ST	Type Reference Batch		
- RAM01	<u>11.700</u>	EA RM			
- RAM02	<u>25.000</u>	EA RM			
- RAM03	<u>10.000</u>	EA RM			
- RAM04	< <u>EA RM</u>				
1=Select 2=Substitutes					
Reference: <u>W000182</u>		Transaction Type: ____	Date: <u>8/12/95</u> W/S: <u>WS01</u>		
F3=Exit F4=Prompt F8=Confirm All Issues F9=Confirm Selected Issues					
F12=Previous F19=Record Unplanned Issue F22=Expand/Contract					
10-02	SA	MW	KS	IM	II KENB20A PET166S2

The physical quantities called for by the order are displayed and underlined. The physical quantities calculated by Batch Balancing are shown below this figure. This means that ALL the material MUST be issued as selected on order release.

A check is made to ensure that the issues made are not from a different lot or from a quantity greater than the quantity reserved (balanced).

The following fields and functions are displayed:

PC221		Z1 - GB Demonstration Company		USER GBJBAMS	13/12/95
					15:57:41
Record Issues and Adjustments					
Production Order...		W000195		Operation...	Date...: 13/12/95
Workstation.....				Shift.....	00
Process Group/Item:		MS005		Product F	
Order Quantity....		10.000		UOM: EA Quantity Complete:	
S Input	Issue Qty	UOM	ST	Type	Reference
RAM01	6.000	EA	RM		
RAM02	10.000	EA	RM		
RAM03	4.000	EA	RM		
	4.000	EA	RM		LOT01
RAM04	< 4.000	EA	RM		
RAM06	2.000	EA	RM		
1=Select 2=Substitutes					
Reference: W000195		Transaction Type:		Date: 13/12/95	W/S: WS01
F3=Exit F4=Prompt F8=Confirm All Issues F9=Confirm Selected Issues					
F12=Previous F19=Record Unplanned Issue F22=Expand/Contract					
10-02 S2 MK KS IM II KENB20A PET166S2					

Fields:

S

You can enter the following options:

- 1 - Select. When 1 is entered against an item, and **F9=Confirm Selected Issues** is selected, the item is confirmed.
- 2 - Substitutes. Against a particular item to action a substitution. When this option is entered, the Substitutes window is displayed.

Issue Qty

This field displays the quantity required to complete the order. Therefore, if blank, it implies that all current requirements are met. It also implies that backflushed items have not been issued but show zero requirement because their requirements are met automatically on receipt of a parent item at the count point on an operation routing where they are consumed.

Items which have been lot balanced as part of the order release procedure display a quantity to issue above and below the line, and a lot number below the line in the Batch field. The below the line numbers indicate the lots and quantities which have been reserved in the issuing stockroom. These lots can now be issued to the floor stock.

Initially, the stockroom displayed is the issuing stockroom, invoking this issue changes the stockroom to that designated as the floor stock stockroom for the relevant work station/operation if the material being issued is a floor stock item.

If key ingredients are not issued to floor stock, then booking of receipts at the operation where they are required is not permitted as it is a mandatory requirement to select lots at that time. Reserved lots are not made available for subsequent selection.

If an item is to be substituted, then a quantity must be specified before the substitution routine is invoked. It is not possible however to substitute more than has been already issued.

To make an adjustment indicating a return to stock, enter a negative quantity. To do this, enter a quantity with a minus sign suffix, not prefix, for example 2- not -2.

(Untitled)

Stock Indicator. The following can be automatically displayed:

* - Indicates there is not enough stock to meet the requirement. Issuing is allowed for non lot controlled items, for which negative stock balances are allowed. Issuing is not allowed for lot controlled items which cannot hold negative balances.

< - Indicates it is a backflushed item and need not be issued manually.

UOM

Unit of Measurement. This is the issuing UOM of the item.

St

Stockroom. This identifies the issuing stockroom. For lot controlled floor stock items, this is the Inventory stockroom when reserved, but this changes to the floor stock location when consumed during order booking.

Type

Each item issue may be designated a specific transaction type in preference to the default issue transaction type. A transaction type is used for inventory analysis; it does not effect changes to item balances.

Transaction types are defined on the Inventory Management application, descriptions file against type TRAN.

Reference

Each item issue may be given a specific reference which overrides the default issue reference.

Batch

For all lot controlled items, you must enter the lot, batch or serial number for the item to be issued.

You can add an input to the list by entering details in the Reference, Transaction Type, Date and W/S fields.

Reference:

Each issue recorded can be assigned a reference; this defaults to the production order number but this may be overridden. In addition, each item issued may be given an individual reference if required.

Transaction Type:

Each issue may be designated a particular transaction type. In addition, each item may be assigned to its own type if required. A transaction type is used for inventory analysis, it does not effect change to item balances.

Transaction types are defined on the Inventory Management application, descriptions file against type TRAN.

Date

This field defaults to the date entered on the Issue Materials screen. However, you can enter another issue date.

W/S

Work station. If an operation sequence has been specified on the first screen, the option is given to select a work station to issue to. The default is that originally entered.

Functions:

F9

Confirm Selected Issues. This function only updates items which are marked specifically. When 1 is entered against items in the S field, and **F9=Confirm Selected Issues** is selected, the items are confirmed.

F19

Record Unplanned Issue. When this function is selected the Record Unplanned Issue window is displayed.



Note: This function is not available when using process groups with lot balancing.

F22

Expand/Contract. When this function is selected, additional details for each input are displayed.



When 2 is entered in the S field on the Record Issues And Adjustments screen, the Substitutes window is displayed.



When **F8=Confirm All Issues** is selected, all items on the screen are confirmed.



When **F19=Record Unplanned Issue** is selected on the Record Issues And Adjustments screen, the Record Unplanned Issue window is displayed.

Substitutes Window (Option 2)

You can display the substitute items which have been defined for the selected item.



When 2 is entered in the S field on the Record Issues And Adjustments screen, the Substitutes window is displayed.

The following fields and functions are displayed:

PC221		Z1 - GB Demonstration Company		USER GBJBAMS	8/12/95
					15:51:05
Record Issues and Adjustments					
Production Order...: W000102		Operation...:		Date...: 8/12/95	
Substitutes					
Orig Item	RAM01	Desc Raw material 1		Qty O/S	11.700
Seq	Subst	Item	Description	Qty Req	St UOM Avail Qty
001	RAM02		Raw material 2	11.700 RM EA	3782.000
			Lot:	Qty To Be Issued	.000
003	RAM04		Raw material 4	11.700 RM EA	1249.500
				Qty To Be Issued	.000
1=Select 2=View Stock					
F8=Issue Substitute F12=Previous					
09-03 S2 MW KS IM II KENB20A PET166S2					

Fields:

(Untitled)

You can enter the following options:

1 - Select. You can select a substitute and change the quantity to be issued. Press **Enter** and select **F8=Issue Substitutes**.

2 - View Stock. You can display the stock of a substitute. Further details of the stock position can be seen by using **F22=Expand/Contract**. Select the substitute required with a 1. After issuing a substitute returning to the same order displays the substitute issue.



Note: Substitutes cannot be used when the Issue Qty is zero, i.e. the full quantity has already been issued.

Record Unplanned Issue Window (F19)



Note: This function is not available when using process groups with lot balancing.



When **F19=Record Unplanned Issue** is selected on the Record Issues And Adjustments screen, the Record Unplanned Issue window is displayed.

The following fields and functions are displayed:

PC221	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 15:52:29
-------	-------------------------------	--------------	---------------------

Record Issues and Adjustments
 Production Order...: W000182 Operation...: Date...: 8/12/95
 Workstation.....: WS01 Shift.....: 00
 Process Group/Item: MS001 Product A
 Order Quantity....: 5.000 UOM: EA Quantity Complete:

S	Input	Issue Qty	UOM	ST	Type	Reference	Batch
	RAM01	11.700	EA	RM			

Record Unplanned Issue

Operation Sequence: _____
 Unplanned Input?...: _____
 Quantity.....: _____ UOM...?...: _____
 Stockroom.....?...: _____ Batch?...: _____
 Reference.....: W000182
 Transaction Type?...: _____
 Date.....: 8/12/95 Reason Code...?...: _____

F4=Prompt F8=Confirm Issue F12=Previous

Reference: W000182 Transaction Type: _____ Date: 8/12/95 W/S: WS01

F3=Exit	F4=Prompt	F8=Confirm All Issues	F9=Confirm Selected Issues
F12=Previous	F19=Record Unplanned Issue	F22=Expand/Contract	

12-25 **SP** MW KS IM II KENB20A PET166S2

Fields:

Operation Sequence

Enter the operation sequence at which the material is to be issued. If no operation is entered, the first operation on the route is defaulted to and displayed when Enter is pressed.

Unplanned Input

Enter the item to be issued.

Quantity

Enter the quantity to be issued.

UOM

Enter a valid issuing unit of measurement, as defined to Inventory, for the input. If no entry is made in this or the Stockroom field, the system defaults to and displays the UOM in the primary stockroom when Enter is pressed.

Stockroom

Enter a valid stockroom for the input. If no entry is made the system defaults to and displays the primary stockroom for the item when Enter is pressed.

Batch

If the input is lot controlled, then a lot reference number must be entered.

Reference

Each item may be given a specific reference which overrides the default issue reference. The production order reference is displayed as default for the item.

Transaction Type

Each item may be designated a specific transaction type in preference to the default issue transaction type. a transaction type is used for inventory analysis; it does not effect changes to item balances.

Transaction types are defined in the Inventory Management application, descriptions file against type TRAN.

Date

Each item issue may be given an issue date. If no date is entered, the current system date for all issues is assumed.

Reason Code

This is an analysis code which can be used in variance reports. Entry of a code is mandatory.

Reason codes are defined in the Inventory Management descriptions file against type MOVR.



When the appropriate data is entered in the fields and **F8=Confirm Issue** is selected, the item is confirmed and the Record Issues And Adjustments screen is displayed.

Production Order Booking



12/PCM



When Production Order Booking is selected on the menu, the first Production Order Booking screen is displayed.

Production reporting includes the capture of any information which can be meaningfully associated with activities and events which involve productive resources. This includes information about operators, work stations, materials and subcontractors. This information, may include all or part of what, who, why, when, where and how activity has occurred.

The activities reported and detail required in reporting these activities is controlled by you. Each organisation can collect meaningful information without unnecessary detail and in a manner which is clear and understandable to its reporting community.

The activities you wish to report must first be defined using the Maintain Activity Control File function, ensuring that the activity indicators are set correctly. These establish the mandatory, optional and prohibited data entry requirements for each activity type. These definitions also determine the information included in transaction files for which production activity database records are written.

The activity type selected for the booking session determines the range of fields prompted, and their compulsory or optional completion. For this reason, it is not possible to state against every field whether or not it is a mandatory requirement to complete it.

In addition to the activity type definition, the format of, interpretation of and use of details prompted is further qualified by flag settings on the company profile, organisational model, and route against which a booking is being processed.

On completing all required fields on the entry screen header and details section, press **Enter**. The system validates all entries made, and highlights any with invalid data. These fields must then be re-entered.

A subsequent **Enter** may display windows for the entry or confirmation of outputs or inputs or for operation/order completion.

During bookings, function keys allow the entry, review, or amendment of crew, input, output, scrap and held details in a window associated with the specific bookings. These windows may be used to revise the standard input/output quantities or to indicate where non standard items are consumed/produced; to enter scrap or held references; or to set the codes and working time associated with individual operators within a crew.

A Booking Details window is opened after entry and completion of the first operation booking. This window is updated after each operation booking is completed and it displays a cumulative listing of bookings made for the session to-date. After completion of each booking the detail entry fields are cleared, leaving the previous bookings values in the header fields.

Access to the Booking Details Window directly to allow amendments is allowed.



Note: For production orders with no inspection order but with an inspection policy of 2 (Bookings), an inspection order is automatically generated for each production order booking made at a quality controlled operation.

Bookings can be made in two ways for production orders - the order reference is required for either method:

Production Order Booking

This provides a convenient means for an operator or crew to book a number of activities they have performed on a number of orders, without having to re-input information about themselves for every order/activity. For example, set up, production booking or scrap reporting.

When booking production information, you do not necessarily have to enter amounts against the main item of the process in order to reflect that quantities of co-products, waste products and by-products exist. Outputs defined with zero quantities are highlighted as warnings but do not prevent the entry of other output type detail.

Operator Booking

This option allows the entry of an order reference and without the need to input the order heading details again, and enables the booking of multiple events which relate to this item/order.

The Order and Operator booking options each utilise the same processing mechanism for doing all types of production reporting. Activity can be reported through either method for any of the activity types that have been established for the company.

Production Order Booking Screen 1



When Production Order Booking is selected on the menu, the first Production Order Booking screen is displayed.

The following fields and functions are displayed:

MG200	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 15:59:50
Production Order Booking			
Header details			
Date.....	8/12/95	Shift	__
Work Station.?	__	Dept.?	__
Operator.....?	__	Cr.?	__
F3=Exit F4=Prompt			
05-10	8	MW	KS IM II KENB20A PET166S2

Fields:

Header Details

Date

This field defaults to the current system date, and a date must be in this field. You can enter another date for this booking if the current system date is not appropriate. All bookings made during this session are recorded against the date entered, unless amended at a later stage.

Shift

You can enter the shift number to which the booking relates. This provides a more precise time frame for recording booking if a start and finish time are not entered. For example if the booking has an elapsed time in 3 hours, this might be linked to shift 2 which runs 16:00 to 24:00. If entered this should be a shift number on the shift profile in force on the booking date at the work station at which the booking is made.

Work Station

You must enter a value in either the Work Station and/or the Dept field.

You can enter the work station against which the booking is to be made. This would usually be the work station assigned to the operation on the relevant production route for the production order.

If a non standard work station (that is, not the work station expected by the route) is entered, any WIP inventory resulting from the booking is recorded against the WIP location associated with the booking work station; which may differ to the standard route.

If the work station WIP location is different, the system displays a warning message stating Reported WIP location is not the standard for this operation and continuation must be manually confirmed to progress the booking.

If the operation booking involves the issue of floor stock materials from a floor stock location linked to the standard work station on the route, then any non standard work station must also be associated with that floor stock location in order to issue materials previously allocated to this order. If it is not, the allocated stock of materials must be transferred on the system to the new floor stock location.

Dept

You must enter a value in either the Work Station and/or the Dept field.

Departments are an analysis and (optionally) MRP planning tool and do not impose any constraints over WIP inventory, work station operator or crew bookings. For each booking, a work station or department must be defined.

If a work station is entered but not a department, the system defaults to and displays the department assigned to the work station definition, if one exists, when Enter is pressed to validate header details.

If a work station is not entered, but a department is, booking details assumes the standard work station defined for the operation on the order route.

If a department is not entered, but the operator has been assigned a department via Operator Maintenance the system defaults to and displays the department when Enter is pressed to validate the header details.

Departments are user-defined and are entered on the system via the Maintain Parameters facility, against type DEPT.



Note: Departments can also be entered against a stockroom details record in Inventory Management. If Department (Cellular) MRP planning or Departmental Cost Analysis is to be used, it is important that Production and Inventory Management departments codes are kept in tandem.

Operator

You can enter data in either the Operator field or the Cr field, but not in both.

You can enter an operator code identifying the person who performed the work.

Alternatively, a crew code may be entered if a crew (group or operators) rather than an individual was responsible for the work being reported.

Cr

You can enter data in either the Operator field or the Cr field, but not in both.

Crew. Enter a crew code identifying the people (operators) who performed the work.

Alternatively, an operator code may be entered if an individual, rather than a crew was responsible for the work. Crew and operator codes are mutually exclusive.

Any booked time associated with the operation is allocated to each member of the crew automatically. For example, if an operator time of 8 hours is entered, each member of the crew is assumed to have worked 8 hours on the operation. To amend these times, select **F13=Crew Details**, which allows you to modify the time on an individual basis.



When **Enter** is pressed on the first Production Order Booking screen, the second screen is displayed.

Production Order Booking Screen 2



When **Enter** is pressed on the first Production Order Booking screen, the second screen is displayed.

The following fields and functions are displayed:

MG200	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 15:59:50
Production Order Booking			
Header details			
Date.....	8/12/95	Shift	__
Work Station.?	WS01	Dept.?	__
Operator.....?	__	Cr.?	__
Booking Details			
Activity.....?	PRODRP	Rev Ind	@
Work Order....?	__		
Operation.....?	__		
Lot Number....	__		
Time			
Oper Elapsed.	__	.00	
W/S Elapsed.	__	.00	
Quantity			
Good..	__	.000	
Scrap..	__	.000	Reason.? SC
Held..	__	.000	Reason.? QI
Op Complete.	@	Order Complete.	@
F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details			
F16=Outputs F17=Scrap F18=Hold F19=Booking Details			
10-10 S2 MW KS IM II KENB20A PET166S2			

Fields:

Booking Details

Activity

You can enter the code of the activity type to be reported. This must be an activity type that has been defined using the Production Activity Control File Maintenance function. Every activity type is associated with a reporting type that determines which fields are mandatory or optional and which transactions are captured when reported. This field defaults to the activity type with the lowest sequence value.



Warning: Check that the default activity code is correct for the booking you are about to make. The cursor does not go directly into this field.



Note: If the activity code is changed from the default then press Enter to pick up the new validation for this code before attempting to put in further detail.

Rev Ind

Reversal indicator. This flag indicates whether or not the booking is being entered to correct a previous booking. You can enter the following options:

0 - Standard Booking.

1 - Reversal. Indicates that the activity being reported is a reversal. This means that any quantity entered moves the opposite way to the standard transaction and any times and input/output booked quantities are reported as negative. When displayed to the Booking Details Window, the associated order number is highlighted.

Work Order

Enter the order number against which the booking is to be made. The order must be at a status of Released or Active or an error message is displayed.

Operation

Enter the operation to which the time and/or quantity relates. The work station/operation relationship determines the WIP location used to create, ascertain and maintain WIP inventory balances. This would usually be that defined on the planning route, but sometimes as work may be reported at non-standard work stations, WIP inventory may be recorded as being held at different WIP locations for the same order.

For successful backflushing of WIP inventory between count point operations, it is essential that all inventory pertaining to an order is recorded as existing in the standard WIP location. This is achieved by always booking at the standard work station; or booking against a different work station with the same WIP location.

Bookings against a non-standard work station, with a different WIP location, necessitate transferring WIP from the posted WIP location to the standard WIP location.

To book WIP inventory, the Reporting Type flag on the route operation must be set to 0 (count point). Actioning booking updates WIP inventory balances at the booking operation and backflushes all operations back to but excluding the previous count point operation. The last operation on the route must be a count point.

If the Reporting Type flag on the route/operation has been set to 1 (backflushed) then operator, crew and work station time, and operation rework activity may only be booked by certain activity type codes; together with scrap and held details.

If the operation is subcontracted, then no operator/order booking may be made; the facility is effectively replaced by the Ship WIP and Receive from Subcontractor routines.

If the Generate Cost Recovery flag on the Organisational Model is set to 1 (yes) then standard activity cost records are created when WIP inventory is booked at a reporting type 0 or (count point) operation. This calculates the value of WIP inventory at that count point operation and for any backflush operations. Shrinkage on the route may be booked as scrap quantity.

Lot Number

You can enter a lot number relating to the quantity being booked. This is only ever a memorandum field for non lot controlled items. The number need not be that entered as a final lot when received into inventory.

If the WIP Lot Tracking flag on the Organisational Model is set to 1 (yes) then a lot number is a mandatory requirement, and the quantity booked at an operation

must be less than or equal to the quantity booked against the same lot number at the previous count point operation.

If WIP lot tracking is not used, then a lot number need not be entered, even for lot controlled items at this point: but must be entered when the item is received into inventory as finished goods.

If a key ingredient is an input to an operation, then the lot number should be left blank. Selection of the key ingredient lot from the floor stockroom sets the required lot number in this field. This function occurs irrespective of the WIP Lot Tracking field setting.

If the key ingredient is input to an operation other than the first, and WIP lot tracking is required, lot numbers must be used at all operations up to and including the key ingredient input operation. However, all subsequent operations enforce the use of the key ingredient lot number.

Time Oper Elapsed



Note: It is only possible to specify a maximum of 24 hrs per booking; and the time entered is synonymous with labour time when producing costings.

The methodology used to enter times is dependent on two flag settings on the Organisational Model.

If the Time Reporting Policy flag is set to 0 (elapsed time), then a single entry specifying time spent must be entered. This field is further qualified by the Time Booking Policy flag which determines whether time should be booked in decimal hours (for example, 1.50 equates to 1 hour 30 minutes) or hours and minutes (for example, 1.30 equates to 1 hour 30 minutes). It is essential that you understand which policy is in operation before booking time, or it can result in incorrect times, costs and efficiencies.

If the Time Reporting Policy flag is set to 1 (time in, time out) a start and finish time must be entered in 24 hr clock format. For example, 0800 1430 the system calculates the resultant time spent (6.5 hours).

Time spent is allocated to the operator if specified; or to each member of the crew if a crew code was entered, or to the standard crew size on the route if neither operator nor crew were entered.

Time W/S Elapsed

Enter the work station usage time. This may be more or less than or equal to the operator/crew time.



Note: It is only possible to enter a maximum of 24 hrs per booking.

The methodology used to enter times is dependent on two flag settings on the Organisational Model.

If the Time Reporting Policy flag is set to 0 (elapsed time), then a single entry specifying time spent need be entered. This field is further qualified by the Time Booking Policy flag which determines whether time should be booked in decimal hours (for example, 1.50 equates to 1 hour 30 minutes) or hours and minutes (for

example, 1.30 equates to 1 hour 30 minutes). It is essential that you understand which policy is in operation before booking time.

If the Time Reporting Policy flag is set to 1 (time in, time out) a start and finish time must be entered in 24 hr clock format. The system calculates the resultant time spent.

Quantity Good

The methodology used and the interpretation of, the quantity entered here is dependent on several flag settings which are explained below. The Quantity Reporting flag on the Organisational Model can be set to:

0 - Exclude Scrap & Held. In this case the first Quantity field is displayed as Good on the booking screens and excludes the scrap and held quantities entered in the following fields.

1 - Include Scrap & Held. In this case the Quantity field is displayed as Total and includes scrap and held quantities booked.

Scrap and held quantities are always entered independently of the quantity (good or total).

The Count Reporting Policy flag on the Organisational Model may be set to 0 (total quantity) whereby a single number is prompted, or 1 (count in, count out) where a start and end number is prompted, leaving the system to determine the actual quantity by subtracting in from out. Care should be taken with this policy if the quantity being reported is exclusive of scrap and held.

If the parent item is a process group, the quantity entered is qualified by the Output Validation flag on the route header. If set to 0 (co-product quantity) the quantity entered should be that for the primary co-product only, all other co-products, by-products and waste quantities are calculated accordingly. If set to 1 (all quantities) then the booked quantity should be equal to the sum of all output quantities. If set to 2 (no validation) then the process group quantity should be booked and individual outputs confirmed.

If operation WIP is booked in a different UOM to the parent item (as defined on the route as the Reporting UOM) the system uses the UOM Conversion factor (again defined on the route) to determine the parent equivalent quantity in order to determine the outstanding planned quantity. For example, if WIP is booked in grams and the parent quantity is 1 Kg, then booking 500 at the WIP operation leaves an outstanding quantity of 0.5 Kg, not an overproduction of 499 Kg.

If WIP lot tracking is being used, then the quantity entered must be less than or equal to the quantity reported at the previous count point operation for the lot number entered.

If the reported quantity this session, plus the quantities booked to-date equal the planned order quantity, the system automatically prompts with Operation complete, press Enter to continue.

Quantity Scrap

Enter the quantity scrapped at this operation. The system assumes that the full quantity of materials, labour and work station time required to make an equivalent good quantity is also consumed in the production of scrap.

F17=Scrap can be used to enter a reference and scrap reason code against the full quantity; or a range of codes against a number of quantities. Entry of a reference is never mandatory.

Scrap balances are not maintained for an item/operation.

If the quantity has not yet been scrapped, but is to be scrapped, then record the balance as held, defining a reason code for the held quantity to indicate that it is waiting to be scrapped.

Reason

Scrap Reason. If a scrap quantity is reported, then a reason code must be entered. By associating each scrap transaction with a reason, information is captured which enables analysis of item/operations scrapped, detailed by reason code.

Enter a default reason code. The initial code displayed is that held on the Organisational Model.

Codes are defined on the Inventory Management, descriptions file, against type MOVR.

Quantity Held

Enter any quantity that was held resulting from the activity being reported. The held balance is updated for the item/operation being reported. A reason code for holding the stock must be entered if any quantity is entered in this field.

Enter the quantity held at this operation. Quantities may be held, for example, for rework or quality inspection.

F18=Hold may be used to enter a reference and held reason code against the full quantity; or a range of codes against a number of quantities.

If a rework activity type is booked at an operation, a held quantity equal to that reworked should have been recorded in WIP inventory at the previous operation. Held quantities are subsequently reduced when the rework is booked good.

There is also an activity type available to record rework associated with extra time spent on an operation. This has no effect on standard WIP but can generate an actual time booking/cost against the order.

If the Held Inventory Tracking flag on the Organisational Model is set to 1 (yes) then entry of a held reference is mandatory; and the system prompts for entry when Enter is pressed to validate booking details.

To make held WIP inventory available, you may use the Release Inventory function on the menu.

Alternatively, held WIP inventory may be scrapped using the Scrap Held Inventory on the same menu.

Reason

Held Reason. If a held quantity is reported, then a reason code must be entered. The code entered should indicate the reason why the quantity is being reported as held.

Enter a default reason code. The initial code displayed is that held on the Organisational Model.

Codes are defined on the Inventory Management, descriptions file, against type MOVR.

Op Complete

This field is automatically prompted following entry of a good quantity that causes booked WIP inventory to equal planned operation quantity. The field indicates whether or not any further booking is expected at that operation. You can enter the following options:

0 - If the operation is not complete; further booking is expected.

1 - Operation complete. No further booking is expected. The total booked may be less than or greater than planned.

An operation may also be set to Complete via the Order Completion routine on the menu, and a Complete operation may be re-opened using the same facility.

Order Complete

This field is automatically prompted following entry of a good quantity that causes WIP inventory to equal planned (order) output quantity. The field indicates whether or not any further bookings of outputs are expected. You can enter the following options:

0 - If the order is not complete; further booking is expected.

1 - Order complete. No further booking is expected. The total booked may be less than or greater than planned.

An order may also be set to Complete via the Order Completion routine on the menu, and a Complete order may be re-opened using the same facility.



When **Enter** is pressed, the entries are validated and the Booking Details window is displayed.



*Note: If inputs are backflushed or warehouse controlled, floor stock items or key input items, as a result of booking this operation, the Input Details window is displayed. This window enables additions or amendments to be made to the standard quantities/items expected for this booking quantity. If no changes are required then selecting F8 confirms component issue and closes the window. A further **Enter** displays the Item Booking Details window.*



Note: When the materials are warehouse controlled, it is necessary to follow a series of picking and/or issue routines in the Warehousing application to issue the materials for the operation/order before the transaction booking is begun.

Functions:

F13

Crew Details. When this function is selected the Crew Details window is displayed.

F14

Component Details. When this function is selected the Component Details window is displayed.

F16

Outputs. When this function is selected the Outputs window is displayed.

F17

Scrap. When this function is selected the Scrap WIP Details window is displayed.

F18

Hold. When this function is selected the Held WIP Details window is displayed.

F19

Booking Details. When this function is selected the Booking Details window is displayed.

Crew Details Window (F13)

This window displays the operators who are members of the crew. Additions, amendments and deletions can be made if required to the default crew members and job times for the activity reported.



When **F13=Crew Details** is selected on the second Production Order Booking screen, the Crew Details window is displayed.

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User	GBJBAMS	8/12/95
						15:59:50
Production Order Booking						
Header details						
Date.....	8/12/95	Shift				
Work Station.?	WS01	Dept.?				
Operator.....?		Cr.?	Z1			
Booking Details						
Activity.....?	PRODRP	Rev Ind	0			
Work Order....?	W000182					
Operation....?	20					
Lot Number....						
Time						
Oper Elapsed.	2.00					
W/S Elapsed.	3.50					
Quantity						
Good..	1.000					
Scrap.	.000	Reason.?	SC			
Held..	.000	Reason.?	QI			
Op Complete.	0	Order Complete.	0			
F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details						
F16=Outputs F17=Scrap F18=Hold F19=Booking Details						
06-42 SF MW KS IM II KENB20A PET166S2						

Crew Details			
S Operator	Time-In	Time-Out	Elapsed
- Z1.1	.00	.00	2.00
- Z1.2	.00	.00	2.00
- Z1.3	.00	.00	2.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00
-	.00	.00	.00

4=Delete
F12=Previous ENTER to Accept

Fields:

S

Select. You can enter the following option:

4 - Delete. You can remove crew members from the crew (for this activity only). When this option is entered, press **Enter**, then select **F11** to confirm deletion.

Operator

You can enter the names of the individual crew members.

Time-In

If Time Reporting policy for Organisational Model is 1 (Start/End), you can enter the start time.

Time-Out

If Time Reporting policy for Organisational Model is 1 (Start/End), you can enter the finish time.

Elapsed

If Time Reporting policy for Organisational Model is 0 (Elapsed), you can enter the elapsed time.



When the appropriate data is entered in the fields and **Enter** is pressed, the data is validated and the Production Order Booking screen is displayed.

Component Details Window (F14)

This window is opened automatically for floor stock issue and warehouse controlled backflush items.

This window shows any backflush, floor stock items, or key ingredient items which are included in the route for the parent item being booked. If necessary the quantity can be amended. This window would not be used for issuing materials with a Material Type of 0 (formal issue) on production orders.



When **F14=Component Details** is selected on the second Production Order Booking screen, the Input Details window is displayed.

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User GBJBAMS		8/12/95 15:59:50	
Production Order Booking							
Header details							
Date.....	8/12/95	Shift					
Work Station.?	WS01	Dept.?					
Operator.....?		Cr.?					
Booking Details							
Activity.....?	PRODRP	Rev Ind	0				
Work Order....?	W000182						
Operation....?	10						
Lot Number....							
Time							
Oper Elapsed.	2.00						
W/S Elapsed.	2.00						
Quantity							
Good..	1.000						
Scrap.	1.000	Reason.?	SC				
Held..	1.000	Reason.?	QI				
Op Complete.	0	Order Complete.	0				
F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details							
F16=Outputs F17=Scrap F18=Hold F19=Booking Details							
15-44 52 MW KS IM II KENB20A PET166S2							

Component Details		
S Component	Opsq	Quantity
- RAM04	0010	4.500
Add/Amend		
		.000
Stockroom....		
1=Select Lots		3=Amend
F8=Confirm		F12=Previous

Fields:

S

Select. Select an input detail for lot definition or amendment. You can enter the following options:

- 1 - Select Lots. This option selects lots consumed for lot controlled inputs.
- 3 - Amend. This option allows a line quantity or stockroom to be amended.

Component

The input inventory part number. This field displays the component name.

Opsq

Operation Sequence. This field displays the operation sequence number of the component.

Quantity

The standard quantity that is backflushed based upon the operation quantity of the activity reported. Or the amended quantity if this has just been changed.

Add/Amend

You can add a new component or amend the details of an existing component by entering the component, operation sequence and quantity in the fields under the add/Amend heading.

Stockroom

You can enter the stockroom name in this field.



When the appropriate data is entered in the fields and **F8=Confirm** is selected, the data is validated and the second Production Order Booking screen is displayed.

Outputs Window (F16)

This window is automatically displayed for:

- Process groups
- Lot controlled items

The standard output quantities are shown and can be amended to record the actual quantities. A facility is also provided to record any unplanned outputs **F14=Unplanned Output**.

The window includes a display field which indicates which output is primary, if any, flagged with a 1 on a process group route. The screen offers a number of processing options both in terms of option keys and function keys.



When **F16=Outputs** is selected on the second Production Order Booking screen, the Outputs window is displayed.

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User GBJBAMS		13/12/95	
						16:20:52	
Operator Booking							
Header details							
Date.....	13/12/95	Shift	__				
Work Station.?	WS01	Dept.?	__				
Work Order....	W000199						
Operation....?	30						
Lot Number....	LOT01						
Booking Details							
Activity.....?	PRODRP	Rev	Ind	0			
Operator.....?	__	Cr.?	__				
Time							
Oper Elapsed.	4.00						
W/S Elapsed.	5.00						
Quantity							
Good..	2.000						
Scrap..	.000	Reason.?	SC				
Held..	.000	Reason.?	QI				
Op Complete.	0	Order Complete.	0				
F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details F16=Outputs F17=Scrap F18=Hold F19=Booking Details							
07-42 SF MK KS IM II KENB20A PET166S2							

Outputs			
1 Output	Quantity	UOM	ST
Lot Number	Qty. Outstd.	Prmy	
COP01	6.000	EA	FG
LOT01	300.000	1	
COP02	2.000	EA	FG
LOT01	100.000		
BVP01	10.000	EA	FG
LOT01	500.000		
WAS01	8.000	EA	FG
LOT01	400.000		

1=Select 2=Autoreceive 3=Ignore
4=Complete 5=Lot Details

F8=Confirm F9=Receive Sel
F12=Previous F14=Unplanned Output

Fields:

1

You can enter one of the following options:

1 - Select. This selects an item. When this option is entered, the Add/Amend Output window is displayed, which allows changes to be made to the line selected.

When 1 is entered in this field and **F9=Receive Sel** is selected, this allows part receipt of the screens listing, of the selected lines, into Inventory, with displayed quantities.

2 - Autoreceive. On a process group route, if outputs listed are co-products and by-products, they are associated in terms of an output ratio defined on the route. When this option is entered, the Add/Amend Output screen is displayed. Changes to the quantity of any one output, results in the Output details screen being refreshed with new quantities for the rest of the group, in accordance with the amendment, to maintain the ratio defined in the route.

Autoreceive is the highest priority amendment for quantities. If a line is amended on its own, either by selecting it with a 1 or a 3, if subsequently, the process group is selected with a 2, the quantities are revised for these lines again.

3 - Ignore. When this option is entered, the quantity for a line is changed to zero. This means that the Inventory stock held for this product is not updated.

4 - Complete. This only applies to production orders. It sets the flag on the order to 1, to signify that the order is complete and as such that there is not more expected to be booked against it.

5 - Lot Details. When this option is entered the Select Location/Batch window is displayed.

Output

This field displays the name of the output item.

Quantity

This field displays the quantity of the output item.

UOM

This field displays the unit of measure of the output item.

St

This field displays the name of the stockroom where the output item is stored.

Lot Number

This field displays the lot number of the output item.

Qty Outsd

This field displays the quantity of the output item still outstanding.

Prmy

This field displays which output item is the primary item of a process group. A 1 is displayed in this field if the output item is the primary item.

Functions:

F9

Receive Sel. For outputs with option 1 in the 1 field, this allows part receipt of the screens listing, of the selected lines, into Inventory, with displayed quantities.

F14

Unplanned Output. If an unplanned output occurs at this item/operation that is not defined on the standard route, when this function is selected the Add/Amend Output screen is displayed. This screen allows the additional output to be recorded for posting to Inventory Management. As such, the item must be a valid

Inventory item associated to a valid Inventory stockroom for the additional screen to be accepted.



When **F8=Confirm** is selected, the second Production Order Booking screen is displayed.

Add/Amend Output Window (Option 1)

The default details displayed for amendment are taken from the relevant route.



When 1 is entered in the 1 field on the Outputs window, the Add/Amend Output window is displayed.

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User	GBJBAMS	13/12/95
						16:20:52
Operator Booking						
Header details						
Date.....	13/12/95	Shift	___			
Work Station.?	WS01	Dept.?	___			
er....?	W000199					
Operation....?	30					
Lot Number....	LOT01					
Booking Details						
Activity.....?	PRODRP	Rev Ind	0			
Operator.....?	___	Cr.?	___			
Time						
Oper Elapsed.	4.00					
W/S Elapsed.	5.00					
Quantity						
Good..	2.000					
Scrap.	.000	Reason.?	SC			
Held..	.000	Reason.?	QI			
Op Complete.	0	Order Complete.	0			
F3=Exit	F4=Prompt	F12=Previous	F13=Crew Details	F14=Component Details		
F16=Outputs	F17=Scrap	F18=Hold	F19=Booking Details			
10-61	SA	MA	KS	IM	II	KENB20A PET166S2

Outputs

1	Output	Quantity	UOM	ST	
	Lot Number	Qty.	Outstd.	Prmy	
1	C	Add/Amend Output			
L	Op. Seq....:	30			
C	Output.....:	COP01			
L	Quantity....:	6.000			
B	UOM.....?:	EA			
L	Stockroom.?:	FG			
W	Lot.....?:	LOT01			
L	Narrative...: W0001990030				
1=S	Tran Type.?:				
4=C	F4=Prompt F12=Previous				
F8=Confirm F9=Receive Sel					
F12=Previous F14=Unplanned Output					

Fields:

Op Seq

Operation sequence. If adding an unplanned output, enter the operation sequence at which the output was produced. For amendments, this is a display only.

The field shows 9999 indicating that it is a final operation for single item routes; or the relevant operation for multi-output routes.

Output

This refers to the Inventory item being produced. Outputs must be valid Inventory items with valid Inventory stockrooms assigned to them. If adding an unplanned output, enter the inventory item code for the output produced.

For amendments, this is a display only field, showing the Inventory item listed on the line selected.

Quantity

This refers to the quantity to which the Inventory stock of this item is updated.

If adding an unplanned output, enter the amount produced.

If amending a line, enter the actual amount produced and available for Inventory.

UOM

This refers to the unit in which stock of this output is measured in Inventory. For additions or amendments, enter the UOM the item is stocked in.

Stockroom

This refers to the Inventory stockroom the output is to be received into. Any stockroom entered here must be a valid Inventory stockroom, to which the item has been defined.

Lot

If the item is lot controlled a lot reference must be entered. The default is the production lot. If the quantity being booked is to be added to an existing Inventory lot, you can enter the lot number.

A new lot reference can be entered. If this is the case on confirming details in the Outputs screen (F8=Confirm, or F9=Receive Sel) the lot reference maintenance screen is displayed to allow the parameters for the new lot to be defined.

Reason

This field is only prompted if an unplanned output is being entered, and then entry is mandatory.

Codes are defined in the Inventory Management application, descriptions file, against major type MOVR.

Narrative

This field allows for specific narrative to be associated with this item in Inventory. The default narrative is the WIP lot reference for item/operation booking, or the concatenation of the production order with the operation when processing orders. If, when adding an unplanned output narrative is not specified, the relevant default is used.

Tran Type

Inventory transaction type. This becomes a mandatory field when lot tracking is on, as it requires all movements to be traceable by location and usage.

A transaction is used for inventory analysis only and does not affect changes to any item stock balances. Transaction types are defined in the Inventory Management application, descriptions file against type TRAN.



When the appropriate data is entered in the fields and **Enter** is pressed, the data is validated.
When **Enter** is pressed again, the Outputs window is displayed.

Select Location/Batch Window (Option 5)

This displays existing Inventory lot references, with the physical and available quantities for each listing. The list relates to stocks in the default stockroom for this item. Additional stockrooms can be reviewed by entering a new stockroom code. The window allows a particular lot to be selected, to which the current output quantity is added.



When 5 is entered in the 1 field on the Outputs window, the Select Location/Batch window is displayed.

The following fields and functions are displayed:

MG200 Z1 - GB Demonstration Company User GBJBAMS 13/12/95 16:20:52

Operator Booking
Header details
Date..... 13/12/95 Shift ____
Work Station.? WS01 Dept.? ____
Work Order.... W000199
Operation.... 30
Lot Number.... LOT01
Booking Details

Select Location/Batch

1=Select
Part Number: COP02 Stock Room: FG
F12=Previous F13=Expand/contract

13-04 SP MW KS IM II KENB20A PET166S2

1	Output	Quantity	UOM	ST
	Lot Number	Qty. Outstd.	Prmy	
-	COP01	6.000	EA	FG
	LOT01	300.000	1	
5	COP02	2.000	EA	FG
	LOT01	100.000		

Fields:

Select

You can enter the following option:

1 - Select a lot.

Stockroom

Enter the stockroom which receives the output. This must be a valid Inventory stockroom to which the output item is defined. The default is the one named as the receiving stockroom on the output details window on the route.



Select **F8** to save output details and press **Enter** to display the Booking Details window which is redisplayed and updated. Complete the session and initiate update with **F8**

Functions:

F13

Expand/Contract. This is a toggle key which, for each lot, displays or suppresses the production date and balances for the following quantities: on order, transfer out, transfer in, back order, allocated and frozen.

Scrap WIP Details Window (F17)

This window allows flexibility in reporting WIP scrap. It allows multiple quantity/reason code combinations to be reported within a single activity transaction.



When **F17=Scrap** is selected on the second Production Order Booking screen, the Scrap WIP Details window is displayed.

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User GBJBAMS		8/12/95	
						15:59:50	
Production Order Booking							
Header details							
Date.....	8/12/95	Shift	___				
Work Station.?	WS01	Dept.?	___				
Operator.....?	___	Cr.?	___				
Booking Details							
Activity.....?	PRODRP	Rev	Ind 0				
Work Order....?	W000182						
Operation....?	30						
Lot Number....	___						
Time							
Oper Elapsed.	1.00						
W/S Elapsed.	2.00						
Quantity							
Good..	1.000						
Scrap.	1.000	Reason.?	SC				
Held..	.000	Reason.?	QI				
Op Complete.	0	Order Complete.	0				
F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details							
F16=Outputs F17=Scrap F18=Hold F19=Booking Details							
10-42 SF MW KS IM II KENB20A PET166S2							

Scrap WIP Details

Item MS001 Oper 0030

Quantity Scrap 1.000

Remaining 1.000

Reference	Quantity	Reason ?
SCRAPREF:01	1	SC
	.000	
	.000	
	.000	
	.000	
	.000	
	.000	
	.000	

F12=Previous ENTER to Accept

Fields:

Quantity Scrap

The total scrap quantity from the Booking screen is displayed for your information only.

Remaining

The quantity of the total Quantity Scrap not yet accounted for is displayed for your information only.

Reference

You can enter a reference value. This might be a QA reference or a functional notation.

Quantity

You can enter the quantity of scrap relating to this line.

Reason

You can enter the reason code associated with this scrap quantity.



When the appropriate data is entered in the fields and **Enter** is pressed, the data is validated. When **Enter** is pressed again, the second Production Order Booking screen is displayed.

Held WIP Details Window (F18)

This window allows multiple quantity/reason code combinations to be reported within a single activity transaction.



When **F18=Hold** is selected on the second Production Order Booking screen, the Held WIP Details window is displayed.



Note: If Held WIP Tracking is in use then you must use this function and enter reference, quantity, reason codes as required

The following fields and functions are displayed:

MG200		Z1 - GB Demonstration Company		User GJBAMS		8/12/95	
						15:59:50	
Production Order Booking							
Header details							
Date.....		8/12/95		Shift		___	
Work Station.?		WS01		Dept.?		___	
Operator.....?		___		Cr.?		___	
Booking Details							
Activity.....?		PRODRP		Rev Ind		0	
Work Order....?		W000182					
Operation....?		30					
Lot Number....		___					
Time		___					
Oper Elapsed.		1.00					
W/S Elapsed.		2.00					
Quantity							
Good..		1.000					
Scrap.		1.000		Reason.?		SC	
Held..		1.000		Reason.?		QI	
Op Complete.		0		Order Complete.		0	
F3=Exit		F4=Prompt		F12=Previous		F13=Crew Details	
F16=Outputs		F17=Scrap		F18=Hold		F14=Component Details	
10-42		SF		MW		KS	
				IM		II	
				KENB20A		PET166S2	

Held WIP Details

Item MS001	Oper	0030
Quantity Held		1.000
Remaining		1.000
Reference	Quantity	Reason ?
HELDREF:02	1	SC
	.000	
	.000	
	.000	
	.000	
	.000	
	.000	
	.000	

F12=Previous ENTER to Accept

Fields:

Quantity Held

The total held quantity from the Booking screen is displayed for your information only.

Remaining

The quantity of the total Quantity Held not yet accounted for is displayed for your information only.

Reference

You can enter a reference value. This might be a QA reference or a functional notation.

Quantity

You can enter the quantity of held WIP defined by this line.

Reason

You can enter the reason code associated with this held quantity.



When the appropriate data is entered in the fields and **Enter** is pressed, the data is validated. When **Enter** is pressed again, the second Production Order Booking screen is displayed.



Select **F8** to apply the transactions entered, then display the first Production Order Booking screen. Select **F3=Exit** to return to a menu.


Booking Details Window (F19)

This window is opened and updated automatically when a booking has been completed.

Each new line appears under the last line posted. It shows a short history of the bookings that have been made before they are released for processing via the Transaction Manager update routines.

-  When **F19=Booking Details** is selected on the second Production Order Booking screen, the Booking Details window is displayed.
-  When **Enter** is pressed on the second Production Order Booking screen, the entries are validated and the Booking Details window is displayed.

The following fields and functions are displayed:



MG200 Z1 - GB Demonstration Company User GBJBAMS 8/12/95
15:59:50

Production Order Booking

Header details
Date..... 8/12/95 Shift ____
Work Station.? W001 Dept.? ____
Operator.....? Cr.? ____

Booking Details
Activity.....? PRODRP Rev Ind @
Work Order....? ____
Operation.....? ____
Lot Number.... ____
Time
Oper Elapsed. .00
W/S Elapsed. .00

Quantity
Good.. .000
Scrap. .000 Reason.? SC
Held.. .000 Reason.? QI
Op Complete. @ Order Complete. @

F3=Exit F4=Prompt F12=Previous F13=Crew Details F14=Component Details
F16=Outputs F17=Scrap F18=Hold F19=Booking Details

10-10 S MW KS IM II KENB20A PET166S2

Booking Details
S Work Order Opsq Quantity Act.
_ W000182 10 1.000 PRODRP

2=Amend 4=Delete
F8=Update F12=Previous

Fields:

S

Select. You can select or delete a reported entry. You can enter the following options:

2 - Amend. This option allows amendment of the selected line by reinstatement of the line information back into the Item Booking entry screen ready for amendment.

4 - Delete. This option requests deletion of the selected line, which you can confirm by selecting **F11=Delete**.

Work Order

The order against which a booking has been entered in this session is displayed for your information only.

Op Sq

Operation Sequence. The operation sequence number of the booking is displayed for your information only.

Quantity

The good quantity of the booking is displayed for your information only.

Act

Activity. The activity type of the booking is displayed for your information only.



When the appropriate data is entered in the fields and **F8=Update** is selected, the data is validated and the second Production Order Booking screen is displayed.

Functions:

F19

Acts as a toggle between the Booking Entry screen and the Booking Details window.

Operator Booking



Note: For production orders with no inspection order but with an inspection policy of 2 (Bookings), an inspection order is automatically generated for each production order booking made at a quality controlled operation.



13/PCM



When Operator Booking is selected on the menu, the first Operator Booking screen is displayed.

Operator Booking Screen 1



When Operator Booking is selected on the menu, the first Operator Booking screen is displayed.

The following fields and functions are displayed:

MG200	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 16:21:19
Operator Booking			
Header details			
Date.....	8/12/95	Shift	__
Work Station.?	__	Dept.?	__
Work Order...?	__		
Operation....?	__		
Lot Number....	__		
F3=Exit F4=Prompt			
05-10	82	MW	KS IM II KENB20A PET166S2

Fields:

Header Details

Date

This field defaults to the current system date, and a date must be in this field. You can enter another date for this booking if the current system date is not appropriate. All bookings made during this session are recorded against the date entered, unless amended at a later stage.

Shift

You can enter the shift number to which the booking relates. This provides a more precise time frame for recording booking if a start and finish time are not entered. For example if the booking has an elapsed time in 3 hours, this might be linked to shift 2 which runs 16:00 to 24:00. If entered this should be a shift number on the shift profile in force on the booking date at the work station at which the booking is made.

Work Station

You must enter a value in either the Work Station and/or the Dept field.

You can enter the work station against which the booking is to be made.

Dept

You must enter a value in either the Work Station and/or the Dept field.

You can enter the department against which the booking is to be made.

Departments are an analysis and (optionally) MRP planning tool and do not impose any constraints over WIP inventory, work station operator or crew bookings.

If a work station is entered but not a department, the system defaults to and displays the department assigned to the work station definition, if one exists, when **Enter** is pressed to validate header details.

If a work station is not entered, but a department is, booking details assumes the standard work station defined for the operation on the order route.

If a department is not entered, but the operator has been assigned a department via Operator Maintenance the system defaults to and displays the department when **Enter** is pressed to validate the header details.

Departments are user-defined and are entered on the system via the Maintain Parameters facility, against type DEPT.



Note: Departments can also be entered against a stockroom details record in Inventory Management. If Department (Cellular) MRP planning or Departmental Cost Analysis is to be used, it is important that Production and Inventory Management departments codes are consistent.

Work Order

You can enter the work order in this field.

Operation

You must enter an operation in this field.

Lot Number

You can enter the lot number in this field.



When **Enter** is pressed on the first Operator Booking screen, the second screen is displayed.

Operator Booking Screen 2

The reporting facilities for operator booking are similar to Production Order Bookings. As each booking is completed the details are displayed in the Booking Details window as in Production Order Booking.



When **Enter** is pressed on the first Operator Booking screen, the second screen is displayed.

The following fields and functions are displayed:

```

MG200                Z1 - GB Demonstration Company      User GBJBAMS      8/12/95
                                                           16:21:19

Operator Booking
Header details
Date..... 8/12/95 Shift ____
Work Station.? WSO1 Dept.? ____
Work Order...? W000191
Operation....? 10
Lot Number....
Booking Details
Activity.....? PRODRP Rev Ind 0
Operator.....? Cr.? ____
Time
Oper Elapsed. .00
W/S Elapsed. .00

Quantity
Good.. .000
Scrap. .000 Reason.? SC
Held.. .000 Reason.? QI
Op Complete. 0 Order Complete. 0
F3=Exit      F4=Prompt  F12=Previous  F13=Crew Details  F14=Component Details
F16=Outputs  F17=Scrap   F18=Hold    F19=Booking Details
12-18      SC      MW      KS      IM      II  KENB20A  PET166S2
  
```

Booking the Last Operation

Special consideration must be given to booking the last operation.



Warning: Booking the last operation on a route for a production order (or a schedule) means the item quantity booked as good (i.e. not scrap or held) is recorded against the finished goods stockroom that was defined for that item on its planned route (or the stockroom entered on the Outputs window if different)

This method of transfer is regarded as being the normal way of transferring completed items into inventory.

If this transfer is not required at the booking stage it is necessary to hold the items, which can then be released later as required.

When an operation is completed by making the booking, a window is displayed asking if you wish to consider the operation complete. If you press **Enter** to confirm, then the status of the operation is updated to completed and further bookings or material issues are prohibited for this operation.

If the booking completes the last operation, a window is displayed asking if the order is to be considered complete.

If you press **Enter** to confirm completion, the status of the order is updated to completed and no further bookings can be made.

Any order or operation which has had its status changed to complete can be reopened by using Order Completion.

Backflush Production Receipts

1... 2... 14/PCM

This task enables you to record the receipt of finished items and to backflush the equivalent input issues without using the control mechanism of a production order



Note: This option would not normally be used when production is controlled by production orders

The main aims of this task are:

- Receive quantities of finished items into Inventory Management.
- Backflush bulk issue components using a specified route.
- Calculate costs of receipts using standard routes and standard issues.



When Backflush Production Receipts is selected on the menu, the first Backflush Receipts screen is displayed.

Fields:

Item

Enter the parent item to be received into stock. This cannot be a process group item.



When **Enter** is pressed on the first Backflush Receipts screen, the second screen is displayed.

The following fields and functions are displayed:

PC020	Z1 - GB Demonstration Company	USER GBJBAMS	8/12/95 16:47:20
Backflush Receipts			
Item.....?..	MS001	Product A	
Quantity Received...			
UOM.....?..	EA		
Stockroom.....?..	FG		
Reference.....			
Transaction Type.?..			
Transaction Date....	8/12/95		
Backflush Route..?..	1		
F3=Exit F4=Prompt F12=Previous			
08-23	SP	MM	KS IM II KENB20A PET166S2

Fields:

Quantity Received

Enter the quantity of the finished item being received into Inventory. This is used in conjunction with the lot size, unit of measure, shrinkage and quantity per on the route entered to determine the quantities to be backflushed. A negative quantity may be entered to record and backflush an adjustment.

UOM

Unit Of Measure. Enter the units in which the quantity entered is expressed. The value initially displayed is the issue unit of measure in the stock room associated with the planning route of the item received, or the issue unit of measure in the primary stockroom. Any conversion necessary is performed to the unit of measure in the backflushing route stockroom for calculation of quantities.

Stockroom

The initial value is the stockroom held on the planning route for the primary stockroom held on the item master. It may be changed to any stockroom which is valid for this item for which a valid route exists.

Batch

This field is only displayed if the item received is lot controlled. An existing batch number may be entered or a new batch number may be specified via the Create New Batch field.

Create New

Enter 1 if the batch entered is a new one.

Reference

Batch Reference. Any reference you enter is recorded on all the Inventory movements for the finished item receipt and component issues.

Transaction Type

You may enter a transaction type for production purposes. The movement type recorded in Inventory Management is taken from the Inventory Processing Profile definition for the movement.

Transaction Date

Enter the date of the receipt. Each of the issues backflushed carries the same date and this is used to check the effectivity of inputs. The system defaults to the current system date.

Backflush Route

Enter the route to be used by the backflush process. This must be a route which is defined for the received item. The initial route displayed is the planning route for the item as defined on the manufacturing Item Master. If this does not exist, the transaction is disallowed unless a valid alternative route is entered.



Press **Enter** to validate the details, A warning is given if the result is negative stocks. Press **Enter** to update the transaction.

An audit report is produced listing the receipts made and, using backflush issues, the resulting costs This also lists the components which were not backflushed because they were not specified as bulk issue on the item master or are batch

controlled. It suggests an issue/adjustment quantity and recommends that a manual adjustment is performed.

Subcontractor WIP Shipper



15/PCM

Subcontract booking allows items to be sent (shipped) to the subcontractor as determined by the production route. The booking options also allow additional component/raw materials/ingredients to be sent to the subcontractor if they are specified for the subcontractor on the route. They are normally defined as backflushed items.

There are some important set-up considerations with regard to subcontract operations. These are fully discussed in Production Definition Management. When defining subcontract operations the following must be noted:

1. The subcontractor code must be valid in the Accounts Payable application. That is, he must be a valid supplier.
2. Define the subcontractor in the Purchase Management application, and add the item/supplier profile.
3. The subcontract operation must be a count point operation.
4. The operation before a subcontract operation must be a count point operation unless it is the first one on a route.
5. The Subcontractor Maintenance function is used to define both the operation and the operation before the subcontract operation itself. This is to allow WIP quantities booked on the previous operation to be available for shipment to the subcontractor. (Subcontract at the first operation does not require WIP shipment)
6. Subcontractor definitions may also be created for operations which are normally performed in-house.
7. A subcontract stockroom must be defined in the Organisational Model. It is used to record materials shipped to a subcontractor and to record materials consumed by the subcontract operation if defined on the route, but not WIP.

This screen allows the booking out of WIP inventory items which are to be sent to the subcontractor for a subcontract operation. This operation must be defined on the production route.



When Subcontractor WIP Shipper is selected on the menu, the Subcontractor WIP Shipper Entry screen is displayed.

Subcontractor WIP Shipper Entry Screen



When Subcontractor WIP Shipper is selected on the menu, the Subcontractor WIP Shipper Entry screen is displayed.

The following fields and functions are displayed:

MG230		Z1 - GB Demonstration Company		User GBJBAMS		8/12/95	
						16:36:26	
Subcontractor WIP Shipper Entry							
Shipper Header							
Date	8/12/95	Shift					
WIP Location.....?	FS						
Subcontractor.....?	ES01						
Shipper Number.....?							
Ship Via.....?							
Shipper Details							
Order.....?	W000191						
Operation.....?	10						
Lot Number.....?							
PO Number.....?							
PO Line Number...							
Quantity							
Shipped.....	2.000						
Due Date.....	12/01/96						
Rework Indicator.	0						
Reversal.....	0						
Shipper Details S Order Oper Lot Number Deleted 2=Amend 4=Delete F12=Previous							
F3=Exit F4=Prompt F8=Update F16=Order Stock Status F19=Shipper Details 07-23 SE MW KS IM II KENB20A PET166S2							

Fields:

Shift

Optionally, enter the shift from which the WIP item(s) is to be shipped. This provides a more precise time frame for recording the shipment on the stated date. Shift profiles are defined as part of the system set up procedures and may be specified uniquely for each work station.

WIP Location

This is the WIP inventory location balance which is to be updated when items are shipped. A WIP location may indicate a physical or a logical area of the shop floor, and it is defined in the Inventory Management application on the system as a stockroom and linked to work stations(s) in Production.

If a WIP location is not entered, following validation of all prompted details and pressing Enter, the system assumes and displays the default location associated with the operation.



Note: Several WIP locations may be valid if an operation of work is booked against non standard (route designated) work stations with dissimilar WIP locations

If a WIP Lot Tracking is active, and the balance at this location is not compatible with the shipment requested, that is, there is insufficient inventory recorded at the WIP location, an error message is displayed; F14 can be used to override.

Subcontractor

Enter the subcontractor to whom the inventory is to be shipped. The operation, route and subcontractor code must already have been defined to the system as a valid combination via the Subcontractors Maintenance program.

If no entry is made, the system selects and displays the first subcontractor defined for the item/route/operation when details are validated after pressing Enter

Shipper Number

This reference is required when the items are returned from the subcontractor. If Shipper Tracking is activated, then a shipper number is required. If no number is quoted at the time of booking, the system assigns a sequence number.

When shipper tracking is used, when recording receipts from the subcontractor, the relevant shipper number must be quoted, and this is used to validate the receipt against the WIP quantities shipped against that operation.

The last used shipper number is displayed on the Organisational Model.

The same number may be entered against a number of items, operations or orders, if multiple despatches of WIP materials to the same subcontractor are to be recorded on the same shipment, and printed on the same document (shipper note) when required.

Ship Via

If Purchase Management ship via codes have been set up, one may be chosen to indicate the method of transport, or the transporter, used to move the shipment.

Order

Enter the production order number against which the shipment is to be recorded. Once an order number and operation have been entered the F16=Order Stock Status option may be taken to review the WIP inventory balances at the operation; i.e. the WIP locations.

Operation

Enter the operation number prior to that defined as subcontracted for the item(s) being shipped; unless it is the first operation on the route when WIP shipment is not required.



Note: If the item(s) is to be reworked, then the actual subcontracted operation should be specified and the Rework Indicator set to 1. Note that a review of the stock status available via F16=Order Stock Status is not allowed until the Rework Indicator has been set to 1 (yes).

Lot Number

If WIP Lot Tracking is active, then the WIP lot to be shipped must exist. If not active, you may enter a lot number.

Po Number

If Purchase Management is live, then the shipment may be recorded against an active purchase order. Any number entered here is validated in Purchase Management.

Po Line Number

If a purchase order number has been entered, a valid line number on the order must also be quoted.

Quantity Shipped

Enter WIP quantity being shipped.

Due Date

Enter the date when completion and return from the subcontractor is expected. The due date is displayed on enquiries and printed on reports. Entry is optional.

Rework Indicator

If the item is being returned to the subcontractor because it is faulty or does not meet quality requirements but can be reworked, then this should be indicated by this flag.

0 - If the item is being shipped for the first time.

1 - If the item is to be reworked. The system checks that there is a sufficient held WIP quantity at the receiving operation to warrant the return. An error message is displayed if there is insufficient to ship.

Reversal

This field can be used to correct an error made in a previous shipment detail, or to book back items which were not used by the subcontractor.

0 - Standard booking.

1 - To make a reverse booking.



Warning: This option must not used to receive back completed WIP from the subcontractor; use Receive From Subcontractor for this.

Functions:

F16

Order Stock Status. Opens a window which shows the WIP Location Stock Status

F19

Shipper Details. Toggle key; to allow entry in either the main booking window entry screen or the shipper details window



Press **Enter** to validate and display the Shipper Details window and clear detail fields.



Select **F8** to confirm and update the booking.

Subcontractor Material Shipper



16/PCM

This screen allows the booking out of materials needed by the subcontractor. This material must be as defined on the production route at the subcontract operation.

This generates an increase in the stock of the material item in the Subcontractor stockroom defined in the Organisational Model and a decrease in the issuing stockroom.



When Subcontractor Material Shipper is selected on the menu, the Subcontractor Material Shipper/Return screen is displayed.

Subcontractor Material Shipper/Return Screen



When Subcontractor Material Shipper is selected on the menu, the Subcontractor Material Shipper/Return screen is displayed.

The following fields and functions are displayed:

PC250	Z1 - GB Demonstration Company	User GJBAMS	8/12/95 16:38:44
Subcontractor Material Shipper/Return			
Shipper Header			
Date <u>8/12/95</u> Shift			
Stockroom.....? ☐			
Org.Model.....?			
Subcontractor.....?			
Shipper Number....?			
Ship Via.....?			
Shipper Details			
Item.....?			
Lot Number.....?			
Quantity			
Shipped/Returned.			
Return Indicator. <u>0</u>			
F3=Exit F4=Prompt F8=Update F16=Item/Stockroom Enquiry			
F19=Shipper Details			
06-23 ☐ MW KS IM II KENB20A PET166S2			

Fields:

Date

The system defaults to the current system date.

Shift

Optionally, enter the shift during which the material(s) is to be shipped. This provides a more precise time frame for recording the shipment on the stated date. If entered, this should be a shift number on the shift profile in force on the shipment date at the work station defined to the subcontracted operation.

Org Model

Enter the live Organisational Model on which is defined the subcontractor stockroom to which materials are transferred.

Subcontractor

Enter the subcontractor to whom the materials are to be shipped. The entry is validated against the Purchase Ledger (Accounts Payable) list of suppliers (vendors).

Shipper Number

Each subcontractor or shipment can be referenced by a shipper number. If the Shipper Tracking flag on the Organisational Model is set, this is a mandatory field.

An Entry may be made manually, or generated by the system automatically when Enter is pressed. The last used number is updated and displayed on the company's Organisational Model.

The same number may be entered against a number of items if multiple despatches to the same subcontractor are to be recorded on the same shipment, and printed on the same document (shipper note) when required..

Ship Via

If Purchase Management ship via codes have been set up, one may be chosen to indicate the method of transport, or the transporter, used to move the shipment.

Item

Enter the material to be shipped. This must be a backflush type item, which must have a valid item/stockroom relationship with both the issuing and subcontractor stockroom.

Once an item and issuing stockroom have been entered, F16=Item/Stockroom Enquiry may be taken to review inventory at that stockroom.

Lot Number

If the material is lot controlled a valid lot reference must be entered. Any returns of material are validated against the lot shipped. (As well as the shipper number if Shipper Tracking used).

Quantity Shipped/Returned

Enter the quantity to be shipped to or back received from the subcontractor. Any receipt quantity should be equal to or less than that recorded as shipped to the subcontractor and requires the setting of the Return Indicator field to 1.

Return Indicator

Indicates whether the materials are being shipped to or from the subcontractor.

0 - To ship to subcontractor.

1 - To receive from the subcontractor.

Functions:

F16

Item/Stockroom Enquiry.

F19

Shipper Details.



Press **Enter** to validate and **F8** to confirm and update the booking.

Receive From Subcontractor



17/PCM

This screen allows the recording of WIP inventory which has been sent to the subcontractor, and worked on by the subcontractor.

The validation checks that the quantity received exists in the WIP location for the subcontractor at the previous operation. This causes a decrease in the WIP stock of the item shown as Subcontract at the prior operation WIP location and an increase in the WIP stock at the receiving operation. If this is the last operation, this generates a receipt into the finished goods stockroom designated on the route.



When Receive From Subcontractor is selected on the menu, the Subcontractor Order Receipts Entry screen is displayed.

Subcontractor Order Receipts Entry Screen



When Receive From Subcontractor is selected on the menu, the Subcontractor Order Receipts Entry screen is displayed.

The following fields and functions are displayed:

MG240	Z1 - GB Demonstration Company	User GBJBAMS	8/12/95 16:40:39															
Subcontractor Order Receipts Entry																		
Advice Note Header																		
Date 8/12/95 Shift █																		
WIP Location...? █																		
Subcontractor...? █																		
Advice Note..... █																		
Advice Note Details																		
Order.....? █																		
Operation.....? █																		
Lot Number.....? █																		
PO Number.....? █																		
PO Line Number.. █ Ship Close @																		
Shipper Number.? 00000000																		
Quantity																		
Good... █																		
Scrap.. █ Reason.? █																		
Held... █ Reason.? █																		
Op.Complete..... @ Order Complete.. @																		
<table border="0"> <tr> <td>F3=Exit</td> <td>F4=Prompt</td> <td>F8=Update</td> <td>F14=Input Details</td> <td>F16=Output Details</td> </tr> <tr> <td>F17=Scrap</td> <td>F18=Held</td> <td>F19=Receipt Details</td> <td></td> <td></td> </tr> <tr> <td>05-23</td> <td>82</td> <td>MW</td> <td>KS</td> <td>IM II KENB20A PET166S2</td> </tr> </table>				F3=Exit	F4=Prompt	F8=Update	F14=Input Details	F16=Output Details	F17=Scrap	F18=Held	F19=Receipt Details			05-23	82	MW	KS	IM II KENB20A PET166S2
F3=Exit	F4=Prompt	F8=Update	F14=Input Details	F16=Output Details														
F17=Scrap	F18=Held	F19=Receipt Details																
05-23	82	MW	KS	IM II KENB20A PET166S2														

Fields:

Date

The system defaults to the current system date.

Shift

Optionally, enter the shift during which the item was received. This provides a more precise time frame for recording the receipt on the stated date.

If entered, this should be a shift number on the shift profile in force on the shipment date at the work station defined to the subcontracted operation.

WIP Location

Enter the subcontract WIP location; this should be the location defined for the default work station entered on the order route for the subcontracted operation, not the prior operation from which inventory was originally shipped.

If the WIP location entered is different to standard a warning message is displayed and it may be necessary to transfer lots to the standard location before the next operation is booked if WIP Lot Tracking is in use.

Subcontractor

Enter the subcontractor supplying the items.

If Shipper Tracking is effective, then the quantity of an item received against a subcontractor/order/operation/shipper number must be equal to or less than that

shipped. An error message is displayed if a quantity in excess of that recorded as shipped is entered.

If no entry is made, but an order, operation, and shipper number is entered, the system defaults to and accepts the subcontractor entered at shipment time.

Advice Note

This is a free format, optional field which may be used to record the document number accompanying the received items, this would usually be an advise or despatch note. The number is printed on reports and displayed on enquiries to identify the receipt.

Order

Enter the production order number to which the receipt relates.

Once an order number and operation quantity have been entered the F14=Input Details and F16=Output Details options may be taken if you want to override standard input requirements, or standard outputs received.

Operation

Enter the sequence number of the subcontracted operation.

Lot Number

If the item WIP shipped was lot controlled, enter the lot number of the item WIP shipped now being received back.

Po Number

Enter the relevant purchase order number as quoted on the WIP shipment.

Po Line Number

If a purchase order number was entered, specify the line number on which the item appears.

Ship Close

This indicates whether this receipt is the last shipment to be recorded against the entered shipper number.

0 - If more receipts are expected

1 - If this booking completes the shipment from the subcontractor

Shipper Number

This reference must relate to that used when the WIP inventory was shipped to the subcontractor, and is now being received back. It is mandatory if Shipper Tracking is in use.

Quantity Good

Enter the quantity of items received in satisfactory status, which then became available at the next operation or for booking into finished goods stock if this is the last operation on the route.

Quantity Scrap

Enter any scrap quantity. This is added to the good quantity when determining input usage.

Quantity Held

Enter any held quantity. This is necessary if items are to be returned to the subcontractor for rework. If items are subsequently sent back to the subcontractor for rework, this held balance is reduced by the rework quantity so that on completion it can be received once more at a later date. If the held WIP Tracking flag on the Organisational Model is set to 1 (yes), once a held quantity has been entered the Held details screen must be accessed (**F18=Held**) to record alongside its reason code a tracking reference.

Held quantities can also be released by the Release WIP Inventory option in the Production Support module. Releasing held WIP makes it available for further operations or for booking into finished goods stockroom if this is at the last operation. Alternatively, held WIP can be scrapped by the Scrap Held Inventory option from the same module.

Op Complete

This flag should be set when all receipts relating to this operation on this order have been received. Enter 1 for complete or leave 0 if not complete

Order Complete

If the subcontracted operation is the final operation on the route, the order may be flagged as complete. Enter 1 for complete or leave 0 if not complete

Functions:

F14

Input Details. Displays the details of the input items for the operation.

F16

Output Details. Displays the details of the outputs received.

F17

Scrap. Allows scrapped quantities to be given reference(s) and reason code(s).

F18

Held. Allows held items to be referenced separately.

F19

Receipt Details. Toggle key to allow entry in either the main entry screen or the Receipt Details window.



Press **Enter** to display the Receipt Details window; and then **F8=Update** to confirm/update the booking.