

-
-
-
-
-

Chapter 3

Stock Counting



Processes Within Stock Counting



/STINS

While printing the stock count sheets, the computer stock figure is recorded. After the entry of the count the two figures are compared. The application does not prevent movements from taking place between the printing of the sheets and the entry of the count. It is therefore recommended that this time window is kept to a minimum.



Tip: It is sensible to count only a limited number of products at one time and to perform the count at a time of day when normal stock movement activity is at its lowest.

To assist in the identification of any movements that may have taken place, movement reports and enquiries are provided. These can display the full details of movements, including date, time and the resulting stock balance after the movement has taken place. Once a difference has been accepted as real, a manual or an automatic movement can take place to adjust the computer stock figure.

This section details the functions that are available as options within Inventory Stock Counting. The options are designed to allow a greater amount of control when working within stock counting procedures.

This section goes on to discuss the processes as they are listed within Stock Counting.

Count Profile Maintenance



1/STINS

This option allows you to set up profiles which control the range of items that you want to count and the time in which it is done.

Stock Count Profile Maintenance Screen 1



Stock Count Profile Maintenance Screen 1 is displayed when you select the Count Profile option.

It enables you to specify the stockroom you wish to make the stock count from.

```

IN106          ST - JBA System Test Company      User GBJBARW2      9/11/95
                                           9:16:36

Stock Count Profile Maintenance

Stockroom .....?.. 01

F3=Exit        F4=Prompt

05-27  Sf      MW      KS      IM      II  KENB20A  PET178S2

```

Fields:

Stockroom

The stockroom code must be defined to the Inventory company profile and it represents a discrete area of the company where stock needs to be recorded and controlled separately from other company stocks.



Press **Enter** to display the Stock Count Profile Maintenance Screen 2.

Stock Count Profile Maintenance Screen 2



This screen is displayed when you press **Enter** on the initial Count Profile maintenance screen.

It enables the entry of the counting criteria for Stockroom or warehouse.

INI06	ST - Style Distribution Company	User STYLEEDU	26/08/97 12:23:49
Stock Count Profile Maintenance			
Stockroom	FG	Studley Stores	
Last count number			
Overdue days	1		
Time fence days	1		
View quantity on count ..	0	0=No 1=Print 2=Panel 3=Both	
Count by class	0	0=No,1=Yes	
Tolerances:			
Percentage (-ve)			
Percentage (+ve)			
Value (-ve)			
Value (+ve)			
F3=Exit F8=Update F12=Previous			
8-27 SA MW KS CL IM DM II EDN400A KB PET310S1			

Fields:

Last Count Number

This is the Last Count Number used within the stockroom or warehouse.

Overdue Days

Overdue Days represents the number of days at which the counts become overdue for printing. This is based on the date of the count recommendation as entered at count request time.

Time Fence Days

Number of days per year together with the count objective enables the calculation of the next due count date for each item within the stockroom.

View Quantity On Count

View Quantity on Count defines whether the recorded or computer stock figures are visible to you after it has printed the count sheets.

Count By Class

This defines if Count by Class is allowed for the stockroom. If switched on (by entering 1 in this field) tolerances must be defined for each class.

Negative Percentage Tolerance

Maximum percentage tolerance for stock shortage

Positive Percentage Tolerance

Maximum percentage tolerance for stock excess. An excess greater than this tolerance is considered to be account error at reconciliation.



After you have entered or amended the details press **F8=Update** to validate the details and return you to the initial selection screen.

Count Profile Enquiry

1... **2/STINS**

This enables the enquiry of count processing criteria and item/stockroom ABC classification for an Inventory stockroom or warehouse.

Stock Count Profile Enquiry Screen 1

The Stockroom Select screen is displayed when you select the enquiry option in the same way as in the count profile maintenance function.

The stockroom is then selected in the same way using the initial screen .



Press **Enter** when you have entered a stockroom
to display the detail screen.

Stock Count Profile Enquiry Screen 2



This screen is displayed when you have selected a valid stockroom on the initial screen.

It provides a detailed break down of the stock count for the selected stockroom including negative/positive tolerances and count by class specifications if permissible within that particular stockroom.

IN106	ST - Style Distribution Company	User STYLEEDU	26/08/97 12:32:02
Stock Count Profile Maintenance			
Stockroom	FG	Studley Stores	
Last count number			
Overdue days	1		
Time fence days	1		
View quantity on count ..	0	0=No 1=Print 2=Panel 3=Both	
Count by class	0	0=No,1=Yes	
Tolerances:			
Percentage (-ve)			
Percentage (+ve)			
Value (-ve)		.00	
Value (+ve)		.00	
F3=Exit F8=Update F12=Previous			
8-27	SA	MW	KS CL IM DM II EDN400A KB PET310S1

Fields:

Last Count Number

This is the Last Count Number used within the stockroom or warehouse.

Overdue Days

Overdue Days represents the number of days at which the counts become overdue for printing. This is based on the date of the count recommendation as entered at count request time.

Time Fence Days

Number of days per year together with the count objective enables the calculation of the next due count date for each item within the stockroom.

View Quantity On Count

View Quantity on Count defines whether the recorded or computer stock figures are visible to you after it has printed the count sheets.

Count By Class

This defines if Count by Class is allowed for the stockroom. If switched on (by entering 1 in this field) tolerances must be defined for each class.

Negative Percentage Tolerance

Maximum percentage tolerance for stock shortage

Positive Percentage Tolerance

Maximum percentage tolerance for stock excess. an excess greater than this tolerance is considered to be account error at reconciliation.



Press **F8=Update** to update the details.

Regenerate ABC Classifications



11/STINS

This option reclassifies items within a stockroom based on their average usage and cost in relation to the stockroom cost/usage matrix. When reclassified the next count date for each item in the stockroom is recalculated based on the last count date and criteria defined for the stockroom count profile.

This option should be used to reassign classifications and the next count dates to items and may be necessary if a stockroom matrix or stockroom count profile has been changed. The option is prompted at period end processing within Inventory when average usage for stockroom/item profiles are recalculated.

You can view the ABC classification of items in the item/stockroom enquiry.



Tip: If Warehousing is installed the stockroom selected will be assumed to be the default warehouse.

You can view the ABC classification of items in the Item/Stockroom Enquiry.

ABC Recommendations



21/STINS

This option is used to allow the creation of counts based on the next due for count date defined for each item within the stockroom.

A count is produced for any item that is due for count before or on the count recommendation date entered on the screen.

Additional counts will be produced for each day after the date up to the number of days specified. These counts will contain items that are due on those days only. This provides a method of evaluating future work loads.

This function consists of the following two processing screens:

- Create Count by ABC Recommendation - Stockroom select.
- Create Count by ABC Recommendation - Details.



Note: Create Count by ABC Recommendation Stockroom select is carried out as described previously in Count Profile Maintenance.

Create Count By ABC Recommendation Detail Screen



Select the stockroom on the initial screen and press **Enter**, the detail screen is then displayed which prompts for the following information:

Fields:

Number Of Days

This field is used to define the number of days after the date of recommendation. This is reviewed separately for the count creation.

From ... Date

The date of recommendation is the date from which items are selected based on their next 'due for count date'.

Print Count Sheets

This field indicates whether count sheets should be printed immediately upon generation of recommendations. If selected for print the balance becomes outstanding immediately after generation and the option to review recommendations prior to print is bypassed.

Number Of Instructions Per List

This value is the maximum number of items or print location details that are to be printed on an action list.



Note: If Warehousing is attached, the value will default to the value that has been defined for the warehouse list profile for count lists.



Tip: After running this procedure it is possible that no counts are actually produced. This could be for one of the following two reasons:

- On the count profile you will have specified how often each item classification (A, B, or C) should be counted. If the number of counts per year field is set to count items relatively infrequently and all items have been recently counted, then no items may be due to be counted. Therefore no count recommendations will be produced.
- Items that are currently being counted cannot be included on other count lists, whether active or recommended. Hence any items appearing on manually requested count lists, at either a summary or detail level, will not appear on a count list created by ABC Recommendation.



Press **F8=Submit** to create the count.

Create Count By Manual Range



22/STINS

Counts can be created for one or more stockrooms, based on the item range selection or item attribute selection.

A single stockroom or range of stockrooms may be entered in addition to a single selection or range of one of the following item attributes as defined for the item:

- Item number.
- Item group (major / minor).
- Item type.
- Item class.
- Count Class (A,B,C or Z).

Create Count By Item Selection Screen



This screen is displayed when you select the Create Count by Item option.

It allows you to by select an item on which to base a stockcount.

IN120		ST - JBA System Test Company		User	GBJBARW2	9/11/95
						9:19:27
Create Count by Item Selection						
Selection criteria	Range from	Range to				
Stockroom?..	___	___				
AND						
Item?..	_____	_____				
OR						
Item group major/minor...?..	___	___	___			
OR						
Item type?..	___	___				
OR						
Item class?..	___	___				
OR						
Count class	___	___				
Count date	9/11/95					
Print count sheets	0	0=No,1=Yes	No of instructions/list....		0	
F3=Exit F4=Prompt F5=Refresh F8=Submit						
07-30	SP	MW	KS	IM	II	KENB20A PET178S2

Fields:

Stockroom

This is the stockroom code for the stockroom which contains the items selected for the count.

Item

This is the unique code used to identify the item - If a single item is selected it must exist on the master file. If you are entering a range of items, the from and to used to define the range do not have to be on the master file, (unless they are the same value).

Item Group Major

You have to enter a valid code as defined to the descriptions file against the major type PGMJ.

Item Group Minor

This is the item group minor as defined against the major type PGMN.

Item Type

This is the item type as defined against the major type PTYP.

Item Class

This is the item class as defined against the major type PCLS.

Count Class

This is the classification of items within a given stockroom by a combination of their usage and value. They are then categorised by this into classes A, B and C. Items which have the highest usage and value are generally classified as A. Class B receives less attention, while C class with the lowest usage and value receives the least attention.

Count Date

This is the date which is associated with this count recommendation.

Print Count Sheets

This field indicates whether the count should be printed immediately. If selected for print the count becomes outstanding immediately after generation and the option to review recommendations prior to print, is bypassed.

No. Of Instructions/List

When printing counting recommendations, this value is the maximum number of item or location details that are to be printed on an action list.



Note: If warehousing is attached then the value will default to the value defined for the warehouse List Profile for count lists.



Tip: A blank range selection for stockrooms will default to all stockrooms



Press **F8=Submit** to create the count.

Maintain Count Recommendations



31/STINS

Recommended counts can be reviewed prior to printing if the option to print count sheets was not taken when the count was requested.

Summary recommendations, i.e. a request to count all balances for an item can be added or deleted. In addition detail recommendations, (specific lots, batches or serial numbers) can be requested for count. Counts can be deleted in their entirety and all associated items taken 'off count'.

Any additions are considered 'unplanned' requests and an appropriate reason code must be entered.

This function involves four screens:

- Count Select.
- Details.
- Additions.
- Count warnings.

Maintain Count Screen 1



This screen is displayed when the Maintain Count option is selected.

It allows you to select the count number and stockroom for the count which is to be reviewed.

```

IN129A          ST - JBA System Test Company      User GBJBARW2      9/11/95
                                                    9:20:21

Maintain Count

Stockroom .....?.. 01

Count number .....?.. ____0

F3=Exit        F4=Prompt

07-32      SF      MW      KS      IM      II  KENB20A  PET178S2

```

Fields:

Stockroom

Enter a stockroom code.

Count Number

This is the count number which is to be reviewed. The count must be of recommended status, i.e. not outstanding. Counts are considered to be outstanding once the count sheet has been printed. A prompt is available.



*Note: You must **Enter** the stockroom code in order to prompt on the associated counts.*



Enter the stockroom code and the count (you can prompt on the count number). Press **Enter** to display the second maintain count screen.

Maintain Count Screen 2



This screen is displayed when you press **Enter** on the initial screen after having entered a count number and stockroom code.

It allows the addition and deletion of summary or detail item recommendations. The stockroom, count number and the number of items or lots to count are displayed at the top of the screen. Detail recommendations are a request to count specific lot, batch or serial numbers. Only counts of recommended status, i.e. not outstanding, may be reviewed.

IN129B		Z1 - Demonstration Company		User SP1	5/09/94 12:32:06
Maintain Count					
Stockroom		01	Item summaries to count		8
Count number		4	Item details to count		1
Create date/time		5/09/94 12:28:01	Item summaries cancelled		1
			More:		
Item	Lot	Reason			
- 5011		Planned Count			
- 5013	B002	Unplanned Request			
- 5014		Planned Count			
- 5015		Planned Count			
- 5016		Planned Count			
- 5017		Planned Count			
- 5018		Planned Count			
- 5019		Planned Count			
- 5020		Planned Count			
			Position to item ..		
4=Delete					
F3=Exit		F5=Refresh	F8=Update	F9=Add	F11=Delete
F12=Previous					

Fields:

Select

This field is untitled on screen.

Enter 4 to delete count recommendation for a particular line and select **F8=Update**. The count recommendation will no longer be included in the count and the application will immediately return to the count selection screen.

Position To Item

If the list extends over a single screen, enter the item reference number or the first few characters of an item in order to position the count list to the required point.

Functions:

F9

Add. The Addition window is displayed

F11

Delete.



To delete the entire count, press **F11** twice.



Warning: Summary recommendations must be deleted before a detail recommendation can be added for an item.



Warning: Lot controlled items are only shown at summary level. You can specify individual lots by pressing F9.



Press **F8** to update all item additions and deletions.



Note: If a count exists for a particular item at summary level, a detailed count recommendation cannot be generated for the same item, and vice versa.

Addition Window (F9)

This screen is displayed when you select **F9=Addition** on the Maintain Count Screen 2.

It enables you to specify individual lots to add to the count.

IN129B		Z1 - Demonstration Company		User SP1		5/09/94 12:31:54	
Maintain Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		0	
Create date/time		5/09/94 12:28:01		Item summaries cancelled		1	
				More:			
Item	Lot	Reason					
- 5011		Planned Count					
- 5014		Planned Count					
- 5015		Planned Count					
- 5016		Planned Count					
- 5017		Planned Count					
- 5018		P		Addition			
- 5019		P		Item?.. 5013			
- 5020		P		Lot?.. B002			
				Reason code ?.. UN			
				F4=Prompt F12=Previous			
				Position to item ..			
4=Delete		F3=Exit		F5=Refresh		F8=Update	
F12=Previous				F9=Add		F11=Delete	

Fields:

Item

Enter an item.

Lot

Enter a lot number where relevant.

Reason Code

The reason code must be a valid entry as defined to the descriptions file against the major type CTRE and must be of an unplanned nature i.e. the reserved code of #1 which represents a Planned request for an item originating from an initial count request cannot be used.



To delete the entire count, press **F11=Delete** twice.



Warning: Summary recommendations must be deleted before a detail recommendation can be added for an item.



Warning: Lot controlled items are only shown at summary level. You can specify individual lots by pressing F9=Add.



Press **F8=Update** to update all item additions and deletions.



Note: If a count exists for a particular item at summary level, a detailed count recommendation cannot be generated for the same item, and vice versa.

Count Size Warning Window



A screen is displayed as a warning on update for count request by ABC classification where the number of items specified for any of the classifications exceeds the maximum number of items per count sheet as maintained against the stockroom count profile.

This situation can arise where unplanned additions are made to the count.

IN129B	Z1 - Demonstration Company	User SP1	05/09/94 12:36:13
Maintain Count			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	Class
- 5011		Planned Count	B
- 5013	B002	Unplanned Request	B
- 5014			
- 5015			
- 5016			
- 5017			
- 5018			
- 5019			
- 5020			

Count Size Warning

Number of class A items in count	2
Maximum class A items specified	10
Number of class B items in count	6
Maximum class B items specified	5
Number of class C items in count	1
Maximum class C items specified	20

F12=Previous

4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous



Select **F12=Previous** to amend the current count.



Press **Enter** to accept the count with the excess items.

Enter Count Details



32/STINS

Counted details are entered on a list by list basis. Details can be added, changed or deleted until the list is recorded as complete. Lists can be deleted in their entirety and all associated items taken off count (unless item details span a number of lists). Item details can only be added if the item already exists as on count for this particular count. Any additions are considered Override details and an appropriate reason code must be entered. It is recommended that the list is not completed until the reconciled details have been reviewed, since, once recorded as complete, a list can no longer be maintained.



Select Enter Count Details from within Inventory Stock Counting.

Enter Count Screen 1

 This screen is displayed when you select the Enter Count option.

It enables you to select the stockroom and enter other details for the count.

IN133A Z1 - Demonstration Company User SP1 5/09/94
12:33:15

Enter Count
Stockroom?.. 01
Count number?.. 4
List number?.. _____

Select List Number
Central Warehouse
Count No..... 4
More:

S Number	S Number
1	4
-	5
-	6
-	7

1=Select
Position to...
F12=Previous

F3=Exit F4=Prompt

 Enter or prompt on the data required. (if you prompt on the count list number a select list number window is displayed.) Press **Enter**. The details screen is then displayed.

Enter Count Screen 2



This screen is displayed when you press **Enter** having selected a count number on the initial screen.

It enables you to enter or amend details for an item count.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:33:59	
Enter Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		1	
List number		4		Item summaries cancelled		1	
Create date/time		5/09/94 12:28:01		More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B002	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L001	#1	575.000	575.000			
I 5015	LP054	#1	159.000	.000			
- 5015	L002	#1	625.000	.000			
1=Select 2=Lot header 4=Delete				Position to item ..			
F3=Exit		F5=Refresh		F9=Add		F11=Delete	
F12=Previous							

Fields:

Select

This field is untitled on screen.

Enter 1 to select one or more lines for entering or amending detail item count quantities by entering a 1 against the required lines. When you press Enter, the Amendment window is displayed which shows current information available for amendment.

Enter 2 to display the lot header screen for a detail count line that appears on this enter count screen. See the Lot, Grade, Potency section for more details on the resulting window.

Enter 3 to delete. The third Enter Count screen is displayed.

Position To Item

Enter an item code to display a selected range of items.

Functions:

F9

Add. Item details can only be added if the item already exists as on count in this particular count. Typically, this is where different lots of an item are found that were not on the original count sheets. If the item is lot controlled, the Lot Reference

Maintenance window is automatically presented and must be completed. Additions are considered as overrides and a reason code must be entered.

Enter Count Screen 2 Amendment Window (Option 1)



This window is displayed when an item is selected on the second Enter Count screen.

The Amendment window displays current information available for amendment. You can enter the quantity directly into the column marked Entered Qty beside the appropriate item count line.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:33:59	
Enter Count							
Stockroom 01				Item summaries to count 8			
Count number 4				Item details to count 1			
List number 4				Item summaries cancelled 1			
Create date/time 5/09/94 12:28:01				More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B0 02	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L0 01						
- 5015	LP054						
- 5015	L0 02						

Amendment

Item 5015

Lot LP054

Reason #1

Recorded qty ... 159.000

Entered qty 160

F12=Previous

Position to item .. _____

1=Select 2=Lot header 4=Delete

F3=Exit F5=Refresh F8=Update F9=Add F11=Delete

F12=Previous

Enter Count Screen 2 Delete (Option 4)



This screen is displayed when an item is flagged for deletion on the second Enter Count screen.

IN133B		Distribution V3 -> V3 Financials		User GBJBAMV1	16/11/95
					15:43:59
Enter Count					
Stockroom	#P	Item summaries to count		1	
Count number	5	Item details to count		0	
List number	4	Item summaries cancelled		0	
Create date/time		23/10/95 14:59:42		More:	
Item	Lot	Reason	Recorded qty	Entered qty	
4 ROB		#1	25000.000	.000	
Position to item ..					
1=Select 2=Lot header 4=Delete					
F3=Exit		F5=Refresh		F8=Update	
F12=Previous		F9=Add		F11=Delete	
10-02		SA		MW KS IM II KENB20A PET129S1	

Fields:

Entered Quantity

Enter the counted quantity associated with the item record. The quantity must be entered in the issue unit of measure defined for the item within the stockroom.

Enter Count Screen 2 Addition Window (F9)

This screen is displayed when the **F9=Add** option is selected from the Enter Count Screen 2 Delete (Option 4) screen.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:34:11	
Enter Count							
Stockroom		01		Item summaries to count		8	
Count number		4		Item details to count		1	
List number		4		Item summaries cancelled		1	
Create date/time		5/09/94 12:28:01		More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B0 02	UN	719.000	.000			
- 5014	LP004	#1	138.000	138.000			
- 5014	L0 01			00			
- 5015	LP054			00			
- 5015	L0 02			00			

Addition

Item?.. 5013

Lot?.. B009

Reason code .?.. UN

Entered qty 325

F4=Prompt F12=Previous

Position to item ..

1=Select 2=Lot header 4=Delete
F3=Exit F5=Refresh F8=Update F9=Add F11=Delete
F12=Previous

Fields:

Item

Enter a valid item number, that is defined to the current stockroom and is already on count in this count.

Lot

Enter a valid lot, batch or serial number. This is only required if item is lot, batch or serial controlled.

Reason Code

Enter the reason code to be associated with the additional item details. The reason code must be a valid entry as defined to the descriptions file under major type CTRE and must be of an override nature. The reserved code of #1 which represents a Planned request for an item originating from an initial count request cannot be selected.

Quantity

Enter the counted quantity in the issue unit of measure defined for the item within the stockroom.

Press **Enter** to return the application to the details screen. The stock balance for the additional item will not have been calculated, and will not be displayed in the Recorded quantity column. The complete list may be deleted with **F11**, and all associated items taken off count (unless the item details span a number of lists).



Press **F8=Update** to update the list.



If no errors occur, the Update Confirmation window is displayed.

Update Confirmation Window

The Confirmation window is displayed if no errors occur when **F8=Update** is selected on the second Enter Count screen.

It allows you to confirm the list is completed.



All lists associated with a count must be completed before reconciliation with update can take place.

IN133B		Z1 - Demonstration Company		User SP1		5/09/94 12:36:16	
Enter Count							
Stockroom 01				Item summaries to count		8	
Count number 4				Item details to count		1	
List number 4				Item summaries cancelled		1	
Create date/time 5/09/94 12:28:01				More:			
Item	Lot	Reason	Recorded qty	Entered qty			
- 5011		#1	512.000	512.000			
- 5013	B002	UN	719.000	720.000			
- 5014	LP004	#1	138.000	.000			
- 5014	L001	#1	575.000	.000			
- 5015	LP054	#1	159.000	.000			
- 5015				.000			
- 5013				.000			
Update Confirmation							
Complete list ? 0					1=Yes 0=No		
F12=Previous							
1=Select 2=Lot header 4=Delete				Position to item ..			
F3=Exit		F5=Refresh		F8=Update		F9=Add	
F12=Previous						F11=Delete	

Fields:

Complete List

Indicates whether the list is to be considered complete. Once flagged as complete a list cannot be further maintained.



Note: It is recommended that a list is not completed until after reconciliation, as a completed list can no longer be maintained.

Complete Count Lists

1... **2...** 33/STINS

As an alternative to flagging lists as complete through the count entry option, all lists associated with a count can be completed en masse, after details have been entered and the results of reconciliation reviewed before the final update.

Lists cannot be complete if they contain detail records with lots referring to the special case of * Lot Error *. These lots are generated during the printing of count sheets if no lots exist for a batch, lot or serial controlled item.



Select the Complete Count Lists option to display the initial screen.

The screenshot shows the 33/STINS screen. At the top, it displays 'IN181A', 'Z1 - Demonstration Company', 'User SP1', and the date/time '5/09/94 12:38:07'. The main section is titled 'Count Completion' and contains two prompts: 'Stockroom?.. 01' and 'Count number?.. 4'. A window titled 'Select List Number' is open over the bottom right. This window shows 'Central Warehouse' and 'Count No..... 4'. It has two columns, 'S Number' and 'S Number', with values 1, 4, 5, 6, 7 listed. At the bottom of the window, it says '1=Select', 'Position to....', and 'F3=Exit F8=Update F12=Previous'. At the bottom of the main screen, it says 'F3=Exit' and 'F4=Prompt'.

Fields:

Stockroom

Enter a stockroom code.

Count Number

Enter a count number.



If you prompt on the count number using **F4=Prompt**, a selection window will be displayed.

Select

This field is titled S on the window.

Enter 1 against a count number to select it.



Press **F8=Update** to update the details.

Print Count Sheets



41/STINS

Once the count recommendations have been reviewed the stock count sheets can be printed. This is the point at which computer stock figures are recorded and recommendations are expanded.

If a lot, batch or serial controlled item has no recorded lots, a record will be added to the count with a lot reference of *Lot error*.

The method of printing the count sheet is purely a case of selecting the stockroom and count number required. (The F4 prompt facility is available on both fields.)



Note: A blank range selection of counts will default to all recommended counts for the stockroom you have entered.

There is also a facility to reprint count sheets if required.

Reprint Count Sheets



42/STINS

This facility provides for the reprinting of count sheets. All lists for a count can be reprinted or specific lists can be selected.



Select the Reprint Count Sheets option. The Reprint screen is then displayed.

Fields:

Stockroom

Enter the stockroom code.

Count Number From/To

If a single count is entered, it must be valid and in an outstanding status. If a range is entered, these need not be valid, but may act as limiters. If left blank, all recommendations are included.

List Number From/To

If a range is entered, these need not be valid, but may act as limiters. If left blank, all recommendations are included.

As well as count numbers, enter action list numbers.

List numbers must be valid and of incomplete or outstanding status, if a single number is entered. Otherwise, the From/To numbers may be used as range limiters.



Press **F8=Submit** to action the batch job.

Count Reconciliation

Reconciliation is the comparison of counted stock quantities with recorded computer stock quantities in order to assess any stock count errors.

Stock errors are assessed as both percentage quantity variance and a value variance basis as defined by the tolerances specified for the stockroom count profile. This process is split into two functions:

- With update.
- Without update.

Both functions are initially accessed by the same basic screen requesting stockroom and count number. When these details have been entered the with or without update screen is displayed depending on which one you have requested.

Reconciliation (without update) can be restricted to 'complete' lists within the count, or can additionally include 'open' lists that are still available for modification.

You can print full detail or summary information by item, with selection by item range. Any detail or item summaries that are considered to be in error are flagged with an '*' at the right hand side of the report. If an item summary is found to be in error but no errors have occurred for the detail lines, the summary is flagged for attention with a '**'. This situation normally arises due to a small number of variances (positive or negative) which in total constitute an error.

Reconciliation Without Update



51/STINS



Select the Reconciliation Without Update option to display the initial screen. Key in a stockroom code and count number, then press **Enter** to display the detail screen.

```

IN136B          ST - JBA System Test Company      User GBJBARW2      9/11/95
                                                    9:22:29
Request Count Reconciliation (without update)

Stockroom..... 01   Leeds Warehouse

Count number.....      2

Count lists..... 2    1=Completed 2=All
Report content..... 1  1=Detail 2=Summary
Print movements..... 1  0=No,1=Yes

Items to be included.... 2  0=None 1=Variance 2=All

Range of items:
  From.....?..      To.....?..

F3=Exit      F4=Prompt      F8=Submit      F12=Previous
09-27      SF      MW      KS      IM      II KENB20A PET178S2
  
```

Fields:

Count Lists

The following entries are valid:

- 1 - Completed. Only completed lists will be included on the report.
- 2 - All. Both open and completed lists will be included on the report.

Report Content

The following entries are valid:

- 1 - Detail, Item detail, i.e. lots, batches and serial numbers will be included on the report.
- 2 - Summary. Only item totals will be included on the report.

Print Movements

Enter 1 to print the movements: counted quantity, value of the count and recorded quantity of items. The items printed on the report will depend on the entry in the field Items to be included. Otherwise enter 0.

Items To Be Included

The valid entries for this field are:

0= None

No details will be included on the report.

1 - Variance. Only those details with either a quantity or value variance will be included on the report.

2 - All. All detail regardless of variance will be included on the report.

Range Of Items From..To..

Enter the valid item reference number required. If a single item is selected it must exist on the item master file. However, if entering a range, the 'from' and 'to' items which are used to define the range need not exist on the item master file except when they are the same value.

If the to item is left blank, it will default to the 'from' item.

Range restriction of the report can be used to investigate specific item discrepancies.



Note: A blank range selection for items will default to all items on the count.



Press **F8=Submit** to submit the details for processing.

Reconciliation With Update



52/STINS



Select the Reconciliation With Update to display this screen.



Note: If an item is Lot/batch controlled, then any discrepancies will be reported, but no stock adjustment will be carried out. The required stock adjustments must be carried out manually.

Fields:

Report Content

The following entries are valid:

- 1 - Detail. Item detail, i.e. lots, batches and serial numbers will be included on the report.
- 2 - Summary. Only item totals will be included on the report.

Print Movements

- 0 - No. No movements will be printed.
- 1 - Yes. Movements will be printed for all items that are in error.

Items To Be Included

The following entries are valid:

- 0 - None. No details will be included on the report.
- 1 - Variance. Only those details with either a quantity or value variance will be included on the report.
- 2 - All. All detail regardless of variance will be included on the report.

Generate Adjustments

The following entries are valid:

- 0 - None. No adjustments to stock figures will be made.
- 1 - All. All quantity variances regardless of size will be adjusted within inventory.
- 2 - Outside tolerances. Only those variances which are flagged as errors (i.e. with `*') will be adjusted within Inventory.

Reason Code

A movement reason must be entered if adjustments are requested. Reason codes are defined to the descriptions file against the major type MOVR.



Press **F8=Submit** to submit the details for processing.

The following count history updates are performed if count reconciliation is requested with update:

Item Count History

1 - Count by Class

The number of recommended counts is incremented if the item was a planned summary recommendation.

The number of unplanned counts is incremented if the item was an unplanned recommendation, i.e. originating from an addition via recommendations maintenance.

2 - Count by Manual Range

Number of unplanned counts is incremented.

Stockroom Count History

1 - Count By Class

Numbers of A, B and C items counted are incremented for all items that were planned via summary recommendations. In addition the numbers of A, B and C items that are in error are incremented for all items in error that were planned summary recommendations.

2 - Count By Manual Range

Number of other counts is incremented. In addition the numbers of other counts that are in error are incremented if any of the items on those counts are in error.

If Warehousing is installed and count by Warehouse location was selected, other updates associated with these counts are performed. For a full explanation, see the Stock Counting section within the Warehousing application.

Recommended Counts Enquiry



61/STINS



Select the Recommended Counts Enquiry option to provide a view-only facility of the Maintain Count details which, therefore, does allow any maintenance operations to be carried out.

Outstanding Counts Enquiry



62/STINS

This facilitates the enquiry of outstanding counts for a stockroom. Open or complete lists can be reviewed for a count.



Select the Outstanding Counts option to display the Count Details Enquiry Screen.

Count Details Enquiry Screen

This screen enables you to specify the stockroom location, the count number and the list number from which you wish to make your count details enquiry.

IN146A	Z1 - Demonstration Company	User SP1	5/09/94 12:36:35
Count Details Enquiry			
Stockroom?.. <u>01</u>			
Count number?.. <u>4</u>			
List number?.. <u>4</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Count Number

Enter a count number.

List Number

Enter a list number.



Press **Enter** to display the detail screen.

Count Enquiry Screen



This screen is displayed when you press **Enter** having selected the criteria for the count on the initial screen.

It provides a detailed count analysis.

IN142B	Z1 - Demonstration Company	User SP1	5/09/94 12:32:37
Count Enquiry			
Stockroom	01	Item summaries to count	8
Count number	4	Item details to count	1
Create date/time	5/09/94 12:28:01	Item summaries cancelled	1
		More:	
Item	Lot	Reason	
5011		Planned Count	
5013	B002	Unplanned Request	
5014		Planned Count	
5015		Planned Count	
5016		Planned Count	
5017		Planned Count	
5018		Planned Count	
5019		Planned Count	
5020		Planned Count	
			Position to item .. _____
F3=Exit		F12=Previous	

Fields:

Position To Item

Enter an item code to commence the display.

Item Count Summary Enquiry



63/STINS

This function allows you to look at yearly summary count information by item, i.e. the number and type of counts carried out to date, with dates of the last count and the next count due.



Select the Item Count Summary option to display the initial screen.

Item Count Summary Enquiry Screen 1

This screen provides an item count summary enquiry for specified stockrooms and selected items.

IN174A	Z1 - Demonstration Company	User SP1	5/09/94 12:37:51
Item Count Summary Enquiry			
Stockroom?.. <u>01</u>			
Item?.. <u>5013</u>			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter a stockroom code.

Item

Optionally, enter an item code to display count details for that item only. The field can be left blank to display all item summaries associated with the specified stockroom.



Note: If you enter a stockroom and leave the item field blank, the screen is displayed which shows summary count information for all items in the specified stockroom.

Item Count Summary Enquiry Screen 2



This screen is displayed when you press **Enter** on the initial screen.

It lists count details for selected items in a specified stockroom.

IN174C		Z1 - Demonstration Company		User SP1		21/09/94 9:48:03	
Item Count Summary Enquiry							
Stockroom 01 Central Stockroom							
Item	Year	Counts recommended	Counts unplanned	Last count date	time	Next count date	time
- 5001	94	0	0	11/08/94		17/12/94	
- 5002	94	0	0	11/08/94		17/12/94	
- 5003	94	1	0	16/08/94		22/12/94	
- 5004	94	0	1	5/09/94		12/01/95	
- 5005	94	0	0	11/08/94		17/12/94	
- 5006	94	1	0	16/08/94		22/12/94	
- 5007	94	1	0	16/08/94		22/12/94	
- 5008	94	0	0	11/08/94		17/12/94	
- 5009	94	0	0	11/08/94		17/12/94	
- 5010	94	0	0	11/08/94		17/12/94	
- 5011	94	0	0	11/08/94		17/12/94	
- 5012	94	0	2	5/09/94		12/01/95	
Position to item							
F3=Exit		F12=Previous					

Fields:

Select

This field is untitled on screen.

Enter 1 against a line to display count details for that item

Position To Item

If the list extends over a single screen, enter the item reference number or the first few characters of an item in order to reposition the count list.

Item Count Summary Enquiry Screen 3



This screen is displayed when you press **Enter** on the second screen.

The item and stockroom (selected on the second screen) are displayed at the top of the this (summary) screen. These are immediately followed by the year and the dates/times (details of the time may not be stored) of the last and next counts.

IN174B	Z1 - Demonstration Company	User SP1	5/09/94 12:37:56
Item Count Summary Enquiry			
Stockroom	01	Central Stockroom	
Item	5013		
Year	94		
Date/time of last count	5/09/94	0:00:00	
Date/time of next count	12/01/95	0:00:00	
Recommended counts	0		
Unplanned counts	2		
Negative stock counts	0		
Low stock counts	0		
Zero stock counts	0		
Transaction frequency counts	0		
F3=Exit F12=Previous			

Fields:

Recommended Counts

The number of counts recommended by the application that have been carried out this year.

Unplanned Counts

The number of unplanned, or manually requested, counts that have been carried out this year.



Note: Low Stock Counts, Zero Stock Counts, Transaction Frequency Counts are currently unsupported count methodologies, which will be provided for recommending counts in the future.

Count History Enquiry



64/STINS

This function allows you to see stockroom summary count information by period. Counts are only included in this enquiry once a reconciliation with update has been run, even if no stock adjustments were actually generated.

At summary level the total number of counts is displayed, with information on the number of each ABC classified item counted with the number of items in error.

The number of other counts (those where the range is selected manually) and other counts in error are displayed only at a detail level on an individual period basis.



Select Count History from within Inventory Stock Counting to display the initial screen.

Count History Enquiry Screen 1



This screen is displayed when you select the Count History Enquiry option.

It enables you to enter the stockroom and period for the enquiry details you require.

IN177A	Z1 - Demonstration Company	User SP1	5/09/94 12:39:06
Count History Enquiry			
Stockroom?.. <u>01</u>			
Period ____			
F3=Exit F4=Prompt			

Fields:

Stockroom

Enter the stockroom code for which count summaries are to be reviewed.

Period

Enter the week or period to be reviewed. The entry must be in the following format and in the same units as the usage cycle:

- YYMM If usage cycle is Monthly.
- YYWW If usage cycle is Weekly.

Where YY is the current year, MM is the current period and WW is the current week.

The usage cycle is defined to the Inventory company profile maintenance.

The period field can be left blank to display all period summaries associated with stockroom. Summaries are displayed in descending period sequence by year.



Enter the details and press **Enter** to display the second Count History Enquiry screen.

Count History Enquiry Screen 2

 This is displayed when you press **Enter** on the initial Count History Enquiry Screen.

It displays detailed stockroom enquiry information broken down into class type categories.

IN177C	Z1 - Demonstration Company	User SP1	5/09/94 12:39:09
Count History Enquiry			
Stockroom 01 Central Stockroom			
Period	Counts	Class A counts	Class B counts
Class C counts	Count A errors	Class B errors	Class C errors
_ 08	2	0	0
		0	0
		0	0
Position to ____			
F3=Exit		F12=Previous	

Fields:

Select

This field is untitled on screen.

Enter 1 against a period to display more detailed count history. The third Count History Enquiry screen is displayed.

Position To

If the summary count history extends over more than a single screen then enter the required period in the position to field to position the list at the selected period. The entry is required in YYMM or YYWW format, in accordance with the usage cycle. (See the company profile- usage profile section).

 Enter a 1 against the count to display the third Count History screen.

Count History Enquiry Screen 3 (Option 1)



This screen is displayed when you enter a 1 against the count number on the second Count History Enquiry screen.

The screen shows summary period information for the stockroom , including the number of ABC classified items counted and the number of items with errors.

IN177B	Z1 - Demonstration Company	User SP1	5/09/94 12:44:20
Count History Enquiry			
Stockroom 01 Central Stockroom			
Period 9408			
Number of counts 3			
Number of class A items counted ... 0			
Number of class B items counted ... 0			
Number of class C items counted ... 0			
Number of class A item errors 0			
Number of class B item errors 0			
Number of class C item errors 0			
Number of other counts 3			
Number of other count errors 1			
F3=Exit F12=Previous			