

-
-
-
-
-

Chapter 1

Auto Day Routines



Auto Day Start Jobs

Use this function to create and maintain those tasks which are part of the daily system start up activities, that is those tasks you want to perform after the IPL.

```

MNGADSJOB                                     Machine Manager                               System: STUDB30A
Manage Auto Day-Start Jobs

Type options, press Enter
1=Select, 2=Override, 3=No override

  0  Segn Job name      Days      Last      Duration  St Description
    - 0010          1111111 240691    0:00:00  SS Start Subsystem QINTER
    - 0020          1111111 240691    0:00:00  SS Start Subsystem QBATCH
    - 0025          1111111 240691    0:00:00  SS Start Subsystem QPGMR
    - 0030          1111111 240691    0:00:00  SS Start Subsystem QSPL
    - 0035          1111111 240691    0:00:00  SS Start Subsystem QCMN
    - 0040          1111111 240691    0:00:00  SS Start Subsystem QSNADS
    - 0050          1111111 240691    0:00:00  SS Start Spool Distributor
    - 0061          0000000 280391    0:00:00  RF Temp - Hold T_STUDB30A
    - 5001          0000000 000000    0:00:00  RM Clear out temporary dat
    - 9900          1111111 240691    0:00:00  SS ENDDAY initiation
    - 9999          1111111 240691    0:00:00  SS Delete ADS overrides
                                     Bottom

Jobs in high intensity are due to run tomorrow.
RUNADSJOB last executed by QSTRUPJD QPGMR 021506 24/06/91 19:15:13
F3=Exit F5=Refresh F8=Add

```



Note: Jobs which are scheduled to run as part of the next day start are highlighted.

Fields:

Option

1 - Select a task for maintenance. If you want to maintain many tasks then select the ones you require, the system pages through the tasks you have selected. Maintaining Auto Day-Start Jobs describes the maintenance of Auto Day-Start Jobs.

2 - Force the task to run as part of the next day-start. This override is reset if the Delete ADS (Auto Day-Start) Overrides task is made the last Auto Day-Start Job.

3 - Prevent the task from running as part of the next day-start. This override is reset if the Delete ADS Overrides task is made the last Auto Day-Start Job.



Note: A standard job is available to delete your auto day-start overrides, see the Standard Jobs section for more details about standard jobs.



Note: In the Ovr field 1 indicates the task is run as part of the next day start. 0 indicates that the task is not run as part of the next day start.



Select **F8=Update** to add a new task.

Manage Auto Day-Start Jobs



Select **F8=Update** from the Manage Auto Day-Start Jobs screen to display this screen. Enter the sequence number to be allocated, this must be a new number. Then Press **Enter** to display the Manage Auto Day-Start Jobs Screen.

```

MNGADSJOB          Machine Manager          System: STUDB30A
Manage Auto Day-Start Jobs

Sequence . . . 9090 Addition _____
Job name . . . _____ Blank for job to be run rather than submitted.

Request data. . _____
_____
_____

Day mask . . . 111111 SMTWTFSS Enter 1=Run, 0=No run for each day
Override . . . 1=Force run tomorrow, 0=Force no run
Scheduled time 99:99:99 999999 to run at day start
Schedule group _____
Last submitted . 000000
Last run started 000000 Job status . RN Never Run

F3=Exit   F4=Browse   F5=Refresh   F10=Standard jobs   F12=Previous
F18=Update with errors   F24=Application Mgr jobs
  
```

Fields:

Desc

The textual description associated with the job. This is a mandatory entry.

Job Name

The Job Name if the job is to be submitted.



*Note: If the job you want to run has been defined as an Application Manager job (via **F24**) leave the job name blank. The job is submitted and the job name taken from the Application Manager task details.*

Request Data

Specify a valid command which the job is to execute. For example:

STRSBS SBSD(QINTER)

This starts subsystem QINTER. (This is provided as a standard job. See the Standard Jobs section).



*Note: Select **F4=Prompt** to either prompt on an entered command or display the Standard IBM Major Command Groups menu so you can select*

any standard IBM command.



*Note: You can use **F10=Standard Jobs**, and **F24=Application Manager Jobs** to provide a fast method of completing the screen.*

Day Mask

A day mask indicating on which day(s) you want the job to be executed. 1 indicates that the job should be performed and 0 that it should not.

Override

Enter 1 to force the job to be run tonight, 0 to prevent the job from running.



Note: The Delete Auto Day-Start Overrides command resets the overrides. A standard job is supplied with Machine Manager so you can set up the delete overrides task. See the Standard Jobs section.

Scheduled Time

The time defaults to 99:99:99 so it runs as part of the Day-Start Jobs using the sequence number to determine when the job should be run.

If a specific time is entered then the execution of the job is controlled by the Job Scheduling programs, see the section on Job Schedules.

Schedule Group

Specify the date you want the job to run on. The dates are maintained via Group Schedules (see the Group Schedules section). Enter the name of the schedule group you want to associate with this job.



Note: For each job you may enter either a schedule group or a day mask.

Functions:

F10

List the standard jobs which you may want to run. Select one of the jobs will automatically complete all the relevant fields on the screen. These standard jobs are described in the section Standard Jobs.

F18

If the command you have entered does not exist in the current library list, but will be in the library list at the time of execution, then the command can be accepted by selecting **F18**.

F24

Run an Application Manager job as part of your Day-Start Jobs. See the section Application Manager Jobs.



Press **Enter**.

Maintaining Existing Auto Day Start Jobs

The process of maintaining an existing job is essentially the same as Adding a New Job described above. The only difference being that the following function keys are made available when maintaining a job:

Fields:

F13

Each time the Auto Day-Start Job is run an entry is made on a history log. **F13** clears this log. See the section Machine Management Log.

F16

Execute the job now. A screen enables you to change the parameters of the job for this run. Select **F16** again to confirm that you want to execute the job.

F17

This uses the IBM command WRKJOB - Work with Job to display information about the job from its last execution.



Note: If the job has completed and is no longer in the system then there will be no details to display.

Application Manager Jobs (F24)



If you select **F24=Application Mgr Jobs** to set up an Application Manager Job as part of your Day-Start or Day-End routines the Select Application Manager Task to Run Screen is displayed.

XA525 Application Manager System: STUDB3.0A

Select Application Manager Task to Run

Application ID . . . ____
Environment . . . ____
Release . . . ____
Task code . . . ____

Company code . . . ____
User name . . . ____

F3=Exit F4=Browse

Fields:

Application ID

A two character code which is used to identify applications. For example, Inventory Management uses the code IN.

Environment

A three character code which enables you to have many environments for each application. For example, TST may be used to describe a Test environment.

Release

A two character code which identifies the release level of the application. For example Version 2 of Inventory Management will have a Release code of 02.



Note: Application ID, Environment, and Release together for the identity to each unique application. For further details see Maintain Applications.



Note: This function does not support tasks that are IPG/400 function lists. Function lists are designed to be run interactively and thus are not suited to scheduling.

Task Code

A numeric code to identify a task to run within the specified application. For further details see Maintain Tasks.

Company Code

A two character code to identify which company the task should run for.



Note: If you want to run the same task for many companies you would need to set up many jobs each one identifying a different company.

User Name

A user who is identified to Administration Functions needs to be identified to determine the appropriate job and output queue overrides. For further details see Maintain User Profiles.

If the application task you have selected requires selection parameters then the selection screens automatically display for your selection criteria. The Product Guide for the application you have selected will contain full details of the required parameters. You should complete the screen by entering the selection criteria you require.



Note: If the task you have selected is interactive then Machine Manager will not process it.

For example, the screen below is displayed if you have selected to run the task List Supplier Names & Addresses from Accounts Payable.

PL021	Multi-Currency Company	USER BRIGHTN	5/07/91 17:17:17
-------	------------------------	--------------	---------------------

List Supplier Names & Addresses

ALL Addresses in ACCOUNT CODE sequence 1 Please enter '1' against ONE
Select a RANGE of ACCOUNT CODES - report type only.

Sequenced by content of SUPPLIER GROUP 1 -
Sequenced by content of SUPPLIER GROUP 2 -
Sequenced by content of SUPPLIER GROUP 3 -
Sequenced by content of SUPPLIER GROUP 4 -
Sequenced by content of ALPHA SEQUENCE CODE.: -

Enter a '1' here to obtain ALL details on the Report
Otherwise a summary report will be printed (one line per supplier).

F3=Exit (no print).

Standard Jobs (F10)



Select F10=Standard Jobs.

Machine Manager is shipped with a number of default routines and a Standard Jobs facility. This facility enables you to select a day-start or day-end job from a window screen, and as a result of selecting a standard job all of the required parameters for the job are automatically completed.

MNGADEJOB Machine Manager System: STUDB30A

Manage Auto Day-End Jobs

Sequence . . . 9090 Addition _____

Job name . . . Blank for job to be run rather than submitted.

Request data. . .

Day mask . . . 1

Override . . . 9

Scheduled time 9

Schedule group

Last submitted .

Last run started

F3=Exit F4=Bro
F10=Update with e F12=Previous

Select Auto Day-End Jobs

Type option, press ENTER

1=Select Job

Position list to. . .

Opt	Module	Job description
-	AM	Application Manager Day End
-	HK	Housekeeping Save Libraries
-	HK	Housekeeping Save Folders
-	HK	Housekeeping Save Groups
-	HK	Housekeeping Size Libraries
-	HK	Housekeeping Re-organise Files
-	HK	Housekeeping Compress Libraries
-	HK	Housekeeping Delete Unknown Libraries
-	MM	Clear Unprotected Output Queues
-	MM	Clear Unprotected Message Queues

More..

Fields:

Opt

Enter 1 alongside the job you want to run.

The screen displays details of the System Manager module which the job belongs to and its description.

The jobs supplied as standard jobs are those which the majority of IBM AS/400 installations would want to use to manage and control their processor. The sections Standard Day-Start Jobs and Standard Day-End Jobs provide a summary of the standard jobs supplied.

Auto Day End Jobs

This function enables the creation and maintenance of those tasks which are part of the daily system day end activities, that is those tasks you want to perform before the system power down.

MNGADEJOB Machine Manager System: STUDB30A									
Manage Auto Day-End Jobs									
Type options, press Enter 1=Select, 2=Override, 3=No override									
0	Seqn	Job name	Days	SMTWTFSS	Override	Last Run	Duration	St	Description
-	0100		11111111			240691	0:00:00	SS	Clear Unprotected Outqs
-	0200		00000000			000000	0:00:00	RM	Application Manager Day
-	0510		11111111			240691	0:00:00	SS	End Networker Spool Fil
-	1005	HK_RGZFILE	00000001			240691	0:15:01	RS	Housekeeping Re-organis
-	1010	HK_COMPLIB	00000001		0	240691	0:03:42	RS	Housekeeping Compress L
-	1020	HK_SAVLIB	11111100			240691	0:11:41	RS	Housekeeping Saves to S
-	1030	HK_FLRSV	00000000			260291	0:00:00	RF	Housekeeping Folder Sav
-	1040	HK_SAVGRP	00000000			000000	0:00:00	SS	Housekeeping Save Group
-	1050	HK_SIZELIB	00000010			140691	1:16:00	RS	Housekeeping Size Libra
-	6010		00000010			140691	0:00:00	SS	Delete Log History
-	8001		00000001			240691	0:00:00	SS	Clear Network Log
More..									
Jobs in high intensity are due to run tonight.									
RUNADEJOB last executed by JOBSCH QPGMR 021508 24/06/91 20:06:08									
F3=Exit F5=Refresh F8=Add									



Note: Jobs which are scheduled to run as part of the next day end are highlighted.

Fields:

Option

1 - Select a task for maintenance. If you want to maintain many tasks then select the ones you require, the system will page through the tasks you have selected. The section Maintaining Auto Day-End Jobs describes the maintenance of Auto Day-End Jobs.

2 - Force the task(s) to run as part of the next day-end. This override will be reset if the Delete ADE (Auto Day-End) Overrides task is made the last Auto Day-End Job.

3 - Prevent the task(s) from running as part of the next day-end. This override will be reset if the Delete ADE Overrides task is made the last Auto Day-End Job.



Note: A standard job (see the Standard Jobs section) is available to delete your Auto Day-End overrides.

Seqn

The sequence number of the task determines the order in which tasks are executed.

Job Name

The job name if the task is to be submitted for batch processing.

Day

A day mask indicating which day(s) the task will be executed.

Ovr

Task overrides. A 1 indicates that the task will be run as part of the next day end.
A 0 indicates that the task will not be run as part of the next day end.

Last Run

The date when the task was last executed.

Duration

The time taken to complete the task the last time it was executed.

St

The completion status of the task last time it was executed. Status codes are:

RS - Ran successfully

RN - Never run

RF - Run failed

SS - Submitted successfully

Description

The textual description associated with the task.



Press **F8=Update** to add a new task.

Adding A New Auto Day End Job (F8)

-  Select **F8=Update** from the Manage Auto Day-End Jobs screen. Enter a new sequence number to allocate. Press **Enter** to see the next screen.

MNGADEJOB
Machine Manager
System: STUDB30A

Manage Auto Day-End Jobs

Sequence . . . **9090** Addition _____

Job name . . . _____ Blank for job to be run rather than submitted.

Request data. . . _____

Day mask . . . **111111** SMTWTFSS Enter 1=Run, 0=No run for each day

Override . . . _____ 1=Force run tonight, 0=Force no run

Scheduled time **99:99:99** 999999 to run at day end

Schedule group _____

Last submitted . 000000

Last run started 000000 Job status . RN Never Run

F3=Exit F4=Browse F5=Refresh F10=Standard jobs F12=Previous

F18=Update with errors F24=Application Mgr jobs

Fields:

Desc

The textual description associated with the job. This is a mandatory entry.

Job Name

The Job Name if the job is to be submitted.



*Note: If the job is defined as an Application Manager job (via **F24**), leave the job name blank. The job is submitted and the job name defaults from the Application Manager task details.*

Request Data

Specify a valid command which the job is to execute. For example:

CLRUNPOUTQ

This job clears out unprotected output queues.



*Note: Select **F4=Prompt** to prompt on a command or, if you have not entered a command, this displays the Standard IBM Major Command Groups menu so you can select any standard IBM command.*



*Note: Use functions **F10=Standard Jobs**, and **F24=Application Manager Jobs** to quickly*

complete the screen. See below for a description of the function keys and their usage.

Day Mask

A day mask indicating on which day(s) you want the job to be executed. A 1 indicates that the job should be performed and a 0 that it should not.

Override

Enter 1 to force the job to be run tonight or a 0 to prevent the job from running.



Note: The Delete Auto Day-End Overrides command will reset the overrides. A standard job is supplied with Machine Manager to enable you to set up the delete overrides task. See the Standard Jobs section.

Scheduled Time

The time defaults to 99:99:99 this means that it will be run as part of the Day End Jobs using the sequence number to determine when the job should be run.

If a specific time is entered then the execution of the job will be controlled by the Job Scheduling programs, see the section on Job Schedules in Chapter 3.

Schedule Group

In addition to being able to select the day(s) of the week on which a job to be run, you are able to schedule a job to run on a specific set of dates. The dates are maintained via Group Schedules (see the Group Schedules section in Chapter 3). Enter the name of the schedule group you want to associate with this job or press F4=Prompt to select from a list of schedule groups.



Note: For each job you may enter either a schedule group or a day mask.



Press **Enter**.

Functions:

F10

This provides a list of Standard jobs which you may want to run. Selecting one of the jobs will automatically complete all the relevant fields on the screen.

These standard jobs are described in the section Standard Jobs.

F18

If the command you have entered does not exist in the current library list, but will be in the library list at the time of execution then the command can be accepted by selecting **F18**.

F24

Run an Application Manager job as part of your Day End Jobs. See the section Application Manager Jobs.

Maintaining Existing Auto Day End Jobs

The process of maintaining an existing job is essentially the same as Adding a New Job described above. The only difference being that the following function keys are made available when maintaining a job:

Fields:

F13

Each time the Auto Day End Job is run an entry is made on a history log. Pressing **F13** will clear this log. See the section Machine Management Log.

F16

Execute the job now. You will see a screen enabling you to change the parameters of the job for this run. Press **F16** again to confirm that you want to execute the job.

F17

This uses the IBM command WRKJOB - Work with Job to display or change information about the job from its last execution.



Note: If the job has completed and is no longer in the system then there will be no details to display.