

-
-
-
-
-

Chapter 1

Send Objects



Send Objects Menu

You can use Send Objects to send objects, for example, files, folders and libraries, from one system to another.

You can transmit:

- A document or an entire folder from your system to a specific folder on any target system in the network. You can also compress the data on the document or folder before it is transmitted.
- An entire library from your system to any library on any target system in the network. You can pre-check the object, save access paths, and compress the data.
- One object from your system to any library on any target system in the network. You can also specify an object pre-check, save access paths, and enable data compression.
- A single source member from your system to any library on any target system in the network.
- A source library. If you need to send more than one source member from a library it is easier to send the entire source library from your system to any target system in the network.



To display the Send Objects menu, select Send Objects from the Network Manager Main Menu and press **Enter**.

Document Library Object



Select Document Library Object and press **Enter**.

Use this option to transmit a document or an entire folder from your system to a specific folder on any target system in the network. You can also specify that the data is compressed.

```
NW240                      Network Manager                      System: STUDB30A
Send Document Library Object (SNDDL0)

Document Library Object . . . _____
Folder. . . . . _____

To system . . . . . _____

Additional Parameters
Target release . . . . . V2R1M1 (*CURRENT,*PRV,V2R1M0,V2R1M1,V2R2M0)
Receive into Folder . . . . *SAME
Data compression. . . . . *YES (*YES,*NO)

F3=Exit  F4=Browse  F12=Previous
```

Fields:

Document Library Object

Enter the name of the document library object. Enter *ALL to select all objects in the chosen folder.

Folder

Enter the name of the folder containing the document library object. If you enter *ALL in the previous field the entire folder is transmitted.

To System

Enter the name of the system to which you want to send the object.



Tip: To display the following fields, select **F10=Extras**.

Target Release

Specify the release level of the operating system (OS/400) on the target machine.

Receiving Into Folder

Enter the name of the folder on the target system.



Note: Send Library does not overwrite an existing library. If the library exists on the target

system use this field to send the library to a different name on the target system.

Data Compression

Enter one of the following:

*Yes - To compress the data for more efficient transmission. Data compression removes contiguous blank spaces contained in lines of code and replaces them with an edit code indicating the number of blank spaces removed. This process can typically reduce the size of a transmitted object by 30 to 40%. The compressed objects are automatically de-compressed during the restoration process at the target system.

*No - Not to compress the data.




Press **Enter** to start the transmission.

Library

 Select Library and press **Enter**.

Use this option to transmit an entire library from your system to any library on any target system in the network. You can run an object pre-check, save access paths, and compress the data.



```

NW210                                Network Manager                                System: STUDB30A
Send Library (SNDLIB)

Library . . . . . _____
To system . . . . . _____

Additional Parameters
Target release . . . V2R1M1      (*CURRENT,*PRV,V2R1M0,V2R1M1,V2R2M0)
Receiving Library . . *SNDLIB    (Name, *SNDLIB)
Object pre-check . . *YES       (*YES, *NO)
Save access path . . *NO        (*NO, *YES)
Data compression . . *YES       (*YES, *NO)

F3=Exit  F4=Browse  F12=Previous
  
```

Fields:

Library

Enter the name of the library to transmit.

To System

Enter the name of the target system.



Tip: To display the following fields, select **F10=Extras**.

Target Release

Specify the release level of the operating system (OS/400) on the target machine.

Receiving Library

Enter the name of the receiving library or use *SNDLIB to create a library on the target system with the same name as the transmitted library.



Note: Send Library does not overwrite an existing library. If the library exists on the target system use this field to send the library to a different name on the target system.

Object Pre-Check

Enter one of the following:

*YES - The send library operation ends if any of the following conditions are true:

1. Any of the objects do not exist.
2. Any of the objects are damaged.
3. Any of the objects are locked by another job.
4. You do not have authority to the objects.

*NO - The operation continues only sending the objects which satisfy the above conditions.

Save Access Path

Enter one of the following:

*YES - To transmit the logical file access paths associated with the physical files.

*NO - To prevent the logical file access paths from being transmitted with the library, for faster data transmission.



Note: The logical file access paths are re-built when specified for Access Path Recovery when the logical file was created, that is when the file is opened, after IPL, or during IPL.

Data Compression

Enter one of the following:

*Yes - To compress the data for more efficient transmission. Data compression removes contiguous blank spaces contained in lines of code and replaces them with an edit code indicating the number of blank spaces removed. This process can typically reduce the size of a transmitted object by 30 to 40%. The compressed objects are automatically de-compressed during the restoration process at the target system.

*No - Not to compress the data.



Press **Enter** to start the transmission.

Single Object



Select Single Object and press **Enter**.

Use this to send one object from your system to any library on any target system in the network. You can also specify an object pre-check, save access paths, and compress data.

```

NW211                                     Network Manager                               System: STUDB30A
Send Object (SND OBJ)

Object . . . . .
Library . . . . . *CURLIB (Name> *CURLIB)
Object type . . . . .
To system . . . . .

Additional Parameters
Target release . . . V2R1M1 (*CURRENT,*PRV,V2R1M0,V2R1M1,V2R2M0)
Receiving Library . . *SNDLIB (Name> *SNDLIB)
Object pre-check . . *YES (*YES, *NO)
Save access path . . *NO (*NO, *YES)
Data compression . . *YES (*YES, *NO)

F3=Exit F4=Browse F12=Previous
  
```

Fields:

Object

Enter the name of the object to transmit.

Library

Enter the name of the library containing the object to transmit.

Object Type

Specify the object type, for example, *CMD - command, *FILE - file, *PGM - program.

To System

Enter the name of the target system.



Tip: To display the following fields, select **F10=Extras**.

Target Release

Specify the release level of the operating system (OS/400) on the target machine.

Receiving Library

Enter the name of the receiving library or use *SNDLIB to create a library on the target system with the same name as the transmitted library.



Note: Single Object overwrites an object on the target system if it can be deleted. If the library to contain the object does not exist it is created.

Object Pre-Check

Enter one of the following:

*YES - The send library operation ends if any of the following conditions are true:

1. Any of the objects do not exist.
2. Any of the objects are damaged.
3. Any of the objects are locked by another job.
4. You do not have authority to the objects.

*NO - The operation continues only sending the objects which satisfy the above conditions.

Save Access Path

Enter one of the following:

*YES - To transmit the logical file access paths associated with the physical files.

*NO - To prevent the logical file access paths from being transmitted with the library, for faster data transmission.



Note: The logical file access paths are re-built when Access Path Recovery is specified, when the logical file was created, that is when the file is opened, after IPL, or during IPL.

Data Compression

Enter one of the following:

*Yes - To compress the data for more efficient transmission. Data compression removes contiguous blank spaces contained in lines of code and replaces them with an edit code indicating the number of blank spaces removed. This process can typically reduce the size of a transmitted object by 30 to 40%. The compressed objects are automatically de-compressed during the restoration process at the target system.

*No - Not to compress the data.



Press **Enter** to start the transmission.

Source Member



Select Source Member and press **Enter**.

Use this facility to send a single source member from your system to any library on any target system in the network.

NW220 **Network Manager** System: STUDB 30A

Send Source Member - SNDSRC

File
Library *CURLIB (name,*CURLIB)
Member (name,*FIRST)
To system.

Additional Parameters
Receiving library. . *SNDLIB (name,*SNDLIB)

F3=Exit F4=Browse F12=Previous

Fields:

File

Enter the file name of the file containing the member to transmit.

Library

Enter the name of the library containing the member to transmit.

Member

Enter the name of the source member to transmit or enter *FIRST to send the first member in the file.

To System

Enter the name of the target system.



Tip: To display the following field, select **F10=Extras**.

Receiving Library

Enter the name of the receiving library or use *SNDLIB to create a library on the target system with the same name as the transmitted library.



Note: Send Source Member does not overwrite an object on the target system. If the file or library does not exist it is created.

Source Library

 Select Source Library and press **Enter**.

If you need to send more than one source member from a library it is easier to use this facility to send the entire source library from your system to any target system in the network.



NW230 **Network Manager** System: STUDB30A

Send Source Library - SNDSRCLIB

Source library _____

To system _____

Additional Parameters

Receiving library . . . *SNDLIB (name,*SNDLIB)

F3=Exit F4=Browse F12=Previous

Fields:

Source Library

Enter the name of the source library to transmit.

To System

Enter the name of the target system.

 **Tip:** To display the following field, select **F10=Extras**.

Receiving Library

Enter the name of the receiving library or use *SNDLIB to create a library on the target system with the same name as the transmitted library.

 **Note:** Send source library does not overwrite an existing library. If the library exists on the target system use this field to send the library to a different name on the target system.

 Press **Enter** to start the transmission.