

-
-
-
-
-

Chapter 3

Constructor Windows



Activate Window



To display this window select the Activate option on the Work Management Menu.

Use the Activate Window to load data from the design-time database on your PC to the Work Management files on the server of your choice. There are two panels:

- Use the General Panel to activate one or more Business Processes and all their associated components. This means uploading a Business Process to the server so that Work Management can then run it using the Work Management Engine. All the components associated with a Business Process are held in the design-time database on your PC with the Business Process and when you activate all these components are saved on the Work Management files on the server with the Business Process.
- Use the Advanced Panel to individually activate Document Types, Execution Modes, Data Fields, Escalation Rules and Schedule Rules. You specifically update various components in the Work Management files. For example you could update Data Fields from the design-time database on the PC to the Data Fields table on the server.



Tip: If you want to activate only a Business Process then you can ignore the Advanced panel entirely. Everything associated with the Business Process will be moved to the server for you, except for the Escalation And Delegation rules. Use the Advanced Panel for this.

Activation does the following things:

- Validate. This performs the same validation as the Validate button. If you previously validated and it failed then you will not be able to Activate either.
- Compiles the configuration.
- Updates the Work Management Engine's files on the server. The Work Management Engine checks that the Business Process has a Code. If the Business Process does not have a Code then it cannot be activated. Please refer to Business Process Code.

Each time a Business Process is activated a new version is created on the server. When the files are on the server you can then manage them. Please refer to the Business Process Status Windows. You might want to view version details or delete a version. You can change the status of the Business Process to disabled or back again to enabled. If it is disabled this means that although the Business Process exists on the server, it is not available to the Work Management Engine. You can also define dates between which the Business Process will be enabled or disabled.


Before you start please note the following:

- You need a connection to the Work Management database on the server. If you have no connection to the server, for example if you are working on a laptop computer, then you cannot perform the activation.
- You need an ODBC data source set up using your Windows Control panel, which points to the Work Management library on the server. Refer to the documentation supplied with the communications package, for example Client Access, which you use to communicate with your AS/400 server.

- All the changes which you have made during the construction of your Business Process have only been local to your PC, saved on the design-time database. Whatever you load now will make those changes effective on the server for everyone. Take care.

Fields:

General Panel




This panel lists all the Business Processes, saved to the design-time database on your PC, that have a Business Process Code.



Note: You can enter the Business Process Code, for a Business Process, by selecting Properties on the Workspace pop up menu.

You select one or more Business Processes from the list. If you select more than one then these are activated one at a time.

Advanced Panel



Here you select components to be updated on the server.



Tip: If you want to activate only a Business Process then you can ignore the Advanced panel entirely. Everything associated with the Business Process will be moved to the server for you. Use the Advanced Panel only to specifically update components.



Warning: *If you check the boxes then you will be replacing items on the Work Management files on the server and this will affect all users.*

Even though a Business Process, when activated, takes all its associated components with it to the server, if any of these components are individually activated later, using the Advanced Panel, they will overwrite those already associated with the Business Process. For example, a Business Process might use a CustName Data Field and when the Business Process is activated CustName will be updated on the server too. If Data Field is activated separately at a later date then the Business Process will pick up the later version automatically when any of its activities are executed by the Explorer user.

Type

This column displays all the types of components which you can activate to the server.

Select

You select here which sort of items you want to be inserted or overwritten on the Work Management Files Library on the server. The following table shows which Type of activation option updates which files:

Type	File(s) Updated
Document Types	WFP06
Execution Modes	WFP01/98
Data Fields	WFP05
Escalation Rules	WFP07
Schedule Rules	WFP09
Business Processes	WFP03/04/17/18/20/21/26/27/28

Conflict Replace

There are three possible options to determine how the data on the server database is to be replaced:

- Prompt - prompts you before replacing
- Replace - replaces without prompting
- Retain - does not replace at all.

Schedule Rules are always replaced.

For example, if you select the Document Types box, and select Prompt in the Conflict Replace field then you are saying that you want to copy all the Document Types in the design-time database on the PC to the WFP06 files on the server. If a Document Type on the design-time database has the same name as a Document Type on WFP06 then you want the Document Type on WFP06 to be replaced only after you have been prompted and have confirmed the copying process.

Status

This displays the results of the Activation. It tells you when the activation started and finished and lists any errors so that you can make corrections and activate again.



Note: The following fields concern the Activation Log.

Progress

Check this to display basic progress messages.

Totals

Tells you how many components of each type have been activated.

Detail

Check this to display detailed progress messages.

Timestamps

Puts the time against each item on the log.

Buttons:

Activate

This starts the Activation process and the Status box displays activation messages.


First the Business Process is validated and you may see Error Messages and Warning Messages. Error Messages must be corrected before you can continue. Warning messages may be ignored but we recommend that you check the reason for each one as there may be an element of your design which could be improved.

At the end of the validation you will see the message: 'Validation Ends' and Constructor connects you to the server and presents you with the logon window. You are informed that the connection is successful as shown below:

```

13:40:23      Reference 'Order entry (conversational)' has not got an error role defined
13:40:23      Reference 'Confirmation of despatch' has not got an error role defined
13:40:24      Validation of 'Business Process' Ends - Warnings Logged
13:40:24      1 Business Processes validated
13:40:24      Validation Ends at 13:40:24 on 13 July 1998
13:40:24
13:40:30      Connection [ewm2connect] Starts at 13:40:30 on 13 July 1998
13:42:18      Connection Successful
  
```

If you have activated this Business Process before Constructor recognises that there is a previous version in existence and prompts you as follows:



This warning message tells you what the latest version of the Business Process is on the server, for example Version 1, and tells you which version you are trying to activate, for example, Version 2.

If you answer Yes then the previous version will be disabled and the current version will be copied to the server and enabled.

If you answer No then the previous version will remain enabled and the current version will be copied to the server and disabled.



Note: You can view the status of all the Business Processes which have been activated on the server by selecting the Manage Activated Processes option on the Work Management Menu. You can also delete a Business Process using this option if you feel that you have made a mistake in activating this Business Process.

Server

Displays the Data Source Window. Use this only if you want to change the server.

Close

Close the window.

Copy

Save the log to a file.

Application Server Settings Window



To display this window double click on an activity to go through to the System 21 application.



*Note: If you double click on an activity, expecting to see this window, but instead you see the message 'Failed to create an instance of the Runtime engine', then please do as follows:
Using Windows Explorer, please locate this file
c:\Program Files\JBASys21\RTIMEEngine.exe
and then double click on the file. This will correct the error for you. You do not need to reboot, just continue as before.*

You can enter logon details. If your details are correct Constructor connects you to the Server system. For example: if you had double clicked on a component called Enter Order then after a successful logon the Enter Order window would be displayed for you to use.

The text at the top of the window tells you which application you are connecting to, for example: This will be used to run Report Generator.

Fields:

Server

Displays the default Server saved from your last System 21 session. Either use the default server name, or select another from the drop-down list.

This list is set up for you by your System Administrator, using System Configuration.

User name

Your User name identifies you to the server. The first time you use System 21, this field defaults to the dummy sign on USERID. You should enter your User ID details.

For future logons System 21 will default to the User ID that you initially entered.

Password

Your password. This field is always blank at Logon - enter your password. The password is not displayed on screen - each typed character is represented by an asterisk (*).



Note: If your password has expired, the Change Password Window is displayed, enabling you to change your password.

Company

This group box contains the following radio buttons:

User Default

Select this to accept your user default company. JBA System 21 is multi-company software where each user can have their own default company set up.

Use

Select this and enter a two-character company code if you want to override your user default. This displays the AS/400 Session Manager window called Select Company. Please refer to your AS/400 Session Manager help guides.

The browse button is available only when you log onto System 21 for a second or subsequent time. This is because the Server builds a list of companies after you log in for the first time.



Note: The System Administrator can use the System Configuration Servers Window to set defaults for the Server.

Environment

This group box contains the following radio buttons:

Server Default

Select this to accept the default environment for the server.

Use

Select this and enter an environment code if you want to override the default environment for the system.

Save As Default For **SERVERNAME**

Where **SERVERNAME** is the name of the server selected in the Server field above.

Check this box to save the settings for the default server.



Note: The System Administrator can use the System Configuration Servers Window to set defaults for the Server.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Business Process Status Windows

Use these windows to manage the activated business processes on the server. This is what you can do:


- You can view the Business Process details, including the version number and effectivity dates. There is a row of details for each version of the Business Process.
- You can change the status of the Business Process to disabled or back again to enabled. If it is disabled this means that although the Business Process exists on the server, it is not considered by the Work Management Engine for possible initial activities, although it will complete any processes which it has already started under its control.
- You can define dates between which the Business Process will be enabled or disabled.
- You can delete a Business Process version.

There are two windows and this is how to use them:

- First use the Business Process Status Window. To display this window select Manage Activated Processes on the Work Management Menu. This screen is also displayed for you during the Activation process. Use the Edit button to display the second window.
- Secondly edit any Business Process details using the Edit Process Control Properties Window.

Business Process Status Window

-  To display this window select Manage Activated Processes on the Work Management Menu. This screen is also displayed for you during the Activation process.



Process Code	Version	Enabled	Created	User	From	To
✓ AE1	1	Yes	09/07/1998 12:46	GBJBAZBR	No Restriction	No Restriction
✓ BPR006	1	Yes	07/07/1998 15:00	GBJBAZBR	No Restriction	No Restriction
✗ DYCI01	1	No	09/07/1998 13:38	GBJBAHA	No Restriction	No Restriction
✓ DYCI01	2	Yes	09/07/1998 13:41	GBJBAHA	No Restriction	No Restriction
✓ NGSOP1	1	Yes	09/07/1998 12:21	GBJBANER	No Restriction	No Restriction
✓ PT001	1	Yes	03/07/1998 13:07	GBJBAPCW	14/07/1998	No Restriction
✓ PT007	1	Yes	03/07/1998 13:09	GBJBAPCW	No Restriction	No Restriction

Buttons: Delete, Edit..., OK, Cancel

You see a view of all the Business Processes which have been activated to the server. You can view and go on to edit the WFP20 Work Management file on the server by clicking the Edit button or double clicking on a Business Process.

These are the possible statuses of the Business Process:

-  Disabled and not considered by the Work Management Engine for possible initial activities, although it will complete any processes which it has already started under its control.
- ✓ Enabled and available to the Work Management Engine.
-  Deleted from WFP20.

Fields:

Process Code

Please refer to Business Process Code.

Version

This is the version number of the Business Process.

Enabled

Yes means the Business Process on WFP20 is available to the Work Management Engine.

No means the Business Process on WFP20 is not available to the Work Management Engine.

Created

The date when the Business Process was last activated and the latest version was saved as a file on the server.

User

The name you use to log on to the server.

From and To

The dates between which the Business Process is to be enabled or disabled. Where there is no date defined this means there is no restriction on the enablement or disablement. It is possible to have only a From date or a To date.

Buttons:**Delete(or Undelete)**

This button toggles to Delete or Undelete the Business Process from WFP20. However the deletion is not saved until you click the OK button.

Edit

Displays the Edit Process Control Properties Window. You can edit any of the details however, the changes are not saved until you click the OK button on the Business Process Status Window.

OK

Close the window and save the changes to WFP20. You are prompted to confirm the changes.

Cancel

Close the window without updating WFP20.

Edit Process Control Properties Window



To display this window either select Edit or double click on a Business Process, in the Business Process Status Window.

You can edit any of the details, however the changes are not saved until you click the OK button on the Business Process Status Window.

You can view and directly edit one of the Business Processes on the WFP20 Work Management file on the server. This is a Business Process which has been activated to the server.



Note: To save the changes you make you have to click OK to return to the Business Process Status Window, where the new details are displayed, and then click OK again.

Fields:

Process Code

Display only.

Status

Disabled means the Business Process on WFP20 is not available to the Work Management Engine.

Enabled means the Business Process on WFP20 is available to the Work Management Engine.

Effective From or Effective To

These two group boxes both have an unnamed date selection field and a No Restriction checkbox and the combination of these fields enables you to put a restriction on the state of the Business Process. You can define dates between which the Business Process will be enabled or disabled.

For example, if you have a Status of Enabled, and you leave the No Restriction boxes unchecked, you can then select dates between which the Business Process will be enabled. However, if the No Restriction boxes are both checked this means that the Business Process is unconditionally enabled and has no restriction either now or in the future.



Note: This applies both to enabling and disabling and you can have both Effective From and Effective To dates or just one of these.



Note: You can edit a Business Process with a Deleted status and change the status to Enabled.

Buttons

OK

Return to the Business Process Status Window and carry forward the changes. The changes are not saved until you click the OK button on the Business Process Status Window.

Cancel

Return to the Business Process Status Window and lose any changes.

Conditions Window



To display this window select Conditions from either the Elemental Activity or Business Methods pop up menu on the Workspace.

You can view the input conditions and node settings which apply for the Elemental Activity or Business Method.



Note: You cannot edit this information here. To do this you need the Properties Window.

Fields:

Input Conditions

These are the conditions which have to be set up before you can execute this component. For example: a particular field may need to be set up in the Data Exchange Area, or customer details may need to have been set up.

Parameter Settings

All Nodes

This field works in conjunction with the Node Setting list field and may be blank. If text is present it will show the parameters set by all exit nodes and is therefore not conditional.

Node Setting

This is list of all the nodes which have been set up on the database for the component.

For example: OK and Cancel. These correspond exactly to both the nodes displayed on the symbol on the Workspace and to the buttons on the application's window which are used to exit from that window.

Unnamed

Contains instruction, corresponding to the currently displayed Node Setting, which indicates the condition satisfied by this exit point from the component.

For example: Consider a component which exists to set up a customer. If a Node setting in this component is called OK, and states that a Customer must be set up, then the fact that the user has pressed OK and exited from this component means that the Customer has to have been set

up. The condition of the customer having been set up can then become an input condition for a subsequent component in the process.

Buttons:


OK

Close the window and save the changes made.

Consumable Details Window



To display this window select Consumables on either the Elemental Activity or Business Methods pop up menu.



You can define which consumables are to be used for an Elemental Activity or Business Method.



Tip: When you validate a process you may have Consumable errors reported and this is the window you would use to edit and correct the Consumables.

Fields:

Available Consumables

This is a browser list of all those value components available for you to choose from. You select a value and drag it across to the list of defined consumables on the right side of the window. For example: VAT code 1.

Defined Consumables

This is a list of blank consumables which have already been defined for the Elemental Activity or Business Method. For example: VAT Consumable=?



Note: To set up the blank Consumables on the database you need the Properties Window.

These consumables hold no values at this point: it is a storage area for variables. For example: you might want to have a consumable for holding Tax Codes. You can then select, drag and drop the value you need, as appropriate for individual applications and local tax rules, from the Available Consumables list onto the Defined Consumables list. The value you choose is used to complete the definition.

This is what you could see:

- On the left - VAT code 1 (this is what you drag across)
- On the right (Before) - VAT Consumable=?
- On the right (After) - VAT Consumable=VAT Code 1.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Data Fields Windows

There are three windows:

- Maintain Data Field where you select a Document Type and display a list of Data Fields. There are buttons where you go on to Add or Edit.
- Add Data Field Window.
- Edit Data Field Window.

Maintain Data Field Window



To display this window select the Data Fields option on the Work Management menu.

Document type	Data field name	Description	Field type	Usage	Data field
PICKNOTE	AcknowledgePrtFlag	Acknowledge Print Flag	S	D	Select PI
SALESORDER	Activity	Activity	W	D	
	Agent	Agent	S	D	Select AI
	BaseOrderValue	Base Order Value	S	D	Select Br
	BusinessObject	BusinessObject	W	D	
	BusinessProcess	BusinessProcess	W	D	
	Carrier	Carrier	S	D	Select C
	Company	Company	W	D	
	CurrencyCode	Currency Code	S	D	Select CI
	CurrencyRate	Currency Rate	S	D	Select CI
	CurrencyRateCode	Currency Rate Code	S	D	Select CI
	CurrentDate	CurrentDate	W	D	
	CurrentTime	CurrentTime	W	D	
	CustAccomInvoiceFlag	Customer Accompanying Invoice F...	S	D	Select AI
	CustAcknowledgement	Customer Acknowledgment	S	D	Select AI
	CustAcMgr	Customer Account Manager	S	UD	Select PI
	CustAddressLine1	Customer Address Line 1	S	D	Select C
	CustAddressLine2	Customer Address Line 2	S	D	Select C
	CustAddressLine3	Customer Address Line 3	S	D	Select C
	CustAddressLine4	Customer Address Line 4	S	D	Select C
	CustAddressLine5	Customer Address Line 5	S	D	Select C
	CustAgent	Customer Agent	S	D	Select AI
	CustAllowDaysOutTerm	Customer Allowed Days Out Term	S	D	Select CI



Note: Data Fields are variables which are resolved for each document at run time.

You can display, select and maintain Data Field details for a Document Type. Select a Document Type from the list to display all the Data Field details. Then select a Data Field and use the Add, Edit and Delete buttons to maintain the details.



Tip: Refer to the Enterprise Work Management guide for tutorials to help you with adding Data Fields.

Fields:

Document Type

Select a Document Type from the list to display all the details for the Data Fields relating to this Document Type.

Data Field Name

For example, CustAcMgr.

Description

For example Customer Account Manager.

Field Type

T=Text

S=SQL

P=Programmatic

W=Workflow

Usage

R=Role

U=User

E=Email

P=Priority

D=Description

Data Field Information

The contents of this field vary according to the Field Type. You could see:

- Nothing at all for a Workflow type
- An SQL Statement for an SQL type
- A Program Code or another Data Field, for a Programmatic type
- A string of text for a Text type.

Data Type

A= Alpha String

N=Numeric String

P=Packed Decimal

B=Binary Numeric

S=Signed Numeric

Field Length

For example 5 for a program, 35 for an SQL statement.

Decimal Places

Number of decimal places.

Buttons:

Add

Displays the Add Data Field Window.

Edit

Displays the Edit Data Field Window.

Delete


Deletes the line of Data Field details. You are not prompted to confirm this particular deletion; however, you have the opportunity to close without saving any details when you click the Close button.

Close

Prompts you to decide whether or not to save the changes you have made and then closes the window.

Add Data Field Window

 To display this window select the Add button on the Data Fields Window.



You can enter details for a Data Field. Each Data Field has to be assigned to a Document Type.

Fields:

Data Field Name

You create this name. For example, CustAcMgr.

Document Type

Select a Document Type to which the Data Field will then be associated.

Data Field Type

Select the type of Data Field:



Warning: You can safely add Text and SQL types. However, take great care with Programmatic types and do not use Workflow types unless instructed by JBA.

Text

Literal text can be defined up to 256 characters long.

SQL

A Data Field is evaluated by executing an SQL statement. SQL statements may themselves contain variables hence resolving a Data Field may require recursive variable resolution. The SQL statement is defined in Constructor.

Programmatic



Warning: If you add a Programmatic type of Data Field then you need to create an RPG

program with a subroutine for each Data Field. Please refer to Enterprise Work Management guide for help you with this.

This calls a program defined in Constructor to evaluate Data Fields.



Note: All programs written to evaluate run-time Data Fields will be of the same structure as the Skeleton program QRPGRSRC/@SWMVARSUB. Output, P#VARV. Please refer to your Enterprise Work Management guide. One program may be used to evaluate many Data Fields. Each Data Field will have its own subroutine within its program.

Workflow



Warning: Workflow Data Fields need to be supported by the Work Management Engine. You will only need to amend these under exceptional circumstances and with guidance from JBA.

These are the Work Management information Data Fields:

- Company
- Business Process
- Business Object
- Document
- Activity
- Current Time
- Current Date.

Description

Enter your own description. For example Customer Account Manager.

Usage

Check any number of boxes to enable the Data Field to be used in different contexts. You have to check at least one box. Description is checked by default but you can uncheck it. Refer also to the Execution Details.



Note: There are three different names for the following field, depending on the Data Field Type:

- Data Field Information
- SQL Statement
- Program.

Data Field Information

You see this field only if the Data Field Type is Text or Workflow. If it is Text then you can enter a textual string of characters. If it is Workflow then it is disabled.

SQL Statement

You see this field only if the Data Field Type is SQL. You enter the SQL statement in here. This statement can also contain other Data Fields, for example, Company. To insert Data Fields you right click on the field to display the Select Data Field Window.

Program

You see this field only if the Data Field Type is Programmatic. Enter the program code, for example, AA1001.

You could insert a Data Field here, to perhaps point to a program instead of entering the program code directly. To insert Data Fields you right click on the field to display the Select Data Field Window.

Data Type

Select from the list to define the field as an Alpha or Numeric string or as a Signed, Packed Decimal or Binary Numeric.

Field Length

Use the spin buttons to determine the field length. For example 5 for a program, 35 for an SQL statement.

Decimal Places

Use the spin buttons to determine the number of decimal places. This could be zero.

Buttons:

OK

Close the window and save the changes to a temporary file so that they are reflected in the list on the Data Fields Window. You can then use the Close button on the Data Fields Window to save the changes to the database.

Cancel

Close the window without saving the changes.

Edit Data Field Window



To display this window select the Edit button on the Data Fields Window.

The 'Edit data field' window displays the following information:

- Data field name:** CustomerCreditUsage
- Document type:** SALESORDER
- Data field type:** Programmatic
- Description:** Customer Credit Usage Percentage
- Program:** AA1001
- Usage:** ☐ Role, ☐ User, ☐ E-mail address, ☐ Priority, ☒ Description
- Data type:** Packed decimal numeric
- Field length:** 5
- Decimal places:** 2

Buttons: OK, Cancel

The 'Edit data field' window displays the following information:

- Data field name:** CustAddressLine1
- Document type:** SALESORDER
- Data field type:** SQL
- Description:** Customer Address Line 1
- SQL statement:** Select CAD105 from OEP40,SLP05 where CONO05 = CONO40 AND CUSN05 = CUSN40 AND DSEQ05 = DSEQ40 AND CONO40 = Company and ORDN40 = Document
- Usage:** ☐ Role, ☐ User, ☐ E-mail address, ☐ Priority, ☒ Description
- Data type:** Alpha string
- Field length:** 35
- Decimal places:** 0

Buttons: OK, Cancel

You can edit details for a Data Field. Each Data Field has to be assigned to a Document Type.

Fields:

Data Field Name

For display only.

Document Type

For display only.

Data Field Type

Select the type of Data Field:



Warning: You can safely add Text and SQL types. However, take great care with Programmatic types and do not use Workflow types unless instructed by JBA.

Text

Literal text can be defined up to 256 characters long.

SQL

A Data Field is evaluated by executing an SQL statement. SQL statements may themselves contain variables hence resolving a Data Field may require recursive variable resolution. The SQL statement is defined in Constructor.

Programmatic



Warning: If you add a Programmatic type of Data Field then you need to create an RPG program with a subroutine for each Data Field. Please refer to Enterprise Work Management guide for help you with this.

This calls a program defined in Constructor to evaluate Data Fields.



Note: All programs written to evaluate run-time Data Fields will be of the same structure as the

*Skeleton program QRPGRSRC/@SWMVARSUB.
Output, P#VARV. Please refer to your Enterprise
Work Management guide. One program may be
used to evaluate many Data Fields. Each Data
Field will have its own subroutine within its
program.*

Workflow



Warning: Workflow Data Fields need to be supported by the Work Management Engine. You will only need to amend these under exceptional circumstances and with guidance from JBA.

These are the Work Management information Data Fields:

- Company
- Business Process
- Business Object
- Document
- Activity
- Current Time
- Current Date.

Description

Enter your own description. For example Customer Account Manager.

Usage

Check any number of boxes to enable the Data Field to be used in different contexts. You have to check at least one box. Description is checked by default but you can uncheck it. Refer also to the Execution Details.



Note: There are three different names for the following field, depending on the Data Field Type:

- Data Field Information
- SQL Statement
- Program.

Data Field Information

You see this field only if the Data Field Type is Text or Workflow. If it is Text then you can enter a textual string of characters. If it is Workflow then it is disabled.

SQL Statement

You see this field only if the Data Field Type is SQL. You enter the SQL statement in here. This statement can also contain other Data Fields, for example, Company. To insert Data Fields you right click on the field to display the Select Data Field Window.

Program

You see this field only if the Data Field Type is Programmatic. Enter the program code, for example, AA1001.

You could insert a Data Field here, to perhaps point to a program instead of entering the program code directly. To insert Data Fields you right click on the field to display the Select Data Field Window.

Data Type

Select from the list to define the field as an Alpha or Numeric string or as a Signed, Packed Decimal or Binary Numeric.

Field Length

Use the spin buttons to determine the field length. For example 5 for a program, 35 for an SQL statement.

Decimal Places

Use the spin buttons to determine the number of decimal places. This could be zero.

Buttons:**OK**

Close the window and save the changes to a temporary file so that they are reflected in the list on the Data Fields Window. You can then use the Close button on the Data Fields Window to save the changes to the database.


Cancel

Close the window without saving the changes.

Select Data Field Window.



To display this window select the Insert Data Field option from the Manual Activity Panels Menu. To display this menu please click with the right mouse button on the Message Panel or Title Overrides Panel on the Properties for Manual Activity Window.



You can select a Data Field from the list.

Buttons:

OK

Save the changes and close the window.


Cancel

Close the window without saving the changes.

Data Source Window



This window is displayed when you Activate, Retrieve or Manage Activated processes. These are all options on the Work Management Menu



This displays a list of ODBC connections which have been established on your PC. You enter the database name, and then log on to the Server.



Note: If you expect to connect to the server but instead see the message 'Failed to create an instance of the Runtime engine', then please do as follows:

*Using Windows Explorer, please locate this file
c:\Program Files\JBASys21\RTIMEEngine.exe
and then double click on the file. This will correct the error for you. You do not need to reboot, just continue as before.*




Note: You could have two completely different environments set up on two different servers. In which case you would have a Work Management engine and Work Management files set up on each server.



Warning: If you check the Turbo Mode box, then you must check your ODBC configuration to make sure that the Enable Pre-Fetch During Execute field on the ODBC Performance panel is unchecked (default). If both Turbo Mode and Pre-Fetch are on then items could be lost during an activation.

This is how the configuration should be set up. The only field that you could adjust is the Size field.



Fields:

Name

The name of the Work Management database on the server. Check carefully which one you are to use. If you have no connection to the server, for example if you are working on a laptop computer, then you cannot perform the activation.

Driver

You need an ODBC data source set up using your Windows Control panel, which points to the Work Management library on the server. Refer to the documentation supplied with the communications package, for example Client Access, which you use to communicate with your AS/400 server.

User

Valid User name to log on to server using the ODBC connection.

Password

Valid Password.

Turbo Mode

This box is checked, by default, to speed up the connection to the server. If your ODBC driver does not support this type of access, or you see error messages in connection with your driver then you can turn this facility off and this will send one record at a time. If you switch off and then on again you will be warned that not all ODBC drivers are supported and if in doubt switch off.



Warning: If you check the Turbo Mode box, then you must check your ODBC configuration to make sure that the Enable Pre-Fetch During Execute field on the ODBC Performance panel is unchecked (default). If both Turbo Mode and Pre-Fetch are on then

items could be lost during an activation.

Buttons:

OK

Continue with the activation and log in to the AS/400.


Cancel

Close the window without continuing the activation.

Define Menu Window



To display this window select Define Menu on either the Elemental Activity or Business Methods pop up menu.



You can create a menu for the user to use at runtime. You create a normal Windows, context sensitive, pop up menu which is displayed when the user clicks with the right mouse button on the application window.

Each menu option sets off an independent piece of processing. Use this to offer the user more pathways out of the process. For example perhaps to offer extra printing facilities.



Tip: Do not confuse these pathways or exit points with those contained within the process you see on the Workspace. These pathways have no nodes and do not interfere with the process. Think of them conceptually as going off at a tangent to the process rather than interfering with it.

Fields:

Available Options

A list of Elemental Activities and Business Methods available for you to choose from. You drag them across to the Selected Options list.

Selected Options

A list of options which you have chosen and which then become menu options for the users context sensitive pop up menu on the application window.



Tip: You can click with the right mouse button on any of these options to display the Design Menu Options Menu. This is a Constructor pop up

menu for you to determine characteristics for each item on the users pop up menu.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Define Reason Codes Window



To display this window select Reason Codes from the Properties Grid Menu. The title bar says Add or Maintain depending on which row of the grid is selected when the right mouse button is clicked.

Reason Code	Description
01	Invoice waiting processing via EDI
02	Invoice is consolidated with period still open
03	Invoice waiting printing of delivery document.
04	Invoice is not domestic

You can maintain a file of Reason Codes. These codes are used to explain why a process has failed.

This window has a grid box but there is no pop up menu.



Note: This file is not global. The Reason Codes relate only to the Completion Code, within the Document Type, within the Activity.

Fields:

Document Type

You don't need to enter this. It is carried forward from the previous window.

Completion Node

You don't need to enter this. It is carried forward from the previous window.

Reason Code

Enter a two character numeric code.

Description

Describe the Reason Code. For example: Invoice waiting printing of delivery document.

Buttons:

OK

Save the changes and close the window.


Cancel

Close the window without saving the changes.

Display Details Window



To display this window select Display Details on either the Elemental Activity or the Business Methods pop up menu.



You can determine the startup position of an application window.

Fields:

Window Position

Choose the position of the window in relation to the whole screen.



Warning: *You may find that your setting here does not work. This is because the component may be programmed not to implement this feature.*

Remove On Next Method

If you select this then the window will disappear from view as the next one is displayed.

Clear Screen Before Display

If you select this then the screen will be cleared before the window is displayed.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Document Types Windows


There are three windows:

- Document Types Window where you maintain a file of Document Types. There are buttons for you to go on to Add or Edit.
- Add Document Type Window.
- Edit Document Type Window.

Document Types Window



To display this window select the Document Types option on the Work Management Menu.



You can maintain a file of Document Types.



Note: This file is global across all applications.

Fields:

Document Type

A unique 10 character code.



Note: If you want to change this code you have to delete the old Document Type and create a new one using the Delete and Add buttons.

Description

This is intended for your internal administration and is not seen by the System 21 Explorer user. You would probably want to use the same text as that used for the Short Description.

Short Description

Use 15 characters only. This is the description which is seen by the System 21 Explorer user.

Business Sector

Not used.

Buttons:

Add

Displays the Add Document Type Window.

Edit

Displays the Edit Document Type Window.

Delete

Prompts you to confirm whether to delete the Document Type from file.



Warning: You are prevented from doing this if the Document Type is used by another application.

Close

Prompts you to select whether to save the changes or not when you close the window.

Add Document Type Window



To display this window select the Add button on the Document Types Window.

You can create a new Document Type.

Fields:

Document Type

Enter a unique 10 character code.

Description

You can enter any text here. This is intended for your internal administration and is not seen by the System 21 Explorer user. You would probably want to use the same text as that used for the Short Description.

Short Description

Use 15 characters only. This is the description which is seen by the System 21 Explorer user.

Business Sector

Not used.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Edit Document Type Window



To display this window select the Edit button on the Document Types Window.

The screenshot shows a standard Windows-style dialog box titled "Edit Document type". It has a close button (X) in the top right corner. The dialog is divided into four sections, each with a label and a text input field: "Document Type" with the value "CALL", "Description" with the value "Call list", "Short Description" with the value "Call list", and "Business Sector" which is empty. At the bottom right of the dialog are two buttons: "OK" and "Cancel".

You can edit the Document Type details.

Fields:

Document Type

For display only.



Note: You can only enter this field if you are adding a new Document Type. If you want to change the name you have to delete the old Document Type and create a new one.

Description

You can enter any text here. This is intended for your internal administration and is not seen by the System 21 Explorer user. You would probably want to use the same text as that used for the Short Description.

Short Description

Use 15 characters only. This is the description which is seen by the System 21 Explorer user.

Business Sector

Not used.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Edit Properties Window



To display this window select the Properties option from the Workspace Menu for a Business Process or Activity.

The screenshot shows a standard Windows-style dialog box titled "Edit Properties". It has a blue title bar with a close button (X) on the right. The dialog contains three text input fields. The first field is labeled "Name" and contains the text "Ae3". The second field is labeled "Business Process Code" and contains the text "AE3". The third field is labeled "Description" and is currently empty. At the bottom of the dialog are two buttons: "OK" and "Cancel".



Warning: Please be aware that the details you enter here relate to the entire Business Process or Activity.

You can enter details for the Business Process or Activity.

Fields:

Name

Name of the Business Process or Activity. This is also displayed on the title bar.

Business Process Code or Activity Process Code

The unique code for the Business Process or Activity.

Description

Your description. This is displayed on the tooltip, against the symbol on the Workspace, for the Business Process or Activity.



Note: You only see the symbol for a Business Process when Business Processes are nested.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

End Details Window



To display this window select Edit on the End Condition pop up menu.

You can define all the conditions relating to the end of the Business Process or activity, when you exit via this particular End Condition.



Note: Your Business Process, Subassembly or activity can have more than one End Condition Process Control tool and therefore more than one route out of the process. An Activity List has to have only one End Condition.



Note: That the Start Details Window enables you to set conditions for the entire Business Process or activity.

Fields:

Name



Warning: This is not the name of the process. The name you enter here becomes the node name for the process in the next level up in the hierarchy.

End Condition

These are the conditions which are satisfied when you exit via this node.

Process Code

You cannot use this field.

Document Type

You cannot use this field.

Description

Your description for this end condition.

Default Start Node For This Document Type

You cannot use this field.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Escalation Windows

What does Escalation And Delegation mean?

Escalation And Delegation means either moving items from one user's Action List on to another user's Action List or moving items up or down the same Action List. You use this Escalation And Delegation Window to define rules to govern the criteria for moving these items.



Note: You use the Action List panel on the Execution Details Window to determine which users are the first to receive the items in their Action Lists.

Escalation means moving an item from one user's Action List to another user's Action List after a period of time. You could use this, for example, if a manager wanted to pick up all activities outstanding after a period of time. Escalation can also be used to give an item a higher or lower priority after a period of time so that it moves higher or lower up the same Action List.


Delegation means moving an item automatically from one user's Action List to another user's Action List. You could use this where someone was on holiday or absent for a period of time so that the items would appear only in the Action List of the user who was taking over that activity.

There are two windows to use:

- First use the Escalation And Delegation Window to maintain the Escalation Rules.
- Secondly use the Add Or Edit Escalation Rules Window to add or edit a single rule.

Escalation And Delegation Window

-  To display this window select Escalation And Delegation on one of the following menus:
- Work Management Menu
 - Component Browser Area Pop Up Menu, for a component
 - Elemental Activity Pop Up Menu
 - Workspace Pop Up Menu.



How to use this window

On this window there is a list of Escalation Rules on the design-time database on your PC. The extent of this list varies depending on the context from which the Escalation And Delegation option was selected. For example, if you select Escalation And Delegation from the Work Management Menu then this list shows all the rules on the design-time database, whereas if you select Escalation And Delegation from a component in the Component Browser Area then only the rules relating to the component are displayed.

You can have multiple rules governing the moving of the same activity. The order of the list presents you with an image of how those rules will be applied, whereby the first rule to be applied will be at the top of the list. Below the list is a descriptive area where you can see an explanation for the rule which you select from the list. You can use the buttons to maintain the list details.

How the Engine uses these rules

Each time the Work Management Engine processes an activity it makes a note of the Business Process Code, Activity Code and Priority and checks the Escalation And Delegation rules for a match. It notes all the rules where there is a match, sorts them according to Time Limits and processes the ones specifying the least amounts of time first. For example, you could move an item higher up an Action List after five hours, but then move it on to another user after two days.

You can delegate an activity by giving it a Time Limit of zero, thereby making the item move automatically from one user's Action List to another user's Action List.

If there are no time limits specified within the rule or if there are two rules with the same time limit then the Work Management Engine sorts according to descending Priority order, processing the ones with Urgent priority first.

If there are no time limits or Priorities specified within the rule, or if there are two rules with the same time limit and priority then the Work Management Engine sorts according Role or User and then Activity and finally Business Process provided that these are specified.

These are the criteria by which rules are sorted to enable Escalation And Delegation:

Sort Order	Criteria	Comment
First	Time in days, hours and minutes	Ascending order. Any rule with a zero time is evaluated first and this becomes a Delegation
Second	Priority	Descending: Urgent, High, Medium and then Low.
Third	Role and User	Where the Role or User is specifically named this rule is processed first.
Fourth	Activity	Where the activity is specifically named this rule is processed first.
Fifth	Business Process	Where the Business Process is specifically named this rule is processed first.

Fields:

Time Limit

The length of time the activity will remain as an item on the Explorer user's Action List before being escalated. A zero time limit results in an automatic delegation.

Bus Process

Business Process Code. The Work Management Engine matches this rule against any activity within the Business Process which has this Business Process Code.

Activity

The Activity Code. The Work Management Engine matches this rule against any activity with this Activity Code. Note that for a Manual Activity this is always MANACT.

No

Each component of a Business Process has an element identification number. Usually these numbers are hidden but you can display them on the Workspace by checking the box called Include Element Numbers On Captions on the Preferences Advanced Panel.

Recipient

This could be a Role, a User, an Email address, All Roles or All Recipients. This is the initial recipient.

Reassigned To

Enter the name of the Role, for example Account Clerk. This is the person who is to receive the escalated activity in their Action List.

Priority

This could be Urgent, High, Medium, Low or any. This is the priority of the Action List item before it is escalated.

New Priority

This could be Urgent, High, Medium, Low, Increase, Decrease or No Change. This is the priority of the Action List item after it is escalated.

Enter the name of the Role, for example Customer Account Manager. This is the person to whom the item is to be escalated.

Buttons:

Add

Displays the Add Or Edit Escalation Rules Window for you to create a new rule and add it to the list. The order in which the rules are displayed is the order in which the Work Management Engine will apply the rules. Your new rule will be slotted in to the existing list of rules in a position appropriate to its running order.

Edit

Displays the Add Or Edit Escalation Rules Window for you to edit details for the selected rule.

Delete

Prompts you to confirm that you wish to delete the rule you have selected. Once you confirm the deletion there is no recovery process.

Copy

You can copy the rule either to a file or to the clipboard.

Close

This closes the window without saving changes.

Add Or Edit Escalation Rules Window



To display this window select Add or Edit from the Escalation And Delegation Window.

You can add a new Escalation Rule or edit the details for a single Escalation Rule. The availability of some of the fields on this window depends both on the context from which the window was selected and on whether you are adding a new rule or editing an existing one. For example, if Business Process Ae3 is currently displayed on the Workspace and the Escalation And Delegation option selected from the Workspace pop up menu, and then you choose to Edit a rule, the Business Process Code will say AE3 and you will not be able to change it.

The fields at the top of the window are for you to identify the activities for which the Escalation and Delegation rules are applicable. The Recipient Details Panel is for you to identify the user(s) from whom the Action List entry is to be escalated or delegated. The Reassignment Details Panel is for you to identify the user(s) to whom the Action List entry is to be escalated.



Note: When a rule has been created you cannot change the Business Process, Activity Code, Recipient or Time Limit, for which it is applicable. If these two details are incorrect you must delete the rule and create a new one.

Fields:

Business Process Code

The Work Management Engine matches this rule against any activity within this Business Process. If you select Escalation And Delegation from the Work Management Menu, and then choose to Add a new rule, this field will say All.

All Process Codes

Check this box if you want the rule to apply to all Business Processes.

Activity Code

The Work Management Engine matches this rule against any activity with this Activity Code. Note that for a Manual Activity this is always MANACT.

If you select Escalation And Delegation from the Workspace Menu for a particular Business Process, and then choose to Add a new rule, this field will say All.

All Activity Codes

Check this box if you want the rule to apply to all Activities.

Selected Instance Only

A Business Process often has more than one Activity with the same Activity Code. This is especially true where there is more than one Manual Activity because Manual Activities always have an Activity Code of MANACT. In this case you can identify an individual instance of the same activity.

This field is available only if you select Escalation And Delegation from the right click menu for the symbol on the Workspace.

Element Number

Each component of a Business Process has an element identification number. Usually these numbers are hidden but you can display them on the Workspace by checking the box called Include Element Numbers On Captions on the Preferences Advanced Panel.

This field is available only if you have checked the Selected Instance Only box, which in turn is only available if you select Escalation And Delegation from the right click menu for the symbol on the Workspace.

Recipient Details Panel

The Recipient is the person who is scheduled to have the item initially, before Escalation And Delegation takes place.

Type

This could be All Recipients, Role, All Roles, User or All Users. Note that you cannot enter Email for the Recipient Type but you can do so for the Next Recipient Type.

Recipient

Enter the name of the Role or User. This is the person who is scheduled to have the item initially. This field is available only when the Recipient Type is Role or User.

Priority


This could be Normal, High or Low.

Time Limit

You can Delegate or Escalate. If you Escalate you also have to enter a time limit. This is in the format hours and minutes (HH:MM). If you select Delegate then the Time Limit is always zero.

Reassignment Details Panel

Select the person to whom the item is to be escalated.



The dialog box is titled "Add Escalation Rule" and contains the following elements:

- Business Process Code:** A dropdown menu with "[All]" selected and a checked checkbox labeled "All Process Codes".
- Activity Code:** A dropdown menu with "[All]" selected, a checked checkbox labeled "All Activity Codes", and an unchecked checkbox labeled "Selected Instance Only".
- Buttons:** "OK" and "Cancel" buttons are located to the right of the dropdowns.
- Element No.:** A text input field.
- Tabs:** "Recipient Details" and "Reassignment Details". The "Recipient Details" tab is active.
- Recipient Details Section:**
 - Next Recipient Type:** A dropdown menu with "Role" selected.
 - Next Recipient:** A dropdown menu.
 - Priority Change:** A dropdown menu with "(No change)" selected.
- Description:** A text area at the bottom containing the text: "After 01:00 hours, escalate all activities in all business processes from All Roles to Role (Any)".

Next Recipient Type

Select Role, User, Email or No Change. This is the type of person to whom the item is to be escalated.

Next Recipient

Select the person to whom the item is to be escalated.

Priority Change

Use this when you want to determine the priority of the item after it has been escalated.

This is particularly useful for changing the priority of an Action List item and moving it up or down the same Action List. In which case the Next Recipient Type would display the No Change option.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Execution Details Window



To display this window select Edit on the Business Process Link pop up menu.

You can schedule an Elemental Activity, or Manual Activity, within a Business Process by clicking on the connection in front of the activity. A symbol is placed on the connection to indicate the type of execution for which the activity has been scheduled.

There are three subpanels on this window:

- Schedule
- Roles
- Activity List.

However, not all the panels are available to you at once. Their availability depends on the Schedule Type Selected.



Tip: It is important to understand how the Schedule Type selected governs the whole of this window.

Schedule Type Field

This is a radio button field which enables you to select the type of schedule you want. However, please note that:

- Not all options are available to you
- The option you choose determines which subpanels will be made available to you.

Note which type of activity you are scheduling:

- For a Manual Activity the Schedule Type defaults to User Controlled
- For an Elemental Activity the choice you have is governed by the Execution Modes listed on the Properties Work Mgt Panel for the Activity which you are selecting.

There are four Execution Modes which JBA have predefined (10, 20, 30 and 40) and you may have others which you have created yourself and which are also selected on the Properties for the activity.



Warning: If you are not happy with the options available to you, do not be tempted to change the Properties for the activity without taking advice from your JBA consultant. In most cases properties are defined by JBA and are stored on your database. It is unlikely that you should need to change them. Please bear in mind that when you edit the Properties Window you are also updating the design-time database.

The Execution Modes listed in the Properties determine your choices here:

10 - User Controlled

User Controlled means that the user intervenes in the execution of the process by making a decision about which pathway the processing will follow. For example by choosing whether to contact a customer about a failed credit check or cancel the order.

For an Elemental Activity the button is enabled and the Roles panel and Action List panel are enabled.

For a Manual Activity the button is disabled and only the Action List panel is enabled.

There are three ways to send notification to another user, within the organisation, that they are to complete the next task in the Business Process. You determine this by using the Recipient Type field on the Action List panel.

The three choices are represented as follows:

- Email: This is where an Email is sent to the user's PC.

Schedule Type

☒ User Controlled ☐ Automatic Batch ☐ Other

☐ Automatic Immediate ☐ Scheduled Batch

- User: This is where the activity to be completed by the user is sent to their Action List.

Schedule Type

☒ User Controlled ☐ Automatic Batch ☐ Other

☐ Automatic Immediate ☐ Scheduled Batch

- Role: This is where the activity to be completed is sent to the Action Lists of all users with particular role.

Schedule Type

☒ User Controlled ☐ Automatic Batch ☐ Other

☐ Automatic Immediate ☐ Scheduled Batch

20 - Automatic Immediate

Automatic Immediate means the execution of the process will continue automatically.

☐ User Controlled ☐ Automatic Batch ☐ Other

☒ Automatic Immediate ☐ Scheduled Batch

None of the subpanels are enabled.

30 - Automatic Batch - submits to a single thread job queue

Automatic Batch means the execution of the process will continue automatically but will form part of a queue of batch jobs.

☐ User Controlled ☐ Automatic Batch ☐ Other

☐ Automatic Immediate ☒ Scheduled Batch

None of the subpanels are enabled.

40 - Scheduled Batch

Scheduled Batch means the execution of the process will continue as part of a queue of batch jobs scheduled to start at a certain time.

☐ User Controlled ☐ Automatic Batch ☐ Other

☐ Automatic Immediate ☒ Scheduled Batch

Only the Schedule panel is enabled.

?? - Other (ones you maintain yourself)

The Other option is available only if you have defined your own execution modes.



Tip: If you want your own Execution Mode then you have to create one using the Execution Modes option on the Work Management menu. Once created this new entry will be included on the drop down list in the grid box on the Properties Work Mgt Window and this in turn will enable the Other option on this Execution Details Window. However, please do not do this without consulting your System Administrator because you will be updating the database for everyone.

Multiple Object Processing Field


This field is available only if the field, with the same name, is checked on the Maintain Execution Mode Window.

Check this box where you want to process more than one Document Type within a process.

Schedule Panel



Note: The Schedule panel is only enabled if you select Scheduled Batch for the Schedule Type. If this option is also not available to you it means that there is no scheduled Execution Mode defined for the Activity. Go into Properties Work Mgt Window for the Activity and define an Execution Mode 40.



This displays a schedule which has previously been defined. Use the Change button to change this schedule for another.


Change Button

Displays the Select Schedule Window for you to select a schedule from a list, for this particular activity.

Roles Panel



Note: The Roles panel is only enabled if you select User Controlled for the Schedule Type. If this option is also not available to you it means that there is no scheduled Execution Mode defined for the Activity. Go into Properties Work Mgt Window for the Activity and define an Execution Mode 10.



Note: When the Roles panel is enabled than the Action List panel is always enabled too.

There are two lists here. Use the arrow buttons in the centre of the panel to move roles between lists.

You can give Role users access to the activity which you are scheduling.

All Roles

Lists all the roles from which you can choose.

Roles Having Access To This Activity

Lists the roles which you choose to have access to the activity.



Note: This list is then used to form the list in the Recipient field on the Action List panel.

Action List Panel



Note: The Action List panel is only enabled if you select User Controlled for the Schedule Type. If this option is also not available to you, or not already selected as is the case for a Manual Activity, it means that there is no scheduled Execution Mode defined for the Activity. Go into Properties Work Mgt Window for the Activity and define an Execution Mode 10.

Use this panel to determine the criteria for sending items to Action Lists. Each item on the list represents an Activity.

You use this panel to determine which users are the first to receive the items in their Action Lists. However, please note that you can also move these items on to other users' Action Lists, for example if the user is on holiday, or if the item has been waiting on the Action List for a specified time. You define rules to govern the criteria for moving these items. This process is called Escalation And Delegation and you define the rules on the Escalation And Delegation Window.

Fields:

Recipient Type

You define which method is to be used for prompting the user that the activity is outstanding:

- Email: This is where an Email is sent to the user's PC.
- User: This is where the activity to be completed by the user is sent to their Action List.

- **Role:** This is where the activity to be completed is sent to the Action Lists of all users with a particular role.

Document Type

This is the Document Type carried forward along the connection line and into the activity. You cannot change it.

Recipient

You determine who gets the notification.

The contents of the list varies depending on what the Recipient Type is and whether you choose Static or Data Field.



Note: The Data Fields are set up in Constructor using the Data Field option on the Work Management Menu.

User

If you have a Recipient Type of User and you select Static then you select users from the list for this field.



Note: These users are set up in System 21 Explorer using the User Role Maintenance facility.

If you have a Recipient Type of User and you select Data Field then you select Data Fields from the list for this field. You see here only those Data Fields with a Usage of User.

Role

If you have a Recipient Type of Role and you select Static then you select roles from the list for this field.



Note: These are the roles which are set up in the Roles Panel.

If you have a Recipient Type of Role and you select Data Field then you select Data Fields from the list for this field. You see here only those Data Fields with a Usage of Role.

You are saying that you want the Activity to be scheduled so that all the users, who log on with access to this role, will get notified via their Action Lists that this activity is outstanding. Then when one of the users actions this activity it will then be disabled for all the remaining users.

Email

If you have a Recipient Type of Email and you select Static then you enter an Email address.

If you have a Recipient Type of Email and you select Data Field then you select Data Fields from the list for this field. You see here only those Data Fields with a Usage of Role.

Priority

When you send a notification to an Action List under normal conditions the item will be added to the bottom of the list. However, you can use this field to give each one a priority:

If you choose Static then you choose as follows:

- High moves an item to the top of the list
- Low keeps an item at the bottom of the list
- Normal adds an item to the end of the list but it moves up the list in turn.

If you choose Data Field then you select Data Fields from the list for this field. You see here only those Data Fields with a Usage of Priority. The Data Field will hold a numeric value which is then used to prioritise the Action List with the highest numbers being moved to the top of the list.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Execution Modes Windows


There are three windows:

- Execution Modes Window where you can view the file of Execution Modes
- Maintain Execution Mode Window where you edit or delete Execution Modes
- Add Execution Mode Window.

Execution Modes Window



To display this window select the Execution Modes option on the Work Management menu.



You can view the file of Execution Modes. This file is global and can be used for all applications. Use the Add and Edit buttons to maintain the file. Use the Edit button to delete.

The Execution Modes which JBA have predefined are listed as follows, but you can add others to this list:

- 10 - User Controlled.
- 20 - Automatic Immediate.
- 30 - Automatic Batch - submits to a single thread job queue.
- 40 - Scheduled Batch.

Fields:

Execution Mode

A two character numeric code.

Description

Describes the Execution Mode.

Short Description

15 Characters only.

Multi Object Processing

Yes or No indicates the ability, or not, to process more than one Document Type within a process.

Buttons:

Add

Displays the Add Execution Mode Window.

Edit

Displays the Maintain Execution Mode Window.



Tip: You can make changes or Delete from here.

Close

You are prompted to confirm that you want to save any changes before closing the window.

Maintain Execution Mode Window



To display this window select Edit on the Execution Modes Window.

You can make changes to, or delete, Execution Modes.



Warning: You cannot make changes to predefined modes: 10, 20, 30 and 40.

Fields:

Execution Mode

For display only.

Description

Describes the Execution Mode.

Short Description

15 Characters only.

Multi Object Processing

Check this box where you want to process more than one Document Type within a Business Process.

Submission Details

Job Queue

To which queue do you want to submit the job?

Library

To which library do you want to submit the job.

Wait Time

Not available.

Relates only to Execution Mode 40.

Buttons:

OK

Close the window and save the changes to a temporary file so that they are reflected in the list on the Execution Modes Window. You can then use the Close button on the Execution Modes to save the changes to the database.

Delete

Deletes the Execution Mode from a temporary file so that the change is reflected in the list on the Execution Modes Window. You can then use the Close button on the Execution Modes window to confirm the deletion from the database.



Note: You cannot delete predefined modes.

Cancel

Close the window without saving the changes.

Add Execution Mode Window



To display this window select Add on the Execution Modes Window.

You can add to the file of Execution Modes. This file is global and can be used for all applications.

Fields:

Execution Mode

Enter a two character numeric code. Note that 10, 20, 30 and 40 are predefined.

Description

Describes the Execution Mode.

Short Description

15 Characters only.

Multi Object Processing

Check this box where you want to process more than one Document Type within a Business Process.

Submission Details

Job Queue

To which queue do you want to submit the job?

Library

To which library do you want to submit the job?

Wait Time

Number of seconds that you want the System 21 Interface to wait before initiating the process.
Currently available only for Execution Mode 40.

Buttons:

OK

Close the window and save the changes to a temporary file so that they are reflected in the list on the Execution Modes Window. You can then use the Close button on the Execution Modes to save the changes to the database.

Delete


Unavailable.

Cancel

Close the window without saving the changes.

Export Selection Window

 To display this window select Export on the File Menu.



This gives you a view of all Business Processes, Assembled Activities, Subassemblies and Activity Lists on your design-time database. You select items to export.

 **Warning:** *This list does not include Elemental Activities; this is because you cannot export or import these directly. However, you could create a Business Process, containing Elemental Activities, and export the Business Process.*

 **Note:** *When you Export or Import a Business Process all the associated components are copied with it, for example any associated Document Types or Data Fields.*

Fields:

Export As Individual Files

Unchecked

If this box is by default left unchecked you can create a single compressed standalone file, with a .con extension, from one or more files on the design-time database. This standalone .con file can then be sent, for example by Email, to another user connected to a different server. In this way you can use Export and Import to move Business Processes from one server to another.

Checked

If this box is by checked you can create individual standalone files, from one or more files on the design-time database.

Check this box to create export files in any of the following formats:

- Business Process Files (.bpr)
- Assembled Activity Files (.act)
- Activity List Files (.tsk)
- Subassembly Files (.sas).

These standalone files can then be sent, for example by Email, to another user.

Use this primarily for giving another Explorer user your Assembled Activities and Action Lists, where these will then appear on the user's Application Browser Area. This is the procedure:

1. Design the Assembled Activity (*.act), or Action List (*.tsk) in Constructor.
2. Export the .act or .tsk file, with the Export As Individual Files box checked.
3. Email the file to the new user.
4. Check the System Configuration File Paths Window on the new user's PC and note the folder in the Processes And Activity Lists Field.
5. The new user receives the Email and detaches the .act or .tsk file to the folder you noted in step 4.
6. The new user then opens Explorer and the Assembled Activity or Action List appears in the Application Browser Area and they can then execute it.

Buttons:

Export

You enter the location and name for the export file. If you select more than one file to be exported, and check the box called Export As Individual Files, then Constructor displays each file in turn for you to enter location and name details.

Close

This only closes the window. The export file has already been created and saved by the time you reach this point.

Import Files Windows


There are several Windows to complete:

- Import Files (Empty) Window
- Import Files (Select File) Window
- Import File (List Files) Window
- File Properties Window
- File Contents Window
- Progress Window.

Import Files (Empty) Window



To display this window select Import on the File Menu.



The window is empty at first. You have two choices only: you can click Add to display the Import Files (Select File) Window or Close to leave without importing any files.

Import Files (Select File) Window



To display this window click Add from the Import Files (Empty) Window



Note: This is a standard Microsoft Open File Window format.

You select the file(s) to be imported and click Open.


Files of the following formats can be imported:

- Business Process Files (.bpr)
- Assembled Activity Files (.act)
- Activity List Files (.tsk)
- Subassembly Files (.sas)
- Export Files (.con).

Import File (List Files) Window



To display this window click Open from the Import Files (Select File) Window



The file you import is listed in the window. You can then use the buttons as follows.

Buttons:

Add

You can then choose to add another file to the list. This displays the Import Files (Select File) Window

Delete

Deletes a file from the list. This does not delete the file itself.

Properties

Displays the File Properties Window

Import

When you click Import the copying then begins.


Close

Close the window without importing.

File Properties Window



To display this window click Properties from the Import Files (List Files) Window



This displays the properties and you can use the buttons as follows.

Buttons:

Contents

Gives you a logical breakdown of the files properties.


Close

Return to the File Properties Window.

File Contents Window



To display this window click Contents from the File Properties Window.




You can view the breakdown of the Properties as you would in Constructor's Component Browser Area and then click Close.

Progress Window



To display this window click Import from the Import File (List Files) Window



This shows you each element of the file which you have selected to copy. It lists the elements and puts a tick alongside each one as it is copied to the design-time database.

If these elements already exist on the design-time database, you are prompted to confirm the action and then they are overwritten. A message displays when the import is complete.



Note: When you Export or Import a Business Process all the associated components are copied with it, for example any associated Document Types or Data Fields.

Buttons:

Close

This Closes the window. The files have already been saved at this point.

Initialise Data Exchange Area Window



To display this window select Initialise Parameters on the Start Condition pop up menu.

The screenshot shows a window titled 'Initialise Data Exchange Object'. It has a 'Variable details' section with 'Name' and 'Value' text boxes, a 'Type' section with 'Integer' and 'String' radio buttons, and 'Add' and 'Remove' buttons. Below this is a table with columns 'Name', 'Value', and 'Type'. The table contains one row: 'CONO', 'Z1', 'String'. At the bottom are 'Save' and 'Cancel' buttons.

Name	Value	Type
CONO	Z1	String

You can add to the list of Data Exchange Area variables.



Warning: *This window is intended for JBA developers only.*

Fields:

Variable Details

Use these details in conjunction with the list view at the bottom of the window. Enter new variable details here, press the Add button and they will appear at the bottom of the list view below. To remove a variable you have to select it first in the list view and then press the Remove button to remove it from the list.

List View

Name

Name of the variable in the Data Exchange Area.

Value

Enter the value which you want to be set for testing purposes.

Type

Choose whether the variable is to be stored as an integer or a string.

List View

This list displays how many variables there are associated with the start of the process.

Buttons:

Add

Enter new variable details, press the Add button and the details will appear as a new line at the bottom of the list view.

Remove

To remove a variable you have to select it first in the list view and then press the Remove button to remove it from the list.

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Local PC File Or Program Window



To display this window select the New\PC Program option from the Workspace Menu when working with a Business Process.

You can create a symbol on the Workspace to represent a PC program. This could be a Microsoft program for example or a bespoke program.

Fields:

Name

This name will appear alongside the symbol.

Description

This will be on the tooltip.

File Path

This is the location of the program file. Use the three-dots button to browse.

Startup Folder

This is the folder where the program's .EXE file is located. Use the three-dots button to browse.

Startup Style

You decide how the program is to be displayed on the screen.

Save Definition To Palette On Exit

If you check this field you are then able to copy symbols from one design to another. You can copy an activity to the clipboard and the name of the activity appears in the list of activities in the Component Browser Area. Then you can drag it out to another Business Process on the Workspace.

Buttons:

OK

Save the changes and close the window.


Cancel

Close the window without saving the changes.

Menu Consumable Details Window



To display this window click with the right mouse button on an item in the Selected Options list on the Design Menu Window. This displays the Design Menu Options Menu. Then select the Consumables option.



You are creating a menu for the user to use at runtime and have selected a constructable to become an option on this menu. Here you can determine which consumables are to be used by the constructable.

Fields:

Available Consumables

A list of consumables available for you to choose from. You drag them across to the Defined Consumables list.

Defined Consumables

A list of consumables which you have chosen and which then become used by the component.

Buttons:

OK


Save the changes and close the window.

Cancel

Close the window without saving the changes.

Node Mapper Window

- ➡ To display this window attempt to replace one symbol on the Workspace with another, either by copying and pasting or by dragging and dropping. Constructor asks you if you want to replace one symbol with another and if you reply Yes then this Window is displayed.



This contains a JBA grid box with two columns listing the old and new Node Exit Names belonging to the existing symbol on the Workspace and its replacement. If both symbols have an equal number of exit points then you might just want to confirm the Nodes. If not then you might want to re-map the nodes to make sure that you still have correctly defined exit points for the newly placed symbol. Constructor attempts to match replacement nodes where possible.

There are no fields and only an OK button.

Select the OK button to confirm the mapping.

Parallel Path Window



To display this window select Edit on the Parallel Path pop up menu.

The screenshot shows a dialog box titled "Parallel Paths". It has a "Description" field containing the text "Inform Customer". Below this is a "Nodes" section containing a list box with three items: "Parallel Path 1", "Parallel Path 2", and "Parallel Path 3". "Parallel Path 2" is currently selected and highlighted with a yellow background. Below the list box is a large, empty grid area. At the bottom of the dialog are two buttons: "OK" and "Cancel".

You can enter decision pathway details. All parallel pathways are processed simultaneously.



Note: These details are not uploaded to Work Management.

Fields:

Description

Name of the Parallel Path which you can now change.

Node

This is a grid box. Enter a name for each parallel pathway. These are displayed on the tooltips.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Preferences Window



To display this window select Preferences on the Edit menu.

These are the panels:

- General
- Advanced
- Paths.

Buttons:

System Configuration

Launches the System Configuration utility.

OK

Save the changes and close the Window.


Cancel

Close the Window without saving the changes.

Preferences General Panel



To display this panel select Preferences on the Edit menu and then select the General panel.



You can maintain your general design options.

Fields:

Default Text Position

Choose the position for the text for a symbol on the Workspace; whether to put it above or below the symbol.

Auto Zoom Extents On Open

Check this box to enable Constructor to automatically make a single zoom, every time you drop a new Business Process or activity onto the Workspace, so that the entire design fits into its own window. However, if you then maximise the window, the actual size of the design will remain the same. If you want it to expand, when you maximise, so that it fits into the Workspace you must also check the Auto Zoom Extents On Restore field.



Note: This is the same as the Zoom Extents button on the toolbar but this works automatically.

Auto Zoom Extents On Restore

Check this box to enable Constructor to automatically expand the design when you maximise the Workspace. Constructor works out the extent of the zoom for you so that the entire design fits onto the Workspace. If this box is not checked then the design remains the same size, even though you maximise the Workspace.

Open Full Screen

Check this box to close the Component Browser Area when you open a design on the Workspace, so that the design covers the whole screen from left to right.

Auto Arrange

Check this box for Constructor to automatically arrange the design on the Workspace for you, every time you drop a new component onto the Workspace, without you having to click the Arrange button on the toolbar each time.

Show Descriptions As ToolTips

Check this box to display the components' descriptions as tooltips on the Workspace.

Execute Function if it Exists

Use this when you are first creating an activity and you do not want to execute the function behind it. If you leave this box unchecked then Constructor will never try to execute the function and will instead display the Properties Details Panel for you. When you are more confident about your design then you can check this box and forget about it.

However, if you check this box and the function does not exist then Constructor will display the Properties Details Panel instead.

Use White Background

Change the Workspace background from grey to white.


Auto Orthogonal

Make any connections display with right-angles rather than cut across any symbols.

Preferences Advanced Panel



To display this panel select Preferences on the Edit menu and then select the Advanced panel.



You can maintain your advanced design options.

Fields:

DEA Protocol

Enter the type of protocol you want to use for Constructor. Use upper case letters.

The default is TCP.



Note: To enter any pathways, use the Preferences Paths Window.

Wrapping Width

Specify how many characters in width you want to allow for the text above, or below, each symbol on the Workspace.

Include Element Numbers On Captions

Each component of a Business Process has an element identification number. Usually these numbers are hidden but you can display them on the Workspace by checking this box. These numbers can be entered on the Escalation And Delegation Windows.

Preferences Paths Panel




To display this panel select Preferences on the Edit menu and then select the Paths panel.



Note: The fields on this Panel each have a button at the end. If the button is available to you this means you can edit the path.



Warning: The first four fields on this Panel are always greyed out. This is because they are for viewing purposes only. They display Paths which have been set using Explorer's System Configuration utility. However, the button at the end of the field takes you into System Configuration and you can change the path if you need to. The changes you make will be reflected on this panel only when you restart Constructor.



You can maintain the file pathways details.



Note: To choose a protocol for Constructor you select Edit\Preferences from the Main Menu Bar and then select the Advanced panel.

Fields:

Database path

View System Configuration's path to the company wide .mdb database files holding the design details. The accompanying button takes you into Explorer's System Configuration utility if you need to change it.

Cloud Manager Location

View System Configuration's path to the Data Exchange Area program. You cannot change it.

Role Files Path

View System Configuration's path to the Role files. The accompanying button takes you into Explorer's System Configuration utility if you need to change it.

File Path(*.act,*.bpr,*.tsk)

View System Configuration's path to the files containing Activities (.act files), Business Processes (*.bpr files) and Activity Lists (*.tsk files). The accompanying button takes you into Explorer's System Configuration utility, if you need to change it.

Server Path

The name of the machine from where the Data Exchange Area will be run. This could be local or remote. The default is localhost which means the Data Exchange Area resides on your own machine. You can use the accompanying button to enter another server name to run from a remote Data Exchange Area.

Visual Basic Location

The path to the VB executable files. You will not be able to execute the processes and activities created by Constructor unless this pathway is completed. You can use the accompanying button to enter a new path.

VBP Path

The path to any Visual Basic applications. You can use the accompanying button to enter a new path.

Properties Window



There are several ways to display this window:
Select Properties on the Elemental Activities pop up menu.
Or: Select Properties on the Business Methods pop up menu.
Or: Select New\Component on the Workspace Menu.
Or: Select New\Elemental Activities on the Workspace Menu.
Or: Attempt to preview a Business Method or an Elemental Activity for which there is no corresponding component on the server or the PC. In this instance, the window is displayed for information only and you cannot change any field details.



Warning: In most cases properties are defined by JBA and are stored on your database. It is unlikely that you should need to change anything on this window. We strongly advise you not to do so without taking advice from your JBA consultant. The accuracy of the syntax is extremely critical because it is validated before the component can be executed. Please bear in mind that when you edit the Properties Window you are also updating the design-time database.



Note: The panels and fields available to you on the Properties Window varies depending on the context from which it was called. For example the Consumables Panel is available only when you select Properties for a Business Method.

You can maintain properties for the current process. Please refer to the Components Hierarchy Diagram.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Properties General Panel



To display this panel select the General tab on the Properties Window.

The 'Update Activity' dialog box has a title bar with a close button. It contains four tabs: 'General' (selected), 'Details', 'Advanced', and 'Work Mgt'. The 'General' tab contains the following fields: 'Name' with text 'Order amend', 'Description' with text 'Order amend' and a scroll bar, 'Menu Option' with text '2/AQP', and 'Input Document Type' with a dropdown menu showing 'Sales Order'. There is a checkbox labeled 'Work Management Enabled' which is checked. At the bottom are 'Ok' and 'Cancel' buttons.

The 'Properties for Updating Component' dialog box has a title bar with a close button. It contains four tabs: 'General' (selected), 'Details', 'Advanced', and 'Consumables'. The 'General' tab contains the following fields: 'Name' with text 'Sample - Order Header', and 'Description' with text 'Order header details' and a scroll bar. At the bottom are 'Ok' and 'Cancel' buttons.

This panel enables you to define the general properties.

Fields:

Name

The name of the Elemental Activity or Business Method, to be displayed on the Workspace alongside the component.

Description

The description of the Elemental Activity or Business Method to be displayed:

- As a tooltip when you place the cursor over the component without clicking, provided that the Show Descriptions As Tooltips field, on the Preferences General Panel, is checked.
- As a pop up when you select Description from the pop up menu for the component.



Note: The remaining fields on this panel are available for Elemental Activities only.

Menu Option

This is the shortcut code for the activity. For example, for Order Amend this would be 2/AOP.

Type

These option buttons enable you to choose between an Assembled Activity or an Elemental Activity.



Warning: When updating an Elemental Activity this option button has Elemental selected by default. If you then change it to Assembled please note that you will not be able to change it back again. This is because an Assembled Activity does not have a Properties option in its pop up menu. If you changed it by mistake to Assembled you would need to delete the Assembled Activity and recreate an Elemental Activity.

Input Document Type

This is the Document Type with which you initiate the activity. If there is no initial Document Type for the activity, for example as in a Sales Order Entry activity where perhaps a telephone call starts off the process, then you can leave this field blank.

Work Management Enabled

Check this box if you want to be able to upload the Elemental Activity as part of a Business Process. This enables the Properties Work Mgt Panel so you can enter the details needed by the uploading software.




Warning: The Elemental Activity will not pass validation checks without these details.

Properties Details Panel




To display this panel select the Details tab on the Properties Window.



The 'Properties for Updating Activity' dialog box has five tabs: General, Details (selected), Advanced, Work Mgt, and Overrides. The Details tab contains an 'Attributes' section with three radio buttons: 'Constructable only' (selected), 'Consumable only', and 'Constructable and Consumable'. Below this is a 'Nodes' table with five columns: Node, Description, Business object, Completion Action, and an empty column. The table contains one data row: 'Order releases from suspension', 'SALESORDER', and an empty 'Completion Action' cell. The bottom of the dialog has 'Ok' and 'Cancel' buttons.

Node	Description	Business object	Completion Action	
	Order releases from suspension	SALESORDER		



The 'Properties for Updating Component' dialog box has four tabs: General, Details (selected), Advanced, and Consumables. The Details tab contains an 'Attributes' section with three radio buttons: 'Constructable only' (selected), 'Consumable only', and 'Constructable and Consumable'. Below this is a 'Nodes' list box containing the text 'OK', 'Previous', and 'Cancel'. The bottom of the dialog has 'Ok' and 'Cancel' buttons.

This panel enables you to define the constructable and consumable properties.

Fields:

Attributes

This option button determines whether the component is to be a Constructable or a Consumable or both.

Nodes

This varies depending on whether you are defining the Properties for an Elemental Activity or a Business Method.

For a Business Method

This is a list of node descriptions. For example: OK, Previous, Cancel.

Displayed in the nodes tooltips on the Workspace.

For An Elemental Activity

This is a grid box. If you click with the right mouse button you display the Properties Grid Pop Up menu.

You enter the node details for the buttons which are to be displayed on the window for the component. Each entry you make will be reflected in the nodes shown on the symbol for the component. For example this symbol has two nodes shown to the right of the circle and this would be reflected by two rows in the grid box.



You can use each node in your design to link to other components.

Node

This is the two character numeric completion code. The default is blank: use this for a standard route through the Business Process where there are no problems, for example where an invoice prints correctly. Use the numeric code where there is a failure, for example where there is a failed invoice print.

Description

Description of the node, for example: Invoice Printed or Invoice Failed. Displayed in the tooltips.

Document Type

Valid Document Type name to be used by the node, for example INVOICE.

Completion Action

You can safely ignore this field in most cases. Use this only where you want to define special processing for the completion node.

Blank - no specific action to be taken and transaction completed.

1 - Cancel Transactions. This sets the Document Type to completed status and then cancels anything which is pending.

2 - Assign New Thread. This assigns a unique identifier to all the Document Types associated with this activity.

Properties Advanced Panel



To display this panel select the Advanced tab on the Properties Window.

The screenshot shows the 'Properties for Updating Activity' dialog box with the 'Advanced' tab selected. The dialog has five tabs: General, Details, Advanced, Work Mgt, and Overrides. The 'Advanced' tab contains the following fields: 'Function' (text box with 'SessionManager.Emulator OE 031070'), 'SourceFile' (empty text box), 'Parameters set' (empty list box with up/down arrows), 'Conditions' (empty list box with up/down arrows), 'Server' (empty text box), and 'UserId' (empty text box). At the bottom are 'Ok' and 'Cancel' buttons.

The screenshot shows the 'Properties for Updating Component' dialog box with the 'Advanced' tab selected. The dialog has four tabs: General, Details, Advanced, and Consumables. The 'Advanced' tab contains the following fields: 'Function' (text box with 'jbaOrderHeader1.OrderHeader1'), 'SourceFile' (text box with 'OrdHdr01'), 'Parameters set' (empty list box with up/down arrows), and 'Conditions' (empty list box with up/down arrows). At the bottom are 'Ok' and 'Cancel' buttons.

This panel enables you to define the more detailed properties.

Fields:

Function

Name of the OLE server or System 21 activity to execute the process.

Source File

Name of the VB project file.

Parameter Set

Contains a list of node settings and conditions which are satisfied when these exit points from the window are used during execution.

For example: OK = Customer Set. Consider a component which exists to set up a customer. If a Node setting in this component is called OK, and states that a Customer must be set up, then the fact that the user has pressed OK to exit from this component means that the Customer has to have been set up. The condition of the customer having been set up can then become an input condition for a subsequent component in the process.

There may be a setting called All Nodes = . If this is present it will contain a condition which is satisfied by all of the exit points from the component that can be used during execution.

Conditions

These are the conditions which have to be set up before you can execute this component. For example a particular field may need to be set up in the Data Exchange Area, or customer details may need to have been set up.



Note: All these condition details can also be viewed on the Conditions Window in fields called: Input Conditions; All Nodes; Node Setting; Unnamed.



Note: The remaining fields on this panel are available for Elemental Activities only.

Server

The name of the server on which the activity is to be executed.

User Id

Valid user logon.

Properties Work Mgt Panel



To display this panel select the Work Mgt tab on the Properties Window.



Note: This panel is available only when you define Properties for Elemental Activities.

Mode	Description	Processor	Processor type	Function
10	User invoked	OE 031070	TASK	

This panel is available only if the Work Management Enabled box has been checked on the General panel. Complete these details, in particular the Activity Code, if you want to be able to upload the Elemental Activity as part of a Business Process.

Fields:

Global Activity

Default is off. Check this box if you want the activity to be available across all applications.

Activity Code



Warning: The Elemental Activity will not pass the validation checks in the uploading software without this code.

10 character code in uppercase. This is the code which is written into the application program. For example: ENTORDADV for SalesOrderCreated.

Error Role

If an error occurs during a batch process then this role entered here is the one which will be notified via the Action List. The notification appears for all those users who are assigned to that role.

Execution Modes

This is a grid box. If you click with the right mouse button you display the Properties Grid Pop Up menu. You define all the Execution Modes which the activity supports.

Mode

A two character numeric code.



Note: To maintain Execution Modes you select Maintain Mode for the Properties Grid Pop Up menu. This displays the Execution Modes Add Or Maintain Window.

Description

Displayed for you when you enter the Mode.

Processor

11 character code:

1-2 Application identifier for example AO.

3-5 Environment Code for example SL.

6-7 Release Level for example 03.

8-11 Task Code defined in JBA Application Manager.

Processor Type

Enter TASK.

Function

Not used.


Properties Overrides Panel



To display this panel select the Consumables tab on the Properties For Updating Activity Window.



Note: This panel is available only when you define Properties for Elemental Activities.



This panel enables you to override the name of the activity when it appears in the users Action List. Note that the name on the Workspace remains the same as before.

Fields:

Activity Title

The new name to appear in the Action List.




Note: If you right click in this field you get a context sensitive pop up menu. Select Insert Data Fields to include Data Fields in the name on the Action List. To highlight, edit or delete one of these data fields you must first double click on it.

Properties Consumables Panel

 To display this panel select the Consumables tab on the Properties For Updating Component Window.

 *Note: This panel is available only when you define Properties for Business Methods.*



This panel enables you to maintain a list of consumable properties. These consumables hold no values at this point. For example: you might want to have a consumable for holding Tax Codes so that you could use the Consumable as a variable storage area, into which you can then move values of codes as appropriate for individual applications and local tax rules.

 *Note: To move values into Consumables you need the Consumable Details Window.*

Fields:

Name

A scrollable list of names of Constructables being used by this component. For example: VAT.

Description

A scrollable list of descriptions of Constructables being used by this component. For example: VAT Consumable.

Properties For Action Agent Window



This window has two modes of display:

1 - New mode

If you right click on the Workspace, when designing a Business Process, and select New\Action Agent from the Workspace Menu the window displays and you see only the Name, Document Type and Description fields. Document Type is unknown at this stage.

2 - Joined up mode

It is only when you join up the Action Agent to another component on the Workspace that the window expands to show the grid box for the node rules. You display the window in this mode by selecting Properties from the Action Agent pop up menu.

Properties for Action Agent

Name:

Document type:

Description:

Title overrides:

Cannot define exit node rules!
No valid document type can be inherited

Properties for Action Agent

Name: Credit Check Document type: SALESORDER

Description: Server executed Action Agent to check the percentage of the available credit limit that a customer has used.

Title overrides: Credit Checking is now taking place.

Define exit node rules

Code	Combination	Input Condition	Operator	Test Condition	Display Name	
01	1st Rule	Customer Credit Usage Percentage	>	100	Fail	
(Default)					Passed	
02	1st Rule	Customer Credit Usage Percentage	>=	75	Inform	
02	And	Customer Credit Usage Percentage	<=	100	Inform	

☐ Save definition to palette on exit

OK Cancel

An Action Agent is a hidden piece of programming. For example you could use an Action Agent to tell the Business Process how to handle credit checking after the processing for Order Entry. You would put an Action Agent called Credit Action Agent between Order Entry and Picking Notes.

The only indication the user has, that this programming is taking place, is the appearance of an entry in Action Tracker during execution. Use the Title Overrides field to give the user a meaningful message.

Fields:

Name

This says New Action Agent when you first display this window. You change it to a name to suit your design, for example Credit Action Agent.

Document Type

This field is disabled and says Unknown when you first display this window. A message displays below the field:

Cannot define Exit Node Rules! No valid Document Type can be inherited.

The field becomes enabled when you join up the Action Agent to another component on the Workspace.

Description

The text you enter here forms the tooltip for the Action Agent symbol on the Workspace.

Title Overrides

If you ignore this field the Explorer user will see the words 'Action Agent' displayed in the Action Tracker. You can enter text here to give the user a more meaningful message; for example, 'Credit Checking now taking place'.

Define Exit Node Rules

This is a grid box where you define the exit rules. In doing so you create a piece of programming function which is transparent to the user but determines how the Business Process proceeds from this point onwards through the design.

Code

You can have one or more rows for each exit node, and each row represents a rule. The value in the Code field represents the number of the exit node. For example, if the third node had two rules to condition it then you would see two rows and the Code field would be 3 in both cases.



Warning: A Default condition is set up for you. This represents the Code 1, the first exit node. Leave this as it is.



Note: Do not worry if the nodes are in the wrong sequence on the Workspace. You can later use the Resequence Links option from the pop up menu.

Combination

Where the row represents the first rule for an exit node then enter 1st Rule.

Where the row represents a further rule for an exit node then either enter And or enter Or.

Input Condition

Enter a Data Field name, a piece of text or a numeric value.

To enter a Data Field you click the three-dots browse button to display the Select A Data Field window. The value of the Data Field at runtime, together with the Rule, will be used to determine which node is used for the pathway through the Business Process.



Warning: If the Data Field you want does not appear in the browse list do not attempt to create it. Consult the person who manages your database.

Operator

This is an operand and these are your choices:

<	less than
<=	less than or equal to
=	equal to
>	greater than
>=	greater than or equal to
<>	not equals

Test Condition

Enter a Data Field name, a piece of text or a numeric value.

To enter a Data Field you click the three-dots browse button to display the Select A Data Field window. The value of the Data Field at runtime, together with the Rule, will be used to determine which node is used for the pathway through the Business Process.



Warning: If the Data Field you want does not

appear in the browse list do not attempt to create it. Consult the person who manages your database.

Display Name

The text you enter here forms the tooltip for the Node on the Workspace.

Save Definition To Palette On Exit

If you check this field you are then able to copy symbols from one design to another. You can copy an activity to the clipboard and the name of the activity appears in the list of activities in the Component Browser Area. Then you can drag it out to another Business Process on the Workspace.

Buttons:**OK**

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Properties For Manual Activity Window



There are two ways to display this window:
Select Properties on the Manual Activity pop up menu.
Or: Select New\Manual Activity on the Workspace Menu.

A Manual Activity is a way of allowing the user to have an input to the process. You could display a window with buttons so that the user could select an action. For example you could have a Manual Activity to enable the user to decide what to do about failed credit checks.

There are four panels:

- Details
- Message. Note that you can display the Select Button Window from this panel.
- Nodes
- Title Overrides.

Field Common To All Panels:

Save Definition To Palette On Exit

If you check this field you are then able to copy symbols from one design to another. You can copy an activity to the clipboard and the name of the activity appears in the list of activities in the Component Browser Area. Then you can drag it out to another Business Process on the Workspace.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Properties For Manual Activity Details Panel



To display this panel select the Details tab on the Properties For Manual Activity Window.

Manual Activity

Details | Message | Nodes | Title Overrides

Activity Description
Credit Check Failed - Contact customer

Input document type
SALESORDER ...

☐ Automatically complete when sent via Email

☐ Save definition to Palette on Exit

OK Cancel

Fields:

Activity Description

The default description is New Manual Activity followed by the date of creation. You can change this. This will be the name that is placed alongside the symbol on the Workspace.

Input Document Type

Select the Document Type from the list.



Warning: You must make sure that this Document Type matches the Document Type coming out of the previous component on the Workspace by checking the Properties for the previous component.


Automatically Complete When Sent Via Email

You must check this box if you are sending Manual Activities by Email. Otherwise the Action Tracker will permanently report this as 'pending', with a red icon, even when the Email has been sent.

Properties For Manual Activity Message Panel



To display this panel select the Message tab on the Properties For Manual Activity Window.



This message is what the user will see on the screen.

There are three types of text:


- The black text is actual text which the user sees, for example, Customer, which you type in.
- The red text is Variable Data, for example Customer Name which is stored as a Data Field. To insert red text fields use the right click menu and select Insert Data Field. If a field name does not exist then select the Maintain Data Field option and add to the list. However, please consult your Database Administrator because this will update the Properties details for everyone.
- The blue underlined text represents a button on the screen which the user can see and use. For example, Credit Manager Inquiry, which is a program. Add a button by selecting Insert Button on the right click menu. This displays the Select Button Window. This button represent a pathway which goes off at a tangent to the processing and does not interfere in any way with the logical flow through the Business Process. For example if the user pressed the Credit Manager Inquiry button then this would result in the Credit Manager Inquiry being run.

Defer button

Please note that in addition to the buttons defined here, there is a Defer Button which is always displayed for the user, as part of the Manual Activity process. This enables the user to leave the Manual Activity on the Action List, halted at this point, ready for later processing.




Note: The Message text also appears on the tooltips for the activities.



Properties For Manual Activity Nodes Panel



To display this panel select the Nodes tab on the Properties For Manual Activity Window.



This is a grid box where each row in the grid represents an exit node from the Manual Activity as represented by the design on the Workspace.

The default is OK but you can change this. For example, you might change the OK to Release Order and add another row for Cancel Order.

Fields:

Node

A numeric value starting from 1. For example the number for the third node would be 3.

Caption

This is the tooltip for the node on the Workspace.

Completion Action

You can safely ignore this field in most cases. Use this only where you want to define special processing for the completion node.

Blank - no specific action to be taken and transaction completed.


1 - Cancel Transactions. This sets the Document Type to completed status and then cancels anything which is pending.

2 - Assign New Thread. This assigns a unique identifier to all the Document Types associated with this activity.

Properties For Manual Activity Title Overrides Panel



To display this panel select the Title Overrides tab on the Properties For Manual Activity Window.



The text you enter here will override the title of the Manual Activity when the user sees the screen.

For example, you could enter Credit check failed for CustName, where Custname is a variable displaying actual text. The user could then see Credit check failed for A.E.Smith, for example.


Register Components Window



Warning: *This option is currently reserved for JBA developers only.*



To display this window select Register Components on the File menu.



This window displays a list of Business Methods. You can select an item on the list and choose to Register or Unregister the item using the buttons.



Note: *When you edit a component on the Workspace you do not have to register the component again.*



Tip: If an item on the list is Registered but the File is not found, then unregister the item, because you will not be able to use the Business Method if the file is not on the machine.

Fields:

Method Identification

For JBA developers only.

Method Name

For JBA developers only.

Method Description

For JBA developers only.

Buttons:

Open File

Open one of these types of files: .exe, .dll or .mlf.

Register

Register the Business Method which you have selected.

Unregister

Unregister the Business Method which you have selected.

Close


Close the Register Files Window and save the changes made.

Resequence Links Window



To display this window select Resequence Links on one of the following menus:

Action Agent Menu
Business Method Menu
Business Process Menu
Elemental Activity Menu
Manual Activity Menu
Parallel Path Menu.



Most symbols have more than one node. These nodes represent the exit points from the component, for example for OK and Cancel buttons. When you join up one symbol to another you have to make sure you have joined up the correct node.

If you find that the nodes are in the wrong order you can either :

- On the Workspace, drag the nodes into a new position.
- Use this window to reorganise them. Select a node in the list and either use the up and down arrows, or drag and drop the item, to re-position it.




Warning: You can reorder the nodes and it will affect only your design, However, don't edit the Properties or you will update the Design Time Database for all users.

Retrieve Window



To display this window select the Retrieve option on the Work Management Menu.



Use the Retrieve Window to load components from the Work Management files on the server to the design-time database on your PC.

Type

This column displays all the types of components which you can retrieve from the server.



Note: You cannot currently retrieve a Business Process but this is planned for a future release of Constructor.

The following table shows where the files originate in the Enterprise Work Management Files Library:

Type	File(s) Updated
Document Types	WFP06
Execution Modes	WFP01/98
Data Fields	WFP05
Escalation Rules	WFP07
Schedule Rules	WFP09

Business Processes WFP03/04/17/18/20/21/26/27/28

Select

You select here which type of components you want to be overwritten on the PC. You will be prompted later to define the particular components.



Note: The server files remain unchanged.

Conflict Replace

This conditions what will happen if the details being saved contradict those found on the PC. The details will either be replaced or left unchanged. There are three possible options to determine how the data on the PC is to be replaced:

- Prompt - prompts you before replacing
- Replace - replaces without prompting
- Retain - does not replace at all.

Schedule Rules are always replaced.

For example, if you select the Document Types box, and select Prompt in the Conflict Replace field then you are saying that you want to copy all the Document Types from the WFP06 files on the server to the design-time database on the PC. If a Document Type on WFP06 has the same name as a Document Type on the design-time database, then you want the Document Type to be replaced only after you have been prompted and have confirmed the copying process.



Warning: Once a component has been retrieved it will be used automatically by the existing Business Processes on your PC.

Status

This displays the results of the Retrieval. It tells you when the Retrieval started and finished and lists any errors.



Note: The following fields concern the Retrieval Log.

Progress

Check this to display basic progress messages.

Totals

Tells you how many components of each type have been retrieved.

Detail

Check this to display detailed progress messages.

Timestamps

Puts the time against each item on the log.


Buttons:

Retrieve

This starts the Retrieval process. If you have not previously connected to the server then the Data Source Window is displayed for you.

After a connection has been made to the server a selection window is displayed giving you a list of components to select for Retrieval. For example if you chose to retrieve Data Fields the

selection window gives you a list of Data Fields with the words Exist or New alongside each item. This tells you whether the Data Fields already exist on the PC or whether they are new to the PC. You can select any of the items and click OK to continue with the Retrieval.



You can select any of the items and click OK to continue with the Retrieval.

Server

Displays the Data Source Window for you to change the server.

Close

Close the window.


Copy

Save the log to the clipboard. If you have Microsoft Notepad then Notepad is launched for you.

Right Click Menu Options Window



To display this window click with the right mouse button on an item in the Selected Options list on the Design Menu Window. This displays the Design Menu Options Menu. Then select Options.



You are creating a menu for the user to use at runtime and have selected a constructable to become an option on this menu. Here you can determine how that constructable is to be dismissed and whether to override the description normally associated with the constructable.



Tip: Dismissed means the same as closed down.

Fields:

Dismissal Option

This group box contains two check boxes. You can check either box, both boxes or leave them both unchecked.

Status Change

If you check this box the constructable will be instructed to dismiss, by the operating software controlling its execution, whenever the status of the component changes. The status of the component is determined by the Application Code.

Dismissal Of Parent

If you check this box the constructable will be instructed to dismiss whenever the parent component is dismissed. The parent may be dismissed, by the operating software controlling its execution, or it may be programmed to dismiss itself.



Note: The parent constructable is the one you selected in the Selected Options list on the Design Menu Window.

Description

The text that forms an option on the user's pop up menu. To display this pop up menu the user has to click with the right mouse button on any space on the application window.



Note: This description overrides the description normally associated with the constructable that is being launched via the users pop up menu.

Buttons:

OK

Save the changes and close the window.


Cancel

Close the window without saving the changes.

Select Button Window



To display this window select the Insert Button option from the Manual Activity Panels Menu. To display this menu please click with the right mouse button on the Message Panel or Title Overrides Panel on the Properties for Manual Activity Window.



You can set up buttons on the users window during processing of a Manual Activity.

Fields:

Button Panel

Button Type

Determine how you want the button to execute:

Activity - this refers to an Elemental Activity and for this you need a shortcut code. When the user clicks the button on the application window then it launches an Elemental Activity. You can also use the Override Panel to change the button name.

Other Program Or File - this refers to an external Microsoft Program or a file which you have on your machine. The Override Panel is not available for this option.

Button Caption



Tip: Go on to complete the Button Shortcut field and this field will be completed for you at the same time.

This is the text which is held on the database and will appear on the button seen by the user.


Button Shortcut

If you selected Activity for the Button Type


This is for the shortcut code for the activity, for example, OE 031210 for Order Entry.

There are two ways to complete this field:

Firstly, if you know the shortcut code you can enter the code directly as follows; for example, SL 031410; and the Button Caption, Credit Manager, is completed too.




Secondly, you can use the search method. Please ignore the Button Caption field and click the three-dots browse button alongside the Button Shortcut field. This displays the Select Activity window. Right click on the window to display a Search option on a pop up menu.



Click Search to display a text box at the top of the window. Enter search details, for example Credit Manager and press Return. This starts the search.

The search tells you if a match has been found and lists the results in a browser menu format.



Warning: If your search finds no match then please report this to the person who manages your database.


Select the activity from the list of items you have just found and click OK. This returns you to the Select Button Window and completes all the details you need.

Note that the Message text also appears on the tooltips for the activities.

If you selected Other Program or File for the Button Type

This is pathway for the program or file on your machine. You can enter the pathway directly or click the three-dots browse button alongside the Button Shortcut field. You can then locate the program or file that you need.

Overrides Panel



This enables you to override the contents of a field.

Operation

Fill Field - default.

Fill Row & Col - not supported for this release.

Target

The field number.

Data

Select a Data Field from the list. The contents of this Data Field will be used to fill the field.

Screen Identifier

Not supported for this release.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Schedule Windows

There are two windows:

- Select Schedule Window where you maintain a list of Schedules. Use the Add and Edit buttons
- Schedule Information Window where you can add or edit details.




Note: You cannot delete a schedule.

Select Schedule Window



There are two ways to display this window:
Select the Change button on the Execution
Details Window.
Or: Select the Schedule Rules option on the
Work Management Menu.



You can maintain a list of schedules. Use the New and Edit buttons to make any changes.

Buttons:



*Note: The buttons vary depending on the context
from which the window is displayed.*

OK

Save the changes and close the window.

New

Displays the Schedule Information Window for you to define a new schedule to add to the list.

Edit

Select a schedule from the list then use this button to display the Schedule Information Window and edit the details.

Cancel

Close the window without saving the changes.

Schedule Information Window



To display this window click the New button or the Edit button on the Select Schedule Window.

You can enter details for a new schedule or edit an existing schedule.

Fields:

Schedule Name

Enter your own name for a new schedule.

Default Schedule

Check this box to specify one default rule only.



Note: You can enter a further default schedule but you cannot edit the initial default rule.

Schedule for Days

Choose which days of the week on which you want the process to run.

Schedule Frequency

Choose the frequency at which you want the process to be run:

- Timed Execution needs a precise At Time only. For example: where you want to start a job on 2pm every Tuesday then you enter 14:00 for the At Time and check the Tuesday box.
- Execute at Fixed Times needs an At Time, Start Time and End Time. For example: where you want to start a job at 15 minutes past the hour, every hour between 9am and 9pm, then you enter 0:15 for the At Time, 9:00 for the Start Time, 21:00 for the End Time.
- Execute Periodically needs a Start Time, End Time and Interval. For example: where you want to start a job every half hour between 9am and 9pm then you enter 9:00 for the Start Time, 21:00 for the End Time and 0:30 for the Interval.

- Reschedule Periodically needs an Interval only to tell Constructor to delay the start of a job after it has been submitted to System 21. For example: where you want to wait to start a job for an hour after it has been submitted to the system then you enter 1:00 for the Interval.

At Time

The time at which to start a job.

Start Time

The time at which to start a job.

End Time

The time at which to end a job.

Interval

The time interval at which to run a job. For example: every 30 minutes.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.


Select Start Node Window



To display this window select the Select Start Node option on the Business Process Link pop up menu.



Note: You only see this menu option when you have a top level Business Process calling a second level Business Process for which there is more than one Start Condition. The symbol for the second level Business Process has a yellow dot to indicate more than one Start Node.



You can select which start node you want to use for the second level Business Process, when it gets called by the top level Business Process.

You don't have to use this window. Please refer to Nesting Business Processes.

Fields:

Document Type

You cannot update this field. It displays the Document Type relating to the Start Node which you select.

Start Node

Select a Start Node from the drop down list.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

Start Details Window



To display this window select Edit from the Start Condition context sensitive pop up menu.

You can edit details for the Start Condition.



Note: Details relating to the entire Business Process or Activity can be maintained using the Edit Properties Window. Select the Properties option from the Workspace Menu



Note: Business Processes can have any number of Start Conditions but Assembled Activities, Subassemblies and Activity Lists must have only one.



Note: That the End Details Window enables you to set conditions for a single ending point of the Business Process or activity. You can have more than one end point.

Fields:

Name

The name of the process. If you ignore it your process will be called Start Condition n , where n is a numeric value which is automatically defined and incremented by Constructor each time you create a Start Condition. The first Start Condition will be called Start Condition 1.

Starting Condition

These are the conditions which have to be set before you can begin to execute the process.



Note: This corresponds to the Input Conditions field on the Conditions Window.

Description

Your description of the process.



Note: The remaining fields are enabled only for a Business Process or Activity List.

Process Code or Activity Code

For Display only.



Note: Details relating to the entire Business Process or Activity, such as the Process Code or Activity Code, can be maintained using the Edit Properties Window. Select the Properties option from the Workspace Menu.



Note: Each Activity in the Business Process also has to have a unique Activity code.

Document Type

Select the Document Type from where this newly designed component will be initiated. For example, it might start from the INVOICE or PICKNOTE.

Default Start Node For This Document Type

This field is designed for use with nested Business Processes, when you have a top level Business Process calling a second level Business Process for which there is more than one Start Condition. You can select which start condition you want to use for the second level Business Process, when it gets called by the top level Business Process. The symbol for the second level Business Process has a yellow dot.



You don't have to use this box. Please refer to Nesting Business Processes.



Warning: Constructor uses the last setting you make as the default. If you check the box for one Start Condition and then go on to check another it does not warn you that you have overridden the first.

Buttons:

OK

Save the changes and close the window.



Note: You cannot close the window without saving the changes.

Cancel

Close the window without saving the changes.

User Selected Path Window



This window displays when you preview or execute a component.



You can make a decision, as the user would, about the route you want to take through your process.

Fields:

Select the Route Forward

This displays option buttons for you to choose the node from which you want to proceed.



Tip: When you first drag the User Selected Path tool onto the Workspace there will be only one node and you will have to add others if you need them.

Each option button represents a node or exit point on the symbol and you can maintain this list by selecting Edit on the pop up menu for the component and using the User Selected Path Description Window.

Buttons:

OK

Save the changes and close the window.

Cancel

Close the window without saving the changes.

User Selected Path Details Window



To display this window select Edit on the User Selected Path pop up menu.

Name	1st Parameter	Operator	2nd Parameter
Print			
Fax			
EMail			

You can enter decision pathway details.

Fields:

Description

Name of the User Selected Path which you can now change.

DEA Field Name

Not available.

Execution Mode

User Selected means that you select which exit point Constructor is to use from the User Selected Path tool.

Data Selected means that Constructor decides which exit point it is to use from the User Selected Path tool, based on data conditions.

Subassembly Executor is not available.

Node Details

Use these details in conjunction with the list view at the bottom of the window. Enter new node details here, press the Add button and they will appear at the bottom of the list view below. To remove a node you have to select it first in the list view and then press the Remove button to

remove it from the list. You can also amend if you overwrite details and then press the Add button.



Note: The number of entries in the list is equal to the number of segments on the symbol on the Workspace.

Name

Name of the node. This is displayed in the tooltips.

Condition

Enter condition details for the node. For example: you might want to set the condition that the Invoice value must be equal to zero before using the node as an exit point and going on to print to an error report. Then, you might enter something like this: INVVAL = 0.

1st Parameter

This is a variable name. For example, for the condition VAR1 = VAR2 the 1st Parameter is VAR1.

Operator

This is an operand and these are your choices:

=	equals
==	not equals
<>	not equals
<	less than
>	greater than
<=	less than or equals
>=	greater than or equals

For example, for the condition VAR1 = VAR2 the Operator is =

2nd Parameter

This is a variable name or a value. For example, for the condition VAR1 = VAR2 the 2nd Parameter is VAR2.

List View

This list view displays how many nodes or exit points there are associated with the Process Control tool. The number of entries in the list is equal to the number of segments on the symbol on the Workspace.

Buttons:

Add

Enter new Node Details, press the Add button and the details will appear as a new line at the bottom of the list view.

Remove

To remove a node you have to select it first in the list view and then press the Remove button to remove it from the list.

OK

Save the changes and close the window.


Cancel

Close the window without saving the changes.

Validation Progress Report Window



To display this window click on the Validate button on the Toolbar.



This validates the design by checking that the process you have defined meets the rules for your organisation.

The Validation Progress Report Window displays a list for you to examine and then correct any errors.

The list tells you whether all the output nodes are connected, whether all the input conditions are satisfied, whether all the necessary connections have been made, and whether all the consumables are present and correct.

There is no limit to the number of times you can validate.



Tip: There are no fields but there is a display area above the Close button. If you select an item from the validation details the description for that item is displayed in this area.

Buttons:

Close

Close the window.