

-
-
-
-
-

Chapter 1

Installing System 21 Client Workspace



Product Information

The software is available on CD-ROM.

This is what is shipped:

- System 21 Client Workspace version 3.5.2b. This contains the program software, including Designer, and the JBA System 21 Client Workspace Help.
- Soft Menu Maintenance.
- InfoBase Help (UK or US). You can install this with Client Workspace or there is a standalone CD-ROM available.



Warning: For a Network Client Installation Client Workspace must be installed from the server. Do not install directly from supplied media or your main directory. The Network Client Installation provides access to server installed products.



Note: No Host (Server) objects are shipped with Client Workspace.

Authorisation Codes

Before you can use these applications, you must enter authorisation codes:

- JBA Client Workspace (21/V3)
- JBA Workspace Designer (DG/V3).

Pre-Requisites

There are both hardware and software requirements.

Hardware Requirements

To install Client workspace you must have at least 18 Mb available on your hard disk.

You only need 3 Mb for a Network Client install.



Warning: For a Network Client Installation, you must install Client Workspace from the server. Do not install directly from supplied media or your main directory. The Network Client Installation provides access to server installed products.

Software Requirements

To install Client Workspace correctly, you must have the following:

AS/400 Host

JBA Application Manager Version 3.5.



Warning: If you use TCP/IP to connect to an AS/400 Host, the TCP/IP licensed program (57xx TC1) must be installed on the AS/400. This is automatically installed with Operating System OS/400 V3R7M0 or later.

UNIX Host

JBA System 21 for AIX (including Version 3.5.2a applications).

JBA Runtime Release 1.3.5 or later.

PC Client

Supported configuration (platform or router).

Authorisation for Client Workspace (21V3) and Designer (DGV3) as required.



Note: Please refer to the latest JBA International System 21 Supported Configuration Information sheet for pre-requisites and current version details. This sheet is available on the JBA BID system.



Warning: Any site not using a supported configuration must have JBA Branch agreement for local support of the product. Please confirm the set up is supported BEFORE installing the product.

All previous host objects are now shipped with System 21 Application Manager or with Guidelines 3.4 Host runtime support. The System 21 Configuration Sheet details both of these. They are both supplied with their own installation instructions.

Installing The Software



Note: Client Workspace does not support a Japanese language version. If you want to install a Japanese version System 21 Interface then you need to upgrade to System 21 Explorer.

Tutorial

This is what to do:

Step 1

From the PC, make sure that Windows and your Router have been started.

Step 2

From Windows Program Manager on the File menu select the Run Option. The Run window is displayed.

Step 3

In the Command Line field enter :[Drive]:SETUP (where [DRIVE] is the drive letter from which you are installing the software). Select the OK button.



Tip: Use the default directory C:\Jbas21 where possible. Always install future System 21 components to the same directory. It is faster to install all required components at the same time (multiple selection).

Step 4

Complete the installation.



Tip: Online help and instructions are provided during the installation. You most likely want to accept the displayed default settings and need only click the Next button to progress through the installation.



Note: You will be asked whether you want InfoBase help or not. Please refer to About The Help Files for more information.

Step 5

At the end of the installation you can choose to reboot now or later.



Warning: JBA strongly recommends you to reboot now.

About The Help Files

There are two kinds of Help which you might need:

- **InfoBase** - This is help for the application software for System 21. During Client Workspace installation you are asked whether or not to install this InfoBase. If you reply Yes then a directory \Help is created within C:\Jbas21 and InfoBase is installed into C:\Jbas21\Help. If you reply No, then the \Help directory is not created and InfoBase is not installed
- **Technical Information** - This is the Help file which you are reading now. It is for System Administrators and consultants and includes Installation instructions, tips and techniques for all the System 21 Interfaces. It gives you troubleshooting help to assist you with error messages.

Possible Problem

The Technical Information help file is wi.hlp and is automatically installed into C:\Jbas21. This is so that the links with the error messages still work even if the \Help directory is not created and InfoBase is not installed. However, the HelpPath in the configuration file, JBAS21P.INI, is always set to C:\Jbas21\Help and the links will fail if you do not install InfoBase.

What To Do

If you are going to install InfoBase then you need do nothing at all.

If you are not going to install InfoBase then you need to set the HelpPath to C:\Jbas21. You can either do this manually or via the Preferences panel within Client Workspace.

About Network Installations



Warning: For a Network Client Installation, you must install Client Workspace from the server. Do not install directly from supplied media or your main directory. The Network Client Installation provides access to server installed products.

With a network installation, you load Client Workspace onto a Server, then minimally load it on the PC and run it against server.

- Network Server - this loads the Server portion. You can run client and stand-alone installations from here. All network versions are run against this server.
- Network Client - this loads minimal Client portion. You can install this from the Server install. Provides access to Server Installed products.



Note: The performance of the Network Version depends upon the speed and quality of the network. The time to install applications will vary depending on the speed of your Host, your Network and your PC.

The advantages of a Network Installation are:

- You install just once, and everyone can install from the central place.
- Once installed on a server, the PC Client install takes a fraction of the normal installation time.
- The Network Administrator can set up configuration files on their PC, copy them to the server, and they will be auto-installed onto all other PCs during a Client Install. Therefore you only need to do jobs such as host configuration, preference setting, host screen recognition changes once.
- It saves space on the PC (see Pre-Requisites section for current space savings).



Tip: Please refer also to LUEINFO.CFG.



Tip: For a fast install onto many PCs, run a Network Server Install once only, followed by short Network Client installation onto each PC. These PCs will then run System 21 Client Workspace over a network.

About Client Workspace

There are six icons provided with Client Workspace. All access System 21 Host applications, but with soft menus tailored to each product area. These are:

Class

Common applications in a sensible class based grouping.

Job Management

Specific area grouping.

Service

Specific area grouping.

Style

Specific area grouping.

Classic

Menu options as on the traditional Green-on-Black common applications.

Drinks

Specific area grouping.

About Soft Menu Maintenance And Other Utilities

Client Workspace provides Utilities in a separate PC folder. Icons are created for:

CSS Configuration

Used by many applications. Client Workspace is supplied with default configuration for all applications, but it may require customising. Use this utility to customise the configuration.

SMU Maintenance

To customise the System 21 menu options.

Syslevel Monitor

For Version reference of key components of Client Workspace.



Tip: Remove any icons not used by the company or individual from the desktop following installation.

About Designer

This product is now wholly integrated into the Client Workspace. It appears as a toolbar icon, which when selected, enables a special Designer toolbar.

To enable the Designer, it must be authorised on the Host, and then switched on the PC.

To achieve this, change the JBAS21P.INI file as follows:

Set the line:

`Designer=0`

to

`Designer=1`

Leave the DesignFiles option set to zero as shipped.

About Fonts

When you install Client Workspace the fonts are automatically installed too.

There are three fonts, each with a choice of bold and normal style making a total of six combinations:

- Arial Monospaced
- Arial Monospaced Bold
- Arial Monospaced CE
- Arial Monospaced CE Bold
- Arial Monospaced Zero-Dot
- Arial Monospaced Zero-Dot Bold.

They are saved as .TTF files in the installed software directory with a subdirectory \Fonts.



Note: For foreign languages, you can get alternative fonts separately, and amend the INI file attribute to search for that font first.

Usually these fonts install correctly. However, you may get an error during the installation:

Arial Monospaced Font Not Found

This is caused by a font having been previously uninstalled incorrectly. The installation process then cannot install the new font as it expects to and reports that the font is not found.

The way around this problem is to manually install the font to the FONTS directory.

An incorrectly installed font will also cause problems with screen presentation.



Tip: When you have finished the installation, and rebooted, it is a good idea to check that the fonts have been installed.

Upgrading The Software

You must confirm that the Host and Router configuration are still valid with the latest System 21 product. For more information see Pre-Requisites.

If you have previously installed any of these modules it is recommended that you delete their files, directories, program groups and program items before you begin this installation.

Remember to copy away any work files and extracts that you have previously created. These may include:

- New or changed Soft Menu files (*.SMU)
- Modified Software Recognition files (SRUSER.*)
- Saved Quicklist file (QCKLST.DAT).

About the upgrades:



Note: The INI file JBAS21P.INI can only be saved with minor upgrades (that is CWS3.5.0a to CWS3.5.0b or to CWS3.5.1a).

Major upgrades such as CWS2.02i or CWS3.4.0d to CWS3.5.0a have different file structures which prevent Client Workspace running correctly.

From CWS3.5.0 onwards, a translated version of this INI file will also be available, in supported languages, and most of the variables can be configured on-line with little or no manual editing required.



Note: If you leave the icons loaded, duplicate icons may appear on the desktop after installation.

Uninstalling The Software

The installer shipped with Client Workspace 2.02a onwards includes an Uninstall facility. This will uninstall Client Workspace and its Utilities.

For a previous Server install, there is no Uninstallation. Only the server directory needs to be removed to completely uninstall the product.

Client Workspace should be uninstalled after all other System 21 components have been removed. Failure to do this will result in an unsuccessful Uninstall.



Tip: Sometimes the fonts may not uninstall correctly. Whenever you Uninstall, or Install, then the system prompts you to reboot. When you have rebooted it is a good idea to check that the fonts have all been uninstalled and if not then delete them manually. They are saved as .TTF files in the installed software directory with a subdirectory \Fonts.

Configuring The PC Software

The PC Installer will automatically configure the PC as much as is possible, or prompt to offer advice about what steps are required.



Note: This section cover areas definitely not automatically configured by the Installer.

PC Configuration (Not Host Specific)



Warning: Most settings in the INI file should be maintained through Client Workspace rather than manually.

The first time that you logon to Client Workspace you have no connection to a host and have to establish one yourself. You do this by clicking the Server button from the JBA System 21 logon window to display the Server Configuration window. You can use this window to connect to a server and protocol, maintain a list of available servers and protocols and automatically update the INI file. You can now go into Client Workspace immediately and use the software.

Online help is available on all these windows when you click the Help button.

How To Add A Server

This is what you do:

Step 1

Type in the server name in the Connection Type group box.



Note: This is case sensitive

Step 2

Select a protocol.

There are two protocols for the AS/400 server:

- To use the TCP/IP protocol, it must already be set up in Windows and with a valid TCP/IP address assigned.
- To use AS/400 alone, a valid router must already be connected to the desired host before you start Client Workspace.

Step 3

This is enough to connect Client Workspace with the Server. However, you can enter additional information first. To do this click the Advanced button to display the Advanced window where you can enter more information. The Advanced window also has further help.

Step 4

Click the Add button to update Client Workspace. The new server appears in the list of configured servers in the multiple drop-down list.

Step 5

Click the Save button to save the changes you have made to the INI file and return to the Logon window where the last server added will appear as the System.

How To Control Access To Configuration

The Server button on the Logon window remains enabled until you decide to hide it. To do this check the Hide Configuration check box on the Logon Window. JBA recommends that you do this so that on any subsequent occasion, when you log on, the host is configured for you.



Note: The Hide Configuration check box hides the whole of the Configuration group box. This means that it hides not only the Server button but also the Preferences button and the Hide Configuration field itself, all on the Logon window.

You can override this disabling of the Server button by checking the Hide Configuration check box on the System window. The System window is available from a button on the Preferences window. The Preferences window is available from the Preferences option on the System menu.



Note: The Hide Configuration check box is available in two places: on the Logon Window (unless you have hidden it) and the System window.

PC Configuration (Using AS/400)

There are issues concerning client server configuration and non-English operating systems resulting in changed signon panels.

Client Server Configuration

System 21 applications may require the Client Server Configuration files. System 21 and its components are shipped with pre-configured software, but User and Host details may need to be added before these applications can be used. Also, it may be necessary to customise the configuration using the supplied Utilities.

Features

This Utility has an inbuilt Help File to cover the main configuration requirements step by step. In addition, Client Workspace automatically updates the Host User and Password as well as Host Type for the Default database, when connecting to a host. So any applications running from Client Workspace do not need to be specifically configured, unless a separate Host and User are required. In these cases, refer to the Help File to help configure a different database.

Restoring from Previous Configuration files

Copy any saved configuration files into the Client Workspace folder. If they are of a different type to the latest (for example, between Version 2 and 3 of Client Workspace), accept the message offering to convert the files. Then Verify the configuration with the last step below.

When the configuration changes are complete, delete any Version 2 files copied from the backup directory. These include:

APPLICAT.INI
LOCATION.DAT
HOSTLINK.DAT
FILESYN.DAT
HOSTAPPL.DAT
JCF.INI
JCH.INI
USERHOST.DAT

Basic Configuration Changes And Verification

Select the Client Server Support configuration icon in the JBA System 21 Utilities folder by double-clicking on it.

1. Using the Help File, configure the Host - Make sure that your AS/400 is configured correctly with the appropriate PLU name.
2. Using the Help File, configure the User - Make sure that your local user is the same as that specified on the CSSUSER statement of your AUTOEXEC.BAT file, and is defined in the list of users, with the correct AS/400 user profile and password.
3. Using the Help File, confirm the host link is correctly set up by running the Verify option. If the verification completed successfully, then the link to the host is working.

Non-English Operating Systems And Changed Sign On Panels

If the first words on the AS/400 Sign On Panel are something other than Sign On, then extra processing is required before Client Workspace is run. This is normally due to the Operating System being Non-English, or because the Sign On panel has been customised. The Translated or Customised values for the emulator defaults in Client Workspace must be changed in the JBAS21P.INI file.



Tip: Refer to the SelectHost section of JBAS21P.INI for further details.

PC Configuration (Using UNIX And NT)

This section is targeted for use by a competent UNIX or NT technician. Please refer to the accompanying Tips and Techniques, pre-requisite software and any relevant UNIX or NT documentation material.

Much of the required configuration for UNIX or NT use may have already taken place during the installation of any pre-requisites.

However, as a full checklist, the following sections lists the requirements for host and PC Client.

UNIX And NT Host Requirements.

You must be logged in as root, unless otherwise specified, to perform all UNIX and NT tasks.

1. Create a new UNIX or NT user to run System 21/UNIX/NT and set the profile up as a normal System 21 user.

The user should not be asked for an input during login and must login straight to the Unix or ksh command line. Therefore the user ID should NOT run any sort of menu system.

2. Edit the TCP/IP Services (/etc/services) file so that it contains the following line:

```
jqserv 24000/tcp      # JBA System 21 / UNIX
jbachp 24500/tcp      # JBA System 21 / UNIX
```

Replace 24000 and 24500 with unique port numbers for use by inetd on the system. To make sure that this port is not already used, you should get your System Administrator to check the /etc/services file and also run netstat -an for any other services which use this same number.

3. Edit the TCP/IP Configuration (/etc/inetd.conf) file so that it contains the following lines:

```
jqserv stream tcp nowait s21user / JBA_openroute/bin/sviewstart sviewstart
jbachp stream tcp nowait s21user / JBA_openroute/bin/sviewstart sviewstart -c
```

Replace S21user with the name of the dedicated System 21 user ID on Unix.

4. Run the following commands to force the inetd daemon to recognise the above changes:

```
inetimp    (you do not need this command if you are using version 4 or above of UNIX)
refresh -s inetd
```

Check that the svsignon script in your Release directory has SUID-root switched on by running the following commands:

```
chown root /Release/*/exports/*/bin/svsignon
chmod ug+s /Release/*/exports/*/bin/svsignon
```

UNIX/NT PC Client Requirements

1. In JBAS21P.INI, set:

Hosttype=UNIX

and add

Hostname

2. The JBAS21P.INI file delivered with Client Workspace requires the following change if connecting to an Oracle database using any other character set than US7ASCII:

Under the section entitled [JBAVT] change

OEMCONV=no

to

OEMCONV=yes.

If changed, the PC should be configured to use the same codepage as the database.

3. If more than one host is to be connected to then JBAS21P.INI will require another special change. This is fully detailed in the Tips and Techniques manual.

4. Edit the TCP/IP Services (/etc/services) PC file to contain the following lines:

```
jqserv  24000/tcp          # JBA System 21 / UNIX
jbachp  24500/tcp          # JBA Syncall Call Host
```

Replace 24000 and 24500 with unique port numbers for use by inetd on the UNIX system. These should be the same as specified in the /etc/services file on the UNIX or NT machine.

UNIX Load Balance

To run the UNIX Load Balance program, you must put an entry (dispatch) in the services file on the PC and configure the corresponding entry in inetd on the UNIX host. You must install and run the daemon program which monitors performance on all relevant servers and install the program or shell script which returns the details on the UNIX host (this must be the first host defined in the [JBAVT] section of JBAS21P.INI).

Before starting Client Workspace, amend the JBAS21P.INI file, and set the LoadBalance variable to 1 or 2 (2 includes a display of results, either call the LoadBalancing program).

Add the program and path to the LOADBALANCEPROG and LOADBALANCEPATH variables respectively.

Definition Of Unix Configuration Requirements

There are issues concerning the PC and the Host.

PC

In the System 21 directory the JBAS21P.INI file shipped with Client Workspace holds the host information together with a server name (the section entitled [JBAVT]). The server name defaults to JQSERV. You can change this to a suitable name.

In the TCP/IP directory the \etc\services file is the TCP/IP Services Configuration file and relates the servers with a unique port number (such as 24000/TCP) and a description.

You can amend the application server, jqserv, to a suitable name. It must match that specified in the JBAVT.INI file however.

The Syncall Call Host server, jbachp is used internally by Client Workspace and you cannot change this.

In both cases, you can change the port numbers if necessary.

Host

In the TCP/IP directory the file `/etc/services` is a duplicate file to the TCP/IP Services file on the PC. The server and port numbers must match those on the PC services file.

In the TCP/IP directory the file `/etc/inetd.conf` is the task driver for the application, and resides on the Host in the same directory as the Host services. It is accessed by port number from the Host services only, and holds the path and task details.

For multiple databases, it is recommended to use a new port number and server name throughout the above setup.

Troubleshooting

If you have any problems or questions about JBA System 21 Client Workspace then please refer to Tips And Techniques. This gives you:

- Troubleshooting help.
- Checklists.
- Detailed background information on various subjects such as the routers, the error codes, the configuration files shipped with the product.
- Useful suggestions for making further use of the product. For example how to carry out a trace.

Tips and Techniques refers to all these three interfaces, unless an individual interface is named specifically within the text:

- System 21 Client Workspace
- System 21 Explorer
- System 21 Constructor.

Please refer to your JBA representative at JBA Product Support.