# **GTAS ETL Jobs and ETL Scheduler Deployment Guide (Linux)**

### 1. Required tools

- Java 1.8
- Pentaho Data Integration tool (See separate installation guide)
- Neo4j Graph Database (see separate installation guide) required for Neo4j ETL
- Elasticsearch 7.5.2 and Kibana 7.5.2 required for the report ETL

### 2. Create Local ETL Environment


- a. Create your local ETL parent directory gtas-etl in the root directory (/) Note: Although the ETL jobs and scheduler can be installed under any directory, the following instruction show the installations under the root directory (/). If you choose to create this parent directory at a different location, make sue that you review and update the properties file listed in the next section.
- b. Pull the latest from the GTAS GitHub repository. Go to the gtas-*etl-main* directory and copy ETL and configuration files with their directories to your local ETL parent directory, *gtas-etl*

Copy from	Copy to
GTAS/gtas-etl-main/ (all files and directories)	/gtas-etl/

- c. Go to the GTAS/gtas-etl-scheduler project and build it as follows:
  - mvn clean install

After a successful build, copy the gtas-etl-scheduler.jar file from *GTAS/gtas-etl-scheduler/target* to your ETL parent directory /gtas-etl

d. Verify that your local ETL environment looks as follows:



### 3. Update Property Files

**Note:** If you <u>did not</u> create gtas-etl in the root directory (/), please review each property file carefully. <u>In addition to the following properties</u>, you will have to update properties with values pointing to a file or a directory structure.

#### a. /gtas-etl/config/scheduler/scheduler.properties

No update is required

### b. /gtas-etl/config/neo4j-etl/job.properties

- EXT\_VAR\_GTAS\_DB\_USER\_NAME
- EXT\_VAR\_GTAS\_DB\_PASSWORD
- EXT\_VAR\_NEO4J\_DB\_USER\_NAME
- EXT\_VAR\_NEO4J\_DB\_PASSWORD

### c. /gtas-etl/config/report-etl/job.properties

- EXT\_VAR\_GTAS\_DB\_USER\_NAME
- EXT VAR GTAS DB PASSWORD
- EXT VAR ELSEARCH PROTOCOL
- EXT\_VAR\_ELSEARCH\_HOST\_NAME
- EXT\_VAR\_ELSEARCH\_USERNAME
- EXT VAR ELSEARCH PASSWORD
- EXT\_VAR\_KIBANA\_PROTOCOL
- EXT\_VAR\_KIBANA\_HOST\_NAME
- EXT\_VAR\_KIBANA\_USERNAME
- EXT\_VAR\_KIBANA\_PASSWORD

**Note**: If you have configured your Kibana and Elasticsearch environments to use the HTTPS protocol with SSL certificate, then import the public certificate to your local java keystore and set the following properties:

- EXT\_VAR\_JAVA\_TRUST\_STORE
- EXT\_VAR\_JAVA\_TRUST\_STORE\_PASSWORD

# 4. Launch the gtas-etl-scheduler

- a. Start the scheduler as follows
  - java -jar gtas-etl-scheduler.jar

# 5. Important features

### a. Job Scheduler properties

Common ETL Properties				
Property	Description	Allowed Values		
opSystem	The operating system on which the	windows/linux		
	ETL is running			
pdiDir	Points to the Pentaho Kitchen	Path to/data-		
	executable file. The full file path to	integration/./kitchen.sh (on		
	kitchen.sh (for Linux) or kitchen.bat	Linux) or/data-		
	(for Windows)	integration/kitchen.bat (on		
		Windows)		
Neo4j ETL properties				
Property	Description	Allowed Value		
neo4j.execInterval	The time interval to launch the Neo4j	The recommended minimum is		
	ETL job after its first execution.	60		
neo4j.enableEtl	Enables/Disables the Neo4j ETL job	true/false		
neo4j.logLevel	The log level for the Neo4j ETL job			
neo4j.etlName	The name given to the Neo4j ETL job	Any name. The default name is NEO4J_ETL		
neo4j.configFilePropertyName	The global parameter name for the config property file name	EXT_ETL_CONFIG_FILE		
neo4j.jobDir	The main entry point of the Neo4j	Path to /gtas-etl/job/neo4j-		
	ETL job	etl/gtas-to-neo-job.kjb		
neo4j.logDir	The log file of the Neo4j ETL job	Path to /gtas-etl/log/neo4j-		
		etl/neo4j-etl-log		
neo4j.configFile	The main configuration file of the	Path to /gtas-etl/config/neo4j-		
	Neo4j ETL job	etl/job.properties		
report.execInterval	The time interval to launch the	The recommended minimum is		
	Report ETL job after its first	90		
	execution.			
report.enableEtl	Enables/Disables the Report ETL job	true/false		
report.logLevel	The log level for the Neo4j ETL job			

report.etlName	The name given to the Report ETL	Any name. The default name is
	job	REPORT_ETL
report.configFilePropertyName	The global parameter name for the	EXT_ETL_CONFIG_FILE
	config property file name	
report.jobDir	The main entry point of the Report	Path to /gtas-etl/job/report-
	ETL job	etl/gtas-report-job.kjb
report.logDir	The log file of the Report ETL job	Path to /gtas-etl/log/report-
		etl/report-etl-log
report.configFile	The main configuration file of the	Path to /gtas-etl/config/report-
	Report ETL job	etl/job.properties