A tutorial on the polaron transformed Redfield equation

Huo Chen

November 22, 2020

0.1 Correlation function in the polaron frame

This tutorial demonstrates how to use the polaron transformed Redfield equation (PTRE) in HOQST. For more details on the PTRE, [1] Non-canonical distribution and non-equilibrium transport beyond weak system-bath coupling regime: A polaron transformation approach is a useful reference.

We solve both the Redfield equation and PTRE for a single qubit Hamiltonian

$$H_{\rm S} = \epsilon \sigma_z + \Delta \sigma_x$$

coupled to an Ohmic bath via σ_z interaction:

$$H = H_{\rm S} + \sigma_z \otimes B + H_{\rm B}$$
.

Loosely, the main difference between the Redfield equation and PTRE is that they have different bath correlation functions. For the Redfield equation, the bath correlation function is

$$C(t_1, t_2) = \langle B(t_1)B(t_2) \rangle$$
.

In the polaron frame, however, the bath correlation function becomes

$$K(t_1, t_2) = \exp \left\{ -4 \int_0^t \int_{-\infty}^0 C(t_1, t_2) dt_1 dt_2 \right\}.$$

Interested readers can refer to [2] Macroscopic Resonant Tunneling in the Presence of Low Frequency Noise and [3] Dynamics of the dissipative two-state system for more details.

0.1.1 Error bound on the second-order master equation

The most straightforward analysis is to compare the error bounds given in [4] Completely positive master equation for arbitrary driving and small level spacing between the Redfield equation and PTRE. We define the error scaling parameter as

$$error = \frac{\tau_{\rm B}}{\tau_{\rm SB}}$$
.


Then we plot the error ratio between the Redfield equation and PTRE

$$R = \frac{error_{\text{Redfield}}}{error_{\text{PTRE}}} ,$$

vs. the system bath coupling strength ηg^2 while fixing other parameters in the Ohmic bath.


```
using OrdinaryDiffEq, OpenQuantumTools, Plots
using LaTeXStrings
function err_bound(tf, cfun)
    tsb, esb = \tau_SB(cfun)
    tb, eb = \tau_B(cfun, tf, tsb)
    tb / tsb
end
fc = 4; T = 12; tf = 1000;
\etalist = log_uniform(1e-3, 5, 1000)
err_ratio = []
err_clist = []
err_klist = []
for \eta in \etalist
   bath = Ohmic(\eta, fc, T)
    cfun = (x)->correlation(x, bath)
    pfun = (x)->polaron_correlation(x, bath)
    err_c = err_bound(tf, cfun)
    err_k = err_bound(tf, pfun)
    push!(err_clist, err_c)
    push!(err_klist, err_k)
    push!(err_ratio, err_c/err_k)
end
idx = findfirst((x)->x>=1, err_ratio)
plot(\etalist, err_ratio, xscale=:log10, yscale=:log10, label="", linewidth=2)
vline!([ηlist[idx]], label="", linestyle=:dash, linewidth=2)
annotate!([(0.5, 1.0, Plots.text("polaron")), (0.01, 1.0, Plots.text("Redfield"))])
xlabel!(L"\eta g^2")
```

ylabel!("R")



From the above figure we observe that when the system-bath coupling strength is larger than 10^{-1} , the PTRE should have better error scaling than the standard form of Redfield equation. We also plot the corresponding error values for both the Redfield equation and PTRE:

```
plot(\etalist, err_clist, xscale=:log10, yscale=:log10, label="Redfield", linewidth=2) plot!(\etalist, err_klist, xscale=:log10, yscale=:log10, label="PTRE", linewidth=2) xlabel!(L"\eta g^2") ylabel!("error")
```



The above figure confirms that the Redfield equation applies to the weak-coupling regime while the PTRE applies to the strong coupling regime.

0.1.2 Solving PTRE

Since the Redfield equation and PTRE have identical forms, solve_redfield can also be used for the PTRE. To see this, let's first write down the PTRE for our example.

$$\dot{\rho}_{\rm S} = \epsilon \sigma_z + [\sigma_i, \Lambda_i(t)\rho_{\rm S}(t)] + h.c.$$

where $i, j \in [+, -], i \neq j$ and

$$\Lambda_i(t) = \Delta^2 \int_0^t K(t-\tau)U(t,\tau)\sigma_j U^{\dagger}(t,\tau)d\tau .$$


From the above equations, it is clear that the following steps are needed to define an evolution in the polaron frame:

- 1. define a new Hamiltonian $H = \epsilon \sigma_z$;
- 2. define new coupling operators σ_{-} and σ_{+} ;
- 3. define new correlated bath with two-point correlation $K_{i,j}(t_1, t_2)$;

The following code block illustrates how these can be done in HOQST:

```
# assume \epsilon = 1 const \Delta = 0.1 # define the Ohmic bath in polaron transformed frame
```

```
\eta = 0.5; bath = Ohmic(\eta, fc, T)
    K(t1, t2) = \Delta^2 * polaron_correlation(t1-t2, bath)
    cfun = [nothing K; K nothing]
    pbath = CorrelatedBath(((1,2),(2,1)), correlation=cfun)
    # define coupling as \sigma+ and \sigma- operators
    \sigma p = [0 \ 1; 0 \ 0.0im]; \ \sigma m = [0 \ 0; 1 \ 0.0im]
    coupling = ConstantCouplings([\sigmap, \sigmam])
    # manually define the unitary operator
    U(t) = \exp(-2.0im * \pi * \sigma z * t)
    H = DenseHamiltonian([(s)->1.0], [\sigma z])
    u0 = PauliVec[3][1]
    annealing = Annealing(H, u0, coupling = coupling, bath = pbath)
    tf = 100
    sol_ptre = solve_redfield(annealing, tf, U, alg=Tsit5(), Ta=2, reltol=1e-5)
    pop_e = [real(s[1,1]) for s in sol_ptre.u]
    plot(sol_ptre.t, pop_e, xlabel=L"t\ (\mathrm{ns})", ylabel=L"P_0(t)", label="",
linewidth = 2)
```




For historical reasons, this is known as an example of the "incoherent tunneling". The off-diagonal elements of the density matrix in computational bases(Z-bases) during the entire evolution are 0 (shown in the next section).

0.1.3 Redfield equation

What would happen to the Redfield equation in this regime? We can also try:

```
 H = DenseHamiltonian([(s)->1.0], [\sigma z+0.1*\sigma x]) \\ coupling = ConstantCouplings(["Z"]) \\ annealing = Annealing(H, u0, coupling = coupling, bath = bath) \\ tf = 100
```

```
sol_redfield = solve_redfield(annealing, tf, U, alg=Tsit5(), Ta=40, reltol=1e-5,
callback=PositivityCheckCallback())
pop_e_redfield = [real(s[1,1]) for s in sol_redfield.u]
plot(sol_ptre.t, pop_e, xlabel=L"t\ (\mathrm{ns})", ylabel=L"P_0(t)", label="PTRE",
linewidth = 2, legend = :right)
plot!(sol_redfield.t, pop_e_redfield, xlabel=L"t\ (\mathrm{ns})", ylabel=L"P_0(t)",
label="Redfield", linewidth = 2)
```



The PTRE gives a much stronger decay than Redfield equation for the parameters chosen in this example. One can also verify the amplitude of the off-diagonal elements during the evolution. Unlike the PTRE, the solution of the Redfield equation has non-vanishing off-diagonal elements of the density matrix.

```
t_axis = range(0, 5, length=100)
off_diag_ptre = [abs(sol_ptre(t)[1,2]) for t in t_axis]
off_diag_redfield = [abs(sol_redfield(t)[1,2]) for t in t_axis]
plot(t_axis, off_diag_ptre, xlabel=L"t\ (\mathrm{ns})", ylabel=L"\lvert \rho_{12}\\rvert|(t)", label="PTRE", linewidth = 2, legend=:right)
plot!(t_axis, off_diag_redfield, xlabel=L"t\ (\mathrm{ns})", ylabel=L"|\rho_{12}(t)|", label="Redfield", linewidth = 2)
```

