Underworld2 Cheat Sheet

Where to find us

Underworld homepage & blog:
http://www.underworldcode.org/
Underworld codebase:
https://github.com/underworldcode/underworld2
Issue tracker:
https://github.com/underworldcode/underworld2/issues
Follow us on Facebook! :
https://www.facebook.com/underworldcode/

Useful Docker Commands

Launch a container running Jupyter notebook instance. Port 8888 is published to make the notebook available from host browser (usually at http://localhost:8888):

```
$ docker run -p 8888:8888 underworldcode/underworld2
```

Run an Jupyter notebook mapping the current directory to a container directory, and also publishing port 8888:

```
$ docker run -v $PWD:/workspace/user_data -p 8888:8888 \
                                underworldcode/underworld2
```

Run an Underworld script stored in your current local directory:

```
$ docker run -v $PWD:/workspace underworldcode/underworld2 \
                                python model.py
```

Run a local Underworld script in parallel:

```
$ docker run -v $PWD:/workspace underworldcode/underworld2 \
                                mpirun -np 2 python model.py
```

For OSX/Windows users, to determine your VM ip address:

```
$ docker-machine ip default
```

Update your Underworld2 image:

```
$ docker pull underworldcode/underworld2
```

Note: Ctrl-\can usually be used to terminate a running docker instance.

Jupyter Notebooks

Enter: Enter edit mode.
Esc: Leave edit mode.
Cursor Up/Down: Move to the above/below cell (when not in edit mode).
Ctrl-Enter: Execute current cell.
Shift-Enter: Execute current cell and move to next.
Tab: (After you've commenced typing) Autocomplete.
Shift-Tab: (When inside function parenthesis) List function parameters.

Mesh and MeshVariables

Mesh and MeshVariable objects form the basis for numerical PDE solutions.

uw.mesh.FeMesh_Cartesian:
This class generates a regular cartesian mesh.

Useful methods:
data: (Property) Access mesh vertex coordinate data.
deform_mesh(): (Context manager) Allow mesh deformation.
reset(): Reset the mesh to its original configuration.
specialSets: (Dict) Dictionary of special vertex sets associated with the mesh.

uw.mesh.MeshVariable:
The MeshVariable class adds data at each vertex of the mesh.

Useful methods:
data: (Property) Access variable data.

Example:

```
import underworld as uw
mesh = uw.mesh.FeMesh_Cartesian(elementRes=( 4, 4 ),
                                minCoord=( 0., 0. ),
                                maxCoord=( 1., 1. ))
meshvar = uw.mesh.MeshVariable(mesh, 1)
meshvar.data[:] = 0.       # initialise data to zero
with mesh.deform_mesh():  # deform mesh
  mesh.data[0] = (-0.1,-0.1)
```

Swarms and SwarmVariables

Swarms define arbitrarily located points which may be used to define complex geometries for your dynamics.

uw.swarm.Swarm:
The Swarm class provides a container for particles.

Useful methods:
particleLocalCount: (Property) Returns the swarm local particle count.
particleGlobalCount: (Property) Returns the swarm global particle count.
populate_using_layout(): Populate the swarm globally using provided layout object.
add_particles_with_coordinates(): Populate the swarm using provided coordinates array.
add_variable(): Adds a SwarmVariable to the swarm. Returns the SwarmVariable object.
particleCoordinates: (Property) Handle to the swarm's particle coordinates SwarmVariable.

uw.swarm.SwarmVariable:
The SwarmVariable class adds data to each particle. Note that you will usually create swarm variables via the **add_variable()** method on your swarm object.

Useful methods:
data: (Property) Access the swarm variables underlying data.

Example:

```
import underworld as uw
mesh = uw.mesh.FeMesh_Cartesian()
swarm = uw.swarm.Swarm(mesh)
svar = swarm.add_variable('int',1)
layout = uw.swarm.layouts.PerCellSpaceFillerLayout(swarm,20)
swarm.populate_using_layout(layout)
```

Systems and Conditions

The systems and conditions modules houses PDE related classes.

uw.systems.SteadyStateHeat:
This class implements FEM to constructs an SLE representation of a steady state heat equation of the form:

$$\nabla(k\nabla)T = h$$

uw.systems.Stokes:
This class implements FEM to constructs an SLE representation of a Stokes type system of the form:

$$\tau_{ij,j} - p_{,i} + f_i = 0$$

uw.systems.Solver:
This class returns a solver appropriate for the provide SLE object.

Useful methods:
solve(): Solve the system.

uw.systems.AdvectionDiffusion:
This class constructs an SUPG implementation of an Advection-Diffusion type system of the form:

$$\frac{\partial\phi}{\partial t} + \mathbf{u}\cdot\nabla\phi = \nabla(k\nabla\phi)$$

Useful methods:
get_max_dt(): Returns a CFL type timestep size.
integrate(): Integrate forward in time for provided time interval.

uw.systems.SwarmAdvector:
This class implements a time integration scheme to advect swarm particles using a provided velocity.

Useful methods:
get_max_dt(): Returns a CFL type timestep size.
integrate(): Integrate forward in time for provided time interval.

uw.conditions.DirichletCondition:
This class implements a Dirichlet condition at the specified nodes.

uw.conditions.NeumannCondition:
This class implements a Neumann condition at the specified nodes.

Example:

```
import underworld as uw
mesh = uw.mesh.FeMesh_Cartesian()
temp_var = uw.mesh.MeshVariable( mesh, 1 )
bISet = mesh.specialSets["MinJ_VertexSet"]  # grab bottom set
tISet = mesh.specialSets["MaxJ_VertexSet"]  # grab top set
bcs = uw.conditions.DirichletCondition(temp_var,
                    indexSetsPerDof=bISet+tISet)
temp_var.data[bISet.data] = 1.  # set bottom BC value
temp_var.data[tISet.data] = 0.  # set top BC value
thermal_system = uw.systems.SteadyStateHeat(temp_var,
                                            fn_diffusivity=1.,
                                            conditions=[bcs,])
solver = uw.systems.Solver(thermal_system)
solver.solve()
```

Functions

Functions provide a high level interface to your modelling data and allow you to define model behaviours. Functions are overloaded with the +,-,*,-,[] and ** operators.

uw.function.Function:
This is an abstract class. Any class which inherits from this class is able to behave as a function object.

Useful methods:
evaluate(): Evaluate the function at the provided coordinate or coordinate array. Returns an array of results.

uw.function.coord:
This function returns the coordinate at the evaluation position.

uw.function.analytic:
This module contains various analytic solutions functions.

uw.function.branching:
This module contains various branching functions.

uw.function.exception:
This module contains functions which raise exceptions when things go wrong.

uw.function.math:
This module contains elementary mathematical functions.

uw.function.rheology:
This module contains a function which implements a stress limiting viscosity.

uw.function.shape:
This module contains a Polygon shape.

uw.function.tensor:
This module contains functions for tensor relations.

Visualisation

The Underworld visualisation engine is called **glucifer**.

glucifer.Figure:
The Figure class is the basic container object for visualisation.

Useful methods:
show(): Show the rendered image.
save_image(): Save a rendered image to disk.
append(): Append a drawing object.
clear(): Clear the figure of drawing objects.

glucifer.objects.Drawing:
Subclasses of this class provide the ingredients you will compose your visualisations with. This is an abstract class so you will never use it directly.

glucifer.objects.Mesh:
Draw the provided mesh object.

glucifer.objects.Surface:
Draws the provided function across a mesh surface.

glucifer.objects.Points:
Draws the provided swarm, using functions to determine point attributes.

glucifer.objects.VectorArrows:
Draws the vector arrows across a mesh corresponding to a provided vector function.

glucifer.objects.Volume:
Performs a volume render of the provided function within the provided mesh.

Example:

```
import underworld as uw
import glucifer
fig = glucifer.Figure()
mesh = uw.mesh.FeMesh_Cartesian() # create something to draw
fig.append( glucifer.objects.Mesh(mesh) )
fig.show()
```