

Configuration Coreswitch :

```
hostname FLO-SW-CORE-01
no ip domain-lookup
service password-encryption
```

```
# SSH
ip domain-name lab.local
crypto key generate rsa modulus 2048
username admin secret cisco
ip ssh version 2
access-list 10 permit 172.17.4.0 0.0.0.7
line vty 0 4
access-class 10 in
login local
transport input ssh
```

```
# Spanning-tree
spanning-tree mode rapid-pvst
spanning-tree portfast default
spanning-tree bpduguard default
spanning-tree portfast bpduguard
```

```
# Création des vlans
vlan 10
name users
vlan 20
name wifi
vlan 30
name servers
vlan 40
name mngmt
vlan 50
name inter
```

```
# Conf des int VLAN
int vlan 10
ip addr 172.17.1.254 255.255.255.0
ip helper-address 172.17.3.1
no sh
```

```
int vlan 20
ip addr 172.17.2.254 255.255.255.0
ip helper-address 172.17.3.1
no sh
```

```
int vlan 30
ip addr 172.17.3.6 255.255.255.248
```

```
ip helper-address 172.17.3.1
no sh
```

```
int vlan 40
ip addr 172.17.4.6 255.255.255.248
ip helper-address 172.17.3.1
no sh
```

```
int vlan 50
ip addr 172.17.5.2 255.255.255.252
ip helper-address 172.17.3.1
no sh
```

```
# Port-channel
```

```
int range g2/0/47-48
  channel-group 1 mode active
  no sh
  exit
```

```
int port-channel 1
  switchport mode access
  switchport access vlan 50
  description connexion inter
  no sh
  exit
```

```
int range g2/0/45-46
  channel-group 2 mode active
  no sh
  exit
```

```
int port-channel 2
  switchport mode trunk
  switchport trunk allowed vlan 10,20,30,40,50
  description connexion switch
  no sh
  exit
```

```
# Activer routage IP
```

```
ip routing
```

```
# Pour wipe switch
```

```
write erase
delete flash:vlan.dat
reload
no
```

```
# Conf OSPF
router ospf 1
router-id 172.17.5.2
```

```
network 172.17.0.0 0.0.0.255 area 0
network 172.17.0.0 0.0.0.255 area 0
network 172.17.0.0 0.0.0.7 area 0
network 172.17.0.0 0.0.0.7 area 0
network 172.17.0.0 0.0.0.3 area 0
```

```
# Sécu OSPF
int vlan 50
ip ospf authentication message-digest
ip ospf message-digest-key 1 md5 admin01
```

```
# Ports vers Access Switch
int Te2/1/4
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40
```

Le core switch fonctionne en layer 3, il assure le routage inter-VLAN via des interfaces SVI et échange dynamiquement les routes avec le firewall grâce à OSPF sécurisé.

L'area 0 est le backbone OSPF. Elle est obligatoire et centralise l'échange des routes entre toutes les autres zones. Dans notre infrastructure, l'ensemble des équipements participe à l'area 0 afin de simplifier l'architecture et garantir la stabilité du routage.

Pour connexion avec third partie (prestataire externe) utilisation tunnel (virtuel ou pas) qui crypte données (ipsec)