CDO User Guide

Climate Data Operator Version 2.1.1 November 2022

Uwe Schulzweida – MPI for Meteorology

| 1.1. Installation 1.1.1. Unix 1.1.2 MacOS 1.1.3. Windows 1.2 Usage 1.2.1. Options 1.2.2. Environment variables 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10. Percentile 1.10. Percentile 1.10. Percentile 1.10. Procentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2.1. APPLY - Apply operators 2.2.2. COPY - Copy datasets | 7 | | | | | | | | | | | | | | | n | oductio | 1. Intro | 1. |
|--|----|------|--|--|------------------|-----|-----|----|-----|-----|--------------|----------|-------|---------|--------------|-------------|---------|----------|----|
| 1.1.1. Unix 1.1.2. MacOS 1.1.3. Windows 1.2. Usage 1.2.1. Options 1.2.2. Environment variables 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show artiributes 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2. File operations 2.2. APPLY - Apply operators | 7 | | | | | | | | | | | | | | | | | | |
| 1.1.2. MacOS 1.1.3. Windows 1.2. Usage 1.2.1. Options 1.2.2. Environment variables 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWATTRIBUTE - Show attributes 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | Unix | 1.1.1. | | |
| 1.1.3. Windows 1.2. Usage 1.2.1. Options 1.2.2. Environment variables 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile 1.10.1. Percentile 2.1.1. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.2.1 Options 1.2.2 Environment variables 1.2.3 Operators 1.2.4 Parallelized operators 1.2.5 Operator parameter 1.2.6 Operator chaining 1.2.7 Chaining Benefits 1.3 Advanced Usage 1.3.1 Wildcards 1.3.2 Argument Groups 1.3.3 Apply Keyword 1.4 Memory Requirements 1.5 Horizontal grids 1.5.1 Grid area weights 1.5.2 Grid description 1.5.3 ICON - Grid File Server 1.6 Z-axis description 1.7 Time axis 1.7.1 Absolute time 1.7.2 Relative time 1.7.3 Conversion of the time 1.8 Parameter table 1.9 Missing values 1.9.1 Mean and average 1.10 Percentile 1.10.1 Percentile over timesteps 1.11 Regions 2. Reference manual 2.1 Information 2.1.1 INFO - Information and simple statistics 2.1.2 SINFO - Short information 2.1.3 DIFF - Compare two datasets field by field 2.1.4 NINFO - Print the number of parameters, levels or times 2.1.5 SHOWINFO - Show variables, levels or times 2.1.6 SHOWATTRIBUTE - Show attributes 2.1.7 FILEDES - Dataset description 2.2. File operations 2.2.1 APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.2.1 Options 1.2.2 Environment variables 1.2.3 Operators 1.2.4 Parallelized operators 1.2.5 Operator parameter 1.2.6 Operator chaining 1.2.7 Chaining Benefits 1.3 Advanced Usage 1.3.1 Wildcards 1.3.2 Argument Groups 1.3.3 Apply Keyword 1.4 Memory Requirements 1.5 Horizontal grids 1.5.1 Grid area weights 1.5.2 Grid description 1.5.3 ICON - Grid File Server 1.6 Z-axis description 1.7 Time axis 1.7.1 Absolute time 1.7.2 Relative time 1.7.2 Relative time 1.7.3 Conversion of the time 1.8 Parameter table 1.9 Missing values 1.9.1 Mean and average 1.10 Percentile 1.10.1 Percentile over timesteps 1.11 Regions 2.1.1 INFO - Information and simple statistics 2.1.2 SINFO - Short information 2.1.3 DIFF - Compare two datasets field by field 2.1.4 NINFO - Print the number of parameters, levels or times 2.1.5 SHOWINFO - Show variables, levels or times 2.1.6 SHOWINFO - Show variables, levels or times 2.1.6 SHOWINFO - Show variables, levels or times 2.1.7 FILEDES - Dataset description 2.2. File operations 2.2.1 APPLY - Apply operators 2.2.1 A | | | | | | | | | | | | | | | | | | 1.9 | |
| 1.2.2. Environment variables 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWINFO - Show variables, levels or times 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | 1.2. | |
| 1.2.3. Operators 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | - | | | |
| 1.2.4. Parallelized operators 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2. File operations 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.2.5. Operator parameter 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | - | | | |
| 1.2.6. Operator chaining 1.2.7. Chaining Benefits 1.3. Advanced Usage 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2. File operations 2.2.1. IPDPLY - Apply operators | | | | | | | | | | | | | | | _ | | | | |
| 1.2.7. Chaining Benefits 1.3. Advanced Usage | | | | | | | | | | | | | | | • | - | | | |
| 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.3.1. Wildcards 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWINFO - Show variables, levels or times 2.1.7. FILEDES - Dataset description 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | _ | | 4.0 | |
| 1.3.2. Argument Groups 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | 1.3. | |
| 1.3.3. Apply Keyword 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.4. Memory Requirements 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | _ | | 1.3.2. | | |
| 1.5. Horizontal grids 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10.1. Percentile 1.10.1. Percentile 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | • | | | | |
| 1.5.1. Grid area weights 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.5.2. Grid description 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 17 | | | | | | | | | | | | | | | ntal grids | Horizo | 1.5. | |
| 1.5.3. ICON - Grid File Server 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 1.6. Z-axis description 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 18 | | | | | | | | | | | | | | ription | Grid desc | 1.5.2. | | |
| 1.7. Time axis 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 22 | | | | | | | | | | | | | erver . | rid File Ser | ICON - G | 1.5.3. | | |
| 1.7.1. Absolute time 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile 1.10.1. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 22 | | | | | | | | | | | | | | n | description | Z-axis | 1.6. | |
| 1.7.2. Relative time 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 23 | | | | | | | | | | | | | | | axis | Time a | 1.7. | |
| 1.7.3. Conversion of the time 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 23 | | | | | | | | | | | | | | time | Absolute | 1.7.1. | | |
| 1.8. Parameter table 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 23 | | | | | | | | | | | | | | ime | Relative t | 1.7.2. | | |
| 1.9. Missing values 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 24 | | | | | | | | | | | | | me | n of the tin | Conversio | 1.7.3. | | |
| 1.9.1. Mean and average 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 24 | | | | | | | | | | | | | | | eter table | Param | 1.8. | |
| 1.10. Percentile 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 24 | | | | | | | | | | | | | | | g values. | Missin | 1.9. | |
| 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 25 | | | | | | | | | | | | | | l average . | Mean and | 1.9.1. | | |
| 1.10.1. Percentile over timesteps 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | 1.10 | |
| 1.11. Regions 2. Reference manual 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | | | |
| 2.1. Information 2.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | - | | | | 1.11 | |
| 2.1. Information 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | 3.0 | | |
| 2.1.1. INFO - Information and simple statistics 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 28 | | | | | | | | | | | | | | | | | | 2. |
| 2.1.2. SINFO - Short information 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 29 | | | | | | | | | | | | | | | ation | Inform | 2.1. | |
| 2.1.3. DIFF - Compare two datasets field by field 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 30 | | | | | | | | | | stics | e statis | impl | and si | nformation | INFO - Ir | 2.1.1. | | |
| 2.1.4. NINFO - Print the number of parameters, levels or times 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 31 | | | | | | | | | | | | n . | matio | Short inform | SINFO - | 2.1.2. | | |
| 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 32 | | | | | | | | | 1. | y fiel | field b | asets | o data | ompare two | DIFF - C | 2.1.3. | | |
| 2.1.5. SHOWINFO - Show variables, levels or times 2.1.6. SHOWATTRIBUTE - Show attributes 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | 33 | | | | \mathbf{S} | nes | tim | or | els | lev | ${ m eters}$ | param | er of | numbe | Print the n | NINFO - | 2.1.4. | | |
| 2.1.6. SHOWATTRIBUTE - Show attributes | | | | | | | | | | | | _ | | | | | 2.1.5. | | |
| 2.1.7. FILEDES - Dataset description 2.2. File operations 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | | | | | 2.1.6. | | |
| 2.2. File operations | | | | | | | | | | | | | | | | | | | |
| 2.2.1. APPLY - Apply operators | | | | | | | | | | | | | _ | | | | | 2.2. | |
| | | | | | | | | | | | | | | | | | _ | | |
| <u></u> | | | | | | | | | | | | | | | | | | | |
| 2.2.3. TEE - Duplicate a data stream and write it to file | | | | | | | | | | | | | | | - 0 | | | | |
| 2.2.4. PACK - Pack data | | | | | | | | | | | | | | | - | | | | |
| 2.2.5. BITROUNDING - Bit rounding | | | | | | | | | | | | | | | | | | | |
| 2.2.6. REPLACE - Replace variables | | | | | | | | | | | | _ | | | | | | | |

| | 9.2.7 | DUPLICATE - Duplicates a dataset |
|------|---------|--|
| | | |
| | | 0 0 |
| | | MERGE - Merge datasets |
| | 2.2.10. | SPLIT - Split a dataset |
| | 2.2.11. | SPLITTIME - Split timesteps of a dataset |
| | | SPLITSEL - Split selected timesteps |
| | | DISTGRID - Distribute horizontal grid |
| | | COLLGRID - Collect horizontal grid |
| 2.0 | | |
| 2.3. | | on |
| | | SELECT - Select fields |
| | | SELMULTI - Select multiple fields via GRIB1 parameters |
| | 2.3.3. | SELVAR - Select fields |
| | | SELTIME - Select timesteps |
| | | SELBOX - Select a box |
| | | |
| | | $oldsymbol{arphi}$ |
| | | SELGRIDCELL - Select grid cells |
| | | SAMPLEGRID - Resample grid |
| | 2.3.9. | SELYEARIDX - Select year by index |
| | 2.3.10. | SELSURFACE - Extract surface |
| 2.4. | | ional selection |
| | | COND - Conditional select one field |
| | | COND2 - Conditional select two fields |
| | | |
| | | CONDC - Conditional select a constant |
| | | MAPREDUCE - Reduce fields to user-defined mask |
| 2.5. | Compa | urison |
| | 2.5.1. | COMP - Comparison of two fields |
| | 2.5.2. | COMPC - Comparison of a field with a constant |
| 2.6. | | cation |
| 2.0. | | SETATTRIBUTE - Set attributes |
| | | |
| | | SETPARTAB - Set parameter table |
| | | SET - Set field info |
| | | SETTIME - Set time |
| | 2.6.5. | CHANGE - Change field header |
| | 2.6.6. | SETGRID - Set grid information |
| | 2.6.7. | SETZAXIS - Set z-axis information |
| | | INVERT - Invert latitudes |
| | | INVERTLEV - Invert levels |
| | | |
| | | SHIFTXY - Shift field |
| | | MASKREGION - Mask regions |
| | 2.6.12. | MASKBOX - Mask a box |
| | 2.6.13. | SETBOX - Set a box to constant |
| | 2.6.14. | ENLARGE - Enlarge fields |
| | | SETMISS - Set missing value |
| | | SETGRIDCELL - Set the value of a grid cell |
| 0.7 | | |
| 2.7. | | netic |
| | 2.7.1. | EXPR - Evaluate expressions |
| | 2.7.2. | MATH - Mathematical functions |
| | 2.7.3. | ARITHC - Arithmetic with a constant |
| | 2.7.4. | ARITH - Arithmetic on two datasets |
| | 2.7.5. | DAYARITH - Daily arithmetic |
| | 2.7.6. | MONARITH - Monthly arithmetic |
| | | |
| | 2.7.7. | YEARARITH - Yearly arithmetic |
| | 2.7.8. | YHOURARITH - Multi-year hourly arithmetic |
| | 2.7.9. | YDAYARITH - Multi-year daily arithmetic |
| | | YMONARITH - Multi-year monthly arithmetic |
| | 2.7.11. | YSEASARITH - Multi-year seasonal arithmetic |
| | | ARITHDAYS - Arithmetic with days |
| | | ARITHLAT - Arithmetic with latitude |
| | | 111111111111111111111111111111111 |

| 2.8. | | ical values |
|-------|---------|---|
| | | TIMCUMSUM - Cumulative sum over all timesteps |
| | | CONSECSTAT - Consecute timestep periods |
| | 2.8.3. | VARSSTAT - Statistical values over all variables |
| | 2.8.4. | ENSSTAT - Statistical values over an ensemble |
| | | ENSSTAT2 - Statistical values over an ensemble |
| | 2.8.6. | ENSVAL - Ensemble validation tools |
| | 2.8.7. | FLDSTAT - Statistical values over a field |
| | 2.8.8. | ZONSTAT - Zonal statistical values |
| | 2.8.9. | MERSTAT - Meridional statistical values |
| | 2.8.10. | GRIDBOXSTAT - Statistical values over grid boxes |
| | | REMAPSTAT - Remaps source points to target cells |
| | | VERTSTAT - Vertical statistical values |
| | | TIMSELSTAT - Time range statistical values |
| | | TIMSELPCTL - Time range percentile values |
| | | RUNSTAT - Running statistical values |
| | | RUNPCTL - Running percentile values |
| | | TIMSTAT - Statistical values over all timesteps |
| | | TIMPCTL - Percentile values over all timesteps |
| | | |
| | | HOURSTAT - Hourly statistical values |
| | | HOURPCTL - Hourly percentile values |
| | | DAYSTAT - Daily statistical values |
| | | DAYPCTL - Daily percentile values |
| | | MONSTAT - Monthly statistical values |
| | | MONPCTL - Monthly percentile values |
| | | YEARMONSTAT - Yearly mean from monthly data |
| | | YEARSTAT - Yearly statistical values |
| | | YEARPCTL - Yearly percentile values |
| | 2.8.28. | SEASSTAT - Seasonal statistical values |
| | 2.8.29. | SEASPCTL - Seasonal percentile values |
| | 2.8.30. | YHOURSTAT - Multi-year hourly statistical values |
| | 2.8.31. | DHOURSTAT - Multi-day hourly statistical values |
| | 2.8.32. | YDAYSTAT - Multi-year daily statistical values |
| | 2.8.33. | YDAYPCTL - Multi-year daily percentile values |
| | | YMONSTAT - Multi-year monthly statistical values |
| | | YMONPCTL - Multi-year monthly percentile values |
| | | YSEASSTAT - Multi-year seasonal statistical values |
| | | YSEASPCTL - Multi-year seasonal percentile values |
| | | YDRUNSTAT - Multi-year daily running statistical values |
| | | YDRUNPCTL - Multi-year daily running percentile values |
| 2.9. | | ation and co |
| 2.5. | 2.9.1. | FLDCOR - Correlation in grid space |
| | 2.9.1. | TIMCOR - Correlation over time |
| | 2.9.3. | FLDCOVAR - Covariance in grid space |
| | 2.9.4. | TIMCOVAR - Covariance over time |
| 9.10 | | |
| 2.10. | _ | |
| | | REGRES - Regression |
| | | DETREND - Detrend time series |
| | | TREND - Trend of time series |
| | | TRENDARITH - Add or subtract a trend |
| 2.11. | EOFs | 173 |
| | | EOFS - Empirical Orthogonal Functions |
| | | EOFCOEFF - Principal coefficients of EOFs |
| 2.12. | | blation |
| | | REMAPBIL - Bilinear interpolation |
| | | REMAPBIC - Bicubic interpolation |
| | | REMAPNN - Nearest neighbor remapping |
| | 2.12.4. | REMAPDIS - Distance weighted average remapping |

| | | 2.12.5. REMAPCON - First order conservative remapping | 182 |
|----|------|--|-------------------|
| | | 2.12.6. REMAPCON2 - Second order conservative remapping | 184 |
| | | 2.12.7. REMAPLAF - Largest area fraction remapping | 186 |
| | | 2.12.8. REMAP - Grid remapping | 187 |
| | | 2.12.9. REMAPETA - Remap vertical hybrid level | 188 |
| | | 2.12.10.VERTINTML - Vertical interpolation | 190 |
| | | 2.12.11.VERTINTAP - Vertical pressure interpolation | |
| | | 2.12.12.VERTINTGH - Vertical height interpolation | |
| | | 2.12.13INTLEVEL - Linear level interpolation | |
| | | 2.12.14INTLEVEL3D - Linear level interpolation from/to 3D vertical coordinates | 193 |
| | | 2.12.15INTTIME - Time interpolation | |
| | | 2.12.16JNTYEAR - Year interpolation | |
| | 2.13 | . Transformation | |
| | | 2.13.1. SPECTRAL - Spectral transformation | |
| | | 2.13.2. SPECCONV - Spectral conversion | |
| | | 2.13.3. WIND2 - D and V to velocity potential and stream function | |
| | | 2.13.4. WIND - Wind transformation | |
| | | 2.13.5. FOURIER - Fourier transformation | |
| | 2.14 | . Import/Export | |
| | | 2.14.1. IMPORTBINARY - Import binary data sets | |
| | | 2.14.2. IMPORTCMSAF - Import CM-SAF HDF5 files | |
| | | 2.14.3. IMPORTAMSR - Import AMSR binary files | |
| | | 2.14.4. INPUT - Formatted input | |
| | | 2.14.5. OUTPUT - Formatted output | |
| | | 2.14.6. OUTPUTTAB - Table output | |
| | | 2.14.7. OUTPUTGMT - GMT output | |
| | 2.15 | . Miscellaneous | |
| | | 2.15.1. GRADSDES - GrADS data descriptor file | |
| | | 2.15.2. AFTERBURNER - ECHAM standard post processor | |
| | | 2.15.3. FILTER - Time series filtering | |
| | | 2.15.4. GRIDCELL - Grid cell quantities | 217 |
| | | 2.15.5. SMOOTH - Smooth grid points | 218 |
| | | 2.15.6. DELTAT - Difference between timesteps | 218 |
| | | 2.15.7. REPLACEVALUES - Replace variable values | 219 |
| | | 2.15.8. VARGEN - Generate a field | 220 |
| | | 2.15.9. TIMSORT - Timsort | |
| | | 2.15.10.WINDTRANS - Wind Transformation | |
| | | 2.15.11ROTUVB - Rotation | 223 |
| | | 2.15.12MROTUVB - Backward rotation of MPIOM data | 223 |
| | | 2.15.13.MASTRFU - Mass stream function | 224 |
| | | 2.15.14.DERIVEPAR - Derived model parameters | |
| | | 2.15.15ADISIT - Potential temperature to in-situ temperature and vice versa | |
| | | 2.15.16.RHOPOT - Calculates potential density | 225 |
| | | 2.15.17.HISTOGRAM - Histogram | |
| | | 2.15.18SETHALO - Set the left and right bounds of a field | |
| | | 2.15.19.WCT - Windchill temperature | |
| | | 2.15.20FDNS - Frost days where no snow index per time period | |
| | | 2.15.21 STRWIN - Strong wind days index per time period | |
| | | 2.15.22STRBRE - Strong breeze days index per time period | |
| | | 2.15.23STRGAL - Strong gale days index per time period | |
| | | 2.15.24.HURR - Hurricane days index per time period | |
| | | 2.15.25.CMORLITE - CMOR lite | |
| | | 2.15.26.VERIFYGRID - Verify grid coordinates | 230 |
| 2 | Con | tributors | 23 |
| J. | | | 23. 231 |
| | | External sources | |
| | | | $\frac{231}{231}$ |

| Content |
|---------|
| |

| A. Environment Variables | 235 |
|--|-----|
| B. Parallelized operators | 236 |
| C. Standard name table | 238 |
| D. Grid description examples D.1. Example of a curvilinear grid description | |
| Operator index | 241 |

1. Introduction

The Climate Data Operator (**CDO**) software is a collection of many operators for standard processing of climate and forecast model data. The operators include simple statistical and arithmetic functions, data selection and subsampling tools, and spatial interpolation. **CDO** was developed to have the same set of processing functions for GRIB [GRIB] and NetCDF [NetCDF] datasets in one package.

The Climate Data Interface [CDI] is used for the fast and file format independent access to GRIB and NetCDF datasets. The local MPI-MET data formats SERVICE, EXTRA and IEG are also supported.

There are some limitations for GRIB and NetCDF datasets:

GRIB datasets have to be consistent, similar to NetCDF. That means all time steps need to have the same variables, and within a time step each variable may occur only once. Multiple fields in single GRIB2 messages are not supported!

NetCDF datasets are only supported for the classic data model and arrays up to 4 dimensions. These dimensions should only be used by the horizontal and vertical grid and the time. The NetCDF attributes should follow the GDT, COARDS or CF Conventions.

The main **CDO** features are:

- More than 700 operators available
- Modular design and easily extendable with new operators
- Very simple UNIX command line interface
- A dataset can be processed by several operators, without storing the interim results in files
- Most operators handle datasets with missing values
- Fast processing of large datasets
- Support of many different grid types
- Tested on many UNIX/Linux systems, Cygwin, and MacOS-X

Latest pdf documentation be found here.

1.1. Installation

CDO is supported in different operative systems such as Unix, macOS and Windows. This section describes how to install **CDO** in those platforms. More examples are found on the main website (https://code.mpimet.mpg.de/projects/cdo/wiki)

1.1.1. Unix

1.1.1.1. Prebuilt CDO packages

Prebuilt **CDO** versions are available in online Unix repositories, and you can install them by typing on the Unix terminal

```
apt-get install cdo
```

Note that prebuilt libraries do not offer the most recent version, and their version might vary with the Unix system (see table below). It is recommended to build from the source or Conda environment for an updated version or a customised setting.

Installation Introduction

| Un | CDO Version | |
|----------|----------------------|----------|
| | 11 (Bullseye) | 1.9.10-1 |
| Debian | 10 (Buster) | 1.9.6-1 |
| | Sid | 2.0.6-2 |
| FreeBSD | 13 | 2.0.6 |
| rieepsp | 12 | 2.0.6 |
| openSUSE | Leap 15.3 | 2.0.6 |
| opensosi | Tumbleweed | 2.0.6-1 |
| | 18.04 LTS | 1.9.3 |
| Ubuntu | $20.04~\mathrm{LTS}$ | 1.9.9 |
| | $22.04 \ LTS$ | 2.0.4-1 |

1.1.1.2. Building from sources

CDO uses the GNU configure and build system for compilation. The only requirement is a working ISO C++17 and C11 compiler.

First go to the download page (https://code.mpimet.mpg.de/projects/cdo) to get the latest distribution, if you do not have it yet.

To take full advantage of CDO features the following additional libraries should be installed:

- Unidata NetCDF library (https://www.unidata.ucar.edu/software/netcdf) version 3 or higher. This library is needed to process NetCDF [NetCDF] files with CDO.
- ECMWF ecCodes library (https://software.ecmwf.int/wiki/display/ECC/ecCodes+Home) version 2.3.0 or higher. This library is needed to process GRIB2 files with **CDO**.
- HDF5 szip library (https://www.hdfgroup.org/doc_resource/SZIP) version 2.1 or higher. This library is needed to process szip compressed GRIB [GRIB] files with CDO.
- HDF5 library (https://www.hdfgroup.org) version 1.6 or higher.
 This library is needed to import CM-SAF [CM-SAF] HDF5 files with the CDO operator import_cmsaf.
- PROJ library (https://proj.org) version 5.0 or higher.

 This library is needed to convert Sinusoidal and Lambert Azimuthal Equal Area coordinates to geographic coordinates, for e.g. remapping.
- Magics library (https://software.ecmwf.int/wiki/display/MAGP/Magics) version 2.18 or higher. This library is needed to create contour, vector and graph plots with CDO.

CDO is a multi-threaded application. Therefore all the above libraries should be compiled thread safe. Using non-threadsafe libraries could cause unexpected errors!

Compilation

Compilation is done by performing the following steps:

1. Unpack the archive, if you haven't done that yet:

```
gunzip cdo-$VERSION.tar.gz  # uncompress the archive
tar xf cdo-$VERSION.tar  # unpack it
cd cdo-$VERSION
```

2. Run the configure script:

```
./configure
```

• Optionaly with NetCDF [NetCDF] support:

Introduction Installation

```
./configure --with-netcdf=<NetCDF root directory>
```

• and with ecCodes:

```
./configure --with-eccodes=<ecCodes root directory>
```

For an overview of other configuration options use

```
./configure --help
```

3. Compile the program by running make:

make

The program should compile without problems and the binary (cdo) should be available in the src directory of the distribution.

Installation

After the compilation of the source code do a make install, possibly as root if the destination permissions require that.

```
make install
```

The binary is installed into the directory can be changed with the --prefix option of the configure script.

Alternatively, you can also copy the binary from the src directory manually to some bin directory in your search path.

1.1.1.3. Conda

Conda is an open-source package manager and environment management system for various languages (Python, R, etc.). Conda is installed via Anaconda or Miniconda. Unlike Anaconda, miniconda is a lightweight conda distribution. They can be dowloaded from the main conda Website (https://conda.io/projects/conda/en/latest/user-guide/install/linux.html) or on the terminal

```
wget https://repo.anaconda.com/archive/Anaconda3-2021.11-Linux-x86_64.sh bash Anaconda3-2021.11-Linux-x86_64.sh source ~/.bashrc
```

and

```
wget https://repo.continuum.io/miniconda/Miniconda3-latest-Linux-x86_64.sh sh Miniconda3-latest-Linux-x86_64.sh
```

Upon setting your conda environment, you can install **CDO** using conda

```
conda install cdo
conda install python-cdo
```

1.1.2. MacOS

Among the MacOS package managers, **CDO** can be installed from Homebrew and Macports. The installation via Homebrew is straight forward process on the terminal

```
brew install cdo
```

Installation Introduction

Similarly, Macports

```
port install cdo
```

In contrast to Homebrew, Macport allows you to enable GRIB2, szip compression and Magics++ graphic in **CDO** installation.

```
port install cdo +grib_api +magicspp +szip
```

In addition, you could also set **CDO** via Conda as Unix. You can follow this tutorial to install anaconda or miniconda in your computer (https://conda.io/projects/conda/en/latest/user-guide/install/macos.html). Then, you can install cdo by

```
conda install -c conda-forge cdo
```

1.1.3. Windows

Currently, **CDO** is not supported in Windows system and the binary is not available in the windows conda repository. Therefore, **CDO** needs to be set in a virtual environment. Here, it covers the installation of **CDO** using Windows Subsystem Linux (WSL) and virtual machines.

1.1.3.1. WSL

WSL emulates Unix in your Windows system. Then, you can install Unix libraries and software such as **CDO** or the linux conda distribution in your computer. Also, it allows you to directly share your files between your Windows and the WSL environment. However, more complex functions that require a graphic interface are not allowed.

In Windows 10 or newer, WSL can be readily set in your cmd by typing

```
wsl --install
```

This command will install, by default, Ubuntu 20.04 in WSL2. You could also choose a different system from this list.

```
wsl -l -o
```

Then, you can install your WSL environment as

```
wsl --install -d NAME
```

1.1.3.2. Virtual machine

Virtual machines can emulate different operative systems in your computer. Virtual machines are guest computers mounted inside your host computer. You can set a Linux distribution in your Windows device in this particular case. The advantages of Virtual machines to WSL are the graphical interface and the fully operational Linux system. You can follow any tutorial on the internet such as this one

https://ubuntu.com/tutorials/how-to-run-ubuntu-desktop-on-a-virtual-machine-using-virtualbox#1-overview

Finally, you can install **CDO** following any method listed in the section 1.1.1.

Introduction Usage

1.2. Usage

This section descibes how to use **CDO**. The syntax is:

```
[ Options ] Operator1 [ -Operator2 [ -OperatorN ] ]
```

1.2.1. **Options**

All options have to be placed before the first operator. The following options are available for all operators:

Generate an absolute time axis.

-b < nbits >Set the number of bits for the output precision. The valid precisions depend on the file format:

| <format></format> | < nbits > |
|--------------------------|--------------------|
| grb1, grb2 | P1 - P24 |
| nc1, nc2, nc4, nc4c, nc5 | I8/I16/I32/F32/F64 |
| nc4, nc4c, nc5 | U8/U16/U32 |
| grb2, srv, ext, ieg | F32/F64 |

For srv, ext and ieg format the letter L or B can be added to set the byteorder to Little or Big endian.

--cmor CMOR conform NetCDF output.

-C, --colorColorized output messages.

--double Using double precision floats for data in memory. --eccodes Use ecCodes to decode/encode GRIB1 messages. -f < format >Set the output file format. The valid file formats are:

| File format | <format></format> |
|----------------------------------|-------------------|
| GRIB version 1 | grb1/grb |
| GRIB version 2 | grb2 |
| NetCDF | nc1 |
| NetCDF version 2 (64-bit offset) | nc2/nc |
| NetCDF-4 (HDF5) | nc4 |
| NetCDF-4 classic | nc4c |
| NetCDF version 5 (64-bit data) | nc5 |
| SERVICE | srv |
| EXTRA | ext |
| IEG | ieg |

GRIB2 is only available if **CDO** was compiled with ecCodes support and all NetCDF file types are only available if **CDO** was compiled with NetCDF support!

Define the default grid description by name or from file (see chapter 1.3 on page 18).

-g < grid >Available grid names are: r<NX>x<NY>, lon=<LON>/lat=<LAT>, F<XXX>, gme<NI>

-h, --helpHelp information for the operators.

--no history Do not append to NetCDF history global attribute.

--netcdf hdr pad, --hdr pad, --header pad <nbr>

Pad NetCDF output header with nbr bytes.

-k < chunktype> NetCDF4 chunk type: auto, grid or lines.

Lock I/O (sequential access). $-I_{J}$

Set the missing value of non NetCDF files (default: -9e+33). -m <missval>

Overwrite existing output file, if checked. -O

Existing output file is checked only for: ens<STAT>, merge, mergetime

--operators List of all operators.

-P < nthreads >Set number of OpenMP threads (Only available if OpenMP support was compiled in).

Warnings count as errors. --pedantic

--percentile < method>

Percentile method: nrank nist rtype8 numpy numpy lower numpy higher numpy nearest

Usage Introduction

--reduce_dim Reduce NetCDF dimensions.

-R, --regular Convert GRIB1 data from global reduced to regular Gaussian grid (only with cgribex lib).

-r Generate a relative time axis.

-S Create an extra output stream for the module TIMSTAT. This stream contains

the number of non missing values for each output period.

-s, --silent Silent mode.

--single Using single precision floats for data in memory.
--sortname Alphanumeric sorting of NetCDF parameter names.

-t <partab> Set the GRIB1 (cgribex) default parameter table name or file (see chapter 1.6 on page 24).

Predefined tables are: echam4 echam5 echam6 mpiom1 ecmwf remo

--timestat_date <srcdate>

Target timestamp (temporal statistics): first, middle, midhigh or last source timestep.

-V, --version Print the version number.

-v, --verbose Print extra details for some operators.

-w Disable warning messages.

--worker < num> Number of worker to decode/decompress GRIB records.

-z szip SZIP compression of GRIB1 records.
jpeg JPEG compression of GRIB2 records.
zip[_1-9] Deflate compression of NetCDF4 variables.

1.2.2. Environment variables

There are some environment variables which influence the behavior of **CDO**. An incomplete list can be found in Appendix A.

Here is an example to set the environment variable CDO_RESET_HISTORY for different shells:

Bourne shell (sh): CDO_RESET_HISTORY=1; export CDO_RESET_HISTORY

Korn shell (ksh): export CDO_RESET_HISTORY=1 C shell (csh): setenv CDO_RESET_HISTORY 1

1.2.3. Operators

There are more than 700 operators available. A detailed description of all operators can be found in the **Reference Manual** section.

1.2.4. Parallelized operators

Some of the **CDO** operators are shared memory parallelized with OpenMP. An OpenMP-enabled C compiler is needed to use this feature. Users may request a specific number of OpenMP threads nthreads with the '-P' switch.

Here is an example to distribute the bilinear interpolation on 8 OpenMP threads:

```
cdo -P 8 remapbil, targetgrid infile outfile
```

Many **CDO** operators are I/O-bound. This means most of the time is spend in reading and writing the data. Only compute intensive **CDO** operators are parallelized. An incomplete list of OpenMP parallelized operators can be found in Appendix B.

1.2.5. Operator parameter

Some operators need one or more parameter. A list of parameter is indicated by the seperator ','.

Introduction Usage

• STRING

String parameters require quotes if the string contains blanks or other characters interpreted by the shell. The following command select variables with the name pressure and tsurf:

```
cdo selvar, pressure, tsurf infile outfile
```

• FLOAT

Floating point number in any representation. The following command sets the range between 0 and 273.15 of all fields to missing value:

```
cdo setrtomiss,0,273.15 infile outfile
```

• BOOL

Boolean parameter in the following representation TRUE/FALSE, T/F or 0/1. To disable the weighting by grid cell area in the calculation of a field mean, use:

```
cdo fldmean, weights=FALSE infile outfile
```

INTEGER

A range of integer parameter can be specified by first/last[/inc]. To select the days 5, 6, 7, 8 and 9 use:

```
cdo selday,5/9 infile outfile
```

The result is the same as:

```
cdo selday,5,6,7,8,9 infile outfile
```

1.2.6. Operator chaining

Operator chaining allows to combine two or more operators on the command line into a single **CDO** call. This allows the creation of complex operations out of more simple ones: reductions over several dimensions, file merges and all kinds of analysis processes. All operators with a fixed number of input streams and one output stream can pass the result directly to an other operator. For differentiation between files and operators all operators must be written with a prepended "-" when chaining.

```
cdo -monmean -add -mulc,2.0 infile1 -daymean infile2 outfile (CDO example call)
```

Here monmean will have the output of add while add takes the output of mulc, 2.0 and daymean. infile1 and infile2 are inputs for their predecessor. When mixing operators with an arbitrary number of input streams extra care needs to be taken. The following examples illustrates why.

- 1. cdo info -timavg infile1 infile2
- 2. cdo info -timavg infile?
- 3. cdo timavg infile1 tmpfile cdo info tmpfile infile2 rm tmpfile

All three examples produce identical results. The time average will be computed only on the first input file.

Note(1): In section 1.3.2 we introduce argument groups which will make this a lot easier and less error prone.

Note(2): Operator chaining is implemented over POSIX Threads (pthreads). Therefore this **CDO** feature is not available on operating systems without POSIX Threads support!

Advanced Usage Introduction

1.2.7. Chaining Benefits

Combining operators can have several benefits. The most obvious is a performance increase through reducing disk I/O:

```
cdo sub -dayavg infile2 -timavg infile1 outfile
```

instead of

```
cdo timavg infile1 tmp1
cdo dayavg infile2 tmp2
cdo sub tmp2 tmp1 outfile
rm tmp1 tmp2
```

Especially with large input files the reading and writing of intermediate files can have a big influence on the overall performance.

A second aspect is the execution of operators: Limited by the algorythms potentially all operators of a chain can run in parallel.

1.3. Advanced Usage

In this section we will introduce advanced features of **CDO**. These include operator grouping which allows to write more complex **CDO** calls and the apply keyword which allows to shorten calls that need an operator to be executed on multiple files as well as wildcards which allow to search paths for file signatures. These features have several restrictions and follow rules that depend on the input/output properties. These required properties of operators can be investigated with the following commands which will output a list of operators that have selected properties:

```
cdo --attribs [arbitrary/filesOnly/onlyFirst/noOutput/obase]
```

- arbitrary describes all operators where the number of inputs is not defined.
- filesOnly are operators that can have other operators as input.
- only First shows which operators can only be at the most left position of the polish notation argument chain.
- noOutput are all operators that do not print to any file (e.g info)
- *obase* Here obase describes an operator that does not use the output argument as file but e.g as a file name base (output base). This is almost exclusivly used for operators the split input files.

```
cdo -splithour baseName_
could result in: baseName_1 baseName_2 ... baseName_N
```

For checking a single or multiple operator directly the following usage of --attribs can be used:

```
cdo --attribs operatorName
```

1.3.1. Wildcards

Wildcards are a standard feature of command line interpreters (shells) on many operating systems. They are placeholder characters used in file paths that are expanded by the interpreter into file lists. For further information the Advance Bash Scripting Guide is a valuable source of information. Handling of input is a central issue for **CDO** and in some circumstances it is not enough to use the wildcards from the shell. That's why **CDO** can handle them on its own.

Introduction Advanced Usage

| all files | 2020-2-01.txt 2020-2-11.txt 2020-2-15.txt 2020-3-01.txt 2020-3-02.txt |
|---------------------------|---|
| | 2020-3-12.txt 2020-3-13.txt 2020-3-15.txt 2021.grb 2022.grb |
| wildcard | filelist results |
| 2020-3* and 2020-3-??.txt | 2020-3-01.txt 2020-3-02.txt 2020-3-12.txt 2020-3-13.txt 2020-3-15.txt |
| 2020-3-?1.txt | 2020-3-01.txt |
| *.grb | 2021.grb 2020.grb |

Use single quotes if the input stream names matched to a single wildcard expression. In this case **CDO** will do the pattern matching and the output can be combined with other operators. Here is an example for this feature:

```
cdo timavg -select,name=temperature 'infile?' outfile
```

In earlier versions of **CDO** this was necessary to have the right files parsed to the right operator. Newer version support this with the argument grouping feature (see 1.3.2). We advice the use of the grouping mechanism instead of the single quoted wildcards since this feature could be deprecated in future versions.

Note: Wildcard expansion is not available on operating systems without the qlob() function!

1.3.2. Argument Groups

In section 1.2.6 we described that it is not possible to chain operators with an arbitrary number of inputs. In this section we want to show how this can be achieved through the use of *operator grouping* with angled brackets []. Using these brackets **CDO** can assigned the inputs to their corresponding operators during the execution of the command line. The ability to write operator combination in a parenthis-free way is partly given up in favor of allowing operators with arbitrary number of inputs. This allows a much more compact way to handle large number of input files.

The following example shows an example which we will transform from a non-working solution to a working one.

```
cdo -infon -div -fldmean -cat infile1 -mulc,2.0 infile2 -fldmax infile3
```

This example will throw the following error:

```
cdo (Warning): Did you forget to use '[' and/or ']' for multiple variable input operators?
cdo (Warning): use option --variableInput, for description
cdo (Abort): Too few streams specified! Operator div needs 2 input streams and 1 output stream!
```

The error is raised by the operator div. This operator needs two input streams and one output stream, but the cat operator has claimed all possible streams on its right hand side as input because it accepts an arbitrary number of inputs. Hence it didn't leave anything for the remaining input or output streams of div. For this we can declare a group which will be passed to the operator left of the group.

```
cdo -infon -div -fldmean -cat [ infile1 -mulc,2.0 infile2 ] -fldmax infile3
```

For full flexibility it is possible to have groups inside groups:

```
cdo -infon -div -fldmean -cat [ fileA1 infileC2 -merge [ infileB1 infileB2 ] ] -fldmax infileD
```

Advanced Usage Introduction

1.3.3. Apply Keyword

When working with medium or large number of similar files there is a common problem of a processing step (often a reduction) which needs to be performed on all of them before a more specific analysis can be applied. Ususally this can be done in two ways: One option is to use merge to glue everything together and chain the reduction step after it. The second option is to write a for-loop over all inputs which perform the basic processing on each of the files separately and call merge one the results. Unfortunately both options have side-effects: The first one needs a lot of memory because all files are read in completely and reduced afterwards while the latter one creates a lot of temporary files. Both memory and disk IO can be bottlenecks and should be avoided.

The *apply* keyword was introduced for that purpose. It can be used as an operator, but it needs at least one operator as a parameter, which is applied in parallel to all related input streams in a parallel way before all streams are passed to operator next in the chain.

The following is an example with three input files:

```
cdo -merge -apply,-daymean [ file1 file2 file3 ] outfile
```

would result in:

```
cdo -merge -daymean file1 -daymean file2 -daymean file3 outfile
```

Figure 1.1.: Usage and result of apply keyword

Apply is especially useful when combined with wildcards. The previous example can be shortened further.

```
cdo -merge -apply,-daymean [ file? ] outfile
```

As shown this feature allows to simplify commands with medium amount of files and to move reductions further back. This can also have a positive impact on the performance.

An example where performance can take a hit.

```
cdo -yearmean -daymean -merge [ f1 ... f40 ]
```

An improved but ugly to write example.

```
cdo -yearmean -merge [ -daymean f1 -daymean f2 ... -daymean f40 ]
```

Apply saves the day. And creates the call above with much less typing.

```
cdo -yearmean -merge [ -apply,-daymean [ f1 ... f40 ] ]
```

Figure 1.2.: Apply keyword simplifies command and execution

In the example in figure 1.2 the resulting call will dramatically save process interaction as well as execution times since the reduction (daymean) is applied on the files first. That means that the merge operator will receive the reduced files and the operations for merging the whole data is saved. For other CDO calls further improvements can be made by adding more arguments to apply (1.3)

A less performant example.

```
cdo -aReduction -anotherReduction -daymean -merge [f1 ... f40]

cdo -merge -apply,"-aReduction -anotherReduction -daymean" [f1 ... f40]
```

Figure 1.3.: Multi argument apply

Restrictions: While the apply keyword can be extremely helpful it has several restrictions (for now!).

- Apply inputs can only be files, wildcards and operators that have 0 inputs and 1 output.
- Apply can not be used as the first **CDO** operator.
- Apply arguments can only be operators with 1 input and 1 output.
- Grouping inside the Apply argument or input is not allowed.

1.4. Memory Requirements

This section roughly describes the memory requirements of **CDO**. **CDO** tries to use as little memory as possible. The smallest unit that is read by all operators is a horizontal field. The required memory depends mainly on the used operators, the data format, the data type and the size of the fields.

The operators have partly very different memory requirements. Many **CDO** modules like FLDSTAT process one horizontal field at a time. Memory-intensive modules such as ENSSTAT and TIMSTAT require all fields of a time step to be held in memory. Of course, the memory requirements of each operator add up when they are combined. Some operators are parallelized with OpenMP. In multi-threaded mode (see option -P) the memory requirement can increase for these operators. This increase grows with the number of threads used.

The data type determines the number of bytes per value. Single precision floating point data (float) occupies 4 bytes per value. All other data types are read as double precision floats and thus occupy 8 bytes per value. With the **CDO** option --single all data is read as single precision floats. This can reduce the memory requirement by a factor of 2.

1.5. Horizontal grids

Physical quantities of climate models are typically stored on a horizonal grid. **CDO** supports structured grids like regular lon/lat or curvilinear grids and also unstructured grids.

1.5.1. Grid area weights

One single point of a horizontal grid represents the mean of a grid cell. These grid cells are typically of different sizes, because the grid points are of varying distance.

Area weights are individual weights for each grid cell. They are needed to compute the area weighted mean or variance of a set of grid cells (e.g. fldmean - the mean value of all grid cells). In **CDO** the area weights are derived from the grid cell area. If the cell area is not available then it will be computed from the geographical coordinates via spherical triangles. This is only possible if the geographical coordinates of the grid cell corners are available or derivable. Otherwise **CDO** gives a warning message and uses constant area weights for all grid cells.

The cell area is read automatically from a NetCDF input file if a variable has the corresponding "cell_measures" attribute, e.g.:

Horizontal grids Introduction

```
var:cell_measures = "area: cell_area" ;
```

If the computed cell area is not desired then the **CDO** operator setgridarea can be used to set or overwrite the grid cell area.

1.5.2. Grid description

In the following situations it is necessary to give a description of a horizontal grid:

- Changing the grid description (operator: setgrid)
- Horizontal interpolation (all remapping operators)
- Generating of variables (operator: const, random)

As now described, there are several possibilities to define a horizontal grid.

1.5.2.1. Predefined grids

Predefined grids are available for global regular, gaussian, HEALPix or icosahedral-hexagonal GME grids.

Global regular grid: global <DXY>

global_<DXY> defines a global regular lon/lat grid. The grid increment <DXY> can be chosen arbitrarily. The longitudes start at $<DXY>/2 - 180^{\circ}$ and the latitudes start at $<DXY>/2 - 90^{\circ}$.

Regional regular grid: dcw:<CountryCode>[_<DXY>]

dcw:<CountryCode>[_<DXY>] defines a regional regular lon/lat grid from the country code. The default value of the optional grid increment <DXY> is 0.1 degree. The ISO two-letter country codes can be found on https://en.wikipedia.org/wiki/ISO_3166-1_alpha-2. For the coordinates of a country CDO uses the DCW (Digital Chart of the World) dataset from GMT. This dataset must be installed on the system and the environment variable DIR_DCW must point to it.

Zonal latitudes: zonal_<DY>

zonal_<DY> defines a grid with zonal latitudes only. The latitude increment <DY> can be chosen arbitrarily. The latitudes start at <DY>/2 - 90° . The boundaries of each latitude are also generated. The number of longitudes is 1. A grid description of this type is needed to calculate the zonal mean (zonmean) for data on an unstructured grid.

Global regular grid: r<NX>x<NY>

r<NX>x<NY> defines a global regular lon/lat grid. The number of the longitudes <NX> and the latitudes <NY> can be chosen arbitrarily. The longitudes start at 0° with an increment of $(360/\langle NX\rangle)^{\circ}$. The latitudes go from south to north with an increment of $(180/\langle NY\rangle)^{\circ}$.

One grid point: lon=<LON>/lat=<LAT>

lon=<LON>/lat=<LAT> defines a lon/lat grid with only one grid point.

Introduction Horizontal grids

Full regular Gaussian grid: F<XXX>

F<XXX> defines a global regular Gaussian grid. XXX specifies the number of latitudes lines between the Pole and the Equator. The longitudes start at 0° with an increment of $(360/\text{nlon})^{\circ}$. The gaussian latitudes go from north to south.

Global icosahedral-hexagonal GME grid: gme<NI>

gme<NI> defines a global icosahedral-hexagonal GME grid. NI specifies the number of intervals on a main triangle side.

HEALPix grid: hp<NSIDE>[b] [_<ORDER>]

HEALPix is an acronym for Hierarchical Equal Area isoLatitude Pixelization of a sphere. hp<NSIDE>[b] [_<ORDER>] defines a global HEALPix grid. The NSIDE parameter controls the resolution of the pixellization. It is the number of pixels on the side of each of the 12 top-level HEALPix pixels. The total number of grid pixels is 12*NSIDE*NSIDE. NSIDE=1 generates the 12 (H=4, K=3) equal sized top-level HEALPix pixels. ORDER sets the index ordering convention of the pixels, available are ring (default) or nest ordering. If the parameter b is set, the grid cell corners are also calculated.

1.5.2.2. Grids from data files

You can use the grid description from an other datafile. The format of the datafile and the grid of the data field must be supported by **CDO**. Use the operator 'sinfo' to get short informations about your variables and the grids. If there are more then one grid in the datafile the grid description of the first variable will be used. Add the extension: N to the name of the datafile to select grid number N.

1.5.2.3. SCRIP grids

SCRIP (Spherical Coordinate Remapping and Interpolation Package) uses a common grid description for curvilinear and unstructured grids. For more information about the convention see [SCRIP]. This grid description is stored in NetCDF. Therefor it is only available if **CDO** was compiled with NetCDF support!

SCRIP grid description example of a curvilinear MPIOM [MPIOM] GROB3 grid (only the NetCDF header):

```
netcdf grob3s {
dimensions:
         grid\_size = 12120;
         grid\_corners = 4;
         grid\_rank = 2;
variables:
         int grid_dims(grid_rank) ;
         double grid_center_lat(grid_size);
                   grid_center_lat:units = "degrees";
                   grid_center_lat:bounds = "grid_corner_lat" ;
         double grid_center_lon(grid_size) ;
    grid_center_lon:units = "degrees" ;
                   grid_center_lon:bounds = "grid_corner_lon" ;
         int grid_imask(grid_size)
                   grid_imask:units = "unitless"
                   grid_imask:coordinates = "grid_center_lon grid_center_lat" ;
         double grid_corner_lat(grid_size, grid_corners) ;
    grid_corner_lat:units = "degrees" ;
         double grid_corner_lon(grid_size, grid_corners) ;
    grid_corner_lon:units = "degrees" ;
// global attributes:
                   : title = "grob3s";
```

Horizontal grids Introduction

1.5.2.4. CDO grids

All supported grids can also be described with the **CDO** grid description. The following keywords can be used to describe a grid:

| Keyword | Datatype | Description |
|--|--------------|---|
| gridtype | STRING | Type of the grid (gaussian, lonlat, curvilinear, unstructured). |
| ${f gridsize}$ | INTEGER | Size of the grid. |
| xsize | INTEGER | Size in x direction (number of longitudes). |
| ysize | INTEGER | Size in y direction (number of latitudes). |
| xvals | FLOAT ARRAY | X values of the grid cell center. |
| $\mathbf{y}\mathbf{v}\mathbf{a}\mathbf{l}\mathbf{s}$ | FLOAT ARRAY | Y values of the grid cell center. |
| $\mathbf{nvertex}$ | INTEGER | Number of the vertices for all grid cells. |
| ${f xbounds}$ | FLOAT ARRAY | X bounds of each gridbox. |
| ${f y}{f bounds}$ | FLOAT ARRAY | Y bounds of each gridbox. |
| xfirst, xinc | FLOAT, FLOAT | Macros to define xvals with a constant increment, |
| | | xfirst is the x value of the first grid cell center. |
| yfirst, yinc | FLOAT, FLOAT | Macros to define yvals with a constant increment, |
| | | yfirst is the y value of the first grid cell center. |
| \mathbf{xunits} | STRING | units of the x axis |
| \mathbf{yunits} | STRING | units of the y axis |

Which keywords are necessary depends on the gridtype. The following table gives an overview of the default values or the size with respect to the different grid types.

| gridtype | lonlat | gaussian | projection | curvilinear | unstructured |
|----------|-------------|-------------|-------------|-------------|--------------|
| gridsize | xsize*ysize | xsize*ysize | xsize*ysize | xsize*ysize | ncell |
| xsize | nlon | nlon | nx | nlon | gridsize |
| ysize | nlat | nlat | ny | nlat | gridsize |
| xvals | xsize | xsize | xsize | gridsize | gridsize |
| yvals | ysize | ysize | ysize | gridsize | gridsize |
| nvertex | 2 | 2 | 2 | 4 | nv |
| xbounds | 2*xsize | 2*xsize | 2*xsize | 4*gridsize | nv*gridsize |
| ybounds | 2*ysize | 2*ysize | 2*xsize | 4*gridsize | nv*gridsize |
| xunits | degrees | degrees | m | degrees | degrees |
| yunits | degrees | degrees | m | degrees | degrees |

The keywords nvertex, xbounds and ybounds are optional if area weights are not needed. The grid cell corners xbounds and ybounds have to rotate counterclockwise.

CDO grid description example of a T21 gaussian grid:

```
gridtype = gaussian
xsize
         = 64
ysize
         = 32
xfirst
         = 0
         = 5.625
xinc
yvals
         = 85.76
                   80.27
                           74.75
                                   69.21
                                           63.68
                                                  58.14
                                                          52.61
                                                                  47.07
            41.53
                   36.00
                          30.46
                                                  13.84
                                                           8.31
                                                                   2.77
                                   24.92
                                          19.38
            -2.77
                   -8.31 -13.84 -19.38 -24.92 -30.46
                                                         -36.00 -41.53
           -47.07
                  -52.61
                          -58.14 \quad -63.68
                                         -69.21
                                                  -74.75
                                                         -80.27
```

CDO grid description example of a global regular grid with 60x30 points:

```
gridtype = lonlat
xsize = 60
ysize = 30
```

Introduction Horizontal grids

```
\begin{array}{rcl}
x & \text{first} & = -177 \\
x & \text{inc} & = 6 \\
y & \text{first} & = -87 \\
y & \text{inc} & = 6
\end{array}
```

The description for a projection is somewhat more complicated. Use the first section to describe the coordinates of the projection with the above keywords. Add the keyword **grid_mapping_name** to descibe the mapping between the given coordinates and the true latitude and longitude coordinates. **grid_mapping_name** takes a string value that contains the name of the projection. A list of attributes can be added to define the mapping. The name of the attributes depend on the projection. The valid names of the projection and there attributes follow the NetCDF CF-Convention.

CDO supports the special grid mapping attribute **proj_params**. These parameter will be passed directly to the PROJ library to generate the geographic coordinates if needed.

The geographic coordinates of the following projections can be generated without the attribute **proj_params**, if all other attributes are available:

- rotated_latitude_longitude
- lambert_conformal_conic
- lambert_azimuthal_equal_area
- sinusoidal
- polar_stereographic

It is recommend to set the attribute **proj_params** also for the above projections to make sure all PROJ parameter are set correctly.

Here is an example of a **CDO** grid description using the attribute **proj_params** to define the PROJ parameter of a polar stereographic projection:

```
gridtype = projection
          = 11
xsize
ysize
          = 11
         = "meter"
= "meter"
xunits
yunits
xfirst
          = -638000
          = 150
xinc
          = -3349350
yfirst
          = 150
vinc
grid_mapping = crs
grid_mapping_name = polar_stereographic
proj_params = "+proj=stere +lon_0=-45 +lat_ts=70 +lat_0=90 +x_0=0 +y_0=0"
```

The result is the same as using the CF conform Grid Mapping Attributes:

```
gridtype = projection
xsize
          = 11
         = 11
ysize
xunits
         = "meter"
         = "meter
yunits
         = -638000
xfirst
xinc
         = 150
         = -3349350
vfirst
          = 150
vinc
grid_mapping = crs
grid_mapping_name = polar_stereographic
straight\_vertical\_longitude\_from\_pole = -45.
standard_parallel = 70.
latitude_of_projection_origin = 90.
false\_easting = 0.
false\_northing = 0.
```

CDO grid description example of a regional rotated lon/lat grid:

Z-axis description Introduction

```
gridtype = projection
xsize
         = 81
ysize
         = 91
         = "degrees"
xunits
            "degrees"
vunits
xfirst
             -19.5
xinc
               0.5
             -25.0
yfirst
               0.5
vinc
grid_mapping_name = rotated_latitude_longitude
grid\_north\_pole\_longitude = -170
grid_north_pole_latitude = 32.5
```

Example **CDO** descriptions of a curvilinear and an unstructured grid can be found in Appendix D.

1.5.3. ICON - Grid File Server

The geographic coordinates of the ICON model are located on an unstructured grid. This grid is stored in a separate grid file independent of the model data. The grid files are made available to the general public via a file server. Furthermore, these grid files are located at DKRZ under /pool/data/ICON/grids.

With the **CDO** function setgrid, <gridfile> this grid information can be added to the data if needed. Here is an example:

```
cdo sellonlatbox,-20,60,10,70 -setgrid,<path_to_gridfile> icondatafile result
```

ICON model data in NetCDF format contains the global attribute grid_file_uri. This attribute contains a link to the appropriate grid file on the ICON grid file server. If the global attribute grid_file_uri is present and valid, the grid information can be added automatically. The setgrid function is then no longer required. The environment variable CDO_DOWNLOAD_PATH can be used to select a directory for storing the grid file. If this environment variable is set, the grid file will be automatically downloaded from the grid file server to this directory if needed. If the grid file already exists in the current directory, the environment variable does not need to be set.

If the grid files are available locally, like at DKRZ, they do not need to be fetched from the grid file server. Use the environment variable CDO_ICON_GRIDS to set the root directory of the ICON grids. Here is an example for the ICON grids at DKRZ:

```
CDO_ICON_GRIDS=/pool/data/ICON
```

1.6. Z-axis description

Sometimes it is necessary to change the description of a z-axis. This can be done with the operator setzaxis. This operator needs an ASCII formatted file with the description of the z-axis. The following keywords can be used to describe a z-axis:

| Keyword | Datatype | Description |
|--------------------|-------------|--|
| zaxistype | STRING | type of the z-axis |
| \mathbf{size} | INTEGER | number of levels |
| levels | FLOAT ARRAY | values of the levels |
| lbounds | FLOAT ARRAY | lower level bounds |
| ${f ubounds}$ | FLOAT ARRAY | upper level bounds |
| $\mathbf{vctsize}$ | INTEGER | number of vertical coordinate parameters |
| \mathbf{vct} | FLOAT ARRAY | vertical coordinate table |

The keywords **lbounds** and **ubounds** are optional. **vctsize** and **vct** are only necessary to define hybrid model levels.

Introduction Time axis

Available z-axis types:

| Z-axis type | Description | Units |
|----------------------|--------------------------|------------|
| surface | Surface | |
| pressure | Pressure level | pascal |
| hybrid | Hybrid model level | |
| height | Height above ground | meter |
| $depth_below_sea$ | Depth below sea level | meter |
| $depth_below_land$ | Depth below land surface | centimeter |
| isentropic | Isentropic (theta) level | kelvin |

Z-axis description example for pressure levels 100, 200, 500, 850 and 1000 hPa:

```
zaxistype = pressure
size = 5
levels = 10000 20000 50000 85000 100000
```

Z-axis description example for ECHAM5 L19 hybrid model levels:

Note that the vctsize is twice the number of levels plus two and the vertical coordinate table must be specified for the level interfaces.

1.7. Time axis

A time axis describes the time for every timestep. Two time axis types are available: absolute time and relative time axis. **CDO** tries to maintain the actual type of the time axis for all operators.

1.7.1. Absolute time

An absolute time axis has the current time to each time step. It can be used without knowledge of the calendar. This is preferably used by climate models. In NetCDF files the absolute time axis is represented by the unit of the time: "day as %Y%m%d.%f".

1.7.2. Relative time

A relative time is the time relative to a fixed reference time. The current time results from the reference time and the elapsed interval. The result depends on the calendar used. **CDO** supports the standard Gregorian, proleptic Gregorian, 360 days, 365 days and 366 days calendars. The relative time axis is preferably used by numerical weather prediction models. In NetCDF files the relative time axis is represented by the unit of the time: "time-units since reference-time", e.g "days since 1989-6-15 12:00".

Parameter table Introduction

1.7.3. Conversion of the time

Some programs which work with NetCDF data can only process relative time axes. Therefore it may be necessary to convert from an absolute into a relative time axis. This conversion can be done for each operator with the **CDO** option '-r'. To convert a relative into an absolute time axis use the **CDO** option '-a'.

1.8. Parameter table

A parameter table is an ASCII formated file to convert code numbers to variable names. Each variable has one line with its code number, name and a description with optional units in a blank separated list. It can only be used for GRIB, SERVICE, EXTRA and IEG formated files. The **CDO** option '-t <partab>' sets the default parameter table for all input files. Use the operator 'setpartab' to set the parameter table for a specific file.

Example of a **CDO** parameter table:

```
134
                surface pressure [Pa]
     aps
141
                snow depth [m]
     sn
147
     ahfl
                latent heat flux [W/m**2]
172
     _{
m slm}
                land sea mask
     albedo
175
                surface albedo
211
                ice depth [m]
     siced
```

1.9. Missing values

Missing values are data points that are missing or invalid. Such data points are treated in a different way than valid data. Most **CDO** operators can handle missing values in a smart way. But if the missing value is within the range of valid data, it can lead to incorrect results. This applies to all arithmetic operations, but especially to logical operations when the missing value is 0 or 1.

The default missing value for GRIB, SERVICE, EXTRA and IEG files is $-9.e^{33}$. The **CDO** option '-m <missval>' overwrites the default missing value. In NetCDF files the variable attribute '_FillValue' is used as a missing value. The operator 'setmissval' can be used to set a new missing value.

The **CDO** use of the missing value is shown in the following tables, where one table is printed for each operation. The operations are applied to arbitrary numbers a, b, the special case 0, and the missing value miss. For example the table named "addition" shows that the sum of an arbitrary number a and the missing value is the missing value, and the table named "multiplication" shows that 0 multiplied by missing value results in 0.

Introduction Percentile

| addition | b | | miss |
|----------------|-----------|------|------|
| a | a+b | | miss |
| miss | miss | | miss |
| subtraction | b | | miss |
| a | a-b | | miss |
| miss | miss | | miss |
| multiplication | b | 0 | miss |
| a | a*b | 0 | miss |
| 0 | 0 | 0 | 0 |
| miss | miss | 0 | miss |
| division | b | 0 | miss |
| a | a/b | miss | miss |
| 0 | 0 | miss | miss |
| miss | miss | miss | miss |
| maximum | b | | miss |
| a | max(a, b) | | a |
| miss | b | | miss |
| minimum | b | | miss |
| a | min(a,b) | | a |
| miss | b | | miss |
| sum | b | | miss |
| a | a + b | | a |
| miss | b | | miss |

The handling of missing values by the operations "minimum" and "maximum" may be surprising, but the definition given here is more consistent with that expected in practice. Mathematical functions (e.g. log, sqrt, etc.) return the missing value if an argument is the missing value or an argument is out of range.

All statistical functions ignore missing values, treading them as not belonging to the sample, with the side-effect of a reduced sample size.

1.9.1. Mean and average

An artificial distinction is made between the notions mean and average. The mean is regarded as a statistical function, whereas the average is found simply by adding the sample members and dividing the result by the sample size. For example, the mean of 1, 2, miss and 3 is (1+2+3)/3=2, whereas the average is (1+2+miss+3)/4=miss/4=miss. If there are no missing values in the sample, the average and mean are identical.

1.10. Percentile

There is no standard definition of percentile. All definitions yield to similar results when the number of values is very large. The following percentile methods are available in **CDO**:

Regions Introduction

| Percentile method | Description |
|----------------------|---|
| nrank | Nearest Rank method, the default method used in CDO |
| nist | The primary method recommended by NIST |
| rtype8 | R's type=8 method |
| numpy | numpy.percentile with the option interpolation set to 'linear' |
| numpy_lower | numpy.percentile with the option interpolation set to 'lower' |
| numpy_higher | numpy.percentile with the option interpolation set to 'higher' |
| numpy_nearest | numpy.percentile with the option interpolation set to 'nearest' |

The percentile method can be selected with the **CDO** option --percentile. The Nearest Rank method is the default percentile method in **CDO**.

The different percentile methods can lead to different results, especially for small number of data values. Consider the ordered list {15, 20, 35, 40, 50, 55}, which contains six data values. Here is the result for the 30th, 40th, 50th, 75th and 100th percentiles of this list using the different percentile methods:

| Percentile P | nrank | nist | rtype8 | numpy | numpy lower | numpy higher | numpy nearest |
|------------------|-------|-------|--------|-------|----------------|-----------------|------------------|
| 30th | 20 | 21.5 | 23.5 | 27.5 | 20 | 35 | 35 |
| 40th | 35 | 32 | 33 | 35 | 35 | 35 | 35 |
| 50th | 35 | 37.5 | 37.5 | 37.5 | 35 | 40 | 40 |
| $75 \mathrm{th}$ | 50 | 51.25 | 50.42 | 47.5 | 40 | 50 | 50 |
| 100th | 55 | 55 | 55 | 55 | 55 | 55 | 55 |

1.10.1. Percentile over timesteps

The amount of data for time series can be very large. All data values need to held in memory to calculate the percentile. The percentile over timesteps uses a histogram algorithm, to limit the amount of required memory. The default number of histogram bins is 101. That means the histogram algorithm is used, when the dataset has more than 101 time steps. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The histogram algorithm is implemented only for the Nearest Rank method.

1.11. Regions

The **CDO** operators maskregion and selregion can be used to mask and select regions. For this purpose, the region needs to be defined by the user. In **CDO** there are two possibilities to define regions.

One possibility is to define the regions with an ASCII file. Each region is defined by a polygon. Each line of the polygon contains the longitude and latitude coordinates of a point. A description file for regions can contain several polygons, these must be separated by a line with the character &.

Here is a simple example of a polygon for a box with longitudes from $120\mathrm{W}$ to $90\mathrm{E}$ and latitudes from $20\mathrm{N}$ to $20\mathrm{S}$:

| 120 20 | | | |
|--|--|--|--|
| $ \begin{array}{cccc} 120 & 20 \\ 120 & -20 \\ 270 & -20 \\ 270 & 20 \end{array} $ | | | |
| 270 -20 | | | |
| 270 20 | | | |

With the second option, predefined regions can be used via country codes. The region is specified with dcw:<CountryCode>. Country codes can be combined with the plus sign.

Introduction

Here is an example to select the region Spain and Portugal:

cdo selregion,dcw:ES+PT infile outfile

The ISO two-letter country codes can be found on https://en.wikipedia.org/wiki/ISO_3166-1_alpha-2. For the coordinates of a country ${\tt CDO}$ uses the DCW (Digital Chart of the World) dataset from GMT. This dataset must be installed on the system and the environment variable DIR_DCW must point to it.

2. Reference manual

This section gives a description of all operators. Related operators are grouped to modules. For easier description all single input files are named infile or infile1, infile2, etc., and an arbitrary number of input files are named infiles. All output files are named outfile or outfile1, outfile2, etc. Further the following notion is introduced:

- i(t) Timestep t of infile
- i(t,x) Element number x of the field at timestep t of infile
- o(t) Timestep t of outfile
- o(t,x) Element number x of the field at timestep t of outfile

Reference manual Information

2.1. Information

This section contains modules to print information about datasets. All operators print there results to standard output.

Here is a short overview of all operators in this section:

info Dataset information listed by parameter identifier infon Dataset information listed by parameter name

map Dataset information and simple map

sinfo Short information listed by parameter identifier sinfon Short information listed by parameter name

diff Compare two datasets listed by parameter id
diffn Compare two datasets listed by parameter name

Number of parameters npar nlevel Number of levels Number of years nyear Number of months nmon ndate Number of dates ntime Number of timesteps ngridpoints Number of gridpoints ngrids Number of horizontal grids

showformatShow file formatshowcodeShow code numbersshownameShow variable namesshowstdnameShow standard names

showlevel Show levels

showltype Show GRIB level types

showyearshow monthsShow months

showdateShow date informationshowtimeShow time informationshowtimestampShow timestamp

showattribute Show a global attribute or a variable attribute

partabParameter tablecodetabParameter code tablegriddesGrid descriptionzaxisdesZ-axis descriptionvctVertical coordinate table

Information Reference manual

2.1.1. INFO - Information and simple statistics

Synopsis

<operator> infiles

Description

This module writes information about the structure and contents for each field of all input files to standard output. A field is a horizontal layer of a data variable. All input files need to have the same structure with the same variables on different timesteps. The information displayed depends on the chosen operator.

Operators

info Dataset information listed by parameter identifier

Prints information and simple statistics for each field of all input datasets. For each field the operator prints one line with the following elements:

- Date and Time
- Level, Gridsize and number of Missing values
- Minimum, Mean and Maximum
 The mean value is computed without the use of area weights!
- Parameter identifier

infon Dataset information listed by parameter name

The same as operator info but using the name instead of the identifier to label the parameter.

map Dataset information and simple map

Prints information, simple statistics and a map for each field of all input datasets. The map will be printed only for fields on a regular lon/lat grid.

Example

To print information and simple statistics for each field of a dataset use:

```
cdo infon infile
```

This is an example result of a dataset with one 2D parameter over 12 timesteps:

```
Date
                      Time Level
                                    Size
                                           Miss: Minimum
                                                               Mean Maximum: Name
1 : 1987 - 01 - 31
                  12:00:00
                                    2048
                                           1361
                                                    232.77
                                                             266.65
                                                                      305.31 :
                                                                                SST
                                0
2 : 1987 - 02 - 28
                 12:00:00
                                    2048
                                           1361
                                                    233.64
                                                             267.11
                                                                      307.15
                                                                                SST
   : 1987-03-31 12:00:00
                                    2048
                                                                      307.67
                                                                                SST
                                           1361
                                                    225.31
                                                             267.52
   : 1987 - 04 - 30 \quad 12:00:00
                                    2048
                                                                      310.47
                                                                                SST
                                           1361
                                                    215.68
                                                             268.65
   : 1987-05-31 12:00:00
                                    2048
                                           1361
                                                    215.78
                                                             271.53
                                                                      312.49
                                                                                SST
   : 1987-06-30 12:00:00
                                0
                                    2048
                                           1361
                                                    212.89
                                                             272.80
                                                                      314.18
                                                                                SST
   : 1987-07-31 12:00:00
                                0
                                    2048
                                           1361
                                                    209.52
                                                             274.29
                                                                      316.34
                                                                              : SST
   : 1987-08-31 12:00:00
                                           1361
                                                             274.41
                                                                      315.83 : SST
                                0
                                    2048
                                                    210.48
                                                    210.48
                                                                                SST
  : 1987-09-30 12:00:00
                                0
                                    2048
                                           1361
                                                             272.37
                                                                      312.86
10 : 1987-10-31 12:00:00
                                                                                SST
                                0
                                    2048
                                           1361
                                                    219.46
                                                                      309.51
                                                             270.53
   : 1987-11-30 12:00:00
                                0
                                    2048
                                           1361
                                                    230.98
                                                                      308.61
                                                                                SST
11
                                                             269.85
  : 1987-12-31 12:00:00
                                    2048
                                           1361
                                                    241.25
                                                             269.94
                                                                      309.27
```

Reference manual Information

2.1.2. SINFO - Short information

Synopsis

```
< operator > infiles
```

Description

This module writes information about the structure of infiles to standard output. infiles is an arbitrary number of input files. All input files need to have the same structure with the same variables on different timesteps. The information displayed depends on the chosen operator.

Operators

sinfo

Short information listed by parameter identifier

Prints short information of a dataset. The information is divided into 4 sections. Section 1 prints one line per parameter with the following information:

- institute and source
- time c=constant v=varying
- type of statistical processing
- number of levels and z-axis number
- horizontal grid size and number
- data type
- parameter identifier

Section 2 and 3 gives a short overview of all grid and vertical coordinates. And the last section contains short information of the time coordinate.

sinfon

Short information listed by parameter name

The same as operator sinfo but using the name instead of the identifier to label the parameter.

Example

To print short information of a dataset use:

```
cdo sinfon infile
```

This is the result of an ECHAM5 dataset with 3 parameter over 12 timesteps:

```
-1: Institut Source
                                                                                                                                                                                            T Steptype Levels Num
                                                                                                                                                                                                                                                                                                                                                                               Points Num Dtype: Name
                                    1 : MPIMET
                                                                                                                                   ECHAM5
                                                                                                                                                                                                                                                                                                                                                                                                                                                                     F32
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             : GEOSP
                                                                                                                                                                                          c instant
                                                                                                                                                                                                                                                                                                                   1
                                                                                                                                                                                                                                                                                                                                                1
                                                                                                                                                                                                                                                                                                                                                                                              2048
                                                                                                                                                                                                                                                                                                                                                                                                                                                 1
                                    2: MPIMET
                                                                                                                                   ECHAM5 v instant
                                                                                                                                                                                                                                                                                                                     4
                                                                                                                                                                                                                                                                                                                                                  2
                                                                                                                                                                                                                                                                                                                                                                                              2048
                                                                                                                                                                                                                                                                                                                                                                                                                                                 1
                                                                                                                                                                                                                                                                                                                                                                                                                                                                      F32
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            : T
                                     3 : MPIMET
                                                                                                                                  ECHAM5 v instant
                                                                                                                                                                                                                                                                                                                     1
                                                                                                                                                                                                                                                                                                                                                  1
                                                                                                                                                                                                                                                                                                                                                                                              2048
                                                                                                                                                                                                                                                                                                                                                                                                                                                 1
                                                                                                                                                                                                                                                                                                                                                                                                                                                                      F32
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            : TSURF
                      Grid coordinates:
                                                                                                                                                                                                                                     : points = 2048 (64x32) F16
                                     1 : gaussian
                                                                                                                                                           longitude: 0 to 354.375 by 5.625 degrees_east
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           circular
                                                                                                                                                                  latitude : 85.7606 to -85.7606 degrees_north
                       Vertical coordinates:
                                                                                                                                                                                                                                     : levels=1
                                     1 : surface
                                     2 : pressure
                                                                                                                                                                                                                                    : levels=4
                                                                                                                                                                                       level: 92500 to 20000 Pa
                      Time coordinate:
                                                                                                                                                                                               time: 12 steps
YYYY-MM-DD hh:mm:ss YYYY-MM-DD hh:mm:ss YYYY-MM-DD hh:mm:ss YYYY-MM-DD hh:mm:ss
 1987 - 01 - 31 \quad 12:00:00 \quad 1987 - 02 - 28 \quad 12:00:00 \quad 1987 - 03 - 31 \quad 12:00:00 \quad 1987 - 04 - 30 \quad 12:00:00 \quad 1987 - 12:00:00 \quad 1987 -
 1987 - 05 - 31 \quad 12:00:00 \quad 1987 - 06 - 30 \quad 12:00:00 \quad 1987 - 07 - 31 \quad 12:00:00 \quad 1987 - 08 - 31 \quad 12:00:00
 1987 - 09 - 30 \quad 12:00:00 \quad 1987 - 10 - 31 \quad 12:00:00 \quad 1987 - 11 - 30 \quad 12:00:00 \quad 1987 - 12 - 31 \quad 12:00:00 \quad
```

Information Reference manual

2.1.3. DIFF - Compare two datasets field by field

Synopsis

<operator>[,options] infile1 infile2

Description

Compares the contents of two datasets field by field. The input datasets need to have the same structure and its fields need to have the same header information and dimensions. Try the option *names* if the number of variables differ. Exit status is 0 if inputs are the same and 1 if they differ.

Operators

diff Compare two datasets listed by parameter id

Provides statistics on differences between two datasets. For each pair of fields the operator prints one line with the following information:

- Date and Time
- Level, Gridsize and number of Missing values
- Number of different values
- Occurrence of coefficient pairs with different signs (S)
- Occurrence of zero values (Z)
- Maxima of absolute difference of coefficient pairs
- Maxima of relative difference of non-zero coefficient pairs with equal signs
- Parameter identifier

$$Absdiff(t,x) = |i_1(t,x) - i_2(t,x)|$$

$$Reldiff(t,x) = \frac{|i_1(t,x) - i_2(t,x)|}{\max(|i_1(t,x)|, |i_2(t,x)|)}$$

diffn Compare two datasets listed by parameter name

The same as operator diff. Using the name instead of the identifier to label the parameter.

Parameter

| maxcount | INTEGER | Stop after maxcount different fields |
|----------|-------------------------|---|
| abslim | FLOAT | Limit of the maximum absolute difference (default: 0) |
| rellim | FLOAT | Limit of the maximum relative difference (default: 1) |
| names | STRING the intersect | Consideration of the variable names of only one input file (left/right) or ion of both (intersect). |

Example

To print the difference for each field of two datasets use:

cdo diffn infile1 infile2

This is an example result of two datasets with one 2D parameter over 12 timesteps:

Reference manual Information

```
Time Level Size Miss Diff: S Z Max_Absdiff Max_Reldiff:
                                                                                            Name
             Date
1 : 1987 - 01 - 31 \ 12:00:00
                                                273
                                                     : F F
                                                              0.00010681
                                                                            4.1660\,\mathrm{e}\!-\!07
                                0
                                   2048
                                         1361
     1987 - 02 - 28
                   12:00:00
                                   2048
                                         1361
                                                309
                                                     : F F
                                                              6.1035\,\mathrm{e}\!-\!05
                                                                            2.3742e-07
     1987-03-31 12:00:00
                                0
                                   2048
                                        1361
                                                292
                                                     : F F
                                                              7.6294e-05
                                                                            3.3784e - 07
                                                                                            SST
                                                183 : F F
     1987-04-30 12:00:00
                                0
                                   2048 1361
                                                              7.6294e-05
                                                                            3.5117e - 07
                                                                                            SST
                                                     : F F
     1987-05-31 12:00:00
                                0
                                   2048 1361
                                                207
                                                              0.00010681
                                                                             4.0307\,\mathrm{e}\!-\!07
                                                                                            SST
                                                     : F F
                                                                                            SST
     1987-07-31 12:00:00
                                   2048 1361
                                                317
                                                              9.1553e-05
                                                                            3.5634e - 07
                                                219 : F F
                                                              7.6294e-05
   : 1987-08-31 12:00:00
                                   2048 1361
                                                                            2.8849e - 07
                                                                                            SST
                                                188 : F F
9 : 1987 - 09 - 30 \ 12:00:00
                                   2048 1361
                                                              7.6294\,\mathrm{e}\!-\!05
                                                                            3.6168e - 07
                                                                                            SST
10 : 1987 - 10 - 31 \ 12:00:00
                                   2048 1361
                                                297 : F F
                                                              9.1553\,\mathrm{e}\!-\!05
                                                                            3.5001e-07:
                                                                                            SST
                                                234 : F F
11 : 1987 - 11 - 30 \ 12:00:00
                                0 2048 1361
                                                              6.1035e-05
                                                                             2.3839e-07:
                                                                                            SST
12 : 1987 - 12 - 31 \ 12:00:00
                                0 2048 1361
                                                267 : F F
                                                              9.3553\,\mathrm{e}\!-\!05
                                                                            3.7624e-07:
                                                                                            SST
11 of 12 records differ
```

2.1.4. NINFO - Print the number of parameters, levels or times

Synopsis

```
< operator > infile
```

Description

This module prints the number of variables, levels or times of the input dataset.

Operators

| npar | Number of parameters Prints the number of parameters (variables). |
|------------------------------|---|
| nlevel | Number of levels Prints the number of levels for each variable. |
| nyear | Number of years Prints the number of different years. |
| nmon | Number of months Prints the number of different combinations of years and months. |
| ndate | Number of dates Prints the number of different dates. |
| ntime | Number of timesteps Prints the number of timesteps. |
| $\operatorname{ngridpoints}$ | Number of gridpoints Prints the number of gridpoints for each variable. |
| ngrids | Number of horizontal grids Prints the number of horizontal grids. |

Example

To print the number of parameters (variables) in a dataset use:

```
cdo npar infile
```

To print the number of months in a dataset use:

```
cdo nmon infile
```

Information Reference manual

2.1.5. SHOWINFO - Show variables, levels or times

Synopsis

< operator > infile

Description

This module prints the format, variables, levels or times of the input dataset.

Operators

showformat Show file format

Prints the file format of the input dataset.

showcode Show code numbers

Prints the code number of all variables.

showname Show variable names

Prints the name of all variables.

showstdname Show standard names

Prints the standard name of all variables.

showlevel Show levels

Prints all levels for each variable.

showltype Show GRIB level types

Prints the GRIB level type for all z-axes.

showyear Show years

Prints all years.

showmon Show months

Prints all months.

showdate Show date information

Prints date information of all timesteps (format YYYY-MM-DD).

showtime Show time information

Prints time information of all timesteps (format hh:mm:ss).

showtimestamp Show timestamp

Prints timestamp of all timesteps (format YYYY-MM-DDThh:mm:ss).

Example

To print the code number of all variables in a dataset use:

cdo showcode infile

This is an example result of a dataset with three variables:

129 130 139

To print all months in a dataset use:

cdo showmon infile

This is an examples result of a dataset with an annual cycle:

1 2 3 4 5 6 7 8 9 10 11 12

Reference manual Information

2.1.6. SHOWATTRIBUTE - Show attributes

Synopsis

showattribute[,attributes] infile

Description

This operator prints the attributes of the data variables of a dataset.

Each attribute has the following structure:

```
[var_nm@][att_nm]
var_nm     Variable name (optional). Example: pressure
att_nm     Attribute name (optional). Example: units
```

The value of <code>var_nm</code> is the name of the variable containing the attribute (named <code>att_nm</code>) that you want to print. Use wildcards to print the attribute <code>att_nm</code> of more than one variable. A value of <code>var_nm</code> of <code>'*'</code> will print the attribute <code>att_nm</code> of all data variables. If <code>var_nm</code> is missing then <code>att_nm</code> refers to a global attribute.

The value of **att_nm** is the name of the attribute you want to print. Use wildcards to print more than one attribute. A value of **att_nm** of '*' will print all attributes.

Parameter

attributes STRING Comma-separated list of attributes.

Information Reference manual

2.1.7. FILEDES - Dataset description

Synopsis

< operator > infile

Description

This module provides operators to print meta information about a dataset. The printed meta-data depends on the chosen operator.

Operators

partab Parameter table

Prints all available meta information of the variables.

codetab Parameter code table

Prints a code table with a description of all variables. For each variable the operator

prints one line listing the code, name, description and units.

griddes Grid description

Prints the description of all grids.

zaxisdes Z-axis description

Prints the description of all z-axes.

vct Vertical coordinate table

Prints the vertical coordinate table.

Example

Assume all variables of the dataset are on a Gaussian N16 grid. To print the grid description of this dataset use:

```
cdo griddes infile
```

Result:

```
gridtype
           : gaussian
           : 2048
gridsize
xname
            : lon
xlongname : longitude
xunits
            : degrees_east
yname
           : lat
ylongname : latitude
           : degrees_north
yunits
xsize
           : 64
ysize
           : 32
xfirst
            : 0
            : 5.625
xinc
            : \ 85.76058 \ \ 80.26877 \ \ 74.74454 \ \ 69.21297 \ \ 63.67863 \ \ 58.1429 \ \ 52.6065
yvals
              47.06964 \ \ 41.53246 \ \ 35.99507 \ \ 30.4575 \ \ 24.91992 \ \ 19.38223 \ \ 13.84448
              8.306702\ \ 2.768903\ \ -2.768903\ \ -8.306702\ \ -13.84448\ \ -19.38223
               -24.91992 \ \ -30.4575 \ \ -35.99507 \ \ -41.53246 \ \ -47.06964 \ \ -52.6065
               -58.1429 -63.67863 -69.21297 -74.74454 -80.26877 -85.76058
```

Reference manual File operations

2.2. File operations

This section contains modules to perform operations on files.

Here is a short overview of all operators in this section:

apply Apply operators on each input file.

copycloneCopy datasetsClone datasets

cat Concatenate datasets

tee Duplicate a data stream

pack Pack data

bitrounding Bit rounding

replace Replace variables

duplicate Duplicates a dataset

mergegrid Merge grid

merge Merge datasets with different fields
mergetime Merge datasets sorted by date and time

splitcode Split code numbers

splitparamSplit parameter identifierssplitnameSplit variable names

splitlevelSplit levelssplitgridSplit gridssplitzaxisSplit z-axes

splittabnum Split parameter table numbers

splithourSplit hourssplitdaySplit dayssplitseasSplit seasonssplityearSplit years

splityearmon Split in years and months

splitmon Split months

splitsel Split time selection

distgrid Distribute horizontal grid

collgrid Collect horizontal grid

File operations Reference manual

2.2.1. APPLY - Apply operators

Synopsis

apply, operators infiles

Description

The apply utility runs the named operators on each input file. The input files must be enclosed in square brackets. This utility can only be used on a series of input files. These are all operators with more than one input file (infiles). Here is an incomplete list of these operators: copy, cat, merge, mergetime, select, ENSSTAT. The parameter operators is a blank-separated list of **CDO** operators. Use quotation marks if more than one operator is needed. Each operator may have only one input and output stream.

Parameter

operators STRING Blank-separated list of CDO operators.

Example

Suppose we have multiple input files with multiple variables on different time steps. The input files contain the variables U and V, among others. We are only interested in the absolute windspeed on all time steps. Here is the standard **CDO** solution for this task:

```
cdo expr,wind="sqrt(u*u+v*v)" -mergetime infile1 infile2 infile3 outfile
```

This first joins all the time steps together and then calculates the wind speed. If there are many variables in the input files, this procedure is ineffective. In this case it is better to first calculate the wind speed:

```
cdo mergetime -expr,wind="sqrt(u*u+v*v)" infile1 \
    -expr,wind="sqrt(u*u+v*v)" infile2 \
    -expr,wind="sqrt(u*u+v*v)" infile3 outfile
```

However, this can quickly become very confusing with more than 3 input files. The apply operator solves this problem:

```
cdo mergetime -apply,-expr,wind="sqrt(u*u+v*v)" [ infile1 infile2 infile3 ] outfile
```

Another example is the calculation of the mean value over several input files with ensmean. The input files contain several variables, but we are only interested in the variable named XXX:

```
cdo ensmean -apply,-selname,XXX [ infile1 infile2 infile3 ] outfile
```

Reference manual File operations

2.2.2. COPY - Copy datasets

Synopsis

 $<\!operator\!>$ infiles outfile

Description

This module contains operators to copy, clone or concatenate datasets. infiles is an arbitrary number of input files. All input files need to have the same structure with the same variables on different timesteps.

Operators

copy Copy datasets

Copies all input datasets to outfile.

clone Clone datasets

Copies all input datasets to outfile. In contrast to the copy operator, clone tries not to change the input data. GRIB records are neither decoded nor decompressed.

cat Concatenate datasets

Concatenates all input datasets and appends the result to the end of outfile. If outfile does not exist it will be created.

Example

To change the format of a dataset to NetCDF use:

```
cdo -f nc copy infile outfile.nc
```

Add the option '-r' to create a relative time axis, as is required for proper recognition by GrADS or Ferret:

```
cdo -r -f nc copy infile outfile.nc
```

To concatenate 3 datasets with different timesteps of the same variables use:

```
cdo copy infile1 infile2 infile3 outfile
```

If the output dataset already exists and you wish to extend it with more timesteps use:

```
cdo cat infile1 infile2 infile3 outfile
```

File operations Reference manual

2.2.3. TEE - Duplicate a data stream and write it to file

Synopsis

tee, outfile2 infile outfile1

Description

This operator copies the input dataset to outfile1 and outfile2. The first output stream in outfile1 can be further processesd with other cdo operators. The second output outfile2 is written to disk. It can be used to store intermediate results to a file.

Parameter

outfile2 STRING Destination filename for the copy of the input file

Example

To compute the daily and monthy average of a dataset use:

cdo monavg -tee,outfile_dayavg dayavg infile outfile_monavg

2.2.4. PACK - Pack data

Synopsis

pack infile outfile

Description

Packing reduces the data volume by reducing the precision of the stored numbers. It is implemented using the NetCDF attributes add_offset and scale_factor. The operator pack calculates the attributes add_offset and scale_factor for all variables. The default data type for all variables is automatically changed to 16-bit integer. Use the **CDO** option -b to change the data type to a different integer precision, if needed. Missing values are automatically transformed to the current data type.

Reference manual File operations

2.2.5. BITROUNDING - Bit rounding

Synopsis

bitrounding/,params/ infile outfile

Description

This operator calculates for each field the number of necessary mantissa bits to get a certain information level in the data. With this number of significant bits (numbits) a rounding of the data is performed. This allows the data to be compressed to a higher level.

The default value of the information level is 0.9999 and can be adjusted with the parameter **inflevel**. That means 99.99% of the information in the mantissa bits is preserved.

Alternatively, the number of significant bits can be set for all variables with the **numbits** parameter. Furthermore, **numbits** can be assigned for each variable via the filename parameter. In this case, **numbits** is still calculated for all variables if they are not present in the file.

The analysis of the bit information is based on the Julia library BitInformation.jl. The procedure to derive the number of significant mantissa bits was adapted from the Python library xbitinfo. Quantize to the number of mantissa bits is done with IEEE rounding using code from NetCDF 4.9.0.

Currently only 32-bit float data is rounded. Data with missing values are not yet supported for the calculation of significant bits.

Parameter

| inflevel | FLOAT | Information level $(0 - 1)$ [default: 0.9999] |
|------------|---------|--|
| addbits | INTEGER | Add bits to the number of significant bits [default: 0] |
| minbits | INTEGER | Minimum value of the number of bits [default: 1] |
| maxbits | INTEGER | Maximum value of the number of bits [default: 23] |
| numsteps | INTEGER | Set to 1 to run the calculation only in the first time step |
| numbits | INTEGER | Set number of significant bits |
| print bits | BOOL | Print max. numbits per variable of 1st timestep to stdout [format: name=numbits] |
| filename | STRING | Read number of significant bits per variable from file [format: name=numbits] |

Example

Apply bit rounding to all 32-bit float fields, preserving 99.9% of the information, followed by compression and storage to NetCDF4:

```
cdo -f nc4 -z zip bitrounding,inflevel=0.999 infile outfile
```

Add the option '-v' to view used number of mantissa bits for each field:

```
cdo -v -f nc4 -z zip bitrounding,inflevel=0.999 infile outfile
```

File operations Reference manual

2.2.6. REPLACE - Replace variables

Synopsis

replace infile1 infile2 outfile

Description

This operator replaces variables in infile1 by variables from infile2 and write the result to outfile. Both input datasets need to have the same number of timesteps. All variable names may only occur once!

Example

Assume the first input dataset infile1 has three variables with the names geosp, t and tslm1 and the second input dataset infile2 has only the variable tslm1. To replace the variable tslm1 in infile1 by tslm1 from infile2 use:

cdo replace infile1 infile2 outfile

2.2.7. DUPLICATE - Duplicates a dataset

Synopsis

duplicate/,ndup/ infile outfile

Description

This operator duplicates the contents of infile and writes the result to outfile. The optional parameter sets the number of duplicates, the default is 2.

Parameter

ndup INTEGER Number of duplicates, default is 2.

2.2.8. MERGEGRID - Merge grid

Synopsis

mergegrid infile1 infile2 outfile

Description

Merges grid points of all variables from infile2 to infile1 and write the result to outfile. Only the non missing values of infile2 will be used. The horizontal grid of infile2 should be smaller or equal to the grid of infile1 and the resolution must be the same. Only rectilinear grids are supported. Both input files need to have the same variables and the same number of timesteps.

Reference manual File operations

2.2.9. MERGE - Merge datasets

Synopsis

<operator> infiles outfile

Description

This module reads datasets from several input files, merges them and writes the resulting dataset to outfile.

Operators

merge Merge datasets with different fields

Merges time series of different fields from several input datasets. The number of fields per timestep written to outfile is the sum of the field numbers per timestep in all input datasets. The time series on all input datasets are required to have different fields and the same number of timesteps. The fields in each different input file either have to be different variables or different levels of the same variable. A mixture of different variables on different levels in different input files is not allowed.

mergetime Merge datasets sorted by date and time

Merges all timesteps of all input files sorted by date and time. All input files need to have the same structure with the same variables on different timesteps. After this operation every input timestep is in outfile and all timesteps are sorted by date and time.

Environment

SKIP_SAME_TIME If set to 1, skips all consecutive timesteps with a double entry of the same timestamp.

Note

Operators of this module need to open all input files simultaneously. The maximum number of open files depends on the operating system!

Example

Assume three datasets with the same number of timesteps and different variables in each dataset. To merge these datasets to a new dataset use:

cdo merge infile1 infile2 infile3 outfile

Assume you split a 6 hourly dataset with splithour. This produces four datasets, one for each hour. The following command merges them together:

cdo mergetime infile1 infile2 infile3 infile4 outfile

File operations Reference manual

2.2.10. SPLIT - Split a dataset

Synopsis

<operator>[,params] infile obase

Description

This module splits infile into pieces. The output files will be named <obase><xxx><suffix> where suffix is the filename extension derived from the file format. xxx and the contents of the output files depends on the chosen operator. params is a comma-separated list of processing parameters.

Operators

splitcode Split code numbers

Splits a dataset into pieces, one for each different code number. xxx will have three

digits with the code number.

splitparam Split parameter identifiers

Splits a dataset into pieces, one for each different parameter identifier. xxx will be

a string with the parameter identifier.

splitname Split variable names

Splits a dataset into pieces, one for each variable name. xxx will be a string with

the variable name.

splitlevel Split levels

Splits a dataset into pieces, one for each different level. xxx will have six digits

with the level.

splitgrid Split grids

Splits a dataset into pieces, one for each different grid. xxx will have two digits

with the grid number.

splitzaxis Split z-axes

Splits a dataset into pieces, one for each different z-axis. xxx will have two digits

with the z-axis number.

splittabnum Split parameter table numbers

Splits a dataset into pieces, one for each GRIB1 parameter table number. xxx will

have three digits with the GRIB1 parameter table number.

Parameter

swap STRING Swap the position of obase and xxx in the output filename

uuid=<attname> STRING Add a UUID as global attribute <attname> to each output file

Environment

CDO_FILE_SUFFIX Set the default file suffix. This suffix will be added to the output file names

instead of the filename extension derived from the file format. Set this variable

to NULL to disable the adding of a file suffix.

Note

Operators of this module need to open all output files simultaneously. The maximum number of open files depends on the operating system!

Reference manual File operations

Example

Assume an input GRIB1 dataset with three variables, e.g. code number 129, 130 and 139. To split this dataset into three pieces, one for each code number use:

cdo splitcode infile code

Result of 'dir code*':

 $\verb|code| 129.grb| \verb|code| 130.grb| \verb|code| 139.grb|$

File operations Reference manual

2.2.11. SPLITTIME - Split timesteps of a dataset

Synopsis

```
<operator> infile obase
splitmon[,format] infile obase
```

Description

This module splits infile into timesteps pieces. The output files will be named <obase><xxx><suffix>
where suffix is the filename extension derived from the file format. xxx and the contents of the output files depends on the chosen operator.

Operators

splithour Split hours

Splits a file into pieces, one for each different hour. xxx will have two digits with

the hour.

splitday Split days

Splits a file into pieces, one for each different day. xxx will have two digits with

the day.

splitseas Split seasons

Splits a file into pieces, one for each different season. xxx will have three characters

with the season.

splityear Split years

Splits a file into pieces, one for each different year. xxx will have four digits with

the year (YYYY).

splityearmon Split in years and months

Splits a file into pieces, one for each different year and month. xxx will have six

digits with the year and month (YYYYMM).

splitmon Split months

Splits a file into pieces, one for each different month. xxx will have two digits with

the month.

Parameter

format STRING C-style format for strftime() (e.g. %B for the full month name)

Environment

CDO_FILE_SUFFIX Set the default file suffix. This suffix will be added to the output file names

instead of the filename extension derived from the file format. Set this variable

to NULL to disable the adding of a file suffix.

Note

Operators of this module need to open all output files simultaneously. The maximum number of open files depends on the operating system!

Reference manual File operations

Example

Assume the input GRIB1 dataset has timesteps from January to December. To split each month with all variables into one separate file use:

```
cdo splitmon infile mon
```

Result of 'dir mon*':

2.2.12. SPLITSEL - Split selected timesteps

Synopsis

```
splitsel,nsets[,noffset[,nskip]] infile obase
```

Description

This operator splits infile into pieces, one for each adjacent sequence $t_1, ..., t_n$ of timesteps of the same selected time range. The output files will be named <obase><nnnnnn><suffix> where nnnnnn is the sequence number and suffix is the filename extension derived from the file format.

Parameter

| nsets | INTEGER | Number of input timesteps for each output file |
|---------|---------|---|
| noffset | INTEGER | Number of input timesteps skipped before the first timestep range (optional) $$ |
| nskip | INTEGER | Number of input timesteps skipped between timestep ranges (optional) |

Environment

CDO_FILE_SUFFIX Set the default file suffix. This suffix will be added to the output file names instead of the filename extension derived from the file format. Set this variable to NULL to disable the adding of a file suffix.

File operations Reference manual

2.2.13. DISTGRID - Distribute horizontal grid

Synopsis

 $\mathbf{distgrid}, nx[,ny]$ infile obase

Description

This operator distributes a dataset into smaller pieces. Each output file contains a different region of the horizontal source grid. 2D Lon/Lat grids can be split into nx^*ny pieces, where a target grid region contains a structured longitude/latitude box of the source grid. Data on an unstructured grid is split into nx pieces. The output files will be named <observed swiffix where suffix is the filename extension derived from the file format. xxx will have five digits with the number of the target region.

Parameter

nx INTEGER Number of regions in x direction, or number of pieces for unstructured grids

ny INTEGER Number of regions in y direction [default: 1]

Note


This operator needs to open all output files simultaneously. The maximum number of open files depends on the operating system!

Example

Distribute data on a 2D Lon/Lat grid into 6 smaller files, each output file receives one half of x and a third of y of the source grid:

cdo distgrid,2,3 infile.nc obase

Below is a schematic illustration of this example:



On the left side is the data of the input file and on the right side is the data of the six output files.

Reference manual File operations

2.2.14. COLLGRID - Collect horizontal grid

Synopsis

collgrid[,nx[,names]] infiles outfile

Description

This operator collects the data of the input files to one output file. All input files need to have the same variables and the same number of timesteps on a different horizonal grid region. If the source regions are on a structured lon/lat grid, all regions together must result in a new structured lat/long grid box. Data on an unstructured grid is concatenated in the order of the input files. The parameter nx needs to be specified only for curvilinear grids.

Parameter

nx INTEGER Number of regions in x direction [default: number of input files]names STRING Comma-separated list of variable names [default: all variables]

Note


This operator needs to open all input files simultaneously. The maximum number of open files depends on the operating system!

Example

Collect the horizonal grid of 6 input files. Each input file contains a lon/lat region of the target grid:

```
cdo collgrid infile[1-6] outfile
```

Below is a schematic illustration of this example:



On the left side is the data of the six input files and on the right side is the collected data of the output file.

Selection Reference manual

2.3. Selection

This section contains modules to select time steps, fields or a part of a field from a dataset.

Here is a short overview of all operators in this section:

selectSelect fieldsdeleteDelete fields

selmulti Select multiple fields delmulti Delete multiple fields

changemulti Change identication of multiple fields

selparamSelect parameters by identifierdelparamDelete parameters by identifierselcodeSelect parameters by code numberdelcodeDelete parameters by code number

selnameSelect parameters by namedelnameDelete parameters by name

selstdname Select parameters by standard name

sellevel Select levels

sellevidx Select levels by index

selgridSelect gridsselzaxisSelect z-axes

selzaxisnameSelect z-axes by nameselltypeSelect GRIB level types

seltabnum Select parameter table numbers

seltimestep Select timesteps seltime Select times selhour Select hours selday Select days selmonth Select months selyear Select years Select seasons selseason seldate Select dates

selsmon Select single month

sellonlatbox Select a longitude/latitude box

selindexbox Select an index box

selregion Select cells inside regions selcircle Select cells inside a circle

selgridcellSelect grid cellsdelgridcellDelete grid cells

samplegrid Resample grid

selyearidx Select year by index

bottomvalueExtract bottom leveltopvalueExtract top levelisosurfaceExtract isosurface

Reference manual Selection

2.3.1. SELECT - Select fields

Synopsis

<operator>,params infiles outfile

Description

This module selects some fields from infiles and writes them to outfile. infiles is an arbitrary number of input files. All input files need to have the same structure with the same variables on different timesteps. The fields selected depends on the chosen parameters. Parameter is a comma-separated list of "key=value" pairs. A range of integer values can be specified by first/last[/inc]. Wildcards are supported for string values.

Operators

select Select fields

Selects all fields with parameters in a user given list.

delete Delete fields

Deletes all fields with parameters in a user given list.

Parameter

| name | STRING | Comma-separated list of variable names. |
|-----------|------------------------|--|
| param | STRING | Comma-separated list of parameter identifiers. |
| code | INTEGER | Comma-separated list or first/last [/inc] range of code numbers. |
| level | FLOAT | Comma-separated list of vertical levels. |
| levrange | FLOAT | First and last value of the level range. |
| levidx | INTEGER | ${\it Comma-separated\ list\ or\ first/last[/inc]\ range\ of\ index\ of\ levels.}$ |
| zaxisname | STRING | Comma-separated list of zaxis names. |
| zaxisnum | INTEGER | Comma-separated list or first/last [/inc] range of zaxis numbers. |
| ltype | INTEGER | ${\it Comma-separated\ list\ or\ first/last[/inc]\ range\ of\ GRIB\ level\ types.}$ |
| gridname | STRING | Comma-separated list of grid names. |
| gridnum | INTEGER | Comma-separated list or first/last [/inc] range of grid numbers. |
| steptype | STRING min, max, ra | Comma-separated list of timestep types (constant, avg, accum, ange, diff, sum) |
| date | STRING | $\label{thm:mm:ss} \mbox{Comma-separated list of dates (format YYYY-MM-DDThh:mm:ss)}.$ |
| startdate | STRING | Start date (format YYYY-MM-DDThh:mm:ss). |
| enddate | STRING | End date (format YYYY-MM-DDThh:mm:ss). |
| minute | INTEGER | Comma-separated list or first/last [/inc] range of minutes. |
| hour | INTEGER | Comma-separated list or first/last [/inc] range of hours. |
| day | INTEGER | Comma-separated list or first/last [/inc] range of days. |
| month | INTEGER | Comma-separated list or first/last [/inc] range of months. |
| season | STRING SOND or AN | Comma-separated list of seasons (substring of DJFMAMJJA-NN). |
| | | |

Selection Reference manual

| year | INTEGER | Comma-separated list or $first/last[/inc]$ range of years. |
|----------------------|-------------------------|--|
| dom | STRING | Comma-separated list of the day of month (e.g. 29feb). |
| timestep | INTEGER ative values | Comma-separated list or first/last[/inc] range of timesteps. Negselect timesteps from the end (NetCDF only). |
| $timestep_of_year$ | INTEGER | ${\bf Comma-separated\; list\; or\; first/last[/inc]\; range\; of\; timesteps\; of\; year.}$ |
| timestepmask | STRING | Read timesteps from a mask file. |

Example

Assume you have 3 inputfiles. Each inputfile contains the same variables for a different time period. To select the variable T,U and V on the levels 200, 500 and 850 from all 3 input files, use:

```
cdo select,name=T,U,V,level=200,500,850 infile1 infile2 infile3 outfile
```

To remove the February 29th use:

cdo delete,dom=29feb infile outfile

Reference manual Selection

2.3.2. SELMULTI - Select multiple fields via GRIB1 parameters

Synopsis

 $<\!operator\!>\!,\!selection\text{-}specification$ infile outfile

Description

This module selects multiple fields from infile and writes them to outfile. selection-specification is a filename or in-place string with the selection specification. Each selection-specification has the following compact notation format:

```
<type>(parameters; leveltype(s); levels)
```

type sel for select or del for delete (optional)

parameters GRIB1 parameter code number

leveltype GRIB1 level type levels value of each level

Examples:

```
\begin{array}{c} (1;\ 103;\ 0) \\ (33,34;\ 105;\ 10) \\ (11,17;\ 105;\ 2) \\ (71,73,74,75,61,62,65,117,67,122,121,11,131,66,84,111,112;\ 105;\ 0) \end{array}
```

The following descriptive notation can also be used for selection specification from a file:

```
SELECT/DELETE, PARAMETER=parameters, LEVTYPE=leveltye(s), LEVEL=levels
```

Examples:

```
SELECT, PARAMETER=1, LEVTYPE=103, LEVEL=0
SELECT, PARAMETER=33/34, LEVTYPE=105, LEVEL=10
SELECT, PARAMETER=11/17, LEVTYPE=105, LEVEL=2
SELECT, PARAMETER=71/73/74/75/61/62/65/117/67/122, LEVTYPE=105, LEVEL=0
DELETE, PARAMETER=128, LEVTYPE=109, LEVEL=*
```

The following will convert Pressure from Pa into hPa; Temp from Kelvin to Celsius:

```
SELECT, PARAMETER=1, LEVTYPE= 103, LEVEL=0, SCALE=0.01
SELECT, PARAMETER=11, LEVTYPE=105, LEVEL=2, OFFSET=273.15
```

If SCALE and/or OFFSET are defined, then the data values are scaled as SCALE*(VALUE-OFFSET).

Operators

selmulti Select multiple fields

delmulti Delete multiple fields

changemulti Change identication of multiple fields

Example

Change ECMWF GRIB code of surface pressure to Hirlam notation:

```
cdo changemulti,'{(134;1;*|1;105;*)}' infile outfile
```

Selection Reference manual

2.3.3. SELVAR - Select fields

Synopsis

<operator>,params infile outfile
selcode,codes infile outfile
delcode,codes infile outfile
selname,names infile outfile
delname,names infile outfile
selstdname,stdnames infile outfile
sellevel,levels infile outfile
sellevidx,levidx infile outfile
selgrid,grids infile outfile
selzaxis,zaxes infile outfile
selzaxisname,zaxisnames infile outfile
seltype,ltypes infile outfile
seltabnum,tabnums infile outfile

Description

This module selects some fields from infile and writes them to outfile. The fields selected depends on the chosen operator and the parameters. A range of integer values can be specified by first/last[/inc].

Operators

selparam Select parameters by identifier

Selects all fields with parameter identifiers in a user given list.

delparam Delete parameters by identifier

Deletes all fields with parameter identifiers in a user given list.

selcode Select parameters by code number

Selects all fields with code numbers in a user given list or range.

delcode Delete parameters by code number

Deletes all fields with code numbers in a user given list or range.

selname Select parameters by name

Selects all fields with parameter names in a user given list.

delname Delete parameters by name

Deletes all fields with parameter names in a user given list.

selstdname Select parameters by standard name

Selects all fields with standard names in a user given list.

sellevel Select levels

Selects all fields with levels in a user given list.

sellevidx Select levels by index

Selects all fields with index of levels in a user given list or range.

selgrid Select grids

Selects all fields with grids in a user given list.

Reference manual Selection

selzaxis Select z-axes

Selects all fields with z-axes in a user given list.

selzaxisname Select z-axes by name

Selects all fields with z-axis names in a user given list.

selltype Select GRIB level types

Selects all fields with GRIB level type in a user given list or range.

seltabnum Select parameter table numbers

Selects all fields with parameter table numbers in a user given list or range.

Parameter

| params | STRING | Comma-separated list of parameter identifiers. |
|------------|---------|--|
| codes | INTEGER | ${\bf Comma-separated\ list\ or\ first/last[/inc]\ range\ of\ code\ numbers.}$ |
| names | STRING | Comma-separated list of variable names. |
| stdnames | STRING | Comma-separated list of standard names. |
| levels | FLOAT | Comma-separated list of vertical levels. |
| levidx | INTEGER | ${\it Comma-separated\ list\ or\ first/last[/inc]\ range\ of\ index\ of\ levels.}$ |
| ltypes | INTEGER | Comma-separated list or first/last[/inc] range of GRIB level types. |
| grids | STRING | Comma-separated list of grid names or numbers. |
| zaxes | STRING | Comma-separated list of z-axis types or numbers. |
| zaxisnames | STRING | Comma-separated list of z-axis names. |
| tabnums | INTEGER | Comma-separated list or range of parameter table numbers. |

Example

Assume an input dataset has three variables with the code numbers 129, 130 and 139. To select the variables with the code number 129 and 139 use:

```
cdo selcode, 129, 139 infile outfile
```

You can also select the code number 129 and 139 by deleting the code number 130 with:

cdo delcode, 130 infile outfile

Selection Reference manual

2.3.4. SELTIME - Select timesteps

Synopsis

```
seltimestep,timesteps infile outfile
seltime,times infile outfile
selhour,hours infile outfile
selday,days infile outfile
selmonth,months infile outfile
selyear,years infile outfile
selseason,seasons infile outfile
seldate,startdate[,enddate] infile outfile
selsmon,month[,nts1[,nts2]] infile outfile
```

Description

This module selects user specified timesteps from infile and writes them to outfile. The timesteps selected depends on the chosen operator and the parameters. A range of integer values can be specified by first/last[/inc].

Operators

seltimestep Select timesteps

Selects all timesteps with a timestep in a user given list or range.

seltime Select times

Selects all timesteps with a time in a user given list or range.

selhour Select hours

Selects all timesteps with a hour in a user given list or range.

selday Select days

Selects all timesteps with a day in a user given list or range.

selmonth Select months

Selects all timesteps with a month in a user given list or range.

selyear Select years

Selects all timesteps with a year in a user given list or range.

selseason Select seasons

Selects all timesteps with a month of a season in a user given list.

seldate Select dates

Selects all timesteps with a date in a user given range.

selsmon Select single month

Selects a month and optional an arbitrary number of timesteps before and after this

month.

Reference manual Selection

Parameter

| timesteps | INTEGER ues select ti | Comma-separated list or first/last[/inc] range of timesteps. Negative valmesteps from the end (NetCDF only). |
|-----------|--------------------------|--|
| times | STRING | Comma-separated list of times (format hh:mm:ss). |
| hours | INTEGER | Comma-separated list or first/last[/inc] range of hours. |
| days | INTEGER | Comma-separated list or first/last[/inc] range of days. |
| months | INTEGER | Comma-separated list or first/last[/inc] range of months. |
| years | INTEGER | Comma-separated list or first/last[/inc] range of years. |
| seasons | STRING ANN). | ${\bf Comma-separated\ list\ of\ seasons\ (substring\ of\ DJFMAMJJASOND\ or\ }$ |
| startdate | STRING | Start date (format YYYY-MM-DDThh:mm:ss). |
| enddate | STRING | End date (format YYYY-MM-DDThh:mm:ss) [default: startdate]. |
| nts1 | INTEGER | Number of timesteps before the selected month [default: 0]. |
| nts2 | INTEGER | Number of timesteps after the selected month [default: nts1]. |

Selection Reference manual

2.3.5. SELBOX - Select a box

Synopsis

```
sellonlatbox,lon1,lon2,lat1,lat2 infile outfile
selindexbox,idx1,idx2,idy1,idy2 infile outfile
```

Description

Selects grid cells inside a lon/lat or index box.

Operators

sellonlatbox Select a longitude/latitude box

Selects grid cells inside a lon/lat box. The user must specify the longitude and latitude of the edges of the box. Only those grid cells are considered whose grid center lies within the lon/lat box. For rotated lon/lat grids the parameters must

be specified in rotated coordinates.

selindexbox Select an index box

Selects grid cells within an index box. The user must specify the indices of the edges of the box. The index of the left edge can be greater then the one of the right edge. Use negative indexing to start from the end. The input grid must be a

regular lon/lat or a 2D curvilinear grid.

Parameter

| lon1 | FLOAT | Western longitude in degrees |
|------|---------|--|
| lon2 | FLOAT | Eastern longitude in degrees |
| lat1 | FLOAT | Southern or northern latitude in degrees |
| lat2 | FLOAT | Northern or southern latitude in degrees |
| idx1 | INTEGER | Index of first longitude $(1 - nlon)$ |
| idx2 | INTEGER | Index of last longitude (1 - nlon) |
| idy1 | INTEGER | Index of first latitude $(1 - nlat)$ |
| idy2 | INTEGER | Index of last latitude (1 - nlat) |

Example

To select the region with the longitudes from 30W to 60E and latitudes from 30N to 80N from all input fields use:

```
cdo sellonlatbox,-30,60,30,80 infile outfile
```

If the input dataset has fields on a Gaussian N16 grid, the same box can be selected with selindexbox by:

cdo selindexbox,60,11,3,11 infile outfile

Reference manual Selection

2.3.6. SELREGION - Select horizontal regions

Synopsis

```
selregion,regions infile outfile
selcircle[,lon,lat,radius] infile outfile
```

Description

Selects all grid cells with the center point inside user defined regions or a circle. The resulting grid is unstructured.

Operators

selregion Select cells inside regions

Selects all grid cells with the center point inside the regions. The user has to give ASCII formatted files with different regions. A region is defined by a polygon. Each line of a polygon description file contains the longitude and latitude of one point. Each polygon description file can contain one or more polygons separated by a line with the

character &.

selcircle Select cells inside a circle

Selects all grid cells with the center point inside a circle. The circle is described by

geographic coordinates of the center and the radius of the circle.

Parameter

| regions | STRING | Comma-separated list of ASCII formatted files with different regions |
|---------|--------|--|
| lon | FLOAT | Longitude of the center of the circle in degrees, default lon= 0.0 |
| lat | FLOAT | Latitude of the center of the circle in degrees, default lat= 0.0 |
| radius | STRING | Radius of the circle, default radius=1deg (units: deg, rad, km, m) |

Selection Reference manual

2.3.7. SELGRIDCELL - Select grid cells

Synopsis

<operator>,indices infile outfile

Description

The operator selects grid cells of all fields from infile. The user must specify the index of each grid cell. The resulting grid in outfile is unstructured.

Operators

selgridcell Select grid cells

delgridcell Delete grid cells

Parameter

indices INTEGER Comma-separated list or first/last[/inc] range of indices

2.3.8. SAMPLEGRID - Resample grid

Synopsis

samplegrid, factor infile outfile

Description

This is a special operator for resampling the horizontal grid. No interpolation takes place. Resample factor=2 means every second grid point is removed. Only rectilinear and curvilinear source grids are supported by this operator.

Parameter

factor INTEGER Resample factor, typically 2, which will half the resolution

2.3.9. SELYEARIDX - Select year by index

Synopsis

selyearidx infile1 infile2 outfile

Description

Selects field elements from infile2 by a yearly time index from infile1. The yearly indices in infile1 should be the result of corresponding yearminidx and yearmaxidx operations, respectively.

Reference manual Selection

2.3.10. SELSURFACE - Extract surface

Synopsis

<operator> infile outfile
isosurface,isovalue infile outfile

Description

This module computes a surface from all 3D variables. The result is a horizonal 2D field.

Operators

bottomvalue Extract bottom level

This operator selects the valid values at the bottom level. The NetCDF CF compliant attribute positive is used to determine where top and bottom are. If this

attribute is missing, low values are bottom and high values are top.

topvalue Extract top level

This operator selects the valid values at the top level. The NetCDF CF compliant attribute positive is used to determine where top and bottom are. If this attribute

is missing, low values are bottom and high values are top.

isosurface Extract isosurface

This operator computes an isosurface. The value of the isosurface is specified by the

parameter isovalue. The isosurface is calculated by linear interpolation between

two layers.

Parameter

isovalue FLOAT Isosurface value

Conditional selection Reference manual

2.4. Conditional selection

This section contains modules to conditional select field elements. The fields in the first input file are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false".

Here is a short overview of all operators in this section:

ifthen If then ifnotthen If not then

ifthenelse If then else

ifthencIf then constantifnotthencIf not then constant

reducegrid Reduce input file variables to locations, where mask is non-zero.

Reference manual Conditional selection

2.4.1. COND - Conditional select one field

Synopsis

<operator> infile1 infile2 outfile

Description

This module selects field elements from infile2 with respect to infile1 and writes them to outfile. The fields in infile1 are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false". The number of fields in infile1 has either to be the same as in infile2 or the same as in one timestep of infile2 or only one. The fields in outfile inherit the meta data from infile2.

Operators

$$\begin{array}{llll} \textbf{if then} & & \text{If then} \\ & & o(t,x) = \left\{ \begin{array}{lll} i_2(t,x) & \text{if } i_1([t,]x) \neq 0 & \wedge \ i_1([t,]x) \neq \text{miss} \\ & \text{miss} & \text{if } i_1([t,]x) = 0 & \vee \ i_1([t,]x) = \text{miss} \end{array} \right. \\ \textbf{if not then} & & & \text{If not then} \\ & & & o(t,x) = \left\{ \begin{array}{lll} i_2(t,x) & \text{if } i_1([t,]x) = 0 & \wedge \ i_1([t,]x) \neq \text{miss} \\ & \text{miss} & \text{if } i_1([t,]x) \neq 0 & \vee \ i_1([t,]x) = \text{miss} \end{array} \right. \\ \end{array}$$

Example

To select all field elements of infile2 if the corresponding field element of infile1 is greater than 0 use:

cdo ifthen infile1 infile2 outfile

2.4.2. COND2 - Conditional select two fields

Synopsis

ifthenelse infile1 infile2 infile3 outfile

Description

This operator selects field elements from infile2 or infile3 with respect to infile1 and writes them to outfile. The fields in infile1 are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false". The number of fields in infile1 has either to be the same as in infile2 or the same as in one timestep of infile2 or only one. infile2 and infile3 need to have the same number of fields. The fields in outfile inherit the meta data from infile2.

$$o(t,x) = \begin{cases} i_2(t,x) & \text{if } i_1([t,]x) \neq 0 \\ i_3(t,x) & \text{if } i_1([t,]x) = 0 \\ \text{miss} & \text{if } i_1([t,]x) = \text{miss} \end{cases} \land i_1([t,]x) \neq \text{miss}$$

Example

To select all field elements of infile2 if the corresponding field element of infile1 is greater than 0 and from infile3 otherwise use:

cdo ifthenelse infile1 infile2 infile3 outfile

Conditional selection Reference manual

2.4.3. CONDC - Conditional select a constant

Synopsis

< operator >, c infile outfile

Description

This module creates fields with a constant value or missing value. The fields in infile are handled as a mask. A value not equal to zero is treated as "true", zero is treated as "false".

Operators

ifthenc If then constant

$$o(t,x) = \begin{cases} c & \text{if } i(t,x) \neq 0 & \land i(t,x) \neq \text{miss} \\ \text{miss} & \text{if } i(t,x) = 0 & \lor i(t,x) = \text{miss} \end{cases}$$

ifnotthenc If not then constant

$$o(t,x) = \begin{cases} c & \text{if } i(t,x) = 0 \land i(t,x) \neq \text{miss} \\ \text{miss } & \text{if } i(t,x) \neq 0 \lor i(t,x) = \text{miss} \end{cases}$$

Parameter

c FLOAT Constant

Example

To create fields with the constant value 7 if the corresponding field element of infile is greater than 0 use:

cdo ifthenc,7 infile outfile

Reference manual Conditional selection

2.4.4. MAPREDUCE - Reduce fields to user-defined mask

Synopsis

reducegrid,mask[,limitCoordsOutput] infile outfile

Description

This module holds an operator for data reduction based on a user defined mask. The output grid is unstructured and includes coordinate bounds. Bounds can be avoided by using the additional 'nobounds' keyword. With 'nocoords' given, coordinates a completely suppressed.

Parameter

mask STRING file which holds the mask field

limitCoordsOutput STRING optional parameter to limit coordinates output: 'nobounds' dis-

ables coordinate bounds, 'nocoords' avoids all coordinate information

Example

To limit data fields to land values, a mask has to be created first with

```
cdo -gtc,0 -topo,ni96 lsm_gme96.grb
```

Here a GME grid is used. Say temp_gme96.grb contains a global temperture field. The following command limits the global grid to landpoints.

```
cdo -f nc reduce, lsm_gme96.grb temp_gme96.grb tempOnLand_gme96.nc
```

Note that output file type is NetCDF, because unstructured grids cannot be stored in GRIB format.

Comparison Reference manual

2.5. Comparison

This section contains modules to compare datasets. The resulting field is a mask containing 1 if the comparison is true and 0 if not.

Here is a short overview of all operators in this section:

| \mathbf{eq} | Equal |
|-------------------|---|
| ne | Not equal |
| le | Less equal |
| lt | Less than |
| \mathbf{ge} | Greater equal |
| \mathbf{gt} | Greater than |
| | |
| | E 1 4 4 |
| \mathbf{eqc} | Equal constant |
| nec | Not equal constant |
| - | _ * |
| nec | Not equal constant |
| nec lec | Not equal constant Less equal constant |
| nec lec ltc | Not equal constant Less equal constant Less than constant |

Reference manual Comparison

2.5.1. COMP - Comparison of two fields

Synopsis

<operator> infile1 infile2 outfile

Description

This module compares two datasets field by field. The resulting field is a mask containing 1 if the comparison is true and 0 if not. The number of fields in infile1 should be the same as in infile2. One of the input files can contain only one timestep or one field. The fields in outfile inherit the meta data from infile1 or infile2. The type of comparison depends on the chosen operator.

Operators

$$\mathbf{eq} \qquad \text{Equal}$$

$$o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) = i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) \neq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right.$$

$$o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) \neq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) = i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss } & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right.$$

$$o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) \leq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) > i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss } & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right.$$

$$o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) < i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) \geq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss } & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right.$$

$$\mathbf{ge} \qquad \text{Greater equal} \\ o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) \geq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) < i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss } & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right.$$

$$\begin{aligned} \mathbf{gt} & & \text{Greater than} \\ o(t,x) &= \left\{ \begin{array}{ll} 1 & \text{if } i_1(t,x) > i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ 0 & \text{if } i_1(t,x) \leq i_2(t,x) & \wedge \ i_1(t,x), i_2(t,x) \neq \text{miss} \\ \text{miss} & \text{if } i_1(t,x) = \text{miss} & \vee \ i_2(t,x) = \text{miss} \end{array} \right. \end{aligned}$$

Example

To create a mask containing 1 if the elements of two fields are the same and 0 if the elements are different use:

cdo eq infile1 infile2 outfile

Comparison Reference manual

2.5.2. COMPC - Comparison of a field with a constant

Synopsis

< operator >, c infile outfile

Description

This module compares all fields of a dataset with a constant. The resulting field is a mask containing 1 if the comparison is true and 0 if not. The type of comparison depends on the chosen operator.

Operators

eqc Equal constant

$$o(t,x) = \begin{cases} 1 & \text{if } i(t,x) = c & \wedge i(t,x), c \neq \text{miss} \\ 0 & \text{if } i(t,x) \neq c & \wedge i(t,x), c \neq \text{miss} \\ \text{miss } & \text{if } i(t,x) = \text{miss} & \vee c = \text{miss} \end{cases}$$

nec Not equal constant

$$o(t,x) = \begin{cases} 1 & \text{if } i(t,x) \neq c & \wedge i(t,x), c \neq \text{miss} \\ 0 & \text{if } i(t,x) = c & \wedge i(t,x), c \neq \text{miss} \\ \text{miss } & \text{if } i(t,x) = \text{miss} & \vee c = \text{miss} \end{cases}$$

lec Less equal constant

$$o(t,x) = \begin{cases} 1 & \text{if } i(t,x) \le c & \wedge i(t,x), c \ne \text{miss} \\ 0 & \text{if } i(t,x) > c & \wedge i(t,x), c \ne \text{miss} \\ \text{miss } & \text{if } i(t,x) = \text{miss} & \vee c = \text{miss} \end{cases}$$

ltc Less than constant

$$o(t,x) = \begin{cases} 1 & \text{if } i(t,x) < c & \wedge i(t,x), c \neq \text{miss} \\ 0 & \text{if } i(t,x) \geq c & \wedge i(t,x), c \neq \text{miss} \\ \text{miss } if i(t,x) = \text{miss} & \vee c = \text{miss} \end{cases}$$

gec Greater equal constant

$$o(t,x) = \begin{cases} 1 & \text{if } i(t,x) \ge c & \wedge i(t,x), c \ne \text{miss} \\ 0 & \text{if } i(t,x) < c & \wedge i(t,x), c \ne \text{miss} \\ \text{miss } & \text{if } i(t,x) = \text{miss} & \vee c = \text{miss} \end{cases}$$

gtc Greater than constant

$$o(t,x) = \left\{ \begin{array}{ll} 1 & \text{if } i(t,x) > c & \wedge \ i(t,x), c \neq \text{miss} \\ 0 & \text{if } i(t,x) \leq c & \wedge \ i(t,x), c \neq \text{miss} \\ \text{miss } & \text{if } i(t,x) = \text{miss} & \vee \ c = \text{miss} \end{array} \right.$$

Parameter

c FLOAT Constant

Example

To create a mask containing 1 if the field element is greater than 273.15 and 0 if not use:

cdo gtc,273.15 infile outfile

Reference manual Modification

2.6. Modification

This section contains modules to modify the metadata, fields or part of a field in a dataset.

Here is a short overview of all operators in this section:

setattribute Set attributes

setpartabpSet parameter tablesetpartabnSet parameter table

setcodetab Set parameter code table

setcode Set code number

setparamSet parameter identifiersetnameSet variable namesetunitSet variable unit

setlevel Set level

setltype Set GRIB level type

setdate Set date

settime Set time of the day

setday Set day setmon Set month setyear Set year Set time units settunits settaxis Set time axis Set time bounds settbounds Set reference time setreftime setcalendar Set calendar shifttime Shift timesteps

chcodechparamChange code numberChange parameter identifier

chname Change variable or coordinate name

chunit Change variable unit

chlevel Change level

chlevelc Change level of one codechlevelv Change level of one variable

setgridSet gridsetgridtypeSet grid typesetgridareaSet grid cell areasetgridmaskSet grid mask

setzaxis Set z-axis

genlevelbounds Generate level bounds

invertlat Invert latitudes

invertlev Invert levels

shiftxShift xshiftyShift y

maskregion Mask regions

Modification Reference manual

masklonlatbox Mask a longitude/latitude box

maskindexbox Mask an index box

setclonlatbox Set a longitude/latitude box to constant

setcindexbox Set an index box to constant

enlarge Enlarge fields

setmissvalSet a new missing valuesetctomissSet constant to missing valuesetmisstocSet missing value to constantsetrtomissSet range to missing value

setvrange Set valid range

setmisstonn Set missing value to nearest neighbor

setmisstodis Set missing value to distance-weighted average

setgridcell Set the value of a grid cell

Reference manual Modification

2.6.1. SETATTRIBUTE - Set attributes

Synopsis

setattribute, attributes infile outfile

Description

This operator sets attributes of a dataset and writes the result to outfile. The new attributes are only available in outfile if the file format supports attributes.

Each attribute has the following structure:

```
[var_nm@]att_nm[:s|d|i]=[att_val|{[var_nm@]att_nm}]
var_nm    Variable name (optional). Example: pressure
att_nm    Attribute name. Example: units
att_val    Comma-separated list of attribute values. Example: pascal
```

The value of var_nm is the name of the variable containing the attribute (named att_nm) that you want to set. Use wildcards to set the attribute att_nm to more than one variable. A value of var_nm of '*' will set the attribute att_nm to all data variables. If var_nm is missing then att_nm refers to a global attribute.

The value of **att_nm** is the name of the attribute you want to set. For each attribute a string (att_nm:s), a double (att_nm:d) or an integer (att_nm:i) type can be defined. By default the native type is set.

The value of att_val is the contents of the attribute att_nm. att_val may be a single value or one-dimensional array of elements. The type and the number of elements of an attribute will be detected automatically from the contents of the values. An already existing attribute att_nm will be overwritten or it will be removed if att_val is omitted. Alternatively, the values of an existing attribute can be copied. This attribute must then be enclosed in curly brackets.

A special meaning has the attribute name **FILE**. If this is the 1st attribute then all attributes are read from a file specified in the value of **att_val**.

Parameter

attributes STRING Comma-separated list of attributes.

Note

Attributes are evaluated by **CDO** when opening infile. Therefor the result of this operator is not available for other operators when this operator is used in chaining operators.

Example

To set the units of the variable pressure to pascal use:

```
cdo setattribute,pressure@units=pascal infile outfile
```

To set the global text attribute "my_att" to "my contents", use:

```
cdo setattribute,my_att="my contents" infile outfile
```

Result of 'ncdump -h outfile':

Modification Reference manual

2.6.2. SETPARTAB - Set parameter table

Synopsis

< operator >, table[, convert] infile outfile

Description

This module transforms data and metadata of infile via a parameter table and writes the result to outfile. A parameter table is an ASCII formatted file with a set of parameter entries for each variable. Each new set have to start with "¶meter" and to end with "/".

The following parameter table entries are supported:

| Entry | Type | Description |
|-----------------|---------|--|
| name | WORD | Name of the variable |
| out_name | WORD | New name of the variable |
| param | WORD | Parameter identifier (GRIB1: code[.tabnum]; GRIB2: num[.cat[.dis]]) |
| out_param | WORD | New parameter identifier |
| type | WORD | Data type (real or double) |
| standard_name | WORD | As defined in the CF standard name table |
| long_name | STRING | Describing the variable |
| units | STRING | Specifying the units for the variable |
| comment | STRING | Information concerning the variable |
| cell_methods | STRING | Information concerning calculation of means or climatologies |
| cell_measures | STRING | Indicates the names of the variables containing cell areas and volumes |
| missing_value | FLOAT | Specifying how missing data will be identified |
| valid_min | FLOAT | Minimum valid value |
| valid_max | FLOAT | Maximum valid value |
| ok_min_mean_abs | FLOAT | Minimum absolute mean |
| ok_max_mean_abs | FLOAT | Maximum absolute mean |
| factor | FLOAT | Scale factor |
| delete | INTEGER | Set to 1 to delete variable |
| convert | INTEGER | Set to 1 to convert the unit if necessary |

Unsupported parameter table entries are stored as variable attributes. The search key for the variable depends on the operator. Use setpartabn to search variables by the name. This is typically used for NetCDF datasets. The operator setpartabp searches variables by the parameter ID.

Operators

setpartabp Set parameter table

Search variables by the parameter identifier.

setpartabn Set parameter table

Search variables by name.

Parameter

table STRING Parameter table file or nameconvert STRING Converts the units if necessary

Example

Here is an example of a parameter table for one variable:

To apply this parameter table to a dataset use:

```
cdo setpartabn,mypartab,convert infile outfile
```

This command renames the variable **t** to **ta**. The standard name of this variable is set to **air_temperature** and the unit is set to [K] (converts the unit if necessary). The missing value will be set to **1.0e+20**. In addition it will be checked whether the values of the variable are in the range of **157.1** to **336.3**.

2.6.3. SET - Set field info

Synopsis

```
setcodetab,table infile outfile
setcode,code infile outfile
setparam,param infile outfile
setname,name infile outfile
setunit,unit infile outfile
setlevel,level infile outfile
setltype,ltype infile outfile
```

Description

This module sets some field information. Depending on the chosen operator the parameter table, code number, parameter identifier, variable name or level is set.

Operators

setcodetab Set parameter code table

Sets the parameter code table for all variables.

setcode Set code number

Sets the code number for all variables to the same given value.

setparam Set parameter identifier

Sets the parameter identifier of the first variable.

setname Set variable name

Sets the name of the first variable.

setunit Set variable unit

Sets the unit of the first variable.

setlevel Set level

Sets the first level of all variables.

setltype Set GRIB level type

Sets the GRIB level type of all variables.

Parameter

| table | STRING | Parameter table file or name |
|-------|---------|--|
| code | INTEGER | Code number |
| param | STRING | $Parameter\ identifier\ (GRIB1:\ code[.tabnum];\ GRIB2:\ num[.cat[.dis]])$ |
| name | STRING | Variable name |
| level | FLOAT | New level |
| ltype | INTEGER | GRIB level type |

2.6.4. SETTIME - Set time

Synopsis

```
setdate,date infile outfile
settime,time infile outfile
setday,day infile outfile
setmon,month infile outfile
setyear,year infile outfile
settunits,units infile outfile
settaxis,date,time[,inc] infile outfile
settbounds,frequency infile outfile
setreftime,date,time[,units] infile outfile
setcalendar,calendar infile outfile
shifttime,sval infile outfile
```

Description

This module sets the time axis or part of the time axis. Which part of the time axis is overwritten/created depends on the chosen operator.

Operators

setdate Set date

Sets the date in every timestep to the same given value.

settime Set time of the day

Sets the time in every timestep to the same given value.

setday Set day

Sets the day in every timestep to the same given value.

setmon Set month

Sets the month in every timestep to the same given value.

setyear Set year

Sets the year in every timestep to the same given value.

settunits Set time units

Sets the base units of a relative time axis.

settaxis Set time axis

Sets the time axis.

settbounds Set time bounds

Sets the time bounds.

setreftime Set reference time

Sets the reference time of a relative time axis.

setcalendar Set calendar

Sets the calendar of a relative time axis.

shifttime Shift timesteps

Shifts all timesteps by the parameter sval.

Parameter

| day | INTEGER | Value of the new day |
|-----------|-------------------------|---|
| month | INTEGER | Value of the new month |
| year | INTEGER | Value of the new year |
| units | STRING | Base units of the time axis (seconds, minutes, hours, days, months, years) $$ |
| date | STRING | Date (format: YYYY-MM-DD) |
| time | STRING | Time (format: hh:mm:ss) |
| inc | STRING fault: 1hour] | Optional increment (seconds, minutes, hours, days, months, years) [de- |
| frequency | STRING | Frequency of the time series (hour, day, month, year) |
| calendar | STRING | Calendar (standard, proleptic_gregorian, 360_day, 365_day, 366_day) |
| sval | STRING | Shift value (e.g3hour) |

Example

To set the time axis to 1987-01-16 12:00:00 with an increment of one month for each timestep use:

```
cdo settaxis,1987-01-16,12:00:00,1mon infile outfile
```

Result of 'cdo showdate outfile' for a dataset with 12 timesteps:

To shift this time axis by -15 days use:

```
cdo shifttime,-15days infile outfile
```

Result of 'cdo showdate outfile':

2.6.5. CHANGE - Change field header

Synopsis

chcode,oldcode,newcode[,...] infile outfile
chparam,oldparam,newparam,... infile outfile
chname,oldname,newname,... infile outfile
chunit,oldunit,newunit,... infile outfile
chlevel,oldlev,newlev,... infile outfile
chlevelc,code,oldlev,newlev infile outfile
chlevelv,name,oldlev,newlev infile outfile

Description

This module reads fields from infile, changes some header values and writes the results to outfile. The kind of changes depends on the chosen operator.

Operators

chcode Change code number

Changes some user given code numbers to new user given values.

chparam Change parameter identifier

Changes some user given parameter identifiers to new user given values.

chname Change variable or coordinate name

Changes some user given variable or coordinate names to new user given names.

chunit Change variable unit

Changes some user given variable units to new user given units.

chlevel Change level

Changes some user given levels to new user given values.

chlevelc Change level of one code

Changes one level of a user given code number.

chlevelv Change level of one variable

Changes one level of a user given variable name.

Parameter

| code | INTEGER | Code number |
|-----------------------------|---------|--|
| $old code, new code, \dots$ | INTEGER | Pairs of old and new code numbers |
| $oldparam, newparam, \dots$ | STRING | Pairs of old and new parameter identifiers |
| name | STRING | Variable name |
| $oldname, newname, \dots$ | STRING | Pairs of old and new variable names |
| oldlev | FLOAT | Old level |
| newlev | FLOAT | New level |
| $old lev, new lev, \dots$ | FLOAT | Pairs of old and new levels |

Example

To change the code number 98 to 179 and 99 to 211 use:

cdo chcode, 98, 179, 99, 211 infile outfile

2.6.6. SETGRID - Set grid information

Synopsis

```
setgrid,grid infile outfile
setgridtype,gridtype infile outfile
setgridarea,gridarea infile outfile
setgridmask,gridmask infile outfile
```

Description

This module modifies the metadata of the horizontal grid. Depending on the chosen operator a new grid description is set, the coordinates are converted or the grid cell area is added.

Operators

setgrid Set grid

Sets a new grid description. The input fields need to have the same grid size as the

size of the target grid description.

setgridtype Set grid type

Sets the grid type of all input fields. The following grid types are available:

curvilinear Converts a regular grid to a curvilinear grid

unstructured Converts a regular or curvilinear grid to an unstructured grid

dereference Dereference a reference to a grid

regular Linear interpolation of a reduced Gaussian grid to a regular Gaus-

sian grid

regularnn Nearest neighbor interpolation of a reduced Gaussian grid to a

regular Gaussian grid

lonlat Converts a regular lonlat grid stored as a curvilinear grid back to

a lonlat grid

setgridarea Set grid cell area

Sets the grid cell area. The parameter *gridarea* is the path to a data file, the first field is used as grid cell area. The input fields need to have the same grid size as the grid cell area. The grid cell area is used to compute the weights of each grid cell if

needed by an operator, e.g. for fldmean.

setgridmask Set grid mask

Sets the grid mask. The parameter *gridmask* is the path to a data file, the first field is used as the grid mask. The input fields need to have the same grid size as the grid mask. The grid mask is used as the target grid mask for remapping, e.g. for

remapbil.

Parameter

| grid | STRING | Grid description file or name |
|----------|--------|---|
| gridtype | STRING | Grid type (curvilinear, unstructured, regular, lonlat or dereference) |
| gridarea | STRING | Data file, the first field is used as grid cell area |
| gridmask | STRING | Data file, the first field is used as grid mask |

Example

Assuming a dataset has fields on a grid with 2048 elements without or with wrong grid description. To set the grid description of all input fields to a Gaussian N32 grid (8192 gridpoints) use:

cdo setgrid, n32 infile outfile

2.6.7. SETZAXIS - Set z-axis information

Synopsis

```
setzaxis,zaxis infile outfile
genlevelbounds[,zbot[,ztop]] infile outfile
```

Description

This module modifies the metadata of the vertical grid.

Operators

setzaxis Set z-axis

This operator sets the z-axis description of all variables with the same number

of level as the new z-axis.

genlevelbounds Generate level bounds

Generates the layer bounds of the z-axis.

Parameter

| zaxis | STRING | Z-axis description file or name of the target z-axis |
|-------|------------------|--|
| zbot | FLOAT z-axis. | Specifying the bottom of the vertical column. Must have the same units as |
| ztop | FLOAT | Specifying the top of the vertical column. Must have the same units as z-axis. |

2.6.8. INVERT - Invert latitudes

Synopsis

invertlat infile outfile

Description

This operator inverts the latitudes of all fields on a rectilinear grid.

Example

To invert the latitudes of a 2D field from N->S to S->N use:

cdo invertlat infile outfile

2.6.9. INVERTLEV - Invert levels

Synopsis

invertlev infile outfile

Description

This operator inverts the levels of all 3D variables.

2.6.10. SHIFTXY - Shift field

Synopsis

```
< operator >, < nshift >, < cyclic >, < coord > infile outfile
```

Description

This module contains operators to shift all fields in x or y direction. All fields need to have the same horizontal rectilinear or curvilinear grid.

Operators

shiftx Shift x

Shifts all fields in x direction.

shifty Shift y

Shifts all fields in y direction.

Parameter

nshift INTEGER Number of grid cells to shift (default: 1)

cyclic STRING If set, cells are filled up cyclic (default: missing value)

coord STRING If set, coordinates are also shifted

Example

To shift all input fields in the x direction by +1 cells and fill the new cells with missing value, use:

```
cdo shiftx infile outfile
```

To shift all input fields in the x direction by +1 cells and fill the new cells cyclic, use:

cdo shiftx,1,cyclic infile outfile

2.6.11. MASKREGION - Mask regions

Synopsis

maskregion, regions infile outfile

Description

Masks different regions of fields with a regular lon/lat grid. The elements inside a region are untouched, the elements outside are set to missing value. Considered are only those grid cells with the grid center inside the regions. All input fields must have the same horizontal grid. The user has to give ASCII formatted files with different regions. A region is defined by a polygon. Each line of a polygon description file contains the longitude and latitude of one point. Each polygon description file can contain one or more polygons separated by a line with the character &.

Parameter

regions STRING Comma-separated list of ASCII formatted files with different regions

Example

To mask the region with the longitudes from 120E to 90W and latitudes from 20N to 20S on all input fields use:

```
cdo maskregion, myregion infile outfile
```

For this example the description file of the region myregion should contain one polygon with the following four coordinates:

```
\begin{array}{cccc}
120 & 20 \\
120 & -20 \\
270 & -20 \\
270 & 20
\end{array}
```

2.6.12. MASKBOX - Mask a box

Synopsis

```
masklonlatbox,lon1,lon2,lat1,lat2 infile outfile maskindexbox,idx1,idx2,idy1,idy2 infile outfile
```

Description

Masks grid cells inside a lon/lat or index box. The elements inside the box are untouched, the elements outside are set to missing value. All input fields need to have the same horizontal grid. Use sellonlatbox or selindexbox if only the data inside the box are needed.

Operators

masklonlatbox Mask a longitude/latitude box

Masks grid cells inside a lon/lat box. The user must specify the longitude and latitude of the edges of the box. Only those grid cells are considered whose grid center lies within the lon/lat box. For rotated lon/lat grids the parameters must

be specified in rotated coordinates.

maskindexbox Mask an index box

Masks grid cells within an index box. The user must specify the indices of the edges of the box. The index of the left edge can be greater then the one of the right edge. Use negative indexing to start from the end. The input grid must

be a regular lon/lat or a 2D curvilinear grid.

Parameter

| lon1 | FLOAT | Western longitude |
|------|---------|-------------------------------|
| lon2 | FLOAT | Eastern longitude |
| lat1 | FLOAT | Southern or northern latitude |
| lat2 | FLOAT | Northern or southern latitude |
| idx1 | INTEGER | Index of first longitude |
| idx2 | INTEGER | Index of last longitude |
| idy1 | INTEGER | Index of first latitude |
| idy2 | INTEGER | Index of last latitude |

Example

To mask the region with the longitudes from 120E to 90W and latitudes from 20N to 20S on all input fields use:

```
cdo masklonlatbox, 120, -90, 20, -20 infile outfile
```

If the input dataset has fields on a Gaussian N16 grid, the same box can be masked with maskindexbox by:

cdo maskindexbox,23,48,13,20 infile outfile

2.6.13. SETBOX - Set a box to constant

Synopsis

```
setclonlatbox,c,lon1,lon2,lat1,lat2 infile outfile setcindexbox,c,idx1,idx2,idy1,idy2 infile outfile
```

Description

Sets a box of the rectangularly understood field to a constant value. The elements outside the box are untouched, the elements inside are set to the given constant. All input fields need to have the same horizontal grid.

Operators

setclonlatbox Set a longitude/latitude box to constant

Sets the values of a longitude/latitude box to a constant value. The user has to

give the longitudes and latitudes of the edges of the box.

setcindexbox Set an index box to constant

Sets the values of an index box to a constant value. The user has to give the

indices of the edges of the box. The index of the left edge can be greater than the

one of the right edge.

Parameter

| c | FLOAT | Constant |
|-------|---------|-------------------------------|
| lon1 | FLOAT | Western longitude |
| lon 2 | FLOAT | Eastern longitude |
| lat1 | FLOAT | Southern or northern latitude |
| lat2 | FLOAT | Northern or southern latitude |
| idx1 | INTEGER | Index of first longitude |
| idx2 | INTEGER | Index of last longitude |
| idy1 | INTEGER | Index of first latitude |
| idy2 | INTEGER | Index of last latitude |

Example

To set all values in the region with the longitudes from 120E to 90W and latitudes from 20N to 20S to the constant value -1.23 use:

```
cdo setclonlatbox,-1.23,120,-90,20,-20 infile outfile
```

If the input dataset has fields on a Gaussian N16 grid, the same box can be set with setcindexbox by:

```
cdo setcindexbox, -1.23,23,48,13,20 infile outfile
```

2.6.14. ENLARGE - Enlarge fields

Synopsis

enlarge, grid infile outfile

Description

Enlarge all fields of infile to a user given horizontal grid. Normally only the last field element is used for the enlargement. If however the input and output grid are regular lon/lat grids, a zonal or meridional enlargement is possible. Zonal enlargement takes place, if the xsize of the input field is 1 and the ysize of both grids are the same. For meridional enlargement the ysize have to be 1 and the xsize of both grids should have the same size.

Parameter

grid STRING Target grid description file or name

Example

Assumed you want to add two datasets. The first dataset is a field on a global grid (n field elements) and the second dataset is a global mean (1 field element). Before you can add these two datasets the second dataset have to be enlarged to the grid size of the first dataset:

```
cdo enlarge,infile1 infile2 tmpfile
cdo add infile1 tmpfile outfile
```

Or shorter using operator piping:

```
cdo add infile1 -enlarge, infile1 infile2 outfile
```

2.6.15. SETMISS - Set missing value

Synopsis

setmissval, newmiss infile outfile setctomiss, c infile outfile setmisstoc,c infile outfile setrtomiss, rmin, rmax infile outfile setvrange, rmin, rmax infile outfile setmisstonn infile outfile setmisstodis[,neighbors] infile outfile

Description

This module sets part of a field to missing value or missing values to a constant value. Which part of the field is set depends on the chosen operator.

Operators

setmissval

Set a new missing value $o(t,x) = \left\{ \begin{array}{ll} \text{newmiss} & \text{if} \ i(t,x) = miss \\ i(t,x) & \text{if} \ i(t,x) \neq miss \end{array} \right.$

setctomiss Set constant to missing value

 $o(t,x) = \begin{cases} \text{miss} & \text{if } i(t,x) = c \\ i(t,x) & \text{if } i(t,x) \neq c \end{cases}$

setmisstoc Set missing value to constant

 $o(t,x) = \begin{cases} c & \text{if } i(t,x) = \text{miss} \\ i(t,x) & \text{if } i(t,x) \neq \text{miss} \end{cases}$

Set range to missing value setrtomiss

 $o(t,x) = \left\{ \begin{array}{ll} \text{miss} & \text{if} \ i(t,x) \geq r\min \land i(t,x) \leq r\max \\ i(t,x) & \text{if} \ i(t,x) < r\min \lor i(t,x) > r\max \\ \end{array} \right.$

Set valid range setvrange

 $o(t,x) = \left\{ \begin{array}{ll} \text{miss} & \text{if} \ i(t,x) < \min \lor i(t,x) > \max \\ i(t,x) & \text{if} \ i(t,x) \geq \min \land i(t,x) \leq \max \end{array} \right.$

Set missing value to nearest neighbor setmisstonn

Set all missing values to the nearest non missing value.

 $o(t,x) = \left\{ \begin{array}{ll} i(t,y) & \text{if } i(t,x) = \text{miss} \wedge i(t,y) \neq \text{miss} \\ i(t,x) & \text{if } i(t,x) \neq \text{miss} \end{array} \right.$

Set missing value to distance-weighted average setmisstodis

> Set all missing values to the distance-weighted average of the nearest non missing values. The default number of nearest neighbors is 4.

Parameter

neighbors **INTEGER** Number of nearest neighbors New missing value newmiss **FLOAT FLOAT** Constant cLower bound **FLOAT** rmin Upper bound **FLOAT** rmax

Example

setrtomiss

Assume an input dataset has one field with temperatures in the range from 246 to 304 Kelvin. To set all values below 273.15 Kelvin to missing value use:

```
cdo setrtomiss,0,273.15 infile outfile
```

Result of 'cdo info infile':

| -1 : | Date | Time | Code | Level | Size | $_{ m Miss}$ | : | Minimum | Mean | Maximum |
|------|----------------|----------|------|-------|------|--------------|---|---------|--------|---------|
| 1 : | 1987 - 12 - 31 | 12:00:00 | 139 | 0 | 2048 | 0 | : | 246.27 | 276.75 | 303.71 |

Result of 'cdo info outfile':


| -1 : | Date | Time | Code | Level | Size | Miss | : | Minimum | Mean | Maximum |
|------|----------------|----------|------|-------|------|------|---|---------|--------|---------|
| 1 : | 1987 - 12 - 31 | 12:00:00 | 139 | 0 | 2048 | 871 | : | 273.16 | 287.08 | 303.71 |

setmisstonn

Set all missing values to the nearest non missing value:

```
cdo setmisstonn infile outfile
```

Below is a schematic illustration of this example:



On the left side is input data with missing values in grey and on the right side the result with the filled missing values.

2.6.16. SETGRIDCELL - Set the value of a grid cell

Synopsis

setgridcell,params infile outfile

Description

This operator sets the value of the selected grid cells. The grid cells can be selected by a commaseparated list of grid cell indices or a mask. The mask is read from a data file, which may contain only one field. If no grid cells are selected, all values are set.

Parameter

| value | FLOAT | Value of the grid cell |
|-------|---------|---|
| cell | INTEGER | Comma-separated list of grid cell indices |
| mask | STRING | Name of the data file which contains the mask |

2.7. Arithmetic

This section contains modules to arithmetically process datasets.

Here is a short overview of all operators in this section:

expr Evaluate expressions

exprf Evaluate expressions script

aexprEvaluate expressions and append resultsEvaluate expression script and append results

absAbsolute valueintInteger value

nint Nearest integer value

powPowersqrSquaresqrtSquare rootexpExponentiallnNatural logarithmlog10Base 10 logarithm

Sine \sin cos Cosine Tangent tan asin Arc sine acos Arc cosine Arc tangent atan reci Reciprocal value Logical NOT not

addc
subc
Subtract a constant
mulc
Multiply with a constant
divc
Divide by a constant

minc Minimum of a field and a constant maxc Maximum of a field and a constant

addAdd two fieldssubSubtract two fieldsmulMultiply two fieldsdivDivide two fieldsminMinimum of two fieldsmaxMaximum of two fieldsatan2Arc tangent of two fields

dayaddAdd daily time seriesdaysubSubtract daily time seriesdaymulMultiply daily time seriesdaydivDivide daily time series

monaddAdd monthly time seriesmonsubSubtract monthly time seriesmonmulMultiply monthly time seriesmondivDivide monthly time series

yearadd Add yearly time series
yearsub Subtract yearly time series
yearmul Multiply yearly time series
yeardiv Divide yearly time series

yhouraddAdd multi-year hourly time seriesyhoursubSubtract multi-year hourly time seriesyhourmulMultiply multi-year hourly time seriesyhourdivDivide multi-year hourly time series

ydayadd Add multi-year daily time series
ydaysub Subtract multi-year daily time series
ydaymul Multiply multi-year daily time series
ydaydiv Divide multi-year daily time series

ymonaddAdd multi-year monthly time seriesymonsubSubtract multi-year monthly time seriesymonmulMultiply multi-year monthly time seriesymondivDivide multi-year monthly time series

yseasadd
yseassub
yseasmul
yseasdiv

Add multi-year seasonal time series
Subtract multi-year seasonal time series
Multiply multi-year seasonal time series
Divide multi-year seasonal time series

muldpmMultiply with days per monthdivdpmDivide by days per monthmuldpyMultiply with days per yeardivdpyDivide by days per year

mulcoslat Multiply with the cosine of the latitude

divcoslat Divide by cosine of the latitude

2.7.1. EXPR - Evaluate expressions

Synopsis

```
expr,instr infile outfile
exprf,filename infile outfile
aexpr,instr infile outfile
aexprf,filename infile outfile
```

Description

This module arithmetically processes every timestep of the input dataset. Each individual assignment statement have to end with a semi-colon. The special key _ALL_ is used as a template. A statement with a template is replaced for all variable names. Unlike regular variables, temporary variables are never written to the output stream. To define a temporary variable simply prefix the variable name with an underscore (e.g. _varname) when the variable is declared.

The following operators are supported:

| Operator | Meaning | Example | Result |
|----------|---------------------|-----------|--|
| = | assignment | x = y | Assigns y to x |
| + | addition | x + y | Sum of x and y |
| - | subtraction | x - y | Difference of x and y |
| * | multiplication | x * y | Product of x and y |
| / | division | x / y | Quotient of x and y |
| ^ | exponentiation | x ^ y | Exponentiates x with y |
| == | equal to | x == y | 1, if x equal to y; else 0 |
| != | not equal to | x != y | 1, if x not equal to y; else 0 |
| > | greater than | x > y | 1, if x greater than y; else 0 |
| < | less than | x < y | 1, if x less than y; else 0 |
| >= | greater equal | x >= y | 1, if x greater equal y; else 0 |
| <= | less equal | x <= y | 1, if x less equal y; else 0 |
| <=> | less equal greater | x <=> y | -1, if x less y; 1, if x greater y; else 0 |
| && | logical AND | х && у | 1, if x and y not equal 0; else 0 |
| | logical OR | x y | 1, if x or y not equal 0; else 0 |
| ! | logical NOT | !x | 1, if x equal 0; else 0 |
| ?: | ternary conditional | x ? y : z | y, if x not equal 0, else z |

The following functions are supported:

Math intrinsics:

| abs(x) | Absolute value of x |
|--------------------------|--|
| floor(x) | Round to largest integral value not greater than $\mathbf x$ |
| ceil(x) | Round to smallest integral value not less than x |
| float(x) | 32-bit float value of x |
| int(x) | Integer value of x |
| nint(x) | Nearest integer value of x |
| sqr(x) | Square of x |
| $\operatorname{sqrt}(x)$ | Square Root of x |
| $\exp(x)$ | Exponential of x |

| ln(x) | Natural logarithm of x |
|------------------------------|--|
| log10(x) | Base 10 logarithm of x |
| $\sin(x)$ | Sine of x, where x is specified in radians |
| $\cos(x)$ | Cosine of x, where x is specified in radians |
| tan(x) | Tangent of x, where x is specified in radians |
| asin(x) | Arc-sine of x, where x is specified in radians |
| acos(x) | Arc-cosine of x, where x is specified in radians |
| atan(x) | Arc-tangent of x, where x is specified in radians |
| sinh(x) | Hyperbolic sine of x, where x is specified in radians |
| $\cosh(x)$ | Hyperbolic cosine of x, where x is specified in radians |
| tanh(x) | Hyperbolic tangent of x, where x is specified in radians |
| asinh(x) | Inverse hyperbolic sine of x, where x is specified in radians |
| $\operatorname{acosh}(x)$ | Inverse hyperbolic cosine of x, where x is specified in radians |
| atanh(x) | Inverse hyperbolic tangent of x, where x is specified in radians |
| rad(x) | Convert x from degrees to radians |
| deg(x) | Convert x from radians to degrees |
| rand(x) | Replace x by pseudo-random numbers in the range of 0 to 1 $$ |
| is Missval(x) | Returns 1 where x is missing |
| mod(x,y) | Floating-point remainder of x/ y |
| $\min(x,y)$ | Minimum value of x and y |
| $\max(x,y)$ | Maximum value of x and y |
| pow(x,y) | Power function |
| hypot(x,y) | Euclidean distance function, $sqrt(x*x + y*y)$ |
| atan2(x,y) | Arc tangent function of y/x, using signs to determine quadrants |
| Coordinates: | |
| clon(x) | Longitude coordinate of $\mathbf x$ (available only if $\mathbf x$ has geographical coordinates) |
| clat(x) | Latitude coordinate of $\mathbf x$ (available only if $\mathbf x$ has geographical coordinates) |
| gridarea(x) | Grid cell area of $\mathbf x$ (available only if $\mathbf x$ has geographical coordinates) |
| clev(x) | Level coordinate of x $(0, if x is a 2D surface variable)$ |
| $\operatorname{clevidx}(x)$ | Level index of x (0, if x is a 2D surface variable) |
| cthickness(x) | Layer thickness, upper minus lower level bound of x $(1, if level bounds are missing)$ |
| $\operatorname{ctimestep}()$ | Timestep number (1 to N) |
| cdate() | Verification date as YYYYMMDD |
| ctime() | Verification time as HHMMSS.millisecond |
| cdeltat() | Difference between current and last timestep in seconds |
| $\operatorname{cday}()$ | Day as DD |
| $\mathrm{cmonth}()$ | Month as MM |
| cyear() | Year as YYYY |
| | |

csecond() Second as SS.millisecond

cminute() Minute as MM chour() Hour as HH

Constants:

ngp(x) Number of horizontal grid points

nlev(x) Number of vertical levels

size(x) Total number of elements (ngp(x)*nlev(x))missval(x) Returns the missing value of variable x

Statistical values over a field:

fldmin(x), fldmax(x), fldrange(x), fldsum(x), fldmean(x), fldavg(x), fldstd(x), fldstd1(x), fldvar(x), fldvar(x), fldwar(x), fldwar(x),

Zonal statistical values for regular 2D grids:

zonmin(x), zonmax(x), zonmax(x), zonsum(x), zonmean(x), zonavg(x), zonstd(x), zonstd1(x), zonstd1(x), zonsum(x), zonwar1(x), zonsum(x), zonwar1(x), zonwar1(x)

Vertical statistical values:

vertmin(x), vertmax(x), vertmax(x), vertsum(x), vertmean(x), vertavg(x), vertstd(x), vertstd(x), vertvar(x), vertvar(x)

Miscellaneous:

sellevel(x,k) Select level k of variable x

sellevidx(x,k) Select level index k of variable x

sellevelrange(x,k1,k2) Select all levels of variable x in the range k1 to k2

sellevidxrange(x,k1,k2) Select all level indices of variable x in the range k1 to k2

remove(x) Remove variable x from output stream

Operators

expr Evaluate expressions

The processing instructions are read from the parameter.

exprf Evaluate expressions script

Contrary to expr the processing instructions are read from a file.

aexpr Evaluate expressions and append results

Same as expr, but keep input variables and append results

aexprf Evaluate expression script and append results

Same as exprf, but keep input variables and append results

Parameter

instr STRING Processing instructions (need to be 'quoted' in most cases)

filename STRING File with processing instructions

Note

If the input stream contains duplicate entries of the same variable name then the last one is used.

Example

Assume an input dataset contains at least the variables 'aprl', 'aprc' and 'ts'. To create a new variable 'var1' with the sum of 'aprl' and 'aprc' and a variable 'var2' which convert the temperature 'ts' from Kelvin to Celsius use:

```
cdo expr,'var1=aprl+aprc;var2=ts-273.15;' infile outfile
```

The same example, but the instructions are read from a file:

```
cdo exprf,myexpr infile outfile
```

The file myexpr contains:

```
var1 = aprl + aprc;

var2 = ts - 273.15;
```

2.7.2. MATH - Mathematical functions


Synopsis

```
< operator > infile outfile
```

Description

This module contains some standard mathematical functions. All trigonometric functions calculate with radians.

Operators



Example

To calculate the square root for all field elements use:

cdo sqrt infile outfile

2.7.3. ARITHC - Arithmetic with a constant

Synopsis

< operator >, c infile outfile

Description

This module performs simple arithmetic with all field elements of a dataset and a constant. The fields in outfile inherit the meta data from infile.

Operators

 $\mathbf{addc} \qquad \mathrm{Add\ a\ constant}$

o(t,x) = i(t,x) + c

 ${\bf subc} \qquad {\bf Subtract\ a\ constant}$

o(t,x) = i(t,x) - c

mulc Multiply with a constant

o(t, x) = i(t, x) * c

divc Divide by a constant

o(t,x) = i(t,x)/c

minc Minimum of a field and a constant

 $o(t, x) = \min(i(t, x), c)$

maxc Maximum of a field and a constant

 $o(t, x) = \max(i(t, x), c)$

Parameter

c FLOAT Constant

Example

To sum all input fields with the constant -273.15 use:

cdo addc,-273.15 infile outfile

2.7.4. ARITH - Arithmetic on two datasets

Synopsis

```
< operator > infile1 infile2 outfile
```

Description

This module performs simple arithmetic of two datasets. The number of fields in infile1 should be the same as in infile2. The fields in outfile inherit the meta data from infile1. All operators in this module simply process one field after the other from the two input files. Neither the order of the variables nor the date is checked. One of the input files can contain only one timestep or one variable.

Operators

```
add
           Add two fields
           o(t,x) = i_1(t,x) + i_2(t,x)
sub
           Subtract two fields
           o(t,x) = i_1(t,x) - i_2(t,x)
mul
           Multiply two fields
           o(t,x) = i_1(t,x) * i_2(t,x)
div
           Divide two fields
           o(t,x) = i_1(t,x)/i_2(t,x)
           Minimum of two fields
min
           o(t,x) = \min(i_1(t,x), i_2(t,x))
           Maximum of two fields
max
           o(t, x) = \max(i_1(t, x), i_2(t, x))
atan2
           Arc tangent of two fields
           The atan2 operator calculates the arc tangent of two fields. The result is in radians, which
           is between -PI and PI (inclusive).
           o(t, x) = \text{atan2}(i_1(t, x), i_2(t, x))
```

Example

To sum all fields of the first input file with the corresponding fields of the second input file use:

cdo add infile1 infile2 outfile

2.7.5. DAYARITH - Daily arithmetic

Synopsis

<operator> infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same day, month and year. For each field in infile1 the corresponding field of the timestep in infile2 with the same day, month and year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module DAYSTAT.

Operators

dayadd Add daily time series

Adds a time series and a daily time series.

daysub Subtract daily time series

Subtracts a time series and a daily time series.

daymul Multiply daily time series

Multiplies a time series and a daily time series.

daydiv Divide daily time series

Divides a time series and a daily time series.

Example

To subtract a daily time average from a time series use:

cdo daysub infile -dayavg infile outfile

2.7.6. MONARITH - Monthly arithmetic

Synopsis

< operator > infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same month and year. For each field in infile1 the corresponding field of the timestep in infile2 with the same month and year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module MONSTAT.

Operators

monadd Add monthly time series

Adds a time series and a monthly time series.

monsub Subtract monthly time series

Subtracts a time series and a monthly time series.

monmul Multiply monthly time series

Multiplies a time series and a monthly time series.

mondiv Divide monthly time series

Divides a time series and a monthly time series.

Example

To subtract a monthly time average from a time series use:

cdo monsub infile -monavg infile outfile

2.7.7. YEARARITH - Yearly arithmetic

Synopsis

 $<\!operator\!>$ infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same year. For each field in infile1 the corresponding field of the timestep in infile2 with the same year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module YEARSTAT.

Operators

yearadd Add yearly time series

Adds a time series and a yearly time series.

yearsub Subtract yearly time series

Subtracts a time series and a yearly time series.

yearmul Multiply yearly time series

Multiplies a time series and a yearly time series.

yeardiv Divide yearly time series

Divides a time series and a yearly time series.

Example

To subtract a yearly time average from a time series use:

cdo yearsub infile -yearavg infile outfile

2.7.8. YHOURARITH - Multi-year hourly arithmetic

Synopsis

< operator > infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same hour and day of year. For each field in infile1 the corresponding field of the timestep in infile2 with the same hour and day of year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module YHOURSTAT.

Operators

yhouradd Add multi-year hourly time series

Adds a time series and a multi-year hourly time series.

yhoursub Subtract multi-year hourly time series

Subtracts a time series and a multi-year hourly time series.

yhourmul Multiply multi-year hourly time series

Multiplies a time series and a multi-year hourly time series.

yhourdiv Divide multi-year hourly time series

Divides a time series and a multi-year hourly time series.

Example

To subtract a multi-year hourly time average from a time series use:

cdo yhoursub infile -yhouravg infile outfile

2.7.9. YDAYARITH - Multi-year daily arithmetic

Synopsis

<operator> infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same day of year. For each field in infile1 the corresponding field of the timestep in infile2 with the same day of year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module YDAYSTAT.

Operators

ydayadd Add multi-year daily time series

Adds a time series and a multi-year daily time series.

ydaysub Subtract multi-year daily time series

Subtracts a time series and a multi-year daily time series.

ydaymul Multiply multi-year daily time series

Multiplies a time series and a multi-year daily time series.

ydaydiv Divide multi-year daily time series

Divides a time series and a multi-year daily time series.

Example

To subtract a multi-year daily time average from a time series use:

cdo ydaysub infile -ydayavg infile outfile

2.7.10. YMONARITH - Multi-year monthly arithmetic

Synopsis

< operator > infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same month of year. For each field in infile1 the corresponding field of the timestep in infile2 with the same month of year is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module YMONSTAT.

Operators

ymonadd Add multi-year monthly time series

Adds a time series and a multi-year monthly time series.

ymonsub Subtract multi-year monthly time series

Subtracts a time series and a multi-year monthly time series.

ymonmul Multiply multi-year monthly time series

Multiplies a time series and a multi-year monthly time series.

ymondiv Divide multi-year monthly time series

Divides a time series and a multi-year monthly time series.

Example

To subtract a multi-year monthly time average from a time series use:

cdo ymonsub infile -ymonavg infile outfile

2.7.11. YSEASARITH - Multi-year seasonal arithmetic

Synopsis

<operator> infile1 infile2 outfile

Description

This module performs simple arithmetic of a time series and one timestep with the same season. For each field in infile1 the corresponding field of the timestep in infile2 with the same season is used. The header information in infile1 have to be the same as in infile2. Usually infile2 is generated by an operator of the module YSEASSTAT.

Operators

yseasadd Add multi-year seasonal time series

Adds a time series and a multi-year seasonal time series.

yseassub Subtract multi-year seasonal time series

Subtracts a time series and a multi-year seasonal time series.

yseasmul Multiply multi-year seasonal time series

Multiplies a time series and a multi-year seasonal time series.

yseasdiv Divide multi-year seasonal time series

Divides a time series and a multi-year seasonal time series.

Example

To subtract a multi-year seasonal time average from a time series use:

cdo yseassub infile -yseasavg infile outfile

2.7.12. ARITHDAYS - Arithmetic with days

Synopsis

```
<\!operator\!> infile outfile
```

Description

This module multiplies or divides each timestep of a dataset with the corresponding days per month or days per year. The result of these functions depends on the used calendar of the input data.

Operators

muldpm Multiply with days per month

 $o(t,x) = i(t,x)*days_per_month$

divdpm Divide by days per month

 $o(t,x) = i(t,x)/days_per_month$

muldpy Multiply with days per year

 $o(t, x) = i(t, x) * days_per_year$

divdpy Divide by days per year

 $o(t, x) = i(t, x)/days_per_year$

2.7.13. ARITHLAT - Arithmetic with latitude

Synopsis

```
<\!operator\!> infile outfile
```

Description

This module multiplies or divides each field element with the cosine of the latitude.

Operators

mulcoslat Multiply with the cosine of the latitude

o(t,x) = i(t,x) * cos(latitude(x))

divcoslat Divide by cosine of the latitude

o(t, x) = i(t, x)/cos(latitude(x))

Statistical values Reference manual

2.8. Statistical values

This section contains modules to compute statistical values of datasets. In this program there is the different notion of "mean" and "average" to distinguish two different kinds of treatment of missing values. While computing the mean, only the not missing values are considered to belong to the sample with the side effect of a probably reduced sample size. Computing the average is just adding the sample members and divide the result by the sample size. For example, the mean of 1, 2, miss and 3 is (1+2+3)/3 = 2, whereas the average is (1+2+miss+3)/4 = miss/4 = miss. If there are no missing values in the sample, the average and the mean are identical.

CDO is using the verification time to identify the time range for temporal statistics. The time bounds are never used!

In this section the abbreviations as in the following table are used:

$$\begin{array}{lll} \mathbf{sum} & \sum_{i=1}^n x_i \\ \mathbf{mean} \ \mathrm{resp.} \ \mathbf{avg} & n^{-1} \sum_{i=1}^n x_i \\ \mathbf{mean} \ \mathrm{resp.} \ \mathbf{avg} & \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{i=1}^n w_i \, x_i \\ \mathbf{w}_i, i = 1, \dots, n \} & \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{i=1}^n w_i \, x_i \\ \mathbf{var} & \mathbf{var} & n^{-1} \sum_{i=1}^n (x_i - \overline{x})^2 \\ \mathbf{var} & \left(n - 1\right)^{-1} \sum_{i=1}^n (x_i - \overline{x})^2 \\ \mathbf{var} & \mathbf{weighted} \ \mathbf{by} \\ \left\{w_i, i = 1, \dots, n\right\} & \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{i=1}^n w_i \, \left(x_i - \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{j=1}^n w_j \, x_j\right)^2 \\ \mathbf{Standard} \ \mathbf{deviation} \\ \mathbf{std} & \sqrt{n^{-1} \sum_{i=1}^n (x_i - \overline{x})^2} \\ \mathbf{std} & \sqrt{(n-1)^{-1} \sum_{i=1}^n (x_i - \overline{x})^2} \\ \mathbf{std} & \mathbf{weighted} \ \mathbf{by} \\ \left\{w_i, i = 1, \dots, n\right\} & \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{i=1}^n w_i \, \left(x_i - \left(\sum_{j=1}^n w_j\right)^{-1} \sum_{j=1}^n w_j \, x_j\right)^2 \\ \mathbf{median} & \left\{\frac{x_{\frac{n+1}{2}}}{2} & \text{if n is odd} \\ \frac{1}{2} \left(x_{\frac{n}{2}} + x_{\frac{n}{2} + 1}\right) & \text{if n is even} \end{array}\right. \end{array}$$

Skewness $\frac{\sum_{i=1}^{n} (x_i - \overline{x})/n}{skew}$ s³

Kurtosis $\frac{\sum_{i=1}^{n} (x_i - \overline{x})^4 / n}{s^4}$ kurt

Cumulative Ranked Probability Score

 $\int_{-\infty}^{\infty} \left[H(x_1) - c df(\{x_2 \dots x_n\})|_r \right]^2 dr$

crps

with $cdf(X)|_r$ being the cumulative distribution function of $\{x_i, i=2\dots n\}$ at r

and H(x) the Heavyside function jumping at x.

Here is a short overview of all operators in this section:

timcumsum Cumulative sum over all timesteps

consecsumConsecutive SumconsectsConsecutive Timesteps

varsminVariables minimumvarsmaxVariables maximumvarsrangeVariables rangevarssumVariables sumvarsmeanVariables meanvarsavgVariables average

varsstd Variables standard deviation varsstd1 Variables standard deviation (n-1)

varsvar Variables variance varsvar1 Variables variance (n-1)

ensminEnsemble minimumensmaxEnsemble maximumensrangeEnsemble rangeenssumEnsemble sumensmeanEnsemble meanensavgEnsemble average

ensstd Ensemble standard deviation ensstd1 Ensemble standard deviation (n-1)

ensvarEnsemble varianceensvar1Ensemble variance (n-1)ensskewEnsemble skewnessenskurtEnsemble kurtosisensmedianEnsemble medianenspctlEnsemble percentiles

ensrkhistspaceRanked Histogram averaged over timeensrkhisttimeRanked Histogram averaged over spaceensrocEnsemble Receiver Operating characteristics

enscrps Ensemble CRPS and decomposition

ensbrs Ensemble Brier score

fldminField minimumfldmaxField maximumfldrangeField rangefldsumField sumfldintField integralfldmeanField meanfldavgField average

fldstd Field standard deviation fldstd1 Field standard deviation (n-1)

fldvarField variancefldvar1Field variance (n-1)fldskewField skewnessfldkurtField kurtosisfldmedianField medianfldpctlField percentiles

zonminZonal minimumzonmaxZonal maximumzonrangeZonal rangezonsumZonal sumzonmeanZonal meanzonavgZonal average

zonstdzonstd1Zonal standard deviation (n-1)

zonvarZonal variancezonvar1Zonal variance (n-1)zonskewZonal skewnesszonkurtZonal kurtosiszonmedianZonal medianzonpctlZonal percentiles

merminMeridional minimummermaxMeridional maximummerrangeMeridional rangemersumMeridional summermeanMeridional meanmeravgMeridional average

merstdMeridional standard deviationmerstd1Meridional standard deviation (n-1)

mervarMeridional variancemervar1Meridional variance (n-1)merskewMeridional skewnessmerkurtMeridional kurtosismermedianMeridional medianmerpctlMeridional percentiles

gridboxminGridbox minimumgridboxmaxGridbox maximumgridboxrangeGridbox rangegridboxsumGridbox sumgridboxmeanGridbox meangridboxavgGridbox average

gridboxstd Gridbox standard deviation gridboxstd1 Gridbox standard deviation (n-1)

gridboxvarGridbox variancegridboxvar1Gridbox variance (n-1)gridboxskewGridbox skewnessgridboxkurtGridbox kurtosisgridboxmedianGridbox median

remapminRemap minimumremapmaxRemap maximumremaprangeRemap rangeremapsumRemap sumremapmeanRemap meanremapavgRemap average

remapstdRemap standard deviationremapstd1Remap standard deviation (n-1)

remapvarRemap varianceremapvar1Remap variance (n-1)remapskewRemap skewnessremapkurtRemap kurtosisremapmedianRemap median

vertminVertical minimumvertmaxVertical maximumvertrangeVertical rangevertsumVertical sumvertmeanVertical meanvertavgVertical average

vertstdVertical standard deviationvertstd1Vertical standard deviation (n-1)

vertvarVertical variancevertvar1Vertical variance (n-1)

timselminTime selection minimumtimselmaxTime selection maximumtimselrangeTime selection rangetimselsumTime selection sumtimselmeanTime selection meantimselavgTime selection average

timselstd Time selection standard deviation timselstd1 Time selection standard deviation (n-1)

timselvar Time selection variance timselvar1 Time selection variance (n-1)

timselpctl Time range percentiles

runminRunning minimumrunmaxRunning maximumrunrangeRunning rangerunsumRunning sumrunmeanRunning meanrunavgRunning average

runstd Running standard deviation runstd1 Running standard deviation (n-1)

runvar Running variance runvar1 Running variance (n-1)

runpctl Running percentiles

timminTime minimumtimmaxTime maximumtimrangeTime rangetimsumTime sumtimmeanTime meantimavgTime average

timstd Time standard deviation timstd1 Time standard deviation (n-1)

timvar Time variance timvar1 Time variance (n-1)

timpctl Time percentiles

hourminHourly minimumhourmaxHourly maximumhourrangeHourly rangehoursumHourly sumhourmeanHourly meanhouravgHourly average

hourstd Hourly standard deviation hourstd1 Hourly standard deviation (n-1)

hourvarhourly varianceHourly variance (n-1)

hourpctl Hourly percentiles

dayminDaily minimumdaymaxDaily maximumdayrangeDaily rangedaysumDaily sumdaymeanDaily meandayavgDaily average

daystdDaily standard deviationdaystd1Daily standard deviation (n-1)

dayvarDaily variancedayvar1Daily variance (n-1)

daypctl Daily percentiles

monminMonthly minimummonmaxMonthly maximummonrangeMonthly rangemonsumMonthly summonmeanMonthly meanmonavgMonthly average

monstdMonthly standard deviationmonstd1Monthly standard deviation (n-1)

monvar Monthly variance monvar1 Monthly variance (n-1)

monpctl Monthly percentiles

yearmonmean Yearly mean from monthly data

yearmin Yearly minimum yearmax Yearly maximum

yearminidx Yearly minimum indices yearmaxidx Yearly maximum indices

yearrangeYearly rangeyearsumYearly sumyearmeanYearly meanyearavgYearly average

yearstd Yearly standard deviation yearstd1 Yearly standard deviation (n-1)

yearvar Yearly variance yearvar1 Yearly variance (n-1)

yearpctl Yearly percentiles

seasminSeasonal minimumseasmaxSeasonal maximumseasrangeSeasonal rangeseassumSeasonal sumseasmeanSeasonal meanseasavgSeasonal average

seasstdSeasonal standard deviationseasstd1Seasonal standard deviation (n-1)

seasvarSeasonal varianceseasvar1Seasonal variance (n-1)

seaspctl Seasonal percentiles

yhourmin
yhourmax
Multi-year hourly minimum
Multi-year hourly maximum
yhourrange
yhoursum
yhourmean
yhouravg
Multi-year hourly sum
Multi-year hourly mean
yhouravg
Multi-year hourly average

yhourstd Multi-year hourly standard deviation yhourstd1 Multi-year hourly standard deviation (n-1)

yhourvar Multi-year hourly variance yhourvar1 Multi-year hourly variance (n-1)

dhourminMulti-day hourly minimumdhourmaxMulti-day hourly maximumdhourrangeMulti-day hourly rangedhoursumMulti-day hourly sumdhourmeanMulti-day hourly meandhouravgMulti-day hourly average

dhourstd Multi-day hourly standard deviation
dhourstd1 Multi-day hourly standard deviation (n-1)

dhourvardhourvar1Multi-day hourly variance (n-1)

ydaymin Multi-year daily minimum
ydaymax Multi-year daily maximum
ydayrange Multi-year daily range
ydaysum Multi-year daily sum
ydaymean Multi-year daily mean
ydayavg Multi-year daily average

ydaystd Multi-year daily standard deviation ydaystd1 Multi-year daily standard deviation (n-1)

ydayvar Multi-year daily variance ydayvar1 Multi-year daily variance (n-1)

ydaypctl Multi-year daily percentiles

ymonminMulti-year monthly minimumymonmaxMulti-year monthly maximumymonrangeMulti-year monthly rangeymonsumMulti-year monthly sumymonmeanMulti-year monthly meanymonavgMulti-year monthly average

ymonstd Multi-year monthly standard deviation ymonstd1 Multi-year monthly standard deviation (n-1)

ymonvar Multi-year monthly variance ymonvar1 Multi-year monthly variance (n-1)

ymonpctl Multi-year monthly percentiles

yseasminMulti-year seasonal minimumyseasmaxMulti-year seasonal maximumyseasrangeMulti-year seasonal rangeyseassumMulti-year seasonal sumyseasmeanMulti-year seasonal meanyseasavgMulti-year seasonal average

yseasstd Multi-year seasonal standard deviation yseasstd1 Multi-year seasonal standard deviation (n-1)

yseasvar Multi-year seasonal variance yseasvar1 Multi-year seasonal variance (n-1)

yseaspctl Multi-year seasonal percentiles

| ydrunmin | Multi-year daily running minimum |
|-----------|----------------------------------|
| ydrunmax | Multi-year daily running maximum |
| ydrunsum | Multi-year daily running sum |
| ydrunmean | Multi-year daily running mean |
| ydrunavg | Multi-year daily running average |

ydrunstd Multi-year daily running standard deviation ydrunstd1 Multi-year daily running standard deviation (n-1)

ydrunvar Multi-year daily running variance ydrunvar1 Multi-year daily running variance (n-1)

ydrunpctl Multi-year daily running percentiles

2.8.1. TIMCUMSUM - Cumulative sum over all timesteps

Synopsis

timcumsum infile outfile

Description

The timcumsum operator calculates the cumulative sum over all timesteps. Missing values are treated as numeric zero when summing.

```
o(t, x) = \mathbf{sum}\{i(t', x), 0 < t' \le t\}
```

2.8.2. CONSECSTAT - Consecute timestep periods

Synopsis

<operator> infile outfile

Description

This module computes periods over all timesteps in infile where a certain property is valid. The property can be chosen by creating a mask from the original data, which is the expected input format for operators of this module. Depending on the operator full information about each period or just its length and ending date are computed.

Operators

consecsum Consecutive Sum

This operator computes periods of consecutive timesteps similar to a runsum, but periods are finished, when the mask value is 0. That way multiple periods can be found. Timesteps from the input are preserved. Missing values are handled like 0, i.e. finish periods of consecutive timesteps.

consects Consecutive Timesteps

In contrast to the operator above consects only computes the length of each period together with its last timestep. To be able to perform statistical analysis like min, max or mean, everything else is set to missing value.

Example

For a given time series of daily temperatures, the periods of summer days can be calculated with inplace maskting the input field:

cdo consects -gtc,20.0 infile1 outfile

2.8.3. VARSSTAT - Statistical values over all variables

Synopsis

< operator > infile outfile

Description

This module computes statistical values over all variables for each timestep. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation is written to outfile. All input variables need to have the same gridsize and the same number of levels.

Operators

varsmin Variables minimum

For every timestep the minimum over all variables is computed.

varsmax Variables maximum

For every timestep the maximum over all variables is computed.

varsrange Variables range

For every timestep the range over all variables is computed.

varssum Variables sum

For every timestep the sum over all variables is computed.

varsmean Variables mean

For every timestep the mean over all variables is computed.

varsavg Variables average

For every timestep the average over all variables is computed.

varsstd Variables standard deviation

For every timestep the standard deviation over all variables is computed. Normalize

by n.

varsstd1 Variables standard deviation (n-1)

For every timestep the standard deviation over all variables is computed. Normalize

by (n-1).

varsvar Variables variance

For every timestep the variance over all variables is computed. Normalize by n.

varsvar1 Variables variance (n-1)

For every timestep the variance over all variables is computed. Normalize by (n-1).

2.8.4. ENSSTAT - Statistical values over an ensemble

Synopsis

```
<operator> infiles outfile
enspctl,p infiles outfile
```

Description

This module computes statistical values over an ensemble of input files. Depending on the chosen operator, the minimum, maximum, range, sum, average, standard deviation, variance, skewness, kurtosis, median or a certain percentile over all input files is written to outfile. All input files need to have the same structure with the same variables. The date information of a timestep in outfile is the date of the first input file.

Operators

| ensmin | Ensemble minimum $o(t,x) = \min\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
|----------------|--|
| ensmax | Ensemble maximum $o(t,x) = \max\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| ensrange | Ensemble range $o(t,x) = \mathbf{range}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| enssum | Ensemble sum $o(t,x) = \mathbf{sum}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| ensmean | Ensemble mean $o(t,x) = \mathbf{mean}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| ensavg | Ensemble average $o(t, x) = \mathbf{avg}\{i_1(t, x), i_2(t, x), \dots, i_n(t, x)\}$ |
| ensstd | Ensemble standard deviation Normalize by n. |
| | $o(t,x) = \mathbf{std}\{i_1(t,x), i_2(t,x), \cdots, i_n(t,x)\}$ |
| ${ m ensstd1}$ | Ensemble standard deviation (n-1) Normalize by (n-1). |
| | $o(t,x) = \mathbf{std1}\{i_1(t,x), i_2(t,x), \cdots, i_n(t,x)\}$ |
| ensvar | Ensemble variance Normalize by n. |
| | $o(t,x) = \mathbf{var}\{i_1(t,x), i_2(t,x), \cdots, i_n(t,x)\}$ |
| ensvar1 | Ensemble variance (n-1) Normalize by (n-1). |
| | $o(t,x) = \mathbf{var1}\{i_1(t,x), i_2(t,x), \cdots, i_n(t,x)\}$ |
| ensskew | Ensemble skewness $o(t,x) = \mathbf{skew}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| enskurt | Ensemble kurtosis $o(t,x) = \mathbf{kurt}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| ensmedian | Ensemble median $o(t,x) = \mathbf{median}\{i_1(t,x), i_2(t,x), \dots, i_n(t,x)\}$ |
| enspctl | Ensemble percentiles $o(t,x) = \mathbf{pth} \ \mathbf{percentile}\{i_1(t,x), i_2(t,x), \cdots, i_n(t,x)\}$ |

Parameter

p FLOAT Percentile number in 0, ..., 100

Note

Operators of this module need to open all input files simultaneously. The maximum number of open files depends on the operating system!

Example

To compute the ensemble mean over 6 input files use:

```
cdo ensmean infile1 infile2 infile3 infile4 infile5 infile6 outfile
```

Or shorter with filename substitution:

```
cdo ensmean infile[1-6] outfile
```

To compute the 50th percentile (median) over 6 input files use:

cdo enspct1,50 infile1 infile2 infile3 infile4 infile5 infile6 outfile

2.8.5. ENSSTAT2 - Statistical values over an ensemble

Synopsis

<operator> obsfile ensfiles outfile

Description

This module computes statistical values over the ensemble of ensfiles using obsfile as a reference. Depending on the operator a ranked Histogram or a roc-curve over all Ensembles ensfiles with reference to obsfile is written to outfile. The date and grid information of a timestep in outfile is the date of the first input file. Thus all input files are required to have the same structure in terms of the gridsize, variable definitions and number of timesteps.

All Operators in this module use obsfile as the reference (for instance an observation) whereas ensfiles are understood as an ensemble consisting of n (where n is the number of ensfiles) members.

The operators ensightstspace and ensightstime compute Ranked Histograms. Therefor the vertical axis is utilized as the Histogram axis, which prohibits the use of files containing more than one level. The histogram axis has nensfiles+1 bins with level 0 containing for each grid point the number of observations being smaller as all ensembles and level nensfiles+1 indicating the number of observations being larger than all ensembles.

ensrkhistspace computes a ranked histogram at each timestep reducing each horizontal grid to a 1x1 grid and keeping the time axis as in obsfile. Contrary ensrkhistspace computes a histogram at each grid point keeping the horizontal grid for each variable and reducing the time-axis. The time information is that from the last timestep in obsfile.

Operators

ensrkhistspace Ranked Histogram averaged over time

ensrkhisttime Ranked Histogram averaged over space

ensroc Ensemble Receiver Operating characteristics

Example

To compute a rank histogram over 5 input files ensfile1-ensfile5 given an observation in obsfile

cdo ensrkhisttime obsfile ensfile1 ensfile2 ensfile3 ensfile4 ensfile5 outfile

Or shorter with filename substitution:

cdo ensrkhisttime obsfile ensfile[1-5] outfile

2.8.6. ENSVAL - Ensemble validation tools

Synopsis

```
enscrps rfile infiles outfilebase
ensbrs,x rfile infiles outfilebase
```

Description

This module computes ensemble validation scores and their decomposition such as the Brier and cumulative ranked probability score (CRPS). The first file is used as a reference it can be a climatology, observation or reanalysis against which the skill of the ensembles given in infiles is measured. Depending on the operator a number of output files is generated each containing the skill score and its decomposition corresponding to the operator. The output is averaged over horizontal fields using appropriate weights for each level and timestep in rfile.

All input files need to have the same structure with the same variables. The date information of a timestep in outfile is the date of the first input file. The output files are named as <outfilebase>.<type>.<fileswhere <type> depends on the operator and <filesuffix> is determined from the output file type. There are three output files for operator enscrps and four output files for operator ensbrs.

The CRPS and its decomposition into Reliability and the potential CRPS are calculated by an appropriate averaging over the field members (note, that the CRPS does *not* average linearly). In the three output files $\langle \text{type} \rangle$ has the following meaning: crps for the CRPS, reli for the reliability and crpspot for the potential crps. The relation $CRPS = CRPS_{pot} + RELI$

holds.

The Brier score of the Ensemble given by infiles with respect to the reference given in rfile and the threshold x is calculated. In the four output files $\langle \text{type} \rangle$ has the following meaning: brs for the Brier score wrt threshold x; brsreli for the Brier score reliability wrt threshold x; brsreso for the Brier score resolution wrt threshold x; brsunct for the Brier score uncertainty wrt threshold x. In analogy to the CRPS the following relation holds: BRS(x) = RELI(x) - RESO(x) + UNCT(x).

The implementation of the decomposition of the CRPS and Brier Score follows Hans Hersbach (2000): Decomposition of the Continuous Ranked Probability Score for Ensemble Prediction Systems, in: Weather and Forecasting (15) pp. 559-570.

The CRPS code decomposition has been verified against the CRAN - ensemble validation package from R. Differences occur when grid-cell area is not uniform as the implementation in R does not account for that.

Operators

enscrps Ensemble CRPS and decomposition

ensbrs Ensemble Brier score

Ensemble Brier Score and Decomposition

Example

To compute the field averaged Brier score at x=5 over an ensemble with 5 members ensfile1-5 w.r.t. the reference rfile and write the results to files obase.brs.<suff>, obase.brsreli<suff>, obase.brsreso<suff>, obase.brsunct<suff> where <suff> is determined from the output file type, use

cdo ensbrs,5 rfile ensfile1 ensfile2 ensfile3 ensfile4 ensfile5 obase

or shorter using file name substitution:

cdo ensbrs,5 rfile ensfile[1-5] obase

2.8.7. FLDSTAT - Statistical values over a field

Synopsis

< operator >, weights infile outfile

fldpctl, p infile outfile

Description

This module computes statistical values of all input fields. A field is a horizontal layer of a data variable. Depending on the chosen operator, the minimum, maximum, range, sum, integral, average, standard deviation, variance, skewness, kurtosis, median or a certain percentile of the field is written to outfile.

Operators

fldmin Field minimum

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \min\{i(t,x'), x_1 < x' \le x_n\}$

fldmax Field maximum

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \max\{i(t,x'), x_1 < x' \le x_n\}$

fldrange Field range

For every gridpoint x = 1, ..., x = n of the same field it is:

 $o(t,1) = \mathbf{range}\{i(t,x'), x_1 < x' \le x_n\}$

fldsum Field sum

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{sum}\{i(t,x'), x_1 < x' \le x_n\}$

fldint Field integral

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{sum}\{i(t,x') * cellarea(x'), x_1 < x' \le x_n\}$

fldmean Field mean

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{mean}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldavg Field average

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{avg}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldstd Field standard deviation

Normalize by n. For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{std}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldstd1 Field standard deviation (n-1)

Normalize by (n-1). For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{std1}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldvar Field variance

Normalize by n. For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{var}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldvar1 Field variance (n-1)

Normalize by (n-1). For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{var1}\{i(t,x'), x_1 < x' \le x_n\}$

weighted by area weights obtained by the input field.

fldskew Field skewness

For every gridpoint x = 1, ..., x = n of the same field it is:

 $o(t, 1) = \mathbf{skew}\{i(t, x'), x_1 < x' \le x_n\}$

fldkurt Field kurtosis

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{kurt}\{i(t,x'), x_1 < x' \le x_n\}$

fldmedian Field median

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t, 1) = \mathbf{median}\{i(t, x'), x_1 < x' \le x_n\}$

fldpctl Field percentiles

For every gridpoint $x_1, ..., x_n$ of the same field it is:

 $o(t,1) = \mathbf{pth} \ \mathbf{percentile}\{i(t,x'), x_1 < x' \le x_n\}$

Parameter

weights BOOL weights=FALSE disables weighting by grid cell area [default: weights=TRUE]

p FLOAT Percentile number in 0, ..., 100

Example

To compute the field mean of all input fields use:

cdo fldmean infile outfile

To compute the 90th percentile of all input fields use:

cdo fldpctl,90 infile outfile

2.8.8. ZONSTAT - Zonal statistical values

Synopsis

```
<operator> infile outfile
zonmean[,zonaldes] infile outfile
zonpctl,p infile outfile
```

Description

This module computes zonal statistical values of the input fields. Depending on the chosen operator, the zonal minimum, maximum, range, sum, average, standard deviation, variance, skewness, kurtosis, median or a certain percentile of the field is written to outfile. Operators of this module require all variables on the same regular lon/lat grid. Only the zonal mean (zonmean) can be calculated for data on an unstructured grid if the latitude bins are defined with the optional parameter zonaldes.

Operators

zonmin Zonal minimum

For every latitude the minimum over all longitudes is computed.

zonmax Zonal maximum

For every latitude the maximum over all longitudes is computed.

zonrange Zonal range

For every latitude the range over all longitudes is computed.

zonsum Zonal sum

For every latitude the sum over all longitudes is computed.

zonmean Zonal mean

For every latitude the mean over all longitudes is computed. Use the optional pa-

rameter zonaldes for data on an unstructured grid.

zonavg Zonal average

For every latitude the average over all longitudes is computed.

zonstd Zonal standard deviation

For every latitude the standard deviation over all longitudes is computed. Normalize

by n.

zonstd1 Zonal standard deviation (n-1)

For every latitude the standard deviation over all longitudes is computed. Normalize

by (n-1).

zonvar Zonal variance

For every latitude the variance over all longitudes is computed. Normalize by n.

zonvar1 Zonal variance (n-1)

For every latitude the variance over all longitudes is computed. Normalize by (n-1).

zonskew Zonal skewness

For every latitude the skewness over all longitudes is computed.

zonkurt Zonal kurtosis

For every latitude the kurtosis over all longitudes is computed.

zonmedian Zonal median

For every latitude the median over all longitudes is computed.

zonpctl Zonal percentiles

For every latitude the pth percentile over all longitudes is computed.

Parameter

p FLOAT Percentile number in 0, ..., 100

zonaldes STRING Description of the zonal latitude bins needed for data on an unstructured

grid. A predefined zonal description is zonal_<DY>. DY is the increment of the lati-

tudes in degrees.

Example

To compute the zonal mean of all input fields use:

cdo zonmean infile outfile

To compute the 50th meridional percentile (median) of all input fields use:

cdo zonpctl,50 infile outfile

2.8.9. MERSTAT - Meridional statistical values

Synopsis

<operator> infile outfile
merpctl,p infile outfile

Description

This module computes meridional statistical values of the input fields. Depending on the chosen operator, the meridional minimum, maximum, range, sum, average, standard deviation, variance, skewness, kurtosis, median or a certain percentile of the field is written to outfile. Operators of this module require all variables on the same regular lon/lat grid.

Operators

mermin Meridional minimum

For every longitude the minimum over all latitudes is computed.

mermax Meridional maximum

For every longitude the maximum over all latitudes is computed.

merrange Meridional range

For every longitude the range over all latitudes is computed.

mersum Meridional sum

For every longitude the sum over all latitudes is computed.

mermean Meridional mean

For every longitude the area weighted mean over all latitudes is computed.

meravg Meridional average

For every longitude the area weighted average over all latitudes is computed.

merstd Meridional standard deviation

For every longitude the standard deviation over all latitudes is computed. Normalize

by n.

merstd1 Meridional standard deviation (n-1)

For every longitude the standard deviation over all latitudes is computed. Normalize

by (n-1).

mervar Meridional variance

For every longitude the variance over all latitudes is computed. Normalize by n.

mervar1 Meridional variance (n-1)

For every longitude the variance over all latitudes is computed. Normalize by (n-1).

merskew Meridional skewness

For every longitude the skewness over all latitudes is computed.

merkurt Meridional kurtosis

For every longitude the kurtosis over all latitudes is computed.

mermedian Meridional median

For every longitude the median over all latitudes is computed.

merpctl Meridional percentiles

For every longitude the pth percentile over all latitudes is computed.

Parameter

p FLOAT Percentile number in 0, ..., 100

Example

To compute the meridional mean of all input fields use:

cdo mermean infile outfile

To compute the 50th meridional percentile (median) of all input fields use:

cdo merpctl,50 infile outfile

2.8.10. GRIDBOXSTAT - Statistical values over grid boxes

Synopsis

 $<\!operator\!>,\!nx,\!ny$ infile outfile

Description

This module computes statistical values over surrounding grid boxes. Depending on the chosen operator, the minimum, maximum, range, sum, average, standard deviation, variance, skewness, kurtosis or median of the neighboring grid boxes is written to outfile. All gridbox operators only work on quadrilateral curvilinear grids.

Operators

gridboxmin Gridbox minimum

Minimum value of the selected grid boxes.

gridboxmax Gridbox maximum

Maximum value of the selected grid boxes.

gridboxrange Gridbox range

Range (max-min value) of the selected grid boxes.

gridboxsum Gridbox sum

Sum of the selected grid boxes.

gridboxmean Gridbox mean

Mean of the selected grid boxes.

gridboxavg Gridbox average

Average of the selected grid boxes.

gridboxstd Gridbox standard deviation

Standard deviation of the selected grid boxes. Normalize by n.

gridboxstd1 Gridbox standard deviation (n-1)

Standard deviation of the selected grid boxes. Normalize by (n-1).

gridboxvar Gridbox variance

Variance of the selected grid boxes. Normalize by n.

gridboxvar1 Gridbox variance (n-1)

Variance of the selected grid boxes. Normalize by (n-1).

gridboxskew Gridbox skewness

Skewness of the selected grid boxes.

gridboxkurt Gridbox kurtosis

Kurtosis of the selected grid boxes.

gridboxmedian Gridbox median

Median of the selected grid boxes.

Parameter

nx INTEGER Number of grid boxes in x directionny INTEGER Number of grid boxes in y direction

Example

To compute the mean over 10x10 grid boxes of the input field use:

cdo gridboxmean, 10, 10 infile outfile

2.8.11. REMAPSTAT - Remaps source points to target cells

Synopsis

< operator >, grid infile outfile

Description

This module maps source points to target cells by calculating a statistical value from the source points. Each target cell contains the statistical value from all source points within that target cell. If there are no source points within a target cell, it gets a missing value. The target grid must be regular lon/lat or Gaussian. Depending on the chosen operator the minimum, maximum, range, sum, average, variance, standard deviation, skewness, kurtosis or median of source points is computed.

Operators

remapmin Remap minimum

Minimum value of the source points.

remapmax Remap maximum

Maximum value of the source points.

remaprange Remap range

Range (max-min value) of the source points.

remapsum Remap sum

Sum of the source points.

remapmean Remap mean

Mean of the source points.

remapavg Remap average

Average of the source points.

remapstd Remap standard deviation

Standard deviation of the source points. Normalize by n.

remapstd1 Remap standard deviation (n-1)

Standard deviation of the source points. Normalize by (n-1).

remapvar Remap variance

Variance of the source points. Normalize by n.

remapvar1 Remap variance (n-1)

Variance of the source points. Normalize by (n-1).

remapskew Remap skewness

Skewness of the source points.

remapkurt Remap kurtosis

Kurtosis of the source points.

remapmedian Remap median

Median of the source points.

Parameter

grid STRING Target grid description file or name

Example

To compute the mean over source points within the taget cells, use:

```
cdo remapmean, <targetgrid> infile outfile
```

If some of the target cells contain missing values, use the Operator setmisstonn to fill these missing values with the nearest neighbor cell:

cdo setmisstonn -remapmean,<targetgrid> infile outfile

2.8.12. VERTSTAT - Vertical statistical values

Synopsis

<operator>,weights infile outfile

Description

This module computes statistical values over all levels of the input variables. According to chosen operator the vertical minimum, maximum, range, sum, average, variance or standard deviation is written to outfile.

Operators

vertmin Vertical minimum

For every gridpoint the minimum over all levels is computed.

vertmax Vertical maximum

For every gridpoint the maximum over all levels is computed.

vertrange Vertical range

For every gridpoint the range over all levels is computed.

vertsum Vertical sum

For every gridpoint the sum over all levels is computed.

vertmean Vertical mean

For every gridpoint the layer weighted mean over all levels is computed.

vertavg Vertical average

For every gridpoint the layer weighted average over all levels is computed.

vertstd Vertical standard deviation

For every gridpoint the standard deviation over all levels is computed. Normalize by

n.

vertstd1 Vertical standard deviation (n-1)

For every gridpoint the standard deviation over all levels is computed. Normalize by

(n-1).

vertvar Vertical variance

For every gridpoint the variance over all levels is computed. Normalize by n.

vertvar1 Vertical variance (n-1)

For every gridpoint the variance over all levels is computed. Normalize by (n-1).

Parameter

weights BOOL weights=FALSE disables weighting by layer thickness [default: weights=TRUE]

Example

To compute the vertical sum of all input variables use:

cdo vertsum infile outfile

2.8.13. TIMSELSTAT - Time range statistical values

Synopsis

< operator > , nsets[, noffset[, nskip]] infile outfile

Description

This module computes statistical values for a selected number of timesteps. According to the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of the selected timesteps is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

timselmin Time selection minimum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same selected time

range it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

timselmax Time selection maximum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same selected time

range it is:

 $o(t, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

timselrange Time selection range

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same selected time

range it is:

 $o(t, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

timselsum Time selection sum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same selected time

range it is:

 $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \le t_n\}$

timselmean Time selection mean

For every adjacent sequence t = 1, ..., t = n of timesteps of the same selected time

range it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

timselavg Time selection average

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same selected time

range it is:

 $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \le t_n\}$

timselstd Time selection standard deviation

Normalize by n. For every adjacent sequence t=1,...,t=n of timesteps of the same

selected time range it is:

 $o(t,x) = \mathbf{std}\{i(t',x), t_1 < t' \le t_n\}$

timselstd1 Time selection standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the

same selected time range it is: $c(t, x) = \operatorname{std1}(i(t', x), t, < t' < t)$

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

timselvar Time selection variance

Normalize by n. For every adjacent sequence t = 1, ..., t = n of timesteps of the same

selected time range it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

| timselvar1 Time | selection | variance | (n-1) |) |
|-----------------|-----------|----------|-------|---|
|-----------------|-----------|----------|-------|---|

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same selected time range it is:

$$o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$$

Parameter

| nsets | INTEGER | Number of input timesteps for each output timestep |
|---------|---------|---|
| noffset | INTEGER | Number of input timesteps skipped before the first timestep range (optional) $$ |
| nskip | INTEGER | Number of input timesteps skipped between timestep ranges (optional) |

Example

Assume an input dataset has monthly means over several years. To compute seasonal means from monthly means the first two month have to be skipped:

```
cdo timselmean, 3, 2 infile outfile
```

2.8.14. TIMSELPCTL - Time range percentile values

Synopsis

```
timselpctl,p,nsets[,noffset[,nskip]] infile1 infile2 infile3 outfile
```

Description

This operator computes percentile values over a selected number of timesteps in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The files infile2 and infile3 should be the result of corresponding timeselmin and timeselmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the **CDO** option --timestat_date <first|middle|last>.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same selected time range it is:

```
o(t, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t', x), t_1 < t' \le t_n\}
```

Parameter

| p | FLOAT | Percentile number in 0,, 100 |
|---------|---------|---|
| nsets | INTEGER | Number of input timesteps for each output timestep |
| noffset | INTEGER | Number of input timesteps skipped before the first timestep range (optional) $$ |
| nskip | INTEGER | Number of input timesteps skipped between timestep ranges (optional) |

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

2.8.15. RUNSTAT - Running statistical values

Synopsis

< operator >, nts infile outfile

Description

This module computes running statistical values over a selected number of timesteps. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of a selected number of consecutive timesteps read from infile is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

| runmin | Running minimum $o(t+(nts-1)/2,x)=\min\{i(t,x),i(t+1,x),,i(t+nts-1,x)\}$ |
|--------------------------|--|
| runmax | Running maximum $o(t + (nts - 1)/2, x) = \max\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runrange | Running range $o(t+(nts-1)/2,x) = \mathbf{range}\{i(t,x),i(t+1,x),,i(t+nts-1,x)\}$ |
| runsum | Running sum $o(t + (nts - 1)/2, x) = \mathbf{sum}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runmean | Running mean $o(t + (nts - 1)/2, x) = \mathbf{mean}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runavg | Running average $o(t + (nts - 1)/2, x) = \mathbf{avg}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runstd | Running standard deviation Normalize by n. |
| | $o(t + (nts - 1)/2, x) = \mathbf{std}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| $\operatorname{runstd1}$ | Running standard deviation (n-1) Normalize by (n-1). |
| | $o(t + (nts - 1)/2, x) = \mathbf{std1}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runvar | Running variance Normalize by n. |
| | $o(t + (nts - 1)/2, x) = \mathbf{var}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |
| runvar1 | Running variance (n-1) Normalize by (n-1). |
| | $o(t + (nts - 1)/2, x) = \mathbf{var1}\{i(t, x), i(t + 1, x),, i(t + nts - 1, x)\}$ |

Parameter

nts INTEGER Number of timesteps

Environment

CDO_TIMESTAT_DATE Sets the time stamp in outfile to the "first", "middle" or "last" contributing timestep of infile.

Example

To compute the running mean over 9 timesteps use:

```
cdo runmean,9 infile outfile
```

2.8.16. RUNPCTL - Running percentile values

Synopsis

```
runpctl,p,nts infile outfile
```

Description

This module computes running percentiles over a selected number of timesteps in infile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

```
o(t + (nts - 1)/2, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), i(t + 1, x), ..., i(t + nts - 1, x)\}
```

Parameter

p FLOAT Percentile number in 0, ..., 100

nts INTEGER Number of timesteps

Example

To compute the running 50th percentile (median) over 9 timesteps use:

cdo runpctl,50,9 infile outfile

2.8.17. TIMSTAT - Statistical values over all timesteps

Synopsis

<operator> infile outfile

Description

This module computes statistical values over all timesteps in infile. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of all timesteps read from infile is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

timmin Time minimum

 $o(1, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

timmax Time maximum

 $o(1, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

timrange Time range

 $o(1, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

timsum Time sum

 $o(1,x) = \mathbf{sum}\{i(t',x), t_1 < t' \le t_n\}$

timmean Time mean

 $o(1, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

timavg Time average

 $o(1, x) = \mathbf{avg}\{i(t', x), t_1 < t' \le t_n\}$

timstd Time standard deviation

Normalize by n.

 $o(1, x) = \mathbf{std}\{i(t', x), t_1 < t' \le t_n\}$

timstd1 Time standard deviation (n-1)

Normalize by (n-1).

 $o(1, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

timvar Time variance

Normalize by n.

 $o(1,x) = \mathbf{var}\{i(t',x), t_1 < t' \le t_n\}$

timvar1 Time variance (n-1)

Normalize by (n-1).

 $o(1, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$

Example

To compute the mean over all input timesteps use:

cdo timmean infile outfile

2.8.18. TIMPCTL - Percentile values over all timesteps

Synopsis

```
timpctl,p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding timmin and timmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the **CDO** option --timestat_date <first|middle|last>.

```
o(1,x) = \mathbf{pth} \ \mathbf{percentile}\{i(t',x), t_1 < t' \le t_n\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

CDO PCTL NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the 90th percentile over all input timesteps use:

```
cdo timmin infile minfile
cdo timmax infile maxfile
cdo timpctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo timpctl,90 infile -timmin infile -timmax infile outfile
```

2.8.19. HOURSTAT - Hourly statistical values

Synopsis

< operator > infile outfile

Description

This module computes statistical values over timesteps of the same hour. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of timesteps of the same hour is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

hourmin Hourly minimum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

hourmax Hourly maximum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

 $o(t, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

hourrange Hourly range

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same hour it is:

 $o(t, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

hoursum Hourly sum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

 $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \le t_n\}$

hourmean Hourly mean

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

houravg Hourly average

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

 $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \le t_n\}$

hourstd Hourly standard deviation

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

hour it is:

 $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \le t_n\}$

hourstd1 Hourly standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

hour it is:

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

hourvar Hourly variance

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

hour it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

hourvar1 Hourly variance (n-1)

Normalize by (n-1). For every adjacent sequence t=1,...,t=n of timesteps of the same

hour it is:

 $o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$

Example

To compute the hourly mean of a time series use:

```
cdo hourmean infile outfile
```

2.8.20. HOURPCTL - Hourly percentile values

Synopsis

```
hourpctl,p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps of the same hour in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding hourmin and hourmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the **CDO** option --timestat date <first|middle|last>.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same hour it is:

```
o(t, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t', x), t_1 < t' \le t_n\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the hourly 90th percentile of a time series use:

```
cdo hourmin infile minfile
cdo hourmax infile maxfile
cdo hourpctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo hourpctl,90 infile -hourmin infile -hourmax infile outfile
```

2.8.21. DAYSTAT - Daily statistical values

Synopsis

< operator > infile outfile

Description

This module computes statistical values over timesteps of the same day. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of timesteps of the same day is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

daymin Daily minimum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

daymax Daily maximum

For every adjacent sequence $t_1,...,t_n$ of time steps of the same day it is:

 $o(t,x) = \max\{i(t',x), t_1 < t' \le t_n\}$

dayrange Daily range

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same day it is:

 $o(t, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

daysum Daily sum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day it is:

 $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \le t_n\}$

daymean Daily mean

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

dayavg Daily average

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day it is:

 $o(t,x) = \mathbf{avg}\{i(t',x), t_1 < t' \le t_n\}$

daystd Daily standard deviation

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day

it is:

 $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \le t_n\}$

daystd1 Daily standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1,...,t_n$ of timesteps of the same

day it is:

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

dayvar Daily variance

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day

it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

dayvar1 Daily variance (n-1)

Normalize by (n-1). For every adjacent sequence t=1,...,t=n of timesteps of the same

day it is:

 $o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$

Example

To compute the daily mean of a time series use:

```
cdo daymean infile outfile
```

2.8.22. DAYPCTL - Daily percentile values

Synopsis

```
\mathbf{daypctl}, p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps of the same day in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding daymin and daymax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the **CDO** option --timestat date <first|middle|last>.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same day it is:

```
o(t, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t', x), t_1 < t' \le t_n\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the daily 90th percentile of a time series use:

```
cdo daymin infile minfile
cdo daymax infile maxfile
cdo daypctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo daypctl,90 infile -daymin infile -daymax infile outfile
```

2.8.23. MONSTAT - Monthly statistical values

Synopsis

< operator > infile outfile

Description

This module computes statistical values over timesteps of the same month. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of timesteps of the same month is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

monmin Monthly minimum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same month it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

monmax Monthly maximum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same month it is:

 $o(t, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

monrange Monthly range

For every adjacent sequence $t_1,...,t_n$ of time steps of the same month it is:

 $o(t,x) = \mathbf{range}\{i(t',x), t_1 < t' \le t_n\}$

monsum Monthly sum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same month it is:

 $o(t,x) = \mathbf{sum}\{i(t',x), t_1 < t' \le t_n\}$

monmean Monthly mean

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same month it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

monavg Monthly average

For every adjacent sequence $t_1,...,t_n$ of time steps of the same month it is:

 $o(t,x) = \mathbf{avg}\{i(t',x), t_1 < t' \le t_n\}$

monstd Monthly standard deviation

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

month it is:

 $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \le t_n\}$

monstd1 Monthly standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1,...,t_n$ of timesteps of the same

month it is:

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

monvar Monthly variance

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

month it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

monvar1 Monthly variance (n-1)

Normalize by (n-1). For every adjacent sequence t=1,...,t=n of timesteps of the same

month it is:

 $o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$

Example

To compute the monthly mean of a time series use:

```
cdo monmean infile outfile
```

2.8.24. MONPCTL - Monthly percentile values

Synopsis

```
monpctl,p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps of the same month in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding monmin and monmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the **CDO** option --timestat date <first|middle|last>.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same month it is:

```
o(t,x) = \mathbf{pth} \ \mathbf{percentile}\{i(t',x), t_1 < t' \le t_n\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the monthly 90th percentile of a time series use:

```
cdo monmin infile minfile
cdo monmax infile maxfile
cdo monpctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo monpctl,90 infile -monmin infile -monmax infile outfile
```

2.8.25. YEARMONSTAT - Yearly mean from monthly data

Synopsis

yearmonmean infile outfile

Description

This operator computes the yearly mean of a monthly time series. Each month is weighted with the number of days per month. The time of outfile is determined by the time in the middle of all contributing timesteps of infile.

```
For every adjacent sequence t_1, ..., t_n of timesteps of the same year it is:
o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}
```

Environment

CDO_TIMESTAT_DATE Sets the date information in outfile to the "first", "middle" or "last" contributing timestep of infile.

Example

To compute the yearly mean of a monthly time series use:

cdo yearmonmean infile outfile

2.8.26. YEARSTAT - Yearly statistical values

Synopsis

<operator> infile outfile

Description

This module computes statistical values over timesteps of the same year. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of timesteps of the same year is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

yearmin Yearly minimum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

yearmax Yearly maximum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

yearminidx Yearly minimum indices

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \mathbf{minidx}\{i(t', x), t_1 < t' \le t_n\}$

yearmaxidx Yearly maximum indices

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \mathbf{maxidx}\{i(t', x), t_1 < t' \le t_n\}$

yearrange Yearly range

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

yearsum Yearly sum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \le t_n\}$

yearmean Yearly mean

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

yearavg Yearly average

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

 $o(t,x) = \mathbf{avg}\{i(t',x), t_1 < t' \le t_n\}$

yearstd Yearly standard deviation

Normalize by n. For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

year it is:

 $o(t, x) = \mathbf{std}\{i(t', x), t_1 < t' \le t_n\}$

yearstd1 Yearly standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the

same year it is:

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

yearvar Yearly variance

Normalize by n. For every adjacent sequence t=1,...,t=n of timesteps of the same

year it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

```
yearvar1 Yearly variance (n-1)
```

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

```
o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}
```

Note

The operators yearmean and yearavg compute only arithmetical means!

Example

To compute the yearly mean of a time series use:

```
cdo yearmean infile outfile
```

To compute the yearly mean from the correct weighted monthly mean use:

```
cdo yearmonmean infile outfile
```

2.8.27. YEARPCTL - Yearly percentile values

Synopsis

```
yearpctl,p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps of the same year in infile1. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding yearmin and yearmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the CDO option --timestat_date <first|middle|last>.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same year it is:

```
o(t, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t', x), t_1 < t' \le t_n\}
```

Parameter

p FLOAT Percentile number in 0, ..., 100

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the yearly 90th percentile of a time series use:

```
cdo yearmin infile minfile
cdo yearmax infile maxfile
cdo yearpctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo yearpctl,90 infile -yearmin infile -yearmax infile outfile
```

2.8.28. SEASSTAT - Seasonal statistical values

Synopsis

<operator> infile outfile

Description

This module computes statistical values over timesteps of the same season. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of timesteps of the same season is written to outfile. The time of outfile is determined by the time in the middle of all contributing timesteps of infile. This can be change with the **CDO** option --timestat_date <first|middle|last>. Be careful about the first and the last output timestep, they may be incorrect values if the seasons have incomplete timesteps.

Operators

seasmin Seasonal minimum

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same season it is:

 $o(t, x) = \min\{i(t', x), t_1 < t' \le t_n\}$

seasmax Seasonal maximum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same season it is:

 $o(t, x) = \max\{i(t', x), t_1 < t' \le t_n\}$

seasrange Seasonal range

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same season it is:

 $o(t, x) = \mathbf{range}\{i(t', x), t_1 < t' \le t_n\}$

seassum Seasonal sum

For every adjacent sequence $t_1,...,t_n$ of timesteps of the same season it is:

 $o(t, x) = \mathbf{sum}\{i(t', x), t_1 < t' \le t_n\}$

seasmean Seasonal mean

For every adjacent sequence t = 1, ..., t = n of timesteps of the same season it is:

 $o(t, x) = \mathbf{mean}\{i(t', x), t_1 < t' \le t_n\}$

seasavg Seasonal average

For every adjacent sequence t = 1, ..., t = n of timesteps of the same season it is:

 $o(t, x) = \mathbf{avg}\{i(t', x), t_1 < t' \le t_n\}$

seasstd Seasonal standard deviation

Normalize by n. For every adjacent sequence t=1,...,t=n of timesteps of the same

season it is:

 $o(t,x) = \mathbf{std}\{i(t',x), t_1 < t' \le t_n\}$

seasstd1 Seasonal standard deviation (n-1)

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

season it is:

 $o(t, x) = \mathbf{std1}\{i(t', x), t_1 < t' \le t_n\}$

seasvar Seasonal variance

Normalize by n. For every adjacent sequence t = 1, ..., t = n of timesteps of the same

season it is:

 $o(t, x) = \mathbf{var}\{i(t', x), t_1 < t' \le t_n\}$

seasvar1 Seasonal variance (n-1)

Normalize by (n-1). For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same

season it is:

 $o(t, x) = \mathbf{var1}\{i(t', x), t_1 < t' \le t_n\}$

Example

To compute the seasonal mean of a time series use:

```
cdo seasmean infile outfile
```

2.8.29. SEASPCTL - Seasonal percentile values

Synopsis

```
\mathbf{seaspctl}, p infile1 infile2 infile3 outfile
```

Description

This operator computes percentiles over all timesteps in infile1 of the same season. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by defining the environment variable CDO_PCTL_NBINS. The files infile2 and infile3 should be the result of corresponding seasmin and seasmax operations, respectively. The time of outfile is determined by the time in the middle of all contributing timesteps of infile1. This can be change with the CDO option—timestat_date <first|middle|last>. Be careful about the first and the last output timestep, they may be incorrect values if the seasons have incomplete timesteps.

For every adjacent sequence $t_1, ..., t_n$ of timesteps of the same season it is:

```
o(t, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t', x), t_1 < t' \le t_n\}
```

Parameter

p FLOAT Percentile number in 0, ..., 100

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the seasonal 90th percentile of a time series use:

```
cdo seasmin infile minfile
cdo seasmax infile maxfile
cdo seaspctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo seaspctl,90 infile -seasmin infile -seasmax infile outfile
```

2.8.30. YHOURSTAT - Multi-year hourly statistical values

Synopsis

```
< operator > infile outfile
```

Description

This module computes statistical values of each hour and day of year. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of each hour and day of year in infile is written to outfile. The date information in an output field is the date of the last contributing input field.

Operators

```
yhourmin
                     Multi-year hourly minimum
                      o(0001, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 0001\}
                      o(8784, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 8784\}
yhourmax
                     Multi-year hourly maximum
                      o(0001, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 0001\}
                      o(8784, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 8784\}
yhourrange
                     Multi-year hourly range
                      o(0001, x) = \mathbf{range}\{i(t, x), day(i(t)) = 0001\}
                      o(8784, x) = \mathbf{range}\{i(t, x), day(i(t)) = 8784\}
yhoursum
                     Multi-year hourly sum
                      o(0001, x) = \mathbf{sum}\{i(t, x), day(i(t)) = 0001\}
                      o(8784, x) = \mathbf{sum}\{i(t, x), \operatorname{day}(i(t)) = 8784\}
yhourmean
                     Multi-year hourly mean
                      o(0001,x) = \mathbf{mean}\{i(t,x), \mathrm{day}(i(t)) = 0001\}
                      o(8784, x) = \mathbf{mean}\{i(t, x), day(i(t)) = 8784\}
yhouravg
                     Multi-year hourly average
                      o(0001,x) = \mathbf{avg}\{i(t,x), \mathrm{day}(i(t)) = 0001\}
                      o(8784, x) = \mathbf{avg}\{i(t, x), day(i(t)) = 8784\}
                     Multi-year hourly standard deviation
yhourstd
                     Normalize by n.
                      o(0001, x) = \mathbf{std}\{i(t, x), day(i(t)) = 0001\}
                      o(8784, x) = \mathbf{std}\{i(t, x), day(i(t)) = 8784\}
                     Multi-year hourly standard deviation (n-1)
yhourstd1
                     Normalize by (n-1).
```

$$o(0001,x) = \mathbf{std1}\{i(t,x), \mathrm{day}(i(t)) = 0001\}$$

$$\vdots$$

$$o(8784,x) = \mathbf{std1}\{i(t,x), \mathrm{day}(i(t)) = 8784\}$$

$$\mathbf{yhourvar} \qquad \text{Multi-year hourly variance}$$

$$\mathrm{Normalize\ by\ n.}$$

$$o(0001,x) = \mathbf{var}\{i(t,x), \mathrm{day}(i(t)) = 0001\}$$

$$\vdots$$

$$o(8784,x) = \mathbf{var}\{i(t,x), \mathrm{day}(i(t)) = 8784\}$$

$$\mathbf{yhourvar1} \qquad \text{Multi-year hourly variance\ (n-1)}$$

$$\mathrm{Normalize\ by\ (n-1).}$$

$$o(0001,x) = \mathbf{var1}\{i(t,x), \mathrm{day}(i(t)) = 0001\}$$

$$\vdots$$

$$o(8784,x) = \mathbf{var1}\{i(t,x), \mathrm{day}(i(t)) = 8784\}$$

2.8.31. DHOURSTAT - Multi-day hourly statistical values

Synopsis

```
< operator > infile outfile
```

Description

This module computes statistical values of each hour of day. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of each hour of day in infile is written to outfile. The date information in an output field is the date of the last contributing input field.

Operators

dhourmin Multi-day hourly minimum $o(01, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 01\}$ $o(24, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 24\}$ dhourmax Multi-day hourly maximum $o(01, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 01\}$ $o(24, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 24\}$ dhourrange Multi-day hourly range $o(01, x) = \mathbf{range}\{i(t, x), day(i(t)) = 01\}$ $o(24, x) = \mathbf{range}\{i(t, x), day(i(t)) = 24\}$ dhoursum Multi-day hourly sum $o(01, x) = \mathbf{sum}\{i(t, x), day(i(t)) = 01\}$ $o(24, x) = \mathbf{sum}\{i(t, x), day(i(t)) = 24\}$ dhourmean Multi-day hourly mean $o(01, x) = \mathbf{mean}\{i(t, x), day(i(t)) = 01\}$ $o(24, x) = \mathbf{mean}\{i(t, x), day(i(t)) = 24\}$ dhouravg Multi-day hourly average $o(01, x) = \mathbf{avg}\{i(t, x), day(i(t)) = 01\}$ $o(24, x) = \mathbf{avg}\{i(t, x), day(i(t)) = 24\}$ dhourstd Multi-day hourly standard deviation Normalize by n. $o(01, x) = \mathbf{std}\{i(t, x), day(i(t)) = 01\}$ $o(24, x) = \mathbf{std}\{i(t, x), day(i(t)) = 24\}$ dhourstd1 Multi-day hourly standard deviation (n-1)

Normalize by (n-1).

$$o(01,x) = \mathbf{std1}\{i(t,x), \operatorname{day}(i(t)) = 01\}$$

$$\vdots$$

$$o(24,x) = \mathbf{std1}\{i(t,x), \operatorname{day}(i(t)) = 24\}$$

$$\mathbf{dhourvar}$$
Multi-day hourly variance
Normalize by n.
$$o(01,x) = \mathbf{var}\{i(t,x), \operatorname{day}(i(t)) = 01\}$$

$$\vdots$$

$$o(24,x) = \mathbf{var}\{i(t,x), \operatorname{day}(i(t)) = 24\}$$

$$\mathbf{dhourvar1}$$
Multi-day hourly variance (n-1)
Normalize by (n-1).
$$o(01,x) = \mathbf{var1}\{i(t,x), \operatorname{day}(i(t)) = 01\}$$

$$\vdots$$

$$o(24,x) = \mathbf{var1}\{i(t,x), \operatorname{day}(i(t)) = 24\}$$

2.8.32. YDAYSTAT - Multi-year daily statistical values

Synopsis

```
< operator > infile outfile
```

Description

This module computes statistical values of each day of year. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of each day of year in infile is written to outfile. The date information in an output field is the date of the last contributing input field.

Operators

```
ydaymin
                   Multi-year daily minimum
                     o(001, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 001\}
                     o(366, x) = \min\{i(t, x), \operatorname{day}(i(t)) = 366\}
ydaymax
                   Multi-year daily maximum
                     o(001, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 001\}
                     o(366, x) = \max\{i(t, x), \operatorname{day}(i(t)) = 366\}
ydayrange
                   Multi-year daily range
                     o(001, x) = \mathbf{range}\{i(t, x), day(i(t)) = 001\}
                     o(366, x) = \mathbf{range}\{i(t, x), day(i(t)) = 366\}
ydaysum
                   Multi-year daily sum
                     o(001, x) = \mathbf{sum}\{i(t, x), day(i(t)) = 001\}
                     o(366, x) = \mathbf{sum}\{i(t, x), day(i(t)) = 366\}
ydaymean
                   Multi-year daily mean
                     o(001, x) = \mathbf{mean}\{i(t, x), day(i(t)) = 001\}
                     o(366, x) = \mathbf{mean}\{i(t, x), \operatorname{day}(i(t)) = 366\}
ydayavg
                   Multi-year daily average
                     o(001, x) = \mathbf{avg}\{i(t, x), day(i(t)) = 001\}
                     o(366, x) = \mathbf{avg}\{i(t, x), day(i(t)) = 366\}
ydaystd
                   Multi-year daily standard deviation
                   Normalize by n.
                     o(001, x) = \mathbf{std}\{i(t, x), day(i(t)) = 001\}
                     o(366, x) = \mathbf{std}\{i(t, x), day(i(t)) = 366\}
                   Multi-year daily standard deviation (n-1)
ydaystd1
                   Normalize by (n-1).
```

$$o(001,x) = \mathbf{std1}\{i(t,x), \operatorname{day}(i(t)) = 001\}$$

$$\vdots$$

$$o(366,x) = \mathbf{std1}\{i(t,x), \operatorname{day}(i(t)) = 366\}$$

$$\mathbf{ydayvar}$$
Multi-year daily variance
Normalize by n.
$$o(001,x) = \mathbf{var}\{i(t,x), \operatorname{day}(i(t)) = 001\}$$

$$\vdots$$

$$o(366,x) = \mathbf{var}\{i(t,x), \operatorname{day}(i(t)) = 366\}$$

$$\mathbf{ydayvar1}$$
Multi-year daily variance (n-1)
Normalize by (n-1).
$$o(001,x) = \mathbf{var1}\{i(t,x), \operatorname{day}(i(t)) = 001\}$$

$$\vdots$$

$$o(366,x) = \mathbf{var1}\{i(t,x), \operatorname{day}(i(t)) = 366\}$$

Example

To compute the daily mean over all input years use:

cdo ydaymean infile outfile

2.8.33. YDAYPCTL - Multi-year daily percentile values

Synopsis

```
ydaypctl,p infile1 infile2 infile3 outfile
```

Description

This operator writes a certain percentile of each day of year in infile1 to outfile. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The files infile2 and infile3 should be the result of corresponding ydaymin and ydaymax operations, respectively. The date information in an output field is the date of the last contributing input field.

```
o(001, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), \operatorname{day}(i(t)) = 001\}
\vdots
o(366, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), \operatorname{day}(i(t)) = 366\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the daily 90th percentile over all input years use:

```
cdo ydaymin infile minfile
cdo ydaymax infile maxfile
cdo ydaypctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo ydaypctl,90 infile -ydaymin infile -ydaymax infile outfile
```

2.8.34. YMONSTAT - Multi-year monthly statistical values

Synopsis

```
< operator > infile outfile
```

Description

This module computes statistical values of each month of year. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of each month of year in infile is written to outfile. The date information in an output field is the date of the last contributing input field. This can be change with the **CDO** option --timestat_date <first|middle|last>.

Operators

```
ymonmin
                    Multi-year monthly minimum
                      o(01, x) = \min\{i(t, x), \text{month}(i(t)) = 01\}
                      o(12, x) = \min\{i(t, x), \text{month}(i(t)) = 12\}
                     Multi-year monthly maximum
ymonmax
                      o(01, x) = \max\{i(t, x), \text{month}(i(t)) = 01\}
                      o(12, x) = \max\{i(t, x), \text{month}(i(t)) = 12\}
ymonrange
                     Multi-year monthly range
                      o(01, x) = \mathbf{range}\{i(t, x), \mathbf{month}(i(t)) = 01\}
                      o(12, x) = \mathbf{range}\{i(t, x), \mathbf{month}(i(t)) = 12\}
ymonsum
                    Multi-year monthly sum
                      o(01, x) = \mathbf{sum}\{i(t, x), \text{month}(i(t)) = 01\}
                      o(12, x) = \mathbf{sum}\{i(t, x), \text{month}(i(t)) = 12\}
                     Multi-year monthly mean
ymonmean
                      o(01, x) = \mathbf{mean}\{i(t, x), \mathbf{month}(i(t)) = 01\}
                      o(12, x) = \mathbf{mean}\{i(t, x), \mathbf{month}(i(t)) = 12\}
                     Multi-year monthly average
ymonavg
                      o(01, x) = \mathbf{avg}\{i(t, x), \text{month}(i(t)) = 01\}
                      o(12, x) = \mathbf{avg}\{i(t, x), \mathbf{month}(i(t)) = 12\}
                    Multi-year monthly standard deviation
ymonstd
                     Normalize by n.
                      o(01, x) = \mathbf{std}\{i(t, x), \mathbf{month}(i(t)) = 01\}
                      \vdots \\ o(12,x) = \mathbf{std}\{i(t,x), \mathrm{month}(i(t)) = 12\}
                    Multi-year monthly standard deviation (n-1)
ymonstd1
                    Normalize by (n-1).
```

$$o(01,x) = \mathbf{std1}\{i(t,x), \mathrm{month}(i(t)) = 01\}$$

$$\vdots$$

$$o(12,x) = \mathbf{std1}\{i(t,x), \mathrm{month}(i(t)) = 12\}$$

$$\mathbf{ymonvar}$$
Multi-year monthly variance
$$\mathrm{Normalize\ by\ n.}$$

$$o(01,x) = \mathbf{var}\{i(t,x), \mathrm{month}(i(t)) = 01\}$$

$$\vdots$$

$$o(12,x) = \mathbf{var}\{i(t,x), \mathrm{month}(i(t)) = 12\}$$

$$\mathbf{ymonvar1}$$
Multi-year monthly variance (n-1)
$$\mathrm{Normalize\ by\ (n-1).}$$

$$o(01,x) = \mathbf{var1}\{i(t,x), \mathrm{month}(i(t)) = 01\}$$

$$\vdots$$

$$o(12,x) = \mathbf{var1}\{i(t,x), \mathrm{month}(i(t)) = 12\}$$

Example

To compute the monthly mean over all input years use:

cdo ymonmean infile outfile

2.8.35. YMONPCTL - Multi-year monthly percentile values

Synopsis

```
ymonpctl,p infile1 infile2 infile3 outfile
```

Description

This operator writes a certain percentile of each month of year in infile1 to outfile. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The files infile2 and infile3 should be the result of corresponding ymonmin and ymonmax operations, respectively. The date information in an output field is the date of the last contributing input field.

```
o(01, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), \mathrm{month}(i(t)) = 01\}

\vdots

o(12, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), \mathrm{month}(i(t)) = 12\}
```

Parameter

p FLOAT Percentile number in 0, ..., 100

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

To compute the monthly 90th percentile over all input years use:

```
cdo ymonmin infile minfile
cdo ymonmax infile maxfile
cdo ymonpctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo ymonpctl,90 infile -ymonmin infile -ymonmax infile outfile
```

2.8.36. YSEASSTAT - Multi-year seasonal statistical values

Synopsis

```
<operator> infile outfile
```

Description

This module computes statistical values of each season. Depending on the chosen operator the minimum, maximum, range, sum, average, variance or standard deviation of each season in infile is written to outfile. The date information in an output field is the date of the last contributing input field.

Operators

```
yseasmin
                     Multi-year seasonal minimum
                       o(1,x) = \min\{i(t,x), \text{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \min\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}
                      o(3,x) = \min\{i(t,x), \text{month}(i(t)) = 06, 07, 08\}
                      o(4,x) = \min\{i(t,x), \text{month}(i(t)) = 09, 10, 11\}
                     Multi-year seasonal maximum
yseasmax
                       o(1,x) = \max\{i(t,x), \text{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \max\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}
                      o(3, x) = \max\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}
                       o(4, x) = \max\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}
                     Multi-year seasonal range
yseasrange
                       o(1,x) = \mathbf{range}\{i(t,x), \mathbf{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \mathbf{range}\{i(t, x), \mathbf{month}(i(t)) = 03, 04, 05\}
                      o(3, x) = \mathbf{range}\{i(t, x), \mathbf{month}(i(t)) = 06, 07, 08\}
                       o(4, x) = \mathbf{range}\{i(t, x), \mathbf{month}(i(t)) = 09, 10, 11\}
                     Multi-year seasonal sum
yseassum
                      o(1,x) = \mathbf{sum}\{i(t,x), \mathbf{month}(i(t)) = 12, 01, 02\}
                      o(2,x) = \mathbf{sum}\{i(t,x), \mathbf{month}(i(t)) = 03, 04, 05\}
                      o(3,x) = \mathbf{sum}\{i(t,x), \mathbf{month}(i(t)) = 06, 07, 08\}
                      o(4,x) = \mathbf{sum}\{i(t,x), \text{month}(i(t)) = 09, 10, 11\}
                     Multi-year seasonal mean
yseasmean
                       o(1, x) = \mathbf{mean}\{i(t, x), \mathbf{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \mathbf{mean}\{i(t, x), \mathbf{month}(i(t)) = 03, 04, 05\}
                      o(3,x) = \mathbf{mean}\{i(t,x), \mathbf{month}(i(t)) = 06, 07, 08\}
                       o(4, x) = \mathbf{mean}\{i(t, x), \mathbf{month}(i(t)) = 09, 10, 11\}
yseasavg
                     Multi-year seasonal average
                       o(1, x) = \mathbf{avg}\{i(t, x), \mathbf{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \mathbf{avg}\{i(t, x), \mathbf{month}(i(t)) = 03, 04, 05\}
                      o(3,x) = \mathbf{avg}\{i(t,x), \text{month}(i(t)) = 06, 07, 08\}
                       o(4, x) = \mathbf{avg}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}
                     Multi-year seasonal standard deviation
yseasstd
                       o(1,x) = \mathbf{std}\{i(t,x), \mathbf{month}(i(t)) = 12, 01, 02\}
                      o(2, x) = \mathbf{std}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}
                      o(3,x) = \mathbf{std}\{i(t,x), month(i(t)) = 06, 07, 08\}
                       o(4,x) = \mathbf{std}\{i(t,x), \mathbf{month}(i(t)) = 09, 10, 11\}
```

```
Multi-year seasonal standard deviation (n-1)
yseasstd1
                       o(1,x) = \mathbf{std1}\{i(t,x), month(i(t)) = 12, 01, 02\}
                       o(2, x) = \mathbf{std1}\{i(t, x), month(i(t)) = 03, 04, 05\}
                       o(3,x) = \mathbf{std1}\{i(t,x), \mathbf{month}(i(t)) = 06, 07, 08\}
                       o(4,x) = \mathbf{std1}\{i(t,x), \mathbf{month}(i(t)) = 09, 10, 11\}
yseasvar
                      Multi-year seasonal variance
                       o(1, x) = \mathbf{var}\{i(t, x), \mathbf{month}(i(t)) = 12, 01, 02\}
                       o(2, x) = \mathbf{var}\{i(t, x), \text{month}(i(t)) = 03, 04, 05\}
                       o(3, x) = \mathbf{var}\{i(t, x), \text{month}(i(t)) = 06, 07, 08\}
                       o(4, x) = \mathbf{var}\{i(t, x), \text{month}(i(t)) = 09, 10, 11\}
                      Multi-year seasonal variance (n-1)
yseasvar1
                       o(1,x) = \mathbf{var1}\{i(t,x), \mathbf{month}(i(t)) = 12, 01, 02\}
                       o(2, x) = \mathbf{var1}\{i(t, x), \mathbf{month}(i(t)) = 03, 04, 05\}
                       o(3, x) = \mathbf{var1}\{i(t, x), \mathbf{month}(i(t)) = 06, 07, 08\}
                       o(4,x) = \mathbf{var1}\{i(t,x), \mathbf{month}(i(t)) = 09, 10, 11\}
```

Example

To compute the seasonal mean over all input years use:

```
cdo yseasmean infile outfile
```

2.8.37. YSEASPCTL - Multi-year seasonal percentile values

Synopsis

```
yseaspctl,p infile1 infile2 infile3 outfile
```

Description

This operator writes a certain percentile of each season in infile1 to outfile. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The files infile2 and infile3 should be the result of corresponding yseasmin and yseasmax operations, respectively. The date information in an output field is the date of the last contributing input field.

```
o(1,x) = pth percentile\{i(t,x), month(i(t)) = 12, 01, 02\}

o(2,x) = pth percentile\{i(t,x), month(i(t)) = 03, 04, 05\}

o(3,x) = pth percentile\{i(t,x), month(i(t)) = 06, 07, 08\}

o(4,x) = pth percentile\{i(t,x), month(i(t)) = 09, 10, 11\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100
```

Environment

```
CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.
```

Example

To compute the seasonal 90th percentile over all input years use:

```
cdo yseasmin infile minfile
cdo yseasmax infile maxfile
cdo yseaspctl,90 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo yseaspctl,90 infile -yseasmin infile -yseasmax infile outfile
```

2.8.38. YDRUNSTAT - Multi-year daily running statistical values

Synopsis

< operator >, nts infile outfile

Description

This module writes running statistical values for each day of year in infile to outfile. Depending on the chosen operator, the minimum, maximum, sum, average, variance or standard deviation of all timesteps in running windows of which the medium timestep corresponds to a certain day of year is computed. The date information in an output field is the date of the timestep in the middle of the last contributing running window. Note that the operator have to be applied to a continuous time series of daily measurements in order to yield physically meaningful results. Also note that the output time series begins (nts-1)/2 timesteps after the first timestep of the input time series and ends (nts-1)/2 timesteps before the last one. For input data which are complete but not continuous, such as time series of daily measurements for the same month or season within different years, the operator yields physically meaningful results only if the input time series does include the (nts-1)/2 days before and after each period of interest.

Operators

```
ydrunmin
                   Multi-year daily running minimum
                    o(001,x) = \min\{i(t,x), i(t+1,x), ..., i(t+nts-1,x); \operatorname{day}[(i(t+(nts-1)/2)] = 001\} :
                    o(366, x) = \min\{i(t, x), i(t + 1, x), ..., i(t + nts - 1, x); day[(i(t + (nts - 1)/2))] = 366\}
ydrunmax
                   Multi-year daily running maximum
                    o(001, x) = \max\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); \operatorname{day}[(i(t+(nts-1)/2)] = 001\}
                    o(366, x) = \max\{i(t, x), i(t + 1, x), ..., i(t + nts - 1, x); day[(i(t + (nts - 1)/2))] = 366\}
vdrunsum
                   Multi-year daily running sum
                    o(001, x) = \mathbf{sum}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); \text{day}[(i(t+(nts-1)/2))] = 001\}
                    o(366, x) = \mathbf{sum}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); day[(i(t+(nts-1)/2))] = 366\}
ydrunmean
                   Multi-year daily running mean
                    o(001,x) = \mathbf{mean}\{i(t,x), i(t+1,x), ..., i(t+nts-1,x); \operatorname{day}[(i(t+(nts-1)/2)] = 001\}
                    o(366,x) = \mathbf{mean}\{i(t,x), i(t+1,x), ..., i(t+nts-1,x); \mathrm{day}[(i(t+(nts-1)/2)] = 366\}
ydrunavg
                   Multi-year daily running average
                    o(001,x) = \mathbf{avg}\{i(t,x), i(t+1,x), ..., i(t+nts-1,x); \mathrm{day}[(i(t+(nts-1)/2)] = 001\}
                    o(366, x) = \mathbf{avg}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); day[(i(t+(nts-1)/2))] = 366\}
ydrunstd
                   Multi-year daily running standard deviation
                   Normalize by n.
                    o(001, x) = \mathbf{std}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); \operatorname{day}[(i(t+(nts-1)/2)] = 001\}
                    o(366, x) = \mathbf{std}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); day[(i(t+(nts-1)/2)] = 366\}
```

Parameter

nts INTEGER Number of timesteps

Example

Assume the input data provide a continuous time series of daily measurements. To compute the running multi-year daily mean over all input timesteps for a running window of five days use:

```
cdo ydrunmean,5 infile outfile
```

Note that except for the standard deviation the results of the operators in this module are equivalent to a composition of corresponding operators from the YDAYSTAT and RUNSTAT modules. For instance, the above command yields the same result as:

cdo ydaymean -runmean,5 infile outfile

2.8.39. YDRUNPCTL - Multi-year daily running percentile values

Synopsis

```
ydrunpctl, p, nts infile1 infile2 infile3 outfile
```

Description

This operator writes running percentile values for each day of year in infile1 to outfile. A certain percentile is computed for all timesteps in running windows of which the medium timestep corresponds to a certain day of year. The algorithm uses histograms with minimum and maximum bounds given in infile2 and infile3, respectively. The default number of histogram bins is 101. The default can be overridden by setting the environment variable CDO_PCTL_NBINS to a different value. The files infile2 and infile3 should be the result of corresponding ydrunmin and ydrunmax operations, respectively. The date information in an output field is the date of the timestep in the middle of the last contributing running window. Note that the operator have to be applied to a continuous time series of daily measurements in order to yield physically meaningful results. Also note that the output time series begins (nts-1)/2 timesteps after the first timestep of the input time series and ends (nts-1)/2 timesteps before the last. For input data which are complete but not continuous, such as time series of daily measurements for the same month or season within different years, the operator only yields physically meaningful results if the input time series does include the (nts-1)/2 days before and after each period of interest.

```
o(001, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); \operatorname{day}[(i(t+(nts-1)/2)] = 001\}
\vdots
o(366, x) = \mathbf{pth} \ \mathbf{percentile}\{i(t, x), i(t+1, x), ..., i(t+nts-1, x); \operatorname{day}[(i(t+(nts-1)/2)] = 366\}
```

Parameter

```
p FLOAT Percentile number in 0, ..., 100nts INTEGER Number of timesteps
```

Environment

CDO_PCTL_NBINS Sets the number of histogram bins. The default number is 101.

Example

Assume the input data provide a continuous time series of daily measurements. To compute the running multi-year daily 90th percentile over all input timesteps for a running window of five days use:

```
cdo ydrunmin,5 infile minfile
cdo ydrunmax,5 infile maxfile
cdo ydrunpctl,90,5 infile minfile maxfile outfile
```

Or shorter using operator piping:

```
cdo ydrunpctl,90,5 infile -ydrunmin infile -ydrunmax infile outfile
```

Correlation and co. Reference manual

2.9. Correlation and co.

This sections contains modules for correlation and co. in grid space and over time. In this section the abbreviations as in the following table are used:

Covariance
$$n^{-1} \sum_{i=1}^{n} (x_i - \overline{x})(y_i - \overline{y})$$
covar weighted by
$$\left\{ w_i, i = 1, ..., n \right\} \qquad \left(\sum_{j=1}^{n} w_j \right)^{-1} \sum_{i=1}^{n} w_i \left(x_i - \left(\sum_{j=1}^{n} w_j \right)^{-1} \sum_{j=1}^{n} w_j x_j \right) \left(y_i - \left(\sum_{j=1}^{n} w_j \right)^{-1} \sum_{j=1}^{n} w_j y_j \right)$$

Here is a short overview of all operators in this section:

fldcor Correlation in grid space

timcor Correlation over time

fldcovar Covariance in grid space

timcovar Covariance over time

Reference manual Correlation and co.

2.9.1. FLDCOR - Correlation in grid space

Synopsis

fldcor infile1 infile2 outfile

Description

The correlation coefficient is a quantity that gives the quality of a least squares fitting to the original data. This operator correlates all gridpoints of two fields for each timestep. With

$$S(t) = \{x, i_1(t, x) \neq missval \land i_2(t, x) \neq missval\}$$

it is

$$o(t,1) = \frac{\sum\limits_{x \in S(t)} i_1(t,x) i_2(t,x) w(x) - \overline{i_1(t,x)} \ \overline{i_2(t,x)} \sum\limits_{x \in S(t)} w(x)}{\sqrt{\left(\sum\limits_{x \in S(t)} i_1(t,x)^2 w(x) - \overline{i_1(t,x)}^2 \sum\limits_{x \in S(t)} w(x)\right) \left(\sum\limits_{x \in S(t)} i_2(t,x)^2 w(x) - \overline{i_2(t,x)}^2 \sum\limits_{x \in S(t)} w(x)\right)}}$$

where w(x) are the area weights obtained by the input streams. For every timestep t only those field elements x belong to the sample, which have $i_1(t,x) \neq missval$ and $i_2(t,x) \neq missval$.

2.9.2. TIMCOR - Correlation over time

Synopsis

timcor infile1 infile2 outfile

Description

The correlation coefficient is a quantity that gives the quality of a least squares fitting to the original data. This operator correlates each gridpoint of two fields over all timesteps. With

$$S(x) = \{t, i_1(t, x) \neq missval \land i_2(t, x) \neq missval\}$$

it is

$$o(1,x) = \frac{\sum_{t \in S(x)} i_1(t,x)i_2(t,x) - n \ \overline{i_1(t,x)} \ \overline{i_2(t,x)}}{\sqrt{\left(\sum_{t \in S(x)} i_1(t,x)^2 - n \ \overline{i_1(t,x)}^2\right) \left(\sum_{t \in S(x)} i_2(t,x)^2 - n \ \overline{i_2(t,x)}^2\right)}}$$

For every gridpoint x only those timesteps t belong to the sample, which have $i_1(t, x) \neq missval$ and $i_2(t, x) \neq missval$.

Correlation and co. Reference manual

2.9.3. FLDCOVAR - Covariance in grid space

Synopsis

fldcovar infile1 infile2 outfile

Description

This operator calculates the covariance of two fields over all gridpoints for each timestep. With

$$S(t) = \{x, i_1(t, x) \neq missval \land i_2(t, x) \neq missval\}$$

it is

$$o(t,1) = \left(\sum_{x \in S(t)} w(x)\right)^{-1} \sum_{x \in S(t)} w(x) \left(i_1(t,x) - \frac{\sum_{x \in S(t)} w(x) i_1(t,x)}{\sum_{x \in S(t)} w(x)}\right) \left(i_2(t,x) - \frac{\sum_{x \in S(t)} w(x) i_2(t,x)}{\sum_{x \in S(t)} w(x)}\right)$$

where w(x) are the area weights obtained by the input streams. For every timestep t only those field elements x belong to the sample, which have $i_1(t,x) \neq missval$ and $i_2(t,x) \neq missval$.

2.9.4. TIMCOVAR - Covariance over time

Synopsis

timcovar infile1 infile2 outfile

Description

This operator calculates the covariance of two fields at each gridpoint over all timesteps. With

$$S(x) = \{t, i_1(t, x) \neq missval \land i_2(t, x) \neq missval\}$$

it is

$$o(1,x) = n^{-1} \sum_{t \in S(x)} \left(i_1(t,x) - \overline{i_1(t,x)} \right) \left(i_2(t,x) - \overline{i_2(t,x)} \right)$$

For every gridpoint x only those timesteps t belong to the sample, which have $i_1(t, x) \neq missval$ and $i_2(t, x) \neq missval$.

Reference manual Regression

2.10. Regression

This sections contains modules for linear regression of time series.

Here is a short overview of all operators in this section:

regression Regression

detrend Detrend

trend Trend

addtrendAdd trendsubtrendSubtract trend

Regression Reference manual

2.10.1. REGRES - Regression

Synopsis

regres[,equal] infile outfile

Description

The values of the input file infile are assumed to be distributed as $N(a+bt,\sigma^2)$ with unknown a, b and σ^2 . This operator estimates the parameter b. For every field element x only those timesteps t belong to the sample S(x), which have $i(t,x) \neq \text{miss}$. It is

$$o(1,x) = \frac{\sum\limits_{t \in S(x)} \left(i(t,x) - \frac{1}{\#S(x)} \sum\limits_{t' \in S(x)} i(t',x) \right) \left(t - \frac{1}{\#S(x)} \sum\limits_{t' \in S(x)} t' \right)}{\sum\limits_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum\limits_{t' \in S(x)} t' \right)^2}$$

It is assumed that all timesteps are equidistant, if this is not the case set the parameter equal=false.

Parameter

equal BOOL

Set to false for unequal distributed timesteps (default: true)

2.10.2. DETREND - Detrend time series

Synopsis

detrend/,equal infile outfile

Description

Every time series in infile is linearly detrended. For every field element x only those timesteps t belong to the sample S(x), which have $i(t,x) \neq \text{miss.}$ It is assumed that all timesteps are equidistant, if this is not the case set the parameter equal=false. With

$$a(x) = \frac{1}{\#S(x)} \sum_{t \in S(x)} i(t, x) - b(x) \left(\frac{1}{\#S(x)} \sum_{t \in S(x)} t \right)$$

and

$$b(x) = \frac{\sum_{t \in S(x)} \left(i(t, x) - \frac{1}{\#S(x)} \sum_{t' \in S(x)} i(t', x) \right) \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)}{\sum_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)^2}$$

it is

$$o(t,x) = i(t,x) - (a(x) + b(x)t)$$

Parameter

equal BOOL

Set to false for unequal distributed timesteps (default: true)

Reference manual Regression

Note

This operator has to keep the fields of all timesteps concurrently in the memory. If not enough memory is available use the operators trend and subtrend.

Example

To detrend the data in infile and to store the detrended data in outfile use:

cdo detrend infile outfile

2.10.3. TREND - Trend of time series

Synopsis

trend[,equal] infile outfile1 outfile2

Description

The values of the input file infile are assumed to be distributed as $N(a+bt,\sigma^2)$ with unknown a, b and σ^2 . This operator estimates the parameter a and b. For every field element x only those timesteps t belong to the sample S(x), which have $i(t,x) \neq \text{miss}$. It is

$$o_1(1,x) = \frac{1}{\#S(x)} \sum_{t \in S(x)} i(t,x) - b(x) \left(\frac{1}{\#S(x)} \sum_{t \in S(x)} t \right)$$

and

$$o_2(1,x) = \frac{\sum_{t \in S(x)} \left(i(t,x) - \frac{1}{\#S(x)} \sum_{t' \in S(x)} i(t',x) \right) \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)}{\sum_{t \in S(x)} \left(t - \frac{1}{\#S(x)} \sum_{t' \in S(x)} t' \right)^2}$$

Thus the estimation for a is stored in outfile1 and that for b is stored in outfile2. To subtract the trend from the data see operator subtrend. It is assumed that all timesteps are equidistant, if this is not the case set the parameter equal=false.

Parameter

equal BOOL Set to false for unequal distributed timesteps (default: true)

Regression Reference manual

2.10.4. TRENDARITH - Add or subtract a trend

Synopsis

```
<operator>[,equal] infile1 infile2 infile3 outfile
```

Description

This module is for adding or subtracting a trend computed by the operator trend.

Operators

addtrend

Add trend

It is

$$o(t,x) = i_1(t,x) + (i_2(1,x) + i_3(1,x) \cdot t)$$

where t is the timesteps.

subtrend

Subtract trend

It is

$$o(t,x) = i_1(t,x) - (i_2(1,x) + i_3(1,x) \cdot t)$$

where t is the timesteps.

Parameter

equal

BOOL

Set to false for unequal distributed timesteps (default: true)

Example

The typical call for detrending the data in infile and storing the detrended data in outfile is:

```
cdo trend infile afile bfile cdo subtrend infile afile bfile outfile
```

The result is identical to a call of the operator detrend:

```
cdo detrend infile outfile
```

Reference manual EOFs

2.11. EOFs

This section contains modules to compute Empirical Orthogonal Functions and - once they are computed - their principal coefficients.

An introduction to the theory of principal component analysis as applied here can be found in:

Principal Component Analysis in Meteorology and Oceanography [Preisendorfer]

Details about calculation in the time- and spatial spaces are found in:

Statistical Analysis in Climate Research [vonStorch]

EOFs are defined as the eigen values of the scatter matrix (covariance matrix) of the data. For the sake of simplicity, samples are regarded as **time series of anomalies**

$$(z(t)), t \in \{1, \dots, n\}$$

of (column-) vectors z(t) with p entries (where p is the gridsize). Thus, using the fact, that $z_j(t)$ are anomalies, i.e.

$$\langle z_j \rangle = n^{-1} \sum_{i=1}^n z_j(i) = 0 \ \forall \ 1 \le j \le p$$

the scatter matrix S can be written as

$$\mathbf{S} = \sum_{t=1}^{n} \left[\sqrt{\mathbf{W}} z(t) \right] \left[\sqrt{\mathbf{W}} z(t) \right]^{T}$$

where **W** is the diagonal matrix containing the area weight of cell p_0 in z at $\mathbf{W}(x,x)$.

The matrix **S** has a set of orthonormal eigenvectors $e_j, j = 1, ...p$, which are called *empirical orthogonal* functions (EOFs) of the sample z. (Please note, that e_j is the eigenvector of **S** and not the weighted eigen-vector which would be $\mathbf{W}e_j$.) Let the corresponding eigenvalues be denoted λ_j . The vectors e_j are spatial patterns which explain a certain amount of variance of the time series z(t) that is related linearly to λ_j . Thus, the spatial pattern defined by the first eigenvector (the one with the largest eigenvalue) is the pattern which explains a maximum possible amount of variance of the sample z(t). The orthonormality of eigenvectors reads as

$$\sum_{x=1}^{p} \left[\sqrt{\mathbf{W}(x,x)} e_j(x) \right] \left[\sqrt{\mathbf{W}(x,x)} e_k(x) \right] = \sum_{x=1}^{p} \mathbf{W}(x,x) e_j(x) e_k(x) = \begin{cases} 0 & \text{if } j \neq k \\ 1 & \text{if } j = k \end{cases}$$

If all EOFs e_j with $\lambda_j \neq 0$ are calculated, the data can be reconstructed from

$$z(t,x) = \sum_{j=1}^{p} \mathbf{W}(x,x)a_j(t)e_j(x)$$

where a_j are called the *principal components* or *principal coefficients* or *EOF coefficients* of z. These coefficients - as readily seen from above - are calculated as the projection of an EOF e_j onto a time step of the data sample $z(t_0)$ as

$$a_j(t_0) = \sum_{x=1}^p \left[\sqrt{\mathbf{W}(x,x)} e_j(x) \right] \left[\sqrt{\mathbf{W}(x,x)} z(t_0,x) \right] = \left[\sqrt{\mathbf{W}} z(t_0) \right]^T \left[\sqrt{\mathbf{W}} e_j \right].$$

Here is a short overview of all operators in this section:

eof Calculate EOFs in spatial or time space

eoftime Calculate EOFs in time space eofspatial Calculate EOFs in spatial space

eof3d Calculate 3-Dimensional EOFs in time space

eofcoeff Calculate principal coefficients of EOFs

EOFs Reference manual

2.11.1. EOFS - Empirical Orthogonal Functions

Synopsis

<operator>,neof infile outfile1 outfile2

Description

This module calculates empirical orthogonal functions of the data in infile as the eigen values of the scatter matrix (covariance matrix) S of the data sample z(t). A more detailed description can be found above.

Please note, that the input data are assumed to be anomalies.

If operator eof is chosen, the EOFs are computed in either time or spatial space, whichever is the fastest. If the user already knows, which computation is faster, the module can be forced to perform a computation in time- or gridspace by using the operators eoftime or eofspatial, respectively. This can enhance performance, especially for very long time series, where the number of timesteps is larger than the number of grid-points. Data in infile are assumed to be anomalies. If they are not, the behavior of this module is **not well defined**. After execution outfile1 will contain all eigen-values and outfile2 the eigenvectors e_j . All EOFs and eigen-values are computed. However, only the first neof EOFs are written to outfile2. Nonetheless, outfile1 contains all eigen-values.

Missing values are not fully supported. Support is only checked for non-changing masks of missing values in time. Although there still will be results, they are not trustworthy, and a warning will occur. In the latter case we suggest to replace missing values by 0 in infile.

Operators

eof Calculate EOFs in spatial or time space

eoftime Calculate EOFs in time space

eofspatial Calculate EOFs in spatial space

eof3d Calculate 3-Dimensional EOFs in time space

Parameter

neof INTEGER Number of eigen functions

Environment

CDO_SVD_MODE Is used to choose the algorithm for eigenvalue calculation. Options are 'jacobi'

for a one-sided parallel jacobi-algorithm (only executed in parallel if -P flag is set) and 'danielson_lanczos' for a non-parallel d/l algorithm. The default

setting is 'jacobi'.

CDO_WEIGHT_MODE It is used to set the weight mode. The default is 'off'. Set it to 'on' for a

weighted version.

MAX_JACOBI_ITER Is the maximum integer number of annihilation sweeps that is executed if the

jacobi-algorithm is used to compute the eigen values. The default value is 12.

FNORM_PRECISION Is the Frobenius norm of the matrix consisting of an annihilation pair of eigen-

vectors that is used to determine if the eigenvectors have reached a sufficient level of convergence. If all annihilation-pairs of vectors have a norm below this value, the computation is considered to have converged properly. Otherwise, a

warning will occur. The default value 1e-12.

Reference manual EOFs

Example

To calculate the first 40 EOFs of a data-set containing anomalies use:

```
cdo eof,40 infile outfile1 outfile2
```

If the dataset does not containt anomalies, process them first, and use:

```
cdo sub infile1 -timmean infile1 anom_file
cdo eof,40 anom_file outfile1 outfile2
```

EOFs Reference manual

2.11.2. EOFCOEFF - Principal coefficients of EOFs

Synopsis

eofcoeff infile1 infile2 obase

Description

This module calculates the time series of the principal coefficients for given EOF (empirical orthogonal functions) and data. Time steps in infile1 are assumed to be the EOFs, time steps in infile2 are assumed to be the time series. Note, that this operator calculates a non weighted dot product of the fields in infile1 and infile2. For consistency set the environment variable CDO_WEIGHT_MODE=off when using eof or eof3d. Given a set of EOFs e_j and a time series of data z(t) with p entries for each timestep from which e_j have been calculated, this operator calculates the time series of the projections of data onto each EOF

$$o_j(t) = \sum_{x=1}^p z(t, x)e_j(x)$$

There will be a seperate file o_{j} for the principal coefficients of each EOF.

As the EOFs e_{j} are uncorrelated, so are their principal coefficients, i.e.

$$\sum_{t=1}^{n} o_{j}(t)o_{k}(t) = \begin{cases} 0 \text{ if } j \neq k \\ \lambda_{j} \text{ if } j = k \end{cases} \text{ with } \sum_{t=1}^{n} o_{j}(t) = 0 \forall j \in \{1, \dots, p\}.$$

There will be a separate file containing a time series of principal coefficients with time information from infile2 for each EOF in infile1. Output files will be numbered as <obase><neof><suffix> where neof+1 is the number of the EOF (timestep) in infile1 and suffix is the filename extension derived from the file format.

Environment

CDO FILE SUFFIX

Set the default file suffix. This suffix will be added to the output file names instead of the filename extension derived from the file format. Set this variable to NULL to disable the adding of a file suffix.

Example

To calculate principal coefficients of the first 40 EOFs of anom_file, and write them to files beginning with obase, use:

```
export CDO_WEIGHT_MODE=off
cdo eof,40 anom_file eval_file eof_file
cdo eofcoeff eof_file anom_file obase
```

The principal coefficients of the first EOF will be in the file obase000000.nc (and so forth for higher EOFs, nth EOF will be in obase<n-1>).

If the dataset infile does not containt anomalies, process them first, and use:

```
export CDO_WEIGHT_MODE=off
cdo sub infile -timmean infile anom_file
cdo eof,40 anom_file eval_file eof_file
cdo eofcoeff eof_file anom_file obase
```

Reference manual Interpolation

2.12. Interpolation

This section contains modules to interpolate datasets. There are several operators to interpolate horizontal fields to a new grid. Some of those operators can handle only 2D fields on a regular rectangular grid. Vertical interpolation of 3D variables is possible from hybrid model levels to height or pressure levels. Interpolation in time is possible between time steps and years.

Here is a short overview of all operators in this section:

remapbil Bilinear interpolation

genbil Generate bilinear interpolation weights

remapbic Bicubic interpolation

genbic Generate bicubic interpolation weights

remapnn Nearest neighbor remapping

gennn Generate nearest neighbor remap weights

remapdis Distance weighted average remapping

gendis Generate distance weighted average remap weights

remapcon First order conservative remapping

gencon Generate 1st order conservative remap weights

remapcon2 Second order conservative remapping

gencon2 Generate 2nd order conservative remap weights

remaplaf Largest area fraction remapping

genlaf Generate largest area fraction remap weights

remap Grid remapping

remapeta Remap vertical hybrid level

ml2pl Model to pressure level interpolation ml2hl Model to height level interpolation

ap2pl Air pressure to pressure level interpolation

gh2hl Geometric height to height level interpolation

intlevel Linear level interpolation

intlevel3d Linear level interpolation onto a 3D vertical coordinate

intlevelx3d like intlevel3d but with extrapolation

inttimeInterpolation between timestepsintntimeInterpolation between timesteps

intyear Interpolation between two years

Interpolation Reference manual


2.12.1. REMAPBIL - Bilinear interpolation


Synopsis


<operator>,grid infile outfile

Description

This module contains operators for a bilinear remapping of fields between grids in spherical coordinates. The interpolation is based on an adapted SCRIP library version. For a detailed description of the interpolation method see [SCRIP]. This interpolation method only works on quadrilateral curvilinear source grids. Below is a schematic illustration of the bilinear remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapbil Bilinear interpolation

Performs a bilinear interpolation on all input fields.

genbil Generate bilinear interpolation weights

Generates bilinear interpolation weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same source

grid.

Parameter

grid STRING Target grid description file or name

Environment

REMAP_EXTRAPOLATE This variable is used to switch the extrapolation feature 'on' or 'off'. By default the extrapolation is enabled for circular grids.

Example

Say infile contains fields on a quadrilateral curvilinear grid. To remap all fields bilinear to a Gaussian N32 grid, type:

cdo remapbil, n32 infile outfile

Reference manual Interpolation


2.12.2. REMAPBIC - Bicubic interpolation


Synopsis


< operator >, grid infile outfile

Description

This module contains operators for a bicubic remapping of fields between grids in spherical coordinates. The interpolation is based on an adapted SCRIP library version. For a detailed description of the interpolation method see [SCRIP]. This interpolation method only works on quadrilateral curvilinear source grids. Below is a schematic illustration of the bicubic remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapbic Bicubic interpolation

Performs a bicubic interpolation on all input fields.

genbic Generate bicubic interpolation weights

Generates bicubic interpolation weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same source grid.

Parameter

grid STRING Target grid description file or name

Environment

REMAP_EXTRAPOLATE This variable is used to switch the extrapolation feature 'on' or 'off'. By default the extrapolation is enabled for circular grids.

Example

Say infile contains fields on a quadrilateral curvilinear grid. To remap all fields bicubic to a Gaussian N32 grid, type:

cdo remapbic, n32 infile outfile

Interpolation Reference manual


2.12.3. REMAPNN - Nearest neighbor remapping


Synopsis


< operator >, grid infile outfile

Description

This module contains operators for a nearest neighbor remapping of fields between grids in spherical coordinates. Below is a schematic illustration of the nearest neighbor remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapnn Nearest neighbor remapping

Performs a nearest neighbor remapping on all input fields.

gennn Generate nearest neighbor remap weights

Generates nearest neighbor remapping weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same

source grid.

Parameter

grid STRING Target grid description file or name

Environment

REMAP_EXTRAPOLATE This variable is used to switch the extrapolation feature 'on' or 'off'. By

default the extrapolation is enabled for this remapping method.

CDO_GRIDSEARCH_RADIUS Grid search radius in degree, default 180 degree.


2.12.4. REMAPDIS - Distance weighted average remapping


Synopsis


remapdis,grid[,neighbors] infile outfile
gendis,grid infile outfile

Description

This module contains operators for an inverse distance weighted average remapping of the four nearest neighbor values of fields between grids in spherical coordinates. The interpolation is based on an adapted SCRIP library version. For a detailed description of the interpolation method see [SCRIP]. Below is a schematic illustration of the distance weighted average remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapdis Distance weighted average remapping

Performs an inverse distance weighted average remapping of the nearest neighbors

value on all input fields. The default number of nearest neighbors is 4.

gendis Generate distance weighted average remap weights

Generates distance weighted average remapping weights of the four nearest neighbor values for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this

remapping weights to a data file with the same source grid.

Parameter

grid STRING Target grid description file or name

neighbors INTEGER Number of nearest neighbors

Environment

REMAP_EXTRAPOLATE This variable is used to switch the extrapolation feature 'on' or 'off'. By

default the extrapolation is enabled for this remapping method.

CDO GRIDSEARCH RADIUS Grid search radius in degree, default 180 degree.

Interpolation Reference manual


2.12.5. REMAPCON - First order conservative remapping


Synopsis


< operator >, grid infile outfile

Description

This module contains operators for a first order conservative remapping of fields between grids in spherical coordinates. The operators in this module uses code from the YAC software package to compute the conservative remapping weights. For a detailed description of the interpolation method see [YAC]. The interpolation method is completely general and can be used for any grid on a sphere. The search algorithm for the conservative remapping requires that no grid cell occurs more than once. Below is a schematic illustration of the 1st order conservative remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapcon First order conservative remapping

Performs a first order conservative remapping on all input fields.

gencon Generate 1st order conservative remap weights

Generates first order conservative remapping weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same

source grid.

Parameter

grid STRING Target grid description file or name

Environment

CDO_REMAP_NORM

This variable is used to choose the normalization of the conservative interpolation. By default CDO_REMAP_NORM is set to 'fracarea'. 'fracarea' uses the sum of the non-masked source cell intersected areas to normalize each target cell field value. This results in a reasonable flux value but the flux is not locally conserved. The option 'destarea' uses the total target cell area to normalize each target cell field value. Local flux conservation is ensured, but unreasonable flux values may result.

REMAP_AREA_MIN This variable is used to set the minimum destination area fraction. The default of this variable is 0.0.

Example

Say infile contains fields on a quadrilateral curvilinear grid. To remap all fields conservative to a Gaussian N32 grid, type:

cdo remapcon,n32 infile outfile

Interpolation Reference manual


2.12.6. REMAPCON2 - Second order conservative remapping


Synopsis


<operator>,grid infile outfile

Description

This module contains operators for a second order conservative remapping of fields between grids in spherical coordinates. The interpolation is based on an adapted SCRIP library version. For a detailed description of the interpolation method see [SCRIP]. The interpolation method is completely general and can be used for any grid on a sphere. The search algorithm for the conservative remapping requires that no grid cell occurs more than once. Below is a schematic illustration of the 2nd order conservative remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remapcon2 Second order conservative remapping

Performs a second order conservative remapping on all input fields.

gencon2 Generate 2nd order conservative remap weights

Generates second order conservative remapping weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same source grid.

Parameter

grid STRING Target grid description file or name

Environment

CDO_REMAP_NORM

This variable is used to choose the normalization of the conservative interpolation. By default CDO_REMAP_NORM is set to 'fracarea'. 'fracarea' uses the sum of the non-masked source cell intersected areas to normalize each target cell field value. This results in a reasonable flux value but the flux is not locally conserved. The option 'destarea' uses the total target cell area to normalize each target cell field value. Local flux conservation is ensured, but unreasonable flux values may result.

REMAP_AREA_MIN This variable is used to set the minimum destination area fraction. The default of this variable is 0.0.

Note

The SCRIP conservative remapping method doesn't work correctly for some grid combinations.

Example

Say infile contains fields on a quadrilateral curvilinear grid. To remap all fields conservative (2nd order) to a Gaussian N32 grid, type:

cdo remapcon2,n32 infile outfile

Interpolation Reference manual


2.12.7. REMAPLAF - Largest area fraction remapping


Synopsis


<operator>,grid infile outfile

Description

This module contains operators for a largest area fraction remapping of fields between grids in spherical coordinates. The operators in this module uses code from the YAC software package to compute the largest area fraction. For a detailed description of the interpolation method see [YAC]. The interpolation method is completely general and can be used for any grid on a sphere. The search algorithm for this remapping method requires that no grid cell occurs more than once. Below is a schematic illustration of the largest area fraction conservative remapping:







The figure on the left side shows the input data on a regular lon/lat source grid and on the right side the remapped result on an unstructured triangular target grid. The figure in the middle shows the input data with the target grid. Grid cells with missing value are grey colored.

Operators

remaplaf Largest area fraction remapping

Performs a largest area fraction remapping on all input fields.

genlaf Generate largest area fraction remap weights

> Generates largest area fraction remapping weights for the first input field and writes the result to a file. The format of this file is NetCDF following the SCRIP convention. Use the operator remap to apply this remapping weights to a data file with the same

source grid.

Parameter

grid **STRING** Target grid description file or name

Environment

This variable is used to set the minimum destination area fraction. The default REMAP AREA MIN

of this variable is 0.0.

2.12.8. REMAP - Grid remapping

Synopsis

remap, grid, weights infile outfile

Description

Interpolation between different horizontal grids can be a very time-consuming process. Especially if the data are on an unstructured and/or a large grid. In this case the interpolation process can be split into two parts. Firstly the generation of the interpolation weights, which is the most time-consuming part. These interpolation weights can be reused for every remapping process with the operator remap. This operator remaps all input fields to a new horizontal grid. The remap type and the interpolation weights of one input grid are read from a NetCDF file. More weights are computed if the input fields are on different grids. The NetCDF file with the weights should follow the [SCRIP] convention. Normally these weights come from a previous call to one of the genXXX operators (e.g. genbil) or were created by the original SCRIP package.

Parameter

grid STRING Target grid description file or name

weights STRING Interpolation weights (SCRIP NetCDF file)

Environment

| CDO_REMAP_NORM | This variable is used to choose the normalization of the conservative interpolation. By default CDO_REMAP_NORM is set to 'fracarea'. 'fracarea' uses the sum of the non-masked source cell intersected areas to normalize each target cell field value. This results in a reasonable flux value but the flux is not locally conserved. The option 'destarea' uses the total target cell area to normalize each target cell field value. Local flux conservation is ensured, but unreasonable flux values may result. |
|-------------------|--|
| REMAP_EXTRAPOLATE | This variable is used to switch the extrapolation feature 'on' or 'off'. By default the extrapolation is enabled for remapdis, remapnn and for circular grids. |
| REMAP_AREA_MIN | This variable is used to set the minimum destination area fraction. The default of this variable is 0.0. |

Example

Say infile contains fields on a quadrilateral curvilinear grid. To remap all fields bilinear to a Gaussian N32 grid use:

Grid search radius in degree, default 180 degree.

```
cdo genbil,n32 infile remapweights.nc cdo remap,n32,remapweights.nc infile outfile
```

The result will be the same as:

CDO_GRIDSEARCH_RADIUS

```
cdo remapbil,n32 infile outfile
```

Interpolation Reference manual

2.12.9. REMAPETA - Remap vertical hybrid level

Synopsis

remapeta, vct[,oro] infile outfile

Description

This operator interpolates between different vertical hybrid levels. This include the preparation of consistent data for the free atmosphere. The procedure for the vertical interpolation is based on the HIRLAM scheme and was adapted from [INTERA]. The vertical interpolation is based on the vertical integration of the hydrostatic equation with few adjustments. The basic tasks are the following one:

- at first integration of hydrostatic equation
- extrapolation of surface pressure
- Planetary Boundary-Layer (PBL) proutfile interpolation
- interpolation in free atmosphere
- merging of both proutfiles
- final surface pressure correction

The vertical interpolation corrects the surface pressure. This is simply a cut-off or an addition of air mass. This mass correction should not influence the geostrophic velocity field in the middle troposhere. Therefore the total mass above a given reference level is conserved. As reference level the geopotential height of the 400 hPa level is used. Near the surface the correction can affect the vertical structure of the PBL. Therefore the interpolation is done using the potential temperature. But in the free atmosphere above a certain n (n=0.8 defining the top of the PBL) the interpolation is done linearly. After the interpolation both proutfiles are merged. With the resulting temperature/pressure correction the hydrostatic equation is integrated again and adjusted to the reference level finding the final surface pressure correction. A more detailed description of the interpolation can be found in [INTERA]. This operator requires all variables on the same horizontal grid.

Parameter

| vct | STRING | File name of an ASCII dataset with the vertical coordinate table |
|-----|--------|--|
| oro | STRING | File name with the orography (surf. geopotential) of the target dataset (optional) |

Environment

REMAPETA_PTOP Sets the minimum pressure level for condensation. Above this level the humidity is set to the constant 1.E-6. The default value is 0 Pa.

Note

The code numbers or the variable names of the required parameter have to follow the [ECHAM] convention.

Use the sinfo command to test if your vertical coordinate system is recognized as hybrid system.

In case remapeta complains about not finding any data on hybrid model levels you may wish to use the setzaxis command to generate a zaxis description which conforms to the ECHAM convention. See section "1.4 Z-axis description" for an example how to define a hybrid Z-axis.

Example

To remap between different hybrid model level data use:

```
cdo remapeta, vct infile outfile
```

Here is an example vct file with 19 hybrid model level:

| 0 | 0.000000000000000000 | 0.0000000000000000 | |
|----|---------------------------|----------------------|--|
| 1 | 2000.000000000000000000 | 0.00000000000000000 | |
| 2 | 4000.000000000000000000 | 0.00000000000000000 | |
| 3 | 6046.109375000000000000 | 0.00033899326808751 | |
| 4 | 8267.929687500000000000 | 0.00335718691349030 | |
| 5 | 10609.51171875000000000 | 0.01307003945112228 | |
| 6 | 12851.101562500000000000 | 0.03407714888453484 | |
| 7 | 14698.500000000000000000 | 0.07064980268478394 | |
| 8 | 15861.128906250000000000 | 0.12591671943664551 | |
| 9 | 16116.238281250000000000 | 0.20119541883468628 | |
| 10 | 15356.9218750000000000000 | 0.29551959037780762 | |
| 11 | 13621.460937500000000000 | 0.40540921688079834 | |
| 12 | 11101.558593750000000000 | 0.52493220567703247 | |
| 13 | 8127.14453125000000000 | 0.64610791206359863 | |
| 14 | 5125.140625000000000000 | 0.75969839096069336 | |
| 15 | 2549.96899414062500000 | 0.85643762350082397 | |
| 16 | 783.19506835937500000 | 0.92874687910079956 | |
| 17 | 0.00000000000000000 | 0.97298520803451538 | |
| 18 | 0.000000000000000000 | 0.99228149652481079 | |
| 19 | 0.00000000000000000 | 1.000000000000000000 | |
| | | | |

Interpolation Reference manual

2.12.10. VERTINTML - Vertical interpolation

Synopsis

ml2pl,plevels infile outfile ml2hl,hlevels infile outfile

Description

Interpolates 3D variables on hybrid sigma pressure level to pressure or height levels. The input file should contain the log. surface pressure or the surface pressure. To extrapolate the temperature, the surface geopotential is also needed. It is assumed that the geopotential heights are located on the hybrid layer interfaces. For the lowest layer of geopotential heights the surface geopotential is required. The pressure, temperature, geopotential height, and surface geopotential are identified by their GRIB1 code number or NetCDF CF standard name. Supported parameter tables are: WMO standard table number 2 and ECMWF local table number 128.

| CF standard name | Units | GRIB 1 code |
|----------------------|--------|-------------|
| surface_air_pressure | Pa | 134 |
| air_temperature | K | 130 |
| surface_geopotential | m2 s-2 | 129 |
| geopotential_height | m | 156 |

Use the alias ml2plx/ml2hlx or the environment variable EXTRAPOLATE to extrapolate missing values. This operator requires all variables on the same horizontal grid. Missing values in the input data are not supported.

Operators

ml2pl Model to pressure level interpolation

Interpolates 3D variables on hybrid sigma pressure level to pressure level.

ml2hl Model to height level interpolation

Interpolates 3D variables on hybrid sigma pressure level to height level. The procedure is the same as for the operator ml2pl except for the pressure levels being calculated from the heights by: plevel = 101325 * exp(hlevel/ - 7000)

Parameter

plevels FLOAT Pressure levels in pascalhlevels FLOAT Height levels in meter

Environment

EXTRAPOLATE If set to 1 extrapolate missing values.

Example

To interpolate hybrid model level data to pressure levels of 925, 850, 500 and 200 hPa use:

cdo ml2pl,92500,85000,50000,20000 infile outfile

2.12.11. VERTINTAP - Vertical pressure interpolation

Synopsis

ap2pl,plevels infile outfile

Description

Interpolate 3D variables on hybrid sigma height coordinates to pressure levels. The input file must contain the 3D air pressure in pascal. The air pressure is identified by the NetCDF CF standard name air_pressure. Use the alias ap2plx or the environment variable EXTRAPOLATE to extrapolate missing values. This operator requires all variables on the same horizontal grid.

Parameter

plevels FLOAT Comma-separated list of pressure levels in pascal

Environment

EXTRAPOLATE If set to 1 extrapolate missing values.

Note

This is a specific implementation for NetCDF files from the ICON model, it may not work with data from other sources.

Example

To interpolate 3D variables on hybrid sigma height level to pressure levels of 925, 850, 500 and 200 hPa use:

cdo ap2pl,92500,85000,50000,20000 infile outfile

Interpolation Reference manual

2.12.12. VERTINTGH - Vertical height interpolation

Synopsis

gh2hl, hlevels infile outfile

Description

Interpolate 3D variables on hybrid sigma height coordinates to height levels. The input file must contain the 3D geometric height in meter. The geometric height is identified by the NetCDF CF standard name <code>geometric_height_at_full_level_center</code>. Use the alias <code>gh2hlx</code> or the environment variable <code>EXTRAPOLATE</code> to extrapolate missing values. This operator requires all variables on the same horizontal grid.

Parameter

hlevels FLOAT Comma-separated list of height levels in meter

Environment

EXTRAPOLATE If set to 1 extrapolate missing values.

Note

This is a specific implementation for NetCDF files from the ICON model, it may not work with data from other sources.

Example

To interpolate 3D variables on hybrid sigma height level to height levels of 20, 100, 500, 1000, 5000, 10000 and 20000 meter use:

cdo gh2hl,20,100,500,1000,5000,10000,20000 infile outfile

2.12.13. INTLEVEL - Linear level interpolation

Synopsis

intlevel,levels infile outfile

Description

This operator performs a linear vertical interpolation of 3D variables.

Parameter

levels FLOAT Comma-separated list of target levels

Example

To interpolate 3D variables on height levels to a new set of height levels use:

cdo intlevel, 10, 50, 100, 500, 1000 infile outfile

2.12.14. INTLEVEL3D - Linear level interpolation from/to 3D vertical coordinates

Synopsis

<operator>,tgtcoordinate infile1 infile2 outfile

Description

This operator performs a linear vertical interpolation of 3D variables fields with given 3D vertical coordinates. infile1 contains the 3D data variables and infile2 the 3D vertical source coordinate. The parameter tgtcoordinate is a datafile with the 3D vertical target coordinate.

Operators

intlevel3d Linear level interpolation onto a 3D vertical coordinate

intlevelx3d like intlevel3d but with extrapolation

Parameter

tgtcoordinate STRING filename for 3D vertical target coordinates

Example

To interpolate 3D variables from one set of 3D height levels into another one where

- infile2 contains a single 3D variable, which represents the source 3D vertical coordinate
- infile1 contains the source data, which the vertical coordinate from infile2 belongs to
- tgtcoordinate only contains the target 3D height levels

cdo intlevel3d,tgtcoordinate infile1 infile2 outfile

Interpolation Reference manual

2.12.15. INTTIME - Time interpolation

Synopsis

```
inttime,date,time[,inc] infile outfile
intntime,n infile outfile
```

Description

This module performs linear interpolation between timesteps. Interpolation is only performed if both values exist. If both values are missing values, the result is also a missing value. If only one value exists, it is taken if the time weighting is greater than or equal to 0.5. So no new value will be created at existing time steps, if the value is missing there.

Operators

inttime Interpolation between timesteps

This operator creates a new dataset by linear interpolation between timesteps. The

user has to define the start date/time with an optional increment.

intntime Interpolation between timesteps

This operator performs linear interpolation between timesteps. The user has to define

the number of timesteps from one timestep to the next.

Parameter

| date | STRING | Start date (format YYYY-MM-DD) |
|------|------------------|---|
| time | STRING | Start time (format hh:mm:ss) |
| inc | STRING 0hour] | Optional increment (seconds, minutes, hours, days, months, years) [default: |
| n | INTEGER | Number of timesteps from one timestep to the next |

Example

Assumed a 6 hourly dataset starts at 1987-01-01 12:00:00. To interpolate this time series to a one hourly dataset use:

 $\verb|cdo| inttime|, 1987-01-01|, 12:00:00|, 1 \\ \verb|hour| infile| outfile|$

2.12.16. INTYEAR - Year interpolation

Synopsis

intyear,years infile1 infile2 obase

Description

This operator performs linear interpolation between two years, timestep by timestep. The input files need to have the same structure with the same variables. The output files will be named <obsep><yyyy><suffix> where yyyy will be the year and suffix is the filename extension derived from the file format.

Parameter

years INTEGER Comma-separated list or first/last[/inc] range of years

Environment

CDO_FILE_SUFFIX Set the default file suffix. This suffix will be added to the output file names

instead of the filename extension derived from the file format. Set this variable

to NULL to disable the adding of a file suffix.

Note

This operator needs to open all output files simultaneously. The maximum number of open files depends on the operating system!

Example

Assume there are two monthly mean datasets over a year. The first dataset has 12 timesteps for the year 1985 and the second one for the year 1990. To interpolate the years between 1985 and 1990 month by month use:

```
cdo intyear, 1986, 1987, 1988, 1989 infile1 infile2 year
```

Example result of 'dir year*' for NetCDF datasets:

year1986.nc year1987.nc year1988.nc year1989.nc

Transformation Reference manual

2.13. Transformation

This section contains modules to perform spectral transformations. $\,$

Here is a short overview of all operators in this section:

| $ m sp2gp \ gp2sp$ | Spectral to gridpoint Gridpoint to spectral |
|--------------------|---|
| sp2sp | Spectral to spectral |
| dv2ps | D and V to velocity potential and stream function |
| dv2uv uv2dv | Divergence and vorticity to U and V wind U and V wind to divergence and vorticity |
| fourier | Fourier transformation |

Reference manual Transformation

2.13.1. SPECTRAL - Spectral transformation

Synopsis

<operator>[,gridtype] infile outfile

Description

This module transforms fields on a global regular Gaussian grid to spectral coefficients and vice versa. The transformation is achieved by applying Fast Fourier Transformation (FFT) first and direct Legendre Transformation afterwards in gp2sp. In sp2gp the inverse Legendre Transformation and inverse FFT are used. Missing values are not supported.

The relationship between the spectral resolution, governed by the truncation number T, and the grid resolution depends on the number of grid points at which the shortest wavelength field is represented. For a grid with 2N points between the poles (so 4N grid points in total around the globe) the relationship is:

linear grid: the shortest wavelength is represented by 2 grid points $\rightarrow 4N \simeq 2(TL + 1)$

quadratic grid: the shortest wavelength is represented by 3 grid points \rightarrow 4N \simeq 3(TQ + 1)

cubic grid: the shortest wavelength is represented by 4 grid points \rightarrow 4N \simeq 4(TC + 1)

The quadratic grid is used by ECHAM and ERA15. ERA40 is using a linear Gaussian grid reflected by the TL notation.

The following table shows the calculation of the number of latitudes and the triangular truncation for the different grid types:

| Gridtype | Number of latitudes: nlat | Triangular truncation: ntr |
|-----------|---------------------------|----------------------------|
| linear | NINT((ntr*2 + 1)/2) | (nlat*2 - 1) / 2 |
| quadratic | NINT((ntr*3 + 1)/2) | (nlat*2 - 1) / 3 |
| cubic | NINT((ntr*4 + 1)/2) | (nlat*2 - 1) / 4 |

Operators

sp2gp Spectral to gridpoint

Convert all spectral fields to a global regular Gaussian grid.

gp2sp Gridpoint to spectral

Convert all Gaussian gridpoint fields to spectral fields.

Parameter

gridtype STRING Type of the grid: quadratic, linear, cubic (default: quadratic)

Note

To speed up the calculations, the Legendre polynoms are kept in memory. This requires a relatively large amount of memory. This is for example 12GB for T1279 data.

Example

To transform spectral coefficients from T106 to N80 Gaussian grid use:

cdo sp2gp infile outfile

To transform spectral coefficients from TL159 to N80 Gaussian grid use:

cdo sp2gp, linear infile outfile

Transformation Reference manual

2.13.2. SPECCONV - Spectral conversion

Synopsis

 $\mathbf{sp2sp}$, trunc infile outfile

Description

Changed the triangular truncation of all spectral fields. This operator performs downward conversion by cutting the resolution. Upward conversions are achieved by filling in zeros.

Parameter

trunc INTEGER New spectral resolution

2.13.3. WIND2 - D and V to velocity potential and stream function

Synopsis

dv2ps infile outfile

Description

Calculate spherical harmonic coefficients of velocity potential and stream function from spherical harmonic coefficients of relative divergence and vorticity. The divergence and vorticity need to have the names sd and svo or code numbers 155 and 138.

Reference manual Transformation

2.13.4. WIND - Wind transformation

Synopsis

<operator>[,gridtype] infile outfile

Description

This module converts relative divergence and vorticity to U and V wind and vice versa. Divergence and vorticity are spherical harmonic coefficients in spectral space and U and V are on a global regular Gaussian grid. The Gaussian latitudes need to be ordered from north to south. Missing values are not supported.

The relationship between the spectral resolution, governed by the truncation number T, and the grid resolution depends on the number of grid points at which the shortest wavelength field is represented. For a grid with 2N points between the poles (so 4N grid points in total around the globe) the relationship is:

linear grid: the shortest wavelength is represented by 2 grid points \rightarrow 4N \simeq 2(TL + 1)

quadratic grid: the shortest wavelength is represented by 3 grid points $\rightarrow 4N \simeq 3(TQ + 1)$

cubic grid: the shortest wavelength is represented by 4 grid points \rightarrow 4N \simeq 4(TC + 1)

The quadratic grid is used by ECHAM and ERA15. ERA40 is using a linear Gaussian grid reflected by the TL notation.

The following table shows the calculation of the number of latitudes and the triangular truncation for the different grid types:

| Gridtype | Number of latitudes: nlat | Triangular truncation: ntr |
|-----------|---------------------------|----------------------------|
| linear | NINT((ntr*2 + 1)/2) | (nlat*2 - 1) / 2 |
| quadratic | NINT((ntr*3 + 1)/2) | (nlat*2 - 1) / 3 |
| cubic | NINT((ntr*4 + 1)/2) | (nlat*2 - 1) / 4 |

Operators

 ${f dv2uv}$ Divergence and vorticity to U and V wind

Calculate U and V wind on a Gaussian grid from spherical harmonic coefficients of relative divergence and vorticity. The divergence and vorticity need to have the names sd and svo or code numbers 155 and 138.

uv2dv U and V wind to divergence and vorticity

Calculate spherical harmonic coefficients of relative divergence and vorticity from U and V wind. The U and V wind need to be on a Gaussian grid and need to have the names u and v or the code numbers 131 and 132.

Parameter

gridtype STRING Type of the grid: quadratic, linear (default: quadratic)

Note

To speed up the calculations, the Legendre polynoms are kept in memory. This requires a relatively large amount of memory. This is for example 12GB for T1279 data.

Transformation Reference manual

Example

Assume a dataset has at least spherical harmonic coefficients of divergence and vorticity. To transform the spectral divergence and vorticity to U and V wind on a Gaussian grid use:

cdo dv2uv infile outfile

Reference manual Transformation

2.13.5. FOURIER - Fourier transformation

Synopsis

fourier, epsilon infile outfile

Description

The fourier operator performs the fourier transformation or the inverse fourier transformation of all input fields. If the number of timesteps is a power of 2 then the algorithm of the Fast Fourier Transformation (FFT) is used.

It is

$$o(t,x) = \frac{1}{\sqrt{n}} \sum_{j=0}^{n-1} i(t,x) e^{\epsilon 2\pi i j}$$

where a user given epsilon = -1 leads to the forward transformation and a user given epsilon = 1 leads to the backward transformation.

If the input stream infile consists only of complex fields, then the fields of outfile, computed by

are the same than that of infile. For real input files see function retocomplex.

Parameter

epsilon INTEGER -1: forward transformation; 1: backward transformation

Note

Complex numbers can only be stored in NetCDF4 and EXTRA format.

Import/Export Reference manual

2.14. Import/Export

This section contains modules to import and export data files which can not read or write directly with CDO.

Here is a short overview of all operators in this section:

import_cmsaf Import CM-SAF HDF5 files

import_amsr Import AMSR binary files

input ASCII input

inputsrv SERVICE ASCII input inputext EXTRA ASCII input

outputASCII outputoutputfFormatted outputoutputintInteger output

outputsrvSERVICE ASCII outputoutputextEXTRA ASCII output

outputtab Table output

gmtxyz GMT xyz format

gmtcells GMT multiple segment format

Reference manual Import/Export

2.14.1. IMPORTBINARY - Import binary data sets

Synopsis

```
import_binary infile outfile
```

Description

This operator imports gridded binary data sets via a GrADS data descriptor file. The GrADS data descriptor file contains a complete description of the binary data as well as instructions on where to find the data and how to read it. The descriptor file is an ASCII file that can be created easily with a text editor. The general contents of a gridded data descriptor file are as follows:

- Filename for the binary data
- Missing or undefined data value
- Mapping between grid coordinates and world coordinates
- Description of variables in the binary data set

A detailed description of the components of a GrADS data descriptor file can be found in [GrADS]. Here is a list of the supported components: BYTESWAPPED, CHSUB, DSET, ENDVARS, FILE-HEADER, HEADERBYTES, OPTIONS, TDEF, TITLE, TRAILERBYTES, UNDEF, VARS, XDEF, XYHEADER, YDEF, ZDEF

Note

Only 32-bit IEEE floats are supported for standard binary files!

Example

To convert a binary data file to NetCDF use:

```
cdo -f nc import_binary infile.ctl outfile.nc
```

Here is an example of a GrADS data descriptor file:

```
DSET ^infile.bin
OPTIONS sequential
UNDEF -9e+33
XDEF 360 LINEAR -179.5 1
YDEF 180 LINEAR -89.5 1
ZDEF 1 LINEAR 1 1
TDEF 1 LINEAR 00:00 Z15jun1989 12hr
VARS 1
param 1 99 description of the variable
ENDVARS
```

The binary data file infile bin contains one parameter on a global 1 degree lon/lat grid written with FORTRAN record length headers (sequential).

Import/Export Reference manual

2.14.2. IMPORTCMSAF - Import CM-SAF HDF5 files

Synopsis

import_cmsaf infile outfile

Description

This operator imports gridded CM-SAF (Satellite Application Facility on Climate Monitoring) HDF5 files. CM-SAF exploits data from polar-orbiting and geostationary satellites in order to provide climate monitoring products of the following parameters:

Cloud parameters: cloud fraction (CFC), cloud type (CTY), cloud phase (CPH), cloud top height, pressure and temperature (CTH,CTP,CTT), cloud optical thickness (COT), cloud water path (CWP).

Surface radiation components: Surface albedo (SAL); surface incoming (SIS) and net (SNS) shortwave radiation; surface downward (SDL) and outgoing (SOL) longwave radiation, surface net longwave radiation (SNL) and surface radiation budget (SRB).

Top-of-atmosphere radiation components: Incoming (TIS) and reflected (TRS) solar radiative flux at top-of-atmosphere. Emitted thermal radiative flux at top-of-atmosphere (TET).

Water vapour: Vertically integrated water vapour (HTW), layered vertically integrated water vapour and layer mean temperature and relative humidity for 5 layers (HLW), temperature and mixing ratio at 6 pressure levels.

Daily and monthly mean products can be ordered via the CM-SAF web page (www.cmsaf.eu). Products with higher spatial and temporal resolution, i.e. instantaneous swath-based products, are available on request (contact.cmsaf@dwd.de). All products are distributed free-of-charge. More information on the data is available on the CM-SAF homepage (www.cmsaf.eu).

Daily and monthly mean products are provided in equal-area projections. **CDO** reads the projection parameters from the metadata in the HDF5-headers in order to allow spatial operations like remapping. For spatial operations with instantaneous products on original satellite projection, additional files with arrays of latitudes and longitudes are needed. These can be obtained from CM-SAF together with the data.

Note

To use this operator, it is necessary to build **CDO** with HDF5 support (version 1.6 or higher). The PROJ library (version 5.0 or higher) is needed for full support of the remapping functionality.

Example

A typical sequence of commands with this operator could look like this:

```
cdo -f nc remapbil,r360x180 -import_cmsaf cmsaf_product.hdf output.nc
```

(bilinear remapping to a predefined global grid with 1 deg resolution and conversion to NetCDF).

If you work with CM-SAF data on original satellite project, an additional file with information on geolocation is required, to perform such spatial operations:

```
cdo -f nc remapbil,r720x360 -setgrid,cmsaf_latlon.h5 -import_cmsaf cmsaf.hdf out.nc
```

Some CM-SAF data are stored as scaled integer values. For some operations, it could be desirable (or necessary) to increase the accuracy of the converted products:

Reference manual Import/Export

```
cdo -b f32 -f nc fldmean -sellonlatbox,0,10,0,10 -remapbil,r720x360 \
-import_cmsaf cmsaf_product.hdf output.nc
```

2.14.3. IMPORTAMSR - Import AMSR binary files

Synopsis

import_amsr infile outfile

Description

This operator imports gridded binary AMSR (Advanced Microwave Scanning Radiometer) data. The binary data files are available from the AMSR ftp site (ftp://ftp.ssmi.com/amsre). Each file consists of twelve (daily) or five (averaged) 0.25 x 0.25 degree grid (1440,720) byte maps. For daily files, six daytime maps in the following order, Time (UTC), Sea Surface Temperature (SST), 10 meter Surface Wind Speed (WSPD), Atmospheric Water Vapor (VAPOR), Cloud Liquid Water (CLOUD), and Rain Rate (RAIN), are followed by six nighttime maps in the same order. Time-Averaged files contain just the geophysical layers in the same order [SST, WSPD, VAPOR, CLOUD, RAIN]. More information to the data is available on the AMSR homepage http://www.remss.com/amsr.

Example

To convert monthly binary AMSR files to NetCDF use:

cdo -f nc amsre_yyyymmv5 amsre_yyyymmv5.nc

Import/Export Reference manual

2.14.4. INPUT - Formatted input

Synopsis

input,grid[,zaxis] outfile
inputsrv outfile
inputext outfile

Description

This module reads time series of one 2D variable from standard input. All input fields need to have the same horizontal grid. The format of the input depends on the chosen operator.

Operators

input ASCII input

Reads fields with ASCII numbers from standard input and stores them in outfile. The numbers read are exactly that ones which are written out by the output operator.

inputsrv SERVICE ASCII input

Reads fields with ASCII numbers from standard input and stores them in outfile. Each field should have a header of 8 integers (SERVICE likely). The numbers that are read are exactly that ones which are written out by the outputsrv operator.

inputext EXTRA ASCII input

Read fields with ASCII numbers from standard input and stores them in outfile. Each field should have header of 4 integers (EXTRA likely). The numbers read are exactly that ones which are written out by the outputext operator.

Parameter

grid STRING Grid description file or name

zaxis STRING Z-axis description file

Example

Assume an ASCII dataset contains a field on a global regular grid with 32 longitudes and 16 latitudes (512 elements). To create a GRIB1 dataset from the ASCII dataset use:

cdo -f grb input,r32x16 outfile.grb < my_ascii_data</pre>

Reference manual Import/Export

2.14.5. OUTPUT - Formatted output

Synopsis

output infiles
outputf,format[,nelem] infiles
outputint infiles
outputsrv infiles
outputext infiles

Description

This module prints all values of all input datasets to standard output. All input fields need to have the same horizontal grid. All input files need to have the same structure with the same variables. The format of the output depends on the chosen operator.

Operators

output ASCII output

Prints all values to standard output. Each row has 6 elements with the C-style format

"%13.6g".

outputf Formatted output

Prints all values to standard output. The format and number of elements for each row

have to be specified by the parameters format and nelem. The default for nelem is 1.

outputint Integer output

Prints all values rounded to the nearest integer to standard output.

outputsrv SERVICE ASCII output

Prints all values to standard output. Each field with a header of 8 integers (SERVICE

likely).

outputext EXTRA ASCII output

Prints all values to standard output. Each field with a header of 4 integers (EXTRA

likely).

Parameter

format STRING C-style format for one element (e.g. %13.6g)

nelem INTEGER Number of elements for each row (default: nelem = 1)

Example

To print all field elements of a dataset formatted with "%8.4g" and 8 values per line use:

cdo outputf,%8.4g,8 infile

Example result of a dataset with one field on 64 grid points:

| 261.7 | 262 | 257.8 | 252.5 | 248.8 | 247.7 | 246.3 | 246.1 |
|-------|-------|-------|-------|-------|-------|-------|-------|
| 250.6 | 252.6 | 253.9 | 254.8 | 252 | 246.6 | 249.7 | 257.9 |
| 273.4 | 266.2 | 259.8 | 261.6 | 257.2 | 253.4 | 251 | 263.7 |
| 267.5 | 267.4 | 272.2 | 266.7 | 259.6 | 255.2 | 272.9 | 277.1 |
| 275.3 | 275.5 | 276.4 | 278.4 | 282 | 269.6 | 278.7 | 279.5 |
| 282.3 | 284.5 | 280.3 | 280.3 | 280 | 281.5 | 284.7 | 283.6 |
| 292.9 | 290.5 | 293.9 | 292.6 | 292.7 | 292.8 | 294.1 | 293.6 |
| 293.8 | 292.6 | 291.2 | 292.6 | 293.2 | 292.8 | 291 | 291.2 |
| | | | | | | | |

Import/Export Reference manual

2.14.6. OUTPUTTAB - Table output

Synopsis

outputtab, params infiles outfile

Description

This operator prints a table of all input datasets to standard output. infiles is an arbitrary number of input files. All input files need to have the same structure with the same variables on different timesteps. All input fields need to have the same horizontal grid.

The contents of the table depends on the chosen parameters. The format of each table parameter is keyname[:len]. len is the optional length of a table entry. Here is a list of all valid keynames:

| Keyname | Type | Description |
|----------|---------|--|
| value | FLOAT | Value of the variable [len:8] |
| name | STRING | Name of the variable [len:8] |
| param | STRING | Parameter ID (GRIB1: code[.tabnum]; GRIB2: num[.cat[.dis]]) [len:11] |
| code | INTEGER | Code number [len:4] |
| x | FLOAT | X coordinate of the original grid [len:6] |
| У | FLOAT | Y coordinate of the original grid [len:6] |
| lon | FLOAT | Longitude coordinate in degrees [len:6] |
| lat | FLOAT | Latitude coordinate in degrees [len:6] |
| lev | FLOAT | Vertical level [len:6] |
| xind | INTEGER | Grid x index [len:4] |
| yind | INTEGER | Grid y index [len:4] |
| timestep | INTEGER | Timestep number [len:6] |
| date | STRING | Date (format YYYY-MM-DD) [len:10] |
| time | STRING | Time (format hh:mm:ss) [len:8] |
| year | INTEGER | Year [len:5] |
| month | INTEGER | Month [len:2] |
| day | INTEGER | Day [len:2] |
| nohead | INTEGER | Disable output of header line |

Parameter

params STRING Comma-separated list of keynames, one for each column of the table

Example

To print a table with name, date, lon, lat and value information use:

```
cdo outputtab, name, date, lon, lat, value infile
```

Here is an example output of a time series with the yearly mean temperatur at lon=10/lat=53.5:

| # | name | date | lon | lat | value |
|---|-----------|----------------|-----|------|---------|
| | tsurf | 1991 - 12 - 31 | 10 | 53.5 | 8.83903 |
| | tsurf | 1992 - 12 - 31 | 10 | 53.5 | 8.17439 |
| | tsurf | 1993 - 12 - 31 | 10 | 53.5 | 7.90489 |
| | tsurf | 1994 - 12 - 31 | 10 | 53.5 | 10.0216 |
| | t s u r f | 1995 - 12 - 31 | 10 | 53.5 | 9.07798 |

Reference manual Import/Export

2.14.7. OUTPUTGMT - GMT output

Synopsis

< operator > infile

Description

This module prints the first field of the input dataset to standard output. The output can be used to generate 2D Lon/Lat plots with [GMT]. The format of the output depends on the chosen operator.

Operators

gmtxyz GMT xyz format

The operator exports the first field to the GMT xyz ASCII format. The output can be

used to create contour plots with the GMT module ps contour.


gmtcells GMT multiple segment format

The operator exports the first field to the GMT multiple segment ASCII format. The output can be used to create shaded gridfill plots with the GMT module psxy.

Example

1) GMT shaded contour plot of a global temperature field with a resolution of 4 degree. The contour interval is 3 with a rainbow color table.


```
cdo gmtxyz temp > data.gmt
makecpt -T213/318/3 -Crainbow > gmt.cpt
pscontour -K -JQ0/10i -Rd -I -Cgmt.cpt data.gmt > gmtplot.ps
pscoast -O -J -R -Dc -W -B40g20 >> gmtplot.ps
```



2) GMT shaded gridfill plot of a global temperature field with a resolution of 4 degree. The contour interval is 3 with a rainbow color table.

Import/Export Reference manual

```
cdo gmtcells temp > data.gmt
makecpt -T213/318/3 -Crainbow > gmt.cpt
psxy -K -JQ0/10i -Rd -L -Cgmt.cpt -m data.gmt > gmtplot.ps
pscoast -O -J -R -Dc -W -B40g20 >> gmtplot.ps
```



Reference manual Miscellaneous

2.15. Miscellaneous

This section contains miscellaneous modules which do not fit to the other sections before.

Here is a short overview of all operators in this section:

gradsdes GrADS data descriptor file

after ECHAM standard post processor

bandpassBandpass filteringlowpassLowpass filteringhighpassHighpass filtering

gridarea Grid cell area gridweights Grid cell weights

smoothsmooth grid pointssmooth99 point smoothing

setvals Set list of old values to new values

setrtoc Set range to constant

setrtoc2 Set range to constant others to constant2

const Create a constant field

random Create a field with random numbers topo Create a field with topography

seq Create a time series

stdatm Create values for pressure and temperature for hydrostatic atmosphere

timsort Sort over the time

uvDestagDestaggering of u/v wind componentsrotuvNorthRotate u/v wind to North pole.projuvLatLonCylindrical Equidistant projection

rotuvb Backward rotation

mrotuvb Backward rotation of MPIOM data

mastrfu Mass stream function

sealevelpressure
gheight
Sea level pressure
Geopotential height

adisit Potential temperature to in-situ temperatureadipot In-situ temperature to potential temperature

rhopot Calculates potential density

histcountHistogram counthistsumHistogram sumhistmeanHistogram meanhistfreqHistogram frequency

sethalo Set the left and right bounds of a field

Miscellaneous Reference manual

wct Windchill temperature

fdns Frost days where no snow index per time period

strwin Strong wind days index per time period

strbre Strong breeze days index per time period

strgal Strong gale days index per time period

hurr Hurricane days index per time period

cmorlite CMOR lite

verifygrid Verify grid coordinates

Reference manual Miscellaneous

2.15.1. GRADSDES - GrADS data descriptor file

Synopsis

gradsdes[,mapversion] infile

Description

Creates a [GrADS] data descriptor file. Supported file formats are GRIB1, NetCDF, SERVICE, EXTRA and IEG. For GRIB1 files the GrADS map file is also generated. For SERVICE and EXTRA files the grid have to be specified with the **CDO** option '-g <grid>'. This module takes infile in order to create filenames for the descriptor (infile.ctl) and the map (infile.gmp) file.

Parameter

mapversion

INTEGER Format version of the GrADS map file for GRIB1 datasets. Use 1 for a machine specific version 1 GrADS map file, 2 for a machine independent version 2 GrADS map file and 4 to support GRIB files >2GB. A version 2 map file can be used only with GrADS version 1.8 or newer. A version 4 map file can be used only with GrADS version 2.0 or newer. The default is 4 for files >2GB, otherwise 2.

Example

To create a GrADS data descriptor file from a GRIB1 dataset use:

```
cdo gradsdes infile.grb
```

This will create a descriptor file with the name infile.ctl and the map file infile.gmp.

Assumed the input GRIB1 dataset has 3 variables over 12 timesteps on a Gaussian N16 grid. The contents of the resulting GrADS data description file is approximately:

```
^infile.grb
DSET
DTYPE
      GRIB
INDEX
        `infile.gmp
XDEF 64 LINEAR 0.000000 5.625000
YDEF 32 LEVELS -85.761 -80.269 -74.745 -69.213 -63.679
                                                         -58.143
                -52.607 -47.070 -41.532 -35.995
                                                         -24.920
                                                 -30.458
                -19.382 -13.844
                                 -8.307
                                          -2.769
                                                   2.769
                                                           8.307
                 13.844
                         19.382
                                 24.920
                                         30.458
                                                  35.995
                                                          41.532
                 47.070
                         52.607
                                 58.143
                                         63.679
                                                  69.213
                                                          74.745
                 80.269
                         85.761
ZDEF 4 LEVELS 925 850 500 200
TDEF 12 LINEAR 12:00 Z1jan1987 1mo
TITLE infile.grb T21 grid
OPTIONS yrev
UNDEF -9e+33
VARS 3
            129,1,0
                     surface geopotential (orography)
                                                         [m^2/s^2]
geosp
t
         4
            130,99,0
                      temperature [K]
tslm1
            139,1,0
                     surface temperature of land
ENDVARS
```

Miscellaneous Reference manual

2.15.2. AFTERBURNER - ECHAM standard post processor

Synopsis

```
after[,vct] infiles outfile
```

Description

The "afterburner" is the standard post processor for [ECHAM] GRIB and NetCDF data which provides the following operations:

- Extract specified variables and levels
- Compute derived variables
- Transform spectral data to Gaussian grid representation
- Vertical interpolation to pressure levels
- Compute temporal means

This operator reads selection parameters as namelist from stdin. Use the UNIX redirection "<namelistfile" to read the namelist from file.

The input files can't be combined with other **CDO** operators because of an optimized reader for this operator.

Namelist

Namelist parameter and there defaults:

```
\label{eq:type-0} \texttt{TYPE=0}, \ \texttt{CODE=-1}, \ \texttt{LEVEL=-1}, \ \texttt{INTERVAL=0}, \ \texttt{MEAN=0}, \ \texttt{EXTRAPOLATE=1}
```

TYPE controls the transformation and vertical interpolation. Transforming spectral data to Gaussian grid representation and vertical interpolation to pressure levels are performed in a chain of steps. The TYPE parameter may be used to stop the chain at a certain step. Valid values are:

```
TYPE = 0 : Hybrid
                      level spectral coefficients
TYPE = 10 : Hybrid
                      level fourier
                                     coefficients
TYPE = 11 : Hybrid
                      level zonal mean sections
TYPE = 20 : Hybrid
                      level gauss grids
TYPE = 30 : Pressure level gauss grids
                                    coefficients
     = 40 : Pressure level fourier
     = 41 : Pressure level zonal mean sections
TYPE
     = 50 : Pressure level spectral coefficients
TYPE
     = 60 : Pressure level fourier
                                     coefficients
TYPE
     = 61 : Pressure level zonal mean sections
TYPE = 70 : Pressure level gauss grids
```

Vorticity, divergence, streamfunction and velocity potential need special treatment in the vertical transformation. They are not available as types 30, 40 and 41. If you select one of these combinations, type is automatically switched to the equivalent types 70, 60 and 61. The type of all other variables will be switched too, because the type is a global parameter.

CODE selects the variables by the ECHAM GRIB1 code number (1-255). The default value **-1** processes all detected codes. Derived variables computed by the afterburner:

Reference manual Miscellaneous

| Code | Name | Longname | Units | Level | Needed Codes |
|------|---------------------------|-------------------------------|---------|-------------|----------------------------------|
| 34 | low_cld | low cloud | | single | 223 on modellevel |
| 35 | mid _cld | mid cloud | | single | 223 on modellevel |
| 36 | hih_cld | high cloud | | single | 223 on modellevel |
| 131 | u | u-velocity | m/s | atm (ml+pl) | 138, 155 |
| 132 | v | v-velocity | m/s | atm (ml+pl) | 138, 155 |
| 135 | omega | vertical velocity | Pa/s | atm (ml+pl) | 138, 152, 155 |
| 148 | stream | streamfunction | m^2/s | atm (ml+pl) | 131, 132 |
| 149 | velopot | velocity potential | m^ 2/s | atm (ml+pl) | 131, 132 |
| 151 | slp | mean sea level pressure | Pa | surface | 129, 130, 152 |
| 156 | geopoth | geopotential height | m | atm (ml+pl) | 129, 130, 133, 152 |
| 157 | rhumidity | relative humidity | | atm (ml+pl) | 130, 133, 152 |
| 189 | sclfs | surface solar cloud forcing | | surface | 176-185 |
| 190 | tclfs | surface thermal cloud forcing | | surface | 177-186 |
| 191 | sclf0 | top solar cloud forcing | | surface | 178-187 |
| 192 | tclf0 | top thermal cloud forcing | | surface | 179-188 |
| 259 | windspeed | windspeed | m/s | atm (ml+pl) | $\operatorname{sqrt}(u^*u+v^*v)$ |
| 260 | precip | total precipitation | | surface | 142+143 |

LEVEL selects the hybrid or pressure levels. The allowed values depends on the parameter **TYPE**. The default value **-1** processes all detected levels.

INTERVAL selects the processing interval. The default value 0 process data on monthly intervals. INTERVAL=1 sets the interval to daily.

MEAN=1 compute and write monthly or daily mean fields. The default value 0 writes out all timesteps.

EXTRAPOLATE=0 switch of the extrapolation of missing values during the interpolation from model to pressure level (only available with MEAN=0 and TYPE=30). The default value 1 extrapolate missing values.

Possible combinations of TYPE, CODE and MEAN:

| TYPE | CODE | MEAN |
|---------|------------------------|------|
| 0/10/11 | 130 temperature | 0 |
| 0/10/11 | 131 u-velocity | 0 |
| 0/10/11 | 132 v-velocity | 0 |
| 0/10/11 | 133 specific humidity | 0 |
| 0/10/11 | 138 vorticity | 0 |
| 0/10/11 | 148 streamfunction | 0 |
| 0/10/11 | 149 velocity potential | 0 |
| 0/10/11 | 152 LnPs | 0 |
| 0/10/11 | 155 divergence | 0 |
| >11 | all codes | 0/1 |

Parameter

vct STRING File with VCT in ASCII format

Example

To interpolate ECHAM hybrid model level data to pressure levels of 925, 850, 500 and 200 hPa, use:

```
cdo after infile outfile << EON
   TYPE=30 LEVEL=92500,85000,50000,20000
EON</pre>
```

Miscellaneous Reference manual

2.15.3. FILTER - Time series filtering

Synopsis

bandpass,fmin,fmax infile outfile
lowpass,fmax infile outfile
highpass,fmin infile outfile

Description

This module takes the time series for each gridpoint in infile and (fast fourier) transforms it into the frequency domain. According to the particular operator and its parameters certain frequencies are filtered (set to zero) in the frequency domain and the spectrum is (inverse fast fourier) transformed back into the time domain. To determine the frequency the time-axis of infile is used. (Data should have a constant time increment since this assumption applies for transformation. However, the time increment has to be different from zero.) All frequencies given as parameter are interpreted per year. This is done by the assumption of a 365-day calendar. Consequently if you want to perform multiyear-filtering accurately you have to delete the 29th of February. If your infile has a 360 year calendar the frequency parameters fmin respectively fmax should be multiplied with a factor of 360/365 in order to obtain accurate results. For the set up of a frequency filter the frequency parameters have to be adjusted to a frequency in the data. Here fmin is rounded down and fmax is always rounded up. Consequently it is possible to use bandpass with fmin=fmax without getting a zero-field for outfile. Hints for efficient usage:

- to get reliable results the time-series has to be detrended (cdo detrend)
- the lowest frequency greater zero that can be contained in infile is 1/(N*dT),
- the greatest frequency is 1/(2dT) (Nyquist frequency),

with N the number of timesteps and dT the time increment of infile in years.

Missing value support for operators in this module is not implemented, yet!

Operators

bandpass Bandpass filtering

Bandpass filtering (pass for frequencies between fmin and fmax). Suppresses all vari-

ability outside the frequency range specified by [fmin,fmax].

lowpass Lowpass filtering

Lowpass filtering (pass for frequencies lower than fmax). Suppresses all variability

with frequencies greater than fmax.

highpass Highpass filtering

Highpass filtering (pass for frequencies greater than fmin). Suppresses all variabilty

with frequencies lower than fmin.

Parameter

fmin FLOAT Minimum frequency per year that passes the filter.fmax FLOAT Maximum frequency per year that passes the filter.

Note

For better performace of these operators use the CDO configure option --with-fftw3.

Example

Now assume your data are still hourly for a time period of 5 years but with a 365/366-day- calendar and you want to suppress the variability on timescales greater or equal to one year (we suggest here to use a number x bigger than one (e.g. x=1.5) since there will be dominant frequencies around the peak (if there is one) as well due to the issue that the time series is not of infinite length). Therefor you can use the following:

```
cdo highpass,x -del29feb infile outfile
```

Accordingly you might use the following to suppress variability on timescales shorter than one year:

```
cdo lowpass,1 -del29feb infile outfile
```

Finally you might be interested in 2-year variability. If you want to suppress the seasonal cycle as well as say the longer cycles in climate system you might use

```
cdo bandpass,x,y -del29feb infile outfile
```

with x <= 0.5 and y >= 0.5.

2.15.4. GRIDCELL - Grid cell quantities

Synopsis

<operator> infile outfile

Description

This module reads the grid cell area of the first grid from the input stream. If the grid cell area is missing it will be computed from the grid coordinates. The area of a grid cell is calculated using spherical triangles from the coordinates of the center and the vertices. The base is a unit sphere which is scaled with the radius of the earth. The default earth radius is 6371000 meter. This value can be changed with the environment variable PLANET_RADIUS. Depending on the chosen operator the grid cell area or weights are written to the output stream.

Operators

gridarea Grid cell area

Writes the grid cell area to the output stream. If the grid cell area have to be

computed it is scaled with the earth radius to square meters.

gridweights Grid cell weights

Writes the grid cell area weights to the output stream.

Environment

PLANET_RADIUS This variable is used to scale the computed grid cell areas to square meters. By

default PLANET RADIUS is set to an earth radius of 6371000 meter.

2.15.5. SMOOTH - Smooth grid points

Synopsis

```
smooth[,options] infile outfile
smooth9 infile outfile
```

Description

Smooth all grid points of a horizontal grid. Options is a comma-separated list of "key=value" pairs with optional parameters.

Operators

smooth Smooth grid points

Performs a N point smoothing on all input fields. The number of points used depend on the search radius (radius) and the maximum number of points (maxpoints). Per default all points within the search radius of 1degree are used. The weights for the points depend on the form of the curve and the distance. The implemented form of the curve is linear with constant default weights of 0.25 at distance 0 (weight0) and at the search radius (weightR).

smooth9 9 point smoothing

Performs a 9 point smoothing on all fields with a quadrilateral curvilinear grid. The result at each grid point is a weighted average of the grid point plus the 8 surrounding points. The center point receives a weight of 1.0, the points at each side and above and below receive a weight of 0.5, and corner points receive a weight of 0.3. All 9 points are multiplied by their weights and summed, then divided by the total weight to obtain the smoothed value. Any missing data points are not included in the sum; points beyond the grid boundary are considered to be missing. Thus the final result may be the result of an averaging with less than 9 points.

Parameter

| nsmooth | INTEGER | Number of times to smooth, default nsmooth=1 |
|-----------|---------|--|
| radius | STRING | Search radius, default radius=1deg (units: deg, rad, km, m) |
| maxpoints | INTEGER | ${\bf Maximum\ number\ of\ points}, {\bf default\ maxpoints}{=}{<}{\bf gridsize}{>}$ |
| form | STRING | Form of the curve, default form=linear |
| weight0 | FLOAT | Weight at distance 0, default weight 0=0.25 $$ |
| weightR | FLOAT | Weight at the search radius, default weight R=0.25 $$ |

2.15.6. DELTAT - Difference between timesteps

Synopsis

```
deltat infile outfile
```

Description

This operator computes the difference between each timestep.

2.15.7. REPLACEVALUES - Replace variable values

Synopsis

```
setvals,oldval,newval[,...] infile outfile
setrtoc,rmin,rmax,c infile outfile
setrtoc2,rmin,rmax,c,c2 infile outfile
```

Description

This module replaces old variable values with new values, depending on the operator.

Operators

setvals Set list of old values to new values

Supply a list of n pairs of old and new values.

setrtoc Set range to constant

 $o(t,x) = \left\{ \begin{array}{ll} \mathbf{c} & \text{if } i(t,x) \geq r\min \wedge i(t,x) \leq r\max \\ i(t,x) & \text{if } i(t,x) < r\min \vee i(t,x) > r\max \end{array} \right.$

setrtoc2 Set range to constant others to constant2

 $o(t,x) = \begin{cases} c & \text{if } i(t,x) \ge r\min \land i(t,x) \le r\max \\ c2 & \text{if } i(t,x) < r\min \lor i(t,x) > r\max \end{cases}$

Parameter

c oldval, newval,... FLOAT Pairs of old and new values c Pairs of old and new values c Pairs of old and new values c Dependence c PLOAT Upper bound c New value - inside range c PLOAT New value - outside range

2.15.8. VARGEN - Generate a field

Synopsis

const,const,grid outfile
random,grid[,seed] outfile
topo[,grid] outfile
seq,start,end[,inc] outfile
stdatm,levels outfile

Description

Generates a dataset with one or more fields

Operators

const Create a constant field

Creates a constant field. All field elements of the grid have the same value.

random Create a field with random numbers

Creates a field with rectangularly distrubuted random numbers in the interval [0,1].

topo Create a field with topography

Creates a field with topography data, per default on a global half degree grid.

seq Create a time series

Creates a time series with field size 1 and field elements beginning with a start value in

time step 1 which is increased from one time step to the next.

stdatm Create values for pressure and temperature for hydrostatic atmosphere

Creates pressure and temperature values for the given list of vertical levels. The formu-

lars are:

$$P(z) = P_0 \exp\left(-\frac{g}{R} \frac{H}{T_0} \log\left(\frac{\exp\left(\frac{z}{H}\right)T_0 + \Delta T}{T_0 + \Delta T}\right)\right)$$

$$T(z) = T_0 + \Delta T \exp\left(-\frac{z}{H}\right)$$

with the following constants

 $T_0 = 213$ K : offset to get a surface temperature of 288K

 $\Delta T = 75$ K : Temperature lapse rate for 10Km

 $P_0 = 1013.25 \text{hPa}$: surface pressure H = 10000.0 m : scale height $g = 9.80665 \frac{\text{m}}{\text{S}^2}$: earth gravity

 $R = 287.05 \frac{J}{\text{kgK}}$: gas constant for air

This is the solution for the hydrostatic equations and is only valid for the troposphere (constant positive lapse rate). The temperature increase in the stratosphere and other effects of the upper atmosphere are not taken into account.

Parameter

| const | FLOAT | Constant |
|--------|---------|--|
| seed | INTEGER | The seed for a new sequence of pseudo-random numbers [default: 1] |
| grid | STRING | Target grid description file or name |
| start | FLOAT | Start value of the loop |
| end | FLOAT | End value of the loop |
| inc | FLOAT | Increment of the loop [default: 1] |
| levels | FLOAT | Target levels in metre above surface |
| | | |

Example

To create a standard atmosphere dataset on a given horizontal grid:

```
cdo enlarge,gridfile -stdatm,10000,8000,5000,3000,2000,1000,500,200,0 outfile
```

2.15.9. TIMSORT - Timsort

Synopsis

timsort infile outfile

Description

Sorts the elements in ascending order over all timesteps for every field position. After sorting it is:

$$o(t_1, x) \le o(t_2, x)$$
 $\forall (t_1 < t_2), x$

Example

To sort all field elements of a dataset over all timesteps use:

cdo timsort infile outfile

2.15.10. WINDTRANS - Wind Transformation

Synopsis

```
uvDestag,u,v[,-/+0.5[,-/+0.5]] infile outfile
rotuvNorth,u,v infile outfile
projuvLatLon,u,v infile outfile
```

Description

This module contains special operators for datsets with wind components on a rotated lon/lat grid, e.g. data from the regional model HIRLAM or REMO.

Operators

uvDestag Destaggering of u/v wind components

This is a special operator for destaggering of wind components. If the file contains a grid with temperature (name='t' or code=11) then grid_temp will be used for

destaggered wind.

rotuvNorth Rotate u/v wind to North pole.

This is an operator for transformation of wind-vectors from grid-relative to north-pole relative for the whole file. (FAST implementation with JACOBIANS)

projuvLatLon Cylindrical Equidistant projection

Thus is an operator for transformation of wind-vectors from the globe-spherical coordinate system into a flat Cylindrical Equidistant (lat-lon) projection. (FAST

JACOBIAN implementation)

Parameter

| u,v | STRING | Pair of u,v wind components (use variable names or code numbers) |
|---------------|--------|--|
| -/+0.5,-/+0.5 | STRING | Destaggered grid offsets are optional (default -0.5,-0.5) |

Example

Typical operator sequence on HIRLAM NWP model output (LAMH_D11 files):

```
cdo uvDestag,33,34 inputfile inputfile_destag
cdo rotuvNorth,33,34 inputfile_destag inputfile_rotuvN
```

2.15.11. ROTUVB - Rotation

Synopsis

rotuvb, u, v, ... infile outfile

Description

This is a special operator for datsets with wind components on a rotated grid, e.g. data from the regional model REMO. It performs a backward transformation of velocity components U and V from a rotated spherical system to a geographical system.

Parameter

u,v,... STRING Pairs of zonal and meridional velocity components (use variable names or code numbers)

Note

This is a specific implementation for data from the REMO model, it may not work with data from other sources.

Example

To transform the u and v velocity of a dataset from a rotated spherical system to a geographical system use:

cdo rotuvb, u, v infile outfile

2.15.12. MROTUVB - Backward rotation of MPIOM data

Synopsis

mrotuvb infile1 infile2 outfile

Description

MPIOM data are on a rotated Arakawa C grid. The velocity components U and V are located on the edges of the cells and point in the direction of the grid lines and rows. With mrotuvb the velocity vector is rotated in latitudinal and longitudinal direction. Before the rotation, U and V are interpolated to the scalar points (cell center). U is located with the coordinates for U in infile1 and V in infile2. mrotuvb assumes a positive meridional flow for a flow from grid point(i,j) to grid point(i,j+1) and positive zonal flow for a flow from grid point(i+1,j) to point(i,j).

Note

This is a specific implementation for data from the MPIOM model, it may not work with data from other sources.

2.15.13. MASTRFU - Mass stream function

Synopsis

mastrfu infile outfile

Description

This is a special operator for the post processing of the atmospheric general circulation model [ECHAM]. It computes the mass stream function (code=272). The input dataset have to be a zonal mean of v-velocity [m/s] (code=132) on pressure levels.

Example

To compute the mass stream function from a zonal mean v-velocity dataset use:

cdo mastrfu infile outfile

2.15.14. DERIVEPAR - Derived model parameters

Synopsis

< operator > infile outfile

Description

This module contains operators that calculate derived model parameters. These are currently the parameters sea level pressure and geopotential height. All necessary input parameters are identified by their GRIB1 code number or the NetCDF CF standard name. Supported GRIB1 parameter tables are: WMO standard table number 2 and ECMWF local table number 128.

| CF standard name | Units | GRIB 1 code |
|----------------------|--------|-------------|
| surface_air_pressure | Pa | 134 |
| air_temperature | K | 130 |
| specific_humidity | kg/kg | 133 |
| surface_geopotential | m2 s-2 | 129 |
| geopotential_height | m | 156 |

Operators

sealevelpressure Sea level pressure

This operator computes the sea level pressure (air_pressure_at_sea_level).

 $Required input fields are surface_air_pressure, surface_geopotential \ and \ air_temperature$

on full hybrid sigma pressure levels.

gheight Geopotential height

This operator computes the geopotential height (geopotential_height) on full model levels in metres. Required input fields are surface_air_pressure, surface_geopotential, specific_humidity and air_temperature on full hybrid sigma pressure levels. Note, this procedure is an approximation, which doesn't take

into account the effects of e.g. cloud ice and water, rain and snow.

2.15.15. ADISIT - Potential temperature to in-situ temperature and vice versa

Synopsis

<operator>[,pressure] infile outfile

Description

Operators

adisit Potential temperature to in-situ temperature

This is a special operator for the post processing of the ocean and sea ice model [MPIOM]. It converts potential temperature adiabatically to in-situ temperature to(t, s, p). Required input fields are sea water potential temperature (name=tho; code=2) and sea water salinity (name=sao; code=5). Pressure is calculated from the level information or can be specified by the optional parameter. Output fields are sea water temperature (name=to; code=20) and sea water salinity (name=s; code=5).

adipot In-situ temperature to potential temperature

This is a special operator for the post processing of the ocean and sea ice model [MPIOM]. It converts in-situ temperature to potential temperature tho(to, s, p). Required input fields are sea water in-situ temperature (name=t; code=2) and sea water salinity (name=sao,s; code=5). Pressure is calculated from the level information or can be specified by the optional parameter. Output fields are sea water temperature (name=tho; code=2) and sea water salinity (name=s; code=5).

Parameter

pressure FLOAT Pressure in bar (constant value assigned to all levels)

2.15.16. RHOPOT - Calculates potential density

Synopsis

rhopot[,pressure] infile outfile

Description

This is a special operator for the post processing of the ocean and sea ice model [MPIOM]. It calculates the sea water potential density (name=rhopoto; code=18). Required input fields are sea water in-situ temperature (name=to; code=20) and sea water salinity (name=sao; code=5). Pressure is calculated from the level information or can be specified by the optional parameter.

Parameter

pressure FLOAT Pressure in bar (constant value assigned to all levels)

Example

To compute the sea water potential density from the potential temperature use this operator in combination with adisit:

cdo rhopot -adisit infile outfile

2.15.17. HISTOGRAM - Histogram

Synopsis

<operator>,bounds infile outfile

Description

This module creates bins for a histogram of the input data. The bins have to be adjacent and have non-overlapping intervals. The user has to define the bounds of the bins. The first value is the lower bound and the second value the upper bound of the first bin. The bounds of the second bin are defined by the second and third value, aso. Only 2-dimensional input fields are allowed. The output file contains one vertical level for each of the bins requested.

Operators

histcount Histogram count

Number of elements in the bin range.

histsum Histogram sum

Sum of elements in the bin range.

histmean Histogram mean

Mean of elements in the bin range.

histfreq Histogram frequency

Relative frequency of elements in the bin range.

Parameter

bounds FLOAT Comma-separated list of the bin bounds (-inf and inf valid)

2.15.18. SETHALO - Set the left and right bounds of a field

Synopsis

sethalo, lhalo, rhalo infile outfile

Description

This operator sets the left and right bounds of the rectangularly understood fields. Positive numbers of the parameter lhalo enlarges the left bound by the given number of columns from the right bound. The parameter rhalo does the similar for the right bound. Negative numbers of the parameter lhalo/rhalo can be used to remove the given number of columns of the left and right bounds.

Parameter

lhalo INTEGER Left halorhalo INTEGER Right halo

2.15.19. WCT - Windchill temperature

Synopsis

wct infile1 infile2 outfile

Description

Let infile1 and infile2 be time series of temperature and wind speed records, then a corresponding time series of resulting windchill temperatures is written to outfile. The wind chill temperature calculation is only valid for a temperature of $T \le 33$ °C and a wind speed of $v \ge 1.39$ m/s. Whenever these conditions are not satisfied, a missing value is written to outfile. Note that temperature and wind speed records have to be given in units of °C and m/s, respectively.

2.15.20. FDNS - Frost days where no snow index per time period

Synopsis

fdns infile1 infile2 outfile

Description

Let infile1 be a time series of the daily minimum temperature TN and infile2 be a corresponding series of daily surface snow amounts. Then the number of days where TN < 0 °C and the surface snow amount is less than 1 cm is counted. The temperature TN have to be given in units of Kelvin. The date information of a timestep in outfile is the date of the last contributing timestep in infile.

2.15.21. STRWIN - Strong wind days index per time period

Synopsis

 \mathbf{strwin}/v infile outfile

Description

Let infile be a time series of the daily maximum horizontal wind speed VX, then the number of days where VX > v is counted. The horizontal wind speed v is an optional parameter with default v = 10.5 m/s. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to v. Note that both VX and v have to be given in units of m/s. Also note that the horizontal wind speed is defined as the square root of the sum of squares of the zonal and meridional wind speeds. The date information of a timestep in outfile is the date of the last contributing timestep in infile.

Parameter

v FLOAT Horizontal wind speed threshold (m/s, default v = 10.5 m/s)

2.15.22. STRBRE - Strong breeze days index per time period

Synopsis

strbre infile outfile

Description

Let infile be a time series of the daily maximum horizontal wind speed VX, then the number of days where VX is greater than or equal to 10.5 m/s is counted. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 10.5 m/s. Note that VX is defined as the square root of the sum of squares of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a timestep in outfile is the date of the last contributing timestep in infile.

2.15.23. STRGAL - Strong gale days index per time period

Synopsis

strgal infile outfile

Description

Let infile be a time series of the daily maximum horizontal wind speed VX, then the number of days where VX is greater than or equal to 20.5 m/s is counted. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 20.5 m/s. Note that VX is defined as the square root of the sum of square of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a timestep in outfile is the date of the last contributing timestep in infile.

2.15.24. HURR - Hurricane days index per time period

Synopsis

hurr infile outfile

Description

Let infile be a time series of the daily maximum horizontal wind speed VX, then the number of days where VX is greater than or equal to 32.5 m/s is counted. A further output variable is the maximum number of consecutive days with maximum wind speed greater than or equal to 32.5 m/s. Note that VX is defined as the square root of the sum of squares of the zonal and meridional wind speeds and have to be given in units of m/s. The date information of a timestep in outfile is the date of the last contributing timestep in infile.

2.15.25. CMORLITE - CMOR lite

Synopsis

cmorlite,table[,convert] infile outfile

Description

The [CMOR] (Climate Model Output Rewriter) library comprises a set of functions, that can be used to produce CF-compliant NetCDF files that fulfill the requirements of many of the climate community's standard model experiments. These experiments are collectively referred to as MIP's. Much of the metadata written to the output files is defined in MIP-specific tables, typically made available from each MIP's web site.

The **CDO** operator cmorlite process the header and variable section of such MIP tables and writes the result with the internal IO library [CDI]. In addition to the CMOR 2 and 3 table format, the **CDO** parameter table format is also supported. The following parameter table entries are available:

| Entry | Type | Description |
|-----------------|---------|--|
| name | WORD | Name of the variable |
| out_name | WORD | New name of the variable |
| type | WORD | Data type (real or double) |
| standard_name | WORD | As defined in the CF standard name table |
| long_name | STRING | Describing the variable |
| units | STRING | Specifying the units for the variable |
| comment | STRING | Information concerning the variable |
| cell_methods | STRING | Information concerning calculation of means or climatologies |
| cell_measures | STRING | Indicates the names of the variables containing cell areas and volumes |
| missing_value | FLOAT | Specifying how missing data will be identified |
| valid_min | FLOAT | Minimum valid value |
| valid_max | FLOAT | Maximum valid value |
| ok_min_mean_abs | FLOAT | Minimum absolute mean |
| ok_max_mean_abs | FLOAT | Maximum absolute mean |
| factor | FLOAT | Scale factor |
| delete | INTEGER | Set to 1 to delete variable |
| convert | INTEGER | Set to 1 to convert the unit if necessary |

Most of the above entries are stored as variables attributes, some of them are handled differently. The variable name is used as a search key for the parameter table. valid_min, valid_max, ok_min_mean_abs and ok_max_mean_abs are used to check the range of the data.

Parameter

table STRING Name of the CMOR table as specified from PCMDI

convert STRING Converts the units if necessary

Example

Here is an example of a parameter table for one variable:

```
prompt> cat mypartab
&parameter
name = t
```

```
out_name = ta
standard_name = air_temperature
units = "K"
missing_value = 1.0e+20
valid_min = 157.1
valid_max = 336.3
//
```

To apply this parameter table to a dataset use:

```
cdo -f nc cmorlite,mypartab,convert infile outfile
```

This command renames the variable t to ta. The standard name of this variable is set to $air_temperature$ and the unit is set to [K] (converts the unit if necessary). The missing value will be set to 1.0e+20. In addition it will be checked whether the values of the variable are in the range of 157.1 to 336.3. The result will be stored in NetCDF.

2.15.26. VERIFYGRID - Verify grid coordinates

Synopsis

verifygrid infile

Description

This operator verifies the coordinates of all horizontal grids found in infile. Among other things, it searches for duplicate cells, non-convex cells, and whether the center is located outside the cell bounds. Use the **CDO** option -v to output the position of these cells. This information can be useful to avoid problems when interpolating the data.

3. Contributors

3.1. History

CDO was originally developed by Uwe Schulzweida at the Max Planck Institute for Meteorology (MPI-M). The first public release is available since 2003. The MPI-M, together with the DKRZ, has a long history in the development of tools for processing climate data. **CDO** was inspired by some of these tools, such as the PINGO package and the GRIB-Modules.

PINGO¹ was developed by Jürgen Waszkewitz, Peter Lenzen, and Nathan Gillet in 1995 at the DKRZ, Hamburg (Germany). **CDO** has a similar user interface and uses some of the PINGO routines.

The GRIB-Modules was developed by Heiko Borgert and Wolfgang Welke in 1991 at the MPI-M. **CDO** is using a similar module structure and also some of the routines.

3.2. External sources

CDO has incorporated code from several sources:

afterburner is a postprocessing application for ECHAM data and ECMWF analysis data, originally developed by Edilbert Kirk, Michael Ponater and Arno Hellbach. The afterburner code was modified for the **CDO** operators after, ml2pl, ml2hl, sp2gp, gp2sp.

SCRIP is a software package used to generate interpolation weights for remapping fields from one grid to another in spherical geometry [SCRIP]. It was developed at the Los Alamos National Laboratory by Philip W. Jones. The SCRIP library was converted from Fortran to ANSI C and is used as the base for the remapping operators in **CDO**.

YAC (Yet Another Coupler) was jointly developed by DKRZ and MPI-M by Moritz Hanke and Rene Redler [YAC]. **CDO** is using the clipping and cell search routines for the conservative remapping with remapcon.

libkdtree a C99 implementation of the kd-tree algorithm developed by Jörg Dietrich.

CDO uses tools from the GNU project, including automake, and libtool.

3.3. Contributors

The primary contributors to the **CDO** development have been:

Uwe Schulweida: Concept, design and implementation of CDO, project coordination, and releases.

Luis Kornblueh: He supports **CDO** from the beginning. His main contributions are GRIB performance and compression, GME and unstructured grid support. Luis also helps with design and planning.

Ralf Müller: He is working on CDO since 2009. His main contributions are the implementation of the User Portal, the ruby and python interface for all CDO operators, the building process and the Windows support. The CDO User Portal was funded by the European Commission infracstructure project IS-ENES. Ralf also helps a lot with the user support. Implemented operators: intlevel3d, consecsum, consects, ngrids, ngridpoints, reducegrid

¹Procedural INterface for GRIB formatted Objects

Contributors Contributors

Cedrick Ansorge: He worked on the software package **CDO** as a student assistant at MPI-M from 2007-2011. Implemented operators: eof, eof3d, enscrps, ensbrs, maskregion, bandpass, lowpass, highpass, smooth9

Oliver Heidmann: He worked on the software package **CDO** as a student assistant at MPI-M from 2015-2018.

Karin Meier-Fleischer: She is working in the **CDO** user support since 2017.

Fabian Wachsmann: He is working on **CDO** for the CMIP6 project since 2016. His main task is the implementation and support of the cmor operator. He has also implemented the ETCCDI Indices of Daily Temperature and Precipitation Extremes.

Ralf Quast: He worked on CDO on behalf of the Service Gruppe Anpassung (SGA), DKRZ in 2006. He implemented all ECA Indices of Daily Temperature and Precipitation Extremes, all percentile operators, module YDRUNSTAT and wct.

Kameswarrao Modali: He worked on CDO from 2012-2013.

Implemented operators: contour, shaded, grfill, vector, graph.

Michal Koutek: Implemented operators: selmulti delmulti, changemulti, samplegrid, uvDestag, rotuvNorth, projuvLatLon.

Etienne Tourigny: Implemented operators: setclonlatbox, setcindexbox, setvals, splitsel, histfreq, setrtoc, setrtoc2.

Karl-Hermann Wieners: Implemented operators: aexpr, aexprf, selzaxisname.

Asela Rajapakse: He worked on **CDO** from 2016-2017 as part of the EUDAT project. Implemented operator: verifygrid

Estanislao Gavilan : Improved the CDO documentation for the installation section.

Many users have contributed to **CDO** by sending bug reports, patches and suggestions over time. Very helpful is also the active participation in the user forum of some users. Here is an incomplete list:

Jaison-Thomas Ambadan, Harald Anlauf, Andy Aschwanden, Stefan Bauer, Simon Blessing, Renate Brokopf, Michael Boettinger, Tim Brücher, Reinhard Budich, Martin Claus, Traute Crüger, Brendan de Tracey, Irene Fischer-Bruns, Chris Fletscher, Helmut Frank, Kristina Fröhlich, Oliver Fuhrer, Monika Esch, Pier Giuseppe Fogli, Beate Gayer, Veronika Gayler, Marco Giorgetta, David Gobbett, Holger Goettel, Helmut Haak, Stefan Hagemann, Angelika Heil, Barbara Hennemuth, Daniel Hernandez, Nathanael Huebbe, Thomas Jahns, Frank Kaspar, Daniel Klocke, Edi Kirk, Yvonne Küstermann, Stefanie Legutke, Leonidas Linardakis, Stephan Lorenz, Frank Lunkeit, Uwe Mikolajewicz, Laura Niederdrenk, Dirk Notz, Hans-Jürgen Panitz, Ronny Petrik, Swantje Preuschmann, Florian Prill, Asela Rajapakse, Daniel Reinert, Hannes Reuter, Mathis Rosenhauer, Reiner Schnur, Martin Schultz, Dennis Shea, Kevin Sieck, Martin Stendel, Bjorn Stevens, Martina Stockhaus, Claas Teichmann, Adrian Tompkins, Jörg Trentmann, Álvaro M. Valdebenito, Geert Jan van Oldenborgh, Jin-Song von Storch, David Wang, Joerg Wegner, Heiner Widmann, Claudia Wunram, Klaus Wyser

Please let me know if your name was omitted!

Bibliography

[BitInformation.jl]

M Klöwer, M Razinger, JJ Dominguez, PD Düben and TN Palmer, 2021. Compressing atmospheric data into its real information content. Nature Computational Science 1, 713–724. 10.1038/s43588-021-00156-2

[CDI]

Climate Data Interface, from the Max Planck Institute for Meteorologie

[CM-SAF]

Satellite Application Facility on Climate Monitoring, from the German Weather Service (Deutscher Wetterdienst, DWD)

[CMOR]

Climate Model Output Rewriter, from the Program For Climate Model Diagnosis and Intercomparison (PCMDI)

[ecCodes]

API for GRIB decoding/encoding, from the European Centre for Medium-Range Weather Forecasts (ECMWF)

[ECHAM]

The atmospheric general circulation model ECHAM5, from the Max Planck Institute for Meteorologie

[GMT]

The Generic Mapping Tool, from the School of Ocean and Earth Science and Technology (SOEST)

[GrADS]

Grid Analysis and Display System, from the Center for Ocean-Land-Atmosphere Studies (COLA)

[GRIB]

GRIB version 1, from the World Meteorological Organisation (WMO)

HDF5

HDF version 5, from the HDF Group

[INTERA]

INTERA Software Package, from the Max Planck Institute for Meteorologie

Magics

Magics Software Package, from the European Centre for Medium-Range Weather Forecasts (ECMWF)

[MPIOM]

Ocean and sea ice model, from the Max Planck Institute for Meteorologie

[NetCDF]

NetCDF Software Package, from the UNIDATA Program Center of the University Corporation for Atmospheric Research

[PINGO]

The PINGO package, from the Model & Data group at the Max Planck Institute for Meteorologie

[REMO]

Regional Model, from the Max Planck Institute for Meteorologie

[Preisendorfer]

Rudolph W. Preisendorfer: Principal Component Analysis in Meteorology and Oceanography, Elsevier (1988)

Bibliography

[PROJ]

Cartographic Projections Library, originally written by Gerald Evenden then of the USGS.

SCRIP

SCRIP Software Package, from the Los Alamos National Laboratory

szip

Szip compression software, developed at University of New Mexico.

[vonStorch]

Hans von Storch, Walter Zwiers: Statistical Analysis in Climate Research, Cambridge University Press $\left(1999\right)$

[YAC]

YAC - Yet Another Coupler Software Package, from DKRZ and MPI for Meteorologie

A. Environment Variables

The following table describes the environment variables that affect ${\bf CDO}.$

| Variable name | Default | Description |
|-----------------------|----------|---|
| CDO_DOWNLOAD_PATH | None | Path where CDO can store downloads. |
| CDO_FILE_SUFFIX | None | Default filename suffix. This suffix will be added to the output file |
| | | name instead of the filename extension derived from the file |
| | | format. NULL will disable the adding of a file suffix. |
| CDO_GRIDSEARCH_RADIUS | 180 | Grid search radius in degree. Used by the operators |
| | | setmisstonn, remapdis and remapnn. |
| CDO_HISTORY_INFO | true | 'false' don't write information to the global history attribute. |
| CDO_ICON_GRIDS | None | Root directory of the installed ICON grids (e.g. /pool/data/ICON). |
| CDO_PCTL_NBINS | 101 | Number of histogram bins. |
| CDO_RESET_HISTORY | false | 'true' resets the global <i>history</i> attribute. |
| CDO_REMAP_NORM | fracarea | Choose the normalization for the conservative interpolation |
| CDO_TIMESTAT_DATE | None | Set target timestamp of a temporal statistic operator to the "first", |
| | | "middle", "midhigh" or "last" contributing source timestep. |
| CDO_USE_FFTW | 1 | Set to 0 to switch off usage of FFTW. Used in the Filter module. |
| CDO_VERSION_INFO | true | 'false' disables the global NetCDF attribute CDO. |

B. Parallelized operators

Some of the **CDO** operators are parallelized with OpenMP. To use **CDO** with multiple OpenMP threads, you have to set the number of threads with the option '-P'. Here is an example to distribute the bilinear interpolation on 8 OpenMP threads:

cdo -P 8 remapbil, targetgrid infile outfile

The following ${\bf CDO}$ operators are parallelized with OpenMP:

| Module | Operator | Description |
|-------------|-----------------------|--|
| Afterburner | after | ECHAM standard post processor |
| Detrend | detrend | Detrend |
| EcaEtccdi | etccdi_tx90p | % of days when daily max temperature is > the 90th percentile |
| EcaEtccdi | etccdi_tx10p | % of days when daily max temperature is < the 10th percentile |
| EcaEtccdi | etccdi_tn90p | % of days when daily min temperature is > the 90th percentile |
| EcaEtccdi | etccdi_tn10p | % of days when daily min temperature is $<$ the 10th percentile |
| EcaEtccdi | etccdi_r95p | Annual tot precip when daily precip exceeds the 95th percentile of |
| EcaEtccdi | etccdi_r99p | Annual tot precip when daily precip exceeds the 99th percentile of |
| Ensstat | ens <stat></stat> | Statistical values over an ensemble |
| EOF | eof | Empirical Orthogonal Functions |
| Fillmiss | setmisstonn | Set missing value to nearest neighbor |
| Fillmiss | setmisstodis | Set missing value to distance-weighted average |
| Filter | bandpass | Bandpass filtering |
| Filter | lowpass | Lowpass filtering |
| Filter | highpass | Highpass filtering |
| Fourier | fourier | Fourier transformation |
| Genweights | genbil | Generate bilinear interpolation weights |
| Genweights | genbic | Generate bicubic interpolation weights |
| Genweights | gendis | Generate distance-weighted average remap weights |
| Genweights | gennn | Generate nearest neighbor remap weights |
| Genweights | gencon | Generate 1st order conservative remap weights |
| Genweights | gencon2 | Generate 2nd order conservative remap weights |
| Genweights | genlaf | Generate largest area fraction remap weights |
| Gridboxstat | gridbox <stat></stat> | Statistical values over grid boxes |
| Intlevel | intlevel | Linear level interpolation |
| Intlevel3d | intlevel3d | Linear level interpolation from/to 3D vertical coordinates |
| Remapeta | remapeta | Remap vertical hybrid level |
| Remap | remapbil | Bilinear interpolation |
| Remap | remapbic | Bicubic interpolation |
| Remap | remapdis | Distance-weighted average remapping |
| Remap | remapnn | Nearest neighbor remapping |
| Remap | remapcon | First order conservative remapping |
| Remap | remapcon2 | Second order conservative remapping |
| Remap | remaplaf | Largest area fraction remapping |
| Smooth | smooth | Smooth grid points |
| Spectral | sp2gp, gp2sp | Spectral transformation |

| Module | Operator | Description |
|-----------|--------------|---|
| Vertintap | ap2pl, ap2hl | Vertical interpolation on hybrid sigma height coordinates |
| Vertintgh | gh2hl | Vertical height interpolation |
| Vertintml | ml2pl, ml2hl | Vertical interpolation on hybrid sigma pressure coordinates |

C. Standard name table

The following CF standard names are supported by ${\bf CDO}$.

| CF standard name | Units | GRIB 1 code | variable name |
|---------------------------|--------|-------------|---------------|
| surface_geopotential | m2 s-2 | 129 | geosp |
| air_temperature | K | 130 | ta |
| specific_humidity | 1 | 133 | hus |
| surface_air_pressure | Pa | 134 | aps |
| air_pressure_at_sea_level | Pa | 151 | psl |
| geopotential_height | m | 156 | zg |

D. Grid description examples

D.1. Example of a curvilinear grid description

Here is an example for the **CDO** description of a curvilinear grid. xvals/yvals describe the positions of the 6x5 quadrilateral grid cells. The first 4 values of xbounds/ybounds are the corners of the first grid cell.

```
gridsize
             = 30
             = 6
xsize
ysize
             = 5
                                 0
                                      11
                                                    30
                                                         -25
                                                                         0
                                                                              13
                  -21
                        -11
                                             21
                                                                -13
xvals
                  ^{25}
                         36
                              -31
                                     -16
                                                    16
                                                          31
                                                                 43
                                                                      -38
                                                                             -21
                        21
                               38
                                      52
                                                                 30
                                                                       51
                                            -51
                                                  -30
xbounds
                        -14
                               -17
                                     -28
                                                   -14
                                                          -5
                                                                 -6
                                                                      -17
                                                                                     -5
                                                                                             5
                                                                                                   6
                                                                                                         -6
                         14
                                       6
                                                    14
                                                          23
                                                                 28
                                                                        17
                                                                                     ^{23}
                                                                                            32
                                                                                                  38
                                                                                                         ^{28}
                  -28
                        -17
                               -21
                                     -34
                                                   -17
                                                          -6
                                                                       -21
                                                                                     -6
                                                                                             6
                                                                                                   7
                                                                 34
                                                                                     28
                                                                                                         34
                               21
                                       7
                                                          28
                                                                       21
                                                                                            38
                                                                                                  44
                        17
                                                    17
                   -34
                        -21
                               -27
                                     -41
                                                   -21
                                                                       -27
                         21
                               27
                                                    21
                                                          34
                                                                 41
                                                                       27
                                                                                     34
                                                                                                  52
                                                                                                         41
                                       9
                                                                                            44
                 -41
                        -27
                              -35
                                     -51
                                                   -27
                                                          -9
                                                                -13
                                                                      -35
                                                                                     -9
                                                                                             9
                                                                                                  13
                                                                                                        -13
                         27
                                35
                                      13
                                                    ^{27}
                                                          41
                                                                 51
                                                                        35
                                                                                     41
                                                                                            52
                                                                                                  63
                                                                                                         51
                 -51
                        -35
                               -51
                                     -67
                                                   -35
                                                                -21
                                                                       -51
                                                                                            13
                                                                                                  21
                                                                                                        -21
                                                         -13
                                                                                    -13
                  13
                         35
                                51
                                      21
                                                    35
                                                          51
                                                                 67
                                                                        51
                                                                                     51
                                                                                                         67
yvals
                  29
                         32
                                32
                                      32
                                                    26
                                                          39
                                                                 42
                                                                        42
                                                                              42
                                             52
                  39
                         35
                                48
                                      51
                                                    51
                                                          48
                                                                 43
                                                                        57
                                                                              61
                  62
                         61
                                57
                                      51
                                                    70
                                                          72
                                                                 70
                                                                        65
ybounds
                         26
                                                    26
                                                          27
                                                                 37
                                                                        36
                                                                                     27
                                                                                            27
                                                                                                  37
                                                                                                         37
                  23
                                36
                                      32
                  27
                         26
                                36
                                      37
                                                                                            19
                                                                                                  28
                                                                                                         32
                                                    ^{26}
                                                          23
                                                                 32
                                                                        36
                                                                                     23
                  32
                                                    36
                                                                 47
                                                                                     37
                                                                                                         47
                  37
                         36
                                                    36
                                                          32
                                                                                     32
                                                                                                  36
                                45
                                      47
                                                                 41
                                                                        45
                                                                                            28
                                                                                                         41
                  41
                         45
                                55
                                      50
                                                    45
                                                          47
                                                                 57
                                                                        55
                                                                                     47
                                                                                            47
                                                                                                  57
                                                                                                         57
                  47
                         45
                                55
                                      57
                                                    45
                                                          41
                                                                 50
                                                                        55
                                                                                     41
                                                                                            36
                                                                                                  44
                                                                                                         50
                                                          57
                  50
                         55
                                64
                                      58
                                                    55
                                                                 67
                                                                        64
                                                                                     57
                                                                                            57
                                                                                                  67
                                                                                                         67
                  57
                         55
                                64
                                      67
                                                    55
                                                          50
                                                                 58
                                                                        64
                                                                                     50
                                                                                            44
                                                                                                         58
                  58
                         64
                                72
                                                    64
                                                          67
                                                                 77
                                                                                     67
                                                                                            67
                                                                                                  77
                                                                                                         77
                                      64
                                                                        72
                         64
                                72
                                                    64
                                                                 64
                                                                        72
                                                                                     58
                                                                                                  56
                                                                                                         64
```




Figure D.1.: Orthographic and Robinson projection of the curvilinear grid, the first grid cell is colored red

D.2. Example description for an unstructured grid

Here is an example of the **CDO** description for an unstructured grid. xvals/yvals describe the positions of 30 independent hexagonal grid cells. The first 6 values of xbounds/ybounds are the corners of the first grid cell. The grid cell corners have to rotate counterclockwise. The first grid cell is colored red.

```
= unstructured
gridtype
gridsize
            = 30
nvertex
            = 6
                -36
                       36
                               0
                                                108
                                                       72
                                                              54
                                                                    90
                                                                         180
                                                                               144
                                                                                      126
                                                                                            162 - 108 - 144
xvals
                                   -18
                                           18
               -162
                                   -90
                                                                                                 -108
                     -126
                             -72
                                         -54
                                                  0
                                                       72
                                                             36
                                                                   144
                                                                         108
                                                                               -144
                                                                                      180
                                                                                            -72
                                                                                                        -36
                                   288
                                         288
                                                309
                                                              21
                                                                          72
                                                                                 72
xbounds
                339
                                                                    51
                              21
                                         339
                                                344
                                                                     0
                                                                                      324
                  0
                       16
                                     0
                                                            340
                                                                          -0
                                                                               344
                                                                                            324
                 20
                       36
                              36
                                    16
                                           0
                                                  0
                                                             93
                                                                   123
                                                                         144
                                                                               144
                                                                                       72
                                                                                             72
                              93
                                          51
                                                                                       36
                                                                                             36
                       88
                                    72
                                                 56
                                                              52
                                                                          72
                                                                                 56
                      108
                             108
                 92
                                    88
                                          72
                                                 72
                                                            165
                                                                   195
                                                                         216
                                                                               216
                                                                                      144
                                                                                            144
                144
                      160
                             165
                                   144
                                         123
                                                128
                                                            124
                                                                   144
                                                                         144
                                                                               128
                                                                                      108
                                                                                            108
                164
                      180
                             180
                                   160
                                         144
                                                144
                                                            237
                                                                   267
                                                                         288
                                                                               288
                                                                                      216
                                                                                            216
                216
                      232
                                                200
                                                                   216
                                                                               200
                             237
                                   216
                                         195
                                                            196
                                                                         216
                                                                                      180
                                                                                            180
                ^{236}
                      252
                             252
                                   232
                                                216
                                                             288
                                                                   304
                                                                         309
                                                                               288
                                                                                      267
                                                                                            272
                                         216
                268
                      288
                             288
                                   272
                                         252
                                                252
                                                            308
                                                                   324
                                                                         324
                                                                               304
                                                                                      288
                                                                                            288
                345
                      324
                             324
                                    36
                                          36
                                                 15
                                                             36
                                                                    36
                                                                         108
                                                                               108
                                                                                       87
                                                                                             57
                 20
                       15
                              36
                                    57
                                           52
                                                 36
                                                            108
                                                                   108
                                                                         180
                                                                               180
                                                                                      159
                                                                                            129
                 92
                                                108
                       87
                             108
                                   129
                                         124
                                                            180
                                                                   180
                                                                         252
                                                                               252
                                                                                      231
                                                                                            201
                164
                      159
                             180
                                   201
                                         196
                                                180
                                                            252
                                                                   252
                                                                         324
                                                                               324
                                                                                      303
                                                                                            273
                236
                      231
                             252
                                   273
                                         268
                                                252
                                                            308
                                                                   303
                                                                         324
                                                                               345
                                                                                      340
                                                                                            324
                                                       32
yvals
                              32
                                                                                 32
                                                                                                          32
                 58
                       58
                                     0
                                            0
                                                 58
                                                               0
                                                                     0
                                                                          58
                                                                                        0
                                                                                              0
                                                                                                    58
                              32
                                            0
                                                -58
                                                            -32
                                                                          -32
                                                                                -58
                                                                                            -58
                                                                                                   -32
                                                                                                         -32
                                                      -58
                       53
                                                                          53
                                                                                 71
                                                                                       71
                                                                                             53
ybounds
                 41
                                    71
                                           53
                                                 41
                                                             41
                                                                    41
                              71
                 11
                       19
                              41
                                    53
                                           41
                                                 19
                                                            -19
                                                                          11
                                                                                 19
                                                                                            -11
                -19
                                    19
                                                             41
                                                                    41
                                                                                 71
                                                                                       71
                                                                                             53
                      -11
                                           11
                                                                          53
                 11
                       19
                              41
                                    53
                                           41
                                                 19
                                                            -19
                                                                    -7
                                                                          11
                                                                                 19
                                                                                            -11
                -19
                       -11
                                    19
                                           11
                                                              41
                                                                    41
                                                                          53
                                                                                 71
                                                                                       71
                                                                                             53
                 11
                       19
                              41
                                    53
                                           41
                                                 19
                                                             -19
                                                                          11
                                                                                 19
                                                                                             -11
                                          11
                -19
                                    19
                                                 -7
                                                                    41
                                                                                       71
                      -11
                               7
                                                             41
                                                                          53
                                                                                 71
                                                                                             53
                 11
                        19
                              41
                                    53
                                           41
                                                 19
                                                             -19
                                                                           11
                                                                                 19
                -19
                                                 -7
                                                                    19
                      -11
                                    19
                                                             11
                                                                          41
                                                                                 53
                                                                                       41
                                                                                             19
                                          11
                -19
                              11
                                    19
                                                -11
                                                            -19
                                                                   -11
                                                                                 19
                                                                                       11
                -41
                             -71
                                    -71
                                         -53
                                                                          -71
                      -53
                                                -41
                                                            -53
                                                                   -71
                                                                                -53
                                                                                      -41
                                                                                             -41
                -19
                      -41
                             -53
                                   -41
                                         -19
                                                -11
                                                            -53
                                                                   -71
                                                                         -71
                                                                                -53
                                                                                      -41
                                                                                            -41
                -19
                      -41
                            -53
                                   -41
                                         -19
                                                -11
                                                            -53
                                                                   -71
                                                                         -71
                                                                                -53
                                                                                      -41
                                                                                            -41
                -19
                      -41
                            -53
                                   -41
                                         -19
                                                            -53
                                                                   -71
                                                                         -71
                                                                               -53
                                                                                      -41
                                                                                            -41
                                                -11
                                                                   -41
                                                                                      -19
                -19
                      -41
                                   -41
                                         -19
                            -53
                                                                         -53
                                                                                            -11
                                                -11
                                                            -19
                                                                               -41
```




Figure D.2.: Orthographic and Robinson projection of the unstructured grid

Operator index

| Λ | dormatl 149 |
|---|---|
| abs 96 | daypctl |
| | |
| | v |
| add | |
| addc 98 | daysub |
| addtrend | daysum |
| adipot | dayvar 141 |
| adisit 225 | dayvar1 141 |
| aexpr 92 | delcode |
| aexprf 92 | delete |
| after | delgridcell |
| ap2pl 191 | delmulti |
| apply 38 | delname |
| asin 96 | delparam |
| atan 96 | deltat |
| atan2 99 | detrend |
| D | dhouravg 152 |
| ${f B}$ | dhourmax |
| bandpass | dhourmean |
| bitrounding 41 | dhourmin 152 |
| bottomvalue | dhourrange 152 |
| | dhourstd 152 |
| \mathbf{C} | dhourstd1 152 |
| cat 39 | dhoursum 152 |
| changemulti | dhourvar 152 |
| chcode 78 | dhourvar1 152 |
| chlevel 78 | diff 32 |
| chlevelc 78 | diffn 32 |
| chlevelv 78 | distgrid |
| chname 78 | div 99 |
| chparam | divc 98 |
| chunit | divcoslat 107 |
| clone 39 | divdpm 107 |
| cmorlite 229 | divdpy 107 |
| codetab 36 | duplicate 42 |
| collgrid | dv2ps |
| consecsum 116 | dv2uv 199 |
| consects | _ |
| const 220 | ${f E}$ |
| copy 39 | enlarge 86 |
| cos 96 | ensavg 118 |
| <u>_</u> | ensbrs 121 |
| ${f D}$ | enscrps 121 |
| dayadd 100 | T |
| | enskurt 118 |
| dayavg 141 | 1 |
| dayavg 141 daydiv 100 | enskurt |
| | enskurt 118 ensmax 118 |
| daydiv | enskurt 118 ensmax 118 ensmean 118 |
| daydiv 100 daymax 141 | enskurt 118 ensmax 118 ensmean 118 ensmedian 118 |
| daydiv 100 daymax 141 daymean 141 | enskurt 118 ensmax 118 ensmean 118 ensmedian 118 ensmin 118 |

| angulah iatan aga | 190 | omi do nos | 217 |
|-------------------|-----|---------------|-----|
| ensrkhistspace | 120 | gridarea | 217 |
| ensrkhisttime | 120 | gridboxavg | 129 |
| ensroc | 120 | gridboxkurt | 129 |
| ensskew | 118 | gridboxmax | 129 |
| ensstd | 118 | gridboxmean | 129 |
| ensstd1 | 118 | gridboxmedian | 129 |
| enssum | 118 | gridboxmin | 129 |
| ensvar | 118 | gridboxrange | 129 |
| ensvar1 | 118 | gridboxskew | 129 |
| eof | 174 | gridboxstd | 129 |
| eof3d | 174 | gridboxstd1 | 129 |
| eofcoeff | 176 | gridboxsum | 129 |
| eofspatial | 174 | gridboxvar | 129 |
| eoftime | 174 | gridboxvar1 | 129 |
| eq | 67 | griddes | 36 |
| eqc | 68 | gridweights | 217 |
| exp | 96 | gt | 67 |
| expr | 92 | gtc | 68 |
| exprf | 92 | TT | |
| D | | H | |
| ${f F}$ | | highpass | 216 |
| fdns | 227 | histcount | 226 |
| fldavg | 123 | histfreq | 226 |
| fldcor | 167 | histmean | 226 |
| fldcovar | 168 | histsum | 226 |
| fldint | 123 | houravg | 139 |
| fldkurt | 123 | hourmax | 139 |
| fldmax | 123 | hourmean | 139 |
| fldmean | 123 | hourmin | 139 |
| fldmedian | 123 | hourpctl | 140 |
| fldmin | 123 | hourrange | 139 |
| fldpctl | 123 | hourstd | 139 |
| fldrange | 123 | hourstd1 | 139 |
| fldskew | 123 | hoursum | 139 |
| fldstd | 123 | hourvar | 139 |
| fldstd1 | 123 | hourvar1 | 139 |
| fldsum | 123 | hurr | 228 |
| fldvar | 123 | т | |
| fldvar1 | 123 | I | |
| fourier | 201 | ifnotthen | 63 |
| | | ifnotthenc | 64 |
| \mathbf{G} | | ifthen | |
| ge | 67 | ifthenc | |
| gec | | ifthenelse | 63 |
| genbic | 179 | import_amsr | 205 |
| genbil | 178 | import_binary | 203 |
| gencon | 182 | import_cmsaf | 204 |
| gencon2 | 184 | info | |
| gendis | 181 | infon | |
| genlaf | 186 | input | 206 |
| genlevelbounds | | inputext | 206 |
| gennn | 180 | inputsrv | 206 |
| gh2hl | 192 | int | 96 |
| gheight | 224 | intlevel | 193 |
| gmtcells | 209 | intlevel3d | 193 |
| gmtxyz | 209 | intlevelx3d | 193 |
| gp2sp | 197 | intntime | 194 |
| gradsdes | 213 | inttime | 194 |
| | | | |

| intyear 195 | 5 mrotuvb 223 |
|---------------|-----------------|
| invertlat 81 | 1 mul 99 |
| invertlev | 1 mulc 98 |
| isosurface | 1 mulcoslat |
| т | muldpm 107 |
| ${f L}$ | muldpy 107 |
| le 67 | • |
| lec 68 | ${f N}$ |
| ln 96 | 6 ndate 33 |
| log10 96 | 6 ne 67 |
| lowpass | 6 nec 68 |
| lt 67 | 7 ngridpoints |
| ltc 68 | 8 ngrids |
| | nint |
| ${f M}$ | nlevel |
| map 30 | |
| maskindexbox | |
| masklonlatbox | |
| maskregion 85 | 11par |
| mastrfu | munic |
| max 99 | nycai |
| maxc 98 | |
| meravg | |
| 9 | |
| . 8 | outputext |
| - 6-6 | output |
| mergetime | outputint |
| merkurt | outputsiv |
| mermax | outputtus |
| mermean | · |
| mermedian | · |
| mermin | paci |
| merpctl 127 | F |
| merrange 127 | F |
| merskew | 7 projuvLatLon |
| merstd | |
| merstd1 127 | • |
| mersum | 7 random |
| mervar 127 | 7 reci 96 |
| mervar1 127 | 7 reducegrid 65 |
| min 99 | 9 regres |
| minc 98 | 8 remap |
| ml2hl 190 | 0 remapavg 130 |
| ml2pl 190 | 0 remapbic 179 |
| monadd 101 | 1 remapbil |
| monavg 145 | 3 remapcon |
| mondiv 101 | 1 remapcon2 |
| monmax | 3 remapdis |
| monmean | 3 remapeta |
| monmin | 3 remapkurt 130 |
| monmul 101 | |
| monpctl 144 | |
| monrange | • |
| monstd | <u>.</u> |
| monstd1 | r |
| monsub | |
| monsum | |
| monvar | |
| monvar1 | |
| 110117011 | υ τοπαρωία 130 |
| | |

| 4 11 | 120 | 1 | r.c |
|------------------|------------------|---------------|-----------------|
| 1 | 130 | selyear | |
| · · | 130 | selyearidx | 60 |
| • | 130 | selzaxis | 54 |
| remapvar1 | | selzaxisname | 54 |
| replace | | 1 | 220 |
| rhopot | | setattribute | 71 |
| rotuvb | 223 | setcalendar | 76 |
| rotuvNorth | 222 | setcindexbox | 85 |
| runavg | 135 | setclonlatbox | 85 |
| runmax | 135 | setcode | 75 |
| runmean | 135 | setcodetab | 75 |
| runmin | 135 | setctomiss | 87 |
| runpctl | 136 | setdate | 76 |
| runrange | 135 | setday | 76 |
| _ ~ | 135 | setgrid | 79 |
| runstd1 | 135 | setgridarea | 79 |
| runsum | 135 | setgridcell | 89 |
| | 135 | setgridmask | 79 |
| | 135 | setgridtype | 79 |
| Tully car I | 100 | | 226 |
| ${f S}$ | | setlevel | 75 |
| samplegrid | 60 | setltype | 75 |
| sealevelpressure | 224 | setmisstoc | 87 |
| _ | 148 | | |
| seasavg | | setmisstodis | |
| seasmax | 148 | setmisstonn | 87 |
| seasmean | 148 | setmissval | 87 |
| seasmin | 148 | setmon | 76 |
| seaspctl | 149 | setname | 75 |
| seasrange | 148 | setparam | 75 |
| seasstd | 148 | setpartabn | 73 |
| seasstd1 | 148 | setpartabp | 73 |
| seassum | 148 | setreftime | 76 |
| seasvar | 148 | | 219 |
| seasvar1 | 148 | setrtoc2 | 219 |
| selcircle | 59 | setrtomiss | 87 |
| selcode | 54 | settaxis | 76 |
| seldate | 56 | settbounds | 76 |
| selday | 56 | settime | 76 |
| select | 51 | settunits | 76 |
| selgrid | 54 | setunit | 75 |
| selgridcell | 60 | | 219 |
| selhour | 56 | setvrange | 87 |
| selindexbox | 58 | setyear | 76 |
| sellevel | | setzaxis | 80 |
| sellevidx | 54 | shifttime | 76 |
| sellonlatbox | - | shiftx | 82 |
| selltype | 54 | shifty | 82 |
| selmonth | | showattribute | 35 |
| selmulti | | showcode | $\frac{33}{34}$ |
| _ | | | |
| selname | _ | showdate | 34 |
| selparam | | showformat | 34 |
| selregion | 59 5 <i>e</i> | showlevel | 34 |
| selseason | | showltype | 34 |
| selsmon | | showmon | 34 |
| selstdname | | showname | 34 |
| seltabnum | 54 | showstdname | 34 |
| seltime | | showtime | 34 |
| seltimestep | 56 | showtimestamp | 34 |
| | | | |

| showyear | timsum |
|--|--|
| sin | timvar 137 |
| sinfo | timvar1 137 |
| sinfon 31 | topo |
| smooth | topvalue 61 |
| smooth9 | trend 171 |
| sp2gp 197 | |
| sp2sp | \mathbf{U} |
| splitcode | uv2dv 199 |
| splitday | uvDestag |
| splitgrid | uvDestus |
| 1 0 | ${f V}$ |
| splithour | varsavg 117 |
| splitlevel | |
| splitmon | |
| splitname 44 | varsmean |
| splitparam 44 | varsmin |
| splitseas 46 | varsrange |
| splitsel | varsstd 117 |
| splittabnum 44 | varsstd1 117 |
| splityear 46 | varssum 117 |
| splityearmon 46 | varsvar |
| splitzaxis 44 | varsvar1 117 |
| sqr 96 | vct 36 |
| sgrt 96 | verifygrid |
| stdatm 220 | vertavg |
| strbre | vertmax |
| strgal | vertmean |
| strwin | vertmin |
| sub | vertrange |
| _ | |
| | |
| subc | vertstd |
| subc 98 subtrend 172 | vertstd1 132 |
| subtrend | vertstd1 132 vertsum 132 |
| subtrend | vertstd1 132 vertsum 132 vertvar 132 |
| subtrend 172 T 96 | vertstd1 132 vertsum 132 |
| T tan 96 tee 40 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 |
| subtrend 172 T 96 tee 40 timavg 137 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 |
| T tan 96 tee 40 timavg 137 timcor 167 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 |
| subtrend 172 T 96 tee 40 timavg 137 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W wct wct 227 |
| T tan 96 tee 40 timcor 167 timcovar 168 timcumsum 116 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W wct 227 Y |
| T tan 96 tee 40 timaye 137 timcor 167 timcovar 168 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W wct wct 227 |
| T tan 96 tee 40 timcor 167 timcovar 168 timcumsum 116 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W wct 227 Y |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W wct 227 Y ydayadd 104 |
| T tan 96 tee 40 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W wct 227 Y ydayadd 104 ydayavg 154 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timmin 137 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W 227 Y ydayadd 104 ydayavg 154 ydaydiv 104 |
| T tan 96 tee 40 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timmin 137 timpctl 138 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W 227 Y ydayadd 104 ydayavg 154 ydaymax 154 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W 227 Y ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W 227 Y ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymul 104 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselmean 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymul 104 ydaypctl 156 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpetl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselmin 133 timselmin 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydaypctl 156 ydayrange 154 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timmin 138 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselmin 133 timselpctl 134 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W W Y ydayadd 104 ydayady 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydaypctl 156 ydayrange 154 ydaystd 154 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timmin 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselmin 133 timselpctl 134 timselrange 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaystd1 154 |
| subtrend 172 T T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselrange 133 timselstd 133 | vertstd1 132 vertsum 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaystd1 154 ydaysub 104 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselrange 133 timselstd 133 timselstd1 133 | vertstd1 132 vertvar 132 vertvar1 132 W W ydayadd 104 ydayavg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaystd1 154 ydaysub 104 ydaysum 154 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselrange 133 timselstd1 133 timselsum 133 timselsum 133 | vertstd1 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayave 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysum 154 ydayvar 154 |
| T tan 96 tee 40 timavg 137 timcor 167 timcowar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselstd 133 timselstd1 133 timselsum 133 timselvar 133 timselvar 133 | vertstd1 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysub 104 ydaysum 154 ydayvar 154 ydayvar1 154 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselstd 133 timselstd1 133 timselsum 133 timselvar 133 timselvar 133 timselvar 133 timselvar 133 | vertstd1 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysub 104 ydaysum 154 ydayvar 154 ydayvar1 154 ydrunavg 163 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselstd 133 timselstd1 133 timselsum 133 timselvar 133 timselvar1 133 timsort 221 | vertstd1 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysum 154 ydayvar 154 ydayvar1 154 ydrunavg 163 ydrunmax 163 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselstd 133 timselstd1 133 timselvar 133 timselvar 133 timselvar 133 timselvar 133 timselvar 133 timsort 221 timstd 137 | vertstd1 132 vertvar 132 vertvar1 132 W W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysum 154 ydayvar 154 ydayvar1 154 ydrunavg 163 ydrunmean 163 |
| T tan 96 tee 40 timavg 137 timcor 167 timcovar 168 timcumsum 116 timmax 137 timmean 137 timpctl 138 timrange 137 timselavg 133 timselmax 133 timselmean 133 timselpctl 134 timselrange 133 timselstd 133 timselstd1 133 timselsum 133 timselvar 133 timselvar1 133 timsort 221 | vertstd1 132 vertvar 132 vertvar1 132 W Y ydayadd 104 ydayaveg 154 ydaydiv 104 ydaymax 154 ydaymean 154 ydaymin 154 ydaymul 104 ydayrange 154 ydaystd 154 ydaystd1 154 ydaysub 104 ydaysum 154 ydayvar 154 ydayvar1 154 ydrunavg 163 ydrunmax 163 |

Operator index

| ydrunpctl | 165 | yseasmin | 160 |
|-------------|------------|--------------|-----|
| ydrunstd | 163 | yseasmul | 106 |
| ydrunstd1 | 163 | yseaspctl | 162 |
| ydrunsum | 163 | yseasrange | 160 |
| ydrunvar | 163 | vseasstd | 160 |
| ydrunvar1 | 163 | yseasstd1 | 160 |
| yearadd | 102 | yseassub | 106 |
| | 146 | | 160 |
| yearavg | _ | yseassum | |
| yeardiv | 102 | yseasvar | 160 |
| yearmax | 146 | yseasvar1 | 160 |
| yearmaxidx | 146 | ${f Z}$ | |
| yearmean | 146 | _ | 26 |
| yearmin | 146 | zaxisdes | 36 |
| yearminidx | 146 | zonavg | 125 |
| yearmonmean | 145 | zonkurt | 125 |
| yearmul | 102 | zonmax | 125 |
| yearpctl | 147 | zonmean | 125 |
| yearrange | 146 | zonmedian | 125 |
| yearstd | 146 | zonmin | 125 |
| yearstd1 | 146 | zonpctl | 125 |
| vearsub | 102 | zonrange | 125 |
| yearsum | 146 | zonskew | 125 |
| yearvar | 146 | zonstd | 125 |
| yearvar1 | 146 | zonstd1 | 125 |
| yhouradd | 103 | zonsum | 125 |
| yhouravg | 150 | zonvar | 125 |
| v _ | 103 | zonvar1 | 125 |
| yhourdiv | | Zonvari | 120 |
| yhourmax | 150 | | |
| yhourmean | 150 | | |
| yhourmin | 150 | | |
| yhourmul | 103 | | |
| yhourrange | 150 | | |
| yhourstd | 150 | | |
| yhourstd1 | 150 | | |
| yhoursub | 103 | | |
| yhoursum | 150 | | |
| yhourvar | 150 | | |
| yhourvar1 | 150 | | |
| ymonadd | 105 | | |
| ymonavg | 157 | | |
| ymondiv | 105 | | |
| ymonmax | 157 | | |
| ymonmean | 157 | | |
| ymonmin | 157 | | |
| ymonmul | 105 | | |
| ymonpctl | 159 | | |
| ymonrange | 157 | | |
| | 157 | | |
| ymonstd | 157 | | |
| ymonstd1 | | | |
| ymonsub | 105 157 | | |
| ymonsum | 157 | | |
| ymonvar | 157 | | |
| ymonvarl | 157 | | |
| yseasadd | 106 | | |
| yseasavg | 160 | | |
| yseasdiv | 106 | | |
| yseasmax | 160 | | |
| yseasmean | 160 | | |
| | | | |