



Layout Managers

Arranging Elements in Windows

© 2001-2003 Marty Hall, Larry Brown, http://www.corewebprogramming.com

Agenda

- How layout managers simplify interface design
- Standard layout managers
 - FlowLayout, BorderLayout, CardLayout, GridLayout, GridBagLayout, BoxLayout
- Positioning components manually
- Strategies for using layout managers effectively
- Using invisible components

Layout Managers

Assigned to each Container

- Give *sizes* and *positions* to components in the window
- Helpful for windows whose size changes or that display on multiple operating systems

Relatively easy for simple layouts

 But, it is surprisingly hard to get complex layouts with a single layout manager

Controlling complex layouts

- Use nested containers (each with its own layout manager)
- Use invisible components and layout manager options
- Write your own layout manager
- Turn some layout managers off and arrange some things manually

but Managers www.corewebprogramming.com

FlowLayout

Default layout for Panel and Applet

Behavior

- Resizes components to their preferred size
- Places components in rows left to right, top to bottom
- Rows are centered by default

Constructors

- FlowLayout()
 - Centers each row and keeps 5 pixels between entries in a row and between rows
- FlowLayout(int alignment)
 - Same 5 pixels spacing, but changes the alignment of the rows
 - FlowLayout.LEFT, FlowLayout.RIGHT, FlowLayout.CENTER
- FlowLayout(int alignment, int hGap, int vGap)
 - Specify the alignment as well as the horizontal and vertical spacing between components (in pixels)

www.corewebprogramming.com

ayout Manager

FlowLayout: Example

```
public class FlowTest extends Applet {
  public void init() {
    // setLayout(new FlowLayout()); [Default]
    for(int i=1; i<6; i++) {
      add(new Button("Button " + i));
    }
}
Applet Viewer: FlowTest.class
Applet

Button 1 Button 2 Button 3 Button 4

Button 5

Applet started.

www.corewebprogramming.com</pre>
```

BorderLayout

- Default layout for Frame and Dialog
- Behavior
 - Divides the Container into five regions
 - Each region is identified by a corresponding BorderLayout constant
 - NORTH, SOUTH, EAST, WEST, and CENTER
 - NORTH and SOUTH respect the preferred height of the component
 - EAST and WEST respect the preferred width of the component
 - CENTER is given the remaining space
- Is allowing a maximum of five components too restrictive? Why not?

Lavout Managers

BorderLayout (Continued)

Constructors

- BorderLayout()
 - · Border layout with no gaps between components
- BorderLayout(int hGap, int vGap)
 - Border layout with the specified empty pixels between regions

Adding Components

- add(component, BorderLayout. REGION)
- Always specify the region in which to add the component
 - CENTER is the default, but specify it explicitly to avoid confusion with other layout managers

Layout Managers

www.corewebprogramming.com

BorderLayout: Example

```
public class BorderTest extends Applet {
  public void init() {
    setLayout(new BorderLayout());
    add(new Button("Button 1"), BorderLayout.NORTH);
    add(new Button("Button 2"), BorderLayout.SOUTH);
    add(new Button("Button 3"), BorderLayout.EAST);
    add(new Button("Button 4"), BorderLayout.WEST);
    add(new Button("Button 5"), BorderLayout.CENTER);
             Applet Viewer: BorderTest.class
             Applet
                           Button 1
             Button 4
                           Button 5
                                        Button 3
                           Button 2
             Applet started.
                                          www.corewebprogramming.com
```

GridLayout

Behavior

- Divides window into equal-sized rectangles based upon the number of rows and columns specified
- Items placed into cells left-to-right, top-to-bottom, based on the order added to the container
- Ignores the preferred size of the component; each component is resized to fit into its grid cell
- Too few components results in blank cells
- Too many components results in extra columns

Layout Manager

www.corewebprogramming.com

GridLayout (Continued)

Constructors

- GridLayout()
 - Creates a single row with one column allocated per component
- GridLayout(int rows, int cols)
 - Divides the window into the specified number of rows and columns
 - Either rows or cols (but not both) can be zero
- GridLayout(int rows, int cols, int hGap, int vGap)
 - · Uses the specified gaps between cells

GridLayout, Example


```
public class GridTest extends Applet {
  public void init() {
     setLayout(new GridLayout(2,3)); // 2 rows, 3 cols
    add(new Button("Button One"));
     add(new Button("Button Two"));
     add(new Button("Button Three"));
    add(new Button("Button Four"));
     add(new Button("Button Five"));
     add(new Button("Button Six"));
                 Applet Viewer: GridTest.class
                  Applet
}
                   Button One
                             Button Two
                                       Button Three
                   Button Four
                             Button Five
                                        Button Six
                 Applet started
                                            www.corewebprogramming.com
```

CardLayout

Behavior

- Stacks components on top of each other, displaying the top one
- Associates a name with each component in window
 Panel cardPanel;

```
CardLayout layout new CardLayout();
cardPanel.setLayout(layout);
...
cardPanel.add("Card 1", component1);
cardPanel.add("Card 2", component2);
...
layout.show(cardPanel, "Card 1");
layout.first(cardPanel);
layout.next(cardPanel);
```



GridBagLayout

Behavior

- Divides the window into grids, without requiring the components to be the same size
 - About three times more flexible than the other standard layout managers, but nine times harder to use
- Each component managed by a grid bag layout is associated with an instance of GridBagConstraints
 - The GridBagConstraints specifies:
 - How the component is laid out in the display area
 - In which cell the component starts and ends
 - How the component stretches when extra room is available
 - Alignment in cells

www.corewebprogramming.com

GridBagLayout: Basic Steps

Set the layout, saving a reference to it

```
GridBagLayout layout = new GridBagLayout();
setLayout(layout);
```

Allocate a GridBagConstraints object

```
GridBagConstraints constraints =
  new GridBagConstraints();
```

Set up the GridBagConstraints for component 1

```
constraints.gridx = x1;
constraints.gridy = y1;
constraints.gridwidth = width1;
constraints.gridheight = height1;
```

Add component 1 to the window, including constraints

```
add(component1, constraints);
```

Repeat the last two steps for each remaining component

www.corewebprogramming.com

GridBagConstraints

- Copied when component added to window
- Thus, can reuse the GridBagConstraints

```
GridBagConstraints constraints =
  new GridBagConstraints();
constraints.gridx = x1;
constraints.gridy = y1;
constraints.gridwidth = width1;
constraints.gridheight = height1;
add(component1, constraints);
constraints.gridx = x2;
constraints.gridy = y2;
add(component2, constraints);
```

www.corewebprogramming.com

GridBagConstraints Fields

- gridx, gridy
 - Specifies the top-left corner of the component
 - Upper left of grid is located at (gridx, gridy)=(0,0)
 - Set to GridBagConstraints.RELATIVE to auto-increment row/column

Lavout Manager

www.corewebprogramming.com

GridBagConstraints Fields (Continued)

- · gridwidth, gridheight
 - Specifies the number of columns and rows the Component occupies

```
constraints.gridwidth = 3;
```

- GridBagConstraints.REMAINDER lets the component take up the remainder of the row/column
- weightx, weighty
 - Specifies how much the cell will stretch in the x or y direction if space is left over

```
constraints.weightx = 3.0;
```

- Constraint affects the cell, not the component (use fill)
- Use a value of 0.0 for no expansion in a direction
- Values are relative, not absolute

www.corewebprogramming.com

GridBagConstraints Fields (Continued)

• fill

 Specifies what to do to an element that is smaller than the cell size

constraints.fill = GridBagConstraints.VERTICAL;

- The size of row/column is determined by the widest/tallest element in it
- Can be NONE, HORIZONTAL, VERTICAL, or BOTH

anchor

 If the fill is set to GridBagConstraints.NONE, then the anchor field determines where the component is placed


constraints.anchor = GridBagConstraints.NORTHEAST;

- Can be NORTH, EAST, SOUTH, WEST, NORTHEAST, NORTHWEST, SOUTHEAST, or SOUTHWEST

Layout Managers

www.corewebprogramming.com

GridBagLayout: Example



www.corewebprogramming.com

20

Layout Managers

GridBagLayout: Example

```
public GridBagTest() {
  setLayout(new GridBagLayout());
  textArea = new JTextArea(12, 40); // 12 rows, 40 cols
  bSaveAs = new JButton("Save As");
  fileField = new JTextField("C:\\Document.txt");
  bOk = new JButton("OK");
  bExit = new JButton("Exit");
  GridBagConstraints c = new GridBagConstraints();
  // Text Area.
  c.gridx
  c.gridy
             = 0;
  c.gridwidth = GridBagConstraints.REMAINDER;
  c.gridheight = 1;
  c.weightx = 1.0;
  c.weighty
              = 1.0;
  add(textArea, c);
                                  www.corewebprogramming.com
```

GridBagLayout: Example (Continued)

```
// Save As Button.
c.gridx = 0;
         = 1;
c.gridy
c.gridwidth = 1;
c.gridheight = 1;
c.weightx = 0.0;
c.weighty = 0.0;
           = GridBagConstraints.VERTICAL;
c.fill
add(bSaveAs,c);
// Filename Input (Textfield).
         = 1;
c.gridwidth = GridBagConstraints.REMAINDER;
c.gridheight = 1;
c.weightx = 1.0;

c.weighty = 0.0;
c.fill
             = GridBagConstraints.BOTH;
add(fileField,c);
                                    www.corewebprogramming.com
```

GridBagLayout: Example (Continued)

```
// Exit Button.
c.gridx = 3;
c.gridwidth = 1;
c.gridheight = 1;
c.weightx = 0.0;
c.weighty = 0.0;
c.fill = GridBagConstraints.NONE;
add(bExit,c);

// Filler so Column 1 has nonzero width.
Component filler =
   Box.createRigidArea(new Dimension(1,1));
c.gridx = 1;
c.weightx = 1.0;
add(filler,c);
...
}
```

GridBagLayout: Result



With Box filler at (2,1)



Without Box filler at (2,1)

www.coreweb programming.com

24

_ayout Managers

Disabling the Layout Manager

Behavior

 If the layout is set to null, then components must be sized and positioned by hand

Positioning components

```
component.setSize(width, height)
```

component.setLocation(left, top)

or

component.setBounds(left, top, width, height)

5 Lavout Manage

www.corewebprogramming.com

No Layout Manager: Example

```
setLayout(null);
Button b1 = new Button("Button 1");
Button b2 = new Button("Button 2");
b1.setBounds(0, 0, 150, 50);
b2.setBounds(150, 0, 75, 50);
                   Applet Viewer: NullTest.class
add(b1);
                   Applet
add(b2);
                       Button 1
                                   Button 2
                                           Button 3
. . .
                                       Button 5
                       Button 4
                    Applet started.
                                  www.corewebprogramming.com
```


Using Layout Managers Effectively

- Use nested containers
 - Rather than struggling to fit your design in a single layout, try dividing the design into sections
 - Let each section be a panel with its own layout manager
- Turn off the layout manager for <u>some</u> containers
- Adjust the empty space around components
 - Change the space allocated by the layout manager
 - Override insets in the Container
 - Use a Canvas or a Box as an invisible spacer

Layout Manage

www.corewebprogramming.com

Nested Containers: Example



-----BorderLayou ---- FlowLayout ----- GridLayout

www.corewebprogramming.com

28

Lavout Managers

Nested Containers: Example

```
public NestedLayout() {
    setLayout(new BorderLayout(2,2));

    textArea = new JTextArea(12,40); // 12 rows, 40 cols
    bSaveAs = new JButton("Save As");
    fileField = new JTextField("C:\\Document.txt");
    bOk = new JButton("OK");
    bExit = new JButton("Exit");

    add(textArea,BorderLayout.CENTER);

    // Set up buttons and textfield in bottom panel.
    JPanel bottomPanel = new JPanel();
    bottomPanel.setLayout(new GridLayout(2,1));

Layout Managers

    www.corewebprogramming.com
```

Nested Containers, Example

Nested Containers: Result



Layout Managar


www.corewebprogramming.com

Turning Off Layout Manager for Some Containers: Example

 Suppose that you wanted to arrange a column of buttons (on the left) that take exactly 40% of the width of the container

```
setLayout(null);
int width1 = getSize().width*4/10;,
int height = getSize().height;
Panel buttonPanel = new Panel();
buttonPanel.setBounds(0, 0, width1, height);
buttonPanel.setLayout(new GridLayout(6, 1));
buttonPanel.add(new Label("Buttons", Label.CENTER));
buttonPanel.add(new Button("Button One"));
...
buttonPanel.add(new Button("Button Five"));
add(buttonPanel);
Panel everythingElse = new Panel();
int width2 = getSize().width - width1,
everythingElse.setBounds(width1+1, 0, width2, height);
www.corewebprogramming.com
```

Turning Off Layout Manager for Some Containers: Result



Layout Managar

www.corewebprogramming.com

Adjusting Space Around Components

- Change the space allocated by the layout manager
 - Most LayoutManagers accept a horizontal spacing (hGap) and vertical spacing (vGap) argument
 - For GridBagLayout, change the insets
- Use a Canvas or a Box as an invisible spacer
 - For <u>AWT</u> layouts, use a <u>Canvas</u> that does not draw or handle mouse events as an "empty" component for spacing.
 - For <u>Swing</u> layouts, add a <u>Box</u> as an invisible spacer to improve positioning of components

Invisible Components in Box Class

Rigid areas

- Box.createRigidArea(Dimension dim)
 - Creates a two-dimensional invisible Component with a fixed width and height

Component spacer =
Box.createRigidArea(new Dimension(30, 40));

Struts

- Box.createHorizontalStrut(int width)
- Box.createVerticalStrut(int width)
 - Creates an invisible Component of fixed width and zero height, and an invisible Component of fixed height and zero width, respectively

Layout Managers

www.corewebprogramming.com

Invisible Components in Box Class (Continued)


Glue

- Box.createHorizontalGlue()
- Box.createVerticalGlue()
 - Create an invisible Component that can expand horizontally or vertically, respectively, to fill all remaining space

- Box.createGlue()

- Creates a Component that can expand in both directions
- A Box object achieves the glue effect by expressing a maximum size of Short.MAX VALUE
- Only apply glue to layout managers that respect the maximum size of a Component

Invisible Components: Example



Layout Managar

www.corewebprogramming.com

BoxLayout

Behavior

- Manager from Swing; available only in Java 2
- Arranges Components either in a horizontal row,
 BoxLayout.X_AXIS, or in a vertical column,
 BoxLayout.Y_AXIS
- Lays out the components in the order in which they were added to the Container
- Resizing the container does not cause the components to relocate
- Unlike the other standard layout managers, the BoxLayout manager cannot be shared with more than one Container

Component Arrangement for BoxLayout

Attempts to arrange the components with:

- Their preferred widths (vertical layout), or
- Their preferred heights (horizontal layout)

Vertical Layout

- If the components are not all the same width,
 BoxLayout attempts to expand all the components to the width of the component with the largest preferred width
- If expanding a component is not possible (restricted maximum size), BoxLayout aligns that component horizontally in the container, according to the x alignment of the component

Layout Manager

www.corewebprogramming.com

Component Arrangement for BoxLayout (Continued)

Horizontal Layout

- If the components are not all the same height,
 BoxLayout attempts to expand all the components to the height of the tallest component
- If expanding the height of a component is not possible,
 BoxLayout aligns that component vertically in the container, according to the y alignment of the component.

www.corewebprogramming.com

Component Alignment for BoxLayout

- Every lightweight Swing component can define an alignment value from 0.0f to 1.0f
 - 0.0 represents positioning the component closest to the axis origin in the container
 - 1.0 represents positioning the component farthest from the axis origin in the container
 - The Component class predefines five alignment values:
 - LEFT_ALIGNMENT (0.0)
 - CENTER ALIGNMENT (0.5)
 - RIGHT ALIGNMENT (1.0)
 - TOP_ALIGNMENT (0.0)
 - BOTTOM_ALIGNMENT (1.0)

Lavout Managers


www.corewebprogramming.com

Component Alignment for BoxLayout (Continued)


- Most Swing components have a default x-axis alignment of center
 - Exceptions include JButton, JComboBox, JLabel, and JMenu, which have x-axis alignment of left
- Set the Component alignment

```
component.setAlignmentX(Component.Xxx_ALIGNMENT)
component.setAlignmentY(Component.Xxx_ALIGNMENT)
```

BoxLayout: Example



• All components have a 0.0 (left) alignment



- The label has a 0.0 alignment
- The buttons have a 1.0 (right) alignment

www.corewebprogramming.com

Summary

- **Default layout managers**
 - Applet and Panel: FlowLayout
 - Frame and Dialog: BorderLayout
- Layout managers respect the preferred size of the component differently
- GridBagLayout is the most complicated but most flexible manager
 - Use GridBagConstraints to specify the layout of each component
- Complex layouts can often be simplified through nested containers
- In AWT use a Canvas as a spacer; in Swing use a Box as a spacer



Questions?

© 2001-2003 Marty Hall, Larry Brown, http://www.corewebprogramming.com