


z/OS Basic Skills: Introduction to ISPF

Unit 3: Using the ISPF utilities Module 3: Using the ISPF move/copy utility













Using the ISPF move/copy utility – Introduction

The ISPF utilities provide a variety of functions for library, data set, and catalog maintenance. In this module, *Using the ISPF move/copy utility*, we'll explore a set of utilities that allow you to copy or move a sequential or partitioned data set (PDS), or move one or more members from one PDS to another.

Copying a data set or member reproduces it in another location, which gives you two versions of the same information. However, moving a data set or member deletes the original copy so you have only one copy of the information in a new location.

Menu Utilities Compilers Options Status ISPF Primary Option Menu Option ===> 3 Settings Terminal and user parameters User ID . : SMCHUGH View Display source data or listings Time. . . : 15:04 Edit Create or change source data Terminal: : 3278 Utilities Perform utility functions Screen. . : 1 Foreground Interactive language processing Language. : ENGLISH Batch Submit job for language processing Appl ID . : PDF Command Enter TSO or Workstation commands TSO logon : IKJACCT Dialog Test Perform dialog testing TSO prefix: SMCHUGH IBM Products IBM program development products System ID : SC76 10 SCLM SW Configuration Library Manager MVS acct. : ACCNT# 11 Workplace ISPF Object/Action Workplace Release . : ISPF 5.7 Enter X to Terminate using log/list defaults F1=Help F2=Split F3=Exit F7=Backward F8=Forward F10=Actions F12=Cancel

Time to complete: 15 - 20 minutes



Using the ISPF move/copy utility — Objectives

Upon completion of this module, you should be able to:

- Access and use the ISPF move/copy utility
- Select move/copy utility options
- Use the main functions of the move/copy utility



Using the ISPF move/copy utility - Accessing the Utility Selection Panel

When you select option 3 on the Primary Options Menu, the Utility Selection Panel appears. This panel typically gives you access to many different utility options. In this series of modules on ISPF utilities, we explore some of the most commonly used utilities:

- · The library utility
- The data set utilities
- The move/copy utility
- The dslist utility
- The compare and search utilities.

```
Utility Selection Panel
                                                                  More:
1 Libraru
               Compress or print data set. Print index listing.
                rename, delete, browse, edit or view members
  Data Set
               Allocate, rename, delete, catalog, uncatalog, or display
                 information of an entire data set
  Move/Copu
              Move, or copy members or data sets
  Dslist
               Print or display (to process) list of data set names.
                Print or display VTOC information
               Reset statistics for members of ISPF library
  Hardcopy
               Initiate hardcopy output
  Transfer
              Download ISPF Client/Server or Transfer data set
              Display, delete, or print held job output
              Create/change an application command table
  Format
              Format definition for formatted data Edit/Browse
12 SuperC
               Compare data sets
                                                              (Standard Dialog
13 SuperCE
               Compare data sets Extended
                                                              (Extended Dialog
14 Search-For Search data sets for strings of data
                                                             (Standard Dialog
15 Search-ForE Search data sets for strings of data Extended (Extended Dialog
                                        F7=Backward F8=Forward F9=Swap
             F2=Split
                           F3=Exit
 10=Actions F12=Cancel
                                                                         04/01
```



Using the ISPF move/copy utility – Starting the ISPF move/copy utility

To access the move/copy utility, select option 3 on the Utility Selection Panel and press the Enter (right Ctrl) key*.

Alternatively, you can jump directly to

Alternatively, you can jump directly to the Data Set Utility panel from the Primary Options Menu by enter 3.3 on the Primary Options Menu and pressing the Enter (right Ctrl) key*.

* The default Enter key for a Personal Communications (PCOMM) terminal emulator session is the right Ctrl key. If you are using a different terminal emulator, or your PCOMM keyboard has been customized, you may have a different Enter key.

```
<u>M</u>enu <u>H</u>elp
                           Utility Selection Panel
Option ===> 3
1 Library
                                                                   Print.
               Compress or print data set. Print index listing.
                 rename, delete, browse, edit or view members
2 Data Set
               Allocate, rename, delete, catalog, uncatalog, or display
                 information of an entire data set
 Move/Copy
               Move, or copy members or data sets
               Print or display (to process) list of data set names.
  Dslist
                Print or display VTOC information
  Reset
               Reset statistics for members of ISPF library
  Hardcopy
               Initiate hardcopy output
  Transfer
               Download ISPF Client/Server or Transfer data set
  Outlist
               Display, delete, or print held job output
  Commands
               Create/change an application command table
11 Format
               Format definition for formatted data Edit/Browse
12 SuperC
               Compare data sets
                                                              (Standard Dialog)
13 SuperCE
                                                              (Extended Dialog)
               Compare data sets Extended
14 Search-For Search data sets for strings of data
                                                              (Standard Dialog)
15 Search-ForE Search data sets for strings of data Extended (Extended Dialog)
F1=Help
              F2=Split
                                         F7=Backward F8=Forward
F10=Actions F12=Cancel
                                                                          04/01
```



Using the ISPF move/copy utility – Exploring the ISPF Move/Copy Utility panel

The Move/Copy Utility panel has several sections. Like most ISPF panels, this one has an action bar at the top.

The options you can select on this panel can operate on either an entire data set or a member.

The library and other data set section is similar to the section on the View Entry panel or the Edit Entry panel. This section is where you specify the name of the data set from which you want to copy or move information.

The password section allows you to enter a password to access password protected data sets.

```
RefList Utilities Help
                              Move/Copy Utility
                 Option section
C Copy data set or member(s)
                                        CP Copy and print
                                        MP Move and print
   Move data set or member(s)
pecify "From" Data Set below, then press Enter key
                 Library and other data set section
                               (--- Options C and CP only
                                  (Blank or pattern for member list,
                                   "x" for all members)
From Other Partitioned or Sequential Data Set:
                                      password protected
F10=Actions F12=Cancel
                                                                          04/014
```



Using the ISPF move/copy utility – Move/copy utility options

You can use the following options on an entire data set or member:

- C copy a data set or members
- M move a data set or members
- CP copy and print
- MP move and print

```
Menu RefList Utilities Help
                             Move/Copy Utility
Option ===>
 C Copy data set or member(s)
                                      CP Copy and print
 M Move data set or member(s)
                                       MP Move and print
Specify "From" Data Set below, then press Enter key
From ISPF Library:
   Project . . . SMCHUGH
                              (--- Options C and CP only
   Group . . . . TEST
   Type . . . . C080L
  Member . . . _____
                                 (Blank or pattern for member list,
                                 "x" for all members)
From Other Partitioned or Sequential Data Set:
  Data Set Name . . .
  Volume Serial . . . _____ (If not cataloged)
Data Set Password . .
                                 (If password protected)
F1=Help
             F2=Split
                                       F7=Backward F8=Forward F9=Swap
F10=Actions F12=Cancel
                                                                       04/014
```



Using the ISPF move/copy utility – Copying or moving a data set

Use the C or M options to either copy or move a data set, respectively. If you also want a printout of the contents of the data set, use CP or MP. ISPF copies the data set contents into the list data set that it submits for batch printing when you end the ISPF session.

If you are searching for a specific member to copy, you can enter up to four library names. ISPF concatenates the search for each of the libraries until it finds the specified member. Concatenated search works only for copy options.

To copy a sequential data set, enter the name of the sequential data set in the Other Data Set Name field. Select your copy or move option, then press Enter.

```
RefList Utilities Help
                              Move/Copy Utility
Option ===> C
  Copy data set or member(s)
                                        CP Copy and print
   Move data set or member(s)
                                        MP Move and print
Specify "From" Data Set below, then press Enter key
From ISPF Library:
                                (--- Options C and CP onlu
  Project . . .
                TEST
                                               TEST2
                 IGYADXIT
From Other Partitioned or Sequential Data Set:
                                                 For the copy options you can
                                                specify up to 4 library names
                                  (If not car
                                                for a concatenated search
Data Set Password
                                  (If password protected)
F1=Help
              F2=Split
                           F3=Exit
                                        F7=Backward F8=Forward
F10=Actions F12=Cancel
                                                                          04/01
```



Using the ISPF move/copy utility – Specifying the target data set

On the panel that follows, enter either the project, group, and type in the To ISPF Library fields or the fully qualified data set name in the To Other Partitioned or Sequential Data Set field. If you left the member field blank or specified an asterisk (the symbol *) in the member name field on the previous panel, the member name field does not appear on this panel.

If you specified a member on the previous panel, the member field appears here. Leave the member field blank to keep the copied member name the same.

If you want the copied member to have a new member name, type the new name in this field.

```
RefList Utilities Help
        From SMCHUGH.TEST.COBOL(IGYADXIT)
Command ===>
To ISPF Library:
  Project . . SMCHUGH
                                   Enter "/" to select option
  Group . . TEST3
                                     Replace like-named members
  Type . . . . COBOL
  Member . . . IGYADX3 (Blank unless member is to be renamed)
To Other Partitioned or Sequential Data Set:
  Data Set Name . . .
                                (If not cataloged)
  Volume Serial . . . _____
                                (If password protected)
Data Set Password . .
To Data Set Options:
  Sequential Disposition
                                Pack Option
                                                   SCLM Setting

    Mod

                                Yes
     2. 01d

 No

                                   Default
 F1=Help
             F2=Split
                          F3=Exit
                                      F7=Backward F8=Forward
                                                               F9=Swap
F10=Actions F12=Cancel
                                                                       10/02
```



Using the ISPF move/copy utility – Specifying copy options

The options on the target data set panel include:

Replace like-named members replaces members in the To data set with a like-named member in the From data set. This means that duplicate members will be deleted from the To data set before they are copied or moved. If you do not select this option, duplicate members will not be copied or moved.

Process member aliases allows the primary member and all alias members to be copied together.

```
RefList Utilities Help
COPY
        From SMCHUGH. TEST. COBOL (IGYADXIT)
Command ===>
To ISPF Library:
                               Options:
   Project . . SMCHUGH
                                  Enter "/" to select option
  Group . . . TEST3
                                  Replace like-named members
   Type . . . COBOL
                                   Process member aliases
  Member . . . IGYADX3 (Blank unless member is to be renamed)
To Other Partitioned or Sequential Data Set:
  Data Set Name . . .
  Volume Serial . . . _____ (If not cataloged)
Data Set Password . .
                              (If password protected)
To Data Set Options:
   Sequential Disposition
                               Pack Option
                                                  SCLM Setting

    3 1. SCLM

    Mod

                               Yes
     01d

 No

                                                       Non-SCLM
                                  Default
                                                     As is
 F1=Help
            F2=Split
                         F3=Exit
                                     F7=Backward F8=Forward
F10=Actions F12=Cancel
```



Using the ISPF move/copy utility – Specifying the target data set options

Specify the To Data Set Options at the bottom of the panel

Under Sequential Disposition, select Mod to add the copied or moved data to the end of an existing data set. Select Old to erase the previous contents of the To data set.

Under Pack Option, select Yes to store the output data set in packed (compressed) format, No to store in unpacked format, or Default to accept the same format as the From data set.

The SCLM Setting specifies what type of edit was last performed on the file. You can set this to SCLM, non-SCLM, or to leave the current setting.

```
RefList Utilities Help
COPY
        From SMCHUGH. TEST. COBOL (IGYADXIT)
Command ===>
To ISPF Library:
                               Options:
  Project . . SMCHUGH
                                  Enter "/" to select option
  Group . . . TEST3
                                  Replace like-named members
   Type . . . COBOL
                                    Process member aliases
  Member . . . IGYADX3 (Blank unless member is to be renamed)
To Other Partitioned or Sequential Data Set:
  Data Set Name . . .
  Volume Serial . . . _____ (If not cataloged)
                               (If password protected)
Data Set Password . .
To Data Set Options:
   Sequential Disposition
                               Pack Option
                                                  SCLM Setting

    SCLM

    Mod

                               Yes
     2. Old

 No

                                                       Non-SCLM
                                  Default
                                                     As is
 F1=Help
             F2=Split
                         F3=Exit
                                     F7=Backward F8=Forward
F10=Actions F12=Cancel
                                                                     10/025
```



Using the ISPF move/copy utility – Moving a single member from one PDS to another - simulation

To move a single member from one PDS to another, enter the complete information (including member name) in the From ISPF Library section of the Move/Copy Utility panel. Then type M on the option line and press the Enter key.

To try a simulation of moving a member from one data set to another, click the Launch button.

```
Menu RefList Utilities Help
                            Move/Copy Utility
Option ===> M
C Copy data set or member(s)
                                      CP Copy and print
M Move data set or member(s)
                                      MP Move and print
Specify "From" Data Set below, then press Enter key
From ISPF Library:
  Project . . . SMCHUGH
                              (--- Options C and CP only
  Group . . . . TEST1
  Tupe . . . . COBOL
  Member . . . IGYADX2
                                 (Blank or pattern for member list,
                                 "x" for all members)
From Other Partitioned or Sequential Data Set:
  Data Set Name . . .
  Volume Serial . . . (If not cataloged)
                                 (If password protected)
Data Set Password . .
                          F3=Exit
F1=Help
             F2=Split
                                      F7=Backward F8=Forward
                                                               F9=Swap
F18=Actions F12=Cancel
                                                                      15/026
```



Using the ISPF move/copy utility – Using the copy/move all option - simulation

To copy or move all members from one PDS to another, enter an asterisk (the symbol *) in the member field of the From ISPF Library.

Carefully consider the Replace likenamed members option on the To data set panel. If you want to allow replacement of like-named members in the target data set, use a slash (the symbol /) to select this option. If you want to prevent replacement of likenamed members in the target data set, do not select this option.

To try a simulation, click on the Launch button.

```
RefList Utilities Help
        From SMCHUGH.TEST.COBOL(*)
Command ===>
                                                                 More:
Specify "To" Data Set Below
To ISPF Library:
                                Options:
  Project . . SMCHUGH
                                   Enter "/" to select option
  Group . . . TEST1
                                   Replace like-named members
                                     Process member aliases
To Other Partitioned or Sequential Data Set:
  Data Set Name . . .
  Volume Serial . . .
                                (If not cataloged)
Data Set Password . .
                                (If password protected)
To Data Set Options:
   Sequential Disposition
                                Pack Option
                                                   SCLM Setting

    Mod

    Yes

     01d
F1=Help
             F2=Split
                                       F7=Backward F8=Forward
F10=Actions F12=Cancel
```



Using the ISPF move/copy utility – Selecting multiple members to copy or move

To select multiple members to copy or move from one PDS to another, fill in the Project, Group, and Type, but leave the Member field blank on the From data set panel. Then press the Enter key. In the To ISPF Library, enter the name of the To data set and press the Enter key. Because you left the member name field blank in the From data set, ISPF displays a member selection list. Type an S next to each member you wish to copy or move.

MOVE SMCHUGH. TEST. COBOL Command ===>			TO SMCHUGH. TEST3. COBOL				
Co	mmand === Name	Prompt	Size	Created	Chan		l ===> <u>PAG</u> ID
0	IGYADXIT	Prompt	179	2006/07/13			
	IGYBCMP		153	2006/07/13	2006/07/13		
	IGYBCMPC		70	2006/07/13	2006/07/13		
	IGYBCMP1		57	2006/07/13	2006/07/13		
9	IGYBCMP2		56	2006/07/13	2006/07/13		
	IGYBLNK		161	2006/07/13	2006/07/13		
	IGYBLNKC		85	2006/07/13	2006/07/13		
	IGYBLNK1		60	2006/07/13	2006/07/13		
	IGYBLNK2		71	2006/07/13	2006/07/13		
	IGYCDOPT		21	2006/07/13	2006/07/13		
	IGYFCMP		44	2006/07/13	2006/07/13		
	IGYFINF		80	2006/07/13	2006/07/13		
	IGYFLNK2		59	2006/07/13	2006/07/13		01101100
	IGYFTPAD		65	2006/07/13	2006/07/13		
	IGYISMKD		76	2006/07/13	2006/07/13		
	IGYIVP		454	2006/07/13	2006/07/13		
	IGYIVP2		7	2006/07/13	2006/07/13		SMCHUG
		E2=Sn1i+	F3=Exit				F9=Swap
	0=Left		F12=Cancel	ro-kirilia r	1-0p	-DOMIN	о-знар



Using the ISPF move/copy utility – Summary

In this module, Using the ISPF move/copy utility, you have learned:

- How to access the move/copy utility
- How to copy and move data sets and data set members from one PDS to another