# Parallel Computing Systems and Applications Introduction

Salvatore Filippone

salvatore.filippone@uniroma2.it

# An Example

How do you forecast weather in Europe?

### An Example

How do you forecast weather in Europe? ECMWF (European Centre for Medium range Weather Forecasts)



source:

• HRES model (2016): 904 millions mesh points;

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h;
```

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h;
```

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

Total: 124 samples;

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- Total: 124 samples;
- How many arithmetic operations per sampling point? 10<sup>4</sup>? 10<sup>5</sup>?

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- Total: 124 samples;
- How many arithmetic operations per sampling point? 10<sup>4</sup>? 10<sup>5</sup>?
- If  $10^5$ , then total

$$1.12 \times 10^{16}$$
.

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- Total: 124 samples;
- How many arithmetic operations per sampling point? 10<sup>4</sup>? 10<sup>5</sup>?
- If  $10^5$ , then total

$$1.12 \times 10^{16}$$
.

• If your laptop executes 10<sup>9</sup> arithmetic operations per second, then:

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- Total: 124 samples;
- How many arithmetic operations per sampling point? 10<sup>4</sup>? 10<sup>5</sup>?
- If  $10^5$ , then total

$$1.12 \times 10^{16}$$
.

• If your laptop executes  $10^9$  arithmetic operations per second, then: you need  $\approx 130$  days

- HRES model (2016): 904 millions mesh points;
- 10-days forecast (240 hours):

```
1–90: resolution 1h; 93–144: resolution 3h; 150–240: resolution 6h.
```

- Total: 124 samples;
- How many arithmetic operations per sampling point? 10<sup>4</sup>? 10<sup>5</sup>?
- If  $10^5$ , then total

$$1.12 \times 10^{16}$$
.

- $\bullet$  If your laptop executes  $10^9$  arithmetic operations per second, then: you need  $\approx 130~\mbox{days}$
- ECMWF recomputes this model every 6 hours!



### Another example

#### Theorem

Perron-Frobenius: given a stocastic matrix (state transitions of a Markov chain)

$$e^{T}Q = e^{T}, \qquad Q \ge 0 \qquad e = (1, 1, 1 \dots 1)^{T}$$

if Q is irreducible, then

- **1**  $\lambda = 1$  is the dominant eigenvalue (all otherrs are strictly smaller);
- 2 There exists a unique eigenvector r>0 corresponding to  $\lambda=1$

$$Qr = \lambda r = r$$
;

• r gives the stationary probability distribution of the Markov chain.

What application are we thinking of?



 $\mathsf{Google} = \mathsf{crawling} + \mathsf{matching} + \mathsf{PageRank}$ 

 $\mathsf{Google} = \mathsf{crawling} + \mathsf{matching} + \mathsf{PageRank}$ 

#### Relevance of a WEB page:

The relevance of page i is the (weighted) average of the relevance of all pages j that link i

$$r_i = \sum_j \frac{r_j}{N_j}$$

 $Google = crawling + matching + \frac{PageRank}{PageRank}$ 

#### Relevance of a WEB page:

The relevance of page i is the (weighted) average of the relevance of all pages j that link i

$$r_i = \sum_j \frac{r_j}{N_j}$$

#### PageRank Algorithm:

- Create a list of all WEB pages and their links (connectivity graph of WWW);
- Assign a weight to each link and build matrix Q;
- Find the eigenvector *r*;

The value of entry i of eigenvector r is taken as a measure of the authoritativeness of page i.

#### Building the matrix:

$$Q_{ij} = \left\{ egin{array}{ll} 1/N_j & ext{if page J has a link to page I} \\ 0 & ext{otherwise} \end{array} 
ight.$$

#### Building the matrix:

$$Q_{ij} = \left\{ egin{array}{ll} 1/N_j & ext{if page J has a link to page I} \\ 0 & ext{otherwise} \end{array} 
ight.$$

Q must be corrected with "teleportation" modeling the fact that from a page with no outlinks we jump to an arbitrary, random web page (and this preserves the irreducibility of the matrix, i.e. the connectivity of the graph).

### The \$ 25.000.000.000 eigenvector

Therefore: at the heart of Google we find the computation of a humonguous eigenvector:

$$Ax = \lambda x$$

with A an  $N \times N$  matrix and N = number of WEB pages in the world;

### ■ The \$ 25.000.000.000 eigenvector

Therefore: at the heart of Google we find the computation of a humonguous eigenvector:

$$Ax = \lambda x$$

with A an  $N \times N$  matrix and N = number of WEB pages in the world; we compute it with the *power method* 

#### **Algorithm 2:** Power method

$$\frac{r^{(0)} \leftarrow r_0;}{\text{for } k = 1, \dots \text{ do}} \\
 \begin{vmatrix} q^{(k)} \leftarrow Ar^{(k-1)}; \\ r^{(k)} \leftarrow q^{(k)} / \|q^{(k)}\| \end{vmatrix}$$

A few tens of iterations; the eigenvector is recomputed every week.

# High Performance Computer Architectures and Parallelism


### Computer Architecture

Organization and interaction of the various components making up a computer

- Nomenclature originally introduced in the 60s (IBM 360)
- Basic idea: Von Neumann architecture;
- Evolution over time:
  - "Traditional" systems;
  - "Pipelined" computers;
  - Vector CPUs;
  - Microprocessors;
  - RISC (Reduced Instruction Set Computer) CPUs;
  - SMPs (Symmetric MultiProcessor);
  - MPPs (Massively Parallel Processor).
  - Multi-core computers
  - GPU (Graphical Processing Units) accelerators;

CPU: Central Processing Unit.

## Uon Neumann Architecture



Instruction execution is defined on a sequence of discrete time steps

### Von Neumann Architecture

#### Basic principles:

- Memory is a set of storage cells, identified by an address (a number).
- CPU has a set of registers, holding data from memory;
- Arithmetic instructions are only executed in the CPU (RISC: only on data already in the registers);
- Special registers are used to control the execution sequence;
- Memory holds the instructions making up a program;
- Memory also holds data on which the instructions work.

Note: the ability to interpret the contents of memory as *either* data or instruction is what makes compilers possible! Some areas of memory may be *tagged* as being code, but there is nothing *intrinsic* to the memory contents per se.

### Von Neumann/RISC Architecture

```
Instruction classes:
```

```
Data Movement: LW R1,D(R2) SW R1,D(R2) MOV.D
```

Arithmetics: ADD R3,R2,R1

Floating-point: MUL.D F3,F2,F1

Control: BEQ BNE J JALR

### Von Neumann/RISC Architecture

```
Example:
```

```
c = a + b; LW\ R1,DA(R7) \qquad R1 \leftarrow MEM[DA+[R7]] \\ LW\ R2,DB(R7) \qquad R2 \leftarrow MEM[DB+[R7]] \\ ADD\ R3,R1,R2 \qquad R3 \leftarrow [R1]+[R2] \\ SW\ R3,DC(R7) \qquad MEM[DC+[R7]] \leftarrow [R3] \\ with [] \ we denote access to contents (of a register or of a memory location)
```

### ■ Von Neumann/RISC Architecture

#### Write Access

causes the data sent by the CPU to be written into the memory location specified by the address. Typically, a write access will only occur when a STORE instruction is executed by the CPU. Write accesses to different addresses will go to different parts of the memory.

#### Read Access

causes the data residing at the specified address to be returned to the CPU. Typically, a read access will only occur when a LOAD instruction is executed by the CPU. Read accesses to different addresses will read data from different parts of the memory.

### Processor history

- Accumulator (1948-1956)
- ② Stack Processors (1960s)
- General-Purpose Register processors (1956-)
- Microprocessors (1970s-)
- Vector Processors (1970-)
- **o** RISC (1980-)
- Multi-core
- Many-core (GPUs)

Intel x86 is a peculiar hybrid, integer general-purpose, floating-point stack, apparently CISC, but really a RISC on the inside, "classic" SSE is almost but not quite a vector coprocessor, but Skylake is a vector processor. . .

- Evolution of processor vs. memory technology: differential speed;
- Paging and Virtual Memory;
- Cache memories;

Essential to proper design of software.


### Facts of (memory) life:

Memory can be

- Large;
- Fast;
- Cheap;

but you can choose only two;

Computer architects and programmers want all three anyway! Hence the concept of *Memory Hierarchy* 



#### Why does it work?

- Memory access is latency bound, but data are transferred in blocks;
- Programming locality principles:
  - Temporal locality: if a program accesses a memory location now it will likely access it again in the near future;
  - Spatial locality: if a program accesses a memory location now, it will likely access nearby locations as well.

#### Assume we have two levels:

Cache: Uniform cost: 1 cycle;

Main: 20 cycles for start of blocks of 32 items, with items after the first being made available at full speed.

Average cost of sequential access of 32 items:

$$T_{avg} = \frac{20 \times 1 + 1 \times 31}{32} = 1.59$$

### Performance Metrics

```
Most important:
```

Time to complete a task;

However, there are different viewpoints:

User: Time to response (single task);

Administrator: Throughput (multiple tasks);

Elapsed time: "wall clock"

CPU time: time spent in the CPU on account of a specific task

What is the program with which you perform the measurements?

### Performance Metrics

Benchmark: a program in some ways "representative" of actual usage

- Real applications;
- Modified (simplified) Real applications (aka MiniApps);
- & Kernels;
- Toys;
- Synthetic Benchmarks;

Units of measure: time, MIPS (million instructions per second), MFLOPS (million floating-point operations per second).

Example: LINPACK & friends (see http://www.top500.org)

### Performance Metrics

#### Fundamental equation of computer performance:

$$CPU = IC \times CPI \times Ct$$

IC Instruction count: algorithm, language—compiler, instruction set;

CPI Cycles per Instruction: instruction set, organization of the CPU;

Ct Cycle time: organization of the CPU, semiconductor technology;

Concentrating on CPU time for now (i.e. looking at the CPU internals only).

### Moore's Law

Number of components in an integrated circuit doubles every 18-24 months

... and all other performance measures will follow. This has been true from 1970 for more than 30 years, entailing a performance improvement of  $2^{20}$ ! Since 2008 we are at a density plateau

Problems: Power dissipation, components costs, memory costs.


Solution: Use parallelism

### Moore's law


#### Moore's Law – The number of transistors on integrated circuit chips (1971-2016) Our World



Moore's law describes the empirical regularity that the number of transistors on integrated circuits doubles approximately every two years. This advancement is important as other aspects of technological progress – such as processing speed or the price of electronic products – are strongly linked to Moore's law.



# U CPU Internals: the Execution Cycle



### CPU Internals: the Execution Cycle

#### LW R1,DA(R2)

- IF Instruction fetch: IR ← MEM[PC]
- ID Instruction decode: recognize LW
- EXE Execute: address buffer AB ← DA+[R2]
- MEM Memory: data buffer DB ← MEM[AB]
  - WB Write back:  $R1 \leftarrow [DB]$

Buffer: additional internal register, not addressable explicitly by the programmer.

#### What is a machine cycle?

- One instruction per cycle: means that the machine cycle is the time to complete all five of the above, e.g. 5 ns, with CPI = 1;
- One phase per cycle: e.g. 1 ns, but then we have CPI = 5.

# Pipelining

Can we have our cake and eat it too?

## Pipelining

Can we have our cake and eat it too?

### Definition (Pipelining)

A technique to reduce CPI by increasing throughput

IF	ID	EX	MEM	WB		
	IF	ID	EX	MEM	WB	
		IF	ID	EX	MEM	WB
1	2	3	4	5	6	7

Average instruction time over n instructions:

$$T_{avg} = \frac{T_{tot}}{n} = \frac{T_s + n}{n} \underset{n \to \infty}{\rightarrow} 1$$

### Pipelining

#### Fundamental issue:

How do we provide a stream of mutually independent instructions?

#### A Simple Execution Sequence

- 1 LW R1,DA(R7) R1  $\leftarrow$  MEM[DA+[R7]]
- 2 LW R2,DB(R7) R2  $\leftarrow$  MEM[DB+[R7]]
- $\P$  SW R3,DC(R7) MEM[DC+[R7]]  $\leftarrow$  [R3]

instruction 3 has to wait for completion of 1 and 2, thus generating a "bubble" in the pipeline.

#### Solution strategies in hardware:

- Vector processors;
- RISC Processors (and system);

Solutions depend on **BOTH** programmer and compiler technology.