Guidewire ClaimCenter®

ClaimCenter Installation Guide

RELEASE 8.0.2



Copyright © 2001-2014 Guidewire Software, Inc. All rights reserved.

Guidewire, Guidewire Software, Guidewire ClaimCenter, Guidewire PolicyCenter, Guidewire BillingCenter, Guidewire Reinsurance Management, Guidewire ContactManager, Guidewire Vendor Data Management, Guidewire Client Data Management, Guidewire Rating Management, Guidewire InsuranceSuite, Guidewire ContactCenter, Guidewire Studio, Guidewire Product Designer, Guidewire Live, Guidewire DataHub, Guidewire InfoCenter, Guidewire Standard Reporting, Guidewire ExampleCenter, Guidewire Account Manager Portal, Guidewire Claim Portal, Guidewire Policyholder Portal, ClaimCenter, BillingCenter, PolicyCenter, InsuranceSuite, Gosu, Deliver Insurance Your Way, and the Guidewire logo are trademarks, service marks, or registered trademarks of Guidewire Software, Inc. in the United States and/or other countries.

All other trademarks are the property of their respective owners.

This material is confidential and proprietary to Guidewire and subject to the confidentiality terms in the applicable license agreement and/or separate nondisclosure agreement.

Guidewire products are protected by one or more United States patents.

Product Name: Guidewire ClaimCenter

Product Release: 8.0.2

Document Name: ClaimCenter Installation Guide

Document Revision: 20-May-2014

Contents

	About ClaimCenter Documentation	
	Conventions in This Document	
1	Introduction to Installation	9
	Selecting an Installation Scenario	
	List of Installation Options	
	Viewing the Development and Production Environments	13
2	Preparing a ClaimCenter Environment	15
	Installation Environments Overview	
	Production Environments	16
	Development Environments	16
	Creating Accounts to Run ClaimCenter	16
	Configuring the Application Server	
	General Guidelines for the Application Server	
	Considerations for a Clustered Application Server Environment	
	Configuring the JVM for Environments Without Graphics	
	JVM Heap Size Considerations	
	Load Balancers	
	Optional Components	
	Configuring JBoss	
	Configuring WebLogic	
	Configuring WebSphere	
	Configuring the Database	
	Database Permissions	
	Configuring Linguistic Search Collation	
	Configuring Compression.	
	Configuring DB2 for ClaimCenter	
	Configuring Oracle for ClaimCenter	
	Configuring SQL Server for ClaimCenter	37
	Development Workstation Information	41
	Client Information.	41
	Installing Java	
	Installing the Dynamic Code Evolution Virtual Machine	
	Installing Ant	
	Setting Environment Variables	
	Documenting Your Environment	44
3	Installing a ClaimCenter Development Environment	45
	Using Multiple ClaimCenter Development Instances	46
	Installing the QuickStart Development Environment	
	Advantages to Using the QuickStart Software	
	QuickStart Development Environment Prerequisites	
	Installing with QuickStart	
	QuickStart Commands	
	QuickStart Application Server	
	Troubleshooting QuickStart	49



	Installing a Tomcat Development Environment. Tomcat Development Environment Prerequisites Building a ClaimCenter Development Environment with Tomcat. Using the QuickStart Database Setting the Database Configuration and Mode Limitations to the QuickStart Database Additional References. Using SQL Server or Oracle in a Development Environment Configuring Archiving for Development Testing Installing Sample Data	. 49 . 49 . 51 . 52 . 52 . 52
4	Installing a ClaimCenter Production Environment	55
-	Unpacking the Configuration Files	
	Key ClaimCenter gwcc Commands	
	Configuring a Database Connection	
	The <database> Element</database>	
	Mapping Logical Tablespaces to Physical Tablespaces	
	Configuring Options for Individual Tables	
	Defining Table Groups	
	Defining the JDBC URL	
	Specifying a Database Password	
	Enabling SQL Server JDBC Logging	
	Configuring ClaimCenter to Use a JNDI Data Source	
	Creating a JNDI Data Source on JBoss.	
	Creating a JNDI Data Source on WebLogic	. 71
	Creating a JNDI Data Source on WebSphere	
	Deploying ClaimCenter to the Application Server	
	Installing a JBoss Production Environment	. 78
	Installing a Tomcat Production Environment	. 79
	Installing a WebLogic Production Environment	
	Installing a WebSphere Production Environment	. 82
5	Additional ClaimCenter Setup Tasks	85
	Free-text Search Setup	
	Free-text Search Setup Overview	
	Setting Up Free-text Search for Embedded Operation	
	Setting Up Free-text Search for JBoss	
	Setting Up Free-text Search for Tomcat	. 89
	Setting Up Free-text Search for WebLogic	. 90
	Setting Up Free-text Search for WebSphere	. 91
	Setting Up the Free-text Batch Load Command	. 94
	Changing the Superuser Password	
	Generating Java and SOAP API Libraries	
	Enabling Integration between ClaimCenter and PolicyCenter	. 97
	Enabling Large Loss Notification Integration	
	Enabling Archiving or Disabling Archiving Work Queue	
	Starting ClaimCenter on the Application Server	
	Starting ClaimCenter on JBoss	
	Starting ClaimCenter on Tomcat on Windows	
	Starting ClaimCenter on WebLogic	
	Starting ClaimCenter on WebSphere	103
	Connecting to ClaimCenter with a Web Client	
	Additional Installation Information	
	Integrating ClaimCenter with ContactManager	
	Running ClaimCenter in a Clustered Environment	104



6	Commands Reference	105
	Tuning Command Line Tool Memory Settings	105
	QuickStart Command Tools	106
	Build Tools	106



About ClaimCenter Documentation

The following table lists the documents in ClaimCenter documentation.

Document	Purpose
InsuranceSuite Guide	If you are new to Guidewire InsuranceSuite applications, read the <i>InsuranceSuite Guide</i> for information on the architecture of Guidewire InsuranceSuite and application integrations. The intended readers are everyone who works with Guidewire applications.
Application Guide	If you are new to ClaimCenter or want to understand a feature, read the <i>Application Guide</i> . This guide describes features from a business perspective and provides links to other books as needed. The intended readers are everyone who works with ClaimCenter.
Upgrade Guide	Describes how to upgrade ClaimCenter from a previous major version. The intended readers are system administrators and implementation engineers who must merge base application changes into existing ClaimCenter application extensions and integrations.
New and Changed Guide	Describes new features and changes from prior ClaimCenter versions. Intended readers are business users and system administrators who want an overview of new features and changes to features. Consult the "Release Notes Archive" part of this document for changes in prior maintenance releases.
Installation Guide	Describes how to install ClaimCenter. The intended readers are everyone who installs the application for development or for production.
System Administration Guide	Describes how to manage a ClaimCenter system. The intended readers are system administrators responsible for managing security, backups, logging, importing user data, or application monitoring.
Configuration Guide	The primary reference for configuring initial implementation, data model extensions, and user interface (PCF) files. The intended readers are all IT staff and configuration engineers.
Globalization Guide	Describes how to configure ClaimCenter for a global environment. Covers globalization topics such as global locales, languages, date and number formats, names, currencies, addresses, and phone numbers. The intended readers are configuration engineers who work with locales and languages.
Rules Guide	Describes business rule methodology and the rule sets in ClaimCenter Studio. The intended readers are business analysts who define business processes, as well as programmers who write business rules in Gosu.
Contact Management Guide	Describes how to configure Guidewire InsuranceSuite applications to integrate with ContactManager and how to manage client and vendor contacts in a single system of record. The intended readers are ClaimCenter implementation engineers and ContactManager administrators.
Best Practices Guide	A reference of recommended design patterns for data model extensions, user interface, business rules, and Gosu programming. The intended readers are configuration engineers.
Integration Guide	Describes the integration architecture, concepts, and procedures for integrating ClaimCenter with external systems and extending application behavior with custom programming code. The intended readers are system architects and the integration programmers who write web services code or plugin code in Gosu or Java.
Gosu Reference Guide	Describes the Gosu programming language. The intended readers are anyone who uses the Gosu language, including for rules and PCF configuration.
Glossary	Defines industry terminology and technical terms in Guidewire documentation. The intended readers are everyone who works with Guidewire applications.



Conventions in This Document

Text style	Meaning	Examples
italic	Emphasis, special terminology, or a book title.	A destination sends messages to an external system.
bold	Strong emphasis within standard text or table text.	You must define this property.
narrow bold	The name of a user interface element, such as a button name, a menu item name, or a tab name.	Next, click Submit.
monospaced	Literal text that you can type into code, computer output, class names, URLs, code examples, parameter names, string literals, and other objects that might appear in programming code. In code blocks, bold formatting highlights relevant sections to notice or to configure.	Get the field from the Address object.
monospaced italic	Parameter names or other variable placeholder text within URLs or other code snippets.	Use getName(first, last). http://SERVERNAME/a.html.

Support

For assistance with this software release, contact Guidewire Customer Support:

- At the Guidewire Resource Portal http://guidewire.custhelp.com
- $\bullet \ \ By \ email-{\tt support@guidewire.com}$
- By phone -+1-650-356-4955

chapter 1

Introduction to Installation

This guide describes how to install ClaimCenter. It describes installation options that are available and provides guidance on selecting which option to choose.

The ClaimCenter Installation Guide includes:

- An overview that discusses the different ways to install ClaimCenter that starts with this topic.
- "Preparing a ClaimCenter Environment" on page 15 provides steps to prepare a development or production environment for ClaimCenter.
- "Installing a ClaimCenter Development Environment" on page 45 explains how to install a ClaimCenter development environment using the QuickStart server and database or Tomcat.
- "Installing a ClaimCenter Production Environment" on page 55 explains how to deploy ClaimCenter to an application server and database server production environment.
- "Additional ClaimCenter Setup Tasks" on page 85 explains optional installation tasks you may want to
 perform after you complete the installation and deployment of a ClaimCenter development or production
 environment.
- "Commands Reference" on page 105 lists and describes the QuickStart and build commands. Other ClaimCenter command utilities are described in "ClaimCenter Administrative Commands" on page 181 in the *System Administration Guide*.

This topic includes:

- "Selecting an Installation Scenario" on page 10
- "Viewing the Development and Production Environments" on page 13



Selecting an Installation Scenario

Choose an installation scenario based on the role of the person who uses the ClaimCenter installation. The following table lists installation scenarios that Guidewire recommends for each role.

Role	Description	Consult this Section	
Demonstrator or Trainer	Starts up the application quickly, loads sample data and demonstrates features.	"Installation Environments Overview" on page 15	
		"Installing a ClaimCenter Development Environment" on page 45	
Application Developer	Changes the behavior of the application including the user interface, rules, and appli-	"Installation Environments Overview" on page 15	
	cation logic.	"Installing a ClaimCenter Development Environment" on page 45	
Integration Developer	Develops software to connect ClaimCenter to external systems.	"Installation Environments Overview" on page 15	
		"Installing a ClaimCenter Development Environment" on page 45	
Conversion Developer	Performs analysis and mapping of legacy data structures to Guidewire application	"Installation Environments Overview" on page 15	
	data model.	"Installing a ClaimCenter Development Environment" on page 45	
Build master deploying to testing and production	Deploys finished application to test and production environments.	"Installation Environments Overview" on page 15	
		"Installing a ClaimCenter Production Environment" on page 55.	



List of Installation Options


If you are still questioning your installation options based on your role, this section can provide additional clarification.


Install element	Bundled or Optional	Good to know	Links for more Information
QuickStart Application Server	Bundled	You can immediately use the Quick- Start server without configuring it. It	"Advantages to Using the Quick- Start Software" on page 46
		does not build a WAR or EAR file which is necessary before deployment with other servers.	"QuickStart Application Server" on page 48
		The QuickStart application server can be used for demonstration or development environments. Guidewire does not support QuickStart for a production environment.	
		ClaimCenter can be quickly started in development (dev) mode using the steps in "Installing the QuickStart Development Environment" on page 46. ClaimCenter can not run in production (prod) mode on QuickStart. For more information on server modes, see "Server Modes and Run Levels" on page 60 in the System Administration Guide.	
JBoss Application Server	Optional	Suitable for production environments.	"Configuring the Application Server" on page 17
			"Installing a JBoss Production Environment" on page 78
Tomcat Application Server	omcat Application Server Optional Suitable for production environments. You can use Tomcat instead of the QuickStart server for development work although it requires additional		"Configuring the Application Server" on page 17
			"Installing a Tomcat Develop- ment Environment" on page 49
		configuration.	"Installing a Tomcat Production Environment" on page 79
WebSphere Application Server	Optional	Suitable for production environments.	"Configuring the Application Server" on page 17
			"Installing a WebSphere Production Environment" on page 82
WebLogic Application Server	Optional	Suitable for production environments.	"Configuring the Application Server" on page 17
			"Installing a WebLogic Production Environment" on page 80



Install element	Bundled or Optional	Good to know	Links for more Information
QuickStart Database	Bundled	You can immediately use the Quick- Start database in file mode.	"Advantages to Using the Quick- Start Software" on page 46
		ClaimCenter creates and stores the database files within the tmp directory of the local drive. You can customize this location.	"Using the QuickStart Database" on page 51
		You can use the QuickStart database for demonstration or development environments. Guidewire does not support QuickStart for a production environment.	
		Guidewire does not support upgrades to the QuickStart database. Configuring your application sometimes requires extending the data model, which might require dropping the database.	
		You can not have more than one connection at a time.	
Oracle Database	Optional	You can use Oracle for development and production.	"Configuring the Database" on page 26
			"Configuring Oracle for ClaimCenter" on page 32
			"Configuring a Database Connection" on page 62
SQL Server Database	Optional	You can use SQL Server for development and production.	"Configuring the Database" on page 26
			"Configuring SQL Server for ClaimCenter" on page 37
			"Configuring a Database Connection" on page 62

Viewing the Development and Production Environments





Dotted lines indicate actions that you perform. For example, you create a WAR or EAR file from your configured development environment and move it to the production server.

To assist with this development and testing process, Guidewire bundles the following with the ClaimCenter application:

- · A QuickStart development server
- · A QuickStart database
- · A QuickStart test server that you cannot control
- A QuickStart test database that is separate from the QuickStart database

Guidewire bundles the QuickStart test server and test database for testing. These components are internally controlled. You can use either the bundled QuickStart development server bundled with ClaimCenter or use an external application server such as Tomcat. If you use the QuickStart method, then the default development server is Jetty and the database is H2. Guidewire does not support the QuickStart application server or database for a production environment.



chapter 2

Preparing a ClaimCenter Environment

This topic describes how to install and configure necessary system components so that your network can support ClaimCenter. It also includes preparatory steps for deploying a production instance of ClaimCenter.

The versions of third-party products that Guidewire supports for this release are subject to change without notice. See the *Guidewire Platform Support Matrix* for current system and patch level requirements. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

This topic includes:

- "Installation Environments Overview" on page 15
- "Creating Accounts to Run ClaimCenter" on page 16
- "Configuring the Application Server" on page 17
- "Configuring the Database" on page 26
- "Development Workstation Information" on page 41
- "Client Information" on page 41
- "Installing Java" on page 41
- "Installing Ant" on page 43
- "Setting Environment Variables" on page 43
- "Documenting Your Environment" on page 44

Installation Environments Overview

ClaimCenter has a typical J2EE three-tier architecture: client, application server, and database server. For the application to function, install and configure each tier correctly. Before you get started, have the appropriate software versions to support ClaimCenter. Guidewire strongly recommends that you obtain support contracts with vendors for all tiers of your application infrastructure.



Although production environments can run on operating systems other than Windows, Development environments must be on Windows. However, you can build ClaimCenter on a non-Development Unix system prior to deploying ClaimCenter.

See also

- "Development Workstation Information" on page 41
- "Build Scripts Supported on Unix" on page 113

Production Environments

Guidewire strongly recommends that you allocate dedicated hardware for the application server and database server tiers. Reserve hardware solely for ClaimCenter. Using dedicated hardware is best for performance and for isolating the cause of any issues that arise.

Although production environments can run on operating systems other than Windows, you must build ClaimCenter on a Windows system prior to deploying ClaimCenter.

ClaimCenter requires a 64-bit operating system and JVM for a production installation.

To install a production environment, first review all of the information in "Preparing a ClaimCenter Environment" on page 15. Then proceed to "Installing a ClaimCenter Production Environment" on page 55.

Development Environments

Guidewire supports the use of the bundled QuickStart application server or Tomcat for development environments.

For development, all builds must use the Oracle JDK. See "Development Workstation Information" on page 41.

For all development environments, review the following topics:

- "Development Workstation Information" on page 41
- "Client Information" on page 41
- "Creating Accounts to Run ClaimCenter" on page 16 (Windows information only)
- "Installing Java" on page 41
- "Installing Ant" on page 43
- "Setting Environment Variables" on page 43
- "Documenting Your Environment" on page 44

If using the Tomcat application server in a development environment, also review:

- "Configuring the Application Server" on page 17
- "Configuring Tomcat" on page 22

If using an Oracle or SQL Server database server in a development environment, also review:

• "Configuring the Database" on page 26

After reviewing the relevant development environment information, proceed to "Installing a ClaimCenter Development Environment" on page 45.

Creating Accounts to Run ClaimCenter

It is important that the software processes that support your ClaimCenter application run with the appropriate permissions. How you set up these accounts depends on whether the application server environment is UNIX-based or Windows.



If your network servers are Windows systems, create a user with the Log on as a service right. Ensure that this user is not a member of any groups. Then, start the application server process as this user to ensure that ClaimCenter is run with the correct rights.

If you run Tomcat on Microsoft Windows, install the ClaimCenter server as a Windows service. See "Installing Tomcat as a Windows Service" on page 23 for more information.

For a UNIX-based operating system, the ClaimCenter-related processes must run in non-privileged (user) mode. A process in non-privileged mode can access only its own memory. To ensure the ClaimCenter processes run in the correct mode, create a specific user account on each server and run the corresponding applications under these accounts.

Configuring the Application Server

The ClaimCenter application server relies on a third-party servlet container for execution and connection services. This topic includes some adjustments to supported application servers.

Guidewire supports JBoss, Tomcat, WebLogic and WebSphere for production environments. Guidewire supports the use of the bundled QuickStart application server or Tomcat for development environments. Guidewire also supports JBoss, WebLogic and WebSphere application servers for development use. However, these application servers do not reload resources modified in Studio without a rebuild and redeploy. Therefore, these application servers are not ideal for development work.

See the *Guidewire Platform Support Matrix* for information about which specific application server versions Guidewire supports for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

For information on configuring the QuickStart application server, see "QuickStart Application Server" on page 48.

This topic includes the following:

- "General Guidelines for the Application Server" on page 17
- "Considerations for a Clustered Application Server Environment" on page 18
- "Configuring the JVM for Environments Without Graphics" on page 19
- "JVM Heap Size Considerations" on page 19
- · "Load Balancers" on page 21
- "Optional Components" on page 21
- "Configuring JBoss" on page 21
- "Configuring Tomcat" on page 22
- "Configuring WebLogic" on page 24
- "Configuring WebSphere" on page 24

General Guidelines for the Application Server

Do not include spaces in the installation path of the application server.

Run the application server on hardware supported by the application server provider. Guidewire can provide assistance with hardware requirements for your production implementation.

Only use the JDK or JRE specified in the *Guidewire Platform Support Matrix* or a higher maintenance release. Tomcat requires the JRE only.



Do not run multiple Guidewire applications or multiple instances of a single Guidewire application under a single JVM in a production environment. Guidewire does not support this configuration. Each Guidewire application in a production environment must run in a JVM reserved for that application.

ClaimCenter synchronizes with the database clock. The application server and database server must be within the same time zone. The maximum difference allowed between the application server and database server is 29 minutes.

Considerations for a Clustered Application Server Environment

This topic includes information for clustered environments.

See also

- "Clustering Application Servers" on page 79 in the System Administration Guide
- "Clustering Parameters" on page 45 in the Configuration Guide

Clustering Parameters

The config.xml file includes several parameters to configure a clustered environment, including:

- ClusteringEnabled
- ClusterMulticastAddress
- ClusterMulticastPort
- ClusterMulticastTTL
- ClusterProtocolStack
- ClusterProtocolStackOption1
- ClusterProtocolStackOption2
- ConfigVerificationEnabled
- PDFMergeHandlerLicenseKey

Using ENCRYPT JGroups Protocol

If a cluster is set up in different subnets and there is a risk of traffic sniffing between these subnets, Guidewire recommends using the ENCRYPT JGroups protocol to encrypt messages. This protocol may be configured using the ClusterProtocolStack parameter by including it in the JGroups protocol stack.

Refer to http://jgroups.org/manual/html/protlist.html#d0e6465.

Using TCP Instead of UDP

By default, ClaimCenter uses UDP (User Datagram Protocol) for communication between servers in a clustered environment. For a cluster with fewer than ten nodes, you can use TCP (Transmission Control Protocol) if you prefer. To use TCP, set the ClusterProtocolStack parameter in config.xml to the following:

```
<param name="ClusterProtocolStack"
   value="TCP(bind_port=${jgroups.bind_port};bind_addr=${jgroups.bind_addr}):
gw.JDBC_PING(timeout=5000;num_initial_members=4;num_ping_requests=3;updateInterval=30000):
MERGE2(max_interval=30000;min_interval=10000):
FD(timeout=5000;max_tries=5):
VERIFY_SUSPECT(timeout=3000;num_msgs=3):
pbcast.NAKACK(retransmit_timeout=600,1200,2400,4800;discard_delivered_msgs=true):
UNICAST():
pbcast.STABLE(desired_avg_gossip=5000;max_bytes=4M):
pbcast.GMS(join_timeout=6000;merge_timeout=10000;print_local_addr=true)</pre>
```

Pass two JVM parameters when starting the server: -Djgroups.bind_addr and -Djgroups.bind_port. The values you pass replace the corresponding placeholders in config.xml. Set jgroups.bind_addr to the IP address of the batch server. Set -Djgroups.bind_port to the port you want to use for cluster communication.



Disabling IPv6 in Clustered Environments

Some JDKs do not function correctly with IPv6. Disable IPv6 on any application server hosting Guidewire applications. To disable IPv6, set the following java option for your application server JVM:

```
java.net.preferIPv4Stack=true
```

With Tomcat, add this option to the CATALINA_OPTS environment variable.

With WebLogic, either add this option to the JAVA_OPTIONS environment variable or directly modify the setDomainEnv.sh file for the domain hosting ClaimCenter. If you modify JAVA_OPTIONS, the option applies to all WebLogic instances on that server. If you modify setDomainEnv.sh, the option only applies to that domain. If you modify setDomainEnv.sh, add the option to the line:

```
JAVA_OPTIONS="${JAVA_OPTIONS} ${JAVA_PROPERTIES} -Dwlw.iterativeDev=${iterativeDevFlag}
-Dwlw.testConsole=${testConsoleFlag} -Dwlw.logErrorsToConsole=${logErrorsToConsoleFlag}"
```

With WebSphere, add this option using the Administrative Console. Navigate to Servers \rightarrow Application servers \rightarrow server. In the Server Infrastructure section, click Java and process management \rightarrow Process definition \rightarrow Java virtual machine \rightarrow Custom Properties. Then add the java.net.preferIPv4Stack=true option.

For more information on setting JVM options, see the documentation provided with your application server.

Configuring RedHat for Cluster Communication

In a clustered application server environment, ClaimCenter uses JGroups for some multicast communication between servers within the cluster. In a clustered RedHat environment, the default network setup does not enable proper multicast communication within the cluster.

The fix is relatively easy. Remove any line in etc/hosts that associates a computer by name to a 127.x.x.x address. Then, add new lines to etc/hosts, using the following format:

```
127.0.0.1 localhost
COMPUTER_IP_ADDRESS COMPUTER_NAME.DOMAIN_NAME COMPUTER_NAME
```

This issue might occur with other Linux platforms. Consult the documentation for your operating system for assistance if you have an issue.

Configuring the JVM for Environments Without Graphics

For Unix and Linux environments that do not have graphics support such as an X11 graphics environment, set the Java Virtual Machine (JVM) to run in headless mode. Specify this mode by setting the java.awt.headless JVM parameter to true on your application server. Setting java.awt.headless to true prevents the JVM from attempting to access a native graphics environment that does not exist.

JVM Heap Size Considerations

The heap size determines how much memory the Java Virtual Machine (JVM) allocates to store an executing Java program. Guidewire applications are memory intensive. Optimize performance by using large heaps.

The following sections provide instructions for increasing the JVM heap size:

- "Changing Heap Size in Tomcat on Windows" on page 23
- "Increasing Heap Size for WebLogic" on page 24
- "Increasing Heap Size for WebSphere" on page 24

Refer to the documentation provided with your application server for more information.

32-Bit Versus 64-Bit Applications

32 and 64-bit refers to the size of the pointer used to reference an address.

Production environments must use a 64-bit operating system and 64-bit JVM. 64-bit JVMs inherently use more memory to host the same number of objects. 32-bit JVMs have an inherent memory scalability limit that differs



significantly across platforms. This scalability limit makes those platforms unsuitable production platforms. 64-bit JVMs are a more scalable option.

Typically, a 64-bit JVM has approximately an 80% heap size overhead. For example, a 1024 MB heap for a 32-bit JVM would host the same amount of objects as a 1843 MB heap for a 64-bit JVM. Generally, non-production systems work correctly with an heap size of respectively 1024MB for a 32-bit JVM and 2048 MB for a 64-bit JVM.

The following tables listing limits on heap size serve only as a starting point. They are useful if you are installing ClaimCenter and want to start development work. However, production systems require careful sizing. Consult Guidewire Services for assistance.

For more information on this and tuning your production application to optimal performance, contact Guidewire Support.

Operating System Limits on Heap Size

Operating system heap size limitations are grouped by application server.

For JBoss, Tomcat, and WebLogic

Operating system	32-bit heap size scales to:	64-bit heap size scales to:	
Linux	2.7GB	Very large	
Windows	1.5 GB	Very large	

For WebSphere

Operating system	32-bit heap size scales to:	64-bit heap size scales to:
AIX	2 GB	Very large
Linux	2.56 GB	Very large
Windows	1.5 GB	Very large

Although IBM recommends that the initial Java heap size for WebSphere not be set equal to the maximum Java heap size, Guidewire recommends otherwise. The IBM recommendations are not optimal for ClaimCenter. With a fixed heap, you avoid performance penalties from resizing the heap on the rising edge as the system load rises, or on the falling edge as load drops off. WebSphere provides several garbage collection policies. Guidewire recommends using the generational concurrent (gencon) garbage collection policy with equal minimum and maximum heap size.

To avoid performance degradation caused by forcing the JVM to adjust between two heap size values at runtime, set the initial and maximum values the same. The following table provides recommended heap settings for testing (determined with single user scenarios in mind). For production, consult Guidewire Services.

Single User Testing Heap Size

JVM parameter	Variable name	32-bit value	64-bit value
inital heap size	Xms	1 GB	2 GB
maximum heap size	Xmx	1 GB	2 GB
maximum permanent generation size	MaxPermSize	128 MB	256 MB

There is some variance across JVM technology with regard to memory allocation. Guidewire supports WebSphere on the IBM JVM only. The IBM JVM manages the permanent space without the use of a permanent size setting.



Use the heap size settings as the starting point for tuning optimal JVM settings for your configuration. Since each deployment needs to be tuned for its dataset, the heap sizes depend on your usage and configuration.

Load Balancers

In general, Guidewire supports load balancing of user interface server requests to the extent that load balancers support session affinity. It is more difficult to load balance SOAP calls because the SOAP standard does not provide a standard way to track session state across requests. However, some load balancers support IP affinity, which allows for very coarse load balancing of SOAP requests on a per-system basis. ClaimCenter supports both sessionless and sessioned SOAP calls, the latter of which require IP affinity.

Optional Components

If you plan to have ClaimCenter send email through business logic, have an SMTP-compatible email server, such as Microsoft Exchange or UNIX Sendmail available. It is also helpful to have access to an SNMP-compatible system monitoring tool, such as IBM Tivoli or HP OpenView.

Some internal monitoring tools are built into ClaimCenter. Beyond that, you can use any SNMP-compatible system monitoring tool, such as IBM Tivoli or HP OpenView if you are running on an x86/Tomcat platform.

Configuring JBoss

This topic provides notes on installing JBoss to run ClaimCenter.

Removing JBoss JARs

Remove modules/system/layers/base/org/codehaus/woodstox/main/stax2-api-3.1.1-redhat-3.jar from your JBoss installation, if present. The stax2-api-3.1.1-redhat-3.jar conflicts with ClaimCenter in the JBoss class loader. Not all JBoss versions include this JAR file.

Specifying the Bind Address

JBoss provides two ways to specify the bind address: a bind_addr XML property and a bind.address system property. JBoss uses the bind.address system property over the bind_addr XML property unless the system property -Dignore.bind.address is set to true.

You can set clustering parameters, including bind_addr, with the ClusterProtocolStackOption1 parameter in the ClaimCenter config.xml file. Set -Dignore.bind.address=true when starting JBoss to prevent JBoss from ignoring the bind_addr parameter set in ClusterProtocolStackOption1.

See "ClusterProtocolStackOption1" on page 46 in the *Configuration Guide*.

Installing a JBoss Instance for Free-text Search

Guidewire free-text search requires that you install a different instance of JBoss than the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate JBoss instance on a host separate from the one that hosts ClaimCenter. This separate instance of the application server runs a full-text search engine, Apache Solr.

Whenever you install a separate JBoss instance for Guidewire free-text search, change the HTTP port to 8983. The standard Solr port is 8983. You configure ports on JBoss in the following file:

JBOSS_HOME/server/default/conf/bindingservice.beans/META-INF/bindings-jboss-beans.xml

Edit the file, and change the port property for the WebServer service from 8080 to 8983, as the following example shows.



See also

- "Setting Up Free-text Search for JBoss" on page 88
- "Installing a Tomcat Instance for Free-text Search" on page 24
- "Installing a WebSphere Instance for Free-text Search" on page 26

Configuring Tomcat

This topic provides notes on installing Tomcat to run ClaimCenter. Install Tomcat as a system administrator.

Tomcat Examples

Guidewire recommends that you remove the TOMCAT_HOME/webapps/examples directory from any production Tomcat implementation. Some versions of the example scripts shipped with Tomcat have had security vulnerabilities reported.

Tomcat Native Library

Guidewire recommends that you do not implement the Tomcat Native Library. The major pitfall of using the library is that it mixes Java code and C/C++ code in the same process. This requires the use of Java Native Interface (JNI), which is not optimal for performance. Guidewire has observed performance degradation in tests with the Tomcat Native Library implemented.

The primary intent of the Tomcat Native Library is to execute some capabilities in native code versus Java. One such capability is encryption, which is calculus intensive and not optimally suited for Java. If you want to use encryption, consider offloading the encryption task to a dedicated component such as a hardware appliance, Apache Web Server or Microsoft Internet Information Server. These components are designed for such capabilities and are therefore more secure. Additionally, having a dedicated component enables you to build a more secure network organization with a DMZ.

The Tomcat server reports a message similar to the following upon startup if the Tomcat Native Library is not implemented:

```
INFO: The Apache Tomcat Native library which allows optimal performance in production environments was not found on the java.library.path:
```

Ignore this message.

Increasing the Maximum Concurrent Threads

By default, a Tomcat connector allows a maximum of 40 concurrent threads. Guidewire recommends that you set the maximum number of concurrent threads to 200 instead.

To increase the maximum concurrent threads

- 1. Open the conf/server.xml file in the Tomcat installation directory.
- **2.** Find the definition for the http connector. It looks similar to the following:

3. Add the maxThreads="200" setting to the Connector definition as follows:

- 4. Save server.xml.
- **5.** Restart Tomcat to make these changes effective.



Disabling Session Persistence

By default, Tomcat is configured with persistent sessions, which means Tomcat will write to disk all HTTP sessions which are in memory at the time the server is shut down.

When you restart the Tomcat server, it tries to restore the sessions. However, the session contents are only meaningful to the old instance of ClaimCenter, so ClaimCenter throws an exception such as the following:

```
SEVERE: IOException while loading persisted sessions: java.io.InvalidObjectException: Error deserializing Key of "com.guidewire.commons.entity.Key":null java.io.InvalidObjectException: Error deserializing Key of "com.guidewire.commons.entity.Key":null at com.guidewire.commons.entity.Key.readResolve(Key.java:141)
```

You can configure Tomcat to disable session persistence.

To disable session persistence

- 1. Open the Tomcat conf/context.xml file in a text editor.
- **2.** Uncomment the <Manager> element: <Manager pathname="" />
- 3. Save context.xml.

Installing Tomcat as a Windows Service

If you plan on installing only one application, and using Tomcat, you have the option of using the Microsoft Window Service Installer.

The Windows Service Installer automatically configures Tomcat to run as a Windows Service. If you configure ClaimCenter to run in Tomcat, Tomcat automatically runs as a Windows service. You can then set the server to start automatically as Windows starts and use the standard Windows service management tools to manage the ClaimCenter server.

Before the ClaimCenter application starts, the database server must already be up and running. Keep this order issue in mind as you develop startup procedures and scripts.

Changing Heap Size in Tomcat on Windows

You can increase the Tomcat heap size in one of two ways, depending whether you have installed Tomcat as a Windows service or not.

To increase the Tomcat heap size on Windows when Tomcat is a service

- 1. Start the Tomcat Windows service.
- 2. From the Start menu, click Control Panel.
- 3. Click Administrative Tools.
- 4. Click Services.
- 5. Right-click the Tomcat service and click Properties.
- **6.** Add the following to Start parameters:

```
-Xms1024m -Xmx1024m
```

If you have Tomcat installed, and Tomcat is not run as a Windows Service, set heap size for Tomcat by setting a Windows environment variable.

To increase the Tomcat heap size on Windows when Tomcat is not a service

1. From the Windows desktop, right-click My Computer.



- 2. Select Properties and click the Advanced tab.
- 3. Click the Environment Variables button.
- 4. Under System Variables, click New.
- 5. Set the Variable Name to CATALINA OPTS.
- 6. Set the Variable Value to -Xms1024m -Xmx1024m.
- **7.** Click **OK** until the properties settings closes.

Note: For values in step 6, consult "JVM Heap Size Considerations" on page 19.

Installing a Tomcat Instance for Free-text Search

Guidewire free-text search requires that you set up a different instance of Tomcat than the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate Tomcat instance on a host separate from the one that hosts your ClaimCenter application. This separate instance of the application server runs a full-text search engine, Apache Solr.

Whenever you install a separate Tomcat instance for Guidewire free-text search, change the port for the HTTP/1.1 protocol to 8983. The standard Solr port is 8983. Edit the file TOMCAT_HOME/conf/server.xml, and change the connector port for the HTTP/1.1 protocol from 8080 to 8983, as the following example shows.

See also

- "Setting Up Free-text Search for Tomcat" on page 89
- "Installing a JBoss Instance for Free-text Search" on page 21
- "Installing a Tomcat Instance for Free-text Search" on page 24

Configuring WebLogic

Review this topic if you are using WebLogic as the application server.

Increasing Heap Size for WebLogic

Use the USER_MEM_ARGS environment variable to specify arguments to WebLogic during application server startup.

To increase the WebLogic heap size

- 1. Create an environment variable on your system named USER_MEM_ARGS.
- 2. For the value of USER_MEM_ARGS, enter:

```
-Xms256m -Xmx1024m -Dgw.server.mode=dev
```

The server mode entry is needed for reloading PCF pages. If you want to run the server in production mode, remove the -Dgw.server.mode argument. By default, ClaimCenter starts in production mode on all application servers except the bundled QuickStart server.

Configuring WebSphere

Review this topic if you are using WebSphere as the application server.

Increasing Heap Size for WebSphere

Increase minimum heap size to 256 and maximum heap size to 1024.



To increase the WebSphere Heap Size

- 1. Open the WebSphere Administrative Console.
- 2. From the left menu, select Servers → Server Types → WebSphere application servers, and select your server from the list on the right.
- 3. Under Server Infrastructure select Java and Process Management → Process Definition.
- 4. Under Additional Properties, select Java Virtual Machine.
- **5.** Enter the following heap sizes, then click **OK**.
 - For Initial heap size enter 256
 - For Maximum heap size enter 1024
- 6. Click OK.
- 7. A message displays stating that changes have been made. Click Save.

Adjusting Ping Parameters for WebSphere with Oracle

If WebSphere times out while communicating with Oracle, set the following values:

Server Parameter	Value
ping interval	2000
ping timeout	6000

WebSphere Database Cluster Management

Guidewire supports using WebSphere database cluster management, provided that you use the JDBC JAR file bundled with ClaimCenter.

WebSphere Network Deployment

Guidewire certifies the base version of WebSphere, but supports WebSphere Network Deployment (ND). Guidewire products do not require any ND functionality to run. Some IBM terminology conflicts with Guidewire terminology. These differences are clarified as follows:

ClaimCenter provides cache coherency (clustering) since it maintains an internal cache of objects for performance reasons. After ClaimCenter changes an object in the cache for a single node in a cluster, ClaimCenter sends a message to invalidate the object in other node caches. The Guidewire clustering for cache coherency implementation is completely independent of the application server.

WebSphere ND provides three key features that you might like to use in conjunction with ClaimCenter.

- **Deployment** WebSphere ND includes tools for automatically deploying configurations to servers in a cluster. Guidewire supports these tools if used in conjunction with our Environment Specific Configuration settings.
- Load balancing WebSphere ND provides load balancing capabilities. See "Load Balancers" on page 21.
- Clustering Clustering is different from the ClaimCenter cache coherency capability. WebSphere ND clustering is mostly about session replication, which is the capability to constantly maintain a user's session state across multiple computers in a cluster. Maintaining session state information is useful in the event of failover, in which WebSphere transfers a user from one server to another. This functionality was intended to support lightweight session objects such as those found in online shopping carts. Because Guidewire designed ClaimCenter for enterprise users, each session must preserve a large volume of data. As a result, session replication is prohibitively performance intensive and Guidewire does not support it.



Installing a WebSphere Instance for Free-text Search

Guidewire free-text search requires that you install a different instance of WebSphere than the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate WebSphere instance on a host separate from the one that hosts ClaimCenter. This separate instance of the application server runs a full-text search engine, Apache Solr.

Whenever you install a separate WebSphere instance for Guidewire free-text search, change the HTTP port for the default host and its virtual host to 8983. The standard Solr port is 8983. You configure ports on WebSphere through the administrative console.

To change the port number in WebSphere for your default and virtual hosts

- **1.** Start the application server.
- **2.** Change the port for the default host in your WebSphere application server.
 - a. From the Administrative Console, navigate to Servers → Server Types → WebSphere application servers and select your application server from the list or resources that you can administer.

The console displays the configuration page for your application server.

- b. On the right underneath Communications, click Ports.
- c. In the list of TCP/IP ports, click WC_defaulthost.
- **d.** In the Port field, change the value from 9080 to 8983.
- e. Click Apply.
- f. In the Messages box, Click Save to apply the changes to the master configuration.
- **3.** Change the port number for the virtual host in your WebSphere application server.
 - a. From the Administrative Console, navigate to Environment → Virtual hosts and click the name of your physical host name. The default name of your physical host is default_host.

The console displays the configuration page for your physical host.

- **b.** On the right underneath Additional Properties, click Host Aliases.
- c. Click New.
- **d.** Enter the following values.
- e. Click OK.
- f. In the Messages box, Click Save to apply the changes to the master configuration.
- **4.** Stop and start the application server.

See also

- "Setting Up Free-text Search for WebSphere" on page 91
- "Installing a JBoss Instance for Free-text Search" on page 21
- "Installing a Tomcat Instance for Free-text Search" on page 24

Configuring the Database

Guidewire recommends that you implement the guidelines contained in this topic while you install and configure the database server. ClaimCenter 8.0.2 supports Oracle and SQL Server for production environments. See the *Guidewire Platform Support Matrix* for information about which specific database server versions Guidewire supports for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.



Run the database server on hardware supported by the database server provider. Guidewire can provide assistance with hardware requirements for your production implementation. ClaimCenter depends heavily on back-end database performance, which in turn depends on storage performance. Optimize the performance of your database server.

For production systems, Guidewire recommends using a database server dedicated to ClaimCenter. Production environments must use a 64-bit operating system and 64-bit database engine on the database server.

ClaimCenter synchronizes with the database clock. The application server and database server must be within the same time zone. The maximum difference allowed between the application server and database server is 29 minutes.

This topic includes:

- "Database Permissions" on page 27
- "Configuring Linguistic Search Collation" on page 27
- "Configuring Compression" on page 28
- "Configuring DB2 for ClaimCenter" on page 32
- "Configuring Oracle for ClaimCenter" on page 32
- "Configuring SQL Server for ClaimCenter" on page 37

Database Permissions

Create a user called ccUser in your database. ClaimCenter connects to the ccUser. The ccUser must have the correct permissions. The following table lists the permissions required for each database:

Database	Permissions Required
Oracle	The ccUser must have the following permissions on the ClaimCenter database: create session create procedure create trigger create table create view create sequence query rewrite alter session select any dictionary
	If your users want to see statspack data on the ClaimCenter Info Pages interface, grant the ccUser access to the ClaimCenter performance statistics (perfstat) tables.
SQL Server	The ccUser must have the public and db_owner roles on the ClaimCenter database. ClaimCenter supports several different data management pages for performance analysis of the application. To use these pages, the ccUser must be granted view server state. The server login account must also have view database state permission on each ClaimCenter data management view. The data management views all start with sys.dm_ prefix.
DB2	The ccUser must have the SYSTEM ADMINISTRATOR (SYSADM) privilege.

Configuring Linguistic Search Collation

You can configure how ClaimCenter searches and sorts search results. For example, you can configure whether searching is accent-sensitive or accent-insensitive, case-sensitive or case-insensitive. For more information, contact Guidewire Support.



Configuring Compression

Compression reduces the size of the database. The advantage of compression is reduced cost for storage and backups. Compression can also increase performance by effectively making the database buffer caches larger. The disadvantage to compression is that the database requires more CPU time to compress and decompress data. Furthermore, queries that require either a table scan or a full index scan will require fewer physical and logical reads because more rows fit on a single data page.

Consult with Guidewire Support about whether compression will improve overall performance of your ClaimCenter implementation.

The compression settings examples in the following topics demonstrate the syntax to configure compression. These examples are not provided as guidelines for compression settings for your environment.

A full discussion of table and index compression is beyond the scope of this document. Refer to documentation from your database vendor for details about compression options.

Configuring Compression for DB2

You can specify DB2 compression options for ClaimCenter using the <db2-compression> element in database-config.xm1. The <db2-compression> element is nested as shown below:

You can override options for a specific table by adding a <db2-table-compression> element and setting the index-compression, row-compression, and value-compression attributes. The <db2-table-compression> element is contained within a <db2-table-dd1> element within the <db2-db-dd1> element. For example:

By default, indexes follow the row compression setting of their table, if specified, or the entire database if the table is not specified. You can override compression options for all indexes for a table by setting the index-compression attribute on the <db2-table-compression> element. You can override compression options for a specific index on a table by including the index-compression attribute on the <db2-index-dd1> element. For example:



Configuring Compression for Oracle

You can specify Oracle compression options for ClaimCenter using the <ora-compression> element in database-config.xml. The <ora-compression> element is nested as shown below:

The <ora-compression> element accepts the attributes table-compression and index-compression. You can specify one or both attributes. Attributes that you specify for <ora-compression> apply to all tables and indexes in the database.

You can override options for a specific table by adding an <ora-table-compression> element and setting the table-compression attribute. The <ora-table-compression> element is contained within an <ora-table-ddl> element within the <ora-db-ddl> element. For example:

```
<database>
...
<upgrade>
<ora-db-ddl>
<ora-table-ddl table-name="cc_tableName">
<ora-table-compression table-compression="NONE|BASIC|ADVANCED" />
</ora-table-ddl>
</upgrade>
</database>
```

You can override compression options for all indexes on a specific table by including the index-compression attribute on the <ora-table-compression> element. For example:

You can override options for a specific index by adding an <ora-index-ddl> element within the <ora-table-ddl> element for the table that has the index. For example:

Oracle Table Compression

You can set the table-compression attribute of the <ora-compression> element and the ora-table-compression attribute of the <ora-table-ddl> element to NONE, BASIC or ADVANCED. A value of NONE specifies that the database or table is not compressed. A value of BASIC specifies that the database or table uses Oracle basic compression. A value of ADVANCED specifies that the database or table uses Oracle advanced compression. Oracle advanced compression is part of the Oracle Advanced Compression Option, which requires a separate license. Refer to Oracle documentation for more information about compression.



The following example specifies advanced compression for the entire database and no compression for the cc_Activity and cc_Workflow tables.

Oracle Index Compression

You can set the index-compression attribute of the <ora-compression> and <ora-index-ddl> elements to true or false. Specify an index by setting the key-columns attribute of the <ora-index-ddl> element to a comma-delimited list of key columns in order. Specify DESC after a column name for descending sort order on that column.

An index-compression value of true specifies to compress all columns but the last for unique indexes and to compress all columns for non-unique indexes.

The following example specifies the following:

- · Index compression for the entire database
- No compression for the cc_Activity index that contains key columns PublicID and Retired in key positions one and two, respectively.
- No compression for any indexes on the cc_Workflow table.

Oracle spatial indexes are not compressible. If you use the key-columns attribute to specify a spatial index to compress, ClaimCenter reports an error. If the index is implied to be compressed by the compression configuration of the database or table, ClaimCenter ignores the compression setting for a spatial index.

Configuring Compression for SQL Server

You must have the Enterprise edition of SQL Server to have the SQL Server compression feature.

You can specify SQL Server compression options for ClaimCenter using the <mssql-compression> element in database-config.xml. The <mssql-compression> element is nested as shown below:



The <mssql-compression> element accepts the attributes table-compression and index-compression. You can specify one or both attributes. Attributes that you specify for <mssql-compression> apply to all tables and indexes in the database.

You can override options for a specific table by adding an <mssql-table-compression> element and setting the table-compression attribute. The <mssql-table-compression> element is contained within an <mssql-table-ddl> element within the <mssql-db-ddl> element. For example:

You can override compression options for all indexes on a specific table by including the index-compression attribute on the <mssql-table-compression> element. For example:

You can override options for a specific index by adding an <mssql-index-ddl> element within the <mssql-table-ddl> element for the table that has the index. For example:

SQL Server Table Compression

You can set the table-compression attribute of the <mssql-compression> element and the mssql-table-compression attribute of the <mssql-table-ddl> element to NONE, PAGE, or ROW. A value of NONE specifies that the database or table is not compressed. A value of PAGE specifies that the database or table uses page-level compression. Page compression is applied only when the page gets full. For page compression, the following operations happen in the following order:

- Row compression
- Prefix compression
- Dictionary compression

A value of ROW specifies that the database or table uses row compression. Row compression drastically reduces the metadata needed for variable-length columns.

Refer to SQL Server documentation for more information about SQL Server compression options.

The following example specifies row table compression for the entire database, page compression for the cc_Activity table, and no compression for the cc_Workflow table.



SQL Server Index Compression

The compression setting of a table is not automatically applied to its non-clustered indexes. You must configure compression settings for indexes separately or in bulk.

You can set the index-compression attribute of the <mssql-compression> and <mssql-index-ddl> elements to NONE, PAGE, or ROW.

Specify an index by setting the key-columns attribute of the <mssql-index-ddl> element to a comma-delimited list of key columns in order. Specify DESC after a column name for descending sort order on that column.

The following example specifies the following:

- Row index compression for the entire database.
- No compression for the cc_Activity index that contains key columns PublicID and Retired in key positions one and two, respectively.
- Page compression for any indexes on the cc_Workflow table.

ClaimCenter uses a clustered primary key index. Since this index is actually the table data itself, ClaimCenter uses the compression setting for the table for the primary key index.

Configuring DB2 for ClaimCenter

See the *Guidewire Platform Support Matrix* for information about which specific DB2 versions Guidewire supports for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

ClaimCenter requires the following DB2 configuration:

- The database configuration parameter cur_commit must be set to on.
- The spatial reference system must be set to srs_id 0 and srs_name set to WGS84_SRS_1003.
- The collation of the database must be set to IDENTITY.
- The character set (codeset) must be set to UTF-8.
- The environment registry variable DB2_COMPATIBILITY_VECTOR must be set to 90. This corresponds to bit position 5 (NUMBER data type) and 8 (TRUNCATE TABLE).
- The package cache event monitor must be installed and be active.

Configuring Oracle for ClaimCenter

These directions assume you have already installed Oracle. See the *Guidewire Platform Support Matrix* for information about which specific Oracle versions Guidewire supports for ClaimCenter 8.0.2. The *Guidewire*



Platform Support Matrix is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

ClaimCenter requires Oracle Locator, which is included with Oracle Multimedia. Refer to Oracle MOS (My Oracle Support) note *How To Verify That Oracle Locator Is Installed (Doc ID 357943.1)*.

Prerequisites to Installing on Oracle

Ensure that your Oracle database is running in an environment that optimizes storage performance while maintaining storage maintainability. Oracle recommends you use the SAME (Stripe and Mirror Everywhere) strategy. To learn more about the SAME strategy, consult the following http://www.oracle.com/technology/deploy/performance/pdf/opt_storage_conf.pdf.

Oracle Java Virtual Machine (JVM) must be installed on all Oracle databases hosting ClaimCenter. The only exception is when the ClaimCenter application locale is English and you only require case-insensitive searches. Ensure that Oracle initialization parameter <code>java_pool_size</code> is set to a value of above 50 MB.

Configure Oracle to use asynchronous IOs. Asynchronous IO significantly simplifies a database's IO management while increasing its performance. For performance reasons, tune your operating system to Oracle database requirements. Oracle provides guidance on tuning your database based on:

- · Operating system
- · Available memory
- Database release

Consult Oracle documentation and support web site for information on how to tune your database.

The Oracle database supports server-side caching that can help increase ClaimCenter performance. The size of the Oracle database cache is critical to supporting server-side caching. For internal tests, Guidewire uses a database cache size of 3.6 GB or more. Consult the Oracle documentation for information on selecting a cache size appropriate to your server computer's architecture.

After your database is in production, you can not easily modify the storage architecture. Guidewire recommends that you test and tune your database's storage performance prior to installing ClaimCenter. There are many tools available for optimizing database performance, including an open source tool, IOzone (www.iozone.org).

To prepare an Oracle database for ClaimCenter

1. Create a new database instance for ClaimCenter.

Guidewire recommends that you not share the ClaimCenter database with other data or applications.

IMPORTANT Guidewire currently supports single-byte character sets that are a strict superset of ASCII, and AL32UTF8 or UTF8 for Unicode. Only use a supported character set with ClaimCenter. Refer to your Oracle documentation for a complete list of supported character sets. WE8IS08859P1 is a single-byte character set that supports both Western European languages and American English. AL32UTF8 and UTF8 are Oracle character sets supported for the storage of Unicode data, such as Asian characters. If using the AL32UTF8 or UTF8 character set, the Oracle instance must be configured with nls_length_semantics set to char. Otherwise, the database does not start.

2. Create one or more tablespaces to support the ClaimCenter logical tablespaces. Guidewire recommends that you create a separate tablespace for each logical tablespace:

Logical Name	Usage
ADMIN	Stores system parameters.
OP	Stores the main ClaimCenter data tables.
TYPELIST	Stores system code tables.



Logical Name	Usage
INDEX	Stores system indexes.
STAGING	Stores inbound staging data tables.
LOB	Stores off-row LOB (large object) data. The LOB tablespace is optional. If you do not specify a physical tablespace for the LOB logical tablespace, then LOB data is stored in the tablespace mapped to the OP logical tablespace.
	ClaimCenter uses the LOB tablespace for new tables only. For an existing configuration in which the ClaimCenter schema has been created, if you designate an LOB tablespace, ClaimCenter does not move existing LOB columns to the LOB tablespace. If you add an LOB column to an existing table, ClaimCenter does not put the column in the LOB tablespace. If you define a new table with LOB data, ClaimCenter stores the LOB data in the designated LOB tablespace.
	See "Configuring ClaimCenter to Use Oracle SecureFile LOBs" on page 35.

You can name your tablespaces anything you like in a production environment: either the same as the logical tablespace names or entirely different. As you configure ClaimCenter, you map the tablespaces you created to the ClaimCenter internal logical tablespaces.

For a development environment, use the same tablespace names as the logical names. The gwcc dev-dropdb command only works if the tablespace names match the default logical names.

- **3.** Create a single database user, ccUser, within the ClaimCenter database.
- **4.** Grant ccUser the following permissions:
 - · alter session
 - create procedure
 - · create sequence
 - · create session
 - · create table
 - · create trigger
 - · create view
 - · query rewrite
 - select any dictionary

If your users want to view statspack data on the ClaimCenter Info Pages interface, you also need to grant the ccUser access to Statspack's (perfstat user) tables.

- 5. Grant quota on all the tablespaces listed in step 2 to the ccUser.
- **6.** Set default tablespace for ccUser to the one being mapped to the OP logical tablespace.
- 7. If you run the database server and the application server on the same computer, be aware that Oracle adds directories to the PATH environment variable. To prevent potential conflicts with ClaimCenter files, Guidewire recommends that you edit your PATH variable and move the Oracle directories to the end, after the ClaimCenter directories. Guidewire recommends that you do not run database and application servers on the same computer in a production environment.
- 8. Test a connection to the database from a database client. Verify that all the tablespaces are visible.

Using Oracle Resource Consumer Groups for Slow Claim Queries

Note: The information in this topic is provided for implementations that experience slow claim queries. If you do not experience slow claim queries, you do not need to define a resource consumer group for claim queries.

Oracle provides resource plans and consumer groups to handle resources in the database. One useful feature is to cancel a query based on the execution time. You can configure ClaimCenter to switch to a resource consumer



group that you define to perform claim searches. You can set this resource consumer group to have a time limit and cancel SQL operations for claim searches that exceed the time limit.

ClaimCenter saves the initial resource consumer group detected when the application server is started and reverts to that group following the claim query.

The requirements for using Oracle resource consumer groups for claim queries are:

• The <oracle-settings> attribute db-resource-mgr-cancel-sql is set in database-config.xml to a resource consumer group defined in Oracle. For example:

- The Oracle resource manager plan is set at the system level.
- The ccUser has privileges to switch between the two resource groups.

ClaimCenter checks these conditions when the server starts.

Configuring ClaimCenter to Use Oracle SecureFile LOBs

ClaimCenter supports Oracle SecureFile LOBs for unstructured data. To configure ClaimCenter to use SecureFile LOBs, modify the <database> block in database-config.xml. You can specify to use SecureFile LOBs for all LOBs in the database or for specific tables. You can also configure whether to use caching and the LOB type. The LOB type can be BASIC, SECURE, or SECURE_COMPRESSED. If not specified otherwise ClaimCenter uses SecureFile LOBs.

To specify to use basic file LOBs for all LOBs in the database, add the following to the <database> block.

```
<ora-db-ddl>
  <ora-lobs type="BASIC" caching="true|false"/>
</ora-db-ddl>
```

To specify to use compressed SecureFile LOBs for all LOBs in the database, add the following to the <database> block.

```
<ora-db-ddl>
  <ora-lobs type="SECURE_COMPRESSED" caching="true|false"/>
</ora-db-ddl>
```

To specify to use basic file LOBs for all LOBs on a particular table, add the <ora-lobs> element within the <ora-table-ddl> block for the table.

```
<ora-db-ddl>
  <ora-table-ddl name="cc_tablename">
    <ora-lobs type="BASIC" />
    </ora-table-ddl>
</ora-db-ddl>
```

If any LOBs are configured to be SecureFile LOBs, and the LOB tablespace is configured, it must be managed with Automatic Segment Space Management. If the LOB tablespace is not configured, then the ADMIN, OP and STAGING tablespaces must be managed with Automatic Segment Space Management.

To specify to use caching for LOBs, add the attribute caching="true" to the <ora-lobs> element.

If you configure a LOB type for the database or for a specific table, you cannot change the configuration after the database has been created. You also cannot change the caching configuration after the database has been created.

Refer to Oracle documentation for information about basic file, SecureFile, and compressed SecureFile LOBs.

Configuring Table and Index Partitioning for Oracle

To enable hash partitioning on a table, add the following to the <database> block in database-config.xml:

```
<ora-db-ddl>
  <ora-table-ddl name="Table Name">
       <ora-table-hash-partitioning hash-column="column name" num-partitions="number"/>
```



```
</ora-table-ddl>
</ora-db-ddl>
```

If a keyable table is partitioned, by default, ClaimCenter uses the ID column as the hash column. You can specify a different column by using the hash-column attribute on <ora-table-hash-partitioning>. For non-keyable tables, the hash-column attribute is required.

If a keyable table is partitioned, ClaimCenter also partitions the primary key index and the index on PublicID. This index is on PublicID and Retired if the table is for a retireable entity.

To enable partitioning on an index, add the following to the <database> block in database-config.xml:

```
<oracle-db-ddl>
  <ora-table-ddl name="Table Name">
    <ora-index-ddl key-columns="column1,column2">
        <ora-index-hash-partitioning locality="GLOBAL|LOCAL" num-partitions="number"/>
        </ora-index-ddl>
        </ora-table-ddl>
  </oracle-db-ddl>
```

By default, ClaimCenter uses 128 partitions. You can override this number by defining a num-partitions attribute on <ora-table-hash-partitioning> or <ora-index-hash-partitioning>.

ClaimCenter only creates partitions when creating a table or index. ClaimCenter does not modify existing tables or indexes. If a table is dropped and rebuilt during an upgrader, ClaimCenter partitions the table if the table is configured to be partitioned. The schema verifier detects and flags if a table is configured as partitioned but is not, or if it is not configured as partitioned but is partitioned.

Configuring Oracle Date Interval Partitioning

You can configure ClaimCenter to use Oracle partitioning by date intervals.

To configure date interval partitioning on a table, add an <ora-table-date-interval-partitioning> element within <ora-table-ddl>. The <ora-table-ddl> element is a subelement of <ora-table-ddl> in the <database> element of database-config.xml. The <ora-table-date-interval-partitioning> element has two attributes. Use the datecolumn attribute to specify a non-nullable timestamp column that ClaimCenter will use to determine partition boundaries. Use the interval attribute to specify the period of time for each partition. You can set interval to DAILY, WEEKLY, MONTHLY, QUARTERLY, or YEARLY. For example:

ClaimCenter stores partitioned data in the operational tablespace.

Configuring Oracle Adaptive Optimization for ClaimCenter

Oracle 12c introduced a feature called adaptive optimization. Guidewire has conducted performance testing of ClaimCenter with adaptive optimization enabled and has not observed significant performance improvement. Therefore, you might want to disable adaptive optimization for ClaimCenter.

Although you can completely disable adaptive optimization at the database level, this might impact your integrations and non-Guidewire schemas. So Guidewire provides a configuration option to control adaptive optimization for ClaimCenter only.

You can disable adaptive optimization for ClaimCenter by configuring the adaptive-optimization attribute of the <oracle-settings> element. Or you can set adaptive optimization for ClaimCenter to reporting-only mode. In reporting-only mode, Oracle collects information required for adaptive optimization, but does not modify the plan. You can view this information in the adaptive plan report.

You can set adaptive-optimization to the following values:



- REPORTING_ONLY ClaimCenter sets both OPTIMIZER_ADAPTIVE_FEATURES and OPTIMIZER_ADAPTIVE_REPORTING_ONLY to TRUE every time it initializes a connection.
- OFF ClaimCenter sets both OPTIMIZER_ADAPTIVE_FEATURES and OPTIMIZER_ADAPTIVE_REPORTING_ONLY to FALSE every time it initializes a connection.

For example:

```
<database>
...
<oracle-settings adaptive-optimization="OFF" />
...
</database>
```

If you do not specify a value for adaptive-optimization, ClaimCenter does not set the OPTIMIZER_ADAPTIVE_FEATURES and OPTIMIZER_ADAPTIVE_REPORTING_ONLY Oracle parameters.

Configuring SQL Server for ClaimCenter

This topic includes information on how to configure SQL Server for ClaimCenter. See the *Guidewire Platform Support Matrix* for information about which specific SQL Server versions Guidewire supports for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

Guidewire does not support Windows Integrated Security as an option while connecting to SQL Server.

Prerequisites to Installing on SQL Server

ClaimCenter requires that the collation of the SQL Server database specifies CI, or case-insensitive. The case-sensitivity setting affects table and column names, and ClaimCenter requires these names to be case-insensitive. During startup, ClaimCenter checks that the SQL Server database is case-insensitive.

Decide whether to store all character data in single-byte format in varchar columns, or Unicode multi-byte format stored in nvarchar columns. If using Unicode, such as for Asian languages, then the <sqlserver-settings> element within the database element in database-config.xml must have the unicodecolumns attribute set to true. Then, when the database tables are created the first time the application server is started, all character columns are created with the nvarchar datatype.

The collation setting specifies sorting and comparison rules, and also the code page to use for single-byte data. Microsoft still supports SQL Server collations (that start with SQL_) in addition to Windows collations, but recommends using a Windows collation. Guidewire also recommends that you use a Windows collation. Choose the collation setting carefully. Refer to Collation and International Terminology at http://msdn.microsoft.com/en-us/library/ms143726.aspx for a full discussion. The version of Windows being used for the database and application server is a factor. Some newer collations, such as Japanese_Bushu_Kakusu_100, are only available on Windows 2007 or later and not on Windows 2003.

Creating a SQL Server database with files of sufficient size and parameters is important to future performance and maintenance. A basic discussion can be found online in a Microsoft SQL Server topic "Designing Databases" at http://msdn.microsoft.com/en-us/library/ms187099.aspx?ppud=4.

For production systems Guidewire strongly recommends that you pre-allocate disk space rather than using the SQL Server autogrowth feature. As a general guideline, estimate how big your database might grow in one year and add 20%. Then, allocate enough total file space for this size. Monitor the size of the database and add space during scheduled periods of lower activity. Set the maximum file size to be less than the size of the disk, so that the disk does not fill up.

For your production database, work with your SAN (Storage Area Network) engineers early in implementation to deliver production-realistic performance.

Guidewire recommends that you not share the SQL Server instance on which you are running ClaimCenter with other data or applications.



To install ClaimCenter on SQL Server

- 1. Configure SQL Server. See "Configuring SQL Server in Management Studio" on page 38.
- 2. Create a database for ClaimCenter. See "Creating a ClaimCenter Database in SQL Server" on page 38.
- **3.** Modify the database-config.xml file so that the application correctly points to the database. See "Deploying ClaimCenter to the Application Server" on page 78.
- **4.** Restart the application server and test by opening ClaimCenter in a browser window.

Configuring SQL Server in Management Studio

To configure SQL Server to support ClaimCenter

- 1. Open SQL Server Management Studio.
- **2.** In the **Object Explorer**, right-click the server node you plan to use for ClaimCenter and choose **Properties**. Typically, the node is the same as computer name.

The Server Properties dialog opens.

3. Select the Security page and check SQL Server and Windows Authentication Mode.

WARNING ClaimCenter does not run if authentication is set to Windows Authentication Mode only.

- **4.** Select the Memory page.
- 5. Adjust the Maximum Server Memory to use at least 200 MB.
- 6. With a dedicated host computer running SQL Server, Microsoft recommends that you use the default settings and have SQL Server manage memory. Consult the Microsoft documentation (http://msdn2.microsoft.com/en-us/library/ms178067(d=ide).aspx) for an in-depth discussion of memory options. Setting the maximum server memory to a particular value can cause performance problems.
- 7. Click OK to close the dialog.
- 8. Right-click the SQL Server Agent node and select Properties.
- 9. Select the General page.
- 10. Check Autostart SQL Server if it stops unexpectedly.
- 11. Click **OK** to close the dialog.

Creating a ClaimCenter Database in SQL Server

This topic includes procedures to create and configure a SQL Server database for ClaimCenter.

IMPORTANT If you plan to create additional database instances to support multiple ClaimCenter environments or other Guidewire products, consider applying the changes in the following procedure to the model database. Use the model database as a template for the additional database instances. Before you edit the model database, create a backup.

To create and configure a SQL Server instance for ClaimCenter

1. If you have not already done so, open SQL Server Management Studio. If you are creating a new database, proceed to step 2.

If you are modifying the model database, expand Databases \rightarrow System Databases, right-click model and select Properties, and skip to step 4.



2. Right-click the Databases node and select New Database. Or, your company's database administrator can write a CREATE DATABASE SQL statement to create the database.

Guidewire recommends that you not share the ClaimCenter database with other applications.

- 3. Enter a database name in the New Database dialog and click OK.
- **4.** Optionally, create one or more filegroups to support the ClaimCenter logical tablespaces from the Filegroups page. If you choose to use filegroups, create a separate filegroup for each logical tablespace:

Logical Name	Usage
ADMIN	Stores system parameters.
OP	Stores the main ClaimCenter data tables.
TYPELIST	Stores system code tables.
INDEX	Stores system indexes.
STAGING	Stores inbound staging data tables.
LOB	Stores off-row LOB (large object) data. The LOB filegroup is optional. If you do not specify a filegroup for the LOB logical tablespace, then LOB data is stored in the filegroup mapped to the OP logical tablespace.
	ClaimCenter uses the LOB filegroup for new tables only. For an existing configuration in which the ClaimCenter schema has been created, if you designate an LOB filegroup, ClaimCenter does not move existing LOB columns to the LOB filegroup. If you add an LOB column to an existing table, ClaimCenter does not put the column in the LOB filegroup. If you define a new table with LOB data, ClaimCenter stores the LOB data in the designated LOB filegroup.

With one exception, you can name the filegroups anything you like: either the same as the logical tablespace names or entirely different. INDEX is a reserved name on SQL Server, so you can not map the logical tablespace INDEX to a physical filegroup of the same name.

As you configure the ClaimCenter database connection, you can map the filegroups you created to the ClaimCenter internal logical tablespaces. See "Specifying Filegroups for SQL Server" on page 64.

- **5.** Select the **Options** page.
- **6.** Choose your database collation if not using the SQL Server server default. The only requirement is that it is a CI (case-insensitive) collation.
- **7.** Validate that Auto Create Statistics and Auto Update Statistics are both set to True. During startup, ClaimCenter checks that these properties are set to True and validates that the SQL Server database is case-insensitive.
- **8.** Validate that Auto Shrink is set to False. If set to True, poor performance can result.
- 9. Click OK.
- **10.** Right-click Security and select New \rightarrow Login.
- 11. On the Login New dialog, select SQL Server Authentication if not already selected.
- **12.** Specify a password and password policy options.
- **13.** Click **0**K.
- **14.** In Object Explorer, expand the database and open Security \rightarrow Users.
- 15. Right-click Users and select New User.
- **16.** Enter ccUser for the User name.
- 17. Enter the Login name that you created earlier.



- **18.** Grant ccUser ownership of the ClaimCenter database by selecting db_owner in both Schemes owned by this user and Database role membership panels.
- 19. Click OK.
- 20. ClaimCenter supports several different data management pages for performance analysis of the application. To use these pages, the ccUser must be granted view server state and view database state on each ClaimCenter data management view. The data management views all start with sys.dm_prefix.
 - a. Right-click the database and select Properties.
 - **b.** Select the Permissions page.
 - c. Select ccUser.
 - d. Select the checkbox to grant view database state permission.
 - e. Click OK.
 - f. Right-click the server and select Properties.
 - g. Select the Permissions page.
 - **h.** Select the login associated with ccUser.
 - i. Select the checkbox to grant view server state permission.
 - j. Click OK.
- 21. Guidewire recommends that you do not use the SQL Server autogrowth feature in a production system. Instead, monitor the size of your database and increase the size of the database files as needed during periods of lower activity. SQL Server enables the autogrowth feature by default.

To disable autogrowth

- a. Right-click the database and select Properties.
- **b.** Select the Files page.
- c. For each database file, click the ... button in the Autogrowth column.
- d. Click the checkbox for Enable Autogrowth to deselect it.
- e. Click OK.
- **f.** Repeat step b through step e for each database file.
- g. Click OK on the Database Properties screen.
- **22.** ClaimCenter requires that the READ_COMMITTED_SNAPSHOT option is on.

To set this parameter

- a. Click New Query.
- **b.** In the query pane, enter:

```
ALTER DATABASE dbname
SET READ_COMMITTED_SNAPSHOT ON
WITH ROLLBACK IMMEDIATE
```

c. Click Execute. SQL Server Management Studio informs you that the command completed successfully. During startup, ClaimCenter checks that the READ_COMMITTED_SNAPSHOT option is on.

IMPORTANT The use of READ_COMMITTED_SNAPSHOT greatly increases resource requirements on the tempdb database. Set tempdb to grow in 10% increments, and provide sufficient disk space for tempdb to grow substantially. Performance can be improved if you dedicate separate I/O resources to tempdb.



23. Close SQL Server Management Studio. You do not need to save the READ_COMMITTED_SNAPSHOT query.

Before Continuing...

Check that your SQL server environment is correct. Test that you can connect to the database using the ccUser credentials. Ensure that SQL Server starts automatically as the server starts. To test if your database is starting automatically, reboot your server and attempt to access the database from a client.

Development Workstation Information

Each developer workstation is a contained environment that includes your company's Guidewire applications and the components needed to configure it. Guidewire recommends that development workstation and environment meet requirements beyond end-user workstations.

Guidewire recommends high-performance I/O systems for development, such as RAID-0 and SCSI or SSD disks. Studio is a high I/O application. Installation of software that slows the I/O system, such as encryption or continuous virus scans can handicap development productivity.

See the *Guidewire Platform Support Matrix* for development workstation system requirements for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

Client Information

ClaimCenter is a web application accessed through a web browser. See the *Guidewire Platform Support Matrix* for client system requirements for ClaimCenter 8.0.2. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

Guidewire has graded levels of support for web browsers. The grades of support are:

Full: Guidewire successfully completed functional testing and performance tuning for the browser and fully supports it.

Partial: Guidewire completed some testing for the browser and found significant functional or performance issues that Guidewire could not resolve. The browser might have a known issue that the browser vendor has not committed to resolving. Browsers with partial support also include browsers that have not yet made it past quality assurance but that Guidewire determines might be fine to use. For example, a newer version of a fully supported browser could be partially supported until Guidewire can fully test the new version. The partial support grade functions largely as a staging area while Guidewire verifies all facets of support.

Unsupported: These are browsers that have significant functional or performance issues. Any browser that does not fully support HTML5 and CSS3 is unsupported by Guidewire. Other less commonly used browsers, such as Opera or Dolphin, could be unsupported because Guidewire has not tested them due to a lack of demand. The unsupported grade functions as a collection of browsers that are unlikely to get any support in the medium to long term.

Installing Java

The ClaimCenter application server and Guidewire Studio require a JVM (Java Virtual Machine). The version of the JVM depends on the servlet container and operating system on which the application server runs. See the *Guidewire Platform Support Matrix* for specific version requirements. The *Guidewire Platform Support Matrix*



is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/ products/platform.

IMPORTANT Production environments must use a 64-bit operating system and 64-bit JVM.

To use a 64-bit Oracle JDK for development, add the startup parameter -XX:+UseCompressedOops to the JVM.

By default, Oracle JVMs provide both a client and a server mode. Guidewire supports only the server mode as it yields much higher performance. How you set server mode depends on your application server.

- If using Oracle JVM with Tomcat, then add the -server flag to CATALINA_OPTS.
- If using Oracle JVM with WebLogic, then add the -server flag as an argument while launching the WebLogic start script.
- If using the IBM JVM with WebSphere, the server mode is enabled by default. You probably do not need to change any settings.

Refer to http://www.oracle.com/technetwork/java/javase/downloads/index.html for information on downloading the JDK.

Installing the Dynamic Code Evolution Virtual Machine

The Dynamic Code Evolution Virtual Machine (DCE VM) is a modified version of the Java HotSpot Virtual Machine (VM). The DCE VM supports any redefinition of loaded classes at runtime. You can add and remove fields and methods and make changes to the super types of a class using the DCE VM. The DCE VM is an improvement to the HotSpot VM, which only supports updates to method bodies.

Guidewire strongly recommends the use of the DCE VM for development. Guidewire does not support the DCE VM in a production environment. Performance of the Java Virtual Machine (JVM) might be impacted by the addition of the DCE VM.

The DCE VM is packaged as an executable JAR file. You can download the DCE VM JAR file and find instructions to install it at:

https://guidewire.hivelive.com/hives/7a7bd9d656/summary

Shut down the JVM before you run the DCE VM installer.

To install the DCE VM

- 1. Download the DCE VM installer.
- 2. Click Windows button.
- **3.** In the text box, type cmd but do not press Enter.
- 4. Right-click cmd. exe and click Run as administrator.
- 5. In the command window, navigate to the directory where you downloaded the DCE VM installer.
- **6.** Enter the following command:

```
java -jar dcevm-installer.jar
```

- 7. On the installer window, specify the JDK that you are using for development of ClaimCenter.
- 8. Click Install. The installer replaces %JAVA_HOME%/jre/bin/client/jvm.dll and %JAVA_HOME%/jre/bin/ server/jvm.dll. The installer creates copies of the original jvm.dll files and names these files jvm.dll.backup. The installer also adds dcevm.jar to %JAVA_HOME%/jre/lib/ext.

Once you have installed the DCE VM, you can confirm the installation by running the java -version command. The output from the java -version command lists the Java HotSpot 64-bit Server VM after the Java version information.



See also

- "Studio and the DCE VM" on page 97 in the Configuration Guide
- http://java.net/projects/dcevm/

Installing Ant

Ant is a common tool used for platform-independent scripting with Java systems. The ClaimCenter configuration environment and administration tools use Ant for various system administration scripts. Install Ant on each computer that runs these scripts.

See the *Guidewire Platform Support Matrix* for specific Ant version requirements. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.

Obtain Ant from the following URL:

http://ant.apache.org/bindownload.cgi

If you have an ANT_OPTIONS environment variable set, do not include the -XX:+UseParalleIGC option. The -XX:+UseParalleIGC option is not compatible with the Dynamic Code Evolution Virtual Machine (DCE VM), which requires use of its embedded serial garbage collector. Any -XX options are not standard options. These options can vary between platforms and releases and some -XX options might be incompatible with the DCE VM. If you have issues running Guidewire gwcc commands, remove any -XX options from ANT_OPTIONS to determine if there is a conflict with non-standard options.

Setting Environment Variables

After you install Java and Ant, set environment variables so that ClaimCenter can locate them. Make these environment variables available in the user environment in which you plan to run ClaimCenter. The following table lists the variables to set for the different systems:

System	Variable	Example Values and Notes
Application server (all)	JAVA_HOME	C:\Program Files\Java\jdk1.7.0_17
		The Java installer sets JAVA_HOME automatically, but Guidewire recommends that you verify that it is set correctly.
Application server (Tomcat)	CATALINA_OPTS	Specifies the minimum and maximum memory used by Tomcat. For example, the following value for CATALINA_OPTS would set direct JVM memory allocations to 1024 MB (initially) and 1024 MB (maximum), and would allocate 128 MB of background processing memory:
		-server -Xms1024M -Xmx1024M -XX:PermSize=128m -XX:MaxPermSize=128M
		Make your maximum JVM memory allocation (the -Xmx setting) the maximum likely available memory on the server. Guidewire tests have shown that performance of garbage collections are best if the -Xms and -Xmx are set to the same value. See "Operating System Limits on Heap Size" on page 20 for a detailed discussion.
		For more information on configuration options, run the following command to view the built-in help for Java command line options:
		java -X
Development environment,	JAVA_HOME	C:\Program Files\Java\jdk1.7.0_17
administration tools	ANT_HOME	C:\ant
	Add Ant to Path	C:\ant\bin



Before Continuing

Check that you established your environment correctly. Open a new command prompt and display your environment variables to check them.

Documenting Your Environment

Now that you have established your environment, take some time to document it in preparation for installing ClaimCenter. Enter your configuration values in the following tables:

Database Configuration	Value	
Database Name		
Server Name		
Database server port		
ClaimCenter database user name		
Cache size		
Block size		

Application Server Environment Variables	Value	
The user name application runs under		
ANT_HOME		
JAVA_HOME		
CATALINA_HOME		
CATALINA_OPTS		

chapter 3

Installing a ClaimCenter Development Environment

ClaimCenter supports a variety of development environment options depending on your business needs. You can:

- Perform development work using the default bundled QuickStart application server. To deploy a QuickStart development environment, see "Installing the QuickStart Development Environment" on page 46.
- Configure Tomcat to automatically load configuration changes that you make in Guidewire Studio. For instructions, see "Installing a Tomcat Development Environment" on page 49.
- Work on the local configuration files, repackage the configured application into a WAR or EAR file, and
 deploy it to a local or remote application server. Because you must repackage and redeploy a WAR or EAR
 file after making configuration changes, Guidewire does not recommend this approach for a development
 environment. See:
 - "Installing a JBoss Production Environment" on page 78
 - "Installing a WebSphere Production Environment" on page 82
 - "Installing a WebLogic Production Environment" on page 80

Use the QuickStart method if you want to quickly install a development or demonstration ClaimCenter environment using the fewest steps.

IMPORTANT This topic only provides information for installing a ClaimCenter development environment. To install a production environment, first review "Preparing a ClaimCenter Environment" on page 15 and then proceed to "Installing a ClaimCenter Production Environment" on page 55.

This topic includes:

- "Using Multiple ClaimCenter Development Instances" on page 46
- "Installing the QuickStart Development Environment" on page 46
- "Installing a Tomcat Development Environment" on page 49
- "Using the QuickStart Database" on page 51



- "Using SQL Server or Oracle in a Development Environment" on page 52
- "Configuring Archiving for Development Testing" on page 52
- "Installing Sample Data" on page 53

Using Multiple ClaimCenter Development Instances

Occasionally, a developer might want to connect from one machine to multiple ClaimCenter instances running on the same physical or virtual server. In this case, the port number differs for each instance, but the IP address and domain name are the same between the two application instances.

Most containers hold the session ID in a cookie. The container gives the cookie a default name and associates the cookie with a host name or IP address and a path. If you run multiple application servers for the same application, each one generates a session cookie with the same host name and path. The session cookie does not include the port number. Therefore, if you log into one application instance, the browser ends the session with any other application servers having the same host and path, even if port numbers differ.

Note: This is not an issue if you run two different Guidewire applications on a single machine. The two different applications run under different webapp paths.

To work around this issue, open the application instance sessions using different paths. For example, use the fully qualified domain machine name for one application server and localhost for the second application server. The browser does not associate the same cookie with an IP address and with a machine name.

Installing the QuickStart Development Environment

This topic describes using the ClaimCenter QuickStart development environment. The QuickStart method uses a bundled and lightweight application server and database that are suitable for development and demonstration purposes. Guidewire does not support the QuickStart method for a production environment.

This topic includes:

- "Advantages to Using the QuickStart Software" on page 46
- "QuickStart Development Environment Prerequisites" on page 47
- "Installing with QuickStart" on page 47
- "QuickStart Commands" on page 48
- "QuickStart Application Server" on page 48
- "Troubleshooting QuickStart" on page 49

Advantages to Using the QuickStart Software

The bundled lightweight application server and database provided with ClaimCenter make it possible to accomplish more work with less effort and in less time. The following are some specific benefits to using the Quick-Start configuration with Guidewire Studio as the IDE (Integrated Development Environment):

- Install and run ClaimCenter rapidly without any configuration.
- Configure ClaimCenter without needing to repackage WAR or EAR files.
- Import sample data and create new data through the user interface.
- View and experiment with the default functionality of ClaimCenter.
- Make changes to ClaimCenter using Guidewire Studio.

The QuickStart application server (Jetty) is a fully certified servlet container that starts faster than production application servers. It also provides an instantaneous view of configuration changes. The QuickStart server uses



the ClaimCenter configuration files from the file system, rather than requiring a packaged WAR or EAR file. Therefore, developers can configure ClaimCenter without needing to repackage the application.

Note: If you do not want to use the QuickStart application server for development, you can configure Tomcat to point to the configuration resources being edited by Guidewire Studio. For instructions, consult "Installing a Tomcat Development Environment" on page 49. If you decide to use Tomcat, you must deploy a WAR file for production purposes.

QuickStart Development Environment Prerequisites

- Your environment must meet the minimum requirements for a development workstation. See the *Guidewire Platform Support Matrix* for current system and patch level requirements. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform.
- ClaimCenter requires Java with the Dynamic Code Evolution Virtual Machine (DCE VM) and Ant. If you do not install the DCE VM, you will not be able to see dynamic changes to Gosu code. See "Installing Java" on page 41 and "Installing Ant" on page 43 for installation guidelines.

Installing with QuickStart

This topic includes a procedure to install ClaimCenter with the QuickStart application server.

ClaimCenter uses a QuickStart database by default. See "Using the QuickStart Database" on page 51. You can configure a ClaimCenter development environment to use an Oracle or SQL Server database instead. See "Using SQL Server or Oracle in a Development Environment" on page 52 for instructions.

For instructions to install a QuickStart ContactManager development environment, see "Installing ContactManager with QuickStart for Development" on page 39 in the *Contact Management Guide*.

To install ClaimCenter with the bundled QuickStart application server

- **1.** Create an installation directory for ClaimCenter. Do not use spaces in the installation directory path. This guide uses ClaimCenter as the directory name.
- **2.** Unzip the ClaimCenter ZIP file into the ClaimCenter directory. See "ClaimCenter Configuration Files" on page 93 in the *Configuration Guide* for a list of how the files are organized.
- 3. Open a command prompt to ClaimCenter/bin.
- **4.** If you are reinstalling ClaimCenter and using a QuickStart database, drop the QuickStart database by running gwcc dev-dropdb.
- 5. ClaimCenter uses the QuickStart database by default. You can configure where ClaimCenter stores the QuickStart database files. See "Using the QuickStart Database" on page 51. If you want to use an Oracle or SQL Server database in your development environment, see "Using SQL Server or Oracle in a Development Environment" on page 52. Then continue with this procedure after you have created the database account and configured ClaimCenter to connect to the database.
- **6.** Start the QuickStart server with the following command:

gwcc dev-start

When the server has started, you see: *****ClaimCenter ready***** in the command window.

- 7. Open a browser and navigate to http://localhost:8080/cc and login with the default superuser.
 - · User name is su.
 - Password is gw.

After installing ClaimCenter with the QuickStart application server, see the following topics for procedures you might want to use to set up your development environment:



- "Using the QuickStart Database" on page 51
- "Using SQL Server or Oracle in a Development Environment" on page 52
- "Configuring Archiving for Development Testing" on page 52
- "Installing Sample Data" on page 53
- "Configuring Logging" on page 25 in the System Administration Guide
- To integrate ClaimCenter with ContactManager, see "Integrating ContactManager with Guidewire Core Applications" on page 45 in the *Contact Management Guide*.

QuickStart Commands

You launch many ClaimCenter commands by passing arguments to the gwcc command, located in ClaimCenter/bin. For a complete list of gwcc commands, see "Commands Reference" on page 105.

QuickStart Application Server

The QuickStart application server is Jetty, a Java-based HTTP Server and Servlet Container. Jetty was released as an open source project under the Apache 2.0 License and is fully-featured. Refer to http://jetty.mortbay.com for details. The QuickStart application server is suitable for demonstration and development environments. The QuickStart application server is not suitable nor supported for production environments.

ClaimCenter on the QuickStart server always runs in development mode. You cannot run ClaimCenter on the QuickStart server in production mode.

See also

"Server Modes and Run Levels" on page 60 in the System Administration Guide.

Configuring QuickStart Ports

The ClaimCenter/modules/configuration/etc/jetty.properties file lists the ports used by the QuickStart server. You can specify the port on which the server listens, a debug port, and the port to use to stop the server.

The ClaimCenter QuickStart application server listens on port 8080 by default. The ContactManager QuickStart application server listens on port 8280 by default.

IMPORTANT You cannot assign a port number between 8800 and 8900 to the QuickStart server.

Tuning QuickStart Application Server Memory

The ClaimCenter/modules/configuration/etc/memory.properties file specifies memory settings for the QuickStart application server and other gwcc tools. You can set the starting heap size, maximum heap size and maximum permanent size for the QuickStart server. To change one or more of these settings, edit the following values in ClaimCenter/modules/configuration/etc/memory.properties:

- Starting heap size com.guidewire.commons.jetty.GWServerJettyServerMain.xms
- Maximum heap size com.quidewire.commons.jetty.GWServerJettyServerMain.xmx
- $\bullet \ \ Maximum \ permanent \ size-com.guidewire.commons.jetty. GWS erver Jetty Server Main.max permanent \ size-com.guidewire.gui$

You can also adjust the memory settings for other gwcc tools.

See also

"Tuning Command Line Tool Memory Settings" on page 105.



Troubleshooting QuickStart

If you have problems with QuickStart, consider the following:

Issue: You are unable to upgrade or to see changes after changing database tables.

Solution: First try restarting the server. If that does not work, then drop the database. If the server is running, then stop the server by opening a command prompt, navigating to ClaimCenter/bin and entering the following command:

gwcc dev-stop

Then, drop the database with the command gwcc dev-dropdb.

Issue: You experience port conflicts.

Solution: The QuickStart server listens on a default server port. The default server port might already be in use by your organization. Consult with your IT department to verify which ports to use.

See also

"Configuring QuickStart Ports" on page 48.

Installing a Tomcat Development Environment

Although the QuickStart Jetty application server is suitable for most development needs, some organizations prefer to use Tomcat in their development environment. The following procedure enables you to create a ClaimCenter development environment on Tomcat in which you can make configuration changes without having to repackage the application.

To configure a Tomcat ContactManager development environment, see "Installing ContactManager with Tomcat and SQL Server for Development" on page 41 in the *Contact Management Guide*.

Guidewire provides testing APIs in JAR files with names ending in -gunit.jar for use during configuration and development. These APIs are only available when the application is running in development mode, or from within Guidewire Studio. When WAR or EAR files are built, the testing API JAR files are excluded. If your deployed code makes calls to any testing APIs, it causes ClassNotFoundExceptions and other problems and prevents the application from running properly.

See also "Using Multiple ClaimCenter Development Instances" on page 46.

Tomcat Development Environment Prerequisites

- Your environment must meet the minimum requirements for a development workstation. See the *Guidewire Platform Support Matrix* for current system and patch level requirements. The *Guidewire Platform Support Matrix* is available from the Guidewire Resource Portal at https://guidewire.custhelp.com/app/resources/products/platform. Also see "Development Workstation Information" on page 41.
- ClaimCenter requires Java and Ant. Guidewire strongly recommends that you also install the Dynamic Code Evolution Virtual Machine (DCE VM) on development environments. If you do not install the DCE VM, you will not be able to see dynamic changes to Gosu code. See "Installing Java" on page 41 and "Installing Ant" on page 43 for specific required versions and installation guidelines.
- Do not include spaces in the path to your Tomcat installation.

Building a ClaimCenter Development Environment with Tomcat

The following procedure installs a ClaimCenter development environment on Tomcat. If you want to set up a production environment on Tomcat, see "Installing a Tomcat Production Environment" on page 79



To set up a ClaimCenter development environment on Tomcat

- **1.** If you have not already done so, create an installation directory for ClaimCenter. This guide uses ClaimCenter as the directory name.
- **2.** Unzip the ClaimCenter ZIP file into the ClaimCenter directory. See "ClaimCenter Configuration Files" on page 93 in the *Configuration Guide* for a list of how the files are organized.
- **3.** If you are not using a version control system, make a read-only copy of the ClaimCenter directory. This enables you to recover quickly from accidental changes that can prevent ClaimCenter from starting.
- **4.** Create or modify the CATALINA_OPTS environment variable to include the following:
 - -Xms1024m -Xmx1024m -XX:MaxPermSize=128m -Dgw.server.mode=dev
- 5. Open a command prompt to ClaimCenter/bin.
- **6.** If you are reinstalling ClaimCenter and using the QuickStart database, drop the database by running gwcc dev-dropdb.
- 7. ClaimCenter uses the QuickStart database by default. You can configure where ClaimCenter stores the QuickStart database files. See "Using the QuickStart Database" on page 51. If you want to use an Oracle or SQL Server database in your development environment, see "Using SQL Server or Oracle in a Development Environment" on page 52. Then continue with this procedure after you have created the database account and configured ClaimCenter to connect to the database.
- **8.** Run the following command:

```
gwcc build-tomcat-war-dbcp
```

The gwcc build-tomcat-war-dbcp command creates a cc.war file including JDBC drivers and places the WAR file in the ClaimCenter/dist/war directory.

- 9. Deploy the package to Tomcat by copying the cc.war file to the webapps directory in your Tomcat server.
- 10. Use the Tomcat bin/startup.bat command to start Tomcat and allow it to explode the WAR file. When Tomcat starts, it automatically recognizes the new application and unpacks the cc.war into a directory structure within webapps. For this example, Tomcat creates a webapps/cc directory. Each time you deploy a new copy of a cc.war file, delete the existing cc directory structure before you start Tomcat.
- **11.** Delete the Tomcat webapps\cc\modules\configuration directory.
- **12.** Create a symbolic link from the deployed ClaimCenter application on Tomcat to the ClaimCenter\modules\configuration directory of the original ClaimCenter installation location.

Windows 7 and Vista: Use the mklink command to create the link, as in the example below:

```
\label{lem:mklink d} $$ Mklink /d C:\apache-tomcat-7.0.39\leps\cc\modules\configuration C:\ClaimCenter\modules\configuration \\
```

Windows XP: Use the Windows SysInternals program Junction.exe to create the symbolic link. The Junction.exe program is available at:

http://technet.microsoft.com/en-us/sysinternals/bb896768.aspx

13. Restart the Tomcat server.

To test the ClaimCenter development environment on Tomcat

- **1.** If not already running, start the Tomcat server.
- **2.** Open a browser to the ClaimCenter development environment URL. For example:

```
http://localhost:8080/cc
```

Notice that the login page includes a User name field. You change the User name field in this procedure.

- **3.** Launch Guidewire Studio by running the following command from ClaimCenter/bin: gwcc studio
- 4. Expand Localizations.



- 5. Expand the locale you are using.
- 6. Double-click display.properties.
- 7. Select the Web.Login.Username display key.
- Change the value of the Web.Login.Username display key in an obvious manner. For example, add several question marks.
- **9.** Click the Save All icon to save your changes.
- 10. Log into ClaimCenter with the su account. At this point the User name field is unchanged.
- 11. Press ALT+SHIFT+T to open the Server Tools page.
- 12. Select Internal Tools.
- 13. Select Reload.
- 14. Click Reload PCF Files.
- 15. Click Log Out. ClaimCenter redirects you to the login page.
- **16.** Check for your change to the **User name** field. If you properly set up your development environment, the field now displays with the new name you set to the **Web.Login.Username** display key. You can revert this change once you have confirmed the successful configuration of your development environment.

After installing a ClaimCenter development environment with Tomcat, see the following topics for procedures you might want to use to set up your development environment:

- "Using the QuickStart Database" on page 51
- "Using SQL Server or Oracle in a Development Environment" on page 52
- "Configuring Archiving for Development Testing" on page 52
- "Installing Sample Data" on page 53
- "Configuring Logging" on page 25 in the System Administration Guide
- To integrate ClaimCenter with ContactManager, see "Integrating ContactManager with Guidewire Core Applications" on page 45 in the *Contact Management Guide*.

Using the QuickStart Database

By default, ClaimCenter uses the QuickStart database. The QuickStart database is the *H2 Database Engine*. Guidewire includes the QuickStart database for the convenience of those who need a lightweight solution for demonstration and configuration purposes. By default, ClaimCenter creates and stores H2 database files within the tmp/guidewire directory of the local drive.

Setting the Database Configuration and Mode

Set configuration parameters for H2 in the database-config.xml file. For example:

Guidewire uses tmp/guidewire as the database file location and cc as the file prefix in the default configuration. You can modify the database file location and prefix by modifying the value set to the jdbcURL parameter.



Limitations to the QuickStart Database

While the QuickStart database is convenient, Guidewire does not support using it for production. The following are limitations to using the QuickStart database:

- The QuickStart database only supports one connection at a time. Therefore, you cannot have the server running and look at the schema at the same time.
- You cannot test your cluster against the QuickStart database.
- The QuickStart database does not support all upgrades. Guidewire does not test upgrades on the QuickStart database other than the process of creating a database.

To drop your QuickStart database, open a command prompt at ClaimCenter/bin and enter gwcc dev-dropdb.

Additional References

- For more information about the QuickStart database and tools that you can download to view your schema, see http://www.h2database.com.
- For development environment information, see "The Studio Development Environment" on page 90 in the *Configuration Guide* and "Working with the QuickStart Development Server" on page 91 in the *Configuration Guide*.

Using SQL Server or Oracle in a Development Environment

You can use Oracle or SQL Server with the QuickStart application server instead of the QuickStart database. Such a configuration can be used as a development environment only. Guidewire does not support using the Quickstart server for a production environment.

You can also use Oracle or SQL Server with the Tomcat application server instead of the QuickStart database. Such a configuration can be used as a development or production environment.

For instructions on creating a SQL Server or Oracle database instance, consult "Configuring the Database" on page 26. For instructions on configuring ClaimCenter to connect to the database, consult "Configuring a Database Connection" on page 62.

If you are using the QuickStart application server, use the commands listed in "QuickStart Command Tools" on page 106 to control the application server.

Configuring Archiving for Development Testing

If you plan to use archiving in your production environment, enable archiving on a developer workstation so that you can design and test your custom implementation of the archiving plugin.

The default config.xml file has archiving disabled. This is set by the parameter:

```
<param name="ArchiveEnabled" value="false"/>
```

If you want to enable archiving, set the value of ArchiveEnabled to true. Then review the topics listed further in this section to learn how to configure archiving.

If you do not want to enable archiving, Guidewire recommends that you disable the archive work queue.

To disable the archive work queue

- 1. In a command window, navigate to the ClaimCenter\bin directory in the ClaimCenter installation.
- **2.** Launch Guidewire Studio using the following command:

```
gwcc studio
```



- 3. In Studio, open workqueue → work-queue.xml.
- **4.** Comment out the following block by adding <! -- before the block and --> after it:

5. Save your changes.

See "More Information on Archiving" on page 133 in the Application Guide.

Installing Sample Data

This topic explains how to load the sample data included with the base ClaimCenter installation, and describes how the sample data loading mechanism can be reconfigured.

ClaimCenter includes sample data for use in training, configuration and testing. Guidewire strongly recommends that you not load sample data into a production system.

The ClaimCenter server must be in development mode to load sample data. The QuickStart server is always in development mode. If you are using a Tomcat server in your development environment, start the server in development mode. See "Building a ClaimCenter Development Environment with Tomcat" on page 49.

If you have already loaded a sample data set, you must drop the database before you load a different sample data set.

To install sample data

- 1. Log into ClaimCenter with the su account.
- 2. Press ALT+SHIFT+T to open the Server Tools page.
- 3. Click Internal Tools.
- 4. Click CC Sample Data from the menu on the left.
- **5.** Click Load for either the Admin, Demo, or Catastrophe Search data sets. After ClaimCenter loads the data set, the CC Sample Data screen lists the imported object types.

About Importing and Exporting Data in ClaimCenter

For instructions on how to import or export administrative data, consult "Importing and Exporting Administrative Data" on page 109 in the *System Administration Guide*.



chapter 4

Installing a ClaimCenter Production Environment

Installing a ClaimCenter production environment is a multi-step process that requires you to perform several procedures. The initial installation process can take from two hours to a full day. This topic begins with an overview of the installation process and then guides you through each procedure culminating with the deployment of ClaimCenter to a production environment.

For instructions to install a ClaimCenter development environment, see "Installing a ClaimCenter Development Environment" on page 45 instead of this topic.

This topic includes:

- "Unpacking the Configuration Files" on page 55
- "Configuring a Database Connection" on page 62
- "Deploying ClaimCenter to the Application Server" on page 78

Unpacking the Configuration Files

Guidewire packages ClaimCenter as a ZIP file. This file contains tools and files necessary to build a WAR or EAR file to install on an application server, and contains the developer toolkit and other items.

Unpack the configuration files onto the workstation that you plan to use as the home base for your ClaimCenter configuration. These directions assume you plan to maintain the configuration files on the administrative workstation.

To unpack the ClaimCenter configuration environment

- **1.** If you have not already done so, create an installation directory for ClaimCenter. Do not use spaces in the installation directory path. This guide uses ClaimCenter as the directory name.
- 2. Unzip the ClaimCenter ZIP file into the ClaimCenter directory.



3. If you are not using a version control system, make a read-only copy of the ClaimCenter directory. This enables you to recover quickly from accidental changes that can prevent ClaimCenter from starting.

At this point, you have a full set of ClaimCenter configuration files. For an overview of the directories included with ClaimCenter, see "ClaimCenter Configuration Files" on page 93 in the Configuration Guide.

Guidewire recommends that you maintain your ClaimCenter configuration files in a change control system such as Perforce or SVN. If you have such a system, add your ClaimCenter installation directory and files to it at this point.



Key ClaimCenter gwcc Commands

The following key commands are available with ClaimCenter after unpacking the ClaimCenter ZIP file. Launch these commands by passing the command name as a parameter to the gwcc utility in ClaimCenter/bin:

Command	Action
gwcc -p	Displays all gwcc command options.
gwcc build-jboss-war-dbcp	Builds the generic WAR file for JBoss including JDBC drivers. Use gwcc build-jboss-war-dbcp if you are going to have ClaimCenter manage the database connection pool.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-jboss-war-dbcp -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-jboss-war-jndi	Builds the generic WAR file for JBoss without JDBC drivers. Use gwcc build-jboss-war-jndi only if you are going to use a JNDI database connection managed by JBoss. See "Using a JNDI Data Source" on page 68.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-jboss-war-jndi -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-tomcat-war-dbcp	Builds the generic WAR file for Tomcat including JDBC drivers. Use gwcc build-tomcat-war-dbcp if you are going to have ClaimCenter manage the database connection pool.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-tomcat-war-dbcp -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-tomcat-war-jndi	Builds the generic WAR file for Tomcat without JDBC drivers. Use gwcc build-tomcat-war-jndi only if you are going to use a JNDI database connection managed by JBoss. See "Using a JNDI Data Source" on page 68.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-tomcat-war-jndi -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-weblogic-ear-dbcp	Builds the EAR file for WebLogic including JDBC drivers. Use gwcc build-websphere-ear-dbcp if you are going to have ClaimCenter manage the database connection pool.
gwcc build-weblogic-ear-jndi	Builds the EAR file for WebLogic without JDBC drivers. Use gwcc build-websphere-ear-jndi only if you are going to use a JNDI database connection managed by WebLogic. See "Using a JNDI Data Source" on page 68.



Command	Action
gwcc build-websphere-ear-dbcp	Builds the EAR file for WebSphere including JDBC drivers. Use gwcc build-websphere-ear-dbcp if you are going to have ClaimCenter manage the database connection pool.
gwcc build-websphere-ear-jndi	Builds the EAR file for WebSphere without JDBC drivers. Use gwcc build-websphere-ear-jndi only if you are going to use a JNDI database connection managed by WebSphere. See "Using a JNDI Data Source" on page 68.
gwcc displaykey-diff	 A display key difference tool that does the following: Compares each locale configured on the server against the master display key list. Generates a file that contains a list of any missing keys. See "Localizing Typecodes" on page 41 in the Globalization Guide.
gwcc export-l10ns	Exports a translation file from ClaimCenter into a file.
gwcc export-fions -Dexport.file="translation_file" -Dexport.locale="language to export"	 The -Dexport.file parameter specifies the destination file. If you leave the import translation file in the same location, then enter only the name of the file to import. If you move the translation file to a different location, then enter an absolute path or a relative path to the file from the root of the installation directory.
	The -Dexport.locale parameter specifies the destination language to export. The -Dexport.locale parameter must match a ClaimCenter LanguageType type-code, such as fr or ja.
	See "Localizing Typecodes" on page 41 in the Globalization Guide.
<pre>gwcc import-l10ns -Dimport.file="translation_file"</pre>	Imports a translation file into the configuration.
-Dimport.locale=destination_locale	The -Dimport.file parameter specifies the file that contains the translations. It must be in the same format as an export file from Studio.
	The -Dimport.locale parameter specifies the destination language for the translations. The language must match a ClaimCenter LanguageType typecode, such as fr or ja.
	See "Localizing Typecodes" on page 41 in the Globalization Guide.
<pre>gwcc install-localized-module -Dmodule.file=ZipFileName -Dinstall.type={install upgrade}</pre>	Installs or upgrades a language module. See "Installing Display Languages" on page 23 in the <i>Globalization Guide</i> .
gwcc iterator-upgrade	Upgrades all iterators on toolbar buttons and filters. This command is only used during upgrade from a prior major version. See "Running PCF Iterator Upgrade" on page 232 in the <i>Upgrade Guide</i> .
gwcc regen-datamapping-split	Builds the data mapping files with files split out by table and typelist. Data mapping files represent fields present in the physical database. None of the virtual fields are represented.
	Class: com.guidewire.tools.datamapping.DataMappingTool
gwcc regen-datamapping-together	Builds the data mapping files with all tables and typelists concatenated. represent fields present in the physical database. None of the virtual fields are represented.
	Class: com.guidewire.tools.datamapping.DataMappingTool



Command

gwcc regen-dictionary
-DmaxSPVInclusions=n

-DoutputFormat={html|xml}

Action

Generates the *Data Dictionary* and *Security Dictionary*. The *Data Dictionary* includes physical fields in the database and virtual fields in the data model. The *Security Dictionary* includes application permission keys, system permissions, and roles.

Generate the dictionaries the first time you unzip ClaimCenter and each time you update the data model. Run the gwcc regen-java-api and gwcc regen-soap-api commands each time just prior to regenerating the security and data dictionaries.

gwcc regen-dictionary

To view either dictionary in HTML format, open the index file for it in a browser:

ClaimCenter/dictionary/data/index.html ClaimCenter/dictionary/security/index.html

You can generate the Data Dictionary and Security Dictionary in XML format, with associated XSD files. Use the generated XML and XSD files to import the *Data Dictionary* and *Security Dictionary* into third-party database design tools.

gwcc regen-dictionary -DoutputFormat=xml

This command generates the following XML and XSD files for the dictionaries:

GenericCenter/build/dictionary/data/entityModel.xml GenericCenter/build/dictionary/data/entityModel.xsd GenericCenter/build/dictionary/security/securityDictionary.xml GenericCenter/build/dictionary/security/securityDictionary.xsd

You can generate the dictionaries in HTML format while building a WAR file. See the description for gwcc build-jboss-war or gwcc build-tomcat-war for instructions.

For more information, see "Regenerating the Data Dictionary and Security Dictionary" on page 30 in the *Configuration Guide*.

This command performs PCF validation to catch errors in PCF files, such as:

- Invalid expressions
- · Attributes that have no meaning when another attribute is set
- · Editable cells within non-editable objects
- · Illegal use of check boxes
- · Invalid arguments
- Other errors

Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate 12 x 12 x 12 x 12 = 20,736 combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:

gwcc regen-dictionary -DmaxSPVInclusions=1000

In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.

Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.

The ${\tt maxSPVInclusions}$ property can only be specified as a positive integer value.

For more information on second pass verification, see "Setting Verification Options" on page 95 in the *Configuration Guide*.

Classes:

com.guidewire.tools.dictionary.data.DataDictionaryTool com.guidewire.tools.dictionary.security.SecurityDictionaryTool



Command	Action
gwcc regen-from-wsc	Downloads the WSDL and XSD files for all WSC (Web Service Collection) files. Web service collection files encapsulate the set of resources necessary to connect to a web service on an external system. If you view a web service collection in Studio and click the Fetch Updates button, Studio gets the latest WSDL and XSD files from servers that publish those web services. This tool is equivalent to the Fetch Updates process, but runs from the command line and operates on all web services rather than one.
	See "Loading WS-I WSDL Locally Using Studio Web Service Collections" on page 72 in the <i>Integration Guide</i> .
gwcc regen-gosudoc	Generates Gosu documentation similar to JavaDoc but using the ClaimCenter type system. This command produces documentation at ClaimCenter/build/gosudoc/index.html. See "Gosu Generated Documentation ('gosudoc')" on page 37 in the Gosu Reference Guide.
	Class: com.guidewire.tools.gosudoc.GosuDocMain
gwcc regen-java-api	Builds the Java API toolkit and examples to the ClaimCenter/java-api directory. See "Regenerating Integration Libraries" on page 22 in the <i>Integration Guide</i> .
	Class: com.guidewire.commons.entity.external.ExternalGenerator
gwcc regen-pcfmapping	Builds the PCF mappings.
-DmaxSPVInclusions= <i>n</i>	This command performs PCF validation to catch errors in PCF files, such as: Invalid expressions Attributes that have no meaning when another attribute is set Editable cells within non-editable objects Illegal use of check boxes Invalid arguments Other errors
	Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate 12 x 12 x 12 x 12 = 20,736 combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:
	<pre>gwcc regen-pcfmapping -DmaxSPVInclusions=1000</pre>
	In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.
	Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.
	The maxSPVInclusions property can only be specified as a positive integer value.
	For more information on second pass verification, see "Setting Verification Options" on page 95 in the <i>Configuration Guide</i> .
	Class: com.guidewire.tools.pcfmapping.PCFMappingWriterMain
gwxx regen-phone-metadata	Regenerates phone metadata in config/phone/data. Run this command if you have modified the phone metadata XML files
gwcc regen-rulereport	Generates an XML report describing the existing business rules. See "Generating a Rule Repository Report" on page 87 in the <i>Rules Guide</i> .
gwcc regen-soap-api	Builds the SOAP API toolkit and examples to the ClaimCenter/soap-api directory. See "Regenerating Integration Libraries" on page 22 in the <i>Integration Guide</i> .
	Classes: com.guidewire.tools.wsdl.WSDLGenerator com.guidewire.util.webservices.axis.WSDLToJavaGenerator



Command	Action
gwcc regen-soap-local	Regenerates local files related to RPCE web services. Use this command after adding, changing, or removing web services.
	See "Publishing Web Services (RPCE)" on page 89 in the Integration Guide.
gwcc regen-wsi-local	Regenerates the WSDL for all local web services. ClaimCenter generates the WSDL in the ClaimCenter\wsi-local directory.
	See "Generating WS-I WSDL On Disk" on page 50 in the Integration Guide.
gwcc regen-xsd	Builds the XSD files for data import. See "Creating an XML File for Import" on page 115 in the <i>System Administration Guide</i> and "Importing Administrative Data" on page 145 in the <i>Integration Guide</i> .
gwcc studio	Runs Guidewire Studio.
	Class: com.guidewire.studio.main.Main
gwcc verify-checksum	Verifies module checksums.
	Class: com.guidewire.tools.checksum.ModulesChecksumTool
gwcc verify-resources -DmaxSPVInclusions= <i>n</i>	Checks PCF files, XML schemas, and type loaders for errors.
-DmaxSPVinclusions=n	This command performs PCF validation to catch errors in PCF files, such as: Invalid expressions Attributes that have no meaning when another attribute is set Editable cells within non-editable objects Illegal use of check boxes Invalid arguments Other errors
	The command parses and compiles XML schemas and reports any errors.
	For each type loader, the command verifies the types supported by the loader. The command checks if a Gosu class compiles, or if a typelist can be retrieved properly.
	Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate $12 \times 12 \times 12 \times 12 = 20,736$ combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:
	gwcc verify-resources -DmaxSPVInclusions=1000
	In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.
	Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.
	For more information on second pass verification, see "Setting Verification Options" on page 95 in the <i>Configuration Guide</i> .
	The maxSPVInclusions property can only be specified as a positive integer value.
gwcc version	Displays the product version.

This list does not include commands specific to starting and stopping the QuickStart server. For a full list of gwcc commands, see "Commands Reference" on page 105.



Configuring a Database Connection

Set database connections by uncommenting and modifying the appropriate sample <database> element in the database-config.xml file, accessible from Guidewire Studio under configuration \rightarrow config. In this file you supply connection and configuration parameters for your database.

This topic includes the following:

- "The <database> Element" on page 62
- "Mapping Logical Tablespaces to Physical Tablespaces" on page 63
- "Configuring Options for Individual Tables" on page 65
- "Defining Table Groups" on page 66
- "Defining the JDBC URL" on page 66
- "Specifying a Database Password" on page 67
- "Enabling SQL Server JDBC Logging" on page 68
- "Configuring ClaimCenter to Use a JNDI Data Source" on page 68
- "Creating a JNDI Data Source on JBoss" on page 69
- "Creating a JNDI Data Source on WebLogic" on page 71
- "Creating a JNDI Data Source on WebSphere" on page 73

After you have finished configuring the database connection, proceed to "Deploying ClaimCenter to the Application Server" on page 78 for instructions on deploying ClaimCenter to the application server.

The <database> Element

The <database> element in database-config.xml has the following basic structure:

```
<database name="string" env="string" dbtype="db2|oracle|sqlserver" autoupgrade="true|false"</pre>
checker="true| false" addforeignkeys="true| false" printcommands="true| false">
  // If using database connection pool managed by ClaimCenter
<dbcp-connection-pool jdbc-url="jdbc url" password-file="file name">
    <reset-tool-params collation="collation" db2.instance="DB2 instance name"
    oracle.tnsnames="Oracle TNS name" system.username="system username"</pre>
      system.password="system.password"/>
  </dbcp-connection-pool>
  // If using a JNDI data source
  <jndi-connection-pool datasource-name="JNDI data source name" />
  <oracle-settings query-rewrite="true|false" statistics-level-all="true|false"</pre>
  stored-outline-category db-resource-mgr-cancel-sql >
  <upgrade>
    <oracle-db-ddl>
       <tablespaces admin="admin tablespace" index="index tablespace" op="op tablespace'
        staging="staging tablespace" typelist="typelist tablespace" lob="lob tablespace" />
    </oracle-db-ddl>
  </upgrade>
  // SQL Server only
  <sqlserver-settings jdbc-trace-level="JDBC trace level" jdbc-trace-file="JDBC trace file"
unicode-columns="true|false" />
  <upgrade>
     <mssql-db-ddl>
       <mssql-filegroups admin="admin filegroup" index="index filegroup" op="op filegroup"</pre>
        staging="staging filegroup" typelist="typelist filegroup" lob="lob filegroup" />
    </mssql-db-ddl>
  <upgrade>
  // DB2 Only
  <db2-settings />
  <databasestatistics />
</database>
```



Some elements and attributes are not shown. These elements and attributes are described in other sections.

The attributes in the <database> element are:

Attribute	Description
name	A string specifying the database name.
env	A string identifying the environment in which ClaimCenter uses this connection specification. See "env Property" on page 16 in the <i>System Administration Guide</i> for information about using this attribute.
dbtype	The database vendor. Either h2 (for the QuickStart database), oracle or sqlserver.
autoupgrade	A Boolean value specifying whether the server automatically upgrades the database as it starts. The default is false. This parameter is optional. See "Understanding and Authorizing Database Upgrades" on page 41 in the System Administration Guide.
printcommands	A Boolean value specifying whether the server prints database upgrade messages to the console upon startup. By default, printcommands is set to true. Do not set printcommands to false in a production environment.
checker	A Boolean value specifying whether ClaimCenter runs consistency checks before it starts.
	For development environments with small data sets, you can enable consistency checks to run each time the ClaimCenter server starts. Set the checker attribute of the database block to true to enable to enable checks on startup. By default, this option is set to false.
	Running consistency checks upon starting the server can take a long time, impact performance severely, and possibly time out on very large datasets. Set checker to false under most circumstances. Guidewire recommends that you do not set checker to true except in development environments with small test data sets.
	This parameter is optional.
	See "Checking Database Consistency" on page 42 in the <i>System Administration Guide</i> for more information.
addforeignkeys	Used only for development and testing. Do not use this attribute in production.

See also

- "Configuring the Database" on page 26
- "Configuring and Maintaining the ClaimCenter Database" on page 35 in the System Administration Guide

Mapping Logical Tablespaces to Physical Tablespaces

You can map the logical tablespaces required by ClaimCenter to either Oracle or DB2 tablespaces or SQL Server filegroups. For Oracle and DB2, mapping to tablespaces in database-config.xml is required. For SQL Server, mapping to filegroups is optional. Create these physical tablespaces or filegroups when you set up your database. See "Configuring the Database" on page 26 for information on creating physical tablespaces or filegroups for your database.

Specifying Tablespaces for DB2

To specify tablespaces for DB2, use the following syntax in your database configuration in database-config.xml:



To specify tablespaces for a particular table in DB2, use the following syntax in your database configuration in database-config.xml:

Specifying Tablespaces for Oracle

To specify tablespaces for Oracle, use the following syntax in your database configuration in database-config.xml:

To specify tablespaces for a particular table in Oracle, use the following syntax in your database configuration in database-config.xml:

Specifying Filegroups for SQL Server

To specify filegroups for SQL Server, use the following syntax in your database configuration in database-config.xml:

To specify filegroups for a particular table in SQL Server, use the following syntax in your database configuration in database-config.xml:



```
</upgrade>
</database>
```

Configuring Options for Individual Tables

</mssql-table-ddl> </mssql-db-ddl>

You can configure DDL options for individual tables and indexes. Note however that DDL attributes of the primary key backing index (on column named with suffix ID) cannot be specified in the configuration. These attributes are defaulted by the DBMS.

This topic shows valid syntax in database-config.xml for configuring DDL options for each database type. All options are shown for reference. Information about the DDL options is provided in other topics, listed at the end of this topic.

DB₂

```
<database>
       <upgrade>
           <tablespaces admin="admin tablespace" index="index tablespace" op="op tablespace"
             staging="staging tablespace" typelist="typelist tablespace" lob="lob tablespace" />
           <db2-table-ddl table-name="table name">
              <db2-index-ddl index-compression="true|false" key-columns="column1,column2" />
              <db2-table-compression table-tablespace="table tablespace" lob-tablespace="LOB tablespace"</pre>
               index-tablespace="index tablespace"/>
              <db2-table-tablespaces table-tablespace="table tablespace" lob-tablespace="LOB tablespace"</pre>
               index-tablespace="index tablespace"/>
              <db2-index-dd1>
            </db2-table-ddl>
         </db2-db-dd1>
       </upgrade>
     </database>
Oracle
     <database>
       <upgrade>
         <ora-db-ddl>
           <tablespaces admin="admin tablespace" index="index tablespace" op="op tablespace"
            staging="staging tablespace" typelist="typelist tablespace" lob="lob tablespace" />
           <ora-Compression table-compression="NONE|OLTP" index-compression="true|false">
<ora-lobs type="BASIC|SECURE|SECURE_COMPRESSED" caching="true|false" />
           <ora-table-ddl table-name="cc_tableName">
  <ora-index-ddl key-columns="column1, column2" index-compression="true|false"</pre>
               index-tablespace="index tablespace"
                <ora-index-hash-partitioning locality="GLOBAL|LOCAL" num-partitions="number"/>
              </ora-index-ddl>
              <ora-lobs type="BASIC|SECURE|SECURE_COMPRESSED" caching="true|false" />
             <ora-table-compression table-compression="NONE|OLTP" />
<ora-table-hash-partitioning hash-column="column name" num-partitions="number"/>
              <ora-table-tablespaces table-tablespace="table tablespace" lob-tablespace="LOB tablespace"</pre>
               index-tablespace="index tablespace"/>
            </ora-table-ddl>
         </ora-db-ddl>
       </upgrade>
     </database>
SQL Server
     <database>
       <upgrade>
         <mssql-db-ddl>
            <mssql-filegroups admin="admin filegroup" index="index filegroup" op="op filegroup"</pre>
           staging="staging filegroup" typelist="typelist filegroup" lob="lob filegroup" />
<mssql-table-ddl table-name="table name">
              <mssql-index-ddl key-columns="column1,column2" index-compression="true|false"</pre>
               index-filegroup="index filegroup"/>
              <mssql-table-compression table-compression="NONE|PAGE|ROW"</pre>
               index-compression="NONE| PAGE | ROW" />
              <mssql-table-filegroups table-filegroup="table filegroup" lob-filegroup="LOB filegroup"</pre>
               index-filegroup="index filegroup"/>
```



```
</upgrade>
</database>
```

See also

- "Configuring Compression" on page 28
- "Configuring DB2 for ClaimCenter" on page 32
- "Configuring Oracle for ClaimCenter" on page 32
- "Configuring SQL Server for ClaimCenter" on page 37

Defining Table Groups

You can define zero or more table groups within the config element of config.xml. You can use table groups to specify a set of tables on which to run database consistency checks.

To define a table group, add a <tablegroup> element to the config element in config.xml. The <tablegroup> element has an env attribute, a name attribute and a tables attribute. The env attribute specifies the environment for the table group. You can have different table groups set up for different environments. The name attribute identifies the table group. The tables attribute defines which tables are in the table group. Tables are listed in a comma-separated list. For example:

```
<database>
 <tablegroup name="MyTables" tables="cc_sometable1, cc_someTable2, cc_someTable3"/>
```

When the ClaimCenter server starts, it checks that no table is listed more than once in a single table group definitions and that each table listed exists. If a table is listed more than once in a group or does not exist, the ClaimCenter server logs an error and stops.

For instructions to run consistency checks from the ClaimCenter application for a particular table group, see "Consistency Checks" on page 172 in the System Administration Guide. For instructions to run consistency checks from a command prompt, see "System Tools Command" on page 187 in the System Administration Guide.

Defining the JDBC URL

The jdbc-url attribute of the <dbcp-connection-pool> element stores connection information for the database. Define a jdbc-url attribute unless you use a JNDI data source managed by WebLogic or WebSphere. If you want to use a JNDI data source managed by WebLogic or WebSphere, skip to "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.

Defining JDBC URL for Oracle

Specify the JDBC URL for a standalone Oracle instance in either of the following formats:

```
<dbcp-connection-pool jdbc-url="jdbc:oracle:thin:userName/password@serverName:port/OracleSID" />
<dbcp-connection-pool jdbc-url="jdbc:oracle:thin:userName/password@</pre>
 (DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=serverName)(PORT=port))
 (CONNECT_DATA=(SERVICE_NAME=OracleSID)))"/>
```

For Oracle Real Application Cluster (RAC) implementations, use an expanded form of the latter jdbcURL format. For example, a two node Oracle cluster

```
<dbcp-connection-pool jdbc-url="jdbc:oracle:thin:userName/password@</pre>
 (DESCRIPTION=(ADDRESS=(PROTOCOL=TCP)(HOST=node1)(PORT=port))
(ADDRESS=(PROTOCOL=TCP)(HOST=node2)(PORT=port))(LOAD_BALANCE=yes)
(CONNECT_DATA=(SERVER=DEDICATED)(SERVICE_NAME=0rac1eSID)))"/>
```

The default port number for Oracle is 1521.

You can specify the *serverName* as the computer name or IP address.



Guidewire bundles the Oracle 12.1.0.1.0 Production JDBC Thin Driver, pure Java, Type IV driver in ClaimCenter/admin/lib/ojdbc7-12.1.0.1.0.jar. Oracle documentation describes how to format the URL. Refer to the following page for more information:

http://download.oracle.com/docs/cd/B19306_01/java.102/b14355/urls.htm#BEIJFHHB

Defining JDBC URL for SQL Server

Specify the JDBC URL for SQL Server in the following format:

```
<dbcp-connection-pool jdbc-url="jdbc:sqlserver://serverName[:port];
databaseName=cc;user=ccUser;password=password
[;applicationName=applicationName]"/>
```

Optional parameters are shown in brackets.

The default port number for SQL Server is 1433. If your SQL Server instance listens on the default port, 1433, you can omit the port and preceding colon from the JDBC URL. However, Microsoft recommends that you always specify the port value for security reasons. When you specify the port number, the JDBC driver connects directly to SQL Server and does not make a request to sqlbrowser.exe. If your SQL Server instance is listening to a different port than the default 1433, specify that port number in the JDBC URL.

You can include an applicationName property on the JDBC URL connection string. If you set this value, the server logs and Activity Monitor include it when identifying threads. If you do not specify an applicationName, the ClaimCenter server creates one by concatenating cc, followed by the application version, including build number. Finally, if you defined the SQL Server ADDL_CONN_DESCR system property, ClaimCenter appends this value to the generated applicationName value.

ClaimCenter requires that the selectMethod on the JDBC URL connection be set to direct. This is the default value, so you do not need to include this value in your JDBC URL. If you include selectMethod and set it to cursor, the server does not start.

ClaimCenter defaults the value of the sendStringParametersAsUnicode property to be the correct, appropriate value in the SQL Server JDBC URL connection. ClaimCenter does not override an existing value. If you set sendStringParametersAsUnicode in database-config.xml, the server will validate the value to be correct.

Specifying a Database Password

Supply a password with your database connection parameters. To store the database password in the database-config.xml file, set the password in the JDBC URL. If you do not want to expose this password in database-config.xml, Guidewire provides the following alternatives:

- "Using a Password File" on page 67
- "Using the Database Authentication Plugin" on page 68
- "Using a JNDI Data Source" on page 68

Using a Password File

You can place the password in an external file and reference this file from the database-config.xml file.

To use a password file

- 1. Add the password-file attribute to the <dbcp-connection-pool> element within the <database> element.
- **2.** Set the value of password-file to the absolute path of the password file.
- **3.** Replace the password value in the jdbc-url connection specification with a \${password} placeholder. At run time, ClaimCenter reads the password from the file.

When you are done, your database specification looks similar to the following:

```
<database name="ClaimCenterDatabase" driver="dbcp"
dbtype="sqlserver" autoupgrade="true">
   <dbcp-connection-pool jdbc-url="jdbc:sqlserver://HOSTNAME:1433;databaseName=cc;user=ccUser;</pre>
```



```
password=${password}" password-file="c:\secure\password.txt" />
</database>
```

Using the Database Authentication Plugin

For an even higher level of security, Guidewire provides a database authentication plugin: DBAuthenticationPlugin. You can use this plugin to define a custom method that returns the user name and password in a format that the database system recognizes. For information on implementing this in your environment, see "Database Authentication Plugins" on page 195 in the *Integration Guide*.

Using a JNDI Data Source

You can configure ClaimCenter to use a JNDI data source on a JBoss, WebLogic or WebSphere application server for your database connection. This data source uses a Java 2 Connector (J2C) authentication alias to store the user name and password. See "Configuring ClaimCenter to Use a JNDI Data Source" on page 68 for details.

Enabling SQL Server JDBC Logging

During troubleshooting, Guidewire might request a trace log from the Microsoft JDBC driver. This topic describes how to enable trace logging for SQL Server. Do not turn on logging in other circumstances as it places a heavy overhead on the system, and the files created can quickly become very large.

Microsoft JDBC driver logging can be turned on at startup for ClaimCenter by specifying the jdbc-trace-file and jdbc-trace-level attributes on the <sqlserver-settings> element:

```
<database ...>
    <sqlserver-settings jdbc-trace-file="file name" jdbc-trace-level="trace level" />
</database>
```

The trace level is a string that corresponds to a valid trace level as documented at http://msdn.microsoft.com/en-us/library/ms378517(SQL.90).aspx?ppud=4. The trace file can be specified, or defaults to C:\temp\msjdbctrace%u.log. The trace file specified is a pattern documented at http://java.sun.com/j2se/1.5.0/docs/api/java/util/logging/FileHandler.html. Using %h and %t puts the file in the Documents and Settings directory under the name which is running the application server.

A page called Microsoft JDBC Driver Logging is available in the ClaimCenter Info Pages. This page enables you to start and stop Microsoft driver logging on a running application server. Using this page might be a better option when tracing a particular operation, in order to minimize system impact and size of the trace file. To turn tracing on, choose a logging level, simple or XML logging format and a log file location. Click Set Logging Level. Messages report the outcome of the operation.

If logging has already been enabled through database-config.xml or previous use of this page, then the logging level resets to the new level. ClaimCenter flushes and closes any existing logging files before beginning the new trace. If OFF is the chosen logging level, logging is turned off. Any existing logging files are flushed and closed.

The ability to control logging of the Microsoft JDBC driver through ClaimCenter only works when using the internal connection pool, not when using an external JNDI data source connection pool.

Configuring ClaimCenter to Use a JNDI Data Source

ClaimCenter can use a Java Naming and Directory Interface (JNDI) data source managed by a JBoss, WebLogic, or WebSphere application server. This enables you to configure database parameters, including connection pool size, using the application server. Using a JNDI data source also provides you with another secure alternative to placing the user name and password in the database-config.xml file.

IMPORTANT Guidewire only supports JNDI using the drivers bundled with ClaimCenter. Guidewire does not support the XA versions of a data source.



By default, the database connection in database-config.xml defines a Java Database Connectivity (JDBC) specification for connecting to the database. To specify a JNDI data source connection, replace the <dbcp-connection-pool> element on your <database> element with a <jndi-connection-pool> element.

To configure ClaimCenter to use a JNDI data source

- 1. Open database-config.xml from the Guidewire Studio Project window under configuration → config.
- **2.** Remove the <dbcp-connection-pool> element.
- **3.** Add a <jndi-connection-pool> element and specify the JNDI name you assign to the data source as a datasource-name attribute.

When you are finished, the <database> element looks similar to the following:

This example is for a direct JNDI lookup. If you want to use an indirect JNDI lookup, use the format java:comp/env/jdbc/DataSourceName for the datasource-name value, replacing DataSourceName with the name you assigned to the data source.

- **4.** Close and save the database-config.xml file.
- **5.** Rebuild and install the ClaimCenter application EAR file. See "Deploying ClaimCenter to the Application Server" on page 78 for instructions.

Before deploying ClaimCenter to the application server, create the JNDI data source on the application server. See one of the following topics, depending on your application server type:

- "Creating a JNDI Data Source on JBoss" on page 69
- "Creating a JNDI Data Source on WebLogic" on page 71
- "Creating a JNDI Data Source on WebSphere" on page 73

During startup, ClaimCenter records the connection made through JNDI with an entry similar to the following in the log:

```
2008-06-21 10:49:13,260 INFO Looking up JNDI datasource 'jdbc/ccDataSource'...
```

Creating a JNDI Data Source on JBoss

This topic describes how to create a JNDI data source on JBoss. To configure ClaimCenter to use the data source, see "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.

This topic includes the following:

- "Creating an Oracle JNDI Data Source on JBoss" on page 69
- "Creating a SQL Server JNDI Data Source on JBoss" on page 70

Creating an Oracle JNDI Data Source on JBoss

This section describes how to create an Oracle JNDI data source on JBoss.

To create an Oracle JNDI data source on JBoss

- **1.** Copy the ojdbc7-12.1.0.1.0.jar file from the ClaimCenter/admin/lib directory to the JBoss server/ server/lib directory.
- **2.** Start the JBoss application server.
- **3.** Log in to the JBoss AS Admin Console.
- 4. Select JBossAS Servers \rightarrow JBoss AS 5 (default) \rightarrow Resources \rightarrow Datasources \rightarrow No Tx Datasources.



- 5. Click Add a new resource.
- 6. Select Oracle No TX (No Tx Datasource).
- 7. Click Continue.
- **8.** Enter a JNDI Name, such as ccDataSource. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file.
- **9.** Enter the Username for the database connection.
- 10. Enter the Password.
- 11. Verify that the JDBC Driver Class is oracle.jdbc.driver.OracleDriver.
- **12.** Specify the Connection URL using the following format:

jdbc:oracle:thin:@servername:port:sid

- **13.** Under Advanced, set the following:
 - · Background Validation to Yes
 - · Background Validation Millis to 5000
 - · Use Java Context to No

Accept the default values for the other advanced settings.

- 14. Click Save. The JBoss Administration Console returns to the No Tx Datasource page.
- **15.** Select the new data source.
- 16. Select the Control tab.
- 17. Click Test Connection to verify that the connection is valid.

Creating a SQL Server JNDI Data Source on JBoss

This section describes how to create a SQL Server JNDI data source on JBoss.

To create a SQL Server JNDI data source on JBoss

- **1.** Copy the sqljdbc4-4.0.2206.100.jar file from the ClaimCenter/admin/lib directory to the JBoss server/server/lib directory.
- 2. Start the JBoss application server.
- 3. Log in to the JBoss EAP Admin Console.
- 4. Select JBossAS Servers → JBoss EAP 5 (default) → Resources → Datasources → No Tx Datasources.
- 5. Click Add a new resource.
- 6. Select default (No Tx Datasource).
- 7. Click Continue.
- **8.** Enter a JNDI Name, such as ccDataSource. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file.
- **9.** Enter the Username for the database connection.
- 10. Enter the Password.
- $\textbf{11.} \ Set \ the \ \textbf{JDBC Driver Class} \ to \ \texttt{com.microsoft.sqlserver.jdbc.SQLServerDriver}.$
- **12.** Specify the Connection URL using the following format: jdbc:sqlserver://servername:port;databasename=dbname;user=username
- 13. Under Connection Properties, click Add New.



- 14. Add the property Name sendStringParametersAsUnicode.
- **15.** If using a unicode database, set the **Value** of the property sendStringParametersAsUnicode to true. If using a single-byte database, set sendStringParametersAsUnicode to false.
- **16.** Under Advanced, set the following:
 - · Background Validation to Yes
 - · Background Validation Millis to 5000
 - Use Java Context to No
 - Check Valid Connection SQL to SELECT 1 WHERE 1 = 0

Accept the default values for the other advanced settings.

- 17. Click Save. The JBoss Administration Console returns to the No Tx Datasource page.
- **18.** Select the new data source.
- 19. Select the Control tab.
- **20.** Click Test Connection to verify that the connection is valid.

Creating a JNDI Data Source on WebLogic

This topic describes how to create a JNDI data source on WebLogic. To configure ClaimCenter to use the data source, see "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.

This topic includes the following:

- "Creating an Oracle JNDI Data Source on WebLogic" on page 71
- "Creating a SQL Server JNDI Data Source on WebLogic" on page 72

Creating an Oracle JNDI Data Source on WebLogic

This section describes how to create an Oracle JNDI data source on WebLogic.

To copy the ojdbc7-12.1.0.1.0-prod.jar file to WebLogic

- 1. Copy the ojdbc7-12.1.0.1.0-prod.jar file from the ClaimCenter/admin/lib directory to the server/lib directory within the WebLogic home. The ojdbc7-12.1.0.1.0-prod.jar file contains the APIs for connecting to the ClaimCenter database.
- **2.** Delete the ojdbc6.jar file from the WebLogic server/lib directory.
- 3. Add the ojdbc7-12.1.0.1.0-prod.jar file to the classpath of the WebLogic domain.

To modify the classpath for a single domain, open the *WL_HOME*/common/bin/commEnv script appropriate to your operating system in a text editor. Then, prepend the absolute path to the ojdbc7-12.1.0.1.0-prod.jar file, including file name, to the WEBLOGIC_CLASSPATH environment variable. The WebLogic server must be restarted for this change to take effect.

To modify the classpath for all domains, open the setDomainEnv script appropriate to your operating system in a text editor. Then, prepend the absolute path to the ojdbc7-12.1.0.1.0-prod.jar file to the PRE_CLASSPATH environment variable. The WebLogic server must be restarted for this change to take effect.

4. Restart WebLogic.

To create the data source

- **1.** Open the WebLogic Server Administration Console.
- 2. Choose Service → Data Source.
- 3. Click Lock & Edit.



- 4. Click New to create a Generic Data Source.
- **5.** Enter a name and JNDI name for the data source. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file. The JNDI name typically begins with jdbc/.
- 6. Select Oracle as the Database Type.
- 7. Select Oracle's Driver (Thin) for Service Connections.
- 8. Select Versions: 9.0.1 and later for Database Driver and click Next.
- **9.** Fill in connection properties for your environment and click Next. The WebLogic Server Administration Console displays the Test Database Connection page.
- 10. Leave Driver Class Name as oracle.jdbc.OracleDriver.
- **11.** Click **Test Configuration**. If you configured the connection properly and the database is running, WebLogic displays the message "Connection test succeeded."
- 12. Click Next.
- **13.** Select the servers that use the data source.
- **14.** Click Finish. The WebLogic Server Administration Console returns you to the Summary of JDBC Data Sources page.
- **15.** Click **Activate Changes**. WebLogic displays the message "All changes have been activated. No restarts are necessary."

Creating a SQL Server JNDI Data Source on WebLogic

This section describes how to create a SQL Server JNDI data source on WebLogic.

To copy the sqljdbc4-4.0.2206.100.jar file to WebLogic

- 1. Copy the sqljdbc4-4.0.2206.100.jar file from the ClaimCenter/admin/lib directory to the server/lib directory within the WebLogic home. The sqljdbc4-4.0.2206.100.jar file contains the APIs for connecting to the ClaimCenter database.
- 2. Add the sqljdbc4-4.0.2206.100.jar file to the classpath of the WebLogic domain.

To modify the classpath for a single domain, open the <code>WL_HOME/common/bin/commEnv</code> script appropriate to your operating system in a text editor. Then, prepend the absolute path to the <code>sqljdbc4-4.0.2206.100.jar</code> file, including file name, to the <code>WEBLOGIC_CLASSPATH</code> environment variable. The WebLogic server must be restarted for this change to take effect.

To modify the classpath for all domains, open the setDomainEnv script appropriate to your operating system in a text editor. Then, prepend the absolute path to the sqljdbc4-4.0.2206.100.jar file to the PRE_CLASSPATH environment variable. The WebLogic server must be restarted for this change to take effect.

To create the data source

- **1.** Open the WebLogic Server Administration Console.
- 2. Click Service \rightarrow Data Source.
- 3. Click New to create a Generic Data Source.
- **4.** Enter a Name and JNDI Name for the data source. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file.
- 5. Select MS SQL Server as the Database Type.
- **6.** Select Other as the Database Driver, and click Next.



- 7. Uncheck Supports Global Transactions, and click Next.
- 8. Specify connection properties for the SQL Server database, and click Next.
- 9. Enter com.microsoft.sqlserver.jdbc.SQLServerDriver for the Driver Class Name.
- **10.** Specify the URL using the following format: jdbc:sqlserver://servername:port;databasename=dbname;user=username
- 11. Fill in connection properties for your environment. If using a unicode database, set the property sendStringParametersAsUnicode to true. If using a single-byte database, set sendStringParametersAsUnicode to false.
- **12.** Click **Test Configuration**. If you configured the connection properly and the database is running, WebLogic displays the message "Connection test succeeded."
- 13. Click Next.
- **14.** Select the targets that use the data source.
- **15.** Click Finish. The WebLogic Server Administration Console returns you to the Summary of JDBC Data Sources page.
- **16.** Click **Activate Changes**. WebLogic displays the message "All changes have been activated. No restarts are necessary."

Creating a JNDI Data Source on WebSphere

This topic describes how to create a JNDI data source on WebSphere. To configure ClaimCenter to use the data source, see "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.

This topic includes the following:

- "Creating an Oracle JNDI Data Source on WebSphere" on page 73
- "Creating a SQL Server JNDI Data Source on WebSphere" on page 75

Creating an Oracle JNDI Data Source on WebSphere

This section describes how to create an Oracle data source on WebSphere.

To copy the ojdbc7-12.1.0.1.0-prod.jar file to WebSphere

Before you begin, copy the ojdbc7-12.1.0.1.0-prod.jar file from ClaimCenter/admin/lib to the WebSphere WAS_HOME/lib/ext directory. The ojdbc7-12.1.0.1.0-prod.jar file contains the APIs for connecting to the ClaimCenter database.

To create the JDBC provider

- 1. Open the WebSphere Administrative Console if not already open.
- **2.** Choose Resources \rightarrow JDBC \rightarrow JDBC Providers.
- 3. Set the Scope to Cell.
- 4. Click New to create a new JDBC provider.
- **5.** Select Oracle for the Database type.
- **6.** Select Oracle JDBC Driver for the Provider type.
- 7. Select Connection pool data source for the Implementation type.
- **8.** Supply a new Name for the JDBC provider, for example ccOracle.
- **9.** Enter a Description for the JDBC provider if you want.



- 10. Click Next.
- **11.** Specify the directory location of ojdbc7-12.1.0.1.0-prod.jar. Set the value to the WAS_HOME/lib/ext path where you copied ojdbc7-12.1.0.1.0-prod.jar earlier.
- 12. Click Next.
- 13. Review the Summary page. Click Previous if you need to make changes. Otherwise, click Finish.
- 14. Click Save to apply your changes to the master configuration.
 WebSphere returns you to the JDBC Providers page. At this point, you have completed the creation of the new provider.

To create the data source

- **1.** Open the WebSphere Administrative Console if not already open.
- 2. If you do not yet have a J2C (Java 2 Connector) authentication alias, create a new one.
 - a. Click Security \rightarrow Global security.
 - b. Under Authentication click Java Authentication and Authorization \rightarrow J2C authentication data.
 - c. Click New.
 - **d.** Enter the following.

Parameter	Value
Alias	A string specifying the alias name. The alias can be anything you like, for example ccAlias.
User ID	A string specifying the user name.
Password	A string specifying the password.

- e. Click OK.
- f. Click Save to save apply your changes to the master configuration.
- **g.** Start the procedure to create the data source again, beginning with step 3.
- **3.** Choose Resources \rightarrow JDBC \rightarrow JDBC Providers.
- 4. Set the Scope to Cell.
- 5. Select the JDBC provider that you defined for Oracle. WebSphere displays the Configuration tab.
- 6. Select Data Sources in the Additional Properties section. WebSphere displays the Data sources page.
- 7. Click New to create a new data source.
- **8.** Enter a JNDI name for the data source. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file. See "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.
- 9. Click Next.
- 10. Set the URL value using the jdbc:oracle:thin:@hostname:port:ORACLE_SID format.
- 11. Select Oracle11g data store helper for the Data store helper class name.
- 12. Click Next.
- **13.** Select an authentication alias for the Component-managed authentication alias.
- 14. Select an authentication alias for the Container-managed authentication alias.



- **15.** Click **Next**. Review the information on the **Summary** page. Click **Previous** if you need to make changes. Otherwise, click **Finish**.
- **16.** Click **Save** to save apply your changes to the master configuration.

To configure data source properties

- **1.** Open the WebSphere Administrative Console if it is not already open.
- **2.** Choose Resources \rightarrow JDBC \rightarrow Data sources.
- **3.** Click the data source that you just defined. WebSphere displays the Configuration tab.
- 4. Click WebSphere Application Server data source properties.
- 5. Set Statement cache size to 0.
- 6. Select Non-transactional data source.
- 7. Click OK.
- 8. Under Additional Properties, click Custom Properties.
- 9. At the top of the Custom properties page, click New.
- **10.** Enter the Name commitOrRollbackOnCleanup.
- 11. Enter the Value rollback.
- 12. Click OK.
- 13. Click Save to apply your changes to the master configuration.

To test the connection

- 1. In the WebSphere Administrative Console, select Resources → JDBC → Data sources to return to the Data sources page.
- 2. Select the checkbox next to your ClaimCenter data source.
- 3. Click Test Connection to verify that the connection works.

Creating a SQL Server JNDI Data Source on WebSphere

This section describes how to create a SQL Server JNDI data source on WebSphere.

To copy the sqljdbc4-4.0.2206.100.jar file to WebSphere

Before you begin, copy the sqljdbc4-4.0.2206.100.jar file from ClaimCenter/admin/lib to the WebSphere lib/ext directory. The sqljdbc4-4.0.2206.100.jar file contains the APIs for connecting to the ClaimCenter database.

To create the JDBC provider

- 1. Open the WebSphere Administrative Console if not already open.
- 2. Choose Resources \rightarrow JDBC \rightarrow JDBC Providers.
- 3. Set the Scope to Cell.
- **4.** Click New to create a new JDBC provider.
- 5. Select SQL Server for the Database type.
- 6. Select Microsoft SQL Server JDBC Driver for the Provider type drop down and click OK.
- 7. Select Connection pool data source for the Implementation type.



- 8. Supply a new Name for the JDBC provider, for example ccSQLServer.
- **9.** Enter a Description for the JDBC provider if you want.
- 10. Click Next.
- 11. Specify the directory location of sqljdbc4-4.0.2206.100.jar. Set the value to the WebSphere lib/ext directory. For example, you might set it to:

C:\Program Files\IBM\WebSphere\AppServer\lib\ext

You can ignore that the greyed out Class path box lists the JAR name as sqljdbc.jar instead of sqljdbc4-4.0.2206.100.jar.

You do not need to enter a value for the Native library path.

- 12. Click Next.
- 13. Review the Summary page. Click Previous if you need to make changes. Otherwise, click Finish.
- 14. Click Save to apply your changes to the master configuration.
 WebSphere returns you to the JDBC Providers page. At this point, you have completed the creation of the new provider.
- **15.** Select the JDBC provider you just created.
- **16.** Edit the Class path to change \${MICROSOFT_JDBC_DRIVER_PATH}/sqljdbc.jar to \${MICROSOFT_JDBC_DRIVER_PATH}/sqljdbc4-4.0.2206.100.jar.
- 17. Click OK.
- **18.** Click **Save** to apply your changes to the master configuration.

To create the data source

- 1. Open the WebSphere Administrative Console if it is not already open.
- 2. If you do not yet have a J2C (Java 2 Connector) authentication alias, create a new one.
 - a. Click Global J2C authentication alias.
 - b. Click New.
 - c. Enter the following.

Parameter	Value
Alias	A string specifying the alias name. this can be anything you like, for example ccAlias.
User ID	A string specifying the user name.
Password	A string specifying the password.

- d. Click OK.
- e. Click Save to save apply your changes to the master configuration.
- **f.** Start the procedure to create the data source again, beginning with step 3.
- **3.** Choose Resources \rightarrow JDBC \rightarrow JDBC Providers.
- 4. Set the Scope to Cell.
- **5.** Select the JDBC provider that you created for SQL Server. WebSphere displays the Configuration tab.
- 6. Select Data Sources in the Additional Properties section.

WebSphere displays the Data sources page.



7. Click New to create a new data source.

Enter a JNDI name for the data source, such as jdbc/ccDataSource. The JNDI name must match the value of the datasource-name attribute of the <jndi-connection-pool> element in the database-config.xml file. See "Configuring ClaimCenter to Use a JNDI Data Source" on page 68.

- 8. Click Next.
- 9. Enter the Database name.
- **10.** If using a different port to connect to the database than the default of 1433, change the **Port number** value.
- 11. Enter the Server name for the server hosting SQL Server.
- **12.** Uncheck the box for Use this data source in container managed persistence (CMP).
- 13. Click Next.
- 14. Select an authentication alias for the Component-managed authentication alias.
- 15. Select an authentication alias for the Container-managed authentication alias.
- **16.** Click Next. Review the information on the Summary page. Click Previous if you need to make changes. Otherwise, click Finish.
- 17. Click Save to save apply your changes to the master configuration.

To configure data source properties

- 1. Open the WebSphere Administrative Console if it is not already open.
- **2.** Choose Resources \rightarrow JDBC \rightarrow Data sources.
- 3. Click the data source you created for SQL Server.
- 4. Under Additional Properties, click WebSphere Application Server data source properties.
- 5. Set the Statement cache size to 0.
- 6. Select the Non-transactional data source checkbox.
- 7. Click OK.
- **8.** Click **Save** to apply your changes to the master configuration.
- 9. Click the data source you created for SQL Server.
- 10. Under Additional Properties, click Custom Properties.
- 11. Check the property sendStringParametersAsUnicode. If you are using unicode columns (nvarchar), then this must be set to true. If you are not using nvarchar, but single byte varchar columns, this must be set to false. Your application server will not start up if this setting is incorrect. If you need to change the value, click the property name.
- **12.** At the top of the Custom properties page, click New.
- 13. Enter the Name commitOrRollbackOnCleanup.
- 14. Enter the Value rollback.
- 15. Click OK.
- **16.** Click **Save** to apply your changes to the master configuration.

To test the connection

1. In the WebSphere Administrative Console, select Resources → JDBC → Data sources to return to the Data sources page.



- 2. Select the checkbox next to your ClaimCenter data source.
- 3. Click Test Connection to verify that the connection works.

Deploying ClaimCenter to the Application Server

After you have defined the database connection specification, deploy ClaimCenter to the application server. Deploying ClaimCenter requires creating a WAR or EAR file and installing the package on an application server.

These instructions are for creating a production ClaimCenter environment. For instructions to create a development ClaimCenter environment, see "Installing a ClaimCenter Development Environment" on page 45.

This topic includes the following:

- "Installing a JBoss Production Environment" on page 78
- "Installing a Tomcat Production Environment" on page 79
- "Installing a WebLogic Production Environment" on page 80
- "Installing a WebSphere Production Environment" on page 82

Installing a JBoss Production Environment

If you are running JBoss in a 64-bit JVM, you might need to increase the heap size to prevent JBoss from running out of memory. You can set Java options in the JBoss bin/run.bat or bin/run.sh file by adding a line similar to the following:

```
set JAVA_OPTS=-Xms512M -Xmx1024M -XX:MaxPermSize=512M -Dsun.rmi.dgc.client.gcInterval=3600000 -Dsun.rmi.dgc.server.gcInterval=3600000 -Dorg.jboss.resolver.warning=true -server
```

Alternatively, you can specify the Java options by creating a JAVA_OPTS environment variable.

The specific values used for JAVA_OPTS in this example might not be suitable for your environment. Contact Guidewire if you need assistance.

To deploy ClaimCenter to JBoss, add any additional servlets, then generate and deploy the WAR file.

To add servlet definitions

- **1.** Start Studio by running the following command from the ClaimCenter/bin directory: gwcc studio
- **2.** Open configuration \rightarrow deploy \rightarrow WEB-INF \rightarrow web.xml.
- **3.** Add servlet definitions as needed. See the defined servlets for an example.
- **4.** Add a servlet-mapping definition for each servlet that you add. See the defined servlet mappings for an example.
- **5.** Save your changes.

To generate and deploy the JBoss WAR file

- 1. Open a command prompt.
- 2. Navigate to ClaimCenter/bin.
- **3.** Run one of the following commands:

```
gwcc build-jboss-war-dbcp
gwcc build-jboss-war-jndi
```

Both commands generate the ClaimCenter WAR file in the ClaimCenter dist/war directory. Run gwcc build-jboss-war-dbcp to build the EAR file with JDBC drivers for use with JBoss. Run gwcc build-jboss-war-dbcp if you are going to have ClaimCenter manage the database connection pool. Run



gwcc build-jboss-war-jndi to build the EAR file without JDBC drivers. Use gwcc build-jboss-war-jndi only if you are going to use a JNDI database connection managed by JBoss. See "Using a JNDI Data Source" on page 68.

- **4.** Copy cc.war to the deploy directory in a server configuration directory, for example, \$JBossRoot/jboss-as/server/default/deploy. This example uses the default server configuration directory.
- **5.** For a standalone JBoss server, copy the appropriate database driver JAR file from ClaimCenter/admin/lib to \$JBossRoot/\$servername/lib. Copy the JAR file that contains database drivers for your database type:

Database	Driver JAR
DB2	db2jcc4-4.13.127.jar
Oracle	ojdbc7-12.1.0.1.0.jar
SQL Server	sqljdbc4-4.0.2206.100.jar

For a domain managed server with an SQL Server database, use the following procedure instead:

- **a.** Create folder structure: JBOSS_DIST\modules\com\microsoft\main.
- **b.** Create the following XML file:

- ${f c.}$ Save the file as module.xml in JBOSS_DIST\modules\com\microsoft\main.
- d. Copy the appropriate database driver JAR file sqljdbc4-4.0.2206.100.jar from ClaimCenter/admin/ lib to JBOSS_DIST/modules/com/microsoft.
- e. Open the JBoss command line interface and invoke the following command on one line to deploy the driver:

```
i. /profile=full/subsystem=datasources/jdbc-driver=sqlserver:add(driver-name=sqlserver,
driver-module-name=com.microsoft,
driver-xa-datasource-class-name=com.microsoft.sqlserver.jdbc.SQLServerXADataSource)
```

Review the post-installation tasks in "Additional ClaimCenter Setup Tasks" on page 85. Then proceed to "Starting ClaimCenter on JBoss" on page 102.

Installing a Tomcat Production Environment

Tomcat requires a WAR package file. Before you deploy to Tomcat, check that you have defined the CATALINA_OPTS variable with a value of:

```
-Xms1024M -Xmx1024M -XX:PermSize=128m -XX:MaxPermSize=128M
```

Deploying the Tomcat WAR File

Define any necessary servlets in web.xm1. Then build a WAR file and deploy the WAR file to Tomcat.

To add servlet definitions

- **1.** In Studio, open configuration \rightarrow deploy \rightarrow WEB-INF \rightarrow web.xml.
- **2.** Add a servlet-mapping definition for each servlet that you add. See the defined servlet mappings for an example.



3. Save web.xml.

To deploy to Tomcat

- 1. Open a command window.
- 2. Navigate to ClaimCenter\bin.
- 3. Run one of the following commands:

```
gwcc build-tomcat-war-dbcp
gwcc build-tomcat-war-jndi
```

Both commands generate the ClaimCenter WAR file in the ClaimCenter dist/war directory. Run gwcc build-tomcat-war-dbcp to build the EAR file with JDBC drivers for use with Tomcat. Run gwcc build-tomcat-war-dbcp if you are going to have ClaimCenter manage the database connection pool. Run gwcc build-tomcat-war-jndi to build the EAR file without JDBC drivers. Use gwcc build-tomcat-war-jndi only if you are going to use a JNDI database connection managed by Tomcat. See "Using a JNDI Data Source" on page 68.

4. Deploy the package to Tomcat by copying the cc.war file to the webapps directory in your Tomcat server. When Tomcat starts up, it automatically recognizes ClaimCenter and unpacks the cc.war into a directory structure within Tomcat\webapps. For this example, Tomcat creates a Tomcat\webapps\cc directory. Each time you deploy a new copy of a cc.war file, delete the pre-existing cc directory structure created by the old cc.war file.

Review the post-installation tasks in "Additional ClaimCenter Setup Tasks" on page 85. Then proceed to "Starting ClaimCenter on Tomcat on Windows" on page 102.

Installing a WebLogic Production Environment

For WebLogic, ClaimCenter is packaged into a WebLogic-specific EAR file. This topic explains the steps needed to configure WebLogic and deploy an EAR file.

Perform the steps described in the following sections:

- "Adding Servlet Definitions for WebLogic" on page 80
- "Generating the ClaimCenter EAR file for WebLogic" on page 81
- "Installing the EAR file on WebLogic" on page 81
- "Automatic Versus Manual Startup on WebLogic" on page 82

Adding Servlet Definitions for WebLogic

You might want to add definitions for additional servlets to the web.xml file.

To add servlet definitions

- Start Studio by running the following command from the ClaimCenter/bin directory: gwcc studio
- **2.** Open configuration \rightarrow deploy \rightarrow WEB-INF \rightarrow web.xml.
- **3.** Add servlet definitions as needed. See the defined servlets for an example.
- **4.** Add a servlet-mapping definition for each servlet that you add. See the defined servlet mappings for an example.
- 5. Save web.xml.



Using HTTP Authentication on WebLogic

To authenticate using HTTP authentication on WebLogic, add the following inside the <security-configuration> element of the WebLogic config.xml:

<enforce-valid-basic-auth-credentials>false</enforce-valid-basic-auth-credentials>

Generating the ClaimCenter EAR file for WebLogic

This procedure builds the ClaimCenter EAR file.

To generate the ClaimCenter EAR file

- 1. Open a command prompt.
- 2. Navigate to the ClaimCenter bin directory.
- **3.** Run one of the following commands:

```
gwcc build-weblogic-ear-dbcp
gwcc build-weblogic-ear-jndi
```

Both commands generate the ClaimCenter EAR file in the ClaimCenter dist/ear directory. Run gwcc build-weblogic-ear-dbcp to build the EAR file with JDBC drivers for use with WebLogic. Run gwcc build-weblogic-ear-dbcp if you are going to have ClaimCenter manage the database connection pool. Run gwcc build-weblogic-ear-jndi to build the EAR file without JDBC drivers. Use gwcc build-weblogic-ear-jndi only if you are going to use a JNDI database connection managed by WebLogic. See "Using a JNDI Data Source" on page 68.

Installing the EAR file on WebLogic

This procedure installs the generated ClaimCenter EAR file onto the WebLogic server.

To install the ClaimCenter EAR file

- 1. If WebLogic is not already running, start it now. If WebLogic is running, restart it.
- 2. After the server is running, point your browser to http://localhost:7001/console.

Note: Port 7001 is the default port for WebLogic. If you configured WebLogic with a different port number, then change the port number in the address to the correct one.

- 3. Log in with your user name and password. The default WebLogic user name and password is weblogic.
- 4. On the left side of the user interface, under Domain Structure, click Deployments.
- **5.** On the next screen, above **Domain Structure**, click **Lock & Edit**.
- 6. Within the main panel, under Deployments, click Install.
- 7. Navigate to the EAR file you generated and click Next.
- 8. Select Install this deployment as an application and click Next.
- 9. In the Source accessibility section of the next screen, select I will make the deployment accessible from the following location.
- 10. For the location, enter the path to the ClaimCenter webapps directory and click Next.
- 11. Click Yes, take me to the deployment's configuration screen and click Finish.
- 12. Review your configuration, and click Activate Changes located on the left side of the screen, above Domain Structure.



Automatic Versus Manual Startup on WebLogic

If you have configured WebLogic to automatically start (or restart) applications, WebLogic starts ClaimCenter automatically on startup or on restart if the WebLogic server ever goes down. However, if you have not configured WebLogic to automatically start (or restart) applications, then start ClaimCenter manually. See "Starting ClaimCenter on WebLogic" on page 102.

Installing a WebSphere Production Environment

To deploy a production instance of ClaimCenter on WebSphere, first add a welcome file list and add any necessary servlets to web.xml. Then, generate the WebSphere-specific ClaimCenter EAR file and install the EAR file on WebSphere.

Guidewire only supports externally managed data sources using JDBC drivers shipped with ClaimCenter and not the JDBC drivers that might be installed by default with the application server.

Use the correct port number when you connect to the server in Studio. WebSphere's default port is 9080.

Have the correct version of WebSphere. See the Guidewire Platform Support Matrix for details.

To add a welcome-file-list

This section explains how to add a wecome-file-list to the ClaimCenter web.xml file. If you do not perform this step, WebSphere cannot find your index.html file. Pointing your browser to: http://localhost:9080/ccdoes not work. Point to: http://localhost:9080/cc/Start.do.

1. Start Studio by running the following command from the ClaimCenter/bin directory:

```
gwcc studio
```

- **2.** Open configuration \rightarrow deploy \rightarrow WEB-INF \rightarrow web.xml.
- **3.** At the bottom of the file, just before the </web-app> tag, add the following:

```
<welcome-file-list>
  <welcome-file>index.html</welcome-file>
  <welcome-file>index.htm</welcome-file>
  <welcome-file>index.jsp</welcome-file>
</welcome-file-list>
```

- **4.** Add servlet definitions as needed. See the defined servlets for an example.
- **5.** Add a servlet-mapping definition for each servlet that you add. See the defined servlet mappings for an example.
- 6. Save your changes and close web.xml.

To generate the ClaimCenter EAR File for WebSphere

- 1. Open a command window.
- **2.** Navigate to the ClaimCenter bin directory.
- 3. Run one of the following commands:

```
gwcc build-websphere-ear-dbcp
gwcc build-websphere-ear-jndi
```

These commands build the EAR file and place it in ClaimCenter\dist\ear. The commands package the version of web.xml from the ClaimCenter\modules\configuration\deploy\WEB-INF directory.

Run gwcc build-websphere-ear-dbcp to build the EAR file with JDBC drivers for use with WebSphere. Use gwcc build-websphere-ear-dbcp if you are going to have ClaimCenter manage the database connection pool. Run gwcc build-websphere-ear-jndi to build the EAR file without JDBC drivers. Use gwcc build-websphere-ear-jndi only if you are going to use a JNDI database connection managed by WebSphere. See "Using a JNDI Data Source" on page 68.



To install the ClaimCenter EAR file on WebSphere

- **1.** If WebSphere is not already running, start the application server.
- **2.** Open the WebSphere Administrative Console.
- 3. Click Applications \rightarrow New Application.
- 4. Click New Enterprise Application.
- 5. Click Browse and select the ClaimCenter EAR file in the ClaimCenter/dist/ear directory.
- 6. Click Next.
- 7. Select Fast Path.
- 8. Click Next.
- **9.** Accept the default installation options.
- 10. Click Next.
- 11. On the Map modules to servers page, verify that your targeted server or cluster is selected.
- 12. Click Next.
- 13. On the Metadata for modules page, click Next.
- 14. On the Summary page, review your selections for accuracy. Click Previous to change any settings.
- 15. Click Finish.
- **16.** Click **Save** to apply the changes to the master configuration.
- **17.** Click the cc application.
- 18. Under Detail properties, click Class loading and update detection.
- 19. Under Class loader order, select Classes loaded with local class loader first (parent last).
- 20. Under WAR class loader policy, select Single class loader for application.
- 21. Click OK.
- **22.** Click **Save** to apply the changes to the master configuration.

After you have finished the procedure to install the ClaimCenter EAR file on WebSphere, review post-installation tasks in "Additional ClaimCenter Setup Tasks" on page 85. Then, proceed to "Starting ClaimCenter on WebSphere" on page 103.



chapter 5

Additional ClaimCenter Setup Tasks

This topic describes additional setup tasks that you may want to perform after you install your ClaimCenter development or production environment and deploy ClaimCenter to your application server.

This topic includes:

- "Free-text Search Setup" on page 85
- "Changing the Superuser Password" on page 96
- "Generating Java and SOAP API Libraries" on page 96
- "Enabling Integration between ClaimCenter and PolicyCenter" on page 97
- "Enabling Archiving or Disabling Archiving Work Queue" on page 101
- "Starting ClaimCenter on the Application Server" on page 102
- "Connecting to ClaimCenter with a Web Client" on page 103
- "Additional Installation Information" on page 103

Free-text Search Setup

Guidewire supports deployment of the full-text search engine that free-text search depends on in JBoss, Tomcat, and WebSphere application servers. The full-text search engine is a special distribution of Apache Solr, tailored by Guidewire to work with free-text search. This special distribution is called the *Guidewire Solr Extension*.

Note: For development environments, Guidewire supports running the Guidewire Solr Extension in the bundled QuickStart application server, but only if you configure free-text search for *embedded* operation.

This topic includes:

- "Free-text Search Setup Overview" on page 86
- "Setting Up Free-text Search for Embedded Operation" on page 87
- "Setting Up Free-text Search for JBoss" on page 88
- "Setting Up Free-text Search for Tomcat" on page 89
- "Setting Up Free-text Search for WebLogic" on page 90



- "Setting Up Free-text Search for WebSphere" on page 91
- "Setting Up the Free-text Batch Load Command" on page 94

See also

- "Free-text Search Configuration" on page 360 in the Configuration Guide.
- For specific versions of application servers Guidewire that supports, see the Guidewire Platform Support Matrix on the Guidewire Resource Portal, at https://guidewire.custhelp.com/app/resources/products/platform.

Free-text Search Setup Overview

ClaimCenter free-text search depends on a full-text search engine, the Guidewire Solr Extension. Guidewire supports running the Guidewire Solr Extension in a JBoss, Tomcat, WebLogic, or WebSphere application server in a production environment. In a development environment, Guidewire supports running the Guidewire Solr Extension in the bundled Quickstart server, if you configure free-text search for *embedded* operation.

See also

• "Free-text Search System Architecture" on page 360 in the Configuration Guide

Operating Options for Production and Development

In a production environment, you must configure the free-text search for *external* operation. With external operation in a production environment, the Guidewire Solr Extension must run in a different instance of the application server than the instance that runs your ClaimCenter application. In addition, the separate application server must be on a host or in a server cluster separate from the one that hosts ClaimCenter.

In a development environment, you can configure free-text search for external or *embedded* operation. With external operation in a development environment, the separate application server for the Guidewire Solr Extension can be on the same host as the one that hosts ClaimCenter. With embedded operation, the Guidewire Solr Extension runs automatically as part of the ClaimCenter application in the application server instance that runs ClaimCenter. The Guidewire Solr Extension does not run as a separate application.

Simplified Free-text Search Setup for Embedded Operation

In a development environment, set up the free-text search for embedded operation to simplify your setup procedure. With embedded operation you can avoid the following set-up tasks that external operation requires:

- Setting up a separate application server instance for the Guidewire Solr Extension
- Setting up the free-text batch load command

With embedded operation, your only set-up task involves changes to the solrserver-config.xml file. This configuration file tells the free-text feature in ClaimCenter how to operate and interact with the Guidewire Solr Extension.

See also

"Setting Up Free-text Search for Embedded Operation" on page 87

The Guidewire Solr Extension

Guidewire provides a special distribution of the Apache Solr full-text search engine, the Guidewire Solr Extension. Guidewire provides the Guidewire Solr Extension in a ZIP file located in your installation of ClaimCenter at:

ClaimCenter/solr/cc-gwsolr.zip



The Guidewire Solr Extension runs as a web application in a JBoss, Tomcat, or WebSphere application server. If you configure the Guidewire Solr Extension for embedded operation, it operates as part of ClaimCenter, not as a separate web application.

WARNING Do not use any distribution of the Apache Solr full-text search engine other than the one that Guidewire provides as the Guidewire Solr Extension.

The Guidewire Solr Home Directory

In the instructions that follow, you create an installation directory for the Guidewire Solr Extension. The installation directory is known as the *Guidewire Solr home directory*. Guidewire requires that you create the Guidewire Solr home directory on the host where you installed the separate application server instance for it.

Note: Do not create a Guidewire Solr home directory if you configure free-text search for embedded operation.

The default parameter settings and configuration files for free-text search assume the following directories for the Guidewire Solr home directory:

- On Unix /opt/gwsolr
- On Windows C:\opt\gwsolr

The instructions that follow use /opt/gwsolr for the Guidewire Solr home directory. If you use a different directory than one of those listed above, you must perform additional configuration steps.

The Free-text Batch Load Command

The free-text search feature provides a command-line utility to extract policy data from the ClaimCenter relational database and load the extracted data into the Guidewire Solr Extension. In the instructions that follow, you unpack the files from the Guidewire Solr WAR file, which the free-text batch load command depends on.

Note: Do not set up and configure the free-text batch load command if you configure free-text search for embedded operation.

The free-text batch load command also depends on a Unix-compatible sort binary that performs character-value sorting. The batch load command builds intermediate index documents from the policy data in ClaimCenter. The batch load command sorts the intermediate documents during its process of collating and compiling the final index documents that it loads into the Guidewire Solr Extension. Guidewire supports cygwin on Windows.

In the instructions that follow, you first perform a procedure to set up free-text search for JBoss, Tomcat, or WebSphere. Then, regardless of application server, you perform a separate, follow-on procedure to set up the free-text batch load command.

See also

- "Setting Up the Free-text Batch Load Command" on page 94
- "Configuring the Free-text Batch Load Command" on page 368 in the Configuration Guide

Setting Up Free-text Search for Embedded Operation

Set up free-text search for embedded operation for preliminary testing with small amounts of test data. For final testing with larger volumes of data and to prepare for production, set up free-text search for external operation.

To set up free-text search for embedded operation

1. In Studio, open Configuration \rightarrow config \rightarrow solr \rightarrow solrserver-config.xml.



2. Verify that the file contains a <solrserver> element that matches the following:

3. In the <document> element, change the servername attribute to embedded.

```
<document name="claimcontact" archive="false" servername="embedded"/>
```

- **4.** Save your changes to the solrserver-config.xml file.
- **5.** Open a command prompt to ClaimCenter/bin and run the following command:

```
gwcc solr
```

Setting Up Free-text Search for JBoss

ClaimCenter free-text search requires that you install an instance of JBoss separate from the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate JBoss instance on a host separate from the one that hosts your ClaimCenter application.

To set up free-text search for JBoss

- **1.** On the host where the JBoss instance for free-text search resides, create an installation directory to use as the Guidewire Solr home directory. For example:
 - On Unix /opt/gwsolr
 - On Windows C:\opt\gwsolr

This guide uses /opt/gwsolr as the directory name.

- 2. Create the environment variable GWSOLR_HOME for the directory that you created in step 1.
- **3.** Create a new opt/gwsolr/cc directory and extract to it the file ClaimCenter/solr/cc-gwsolr.zip from the host where your ClaimCenter application resides.
- **4.** Copy the file /opt/gwsolr/cc/cc-gwsolr.war to the directory JBOSS_HOME/server/default/deploy.
- **5.** Edit the file JBOSS_HOME/server/default/conf/jboss-service.xml and add the following lines to the <server> element:

6. Edit the following file:

JBOSS_HOME/server/default/conf/bindingservice.beans/META-INF/bindings-jboss-beans.xml

Change the port property for the WebServer service from 8080 to 8983, as the following example shows.

The standard Solr port is 8983. Generally, you make this configuration change during installation, at the time you install the JBoss instance for free-text search.

7. Start JBoss by running the command *JBOSS_HOME*/bin/run.



You can configure JBoss to access the Guidewire Solr Extension with a remote debugger. Before executing <code>JBOSS_HOME/bin/run</code>, set <code>JAVA_OPTS</code> to have appropriate JVM remote debugging flags, such as:

set JAVA_OPTS=-Xdebug -Xrunjdwp:transport=dt_socket,address=8787,server=y,suspend=y

Note that if suspend=y then JBOSS will not start until the remote debugger is attached. To start JBoss without requiring the remote debugger to be attached, change this flag to suspend=n. Configure the port number to the port number configured for the remote debugger.

- **8.** Examine the log file <code>JBOSS_HOME/server/default/log/server.log</code> to ensure the Guidewire Solr Extension web application started successfully.
 - The application started successfully if you see a number of log entries related to the Guidewire Solr home directory.
- **9.** In a browser, open the administrative user interface for the Guidewire Solr Extension web application by entering the following URL:

```
http://hostName:8983/cc-gwsolr
```

- 10. Verify all the following in the Guidewire Solr Extension administrative user interface.
 - **a.** You see links to administrative pages for each entity type that is searchable in ClaimCenter with free-text search. For example, the link to the administrative page for claim contacts looks like:

```
Admin cc_claimcontact_active
```

- **b.** On the administrative page, you can enter a query and adjust settings.
- 11. Proceed next to "Setting Up the Free-text Batch Load Command" on page 94.

See also

• "Free-text Search System Architecture" on page 360 in the Configuration Guide

Setting Up Free-text Search for Tomcat

ClaimCenter free-text search requires that you set up an instance of Tomcat separate from the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate Tomcat instance on a host separate from the one that hosts your ClaimCenter application.

To set up free-text search for Tomcat

- **1.** On the host where the Tomcat instance for free-text search resides, create an installation directory to use as the Guidewire Solr home directory. For example:
 - On Unix /opt/gwsolr
 - On Windows C:\opt\gwsolr

This guide uses /opt/gwsolr as the Guidewire Solr home directory name.

- **2.** Create the environment variable GWSOLR_HOME for the directory that you created in step 1.
- **3.** Create a new opt/gwsolr/cc directory and extract the file ClaimCenter/solr/cc-gwsolr.zip to it from the host where your ClaimCenter application resides.
- **4.** Copy the file /opt/gwsolr/cc/cc-gwsolr.xml to the directory TOMCAT_HOME/conf/Catalina/localhost.
- **5.** On Windows, do all of the following:
 - **a.** Edit the file *TOMCAT_HOME*\conf\Catalina\localhost\cc-gwsolr.xml, and add the drive specifier to the front of the path in the docBase attribute, as the following example shows.

```
<Context docBase="C:\opt\gwsolr\cc\cc-gwsolr.war" debug="0" crossContext="true">
```

b. Edit the file *GWSOLR_HOME*\cc\solr\solr.xml, and add the drive specifier to the front of the paths in the instanceDir attribute for each <core> element, as the following example shows.



6. Edit the file *TOMCAT_HOME*/conf/server.xml, and change the connector port for the HTTP/1.1 protocol from 8080 to 8983, as the following example shows.

The standard Solr port is 8983. Generally, you make this configuration change during installation, at the time you install the Tomcat instance for free-text search.

7. Start Tomcat by running the command *TOMCAT_HOME*/bin/startup.

If you want to access the Guidewire Solr web application with a remote debugger, start Tomcat by running the following command.

```
TOMCAT_HOME/bin/catalina.sh jpda start
```

Then, you can connect a remote debugging session through port 8000.

8. Examine the log file *TOMCAT_HOME*/logs/catalina to ensure the Guidewire Solr Extension web application started successfully.

The application started successfully if you see a number of log entries related to the Guidewire Solr home directory.

9. In a browser, open the administrative user interface for the Guidewire Solr Extension web application by entering the following URL:

```
http://hostName:8983/cc-gwsolr
```

- 10. Verify all the following in the Guidewire Solr Extension administrative user interface.
 - **a.** You see links to administrative pages for each entity type that is searchable in ClaimCenter with free-text search. For example, the link to the administrative page for claim contacts looks like:

```
Admin cc_claimcontact_active
```

- **b.** On the administrative page, you can enter a query and adjust settings.
- 11. Proceed next to "Setting Up the Free-text Batch Load Command" on page 94.

See also

• "Free-text Search System Architecture" on page 360 in the Configuration Guide

Setting Up Free-text Search for WebLogic

ClaimCenter free-text search requires that you install an instance of WebLogic separate from the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate WebSphere instance on a host separate from the one that hosts your ClaimCenter application.

To set up free-text search for WebLogic

- 1. Create a WebLogic domain/instance running under JDK 1.7.
- **2.** On the host where the WebLogic instance for free-text search resides, create an installation directory to use as the Guidewire Solr home directory. For example:
 - On Unix /opt/gwsolr
 - On Windows C:\opt\gwsolr

This guide uses /opt/gwsolr as the directory name.

3. Create a new opt/gwsolr/cc subdirectory. In that directory, extract the file from your ClaimCenter application files:

```
ClaimCenter/solr/cc-gwsolr.zip
```

4. Within the autodeploy directory in the WebLogic instance, create a subdirectory cc-gwsolr. In that subdirectory, extract the contents of the cc-gwsolr.war.



5. Check the web application deployment descriptor in autodeploy/cc-gwsolr/WEB-INF/web.xml for the definition of the solr.home environment variable:

```
<env-entry>
  <env-entry-name>solr/home</env-entry-name>
  <env-entry-type>java.lang.String</env-entry-type>
  <env-entry-value>/opt/gwsolr/cc/solr</env-entry-value>
</env-entry>
```

If you installed the ZIP file in a directory other than <code>/opt/gwsolr</code>, you must now change the path in the <code><env-entry-value> XML</code> element to match the actual install directory path.

- **6.** Start the WebLogic instance.
- **7.** If you use SolrCloud, specify the appropriate Zookeeper arguments in the JAVA_OPTIONS environment variable. You can set the Zookeeper arguments by using a Unix shell script or a Windows batch file located in the domain base directory:
 - On Unix

Alternatively, set the JAVA_OPTIONS environment variable by editing the setDomainEnv.sh script.

- · On Windows
- **8.** Proceed next to "Setting Up the Free-text Batch Load Command" on page 94.

See also

• "Free-text Search System Architecture" on page 360 in the Configuration Guide

Setting Up Free-text Search for WebSphere

ClaimCenter free-text search requires that you install an instance of WebSphere separate from the instance that runs your ClaimCenter application. In a production environment, Guidewire requires that you set up the separate WebSphere instance on a host separate from the one that hosts your ClaimCenter application.

To set up free-text search for WebSphere

- 1. Install and configure WebSphere
- **2.** On the host where the WebSphere instance for free-text search resides, create an installation directory to use as the Guidewire Solr home directory. For example:
 - On Unix /opt/gwsolr
 - On Windows C:\opt\gwsolr

This guide uses /opt/gwsolr as the directory name.

- **3.** Create the environment variable GWSOLR_HOME for the directory that you created in step 1.
- **4.** Create a new opt/gwsolr/cc directory and extract to it the file ClaimCenter/solr/cc-gwsolr.zip from the host where your ClaimCenter application resides.
- **5.** On Windows, do all of the following:
 - **a.** Edit the file GWSOLR_HOME\cc\cc-gwsolr.xml, and add the drive specifier to the front of the path in the docBase attribute, as the following example shows.

```
<Context docBase="C:\opt\gwsolr\cc\cc-gwsolr.war" debug="0" crossContext="true">
```

b. Edit the file *GWSOLR_HOME*\cc\solr\solr.xml, and add the drive specifier to the front of the paths in the instanceDir attribute for each <core> element, as the following example shows.

```
<core name="cc_claimcontact_active" instanceDir="C:\opt\gwsolr\cc\solr\claimcontatc_active"/>
```



- 6. Start WebSphere:
 - On Unix WEBSHPERE_HOME/bin startServer.sh server1
 - On Windows Start → All Programs → IBM WebSphere → Application Server → Profiles → AppSrv01 → Start the server
- 7. In a browser, open the WebSphere administrative console and log in:

http://localhost:9060/ibm/console/login.do

8. Change the port for the default host in your WebSphere application server and for its virtual host.

ClaimCenter assumes the Solr port is 8983. Generally, you make this configuration change during installation, at the time you install the WebSphere instance for free-text search. If you want to use a different port number, change the port number in the ClaimCenter file solrserver-config.xml.

- a. From the Administrative Console, navigate to Servers → Server Types → WebSphere application servers and click the name of your application server from the list. The default name of your application server is server1. The console displays the configuration page for your application server.
- **b.** On the right underneath Communications, click Ports.
- **c.** In the list of TCP/IP ports, click WC_defaulthost.
- d. In the Port field, change the value from 9080 to 8983.
- e. Click Apply.
- f. In the Messages box, Click Save to apply the changes to the master configuration.
- g. From the Administrative Console, navigate to Environment → Virtual hosts and click the name of your virtual host. The default name of your virtual host is default_host.

The console displays the configuration page for your virtual host.

- h. On the right underneath Additional Properties, click Host Aliases.
- i. Click New.

The console displays the configuration page for your new virtual host alias.

j. Enter the following values.

Field name	Description
Host Name	Enter an asterisk (*).
Port	Enter 8983.

- k. Click Apply.
- I. In the Messages box, Click Save to apply the changes to the master configuration.
- **9.** Install the Guidewire Solr Extension web application:
 - **a.** Log in to the WebSphere administrative console.
 - **b.** Navigate to Applications \rightarrow New application and click New Enterprise Application.
 - c. Under Local file system, click Browse....
 - d. In the dialog, navigate to the file /opt/gwsolr/cc/cc-gwsolr.war and select it. Then, click Open.
 - e. Click Next.

After a moment, a screen appears that asks how you want to install the application.

f. Select the Fast Path radio button and then click Next.

After a moment, a screen appears with steps listed along the left.



g. Click Step 3, to skip past Step 1 and Step 2 and click Next.

The console displays an application resource warning, ADMA8019E, which you can ignore safely.

h. Click Continue.

The console displays the page for step 4, where you map web modules to virtual hosts.

- i. Click Next to accept the mapping of the cc-gwsolr.war web module to the default_host virtual host. The console displays the page for step 5.
- j. In the Context Root field, enter /cc-gwsolr.
- k. Click Next, and on the page for step 6, click Finish.

WebSphere installs the Guidewire Solr Extension web application. The Administration Console displays messages while the installation process progresses. When the installation completes successfully, you see the following:

Application cc-solr_war installed successfully.

- I. Click Save to apply the changes to the master configuration.
- 10. From the Administrative Console, install the necessary shared libraries from the WAR file:
 - a. In the left navigation, expand the Environment node and click Shared Libraries.
 - b. Click New...
 - **c.** For the new shared library, set the name httpclient.

On Unix, set the classpath to /opt/gwsolr/cc/cc-gwsolr/WEB-INF/lib/httpclient-4.1.3.jar On Windows, set the classpath to C:\opt\gwsolr\cc\WEB-INF\lib\httpclient-4.1.3.jar For all operating systems, uncheck the box Use an isolated class loader for this shared library. Click OK.

d. Click New...

For the new shared library, set the name httpcore.

On Unix, set the classpath to /opt/gwsolr/cc/cc-gwsolr/WEB-INF/lib/httpcore-4.1.4.jar On Windows, set the classpath to C:\opt\gwsolr\cc\WEB-INF\lib\httpcore-4.1.4.jar For all operating systems, uncheck the box Use an isolated class loader for this shared library. Click OK.

- e. Expand the Applications node. Click Application Types \rightarrow WebSphere Enterprise Applications. In the right pane, click cc-gwsolr \rightarrow Shared Library References.
- f. In the Application list, select cc-gwsolr.war. Click the Reference Shared Libraries button. Select httpclient and then click the right arrow button to move httpclient from the Available list to the Selected list. Repeat with the httpcore library. Click OK.
- g. In the Module list, select cc-gwsolr.war. Click the Reference Shared Libraries button. Select httpclient and then click the right arrow button to move httpclient from the Available list to the Selected list. Repeat with the httpcore library. Click OK.
- 11. From the Administrative Console, change the class loading order
 - a. Click WebSphere Enterprise Applications \rightarrow cc-gwsolr \rightarrow Class loading and update detection \rightarrow Detail Properties tab.
 - **b.** In the right pane, click Class loading and update detection.
 - c. In the Class Loader Order radio buttons, select Classes loaded with local class loader first (parent last)
 - d. Click OK.
- **12.** Log out of the administrative console and stop and start the application server.



13. Examine the log file WEBSPHERE_HOME/profiles/AppSrv01/logs/server1/SystemOut.log to assure WebSphere initialized the Guidewire Solr web application successfully.

WebSphere initialized the application successfully if you see a log entries similar to the following:

```
[timeStamp] 00000009 SolrResourceL I org.apache.solr.core.SolrResourceLoader locateSolrHome No /solr/home in JNDI
[timeStamp] 00000009 SolrResourceL I org.apache.solr.core.SolrResourceLoader locateSolrHome using system property solr.solr.home: /opt/gwsolr/cc/solr
[timeStamp] 00000009 SolrServlet I org.apache.solr.servlet.SolrServlet init SolrServlet.init() done [timeStamp] 00000009 servlet I com.ibm.ws.webcontainer.servlet.ServletWrapper init SRVE0242I: [cc-gwsolr_war] [/cc-gwsolr] [SolrServer]: Initialization successful.
```

14. In a browser, open the administrative user interface for the Guidewire Solr Extension web application by entering the following URL:

```
http://hostName:8983/cc-gwsolr
```

- **15.** Verify all the following in the Guidewire Solr Extension administrative user interface.
 - **a.** You see links to administrative pages for each entity type that is searchable in ClaimCenter with free-text search. For example, the link to the administrative page for claim contacts looks like:

```
Admin cc_claimcontact_active
```

- **b.** On the administrative page, you can enter a query and adjust settings.
- **16.** Proceed next to "Setting Up the Free-text Batch Load Command" on page 94.

See also

• "Free-text Search System Architecture" on page 360 in the Configuration Guide

Setting Up the Free-text Batch Load Command

Follow these instructions only after you successfully set up free-text search for JBoss, Tomcat, or WebSphere. On Windows, ensure a Unix-compatible sort binary that performs character-value sorting is available. Guidewire supports cygwin on Windows.

Note: Do not set up and configure the free-text batch load command if you configure free-text search for embedded operation.

The configuration files that you modify during set up, including the batch load command itself, are located in the following directory:

```
/opt/gwsolr/cc/solr/claimcontact_active/conf
```

Most of the setup information for the free-text batch load command is located in a configuration file, batchload-config.xml

The configuration parameters that you may need to modify include:

- xsi:noNamespaceSchemaLocation Location of the XSD for batch load configuration files. You must modify this parameter if your Guidewire Solr home directory is other than /opt/gwsolr.
- absolutePathToWorkDir Location of a working directory, possibly on a remote host, for collating and
 compiling large volumes of index documents for the full-text search engine. Generally in a production environment, you modify this parameter. Otherwise, the working directory is within the Guidewire Solr home
 directory. Assure the directory you specify has sufficient high-performance disk space.
- absolutePathToSortTmpDir Location of a working directory into which the sort binary writes its intermediate files. This directory may be the same as or different from the directory specified by absolutePathToWorkDir.
- absolutePathToSortExe Location of a sort binary. You must modify this parameter if you use a binary other than /bin/sort on Unix or c:\cygwin\bin\sort.exe on Windows.
- solrBaseUrl URL for the Guidewire Solr web application. You must modify this parameter if you set up the application server to use a port other than 8983, the default port for the Solr full-text search engine.



- dataSource Connection information for the ClaimCenter relational database. You must modify this parameter to specify the network location of the database and the username and password.
- absolutePathToPostprocessorExe Locates the postprocess shell script of batch file that the batch load command calls after extracting data from the ClaimCenter relational database. You must modify this parameter if your Guidewire Solr home directory is other than /opt/gwsolr.

To set up the free-text batch load command

- 1. Navigate to the Guidewire Solr home directory.
- **2.** Extract the files from the Guidewire Solr WAR file as you would any ZIP file, to the following location, using full directory paths:

```
opt/gwsolr/cc/exploded
```

The free-text batch load command depends on access to JAR files within the WAR file.

- 3. Switch to the configuration directory, opt/gwsolr/cc/solr/claimcontact_active/conf.
- **4.** Edit the batchload shell script or batch file, and modify the CONFIGFILE environment variable to locate the appropriate batch load configuration file for your database brand. For example, if your database brand is Oracle:

On Unix

```
CONFIGFILE=$GWSOLR_HOME/solr/claimcontact_active/conf/batchload-config.xml
```

On Windows

```
set CONFIGFILE=%GWSOLR_HOME%\solr\claimcontact_active\conf\batchload-config.xml
```

- 5. Open the batch load configuration file that you specified in step 4 and do all of the following:
 - a. If you use a directory for the Guidewire Solr home directory other than /opt/gwsolr, modify the xsi:noNamespaceSchemaLocation attribute of the <document> element.
 - **b.** Review the following elements for possible changes.

On Unix

```
<param name="absolutePathToWorkDir"
    value="/opt/gwsolr/cc/solr/claimcontact_active/conf/loadDir"/>
<param name="absolutePathToSortExe" value="/bin/sort"/>
```

On Windows

c. If you the application server for a port other than 8983, modify the following element.

```
<param name="solrBaseUrl" value="http://localhost:8983"/>
```

d. Modify the attributes of the <dataSource> element to match the values for your database. For example, if your database brand is Oracle:

```
<dataSource name="ds_orcl" driver="oracle.jdbc.driver.OracleDriver"
    url="jdbc:oracle:thin://@grinch:11201:gwDiaAsc" user="su" password="gw"/>
```

- **e.** If you use a directory for the Guidewire Solr home directory other than <code>/opt/gwsolr</code>, modify the <code>absolutePathToPostprocessorExe</code> attribute of the <code><postprocessor></code> element.
- **6.** On Windows, edit postprocess.bat and modify the CoreUtils environment variable to locate the sort binary. For example:

```
set CoreUtils C:\opt\cygwin
```

- **7.** If use a directory for the Guidewire Solr home directory other than /opt/gwsolr:
 - **a.** Open the file data-config.xml.



b. Change the value of the url attribute on the <entity> element to match the location of your Guidewire Solr home directory. For example:

```
<entity name="claimcontact"
    orEach="/CONTAINER_ELEM/CLAIMCONTACT"
    url="/opt/gwsolr/cc/solr/claimcontact_active/conf/loadDir/claimcontact"
    stream="true">
```

- **8.** Restart the application server to pick up the changes.
- 9. Run the batchload command to test the setup.
- 10. Examine the status response to verify your setup.
 A problem-free load gives the same positive counts for Total Rows Fetched and Total Documents Processed.

See also

- "Configuring the Free-text Batch Load Command" on page 368 in the Configuration Guide
- "Free-text Search System Architecture" on page 360 in the Configuration Guide

Changing the Superuser Password

ClaimCenter automatically creates an unrestricted superuser named su with full permissions. The default password for this superuser is gw. You create other users with the superuser account. Guidewire strongly recommends that when you start ClaimCenter for the first time, log in to ClaimCenter as user su and change this password.

To change the superuser password

- 1. Open a browser window.
- **2.** Set the URL to the following:

```
http://server:port/cc/ClaimCenter.do
For example, if connecting on your local computer, use: http://localhost:8080/cc/ClaimCenter.do
```

- 3. Log into ClaimCenter as user su with password gw.
- 4. Click the Preferences link on the Desktop and change the password for user su.

You can change which user is the superuser. See "Changing the Unrestricted User" on page 24 in the *System Administration Guide*.

At this point, you have a running ClaimCenter server. However, there is no data in the installation and you have none of the tools available to manage the ClaimCenter server process. Before you use ClaimCenter, follow the processes defined in "Generating Java and SOAP API Libraries" on page 96, and "Connecting to ClaimCenter with a Web Client" on page 103.

Generating Java and SOAP API Libraries

ClaimCenter provides Java and SOAP APIs that you can use to integrate your own applications with ClaimCenter. These APIs are sometimes collectively referred to as the toolkit.

Generate these APIs when you first install ClaimCenter. Because the toolkit contains the ClaimCenter APIs, regenerate the toolkit after every data model change.

To generate the Java and SOAP APIs

- 1. From a command prompt, navigate to ClaimCenter/bin.
- **2.** Execute the following command: gwcc regen-java-api.



This command generates the java-api directory within the top-level ClaimCenter directory.

3. Execute the following command: gwcc regen-soap-api.

This command generates the soap-api directory within the top-level ClaimCenter directory.

For more information, see "Integration Overview" on page 15 in the Integration Guide.

Enabling Integration between ClaimCenter and PolicyCenter

ClaimCenter includes a Gosu plugin that interfaces with a specialized PolicyCenter web service provided with PolicyCenter 7.0.0 or newer. PolicyCenter publishes the following web services in the base configuration:

- gw.webservice.pc.pc700.ccintegration.CCPolicySearchIntegration
- gw.webservice.pc.pc800.ccintegration.CCPolicySearchIntegration

PolicyCenter includes a Gosu plugin that interfaces with a ClaimCenter web service provided with ClaimCenter. This plugin enables PolicyCenter to retrieve claim information from ClaimCenter.

ClaimCenter publishes the following web services in the base configuration:

- gw.webservice.cc.cc700.pcintegration.PCClaimSearchIntegrationAPI
- gw.webservice.cc.cc800.pcintegration.PCClaimSearchIntegrationAPI

This topic includes procedures to enable claim search integration from PolicyCenter and policy search integration from ClaimCenter.

To configure ClaimCenter to retrieve policy information from PolicyCenter

- 1. Start the PolicyCenter server.
- **2.** Launch ClaimCenter Studio. From a command prompt, navigate to the bin directory in your ClaimCenter installation, and type gwcc studio.
- 3. In the Studio Project window, navigate to configuration \rightarrow config \rightarrow Plugins \rightarrow registry and double-click IPolicySearchAdapter.gwp.
- **4.** Click Remove to remove the demonstration implementation, gw.plugin.policy.impl.PolicySearchPluginDemoImpl.
- 5. Click Add +.
- 6. Select Add Gosu Plugin.
- **7.** Enter one of the following for the Gosu Class field, depending on the version of PolicyCenter that you are integrating with ClaimCenter:

PolicyCenter 7.0.2 or later: gw.plugin.pcintegration.pc702.PolicySearchPCPlugin **PolicyCenter 8.0.x:** gw.plugin.pcintegration.pc800.PolicySearchPCPlugin

8. If you are using the pc702 plugin, add user name and password parameters.

Note: The pc800 plugin uses a different technique for authentication. See step 16 for information on using the PCConfigurationProvider class.

- a. Next to Parameters, click Add +.
- **b.** Enter the text username for the Name.
- c. Enter the superuser user name for the Value. By default, the superuser user name is su.
- d. Next to Parameters, click Add +
- e. Enter the text password for the Name.



- f. Enter the superuser password for the Value. By default, the superuser password is gw.
- **9.** In the Studio Project window, navigate to configuration \rightarrow config \rightarrow suite and double-click suite-config.xml.
- **10.** Remove the comment markers <!-- and --> from the line for the PolicyCenter URL:

```
<!--<pre><!--<pre><!--<pre>roduct name="pc" url="http://localhost:8180/pc"/>-->
```

- 11. Update the PolicyCenter URL to match your server and port.
- **12.** In the Studio Project window, navigate to configuration → config and double-click config.xml.
- 13. Set the PolicyCenter URL in the PolicySystemURL configuration parameter. For example, add the following line to this file:

```
<param name="PolicySystemURL" value="http://localhost:8180/pc""/>
```

14. In the Studio Project window, expand configuration → gsrc and then navigate to wsi.remote.gw.webservice.pc. Double-click one of the following web service files, depending on the version of PolicyCenter that you are integrating with ClaimCenter:

PolicyCenter 7.0.2 or later: pc700.wsc PolicyCenter 8.0.x: pc800.wsc

Note: The \${pc} variable for each of the defined web services is defined in suite-config.xml.

- **15.** Ensure that the PolicyCenter server is running. Then select all the web services in Resources and click Fetch Updates. You must refresh the web services, even if you have made no changes to them.
- **16.** In the same editor on the **Settings** tab is the configuration provider class. This class, wsi.remote.gw.webservice.pc.PCConfigurationProvider, is used by the pc800 plugin to define the user name and password that ClaimCenter uses to connect with PolicyCenter.
 - In the base configuration, ClaimCenter defines the user name su and password gw in this class. Guidewire recommends that you change this user name in this class. Then add a new user to PolicyCenter with the same user name and password that you specify in PCConfigurationProvider. That new user must have the soapadmin permission, plus at least the permissions needed to view and edit policies.
 - There is an example of how to configure a user name and password with ContactManager that is similar to the ClaimCenter configuration for PolicyCenter. See "Configuring ClaimCenter-to-ContactManager Authentication" on page 69 in the *Contact Management Guide*.
- **17.** To test the integration, restart the ClaimCenter server. Then start the **New Claim** wizard and search for a Personal Auto or Workers' Compensation policy. The integration with PolicyCenter 8.0 supports all base integration policy types except Farmowner's, Professional Liability, and Personal Travel.

The ClaimCenter plugin implements two methods on IPolicySearchAdapter: searchForPolicies and retrievePolicy. The PolicyCenter web service returns objects that look like ClaimCenter policy entities, so implementation of the plugin is relatively straightforward. The web service performs the conversion by translating to and from the SOAP objects used to communicate with the web service.

The conversion of objects received from PolicyCenter is configurable in the pc-to-cc-data-mapping.xml file.

ClaimCenter Studio provides different versions of this file corresponding to your version of PolicyCenter. Navigate in the Project window to configuration \rightarrow config \rightarrow datamapping \rightarrow pc:

- PolicyCenter 7.0.2 or later: 702 \rightarrow pc-to-cc-data-mapping.xml
- PolicyCenter 8.0.x: $800 \rightarrow pc-to-cc-data-mapping.xml$

The only object that ClaimCenter sends to PolicyCenter is a PCSearchCriteria object. This object is created and populated from the ClaimCenter search criteria by using Gosu. Configuration of this object must be done in Gosu.

Changes to the pc-to-cc-data-mapping.xml file are not picked up automatically by the plugin. After changing the file, restart your ClaimCenter server.



To configure PolicyCenter to retrieve claim information from ClaimCenter

- 1. Start the ClaimCenter server.
- **2.** Launch PolicyCenter Studio. From a command prompt, navigate to the bin directory in your PolicyCenter installation, and type gwpc studio.
- 3. In the Studio Project window, navigate to configuration → config → suite and double-click suite-config.xml.
- **4.** Remove the comment markers <!-- and --> from the line for the ClaimCenter URL: <!--<pre><!--<pre><!--<pre>c url="http://localhost:8080/cc"/>-->
- **5.** Update the ClaimCenter URL to match your server and port.
- **6.** In the Studio Project window, expand configuration → gsrc and then navigate to wsi.remote.gw.webservice.cc. Double-click the web service file cc800.wsc.
 - Note the \${cc} variable for the defined web service. This variable is defined in suite-config.xml.
- **7.** Ensure that the ClaimCenter server is running. Then select the web service in **Resources** and click **Fetch Updates**. You must refresh the web service, even if you have made no changes to it.
- **8.** In the same editor on the **Settings** tab is the configuration provider class. This class, wsi.remote.gw.webservice.cc.CCConfigurationProvider, defines the user name and password that PolicyCenter uses to connect with ClaimCenter.

In the base configuration, PolicyCenter uses the user name su and password gw. Guidewire recommends that you change this user name and password in CCConfigurationProvider and then create a corresponding user with the same user name and password in ClaimCenter. That new user must have the soapadmin permission, plus at least the permissions needed to view and edit claims and policies.

There is an example of how to configure a user name and password with ContactManager that is similar to the PolicyCenter configuration for ClaimCenter. See "Configuring PolicyCenter-to-ContactManager Authentication" on page 71 in the *Contact Management Guide*.

- 9. In the Studio Project window, navigate to configuration → config → Plugins → registry and then double-click IClaimSearchPlugin.gwp.
- **10.** Click Remove to remove the demonstration implementation, gw.plugin.claimsearch.impl.GWDemoClaimSearchPlugin.
- 11. Click Add +.
- 12. Select Add Gosu Plugin.
- 13. Enter gw.plugin.claimsearch.cc800.GWClaimSearchPlugin in the Class field.
- **14.** Navigate in the Project window to configuration → config and double-click config.xml.
- **15.** Set the ClaimSystemURL parameter to the ClaimCenter URL. Before configuration, the ClaimSystemURL is set to a null value. In the installation of the base configuration, the ClaimCenter URL is: http://localhost:8080/cc/ClaimCenter.do
- **16.** Restart PolicyCenter to pick up these changes.

Enabling Large Loss Notification Integration

In the base configuration, ClaimCenter does not enable integration with a policy system for large loss notification. See "Large Loss Notifications" on page 511 in the *Application Guide*.

Perform the following instructions in ClaimCenter Studio to enable this behavior with PolicyCenter. To successfully complete all the steps, the PolicyCenter server must be running. The ClaimCenter server does not need to be running. After performing these instructions, you must restart the ClaimCenter server for the changes to take effect.



To enable large loss notification integration between ClaimCenter 8.0.x and PolicyCenter 8.0.x

- 1. Launch ClaimCenter Studio.
 - From a command prompt, navigate to the bin directory in your ClaimCenter installation, and type gwcc
- 2. In the Studio Project window, navigate to configuration → config → Rule Sets → Preupdate → TransactionSetPreupdate.
- 3. Select the check box for the Large Loss Notification rule to enable that rule.
- Navigate to configuration → config → Rule Sets → EventMessage → EventFired and select the check box for the Policy **System Notification** rule to enable that rule.
- **5.** Navigate to configuration \rightarrow config \rightarrow Messaging, and then double-click messaging-config.xml.
- **6.** In the editor, click the row for the messaging destination Java. MessageDestination. PolicySystemNotification. Name, and then select the Enabled check box.
- 7. In the Studio Project window, navigate to configuration → config → Plugins → registry and double-click policySystemNotificationTransport.gwp.
- 8. In the editor, select the Enabled check box.
- 9. In the Studio Project window, navigate to configuration → config → Plugins → registry and double-click IPolicySystemNotitificationPlugin.gwp. In the base implementation, ClaimCenter uses the plugin implementation gw.plugin.policy.notification.pc800.PCPolicySystemNotificationPlugin.
- **10.** In the editor, select the **Enabled** check box.
- 11. If you have not already done so, update suite-config.xml to enable ClaimCenter to work with PolicyCenter. Also, if necessary, change the URL for the PolicyCenter server to the URL used in your configuration.
 - a. In the Studio Project window, navigate to configuration → config → suite and double-click suite-config.xml to open this file in the editor.
 - b. If present, remove the comment markers <!-- and --> from the line defining the PolicyCenter URL: <!--<pre><!--<pre><!--<pre>roduct name="pc" url="http://localhost:8180/pc"/>-->
 - **c.** If necessary, update the PolicyCenter URL to match your server and port.
- **12.** Verify that the PolicyCenter server is running.
- 13. In the ClaimCenter Studio Project window, navigate to configuration \rightarrow gsrc and then to wsi.remote.gw.webservice.pc.
- **14.** Double-click pc800.wsc to open this web service collection in the editor.
- **15.** Select the web service \${pc}/ws/gw/webservice/pc/pc800/ccintegration/ ClaimToPolicySystemNotificationAPI?wsdl.

Note: The \${pc} part of this path is the PolicyCenter URL defined in suite-config.xml.

- **16.** Click Fetch Updates to refresh the web service.
- 17. In the same editor on the Settings tab is the configuration provider class. This class, wsi.remote.gw.webservice.pc.PCConfigurationProvider, defines the user name and password that ClaimCenter uses to connect with PolicyCenter.
 - For information on setting the user name and password in this class, see step 16 in the previous instructions describing how to configure ClaimCenter to retrieve policy information from PolicyCenter.
- **18.** Restart the ClaimCenter server for these changes to take effect.



Test your integration

In a development system, test the integration by adding a claim to ClaimCenter with a loss that exceeds the threshold for that type of claim. If the integration works correctly, PolicyCenter adds a referral reason and an activity for that policy.

See also

- "Policy System Notifications" on page 512 in the *Integration Guide*
- 19. Add user name and password parameters.
 - a. Next to Parameters, click Add +.
 - **b.** Enter the text username for the Name.
 - c. Enter the superuser user name for the Value. By default, the superuser user name is su.
 - d. Next to Parameters, click Add +.
 - e. Enter the text password for the Name.
 - f. Enter the superuser password for the Value. By default, the superuser password is gw.

Enabling Archiving or Disabling Archiving Work Queue

The default config.xml file has archiving disabled. This is set by the parameter:

```
<param name="ArchiveEnabled" value="false"/>
```

If you want to enable archiving, set the value of ArchiveEnabled to true. Then review the topics listed further in this section to learn how to configure archiving.

If you do not want to enable archiving, Guidewire recommends that you disable the archive work queue.

To disable the archive work queue

- 1. In a command window, navigate to the ClaimCenter\bin directory in the ClaimCenter installation.
- **2.** Launch Guidewire Studio using the following command:

```
gwcc studio
```

- 3. In Studio, open workqueue → work-queue.xml.
- **4.** Comment out the following block by adding <!-- before the block and --> after it:

5. Save your changes.



See also

• "More Information on Archiving" on page 133 in the Application Guide for a list of topics related to archiving.

IMPORTANT Guidewire strongly recommends that you contact Customer Support before implementing archiving.

Starting ClaimCenter on the Application Server

Select the topic below for your application server type to learn how to start ClaimCenter:

- "Starting ClaimCenter on JBoss" on page 102
- "Starting ClaimCenter on Tomcat on Windows" on page 102
- "Starting ClaimCenter on WebLogic" on page 102
- "Starting ClaimCenter on WebSphere" on page 103

ClaimCenter can run in development, test, or production mode and at different run levels. For more information, see "Server Modes and Run Levels" on page 60 in the System Administration Guide.

Starting ClaimCenter on JBoss

ClaimCenter starts when you start JBoss. Use the run command in the JBoss bin directory to start JBoss. Entering the run command without any parameters launches JBoss using the default server configuration.

Starting ClaimCenter on Tomcat on Windows

ClaimCenter starts when you start Tomcat. To start the Tomcat server on Windows, run the following script: Tomcat/bin/startup.bat

By default, Tomcat starts up in a new window. If it encounters errors, the new window might automatically close too quickly for you to read any error messages. In this case, you can run Tomcat in the same command window by editing the startup script. Locate the line in the script that runs Tomcat:

```
startup.bat: call "%EXECUTABLE%" start %CMD_LINE_ARGS%
```

Change the start option in the command to run. Save the script, and then run it again. Tomcat then runs in the same command window, which you can use to view any error messages.

Starting ClaimCenter on WebLogic

To start ClaimCenter on WebLogic

- 1. Start the WebLogic Admin Server if it is not already running.
- 2. Open the WebLogic Administration Console.
- 3. Under Domain Structure, click Deployments.
- 4. Select the checkbox for ClaimCenter.
- $\textbf{5. Click Start} \rightarrow \textbf{Servicing all requests}. \ The \ WebLogic \ Administration \ Console \ informs \ you \ of \ the \ deployments \ that$ you selected to be started.
- 6. Click Yes.



- **7.** Navigate to and select the ClaimCenter application. WebLogic identifies ClaimCenter by the name that you gave to the deployed EAR file.
- 8. Click Deploy Application.

This step launches the ClaimCenter server. The application start process could take a few minutes to complete.

Starting ClaimCenter on WebSphere

To start ClaimCenter on WebSphere

- **1.** Open the WebSphere Administrative Console.
- **2.** Click Applications \rightarrow Application Types \rightarrow WebSphere enterprise applications.
- **3.** Select the checkbox next to the ClaimCenter application, abbreviated by default as cc. If ClaimCenter is already running, and you want to restart ClaimCenter, restart WebSphere. If ClaimCenter is not running, click **Start**. ClaimCenter might take a few minutes to start.

IMPORTANT Guidewire does not support stopping and restarting the ClaimCenter server with the WebSphere Application Server (WAS) tools alone. Instead, to stop the ClaimCenter server, shutdown the WebSphere server itself.

Connecting to ClaimCenter with a Web Client

Users connect to ClaimCenter through a web browser. The URL for ClaimCenter or ContactManager includes the server name, port, and application name. For example:

http://appserver1:8080/cc/ClaimCenter.do

The following list shows default port numbers used by the application servers supported by ClaimCenter. You can configure the application server to listen on a different port than the default.

QuickStart	8080 (ClaimCenter)
	8280 (ContactCenter)
JBoss	8080
Tomcat	8080
WebLogic	7001
WebSphere	9080

Supply users with a user name and password along with the URL for your installation.

See "Client Information" on page 41 for a list of required software and hardware for client computers accessing ClaimCenter.

Additional Installation Information

The following topics link to sources for more information.



Integrating ClaimCenter with ContactManager

To integrate ClaimCenter with ContactManager, see "Integrating ContactManager with Guidewire Core Applications" on page 45 in the Contact Management Guide.

Running ClaimCenter in a Clustered Environment

Running ClaimCenter in a clustered environment requires an in depth understanding of ClaimCenter configuration files. See "Clustering Application Servers" on page 79 in the System Administration Guide.

chapter 6

Commands Reference

This topic lists the commands that are used to operate ClaimCenter in the configuration environment.

Because of their simplicity and power they offer, command line tools are the preferred method of controlling server behavior, loading data, and generating tools in the Guidewire configuration environment. These commands can be configured using familiar files, are invoked using standard developer tools, and are compatible with a wide spectrum of development environments.

This topic includes:

- "Tuning Command Line Tool Memory Settings" on page 105
- "QuickStart Command Tools" on page 106
- "Build Tools" on page 106

See also

• For a description of administrative commands provided with ClaimCenter, see "ClaimCenter Administrative Commands" on page 181 in the *System Administration Guide*.

Tuning Command Line Tool Memory Settings

The ClaimCenter/modules/configuration/etc/memory.properties file specifies memory settings for the QuickStart application server and other gwcc tools. To change one or more of these settings edit the xms, xmx, and maxperm values for the class that runs the tool. The class information is provided with the command lists in "QuickStart Command Tools" on page 106 and "Build Tools" on page 106.

For example, to change the memory settings for the QuickStart server, set the following properties in ClaimCenter/modules/configuration/etc/memory.properties:

- $\bullet \ \ starting \ heap \ size: \verb|com.guidewire.commons.jetty.GWServerJettyServerMain.xms|\\$
- maximum heap size: com.guidewire.commons.jetty.GWServerJettyServerMain.xmx
- maximum permanent size: com.guidewire.commons.jetty.GWServerJettyServerMain.maxperm



QuickStart Command Tools

Use the following commands to control the QuickStart method of installing ClaimCenter on Windows only:

Command	Action
gwcc debug-start	Deprecated. Use dev-debug-shmem or dev-debug-socket instead.
gwcc dev-debug-shmem	Starts ClaimCenter in development mode using shared memory debugging.
gwcc dev-debug-socket	Starts ClaimCenter in development mode using socket debugging.
gwcc dev-deploy	Copies resources for the QuickStart application server.
gwcc dev-dropdb	Prepares a new database for use by the Guidewire application. It will act upon the database configuration in database-config.xml, optionally selected by an env attribute by including the -Denv="env" parameter. If the database has any objects before the command is run, the objects are all dropped and not available for recovery except from a database backup. So, use extreme caution when using this command. The action of the command can be parameterized by settings in the <reset-tools-params> element underneath the <dbcp-connection-pool> element of the <database> element.</database></dbcp-connection-pool></reset-tools-params>
	For SQL Server, the command drops and creates a new database. It creates any filegroups named within the <database> element. The database files will be physically located where the server would put them by default. If specified, the collate attribute specifies the database collation. Otherwise, the default collation of the database server will be used. The command SET READ_COMMITTED_SNAPSHOT ON WITH ROLLBACK IMMEDIATE is issued on the new database. Since a CREATE DATABASE command is used, attributes of the model system database of the server are inherited.</database>
	For DB2, the command may either drop and recreate all the tablespaces on an existing database of the same name, or choose instead to drop and recreate the whole database. A number of parameter settings are used, which will print on the console. The command creates any named tablespaces.
	For Oracle, a Guidewire database corresponds to an Oracle schema: a user and all the objects owned by that user. So, for Oracle, this command drops all objects owned by the schema owner, and only the user is left with the required permissions.
	For both DB2 and Oracle, the system-username and system-password attributes of the <reset-tools-params> element must be specified so that the required permissions are available for these actions.</reset-tools-params>
	Class: com.guidewire.testharness.db.DBResetTool
gwcc dev-start	Starts the bundled QuickStart application server.
	Class: com.guidewire.commons.jetty.GWServerJettyServerMain
gwcc dev-stop	Stops the bundled QuickStart application server.
	$Class: {\tt com.guidewire.commons.jetty.GWServerJettyServerStopMain}$
gwcc dev-suspend-shmem	Starts ClaimCenter in development mode using shared memory debugging. Starts suspended.
gwcc dev-suspend-socket	Start ClaimCenter in development mode using socket debugging. Starts suspended.

Build Tools

Guidewire supports all the build tools that it provides on Windows. Guidewire supports invoking a few build scripts on a non-Development Unix system by invoking Ant directly.

This topic contains:

• "Build Tools Supported on Windows" on page 108



• "Build Scripts Supported on Unix" on page 113



Build Tools Supported on Windows

Use the following commands on Windows instead of any build scripts which accompany your IDE.

Command	Action
gwcc -p	Displays all gwcc command options.
gwcc build-jboss-war-dbcp	Builds the generic WAR file for JBoss including JDBC drivers. Use gwcc build-jboss-war-dbcp if you are going to have ClaimCenter manage the database connection pool.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-jboss-war-dbcp -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-jboss-war-jndi	Builds the generic WAR file for JBoss without JDBC drivers. Use gwcc build-jboss-war-jndi only if you are going to use a JNDI database connection managed by JBoss. See "Using a JNDI Data Source" on page 68.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-jboss-war-jndi -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-tomcat-war-dbcp	Builds the generic WAR file for Tomcat including JDBC drivers. Use gwcc build-tomcat-war-dbcp if you are going to have ClaimCenter manage the database connection pool.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-tomcat-war-dbcp -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-tomcat-war-jndi	Builds the generic WAR file for Tomcat without JDBC drivers. Use gwcc build-tomcat-war-jndi only if you are going to use a JNDI database connection managed by JBoss. See "Using a JNDI Data Source" on page 68.
	You can include the Boolean parameter config.war.dictionary=true to also generate the ClaimCenter <i>Data Dictionary</i> and <i>Security Dictionary</i> while building the WAR file. Use the following command:
	gwcc build-tomcat-war-jndi -Dconfig.war.dictionary=true
	When config.war.dictionary=true, the command creates a dictionary folder within the WAR file. The dictionary folder contains data and security folders. These folders contain the <i>Data Dictionary</i> and <i>Security Dictionary</i> respectively. To view a dictionary, open index.html in the data or security folder.
gwcc build-weblogic-ear-dbcp	Builds the EAR file for WebLogic including JDBC drivers. Use gwcc build-websphere-ear-dbcp if you are going to have ClaimCenter manage the database connection pool.
gwcc build-weblogic-ear-jndi	Builds the EAR file for WebLogic without JDBC drivers. Use gwcc build-websphere-ear-jndi only if you are going to use a JNDI database connection managed by WebLogic. See "Using a JNDI Data Source" on page 68.



Command	Action
gwcc build-websphere-ear-dbcp	Builds the EAR file for WebSphere including JDBC drivers. Use gwcc build-websphere-ear-dbcp if you are going to have ClaimCenter manage the database connection pool.
gwcc build-websphere-ear-jndi	Builds the EAR file for WebSphere without JDBC drivers. Use gwcc build-websphere-ear-jndi only if you are going to use a JNDI database connection managed by WebSphere. See "Using a JNDI Data Source" on page 68.
gwcc displaykey-diff	A display key difference tool that does the following: Compares each locale configured on the server against the master display key list. Generates a file that contains a list of any missing keys.
	See "Localizing Typecodes" on page 41 in the Globalization Guide.
<pre>gwcc export-l10ns -Dexport.file="translation_file"</pre>	Exports a translation file from ClaimCenter into a file.
-Dexport.locale="language to export"	The -Dexport.file parameter specifies the destination file.If you leave the import translation file in the same location, then enter only the name of the file to import.
	 If you move the translation file to a different location, then enter an absolute path or a relative path to the file from the root of the installation directory.
	The -Dexport.locale parameter specifies the destination language to export. The -Dexport.locale parameter must match a ClaimCenter LanguageType type-code, such as fr or ja.
	See "Localizing Typecodes" on page 41 in the Globalization Guide.
gwcc import-l10ns	Imports a translation file into the configuration.
<pre>-Dimport.file="translation_file" -Dimport.locale=destination_locale</pre>	The -Dimport.file parameter specifies the file that contains the translations. It must be in the same format as an export file from Studio.
	The -Dimport.locale parameter specifies the destination language for the translations. The language must match a ClaimCenter LanguageType typecode, such as fr or ja.
	See "Localizing Typecodes" on page 41 in the Globalization Guide.
<pre>gwcc install-localized-module -Dmodule.file=ZipFileName -Dinstall.type={install upgrade}</pre>	Installs or upgrades a language module. See "Installing Display Languages" on page 23 in the <i>Globalization Guide</i> .
gwcc iterator-upgrade	Upgrades all iterators on toolbar buttons and filters. This command is only used during upgrade from a prior major version. See "Running PCF Iterator Upgrade" on page 232 in the <i>Upgrade Guide</i> .
gwcc regen-datamapping-split	Builds the data mapping files with files split out by table and typelist. Data mapping files represent fields present in the physical database. None of the virtual fields are represented.
	Class: com.guidewire.tools.datamapping.DataMappingTool
gwcc regen-datamapping-together	Builds the data mapping files with all tables and typelists concatenated. represent fields present in the physical database. None of the virtual fields are represented.
	Class: com.guidewire.tools.datamapping.DataMappingTool



Command

gwcc regen-dictionary -DmaxSPVInclusions=n

-DoutputFormat={html|xml}

Action

Generates the Data Dictionary and Security Dictionary. The Data Dictionary includes physical fields in the database and virtual fields in the data model. The Security Dictionary includes application permission keys, system permissions, and roles.

Generate the dictionaries the first time you unzip ClaimCenter and each time you update the data model. Run the gwcc regen-java-api and gwcc regen-soap-api commands each time just prior to regenerating the security and data dictionaries.

gwcc regen-dictionary

To view either dictionary in HTML format, open the index file for it in a browser:

ClaimCenter/dictionary/data/index.html ClaimCenter/dictionary/security/index.html

You can generate the Data Dictionary and Security Dictionary in XML format, with associated XSD files. Use the generated XML and XSD files to import the Data Dictionary and Security Dictionary into third-party database design tools.

gwcc regen-dictionary -DoutputFormat=xml

This command generates the following XML and XSD files for the dictionaries:

GenericCenter/build/dictionary/data/entityModel.xml GenericCenter/build/dictionary/data/entityModel.xsd GenericCenter/build/dictionary/security/securityDictionary.xml GenericCenter/build/dictionary/security/securityDictionary.xsd

You can generate the dictionaries in HTML format while building a WAR file. See the description for gwcc build-jboss-war or gwcc build-tomcat-war for

For more information, see "Regenerating the Data Dictionary and Security Dictionary" on page 30 in the Configuration Guide.

This command performs PCF validation to catch errors in PCF files, such as:

- Invalid expressions
- · Attributes that have no meaning when another attribute is set
- · Editable cells within non-editable objects
- · Illegal use of check boxes
- · Invalid arguments
- Other errors

Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate $12 \times 12 \times 12 \times 12 = 20,736$ combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:

gwcc regen-dictionary -DmaxSPVInclusions=1000

In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.

Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.

The maxSPVInclusions property can only be specified as a positive integer value.

For more information on second pass verification, see "Setting Verification Options" on page 95 in the Configuration Guide.

Classes:

com.guidewire.tools.dictionary.data.DataDictionaryTool com.guidewire.tools.dictionary.security.SecurityDictionaryTool



Command

Command	Action
gwcc regen-from-wsc	Downloads the WSDL and XSD files for all WSC (Web Service Collection) files. Web service collection files encapsulate the set of resources necessary to connect to a web service on an external system. If you view a web service collection in Studio and click the Fetch Updates button, Studio gets the latest WSDL and XSD files from servers that publish those web services. This tool is equivalent to the Fetch Updates process, but runs from the command line and operates on all web services rather than one.
	See "Loading WS-I WSDL Locally Using Studio Web Service Collections" on page 72 in the <i>Integration Guide</i> .
gwcc regen-gosudoc	Generates Gosu documentation similar to JavaDoc but using the ClaimCenter type system. This command produces documentation at ClaimCenter/build/gosudoc/index.html. See "Gosu Generated Documentation ('gosudoc')" on page 37 in the Gosu Reference Guide.
	Class: com.guidewire.tools.gosudoc.GosuDocMain
gwcc regen-java-api	Builds the Java API toolkit and examples to the ClaimCenter/java-api directory. See "Regenerating Integration Libraries" on page 22 in the <i>Integration Guide</i> .
	Class: com.guidewire.commons.entity.external.ExternalGenerator
gwcc regen-pcfmapping	Builds the PCF mappings.
-DmaxSPVInclusions= <i>n</i>	This command performs PCF validation to catch errors in PCF files, such as: Invalid expressions Attributes that have no meaning when another attribute is set Editable cells within non-editable objects Illegal use of check boxes Invalid arguments Other errors
	Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate 12 x 12 x 12 x 12 = 20,736 combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:
	gwcc regen-pcfmapping -DmaxSPVInclusions=1000
	In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.
	Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.
	The maxSPVInclusions property can only be specified as a positive integer value
	For more information on second pass verification, see "Setting Verification Options" on page 95 in the <i>Configuration Guide</i> .
	Class: com.guidewire.tools.pcfmapping.PCFMappingWriterMain
wxx regen-phone-metadata	Regenerates phone metadata in config/phone/data. Run this command if you have modified the phone metadata XML files
gwcc regen-rulereport	Generates an XML report describing the existing business rules. See "Generating a Rule Repository Report" on page 87 in the <i>Rules Guide</i> .
gwcc regen-soap-api	Builds the SOAP API toolkit and examples to the ClaimCenter/soap-api directory. See "Regenerating Integration Libraries" on page 22 in the <i>Integration Guide</i> .
	Classes: com.guidewire.tools.wsdl.WSDLGenerator com.guidewire.util.webservices.axis.WSDLToJavaGenerator

Action



Command	Action
gwcc regen-soap-local	Regenerates local files related to RPCE web services. Use this command after adding, changing, or removing web services.
	See "Publishing Web Services (RPCE)" on page 89 in the Integration Guide.
gwcc regen-wsi-local	Regenerates the WSDL for all local web services. ClaimCenter generates the WSDL in the ClaimCenter\wsi-local directory.
	See "Generating WS-I WSDL On Disk" on page 50 in the Integration Guide.
gwcc regen-xsd	Builds the XSD files for data import. See "Creating an XML File for Import" on page 115 in the System Administration Guide and "Importing Administrative Data" on page 145 in the Integration Guide.
gwcc studio	Runs Guidewire Studio.
	Class: com.guidewire.studio.main.Main
gwcc verify-checksum	Verifies module checksums.
	Class: com.guidewire.tools.checksum.ModulesChecksumTool
gwcc verify-resources	Checks PCF files, XML schemas, and type loaders for errors.
-DmaxSPVInclusions= <i>n</i>	This command performs PCF validation to catch errors in PCF files, such as: Invalid expressions Attributes that have no meaning when another attribute is set Editable cells within non-editable objects Illegal use of check boxes Invalid arguments Other errors
	The command parses and compiles XML schemas and reports any errors.
	For each type loader, the command verifies the types supported by the loader. The command checks if a Gosu class compiles, or if a typelist can be retrieved properly.
	Server commands that perform PCF validation, including regen-dictionary, regen-pcfmapping, and verify-resources can take a very long time to complete. The server performs a second-pass verification which, among other operations, verifies all possible combinations of modal sections on each PCF page. For example, a page with 12 modes that is used four times causes the server command to validate 12 x 12 x 12 x 12 = 20,736 combinations. To limit the number of shared section verifications performed by these commands, specify the optional parameter maxSPVInclusions. This parameter defines the depth for second pass verification that limits the number of shared sections that are included in the verification of PCF types. For instance:
	gwcc verify-resources -DmaxSPVInclusions=1000
	In this case, the second pass compilation of PCF files would stop after 1000 permutations of modal PCF files.
	Experiment with values for maxSPVInclusions between 1000 and 1000000 to achieve improved command completion times. However, be aware that limiting the validation depth means that some combinations of PCF modes and uses are not validated.
	For more information on second pass verification, see "Setting Verification Options" on page 95 in the <i>Configuration Guide</i> .
	The maxSPVInclusions property can only be specified as a positive integer value.
gwcc version	Displays the product version.



Build Scripts Supported on Unix

On Windows, you can run various build scripts through the gwcc command. In contrast on Unix, you must invoke Ant directly with the following command:

ant -f ClaimCenter/modules/ant/build.xml buildScript

Substitute *buildScript* with one of the following values:

- build-jboss-war-dbcp Builds a generic WAR file for use with JBoss, including JDBC drivers
- build-jboss-war-jndi Builds a generic WAR file for use with JBoss, without JDBC drivers
- build-tomcat-war-dbcp Builds a generic WAR file for use with Tomcat, including JDBC drivers
- build-tomcat-war-jndi Builds a generic WAR file for use with Tomcat, without JDBC drivers
- build-weblogic-ear-dbcp Builds an EAR file for use with WebLogic, including JDBC drivers
- build-weblogic-ear-jndi Builds an EAR file for use with WebLogic, without JDBC drivers
- build-websphere-ear-dbcp Builds an EAR file for use with WebSphere, including JDBC drivers
- build-websphere-ear-jndi Builds an EAR file for use with WebSphere, without JDBC drivers

Although you can run many build scripts through the gwcc command on Windows, Guidewire supports running only the build scripts in the previous list by invoking Ant on Unix.

