



# **NETWORK SECURITY FUNDAMENTALS**

**Lab 1: Configuring DHCP** 

Document Version: 2021-01-30

Copyright © 2021 Network Development Group, Inc. www.netdevgroup.com

NETLAB+ is a registered trademark of Network Development Group, Inc.

Palo Alto Networks and the Palo Alto Networks logo are trademarks or registered trademarks of Palo Alto Networks, Inc.



# **Contents**

ntrodu	ction	3
Obiecti	ve	
	oology	
-	tings	
	onfiguring DHCP	
	Load Lab Configuration	
	Configure DHCP Server	
	Configure Client for DHCP	
	Configure a DHCP Client Reservation	
	Configure the Firewall Outside Interface for DHCP	



### Introduction

In this lab, you will configure the Palo Alto Networks Firewall as a DHCP server. You will then test the DHCP server with the Client PC.


## **Objective**

In this lab, you will perform the following tasks:

- Configure DHCP Server
- Configure Client for DHCP
- Configure a DHCP Client Reservation
- Configure the Firewall Outside Interface for DHCP



### **Lab Topology**





### **Lab Settings**

The information in the table below will be needed in order to complete the lab. The task sections below provide details on the use of this information.

Virtual Machine	IP Address	Account (if needed)	Password (if needed)
Client	192.168.1.20	lab-user	Train1ng\$
DMZ	192.168.50.10	root	Pal0Alt0
Firewall	192.168.1.254	admin	Train1ng\$




### 1 Configuring DHCP

#### 1.0 Load Lab Configuration

In this section, you will load the Firewall configuration file.

1. Click on the **Client** tab to access the Client PC.




- 2. Log in to the Client PC as username lab-user, password Trainlng\$.
- 3. Double-click the **Chromium Web Browser** icon located on the Desktop.



4. In the *Chromium* address field, type https://192.168.1.254 and press Enter.



5. You will see a "Your connection is not private" message. Click on the **ADVANCED** link.






If you experience the "Unable to connect" or "502 Bad Gateway" message while attempting to connect to the specified IP above, please wait an additional 1-3 minutes for the Firewall to fully initialize. Refresh the page to continue.



6. Click on Proceed to 192.168.1.254 (unsafe).




7. Log in to the Firewall web interface as username admin, password Train1ng\$.







 In the web interface, navigate to Device > Setup > Operations and click on Load named configuration snapshot underneath the Configuration Management section.



9. In the *Load Named Configuration* window, select **pan-nsf-lab-01.xml** from the *Name* dropdown box and click **OK**.



10. In the Loading Configuration window, a message will show Configuration is being loaded. Please check the Task Manager for its status. You should reload the page when the task is completed. Click **Close** to continue.




11. Click the **Tasks** icon located at the bottom-right of the web interface.






12. In the *Task Manager – All Tasks* window, verify the *Load* type has successfully completed. Click **Close.** 



13. Click the **Commit** link located at the top-right of the web interface.



14. In the Commit window, click Commit to proceed with committing the changes.





15. When the commit operation successfully completes, click **Close** to continue.






The commit process takes changes made to the Firewall and copies them to the running configuration, which will activate all configuration changes since the last commit.

### 1.1 Configure DHCP Server

In this section, you will configure a DHCP Server on the Firewall. By adding a DHCP server to the Firewall, clients behind the Firewall will not have to configure IP addresses manually. A client that is configured for DHCP and connected to the same network as the Firewall will receive an IP address automatically, reducing network configuration errors.

1. Navigate to **Network > DHCP > DHCP Server.** 






2. Click on **Add**, located near the bottom-left of the *IP Pools* box.



3. In the DHCP Server window, select ethernet1/2 for the Interface dropdown. Next, in the Mode dropdown, select enabled. Then, in the Lease radio button, select Timeout and give it a value of 2 days. Finally, in the IP Pools, click the Add button at the bottom-left of the IP Pools section and enter 192.168.1.100-192.168.1.110.






ethernet1/2 is selected to run DHCP because this is the network that the Client is connected to. In this configuration, the Client will receive an IP address automatically. By specifying a 2-day timeout, the client will need to request a new IP address every 2 days. The IP Pool created will limit the number of IP addresses that the firewall will automatically distribute.



4. Click on the **Options** tab and type **192.168.1.1** in the *Gateway* field, **255.255.255.0** in the *Subnet Mask* field, and type **8.8.8.8** in the *Primary DNS* field.






The Gateway of 192.168.1.1 is the interface for the Firewall. DHCP will send this to the Client so that the Client will have a default gateway. The Primary DNS server, 8.8.8.8, is one of Google's public DNS servers. DHCP will also send this information to the Client so that the Client will have a DNS server.

- 5. Click the **OK** button on the *DHCP Server* window.
- 6. Click the **Commit** link located at the top-right of the web interface.





7. In the Commit window, click Commit to proceed with committing the changes.



8. When the commit operation successfully completes, click **Close** to continue.






### 1.2 Configure Client for DHCP

In this section, you will confirm the current configuration of the Client. Then, you will configure the client for DHCP and confirm a Dynamic IP address was assigned.

1. Click on the **Connection** icon in the lower-right of the web *Client*. Next, click on **Edit Connections...** 




2. In the *Network Connections* window, under the *Ethernet* dropdown list, double-click **LAN**.





3. In the *Editing LAN* window, click **IPv4 Settings.** Leave the *Editing LAN* window open for the next step.






Notice that the method is set to **Manual**. By default, in this lab environment, the Client is configured with a static IP address of **192.168.1.20**, a Netmask of **24** which is **255.255.255.0**, a default gateway of **192.168.1.1**. The DNS server is set to **192.168.1.20** and the search domain is **lab.local**.



**4.** In the *Editing LAN* window, click on the **Method** and select **Automatic (DHCP).** Click **Save** and close the *Editing LAN* window.



5. Click on the Xfce Terminal icon in the taskbar.





6. In the *Terminal* window, type sudo ifconfig ens160 down. Enter the Train1ng\$ password when prompted, and press Enter. Leave the *Terminal* window open for the next step.

```
Terminal

File Edit View Terminal Tabs Help

C:\home\lab-user> sudo ifconfig ens160 down
[sudo] password for lab-user:

C:\home\lab-user>
```

7. With the *Terminal* window still open, type **sudo ifconfig ens160** up and press **Enter.** Leave the *Terminal* window open for the next step.

```
Terminal

File Edit View Terminal Tabs Help

C:\home\lab-user> sudo ifconfig ens160 down
[sudo] password for lab-user:

C:\home\lab-user> sudo ifconfig ens160 up

C:\home\lab-user>
```

8. In the *Terminal* window, type **ifconfig** and press **Enter**. Notice the IP Address and DHCP Record of the Physical Address, also known as the MAC address, of the *ifconfig* command output. (The MAC address will be used in the next task). Leave the *Terminal* window open for the next task.

```
C:\home\lab-user> ifconfig
docker0: flags=4099<UP, BROADCAST, MULTICAST> mtu 1500
        inet 172.17.0.1 netmask 255.255.0.0 broadcast 172.17.255.255
        ether 02:42:97:02:e9:62 txqueuelen 0 (Ethernet)
        RX packets 0 bytes 0 (0.0 B)
        RX errors 0 dropped 0 overruns 0 frame 0 TX packets 0 bytes 0 (0.0 B)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
ens160 flags=4163<UP.BROADCAST.RUNNING.MULTICAST> mtu 1500
       inet 192.168.1.100 netmask 255.255.255.0 broadcast 192.168.1.255
        inet6 fe80::c317:4ce7:59df:690a prefixlen 64 scopeid 0x20<link>
       ether 00:50:56:8a:0d:49 txqueuelen 1000 (Ethernet)
        RX packets 96 bytes 10601 (10.6 KB)
        RX errors 0 dropped 40 overruns 0 frame 0
        TX packets 168 bytes 20356 (20.3 KB)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP,L00PBACK,RUNNING> mtu 65536
        inet 127.0.0.1 netmask 255.0.0.0
        inet6 ::1 prefixlen 128 scopeid 0x10<host>
        loop txqueuelen 1000 (Local Loopback)
RX packets 1773 bytes 200237 (200.2 KB)
        RX errors 0 dropped 0 overruns 0 frame 0
        TX packets 1773 bytes 200237 (200.2 KB)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
C:\home\lab-user>
```





Notice, the IP address has changed to 192.168.1.100 and is in the DHCP range that was configured in a previous task. The DHCP Server is the IP address of the Firewall.

9. Type exit and press Enter to close the Terminal window.


#### 1.3 Configure a DHCP Client Reservation

In this section, you will configure a DHCP Client Reservation. A client reservation is a way to statically assign an IP address to a client via the DHCP Server. The client remains configured for DHCP; however, the DHCP Server will lease the IP address assigned to that physical address or MAC address every time the Client requests a new IP address. As each computer has a unique MAC address, this will assist the DHCP server in leasing the proper address.

On the Firewall administration page, navigate to Network > DHCP > DHCP
 Server.




2. Click on ethernet1/2.





3. Click on the **Add** button under the *Reserved Address* section on the right. Then, type 192.168.1.51 for the *Reserved Address*. Finally, type the *MAC Address* of the Client, 00:50:56:8a:0d:49.






Notice, the MAC address is displayed slightly differently than it was in the *Terminal* window in the previous task. Different systems represent the MAC address in different ways. In this case, the Firewall requires it use colon notation. The Client uses dash notation. Some systems even condense part of the address, i.e., **0050.568a.0d49**.

- 4. Click the **OK** button to close the *DHCP Server* window.
- 5. Click the **Commit** link located at the top-right of the web interface.





6. In the Commit window, click Commit to proceed with committing the changes.



7. When the commit operation successfully completes, click **Close** to continue.



8. Click on the Xfce Terminal icon in the taskbar.



9. With the *Terminal* window still open, type **sudo ifconfig ens160 down**. Enter the **Train1ng**\$ password when prompted and press **Enter**. Leave the *Terminal* window open for the next step.

```
Terminal

File Edit View Terminal Tabs Help

C:\home\lab-user> sudo ifconfig ens160 down
[sudo] password for lab-user:

C:\home\lab-user>
```



10. With the *Terminal* window still open, type **sudo ifconfig ens160 up** and press **Enter.** Leave the *Terminal* window open for the next step

```
Terminal

File Edit View Terminal Tabs Help

C:\home\lab-user> sudo ifconfig ens160 down
[sudo] password for lab-user:

C:\home\lab-user> sudo ifconfig ens160 up

C:\home\lab-user>
```

11. Type **ifconfig** and press **Enter**. This command will show the new lease from the DHCP server.

```
C:\home\lab-user> ifconfig
docker0: flags=4099<UP, BROADCAST, MULTICAST> mtu 1500
        inet 172.17.0.1 netmask 255.255.0.0 broadcast 172.17.255.255
        ether 02:42:97:02:e9:62 txqueuelen 0 (Ethernet)
        RX packets 0 bytes 0 (0.0 B)
        RX errors 0 dropped 0 overruns 0 frame 0
        TX packets 0 bytes 0 (0.0 B)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
ens160: flags=4163<UP.BROADCAST.RUNNING.MULTICAST> mtu 1500
        inet 192.168.1.51 netmask 255.255.255.0 broadcast 192.168.1.255
        inet6 fe80::c317:4ce7:59df:690a prefixlen 64 scopeid 0x20<link>
ether 00:50:56:8a:0d:49 txqueuelen 1000 (Ethernet)
        RX packets 98 bytes 12122 (12.1 KB)
        RX errors 0 dropped 40 overruns 0 frame 0
        TX packets 161 bytes 21737 (21.7 KB)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
        inet 127.0.0.1 netmask 255.0.0.0
        inet6 ::1 prefixlen 128 scopeid 0x10<host>
        loop txqueuelen 1000 (Local Loopback)
        RX packets 1794 bytes 201504 (201.5 KB)
        RX errors 0 dropped 0 overruns 0 frame 0 TX packets 1794 bytes 201504 (201.5 KB)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
C:\home\lab-user>
```



You should receive an IP address of **192.168.1.51**. This was the address you reserved for the Client machine on the firewall. If you receive a different address, repeat this section and take careful note of the MAC address.


12. Type exit and press **Enter** to exit the *Terminal* window.




### 1.4 Configure the Firewall Outside Interface for DHCP

In this section, you will configure the Firewall outside interface for DHCP. Like the Client in the previous task, the Firewall will obtain an IP address from a DHCP server on the network.

On the Firewall administration page, navigate to Network > Interfaces >
Ethernet.




2. Click on ethernet1/1.






 On the Ethernet Interface window, click on the IPv4 tab. Then, select the DHCP Client radio button in the Type field. Finally, click the OK button.






The **DHCP Client** setting allows the Firewall interface to receive a dynamic IP Address. Some internet service providers will provide an IP address via DHCP, in which case the Firewall will need to be configured to receive a dynamic IP Address.

4. Click the **Commit** link located at the top-right of the web interface.





5. In the Commit window, click Commit to proceed with committing the changes.



6. When the commit operation successfully completes, click **Close** to continue.




7. Click on the **Dynamic-DHCP Client** link under the *IP Address* field for **ethernet1/1**.





8. You should receive an *IP Address* of **203.0.113.x**, where *x* could be any number starting with the number 2 thru 254. This was obtained from the DHCP Server running on the VRouter between the Firewall and the External Network.



9. The lab is now complete; you may end the reservation.