Oracle® Database

In-Memory Guide 12*c* Release 2 (12.2) **E71458-05**

November 2016



Oracle Database In-Memory Guide, 12c Release 2 (12.2)

E71458-05

Copyright © 2016, Oracle and/or its affiliates. All rights reserved.

Primary Author: Lance Ashdown

Contributing Authors: Maria Colgan, Vineet Marwah, Andy Rivenes, Randy Urbano

Contributors: Yasin Baskin, Nigel Bayliss, Eric Belden, Larry Carpenter, Shasank Chavan, William Endress, Katsumi Inoue, Jesse Kamp, Chinmayi Krishnappa, Vasudha Krishnaswamy, Yunrui Li, Yuehua Liu, Aurosish Mishra, Ajit Mylavarapu, Khoa Nguyen, Kathy Rich, Beth Roeser, Rich Strohm, Dina Thomas, Bob Zehian

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Pre	eface			ix
	Auc	lience .		ix
Documentation Accessibility				
Related Documents				
	Cor	ventio	ons	×
Ch	200	e in -	This Release for Oracle Database In-Memory Guide	v
CII	_		•	
	Cha	_	n Oracle Database 12c Release 2 (12.2.0.1)	
		New .	Features	X
Pa	rt I	Orac	cle Database In-Memory Concepts	
1	Intr	oduct	ion to Oracle Database In-Memory	
	1.1	Chall	lenges for Analytic Applications	1-1
	1.2		Single-Format Approach	
	1.3		Oracle Database In-Memory Solution	
			What Is Database In-Memory?	
		1.3.2	Improved Performance for Analytic Queries	1-6
		1.3.3	Improved Performance for Mixed Workloads	1-8
		1.3.4	High Availability Support	1-9
		1.3.5	Ease of Adoption	1-10
	1.4	Prere	equisites for Database In-Memory	1-10
	1.5	Princ	ripal Tasks for Database In-Memory	1-11
	1.6	Tools	s for the IM Column Store	1-12
		1.6.1	In-Memory Advisor	1-13
		1.6.2	Cloud Control Pages for the IM Column Store	1-13
		1.6.3	Oracle Compression Advisor	1-14
		1.6.4	Oracle Data Pump and the IM Column Store	1-14
2	In-N	Лето	ory Column Store Architecture	
	2.1	Dual-	-Format: Column and Row	2-1

		2.1.1 Columnar Data in the In-Memory Area	2-2
		2.1.2 Row Data in the Database Buffer Cache	2-
	2.2	In-Memory Storage Units	2-7
		2.2.1 In-Memory Compression Units (IMCUs)	2-8
		2.2.2 Snapshot Metadata Units (SMUs)	. 2-15
		2.2.3 In-Memory Expression Units (IMEUs)	. 2-17
	2.3	Expression Statistics Store (ESS)	. 2-18
	2.4	In-Memory Process Architecture	. 2-19
		2.4.1 In-Memory Coordinator Process (IMCO)	. 2-19
		2.4.2 Space Management Worker Processes (Wnnn)	. 2-20
	2.5	CPU Architecture: SIMD Vector Processing	. 2-2
Pa	rt II	Configuring the IM Column Store	
3	Ena	abling and Sizing the IM Column Store	
	3.1	Overview of Enabling the IM Column Store	3-
	3.2	Estimating the Required Size of the IM Column Store	3-2
	3.3	Enabling the IM Column Store for a Database	3-3
	3.4	Increasing the Size of the IM Column Store Dynamically	
	3.5	Disabling the IM Column Store	3-
4	Ena	abling Objects for In-Memory Population	
	4.1	About In-Memory Population	4-
		4.1.1 Purpose of In-Memory Population	4-2
		4.1.2 How In-Memory Population Works	4-2
		4.1.3 Controls for In-Memory Population	4-6
	4.2	Enabling and Disabling Tables for the IM Column Store	. 4-1
		4.2.1 Enabling New Tables for the In-Memory Column Store	4-12
		4.2.2 Enabling and Disabling Existing Tables for the IM Column Store	. 4-12
		4.2.3 Enabling and Disabling Tables for the IM Column Store: Examples	. 4-13
	4.3	Enabling and Disabling Columns for In-Memory Tables	. 4-16
		4.3.1 About IM Virtual Columns	. 4-17
		4.3.2 Enabling IM Virtual Columns	. 4-18
		4.3.3 Enabling a Subset of Columns for the IM Column Store: Example	. 4-19
		4.3.4 Specifying INMEMORY Column Attributes on a NO INMEMORY Table: Example	le
	4.4	Enabling and Disabling Tablespaces for the IM Column Store	. 4-23
	4.5	Enabling and Disabling Materialized Views for the IM Column Store	. 4-24
	4.6	Forcing Population of an In-Memory Object: Tutorial	. 4-24
	4.7	Enabling ADO for the IM Column Store	
		4.7.1 About ADO Policies and the IM Column Store	. 4-26
		4.7.2 Purpose of ADO and the IM Column Store	
		4.7.3 How ADO Works with Columnar Data	. 4-28

	4.7.4 Controls for ADO and the IM Column Store	4-30
	4.7.5 Creating an ADO Policy for the IM Column Store	4-32
Ра	art III Optimizing In-Memory Queries	
5	Optimizing Queries with In-Memory Expressions	
	5.1 About IM Expressions	5-1
	5.1.1 Purpose of IM Expressions	5-3
	5.1.2 How IM Expressions Work	5-4
	5.1.3 User Interfaces for IM Expressions	5-9
	5.1.4 Basic Tasks for IM Expressions	5-11
	5.2 Configuring IM Expression Usage	5-11
	5.3 Capturing and Populating IM Expressions	5-12
	5.4 Dropping IM Expressions	5-14
6	Optimizing Joins with Join Groups	
	6.1 About In-Memory Joins	6-1
	6.2 About Join Groups	6-2
	6.3 Purpose of Join Groups	6-2
	6.4 How Join Groups Work	6-4
	6.4.1 How a Join Group Uses a Common Dictionary	
	6.4.2 How a Join Group Optimizes Scans	
	6.5 Creating Join Groups	
	6.6 Monitoring Join Group Usage	6-10
7	Optimizing Joins with In-Memory Aggregation	
	7.1 About IM Aggregation	7-1
	7.2 Purpose of IM Aggregation	7-2
	7.2.1 When IM Aggregation Is Useful	
	7.2.2 When IM Aggregation Is Not Beneficial	7-4
	7.3 How IM Aggregation Works	7-4
	7.3.1 When the Optimizer Chooses IM Aggregation	7-5
	7.3.2 Key Vector	7-6
	7.3.3 Two Phases of IM Aggregation	7-7
	7.3.4 IM Aggregation: Scenario	7-8
	7.4 Controls for IM Aggregation	. 7-14
	7.5 In-Memory Aggregation: Example	7-15
8	Optimizing Repopulation of the IM Column Store	
	8.1 About Repopulation of the IM Column Store	
	8.2 How Data Loading Works with the IM Column Store	8-2
	8.2.1 How Conventional DML Works with the IM Column Store	8-2
	8.2.2 How Direct Path Loads Work with the IM Column Store	8-4

		8.2.3 How a Partition Exchange Load Works with the IM Column Store	. 8-5
	8.3	When the Database Repopulates the IM Column Store	. 8-7
		8.3.1 Threshold-Based and Trickle Repopulation	. 8-7
		8.3.2 Factors Affecting Repopulation	. 8-9
	8.4	Controls for Repopulation of the IM Column Store	8-10
	8.5	Optimizing Trickle Repopulation: Tutorial	8-11
Ра	rt IV	High Availability and the IM Column Store	
9	Ма	naging IM FastStart for the IM Column Store	
	9.1	About IM FastStart	. 9-1
		9.1.1 Purpose of IM FastStart	. 9-2
		9.1.2 How IM FastStart Works	. 9-2
	9.2	Enabling IM FastStart for the IM Column Store	. 9-5
	9.3	Retrieving the Name of the Current IM FastStart Tablespace	. 9-7
	9.4	Migrating the FastStart Area to a Different Tablespace	. 9-8
	9.5	Disabling IM FastStart for the IM Column Store	. 9-9
10	De	eploying IM Column Stores in Oracle RAC	
	10.1	Overview of Database In-Memory and Oracle RAC	10-1
		10.1.1 Multiple IM Column Stores	10-2
		10.1.2 Distribution and Duplication of Columnar Data in Oracle RAC	10-5
		10.1.3 Parallelism in Oracle RAC	10-12
			10-14
	10.2		10-15
			10-15
		,	10-16
		,	10-17
		10.2.4 Configuring an In-Memory Service for a Subset of Nodes: Example	10-18
11	De	eploying an IM Column Store with Oracle Active Data Guard	
	11.1	About Database In-Memory and Active Data Guard	11-1
		11.1.1 Purpose of IM Column Stores in Oracle Active Data Guard	11-1
		11.1.2 How IM Column Stores Work in Oracle Active Data Guard	11-4
	11.2	Configuring IM Column Stores in an Oracle Active Data Guard Environment	11-5
Ра	rt V	Database In-Memory Reference	
12	In	-Memory Initialization Parameters	
40	يرا	MaraaruViausa	
13	ın	-Memory Views	

A Using IM Column Store In Cloud Control

A.1	Meeting Prerequisites for Using IM Column Store in Cloud Control				
A.2	Using the In-Memory Column Store Central Home Page to Monitor In-Memory Support for				
D	Oatabase Objects	A-2			
A.3	Specifying In-Memory Details When Creating a Table or Partition	A-3			
A.4	Viewing or Editing IM Column Store Details of a Table	A-3			
A.5	Viewing or Editing IM Column Store Details of a Partition	A-4			
A.6	Specifying IM Column Store Details During Tablespace Creation	A-4			
A.7	Viewing and Editing IM Column Store Details of a Tablespace	A-5			
A.8	Specifying IM Column Store Details During Materialized View Creation	A-5			
A.9	Viewing or Editing IM Column Store Details of a Materialized View	A-5			

Glossary

Index

Preface

This manual explains the architecture and tasks associated with the Oracle Database In-Memory feature set.

This preface contains the following topics:

Audience (page ix)

Documentation Accessibility (page ix)

Related Documents (page ix)

Conventions (page x)

Audience

This document is intended for database administrators who manage an In-Memory Column Store (IM column store), and developers who optimize analytic queries that use Oracle Database In-Memory features.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

Related Documents

This manual assumes that you are familiar with *Oracle Database Concepts*. The following books are frequently referenced:

- Oracle Database Data Warehousing Guide
- Oracle Database VLDB and Partitioning Guide
- Oracle Database SQL Tuning Guide
- Oracle Database SQL Language Reference

• Oracle Database Reference

Many examples in this book use the sample schemas, which are installed by default when you select the Basic Installation option with an Oracle Database. See *Oracle Database Sample Schemas* for information on how these schemas were created and how you can use them.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Changes in This Release for Oracle Database In-Memory Guide

This preface contains:

Changes in Oracle Database 12c Release 2 (12.2.0.1) (page xi)

Oracle Database In-Memory Guide for Oracle Database 12c Release 2 (12.2.0.1) has the following changes.

Changes in Oracle Database 12c Release 2 (12.2.0.1)

Oracle Database In-Memory Guide for Oracle Database 12c Release 2 (12.2.0.1) has the following changes.

New Features (page xi)

The following major features are new in this release:

New Features

The following major features are new in this release:

In-Memory Column Store (IM column store) dynamic resizing
 You can now dynamically increase the size of the In-Memory Area without reopening the database.

See "Increasing the Size of the IM Column Store Dynamically (page 3-4)".

• In-Memory Expressions (IM expressions)

Oracle Database automatically identifies frequently used ("hot") expressions that are candidates for population in the IM column store. A candidate expression might be (monthly_sales*12)/52. IM expressions can greatly improve the performance of analytic queries that use computationally intensive expressions and access large data sets.

See "Optimizing Queries with In-Memory Expressions (page 5-1)".

In-Memory virtual columns (IM virtual columns)

IM virtual columns enable the IM column store to materialize some or all virtual columns in a table.

See "Enabling and Disabling Columns for In-Memory Tables (page 4-16)".

IM FastStart

IM FastStart optimizes the population of database objects in the IM column store by storing IMCUs directly on disk.

See "Managing IM FastStart for the IM Column Store (page 9-1)".

• Object-level support for services

For an individual object, the INMEMORY ... DISTRIBUTE clause has a FOR SERVICE subclause that limits population to the database instance where this service is allowed to run. For example, you can configure an INMEMORY object to be populated in the IM column store on instance 1 only, or on instance 2 only, or in both instances.

See "Object-Level Service Controls (page 10-16)".

• IM column store on a standby database

You can enable an IM column store in an Oracle Active Data Guard standby database. You can populate a completely different set of data in the in-memory column store on the primary and standby databases, effectively doubling the size of the in-memory column store that is available to the application.

See "Deploying an IM Column Store with Oracle Active Data Guard (page 11-1)".

ADO support for the IM column store

You can use Automatic Data Optimization (ADO) policies to evict objects such as tables, partitions, or subpartitions from the IM column store based on Heat Map statistics. Successful policy completion results in setting NO INMEMORY for the specified object.

See "Enabling ADO for the IM Column Store (page 4-26)".

Join groups

A join group is a user-created object that lists two columns that can be meaningfully joined. In certain queries, join groups enable the database to eliminate the performance overhead of decompressing and hashing column values. Join groups require an IM column store.

See "Optimizing Joins with Join Groups (page 6-1)".

Part I

Oracle Database In-Memory Concepts

This part introduces the Oracle Database In-Memory (Database In-Memory) feature set, and explains the basic architecture of the In-Memory Column Store (IM column store).

This part contains the following chapters:

Introduction to Oracle Database In-Memory (page 1-1)

Oracle Database In-Memory (Database In-Memory) is a suite of features, first introduced in Oracle Database 12*c* Release 1 (12.1.0.2), that greatly improves performance for real-time analytics and mixed workloads. The In-Memory Column Store (IM column store) is the key feature of Database In-Memory.

In-Memory Column Store Architecture (page 2-1)

The **In-Memory Column Store** (IM column store) stores tables and partitions in memory using a **columnar format** optimized for rapid scans. Oracle Database uses a sophisticated architecture to manage data in columnar and row formats simultaneously.

Introduction to Oracle Database In-Memory

Oracle Database In-Memory (Database In-Memory) is a suite of features, first introduced in Oracle Database 12c Release 1 (12.1.0.2), that greatly improves performance for real-time analytics and mixed workloads. The In-Memory Column Store (IM column store) is the key feature of Database In-Memory.

Note:

Database In-Memory features require the Oracle Database In-Memory option.

This chapter contains the following topics:

Challenges for Analytic Applications (page 1-1)

Traditionally, obtaining good performance for analytic queries meant satisfying a number of requirements.

The Single-Format Approach (page 1-2)

Traditionally, relational databases store data in either row or columnar formats. Memory and disk store data in the same format.

The Oracle Database In-Memory Solution (page 1-3)

The Oracle Database In-Memory (Database In-Memory) feature set includes the In-Memory Column Store (IM column store), advanced query optimizations, and availability solutions.

Prerequisites for Database In-Memory (page 1-10)

The Oracle Database In-Memory option is required for all Database In-Memory features. No special hardware is required for an IM column store.

Principal Tasks for Database In-Memory (page 1-11)

For queries to benefit from the IM column store, the only required tasks are specifying a size for the IM column store, and specifying objects and columns for population. Query optimization and availability features require additional configuration.

Tools for the IM Column Store (page 1-12)

No special tools or utilities are required to manage the IM column store or other Database In-Memory features. Administrative tools such as SQL*Plus, SQL Developer, and Oracle Enterprise Manager (Enterprise Manager) are fully supported.

1.1 Challenges for Analytic Applications


Traditionally, obtaining good performance for analytic queries meant satisfying a number of requirements.

In a typical data warehouse or mixed-use database, requirements include the following:

- You must understand user access patterns.
- You must provide good performance, which typically requires creating indexes, materialized views, and OLAP cubes.

For example, if you create 1 to 3 indexes for a table (1 primary key and 2 foreign key indexes) to provide good performance for an OLTP application, then you may need to create additional indexes to provide good performance for analytic queries.

Figure 1-1 Multiple Indexes



Meeting the preceding requirements creates manageability and performance problems. Additional access structures cause performance overhead because you must create, manage, and tune them. For example, inserting a single row into a table requires an update to all indexes on this table, which increases response time.

The demand for real-time analytics means that more analytic queries are being executed in a mixed-workload database. The traditional approach is not sustainable.

1.2 The Single-Format Approach

Traditionally, relational databases store data in either row or columnar formats. Memory and disk store data in the same format.

An Oracle database stores rows contiguously in data blocks. For example, in a table with three rows, an Oracle data block stores the first row, and then the second row, and then the third row. Each row contains all column values for the row. Data stored in row format is optimized for transaction processing. For example, updating all columns in a small number of rows may modify only a small number of blocks.

To address the problems relating to analytic queries, some database vendors have introduced a columnar format. A columnar database stores selected columns—not rows—contiguously. For example, in a large sales table, the sales IDs reside in one column, and sales regions reside in a different column.

Analytical workloads access few columns while scanning, but scan the entire data set. For this reason, the columnar format is the most efficient for analytics. Because columns are stored separately, an analytical query can access only required columns, and avoid reading inessential data. For example, a report on sales totals by region can rapidly process many rows while accessing only a few columns.

Database vendors typically force customers to *choose* between a columnar and row-based format. For example, if the data format is columnar, then the database stores data in columnar format both in memory and on disk. Gaining the advantages of one format means losing the advantages of the alternate format. Applications either

achieve rapid analytics or rapid transactions, but not both. The performance problems for mixed-use databases are not solved by storing data in a single format.

1.3 The Oracle Database In-Memory Solution

The Oracle Database In-Memory (Database In-Memory) feature set includes the In-Memory Column Store (IM column store), advanced guery optimizations, and availability solutions.

The Database In-Memory optimizations enable analytic queries to run orders of magnitude faster on data warehouses and mixed-use databases.

This section contains the following topics:

What Is Database In-Memory? (page 1-3)

The Database In-Memory feature set includes the IM column store, advanced query optimizations, and availability solutions. These features combine to accelerate analytic queries by orders of magnitude without sacrificing OLTP performance or availability.

Improved Performance for Analytic Queries (page 1-6)

Because the IM column store populates database objects in a compressed columnar format, Oracle Database can perform faster scans, queries, joins, and aggregates.

Improved Performance for Mixed Workloads (page 1-8)

Although OLTP applications do not benefit from accessing data in the IM column store, the dual-memory format can indirectly improves OLTP performance.

High Availability Support (page 1-9)

The IM column store is fully integrated into Oracle Database. All High Availability features are supported.

Ease of Adoption (page 1-10)

Database In-Memory is simple to implement, and requires no application changes.

1.3.1 What Is Database In-Memory?

The Database In-Memory feature set includes the IM column store, advanced query optimizations, and availability solutions. These features combine to accelerate analytic queries by orders of magnitude without sacrificing OLTP performance or availability.

IM Column Store

The IM column store maintains copies of tables, partitions, and individual columns in a special compressed columnar format that is optimized for rapid scans. The IM column store resides in the In-Memory Area, which is an optional portion of the system global area (SGA).

The IM column store does not replace row-based storage or the database buffer cache, but supplements it. The database allows data to be in memory in both a row-based and columnar format, providing the best of both worlds. The IM column store provides an additional transaction-consistent copy of table data that is independent of the disk format. Objects populated in the IM column store do not also need to be loaded into the buffer cache.

Transactions

Normal Buffer Cache

New In-Memory Format

Reports

Sales

Columnar Format

Sales

Table

Database

Figure 1-2 Dual-Format Database

Use the INMEMORY clause in DDL statements to enable the IM column store at any of the following levels:

- Column (nonvirtual or virtual)
- Table, materialized view, or partition
- Tablespace

If the INMEMORY attribute is specified at the tablespace level, then all new tables and materialized views in the tablespace are enabled for the IM column store by default. In the context of Database In-Memory, population is the automatic transformation of row-based data on disk into columnar data in the IM column store. You can configure all or a subset of a database object's columns for population in the IM column store. Similarly, for a partitioned table or materialized view, you can configure all or a subset of the partitions for population.

For example, you might configure three tables from the sh schema for population into the IM column store: customers, products, and sales. The IM column store stores the data for each table by column rather than by row, and divides each column into separate row subsets. A special container called an In-Memory Compression Unit (IMCU) stores all columns for a subset of rows in a table segment.

Video:

Oracle Database 12c demos: In-Memory Column Store Columns

Advanced Query Optimizations

Database In-Memory includes several performance optimizations for analytic queries. Optimizations include:

 An expression is a combination of one or more values, operators, and SQL functions (DETERMINISTIC only) that resolve to a value. By default, the InMemory Expression (IM expression) optimization enables the DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS procedure to identify and populate "hot" expressions in the IM column store. An IM expression is materialized as a hidden virtual column, but is accessed in the same way as a nonvirtual column.

- A join group is a user-defined object that specifies the columns that join two or more tables in a query. In certain queries, join groups enable the database to eliminate the performance overhead of decompressing and hashing column values.
- For aggregation queries that join small dimension tables to a large fact table, In-Memory Aggregation (IM aggregation) uses the VECTOR GROUP BY operation to enhance performance. This optimization aggregates data during the scan of the fact table rather than afterward.
- In the IM column store, repopulation is the automatic update of IMCUs after the data within them has been significantly modified. If an IMCU has stale entries but does not meet the staleness threshold, then background processes may instigate trickle repopulation, which is the gradual repopulation of the IM column store.

See Also:

"Optimizing In-Memory Queries (page 1)"

High Availability Support

Availability is the degree to which an application, service, or function is accessible on demand. Database In-Memory supports the following availability features:

- In-Memory FastStart (IM FastStart) reduces the time to populate data into the IM column store when a database instance restarts. IM FastStart achieves this by periodically saving a copy of the data currently populated in the IM column store on the disk in its compressed columnar format.
- Each node in an Oracle Real Application Clusters (Oracle RAC) environment has its own IM column store. It is possible to have completely different objects populated on every node, or to have larger objects distributed across all IM column stores in the cluster. In Engineered Systems, it is also possible to have the same objects appear in the IM column store on every node.
- Starting in Oracle Database 12c Release 2 (12.2), an IM column store is supported on a standby database in an Active Data Guard environment.

See Also:

- "In-Memory Column Store Architecture (page 2-1)"
- "In-Memory Initialization Parameters (page 12-1)"
- "Enabling the IM Column Store for a Database (page 3-3)"
- "High Availability and the IM Column Store (page 1)"
- Oracle Database SQL Language Reference for more information about the INMEMORY clause
- Oracle Database Licensing Information

1.3.2 Improved Performance for Analytic Queries

Because the IM column store populates database objects in a compressed columnar format, Oracle Database can perform faster scans, queries, joins, and aggregates.

This section contains the following topics:

Improved Performance for Data Scans (page 1-6)

The columnar format provides fast throughput for scanning large amounts of data. You can analyze data in real time, enabling you to explore different possibilities and perform iterations.

Improved Performance for Joins (page 1-8)

A **Bloom filter** is a low-memory data structure that tests membership in a set. The IM column store takes advantage of Bloom filters to improve the performance of joins.

Improved Performance for Aggregation (page 1-8)

An important aspect of analytics is to determine patterns and trends by aggregating data. Aggregations and complex SQL queries run faster when data is stored in the IM column store.

1.3.2.1 Improved Performance for Data Scans

The columnar format provides fast throughput for scanning large amounts of data. You can analyze data in real time, enabling you to explore different possibilities and perform iterations.

The IM column store can drastically improve performance for the following types of queries:

- A query that scans a large number of rows and applies filters that use operators such as <, >, =, and IN
- A query that selects a small number of columns from a table or a materialized view having large number of columns, such as a query that accesses 5 out of 100 columns

Video:

Oracle Database 12c demos: In-Memory Column Store Queries

Columnar format uses fixed-width columns for most numeric and short string data types. This optimization enables rapid vector processing, which enables the database to answer queries faster (see "CPU Architecture: SIMD Vector Processing (page 2-21)").

Scans of the IM column store are faster than scans of row-based data for the following reasons:

Elimination of buffer cache overhead

The IM column store stores data in a pure, in-memory columnar format. The data does not persist in the data files (or generate redo), so the database avoids the overhead of reading data from disk into the buffer cache.

Data pruning

The database scans only the columns necessary for the query rather than entire rows of data. Furthermore, the database uses storage indexes and an internal dictionary to read only the necessary IMCUs for a specific query. For example, if a query requests all sales for a store with a store ID less than 8, then the database can use IMCU pruning to eliminate IMCUs that do not contain this value.

Compression

Traditionally, the goal of compression is to save space. In the IM column store, the goal of compression is to accelerate scans. The database automatically compresses columnar data using algorithms that allow WHERE clause predicates to be applied against the compressed formats. Depending on the type of compression applied, Oracle Database can scan data in its compressed format without decompressing it first. Therefore, the volume of data that the database must scan in the IM column store is less than the corresponding volume in the database buffer cache.

Vector processing

Each CPU core scans local in-memory columns. To process data as an array (set), the scans use SIMD vector instructions. For example, query can read a set of values in a single CPU instruction rather than read the values one by one. Vector scans by a CPU core are orders of magnitude faster than row scans.

For example, suppose a user executes the following ad hoc query:

```
SELECT cust_id, time_id, channel_id
FROM sales
WHERE prod_id BETWEEN 14 and 29
```

When using the buffer cache, the database would typically scan an index to find the product IDs, use the rowids to fetch the rows from disk into the buffer cache, and then discard the unwanted column values. Scanning data in row format in the buffer cache requires many CPU instructions, and can result in suboptimal CPU efficiency.

When using the IM column store, the database can scan only the requested sales columns, avoiding disk altogether. Scanning data in columnar format pipelines only necessary columns to the CPU, increasing efficiency. Each CPU core scans local inmemory columns using SIMD vector instructions.

See Also:

- "Dual-Format: Column and Row (page 2-1)"
- "Configuring the IM Column Store (page 1)" to learn how to configure the IM column store

1.3.2.2 Improved Performance for Joins

A **Bloom filter** is a low-memory data structure that tests membership in a set. The IM column store takes advantage of Bloom filters to improve the performance of joins.

Bloom filters speed up joins by converting predicates on small dimension tables to filters on large fact tables. This optimization is useful when performing a join of multiple dimensions with one large fact table. The dimension keys on fact tables have many repeat values. The scan performance and repeat value optimization speeds up joins by orders of magnitude.

See Also:

"About In-Memory Joins (page 6-1)"

1.3.2.3 Improved Performance for Aggregation

An important aspect of analytics is to determine patterns and trends by aggregating data. Aggregations and complex SQL queries run faster when data is stored in the IM column store.

In Oracle Database, aggregation typically involves a GROUP BY clause. Traditionally, the database used SORT and HASH operators. Starting in Oracle Database 12c Release 1 (12.1), the database offered VECTOR GROUP BY transformations to enable efficient inmemory, array-based aggregation.

During a fact table scan, the database accumulates aggregate values into in-memory arrays, and uses efficient algorithms to perform aggregation. Joins based on the primary key and foreign key relationships are optimized for both star schemas and snowflake schemas.

See Also:

- "Optimizing Joins with In-Memory Aggregation (page 7-1)"
- Oracle Database Data Warehousing Guide to learn more about SQL aggregation

1.3.3 Improved Performance for Mixed Workloads

Although OLTP applications do not benefit from accessing data in the IM column store, the dual-memory format can indirectly improves OLTP performance.

When all data is stored in rows, improving analytic query performance requires creating access structures. The standard approach is to create analytic indexes, materialized views, and OLAP cubes. For example, a table might require 3 indexes to improve the performance of the OLTP application (1 primary key and 2 foreign key

indexes) and 10-20 additional indexes to improve the performance of the analytic queries. While this technique can improve analytic query performance, it slows down OLTP performance. Inserting a row into the table requires modifying all indexes on the table. As the number of indexes increases, insertion speed decreases.

When you populate data into the IM column store, you can drop analytic access structures. This technique reduces storage space and processing overhead because fewer indexes, materialized views, and OLAP cubes are required. For example, an insert results in modifying 1-3 indexes instead of 11-23 indexes.

While the IM column store can drastically improve performance for analytic queries in business applications, ad-hoc analytic queries, and data warehouse workloads, pure OLTP databases that perform short transactions using index lookups benefit less. The IM column store does not improve performance for the following types of queries:

- A query with complex predicates
- A query that selects a large number of columns
- A query that returns a large number of rows

See Also:

Oracle Database Data Warehousing Guide to learn more about physical data warehouse design

1.3.4 High Availability Support

The IM column store is fully integrated into Oracle Database. All High Availability features are supported.

The columnar format does not change the Oracle database on-disk storage format. Thus, buffer cache modifications and redo logging function in the same way. Features such as RMAN, Oracle Data Guard, and Oracle ASM are fully supported.

In an Oracle Real Application Clusters (Oracle RAC) environment, each node has its own IM column store by default. Depending on your requirements, you can populate objects in different ways:

- Different tables are populated on every node. For example, the sales fact table is on one node, whereas the products dimension table is on a different node.
- A single table is distributed among different nodes. For example, different partitions of the same hash-partitioned table are on different nodes, or different rowid ranges of a single nonpartitioned table are on different nodes.
- Some objects appear in the IM column store on every node. For example, you
 might populate the products dimension table in every node, but distribute
 partitions of the sales fact table across different nodes.

See Also:

- "High Availability and the IM Column Store (page 1)"
- Oracle Database High Availability Overview for an introduction to high availability

1.3.5 Ease of Adoption

Database In-Memory is simple to implement, and requires no application changes. Key aspects of Database In-Memory adoption include:

• Ease of deployment

No user-managed data migration is required. The database stores data in row format on disk and automatically converts row data into columnar format when populating the IM column store.

Compatibility with existing applications

No application changes are required. The optimizer automatically takes advantage of the columnar format. If your application connects to the database and issues SQL, then it can benefit from Database In-Memory features.

Full SQL compatibility

Database In-Memory places no restrictions on SQL. Analytic queries can benefit whether they use Oracle analytic functions or customized PL/SQL code.

· Ease of use

No complex setup is required. The INMEMORY_SIZE initialization parameter specifies the amount of memory reserved for use by the IM column store. The INMEMORY clause in DDL statements specifies the objects or columns to be populated into the IM column store. By configuring the IM column store, you can immediately improve the performance of existing analytic workloads and ad-hoc queries.

See Also:

- "Enabling and Sizing the IM Column Store (page 3-1)" to learn how to enable the IM column store
- *Oracle Database Reference* to learn about the INMEMORY_SIZE and INMEMORY_FORCE initialization parameters

1.4 Prerequisites for Database In-Memory

The Oracle Database In-Memory option is required for all Database In-Memory features. No special hardware is required for an IM column store.

Prerequisites include:

- The IM column store requires a minimum of 100 MB of memory. The store size is included in MEMORY_TARGET. See "Estimating the Required Size of the IM Column Store (page 3-2)".
- For Oracle RAC databases, the DUPLICATE and DUPLICATE ALL options require Oracle Engineered Systems. See "Deploying IM Column Stores in Oracle RAC (page 10-1)".

See Also:

Oracle Database Licensing Information for all licensing-related information

1.5 Principal Tasks for Database In-Memory

For queries to benefit from the IM column store, the only *required* tasks are specifying a size for the IM column store, and specifying objects and columns for population. Query optimization and availability features require additional configuration.

Principal Tasks for Configuring the IM Column Store

The principal tasks are:

- Enable the IM column store by specifying its size.
 See "Enabling the IM Column Store for a Database (page 3-3)".
- Specify tables, columns, tablespaces, or materialized views for population into the IM column store.

See "Enabling Objects for In-Memory Population (page 4-1)".

• Optionally, you can create Automatic Data Optimization (ADO) policies to set INMEMORY attributes on objects in the IM column store. For example, a policy can evict the sales table from the IM column store after 10 days of no access. Inmemory ADO features require the initialization parameter settings HEAT_MAP=ON and a nonzero setting for INMEMORY_SIZE.

See "Enabling ADO for the IM Column Store (page 4-26)".

Principal Tasks for Optimizing In-Memory Queries

In-memory query optimizations are not required for the IM column store to function. The following optimization tasks are optional:

Manage automatic detection of IM expressions in the IM column store by using the
DBMS_INMEMORY_ADMIN package. For example, invoke the
IME_CAPTURE_EXPRESSIONS procedure to define the period of time in which the
database can identify "hot" expressions, and then gradually populate them. The
INMEMORY_EXPRESSIONS_USAGE initialization parameter controls the type of IM
expression that the database can populate: static, dynamic, or both.

See "INMEMORY_EXPRESSIONS_USAGE (page 5-9)".

• Define join groups using the CREATE INMEMORY JOIN GROUP statement. Candidates are columns that are frequently paired in a join predicate, for example, a column joining a fact and dimension table.

See "Creating Join Groups (page 6-7)".

• If necessary for a particular query block, specify the VECTOR_TRANSFORM hint to enable in-memory aggregation, or NO_VECTOR_TRANSFORM to disable it. Inmemory aggregation is an automatically enabled feature that cannot be controlled with initialization parameters or DDL.

See "Controls for IM Aggregation (page 7-14)".

• Limit the number of IMCUs updated through trickle repopulation within a two-minute interval by setting the initialization parameter

INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT. You can disable trickle repopulation by setting this initialization parameter to 0.

See "Threshold-Based and Trickle Repopulation (page 8-7)".

Principal Tasks for Managing Availability

The principal tasks are:

 Specify an In-Memory FastStart (IM FastStart) tablespace using the DBMS_INMEMORY_ADMIN.ENABLE_FASTSTART procedure. IM FastStart optimizes the population of database objects in the IM column store when the database is restarted. IM FastStart stores information on disk for faster population of the IM column store.

See "Enabling IM FastStart for the IM Column Store (page 9-5)".

For an object or tablespace, specify INMEMORY in DDL statement with the
DISTRIBUTE or DUPLICATE keywords to control the distribution of data in Oracle
RAC. By default, each In-Memory object is distributed among the Oracle RAC
instances, effectively employing a share-nothing architecture for the IM column
store.

See "Deploying IM Column Stores in Oracle RAC (page 10-1)".

In an Oracle Data Guard environment, you can use the same Database In-Memory
initialization parameters and statements on a primary or standby database. For
example, you can enable the IM column store on both a primary and standby
database by setting INMEMORY_SIZE. Optionally, use the INMEMORY
DISTRIBUTE FOR SERVICE clause in DDL to populate a different set of data in
the IM column store on the primary and standby databases.

See "About In-Memory Population (page 4-1)".

1.6 Tools for the IM Column Store

No special tools or utilities are required to manage the IM column store or other Database In-Memory features. Administrative tools such as SQL*Plus, SQL Developer, and Oracle Enterprise Manager (Enterprise Manager) are fully supported.

This section describes tools that have specific Database In-Memory feature support:

In-Memory Advisor (page 1-13)

The **In-Memory Advisor** is a downloadable PL/SQL package that analyzes the analytical processing workload in your database. This advisor recommends a size for the IM column store and a list of objects that would benefit from In-Memory population.

Cloud Control Pages for the IM Column Store (page 1-13)

Enterprise Manager Cloud Control (Cloud Control) provides the In-Memory Column Store Central Home page. This page gives a dashboard interface to the IM column store.

Oracle Compression Advisor (page 1-14)

Oracle Compression Advisor estimates the compression ratio that you can realize using the MEMCOMPRESS clause. The advisor uses the DBMS_COMPRESSION interface.

Oracle Data Pump and the IM Column Store (page 1-14)

You can import database objects that are enabled for the IM column store using the TRANSFORM=INMEMORY: y option of the impdp command.

1.6.1 In-Memory Advisor

The **In-Memory Advisor** is a downloadable PL/SQL package that analyzes the analytical processing workload in your database. This advisor recommends a size for the IM column store and a list of objects that would benefit from In-Memory population.

The In-Memory Advisor differentiates analytics processing from other database activity based upon SQL plan cardinality, Active Session History (ASH), parallel query usage, and other statistics. The In-Memory Advisor estimates the size of objects in the IM column store based on statistics and heuristic compression factors.

The In-Memory Advisor estimates analytic processing performance improvement factors based on the following:

- Elimination of wait events such as user I/O waits, cluster transfer waits, and buffer cache latch waits
- Query processing advantages related to specific compression types
- Decompression cost heuristics for specific compression types
- SQL plan cardinality, number of columns in the result set, and so on

The output of the In-Memory Advisor is a report with recommendations. The advisor also generates a SQL*Plus script that alters the recommended objects with the INMEMORY clause.

The In-Memory Advisor is *not* included in the stored PL/SQL packages. You must download it from Oracle Support.

See Also:

My Oracle Support note 1965343.1 to learn more about the In-Memory Advisor:

https://support.oracle.com/CSP/main/article?cmd=show&type=NOT&id=1965343.1

1.6.2 Cloud Control Pages for the IM Column Store

Enterprise Manager Cloud Control (Cloud Control) provides the In-Memory Column Store Central Home page. This page gives a dashboard interface to the IM column store.

Use this page to monitor in-memory support for database objects such as tables, indexes, partitions and tablespaces. You can view In-Memory functionality for objects and monitor their In-Memory usage statistics. Unless otherwise stated, this manual describes the command-line interface to Database In-Memory features.

See Also:

"Using IM Column Store In Cloud Control (page A-1)" explains how to use Cloud Control to manage the IM column store.

1.6.3 Oracle Compression Advisor

Oracle Compression Advisor estimates the compression ratio that you can realize using the MEMCOMPRESS clause. The advisor uses the DBMS_COMPRESSION interface.

See Also:

- "Oracle Compression Advisor (page 4-11)"
- Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS COMPRESSION

1.6.4 Oracle Data Pump and the IM Column Store

You can import database objects that are enabled for the IM column store using the TRANSFORM=INMEMORY: y option of the impdp command.

With this option, Oracle Data Pump keeps the IM column store clause for all objects that have one. When the TRANSFORM=INMEMORY:n option is specified, Data Pump drops the IM column store clause from all objects that have one.

You can also use the TRANSFORM=INMEMORY_CLAUSE: string option to override the IM column store clause for a database object in the dump file during import. For example, you can use this option to change the IM column store compression for an imported database object.

Video:

Oracle Database 12c demos: In-Memory Column Store Monitored and Oracle Data Pump

See Also:

Oracle Database Utilities for more information about the TRANSFORM impdb parameter

In-Memory Column Store Architecture

The **In-Memory Column Store** (IM column store) stores tables and partitions in memory using a columnar format optimized for rapid scans. Oracle Database uses a sophisticated architecture to manage data in columnar and row formats simultaneously.

This chapter contains the following topics:

Dual-Format: Column and Row (page 2-1)

When you enable an IM column store, the SGA manages data in separate locations: the In-Memory Area and the database buffer cache.

In-Memory Storage Units (page 2-7)

The IM column store manages both data and metadata in optimized storage units, not in traditional Oracle data blocks.

Expression Statistics Store (ESS) (page 2-18)

The Expression Statistics Store (ESS) is a repository maintained by the optimizer to store statistics about expression evaluation. The ESS resides in the SGA and also persists on disk.

In-Memory Process Architecture (page 2-19)

In response to queries and DML, server processes scan columnar data and update SMU metadata. Background processes populate row data from disk into the IM column store.

CPU Architecture: SIMD Vector Processing (page 2-21)

For data that does need to be scanned in the IM column store, the database uses SIMD (single instruction, multiple data) vector processing.

2.1 Dual-Format: Column and Row


When you enable an IM column store, the SGA manages data in separate locations: the In-Memory Area and the database buffer cache.

The IM column store encodes data in a columnar format: each column is a separate structure. The columns are stored contiguously, which optimizes them for analytic queries. The database buffer cache can modify objects that are also populated in the IM column store. However, the buffer cache stores data in the traditional row format. Data blocks store the rows contiguously, optimizing them for transactions.

The following figure illustrates the difference between row-based storage and columnar storage.

Figure 2-1 Columnar and Row-Based Storage

Rows Stored Contiguously



Columns Stored Contiguously



This section creates the following topics:

Columnar Data in the In-Memory Area (page 2-2)

The **In-Memory Area** is an optional SGA component that contains the IM column store.

Row Data in the Database Buffer Cache (page 2-5)

The database buffer cache stores and processes data blocks in the same way whether the IM column store is enabled or disabled. Buffer I/O and buffer pools function exactly the same.

2.1.1 Columnar Data in the In-Memory Area

The **In-Memory Area** is an optional SGA component that contains the IM column store.

This section contains the following topics:

Size of the In-Memory Area (page 2-2)

The In-Memory Area is controlled by the INMEMORY_SIZE initialization parameter. By default, the size of the In-Memory Area is 0, which means the IM column store is disabled.

Memory Pools in the In-Memory Area (page 2-4)

The In-Memory Area is divided into subpools for columnar data and metadata.

2.1.1.1 Size of the In-Memory Area

The In-Memory Area is controlled by the INMEMORY_SIZE initialization parameter. By default, the size of the In-Memory Area is 0, which means the IM column store is disabled.

To enable the IM column store, set the In-Memory Area to at least 100 MB. The size is shown in V\$SGA.

The In-Memory Area is subtracted from the SGA_TARGET initialization parameter setting. For example, if you set SGA_TARGET to 10 GB, and if you set the INMEMORY_SIZE to 4 GB, then 40% of the SGA_TARGET setting is allocated to the In-Memory Area. The following graphic illustrates the relationship.

SGA_MAX_SIZE Unused SGA_TARGET **SGA** Dynamic INMEMORY SIZE **In-Memory Area** Static

Figure 2-2 INMEMORY SIZE and SGA TARGET

Unlike the other components of the SGA, including the buffer cache and the shared pool, the In-Memory Area size is not controlled by automatic memory management. The database does not automatically shrink the In-Memory Area when the buffer cache or shared pool requires more memory, or increase the In-Memory Area when it runs out of space. You can only increase the size of the In-Memory Area by manually adjusting the INMEMORY_SIZE initialization parameter.

Starting in Oracle Database 12c Release 2 (12.2), you can dynamically increase INMEMORY_SIZE by using the ALTER SYSTEM statement. The database allocates increased memory when the following conditions are met:

- Free memory is available in the SGA.
- The new size for INMEMORY_SIZE is at least 128 MB greater than the current setting.

Note:

You cannot use ALTER SYSTEM to reduce INMEMORY_SIZE.

The V\$INMEMORY_AREA and V\$SGA views immediately reflect the change.

See Also:

- "Increasing the Size of the IM Column Store Dynamically (page 3-4)"
- Oracle Database Administrator's Guide to learn more about automatic memory management
- Oracle Database Reference to learn about INMEMORY_SIZE, V \$INMEMORY_AREA, and V\$SGA

2.1.1.2 Memory Pools in the In-Memory Area

The In-Memory Area is divided into subpools for columnar data and metadata.

The In-Memory area is subdivided into the following subpools:


The columnar data pool

This subpool stores the IMCUs, which contain the columnar data. The V \$INMEMORY_AREA.POOL column identifies this subpool as 1MB POOL, as shown in Example 2-1 (page 2-4).

• The metadata pool

This subpool stores metadata about the objects that reside in the IM column store. The V\$INMEMORY_AREA.POOL column identifies this subpool as 64KB POOL, as shown in Example 2-1 (page 2-4).

Figure 2-3 Subpools in the In-Memory Area



The database determines the relative size of the two subpools using internal heuristics. The database allocates the majority of space in the In-Memory Area to the columnar data pool (1 MB pool).

Note:

Oracle Database automatically determines the subpool sizes. You cannot change the space allocations.

Example 2-1 V\$INMEMORY_AREA View

This example queries the V\$INMEMORY_AREA view to determine the amount of available memory in each subpool (sample output included):

```
COL POOL FORMAT a9
COL POPULATE_STATUS FORMAT a15
SSELECT POOL, TRUNC(ALLOC_BYTES/(1024*1024*1024),2) "ALLOC_GB",
TRUNC(USED_BYTES/(1024*1024*1024),2) "USED_GB",
```

POPULATE_STATUS FROM V\$INMEMORY_AREA;

POOL	ALLOC_GB	USED_GB	POPULATE_STATUS
1MB POOL	7.99	0	DONE
64KB POOL	1.98	0	DONE

The current size of the In-Memory area is visible in V\$SGA:

```
SELECT NAME, VALUE/(1024*1024*1024) "SIZE_IN_GB"
FROM VSSGA
WHERE NAME LIKE '%Mem%';
NAME
               SIZE_IN_GB
_____
In-Memory Area
               1.0
```

In this example, the memory allocated to the subpools is 9.97 GB, whereas the size of the In-Memory Area is 10 GB. The database uses a small percentage of memory for internal management structures.

See Also: Oracle Database Reference to learn about V\$INMEMORY_AREA

2.1.2 Row Data in the Database Buffer Cache

The database buffer cache stores and processes data blocks in the same way whether the IM column store is enabled or disabled. Buffer I/O and buffer pools function exactly the same.

The IM column store enables data to be simultaneously populated in the SGA in both the traditional row format (the buffer cache) and the columnar format. The database transparently sends OLTP queries (such as primary key lookups) to the buffer cache, and analytic and reporting queries to the IM column store. When fetching data, Oracle Database can also read data from both memory areas within the same query.


Note:

In the execution plan, the operation TABLE ACCESS IN MEMORY FULL indicates that some or all data is accessed in the IM column store.

The dual-format architecture does not double memory requirements. The buffer cache is optimized to run with a much smaller size than the size of the database.

The following figure shows a sample IM column store. The database stores the sh.sales table on disk in traditional row format. The SGA stores the data in columnar format in the IM column store, and in row format in the database buffer cache.

Figure 2-4 IM Column Store



Every on-disk data format for permanent, heap-organized tables is supported by the IM column store. The columnar format does not affect the format of data stored in data files or in the buffer cache, nor does it affect undo data and online redo logging.

The database processes DML modifications in the same way, regardless of whether the IM column store is enabled, by updating the buffer cache, online redo log, and undo tablespace. However, the database uses an internal mechanism to track changes and ensure that the IM column store is consistent with the rest of the database. For example, if the sales table is populated in the IM column store, and if an application

updates a row in sales, then the database automatically keeps the copy of the sales table in the IM column store transactionally consistent. A query that accesses the IM column store always returns the same results for a query that accesses the buffer cache.

See Also:


Oracle Database Concepts to learn more about the database buffer cache

2.2 In-Memory Storage Units

The IM column store manages both data and metadata in optimized storage units, not in traditional Oracle data blocks.

Oracle Database maintains the storage units in the In-Memory Area. The following graphic gives an overview of the In-Memory Area and the database processes that interact with it. The remaining chapter describes the various memory components.

Figure 2-5 IM Column Store: Memory and Process Architecture



This section contains the following topics:

In-Memory Compression Units (IMCUs) (page 2-8)

An **In-Memory Compression Unit (IMCU)** is a compressed, read-only storage unit that contains data for one or more columns.

Snapshot Metadata Units (SMUs) (page 2-15)

A Snapshot Metadata Unit (SMU) contains metadata and transactional information for an associated IMCU.

In-Memory Expression Units (IMEUs) (page 2-17)

An **In-Memory Expression Unit** (IMEU) is a storage container for materialized **In-Memory Expressions** (IM expressions) and user-defined virtual columns.

2.2.1 In-Memory Compression Units (IMCUs)

An **In-Memory Compression Unit (IMCU)** is a compressed, read-only storage unit that contains data for one or more columns.

An IMCU is analogous to a tablespace extent. An IMCU has two parts: a set of Column Compression Units (CUs), and a header that contains metadata such as the IM storage index.

This section contains the following topics:

IMCUs and Schema Objects (page 2-8)

The IM column store stores data for a single object (table, partition, materialized view) in a set of IMCUs. An IMCU stores columnar data for one and only one object.

Column Compression Units (CUs) (page 2-12)

A **Column Compression Unit (CU)** is contiguous storage for a single column in an IMCU. Every IMCU has one or more CUs.

In-Memory Storage Indexes (page 2-14)

Every IMCU header automatically creates and manages **In-Memory Storage Indexes** (IM storage indexes) for its CUs. An IM storage index stores the minimum and maximum for all columns within the IMCU.

2.2.1.1 IMCUs and Schema Objects

The IM column store stores data for a single object (table, partition, materialized view) in a set of IMCUs. An IMCU stores columnar data for one and only one object.

For an object specified as INMEMORY, every column listed in the INMEMORY clause is included in every IMCU. For example, the sh.sales table has 7 columns, as shown in Figure 2-6 (page 2-10). The following DDL statement specifies the table as INMEMORY, which means that every IMCU for sales includes columnar data for these 7 columns:


ALTER TABLE sh.sales INMEMORY MEMCOMPRESS FOR QUERY LOW;

To apply the INMEMORY attribute to a subset of columns in a segment, you must specify all columns as INMEMORY in one DDL statement, and then issue a second DDL statement to specify the NO INMEMORY attribute on the *excluded* columns. For example, the following statement specifies that 3 columns in sh.sales are NO INMEMORY, which means that the other 4 columns in the table retain their INMEMORY attribute:

ALTER TABLE sh.sales INMEMORY MEMCOMPRESS FOR QUERY LOW NO INMEMORY (promo_id, quantity_sold, amount_sold);

The following graphic represents three tables from the sh schema populated in the IM column store: customers, products, and sales. In this example, each table has a different number of columns specified INMEMORY. The IMCUs for each table include only data for the specified columns.

Figure 2-6 Columns and IMCUs



This section contains the following topics:

In-Memory Compression (page 2-11)

The IM column store uses special compression formats optimized for access speed rather than storage reduction. The columnar format enables queries to execute directly against the compressed columns.

IMCUs and Rows (page 2-11)

Each IMCU contains all column values (including nulls) for a subset of rows in a table segment. A subset of rows is called a *granule*.

See Also:

Oracle Database SQL Language Reference to learn about the ALTER TABLE statement

2.2.1.1.1 In-Memory Compression

The IM column store uses special compression formats optimized for access speed rather than storage reduction. The columnar format enables queries to execute directly against the compressed columns.

Compression enables scanning and filtering operations to process a much smaller amount of data, which optimizes query performance. Oracle Database only decompresses data when it is required for the result set.

The compression applied in the IM column store is closely related to Hybrid Columnar Compression. Both technologies process column vectors. The primary difference is that the column vectors for the IM column store are optimized for SIMD vector processing, whereas the column vectors for Hybrid Columnar Compression are optimized for disk storage.

When you enable an object for population into the IM column store, you specify the type of compression in the INMEMORY clause: FOR DML, FOR QUERY (LOW or HIGH), FOR CAPACITY (LOW or HIGH), or NONE.

See Also:

- "Controls for In-Memory Population (page 4-6)"
- *Oracle Database Concepts* to learn more about Hybrid Columnar Compression

2.2.1.1.2 IMCUs and Rows

Each IMCU contains all column values (including nulls) for a subset of rows in a table segment. A subset of rows is called a *granule*.

All IMCUs for a given segment contain approximately the same number of rows. Oracle Database determines the size of a granule automatically depending on data type, data format, and compression type. A higher compression level results in more rows in the IMCU.

A one-to-many mapping exists between an IMCU and a set of database blocks. As illustrated in Example 2-2 (page 2-12), each IMCU stores the values for columns for a different set of blocks.

The columns in an IMCU are not sorted. Oracle Database populates them in the order that they are read from disk.

The number of rows in an IMCU dictates the amount of space an IMCU consumes. If the target number of rows causes an IMCU to grow beyond the amount of contiguous 1 MB extents available in the 1 MB pool, then the IMCU creates additional extents (pieces) to hold the remaining column CUs. An IMCU always allocates space in 1 MB increments.

Example 2-2 IMCUs and Row Subsets

In this simplified example, only the following 4 columns of the customers table have the INMEMORY attribute: cust_id, cust_first_name, cust_last_name, and cust_gender. Only 5 rows exist in the table, stored in 2 data blocks. Conceptually, the first data block stores its rows as follows:

```
82, Madeline, Li, F; 37004, Abel, Embrey, M; 1714, Hardy, Gentle, M
```

The second data block stores rows as follows:

```
100439, Uma, Campbell, F; 3047, Lucia, Downey, F
```

Assume IMCU 1 stores the data for the first data block. In this case, the <code>cust_id</code> column values for the 3 rows in this data block stores are stored "vertically" within a CU as follows:

```
82
37004
1714
```

IMCU 2 stores the data from the second data block. The cust_id column values for these 2 rows are stored within a CU as follows:

```
100439
3047
```

Because the <code>cust_id</code> value is the first value for each row in the data block, the <code>cust_id</code> column is in the first position within the IMCU. Columns always occupy the same position, so Oracle Database can reconstruct the rows by reading the IMCUs for a segment.

See Also:

"Controls for In-Memory Population (page 4-6)"

2.2.1.2 Column Compression Units (CUs)

A **Column Compression Unit (CU)** is contiguous storage for a single column in an IMCU. Every IMCU has one or more CUs.

This section contains the following topics:

```
Structure of a CU (page 2-12)
```

A CU is divided into a body and a header.

```
Local Dictionary (page 2-13)
```

In a CU, the local dictionary has a list of distinct values and their corresponding dictionary codes.

2.2.1.2.1 Structure of a CU

A CU is divided into a body and a header.

The body of every CU stores the column values for the range of rows included in the IMCU. The header contains metadata about the values stored in the CU body, for example, the minimum and maximum value within the CU. It may also contain a local dictionary, which is a sorted list of the distinct values in that column and their corresponding dictionary codes.

The following figure shows an IMCU with 4 CUs for the sales table: prod_id, cust_id, time_id, and channel_id. Each CU stores the column values for the range of rows included in the IMCU.




Figure 2-7 CUs in an IMCU

The CUs store values in rowid order. For this reason, the database can answer queries by "stitching" the rows back together. For example, an application issues the following query:

```
SELECT cust_id, time_id, channel_id
FROM sales
WHERE prod_id =5;
```


The database begins by scanning the prod_id column for entries with the value 5. Assume that the database finds 5 in position two in the prod_id column. The database now must find the corresponding cust_id, time_id, and channel_id for this row. Because the CUs store data in rowid order, the database can find the corresponding cust_id, time_id, and channel_id values in position 2 in those columns. Thus, to answer the query, the database must extract the values from position 2 in the cust_id, time_id, and channel_id columns, and then stitch the row back together to return it to the end user.

2.2.1.2.2 Local Dictionary

In a CU, the local dictionary has a list of distinct values and their corresponding dictionary codes.

The local dictionary stores the symbol contained in the column. The following figure illustrates how a CU stores a name column in a vehicles table.

Figure 2-8 Local Dictionary



In the preceding figure, the CU contains only 7 rows. Every distinct value in this CU, such as Cadillac or Audi, is assigned a different dictionary code, such as 2 for Cadillac and 0 for Audi. The CU stores the dictionary code rather than the original value.

Note:

When the database uses a common dictionary for a join group, the local dictionary contains *references* to the common dictionary rather than the *symbols*. For example, rather than storing the values Audi, BWM, and Cadillac for the vehicles.name column, the local dictionary stores dictionary codes such as 101, 220, and 66.

The CU header contains the minimum and maximum values for the column. In this example, the minimum value is Audi and the maximum value is Cadillac. The local dictionary stores the list of distinct values: Audi, BMW, and Cadillac. Their corresponding dictionary codes (0, 1, and 2) are implicit. The local dictionary for a CU in each IMCU is independent of the local dictionaries in other IMCUs.

If a query filters on Audi automobiles, then the database scans this IMCU for only 0 codes.

See Also:

"How a Join Group Uses a Common Dictionary (page 6-4)"


2.2.1.3 In-Memory Storage Indexes


Every IMCU header automatically creates and manages **In-Memory Storage Indexes** (IM storage indexes) for its CUs. An IM storage index stores the minimum and maximum for all columns within the IMCU.


For example, sales is populated in the IM column store. Every IMCU for this table has all columns. The sales.prod_id column is stored in a separate CU within every IMCU. The IMCU header has the minimum and maximum values of each prod_id CU (and every other CU).


To eliminate unnecessary scans, the database can perform IMCU pruning based on SQL filter predicates. The database scans only the IMCUs that satisfy the query predicate, as shown in the WHERE prod_id > 14 AND prod_id < 29 example in the following graphic.

Figure 2-9 Storage Index for Columnar Data









2.2.2 Snapshot Metadata Units (SMUs)

A Snapshot Metadata Unit (SMU) contains metadata and transactional information for an associated IMCU.

This section contains the following topics:

IMCUs and SMUs (page 2-16)

The columnar pool of the In-Memory Area stores the actual data: IMCUs and IMEUs. The metadata pool in the In-Memory Area stores the SMUs.

Transaction Journal (page 2-16)


Every SMU contains a **transaction journal**. The database uses the transaction journal to keep the IMCU transactionally consistent.

2.2.2.1 IMCUs and SMUs

The columnar pool of the In-Memory Area stores the actual data: IMCUs and IMEUs. The metadata pool in the In-Memory Area stores the SMUs.

Figure 2-10 IMCUs and SMUs

This figure shows IMCUs in the data pool, and SMUs in the metadata pool.



Every IMCU maps to a separate SMU. Thus, if the columnar data pool contains 100 IMCUs, then the metadata pool contains 100 SMUs. The SMUs store several types of metadata for their associated IMCUs, including the following:


- Object numbers
- Column numbers
- Mapping information for rows

2.2.2.2 Transaction Journal

Every SMU contains a **transaction journal**. The database uses the transaction journal to keep the IMCU transactionally consistent.

The database uses the buffer cache to process DML, just as when the IM column store is not enabled. For example, an UPDATE statement might modify a row in an IMCU. In this case, the database adds the rowid for the modified row to the transaction journal and marks it stale as of the SCN of the DML statement. If a query needs to accesses the new version of the row, then the database obtains the row from the database buffer cache.





The database achieves read consistency by merging the contents of the column, transaction journal, and buffer cache. When the IMCU is refreshed during repopulation, queries can access the up-to-date row directly from the IMCU.

See Also:

"Optimizing Repopulation of the IM Column Store (page 8-1)" for an indepth discussion of how the IM column store maintains transactional consistency

2.2.3 In-Memory Expression Units (IMEUs)

An **In-Memory Expression Unit** (IMEU) is a storage container for materialized **In-Memory Expressions** (IM expressions) and user-defined virtual columns.

The database treats materialized expressions just like other columns in the IMCU. Conceptually, an IMEU is a logical extension of its parent IMCU. Just as an IMCU can contain multiple columns, an IMEU can contain multiple virtual columns.

Every IMEU maps to exactly one IMCU, mapping to the same row set. The IMEU contains expression results for the data contained in its associated IMCU. When the IMCU is populated, the associated IMEU is also populated.

A typical IM expression involves one or more columns, possibly with constants, and has a one-to-one mapping with the rows in the table. For example, an IMCU for an employees table contains rows 1–1000 for the column weekly_salary. For the rows stored in this IMCU, the IMEU calculates the automatically detected IM expression weekly_salary*52, and the user-defined virtual column quarterly_salary defined as weekly_salary*12. The 3rd row down in the IMCU maps to the 3rd row down in the IMEU.

The IMEU is a logical extension of the IMCUs of a particular segment. By default, the IMEU inherits the INMEMORY clause properties, including Oracle Real Application Clusters (Oracle RAC) properties such as DISTRIBUTE and DUPLICATE, from the base segment. You can selectively enable or disable virtual columns for storage in IMEUs. You can also specify compression levels for different columns.

See Also:

- "About IM Virtual Columns (page 4-17)"
- "In-Memory Views (page 13-1)"

2.3 Expression Statistics Store (ESS)

The **Expression Statistics Store (ESS)** is a repository maintained by the optimizer to store statistics about expression evaluation. The ESS resides in the SGA and also persists on disk.

When an IM column store is enabled, the database leverages the ESS for its In-Memory Expressions (IM expressions) feature. However, the ESS is independent of the IM column store. The ESS is a permanent component of the database and cannot be disabled.

The database uses the ESS to determine whether an expression is "hot" (frequently accessed), and thus a candidate for an IM expression. During a hard parse of a query, the ESS looks for active expressions in the SELECT list, WHERE clause, GROUP BY clause, and so on.

For each segment, the ESS maintains expression statistics such as the following:

- Frequency of execution
- Cost of evaluation
- Timestamp evaluation

The optimizer assigns each expression a weighted score based on cost and the number of times it was evaluated. The values are approximate rather than exact. More active expressions have higher scores. The ESS maintains an internal list of the most frequently accessed expressions.

Control the behavior of IM expressions using the DBMS_INMEMORY_ADMIN package. For example, the IME_CAPTURE_EXPRESSIONS procedure prompts the database to identify and gradually populate the hottest expressions in the database. The IME_POPULATE_EXPRESSIONS procedure forces the database to populate the expressions immediately.

ESS information is stored in the data dictionary and exposed in the DBA_EXPRESSION_STATISTICS view. This view shows the metadata that the optimizer has sent to the ESS. IM expressions are exposed as system-generated virtual columns, prefixed by the string SYS_IME, in the DBA_IM_EXPRESSIONS view.

See Also:

- "About IM Expressions (page 5-1)"
- Oracle Database SQL Tuning Guide to learn more about ESS
- Oracle Database Reference to learn more about the DBA_EXPRESSION_STATISTICS view
- Oracle Database PL/SQL Packages and Types Reference to learn more about the DBMS_INMEMORY_ADMIN package

2.4 In-Memory Process Architecture

In response to queries and DML, server processes scan columnar data and update SMU metadata. Background processes populate row data from disk into the IM column store.

This section contains the following topics:

In-Memory Coordinator Process (IMCO) (page 2-19)

The In-Memory Coordinator Process (IMCO) manages many tasks for the IM column store. Its primary task is to initiate background population and repopulation of columnar data.

Space Management Worker Processes (Wnnn) (page 2-20)

Space Management Worker Processes (*Wnnn*) populate or repopulate data on behalf of IMCO.

2.4.1 In-Memory Coordinator Process (IMCO)

The In-Memory Coordinator Process (IMCO) manages many tasks for the IM column store. Its primary task is to initiate background population and repopulation of columnar data.

Population is a streaming mechanism, converting row data into columnar format, and then compressing it. IMCO automatically initiates population of INMEMORY objects with any priority other than NONE. When objects with priority NONE are accessed, IMCO populates them using Space Management Worker Process (*Wnnn*) processes.

The IMCO background process also initiates threshold-based repopulation of IM column store objects when they meet a staleness threshold. IMCO may instigate trickle repopulation for any IMCU in the IM column store that has stale entries but does not meet the staleness threshold.

Trickle repopulation occurs automatically in the background. The steps are as follows:

- 1. IMCO wakes up.
- **2.** IMCO determines whether population tasks need to be performed, including whether any stale entries exist in an IMCU.
- **3.** If IMCO finds stale entries, then it triggers a Space Management Worker Process to repopulate these entries in the IMCU.
- **4.** IMCO sleeps for two minutes, and then returns to Step 1.

See Also:

- "Optimizing Repopulation of the IM Column Store (page 8-1)"
- Oracle Database Reference to learn more about background processes

2.4.2 Space Management Worker Processes (Wnnn)

Space Management Worker Processes (Wnnn) populate or repopulate data on behalf of IMCO.

During population, Wnnn processes are responsible for creating IMCUs, SMUs, and IMEUs. When creating IMEUs, the worker processes perform the following tasks:

- Identify virtual columns for population
- Create virtual column values
- Compute values for each row, transform the data into columnar format, and compress it
- · Register the objects with the space layer
- Associate the IMEUs with their corresponding IMCUs

Note:

During IMEU creation, parent IMCUs remain available for queries.

During repopulation, the Wnnn processes create new versions of the IMCUs based on the existing IMCUs and transactions journals, while temporarily retaining the old versions. This mechanism is called double buffering.

The database can quickly move IM expressions in and out of the IM column store. For example, if an IMCU was created without an IMEU, then the database can add an IMEU later without forcing the IMCU to undergo the full repopulation mechanism.

The INMEMORY_MAX_POPULATE_SERVERS initialization parameter controls the maximum number of worker processes that can be started for population. The INMEMORY_TRICKLE_REPOPULATE_PERCENT initialization parameter controls the maximum percentage of time that worker processes can perform trickle repopulation.

See Also:

- "About In-Memory Population (page 4-1)"
- "About Repopulation of the IM Column Store (page 8-1)"
- "In-Memory Initialization Parameters (page 12-1)"
- Oracle Database Reference to learn more about background processes

2.5 CPU Architecture: SIMD Vector Processing

For data that does need to be scanned in the IM column store, the database uses SIMD (single instruction, multiple data) vector processing.

The IM column store maximizes the number of column entries that the CPU can load into the vector registers and evaluate. Instead of evaluating each entry in the column one at a time, the database evaluates a set of column values in a single CPU instruction. SIMD vector processing enables the database to scan billions of rows per second.

For example, an application issues a query to find the total number of orders in the sales table that use the promo_id value of 9999. The sales table resides in the IM column store. The query begins by scanning only the sales.promo_id column, as shown in the following diagram:




Figure 2-12 SIMD Vector Processing

The CPU evaluates the data as follows:

- 1. Loads the first 8 values (the number varies depending on data type and compression mode) from the promo_id column into the SIMD register, and then compares them with the value 9999 in a single instruction
- **2.** Discards the entries.
- **3.** Loads another 8 values into the SIMD register, and then continues in this way until it has evaluated all entries.

Part II

Configuring the IM Column Store

You can enable and size the In-Memory Column Store (IM column store). You can also populate objects into the IM column store.

This part contains the following chapters:

Enabling and Sizing the IM Column Store (page 3-1)

Enable the IM column store by specifying its size. You can also resize the IM column store, or disable it.

Enabling Objects for In-Memory Population (page 4-1)

This chapter explains how to enable and disable objects for population in the IM column store, including setting compression and priority options.

Enabling and Sizing the IM Column Store

Enable the IM column store by specifying its size. You can also resize the IM column store, or disable it.

This chapter contains the following topics:

Overview of Enabling the IM Column Store (page 3-1)

By default, the INMEMORY_SIZE initialization parameter is set to 0, which means the IM column store is disabled. To enable the IM column store, set the initialization parameter INMEMORY_SIZE to a non-zero value before restarting the instance.

Estimating the Required Size of the IM Column Store (page 3-2)

Estimate the size of the IM column store based on your requirements, and then resize the IM column store to meet those requirements. Applying compression can reduce memory size.

Enabling the IM Column Store for a Database (page 3-3)

Before tables or materialized views can be populated into the IM column store, you must enable the IM column store for the database.

Increasing the Size of the IM Column Store Dynamically (page 3-4)

When more memory is required for the IM column store, you can increase its size dynamically.

Disabling the IM Column Store (page 3-5)

You can disable the IM column store by setting the INMEMORY_SIZE initialization parameter to zero, and then reopening the database.

3.1 Overview of Enabling the IM Column Store

By default, the INMEMORY_SIZE initialization parameter is set to 0, which means the IM column store is disabled. To enable the IM column store, set the initialization parameter INMEMORY_SIZE to a non-zero value before restarting the instance.

You can dynamically increase the INMEMORY_SIZE size setting by using an ALTER SYSTEM statement.

By default, you must specify candidates for population in the IM column store using the INMEMORY clause of a CREATE or ALTER statement for a table, tablespace, or materialized view.

See Also:

- "In-Memory Initialization Parameters (page 12-1)"
- Oracle Database Reference to learn more about the INMEMORY_SIZE initialization parameter
- Oracle Database SQL Language Reference for more information about the INMEMORY clause

3.2 Estimating the Required Size of the IM Column Store

Estimate the size of the IM column store based on your requirements, and then resize the IM column store to meet those requirements. Applying compression can reduce memory size.

The amount of memory required by the IM column store depends on the database objects stored in it and the compression method applied on each object. When choosing a compression method for the INMEMORY objects, balance the performance benefits against the amount of available memory:

- To make the greatest reduction in memory size, choose the FOR CAPACITY HIGH or FOR CAPACITY LOW compression methods. However, these options require additional CPU during query execution to decompress the data.
- To get the best query performance, choose the FOR QUERY HIGH or FOR QUERY LOW compression methods. However, these options consume more memory.

When sizing the IM column store, consider the following guidelines:

1. For every object to be populated into the IM column store, estimate the amount of memory it consumes.

Oracle Compression Advisor estimates the compression ratio that you can realize using the MEMCOMPRESS clause. The advisor uses the DBMS_COMPRESSION interface.

2. Add the individual amounts to together.

Note:

After population, V\$IM_SEGMENTS shows the actual size of the objects on disk and their size in the IM column store. You can use this information to calculate the compression ratio for the populated objects. However, if the objects were compressed on disk, then this query does not show the correct compression ratio.

3. Add additional space to account for the growth of database objects, and to store updated versions of rows after DML operations.

The minimum amount for dynamic resizing is 128 MB.

See Also:

- "IM Column Store Compression Methods (page 4-9)"
- "Enabling the IM Column Store for a Database (page 3-3)"
- "Increasing the Size of the IM Column Store Dynamically (page 3-4)"
- Oracle Database Reference to learn about V\$IM_SEGMENTS
- Oracle Database Administrator's Guide to learn how to estimate compression ratio using Compression Advisor

3.3 Enabling the IM Column Store for a Database

Before tables or materialized views can be populated into the IM column store, you must enable the IM column store for the database.

Prerequisites

This task assumes that the following:

- The database is open.
- The COMPATIBLE initialization parameter is set to 12.1.0 or higher.
- The INMEMORY_SIZE initialization parameter is set to 0 (default).

To enable the IM column store:

- **1.** In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- **2.** Set the INMEMORY_SIZE initialization parameter to a non-zero value.

The minimum setting is 100M.

When you set this initialization parameter in a server parameter file (SPFILE) using the ALTER SYSTEM statement, you must specify SCOPE=SPFILE.

For example, the following statement sets the In-Memory Area size to 10 GB:

```
ALTER SYSTEM SET INMEMORY_SIZE = 10G SCOPE=SPFILE;
```

3. Shut down the database, and then reopen it.

You must reopen the database to initialize the IM column store in the SGA.

4. Optionally, check the amount of memory currently allocated for the IM column store:

SHOW PARAMETER INMEMORY_SIZE

Note: After the IM column store is enabled, you can increase its size dynamically without reopening the database.

Example 3-1 Enabling the IM Column Store

Assume that the INMEMORY_SIZE initialization parameter is set to 0. The following SQL*Plus example sets INMEMORY_SIZE to 10 GB, shuts down the database instance, and then reopens the database so that the change can take effect:

SQL> SHOW PARAMETER INMEMORY_SIZE

NAME	TYPE	VALUE
inmemory_size	big integer	0

SQL> ALTER SYSTEM SET INMEMORY_SIZE=10G SCOPE=SPFILE;

System altered.

SQL> SHUTDOWN IMMEDIATE Database closed. Database dismounted. ORACLE instance shut down.

SQL> STARTUP

ORACLE instance started.

Total System Global Area 11525947392 bytes
Fixed Size 8213456 bytes
Variable Size 754977840 bytes
Database Buffers 16777216 bytes
Redo Buffers 8560640 bytes
In-Memory Area 10737418240 bytes

Database mounted.
Database opened.

SQL> SHOW PARAMETER INMEMORY_SIZE

NAME	TYPE	VALUE
inmemory_size	big integer	10G

See Also:

- "Multiple IM Column Stores (page 10-2)"
- Oracle Database Upgrade Guide for information about setting the database compatibility level
- Oracle Database Reference for more information about the INMEMORY_SIZE initialization parameter

3.4 Increasing the Size of the IM Column Store Dynamically

When more memory is required for the IM column store, you can increase its size dynamically.

The size of the IM column store cannot be decreased dynamically. If you set INMEMORY_SIZE to a value smaller than its current setting, then you must specify SCOPE=SPFILE in the ALTER SYSTEM statement. If you set this parameter by specifying SCOPE=SPFILE, then you must restart the database for the change to take effect.

Prerequisites

To increase the size of the IM column store dynamically, you must meet the following prerequisites:

- The column store must be enabled.
- The compatibility level must be 12.2.0 or higher.
- The database instances must be started with an SPFILE.
- The new size of the IM column store must be at least 128 megabytes greater than the current INMEMORY_SIZE setting.
- 1. In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- 2. Optionally, check the amount of memory currently allocated for the IM column store:

```
SHOW PARAMETER INMEMORY_SIZE
```

3. Set the INMEMORY_SIZE initialization parameter to a value greater than the current size of the IM column store with an ALTER SYSTEM statement that specifies SCOPE=BOTH or SCOPE=MEMORY.

When you set this parameter dynamically, you must set it to a value that is higher than its current value, and there must be enough memory available in the SGA to increase the size of the IM column store dynamically to the new value.

For example, the following statement sets INMEMORY_SIZE to 500M dynamically:

ALTER SYSTEM SET INMEMORY_SIZE = 500M SCOPE=BOTH;

See Also:

- "Enabling the IM Column Store for a Database (page 3-3)"
- Oracle Database Reference for more information about the INMEMORY_SIZE initialization parameter

3.5 Disabling the IM Column Store

You can disable the IM column store by setting the INMEMORY_SIZE initialization parameter to zero, and then reopening the database.

Assumptions

This task assumes that the IM column store is enabled in an open database.

To disable the IM column store:

- Set the INMEMORY_SIZE initialization parameter to 0 in the server parameter file (SPFILE).
- Shut down the database.

3. Start a database instance, and then open the database.

See Also:

 $\label{thm:condition} \textit{Oracle Database Reference} \ \text{for information about the } \ \texttt{INMEMORY_SIZE} \\ initialization \ parameter$

Enabling Objects for In-Memory Population

This chapter explains how to enable and disable objects for population in the IM column store, including setting compression and priority options.

This chapter contains the following topics:

About In-Memory Population (page 4-1)

In-Memory population (population) occurs when the database reads existing row-format data from disk, transforms it into columnar format, and then stores it in the IM column store. Only objects with the INMEMORY attribute are eligible for population.

Enabling and Disabling Tables for the IM Column Store (page 4-11)

Enable a table for the IM column store by including an INMEMORY clause in a CREATE TABLE or ALTER TABLE statement. Disable a table for the IM column store by including a NO INMEMORY clause in a CREATE TABLE or ALTER TABLE statement.

Enabling and Disabling Columns for In-Memory Tables (page 4-16)

You can specify the INMEMORY clause for individual columns. Both nonvirtual columns and In-Memory virtual columns (IM virtual columns) are eligible for population into the IM column store.

Enabling and Disabling Tablespaces for the IM Column Store (page 4-23) You can enable or disable tablespaces for the IM column store.

Enabling and Disabling Materialized Views for the IM Column Store (page 4-24)

You can enable and disable materialized views for the IM column store.

Forcing Population of an In-Memory Object: Tutorial (page 4-24)

Enabling an object for In-Memory population does not immediately populate the object.

Enabling ADO for the IM Column Store (page 4-26)

Information Lifecycle Management (ILM) is a set of processes and policies for managing data from creation to archival or deletion.

4.1 About In-Memory Population

In-Memory population (population) occurs when the database reads existing row-format data from disk, transforms it into columnar format, and then stores it in the IM column store. Only objects with the INMEMORY attribute are eligible for population.

This section contains the following topics:

Purpose of In-Memory Population (page 4-2)

The IM column store does not automatically load all objects in the database into the IM column store.

How In-Memory Population Works (page 4-2)

You can specify that the database populates objects in the IM column store either at database instance startup or when INMEMORY objects are accessed. The population algorithm also varies depending on whether you use single-instance or Oracle RAC.

Controls for In-Memory Population (page 4-6)

Use the INMEMORY clause in data definition language (DDL) statements to specify which objects are eligible for population into the IM column store. You can enable tablespaces, tables, partitions, and materialized views.

4.1.1 Purpose of In-Memory Population

The IM column store does not automatically load all objects in the database into the IM column store.

If you do not use DDL to specify any objects as INMEMORY, then the IM column store remains empty. Population is necessary to transform rows from user-specified INMEMORY objects into columnar format, so that they are available for analytic queries.

Population, which transforms *existing* data on disk into columnar format, is different from repopulation, which loads new data into the IM column store. Because IMCUs are read-only structures, Oracle Database does not populate them when rows change. Rather, the database records the row changes in a transaction journal, and then creates new IMCUs as part of repopulation.

See Also:

- "Optimizing Repopulation of the IM Column Store (page 8-1)"
- "In-Memory Compression Units (IMCUs) (page 2-8)"

4.1.2 How In-Memory Population Works

You can specify that the database populates objects in the IM column store either at database instance startup or when INMEMORY objects are accessed. The population algorithm also varies depending on whether you use single-instance or Oracle RAC.

This section contains the following topics:

Prioritization of In-Memory Population (page 4-2)

DDL statements include an INMEMORY PRIORITY subclause that provides more control over the population queue.

How Background Processes Populate IMCUs (page 4-5)

During population, the database reads data from disk in its row format, pivots the rows to create columns, and then compresses the data into In-Memory Compression Units (IMCUs).

4.1.2.1 Prioritization of In-Memory Population

DDL statements include an INMEMORY PRIORITY subclause that provides more control over the population queue.

Note:

The INMEMORY PRIORITY subclause controls the priority of population, but not the speed of population.

The priority level setting applies to an entire table, partition, or subpartition, not to different column subsets. Setting the INMEMORY attribute on an object means that this object is a *candidate* for population in the IM column store. It does not mean that the database immediately populates the object. Oracle Database manages prioritization as follows:

• On-demand population

By default, the INMEMORY PRIORITY parameter is set to NONE. In this case, the database *only* populates the object when it is accessed through a full table scan. If the object is never accessed, or if it is accessed only through an index scan or fetch by rowid, then population never occurs.

• Priority-based population

When PRIORITY is set to a value *other than* NONE, Oracle database automatically populates the objects using an internally managed priority queue. In this case, a full scan is not a necessary condition for population. The database does the following:

- Populates columnar data in the IM column store automatically after the database instance restarts
- Queues population of INMEMORY objects based on the specified priority level
 For example, a table altered with INMEMORY PRIORITY CRITICAL takes precedence over a table altered with INMEMORY PRIORITY HIGH, which in turn takes precedence over a table altered with INMEMORY PRIORITY LOW. If the IM column store has insufficient space, then Oracle Database does not populate additional objects until space is available.
- Waits to return from ALTER TABLE or ALTER MATERIALIZED VIEW statements until the changes to the object are recorded in the IM column store

After a segment is populated in the IM column store, the database only evicts it when the segment is dropped or moved, or the segment is updated with the NO INMEMORY attribute. You can evict a segment manually or by means of an ADO policy.

Example 4-1 Population of an Object in the IM Column Store

Before completing this example, the IM column store must be enabled for the database.

1. Log in to the database as an administrator, and then query the customers table as follows:

```
SELECT cust_id, cust_last_name, cust_first_name
FROM sh.customers
WHERE cust_city = 'Hyderabad'
AND cust_income_level LIKE 'C%'
AND cust_year_of_birth > 1960;
```

2. Display the execution plan for the query:

```
SQL> SELECT * FROM TABLE(DBMS_XPLAN.DISPLAY_CURSOR(FORMAT=>'+ALLSTATS'));
SQL_ID frgk9dbaftmm9, child number 0
SELECT cust_id, cust_last_name, cust_first_name FROM sh.customers
WHERE cust_city = 'Hyderabad' AND cust_income_level LIKE 'C%' AND
cust_year_of_birth > 1960
Plan hash value: 2008213504
______
______
| 0 | SELECT STATEMENT | 1 | 6 | 00:00:00.01 | 1523 | 
|* 1 | TABLE ACCESS FULL | CUSTOMERS | 1 | 6 | 6 | 00:00:00.01 | 1523 |
Predicate Information (identified by operation id):
```

```
1 - filter(("CUST_CITY"='Hyderabad' AND "CUST_YEAR_OF_BIRTH">1960 AND
           "CUST_INCOME_LEVEL" LIKE 'C%'))
```

3. Enable the sh. customers table for population in the IM column store:

```
ALTER TABLE sh.customers INMEMORY;
```

The preceding statement uses the default priority of NONE. A full scan is required to populate objects with no priority.

To determine whether data from the sh.customers table has been populated in the IM column store, execute the following query (sample output included):

```
SELECT SEGMENT_NAME, POPULATE_STATUS
FROM V$IM SEGMENTS
WHERE SEGMENT_NAME = 'CUSTOMERS';
no rows selected
```

In this case, no segments are populated in the IM column store because the sh.customers table has not yet been scanned.

5. Query sh. customers using the same statement as in Step 1:

```
SELECT cust_id, cust_last_name, cust_first_name
FROM sh.customers
WHERE cust_city = 'Hyderabad'
AND cust_income_level LIKE 'C%'
AND cust_year_of_birth > 1960;
```

6. Querying the cursor shows that the database performed a full scan and accessed the IM column store:

```
SQL> SELECT * FROM TABLE(DBMS_XPLAN.DISPLAY_CURSOR(FORMAT=>'+ALLSTATS'));
SQL_ID frgk9dbaftmm9, child number 0
SELECT cust_id, cust_last_name, cust_first_name FROM sh.customers
WHERE cust_city = 'Hyderabad' AND cust_income_level LIKE 'C%' AND
cust_year_of_birth > 1960
Plan hash value: 2008213504
```

```
| Id| Operation
                  Name
                                  |Starts|E-Rows|A-Rows|A-Time|Buffers| | | |
| 0| SELECT STATEMENT | 1| | 6 |00:00:00.02| 1523 |
|* 1| TABLE ACCESS INMEMORY FULL | CUSTOMERS | 1 | 6 | 6 | 00:00:00.02 | 1523 |
Predicate Information (identified by operation id):
_____
  1 - inmemory(("CUST_CITY"='Hyderabad' AND "CUST_YEAR_OF_BIRTH">1960 AND
       "CUST_INCOME_LEVEL" LIKE 'C%'))
     filter(("CUST_CITY"='Hyderabad' AND "CUST_YEAR_OF_BIRTH">1960 AND
           "CUST_INCOME_LEVEL" LIKE 'C%'))
```

Query V\$IM SEGMENTS again (sample output included):

```
COL SEGMENT_NAME FORMAT a20
SELECT SEGMENT_NAME, POPULATE_STATUS
FROM V$IM SEGMENTS
WHERE SEGMENT_NAME = 'CUSTOMERS';
SEGMENT_NAME
               POPULATE STATUS
_____
CUSTOMERS
                COMPLETED
```

The value COMPLETED in POPULATE_STATUS means that the table is populated in the IM column store.

The DBA_FEATURE_USAGE_STATISTICS view confirms that the database used the IM column store to retrieve the results:

```
COL NAME FORMAT a25
SELECT ul.NAME, ul.DETECTED_USAGES
FROM DBA_FEATURE_USAGE_STATISTICS ul
WHERE ul.VERSION= (SELECT MAX(u2.VERSION)
               FROM DBA_FEATURE_USAGE_STATISTICS u2
                WHERE u2.NAME = u1.NAME
                AND ul.NAME LIKE '%Column Store%');
                   DETECTED_USAGES
_____
In-Memory Column Store 1
```

See Also:

"Priority Options for In-Memory Population (page 4-8)"

Oracle Database SQL Language Reference to learn about the INMEMORY PRIORITY clause

4.1.2.2 How Background Processes Populate IMCUs

During population, the database reads data from disk in its row format, pivots the rows to create columns, and then compresses the data into In-Memory Compression Units (IMCUs).

Worker processes (Wnnn) populate the data in the IM column store. Each worker process operates on a subset of database blocks from the object. Population is a

streaming mechanism, simultaneously compressing the data and converting it into columnar format.

The INMEMORY_MAX_POPULATE_SERVERS initialization parameter specifies the maximum number of worker processes to use for IM column store population. By default, the setting is one half of CPU_COUNT. Set this parameter to an appropriate value for your environment. More worker processes result in faster population, but they use more CPU resources. Fewer worker processes result in slower population, which reduces CPU overhead.

Note:

If INMEMORY_MAX_POPULATE_SERVERS is set to 0, then population is

See Also:

Oracle Database Reference for more information about the INMEMORY_MAX_POPULATE_SERVERS initialization parameter

4.1.3 Controls for In-Memory Population

Use the INMEMORY clause in data definition language (DDL) statements to specify which objects are eligible for population into the IM column store. You can enable tablespaces, tables, partitions, and materialized views.

This section contains the following topics:

The INMEMORY Subclause (page 4-6)

INMEMORY is a segment-level attribute, not a column-level attribute. However, you can apply the INMEMORY attribute to a subset of columns within a specific object.

Priority Options for In-Memory Population (page 4-8)

When you enable a database object for the IM column store, you can either enable Oracle Database to control when the object is populated in the IM column store (default), or you can specify a priority level that determines the priority of the object in the population queue.

IM Column Store Compression Methods (page 4-9)

Depending on your requirement, you can compress In-Memory objects at different levels.

Oracle Compression Advisor (page 4-11)

Oracle Compression Advisor estimates the compression ratio that you can realize using the MEMCOMPRESS clause. The advisor uses the DBMS_COMPRESSION interface.

4.1.3.1 The INMEMORY Subclause

INMEMORY is a segment-level attribute, not a column-level attribute. However, you can apply the INMEMORY attribute to a subset of columns within a specific object.

To enable or disable an object for the IM column store, specify the INMEMORY clause in any of the following statements:

CREATE TABLESPACE or ALTER TABLESPACE

By default, all tables and materialized views in the tablespace are enabled for the IM column store. Individual tables and materialized views in the tablespace may have different INMEMORY attributes. The attributes for individual database objects override the attributes for the tablespace.

• CREATE TABLE OF ALTER TABLE

By default, the IM column store populates all nonvirtual columns in the table. You can specify all or a subset of the columns for a table. For example, you might exclude the weight_class and catalog_url columns in oe.product_information from eligibility. For a partitioned table, you can populate all or a subset of the partitions in the IM column store. By default, for a partitioned table, all table partitions inherit the INMEMORY attribute.

CREATE MATERIALIZED VIEW or ALTER MATERIALIZED VIEW
 For a partitioned materialized view, you can populate all or a subset of the partitions in the IM column store.

The INMEMORY column in the DBA_TABLES view indicates which tables have the INMEMORY attribute set (ENABLED) or not set (DISABLED).

The following objects are not eligible for population in the IM column store:

- Indexes
- Index-organized tables
- Hash clusters
- Objects owned by the SYS user and stored in the SYSTEM or SYSAUX tablespace

If you enable a table for the IM column store and it contains any of the following types of columns, then these columns will not be populated in the IM column store:

- Out-of-line columns (varrays, nested table columns, and out-of-line LOBs)
- Columns that use the LONG or LONG RAW data types
- Extended data type columns

Example 4-2 Specifying a Table as INMEMORY

Assume that you are connected to the database as user sh. You enable the customers table for population in the IM column store, using the default compression level of FOR QUERY LOW (see "In-Memory Compression (page 2-11)"):

CUSTOMERS ENABLED FOR QUERY LOW

See Also: Enabling the IM Column Store for a Database (page 3-3)

4.1.3.2 Priority Options for In-Memory Population

When you enable a database object for the IM column store, you can either enable Oracle Database to control when the object is populated in the IM column store (default), or you can specify a priority level that determines the priority of the object in the population queue.

Oracle SQL includes an INMEMORY PRIORITY clause that provides more control over the queue for population. For example, it might be more important or less important to populate a database object's data before populating the data for other database objects.

Video:

Oracle Database 12c demos: In-Memory Column Store Priority

The following table describes the supported priority levels.

Table 4-1 Priority Levels for Populating a Database Object in the IM Column Store

CREATE/ALTER Syntax	Description
PRIORITY NONE	The database populates the object on demand only. A full scan of the database object triggers the population of the object into the IM column store. This is the default level when PRIORITY is not included in the INMEMORY clause.
PRIORITY LOW	The database assigns the object a low priority and populates it after startup based on its position in the queue. Population does not depend on whether the object is accessed.
	The object is populated in the IM column store before database objects with the following priority level: NONE. The database object's data is populated in the IM column store after database objects with the following priority levels: MEDIUM, HIGH, or CRITICAL.
PRIORITY MEDIUM	The database assigns the object a medium priority and populates it after startup based on its position in the queue. Population does not depend on whether the object is accessed.
	The database object is populated in the IM column store before database objects with the following priority levels: NONE or LOW. The database object's data is populated in the IM column store after database objects with the following priority levels: HIGH or CRITICAL.
PRIORITY HIGH	The database assigns the object a high priority and populates it after startup based on its position in the queue. Population does not depend on whether the object is accessed.
	The database object's data is populated in the IM column store before database objects with the following priority levels: NONE, LOW, or MEDIUM. The database object's data is populated in the IM column store after database objects with the following priority level: CRITICAL.

Table 4-1 (Cont.) Priority Levels for Populating a Database Object in the IM Column Store

CREATE/ALTER Syntax	Description
PRIORITY CRITICAL	The database assigns the object a low priority and populates it after startup based on its position in the queue. Population does not depend on whether the object is accessed.
	The database object's data is populated in the IM column store before database objects with the following priority levels: NONE, LOW, MEDIUM, or HIGH.

When more than one database object has a priority level other than NONE, Oracle Database queues all of the data for the database objects to be populated in the IM column store based on priority level. Database objects with the CRITICAL priority level are populated first; database objects with the HIGH priority level are populated next, and so on. If there is no space remaining in the IM column store, then no additional objects are populated in it until sufficient space becomes available.

Note:

If you specify all objects as CRITICAL, then the database does not consider any object as more critical than any other.

When a database is restarted, all of the data for database objects with a priority level other than NONE are populated in the IM column store during startup. For a database object with a priority level other than NONE, an ALTER TABLE or ALTER MATERIALIZED VIEW DDL statement involving the database object does not return until the DDL changes are recorded in the IM column store.

Note:

- The priority level setting must apply to an entire table or to a table partition. Specifying different IM column store priority levels for different subsets of columns in a table is not permitted.
- If a segment on disk is 64 KB or less, then it is not populated in the IM column store. Therefore, some small database objects that were enabled for the IM column store might not be populated.

See Also:

- "Prioritization of In-Memory Population (page 4-2)"
- Oracle Database SQL Language Reference for CREATE TABLE . . . INMEMORY PRIORITY syntax and semantics

4.1.3.3 IM Column Store Compression Methods

Depending on your requirement, you can compress In-Memory objects at different levels.

Typically, compression is a space-saving mechanism. However, the IM column store can compress data using a new set of algorithms that also improve query performance. If the columnar data is compressed using the FOR DML or FOR QUERY options, then SQL queries execute directly on the compressed data. Thus, scanning and filtering operations execute on a much smaller amount of data. The database only decompresses data when it is required for the result set.

Video:

Oracle Database 12c demos: In-Memory Column Store Compression

The V\$IM_SEGMENTS and V\$IM_COLUMN_LEVEL views indicate the current compression level. You can change compression levels by using the appropriate ALTER command. If a table is currently populated in the IM column store, and if you change any INMEMORY attribute of the table *other than* PRIORITY, then the database evicts the table from the IM column store. The repopulation behavior depends on the PRIORITY setting.

The following table summarizes the data compression methods supported in the IM column store.

Table 4-2 IM Column Store Compression Methods

CREATE/ALTER Syntax	Description
NO MEMCOMPRESS	The data is not compressed.
MEMCOMPRESS FOR DML	This method results in the best DML performance. This method compresses IM column store data the least, with the exception of NO MEMCOMPRESS.
MEMCOMPRESS FOR QUERY LOW	This method results in the best query performance. This method compresses IM column store data more than MEMCOMPRESS FOR DML but less than MEMCOMPRESS FOR QUERY HIGH.
	This method is the default when the INMEMORY clause is specified without a compression method in a CREATE or ALTER SQL statement or when MEMCOMPRESS FOR QUERY is specified without including either LOW or HIGH.
MEMCOMPRESS FOR QUERY HIGH	This method results in good query performance, and saves space. This method compresses IM column store data more than MEMCOMPRESS FOR QUERY LOW but less than MEMCOMPRESS FOR CAPACITY LOW.

Table 4-2 (Cont.) IM Column Store Compression Methods

CREATE/ALTER Syntax	Description
MEMCOMPRESS FOR CAPACITY LOW	This method balances space saving and query performance, with a bias toward space saving.
	This method compresses IM column store data more than MEMCOMPRESS FOR QUERY HIGH but less than MEMCOMPRESS FOR CAPACITY HIGH. This method applies a proprietary compression technique called Oracle Zip (OZIP) that offers extremely fast decompression that is tuned specifically for Oracle Database. That data must be decompressed before it can be scanned.
	This method is the default when MEMCOMPRESS FOR CAPACITY is specified without including either LOW or HIGH.
MEMCOMPRESS FOR CAPACITY HIGH	This method results in the best space saving. This method compresses IM column store data the most.

In a SQL statement, the MEMCOMPRESS keyword must be preceded by the INMEMORY keyword.

See Also:

- "About Repopulation of the IM Column Store (page 8-1)"
- Oracle Database SQL Language Reference for CREATE TABLE ... INMEMORY PRIORITY syntax and semantics

4.1.3.4 Oracle Compression Advisor

Oracle Compression Advisor estimates the compression ratio that you can realize using the MEMCOMPRESS clause. The advisor uses the DBMS_COMPRESSION interface.

When you run DBMS_COMPRESSION.GET_COMPRESSION_RATIO for a table, Oracle Database analyzes a sample of the rows. For this reason, Oracle Compression Advisor provides a good estimate of the compression results that a table achieves after it is populated into the IM column store.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn about DBMS_COMPRESSION.GET_COMPRESSION_RATIO

4.2 Enabling and Disabling Tables for the IM Column Store

Enable a table for the IM column store by including an INMEMORY clause in a CREATE TABLE or ALTER TABLE statement. Disable a table for the IM column store by including a NO INMEMORY clause in a CREATE TABLE or ALTER TABLE statement.

This section contains the following topics:

Enabling New Tables for the In-Memory Column Store (page 4-12)

You enable a new table for the IM column store by including an INMEMORY clause in a CREATE TABLE statement.

Enabling and Disabling Existing Tables for the IM Column Store (page 4-12)

Enable an existing table for the IM column store by including an

INMEMORY clause in an ALTER TABLE statement. Disable a table for the

IM column store by including a NO INMEMORY clause in an ALTER

TABLE statement.

Enabling and Disabling Tables for the IM Column Store: Examples (page 4-13)

The following examples illustrate how to enable or disable tables for the IM column store.

4.2.1 Enabling New Tables for the In-Memory Column Store

You enable a new table for the IM column store by including an INMEMORY clause in a CREATE TABLE statement.

To enable a new table for the IM column store:

- Ensure that the IM column store is enabled for the database.
 See "Enabling the IM Column Store for a Database (page 3-3)".
- 2. Log in to the database as a user with the necessary privileges to create the table.
- 3. Run a CREATE TABLE statement with an INMEMORY clause or a NO INMEMORY clause.

See Also:

- "Enabling and Disabling Tables for the IM Column Store: Examples (page 4-13)"
- "Enabling a Subset of Columns for the IM Column Store: Example (page 4-19)"
- Oracle Database SQL Language Reference for information about the CREATE TABLE statement

4.2.2 Enabling and Disabling Existing Tables for the IM Column Store

Enable an existing table for the IM column store by including an INMEMORY clause in an ALTER TABLE statement. Disable a table for the IM column store by including a NO INMEMORY clause in an ALTER TABLE statement.

To enable or disable an existing table for the IM column store, complete the following steps:

- Ensure that the IM column store is enabled for the database.
 See "Enabling the IM Column Store for a Database (page 3-3)".
- 2. Log in to the database as a user with ALTER TABLE privileges.
- **3.** Run an ALTER TABLE statement with an INMEMORY clause or a NO INMEMORY clause.

4. Optionally, to view metadata (size, priority, compression level) about the In-Memory segment, query V\$IM_SEGMENTS.

See Also:

- "Enabling and Disabling Tables for the IM Column Store: Examples (page 4-13)"
- "Enabling a Subset of Columns for the IM Column Store: Example (page 4-19)"
- Oracle Database SQL Language Reference for information about the ALTER TABLE statement
- Oracle Database Reference for information about the V\$IM_SEGMENTS view

4.2.3 Enabling and Disabling Tables for the IM Column Store: Examples

The following examples illustrate how to enable or disable tables for the IM column store.

Example 4-3 Creating a Table and Enabling It for the IM Column Store

The following example creates the test_inmem table and enables it for the IM column store:

```
CREATE TABLE test_inmem (
    id         NUMBER(5) PRIMARY KEY,
    test_col     VARCHAR2(15))
    INMEMORY;
```

This example uses the defaults for the INMEMORY clause: MEMCOMPRESS FOR QUERY and PRIORITY NONE.

Example 4-4 Enabling a Table for the IM Column Store

The following DDL statement enables the sh.sales table for the IM column store:

```
ALTER TABLE sh.sales INMEMORY;
```

The preceding statement uses the defaults for the INMEMORY clause: MEMCOMPRESS FOR QUERY and PRIORITY NONE.

The following query causes a full scan of sales, which populates the table into the IM column store:

```
SELECT /*+ FULL(sales) NO_PARALLEL(sales) */ COUNT(*) FROM sh.sales;
```

The following query shows the population status of sales (sample output included):

```
COL OWNER FORMAT a3
COL NAME FORMAT a10
COL STATUS FORMAT a20
SELECT OWNER, SEGMENT_NAME NAME,
POPULATE_STATUS STATUS
FROM V$IM_SEGMENTS;
OWN NAME STATUS
```

```
SH SALES COMPLETED
```

The following query calculates the compression ratio. The query assumes that the tables are not further compressed on disk.

```
COL OWNER FORMAT a5
COL SEGMENT NAME FORMAT a5
SET PAGESIZE 50000
SELECT v.OWNER, v.SEGMENT_NAME, v.BYTES ORIG_SIZE,
      v.INMEMORY_SIZE IN_MEM_SIZE,
      ROUND(v.BYTES / v.INMEMORY_SIZE, 2) COMP_RATIO
FROM V$IM_SEGMENTS v
ORDER BY 4;
OWNER SEGME ORIG_SIZE IN_MEM_SIZE COMP_RATIO

      SH
      SALES
      851968
      1310720

      SH
      SALES
      835584
      1310720

      SH
      SALES
      925696
      1310720

                                       .64
                                       .71
SH SALES 958464 1310720
                                       .73
SH SALES 950272 1310720
                                       .73
SH SALES 786432 1310720
                                        . 6
SH SALES 876544 1310720
                                       .67
SH SALES 753664 1310720
                                       .58
SH SALES 1081344 1310720
                                       .83
SH SALES 901120 1310720
                                      .69
SH SALES 925696 1310720
                                       .71
SH SALES 933888 1310720
                                       .71
SH SALES 843776 1310720
                                       .64
SH SALES 999424 1310720
                                       .76
SH SALES 581632 1507328
                                       .39
SH SALES 696320 1507328
                                       .46
```

16 rows selected.

Example 4-5 Enabling a Table for the IM Column Store with FOR CAPACITY LOW Compression

The following DDL statement enables the oe.product_information table for the IM column store and specifies the compression method FOR CAPACITY LOW:

```
ALTER TABLE oe.product_information
INMEMORY
MEMCOMPRESS FOR CAPACITY LOW;
```

The preceding DDL statement uses the default for the PRIORITY clause, which is NONE. The following query scans the oe.product_information table to populate it (sample output included):

The following query calculates the compression ratio (sample output included):

```
COL OWNER FORMAT a5
COL SEGMENT_NAME FORMAT a19
```

Example 4-6 Enabling a Table for the IM Column Store with HIGH Data Population Priority

The following DDL statement enables the oe.product_information table for the IM column store and specifies PRIORITY HIGH for populating the table data in the IM column store:

```
ALTER TABLE

oe.product_information
INMEMORY
PRIORITY HIGH;
```

Example 4-7 Enabling a Table for the IM Column Store with FOR CAPACITY HIGH Compression and LOW Data Population Priority

The following query shows the priority and compression setting for the oe.product_information table:

The following DDL statement alters oe.product_information to use FOR CAPACITY HIGH table compression and PRIORITY LOW:

```
ALTER TABLE oe.product_information
INMEMORY
MEMCOMPRESS FOR CAPACITY HIGH
PRIORITY LOW;
```

Example 4-8 Enabling a Partitioned Table for the IM Column Store

This following DDL statement creates a partitioned table named range_sales and specifies a different compression level for the first three partitions in the IM column store. The last two partitions are not populated in the IM column store.

```
CREATE TABLE range_sales
( prod_id NUMBER(6)
, cust_id NUMBER
, time_id DATE
```

```
, channel_id CHAR(1)
, promo_id NUMBER(6)
    , quantity_sold NUMBER(3)
   , amount_sold NUMBER(10,2)
PARTITION BY RANGE (time_id)
  (PARTITION SALES_Q4_1999
     VALUES LESS THAN (TO_DATE('01-JAN-2015','DD-MON-YYYY'))
     INMEMORY MEMCOMPRESS FOR DML,
  PARTITION SALES_Q1_2000
     VALUES LESS THAN (TO_DATE('01-APR-2015','DD-MON-YYYY'))
     INMEMORY MEMCOMPRESS FOR QUERY,
  PARTITION SALES_Q2_2000
     VALUES LESS THAN (TO DATE('01-JUL-2015','DD-MON-YYYY'))
     INMEMORY MEMCOMPRESS FOR CAPACITY,
  PARTITION SALES 03 2000
     VALUES LESS THAN (TO_DATE('01-OCT-2015','DD-MON-YYYY'))
     NO INMEMORY,
  PARTITION SALES_Q4_2000
     VALUES LESS THAN (MAXVALUE));
```

Example 4-9 Disabling a Table for the IM Column Store

To disable a table for the IM column store, specify the NO INMEMORY clause. The following example disables the oe.product_information table for the IM column store:

```
ALTER TABLE oe.product_information NO INMEMORY;
```

You can query the V\$IM_SEGMENTS view to list the database objects that are populated in the IM column store.

4.3 Enabling and Disabling Columns for In-Memory Tables

You can specify the INMEMORY clause for individual columns. Both nonvirtual columns and In-Memory virtual columns (IM virtual columns) are eligible for population into the IM column store.

This section contains the following topics:

About IM Virtual Columns (page 4-17)

An IM virtual column is like any other column in a table enabled for INMEMORY, except that its value is derived by evaluating an expression. Storing the precalculated IM virtual column values in the IM column store can improve query performance.

Enabling IM Virtual Columns (page 4-18)

IM virtual columns improve query performance by avoiding repeated calculations. Also, the database can scan and filter IM virtual columns using techniques such as SIMD vector processing.

Enabling a Subset of Columns for the IM Column Store: Example (page 4-19)

This example enables all columns in the oe.product_information table for the IM column store except weight_class and catalog_url. It also specifies different IM column store compression methods for the columns enabled for the IM column store.

Specifying INMEMORY Column Attributes on a NO INMEMORY Table: Example (page 4-20)

Starting in Oracle Database 12*c* Release 2 (12.2), you can specify the INMEMORY clause at the column level on an object that is not yet specified as INMEMORY.

4.3.1 About IM Virtual Columns

An IM virtual column is like any other column in a table enabled for INMEMORY, except that its value is derived by evaluating an expression. Storing the precalculated IM virtual column values in the IM column store can improve query performance.

For an IM virtual column, the expression can include columns from the same table, constants, SQL functions, and user-defined PL/SQL functions (DETERMINISTIC only). You cannot explicitly write to an IM virtual column.

Note:

A virtual column or IM expression counts toward the limit of 1000 columns per populated object.

To populate IM virtual columns in the IM column store, set the INMEMORY_VIRTUAL_COLUMNS initialization parameter to one of the following values:

- MANUAL (default): If a table is enabled for the IM column store, then no IM virtual
 columns defined on this table are eligible for population, unless they are explicitly
 set as INMEMORY.
- ENABLE: If a table is enabled for the IM column store, then all IM virtual columns
 defined on this table are eligible for population, unless they are explicitly set as NO
 INMEMORY.

By default, the compression level of the column in the IM column store is the same as the table or partition in which it is stored. However, when a different compression level is specified for the IM virtual column, it is populated at the specified compression level.

To specify that no IM virtual columns are populated in the IM column store, set this initialization parameter to DISABLE.

The underlying storage structures for IM virtual columns and IM expressions are the same. However, different mechanisms control IM expressions and IM virtual columns.

Note:

- The IM column store only populates virtual columns for tables marked INMEMORY.
- To populate IM virtual columns in the IM column store, the value for the initialization parameter COMPATIBLE must be set to 12.1.0 or higher.

See Also:

- "Enabling and Disabling Tables for the IM Column Store (page 4-11)"
- "IM Expressions Infrastructure (page 5-4)"
- "In-Memory Initialization Parameters (page 12-1)"
- Oracle Database SQL Language Reference

4.3.2 Enabling IM Virtual Columns

IM virtual columns improve query performance by avoiding repeated calculations. Also, the database can scan and filter IM virtual columns using techniques such as SIMD vector processing.

Prerequisites

To enable IM virtual columns, the following conditions must be true:

- The IM column store is enabled for the database.
 See "Enabling the IM Column Store for a Database (page 3-3)".
- 2. The table that contains the virtual columns is enabled for the IM column store. See "Enabling and Disabling Tables for the IM Column Store (page 4-11)".
- **3.** The INMEMORY_VIRTUAL_COLUMNS initialization parameter is *not* set to DISABLE.
- **4.** The value for the initialization parameter COMPATIBLE is set to 12.1.0 or higher.

To enable IM virtual columns:

- 1. Connect to the database instance as a user with the appropriate privileges to alter the table and set initialization parameters.
- **2.** Either set the INMEMORY_VIRTUAL_COLUMNS initialization parameter to ENABLE, or enable specific virtual columns for the IM column store.

Example 4-10 Enabling Virtual Columns for the IM Column Store

In this example, you are logged in to the database as SYSTEM. The IM column store is enabled, but population of virtual columns is currently disabled:

SQL> SHOW PARAMETER INMEMORY_SIZE		
NAME	TYPE	VALUE
inmemory_size	big integer	200M
SQL> SHOW PARAMETER INMEMORY_VIRTUAL	_COLUMNS	
NAME	TYPE	VALUE
inmemory_virtual_columns	string	DISABLE

You add a virtual column to the hr.employees table, and then specify that the table is INMEMORY:

```
SQL> ALTER TABLE hr.employees ADD (weekly_sal AS (ROUND(salary*12/52,2)));

Table altered.

SQL> ALTER TABLE hr.employees INMEMORY;

Table altered.
```

At this stage, weekly_sal is not eligible for population, although the non-virtual columns in hr.employees are eligible for population. The following statement enables weekly_sal, and any other virtual columns in hr.employees, to be populated:

```
SQL> ALTER SYSTEM SET INMEMORY_VIRTUAL_COLUMNS=ENABLE SCOPE=SPFILE;
System altered.
```

Example 4-11 Enabling a Specific IM Virtual Column for the IM Column Store

This example assumes that the INMEMORY_VIRTUAL_COLUMNS initialization parameter is set to MANUAL, which means that IM virtual columns must be added to the IM column store explicitly. This example first creates the hr.admin_emp table:

```
CREATE TABLE hr.admin_emp (
empno NUMBER(5) PRIMARY KEY,
ename VARCHAR2(15) NOT NULL,
job VARCHAR2(10),
sal NUMBER(7,2),
hrly_rate NUMBER(7,2) GENERATED ALWAYS AS (sal/2080),
deptno NUMBER(3) NOT NULL)
INMEMORY;
```

At this stage, the hrly_rate virtual column is not eligible for population. The following statement explicitly specifies the virtual column as INMEMORY:

```
ALTER TABLE hr.admin_emp INMEMORY(hrly_rate);
```

4.3.3 Enabling a Subset of Columns for the IM Column Store: Example

This example enables all columns in the oe.product_information table for the IM column store except weight_class and catalog_url. It also specifies different IM column store compression methods for the columns enabled for the IM column store.

```
ALTER TABLE oe.product_information

INMEMORY MEMCOMPRESS FOR QUERY (
    product_id, product_name, category_id, supplier_id, min_price)

INMEMORY MEMCOMPRESS FOR CAPACITY HIGH (
    product_description, warranty_period, product_status, list_price)

NO INMEMORY (
    weight_class, catalog_url);
```

Specifically, this example specifies the following:

- The list of columns starting with product_id and ending with min_price are enabled for the IM column store with the MEMCOMPRESS FOR QUERY compression method.
- The list of columns starting with product_description and ending with list_price are enabled for the IM column store with the MEMCOMPRESS FOR CAPACITY HIGH compression method.

- The weight_class and catalog_url columns are not enabled for the IM column store.
- The table uses the default for the PRIORITY clause, which is PRIORITY NONE.

Note:

The priority level setting must apply to an entire table or partition. Specifying different IM column store priority levels for different subsets of columns in a table is not allowed.

To determine the selective column compression levels defined for a database object, query the V\$IM_COLUMN_LEVEL view, as shown in the following example:

PRODUCT_INFORMATION PRODUCT_ID FOR QUERY LOW PRODUCT_INFORMATION PRODUCT_NAME FOR QUERY LOW PRODUCT_INFORMATION PRODUCT_STATUS FOR CAPACITY HIGH PRODUCT_INFORMATION WARRANTY_PERIOD FOR CAPACITY HIGH PRODUCT_INFORMATION WEIGHT_CLASS NO INMEMORY

See Also:

- "In-Memory Compression (page 2-11)"
- Oracle Database Reference for more information about the V \$IM_COLUMN_LEVEL view

4.3.4 Specifying INMEMORY Column Attributes on a NO INMEMORY Table: Example

Starting in Oracle Database 12*c* Release 2 (12.2), you can specify the INMEMORY clause at the column level on an object that is not yet specified as INMEMORY.

In previous releases, the column-level INMEMORY clause was only valid when specified on an INMEMORY table or partition. This restriction meant that a column could not be associated with an INMEMORY clause before the table or partition was associated with an INMEMORY clause.

Starting in Oracle Database 12c Release 2 (12.2), if you specify the INMEMORY clause at the column level, then the database records the attributes of the specified column. If the table is NO INMEMORY (default), then the column-level attributes do not affect how

the table is queried until the table or partition is specified as INMEMORY. If you mark the table itself as NO INMEMORY, then the database drops any existing column-level attributes.

In this example, your goal is to ensure that column c3 in a partitioned table is never populated in the IM column store. You perform the following steps:

1. Create a partitioned table t as follows:

```
CREATE TABLE t (c1 NUMBER, c2 NUMBER, c3 NUMBER)

NO INMEMORY -- this clause specifies the table itself as NO INMEMORY

PARTITION BY LIST (c1)

( PARTITION p1 VALUES (0),

PARTITION p2 VALUES (1),

PARTITION p3 VALUES (2));
```

Table t is NO INMEMORY. The table is partitioned by list on column c1, and has three partitions: p1, p2, and p3.

2. Query the compression of the columns in the table (sample output included):

```
COL TABLE_NAME FORMAT a20

COL COLUMN_NAME FORMAT a20

SELECT TABLE_NAME, COLUMN_NAME, INMEMORY_COMPRESSION
FROM V$IM_COLUMN_LEVEL
WHERE TABLE_NAME = 'T'
ORDER BY COLUMN_NAME;

no rows selected
```

As shown by the output, no column-level INMEMORY attributes are set.

3. To ensure that column c3 is never populated, apply the NO INMEMORY attribute to column c3:

```
ALTER TABLE t NO INMEMORY (c3);
```

4. Query the compression of the columns in the table (sample output included):

```
SELECT TABLE_NAME, COLUMN_NAME, INMEMORY_COMPRESSION
FROM V$IM_COLUMN_LEVEL
WHERE TABLE_NAME = 'T'
ORDER BY COLUMN_NAME;
```

TABLE_NAME	COLUMN_NAME	INMEMORY_COMPRESSION
T	C1	DEFAULT
T	C2	DEFAULT
Т	C3	NO INMEMORY

The database has recorded the NO $\,$ INMEMORY attribute for c3. The other columns use the default compression.

5. Specify partition p3 as INMEMORY:

```
ALTER TABLE t

MODIFY PARTITION p3

INMEMORY PRIORITY CRITICAL;
```

Because column c3 was previously specified as NO INMEMORY, initial population of partition p3 will not include column c3.

6. Specify the entire table as INMEMORY:

```
ALTER TABLE t INMEMORY;
```

7. Query the compression of the columns in the table (sample output included):

```
SELECT TABLE_NAME, COLUMN_NAME, INMEMORY_COMPRESSION
FROM V$IM_COLUMN_LEVEL
WHERE TABLE_NAME = 'T'
ORDER BY COLUMN_NAME;
```

TABLE_NAME	COLUMN_NAME	INMEMORY_COMPRESSION
T	C1	DEFAULT
T	C2	DEFAULT
T	C3	NO INMEMORY

The database has retained the NO INMEMORY setting for column c3. The other columns use the default compression.

8. Apply different compression levels to columns c1 and c2:

```
ALTER TABLE t
INMEMORY MEMCOMPRESS FOR CAPACITY HIGH (c1)
INMEMORY MEMCOMPRESS FOR CAPACITY LOW (c2);
```

9. Query the compression of the columns in the table (sample output included):

```
SELECT TABLE_NAME, COLUMN_NAME, INMEMORY_COMPRESSION
FROM V$IM_COLUMN_LEVEL
WHERE TABLE_NAME = 'T'
ORDER BY COLUMN_NAME;
```

TABLE_NAME	COLUMN_NAME	INMEMORY_COMPRESSION
T	C1	FOR CAPACITY HIGH
T	C2	FOR CAPACITY LOW
T	C3	NO INMEMORY

Each column now has a different compression level.

10. Specify the entire table as NO INMEMORY:

```
ALTER TABLE t NO INMEMORY;
```

11. Query the compression of the columns in the table (sample output included):

```
SELECT TABLE_NAME, COLUMN_NAME, INMEMORY_COMPRESSION
FROM V$IM_COLUMN_LEVEL
WHERE TABLE_NAME = 'T'
ORDER BY COLUMN_NAME;
```

no rows selected

Because the entire table was specified as NO INMEMORY, the database dropped all column-level INMEMORY attributes.

See Also:

Oracle Database SQL Language Reference for ALTER TABLE syntax and semantics

4.4 Enabling and Disabling Tablespaces for the IM Column Store

You can enable or disable tablespaces for the IM column store.

You can enable a tablespace for the IM column store during tablespace creation with a CREATE TABLESPACE statement that includes the INMEMORY clause. You can also alter a tablespace to enable it for the IM column store with an ALTER TABLESPACE statement that includes the INMEMORY clause.

You disable a tablespace for the IM column store by including a NO INMEMORY clause in a CREATE TABLESPACE or ALTER TABLESPACE statement.

When a tablespace is enabled for the IM column store, all tables and materialized views in the tablespace are enabled for the IM column store by default. The INMEMORY clause is the same for tables, materialized views, and tablespaces. The DEFAULT storage clause is required before the INMEMORY clause when enabling a tablespace for the IM column store and before the NO INMEMORY clause when disabling a tablespace for the IM column store.

When a tablespace is enabled for the IM column store, individual tables and materialized views in the tablespace can have different in-memory settings, and the settings for individual database objects override the settings for the tablespace. For example, if the tablespace is set to PRIORITY LOW for populating data in memory, but a table in the tablespace is set to PRIORITY HIGH, then the table uses PRIORITY HIGH.

To enable or disable a tablespace for the IM column store, complete the following steps:

1. Ensure that the IM column store is enabled for the database.

See "Enabling the IM Column Store for a Database (page 3-3)".

- **2.** Connect to the database instance as a user with the appropriate privileges to either create the tablespace or alter the tablespace.
- **3.** Run a CREATE TABLESPACE or ALTER TABLESPACE statement with an INMEMORY clause or a NO INMEMORY clause.

Example 4-12 Creating a Tablespace and Enabling It for the IM Column Store

The following example creates the users01 tablespace and enables it for the IM column store:

```
CREATE TABLESPACE users01

DATAFILE 'users01.dbf' SIZE 40M

ONLINE

DEFAULT INMEMORY;
```

This example uses the defaults for the INMEMORY clause. Therefore, MEMCOMPRESS FOR QUERY is used, and PRIORITY NONE is used.

Example 4-13 Altering a Tablespace to Enable It for the IM Column Store

The following example alters the users01 tablespace to enable it for the IM column store and specifies FOR CAPACITY HIGH compression for the database objects in the tablespace and PRIORITY LOW for populating data in memory:

```
ALTER TABLESPACE users01 DEFAULT INMEMORY MEMCOMPRESS FOR CAPACITY HIGH PRIORITY LOW;
```

4.5 Enabling and Disabling Materialized Views for the IM Column Store

You can enable and disable materialized views for the IM column store.

Enable a materialized view for the IM column store by including an INMEMORY clause in a CREATE MATERIALIZED VIEW or ALTER MATERIALIZED VIEW statement. Disable a materialized view for the IM column store by including a NO INMEMORY clause in a CREATE MATERIALIZED VIEW or ALTER MATERIALIZED VIEW statement.

To enable or disable a materialized view for the IM column store:

- Ensure that the IM column store is enabled for the database.
 See "Enabling the IM Column Store for a Database (page 3-3)".
- **2.** Log in to the database as a user with the privileges to either create or alter the materialized view.
- **3.** Run a CREATE MATERIALIZED VIEW or ALTER MATERIALIZED VIEW statement with either an INMEMORY clause or a NO INMEMORY clause.

Example 4-14 Creating a Materialized View and Enabling It for the IM Column Store

The following statement creates the oe.prod_info_mv materialized view and enables it for the IM column store:

```
CREATE MATERIALIZED VIEW oe.prod_info_mv INMEMORY
AS SELECT * FROM oe.product_information;
```

This example uses the defaults for the INMEMORY clause: MEMCOMPRESS FOR QUERY LOW and PRIORITY NONE.

Example 4-15 Enabling a Materialized View for the IM Column Store with HIGH Data Population Priority

The following statement enables the oe.prod_info_mv materialized view for the IM column store:

ALTER MATERIALIZED VIEW oe.prod_info_mv INMEMORY PRIORITY HIGH;

This example uses the default compression: MEMCOMPRESS FOR QUERY LOW.

See Also:

Oracle Database SQL Language Reference to learn more about the CREATE or ALTER MATERIALIZED VIEW statements

4.6 Forcing Population of an In-Memory Object: Tutorial

Enabling an object for In-Memory population does not immediately populate the object.

If you enabled an object with PRIORITY set to NONE, and if you want to populate it immediately, you have the following options:

- Force a full table scan
- Use the DBMS_INMEMORY.POPULATE procedure

Assumptions

This tutorial assumes the following:

- The IM column store is enabled.
- You want to enable the sh.customers table for In-Memory population, using the default PRIORITY of NONE.
- You want to force the immediate population of sh.customers into the IM column store.

To force population of an INMEMORY table:

- 1. In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- **2.** Apply the INMEMORY attribute to the table.

For example, enable sh.customers for IM population as follows:

```
ALTER TABLE sh.customers INMEMORY;
```

3. Optionally, to check the population status, query V\$IM_SEGMENTS.

For example, use the following statement (sample output included):

```
SELECT OWNER, SEGMENT_NAME NAME,
POPULATE_STATUS STATUS
FROM V$IM_SEGMENTS
WHERE SEGMENT_NAME = 'CUSTOMERS';
no rows selected
```

The preceding output shows that the object is not yet populated in the IM column store.

4. Execute the DBMS_INMEMORY.POPULATE procedure on the table.

For example, enable this procedure against sh. customers as follows:

```
EXEC DBMS_INMEMORY.POPULATE('SH', 'CUSTOMERS');
```

5. Optionally, to check the population status, query V\$IM_SEGMENTS.

For example, use the following statement (sample output included):

The object is now populated in the IM column store.

See Also:

- Oracle Database Reference to learn about V\$IM_SEGMENTS
- Oracle Database PL/SQL Packages and Types Reference to learn about DBMS_INMEMORY.POPULATE

4.7 Enabling ADO for the IM Column Store

Information Lifecycle Management (ILM) is a set of processes and policies for managing data from creation to archival or deletion.

Automatic Data Optimization (ADO) creates policies, and automates actions based on those policies, to implement your ILM strategy. ADO uses Heat Map, which tracks data access patterns.

Note:

This chapter assumes that you are familiar with the basic concepts of ILM, ADO, and Heap Map. For more background, see *Oracle Database VLDB and Partitioning Guide*.

This section contains the following topics:

About ADO Policies and the IM Column Store (page 4-26)

In Oracle Database 12*c* Release 2 (12.2), ADO manages the IM column store through **ADO policies**. You can only create an ADO policy with an INMEMORY clause at the segment level.

Purpose of ADO and the IM Column Store (page 4-27)

Starting in Oracle Database 12*c* Release 2 (12.2), ADO manages the IM column store as a new data tier.

How ADO Works with Columnar Data (page 4-28)

From the ADO perspective, the IM column store is another storage tier.

Controls for ADO and the IM Column Store (page 4-30)

Enable Heat Map using the HEAT_MAP initialization parameter. Control ADO through a SQL and PL/SQL interface.

Creating an ADO Policy for the IM Column Store (page 4-32)

You can use ADO policies to set, modify, or remove the INMEMORY clause for objects based on Heat Map statistics.

4.7.1 About ADO Policies and the IM Column Store

In Oracle Database 12*c* Release 2 (12.2), ADO manages the IM column store through **ADO policies**. You can only create an ADO policy with an INMEMORY clause at the segment level.

The database treats an ADO policy like an attribute of an object. ADO policies are at the database level, not the instance level. Oracle Database supports the following types of ADO policies for Database In-Memory:

INMEMORY policy

This policy marks objects with the INMEMORY attribute, enables them for population in the IM column store.

Recompression policy

This policy changes the compression level on an INMEMORY object.

NO INMEMORY policy

This policy removes an object from the IM column store and removes its INMEMORY object.

Oracle Database supports for the following criteria for when the policies apply:

- A specified number of days since the object was modified
 Obtain this value from the column SEGMENT_WRITE_TIME in the DBA_HEAT_MAP_SEGMENT view.
- A specified number of days since the object was accessed
 This value is the greater value in the columns SEGMENT_WRITE_TIME,
 FULL_SCAN, and LOOKUP_SCAN in the DBA_HEAT_MAP_SEGMENT view.
- A specified number of days since the object was created
 Obtain this value from the CREATED column in DBA_OBJECTS.
- A user-defined function returns a Boolean value

See Also:

- Oracle Database Reference to learn about the DBA_HEAT_MAP_SEGMENT view
- Oracle Database SQL Language Reference to learn about the INMEMORY clause

4.7.2 Purpose of ADO and the IM Column Store

Starting in Oracle Database 12c Release 2 (12.2), ADO manages the IM column store as a new data tier.

You can create policies to evict objects from the IM column store when they degrade performance, and populate objects when they improve performance. ADO manages the IM column store using Heat Map statistics.

Purpose of INMEMORY Policies

In many databases, segments undergo heavy modification after creation. To maximize performance, ADO can populate these segments in the IM column store when write activity subsides. For example, if you add a partition to a table every day, then you can create a policy that populates the sales_2016_d100 partition one day after creation:

```
ALTER TABLE sales MODIFY PARTITION sales_2016_d100
ILM ADD POLICY SET INMEMORY MEMCOMPRESS FOR QUERY
PRIORITY HIGH
AFTER 1 DAYS OF CREATION
```

Similarly, you may know that write activity on a table subsides two months after creation, and want to populate this object when this time condition is met:

```
ALTER TABLE 2016_ski_sales

ILM ADD POLICY SET INMEMORY MEMCOMPRESS FOR QUERY
PRIORITY CRITICAL

AFTER 60 DAYS OF CREATION
```

The preceding policy causes all existing and new partitions of the 2016_ski_sales table to inherit the policy. When the segment qualifies for the policy, the database marks every partition independently with the specified INMEMORY clause. If the segment already has an INMEMORY policy, then the database ignores the new policy.

Purpose of Recompression Policies

You may want to compress data in the IM column store based on access patterns. For example, you may want to change a segment from DML compression to query compression 2 days after DML activity on the segment has ceased:

```
ALTER TABLE lineorders

ILM ADD POLICY MODIFY INMEMORY MEMCOMPRESS FOR QUERY HIGH
AFTER 2 DAYS OF NO MODIFICATION
```

If the object is not populated in IM column store, then this policy only changes the compression attribute. If the object is populated in the IM column store, then ADO repopulates the object using the new compression level. The database ignores the policy if the segment does not already have the INMEMORY attribute.

Purpose of NO INMEMORY Policies

To optimize space in the IM column store, you may want to evict inactive segments using a NO INMEMORY policy. This policy is also useful for preventing population of inactive segments by infrequent queries. For example, if reports on a specific sales partition run frequently during the year, but typically not every week, then you may want to may want to evict this partition after a week of no access:

```
ALTER TABLE sales MODIFY PARTITION sales_2015_q1 ILM ADD POLICY NO INMEMORY AFTER 7 DAYS OF NO ACCESS;
```

If the sales table for 1998 is rarely queried, then you may want to evict after 1 day of no access:

```
ALTER TABLE sales_1998

ILM ADD POLICY NO INMEMORY AFTER 1 DAYS OF NO ACCESS;
```

Queries of an evicted segment are never blocked. The database can always access the data through the traditional buffer cache mechanism.

See Also:

- "Row Data in the Database Buffer Cache (page 2-5)"
- Oracle Database VLDB and Partitioning Guide

4.7.3 How ADO Works with Columnar Data

From the ADO perspective, the IM column store is another storage tier.

This section contains the following topics:

How Heat Map Works (page 4-29)

When enabled, Heat Map automatically discovers data access patterns. ADO uses the Heat Map data to implement user-defined policies at the database level.

How Policy Evaluation Works (page 4-29)

The policy evaluation for IM column store policies uses the same infrastructure as the evaluation of other ADO policies. The database evaluates and executes policies automatically during the maintenance window.

4.7.3.1 How Heat Map Works

When enabled, Heat Map automatically discovers data access patterns. ADO uses the Heat Map data to implement user-defined policies at the database level.

Heat Map automatically tracks usage information at the row and segment levels. At the row level, Heat Map tracks data modification times, and then aggregates these times to the block level. At the segment level, Heat Maps tracks times for modifications, full table scans, and index lookups.

When an IM column store is enabled, Heat Map tracks access patterns for columnar data. For example, the sales table may be "hot," whereas the locations table may be "cold." The ADO algorithms work the same way for columnar data as for row-based data.

The database periodically writes Heat Map data to the data dictionary. The database exposes Heat Map data in data dictionary views. For example, to obtain the read and write time for In-Memory objects, query the ALL_HEAT_MAP_SEGMENT view.

See Also:

- Oracle Database VLDB and Partitioning Guide to learn more about Heat Map
- Oracle Database Reference to learn about the ALL_HEAT_MAP_SEGMENT view

4.7.3.2 How Policy Evaluation Works

The policy evaluation for IM column store policies uses the same infrastructure as the evaluation of other ADO policies. The database evaluates and executes policies automatically during the maintenance window.

The database evaluates policies using Heat Map statistics, which are stored in the data dictionary. Setting INMEMORY attributes is mostly a metadata operation, and thus minimally affects performance.

ADO uses the Job Scheduler to perform population. The In-Memory Coordinator Process (IMCO) performs the population.

See Also:

"In-Memory Coordinator Process (IMCO) (page 2-19)"

4.7.4 Controls for ADO and the IM Column Store

Enable Heat Map using the ${\tt HEAT_MAP}$ initialization parameter. Control ADO through a SQL and PL/SQL interface.

ILM Clause in DDL Statements

No new SQL statements are required to create In-Memory policies, but the ILM clause has new options. The following table describes SQL options for ADO and the IM column store.

Table 4-3 ILM Clause for ADO and the IM Column Store

Clause	Description	Examples
SET INMEMORY	Sets the INMEMORY attribute for the object	ALTER TABLE sh.sales ILM ADD POLICY SET INMEMORY MEMCOMPRESS FOR QUERY LOW PRIORITY HIGH SEGMENT AFTER 30 DAYS OF CREATION;
MODIFY INMEMORY	Modifies the compression level for the object	ALTER TABLE sh.customers ILM ADD POLICY MODIFY INMEMORY MEMCOMPRESS FOR QUERY HIGH PRIORITY CRITICAL SEGMENT AFTER 30 DAYS OF CREATION;
NO INMEMORY	Sets the NO INMEMORY attribute for the object	ALTER TABLE sh.products ILM ADD POLICY NO INMEMORY SEGMENT AFTER 30 DAYS OF CREATION;

Initialization Parameters

The following table describes initialization parameters that are relevant for ADO and the IM column store.

Table 4-4 Initialization Parameters for ADO and the IM Column Store

Initialization Parameter	Description
COMPATIBLE	Specifies the release with which the database must maintain compatibility. For ADO to manage the IM column store, set this parameter to 12.2.0 or higher.
HEAT_MAP	Enables both the Heat Map and ADO features. For ADO to manage the IM column store, set this parameter to ON.

Table 4-4 (Cont.) Initialization Parameters for ADO and the IM Column Store

Initialization Parameter	Description
INMEMORY_SIZE	Enables the IM column store. This parameter must be set to a nonzero value.

PL/SQL Packages

The following table describes PL/SQL packages that are relevant for ADO and the IM column store.

Table 4-5 PL/SQL Packages for ADO and the IM Column Store

Package	Description
DBMS_HEATMAP	Displays detailed Heat Map data at the tablespace, segment, object, extent, and block levels.
DBMS_ILM	Implements ILM strategies using ADO policies.
DBMS_ILM_ADMIN	Customizes ADO policy execution.

V\$ and Data Dictionary Views

The following table describes views that are relevant for ADO and the IM column store.

Table 4-6 Views for ADO and the IM Column Store

View	Description
DBA_HEAT_MAP_SEG_HISTOGRAM	Displays segment access information for all segments visible to the user.
DBA_HEAT_MAP_SEGMENT	Displays the latest segment access time for all segments visible to the user.
DBA_HEATMAP_TOP_OBJECTS	Displays heat map information for the top 10000 objects by default.
DBA_HEATMAP_TOP_TABLESPACES	Displays heat map information for the top 10000 tablespaces.
DBA_ILMDATAMOVEMENTPOLICIES	Displays information specific to data movement-related attributes of an ADO policy in a database. The action_type column describes policies related to the IM column store. Possible values are COMPRESSION, STORAGE, EVICT, and ANNOTATE.
V\$HEAT_MAP_SEGMENT	Displays real-time segment access information.

See Also:

Oracle Database Reference to learn more about initialization parameters, packages, and views

4.7.5 Creating an ADO Policy for the IM Column Store

You can use ADO policies to set, modify, or remove the INMEMORY clause for objects based on Heat Map statistics.

To create an ADO IM column store policy, specify the ILM ADD POLICY clause in an ALTER TABLE statement, followed by one of the following subclauses:

• SET INMEMORY ... SEGMENT

This option is useful when you want to mark segments with the INMEMORY attribute only when DML activity subsides.

• MODIFY INMEMORY ... MEMCOMPRESS ... SEGMENT

Storing data uncompressed or at the MEMCOMPRESS FOR DML level is appropriate when it is frequently modified. The alternative compression levels are more suited for queries. If the activity on a segment transitions from mostly writes to mostly reads, then you can use the MODIFY clause to apply a different compression method.

NO INMEMORY ... SEGMENT

This option is useful when access to a segment decreases with time (it becomes "cold"), and to prevent population of this segment as a result of random access.

Prerequisites

Before you can use an ADO IM column store policy, you must meet the following prerequisites:

- Enable the IM column store for the database by setting the INMEMORY_SIZE initialization parameter to a non-zero value and restarting the database.
- The HEAT_MAP initialization parameter must be set to ON.
 - Heat Map provides data access tracking at the segment-level and data modification tracking at the segment and row level.
- The COMPATIBLE initialization parameter must be set to 12.2.0 or higher.

To create an ADO policy:

- 1. In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- 2. Use an ALTER TABLE statement with the ILM ADD POLICY ... INMEMORY clause.

Example 4-16 Creating an Eviction Policy

In this example, you create a policy specifying that oe.order_items table is evicted from the IM column store if it has not been accessed in three days. An ADO IM column store policy must be a segment-level policy.

```
ALTER TABLE oe.order_items ILM ADD POLICY
NO INMEMORY SEGMENT
AFTER 3 DAYS OF NO ACCESS;
```

Example 4-17 Executing an ILM Policy Using DBMS_ILM

You can also evaluate and executes policies manually. Thus, you can programmatically decide when you want an object compressed or tiered. The following example manually executes an ADO task for sh.sales:

Part III

Optimizing In-Memory Queries

This Part explains how to optimize queries using In-Memory Expressions, join groups, and In-Memory aggregation. It also explains how the IM column store repopulates modified data.

This Part contains the following chapters:

Optimizing Queries with In-Memory Expressions (page 5-1)

In the context of the IM column store, an **expression** is a combination of one or more values, operators, and SQL or PL/SQL functions (DETERMINISTIC only) that resolve to a value.

Optimizing Joins with Join Groups (page 6-1)

A **join group** is a user-created dictionary object that lists two columns that can be meaningfully joined.

Optimizing Joins with In-Memory Aggregation (page 7-1)

Starting with Oracle Database 12*c* Release 1 (12.1.0.2), **In-Memory Aggregation (IM aggregation)** enables queries to aggregate while scanning.

Optimizing Repopulation of the IM Column Store (page 8-1)

The IM column store periodically refreshes objects that have been modified. You can control this behavior using initialization parameters and the DBMS_INMEMORY package.

Optimizing Queries with In-Memory Expressions

In the context of the IM column store, an **expression** is a combination of one or more values, operators, and SQL or PL/SQL functions (DETERMINISTIC only) that resolve to a value.

The Expression Statistics Store (ESS) automatically tracks the results of frequently evaluated ("hot") expressions. You can use the DBMS_INMEMORY_ADMIN package to capture hot expressions and populate them as hidden virtual columns, or drop some or all of them.

This section contains the following topics:

About IM Expressions (page 5-1)

By default, the DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS procedure identifies and populates "hot" expressions, called **In-Memory**

Expressions (IM expressions).

Configuring IM Expression Usage (page 5-11)

Optionally, use INMEMORY_EXPRESSIONS_USAGE to choose which types of IM expressions are eligible for population, or to disable population of all IM expressions.

Capturing and Populating IM Expressions (page 5-12)

The IME_CAPTURE_EXPRESSIONS procedure captures and populates the 20 most frequently accessed ("hottest") expressions in the database in the specified time range. The IME_POPULATE_EXPRESSIONS procedure forces the population of expressions captured in the latest invocation of DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS.

Dropping IM Expressions (page 5-14)

The DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS procedure drops all SYS_IME expression virtual columns in the database. The DBMS_INMEMORY.IME_DROP_EXPRESSIONS procedure drops a specified set of SYS_IME virtual columns from a table.

5.1 About IM Expressions

By default, the DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS procedure identifies and populates "hot" expressions, called **In-Memory Expressions (IM expressions)**.

An IM expression is materialized as a hidden virtual column, but is accessed in the same way as a non-virtual column. To store the materialized expressions, the IM column store uses special compression formats such as fixed-width vectors and dictionary encoding with fixed-width codes.

Oracle Database automatically identifies the expressions that are candidates for population in the IM column store. In DBA_IM_EXPRESSIONS.COLUMN_NAME, IM expression columns have the prefix SYS_IME. You cannot create SYS_IME columns directly. For example, consider the following query, which specifies two expressions, aliased weekly_sal and ann_comp:

The arithmetical expressions ROUND(salary*12/52,2) and 12*(salary*NVL(commission_pct,0)+salary) are computationally intensive and frequently, which makes them candidates for hidden IM expression columns.

The DBMS_INMEMORY_ADMIN package is the primary interface for managing IM expressions:

- To induce the database to identify IM expressions and add them to their respective tables during the next repopulation, use IME_CAPTURE_EXPRESSIONS.
- To force immediate population of IM expressions, use IME_POPULATE_EXPRESSIONS.
- To drop SYS_IME columns, use DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS or DBMS_INMEMORY.IME_DROP_EXPRESSIONS.

This section contains the following topics:

Purpose of IM Expressions (page 5-3)

IM expressions speed queries of large data sets by precomputing computationally intensive expressions. IM expressions especially benefit frequently executed table joins, projections, and predicate evaluations.

How IM Expressions Work (page 5-4)

To identify expressions as candidates for IM expressions, the database queries the ESS. The optimizer uses the ESS to maintain statistics about expression evaluation for a particular table.

User Interfaces for IM Expressions (page 5-9)

The DBMS_INMEMORY_ADMIN package, DBMS_INMEMORY package, and INMEMORY_EXPRESSIONS_USAGE initialization parameter control the behavior of IM expressions.

Basic Tasks for IM Expressions (page 5-11)

The default setting of INMEMORY_EXPRESSIONS_USAGE enables the database to use both dynamic and static IM expressions. You must use DBMS_INMEMORY_ADMIN to populate the expressions in the IM column store.

See Also:

- Oracle Database SQL Language Reference to learn more about expressions
- Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS_INMEMORY_ADMIN
- Oracle Database Reference to learn more about the DBA_IM_EXPRESSIONS view

5.1.1 Purpose of IM Expressions

IM expressions speed queries of large data sets by precomputing computationally intensive expressions. IM expressions especially benefit frequently executed table joins, projections, and predicate evaluations.

The primary advantages of IM expressions are as follows:

- A query does not need to recalculate the expressions every time. If the IM column store does not populate the expression results, then the database must compute them for every row, which can be resource intensive. The database incurs the CPU overhead during the population.
- The materialization of IM expressions enables the database to take advantage of performance-enhancing features such as SIMD vector processing and IMCU pruning.
- The database, rather than the user, tracks which expressions are most active.

IM expressions and materialized views address the same problem: how to avoid repeatedly evaluating expressions. However, IM expressions have advantages over materialized views:

- IM expressions can capture data that is not persistently stored.
 For example, the IM column store can automatically cache internal computations based on expressions in the query.
- To be used effectively, a materialized view must have all columns listed in the query, or the query must join the view and the base tables. In contrast, any query containing an IM expression can benefit.
- The database identifies and creates IM expressions automatically, unlike materialized views, which are user-created objects.

See Also:

- "In-Memory Storage Indexes (page 2-14)"
- "Expression Statistics Store (ESS) (page 2-18)"
- Oracle Database Data Warehousing Guide to learn more about materialized views

5.1.2 How IM Expressions Work

To identify expressions as candidates for IM expressions, the database queries the ESS. The optimizer uses the ESS to maintain statistics about expression evaluation for a particular table.

This section contains the following topics:

IM Expressions Infrastructure (page 5-4)

The IM expressions infrastructure is responsible for computing and populating the results of IM expressions, IM virtual columns, and any other useful internal computations in the IM column store. These optimizations primarily benefit analytic queries.

Capture of IM Expressions (page 5-5)

Whenever you invoke the IME_CAPTURE_EXPRESSIONS procedure, the database queries the ESS, and identifies the 20 most frequently accessed ("hottest") expressions in the specified time range.

How the ESS Works (page 5-6)

The ESS is a repository maintained by the optimizer to store statistics about expression evaluation.

How the Database Populates IM Expressions (page 5-7)

Under the direction of In-Memory Coordinator Process (IMCO), Space Management Worker Processes (Wnnn) load IM expressions into IMEUs automatically.

How IMEUs Relate to IMCUs (page 5-8)

For any row, the physical columns reside in the IMCU, and the virtual columns reside in an associated IMEU. The IMEU is read-only and columnar, just like the IMCU.

5.1.2.1 IM Expressions Infrastructure

The IM expressions infrastructure is responsible for computing and populating the results of IM expressions, IM virtual columns, and any other useful internal computations in the IM column store. These optimizations primarily benefit analytic queries.

Populated results can include function evaluations on columns used in project, scan, or join expressions. The IM column store can automatically cache internal computations based on the expressions evaluated by the SQL runtime engine during query evaluation.

Virtual Columns

Besides populating an IM expression, the IM column store can populate an In-Memory virtual column. The underlying mechanism is the same: an IM expression is a virtual column. However, IM virtual columns are user-created and exposed, whereas IM expressions are database-created and hidden.

See Also:

"Enabling and Disabling Columns for In-Memory Tables (page 4-16)"

Static Expressions: Binary JSON Columns

The IM expressions infrastructure supports both dynamic expressions (IM expressions and virtual columns) and static expressions. Starting in Oracle Database 12c Release 2 (12.2), the IM column store supports a binary JSON format that performs better than row-oriented JSON text storage. The database uses the IM expression infrastructure to load an efficient binary representation of JSON text columns as virtual columns. Queries access the actual JSON data, but use optimized virtual columns to speed access.

Oracle Database supports multiple JSON functions: JSON_TABLE, JSON_VALUE, and JSON_EXISTS. The INMEMORY_EXPRESSIONS_USAGE initialization parameter controls the behavior of both dynamic expressions and static expressions.

See Also:

- Oracle Database JSON Developer's Guide to learn more about using JSON with Database In-Memory
- Oracle Database Reference to learn about INMEMORY_EXPRESSIONS_USAGE and ALL JSON COLUMNS

5.1.2.2 Capture of IM Expressions

Whenever you invoke the IME_CAPTURE_EXPRESSIONS procedure, the database queries the ESS, and identifies the 20 most frequently accessed ("hottest") expressions in the specified time range.

The time range is either the past 24 hours, or since database creation. The database only considers expressions on tables that are at least partially populated in the IM column store.

The database adds the 20 hottest expressions to their respective tables as hidden SYS_IME virtual columns and applies the default INMEMORY column compression clause. If any SYS_IME columns that were added during a previous invocation are no longer in the latest expression list, then the database changes their attribute to NO INMEMORY.

Figure 5-1 Capturing SYS_IME Columns



The maximum number of SYS_IME columns for a table is 50, regardless of whether the attribute is INMEMORY. After a table reaches the 50-expression limit, the database does not add new SYS_IME columns. To permit new expressions, you must drop SYS_IME columns with the DBMS_INMEMORY.IME_DROP_EXPRESSIONS or DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS procedures.

Both SYS_IME virtual columns and user-defined virtual columns count toward the 1000-column limit for a table. For example, if a table contains 980 non-virtual (on-disk) columns, then you can add only 20 virtual columns.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS_INMEMORY_ADMIN

5.1.2.3 How the ESS Works

The ESS is a repository maintained by the optimizer to store statistics about expression evaluation.


For each table, the ESS maintains expression statistics such as frequency of execution and cost of evaluation. When evaluating predicates, Oracle Database tracks and provides run-time feedback on evaluation counts and the dynamic costs of expressions. Based on the ESS statistics, the database may decide that queries would perform better if a specific expression were an IM expression.

Note:

Expressions cached in the ESS for a specific table only involve columns of this table. This rule is especially important when Oracle Database identifies deterministic PL/SQL functions as candidates for IM expressions.

Figure 5-2 ESS and IM Expressions

In this graphic, the ESS has determined two commonly used expressions on the employees table: $\texttt{ROUND}(\texttt{salary*12/52,2}) \text{ and } 12*(\texttt{salary*NVL}(\texttt{commission_pct,0}) + \texttt{salary}). When the database populates employees in the IM column store, two IMCUs store the columnar data. Each IMCU is associated with its only IMEU, which contains the derived values for the two commonly used expressions for the rows in that IMCU.$



Not every expression is a candidate for an IM expression. The database only considers expressions that will be accessed frequently. Because IM expressions are implemented as hidden virtual columns, they must also meet the restrictions for virtual columns.

Although the IM column store is a client of the ESS, the ESS is independent of Database In-Memory features. Other clients can also use ESS statistics, including the optimizer itself.

See Also:

- "Expression Statistics Store (ESS) (page 2-18)"
- Oracle Database Administrator's Guide to learn more about virtual columns

5.1.2.4 How the Database Populates IM Expressions

Under the direction of In-Memory Coordinator Process (IMCO), Space Management Worker Processes (Wnnn) load IM expressions into IMEUs automatically.

The database augments every In-Memory Compression Unit (IMCU) population or repopulation task with information about which virtual columns, either user-defined or IM expressions, to populate. The decision depends on the settings of the

INMEMORY_EXPRESSION_USAGE and INMEMORY_VIRTUAL_COLUMNS initialization parameters.

Note:

The DBMS_INMEMORY.IME_CAPTURE_EXPRESSIONS procedure adds automatically detected expressions as hidden virtual columns.

The Wnnn processes create the IMCUs. To create the IMEUs, the processes perform the following additional steps:

- **1.** Create the expression values
- **2.** Convert the values into columnar format, and compress them into In-Memory Expression Units (IMEUs)
- 3. Link each IMEU to its associated IMCU

Note:

As the number of expressions to store in IMEUs goes up, the worker processes may consume slightly more CPU to compute the expression values. This overhead may increase population time.

See Also:

- "Expression Statistics Store (ESS) (page 2-18)"
- "Space Management Worker Processes (Wnnn) (page 2-20)"
- "In-Memory Expression Units (IMEUs) (page 2-17)"
- Oracle Database PL/SQL Packages and Types Reference to learn more about the DBMS_INMEMORY.IME_CAPTURE_EXPRESSIONS procedure

5.1.2.5 How IMEUs Relate to IMCUs

For any row, the physical columns reside in the IMCU, and the virtual columns reside in an associated IMEU. The IMEU is read-only and columnar, just like the IMCU.

Because IMEUs are logical extensions of IMCUs created for a particular INMEMORY segment, by default they inherit the INMEMORY clause, and Oracle Real Applications Cluster (Oracle RAC) properties such as DISTRIBUTE and DUPLICATE. An IMEU is associated with one and only one IMCU. However, one IMCU may have multiple IMEUs. The database manages IMEUs as separate structures, making them easier to add and drop.

Note:

The IMEUs also contain user-created IM virtual columns.

If the source data changes, then the database changes the derived data in the IM expression during repopulation. For example, if a transaction updates 100 salary values in a table, then the Space Management Worker Processes (Wnnn) automatically update all IM expression values that are derived from these 100 changed values. The database repopulates an IMCU and its associated IMEUs together rather than first repopulating all IMCUs and then repopulating all IMEUs. IMCUs remain available for queries during IMCU repopulation.

See Also:

- "In-Memory Compression Units (IMCUs) (page 2-8)"
- "About Repopulation of the IM Column Store (page 8-1)"
- "Deploying IM Column Stores in Oracle RAC (page 10-1)"

5.1.3 User Interfaces for IM Expressions

The DBMS_INMEMORY_ADMIN package, DBMS_INMEMORY package, and INMEMORY_EXPRESSIONS_USAGE initialization parameter control the behavior of IM expressions.

This section contains the following topics:

INMEMORY_EXPRESSIONS_USAGE (page 5-9)

The INMEMORY_EXPRESSIONS_USAGE initialization parameter determines which type of IM expression is populated. The INMEMORY_VIRTUAL_COLUMNS initialization parameter controls the population of normal (non-hidden) virtual columns.

DBMS_INMEMORY_ADMIN and DBMS_INMEMORY (page 5-10)

To manage IM expressions, use the DBMS_INMEMORY_ADMIN and DBMS_INMEMORY packages.

5.1.3.1 INMEMORY_EXPRESSIONS_USAGE

The INMEMORY_EXPRESSIONS_USAGE initialization parameter determines which type of IM expression is populated. The INMEMORY_VIRTUAL_COLUMNS initialization parameter controls the population of normal (non-hidden) virtual columns.

When the IM column store is enabled (INMEMORY_SIZE is nonzero), INMEMORY_EXPRESSIONS_USAGE controls the type of IM expression that the database populates. The INMEMORY_EXPRESSIONS_USAGE initialization parameter has the following options:

• ENABLE

The database populates both static and dynamic IM expressions into the IM column store. Setting this value increases the In-Memory footprint for some tables. This is the default.

• STATIC_ONLY

A static configuration enables the IM column store to cache OSON (binary JSON) columns, which are marked with an IS_JSON check constraint. Internally, an OSON column is a hidden virtual column named SYS_IME_OSON.

• DYNAMIC_ONLY

The database only populates frequently used or "hot" expressions that have been added to the table as SYS_IME hidden virtual columns. Setting this value increases the In-Memory footprint for some tables.

• DISABLE

The database does not populate any IM expressions, whether static or dynamic, into the IM column store.

Note:

IM expressions do not support NLS-dependent data types.

Changing the value of INMEMORY_EXPRESSIONS_USAGE does not have an immediate effect on the IM expressions currently populated in the IM column store. For example, if you change INMEMORY_EXPRESSIONS_USAGE from DYNAMIC_ONLY to DISABLE, then the database does not immediately remove the stored IM expressions. Rather, the next repopulation excludes the disabled IM expressions, which effectively removes them.

See Also:

- Oracle Database JSON Developer's Guide to learn more about using JSON with Database In-Memory
- Oracle Database Reference to learn about INMEMORY_EXPRESSIONS_USAGE and ALL JSON COLUMNS

5.1.3.2 DBMS INMEMORY ADMIN and DBMS INMEMORY

To manage IM expressions, use the DBMS_INMEMORY_ADMIN and DBMS_INMEMORY packages.

PL/SQL Procedures for Managing IM Expressions

Package	Procedure	Description
DBMS_INMEMORY_ADMIN	IME_CAPTURE_EXPRESSIONS	This procedure captures and populates the 20 most frequently accessed ("hottest") expressions in the database in the specified time range.
DBMS_INMEMORY_ADMIN	IME_DROP_ALL_EXPRESSIONS	This procedure drops all SYS_IME virtual columns in the database.

Package	Procedure	Description
DBMS_INMEMORY_ADMIN	IME_POPULATE_EXPRESSIONS	This procedure forces the population of IM expressions captured in the latest invocation of the IME_CAPTURE_EXPRESS IONS procedure.
DBMS_INMEMORY	IME_DROP_EXPRESSIONS	This procedure drops a specified set of SYS_IME virtual columns from a table.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS_INMEMORY_ADMIN

5.1.4 Basic Tasks for IM Expressions

The default setting of INMEMORY_EXPRESSIONS_USAGE enables the database to use both dynamic and static IM expressions. You must use DBMS_INMEMORY_ADMIN to populate the expressions in the IM column store.

Typically, you perform IM expression tasks in the following sequence:

- Optionally, change the type of IM expression that the database can use. See "Configuring IM Expression Usage (page 5-11)".
- Capture and populate IM expressions.
 See "Capturing and Populating IM Expressions (page 5-12)".
- Optionally, drop some or all IM expressions.
 See "Dropping IM Expressions (page 5-14)".

5.2 Configuring IM Expression Usage

Optionally, use INMEMORY_EXPRESSIONS_USAGE to choose which types of IM expressions are eligible for population, or to disable population of all IM expressions.

Prerequisites

To enable the database to use IM expressions, the following conditions must be true:

- The INMEMORY_SIZE initialization parameter is set to a non-zero value.
- The value for the initialization parameter COMPATIBLE is set to 12.2.0 or higher.

Note:

In an Oracle Real Applications Cluster (RAC) database, the INMEMORY_EXPRESSIONS_USAGE initialization parameter does not require the same value on every database instance. Each IMCU independently lists virtual columns. Each IMCU could materialize different expressions based on the initialization parameter value and the virtual columns that existed when the IMCU was populated or repopulated.

To configure IM expression usage:

- 1. Log in to the database as a user with the appropriate privileges.
- **2.** To configure IM expression usage, use an ALTER SYSTEM statement to set INMEMORY_EXPRESSIONS_USAGE to any of the following values:
 - ENABLE (default) Enable dynamic and static IM expressions
 - STATIC_ONLY Enable only static IM expressions
 - DYNAMIC_ONLY Enable only dynamic IM expressions
 - DISABLE Disable all IM expressions

Example 5-1 Disabling IM Expressions

The following statement disables storage of IM expressions in the IM column store:

ALTER SYSTEM SET INMEMORY_EXPRESSIONS_USAGE='DISABLE';

See Also:

Oracle Database Reference to learn more about INMEMORY_EXPRESSIONS_USAGE

5.3 Capturing and Populating IM Expressions

The IME_CAPTURE_EXPRESSIONS procedure captures and populates the 20 most frequently accessed ("hottest") expressions in the database in the specified time range. The IME_POPULATE_EXPRESSIONS procedure forces the population of expressions captured in the latest invocation of

DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS.

Whenever you invoke the IME_CAPTURE_EXPRESSIONS procedure, the database queries the Expression Statistics Store (ESS), and considers only expressions on tables that are at least partially populated in the IM column store. The database adds the 20 hottest expressions to their respective tables as hidden virtual columns, prefixed with the string SYS_IME, and applies the default INMEMORY column compression clause. If any SYS_IME columns added during a previous invocation are no longer in the latest top 20 list, then the database marks them as NO INMEMORY.

If you do not invoke IME_POPULATE_EXPRESSIONS, then the database gradually repopulates SYS_IME columns when their parent IMCUs are repopulated. If a table is not repopulated, then the database does not repopulate new SYS_IME columns captured by the IME_CAPTURE_EXPRESSIONS procedure.

IME_POPULATE_EXPRESSIONS solves this problem by forcing repopulation.

Internally, the IME_POPULATE_EXPRESSIONS procedure invokes DBMS_INMEMORY.REPOPULATE for all tables that have SYS_IME columns with the INMEMORY attribute. To populate SYS_IME columns in a specified subset of tables, use DBMS_INMEMORY.REPOPULATE instead of DBMS_INMEMORY_ADMIN.IME_POPULATE_EXPRESSIONS.

Prerequisites

To enable the database to capture IM expressions, the following conditions must be true:

- The INMEMORY_EXPRESSIONS_USAGE initialization parameter must be set to a value other than DISABLE.
- The INMEMORY_SIZE initialization parameter is set to a non-zero value.
- The value for the initialization parameter COMPATIBLE must be set to 12.2.0 or higher.

To capture and populate IM expressions:

- 1. Log in to the database as a user with the appropriate privileges.
- **2.** Execute DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS with any of the following parameters:
 - CUMULATIVE The database considers all expression statistics since the creation of the database.
 - CURRENT The database considers only expression statistics from the past 24 hours.
- **3.** Optionally, execute DBMS_INMEMORY_ADMIN.IME_POPULATE_EXPRESSIONS to force immediate population of the latest IM expressions.

Example 5-2 Capturing the Top 20 IM Expressions in the Past 24 Hours

This example captures IM expressions using only the statistics gathered during the last day, and then forces immediate population:

```
EXEC DBMS_INMEMORY_ADMIN.IME_CAPTURE_EXPRESSIONS('CURRENT');
EXEC DBMS_INMEMORY_ADMIN.IME_POPULATE_EXPRESSIONS();
```

The following query of DBA_IM_EXPRESSIONS shows that two IM expressions are currently populated (sample output provided):

See Also:

- Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS_INMEMORY_ADMIN
- Oracle Database Reference to learn more about the DBA_IM_EXPRESSIONS view

5.4 Dropping IM Expressions

The DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS procedure drops all SYS_IME expression virtual columns in the database. The DBMS_INMEMORY.IME_DROP_EXPRESSIONS procedure drops a specified set of SYS_IME virtual columns from a table.

Typical reasons for dropping SYS_IME columns are space and performance. The maximum number of SYS_IME columns for a table, regardless of whether the attribute is INMEMORY or NO INMEMORY, is 50. After the 50-expression limit is reached for a table, the database will not add new SYS_IME columns. To make space for new expressions, you must manually drop SYS_IME columns with the DBMS_INMEMORY.IME_DROP_EXPRESSIONS or DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS procedures.

The IME_DROP_ALL_EXPRESSIONS procedure drops all SYS_IME columns from all tables, regardless of whether they have the INMEMORY attribute. In effect, the procedure acts as a database-wide reset button.

Using IME_DROP_ALL_EXPRESSIONS triggers a drop of all IMEUs and IMCUs for segments that have SYS_IME columns. For example, if 50 populated tables have one SYS_IME column each, then IME_DROP_ALL_EXPRESSIONS removes all 50 tables from the IM column store. To populate these segments again, you must use the DBMS_INMEMORY.POPULATE procedure or perform a full table scan.

Prerequisites

To drop IM expressions, the following conditions must be true:

- The INMEMORY_EXPRESSIONS_USAGE initialization parameter must be set to a value other than DISABLE.
- The INMEMORY_SIZE initialization parameter is set to a non-zero value.
- The value for the initialization parameter COMPATIBLE must be set to 12.2.0 or higher.

To drop IM expressions:

- 1. Log in to the database as a user with the appropriate privileges.
- 2. Execute either DBMS_INMEMORY_ADMIN.IME_DROP_ALL_EXPRESSIONS or DBMS_INMEMORY.IME_DROP_EXPRESSIONS. If you execute IME_DROP_EXPRESSIONS, then specify the following parameters:
 - schema_name The name of the schema that contains the In-Memory table
 - table_name The name of the In-Memory table

• column_name — The name of the SYS_IME column. By default this value is null, which specifies all SYS_IME columns in this table.

Example 5-3 Dropping All IM Expressions in a Table

This example drops all IM expressions in the hr.employees table:

EXEC DBMS_INMEMORY.IME_DROP_EXPRESSIONS('HR', 'EMPLOYEES');

See Also:

- *Oracle Database Reference* to learn more about the INMEMORY_EXPRESSIONS_USAGE initialization parameter
- Oracle Database PL/SQL Packages and Types Reference to learn more about the DBMS_INMEMORY_ADMIN and DBMS_INMEMORY packages
- Oracle Database Reference to learn more about the DBA_IM_EXPRESSIONS view

Optimizing Joins with Join Groups

A **join group** is a user-created dictionary object that lists two columns that can be meaningfully joined.

This chapter contains the following topics:

About In-Memory Joins (page 6-1)

Joins are an integral part of data warehousing workloads. The IM column store enhances the performance of joins when the tables being joined are stored in memory.

About Join Groups (page 6-2)

When the IM column store is enabled, the database can use join groups to optimize joins of tables populated in the IM column store.

Purpose of Join Groups (page 6-2)

In certain queries, join groups eliminate the performance overhead of decompressing and hashing column values.

How Join Groups Work (page 6-4)

In a join group, the database compresses all columns in the join group using the same common dictionary.

Creating Join Groups (page 6-7)

Define join groups using the CREATE INMEMORY JOIN GROUP statement. Candidates are columns that are frequently paired in a join predicate, for example, a column joining a fact and dimension table.

Monitoring Join Group Usage (page 6-10)

To determine whether queries are using the join group, you can pass the SQL ID to the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML function.

6.1 About In-Memory Joins

Joins are an integral part of data warehousing workloads. The IM column store enhances the performance of joins when the tables being joined are stored in memory.

Because of faster scan and join processing, complex multi-table joins and simple joins that use Bloom filters benefit from the IM column store. In a data warehousing environment, the most frequently-used joins involved a fact table and one or more dimension tables.

The following joins run faster when the tables are populated in the IM column store:

- Joins that are amenable to using Bloom filters
- Joins of multiple small dimension tables with one fact table
- Joins between two tables that have a primary key-foreign key relationship

6.2 About Join Groups

When the IM column store is enabled, the database can use join groups to optimize joins of tables populated in the IM column store.

A join group is a set of columns on which a set of tables is frequently joined. The column set contains one or more columns; the table set contains one or more tables. The columns in the join group can be in the same or different tables. For example, if sales and times frequently join on the time_id column, then you might create a join group for (times(time_id), sales(time_id)). The maximum number of columns in a join group is 255.

Note:

A column cannot be a member of multiple join groups.

When you create a join group, the database invalidates the current In-Memory contents of the tables referenced in the join group. Subsequent repopulation causes the database to re-encode the IMCUs of the tables with the common dictionary. Thus, Oracle recommends that you first create the join group, and then populate the tables.

Create join groups using the CREATE INMEMORY JOIN GROUP statement. To add columns to or drop columns from a join group, use an ALTER INMEMORY JOIN GROUP statement. Drop a join group using the DROP INMEMORY JOIN GROUP statement.

Note:

In Oracle Active Data Guard, a standby database ignores join group definitions. A standby database does not use common dictionaries, and executes queries as if join groups did not exist.

Example 6-1 Creating a Join Group

This example creates a join group named deptid_jg that includes the department_id column in the hr.employees and hr.departments tables.

```
CREATE INMEMORY JOIN GROUP deptid_jg
(hr.employees(department_id),hr.departments(department_id));
```

6.3 Purpose of Join Groups

In certain queries, join groups eliminate the performance overhead of decompressing and hashing column values.

Without join groups, if the optimizer uses a hash join but cannot use a Bloom filter, or if the Bloom filter does not filter rows effectively, then the database must decompress IMCUs and use an expensive hash join. To illustrate the problem, assume a star schema has a sales fact table and a vehicles dimension table. The following query joins these tables, but does not filter the output, which means that the database cannot use a Bloom filter:

```
SELECT v.year, v.name, s.sales_price
FROM vehicles v, sales s
WHERE v.name = s.name;
```

2 Hash Table 5 Hash Join Use the vehicle ID to Build a hash table using **PGA** uncompressed join column probe the hash table values from VEHICLES and find matching rows Row Sent to Hash Join Decompress only matching rows, hash them, and then send to hash join Sales **Table Scan** Scan the table, decompress matching rows, and then send them to the hash join Vehicles Table 3 Table Scan

The following figure illustrates how the database joins the two data sets.

Figure 6-1 Hash Join without Join Group

The database performs a hash join as follows:

1. Scans the vehicles table, decompresses the rows that satisfy the predicate (in this case, all rows satisfy the predicate because no filters exist), and sends the rows to the hash join

Scan SALES, and filter rows based on query predicates

- **2.** Builds a hash table in the PGA based on the decompressed rows
- **3.** Scans the sales table and applies any filters (in this case, the query does not specify filters)
- **4.** Decompresses matching rows from the IMCUs, hashes them, and then sends them to the join
- **5.** Probes the hash table using the join column, which in this case is the vehicle name

If a join group exists on the v.name and s.name columns, however, then the database can make the preceding steps more efficient, eliminating the decompression and filtering overhead. The benefits of join groups are:

- The database operates on *compressed* data.
- In a hash join based on a join group, the database uses an array instead of building a hash table.
 - The database stores codes for each join column value in a common dictionary. The database joins on the codes rather than on the actual column values. This technique avoids the overhead of copying row sources.
- The dictionary codes are dense and have a fixed length, which makes them space efficient.

• Optimizing a query with a join group is sometimes possible when it is not possible to use a Bloom filter.

See Also:

- "How a Join Group Uses a Common Dictionary (page 6-4)"
- "In-Memory Compression Units (IMCUs) (page 2-8)"

6.4 How Join Groups Work

In a join group, the database compresses all columns in the join group using the same common dictionary.

This section contains the following topics:

How a Join Group Uses a Common Dictionary (page 6-4)

A **common dictionary** is a table-level, instance-specific set of dictionary codes.

How a Join Group Optimizes Scans (page 6-5)

The key optimization is joining on common dictionary codes instead of column values, thereby avoiding the use of a hash table for the join.

See Also:

"How a Join Group Uses a Common Dictionary (page 6-4)"

6.4.1 How a Join Group Uses a Common Dictionary

A **common dictionary** is a table-level, instance-specific set of dictionary codes.

The database automatically creates a common dictionary in the IM column store when a join group is defined on the underlying columns. The common dictionary enables the join columns to share the same dictionary codes.

A common dictionary provides the following benefits:

- Encodes the values in the local dictionaries with codes from the common dictionary, which provides compression and increases the cache efficiency of the IMCU
- Enables joins to use dictionary codes to construct and probe the data structures used during hash joins
- Enables the optimizer to obtain statistics such as cardinality, distribution of column values, and so on

The following figure illustrates a common dictionary that corresponds to a join group created on the sales.name and vehicles.name tables.




Figure 6-2 Common Dictionary for a Join Group

	Sales Table			
4 3 0 5	4 3 0 5	2 3 4		
4 2 3 1	4 2 3 1	0 3 2 4		
1 2 5 5	1 2 5 5	2 1 4 5		
2 3 4 2	2 3 4 2	1 5 4 0		

Common Dictionary		
Name	ID	
Audi	0	
BMW	1	
CADILLAC	2	
PORSCHE	3	
TESLA	4	
VW	5	

When the database uses a common dictionary, the local dictionary for each CU does not store the original values: Audi, BMW, and so on. Instead, the local dictionary stores *references* to the values stored in the common dictionary. For example, the local dictionary might store 101 for Audi, 220 for BMW, and so on.

See Also:

"Local Dictionary (page 2-13)"

6.4.2 How a Join Group Optimizes Scans

The key optimization is joining on common dictionary codes instead of column values, thereby avoiding the use of a hash table for the join.


Consider the following query, which uses a join group to join vehicles and sales on the name column:

```
SELECT v.year, v.name, s.sales_price FROM vehicles v, sales s
```

```
WHERE v.name = s.name
AND v.name IN ('Audi', 'BMW', 'Porsche', 'VW');
```

The following figure illustrates how the join benefits from the common dictionary created on the join group.

Figure 6-3 Hash Join with Join Group



As illustrated in the preceding diagram, the database performs a hash join on the compressed data as follows:

- 1. Scans the vehicles table, and sends the dictionary codes (not the original column values) to the hash join: 0 (Audi), 1 (BMW), 2 (Cadillac), and so on
- 2. Builds an array of distinct common dictionary codes in the PGA
- **3.** Scans the sales table and applies any filters (in this case, the filter is for German cars only)
- **4.** Sends matching rows to the join in compressed format
- **5.** Looks up corresponding values in the array rather than probing a hash table, thus avoiding the need to compute a hash function on the join key columns

In this example, the vehicles table has only seven rows. The vehicles.name column has the following values:

```
Audi
BMW
Cadillac
Ford
Porsche
Tesla
VW
```

The common dictionary assigns a dictionary code to each distinct value. Conceptually, the common dictionary looks as follows:

```
Audi 0
BMW 1
Cadillac 2
Ford 3
Porsche 4
Tesla 5
VW 6
```

The database scans vehicles.name, starting at the first dictionary code in the first IMCU and ending at the last code in the last IMCU. It stores a 1 for every row that matches the filter (German cars only), and 0 for every row that does not match the filter. Conceptually, the array might look as follows:

```
array[0]: 1
array[1]: 1
array[2]: 0
array[3]: 0
array[4]: 1
array[5]: 0
array[6]: 1
```

The database now scans the sales fact table. To simplify the example, assume that the sales table only has 6 rows. The database scans the rows as follows (the common dictionary code for each value is shown in parentheses):

```
Cadillac (2)
Cadillac (2)
BMW (1)
Ford (3)
Audi (0)
Tesla (5)
```

The database then proceeds through the vehicles.name array, looking for matches. If a row matches, then the database sends the matching row with its associated common dictionary code, and retrieves the corresponding column value from the vehicles.name and sales.name IMCUs:

```
2 -> array[2] is 0, so no join
2 -> array[2] is 0, so no join
1 -> array[1] is 1, so join
3 -> array[3] is 0, so no join
0 -> array[0] is 1, so join
5 -> array[5] is 0, so no join
```

6.5 Creating Join Groups

Define join groups using the CREATE INMEMORY JOIN GROUP statement. Candidates are columns that are frequently paired in a join predicate, for example, a column joining a fact and dimension table.

The CREATE INMEMORY JOIN GROUP statement immediately defines a join group, which means that its metadata is visible in the data dictionary. The database does not immediately construct the common dictionary. Rather, the database builds the common dictionary the next time that a table referenced in the join group is populated or repopulated in the IM column store.

Guidelines

Creating, modifying, or dropping a join group typically invalidates all the underlying tables referenced in the join group. Thus, Oracle recommends that you create join groups *before* initially populating the tables.

To create a join group:

- 1. In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- **2.** Create a join group by using a statement in the following form:

```
CREATE INMEMORY JOIN GROUP join_group_name ( table1(col1), (table2(col2) );

For example, the following statement creates a join group named sales_products_jg:
```

```
CREATE INMEMORY JOIN GROUP sales_products_jg (sales(prod_id), products(prod_id));
```

3. Optionally, view the join group definition by querying the data dictionary (sample output included):

4. Populate the tables referenced in the join group, or repopulate them if they are currently populated.

See Also:

Oracle Database SQL Language Reference to learn about the CREATE INMEMORY JOIN GROUP statement

Example 6-2 Optimizing a Query Using a Join Group

In this example, you log in to the database as SYSTEM, and then create a join group on the prod_id column of sales and products, which are not yet populated in the IM column store:

```
CREATE INMEMORY JOIN GROUP
sh.sales_products_jg (sh.sales(prod_id), sh.products(prod_id));
```

You enable the sh.sales and sh.products tables for population in the IM column store:

```
ALTER TABLE sh.sales INMEMORY;
ALTER TABLE sh.products INMEMORY;
```

The following query indicates the tables are not yet populated in the IM column store (sample output included):

```
COL OWNER FORMAT a3
COL NAME FORMAT al0
COL STATUS FORMAT a20
SELECT OWNER, SEGMENT NAME NAME,
     POPULATE_STATUS STATUS
FROM V$IM_SEGMENTS;
no rows selected
```

Query both tables to populate them in the IM column store:

```
SELECT /*+ FULL(s) NO_PARALLEL(s) */ COUNT(*) FROM sh.sales s;
SELECT /*+ FULL(p) NO_PARALLEL(p) */ COUNT(*) FROM sh.products p;
```

The following query indicates the tables are now populated in the IM column store (sample output included):

```
COL OWNER FORMAT a3
COL NAME FORMAT al0
COL PARTITION FORMAT al3
COL STATUS FORMAT a20
SELECT OWNER, SEGMENT_NAME NAME, PARTITION_NAME PARTITION,
     POPULATE_STATUS STATUS, BYTES_NOT_POPULATED
FROM V$IM_SEGMENTS;
```

OWN	NAME	PARTITION	STATUS	BYTES_NOT_POPULATED
SH	SALES	SALES_Q3_1998	COMPLETED	0
SH	SALES	SALES_Q4_2001	COMPLETED	0
SH	SALES	SALES_Q4_1999	COMPLETED	0
SH	PRODUCTS		COMPLETED	0
SH	SALES	SALES_Q1_2001		0
SH	SALES	SALES_Q1_1999		0
SH	SALES	SALES_Q2_2000		0
SH	SALES	SALES_Q2_1998	COMPLETED	0
SH	SALES	SALES_Q3_2001		0
SH	SALES	SALES_Q3_1999	COMPLETED	0
SH	SALES	SALES_Q4_2000		0
SH	SALES	SALES_Q4_1998	COMPLETED	0
SH	SALES	SALES_Q1_2000	COMPLETED	0
SH	SALES	SALES_Q1_1998	COMPLETED	0
SH	SALES	SALES_Q2_2001	COMPLETED	0
SH	SALES	SALES_Q2_1999	COMPLETED	0
SH	SALES	SALES_Q3_2000	COMPLETED	0

Query DBA_JOINGROUPS to get information about the join group (sample output included):

```
COL JOINGROUP_NAME FORMAT a18
COL TABLE_NAME FORMAT a8
COL COLUMN_NAME FORMAT a7
SELECT JOINGROUP_NAME, TABLE_NAME, COLUMN_NAME, GD_ADDRESS
FROM DBA_JOINGROUPS;
JOINGROUP_NAME TABLE_NA COLUMN_ GD_ADDRESS
```

```
SALES_PRODUCTS_JG SALES PROD_ID 00000000142AE50 SALES_PRODUCTS_JG PRODUCTS PROD_ID 00000000142AE50
```

The preceding output shows that the join group sales_products_jg joins on the same common dictionary address.

See Also:

- Oracle Database SQL Language Reference to learn about the CREATE INMEMORY JOIN GROUP statement
- Oracle Database Reference to learn about the DBA_JOINGROUPS view

6.6 Monitoring Join Group Usage

To determine whether queries are using the join group, you can pass the SQL ID to the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML function.

From the command line, Oracle recommends querying the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML output for a SQL ID. If the query returns rows, then the database used the join group for the statement associated with this SQL ID. Otherwise, the database did not use the join group.

Prerequisites

To monitor join groups, you must meet the following prerequisites:

- A join group must exist.
- The columns referenced by the join group must have been populated after join group creation.
- You must execute a join query that could potentially use the join group.

To monitor join group usage:

- 1. Log in to the database with the necessary privileges.
- **2.** Obtain the SQL ID for the query you want to monitor.
 - For example, execute the query that you want to monitor, and then query $V \SESSION.PREV_SQL_ID.$
- **3.** Use the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML.EXTRACT function to determine whether the database used the join group in the hash join.
 - If querying the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML.EXTRACT function output returns rows, then the database used the join group.

Example 6-3 Monitoring a Join Group

In this example, you create a join group on the prod_id columns of sh.products and sh.sales tables, and then join these tables on this column. Your goal is to determine whether the join query used the join group. You grant the sh account administrative privileges. You log in as sh, and then proceed as follows:

1. Create a SQL*Plus variable for the SQL ID as follows:

```
VAR B_SQLID VARCHAR2(13)
```

2. Apply the INMEMORY attribute to the sh.products and sh.sales tables as follows:

```
ALTER TABLE sales INMEMORY MEMCOMPRESS FOR QUERY; ALTER TABLE products INMEMORY MEMCOMPRESS FOR QUERY;
```

3. Create a join group on prod_id:

```
CREATE INMEMORY JOIN GROUP sh_jg (products(prod_id));
```

4. Scan the tables to populate them in the IM column store:

```
SELECT /*+ FULL(s) */ COUNT(*) FROM sales s;
SELECT /*+ FULL(p) */ COUNT(*) FROM products p;
```

5. Execute a query that joins on the prod_id column, and then aggregates product sales:

```
SELECT /*+ USE_HASH(sales) LEADING(products sales) MONITOR */
    products.prod_id, SUM(sales.amount_sold)
FROM products, sales
WHERE products.prod_id = sales.prod_id
GROUP BY products.prod_id;
```

6. Obtain the SQL ID of the preceding aggregation query:

```
BEGIN

SELECT PREV_SQL_ID

INTO :B_SQLID

FROM V$SESSION

WHERE SID=USERENV('SID');

FND;
```

7. Determine whether the database used the join group:

The query returned rows, so the database used the join group for the statement associated with this SQL ID.

See Also:

- Oracle Database PL/SQL Packages and Types Reference to learn about the DBMS_SQLTUNE.REPORT_SQL_MONITOR_XML function
- Oracle Database Reference to learn about the V\$SESSION view

Optimizing Joins with In-Memory Aggregation

Starting with Oracle Database 12*c* Release 1 (12.1.0.2), **In-Memory Aggregation (IM aggregation)** enables queries to aggregate while scanning.

This section contains the following topics:

About IM Aggregation (page 7-1)

IM aggregation optimizes query blocks involving aggregation and joins from a large table to multiple small tables.

Purpose of IM Aggregation (page 7-2)

IM aggregation pre-processes the small tables to accelerate the per-row work performed on the large table.

How IM Aggregation Works (page 7-4)

A typical analytic query distributes rows among processing stages.

Controls for IM Aggregation (page 7-14)

IM aggregation is integrated with the optimizer. No new SQL or initialization parameters are required. IM aggregation does not need additional indexes, foreign keys, or dimensions.

In-Memory Aggregation: Example (page 7-15)

In this example, the business question is "How many products were sold in each category in each calendar year?"

7.1 About IM Aggregation

IM aggregation optimizes query blocks involving aggregation and joins from a large table to multiple small tables.

The KEY VECTOR and VECTOR GROUP BY operations use efficient arrays for joins and aggregation. The optimizer chooses VECTOR GROUP BY for GROUP BY operations based on cost. The optimizer does not choose VECTOR GROUP BY aggregations for GROUP BY ROLLUP, GROUPING SETS, or CUBE operations.

Note:

IM aggregation is also called *vector aggregation* and *VECTOR GROUP BY aggregation*.

IM aggregation requires INMEMORY_SIZE to be set to a nonzero value. However, IM aggregation does not require that the referenced tables be *populated* in the IM column store.

See Also:

- "Enabling the IM Column Store for a Database (page 3-3)"
- Oracle Database Data Warehousing Guide to learn more about SQL aggregation

7.2 Purpose of IM Aggregation

IM aggregation pre-processes the small tables to accelerate the per-row work performed on the large table.

A typical analytic query aggregates from a fact table, and joins it to dimension tables. This type of query scans a large volume of data, with optional filtering, and performs a GROUP BY of between 1 and 40 columns. The first aggregation on the fact table processes the most rows.

Before Oracle Database 12c, the only GROUP BY operations were HASH and SORT. The VECTOR GROUP BY is an additional cost-based transformation that transforms a join between a dimension and fact table into a filter. The database can apply this filter during the fact table scan. The joins use key vectors, which are similar to Bloom filters, and the aggregation uses a VECTOR GROUP BY.

Note:

Although vector transformations are independent of the IM column store, they can be applied very efficiently to In-Memory data through SIMD vector processing.

IM aggregation enables vector joins and GROUP BY operations to occur *simultaneously* with the scan of the large table. Thus, these operations aggregate as they scan, and do not need to wait for table scans and join operations to complete. IM aggregation optimizes CPU usage, especially the CPU cache.

IM aggregation can greatly improve query performance. The database can create a report outline dynamically, and then fill in report details during the scan of the fact table.

This section contains the following topics:

When IM Aggregation Is Useful (page 7-3)

IM aggregation improves performance of queries that join relatively small tables to a relatively large fact table, and aggregate data in the fact table. This typically occurs in a star or snowflake query.

When IM Aggregation Is Not Beneficial (page 7-4)

IM aggregation benefits certain star queries when sufficient system resources exist. Other queries may receive little or no benefit.

See Also:

- "CPU Architecture: SIMD Vector Processing (page 2-21)"
- Oracle Database SQL Tuning Guide to learn more about query transformations

7.2.1 When IM Aggregation Is Useful

IM aggregation improves performance of queries that join relatively small tables to a relatively large fact table, and aggregate data in the fact table. This typically occurs in a star or snowflake query.

Both row-store tables and tables in the IM column store can benefit from IM aggregation.


Example 7-1 VECTOR GROUP BY

Consider the following query, which performs a join of the customers dimension table with the sales fact table:

```
SELECT c.customer_id, s.quantity_sold, s.amount_sold
FROM customers c, sales s
WHERE c.customer_id = s.customer_id
AND c.country_id = 'FR';
```

When both tables are populated in the IM column store, the database can use SIMD vector processing to scan the row sets and apply filters. The following figure shows how the query uses vector joins. The optimizer converts the predicate on the customers table, c.country_id='FR' into a filter on the sales fact table. The filter is country_id='FR'. Because sales is stored in columnar format, the query only needs to scan one column to determine the result.

Figure 7-1 Vector Joins Using In-Memory Column Store



See Also:

"CPU Architecture: SIMD Vector Processing (page 2-21)"

7.2.2 When IM Aggregation Is Not Beneficial

IM aggregation benefits certain star queries when sufficient system resources exist. Other queries may receive little or no benefit.

Situations Where VECTOR GROUP BY Aggregation Is Not Advantageous

Specifically, VECTOR GROUP BY aggregation does not benefit performance in the following scenarios:

- Joins are performed between two very large tables.
 - By default, the optimizer chooses a VECTOR GROUP BY transformation only if a relatively small table is joined to a relatively large table.
- Dimensions contain more than 2 billion rows.
 - The VECTOR GROUP BY transformation is not used if a dimension contains more than 2 billion rows.
- The system does not have sufficient memory.

Most databases that use the IM column store benefit from IM aggregation.

7.3 How IM Aggregation Works

A typical analytic query distributes rows among processing stages.

The stages are as follows:

- 1. Filtering tables and producing row sets
- 2. Joining row sets
- **3.** Aggregating rows

The VECTOR GROUP BY transformation combines the work in the different stages, converting joins to filters and aggregating while scanning the fact table.

The unit of work between stages is called a data flow operator (DFO). VECTOR GROUP BY aggregation uses a DFO for each dimension to create a key vector structure and temporary table. When aggregating measure columns from the fact table, the database uses this key vector to translate a fact join key to its dense grouping key. The late materialization step joins on the dense grouping keys to the temporary tables.

This section contains the following topics:

When the Optimizer Chooses IM Aggregation (page 7-5)

The optimizer decides whether to use vector transformation based on the size of the key vector (that is, the distinct join keys), the number of distinct grouping keys, and other factors. The optimizer tends to choose this transformation when dimension join keys have low cardinality.

Key Vector (page 7-6)

A **key vector** is a data structure that maps between dense join keys and dense grouping keys.

Two Phases of IM Aggregation (page 7-7)

Typically, VECTOR GROUP BY aggregation processes each dimension in sequence, and then processes the fact table.

IM Aggregation: Scenario (page 7-8)

This section gives a conceptual example of how VECTOR GROUP BY aggregation works.

7.3.1 When the Optimizer Chooses IM Aggregation

The optimizer decides whether to use vector transformation based on the size of the key vector (that is, the distinct join keys), the number of distinct grouping keys, and other factors. The optimizer tends to choose this transformation when dimension join keys have low cardinality.

Oracle Database uses VECTOR GROUP BY aggregation to perform data aggregation when the following conditions are met:

• The queries or subqueries aggregate data from a fact table and join the fact table to one or more dimensions.

Multiple fact tables joined to the same dimensions are also supported assuming that these fact tables are connected only through joins to the dimension. In this case, VECTOR GROUP BY aggregates fact table separately and then joins the results on the grouping keys.

 The dimensions and fact table are connected to each other only through join columns.

Specifically, the query must not have any other predicates that refer to columns across multiple dimensions or from both a dimension and the fact table. If a query performs a join between two or more tables and then joins the result to the fact, then VECTOR GROUP BY aggregation treats the multiple dimensions as a single dimension.

Note:

You can direct the database to use VECTOR GROUP BY aggregation for a query by using query block hints or table hints.

VECTOR GROUP BY aggregation does not support the following:

- Semi-joins and anti-joins across multiple dimensions or between a dimension and the fact table
- Equijoins across multiple dimensions
- Aggregations performed using the DISTINCT function

Note:

Bloom filters and VECTOR GROUP BY aggregation and are mutually exclusive. Therefore, if a query uses Bloom filters to join row sets, then VECTOR GROUP BY aggregation is not applicable to the processing of this query.

See Also:

Oracle Database Data Warehousing Guide to learn more about SQL aggregation

7.3.2 Key Vector

A **key vector** is a data structure that maps between dense join keys and dense grouping keys.

A dense key is a numeric key that is stored as a native integer and has a range of values. A dense join key represents all join keys whose join columns come from a particular fact table or dimension. A dense grouping key represents all grouping keys whose grouping columns come from a particular fact table or dimension. A key vector enables fast lookups.

Example 7-2 Key Vector

Assume that the hr.locations tables has values for country_id as shown (only the first few results are shown):

SQL> SELECT country_id FROM locations;

CO
-IT
IT
JP
JP
US
US
US
US
US
CA
CA
CA
CN

A complex analytic query applies the filter WHERE country_id='US' to the locations table. A key vector for this filter might look like the following one-dimensional array:

In the preceding array, 1 is the dense grouping key for country_id='US'. The 0 values indicate rows in locations that do not match this filter. If a query uses the filter WHERE country_id IN ('US','JP'), then the array might look as follows, where 2 is the dense grouping key for JP and 1 is the dense grouping key for US:

0 0 2

7.3.3 Two Phases of IM Aggregation


Typically, VECTOR GROUP BY aggregation processes each dimension in sequence, and then processes the fact table.

When performing IM aggregation, the database proceeds as follows:

- 1. Process each dimension sequentially as follows:
 - a. Find the unique dense grouping keys.
 - **b.** Create a key vector.
 - **c.** Create a temporary table (CURSOR DURATION MEMORY).

The following figure illustrates the steps in this phase, beginning with the scan of the dimension table in DFO 0, and ending with the creation of a temporary table. In the simplest form of parallel GROUP BY or join processing, the database processes each join or GROUP BY in its own DFO.

Figure 7-2 Phase 1 of In-Memory Aggregation



- **2.** Process the fact table.
 - a. Process all the joins and aggregations using the key vectors created in the preceding phase.
 - **b.** Join back the results to each temporary table.

Figure 7-3 (page 7-8) illustrates phase 2 in a join of the fact table with two dimensions. In DFO 0, the database performs a full scan of the fact table, and then uses the key vectors for each dimension to filter out nonmatching rows. DFO 2 joins the results of DFO 0 with DFO 1. DFO 4 joins the result of DFO 2 with DFO 3.




Figure 7-3 Phase 2 of In-Memory Aggregation

7.3.4 IM Aggregation: Scenario

This section gives a conceptual example of how VECTOR GROUP BY aggregation works.

Note:

The scenario does not use the sample schema tables or show an actual execution plan.

This section contains the following topics:

Sample Analytic Query of a Star Schema (page 7-9)

This sample star schema in this scenario contains the sales_online fact table and two dimension tables: geography and products.

Step 1: Key Vector and Temporary Table Creation for geography Dimension (page 7-10)

In the first phase of VECTOR GROUP BY aggregation for this query, the database creates a dense grouping key for each city/state combination for cities in the states of Washington or California.

Step 2: Key Vector and Temporary Table Creation for products Dimension (page 7-11)

The database creates a dense grouping key for each distinct category/subcategory combination of an Acme product.

Step 3: Key Vector Query Transformation (page 7-13)

In this phase, the database processes the fact table.

Step 4: Row Filtering from Fact Table (page 7-13)

This phase obtains the amount sold for each combination of grouping keys.

Step 5: Aggregation Using an Array (page 7-14)

The database uses a multidimensional array to perform the aggregation.

Step 6: Join Back to Temporary Tables (page 7-14)

In the final stage of processing, the database uses the dense grouping keys to join back the rows to the temporary tables to obtain the names of the regions and categories.

7.3.4.1 Sample Analytic Query of a Star Schema

This sample star schema in this scenario contains the sales_online fact table and two dimension tables: geography and products.

Each row in geography is uniquely identified by the geog_id column. Each row in products is uniquely identified by the prod_id column. Each row in sales_online is uniquely identified by the geog_id, prod_id, and amount sold.

Table 7-1 Sample Rows in geography Table

•			
country	state	city	geog_id
USA	WA	seattle	2
USA	WA	spokane	3
USA	CA	SF	7
USA	CA	LA	8

Table 7-2 Sample Rows in products Table

manuf	category	subcategory	prod_id
Acme	sport	bike	4
Acme	sport	ball	3
Acme	electric	bulb	1
Acme	electric	switch	8

Table 7-3 Sample Rows in sales_online Table

prod_id	geog_id	amount
8	1	100
9	1	150
8	2	100
4	3	110
2	30	130

4

prod_id	geog_id	amount
6	20	400
3	1	100
1	7	120
3	8	130

Table 7-3 (Cont.) Sample Rows in sales_online Table

3

A manager asks the business question, "How many Acme products in each subcategory were sold online in Washington, and how many were sold in California?" To answer this question, an analytic query of the sales_online fact table joins the products and geography dimension tables as follows:

200

```
SELECT p.category, p.subcategory, g.country, g.state, SUM(s.amount)
FROM sales_online s, products p, geography g
WHERE s.geog_id = g.geog_id
AND s.prod_id = p.prod_id
     g.state IN ('WA','CA')
AND
AND
      p.manuf = 'ACME'
GROUP BY category, subcategory, country, state
```

7.3.4.2 Step 1: Key Vector and Temporary Table Creation for geography Dimension

In the first phase of VECTOR GROUP BY aggregation for this query, the database creates a dense grouping key for each city/state combination for cities in the states of Washington or California.

In Table 7-6 (page 7-11), the 1 is the USA, WA grouping key, and the 2 is the USA, CA grouping key.

country	state	city	geog_id	dense_
USA	WA	seattle	2	1

Table 7-4 Dense Grouping Key for geography

country	state	city	geog_id	dense_gr_key_geog
USA	WA	seattle	2	1
USA	WA	spokane	3	1
USA	CA	SF	7	2
USA	CA	LA	8	2

A key vector for the geography table looks like the array represented by the final column in Table 7-5 (page 7-11). The values are the geography dense grouping keys. Thus, the key vector indicates which rows in sales_online meet the geography. state filter criteria (a sale made in the state of CA or WA) and which country/state group each row belongs to (either the USA, WA group or USA, CA group).

Table 7-5 Online Sales

prod_id	geog_id	amount	key vector for geography
8	1	100	0
9	1	150	0
8	2	100	1
4	3	110	1
2	30	130	0
6	20	400	0
3	1	100	0
1	7	120	2
3	8	130	2
4	3	200	1

Internally, the database creates a temporary table similar to the following:

```
CREATE TEMPORARY TABLE tt_geography AS

SELECT MAX(country), MAX(state), KEY_VECTOR_CREATE(...) dense_gr_key_geog

FROM geography

WHERE state IN ('WA','CA')

GROUP BY country, state
```

Table 7-6 (page 7-11) shows rows in the tt_geography temporary table. The dense grouping key for the USA, WA combination is 1, and the dense grouping key for the USA, CA combination is 2.

Table 7-6 tt_geography

country	state	dense_gr_key_geog
USA	WA	1
USA	CA	2

7.3.4.3 Step 2: Key Vector and Temporary Table Creation for products Dimension

The database creates a dense grouping key for each distinct category/subcategory combination of an Acme product.

For example, in Table 7-7 (page 7-11), the 4 is the dense grouping key for an Acme electric switch.

Table 7-7 Sample Rows in products Table

manuf	category	subcategory	prod_id	dense_gr_key_prod
Acme	sport	bike	4	1
Acme	sport	ball	3	2

Table 7-7 (Cont.) Sample Rows in products Table

manuf	category	subcategory	prod_id	dense_gr_key_prod
Acme	electric	bulb	1	3
Acme	electric	switch	8	4

A key vector for the products table might look like the array represented by the final column in Table 7-8 (page 7-12). The values represent the products dense grouping key. For example, the 4 represents the online sale of an Acme electric switch. Thus, the key vector indicates which rows in sales_online meet the products filter criteria (a sale of an Acme product).

Table 7-8 Key Vector

prod_id	geog_id	amount	key vector for products		
8	1	100	4		
9	1	150	0		
8	2	100	4		
4	3	110	1		
2	30	130	0		
6	20	400	0		
3	1	100	2		
1	7	120	3		
3	8	130	2		
4	3	200	1		

Internally, the database creates a temporary table similar to the following:

```
CREATE TEMPORTARY TABLE tt_products AS

SELECT MAX(category), MAX(subcategory), KEY_VECTOR_CREATE(...) dense_gr_key_prod

FROM products

WHERE manuf = 'ACME'

GROUP BY category, subcategory
```

Table 7-9 (page 7-12) shows rows in this temporary table.

Table 7-9 tt_products

category	subcategory	dense_gr_key_prod
sport	bike	1
sport	ball	2
electric	bulb	3

Table 7-9 (Cont.) tt_products

category	subcategory	dense_gr_key_prod
electric	switch	4

7.3.4.4 Step 3: Key Vector Query Transformation

In this phase, the database processes the fact table.

The optimizer transforms the original query into the following equivalent query, which accesses the key vectors:

```
SELECT KEY_VECTOR_PROD(prod_id),

KEY_VECTOR_GEOG(geog_id),

SUM(amount)

FROM sales_online

WHERE KEY_VECTOR_PROD_FILTER(prod_id) IS NOT NULL

AND KEY_VECTOR_GEOG_FILTER(geog_id) IS NOT NULL

GROUP BY KEY_VECTOR_PROD(prod_id), KEY_VECTOR_GEOG(geog_id)
```

The preceding transformation is not an exact rendition of the internal SQL, which is much more complicated, but a conceptual representation designed to illustrate the basic concept.

7.3.4.5 Step 4: Row Filtering from Fact Table

This phase obtains the amount sold for each combination of grouping keys.

The database uses the key vectors to filter out unwanted rows from the fact table. In Table 7-10 (page 7-13), the first three columns represent the sales_online table. The last two columns provide the dense grouping keys for the geography and products tables.

Table 7-10 Dense Grouping Keys for the sales_online Table

prod_id	geog_id	amount	dense_gr_key_prod	dense_gr_key_geog
7	1	100	4	
9	1	150		
8	2	100	4	1
4	3	110	1	1
2	30	130		
6	20	400		
3	1	100	2	
1	7	120	3	2
3	8	130	2	2
4	3	200	1	1

As shown in Table 7-11 (page 7-14), the database retrieves only those rows from sales_online with non-null values for both dense grouping keys, indicating rows that satisfy all the filtering criteria.

Table 7-11 Filtered Rows from sales_online Table

geog_id	prod_id	amount	dense_gr_key_prod	dense_gr_key_geog
2	8	100	4	1
3	4	110	1	1
3	4	200	1	1
7	1	120	3	2
8	3	130	2	2

7.3.4.6 Step 5: Aggregation Using an Array

The database uses a multidimensional array to perform the aggregation.

In Table 7-12 (page 7-14), the geography grouping keys are horizontal, and the products grouping keys are vertical. The database adds the values in the intersection of each dense grouping key combination. For example, for the intersection of the geography grouping key 1 and the products grouping key 1, the sum of 110 and 200 is 310.

Table 7-12 Aggregation Array

dgkp/dgkg	1	2
1	110,200	
2		130
3		120
4	100	

7.3.4.7 Step 6: Join Back to Temporary Tables

In the final stage of processing, the database uses the dense grouping keys to join back the rows to the temporary tables to obtain the names of the regions and categories.

The results look as follows:

CATEGORY	SUBCATEGORY	COUNTRY	STATE	AMOUNT
${\tt electric}$	bulb	USA	CA	120
${\tt electric}$	switch	USA	WA	100
sport	ball	USA	CA	130
sport	bike	USA	WA	310

7.4 Controls for IM Aggregation

IM aggregation is integrated with the optimizer. No new SQL or initialization parameters are required. IM aggregation does not need additional indexes, foreign keys, or dimensions.

You can use the following pairs of hints:

· Query block hints

VECTOR_TRANSFORM enables the vector transformation on the specified query block, regardless of costing. NO_VECTOR_TRANSFORM disables the vector transformation from engaging on the specified query block.

Table hints

You can use the following pairs of hints:

- VECTOR_TRANSFORM_FACT includes the specified FROM expressions in the fact table generated by the vector transformation. NO_VECTOR_TRANSFORM_FACT excludes the specified FROM expressions from the fact table generated by the vector transformation.
- VECTOR_TRANSFORM_DIMS includes the specified FROM expressions in enabled dimensions generated by the vector transformation.
 NO_VECTOR_TRANSFORM_DIMS excludes the specified from expressions from enabled dimensions generated by the vector transformation.

See Also:

Oracle Database SQL Language Reference to learn more about the VECTOR_TRANSFORM_FACT and VECTOR_TRANSFORM_DIMS hints

7.5 In-Memory Aggregation: Example

In this example, the business question is "How many products were sold in each category in each calendar year?"

You write the following query, which joins the times, products, and sales tables:

```
SELECT t.calendar_year, p.prod_category, SUM(quantity_sold)
FROM times t, products p, sales s
WHERE t.time_id = s.time_id
AND p.prod_id = s.prod_id
GROUP BY t.calendar_year, p.prod_category;
```

Example 7-3 VECTOR GROUP BY Execution Plan

The following example shows the execution plan contained in the current cursor. Steps 4 and 8 show the creation of the key vectors for the dimension tables times and products. Steps 17 and 18 show the use of the previously created key vectors. Steps 3, 7, and 15 show the VECTOR GROUP BY operations.

4	KEY VECTOR CREATE BUFFERED	:KV0000	1826	29216	3(100)	00:00:01		
5	TABLE ACCESS INMEMORY FULL	TIMES	1826	21912	1(100)	00:00:01		
6	LOAD AS SELECT	SYS_TEMP_OFD9D6645_11CBE8						
7	VECTOR GROUP BY		5	125	1(100)	00:00:01		
8	KEY VECTOR CREATE BUFFERED	:KV0001	72	1800	1(100)	00:00:01		
9	TABLE ACCESS INMEMORY FULL	PRODUCTS	72	1512	0 (0)			
10	HASH GROUP BY		18	1440	282 (99)	00:00:01		
11	HASH JOIN		18	1440	281 (99)	00:00:01		
12	HASH JOIN		18	990	278(100)	00:00:01		
13	TABLE ACCESS FULL	SYS_TEMP_0FD9D6644_11CBE8	5	80	2 (0)	00:00:01		
14	VIEW	VW_VT_AF278325	18	702	276(100)	00:00:01		
15	VECTOR GROUP BY		18	414	, ,	00:00:01		
16	HASH GROUP BY		18	414	276(100)	00:00:01		
17	KEY VECTOR USE	:KV0000	918K	20M	276(100)	00:00:01		
18	KEY VECTOR USE	:KV0001	918K	16M	272(100)	00:00:01		
19	PARTITION RANGE ALL		918K	13M	257(100)	00:00:01	1 28	
20	TABLE ACCESS INMEMORY FULL	SALES	918K	13M	257(100)	00:00:01	1 28	
21	TABLE ACCESS FULL	SYS_TEMP_0FD9D6645_11CBE8	5	125	2 (0)	00:00:01		

Predicate Information (identified by operation id):

- -

11 - access("ITEM_10"=INTERNAL_FUNCTION("C0") AND "ITEM_11"="C2")

12 - access("ITEM_8"=INTERNAL_FUNCTION("CO") AND "ITEM_9"="C2")

Note

- vector transformation used for this statement

45 rows selected.

Optimizing Repopulation of the IM Column Store

The IM column store periodically refreshes objects that have been modified. You can control this behavior using initialization parameters and the DBMS_INMEMORY package.

This chapter contains the following topics:

About Repopulation of the IM Column Store (page 8-1)

The automatic refresh of columnar data after significant modifications is called **repopulation**.

How Data Loading Works with the IM Column Store (page 8-2)

The IM column store uses different mechanisms depending on the type of data loading: conventional DML, direct path loads, and partition exchange loads.

When the Database Repopulates the IM Column Store (page 8-7)

The database repopulates the IM column store automatically according to an internal algorithm. You can manually disable repopulation, and also influence its aggressiveness.

Controls for Repopulation of the IM Column Store (page 8-10)

Repopulation occurs automatically by default, but you can control its aggressiveness, or disable it altogether.

Optimizing Trickle Repopulation: Tutorial (page 8-11)

In this tutorial, you increase the percentage of background processes available for trickle repopulation.

8.1 About Repopulation of the IM Column Store

The automatic refresh of columnar data after significant modifications is called **repopulation**.

An In-Memory Compression Unit (IMCU) is a read-only structure that does not modify the data in place when DML occurs on the table. Instead, the Snapshot Metadata Unit (SMU) associated with each IMCU tracks row modifications in a transaction journal. If a query accesses the data, and discovers modified rows, then it can obtain the corresponding rowids from the transaction journal, and then retrieve the modified rows from the buffer cache.

As the number of modifications increase, so do the size of SMUs, and the amount of data that must be fetched from the transaction journal or database buffer cache. To avoid degrading query performance through journal access, background processes repopulate modified objects.

Automatic repopulation takes two forms: threshold-based repopulation, and trickle repopulation. The first form depends on the percentage of stale entries in the transaction journal for an IMCU. Trickle repopulation supplements threshold-based repopulation by periodically refreshing stale columnar data even when the threshold has not been reached.

During repopulation, traditional access mechanisms are available. Data is always accessible from the buffer cache or disk. Additionally, the IM column store is always transactionally consistent with the data on disk. No matter where the query accesses the data, the database always returns consistent results.

See Also:

- "Transaction Journal (page 2-16)"
- "In-Memory Process Architecture (page 2-19)"

8.2 How Data Loading Works with the IM Column Store

The IM column store uses different mechanisms depending on the type of data loading: conventional DML, direct path loads, and partition exchange loads.

This section contains the following topics:

How Conventional DML Works with the IM Column Store (page 8-2)

Conventional DML processes one row or array of rows at a time, and inserts rows below the high water mark. Regardless of whether the IM column store is enabled, the database processes DML using the buffer cache.

How Direct Path Loads Work with the IM Column Store (page 8-4)

A direct path load is an INSERT /*+APPEND*/ statement or a SQL*Loader operation in which DIRECT=true.

How a Partition Exchange Load Works with the IM Column Store (page 8-5)

A partition exchange load is a technique that exchanges a table for a partition. An exchange load is almost instantaneous because it modifies metadata instead of data.

8.2.1 How Conventional DML Works with the IM Column Store

Conventional DML processes one row or array of rows at a time, and inserts rows below the high water mark. Regardless of whether the IM column store is enabled, the database processes DML using the buffer cache.

IMCUs are read-only. When a statement modifies a row in an IMCU, the IM column store records the rowid in the associated SMU.

A Column Compression Unit (CU) entry becomes stale when its value differs from the value in its corresponding journal entry. For example, a transaction may change an employee's weekly salary from 1000 to 1200, but the actual value in the IMCU is still 1000. The transaction journal records the rowid of the stale row and its SCN.

Note:

The transaction journal does not record the new value. Rather, it indicates the corresponding row as stale as of a specific SCN.

This section contains the following topics:

Staleness Threshold (page 8-3)

The more stale entries that exist in an IMCU, the slower the IMCU scan becomes.

Double Buffering (page 8-3)

In double buffering, background processes create new IMCU versions by combining the original rows with the latest modified rows.

See Also:

"Column Compression Units (CUs) (page 2-12)"

8.2.1.1 Staleness Threshold

The more stale entries that exist in an IMCU, the slower the IMCU scan becomes.

Performance decreases because the database must fetch the modified rows from the buffer cache or disk, rather than from the IM column store. For this reason, Oracle Database repopulates an IMCU when the number of stale entries in an IMCU reaches an internal staleness threshold.

The database determines the threshold using heuristics that take into account the frequency of IMCU access and the number of stale rows. Repopulation is more frequent for IMCUs that are accessed frequently or have a higher percentage of stale rows.

See Also:


- "In-Memory Compression Units (IMCUs) (page 2-8)"
- Oracle Database Concepts to learn more about the database buffer cache

8.2.1.2 Double Buffering

In double buffering, background processes create new IMCU versions by combining the original rows with the latest modified rows.

When the database begins either threshold-based repopulation or trickle repopulation, the IM column store uses double buffering. As shown in the following figure, the IM column store maintains two versions of an IMCU simultaneously, with the original stale IMCU remaining accessible to queries.

Figure 8-1 Double Buffering



The basic steps of double buffering are:

- 1. In the original SMU, the database marks the existing IMCU as the original version as of a specific SCN.
- **2.** Background processes create a new version of the IMCU by combining the original rows with the latest versions of the modified rows.
- **3.** In the journal of the new SMU, the database tracks DML operations that occur during IMCU creation.

In this way, the original IMCU stays online. The database keeps both old and new IMCUs versions for as long as they are useful, or until the IM column store is under space pressure.

See Also:

- "Snapshot Metadata Units (SMUs) (page 2-15)"
- "In-Memory Process Architecture (page 2-19)"

8.2.2 How Direct Path Loads Work with the IM Column Store

A direct path load is an INSERT /*+APPEND*/ statement or a SQL*Loader operation in which DIRECT=true.

In a direct path load, the database writes formatted data blocks directly to the data files, bypassing the database buffer cache. The database appends the data above the high water mark, which is the boundary between used and unused space in a segment. Direct path loads operate are "all or nothing" operations: the operation either inserts all data or no data.

Sales Table Sales Table Sales Table High Water Mark New Data High Water Mark High Water Mark

Figure 8-2 Direct Path Loads and the High Water Mark

When the segment is populated in the IM column store, a direct path load works as follows:

- You load data using a CREATE TABLE AS SELECT or INSERT /*+APPEND*/ statement. Only the current session is aware of the DML.
- You commit the statement. 2.
- The high water mark moves to encompass the new data, which alerts the IMCU that data is missing. V\$IM_SEGMENTS.BYTES_NOT_POPULATED now indicates the size of the newly inserted data.
- The IM column store manages repopulation based on the following algorithm:
 - If the affected object has a PRIORITY set to a value other than NONE, then the database repopulates the data.
 - If the affected object has a PRIORITY set to NONE, then the database repopulates at the next full scan of the object.

See Also:

"Prioritization of In-Memory Population (page 4-2)"

8.2.3 How a Partition Exchange Load Works with the IM Column Store

A partition exchange load is a technique that exchanges a table for a partition. An exchange load is almost instantaneous because it modifies metadata instead of data.

To perform an exchange load, follow these steps:

- Create a nonpartitioned table, called a *source table*.
- Load rows into the source table. 2.
- Exchange an existing table partition, called the *target partition*, with the table.

For the target partition to be populated in the IM column store after the exchange, the source table must be populated in the IM column store before the exchange. The following scenarios are possible, depending on the whether the target partition is populated:

- Before the exchange, the target partition is not populated in the IM column store. For example, the partition is empty.
 - After the exchange, the source table is no longer populated in the IM column store. The source IMCUs are now associated with the target partition.
- Before the exchange, the target partition is populated in the IM column store. After the exchange, the source table remains populated in the IM column store.

Example 8-1 INMEMORY Partition Exchange Load

In this example, the sales table, which is partitioned, has the INMEMORY attribute set at the table level. All non-empty partitions in this table are currently populated. The sales_p042616 partition is currently empty. Your goal is to populate the empty partition sales_p042616 with data contained in text files. The following figure illustrates the before and after scenarios.

IM Column Store IM Column Store IM Column Store Sales Table Sales Table Sales Table sales_p042016 sales_p042016 sales_p042016 sales_p042116 sales_p042116 sales_p042116 sales_p042216 sales_p042216 sales_p042216 sales_p042316 sales_p042316 sales_p042316 sales_p042416 sales_p042416 sales_p042416 sales p042516 sales p042516 sales p042516 sales_p042616 sales_tmp_ld After the partition **Before** After sales_tmp_ld sales_tmp_ld exchange is populated is populated

Figure 8-3 Partition Exchange

To perform the exchange, do the following:

- Create an external table sales_tmp_ext using the CREATE TABLE ... ORGANIZATION EXTERNAL statement.
 - The external table does not reside in the database, and can be in any format for which an access driver is provided. The table is read-only.
- Create a nonpartitioned table named sales_tmp_ld using CREATE TABLE ... AS SELECT * FROM sales_tmp_ext.
 - The sales_tmp_ld table is not external, which means it stores rows in the data files.

- 3. Set the INMEMORY attribute in sales_tmp_ld using an ALTER TABLE statement. The sales_tmp_ld table is now marked as INMEMORY, but it is not yet populated into the IM column store.
- **4.** Populate sales_tmp_1d into the IM column store by forcing a full table scan.

For example, the following query forces a full scan:

```
SELECT /*+ FULL(s) NO_PARALLEL(s) */ COUNT(*) FROM sales_tmp_ld s;
```

5. Exchange the sales_p042616 partition with the sales_tmp_ld table.

For example, alter the sales table as follows:

```
ALTER TABLE sales EXCHANGE PARTITION sales_p042616 WITH TABLE sales_tmp_ld;
```

After the exchange completes, the sales_p042616 partition is populated in the IM column store, and the sales_tmp_ld is no longer populated.

See Also:

Oracle Database VLDB and Partitioning Guide to learn more about partition exchange loads

8.3 When the Database Repopulates the IM Column Store

The database repopulates the IM column store automatically according to an internal algorithm. You can manually disable repopulation, and also influence its aggressiveness.

Note:

This section describes automatic repopulation. You can force repopulation manually by using the DBMS_INMEMORY.REPOPULATE procedure.

This section contains the following topics:

Threshold-Based and Trickle Repopulation (page 8-7)

Automatic repopulation takes two forms: **threshold-based repopulation** and **trickle repopulation**.

Factors Affecting Repopulation (page 8-9)

The algorithm that triggers repopulation is internal, and depends on several factors.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn about the DBMS_INMEMORY.REPOPULATE procedure

8.3.1 Threshold-Based and Trickle Repopulation

Automatic repopulation takes two forms: **threshold-based repopulation** and **trickle repopulation**.

Automatic repopulation always checks stale journal entries and uses double buffering. However, repopulation has different triggers:

Threshold-based repopulation

The database repopulates IMCUs when the number of changes recorded in the transaction journal reaches an internal staleness threshold. Threshold-based repopulation occurs automatically when INMEMORY_MAX_POPULATE_SERVERS initialization parameter is set to a value other than 0.


Trickle repopulation

The IMCO (In-Memory Coordinator) background process periodically checks whether stale rows exist, and then adds IMCUs to a repopulation queue. This mechanism does *not* depend on meeting the staleness threshold. The INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT initialization parameter limits the number of background processes used for trickle repopulation. Setting this parameter to 0 disables trickle repopulation.

Trickle repopulation is analogous to Java garbage collection. The mechanism works as follows:

- 1. IMCO wakes up.
- **2.** IMCO determines whether any population tasks need to be performed, including whether any stale entries exist in the transaction journal associated with an IMCU.
- **3.** If IMCO finds stale entries, then it triggers a Space Management Worker Process (*Wnnn*) to create a new version of the IMCU.
 - During IMCU creation, the database records the rowids of modified rows in the transaction journal.
- **4.** IMCO sleeps for two minutes, and then returns to Step 1.

Figure 8-4 Trickle Repopulation



For example, a database may be busy for 8 hours per day. A majority of SMUs contain a small number of transaction journal entries (below the staleness threshold). When the database is quiet, IMCO wakes up, checks the journals to determine which IMCUs have stale entries, and then uses trickle repopulation to refresh the IMCUs.

See Also:

- "In-Memory Process Architecture (page 2-19)"
- "Transaction Journal (page 2-16)"
- Oracle Database Reference to learn about In-Memory background processes

8.3.2 Factors Affecting Repopulation

The algorithm that triggers repopulation is internal, and depends on several factors. The principal factors affecting repopulation are as follows:

Rate of DML changes

As the database modifies more rows, columnar data becomes more stale. The transaction journal grows, increasing the need to use the buffer cache to satisfy queries.

Type of DML operations

Typically, inserts have less performance overhead than deletes and updates because inserts often go into a new data block.

Location of modified rows within a data block

Changes grouped within the same database block or table partition have less effect then changes distributed across an entire table. Versioning every IMCU has a greater impact than versioning a small number of IMCUs.

Compression level applied to INMEMORY objects

Because of double buffering, tables with higher compression levels incur more query and DML overhead during repopulation. For example, MEMCOMPRESS FOR CAPACITY HIGH incurs more overhead than MEMCOMPRESS FOR DML.

Number of active worker processes

As the number of worker processes increases, more work occurs in parallel. Consequently, the rate of repopulation increases.

See Also:

- "IM Column Store Compression Methods (page 4-9)"
- Oracle Database Reference to learn about the INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT initialization parameter

8.4 Controls for Repopulation of the IM Column Store

Repopulation occurs automatically by default, but you can control its aggressiveness, or disable it altogether.

Initialization Parameters

The following initialization parameters influence background process behavior:

• INMEMORY MAX POPULATE SERVERS

This parameter limits the maximum number of *Wnnn* processes available for population and repopulation (threshold-based and trickle). The default value is half the CPU_COUNT. This parameter acts as a throttle, preventing these server processes from overloading the rest of the database. Setting this parameter to 0 disables both population and repopulation.

Caution:

Be careful not to set the value of this parameter too high. If it is set close to the number of cores or higher, then no CPU may be available for the rest of the system to run.

• INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT

This parameter limits the percentage of the total population and repopulation processes that perform trickle repopulation. Its effect is to limit the number of IMCUs repopulated through trickle repopulation within a two-minute interval.

The value for this parameter is a percentage of the INMEMORY_MAX_POPULATE_SERVERS value. For example, if INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT is 5 percent, and if INMEMORY_MAX_POPULATE_SERVERS is 20, then the IM column store uses an average of 1 core (.05 * 20) for trickle repopulation.

To increase throughput at the expense of increased background CPU, set this parameter to higher values such as 5 or 10. A value greater than 50 is not allowed, so that at least half of the INMEMORY_MAX_POPULATE_SERVERS processes are available for other tasks.

Setting this parameter to 0 disables trickle population.

See Also:

- Oracle Database Reference to learn about
 INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT
- Oracle Database Reference to learn about INMEMORY_MAX_POPULATE_SERVERS

DBMS INMEMORY.REPOPULATE Procedure

To manually repopulate a table, partition, or subpartition, use the DBMS_INMEMORY.REPOPULATE procedure. Only objects that are currently populated in the IM column store are eligible for repopulation.

The following values are possible for the force parameter:

- FALSE The database repopulates only IMCUs containing modified rows. This is the default.
- TRUE The database drops the segment, and then rebuilds it. The database increments the statistics and performs all other tasks related to initial population.

For example, IMCU 1 contains rows 1 to 500,000, and IMCU 2 contains rows 500,001 to 1,000,000. A statement modifies row 600,000. When force is FALSE, the database only repopulates IMCU 2. When force is TRUE, the database repopulates both IMCUs.

Consider further that the INMEMORY_VIRTUAL_COLUMNS initialization parameter is set to ENABLE, and an application creates a new virtual column. When force is FALSE, the database only repopulates IMCU 2 with the new column. When force is TRUE, the database repopulates both IMCUs with the new column.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn more about DBMS_INMEMORY.REPOPULATE

8.5 Optimizing Trickle Repopulation: Tutorial

In this tutorial, you increase the percentage of background processes available for trickle repopulation.

Assumptions

This tutorial assumes the following:

- The IM column store is enabled.
- You want to devote more CPU to the Space Management Worker Processes (Wnnn) that perform trickle repopulation.
- The database server has 12 CPU cores.

To increase the aggressiveness of repopulation:

- 1. In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- 2. Show the settings for the initialization parameters relating to repopulation (sample output included):

SHOW PARAMETER POPULATE_SERVERS

NAME	TYPE	VALUE
inmemory_max_populate_servers	integer	12
<pre>inmemory_trickle_repopulate_servers_percent</pre>	integer	1

The preceding output indicates that 12 cores are available for population and repopulation tasks. The INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT is 1% of the INMEMORY_MAX_POPULATE_SERVERS value. Of the server processes available for population and repopulation tasks, the IM column store can use a maximum of .12 CPU cores (.01 * 12) for trickle repopulation.

3. Increase the trickle repopulation maximum to 25% of the INMEMORY_MAX_POPULATE_SERVERS initialization parameter value.

For example, use the following statement:

ALTER SYSTEM SET INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT=25;

As a result, the IM column store now uses a maximum of 3 CPU cores (.25 * 12) for trickle repopulation, out of a total of 12 that are available for population and repopulation work.

See Also:

- Oracle Database Reference to learn about INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT
- Oracle Database Reference to learn about INMEMORY_MAX_POPULATE_SERVERS

Part IV

High Availability and the IM Column Store

This part explains how to use the IM column store with high availability features such as In-Memory FastStart (IM FastStart), Oracle Data Guard, and Oracle Real Application Clusters (Oracle RAC).

This section contains the following topics:

Managing IM FastStart for the IM Column Store (page 9-1)

When the IM column store is enabled, In-Memory FastStart (IM FastStart) enables the database to open faster by storing columnar data on disk.

Deploying IM Column Stores in Oracle RAC (page 10-1)

This chapter explains how to enable IM column stores in an Oracle Real Application Clusters (Oracle RAC) environment, and configure objects for population.

Deploying an IM Column Store with Oracle Active Data Guard (page 11-1)

This chapter explains how Database In-Memory feature works in an Oracle Active Data Guard environment.

See Also:

- Oracle Database High Availability Overview for an overview of High Availability
- The MAA white paper Oracle Database In-Memory High Availability Best Practices

Managing IM FastStart for the IM Column Store

When the IM column store is enabled, In-Memory FastStart (IM FastStart) enables the database to open faster by storing columnar data on disk.

This chapter contains the following topics:

About IM FastStart (page 9-1)

IM FastStart optimizes the population of database objects in the IM column store by storing IMCUs directly on disk.

Enabling IM FastStart for the IM Column Store (page 9-5)

Specify a tablespace for the FastStart area using the DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE procedure.

Retrieving the Name of the Current IM FastStart Tablespace (page 9-7)

Obtain the name of the tablespace that is currently designated as the FastStart area by querying V\$INMEMORY_FASTSTART_AREA view.

Migrating the FastStart Area to a Different Tablespace (page 9-8)

You can migrate the FastStart area to a different tablespace by running the FASTSTART_MIGRATE_STORAGE procedure in the DBMS_INMEMORY_ADMIN package.

Disabling IM FastStart for the IM Column Store (page 9-9)

When you disable IM FastStart, the database no longer maintains the FastStart area. The database does not use IM FastStart to populate the IM column store when the database reopens.

9.1 About IM FastStart

IM FastStart optimizes the population of database objects in the IM column store by storing IMCUs directly on disk.

The database can read from the IM FastStart area after crash and recovery, or during duplication to a different Oracle RAC instance.

Note:

IM FastStart is not supported in a standby database, which is read-only.

This section contains the following topics:

Purpose of IM FastStart (page 9-2)

The IM column store is populated whenever a database instance restarts, which can be a slow operation that is I/O-intensive and CPU-intensive.

How IM FastStart Works (page 9-2)

A FastStart area is a designated tablespace where IM FastStart stores and manages data for INMEMORY objects. Oracle Database manages the FastStart tablespace without DBA intervention.

9.1.1 Purpose of IM FastStart

The IM column store is populated whenever a database instance restarts, which can be a slow operation that is I/O-intensive and CPU-intensive.

When IM FastStart is enabled, the database periodically saves a copy of columnar data to disk for faster repopulation during instance restarts. If the database re-opens after being closed, then the database reads columnar data from the FastStart area, and then populates it into the IM column store, ensuring that all transactional consistencies are maintained.

An IM FastStart tablespace requires intermittent I/O while the database is open and operational. The performance gain occurs when the database re-opens because the database avoids the CPU-intensive compression and formatting of data.

9.1.2 How IM FastStart Works

A FastStart area is a designated tablespace where IM FastStart stores and manages data for INMEMORY objects. Oracle Database manages the FastStart tablespace without DBA intervention.

Only one FastStart area, and one designated FastStart tablespace, is allowed for each PDB or non-CDB. You cannot alter or drop the tablespace while it is the designated IM FastStart tablespace. In an Oracle RAC database, all nodes share the FastStart data.

Enable a FastStart tablespace using the

DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE procedure. The Space Management Worker Processes (Wnnn) creates an empty SecureFiles LOB named SYSDBinstance_name_LOBSEG\$.

Note:

Enabling the IM FastStart area is not sufficient to create the FastStart area. Data population or repopulation is required.

This section contains the following topics:

How the Database Manages the FastStart Area (page 9-3)

During the first population or repopulation after the FastStart area is enabled, the database creates the FastStart area.

How the Database Reads from the FastStart Area (page 9-5)

The FastStart area defines *what* data is loaded when the database reopens, but not *when* it is loaded. Population is controlled by the priority settings.

See Also:

- "Space Management Worker Processes (Wnnn) (page 2-20)"
- "About Repopulation of the IM Column Store (page 8-1)"
- Oracle Database PL/SQL Packages and Types Reference to learn about the DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE procedure

9.1.2.1 How the Database Manages the FastStart Area

During the first population or repopulation after the FastStart area is enabled, the database creates the FastStart area.

The database manages the FastStart area automatically as follows:

• Whenever population or repopulation of an object occurs, the database writes its columnar data to the FastStart area.

Note:

The database writes segments from encrypted tablespaces to the FastStart area only if the FastStart tablespace is also encrypted.

The Space Management Worker Processes (Wnnn) write IMCUs (not IMEUs or SMUs) to the SecureFiles LOB named SYSDBinstance_name_LOBSEG\$. The database writes FastStart metadata to the SYSAUX tablespace, which must be online.

Depending on how much DML activity occurs for a CU, a lag can exist between the CUs in the FastStart area and the CUs in the IM column store. The "hotter" a CU is, the less frequently the database populates it in the IM column store and writes it to the FastStart area. If the database crashes, then some CUs that were populated in the IM column store may not exist in the FastStart area.

Note:

If the FastStart area becomes temporarily inaccessible, then In-Memory population is unaffected.

- If you define an ADO policy on a segment, then the database manages the segment in the FastStart area based on the rule in the policy. For example, if ADO specifies that an object changes its attribute to NO INMEMORY based on a policy, then the IM column store removes its data from the FastStart area.
- If the attribute of a populated object is changed to NOINMEMORY, then the database automatically removes its IMCUs from the FastStart area.
- If the FastStart tablespace runs out of space, then the database uses an internal algorithm to drop the oldest segments, and continues writing to the FastStart area. If no space remains, then the database stops writing to the FastStart area.

The following figure shows products, customers, and sales populated in the IM column store.

Instance System Global Area (SGA) **Database Buffer Cache In-Memory Column Store** products IMCU 1 IMCU 2 customers IMCU 3 sales IMCU 5 IMCU 6 **USERS Tablespace** FS_TBS Disk Disk IMCU 1 IMCU 6 IMCU 5 IMCU 3 IMCU 4 sales customers Segment Seament products Segment

Figure 9-1 FastStart Area

When the FastStart area is enabled, the database also writes the IMCUs for these segments to the FastStart area in fs_tbs. If the database re-opens or if the instance restarts, then the database can validate the IMCUs for modifications to ensure the transactional consistency, and reuse the IMCUs. Regardless of whether the FastStart area is enabled, the database stores data blocks and segments on disk in the users tablespace.

Note:

You cannot manually force the IM column store to write data to the FastStart tablespace.

See Also:

- "Enabling ADO for the IM Column Store (page 4-26)"
- "FastStart Area in Oracle RAC (page 10-14)"
- "About Repopulation of the IM Column Store (page 8-1)"

9.1.2.2 How the Database Reads from the FastStart Area

The FastStart area defines what data is loaded when the database reopens, but not when it is loaded. Population is controlled by the priority settings.

When the database reopens, the standard PRIORITY rules determine population. For example, the database populates objects with PRIORITY NONE on demand. Objects with priority CRITICAL are higher in the automatic population queue than objects with priority LOW.

For example, in a single-instance database, the sales, customers, and product tables are populated with PRIORITY NONE in the IM column store. At every repopulation, the database saves the IMCUs for these tables to the FastStart area. Assume that the instance unexpectedly terminates. When you reopen the database, the IM column store is empty. If a query scans the sales, customers, or product table, then the database loads the IMCUs for this table from the FastStart area into the IM column store.

In most cases, the FastStart area increases the speed of population. However, if any CU stored in the FastStart area reaches an internal threshold of DML activity, then the database populates the row data from data files instead of from the FastStart area.

See Also:

- "Prioritization of In-Memory Population (page 4-2)"
- "FastStart Area in Oracle RAC (page 10-14)"

9.2 Enabling IM FastStart for the IM Column Store

Specify a tablespace for the FastStart area using the DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE procedure.

Optionally, set the logging mode of the LOB created for the FastStart area. If the nologging parameter is set to FALSE (default), then the database creates the LOB with the NOLOGGING option. If nologging is set to TRUE, then the database creates the FastStart LOB with the LOGGING option.

Prerequisites

To create a FastStart area, you must meet the following prerequisites:

- The tablespace that will be designated as the FastStart area must exist.
- This tablespace must have enough space to store data for the IM column store, and
 it must not contain any other data before you designate it as the FastStart area.
 Oracle recommends that you create the FastStart tablespace with twice the size of
 the INMEMORY_SIZE setting.
- You must have administrator privileges.

To create the IM FastStart area:

- 1. In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- 2. Use the DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE procedure.

Example 9-1 Designating an IM FastStart Area

This example creates a tablespace and designates it as the FastStart area.

- **1.** In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- **2.** Create a tablespace named fs_tbs:

```
CREATE TABLESPACE fs_tbs

DATAFILE 'fs_tbs.dbf' SIZE 500M REUSE
AUTOEXTEND ON NEXT 500K MAXSIZE 1G;
```

3. Enable IM FastStart, and designate the fs_tbs tablespace as the FastStart area, using the default NOLOGGING option for the FastStart LOB:

```
EXEC DBMS_INMEMORY_ADMIN.FASTSTART_ENABLE('fs_tbs');
```

4. Query the status and size of the FastStart area:

At this stage, no user data is in the FastStart area.

5. Query the logging mode of the FastStart LOB:

6. Force the IM column store to repopulate any currently populated objects.

The following queries force the repopulation of the sales, products, and customers tables:

```
SELECT /*+ FULL(s) NO_PARALLEL(s) */ COUNT(*) FROM sh.sales s;
SELECT /*+ FULL(p) NO_PARALLEL(p) */ COUNT(*) FROM sh.products p;
SELECT /*+ FULL(c) NO_PARALLEL(c) */ COUNT(*) FROM sh.customers c;
```

7. Query the size of the FastStart area:

Now the same query shows that 2.25 MB of the FastStart area has been filled.

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn about the DBMS_INMEMORY_ADMIN package

9.3 Retrieving the Name of the Current IM FastStart Tablespace

Obtain the name of the tablespace that is currently designated as the FastStart area by querying V\$INMEMORY_FASTSTART_AREA view.

If no FastStart tablespace is enabled, then the STATUS column shows NOT ENABLED; otherwise, the column shows the tablespace name.

Prerequisites

To retrieve the name of the FastStart tablespace, you must have administrator privileges.

To retrieve the name of the FastStart tablespace:

- 1. In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- 2. Query the V\$INMEMORY_FASTSTART_AREA view.

Example 9-2 Getting the Name of the Current IM FastStart Tablespace

This example queries the name and status of the FastStart tablespace (sample output included):

See Also:

Oracle Database Reference to learn about the V\$INMEMORY_FASTSTART_AREA view

9.4 Migrating the FastStart Area to a Different Tablespace

You can migrate the FastStart area to a different tablespace by running the FASTSTART_MIGRATE_STORAGE procedure in the DBMS_INMEMORY_ADMIN package.

In a non-CDB or PDB, you can designate only one tablespace at a time as the FastStart area.

Prerequisites

To migrate a FastStart area, you must meet the following prerequisites:

- The tablespace that will be designated as the new FastStart area must exist.
- This tablespace must have enough space to store data for the IM column store, and it must not contain any other data before it is designated as the FastStart area.
- You must have administrator privileges.

To migrate the IM FastStart area:

- 1. In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- 2. Run the DBMS_INMEMORY_ADMIN.FASTSTART_MIGRATE_STORAGE procedure.

Example 9-3 Migrating the FastStart Area to a Different Tablespace

This example migrates the IM FastStart area to the new_fs_tbs tablespace.

- 1. In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- **2.** Query the name of the current FastStart tablespace:

3. Create a tablespace named new_fs_tbs:

```
CREATE TABLESPACE new_fs_tbs

DATAFILE 'new_fs_tbs.dbf' SIZE 500M REUSE

AUTOEXTEND ON NEXT 500K MAXSIZE 1G;
```

4. Migrate the FastStart area to the new tablespace:

```
EXEC DBMS_INMEMORY_ADMIN.FASTSTART_MIGRATE_STORAGE('new_fs_tbs');
```

5. Query the name of the current FastStart tablespace:

```
TABLESPACE_NAME
              STATUS
NEW_FS_TBS
              ENABLE
```

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn about the FASTSTART MIGRATE STORAGE procedure

9.5 Disabling IM FastStart for the IM Column Store

When you disable IM FastStart, the database no longer maintains the FastStart area. The database does not use IM FastStart to populate the IM column store when the database reopens.

Prerequisites

To disable the FastStart area, the following conditions must be true:

- The FastStart area must be enabled.
- You must have administrator privileges.

To disable the FastStart tablespace:

- In SQL*Plus or SQL Developer, log in to the database with the necessary privileges.
- Query V\$INMEMORY FASTSTART AREA to confirm that the IM FastStart area is enabled.
- Execute the DBMS_INMEMORY_ADMIN.FASTSTART_DISABLE procedure.
- Optionally, drop the FastStart tablespace.

Example 9-4 Disabling IM FastStart

This example disables the IM FastStart area, and then drops the fs_tbs tablespace.

- In SQL*Plus or SQL Developer, log in to the database with administrative privileges.
- Query the status of the FastStart area:

```
COL TABLESPACE_NAME FORMAT a15
SELECT TABLESPACE_NAME, STATUS
FROM V$INMEMORY_FASTSTART_AREA;
TABLESPACE_NAME STATUS
_____
             ENABLE
FS_TBS
```

Disable the FastStart area:

```
EXEC DBMS_INMEMORY_ADMIN.FASTSTART_DISABLE;
```

Query the status of the FastStart area:

SELECT TABLESPACE_NAME, STATUS
FROM V\$INMEMORY_FASTSTART_AREA;

When IM FastStart is not enabled, the value of TABLESPACE_NAME is INVALID_TABLESPACE and the value of STATUS is DISABLE.

5. Drop the former FastStart tablespace:

DROP TABLESPACE fs_tbs INCLUDING CONTENTS AND DATAFILES;

See Also:

Oracle Database PL/SQL Packages and Types Reference to learn about the FASTSTART_DISABLE procedure

Deploying IM Column Stores in Oracle RAC

This chapter explains how to enable IM column stores in an Oracle Real Application Clusters (Oracle RAC) environment, and configure objects for population.

This section contains the following topics:

Overview of Database In-Memory and Oracle RAC (page 10-1)

Each node in an Oracle RAC environment has its own In-Memory (IM) column store. By default, populated objects are distributed across all IM column stores in the cluster.

Configuring In-Memory Services in Oracle RAC (page 10-15)

A **service** represents a set of instances. In Oracle RAC, you can use services to direct connections or applications to a subset of nodes in the cluster.

10.1 Overview of Database In-Memory and Oracle RAC

Each node in an Oracle RAC environment has its own In-Memory (IM) column store. By default, populated objects are distributed across all IM column stores in the cluster.

Each node in an Oracle RAC environment has its own In-Memory (IM) column store. Oracle recommends that you equally size the IM column stores on each Oracle RAC node. For any Oracle RAC node that does not require an IM column store, set the INMEMORY_SIZE parameter to 0.

It is possible to have completely different objects populated on every node, or to have larger objects distributed across all of the IM column stores in the cluster. It is also possible to have the same objects appear in the IM column store on every node (on engineered systems, only). The distribution of objects across the IM column stores in a cluster is controlled by two additional sub-clauses to the INMEMORY attribute; DISTRIBUTE and DUPLICATE.

In an Oracle RAC environment, an object that only has the INMEMORY attribute specified on it is automatically distributed across the IM column stores in the cluster. The DISTRIBUTE clause can be used to specify how an object is distributed across the cluster. By default, the type of partitioning used (if any) determines how the object is distributed. If the object is not partitioned it is distributed by rowid range. Alternatively, you can specify the DISTRIBUTE clause to over-ride the default behavior.

On an Engineered System, it is possible to duplicate or mirror objects populated in memory across the IM column store in the cluster. This provides the highest level of redundancy. The DUPLICATE clause is used to control how an object should be duplicated across the IM column stores in the cluster. If you specify just DUPLICATE, then one mirrored copy of the data is distributed across the IM column stores in the cluster. If you want to duplicate the entire object in each IM column store in the cluster, then specify DUPLICATE ALL.

Note:

When you deploy Oracle RAC on a non-Engineered System, the DUPLICATE clause is treated as NO DUPLICATE.

Multiple IM Column Stores (page 10-2)

In Oracle RAC, each database instance has its own IM column store.

Distribution and Duplication of Columnar Data in Oracle RAC (page 10-5)

When INMEMORY is specified, the DISTRIBUTE and DUPLICATE keywords control the distribution of objects.

Parallelism in Oracle RAC (page 10-12)

A database instance must access the IMCUs in the IM column store in which they reside. Population and access of IM column stores in Oracle RAC must occur in parallel so that all IM column stores are accessible from any instance.

FastStart Area in Oracle RAC (page 10-14)

The FastStart area is shared across all Oracle RAC nodes. This feature enables maximum sharing and reusability across the cluster.

Related Topics:

Oracle Database In-Memory Guide


10.1.1 Multiple IM Column Stores

In Oracle RAC, each database instance has its own IM column store.

Conceptually, the IM column store in Oracle RAC environment uses a shared-nothing architecture. On each database instance, you size and manage the IM column separately. The database instances do *not* use Cache Fusion to transfer IMCUs back and forth.

Figure 10-1 IM Column Stores in an Oracle RAC Database


This figure shows a two-node Oracle RAC cluster. Each instance has a separately configured IM column store.



Oracle recommends that you set the size of the IM column stores on every Oracle RAC node to an equal value. For example, you might assign every IM column store 100 GB of memory. For any node that does not require an IM column store, set the INMEMORY_SIZE initialization parameter on this node to 0.

Figure 10-2 Three-Node Oracle RAC Database with Two IM Column Stores

In this example, instance 1 and instance 2 both have IM column stores. Instance 3 does not require an IM column store, so the INMEMORY_SIZE initialization parameter on this node is set to 0.



See Also:

- "Enabling the IM Column Store for a Database (page 3-3)"
- *Oracle Database Reference* for more information about the INMEMORY_SIZE initialization parameter
- Oracle Real Application Clusters Administration and Deployment Guide for an introduction to Oracle RAC

10.1.2 Distribution and Duplication of Columnar Data in Oracle RAC

When INMEMORY is specified, the DISTRIBUTE and DUPLICATE keywords control the distribution of objects.

Oracle RAC provides multiple distribution options. You can have different objects populated on each node, or have larger objects distributed across all IM column stores in the Oracle RAC cluster. You can also have the same objects populated in the IM column store on every node (Oracle Engineered Systems only).

Note:

If a table is currently populated in the IM column store, and if you change any INMEMORY attribute of the table *other than* PRIORITY, then the database evicts the table from the IM column store. The repopulation behavior depends on the PRIORITY setting.

This section contains the following topics:

Distribution of Columnar Data in Oracle RAC (page 10-5)

The DISTRIBUTE clause of INMEMORY controls how table data in the IM column store is distributed across Oracle RAC instances.

Duplication of Columnar Data in Oracle RAC (page 10-9)

The DUPLICATE clause controls how an Oracle RAC database duplicates columnar data across Oracle RAC instances.

10.1.2.1 Distribution of Columnar Data in Oracle RAC

The DISTRIBUTE clause of INMEMORY controls how table data in the IM column store is distributed across Oracle RAC instances.

When the default option of AUTO is set, the Oracle RAC instances distribute data automatically. While populating a segment, Space Management Slave Processes (*Wnnn*) processes attempt to put an equal amount of data on each instance. Distribution depends on access patterns and object size. Alternatively, you can manually specify how the database must distribute partitions, subpartitions, or rowid ranges across instances.

Equal data distribution is important for performance. The goal is for parallel query processes to work on equal data set sizes so that they all finish in the minimum amount of time. If data distribution is skewed, then a long-running process delays the completion of the query.

If an Oracle RAC instance fails, then the IMCUs on the failed instance are unavailable. Consequently, a query that needs data stored in the inaccessible IMCUs must read it from somewhere else: the database buffer cache, flash storage, disk, or mirrored IMCUs in other IM column stores.

The DBA_TABLES.INMEMORY_DISTRIBUTE column indicates how IMCUs are distributed. When the AUTO option is set, the column value is AUTO-DISTRIBUTE.

Example 10-1 Default Distribution

This example shows the database distributing a sales table that contains only partitions: sales_2013_pt and sales_2014_pt. The database automatically places the sales_2013_pt partition in Instance 1, and sales_2014_pt in Instance 2.

Oracle RAC Database Instance 1 Instance 2 System Global Area (SGA) System Global Area (SGA) **Database Buffer Cache In-Memory Column Store Database Buffer Cache In-Memory Column Store** sales_2013_pt sales_2014_pt IMCU 1 IMCU 1 IMCU 2 IMCU 2 **Database** Data Control Online Redo Files

Figure 10-3 Automatic In-Memory Distribution in Oracle RAC

This section contains the following topics:

See Also:

- "Space Management Worker Processes (Wnnn) (page 2-20)"
- Oracle Real Application Clusters Administration and Deployment Guide to learn how to manage the IM column store on Oracle RAC
- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE clause
- Oracle Database Reference to learn about the Wnnn background processes

Distribution by Partition (page 10-6)

You can use the DISTRIBUTE BY PARTITION clause to distribute data in partitions to different Oracle RAC instances.

Distribution by Subpartition (page 10-7)

In tables with a composite partitioning scheme, you can use the DISTRIBUTE BY SUBPARTITION clause to distribute data in subpartitions to different instances.

Distribution by Rowid Range (page 10-8)

You can use the DISTRIBUTE BY ROWID RANGE clause to distribute data in specific ranges of rowids to different Oracle RAC instances.

10.1.2.1.1 Distribution by Partition

You can use the DISTRIBUTE BY PARTITION clause to distribute data in partitions to different Oracle RAC instances.

This technique is ideal for hash partitions. For example, to distribute partitions in the orders table equally, you could partition by hash on the order_id column. As shown in the following figure, Oracle Database distributes partitions among four instances by hashing on the order_id column.

ORDERS

PARTITION BY
HASH ON
ORDER_ID

1
2
3
4

Figure 10-4 Distributing Partitions by Hash

This technique is suitable for other partitioning schemes when the partitions are uniformly accessed. The DISTRIBUTE BY PARTITION clause also supports partitionwise joins.

Note:

If your partitioned strategy results in a large data skew, that is, one partition is much larger than the others, then Oracle recommends that you override the default distribution (BY PARTITION) by manually specifying DISTRIBUTE BY ROWID RANGE.

See Also:

- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE BY PARTITION subclause
- Oracle Database VLDB and Partitioning Guide for an introduction to partitioned tables

10.1.2.1.2 Distribution by Subpartition

In tables with a composite partitioning scheme, you can use the DISTRIBUTE BY SUBPARTITION clause to distribute data in subpartitions to different instances.

This technique is ideal for hash subpartitions. For example, to distribute partitions in the orders table equally, you could partition by range on the order_date column and by hash on the order_id column.




Figure 10-5 Distributing Partitions by Range and Subpartitions by Hash

This technique is suitable for other partitioning schemes when the subpartitions are uniformly accessed. The DISTRIBUTE BY PARTITION . . . SUBPARTITION clause also supports partition-wise joins.

See Also:

- Oracle Database VLDB and Partitioning Guide to learn more about composite partitioning
- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE BY PARTITION ... SUBPARTITION subclause

10.1.2.1.3 Distribution by Rowid Range

You can use the DISTRIBUTE BY ROWID RANGE clause to distribute data in specific ranges of rowids to different Oracle RAC instances.

This technique distributes IMCUs by uniform hash on the first rowid. For example, Oracle Database might distribute rows 1-105 in the orders table to one database instance, rows 106-121 to a different instance, and so on.

ORDERS

Rowid_Ranges

1-105
106-201
202-310
311-421
422-535

Figure 10-6 Distribution by Rowid Range

The rowid distribution technique is most useful for nonpartitioned tables. However, if your partitioned strategy results in a large data skew, for example, one partition is much larger than the others, then Oracle recommends overriding the default distribution (BY PARTITION) by manually specifying DISTRIBUTE BY ROWID RANGE.

See Also:

Oracle Database SQL Language Reference to learn more about the DISTRIBUTE BY ROWID RANGE subclause

10.1.2.2 Duplication of Columnar Data in Oracle RAC

The DUPLICATE clause controls how an Oracle RAC database duplicates columnar data across Oracle RAC instances.

Note:

The DUPLICATE clause is only available with Oracle RAC on an Oracle Engineered System. When Oracle RAC does *not* run on an Oracle Engineered System, the DUPLICATE clause is functionally equivalent to NO DUPLICATE.

To provide IM column store fault tolerance, you may choose to mirror the IMCUs. With IMCU mirroring, the same IMCU resides in multiple IM column stores. This technique is analogous to storage mirroring.




Figure 10-7 Duplication of IMCUs in Oracle RAC

Using the DUPLICATE clause to mirror data at the tablespace or object (table, partition, or subpartition) level provides the following benefits:

- Provides fault tolerance because if one node fails, then the mirrored columnar data is accessible from a different node
- Improves performance because queries can access data locally, thus avoiding buffer cache or disk access

For example, in a star query, the fact table might be partitioned, whereas the dimension tables use <code>DUPLICATE</code> ALL. In this scenario, all joins take place fully on the local nodes.

Enhances manageability because you can duplicate a subset of objects
 For example, you can duplicate this year's partitions while leaving others partitions from the same table not duplicated.

A disadvantage of IMCU mirroring is that when an object is duplicated n times, its memory requirements increase by a factor of n. For example, a 500 MB table that is duplicated in 4 instances occupies a total of 2000 MB of memory.

This section contains the following topics:

DUPLICATE Clause in Oracle RAC (page 10-11)

The DUPLICATE clause specifies that the database maintain a copy of every IMCU in a second database instance. Thus, the same segment is populated in exactly two Oracle RAC instances.

DUPLICATE ALL Clause in Oracle RAC (page 10-11)

The DUPLICATE ALL clause specifies that every In-Memory object is mirrored on every database instance.

NO DUPLICATE Clause in Oracle RAC (page 10-12)

The default NO DUPLICATE clause specifies that the database maintain only one copy of an object.

See Also: Oracle Database SQL Language Reference to learn more about the DUPLICATE clause

10.1.2.2.1 DUPLICATE Clause in Oracle RAC

The DUPLICATE clause specifies that the database maintain a copy of every IMCU in a second database instance. Thus, the same segment is populated in exactly two Oracle RAC instances.

For each object, one IMCU is primary. A secondary IMCU resides on a different database instance. The database can use either copy to satisfy a query. If the database instance with the primary copy of the IMCU fails, then the database can use the surviving IMCU to satisfy the query.

For example, you might specify DUPLICATE for the partition $sales_q1_2014$. The IM column stores in instance 1 and instance 2 both have an identical copy of the data. If instance 1 terminates, then the IM column store on instance 2 can satisfy requests for $sales_q1_2014$.

See Also:

- "In-Memory Compression Units (IMCUs) (page 2-8)"
- Oracle Database SQL Language Reference to learn more about the DUPLICATE clause

10.1.2.2.2 DUPLICATE ALL Clause in Oracle RAC

The DUPLICATE ALL clause specifies that every In-Memory object is mirrored on every database instance.

This setting provides the highest level of redundancy and provides linear scalability because queries can execute completely within a single node. For example, every IMCU for the sales table is populated in the IM column store in instance 1, instance 2, and instance 3. Thus, any database instance can retrieve the data requested by a query of sales.

A consequence of the DUPLICATE ALL clause is that the DISTRIBUTE subclause has no application because all IMCUs for the object are distributed. You specify duplication at the object level, which means that not all objects in the IM column store required the DUPLICATE ALL clause.

The primary advantages of the DUPLICATE ALL technique are:

High availability

When you use DUPLICATE ALL clause for all In-Memory objects, an Oracle RAC database with *n* instances can sustain *n*-1 Oracle RAC instance failures. If you need take one database instance out of service for maintenance, then critical data is available in at least one IM column store. The only scenario in which all data is inaccessible is a failure of all database instances in the cluster.

Performance of star queries

If queries join smaller dimension tables to a large partitioned fact table, then you can use <code>DUPLICATE</code> ALL to mirror dimension tables in every Oracle RAC instance. The fact table is distributed by partition or subpartition. In this strategy, the IM column store in every database instance has the data necessary for a star join. This technique is analogous to a partition-wise join because the entire dimension table is populated in every IM column store.

See Also:

Oracle Database SQL Language Reference to learn more about the DUPLICATE ALL clause

10.1.2.2.3 NO DUPLICATE Clause in Oracle RAC

The default NO DUPLICATE clause specifies that the database maintain only one copy of an object.

For example, a three-node Oracle RAC database might store the 2012 partition of a sales table in instance 1, the 2013 partition in instance 2, and the 2014 partition in instance 3. Each table partition resides in exactly one database instance.

If an Oracle RAC node does not duplicate the columnar data, then the columnar data on the failed node is not available in the IM column store on the cluster. Queries issued against missing data do not fail. Instead, queries access the data either from the database buffer cache or permanent storage, which may negatively affect performance. If the node remains down for some time, and if space exists in the surviving IM column stores, then Oracle RAC populates the missing objects or pieces of the objects on the remaining nodes in the cluster.

See Also:

Oracle Database SQL Language Reference to learn more about the NO DUPLICATE clause

10.1.3 Parallelism in Oracle RAC

A database instance must access the IMCUs in the IM column store in which they reside. Population and access of IM column stores in Oracle RAC must occur in parallel so that all IM column stores are accessible from any instance.

This section contains the following topics:

Serial and Parallel Queries in Oracle RAC (page 10-13)

Database In-Memory in Oracle RAC is a shared-nothing architecture. Unless at least one parallel server process runs on every active instance, a query is not guaranteed to access all necessary data from the IM column stores.

Auto DOP in Oracle RAC (page 10-13)

With Automatic Degree of Parallelism (Auto DOP), the optimizer performs a cost-based calculation to determine the degree of parallelism for a SQL statement.

10.1.3.1 Serial and Parallel Queries in Oracle RAC

Database In-Memory in Oracle RAC is a shared-nothing architecture. Unless at least one parallel server process runs on every active instance, a query is not guaranteed to access all necessary data from the IM column stores.

A serial query that runs on one node in an Oracle RAC database cannot access IMCUs in the other IM column stores. For example, a serial query running on instance 1 requests a full scan of sales. Some sales partitions are populated in the IM column store in instance 1, whereas the others are populated in the IM column store in instance 2. The query can only access the IMCUs in the IM column store on instance 1: the remaining data must come from on-disk storage.

The situation is similar when parallel execution is enabled, but the PARALLEL_DEGREE_POLICY initialization parameter is not set to AUTO. The query coordinator runs on the instance where the query executes. The PQ processes send data to the coordinator. In this case, the database starts multiple PQ processes. However, unless the DOP is greater than or equal to the number of IM column stores containing IMCUs populated for objects referenced in the query, not all data will be accessed from the IM column store. When Auto DOP is not enabled, you must ensure that the DOP is at least as great as the IM column stores with IMCUs for the populated objects in the query.

See Also:

- Oracle Database VLDB and Partitioning Guide to learn more about parallel queries in Oracle RAC
- Oracle Database Reference to learn more about the PARALLEL_DEGREE_POLICY initialization parameter

10.1.3.2 Auto DOP in Oracle RAC

With Automatic Degree of Parallelism (Auto DOP), the optimizer performs a cost-based calculation to determine the degree of parallelism for a SQL statement.

Enable Auto DOP by setting the PARALLEL_DEGREE_POLICY initialization parameter to AUTO. When the optimizer parses a SQL statement, it estimates the execution time. It checks this estimate against the setting of the PARALLEL_MIN_TIME_THRESHOLD initialization parameter, which is automatically set when the IM column store is enabled. The optimizer then makes the following cost-based decision:

- If the estimated time is less than PARALLEL_MIN_TIME_THRESHOLD, then the statement executes serially.
- If the estimated time is greater than PARALLEL_MIN_TIME_THRESHOLD, then the statement executes in parallel.

The optimizer calculates the degree of parallelism based on resource requirements. The calculation is limited by the PARALLEL_DEGREE_LIMIT initialization parameter and, if configured, the Database Resource Manager.

When using IM column stores in an Oracle RAC environment, the goal is to avoid disk or buffer cache access. To this end, you must *guarantee* that at least one parallel server process runs on every active database instance. Auto DOP is the recommended way to achieve this goal.

Note:

If you do not use Auto DOP, then you must ensure that the DOP is greater than or equal to the number of IM column stores containing the IMCUs required by the query.

Auto DOP guarantees an adequate distribution of processes because every shared pool stores metadata that indicates where all the IMCUs are located, how large they are, and so on. The same map is in every shared pool. No matter where the query originates in the cluster, the parallel query coordinator is aware of the home location (instance of residence) of the IMCUs.

For example, the PQ coordinator knows that the sales partitions for 2016 are located in instance 1, whereas the partitions for 2015 are located in instance 2. If a query running on instance 1 requests both 2015 and 2016 partitions, then the query coordinator uses the home location to determine which IM column stores to access. If the DOP has been set high sufficiently high, then the coordinator automatically starts PQ processes on both instances, and the processes send the requested data back to the query coordinator.

See Also: Oracle Database VLDB and Partitioning Guide to learn about Auto DOP

10.1.4 FastStart Area in Oracle RAC

The FastStart area is shared across all Oracle RAC nodes. This feature enables maximum sharing and reusability across the cluster.

Only one copy of an IMCU resides in the FastStart area. For example, if DUPLICATE ALL is specified for an object in a four-node cluster, then four copies of the object exist in the IM column stores. However, the database saves only one copy to the FastStart area.

Any database instance in an Oracle RAC cluster can use an IMCU in the FastStart area. This feature improves performance of instance restarts in an Oracle RAC environment.

For example, the sales table might have three partitions: sales_2014, sales_2015, and sales_2016, with each partition populated in a different instance. An instance failure occurs, with one instance unable to restart. If sufficient space is available in the IM column stores, then the surviving instances can read the IMCUs that were previously populated in the inaccessible instance. Thus, all three sales table partitions are available to applications.

See Also:

- "FastStart Area in Oracle RAC (page 10-14)"
- Oracle Database SQL Language Reference to learn more about the DUPLICATE ALL clause

10.2 Configuring In-Memory Services in Oracle RAC

A **service** represents a set of instances. In Oracle RAC, you can use services to direct connections or applications to a subset of nodes in the cluster.

This section contains the following topics:

Instance-Level Service Controls (page 10-15)

In Oracle RAC, the population and access of IM column stores must occur in parallel so that all IM column stores are accessible from any database instance.

Object-Level Service Controls (page 10-16)

For an individual object, the INMEMORY ... DISTRIBUTE clause has a FOR SERVICE subclause that limits population to the database instance where this service is allowed to run.

Benefits of Services for Database In-Memory in Oracle RAC (page 10-17)

The combination of services and DUPLICATE enables you to control node access and In-Memory population.

Configuring an In-Memory Service for a Subset of Nodes: Example (page 10-18)

This task explains how to assign an In-Memory service to a subset of nodes in an Oracle RAC database.

See Also:

Oracle Real Application Clusters Administration and Deployment Guide to learn more about services in Oracle RAC

10.2.1 Instance-Level Service Controls

In Oracle RAC, the population and access of IM column stores must occur in parallel so that all IM column stores are accessible from any database instance.

The PARALLEL_INSTANCE_GROUP initialization parameter restricts parallel query operations to the specified service. For example, if three out of four database instances in a cluster have an IM column store, then you might create a service named dbmperf and use PARALLEL_INSTANCE_GROUP to assign these three instances to this service. You can then restrict all client connections to the dbmperf service. Parallel operations spawn parallel execution processes only on the instances defined in the service.




Figure 10-8 Assigning a Subset of Instances to a Service

See Also: Oracle Database Reference to learn more about the PARALLEL_INSTANCE_GROUP initialization parameter

10.2.2 Object-Level Service Controls

For an individual object, the INMEMORY ... DISTRIBUTE clause has a FOR SERVICE subclause that limits population to the database instance where this service is allowed to run.

The Parallel_Instance_group initialization parameter controls segments at the service level, where a service represents one or more instances. In contrast, Inmemory . . . Distribute for Service controls distribution at the segment level. For example, you can configure an Inmemory object to be populated in the IM column store on instance 1 only, or on instance 2 only, or in both instances.

The DISTRIBUTE FOR SERVICE options are:

- DEFAULT If PARALLEL_INSTANCE_GROUP is set, then the object is populated in all database instances that have an IM column store specified in PARALLEL_INSTANCE_GROUP. If PARALLEL_INSTANCE_GROUP is not set, then the object is populated in all instances that have an IM column store.
 - Specifying FOR SERVICE is equivalent to specifying FOR SERVICE DEFAULT.
- ALL The database populates the object in all instances that have an IM column store.

Note:

If PARALLEL_INSTANCE_GROUP is not set, then DEFAULT and ALL are functionally equivalent.

• *service_name* - As part of its duties, IMCO triggers the removal of the object from the database instances assigned to the previous service, and populates it into the instances assigned to the new service.

When redistributing segments, the database does the minimum work necessary. For example, service dbmperf is assigned to instance 1 and instance 2. The sales partitions are evenly distributed between instance 1 and instance 2. You add instance 3 to this service. The database only populates IMCUs in instance 3 and then removes them from instance 1 or instance 2 when necessary for even distribution. Some IMCUs remain in their original location.

 NONE - IMCO removes the object from the IM column stores of the currently specified services.

If the object has PRIORITY set to a value other than NONE, then Wnnn processes populate the object during the next IMCO cycle after the DDL executes or the service starts. If the object has PRIORITY set to NONE, however, then the object is not populated until it undergoes a full table scan. The scan triggers In-Memory population on all instances on which the specified service for the table is active and not blocked. Note that this service can be different from the scan of the issuing service.

If a service that is used for In-Memory population stops, then the database removes the segment from the IM column stores represented by this service. In this respect, stopping the service is like shutting down the instances. The INMEMORY attributes of this object do not change. If the service starts again, then the database populates the object according to its INMEMORY attributes. To remove an object from the IM column store, specify NO INMEMORY in a DDL statement.

You can combine DUPLICATE with DISTRIBUTE FOR SERVICE. For example, you might specify that an object use DUPLICATE ALL for service dbmperf, which is assigned to three nodes out of four. In this case, the IM column store on each of these three nodes has a copy of the object.

See Also:

- "Prioritization of In-Memory Population (page 4-2)"
- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE FOR SERVICE subclause

10.2.3 Benefits of Services for Database In-Memory in Oracle RAC

The combination of services and DUPLICATE enables you to control node access and In-Memory population.

Benefits of services include the following:

Rolling patches and upgrades

Suppose you set up an Oracle RAC service to direct client queries to the instances that contain an IM column store. If you use the DUPLICATE clause, then you can selectively remove an instance without affecting query response time. This

approach assumes that sufficient resources exist on the other instances in the service to handle the workload of the removed instance.

For example, in a four-node cluster, you could remove each node in turn, patch it, and then make it available again. The IMCUs for the temporarily inaccessible node are available on at least one other node, depending on whether you use the DUPLICATE or DUPLICATE ALL clause. Thus, application access to columnar data remains uninterrupted.

Application affinity

You can restrict application access to a single node based on service name. For example, service <code>dbmperf1</code> is restricted to node 1, service <code>dbmperf2</code> is restricted to node 2, and so on. When an application connects to a specific service and submits a parallel query, the query uses processes on the nodes belonging to the same service. For example, an application that connects to service <code>dbmperf1</code> only uses processes on node 1.

Applications can coexist in an Oracle RAC database independently and access columnar data. Completely different objects can be populated in each node. For example, you could direct an HR application to service dbmperf1, and direct a sales history application to service dbmperf2.

See Also:

"About In-Memory Population (page 4-1)"

10.2.4 Configuring an In-Memory Service for a Subset of Nodes: Example

This task explains how to assign an In-Memory service to a subset of nodes in an Oracle RAC database.

The goal is the following:

- Create IM column stores on a subset of nodes in a RAC database
- Define a service to allow access to only the nodes that have an IM column store

Assumptions

This task assumes the following:

- The Oracle RAC database named dbmm has four instances: dbm1, dbm2, dbm3, and dbm4. See "Figure 10-8 (page 10-16)".
- All instances except dbm4 have INMEMORY_SIZE set to a nonzero value.
- You want to add a service named dbmperf and assign it to the three nodes that have an IM column store.
- You want to populate the sales table in the IM column stores attached to the service.

To configure an In-Memory service for a subset of nodes:

1. Create a service that represents the three nodes running IM column stores.

On the operating system command line, use the srvctl command using the following form:

```
srvctl add service -db db_name -s service_name
-preferred "instance_names"
```

For example, enter the following command:

```
srvctl add service -db dbmm -s dbmperf -preferred "dbm1, dbm2, dbm3"
```

2. Start the service.

For example, to start the dbmperf service, use the following command:

```
srvctl start service -db dbmm -service "dbmperf"
```

3. Create a net service name for a connection to the service.

For example, update the tnsnames.ora file as follows:

4. Assign the INMEMORY attribute to the tables that you intend to populate, using the DISTRIBUTE FOR SERVICE subclause.

For example, alter sales as follows:

```
ALTER TABLE sales INMEMORY DISTRIBUTE FOR SERVICE "dbmperf";
```

The preceding statement uses the default PRIORITY setting of NONE for the sales table. Therefore, population of this table occurs on demand rather than automatically.

5. To populate the sales table, connect to the dbmperf service, and then initiate a full scan of the table.

For example, force a full scan by querying sales as follows:

```
SELECT /*+ FULL(s) */ COUNT(*) FROM sales s;
```

See Also:

- Oracle Database SQL Language Reference to learn more about the INMEMORY DISTRIBUTE FOR SERVICE clause of ALTER TABLE
- *Oracle Database Administrator's Guide* to learn more about the srvctl utility
- Oracle Database Net Services Administrator's Guide to learn more about net service names

Deploying an IM Column Store with Oracle Active Data Guard

This chapter explains how Database In-Memory feature works in an Oracle Active Data Guard environment.

This chapter contains the following topics:

About Database In-Memory and Active Data Guard (page 11-1)

Starting in Oracle Database 12*c* Release 2 (12.2.0.1), Oracle Database In-Memory is supported on a standby database in an Oracle Active Data Guard environment.

Configuring IM Column Stores in an Oracle Active Data Guard Environment (page 11-5)

Configuring IM column stores in Oracle Active Data Guard requires setting INMEMORY_SIZE, and setting the INMEMORY attribute appropriately for the objects to be populated.

11.1 About Database In-Memory and Active Data Guard

Starting in Oracle Database 12*c* Release 2 (12.2.0.1), Oracle Database In-Memory is supported on a standby database in an Oracle Active Data Guard environment.

This section contains the following topics:

Purpose of IM Column Stores in Oracle Active Data Guard (page 11-1)

You can configure an IM column store only on the primary database, only on a standby database, or on both the primary and standby databases.

How IM Column Stores Work in Oracle Active Data Guard (page 11-4)

In an Oracle Active Data Guard environment, the object-level PRIORITY attribute governs population. An object is only populated in the database instances on which the service is active.

See Also:

Oracle Data Guard Concepts and Administration for an introduction to Oracle Active Data Guard

11.1.1 Purpose of IM Column Stores in Oracle Active Data Guard

You can configure an IM column store only on the primary database, only on a standby database, or on both the primary and standby databases.

If you configure an IM column store for both databases, then you can populate the same or a different set of objects on the two instances. This technique effectively increases the IM column store size.

This section contains the following topics:

Identical IM Column Stores in Primary and Standby Databases (page 11-2)

In the simplest scenario, the primary and standby databases both contain an IM column store with the same size (which is not required). The IM column stores contain the same objects.

IM Column Store in Standby Database Only (page 11-3)

In this scenario, an IM column store exists in the standby database, but not in the primary database.

Different Objects in the Primary and Standby IM Column Stores (page 11-3)

The most flexible scenario is separately configuring the IM column stores for primary and standby databases.

11.1.1.1 Identical IM Column Stores in Primary and Standby Databases

In the simplest scenario, the primary and standby databases both contain an IM column store with the same size (which is not required). The IM column stores contain the same objects.

The advantage of this scenario is that analytic queries can access the IM column store on either database. Therefore, you can direct analytic queries to the standby database and not consume resources on the primary database. As a result, the primary database can support the transactional workload, while the standby database supports the analytic workload.

The primary tasks are as follows:

- Set the INMEMORY_SIZE initialization parameter on both the primary and standby database instances.
- Ensure that the INMEMORY_ADG_ENABLED initialization parameter is set to true (default) on the standby database instance.
- Set the INMEMORY attribute on all objects to be populated in the two IM column stores.

If you change the INMEMORY attributes of an object, then the primary database propagates the change to the standby database. For example, if you set the NO INMEMORY attribute on the sales table, then both IM column stores evict sales.

On the primary database, you can enable a subset of columns of a table for population into the IM column store. You can also specify different compression levels for different columns. Enabling specific columns involves a dictionary change. DDL on the primary database is propagated to the Oracle Active Data Guard database.

See Also:

- "Enabling the IM Column Store for a Database (page 3-3)"
- Oracle Database SQL Language Reference for information about the CREATE TABLE statement
- Oracle Database Reference for more information about the INMEMORY_SIZE and INMEMORY_ADG_ENABLED initialization parameters

11.1.1.2 IM Column Store in Standby Database Only

In this scenario, an IM column store exists in the standby database, but not in the primary database.

In this scenario, the primary database can function as a pure OLTP database. No extra memory is required in the primary database for an IM column store. You can direct analytic reporting applications to the standby database without sacrificing performance or consuming resources on the primary database.

The primary tasks are as follows:

- Set the INMEMORY_SIZE initialization parameter to a non-zero value in the standby database instance, and set it to 0 in the primary database instance.
- Ensure that the INMEMORY_ADG_ENABLED initialization parameter is set to true (default) on the standby database instance.
- Set the INMEMORY attribute with the DISTRIBUTE FOR SERVICE clause on all objects to be populated in the IM column store in the standby database.

For example, if you log in to the primary database, and if you set the INMEMORY attribute on the sh.sales table, then this table will not be populated in the IM column store on the primary database—because no IM column store exists on this database. However, the standby database will inherit the INMEMORY attribute on the sh.sales table. The table will be populated in the IM column store in the standby database.

11.1.1.3 Different Objects in the Primary and Standby IM Column Stores

The most flexible scenario is separately configuring the IM column stores for primary and standby databases.

The advantage of this scenario is that you can run different workloads in each database. For example, an HR application runs reports in the primary database, while a sales history application runs reports in the standby database. Thus, neither database bears the full burden of analytic reporting.

The primary tasks are as follows:

- Set the INMEMORY_SIZE initialization parameter to a non-zero value on the standby and primary database instance. The values do not need to be identical.
- Ensure that the INMEMORY_ADG_ENABLED initialization parameter is set to true (default) on the standby database instance.
- Set the INMEMORY ... DISTRIBUTE FOR SERVICE clause on all objects to be populated in the two IM column stores. The service specifies the instance into which the object is populated.

Three-Service Configuration

In a typical configuration, you create three services: standby-only, primary-only, and primary-and-standby. For example, you may want the latest month of sales fact table data in the primary instance, but the previous sales data in the standby instance. You want the dimension tables populated in both instances. For each sales partition, you use INMEMORY ... DISTRIBUTE FOR SERVICE to specify either the standby or primary service. For each dimension table, you specify the service that includes both primary and standby database instances.

Note:

As long as the service name is defined for both the primary and standby instances, you can specify the same service name in DISTRIBUTE FOR SERVICE to populate the same tables in the primary and standby databases.

Oracle RAC and Oracle Active Data Guard

In Oracle RAC, you can combine the FOR SERVICE clause, which specifies the instance for population, with the DISTRIBUTE AUTO or DISTRIBUTE BY clause, which controls the distribution of IMCUs. However, in Oracle Active Data Guard, the FOR SERVICE clause specifies the primary or standby instances in which to *populate* the specified object: you cannot use DISTRIBUTE AUTO or DISTRIBUTE BY to distribute IMCUs *between* the primary and standby instances. For example, you cannot divide the population of the sales table between the primary instance and standby instance, so that half the IMCUs are in the primary instance and half the IMCUs are in the standby instance.

See Also:

- "Object-Level Service Controls (page 10-16)"
- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE FOR SERVICE subclause

11.1.2 How IM Column Stores Work in Oracle Active Data Guard

In an Oracle Active Data Guard environment, the object-level PRIORITY attribute governs population. An object is only populated in the database instances on which the service is active.

Population is either on-demand on priority-based, depending on the PRIORITY value. When a role change or switchover occurs, the database repopulates the tables according to the set of database instances to which the service is newly mapped.

Note:

Standby databases do not support IM FastStart, join groups, capturing IM expressions, or multi-instance redo apply.

The following graphic illustrates the internal mechanism for updating a standby database with redo from the primary database.

Primary Site Secondary Site IM Column Store IM Column Store IMCU's for IMCU's for SMU sales table sales table Invalidation data redo shipping applied to SMUs IM column store Special Redo populated on demand or by Data blocks Generation recovered on disk priority

Figure 11-1 Updating a Standby Database

The process is as follows:

- The primary database generates redo, and then transfers the redo to the standby database.
 - The redo generated on the primary database for all DML statements includes metadata indicating whether the change is to an INMEMORY object.
- 2. The standby database applies the redo to the data blocks stored in disk.

 As the standby database applies redo generated from ongoing operations on the primary database, the standby database keeps them transactionally consistent.
- **3.** If an INMEMORY object is modified, then the standby database invalidates the modified rows just as it does on the primary database, using the transaction journal and Snapshot Metadata Unit (SMU) to track the changes.

The repopulation mechanism works the same way in a standby database as it does in a primary database. When sufficient DML occurs on an object to reach an internal threshold, the standby database repopulates the object in the IM column store.

See Also:

- "About Repopulation of the IM Column Store (page 8-1)"
- "About Join Groups (page 6-2)"
- Oracle Data Guard Concepts and Administration to learn more about multiinstance redo apply

11.2 Configuring IM Column Stores in an Oracle Active Data Guard Environment

Configuring IM column stores in Oracle Active Data Guard requires setting INMEMORY_SIZE, and setting the INMEMORY attribute appropriately for the objects to be populated.

This task assumes thorough knowledge of Oracle Active Data Guard concepts and procedures.

Prerequisites

You must meet the following requirements:

- The COMPATIBLE setting must be 12.2.0 or greater.
- To populate different objects in each database, configure the appropriate services.

To configure IM column stores in an Oracle Active Data Guard environment:

1. Set the INMEMORY_SIZE initialization parameter on the database instances that will contain an IM column store.

Follow these guidelines:

- To configure IM column stores on the primary and standby databases, set INMEMORY_SIZE on both database instances.
- To configure IM column stores on the standby database only, set INMEMORY_SIZE on the standby database instance.
- **2.** Ensure that the INMEMORY_ADG_ENABLED initialization parameter is set to true (default) on the standby database instance.
- 3. On the primary database, execute DDL statements with the INMEMORY attribute.

 The task depends on where the IM column stores exist, and whether different objects will be populated in each IM column store:
 - If an IM column store exists in both databases, then connect to the primary database, and set INMEMORY attributes without a DISTRIBUTE FOR SERVICE clause. For example, apply the INMEMORY attribute to the sh.sales table.
 - Population occurs on each database according to the standard rules. For example, if sales on the standby database has priority NONE, then a query of the standby database that triggers a full scan of sales populates this table in the standby IM column store.

Note:

A full scan of sales on the *standby* database does not populate this table in the IM column store in the *primary* database.

- If an IM column store exists in the standby database only, then log in to the primary database, and set INMEMORY attributes without a DISTRIBUTE FOR SERVICE clause.
 - During redo transfer, the standby database receives this DDL statement from the primary database. Population occurs on the standby database in the normal way. For example, if sales has the INMEMORY attribute and priority NONE, then the table must undergo a full scan for population to occur.
- If an IM column store exists in both databases, and if you want these IM column stores to contain different objects, then log in to the primary database,

and set INMEMORY ... DISTRIBUTE FOR SERVICE as appropriate for each object.

In each DDL statement, the service specifies the instances in which the object should be populated. For example, to enable sales for population only in the standby database, specify a standby-only service in the DDL statement. To enable products for population in both databases, specify a standby-and-primary service in the DDL statement.

See Also:

- "Prioritization of In-Memory Population (page 4-2)"
- Oracle Database SQL Language Reference to learn more about the DISTRIBUTE FOR SERVICE subclause
- *Oracle Database Reference* for more information about the INMEMORY_SIZE and INMEMORY_ADG_ENABLED initialization parameters

Part V

Database In-Memory Reference

The Part contains initialization parameters and views relevant for the In-Memory Column Store (IM column store).

In-Memory Initialization Parameters (page 12-1)

This topic describes initialization parameters related to the IM column store.

In-Memory Views (page 13-1)

This topic describes data dictionary and dynamic performance views related to the In-Memory Column Store (IM column store).

In-Memory Initialization Parameters

This topic describes initialization parameters related to the IM column store.

Table 12-1 Initialization Parameters Related to the IM Column Store

Initialization Parameter	Description
INMEMORY_ADG_ENABLED	Indicates whether In-Memory for Oracle Active Data Guard is enabled (TRUE) or disabled (FALSE) on the standby database. The default is TRUE.
	For Active Data Guard, media recovery must retrieve In-Memory objects when applying redo and invalidate the related objects after the query advance. This parameter controls whether media recovery performs the retrieving and invalidating.
	You can only modify this system-level parameter when standby recovery is not running. If the standby database uses Oracle RAC, then this parameter must be set to the same value on every instance.
INMEMORY_CLAUSE_DEFAULT	Specifies a default IM column store clause for new tables and materialized views.
	This parameter supports the following options:
	 To specify that there is no default IM column store clause for new tables and materialized views, leave this parameter unset or set it to an empty string. Setting this parameter to NO INMEMORY has the same effect as setting it to the default value (the empty string). To specify that the clause is the default for all new tables and materialized views, set this parameter to a valid INMEMORY clause. The clause can include valid clauses for IM column store compression methods and data population options. The options are: If the clause starts with INMEMORY, then all new tables and materialized views, including those without an INMEMORY clause, are populated in the IM column store.
	 If the clause omits INMEMORY, then it only applies to new tables and materialized views that are enabled for the IM column store with an INMEMORY clause during creation.

Table 12-1 (Cont.) Initialization Parameters Related to the IM Column Store

Initialization Parameter	Description
INMEMORY_EXPRESSIONS_USAGE	Controls which IM expressions are eligible to be populated in the IM column store.
	This parameter supports the following options:
	• ENABLE
	The database populates both static and dynamic IM expressions into the IM column store. Setting this value increases the In-Memory footprint for some tables. This is the default. • STATIC_ONLY
	A static configuration enables the IM column store to cache OSON (binary JSON) columns, which are marked with an IS_JSON check constraint. Internally, an OSON column is a hidden virtual column named SYS_IME_OSON. • DYNAMIC_ONLY
	The database only populates frequently used or "hot" expressions that have been added to the table as SYS_IME hidden virtual columns. Setting this value increases the In-Memory footprint for some tables.
	• DISABLE
	The database does not populate any IM expressions, whether static or dynamic, into the IM column store.
	Note: IM expressions do not support NLS-dependent data types.
INMEMORY_FORCE	Enables or disables tables and materialized views for the IM column store. This parameter supports the following options: • To allow the INMEMORY or NO INMEMORY
	attributes to determine population, set this parameter to DEFAULT (the default value). • To disable all tables and materialized views for the IM column store, set this parameter to OFF.

Table 12-1 (Cont.) Initialization Parameters Related to the IM Column Store

Initialization Parameter	Description
INMEMORY_MAX_POPULATE_SERVERS	Specifies the maximum number of Space Management Worker Processes (Wnnn) to use for population so that the processes do not overload the rest of the system. Set this parameter to an appropriate value based on the number of cores in the system. The default is half the effective CPU thread count or the PGA_AGGREGATE_TARGET value divided by 512 MB, whichever is less. Note: When INMEMORY_MAX_POPULATE_SERVERS is set to 0, objects cannot be populated in the IM column
INMEMORY_QUERY	 Specifies whether In-Memory queries are allowed: To allow queries to access populated objects, set this parameter to ENABLE (the default). To disable access to populated objects, set this parameter to DISABLE.
INMEMORY_SIZE	Sets the size of the IM column store in a database instance. The default is 0, which disables the IM column store. The minimum non-zero setting is 100M.
INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT	Limits the percentage of the total population and repopulation processes that perform trickle repopulation. The value for this parameter is a percentage of the INMEMORY_MAX_POPULATE_SERVERS initialization parameter value. For example, if INMEMORY_TRICKLE_REPOPULATE_SERVERS_PERCENT is 5 percent, and if INMEMORY_MAX_POPULATE_SERVERS is 20, then the IM column store uses an average of 1 core (.05 * 20) for trickle repopulation.
INMEMORY_VIRTUAL_COLUMNS	Controls which expressions are populated in the IM column store. This parameter supports the following options: ENABLE permits population of all IM virtual columns in an INMEMORY table, unless these columns have been explicitly excluded from the IM column store. MANUAL (the default) permits population of IM virtual columns explicitly specified as INMEMORY. DISABLE specifies that no IM virtual columns are eligible for population.

Table 12-1 (Cont.) Initialization Parameters Related to the IM Column Store

Initialization Parameter	Description
OPTIMIZER_INMEMORY_AWARE	Controls the optimizer cost model enhancements for Database In-Memory.
	This parameter supports the following options:
	TRUE (default) optimizes SQL statements that reference INMEMORY objects.
	FALSE ignores the INMEMORY attribute of tables during optimization.

In-Memory Views

This topic describes data dictionary and dynamic performance views related to the In-Memory Column Store (IM column store).

Table 13-1 In-Memory Views

Latter Control	B
Initialization Parameter	Description
DBA_EXPRESSION_STATISTICS	Provides expression usage tracking statistics for all the tables in the database.
DBA_FEATURE_USAGE_STATISTICS	Displays information about database feature usage statistics. When the IM column store is accessed, the NAME column shows In-Memory Column Store.
DBA_HEAT_MAP_SEGMENT	Displays the latest segment access time for all segments. The timestamps in the view are coarse with a granularity of a day reflecting the flush times of the heat map.
DBA_ILMDATAMOVEMENTPOLICIES	Contains information specific to data movement-related attributes of an Automatic Data Optimization policy in a database.
DBA_IM_EXPRESSIONS	Describes the IM expressions, which have the column prefix SYS_IME, that have the INMEMORY attribute.
DBA_JOINGROUPS	Describes join groups in the database. A join group is a user-created object that lists two columns that can be meaningfully joined.
DBA_SEGMENTS	Describes the storage allocated for all segments in the database. Several columns, including INMEMORY and INMEMORY_PRIORITY, describe In-Memory attributes of the segment.
DBA_TABLES	Indicates which tables have the INMEMORY attribute set (the INMEMORY column is ENABLED) or not set (DISABLED).
V\$ACTIVE_SESSION_HISTORY	Displays sampled session activity. Several columns, including INMEMORY_QUERY and INMEMORY_POPULATE, describe session activity relating to the In-Memory Column Store at the time of sampling.
V\$HEAT_MAP_SEGMENT	Displays real-time segment access information.
V\$IM_COLUMN_LEVEL	Presents the selective column compression levels that are defined using the INMEMORY clause of the CREATE TABLE statement. SYS_IME hidden virtual columns are not shown in this view.

Table 13-1 (Cont.) In-Memory Views

Initialization Parameter	Description
V\$IM_SEGMENTS	Presents information about all In-Memory segments in the database. Only segments that have an In-Memory representation are displayed. If a segment is marked for the IM column store but is not populated, the view does not contain a corresponding row for this segment.
V\$INMEMORY_AREA	Displays information about the space allocation inside the In- Memory Area.
V\$INMEMORY_FASTSTART_AREA	Provides information about the In-Memory FastStart (IM FastStart) area.
V\$SGA	Displays the size of the In-Memory Area.

Using IM Column Store In Cloud Control

You can configure and manage the IM column store in Oracle Enterprise Manager Cloud Control (Cloud Control).

Video:

Oracle Database 12c demos: In-Memory Column Store Monitored with Enterprise Manager

Meeting Prerequisites for Using IM Column Store in Cloud Control (page A-2)

Before you can enable a database to use the IM column store, ensure that the COMPATIBLE is set to 12.1.0.0 or higher.

Using the In-Memory Column Store Central Home Page to Monitor In-Memory Support for Database Objects (page A-2)

Use the In-Memory Column Store Central Home page to monitor In-Memory support for database objects such as tables, indexes, partitions and tablespaces. You can view in-memory functionality for objects and monitor their In-Memory usage statistics.

- Specifying In-Memory Details When Creating a Table or Partition (page A-3) You can specify IM column store details when creating a table or partition.
- Viewing or Editing IM Column Store Details of a Table (page A-3) You can view or edit IM column store details of a table.
- Viewing or Editing IM Column Store Details of a Partition (page A-4) You can view or edit IM column store details of a partition.
- Specifying IM Column Store Details During Tablespace Creation (page A-4) You can specify IM column store details when creating a tablespace.
- Viewing and Editing IM Column Store Details of a Tablespace (page A-5) You can view or edit IM column store details of a tablespace.
- Specifying IM Column Store Details During Materialized View Creation (page A-5)

You can specify IM column store details when creating a materialized view.

Viewing or Editing IM Column Store Details of a Materialized View (page A-5)

You can view or edit IM column store details of a materialized view.

A.1 Meeting Prerequisites for Using IM Column Store in Cloud Control

Before you can enable a database to use the IM column store, ensure that the COMPATIBLE is set to 12.1.0.0 or higher.

To set the compatibility level, follow these steps:

1. From the Database Home page in Enterprise Manager, choose **Initialization Parameters** from the **Administration** menu to navigate to the Initialization Parameters page.

You can use this page to set or change the compatibility level.

2. Search for the COMPATIBLE initialization parameter.

The category for the parameter is Miscellaneous.

3. Change the value to 12.1.0.0 and click **Apply**.

Cloud Control prompts you to restart the database. After the database is restarted, the new value takes effect.

To set or change the size of the IM column store, follow these steps:

- From the Database Home page in Enterprise Manager, choose Initialization Parameters from the Administration menu to navigate to the Initialization Parameters page.
- **2.** Search for the parameter INMEMORY_SIZE. The category for the parameter is In-Memory.
- **3.** Change the value and click **Apply**.

You can set the value to any value above the minimum size of 100 MB.

You will then be prompted to restart the database.

A.2 Using the In-Memory Column Store Central Home Page to Monitor In-Memory Support for Database Objects

Use the In-Memory Column Store Central Home page to monitor In-Memory support for database objects such as tables, indexes, partitions and tablespaces. You can view in-memory functionality for objects and monitor their In-Memory usage statistics.

You can complete the following actions on the In-Memory Column Store Central Home page:

- The In-Memory Object Access Heatmap displays the top 100 objects in the IM column store with their relative sizes and shows you how frequently objects are accessed, represented by different colors. To activate the heat map, you must turn on the option for the Heat Map in the initialization parameter file. Typically, there is a one day wait period before the map is activated. You can use the date selector to pick the date range for objects displayed in the Heat Map. You can also use the slider to control the granularity of the color.
- Use the Configuration section to view the status settings such as In-Memory Query, In-Memory Force, and Default In-Memory Clause. Click Edit to navigate to the Initialization Parameters page where you can change the values and settings

displayed in this section. Use the Performance section to view the metrics for Active Sessions.

- Use the Objects Summary section to view the Compression Factor and data about
 the memory used by the populated objects. The In-Memory Enabled Object
 Statistics are available in a pop-up window through a drill-down from the View InMemory Enabled Object Statistics link on the page.
- Use the In-Memory Objects Distribution section to view the distribution on a
 percentage basis of the various objects used in memory. The section includes a
 chart showing the distribution of Partitions, Subpartitions, Non-partitioned Tables,
 and Non-partitioned Materialized Views. The numerical values for each are
 displayed above the chart.
- Use the In-Memory Objects Search section to search for objects designated for In-Memory use. Click Search after you enter the parameters by which you want to search. The results table shows the Name of each object found along with its Size, Size in Memory, Size on Disk, In-Memory percentage, and its In-Memory parameters. You can also search for accessed objects that are either in-memory or not in-memory. If the Heat Map is enabled, then the Accessed Objects option appears in the drop-down list in the View field of the In-Memory Objects Search box. When you select Accessed Objects, you can filter based on the top 100 objects with access data that are either in-memory or not in-memory. You can select a time range and search for objects within that range. If you select the All Objects In-Memory option, you can view the list of top 100 objects that are in-memory based on their in-memory size.

If you are working in an Oracle RAC environment, you can quickly move between instances by selecting the instance in the Instances selection box above and on the right side of the Heat Map.

A.3 Specifying In-Memory Details When Creating a Table or Partition

You can specify IM column store details when creating a table or partition.

- 1. From the Schema menu, choose Database Objects, then select the Tables option.
- 2. Click Create to create a table.
 - The Create Table page is shown. Select the In-Memory Column Store tab to specify the in-memory options for the table.
- **3.** Choose to override the column level in-memory details (if required) in the table below where the columns are specified.
- **4.** Optionally, you can click on the **Partitions** tab.
- **5.** Create table partitions as needed using the wizard.
 - To specify IM column store details for a partition, select it from the table in the Partitions tab, and then click **Advanced Options**.
- **6.** After entering all necessary IM column store details at the table level, column level, and partitions level, click **Show SQL** to see the generated SQL. Click **OK** to create the table.

A.4 Viewing or Editing IM Column Store Details of a Table

You can view or edit IM column store details of a table.

- **1.** From the **Schema** menu, choose **Database Objects**, and then select the **Tables** option.
- **2.** Search for the desired table, and then click **View** to view its details.
- **3.** Click **Edit** to launch the Edit Table page.

Alternatively, on the Search page, click **Edit**. Click the **In-Memory Column Store** tab to specify In-Memory options for the table.

- **4.** Edit the required details.
- 5. Click Apply.

A.5 Viewing or Editing IM Column Store Details of a Partition

You can view or edit IM column store details of a partition.

- 1. From the Schema menu, choose Database Objects, then select the Tables option.
- **2.** Search for the table that contains the desired partition, select it, and then click **View**.
- **3.** Click **Edit** to launch the Edit Table page.

Alternatively, on the Table Search page, click **Edit**.

- **4.** Click the **Partitions** tab, and then select the desired partition.
- 5. Click Advanced Options.
- **6.** Edit the required details.
- 7. Click **OK** to return to the Partitions tab.
- **8.** After making similar changes to all desired partitions of the table, click **Apply**.

A.6 Specifying IM Column Store Details During Tablespace Creation

You can specify IM column store details when creating a tablespace.

- 1. From the **Administration** menu, choose **Storage**, and then select **Tablespaces**.
- **2.** Click **Create** to create a tablespace.
- **3.** Enter the details that appear on the General tab.
- **4.** Click the **In-Memory Column Store** tab.
- **5.** Enter all required IM column store details for the tablespace.
- **6.** Click **Show SQL**.
- **7.** In the Show SQL page, click **Return**.

Another page appears.

- 8. Click OK.
- **9.** Click **OK** to create the tablespace.

The IM column store settings of a tablespace apply for any new table created in the tablespace. IM column store configuration details must be specified at the individual table level if a table must override the configuration of the tablespace.

A.7 Viewing and Editing IM Column Store Details of a Tablespace

You can view or edit IM column store details of a tablespace.

- **1.** From the **Administration** menu, choose **Storage**, then select the **Tablespaces** option.
- **2.** Search for the desired tablespace, select it, then click **View**.
- 3. Click **Edit** to launch the Edit Tablespace page, then click the **In-Memory Column** Store tab.
- 4. Edit the required details and click Apply.

A.8 Specifying IM Column Store Details During Materialized View Creation

You can specify IM column store details when creating a materialized view.

- From the Schema menu, choose Materialized Views, then select the Materialized Views option.
- 2. Click Create to create a materialized view.
- 3. Enter the materialized view name, and specify its query.
- Click the In-Memory Column Store tab to specify IM column store options for the materialized view.
- **5.** After entering all necessary IM column store details, click **Show SQL**. Click **Return** from the Show SQL page, and then in the resulting page click **OK**.
- **6.** Click **OK** to create the materialized view.

A.9 Viewing or Editing IM Column Store Details of a Materialized View

You can view or edit IM column store details of a materialized view.

- From the Schema menu, choose Materialized Views, then select the Materialized Views option.
- **2.** Search for the desired materialized view, and click **View** to view its details.
- 3. Click **Edit** to launch the Edit Materialized View page.
- **4.** Click the **In-Memory Column Store** tab to specify IM column store options for the materialized view.
- **5.** Edit the required details, and click **Apply**.

Glossary

ADO policy

A policy that specifies a rule and condition for Automatic Data Optimization (ADO). For example, an ADO policy may specify that an object is marked NOINMEMORY (action) 30 days after creation (condition). Specify ADO policies using the ILM clause of CREATE TABLE and ALTER TABLE statements.

Automatic Data Optimization (ADO)

A technology that creates policies, and automates actions based on those policies, to implement an Information Lifecycle Management (ILM) strategy.

availability

The degree to which an application, service, or function is accessible on demand.

Bloom filter

A low-memory data structure that tests membership in a set. The database uses Bloom filters to improve the performance of hash joins.

Column Compression Unit (CU)

Contiguous storage for a column in an In-Memory Compression Unit (IMCU).

columnar data pool

The subpool in the In-Memory Area that stores columnar data. It is also known as the 1 MB pool.

columnar format

The column-based format for objects that reside in the In-Memory Column Store. The columnar format contrasts with the row format used in data blocks.

common dictionary

A segment-level, instance-specific set of master dictionary codes, created from local dictionaries. A local dictionary is a sorted list of dictionary codes specific to a Column Compression Unit (CU). A join group uses a common dictionary to optimize joins.

compression tiering

The application of different levels of compression to data based on its access pattern. For example, administrators may compress inactive data at a higher rate of compression at the cost of slower access.

data flow operator (DFO)

The unit of work between data redistribution stages in a parallel query.

dense grouping key

A key that represents all grouping keys whose grouping columns come from a particular fact table or dimension.

dense join key

A key that represents all join keys whose join columns come from a particular fact table or dimension.

dense key

A numeric key that is stored as a native integer and has a range of values.

double buffering

A repopulation mechanism in which background processes create new In-Memory Compression Unit (IMCU) versions by combining the original rows with the latest modified rows. During repopulation, the stale IMCUs remain accessible for queries.

expression

A combination of one or more values, operators, and SQL functions that resolves to a value.

Expression Statistics Store (ESS)

A repository maintained by the optimizer to store statistics about expression evaluation. For each segment, the ESS monitors statistics such as frequency of execution, cost of evaluation, timestamp evaluation, and so on. The ESS is persistent in nature and also has an SGA representation for fast lookup of expressions.

FastStart area

A designated tablespace to which the database periodically writes In-Memory columnar data.

Heat Map

Heat Map shows the popularity of data blocks and rows. Automatic Data Optimization (ADO) to decide which segments are candidates for movement to a different storage tier.

home location

The database instance in which an IMCU resides. When auto DOP is enabled on Oracle RAC, the parallel query coordinator uses home location to determine where each IMCU is located, how large it is, and so on.

IM aggregation

An optimization that accelerates aggregation for queries that join from a single large table to multiple small tables. The transformation uses KEY VECTOR and VECTOR GROUP BY operators, which is why it is also known as VECTOR GROUP BY aggregation.

IM column store

An optional SGA area that stores copies of tables and partitions in a columnar format optimized for rapid scans.

IM expression

A SQL expression whose results are stored in the In-Memory Column Store. If last_name is a column stored in the IM column store, then an IM expression might be UPPER(last_name).

IMCU mirroring

In Oracle RAC, the duplication of an IMCU in multiple IM column stores. For example, the IM column stores on instance 1 and instance 2 are populated with the same sales table.

IMCU pruning

In a query of the In-Memory Column Store, the elimination of IMCUs based on the high and low values in each IMCU. For example, if a statements filters product IDs greater than 100, then the database avoids scanning IMCUs that contain values less than 100.

IM storage index

A data structure in an IMCU header that stores the minimum and maximum for all columns within the IMCU.

In-Memory Advisor

A downloadable PL/SQL package that analyzes the analytical processing workload in your database. This advisor recommends a size for the IM column store and a list of objects that would benefit from In-Memory population.

In-Memory Aggregation

See IM aggregation.

In-Memory Area

An optional SGA component that contains the IM column store.

In-Memory Column Store

See IM column store.

In-Memory Compression Unit (IMCU)

A storage unit in the In-Memory Column Store that is optimized for faster scans. The In-Memory Column Store stores each column in table separately and compresses it. Each IMCU contains all columns for a subset of rows in a specific table segment.

A one-to-many mapping exists between an IMCU and a set of database blocks. For example, if a table contains columns c1 and c2, and if its rows are stored in 100 database blocks on disk, then IMCU 1 might store the values for both columns for blocks 1-50, and IMCU 2 might store the values for both columns for blocks 51-100.

In-Memory Coordinator Process (IMCO)

A background process whose primary task is to initiate background population and repopulation of columnar data.

In-Memory Expression

See IM expression.

In-Memory Expression Unit (IMEU)

A container that stores the computed result of an In-Memory Expression (IM expression). Each IMEU resides in its own In-Memory Compression Unit (IMCU).

In-Memory FastStart

A feature that significantly reduces the time to populate data into the IM column store when a database instance restarts.

In-Memory population

See population.

In-Memory virtual column

A virtual column that is eligible to be populated in the In-Memory Column Store.

Information Lifecycle Management (ILM)

A set of processes and policies for managing data throughout its useful life.

join group

A user-defined object that specifies the columns that join two or more tables in a query. Join groups are only supported when INMEMORY_SIZE is a nonzero value.

key vector

A data structure that maps between dense join keys and dense grouping keys.

local dictionary

A sorted list of dictionary codes specific to a Column Compression Unit (CU).

metadata pool

A subpool of the In-Memory Area that stores metadata about the objects that reside in the IM column store. The metadata pool is also known as the *64 KB pool*.

on-demand population

When INMEMORY PRIORITY is set to NONE, the IM column store *only* populates the object when it is accessed through a full scan. If the object is never accessed, or if it is accessed only through an index scan or fetch by rowid, then it is never populated.

OZIP

A proprietary compression technique that offers extremely fast decompression. OZIP is tuned specifically for Oracle Database.

partition exchange load

A technique in which you create a table, load data into it, and then exchange an existing table partition with the table. This exchange process is a DDL operation with no actual data movement.

population

The operation of reading existing data blocks from data files, transforming the rows into columnar format, and then writing the columnar data to the IM column store. In contrast, *loading* refers to bringing new data into the database using DML or DDL.

priority-based population

When PRIORITY is set to a value other than NONE, Oracle Database adds the object to a prioritized population queue. The database populates objects based on their queue position, from CRITICAL to LOW. It is "priority-based" because the IM column store automatically populates objects using the prioritized list whenever the database reopens. Unlike in on-demand population, objects do not require a full scan to be populated.

repopulation

The automatic refresh of a currently populated In-Memory Compression Unit (IMCU) after its data has been significantly modified. In contrast, population is the initial creation of IMCUs in the IM column store.

service

The logical representation of an application workload that shares common attributes, performance thresholds, and priorities. A single service can be associated with one or more instances of an Oracle RAC database, and a single instance can support multiple services.

Snapshot Metadata Unit (SMU)

A storage unit in the In-Memory Area that contains metadata and transactional information for an associated In-Memory Compression Unit (IMCU).

Space Management Worker Process (W*nnn*)

A process that populates or repopulates data in the IM column store on behalf of In-Memory Coordinator Process (IMCO).

staleness threshold

An internally set percentage of entries in the transaction journal for an IMCU that initiates repopulation.

storage tiering

The deployment of data on different tiers of storage depending on its level of access. For example, administrators migrate inactive data from high-performance, high-cost storage to low-cost storage.

threshold-based repopulation

The automatic repopulation of an IMCU when the number of stale entries in an IMCU reaches an internal staleness threshold.

transaction journal

Metadata in a Snapshot Metadata Unit (SMU) that keeps the IM column store transactionally consistent.

trickle repopulation

A supplement to threshold-based repopulation. The In-Memory Coordinator Process (IMCO) may instigate trickle repopulation automatically for any IMCU in the IM column store that has stale entries but does not meet the staleness threshold.

vector aggregation

See IM aggregation.

virtual column

A column that is not stored on disk. The database derives the values in virtual columns on demand by computing a set of expressions or functions.

Index

A	compression
Active Data Guard about, 11-1 how IM column store works, 11-4 purpose, 11-1, 11-2	affect on repopulation, <i>8-9</i> Hybrid Columnar Compression, <i>2-11</i> In-Memory Column Store, <i>2-11</i> methods, <i>4-9</i> conventional DML, <i>8-2</i>
Active Session History (ASH), 1-13 advisors	CPU architecture
In-Memory Advisor, 1-13	SIMD vector processing, 1-6, 7-2
Oracle Compression Advisor, 1-14, 3-2	CPU_COUNT initialization parameter, 4-5
ALL_HEAT_MAP_SEGMENT view, 4-29	CREATE MATERIALIZED VIEW statement, 4-6, 4-24 CREATE TABLE AS SELECT statement, 8-4
ALL_JSON_COLUMNS view, 5-4	CREATE TABLE AS SELECT statement, 8-4 CREATE TABLE statement, 4-6, 4-9
ALTER MATERIALIZED VIEW statement, 4-6, 4-24	CREATE TABLES statement, 4-6 CREATE TABLESPACE statement, 4-6
ALTER TABLE statement, 2-8, 4-6, 4-9, 4-12	CUs
ALTER TABLESPACE statement, 4-6	See Column Compression Units (CUs)
analytic indexes, 1-8	1
analytic queries, 1-1, 1-3, 1-6, 1-8	D
Auto DOP, 10-13	
Automatic Data Optimization (ADO)	data flow operator (DFO), $7-4$
Heat Map, 4-29	data loading, into IM column store, 8-2
how policies work, 4-29	database buffer cache, 2-5
In-Memory Column Store, 4-32	Database In-Memory
policies, 4-26	about, 1-3
purpose, 4-27	introduction, 1-1
user interface, 4-30	principal tasks, 1-11
	tools for, 1-12
В	database instances
	multiple IM column stores, 10-2
Bloom filters, 1-8, 6-1, 7-2, 7-5	DBA_EXPRESSION_STATISTICS view, 13-1
	DBA_FEATURE_USAGE_STATISTICS view, 13-1
C	DBA_HEAT_MAP_SEGMENT view, 4-26, 13-1
	DBA_ILMDATAMOVEMENTPOLICIES view, 13-1
Column Compression Units (CUs)	DBA_IM_EXPRESSIONS view, 5-1, 13-1
FastStart area, 9-3	DBA_JOINGROUPS view, 13-1
local dictionary, 2-12	DBA_TABLES view, 4-6, 10-5, 13-1
row modifications, 8-2	DBMS_COMPRESSION PL/SQL package, 3-2, 4-11
columnar data pool, 2-4	DBMS_HEATMAP PL/SQL package, 4-30
columnar format	DBMS_ILM PL/SQL package, 4-30, 4-32
benefits, 1-6	DBMS_ILM_ADMIN PL/SQL package, 4-30
single-format approach, 1-2	DBMS_INMEMORY package, 5-1, 5-10, 5-14
common dictionaries, 6-4	DBMS_INMEMORY PL/SQL package, 8-10
COMPATIBLE initialization parameter, 3-3, 4-17, 4-18, 4-30	DBMS_INMEMORY_ADMIN package, 5-1, 5-5, 5-10-5-12, 5-14, 9-2, 9-8

DBMS_INMEMORY_ADMIN PL/SQL package, 9-9	
DBMS_INMEMORY.REPOPULATE procedure, 8-7	1
DBMS_SQLTUNE PL/SQL package, 6-10	<u>-</u>
dense keys	ILM clause of ALTER TABLE, 4-32
dense grouping keys, 7-4, 7-6	IM column store
dense join keys, 7-6	See In-Memory Column Store
dictionaries	IM expressions
common, 6-4	administering, 5-10
local, 2-13	basic tasks, 5-11
direct path loads	benefits, 5-3
into IM column store, 8-4	capturing, <i>5-5</i> , <i>5-12</i>
DISTRIBUTE clause of CREATE TABLE, 10-5–10-8	configuring, 5-11
DISTRIBUTE FOR SERVICE subclause of CREATE	dropping, 5-14
TABLE, 10-16, 11-5	Expression Statistics Store (ESS), 5-6
DML	JSON columns, 5-9
conventional, 8-2	JSON optimizations, 5-4
direct path loads, 8-4	materialized views, 5-3
double buffering, 8-3	modes of operation, 5-9
staleness threshold, 8-3	overview, 2-17, 5-1
double buffering, 8-3, 8-9	
DUPLICATE clause of CREATE TABLE, 10-5, 10-9,	populating, 5-12
10-11, 10-14, 10-17	population, 5-7
	storage in IMEUs, 5-8
duplication, Oracle RAC, 10-9, 10-11, 10-12	user interfaces, 5-9
	virtual columns, 5-4
E	IM expressions (IMEs)
	Expression Statistics Store (ESS), 2-18
Enterprise Manager Cloud Control (Cloud Control),	IM FastStart
1-13	See In-Memory FastStart
Expression Statistics Store (ESS), 2-7, 2-18, 5-6	IM storage indexes, 2-14
expressions, In-Memory, 2-17, 5-1, 5-9	IMCO
	See In-Memory Coordinator Process (IMCO)
F	IMCU
	See In-Memory Compression Units (IMCUs)
FastStart area	IME_CAPTURE_EXPRESSIONS procedure, 5-7, 5-10,
disabling, 9-9	5-12
migrating, 9-8	IME_DROP_ALL_EXPRESSIONS procedure, 5-5,
FASTSTART_DISABLE procedure, 9-9	5-10, 5-14
FASTSTART_ENABLE procedure, 9-2, 9-5	IME_DROP_EXPRESSIONS procedure, 5-5, 5-10, 5-14
FASTSTART_MIGRATE_STORAGE procedure, 9-8	IME_POPULATE_EXPRESSIONS procedure, 5-10
FOR SERVICE subclause of CREATE TABLE, 10-18	IMEUs
	See In-Memory Expression Units (IMEUs)
^	In-Memory Advisor, 1-13
G	In-Memory Aggregation
granules, 2-11	about, 7-1
5 minutes, 2 11	controls, 7-14
•	how it works, 7-4
H	phases, 7-7
Heat Map, 4-27, 4-29	purpose, 7-2
HEAT_MAP initialization parameter, 4-30	scenario, 7-8
	when it occurs, 7-5
High Availability	In-Memory Area
benefits of the DUPLICATE ALL clause, 10-11	columnar data pool, 2-4
benefits of the NO DUPLICATE clause, 10-12	estimating size, 3-2
IM column store, 1	metadata pool, 2-4
hints	setting size, 3-3
VECTOR_TRANSFORM_DIMS, 7-14	size, 2-2
VECTOR_TRANSFORM_FACT, 7-14	
Hybrid Columnar Compression, 2-11	Snapshot Metadata Units (SMUs), 2-16

In-Memory Column Store	In-Memory Compression Units (IMCUs) (continued)
about, 1-1	mirroring, 10-9, 10-11, 10-12
Active Data Guard, 11-1-11-3	relationship to IMEUs, 5-8
advantages, 1-3	row subsets, 2-11
and Oracle RAC, 10-1	schema objects and, 2-8
architecture, 2-7	Snapshot Metadata Units (SMUs), 2-16
Automatic Data Optimization, 4-32	transaction journals, 2-16
benefits, 1-10	In-Memory Coordinator Process (IMCO), 2-19, 5-7,
columnar format, 2-1	8-7
compression, 2-11, 4-9	In-Memory data affinity
compression units, 1-6, 2-8	Oracle RAC, 10-12
consistency with buffer cache, 2-5	In-Memory Expression Units (IMEUs), 2-17, 5-7, 5-8
disabling, 3-5	In-Memory Expressions
disabling tables, 4-12	See IM expressions In-Memory FastStart
dual memory formats, 2-1, 2-5	disabling, 9-9
enabling existing tables, 4-12	enabling, 9-5
enabling for a database, 3-3	FastStart area, 9-2, 9-3, 9-5
enabling for materialized views, 4-24	managing, 9-1
enabling for tablespaces, 4-23	9 9
enabling new tables, 4-12	migrating tablespace, 9-8
estimating size, 3-2	Oracle RAC, 10-14
FastStart tablespace, 9-2	purpose, 9-2
High Availability, 1	retrieving tablespace name, 9-7 See also IM FastStart
IM expressions, 2-17, 5-1, 5-3, 5-5, 5-9	In-Memory process architecture
IM FastStart	In-Memory Coordinator Process (IMCO), 2-19
about, 9-1	Space Management Worker Processes (Wnnn),
IM storage indexes, 2-14	2-20
In-Memory Advisor, 1-13	In-Memory virtual columns
In-Memory Area, 1-3, 2-2, 3-1, 4-18	enabling, 4-18
increasing dynamically, 3-4	indexes, analytic, 1-8
initialization parameters, 12-1	INMEMORY clause of ALTER TABLE, 4-12, 11-2,
join groups, 6-2	11-3
JSON optimizations, 5-4	INMEMORY clause of CREATE TABLE, 4-12
Oracle Data Pump, 1-14	INMEMORY clause of CREATE TABLESPACE, 4-23
Oracle Enterprise Manager Cloud Control, A-1	INMEMORY CLAUSE_DEFAULT initialization
Oracle RAC, 10-1, 10-5–10-9, 10-11, 10-12	parameter, 12-1
overview, 10-1	INMEMORY_EXPRESSIONS_USAGE initialization
performance benefits, 1-6	parameter, 5-4, 5-7, 5-9, 5-11, 12-1
population, 4-1, 4-2, 4-5	INMEMORY_FORCE initialization parameter, 12-1
population of columnar data, 4-2	INMEMORY_MAX_POPULATE_SERVERS
population of data at startup, 9-2	initialization parameter, 4-5, 8-7, 8-10, 12-1
prioritization of data population, 4-2, 4-8, 9-5	INMEMORY_QUERY initialization parameter, 12-1
priority options, 4-8, 9-5	INMEMORY_SIZE initialization parameter, 1-10, 2-2,
repopulation, 8-1, 8-4	3-1, 3-3-3-5, 4-30, 4-32, 5-9, 5-11, 7-1, 10-18,
SIMD vector processing, 2-21, 7-2	11-2, 11-3, 12-1
storage units, 2-7	INMEMORY_TRICKLE_POPULATE_SERVERS_PERC
trickle repopulation, 8-7	ENT initialization parameter, 12-1
VECTOR GROUP BY, 7-2, 7-4	INMEMORY_TRICKLE_REPOPULATE_SERVERS_PE
vector joins, 6-1	RCENT initialization parameter, $8-7$,
virtual columns, 4-17, 5-5	8-9-8-11
In-Memory Compression Units (IMCUs)	INMEMORY_VIRTUAL_COLUMNS initialization
Column Compression Units (CUs), 2-12	parameter, 4-17, 4-18, 5-7, 12-1
common dictionaries, 6-4	1 , , , , , , , , , , , , , , , , , , ,
double buffering, 8-3	1
FastStart area, 9-3	J
In Momerty Expression Units (IMEUs) 2-17	ioin groups

join groups (continued)	Oracle RAC (continued)
benefits, 6-2	distribution of subpartitions, 10-7
common dictionaries, 6-4	duplication, 10-9, 10-11, 10-12
creating, 6-7	IM column store, 10-1
how they work, 6-4	IM FastStart, 10-14
In-Memory Column Store, 6-2	In-Memory data affinity, 10-12
monitoring, 6-10	serial queries, 10-13
scan optimization, 6-5	services, 10-15-10-17, 11-5
joins	shared-nothing architecture, 10-2
Bloom filters, 1-8, 6-1, 7-5	Oracle Real Application Clusters (Oracle RAC), 1-9
join groups, 6-2	See also Oracle RAC
star queries, 6-1, 10-11	
JSON	Р
IM expressions infrastructure, 5-4	<u> </u>
	parallel queries
K	Oracle RAC, 10-12
	PARALLEL_DEGREE_LIMIT initialization
key vectors, 7-6	parameter, 10-13
•	PARALLEL_DEGREE_POLICY initialization
1	parameter, 10-13
<u> </u>	PARALLEL_INSTANCE_GROUP initialization
local dictionaries, 2-12, 2-13	parameter, 10-15, 10-16, 11-5
	PARALLEL_MIN_TIME_THRESHOLD initialization
M	parameter, 10-13
M	partition exchange loads, 8-5
materialized views	partitioned tables
IM expressions, 5-3	distributing in Oracle RAC, 10-5-10-7
In-Memory Column Store, 4-24	repopulating, 8-5
MEMCOMPRESS clause of CREATE TABLE, 4-9, 4-19	policies, ADO, 4-26, 4-29
metadata pool	population, In-Memory
Snapshot Metadata Units (SMUs), 2-16	forcing, 4-24
1 "	purpose, 4-2
M	primary databases, Active Data Guard, 11-1-11-3
N	prioritization
NO DUPLICATE clause of CREATE TABLE, 10-12	of In-Memory population, 9-5
,	prioritization, of In-Memory population, $4-2$, $4-8$
^	PRIORITY clause of CREATE TABLE, 4-8, 9-5
0	
optimizer	Q
ESS statistics, 5-6	-
OPTIMIZER_INMEMORY_AWARE initialization	queries, analytic, 1-1, 1-3, 1-6, 1-8
parameter, 12-1	query transformations
Oracle Compression Advisor, 3-2, 4-11	In-Memory Aggregation, 7-1
Oracle Data Guard, 1-9	
Oracle Data Pump	R
In-Memory Column Store, 1-14	
Oracle Database In-Memory	REPOPULATE procedure, 8-10
See Database In-Memory	repopulation
Oracle Engineered Systems, 10-9, 10-11	controlling, 8-10
Oracle Enterprise Manager Cloud Control	data loading, 8-2
In-Memory Column Store, A-1	definition, 8-1
Oracle RAC	direct path loads, 8-4
Auto DOP, 10-13	double buffering, 8-3, 8-9
deploying IM column stores, 10-1	factors affecting, 8-9
distribution and duplication of data, 10-5	IMEUs, 5-8
distribution by rowid, 10-8	partition exchange load, 8-5
distribution of partitions, 10-5, 10-6	staleness threshold, 8-3

repopulation (continued) threshold-based, 8-3, 8-7 trickle, 8-3, 8-7 tutorial, 8-11 when it occurs, 8-7 REPORT_SQL_MONITOR_XML function, 6-10 row format, 2-1 rowids distributing by in Oracle RAC, 10-8	tables (continued) tablespaces In-Memory Column Store, 4-23 threshold-based repopulation, 8-3, 8-7 transaction journals, 2-16, 8-1-8-3, 8-7 transformations VECTOR GROUP BY, 1-8, 7-2 trickle repopulation factors affecting repopulation, 8-9
S	V
SecureFiles LOB, 9-3 SecureFiles LOBs, 9-2 services, Oracle RAC, 10-15-10-18, 11-5 SGA (system global area) In-Memory Area, 1-3, 2-2, 3-1, 4-18 In-Memory Column Store, 2-1 SGA_TARGET initialization parameter, 2-2 SIMD vector processing, 1-6, 2-21, 4-18, 7-2 SMUs See Snapshot Metadata Units (SMUs) Snapshot Metadata Units (SMUs) In-Memory Compression Units (IMCUs), 2-16 transaction journals, 2-16 Space Management Slave Processes (Wnnn), 10-5, 10-7 Space Management Worker Processes (Wnnn), 2-20, 4-5, 5-7, 8-7, 8-11, 9-2, 9-3 SRVCTL, 10-18 standby databases, Active Data Guard, 11-1-11-3 star queries, 6-1, 7-9, 10-11, 10-12 storage mirroring, 10-9 subpartitioned tables, 10-7 SYS_IME virtual columns, 5-5, 5-12 SYSAUX tablespace, 9-3	V\$HEAT_MAP_SEGMENT view, 13-1 V\$IM_COLUMN_LEVEL view, 4-19, 13-1 V\$IM_SEGMENTS view estimating memory, 3-2 V\$INMEMORY_AREA initialization parameter, 2-4 V\$INMEMORY_AREA view, 2-2, 13-1 V\$INMEMORY_FASTSTART_AREA view, 9-7 V\$SESSION view, 6-10 V\$SGA view, 2-2, 13-1 vector aggregation See In-Memory Aggregation VECTOR GROUP BY aggregation IM column store, 7-4 scenarios, 7-3 VECTOR GROUP BY transformations, 1-8 vector joins In-Memory Column Store, 6-1 vector processing, SIMD, 2-21, 4-18 VECTOR_TRANSFORM_DIMS hint, 7-14 VECTOR_TRANSFORM_FACT hint, 7-14 virtual columns hidden, 5-5, 5-6 IM expressions infrastructure, 5-4 IMEU storage, 5-8 virtual columns, In-Memory, 4-17
<u> </u>	, , , , , , , , , , , , , , , , , , , ,
TABLE ACCESS IN MEMORY FULL operation, 2-5 tables In-Memory Column Store, 4-12	Wnnn processes See Space Management Worker Processes (Wnnn)