Bahria University, Islamabad

Department of Software Engineering

Software Quality Engineering (Spring-2026)

Instructor: Engr. Tamim Khan

Student: Waleed Ahmed Razzaqi and Amir Ali

Enrollment: 01-131232-093 and 01-131232-011

Link: https://ai-project-2026.atlassian.net/jira/software/projects/SQE/boards/34?atlOrigin=eyJpIjoiOGQ1MjhkYTc4ODhjNDVmZTk2MTc3NWM2MjA4MzZiODkiLCJwIjoiaiJ9

Assignment: 03

Date: 5/9/26

Task No:	Task Wise Marks		Documentation Mrks		Total Marks (20)
	Assigned	Obtained	Assigned	Obtained	
1					
2					
3					
4					
5					

Comments:

Signature

1. Document Overview

This document presents the Assignment 3 UI testing plan for the 3D-DET CMS module. The assigned scope is US-01 to US-09, covering company hierarchy creation, building/floor/room/table management, job and function UI, process/task UI, task-job linking, and hierarchy tree view. The test cases are prepared for Jira AIO and are marked Not Executed because execution, pass/fail recording, bug reporting, and AIO execution report generation belong to Assignment 4.

2. Scope of UI Testing

2.1 In Scope

- CMS form visibility, labels, required fields, validation messages, button states, and layout consistency.
- User Stories US-01 to US-09: Company, Building, Floor, Room, Table, Job assignment, Job/Function, Process/Task, Task-Job link, and Tree View.
- Manual UI testing on Chrome and Firefox.
- Browser layout checks using normal desktop screen and responsive browser DevTools where required.
- Jira AIO test case preparation with pre-conditions, numbered steps, expected results, priority, tester, and planned evidence name.

2.2 Out of Scope


- Actual execution of test cases, pass/fail results, bug tickets, and screenshots as evidence. These are for Assignment 4.
- Load testing, stress testing, security testing, backend API performance testing, and database-level verification.
- Unity 3D performance testing. Only UI reflection of job-table assignment is planned where applicable.

3. Jira and AIO Setup Summary


Jira Project	[Paste final shared Jira project name/link here]
AIO Tests	Installed/enabled in final project
Instructor Access	huzaifaahmed90000@gmail.com invited to final project for verification
AIO Folder Structure	US-01 to US-09 folders created inside AIO Cases
Test Case Count	90 UI test cases planned: 45 acceptance criteria x 2 test cases
Execution Status	Not Executed for Assignment 3


3.1 Screenshot Placeholders for Jira Setup


Jira project dashboard / project home page




Instructor invitation / project access page







Test Cycles



4. UI Testing Strategy

Testing Approach	Manual UI testing using black-box test design
Primary UI Focus	Element visibility, form validation, button state, list/hierarchy display, layout consistency, and navigation behavior
Design Basis	User Story acceptance criteria from US-01 to US-09
Test Design Techniques	Positive testing, negative/validation testing, boundary-style UI checks, compatibility checks, and state-transition checks for expand/collapse or link/unlink flows
Browsers	Chrome and Firefox minimum
Evidence Plan	Screenshots will be captured during Assignment 4 execution; placeholders are provided in this Word file for later insertion

5. Browser Compatibility Matrix

Browser	Operating System	Viewport/Screen	Purpose	Assignment 3 Status
Google Chrome	Windows	1920 x 1080	Primary CMS UI test planning and execution browser	Planned


Mozilla Firefox	Windows	1920 x 1080	Cross-browser compatibility verification	Planned
Chrome DevTools	Responsive Mode	1366 x 768 / 768 x 1024	Layout and responsiveness check for forms and tree view	Planned

6. UI Checklist

Checklist Area	UI Checks	Covered User Stories	Planned Evidence
Navigation and Entry Points	Menu/dashboard links are visible, clickable, and readable.	US-01 to US-09	Navigation screenshot
Forms and Field Labels	Required form fields are present, clearly labeled, and aligned.	US-01 to US-08	Form screenshots
Validation Messages	Blank, duplicate, invalid, or missing input shows clear messages near the field.	US-01 to US-08	Validation screenshots
Button States	Save, Create, Edit, Assign, Unassign, Cancel, Expand, and Collapse buttons are visible and usable.	US-01 to US-09	Action screenshots
Hierarchy Placement	Saved entities appear under the correct company, building, floor, room, table, job, process, or task view.	US-01 to US-09	Hierarchy screenshots
Layout Consistency	Pages do not show broken alignment, overlap, hidden buttons, or unreadable text in Chrome/Firefox.	US-01 to US-09	Browser comparison screenshot
Tree Interaction	Tree nodes expand/collapse, show correct levels, and selected node opens correct detail.	US-09	Tree view screenshots


7. Screenshot

Folder Structure




US 1 TO 9 Few Screen Shots


US 1




US 2



US 3



US-09 test case list in AIO



Key	Version	Title	Owner
SQE-TC-78	1	TC-UI-US09-AC05-01] Verify newly created company is available in hierarchy company selection	WA
SQE-TC-70	1	[TC-UI-US09-AC01-02] Verify company search dropdown is available in Hierarchical View	WA
SQE-TC-71	1	[TC-UI-US09-AC02-01] Verify existing companies are available for hierarchy selection	WA
SQE-TC-72	1	[TC-UI-US09-AC02-02] Verify selected company displays hierarchy response area	WA
SQE-TC-73	1	[TC-UI-US09-AC03-01] Verify hierarchy tree nodes are not displayed when no functions exist	WA
SQE-TC-74	1	[TC-UI-US09-AC03-02] Verify expand and collapse controls are unavailable when tree is empty	WA
SQE-TC-75	1	[TC-UI-US09-AC04-01] Verify no node detail opens when hierarchy nodes are unavailable	WA
SQE-TC-81	1	[TC-UI-US09-AC05-02] Verify hierarchy view updates after selecting available company	WA

8. Test Case Design Rationale

- Each acceptance criterion is converted into two UI test cases: one positive/happy-path case and one negative, validation, compatibility, or layout-focused case.
- Positive cases verify that the UI allows valid actions such as creating a company, adding a building, assigning a job, or opening the tree view.
- Negative and validation cases verify missing fields, spaces-only values, duplicate values, disabled buttons, cancellation behavior, and incorrect hierarchy placement.
- Compatibility cases verify that important UI actions remain accessible on Chrome and Firefox and that the layout does not break under common viewport conditions.
- State-transition cases are used where UI state changes matter, such as assign/unassign, link/unlink, expand/collapse, and detail panel switching.

8.1 Test Case Count Summary

User Story	Acceptance Criteria	Cases per AC	Total Cases
US-01 - Create a Company	5	2	10
US-02 - Add a Building to a Company	5	2	10
US-03 - Add a Floor to a Building	5	2	10
US-04 - Place a Table on a Floor Inside a Room	5	2	10
US-05 - Assign a Job to a Table	5	2	10
US-06 - Add a Job and a Function	5	2	10
US-07 - Add a Process and Link Tasks to It	5	2	10
US-08 - Link Tasks and Jobs to Each Other	5	2	10

US-09 - View Company Hierarchy in Tree Form	5	2	10
Total	45	2	90

9. Full Test Suite Table

All test cases below are planned in Jira AIO and remain Not Executed for Assignment 3. Actual result, pass/fail status, screenshots, and bug tickets will be completed during Assignment 4.

US-01 - Create a Company

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US01-AC01-01	AC01: A 'Create Company' option is accessible from the CMS dashboard or navigation	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open the CMS dashboard. 2. Locate the navigation menu or dashboard action area. 3. Verify that 'Create Company' option is visible and clickable.	Browser: Chrome	The 'Create Company' option is visible, readable, and clickable from the dashboard or navigation.	High	M1/M2	Not Executed	SS_TC-UI-US01-AC01-01.png
TC-UI-US01-AC01-02	AC01: A 'Create Company' option is accessible from the CMS dashboard or navigation	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the CMS dashboard in Firefox. 2. Reduce browser width to 1366 x 768 using DevTools. 3. Verify that 'Create Company' option remains accessible without overlap.	Browser: Firefox, viewport: 1366 x 768	The option remains accessible and does not disappear, overlap, or become unreadable in the tested layout.	High	M1/M2	Not Executed	SS_TC-UI-US01-AC01-02.png
TC-UI-US01-AC02-01	AC02: The form includes at minimum: Company Name and any required fields	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Create Company'. 2. Inspect all visible fields on the form. 3. Confirm that 'Company Name' field is present.	Company form	Create Company form displays Company Name and any other required fields clearly.	Medium	M1/M2	Not Executed	SS_TC-UI-US01-AC02-01.png
TC-UI-US01-AC02-02	AC02: The form includes at minimum: Company Name and any required fields	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Click 'Create Company'. 2. Check required field indicators. 3. Verify required fields are marked or made clear before submission.	Required field indicator check	Required fields are visually identifiable and understandable to the user.	Medium	M1/M2	Not Executed	SS_TC-UI-US01-AC02-02.png
TC-UI-US01-AC03-01	AC03: Submitting valid data creates the company and it appears in the company list	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Create Company'. 2. Enter Company Name. 3. Click 'Save' or 'Create'.	Company Name: UI Test Company A3	Company is saved successfully and appears in the company list.	High	M1/M2	Not Executed	SS_TC-UI-US01-AC03-01.png
TC-UI-US01-AC03-02	AC03: Submitting valid data creates the company and it appears in the company list	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Create a company using valid data. 2. Observe the company list immediately after save.	Company Name: UI Test Company A3 List Check	The newly created company appears in the list immediately after successful save.	Medium	M1/M2	Not Executed	SS_TC-UI-US01-AC03-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
				3. Check that the created record is displayed without manual refresh.						
TC-UI-US01-AC04-01	AC04: Submitting with missing required fields shows a validation error	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Create Company'. 2. Leave Company Name blank. 3. Click 'Save' or 'Create'.	Company Name: blank	A required-field validation message is shown and the company is not created.	High	M1/M2	Not Executed	SS_TC-UI-US01-AC04-01.png
TC-UI-US01-AC04-02	AC04: Submitting with missing required fields shows a validation error	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Click 'Create Company'. 2. Enter only spaces in Company Name. 3. Click 'Save' or 'Create'.	Company Name: spaces only	The system treats spaces as invalid input and shows an appropriate validation message.	High	M1/M2	Not Executed	SS_TC-UI-US01-AC04-02.png
TC-UI-US01-AC05-01	AC05: The newly created company can be opened/viewed immediately after creation	Positive UI	Admin is logged into the CMS with access to the required module.	1. Create a valid company. 2. Locate the company in the company list. 3. Click the created company row/name.	Company Name: UI Test Company A3	The created company opens successfully in detail/view mode.	Medium	M1/M2	Not Executed	SS_TC-UI-US01-AC05-01.png
TC-UI-US01-AC05-02	AC05: The newly created company can be opened/viewed immediately after creation	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the created company detail view. 2. Compare displayed company name with submitted value. 3. Check that the view is readable and correctly aligned.	Expected displayed name: UI Test Company A3	Company detail view displays the correct company name and relevant information clearly.	Medium	M1/M2	Not Executed	SS_TC-UI-US01-AC05-02.png

US-02 - Add a Building to a Company

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US02-AC06-01	AC06: Admin can navigate into a Company and find an option to add a Building	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing company from the company list. 2. Review the company detail/hierarchy area. 3. Verify that 'Add Building' or equivalent action is available.	Company: UI Test Company A3	Admin can access the Add Building option inside a company.	High	M1/M2	Not Executed	SS_TC-UI-US02-AC06-01.png
TC-UI-US02-AC06-02	AC06: Admin can navigate into a Company and find an option to add a Building	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the company page in Firefox. 2. Check the location of Add Building button. 3. Verify the button	Browser: Firefox	Add Building button is visible and accessible without layout break in Firefox.	Medium	M1/M2	Not Executed	SS_TC-UI-US02-AC06-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
				remains readable and accessible.						
TC-UI-US02-AC07-01	AC07: Building form includes at minimum a Building Name	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Add Building'. 2. Inspect the form fields. 3. Confirm that 'Building Name' field is displayed.	Building form	Building form contains a clearly labeled Building Name field.	Medium	M1/M2	Not Executed	SS_TC-UI-US02-AC07-01.png
TC-UI-US02-AC07-02	AC07: Building form includes at minimum a Building Name	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Click 'Add Building'. 2. Leave Building Name empty. 3. Click 'Save'.	Building Name: blank	The form shows validation for empty Building Name and does not save.	High	M1/M2	Not Executed	SS_TC-UI-US02-AC07-02.png
TC-UI-US02-AC08-01	AC08: Saved building appears under the correct Company in the hierarchy	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a company. 2. Click 'Add Building'. 3. Enter Building Name and save.	Building Name: Main Building A	Saved building appears under the selected company in the hierarchy.	High	M1/M2	Not Executed	SS_TC-UI-US02-AC08-01.png
TC-UI-US02-AC08-02	AC08: Saved building appears under the correct Company in the hierarchy	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Create a building under Company A. 2. Open another company if available. 3. Verify the building does not appear under the wrong company.	Company hierarchy verification	Building is shown only under the correct company.	Medium	M1/M2	Not Executed	SS_TC-UI-US02-AC08-02.png
TC-UI-US02-AC09-01	AC09: A company can have more than one building	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing company. 2. Add first building with valid name. 3. Add second building with a different valid name.	Building Names: Main Building A, Main Building B	Both buildings are saved and shown under the same company.	Medium	M1/M2	Not Executed	SS_TC-UI-US02-AC09-01.png
TC-UI-US02-AC09-02	AC09: A company can have more than one building	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the building list under a company. 2. Verify multiple building rows/cards display correctly. 3. Check that names are not visually overlapped or truncated unnecessarily.	Multiple building list UI	Multiple building entries are displayed clearly in the list/hierarchy.	Medium	M1/M2	Not Executed	SS_TC-UI-US02-AC09-02.png
TC-UI-US02-AC10-01	AC10: Entering duplicate or invalid data shows an appropriate error	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Add Building form. 2. Enter an existing Building Name for the same company. 3. Click Save.	Duplicate Building Name: Main Building A	System shows duplicate/invalid data warning or prevents duplicate entry according to UI rule.	High	M1/M2	Not Executed	SS_TC-UI-US02-AC10-01.png
TC-UI-US02-AC10-02	AC10: Entering duplicate or invalid	Negative/UI Validation	Admin is logged into the CMS with access	1. Open Add Building form. 2. Enter invalid	Building Name: blank or invalid symbols	Appropriate error message appears and	High	M1/M2	Not Executed	SS_TC-UI-US02-AC10-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
	data shows an appropriate error		to the required module.	characters or blank input. 3. Click Save.		invalid building is not created.				

US-03 - Add a Floor to a Building

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US03-AC11-01	AC11: Admin can navigate into a Building and find an option to add a Floor	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a company. 2. Open an existing building. 3. Verify that 'Add Floor' option is available.	Building: Main Building A	Admin can navigate into a building and access Add Floor action.	High	M1/M2	Not Executed	SS_TC-UI-US03-AC11-01.png
TC-UI-US03-AC11-02	AC11: Admin can navigate into a Building and find an option to add a Floor	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open building detail page in Firefox. 2. Verify Add Floor location and button state. 3. Check that no major layout issue hides the action.	Browser: Firefox	Add Floor option remains visible and accessible in Firefox layout.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC11-02.png
TC-UI-US03-AC12-01	AC12: Floor form includes at minimum a Floor Name or Number	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Add Floor'. 2. Inspect the form fields. 3. Verify Floor Name or Floor Number field is present.	Floor form	Floor form displays a Floor Name or Number input field clearly.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC12-01.png
TC-UI-US03-AC12-02	AC12: Floor form includes at minimum a Floor Name or Number	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Click 'Add Floor'. 2. Check required field marking for Floor Name/Number. 3. Verify label is understandable.	Required field indicator check	Required floor field is visually marked and properly labeled.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC12-02.png
TC-UI-US03-AC13-01	AC13: Saved floor appears under the correct Building	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a building. 2. Add a floor using valid data. 3. Save the floor.	Floor Name/Number: Floor 1	Saved floor appears under the correct building.	High	M1/M2	Not Executed	SS_TC-UI-US03-AC13-01.png
TC-UI-US03-AC13-02	AC13: Saved floor appears under the correct Building	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Create a floor under Building A. 2. Open another building if available. 3. Verify the floor does not appear under the wrong building.	Building hierarchy verification	Floor remains associated with the correct building only.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC13-02.png
TC-UI-US03-AC14-01	AC14: Multiple floors can be added to the same building	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing building. 2. Add Floor 1. 3. Add Floor 2.	Floor Names: Floor 1, Floor 2	Multiple floors are saved under the same building.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC14-01.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US03-AC14-02	AC14: Multiple floors can be added to the same building	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the floor list under a building. 2. Verify multiple floors are visible. 3. Check that floor rows/cards remain readable.	Multiple floor list UI	Multiple floor entries display clearly without UI overlap.	Medium	M1/M2	Not Executed	SS_TC-UI-US03-AC14-02.png
TC-UI-US03-AC15-01	AC15: Attempting to save an unnamed floor shows a validation error	Positive UI	Admin is logged into the CMS with access to the required module.	1. Click 'Add Floor'. 2. Leave Floor Name/Number empty. 3. Click Save.	Floor Name/Number: blank	Validation message appears and unnamed floor is not saved.	High	M1/M2	Not Executed	SS_TC-UI-US03-AC15-01.png
TC-UI-US03-AC15-02	AC15: Attempting to save an unnamed floor shows a validation error	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Click 'Add Floor'. 2. Enter spaces only in Floor Name/Number. 3. Click Save.	Floor Name/Number: spaces only	System rejects spaces-only floor input and shows an appropriate validation message.	High	M1/M2	Not Executed	SS_TC-UI-US03-AC15-02.png

US-04 - Place a Table on a Floor Inside a Room

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US04-AC16-01	AC16: Admin can add a Room to a Floor	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a company, building, and floor. 2. Click 'Add Room'. 3. Enter Room Name and save.	Room Name: Room A101	Room is created and displayed under the selected floor.	High	M1/M2	Not Executed	SS_TC-UI-US04-AC16-01.png
TC-UI-US04-AC16-02	AC16: Admin can add a Room to a Floor	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Add Room form. 2. Leave Room Name empty. 3. Click Save.	Room Name: blank	Empty Room Name shows validation and room is not saved.	High	M1/M2	Not Executed	SS_TC-UI-US04-AC16-02.png
TC-UI-US04-AC17-01	AC17: Admin can add a Table within a Room	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing room. 2. Click 'Add Table'. 3. Enter Table Name and save.	Table Name: Table A101-01	Table is created and displayed inside the selected room.	High	M1/M2	Not Executed	SS_TC-UI-US04-AC17-01.png
TC-UI-US04-AC17-02	AC17: Admin can add a Table within a Room	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Add Table form. 2. Leave Table Name empty. 3. Click Save.	Table Name: blank	Empty Table Name shows validation and table is not saved.	High	M1/M2	Not Executed	SS_TC-UI-US04-AC17-02.png
TC-UI-US04-AC18-01	AC18: Table is saved and appears under the correct Room > Floor > Building hierarchy	Positive UI	Admin is logged into the CMS with access to the required module.	1. Create or open a table inside a room. 2. View the hierarchy/breadcrumb area. 3. Check the Room > Floor > Building path.	Hierarchy: Main Building A > Floor 1 > Room A101 > Table A101-01	Table appears under the correct Room > Floor > Building hierarchy.	High	M1/M2	Not Executed	SS_TC-UI-US04-AC18-01.png
TC-UI-US04-AC18-02	AC18: Table is saved and appears under	Compatibility/UI	Admin is logged into the CMS with access	1. Open another room/floor if	Hierarchy placement verification	Table remains visible only under the	Medium	M1/M2	Not Executed	SS_TC-UI-US04-AC18-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
	the correct Room > Floor > Building hierarchy		to the required module.	available. 2. Verify the created table is not shown in incorrect locations. 3. Return to original room and confirm table exists.		correct room hierarchy.				
TC-UI-US04-AC19-01	AC19: Multiple tables can be placed in one room	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open one room. 2. Add Table A. 3. Add Table B.	Tables: Table A101-01, Table A101-02	Multiple tables are placed and visible in one room.	Medium	M1/M2	Not Executed	SS_TC-UI-US04-AC19-01.png
TC-UI-US04-AC19-02	AC19: Multiple tables can be placed in one room	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open table list/grid for the room. 2. Verify more than one table is visible. 3. Check alignment, spacing, and readability.	Multiple table layout check	Multiple table entries display properly without overlap or broken layout.	Medium	M1/M2	Not Executed	SS_TC-UI-US04-AC19-02.png
TC-UI-US04-AC20-01	AC20: Room and Table names are editable after creation	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing room. 2. Click 'Edit' on room. 3. Update Room Name and save.	Updated Room Name: Room A101 Updated	Room name is updated successfully and visible in the UI.	Medium	M1/M2	Not Executed	SS_TC-UI-US04-AC20-01.png
TC-UI-US04-AC20-02	AC20: Room and Table names are editable after creation	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open an existing table. 2. Click 'Edit' on table. 3. Update Table Name and save.	Updated Table Name: Table A101-01 Updated	Table name is updated successfully and visible in the UI.	Medium	M1/M2	Not Executed	SS_TC-UI-US04-AC20-02.png

US-05 - Assign a Job to a Table

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US05-AC21-01	AC21: Admin can assign an existing Job to a Table	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing table. 2. Open job assignment area/dropdown. 3. Select an existing job and click Assign.	Job: Receptionist	Existing job can be selected and assigned to the table.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC21-01.png
TC-UI-US05-AC21-02	AC21: Admin can assign an existing Job to a Table	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open job assignment area. 2. Do not select any job. 3. Attempt to click Assign.	Job: not selected	Assign action is disabled or validation appears when no job is selected.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC21-02.png
TC-UI-US05-AC22-01	AC22: The Job-Table assignment is saved and visible in the hierarchy	Positive UI	Admin is logged into the CMS with access to the required module.	1. Assign an existing job to a table. 2. Save the assignment. 3. Check table	Table: Table A101-01, Job: Receptionist	Job-table assignment is saved and visible in the hierarchy/table details.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC22-01.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
				detail/hierarchy view.						
TC-UI-US05-AC22-02	AC22: The Job-Table assignment is saved and visible in the hierarchy	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Refresh or reopen the table detail page after assignment. 2. Check assigned job display. 3. Verify the displayed job name remains correct.	Persistence check after reopen	Saved assignment remains visible after reopening or refreshing the view.	Medium	M1/M2	Not Executed	SS_TC-UI-US05-AC22-02.png
TC-UI-US05-AC23-01	AC23: A table can have a job assigned and unassigned	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a table with an assigned job. 2. Click 'Unassign' or remove job action. 3. Confirm removal if prompted.	Assigned job: Receptionist	Assigned job is removed and table shows no assigned job.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC23-01.png
TC-UI-US05-AC23-02	AC23: A table can have a job assigned and unassigned	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open a table with no assigned job. 2. Review job section. 3. Verify no misleading assigned-job label is shown.	Table with no assigned job	Unassigned table state is clear and does not display an incorrect job.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC23-02.png
TC-UI-US05-AC24-01	AC24: The assignment is reflected in the 3D Unity visualization	Positive UI	Admin is logged into the CMS with access to the required module.	1. Assign a job to a table in CMS. 2. Open/refresh Unity 3D visualization. 3. Locate the same table/workstation.	Unity check for Table A101-01 + Receptionist	Assigned job is reflected in Unity visualization or visible label/state if the feature is available.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC24-01.png
TC-UI-US05-AC24-02	AC24: The assignment is reflected in the 3D Unity visualization	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open Unity view after assignment. 2. Observe loading/sync status. 3. Verify UI shows an understandable loading or unavailable state if sync is delayed.	Unity sync/loading state	Unity reflection delay is handled with a readable loading or status message; no broken UI is shown.	Medium	M1/M2	Not Executed	SS_TC-UI-US05-AC24-02.png
TC-UI-US05-AC25-01	AC25: Assigning a job to a table that already has one shows a confirmation or replaces it	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a table already assigned to one job. 2. Select a different job. 3. Click Assign/Replace.	Old Job: Receptionist, New Job: Engineer	System shows confirmation or replaces assignment according to UI behavior.	High	M1/M2	Not Executed	SS_TC-UI-US05-AC25-01.png
TC-UI-US05-AC25-02	AC25: Assigning a job to a table that already has one shows a confirmation or replaces it	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. When replacement confirmation appears, click Cancel. 2. Return to table detail view.	Cancel replacement confirmation	Cancel action keeps the old job assignment unchanged.	Medium	M1/M2	Not Executed	SS_TC-UI-US05-AC25-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
				3. Verify original job is still assigned.						

US-06 - Add a Job and a Function

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US06-AC26-01	AC26: Admin can create a new Job with a name and relevant details	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Jobs module. 2. Click 'Create Job'. 3. Enter Job Name and relevant details, then save.	Job Name: Safety Officer	New job is created and displayed in the Jobs list.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC26-01.png
TC-UI-US06-AC26-02	AC26: Admin can create a new Job with a name and relevant details	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Create Job form. 2. Leave Job Name blank. 3. Click Save.	Job Name: blank	Validation appears and empty job is not created.	High	M1/M2	Not Executed	SS_TC-UI-US06-AC26-02.png
TC-UI-US06-AC27-01	AC27: Admin can create a new Function with a name	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Functions module. 2. Click 'Create Function'. 3. Enter Function Name and save.	Function Name: Operations	New function is created and displayed in the Functions list.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC27-01.png
TC-UI-US06-AC27-02	AC27: Admin can create a new Function with a name	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Create Function form. 2. Leave Function Name blank. 3. Click Save.	Function Name: blank	Validation appears and empty function is not created.	High	M1/M2	Not Executed	SS_TC-UI-US06-AC27-02.png
TC-UI-US06-AC28-01	AC28: Both Job and Function appear in their respective lists after creation	Positive UI	Admin is logged into the CMS with access to the required module.	1. Create a valid Job. 2. Create a valid Function. 3. Open the respective lists.	Job: Safety Officer, Function: Operations	Both created Job and Function appear in their respective lists.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC28-01.png
TC-UI-US06-AC28-02	AC28: Both Job and Function appear in their respective lists after creation	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Search/filter the Jobs and Functions lists if search is available. 2. Verify created entries are findable. 3. Check list layout after entries appear.	List/search visibility check	Created items remain visible/findable and list layout remains readable.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC28-02.png
TC-UI-US06-AC29-01	AC29: A Function can have multiple Jobs associated with it	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a Function detail view. 2. Associate Job A with the Function. 3. Associate Job B with the same Function.	Jobs: Safety Officer, Receptionist	Function displays multiple associated jobs.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC29-01.png
TC-UI-US06-AC29-02	AC29: A Function can have multiple Jobs associated with it	Compatibility/UI	Admin is logged into the CMS with access	1. Open the associated jobs section.	Multiple associated jobs layout	Multiple job associations display	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC29-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
			to the required module.	2. Verify multiple job names are visible. 3. Check that multiple tags/rows do not overlap.		clearly under the same function.				
TC-UI-US06-AC30-01	AC30: Invalid or empty submissions show appropriate validation messages	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Job creation form. 2. Submit with missing required fields. 3. Observe validation message.	Job form empty	Invalid or empty Job submission shows validation and does not save.	Medium	M1/M2	Not Executed	SS_TC-UI-US06-AC30-01.png
TC-UI-US06-AC30-02	AC30: Invalid or empty submissions show appropriate validation messages	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Function creation form. 2. Submit with missing required fields. 3. Observe validation message.	Function form empty	Invalid or empty Function submission shows validation and does not save.	High	M1/M2	Not Executed	SS_TC-UI-US06-AC30-02.png

US-07 - Add a Process and Link Tasks to It

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US07-AC31-01	AC31: Admin can create a new Process with a name and description	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Processes module. 2. Click 'Create Process'. 3. Enter Process Name and Description, then save.	Process: Visitor Registration Process, Description: Front desk visitor workflow	New process is created successfully with name and description.	High	M1/M2	Not Executed	SS_TC-UI-US07-AC31-01.png
TC-UI-US07-AC31-02	AC31: Admin can create a new Process with a name and description	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open Create Process form. 2. Check Name and Description field labels. 3. Verify required/optional indicators are understandable.	Process form UI check	Process fields are visible, labeled, and visually understandable.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC31-02.png
TC-UI-US07-AC32-01	AC32: Admin can add Tasks within a Process	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing process. 2. Click 'Add Task'. 3. Enter Task Name and save.	Task: Verify Visitor Details	Task is added within the selected process.	High	M1/M2	Not Executed	SS_TC-UI-US07-AC32-01.png
TC-UI-US07-AC32-02	AC32: Admin can add Tasks within a Process	Negative/UI Validation	Admin is logged into the CMS with access to the required module.	1. Open Add Task form. 2. Leave Task Name blank. 3. Click Save.	Task Name: blank	Validation appears and empty task is not created.	High	M1/M2	Not Executed	SS_TC-UI-US07-AC32-02.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US07-AC33-01	AC33: Tasks appear under the correct Process	Positive UI	Admin is logged into the CMS with access to the required module.	1. Add a task inside a process. 2. Open the process task list. 3. Verify the task appears under the same process.	Process: Visitor Registration Process, Task: Verify Visitor Details	Task appears under the correct process.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC33-01.png
TC-UI-US07-AC33-02	AC33: Tasks appear under the correct Process	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open another process if available. 2. Verify the task is not shown under the wrong process. 3. Return to original process and confirm task exists.	Process-task placement check	Task remains associated with the correct process only.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC33-02.png
TC-UI-US07-AC34-01	AC34: Tasks can be reordered or edited	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open process task list. 2. Use edit option on a task. 3. Update task name and save.	Updated Task Name: Verify Visitor Details Updated	Task is edited successfully and updated name is visible.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC34-01.png
TC-UI-US07-AC34-02	AC34: Tasks can be reordered or edited	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open process task list. 2. Use reorder control if available. 3. Move a task up/down and observe order.	Task reorder UI check	Task order changes visibly or system provides a clear control/status for ordering.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC34-02.png
TC-UI-US07-AC35-01	AC35: A Process with no Tasks can still be saved	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Create Process form. 2. Enter Process Name and Description. 3. Save without adding tasks.	Process with zero tasks	Process is saved successfully even when it has no tasks.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC35-01.png
TC-UI-US07-AC35-02	AC35: A Process with no Tasks can still be saved	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open saved process with no tasks. 2. Review task section. 3. Verify empty-state message is readable.	Empty task list UI	No-task state is displayed clearly without broken layout.	Medium	M1/M2	Not Executed	SS_TC-UI-US07-AC35-02.png

US-08 - Link Tasks and Jobs to Each Other

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US08-AC36-01	AC36: Admin can open a Task and assign a Job to it or vice versa	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open an existing task. 2. Open job assignment/link section.	Task: Verify Visitor Details, Job: Receptionist	Admin can assign/link a job to the task.	High	M1/M2	Not Executed	SS_TC-UI-US08-AC36-01.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
				3. Select a job and save link.						
TC-UI-US08-AC36-02	AC36: Admin can open a Task and assign a Job to it or vice versa	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open job detail view if reverse linking is available. 2. Attempt to link the job to a task. 3. Verify reverse workflow is accessible or clearly unavailable.	Reverse linking UI check	Task-job linking is available from at least one valid UI path and the UI is clear.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC36-02.png
TC-UI-US08-AC37-01	AC37: The link between Task and Job is saved and visible in both the task and job views	Positive UI	Admin is logged into the CMS with access to the required module.	1. Link a job to a task. 2. Open task view and check linked job. 3. Open job view and check linked task.	Task: Verify Visitor Details, Job: Receptionist	The link is visible in both task and job views.	High	M1/M2	Not Executed	SS_TC-UI-US08-AC37-01.png
TC-UI-US08-AC37-02	AC37: The link between Task and Job is saved and visible in both the task and job views	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Refresh/reopen both views after linking. 2. Check the link display again. 3. Verify names remain correct.	Persistence check after reopen	The link persists and remains visible after reopening views.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC37-02.png
TC-UI-US08-AC38-01	AC38: A Task can be linked to more than one Job	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a task. 2. Link Job A. 3. Link Job B to the same task.	Jobs: Receptionist, Engineer	Task displays more than one linked job.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC38-01.png
TC-UI-US08-AC38-02	AC38: A Task can be linked to more than one Job	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Review linked job list/tags for the task. 2. Verify multiple linked jobs are readable. 3. Check that UI spacing is not broken.	Multiple linked jobs UI	Multiple linked jobs display clearly without overlap.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC38-02.png
TC-UI-US08-AC39-01	AC39: A Job can appear in multiple Tasks	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open Task A and link a job. 2. Open Task B and link the same job. 3. Open the job view.	Job: Receptionist linked to Task A and Task B	The same job appears in multiple tasks and shows related task links.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC39-01.png
TC-UI-US08-AC39-02	AC39: A Job can appear in multiple Tasks	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Review the job view with multiple task links. 2. Verify task names are readable. 3. Check that list layout remains stable.	Multiple task links UI	Multiple task links display clearly under the job view.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC39-02.png
TC-UI-US08-AC40-01	AC40: Removing a link does not delete either the Task or the Job	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open a linked task-job relationship. 2. Remove the link. 3. Verify task and job records still exist.	Remove task-job link	Removing a link deletes only the relationship, not the task or job.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC40-01.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US08-AC40-02	AC40: Removing a link does not delete either the Task or the Job	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. After removing the link, open task list and job list. 2. Confirm both records remain available. 3. Verify no misleading deletion message appears.	Record existence check after unlink	Both task and job remain in their lists after unlinking.	Medium	M1/M2	Not Executed	SS_TC-UI-US08-AC40-02.png

US-09 - View Company Hierarchy in Tree Form

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US09-AC41-01	AC41: Tree view is accessible from the CMS dashboard or navigation	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open CMS dashboard/navigation. 2. Locate 'Tree View' or hierarchy tree option. 3. Click the tree view option.	Browser: Chrome	Tree view is accessible from dashboard or navigation.	High	M1/M2	Not Executed	SS_TC-UI-US09-AC41-01.png
TC-UI-US09-AC41-02	AC41: Tree view is accessible from the CMS dashboard or navigation	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Open the tree view in Firefox. 2. Check navigation layout. 3. Verify tree view option is not hidden or overlapped.	Browser: Firefox	Tree view entry point remains accessible in Firefox.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC41-02.png
TC-UI-US09-AC42-01	AC42: Tree displays all levels: Company, Building, Floor, Room, Table, Job	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open tree view after creating hierarchy data. 2. Expand the company node. 3. Verify levels down to Job are shown.	Hierarchy: Company > Building > Floor > Room > Table > Job	Tree displays Company > Building > Floor > Room > Table > Job levels.	High	M1/M2	Not Executed	SS_TC-UI-US09-AC42-01.png
TC-UI-US09-AC42-02	AC42: Tree displays all levels: Company, Building, Floor, Room, Table, Job	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Review tree labels for all levels. 2. Check indentation and hierarchy alignment. 3. Verify labels are not truncated unexpectedly.	Tree label/readability check	All hierarchy levels are visually readable and correctly indented.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC42-02.png
TC-UI-US09-AC43-01	AC43: Nodes can be expanded and collapsed	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open tree view. 2. Click expand icon on company/building nodes. 3. Click collapse icon on expanded nodes.	Expand/collapse actions	Nodes expand and collapse correctly.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC43-01.png
TC-UI-US09-AC43-02	AC43: Nodes can be expanded and collapsed	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Rapidly expand and collapse multiple nodes. 2. Observe tree state and layout. 3. Verify no duplicate or broken nodes appear.	Repeated expand/collapse	Tree remains stable and no duplicate/broken nodes appear during expand/collapse.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC43-02.png
TC-UI-US09-AC44-01	AC44: Clicking a node shows the detail of that entity	Positive UI	Admin is logged into the CMS with access to the required module.	1. Open tree view. 2. Click a company/building/floor/room/table/job node. 3. Observe detail panel/page.	Tree node click	Clicking a node shows the correct detail of that entity.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC44-01.png

TC ID	AC	Type	Pre-condition	Steps	Test Data	Expected Result	Priority	Tester	Status	Evidence
TC-UI-US09-AC44-02	AC44: Clicking a node shows the detail of that entity	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Click different nodes one by one. 2. Compare detail view title/name with selected node. 3. Check that previous node details are not shown incorrectly.	Switching between nodes	Detail view updates according to the selected node.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC44-02.png
TC-UI-US09-AC45-01	AC45: Newly added entities appear in the tree without a full page reload	Positive UI	Admin is logged into the CMS with access to the required module.	1. Create a new hierarchy entity in CMS. 2. Return to or observe tree view. 3. Check whether the new entity appears without full page reload.	Newly created company/building/floor/room/table/job	Newly added entity appears in the tree without requiring a full browser reload.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC45-01.png
TC-UI-US09-AC45-02	AC45: Newly added entities appear in the tree without a full page reload	Compatibility/UI	Admin is logged into the CMS with access to the required module.	1. Create another entity and keep tree view open if possible. 2. Observe loading/refresh behavior. 3. Verify no stale tree state is shown.	Tree update/stale-state check	Tree updates or provides a clear refresh/loading state without broken UI.	Medium	M1/M2	Not Executed	SS_TC-UI-US09-AC45-02.png

10. Screenshots to Insert Before Submission

The following evidence screenshots can be inserted in the placeholders above before final LMS submission:

- Final shared Jira project dashboard or project home page.
- Instructor invitation/access page showing the instructor email added or invited.
- AIO Tests app visible in the final Jira project.
- AIO Cases folder structure for US-01 to US-09.
- One opened sample AIO test case showing Title, Pre-condition, Steps, Expected Result, Priority, and Tester.
- AIO list/screenshots showing US-01 to US-09 test cases are created.
- Browser matrix evidence if screenshots are required by your instructor.

11. Assignment 3 Completion Checklist

Requirement	Status
Jira account/project prepared	Done / Pending
AIO Tests installed	Done / Pending
Instructor email invited	Done / Pending
AIO folders for US-01 to US-09 created	Done / Pending
90 UI test cases added to AIO	Done / Pending
Testers assigned as M1/M2	Done / Pending
Test data prepared	Done / Pending