实验 2: 物理内存管理

练习 0: 填写已有实验

答:利用 Ubuntu 系统中的 meld 工具,针对 Lab1 中曾经更改的几个文件,分别对照更正既有代码。

练习 1: 实现 first-fit 连续物理内存分配算法

在实现 first fit 内存分配算法的回收函数时,要考虑地址连续的空闲块之间的合并操作。提示:在建立空闲页块链表时,需要按照空闲页块起始地址来排序,形成一个有序的链表。可能会修改 default*pmm.c 中的 default*init,

default*init*memmap,default*alloc*pages, default*free*pages 等相关函数。请仔细查看和理解 default_pmm.c 中的注释。

```
#define free_list (free_area.free_list)
#define nr_free (free_area.nr_free)
/* 初始化free list同时为nr free置零 */
static void
default init(void) {
  list_init(&free_list); //free_list记录空的块
  nr free = 0; //nr free为当前空块总数
}
/*函数用来初始化一块大小为PGSIZE*n的物理内存区域
调用过程依次为 kern_init --> pmm_init-->page_init-->init_memmap-->
pmm_manager->init_memmap
根据page init函数传参,具体为某个连续地址的空闲块的起始页和页个数,建立空闲块的双
向链表 */
static void
default_init_memmap(struct Page *base, size_t n) {
   assert(n > 0); //确认n的合理性
  struct Page *p = base; //页指针
   for (; p != base + n; p ++) {
      assert(PageReserved(p)); //有效页
      p->flags = 0; //有关有效性标记, 参见pmm.c
      SetPageProperty(p); //设置有效
      p->property = 0; //当前页为空且不为第一页则property为零
      set_page_ref(p, 0); //由于p此时是free状态, ref也应置零
      list_add_before(&free_list, &(p->page_link)); //链接free_list
   }
```

```
base->property = n; //以base为首用property表示内存块page总数
  nr_free += n; //更新物理内存空闲块总数
}
/* 函数用来实现first fit,输入所需的块大小n,返回相应第一个page的地址 */
static struct Page *
default_alloc_pages(size_t n) {
   assert(n > 0); //检查n的合理性
   if (n > nr_free) { //若n太大超过现存空闲块总数,则返回代表无法满足的空指针
     return NULL;
   }
   list_entry_t *le, *len;
  le = &free_list;
  while((le=list_next(le)) != &free_list) { //依次遍历free_list
    struct Page *p = le2page(le, page_link); //得到对应页指针
    if(p->property >= n){ //检查是否是足够大的块
      int i;
     for(i=0;i<n;i++){ //设置已分配的内存空间
       len = list_next(le);
       struct Page *pp = le2page(le, page_link);
       SetPageReserved(pp);
       ClearPageProperty(pp);
       /* 设置PG reserve=1, PG property=0 */
       list_del(le); //删除已申请的页
       le = len;
      if(p->property>n){ //若仍有剩余则将剩余块加回去
       (le2page(le,page_link))->property = p->property - n;
     ClearPageProperty(p);
     SetPageReserved(p);
     nr_free -= n; //更新空块总数
     return p; //返回目标指针
    }
   }
  return NULL; //遍历后找不到符合条件的块则返回空指针
}
/* 函数参数是指向一个page物理地址的指针,以及需要free的pages的个数,主要功能是将
以指针page开始的n块page的内存释放,并将其加入到free_list中 */
static void
default_free_pages(struct Page *base, size_t n) {
  assert(n > 0); //检查n的合理性
  assert(PageReserved(base)); //检查base的合理性
```

```
list_entry_t *le = &free_list; //得到free_list的表头
   struct Page * p; //找到插入位置的页指针
   while((le=list_next(le)) != &free_list) { //从高到低遍历找到合适的插入
位置
    p = le2page(le, page_link); //得到对应页的指针
    if(p>base){
      break;
    }
   }
   //插入链表中并更新相关标记,如p->property等
   for(p=base;p<base+n;p++){</pre>
    list_add_before(le, &(p->page_link));
   }
   base->flags = 0; //重置p->ref, p->flags
   set_page_ref(base, 0);
   ClearPageProperty(base);
   SetPageProperty(base);
   /* 设置PG reserve=1, PG property=0 */
   base->property = n; //设置页大小
   p = le2page(le,page_link);
   if( base+n == p ){
    base->property += p->property;
    p->property = 0;
   }
   le = list_prev(&(base->page_link)); //合并块
   p = le2page(le, page_link);
   if(le!=&free_list && p==base-1){ //检查是否块之间是否可以合并
    while(le!=&free_list){
      if(p->property){
       p->property += base->property;
       base->property = 0;
       break;
      }
      le = list_prev(le);
      p = le2page(le,page_link);
    }
   }
   nr_free += n; //增加空块总数
   return ;
}
```

练习 2: 实现寻找虚拟地址对应的页表项

通过设置页表和对应的页表项,可建立虚拟内存地址和物理内存地址的对应关系。其中的 getpte 函数是设置页表项环节中的一个重要步骤。此函数找到一个虚地址对应的二级页表项的内核虚地址,如果此二级页表项不存在,则分配一个包含此项的二级页表。本练习需要补全 getpte 函数 in kern/mm/pmm.c,实现其功能。请仔细查看和理解 getpte 函数中的注释。getpte 函数的调用关系图如下所示:




图 1 get_pte 函数的调用关系图

```
//get_pte - get pte and return the kernel virtual address of this pte
//
        - if the PT contians this pte didn't exist, alloc a page for
PT
// parameter:
// pgdir: the kernel virtual base address of PDT
         the linear address need to map
// create: a logical value to decide if alloc a page for PT
// return vaule: the kernel virtual address of this pte
pte_t *
get_pte(pde_t *pgdir, uintptr_t la, bool create) {
   /* LAB2 EXERCISE 2: 12307130244
    * If you need to visit a physical address, please use KADDR()
    * please read pmm.h for useful macros
    * Maybe you want help comment, BELOW comments can help you finish
the code
```

* Some Useful MACROs and DEFINEs, you can use them in below

```
implementation.
    * MACROs or Functions:
    * PDX(la) = the index of page directory entry of VIRTUAL
ADDRESS la.
    * KADDR(pa): takes a physical address and returns the
corresponding kernel virtual address.
   * set_page_ref(page,1) : means the page be referenced by one
time
   * page2pa(page): get the physical address of memory which this
(struct Page *) page manages
      struct Page * alloc_page() : allocation a page
      memset(void *s, char c, size_t n) : sets the first n bytes of
the memory area pointed by s
                                   to the specified value c.
   * DEFINEs:
   * PTE_P
                                        // page table/directory
                    0 \times 001
entry flags bit : Present
   * PTE_W
                     0x002
                                        // page table/directory
entry flags bit : Writeable
   * PTE U
                     0x004
                                        // page table/directory
entry flags bit : User can access
   * /
#if 0
   pde_t *pdep = NULL; // (1) find page directory entry
   if (0) {
                      // (2) check if entry is not present
                    // (3) check if creating is needed, then alloc
page for page table
                    // CAUTION: this page is used for page table,
not for common data page
                    // (4) set page reference
      uintptr_t pa = 0; // (5) get linear address of page
                     // (6) clear page content using memset
                     // (7) set page directory entry's permission
   }
   return NULL;  // (8) return page table entry
#endif
找到一个虚地址对应的二级页表项的内核虚地址,若不存在则分配一个包含此项的二级页表
   pde_t *pdep = &pgdir[PDX(la)]; //寻找一级页表表项,获得相应指向页目录表
项的指针
   if (!(*pdep & PTE_P)) { //检查该页目录表项对应的page是否存在
      struct Page *page;
      if (!create | | (page = alloc_page()) == NULL) { //检查是否需要建
立二级页表, 若不存在则分配空间
```

return NULL;

```
}
set_page_ref(page, 1); //设置page_ref
uintptr_t pa = page2pa(page); //获取线性地址,即物理地址
memset(KADDR(pa), 0, PGSIZE); //没有映射故需清空新申请的表,初始化该
page所有位置
*pdep = pa | PTE_U | PTE_W | PTE_P; //设置控制页,将页表的物理地址
处理后赋值给目录表项
}
return &((pte_t *)KADDR(PDE_ADDR(*pdep)))[PTX(la)]; //返回二级页表项
/* *pdep为pdep所指向的页目录表内容,存储了所指向的页表首地址及控制信息
PDE_ADDR(*pdep)为所指向页表首物理地址,KADDR获得了页表首虚拟地址
通过强制类型类型转换(pte_t *)强制转换成执行页表的首地址
通过[PTX(la)]索引获得对应page中的Page table entry
最后利用&操作符取其地址即为所求的pte */
}
```

练习 3: 释放某虚地址所在的页并取消对应二级页表项的映射

当释放一个包含某虚地址的物理内存页时,需要让对应此物理内存页的管理数据结构 Page 做相关的清除处理,使得此物理内存页成为空闲;另外还需把表示虚地址与物理地址对应关系的二级页表项清除。请仔细查看和理解 page remove pte 函数中的注释。为此,需要补全在 kern/mm/pmm.c 中的 page remove pte 函数。page remove pte 函数的调用关系图如下所示:




图 2 page removepte 函数的调用关系图

```
//page_remove_pte - free an Page sturct which is related linear address la
// - and clean(invalidate) pte which is related linear address la
//note: PT is changed, so the TLB need to be invalidate
/* 释放一个包含虚地址的物理内存页时,需要将管理此物理内存页的数据结构page做相应清除处理,使得物理内存页变为空闲状态,另外还需要将记录虚地址与物理地址对应的二级页表项清除 */
static inline void
page_remove_pte(pde_t *pgdir, uintptr_t la, pte_t *ptep) {
    /* LAB2 EXERCISE 3: 12307130244
```

*

```
* Please check if ptep is valid, and tlb must be manually updated
if mapping is updated
    * Maybe you want help comment, BELOW comments can help you finish
the code
    * Some Useful MACROs and DEFINEs, you can use them in below
implementation.
    * MACROs or Functions:
      struct Page *page pte2page(*ptep): get the according page
from the value of a ptep
    * free_page : free a page
    * page_ref_dec(page) : decrease page->ref. NOTICE: ff page->ref
== 0 , then this page should be free.
      tlb_invalidate(pde_t *pgdir, uintptr_t la) : Invalidate a TLB
entry, but only if the page tables being
                       edited are the ones currently in use by the
processor.
   * DEFINEs:
    * PTE P
                    0 \times 001
                                        // page table/directory
entry flags bit : Present
   * /
#if 0
   if (0) {
                           //(1) check if page directory is
present
      struct Page *page = NULL; //(2) find corresponding page to pte
                            //(3) decrease page reference
                            //(4) and free this page when page
reference reachs 0
                            //(5) clear second page table entry
                            //(6) flush tlb
   }
#endif
   if (*ptep & PTE_P) { //检测对应二级页表项是否存在
      struct Page *page = pte2page(*ptep); //搜索相应一级页
      if (page_ref_dec(page) == 0) { //page->ref-=1
         free_page(page); //释放页
      *ptep = 0; //清除二级页表项指针,将ptep所指向内容清空
      tlb_invalidate(pgdir, la); //删除tlb中的缓冲项
   }
}
```