# Lecture 6 Paging

Prof. Yinqian Zhang
Spring 2022

#### Outline

- Introduction to paging
- Multi-level page tables
- Other page table structures
- Real-world paging schemes
- Translation lookaside buffer


# Introduction to Paging

#### Recall: Problems with Segmentation

- OS context switch must also save and restore all pairs of segment registers
- A segment may grow, which may or may not be possible
- Management of free spaces of physical memory with variablesized segments
- External fragmentation: gaps between allocated segments
  - Segmentation may also have internal fragmentation if more space allocated than needed.


#### Solutions for Segmentation

- OS context switch must also save and restore all pairs of segment registers
  - Table of base/bounds stored in memory rather than registers
  - Pointer to the table stored in a register
  - Cons: one more memory read per address translation




### Solutions for Segmentation (Cont'd)

 A segment may grow, which may or may not be possible




### Solutions for Segmentation (Cont'd)

- A segment may grow, which may or may not be possible
  - Virtually continuous memory can be physically discontinuous



### Solutions for Segmentation (Cont'd)

- Management of free spaces of physical memory with variable-sized segments
  - Fixed-sized segments
  - Physical memory curved into fixed sized chunks, index by an integer
  - Can use simple vector of bits to handle allocation (1-allocated, 0-free) 110110101101010110
- External fragmentation
  - Fixed-sized segments
  - Each request is of the same fixed size always fit, no external fragmentation



#### Paging: Put All These Ideas Together


- Physical memory conceptually divided into fixed size
  - Each is called a page frame
  - Typical size 1KB to 16KB, most ISA uses 4KB
- Virtual address space conceptually divided into the same size
  - Each is called a page
- Page mapped to page frame
  One to one mapping
  Many to one mapping -> memory sharing
- One page table per process
  Resides in physical memory

  - One entry for one virtual->physical translation


#### How big is one page (frame)?

- Too big -> internal fragmentation
- Too small -> page table too big


#### Paging Illustrated




Virtual Address = Virtual Page Number || Offset




Physical Address = Physical Page Number || Offset




#### Paging Illustrated (Cont'd)





### Paging Illustrated (Cont'd)




#### Memory Sharing with Paging










#### Virtual Address and Paging

- · Length of virtual address determines size of address space
- · Length of offset determines size of a page/page frame
- In case of m-bit virtual address and k-bit offset
  - Size of address space:  $2^m$
  - Size of a page:  $2^k$
  - e.g., 32-bit virtual address, 4KB page: m = 31, k = 11



CS302 Operating Systems


Page #	Page Frame #
0	PFN
1	PFN
2	PFN
•••	•••••
$2^{m-k}$ -1	PFN

#### Page Table Entry

- An entry in the page table is called a page table entry (PTE).
- Besides PFN, PTE also contains a valid bit
  - Virtual pages with no valid mapping: valid bit = 0
  - Important for sparse address space (e.g., 2<sup>64</sup> bytes)
- PTE also contains protection bits
  - · Permission to read from or write, or execute code on this page
- PTE also contains an access bit, a dirty bit, a present bit
  - Present bit: whether this page is in physical memory or on disk
  - Dirty bit: whether the page has been modified since it was brought into memory
  - · Access bit: whether a page has been accessed

#### How Big are Page Tables


- Assume 32-bit machine and 4KB pages, and each PTE takes 4 bytes (PFN plus status bits)
  - Number of PTEs:  $2^{32-12} = 2^{20}$
  - Size of page table: 4MB
  - What if 100 processes running? 400MB
- Page tables are stored in memory and context switch only changes the pointer to page table (e.g., CR3 register)



# Multi-level Page Tables


#### Two-level Page Tables

• Use two levels of page tables to save space




### A Tree of Page Tables

- A page table also occupies a page frame
  - e.g., 4KB page and 4-byte PTE:
    1024 entries per table
- Two-level page table forms a tree of page tables
  - In theory 1024 level-2 page tables, but only a subset are valid
  - A subset of valid page tables are stored in memory (others on disk)





### A Tree of Page Tables (Cont'd)

Swapped-out pages on disk



CS302 Operating Systems






### Other Page Table Structures

#### Page Table Structures

- Hierarchical page tables
  - 2-level page tables
  - 3-level page tables
  - 4-level page tables
- · Hashed Page Tables
- Inverted Page Tables


#### Hashed Page Tables

- Hash function
  - input: VPN
  - output: index in the hashed page table
- · Collision handling
  - · A linked list
  - Each element consists of three fields: (1) VPN, (2) PFN, and (3) pointer to the next element



#### Inverted Page Tables


- One page table for the whole system
  - Used in 64-bit UltraSPARC and PowerPC
- Each entry corresponds to one physical page frame
  - Process ID and VPN
- Page table lookup requires linear search of the entire table
- Memory sharing is hard




# Real-world Paging Schemes

#### Virtual Memory on RISC-V

- RISC-V supports multiple MMU
  - For RV32: SV32
  - For RV64: SV39 and SV48
- Here we introduce SV39
  - Page size: 4KB
  - Virtual address: 39 bits
    - remaining bits of total 64 bits reserved
  - Physical address: 56 bits



#### SV39: Three Levels of Page Tables




#### SV39: Page Table Entries

- A PTE in SV39 takes 8 bytes (64 bits)
  - Bit 8-0 status bits
  - Bit 53-10 is PFN (or physical page number, PPN)
  - Bits 63-54 reserved
- The 9 status bits
  - D (dirty), A (accessed), V (valid)
  - G (Global): G=1 the page is mapped in all address spaces
  - U (User): U-mode code may access this page
  - RSW: reserved for s-mode

63	54	53	28	27	19	18 1	10 9	8	7	6	5	4	3	2	1	0
Re	served	PPN	[2]	PPN[1]		PPN[0]		RSW	D	A	G	U	X	W	R	V
	10	26		9		9		2	1	1	1	1	1	1	1	1


#### Virtual Memory on IA-32


- Intel's 32-bit CPU (IA-32) uses two stage address translation: segmentation + paging
- A virtual address contains a 16-bit segment selector and 32bit offset



#### Virtual Memory on IA-32

- Two descriptor tables: GDT & LDT
- Six segment register to cache segment base addresses






### Translation Lookaside Buffer

#### Issues of Paging

- Time complexity
  - Extra memory references during address translation
  - Three-level page tables requires 3 additional memory reads
    - If every memory reference needs 4 memory reads

#### Question:


 How to speed up address translation and avoid extra memory reads?




#### Translation Lookaside Buffer

- A translation lookaside buffer (TLB) is a hardware cache that is part of the MMU
  - A cache for the PTEs: holding a translation likely to be re-used
    - Replacement policy: LRU, FIFO, random
  - Each entry holds mapping of a virtual address to a physical address
- Before a virtual-to-physical address translation is to be performed, TLB is looked up using VPN
  - TLB hit: VPN is found, and the PFN of the same entry used
  - TLB miss: VPN not found, page table walk


#### Translation Lookaside Buffer (Cont'd)



#### Translation Lookaside Buffer (Cont'd)




#### Translation Lookaside Buffer (Cont'd)



#### Why Does TLB Work?

- Ideally one page table walk for the entire page
  - TLB is smaller than page table, but
- Spatial locality
  - Sequentially executed instructions, local variables (on stack), arrays (on heap) likely on the same page
  - E.g., accessing a[0] to a[9]
    - m,h,h,m,h,h,h,m,h,h -> 70% hit rate
    - · Large page size increases hit rate
- Temporal locality
  - Accesses to the same page tend to be close in time



#### Issues with Context Switch

 Two process may use the same virtual address

• P1: 100 -> 110

• P2: 100 -> 170

- Solutions
  - Flush TLB upon context switch
    - Invalidate all entries: V->I
  - Extending TLB with address space ID
    - · No need to flush tlb

VPN	PFN	valid	
-	-	_	
100	110	>	
-	-	-	
100	170	V	

VPN	PFN	ASID	
-	-	_	-
100	110	٧	1
-	-	I	-
100	170	V	2

## Thank you!

