GUI64
API Documentation

Programmer's Reference for GUI64 Applications



API version:	1.2
Public API base:	$5F00
Application space:	$B000–$CFFF
CPU:	NMOS 6502
Assembler syntax:	ACME
API entries:	60

Contents

1 Introductory Notes **2**

2 Creating Windows, Controls, Menus, and Dialogs **3**

2.1 Windows . . . 3
2.2 Controls . . . 4
2.3 Menus . . . 6
2.4 Dialogs . . . 6

3 Character set and Keyboard **7**

3.1 The character sets . . . 7
3.2 Keyboard Input . . . 7

4 Sprites and SID **8**

5 Frame and Timer API **9**

5.1 Frame API . . . 9
5.2 Timer API . . . 10
5.3 Timer and Frame Handler Comparison . . . 11

6 Public Jump Table **11**

7 Documentation of API Calls **13**

7.1 Window API . . . 13
7.2 Control API . . . 16
7.3 Application API . . . 19
7.4 Timer API . . . 20
7.5 Frame API . . . 21
7.6 System API . . . 21
7.7 Menu and Mouse API . . . 23
7.8 Dialog API . . . 24
7.9 Input API . . . 25
7.10 Paint API . . . 26

8 Hello World Application **27**

1 Introductory Notes

GUI64 exposes its application interface through a sequence of three-byte `JMP` entries beginning at **`$5F00`**. These routines are given in Section 6 alongside with their particular explanation. However, a programmer should always use the most recent version of the file

`gui64.inc.asm`

which contains these addresses and many other constants definitions. It can always be found in the *Apps* folder in the GUI64 GitHub repository (**`https://github.com/WebFritzi/GUI64/`**).

The current GUI64 application area is:

`$B000` ... **`$CFFF`**

Zeropage

GUI64 extensively makes use of the zeropage. In particular, temporary pointers such as **`$02/$03`**, **`$FB/$FC`**, and **`$FD/$FE`** must be treated as volatile across API calls unless a routine explicitly documents otherwise. Most zeropage addresses are private, but some are public and are documented in the following table.

Address	Name	Meaning
`$10 - $1f`	See Subsection 2.1	Current window information
`$20 - $2f`	See Subsection 2.2	Current control information
`$40`	**`ProgramMode`**	The current state of GUI64 ($00: normal mode, $01: menu mode, $ff: dialog mode)
`$51`	**`MousePosInWndX`**	x coord of mouse cursor relative to current window area
`$52`	**`MousePosInWndY`**	y coord of mouse cursor relative to current window area
`$53`	**`actkey`**	Petscii code of key currently pressed (or **`$ff`** if no key is pressed)
`$5b`	**`wndParam0`**	Is sent to window procs and contains the event code
`$5c`	**`wndParam1`**	Is sent to window procs and contains the program mode at the stage when the event code was sent
`$5d`	**`Param0`**	Used as parameter for some API calls
`$6b`	**`key_shifted`**	Contains zero exactly if currently pressed key is pressed without SHIFT
`$87`	**`CurMenuItem`**	Index of chosen menu item
`$96`	**`res`**	Return value of **`CreateWindow`** and **`CreateWindowEx`**

GUI64 API architecture

- 16-bit addresses are passed with **`X`** as low byte and **`Y`** as high byte (**`Addr(X/Y)`**).
- The current window is mirrored in the static window structure at **`$10–$1F`**.
- The current control is mirrored in the static control structure at **`$20–$2F`**.
- `wndParam0`/`wndParam1` carry window-procedure event information.
- Carry is used by several yes/no-routines as the Boolean result.
- API routines may alter **`A`**, **`X`**, **`Y`**, flags, and GUI64 scratch memory in zero page.

Register and flag effects

Each API description lists which registers and processor flags may change on return. The lists include registers used for return values. A register or flag listed as preserved retains its entry value. Unless an output is explicitly documented, a changed register or flag has no defined meaning. The processor flags considered here are **`C`**, **`N`**, **`Z`**, **`V`**, **`I`**, and **`D`**. The register/flag effects apply to both designs unless a WIN/MAC difference is stated. For calls that dispatch application callbacks, the callback's effects are included in the preservation contract. Such wrappers do not generally save and restore the callback's processor status.

2 Creating Windows, Controls, Menus, and Dialogs

The GUI64 API routines for creating and configuring windows, controls, menus, and dialogs. These interface elements are usually defined by static data structures and can be adjusted at runtime after creation. This chapter describes the basic workflow for creating these elements, modifying their properties, and displaying them on screen.

2.1 Windows

A GUI64 window in C64 memory is defined by a 16 byte structure containing the following properties (the "Reserved"-entries are used by GUI64 internally and should not be modified by an app):

Offset	Name	Meaning
0	`CurrentWindow`	Window identifier handle/index
1	`WindowType`	Window type (must be at least 50)
2	`Reserved`	-
3	`WindowBits`	Window property flags
4	`WindowPosX`	X position
5	`WindowPosY`	Y position
6	`WindowWidth`	Width
7	`WindowHeight`	Height
8	`WindowTitleStr`	16-bit pointer to string in title bar
10	Reserved	-
12	Reserved	-
13	Reserved	-
14	`WindowProc`	16-bit window-procedure pointer

Window bits

The window bits are (see **gui64.inc.asm**) `BIT_WND_HASMENU` (1), `BIT_WND_RESIZABLE` (2), `BIT_WND_FIXEDWIDTH` (4), `BIT_WND_FIXEDHEIGHT` (8), `BIT_WND_CANMAXIMIZE` (16) (WIN only), `BIT_WND_CANMINIMIZE` (32) (WIN only), `BIT_WND_ISMINIMIZED` (64), `BIT_WND_ISMAXIMIZED` (128)(WIN only)

Window proc

An important part of a window is its window proc. This routine handles user input events like mouse/joystick or keyboard actions. When the program pointer enters the window proc, the event code can be read from `wndParam0` (see **gui64.inc.asm**). The events are (see **gui64.inc.asm**):

`EC_RBTNPRESS`, `EC_RBTNRELEASE`, `EC_LBTNPRESS`, `EC_LBTNRELEASE`, `EC_MOUSEMOVE`, `EC_DBLCLICK`, `EC_SCROLLWHEELDOWN`, `EC_SCROLLWHEELUP`, `EC_KEYPRESS`, and `EC_SHUTDOWN`.

The other parameter `wndParam1` contains the **program mode** that was active when the event was triggered. The program modes are (see **gui64.inc.asm**) `PM_NORMAL` (0), `PM_MENU` (1), and `PM_DIALOG` (255). For example, when the user selects a menu item of the window's menu, the window proc receives an event with `EC_LBTNPRESS` in `wndParam0` and `PM_MENU` in `wndParam1`. The program mode can be read at any time from `ProgramMode` (see **gui64.inc.asm**).

> **Note:** In each window proc, apps should call `GUI_StdWndProc` which handles events sent to the GUI64 standard controls. For example, when the user clicks on a button, the standard window proc forwards the event to the standard button action routine.

Creation

A window is created by either using `GUI_CreateWindow` or `GUI_CreateWindowEx`. While the first just creates a window and hence only expects window data, the second creates a window with controls. Therefore, there must be controls data provided right after the window data. Window data must always be provided in the following form:

- window type identifier (value must be at least 50), bits, xPos, yPos, width, height, 16-bit pointer to title string, 16-bit pointer to window proc

Each of the first 6 entries is a byte. The last two are words (pointers in little endian format).

2.2 Controls

Controls are graphical elements in a window. There are 14 standard controls in GUI64 that an app may use. Some of them are dynamic (action) and react to user input, some are static (no action). The list of controls is:

ID	Type identifier	Control	Action
1	`CT_MENUBAR`	Menubar	Yes
2	`CT_BUTTON`	Button	Yes
3	`CT_LISTBOX`	Listbox	Yes
5	`CT_COLORPICKER`	Colorpicker	Yes
6	`CT_RADIOBUTTONGROUP`	Radiobutton group	Yes
7	`CT_UPDOWN`	Up/down control	Yes
8	`CT_EDIT_SL`	Single-line edit	Yes
10	`CT_CHECKBOX`	Checkbox	Yes
31	`CT_LABEL`	Label	No
32	`CT_LABEL_ML`	Multi-line label	No
33	`CT_FRAME`	Frame	No
34	`CT_PROGRESSBAR`	Progressbar	No
35	`CT_COLBOXLABEL`	Colorbox label	No
36	`CT_PANEL`	A box	No

The control type identifier is just a replacement of the ID (e.g., `CT_MENUBAR` = 1). Missing IDs in the above table are GUI64 internal.

Each control in a window has properties, provided by a 16 byte structure in memory. Based on this structure, GUI64 knows how to paint and handle the control. The entries of this structure are:

Offset	Name	Meaning
0	`ControlIndex`	Control index
1	`ControlType`	Control type
2	`ControlColor`	Color
3	`ControlPosX`	X position
4	`ControlPosY`	Y position
5	`ControlWidth`	Width
6	`ControlHeight`	Height
7	`ControlBits`	Control property flags
8	`ControlHilIndex`	Highlighted item index
9	`ControlTopIndex`	Top item / control-specific value
10	`ControlNumStr`	Number of strings
11	`ControlStrings`	16-bit string/string-list pointer
13	-	Control-specific
14	`ControlBitsEx`	Extended control flags
15	-	Control-specific

For some controls, the struct members 9 - 14 are used for something else:

Offset	Name	Meaning
10	`UpDown_LowerLimit`	Lower limit of UpDown value
11	`UpDown_UpperLimit`	Upper limit of UpDown value

12	UpDown_DigitLo	Low digit of UpDown control
13	UpDown_DigitHi	Hi digit of UpDown control
10	ProgressBar_MaxLo	Low byte of maximal value of progress bar
11	ProgressBar_MaxHi	High byte of maximal value of progress bar
12	ProgressBar_ValLo	Low byte of value of progress bar
13	ProgressBar_ValHi	High byte of value of progress bar
9	EditSL_CaretPos	Position of caret in single-line edit control
10	EditSL_MaxStrLen	Maximal string length in single-line edit control
14	EditSL_Forbidden	16-bit pointer to forbidden chars
8	Checkbox_IsChecked	Checked (1) or unchecked (0)
8	Panel_PaintOver	Paint only frame of box (0) or also the interior (1)

Selection and modification

In GUI64, windows and controls are *selected*. This means that window or control structures are copied from the heap to zero page (**$10 - $1f** for a window and **$20 - $2f** for a control). Once selected, a window or control is the *current* window or control. You select windows and controls by using **GUI_SelectWindow** or **GUI_SelectControl**, respectively. After selecting a window or control, any changes made to its zero-page structure must be written back to the heap using **GUI_UpdateWindow** or **GUI_UpdateControl** for the changes to take effect.

Creation

There are two options to create a control. The first is using **GUI_CreateWindowEx**, where a window is created alongside its controls. Static control information data must always be provided in the following form:

- control type identifier, xPos, yPos, width, height, null terminated string

Each entry is a byte. The null-terminated string consists of chars (Petscii) and might be empty (i.e., 0).

When you use **GUI_CreateWindowEx** for creating the controls in your window, you provide the window information data at **Addr(X/Y)**, followed by the list of controls information data. Don't forget to add a terminating zero at the end of the list of controls, so GUI64 knows that this was the last control in the list.

The second option to create a control is to use **GUI_AddControl**. This adds a control with control information of the above form at **Addr(X/Y)** to the current window.

Two designs

As there exist two designs of GUI64 (WIN design and MAC design), the programmer should always make sure the controls are placed as intended in both designs. For figuring out under which design the app is currently running, the app code may call **GUI_GetDesign**.

Events

Input by the user via keyboard, mouse, or joystick is sent as an event to the window proc of the control's parent window. In the window proc, the index of the control that currently possesses the input focus is **WindowFocCtrl**. It may not be selected. Therefore, if an app wants to get information on this control, it should select it first by calling **GUI_SelectControl**.

> **Note:** Please note that a button control should react on **EC_LBTNRELEASE** instead of **EC_LBTNPRESS**.

Custom controls

Programmers may register new control types. Custom control type identifiers start at 50. The new controls are added as described above. Before doing so, however, the programmer must inform GUI64 that custom controls will be added. For this, pointers to two routines have to be provided:

- one routine for painting the new controls
- one routine for defining the default behavior of the new controls (event reaction)

The programmer registers these two routines via **GUI_SetPaintCtrlsRoutine** and **GUI_SetCtrlActionsRoutine**, respectively. When the program counter enters them, the **X** register contains the control type identifier. In the case of the PaintCtrls routine, **$fd/$fe** (**$02/$03**) points to the upper left corner of the control in the paint (color) buffer. A control is painted by storing character indices in **$FD/$FE** (**sta ($fd),y**) and color indices in **$02/$03** (**sta ($02),y**). To get to the next row, one may make use of the API calls **GUI_AddBufWidthToFD** and **GUI_AddBufWidthTo02**, respectively. In the CtrlActions routine, you may use **wndParam0** and **wndParam1** in the same way as in the window proc (see above). If you only use one instance of a custom control, you may alternatively define the control's event behavior in the parent windows's window proc.

2.3 Menus

In GUI64, any window may possess a menubar. This is indicated in the window bits (**BIT_WND_HASMENU**). In the WIN version of GUI64, the menubar is placed inside the window right below the title bar, while it is placed in the system bar at the top of the screen in the MAC version. Therefore, if a window possesses a menubar, its height in the WIN version should be one unit larger than in the MAC version to display the same content. The programmer can take care of this by using the API call **GUI_GetDesign**.

A menubar is in fact a control whose control index should always be zero. As its position is not relevant, the xPos and yPos values in the control information data are used as a pointer to a list of 16-bit pointers to drop-down menus. Each drop-down menu is defined as a structure of the following form:

- menu ID, maximal string length of menu items, number of menu items, list of null-terminated strings

Menu IDs start at **10**.

Here is an example from the demo app *Sweepy*:

```
; Constants
ID_MENU_GAME = 10
ID_MENU_HELP = 11
...
...
...
; Control definition
!byte CT_MENUBAR, <MSMenubar, >MSMenubar, 0, 0
!pet 0
...
...
...
; Definition of menu bar
MSMenubar       !word Menu_MS_Game, Menu_MS_Help
Str_MSMenubar   !pet "Game",0,"?",0
; Definition of menus
; Format: ID, max_str_len, item_count, StringList
Menu_MS_Game    !pet ID_MENU_GAME,4,2,"New",0,"Quit",0
Menu_MS_Help    !pet ID_MENU_HELP,5,1,"About",0
```

2.4 Dialogs

A dialog in GUI64 is a window which sits on top of all other windows and which cannot be minimized, maximized, nor resized. Moreover, a dialog window has the complete focus. That is, if a dialog window is shown, the user can only make clicks inside this very window. All other actions are ignored. When a dialog is shown, the program mode (**ProgramMode**) is set to **PM_DIALOG** (= **$ff**).

There are three system dialogs an app can use:

Dialog	API Call	Purpose
Message box	**GUI_ShowMessage**	Show single- or multi-line message text with an OK button
Error message box	**GUI_ShowErrorMsg**	Same as message box, but with title "Error"
Yes-No dialog	**GUI_ShowYesNoDlg**	Show single- or multi-line message text with Yes and No buttons. Title of dialog has to be provided. Has a return value


Custom Dialogs


An app may define its own dialogs. To create a dialog, first create a window by calling **GUI_CreateWindow** or **GUI_CreateWindowEx** as documented above, optionally make any required adjustments to the controls, and then call **GUI_ShowWndAsDlg**. This displays the window on screen and causes GUI64 to treat it as a dialog. To close the current dialog, call **GUI_KillDialog**. If a dialog, thus created, is closed via a click in its title bar, GUI64 cares for the correct dialog kill.

3 Character set and Keyboard

3.1 The character sets

As most C64 software using character graphics mode, GUI64 uses a custom character set. The character sets of WIN and MAC design look as follows:





The bin files **charsXX_mac.bin** and **charsXX_win.bin** containing the character definitions can be found in the *Code* folder in the GUI64 GitHub repository **https://github.com/WebFritzi/GUI64**.

The 16 blue A's (indices 224 - 239) are at the same place in both designs. This area is reserved for custom characters defined by an app. An app registers new characters by calling **GUI_RegisterChars**. The address of the start of the blue A's area in the character set in memory is publicly available as the constant **APP_CHARSET** (see **gui64.inc.asm**). For writing directly into the charset area, the app should call **GUI_MapOutIO** first. When it has finished writing, it should call **GUI_MapInIO**. However, this should never be done in the IRQ handler.

3.2 Keyboard Input

A window's window proc can react on **EC_KEYPRESS** events. The keycode of the pressed key can then be found at the zero page address **actkey**(=**$53**). Whether the key is pressed together with **SHIFT** is indicated in the zeropage address **key_shifted**(=**$6b**). Its value is 1 if **SHIFT** is pressed and 0 if not. If information about more than just one key is needed, the app can call **GUI_GetPressedKeys** for up to three simultaneously held keys.

Keycode table

The following codes are returned in **actkey** and **GUI_GetPressedKeys** in **A**, **X**, and **Y**. They are translated GUI64 keycodes, not keyboard-matrix indices. WIN and MAC use the same translation tables. The unshifted column applies when **key_shifted**=0; the shifted column applies when **key_shifted**=1.

Key	Without SHIFT	With SHIFT
Letter keys A–Z	**$41–$5A**	**$61–$7A**
0	**$30**	**$30**
1	**$31**	**$21**
2	**$32**	**$22**
3	**$33**	**$23**
4	**$34**	**$24**

Key	Without SHIFT	With SHIFT
5	$35	$25
6	$36	$26
7	$37	$27
8	$38	$28
9	$39	$29
SPACE	$20	$20
+	$2B	$2B
-	$2D	$2D
*	$2A	$2A
/	$2F	$3F
=	$3D	$3D
,	$2C	$3C
.	$2E	$3E
:	$3A	$5B
;	$3B	$5D
@	$40	$40
Pound key (£)	$24	$24
Up-arrow key (↑)	$5E	$5E
Left-arrow key (←)	$5F	$5F
RETURN	$FC	$FC
DEL/INST	$FD	$FD
HOME/CLR	$F9	$F9
RUN/STOP	$F6	$F6
CRSR down/up	$FB	$FB
CRSR right/left	$F8	$F8
F1 / F2	$F1	$F1
F3 / F4	$F3	$F3
F5 / F6	$F5	$F5
F7 / F8	$F7	$F7
CTRL	$F4	$F4
Commodore key (C=)	$FA	$FA
No key / unused snapshot entry	$FF	$FF

The letter-code ranges increase alphabetically: A returns **$41** without SHIFT and **$61** with SHIFT, B returns **$42** or **$62**, and so on. The table gives the actual bytes returned by GUI64, including its mapping of the pound key to **$24**.

SHIFT does not occupy an entry in the returned key snapshot. Read **key_shifted** instead. In contrast, **CTRL** and the Commodore key have their own keycodes (**$F4** and **$FA**). Holding either key does not change the codes returned for other, simultaneously pressed keys. Call **GUI_GetPressedKeys** to detect, e.g., **CTRL + C**.

CRSR down and **up** share **$FB**; cursor right and left share **$F8**. Use **key_shifted** to distinguish the directions. Similarly, F2, F4, F6, and F8 use the codes of F1, F3, F5, and F7, respectively, with **key_shifted**=1. For example, F4 is reported as **$F3** with **SHIFT**, whereas **$F4** denotes **CTRL**. **RESTORE** is not part of the scanned keyboard matrix and is not returned by this API.

The public constants **KEYCODE_NONE** (**$FF**), **KEYCODE_RETURN** (**$FC**), **KEYCODE_CRSR_UD** (**$FB**), and **KEYCODE_CRSR_LR** (**$F8**) are defined in **gui64.inc.asm**.

4 Sprites and SID

In both designs, the mouse pointer always occupies sprites 0 and 1. While there are no further sprites used in the MAC design, the WIN design uses sprites 2, 3, 4, and 5 for the Commodore button and the highlighting in the CBM

'start' menu. Therefore, if an app wants to make extensive use of sprites, it should be written exclusively for the MAC design and shut down immediately if the user is trying to load it in the WIN design:

```
*=$b000
            jsr GUI_GetDesign
            bne +
            ldx #<Str_Mess
            ldy #>Str_Mess
            jmp GUI_ShowMessage
+           ...

Str_Mess    !pet "This app only works in the\MAC design of GUI64.",0
```

If an app is supposed to work with both designs, it should only use sprites 6 and 7.

As the VIC bank is in **$c000 - $ffff**, sprite definitions can be placed in the app area from **$c000** onwards. For saving app RAM space, an app may alternatively copy sprite definitions to the area **$de00 - $dfff**.

The event code EC_SHUTDOWN

When an app shuts down, the event code **EC_SHUTDOWN** is sent to the app's main window proc. If an app uses sprites, it should react to this event code by turning off the respective bits in **$D015**. Also, if an app plays music or sound effects via the **SID** chip, it should react to this event code by setting the SID volume register **$D418** to zero.

5 Frame and Timer API

5.1 Frame API

The frame API provides applications with a callback that is executed once per video frame[1]. It is intended for applications that require frame-synchronous processing, such as games, sprite animation or direct VIC-II effects.

The frame handler is called *directly from the GUI64 raster interrupt*. Consequently, the handler executes in interrupt context and must obey the corresponding restrictions.

The frame API consists of three routines:

- **GUI_SetFrameHandler** registers the application frame handler.
- **GUI_StartFrameHandling** enables frame callbacks.
- **GUI_StopFrameHandling** disables frame callbacks.

A typical setup is:

```
ldx #<FrameHandler
ldy #>FrameHandler
jsr GUI_SetFrameHandler
jsr GUI_StartFrameHandling
...
FrameHandler
; Short, frame-synchronous processing only.
rts
```

The frame handler must return with **rts**.

> **Warning:** The frame handler runs inside the raster IRQ. It must remain short and must not call general GUI64 window, control, dialog or repaint routines. Such routines are not guaranteed to be reentrant and may use GUI64 working memory that was already in use when the interrupt occurred.

GUI64 uses shared internal state including the current window and control structures as well as zero-page working pointers. Calling a non-IRQ-safe API routine from the frame handler could modify this state while an interrupted GUI64 routine still depends on it.

[1] When the GUI is repainting due to user input, frame handling is blocked.

Only API functions explicitly documented as IRQ-safe may therefore be called from a frame handler. In particular, routines that select or update controls, create or remove windows, repaint the GUI, display dialogs or manipulate GUI64 scratch pointers must not be called from frame context. As of *GUI64 API 1.0*, the following API routines are IRQ-safe:

- **GUI_GetDesign**
- **GUI_GetCurMenuID**
- **GUI_GetCSTMWindowColor**
- **GUI_GetCSTMDesktopColor**
- **GUI_GetScreenMem**
- **GUI_StopFrameHandling**
- **GUI_GetPressedKeys**

The application should also avoid lengthy calculations, blocking loops and other operations that could delay subsequent raster interrupts. A frame handler that runs for too long may disturb raster-sensitive GUI64 operations, including display and taskbar processing.

For work that does not require exact frame synchronization, the timer API or normal application event processing should be preferred.

If an app uses frame handling, it should react to the **EC_SHUTDOWN** event code in the main window proc by calling **GUI_StopFrameHandling**.

5.2 Timer API

The GUI64 timer provides applications with periodic callbacks at one-tenth-second intervals. The timer is based on the CIA time-of-day (TOD) clock.

Unlike the frame callback, the application timer handler is *not* executed directly from the raster interrupt. When a timer tick occurs, GUI64 records a timer event. The event is subsequently dispatched by the GUI64 main loop, where the registered application timer handler is called in normal application context.

This distinction is important: because the timer handler does not execute in interrupt context, it may use the regular GUI64 API, including window, control and repaint functions.

The timer API consists of three routines:

- **GUI_InitTimer** registers the application timer handler.
- **GUI_StartTimer** enables periodic timer events.
- **GUI_StopTimer** disables timer events.

A typical timer setup is:

```
ldx #<TimerHandler
ldy #>TimerHandler
jsr GUI_InitTimer
jsr GUI_StartTimer
...
TimerHandler
; Periodic application processing.
; Regular GUI64 API calls are allowed here.
rts
```

The timer handler should return with **rts**.

If an app uses the timer, it should react to the **EC_SHUTDOWN** event code in the main window proc by calling **GUI_StopTimer**.

> **Note:** Timer events are generated at one-tenth-second intervals, but the handler is executed by the GUI64 main loop. Its actual execution may therefore be delayed while GUI64 is processing another event or operation.

5.3 Timer and Frame Handler Comparison

Property	Timer handler	Frame handler
Execution context	GUI64 main loop	Raster IRQ
Callback rate	Every 1/10 second	Once per video frame
Raster synchronized	No	Yes
GUI64 API calls	Regular API calls are allowed	Only API-functions explicitly documented as IRQ-safe may be called
Typical use	Periodic application tasks, status updates and UI changes	Games, animation, and other frame-synchronous processing
Return instruction	`rts`	`rts`

Note: Use the timer API for ordinary periodic application work. Use the frame API only when processing must be synchronized with the video frame.

6 Public Jump Table

The public GUI64 API is exposed through a fixed jump table. Each entry consists of a three-byte `JMP` instruction that transfers control to the corresponding GUI64 routine. Applications should call these public entry points instead of internal GUI64 routines.

The table below lists all currently available public API entries, their fixed addresses, their functional group and a short description. More detailed information about parameters, return values and usage can be found in the following section.

Address	Entry point	Group	Purpose
`$5F00`	`GUI_CreateWindow`	Window	Create a window from a static window definition
`$5F03`	`GUI_CreateWindowEx`	Window	Create a window including the controls that follow the window definition
`$5F06`	`GUI_KillCurWindow`	Window	Remove the current window and its controls
`$5F09`	`GUI_StdWndProc`	Window	Run GUI64 standard window event processing
`$5F0C`	`GUI_IsInCurControl`	Control	Test whether the mouse position is inside the current control
`$5F0F`	`GUI_Repaint`	System	Repaint the entire GUI
`$5F12`	`GUI_GetDesign`	System	Return the active GUI64 design variant (WIN/MAC)
`$5F15`	`GUI_UpdateControl`	Control	Write the current static control structure back to the control heap
`$5F18`	`GUI_SelectCtrl_AddBits`	Control	Select a control, add bits, and update
`$5F1B`	`GUI_SetCtrlStringList`	Control	Assign a string-list pointer and number of strings to the current control
`$5F1E`	`GUI_SetCtrlString`	Control	Assign a string pointer to the current control
`$5F21`	`GUI_SelectControl`	Control	Select a control by its index
`$5F24`	`GUI_SelectControl0`	Control	Select control with index 0
`$5F27`	`GUI_SelectControl1`	Control	Select control with index 1
`$5F2A`	`GUI_SelectControl2`	Control	Select control with index 2
`$5F2D`	`GUI_SelectControl3`	Control	Select control with index 3
`$5F30`	`GUI_SelectControl4`	Control	Select control with index 4
`$5F33`	`GUI_UpdateWindow`	Window	Write the current static window structure back to the window heap
`$5F36`	`GUI_SetEditSLInfo`	Control	Set single-line edit control information
`$5F39`	`GUI_RegisterChars`	Application	Register up to 16 application-defined characters
`$5F3C`	`GUI_SetCtrlActionsRoutine`	Application	Register the application control-event routine for newly defined controls

Address	Entry point	Group	Purpose
$5F3F	GUI_SetPaintCtrlsRoutine	Application	Register the application control-paint routine for newly defined controls
$5F42	GUI_AddBufWidthToFD	Paint	Move paint cursor in $FD/$FE down by 1
$5F45	GUI_AddBufWidthTo02	Paint	Move color cursor in $02/$03 down by 1
$5F48	GUI_IsInCurMenu	Menu	Test whether the mouse position is inside the current menu
$5F4B	GUI_GetCurMenuID	Menu	Return the current menu ID
$5F4E	GUI_ShowMessage	Dialog	Show a message dialog box
$5F51	GUI_GetMousePosInWnd	Mouse	Update MousePosInWndX/Y with coordinates relative to the current window's control area
$5F54	GUI_GetCSTMWindowColor	System	Return the custom window color
$5F57	GUI_GetCSTMDesktopColor	System	Return the custom desktop color
$5F5A	GUI_StartTimer	Timer	Start the application timer; ticks are generated every 1/10 second
$5F5D	GUI_StopTimer	Timer	Stop the application timer
$5F60	GUI_InitTimer	Timer	Register the application timer handler address
$5F63	GUI_RepaintCurWindow GUI_CurWndToScreen	Window	Paint the current window
$5F66	GUI_FindWndByType	Window	Look for a window of window type in Param0
$5F69	GUI_SelectTopWindow	Window	Select window with handle in Param0 and makes it the top window
$5F6C	GUI_AddControl	Control	Add a control to the current window
$5F6F	GUI_SetFrameHandler	Frame	Register the frame handler address
$5F72	GUI_StartFrameHandling	Frame	Start frame handling
$5F75	GUI_StopFrameHandling	Frame	Stop frame handling
$5F78	GUI_MapOutIO	System	Make $d000 - $dfff RAM
$5F7B	GUI_MapInIO	System	Make $d000 - $dfff IO
$5F7E	GUI_GetScreenMem	System	Retrieve the high byte of the screen memory address in A
$5F81	GUI_PaintBox	Control	Paint a box inside a control
$5F84	GUI_ShowYesNoDlg	Dialog	Show a message box with yes and no button
$5F87	GUI_ShowErrorMsg	Dialog	Same as GUI_ShowMessage, but with title "Error"
$5F8A	GUI_SetModalAddress	Dialog	Set the modal address of Yes/No dialog
$5F8D	GUI_GetDialogResult	Dialog	Retrieve user decision upon Yes/No dialog
$5F90	GUI_ShowWndAsDlg	Dialog	Display created window as dialog on screen
$5F93	GUI_KillDialog	Dialog	Kill current dialog
$5F96	GUI_GetLBtnFirePressed	Input	Retrieve current state of left mouse button and fire
$5F99	GUI_CurWndRowToScreen	Window	Paint a certain row of the current window to screen
$5F9C	GUI_GetTopWindow	Window	Retrieve handle of topmost window
$5F9F	GUI_GetWndInfo	Window	Retrieve pointer to window information on heap
$5FA2	GUI_GetPaintBuf	Paint	Retrieve pointer to paint buffer
$5FA5	GUI_GetPressedKeys	Input	Retrieve currently pressed keys
$5FA8	GUI_BeginDiskIO	System	Use before KERNAL function calls
$5FAB	GUI_EndDiskIO	System	Use after KERNAL function calls
$5FAE	GUI_GetAppDevice	Application	Retrieve device number of drive from which the app has been run
$5FB1	GUI_SelectWindow	Window	Select window with handle in Param0

7 Documentation of API Calls

7.1 Window API

GUI_CreateWindow $5F00

Creates a window without controls.

INPUT

Reg.	Value	Meaning
X	address low	Low byte of the static window-definition table
Y	address high	High byte of the static window-definition table

OUTPUT

Reg.	Meaning
res (=$96)	A value of 0 indicates an error

The window-definition table should contain the bytes: window type, bits, xPos, yPos, width, height, pointer to title string, and pointer to window proc.

```
    ldx #<Wnd_Data
    ldy #>Wnd_Data
    jsr GUI_CreateWindow
    ...
    Wnd_Data !byte WT_MyWnd, %00100001,11,2,11,15, <Str_Title, >Str_Title, <MyWndProc, >MyWndProc
```

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z, V may change; I, D are preserved.
In the MAC design, V is also preserved

GUI_CreateWindowEx $5F03

Creates a window with controls.

INPUT

Reg.	Value	Meaning
X	address low	Low byte of the static window-definition table
Y	address high	High byte of the static window-definition table

OUTPUT

Reg.	Meaning
res (=$96)	A value of 0 indicates an error

The window-definition table should contain the bytes: window type, bits, xPos, yPos, width, height, pointer to title string, and pointer to window proc, followed by the static control data and a termination zero byte.

```
    ldx #<Wnd_Data
    ldy #>Wnd_Data
    jsr GUI_CreateWindowEx
    ...
    Wnd_Data !byte WT_MyWnd, %00100001,11,2,11,15, <Str_Title, >Str_Title, <MyWndProc, >MyWndProc
             ; Controls list
             !byte CT_MENUBAR, <Menubar, >Menubar, 0, 0
```

```
            !pet 0
            !byte CT_LABEL, 1, 1, 11, 1
            !pet "Hello world",0
            !byte CT_BUTTON, 6, 0, 5, 3
            !pet " OK ",0
            ; termination zero byte
            !byte 0
```

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

GUI_KillCurWindow $5F06

Removes the current window and its controls from window and control heap.

> **Warning:** This call uses multiple GUI64 zero-page scratch locations. Do not keep an application pointer in temporary GUI64 zero-page storage across this call.

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V**, **I**, **D** may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of **I** and **D** depends on the callback.

GUI_StdWndProc $5F09

Runs the standard GUI64 window proc: updates the mouse position relative to the current window and then dispatches standard behavior for mouse, joystick and keyboard events.

> This routine should be called in each window proc.

```
MyWndProc   jsr GUI_StdWndProc

            ; application-specific processing follows
            rts
```

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V**, **I**, **D** may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of **I** and **D** depends on the callback.

GUI_UpdateWindow $5F33

Copies the 16-byte static current-window structure in **$10 - $1f** to the window heap.

```
    lda #20
    sta WindowWidth
    jsr GUI_UpdateWindow
```

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

GUI_RepaintCurWindow or GUI_CurWndToScreen $5F63

Repaints the current window on screen.

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z, V, I, D may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of I and D depends on the callback.

GUI_FindWndByType $5F66

Looks for a window of window type specified in Param0.

OUTPUT

Result	Meaning
Carry set	Window found
Carry clear	Window not found

If found, the handle of the window is in X.

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z, V may change; I, D are preserved.

GUI_SelectTopWindow $5F69

Selects window with handle in Param0 and makes it the topmost window.

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z may change; V, I, D are preserved.

GUI_CurWndRowToScreen $5F99

Paints row with row number in A of the current window onto the screen. $fd/$fe and $02/$03 should point to the start of the row in the paint and color buffer, respectively.

INPUT

Reg.	Meaning
A	Number of row
$fd/$fe	Pointer to start of row in paint buffer
$02/$03	Pointer to start of row in color buffer

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z, V may change; I, D are preserved.

GUI_GetTopWindow $5F9C

Retrieves the handle of the topmost window in A.

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_GetWndInfo $5F9F

Retrieves a heap-pointer to the window information structure of a window.

INPUT

Reg.	Meaning
A	Window handle ID

OUTPUT

Reg.	Meaning
$fb/$fc	Pointer to window information structure

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: C, N, Z may change; V, I, D are preserved.

GUI_SelectWindow $5FB1

Selects window with handle in Param0.

CLOBBERS

Registers: A, Y may change; X is preserved.
Flags: C, N, Z may change; V, I, D are preserved.

7.2 Control API

GUI_UpdateControl $5F15

Copies the 16-byte static current-control structure in $20 – $2f to the control heap.

```
    lda #CL_WHITE
    sta ControlColor
    jsr GUI_UpdateControl
```

CLOBBERS

Registers: A, Y may change; X is preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_IsInCurControl $5F0C

Checks whether MousePosInWndX/Y lies inside the current control.

OUTPUT

Result	Meaning
Carry set	Mouse is inside the current control
Carry clear	Mouse is outside the current control

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: C, N, Z, V may change; I, D are preserved.
C is the Boolean result documented above.

GUI_SelectCtrl_AddBits $5F18

Selects control (see **GUI_SelectControl**) with index in **Y** and adds the control bits in **A**. Also updates the control.

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

GUI_SetCtrlStringList $5F1B

Assigns a string-list address and its item count to the current control, then updates the heap entry. Hence, no **GUI_UpdateControl** call necessary.

INPUT

Reg.	Value	Meaning
A	count	Number of strings in the list
X	address low	String-list address, low byte
Y	address high	String-list address, high byte

```
    jsr GUI_SelectControl0
    ldx #<Str_Menu
    ldy #>Str_Menu
    lda #2
    jsr GUI_SetCtrlStringList
```

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

GUI_SetCtrlString $5F1E

Assigns a string address to the current control and updates the heap entry. Hence, no **GUI_UpdateControl** call necessary.

INPUT

Reg.	Value	Meaning
X	address low	String address, low byte
Y	address high	String address, high byte

```
    ldx #<Str_Label
    ldy #>Str_Label
    jsr GUI_SetCtrlString
```

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

GUI_SelectControl $5F21

Selects a control by index and loads its heap entry into the static control structure in **$20 - $2f**.

INPUT

Reg.	Value
A	Control index

```
    lda #5
    jsr GUI_SelectControl
```

The convenience entries **GUI_SelectControl0** through **GUI_SelectControl4** select indices 0 through 4 without requiring the index in **A**. The register and flag effects below also apply to these convenience entries.

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

GUI_SetEditSLInfo $5F36

Call after creation of a single-line edit control (**CT_EDIT_SL**). Sets the caret position and maximum input length of the currently selected edit control. Updates the control.

INPUT

Reg.	Meaning
A	Zero-based caret position: 0 places the caret before the first character
X	Maximum number of characters the user may enter

CLOBBERS

Registers: **A**, **Y** may change; **X** is preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

GUI_AddControl $5F6C

Adds a control to the current window and selects it.

INPUT

Reg.	Value	Meaning
X	address low	Control information data, low byte
Y	address high	Control information data, high byte

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

GUI_PaintBox $5F81

Draws a box covering the currently selected control in GUI64's paint buffer. Returns pointers to the control's position in the paint buffer in **$fd/$fe** and in the color buffer in **$02/$03**.

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

7.3 Application API

GUI_RegisterChars $5F39

Copies application-defined character data into the application-character area in the GUI64 character set.

INPUT

Reg.	Value	Meaning
A	1–16	Number of characters
X	address low	Character table address, low byte
Y	address high	Character table address, high byte

Values of 17 or greater are rejected by returning without copying.

```
    ldx #<CharList
    ldy #>CharList
    lda #14
    jsr GUI_RegisterChars
```

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z may change; V, I, D are preserved.

GUI_SetCtrlActionsRoutine $5F3C

Registers the application routine that handles events for application-defined controls.

INPUT

Reg.	Value	Meaning
X	address low	Handler address, low byte
Y	address high	Handler address, high byte

Once the program pointer enters the provided actions routine, the X register is the control type.

```
    ldx #<MyCtrlAction
    ldy #>MyCtrlAction
    jsr GUI_SetCtrlActionsRoutine
```

CLOBBERS

Registers: A, X, Y are preserved.
Flags: All processor flags (C, N, Z, V, I, D) are preserved.

GUI_SetPaintCtrlsRoutine $5F3F

Registers the application routine used to paint application-defined controls.

INPUT

Reg.	Value	Meaning
X	address low	Paint routine address, low byte
Y	address high	Paint routine address, high byte

Once the program pointer enters the provided paint routine, the **X** register is the control type. Moreover, **$fd/$fe** points to the position of the control in the paint buffer, and **$02/$03** points to the position in the color buffer.

```
    ldx #<MyCtrlPaintRoutine
    ldy #>MyCtrlPaintRoutine
    jsr GUI_SetPaintCtrlsRoutine
```

CLOBBERS

Registers: **A**, **X**, **Y** are preserved.
Flags: All processor flags (**C**, **N**, **Z**, **V**, **I**, **D**) are preserved.

GUI_GetAppDevice $5FAE

Returns the device number of the drive the app was loaded from in **A**.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

7.4 Timer API

GUI_InitTimer $5F60

Registers the application's timer handler.

INPUT

Reg.	Value	Meaning
X	address low	Timer-handler address, low byte
Y	address high	Timer-handler address, high byte

```
    ldx #<MyTimerHandler
    ldy #>MyTimerHandler
    jsr GUI_InitTimer
```

CLOBBERS

Registers: **A**, **X**, **Y** are preserved.
Flags: All processor flags (**C**, **N**, **Z**, **V**, **I**, **D**) are preserved.

GUI_StartTimer $5F5A

Starts the application timer. GUI64 generates timer events at one-tenth-second granularity from the CIA TOD clock.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z** may change; **V**, **I**, **D** are preserved.

GUI_StopTimer $5F5D

Stops the application timer.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

7.5 Frame API

GUI_SetFrameHandler $5F6F

Registers the application's frame handler.

INPUT

Reg.	Value	Meaning
X	address low	Frame-handler address, low byte
Y	address high	Frame-handler address, high byte

```
    ldx #<MyFrameHandler
    ldy #>MyFrameHandler
    jsr GUI_SetFrameHandler
```

CLOBBERS

Registers: A, X, Y are preserved.
Flags: All processor flags (C, N, Z, V, I, D) are preserved.

GUI_StartFrameHandling $5F72

Starts frame handling.

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_StopFrameHandling $5F75

Stops frame handling.

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

7.6 System API

GUI_Repaint $5F0F

Repaints the entire GUI.

CLOBBERS

Registers: A, X, Y may change.
Flags: C, N, Z, V, I, D may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of I and D depends on the callback.

GUI_GetDesign $5F12

Determines the currently used GUI64 design.

OUTPUT zero flag (Z=1 (beq): WIN, Z=0 (bne): MAC)

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_GetCSTMWindowColor $5F54

OUTPUT

Reg.	Value
A	Standard window color

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_GetCSTMDesktopColor $5F57

OUTPUT

Reg.	Value
A	Standard desktop color

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_MapOutIO $5F78

Declares $D000 - $DFFF as RAM. The app then has access to the character set in $D000 - $D7FF and sprites in $DE00 - $DFFF.

CLOBBERS

Registers: X may change; A, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_MapInIO $5F7B

Should be called after a call to GUI_MapOutIO. Declares $D000 - $DFFF as IO area.

CLOBBERS

Registers: X may change; A, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_GetScreenMem $5F7E

Returns the high byte of the screen memory address in A. The low byte is always $00.

CLOBBERS

Registers: A may change; X, Y are preserved.
Flags: N, Z may change; C, V, I, D are preserved.

GUI_BeginDiskIO $5FA8

Call before making (disk IO) calls to the KERNAL. It stops the system IRQ, maps the KERNAL in, and renders a "fake taskbar" on screen in the WIN design.

CLOBBERS

Registers: WIN: A, X may change; Y is preserved. MAC: A may change; X, Y are preserved.
Flags: WIN: C, N, Z, V may change. MAC: N, Z may change; C, V are preserved. Both designs return with

I=0 and preserve **D**.

GUI_EndDiskIO $5FAB

Sets GUI64 back into its default state (KERNAL mapped out, system IRQ running, taskbar in WIN design).

CLOBBERS

Registers: WIN: **A**, **X**, **Y** may change. MAC: **A** may change; **X**, **Y** are preserved.
Flags: WIN: **C**, **N**, **Z**, **V**, **D** may change; the taskbar clock code may clear **D**. MAC: **N**, **Z** may change; **C**, **V**, **D** are preserved. Both designs return with **I**=0.

7.7 Menu and Mouse API

GUI_IsInCurMenu $5F48

Updates the mouse-position snapshot and tests whether the mouse is inside the currently displayed menu. Returns **C**=1 if inside and **C**=0 otherwise.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.
C=1 means inside the current menu; **C**=0 means outside.

GUI_GetCurMenuID $5F4B

OUTPUT

Reg.	Value
A	Menu ID

```
                jsr GUI_GetCurMenuID
                cmp #ID_MENU_GAME
                beq GameMenuClicked
                ...
                ...
GameMenuClicked lda CurMenuItem
                beq NewGameClicked
                jmp Exit
```

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

GUI_GetMousePosInWnd $5F51

Updates **MousePosInWndX** and **MousePosInWndY** with coordinates relative to the area of the current window in which controls are placed.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

7.8 Dialog API

GUI_ShowMessage $5F4E

Shows a message dialog box with text in **Addr(X/Y)**, an OK button below it, and "Info" in the titlebar. The text is placed in a multi-line label (**CT_LABEL_ML**). Line feeds are indicated by the backslash symbol (**$1c** in memory).

```
          ldx #<MyMessage
          ldy #>MyMessage
          jsr GUI_ShowMessage
          ...
MyMessage !pet "I am an info box.\Just click OK.",0
```

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V**, **I**, **D** may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of **I** and **D** depends on the callback.

GUI_ShowErrorMsg $5F87

Same as **GUI_ShowMessage**, but with the title "Error".

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: **C**, **N**, **Z**, **V**, **I**, **D** may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of **I** and **D** depends on the callback.

GUI_ShowYesNoDlg $5F84

Shows a message box dialog with two buttons (Yes and No) and text in **Addr(X/Y)**. The string in the title bar has to be specified as a pointer in **$fd/$fe**.
Before the call, the app has to specify an address the program counter should jump to after the user's decision. For this, use **GUI_SetModalAddress** (see below). In the respective routine, the app retrieves the user's decision via **GUI_GetDialogResult** (see below).

```
           ldx #<ModalAddr
           ldy #>ModalAddr
           jsr GUI_SetModalAddress
           lda #<MyTitle
           sta $fd
           lda #>MyTitle
           sta $fe
           ldx #<MyQuestion
           ldy #>MyQuestion
           jmp GUI_ShowYesNoDlg
           ...
ModalAddr  jsr GUI_GetDialogResult
           bne yes
           ; user chose no
           ...
yes        ; user chose yes
           ...
           ...
MyQuestion !pet "Do you want this?",0
MyTitle    !pet "String in title bar",0
```

CLOBBERS

Registers: **A**, **X**, **Y** may change.

Flags: `C`, `N`, `Z`, `V`, `I`, `D` may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of `I` and `D` depends on the callback.

GUI_SetModalAddress $5F8A

Specifies the (modal) address in `Addr(X,Y)`, the program counter should jump to after the user's decision in Yes/No dialog.

INPUT

Reg.	Meaning
`X`	Lobyte of modal address
`Y`	Hibyte of modal address

CLOBBERS
Registers: `A`, `X`, `Y` are preserved.
Flags: All processor flags (`C`, `N`, `Z`, `V`, `I`, `D`) are preserved.

GUI_GetDialogResult $5F8D

Retrieves the user's decision upon question in Yes/No dialog.

OUTPUT zero flag (`Z`=1 (`beq`): No, `Z`=0 (`bne`): Yes)

CLOBBERS
Registers: `A` may change; `X`, `Y` are preserved.
Flags: `N`, `Z` may change; `C`, `V`, `I`, `D` are preserved.

GUI_ShowWndAsDlg $5F90

Sets `ProgramMode` to `PM_DIALOG` and shows the dialog (current window) on screen. The dialog window needs to be created before.

CLOBBERS
Registers: `A`, `X`, `Y` may change.
Flags: `C`, `N`, `Z`, `V`, `I`, `D` may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of `I` and `D` depends on the callback.

GUI_KillDialog $5F93

Kills the dialog (current window) and sets `ProgramMode` back to `PM_NORMAL`.

CLOBBERS
Registers: `A`, `X`, `Y` may change.
Flags: `C`, `N`, `Z`, `V`, `I`, `D` may change.
May invoke application callbacks. The GUI64 wrapper does not save and restore their processor status; in particular, preservation of `I` and `D` depends on the callback.

7.9 Input API

GUI_GetLBtnFirePressed $5F96

Retrieves the state of left mouse button and joystick fire button in `A`. The output in `A` is a flagged byte.

OUTPUT

Bit	Meaning
0	Left mouse button
1	Joystick fire button

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z** may change; **V**, **I**, **D** are preserved.

GUI_GetPressedKeys $5FA5

Retrieves a snapshot of up to three currently held keys. Returns **A**/**X**/**Y** in keyboard scan priority, unused entries are **$ff**. Code in **A** matches actkey. SHIFT is not an entry. Instead, read **key_shifted**.

OUTPUT Currently pressed keys in **A**/**X**/**Y**

CLOBBERS

Registers: **A**, **X**, **Y** may change.
Flags: All processor flags (**C**, **N**, **Z**, **V**, **I**, **D**) are preserved.
All processor flags are restored, including **I**; **N** and **Z** do not describe any returned keycode.

7.10 Paint API

GUI_GetPaintBuf $5FA2

Retrieves a pointer in **Addr(X/Y)** to GUI64's paint buffer. Adding **$0400** to this address yields the color buffer's address.

OUTPUT

Reg.	Meaning
X	LoByte of address
Y	HiByte of address

CLOBBERS

Registers: **X**, **Y** may change; **A** is preserved.
Flags: **N**, **Z** may change; **C**, **V**, **I**, **D** are preserved.

The following public entries expose GUI64 pointer arithmetic. They are useful for custom controls, but unlike higher-level calls they operate on GUI64's scratch pointers directly.

GUI_AddBufWidthToFD $5F42

Adds **BufWidth** to the paint-buffer pointer in **$fd/$fe**, advancing it by one buffer row.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

GUI_AddBufWidthTo02 $5F45

Adds **BufWidth** to the color-buffer pointer in **$02/$03**, advancing it by one buffer row.

CLOBBERS

Registers: **A** may change; **X**, **Y** are preserved.
Flags: **C**, **N**, **Z**, **V** may change; **I**, **D** are preserved.

Warning: These pointers are GUI64 working storage. Their contents are not preserved by unrelated GUI calls.

8 Hello World Application

The following application shows a window with a label displaying the text *Hello World*.

```
!source "gui64.inc.asm"

WT_MYWINDOW = 50

*=$b000
                ldx #<MyWindow
                ldy #>MyWindow
                jmp GUI_CreateWindowEx

MyWndProc       jmp GUI_StdWndProc

MyWindow        !byte WT_MYWINDOW,BIT_WND_CANMINIMIZE,5,5,15,10
                !word Str_Title,MyWndProc
                !byte CT_LABEL,1,1,11,1
                !pet "Hello World",0
                ; Termination zero byte
                !byte 0
Str_Title       !pet "Hi",0
```