Pushing to Multiple Remote Repositories Using Git

When using Git for version control, many people use <u>GitHub</u> as a place to hold remote repositories, and push their repositories there. I recently started using <u>BitBucket</u> also, and wanted to be able to simultaneously update my GitHub and BitBucket repositories when changes were made.

To begin, rename your current remote (most likely named *origin*) to a different name. I'd rename this to the name of the service you are using, such as *github* or *bitbucket*.

```
git remote rename origin github
```

You can then add the remote for your second remote repository, in this case, a BitBucket repository.

```
git remote add bitbucket git@bitbucket
.org:username/example.git
```

Afterwards, you'll want to set up your *origin* remote to push to both of these. Issue the following command:

```
qit confiq -e
```

You will be greeted with your Git configuration (most likely using vim). Add the [remote

"origin"] section to the bottom of the file with the URLs from each remote repository you'd like to push to.

.git/config

```
[core]
  repository format version = 0
  filemode = true
 bare = false
  logallrefupdates = true
  ignorecase = true
 precomposeunicode = false
[branch "master"]
  remote = github
 merge = refs/heads/master
[remote "github"]
 url = git@github.com:username/repo.g
it
  fetch = +refs/heads/*:refs/remotes/g
ithub/*
[remote "bitbucket"]
```

```
url = git@bitbucket.org:username/rep
o.git
    fetch = +refs/heads/*:refs/remotes/b
itbucket/*
[remote "origin"]
    url = git@github.com:username/repo.g
it
    url = git@bitbucket.org:username/rep
o.git
```

You can then push to both repositories by issuing:

```
git push origin master
```

Or to a single one by issuing either of these commands:

```
git push github master git push bitbucket master
```