Quick Links



Online Demo



Download



FAQ



Latest Docs



Ask a
Question



Report a Bug



Screenshots

This page in other versions: <u>Latest</u> (4.19) | 4.18 | 4.17 | 3.6 | 2.1 | 1.6 | <u>Development</u>

pgAdmin 4 4.19 documentation » Creating or Modifying a Table » previous | next | index

Warning: This documentation is for a pre-release version of pgAdmin 4


Contents

- Primary key Dialog
 - Example
- Getting Started
- Connecting To A Server
- Managing Cluster Objects
- Managing Database Objects
- Creating or Modifying a Table
 - Check Dialog
 - Column Dialog
 - Compound Trigger Dialog
 - Exclusion Constraint Dialog
 - Foreign key Dialog
 - Index Dialog
 - Primary key Dialog
 - Rule Dialog
 - Table Dialog
 - Trigger Dialog
 - Unique Constraint Dialog
- Management Basics
- Backup and Restore
- <u>Developer Tools</u>
- pgAgent
- pgAdmin Project Contributions
- Release Notes
- Licence

Primary key Dialog ¶

Use the *Primary key* dialog to create or modify a primary key constraint. A primary key constraint indicates that a column, or group of columns, uniquely identifies rows in a table. This requires that the values in the selected column(s) be both unique and not null.


The *Primary key* dialog organizes the development of a primary key constraint through the *General* and *Definition* tabs. The *SQL* tab displays the SQL code generated by dialog selections.



Use the fields in the *General* tab to identify the primary key:

• Use the *Name* field to add a descriptive name for the primary key constraint. The name will be displayed in the *pgAdmin* tree control.

Click the *Definition* tab to continue.



Use the fields in the *Definition* tab to define the primary key constraint:

• Click inside the *Columns* field and select one or more column names from the drop-down listbox. To delete a selection, click the *x* to the left of the column name. The primary key constraint should be different from any unique constraint defined for the same table; the selected column(s) for the constraints must be distinct.


- Use *Include columns* field to specify columns for *INCLUDE* clause of the index. This option is available in Postgres 11 and later.
- Select the name of the tablespace in which the primary key constraint will reside from the drop-down listbox in the *Tablespace* field.
- Select the name of an index from the drop-down listbox in the *Index* field. This field is optional. Adding a primary key will automatically create a unique B-tree index on the column or group of columns listed in the primary key, and will force the column(s) to be marked NOT NULL.
- Use the *Fill Factor* field to specify a fill factor for the table and index. The fill factor for a table is a percentage between 10 and 100. 100 (complete packing) is the default.
- Move the *Deferrable?* switch to the *Yes* position to specify the timing of the constraint is deferrable and can be postponed until the end of the statement. The default is *No*.
- If enabled, move the *Deferred?* switch to the *Yes* position to specify the timing of the constraint is deferred to the end of the statement. The default is *No*.

Click the SQL tab to continue.

Your entries in the *Primary key* dialog generate a SQL command (see an example below). Use the *SQL* tab for review; revisit or switch tabs to make any changes to the SQL command.

Example ¶

The following is an example of the sql command generated by user selections in the *Primary key* dialog:



The example shown demonstrates creating a primary key constraint named *dept_pkey* on the *dept_id* column of the *dept* table.

- Click the *Info* button (i) to access online help.
- Click the Save button to save work.
- Click the Cancel button to exit without saving work.
- Click the *Reset* button to restore configuration parameters.