

Basic Auton FAR: LEAVE + PARK (WMS Irondogs)

Robot's BACK against the audience wall (Red) / far wall (Blue). OpModes: "Basic Auton RED FAR" and "Basic Auton BLUE FAR".




SET UP

BACK against the wall



YES: back on the wall



NO: side on the wall

RED:
tile B1, BACK touching the AUDIENCE wall, FRONT facing the FAR wall

BLUE:
tile E6, BACK touching the FAR wall, FRONT facing the AUDIENCE

Same as the SET UP line on the INIT screen

Filled box = START (arrow = FRONT, black bar = BACK on the wall). Numbered circles = waypoints. Dashed box = where it PARKS.
Robot size used: 17.98 x 15.99 in (BasicAuton.ROBOT_LENGTH_IN / ROBOT_WIDTH_IN). Blue = Red rotated 180° (decision 011).
HIVE: the UP CELLS shown are at MATCH START (Red: audience side, Blue: far side). Every TIP flips which CELL is up.

The steps (from BasicAuton.java, in inches)

Step	RED x, y, heading	BLUE x, y, heading	What happens
Start	-63.01, 36, 0°	63.01, -36, 180°	Robot set up here. Nothing moves during INIT
1	-48, 40, 0°	48, -40, 180°	LEAVE: drive forward, off the audience wall
2	24, 40, 0°	-24, -40, 180°	drive up column B, clear of the HIVE (column C, y < 24)
3	24, 60, 0°	-24, -60, 180°	PARK: slide left into the AUDIENCE third of the LOADING ZONE

Test log: 5 good runs in a row = ready for competition

Run	Red / Blue	Delay (s)	Parked? (Y/N)	Lights	Time (s)	Notes (overshoot, short, bumped...)
1						
2						
3						
4						
5						