

Infor M3

Outbound BOD Mapping and Descriptions

Copyright © 2023 Infor

All rights reserved.

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor M3

Publication Date: May 26, 2023

Version: 16.0.0.0

List of Nouns

AccountingBookDefinition

AccountingChart
AccountingEntity
AccountingJournal
AdvanceShipNotice

AssetMaster
AssetTransaction
BillOfMaterials
BillOfResources
BillToPartyMaster
CarrierParty
Catalog

ChartOfAccounts CodeDefinition

ConfiguredAssetMaster

ContactMaster Contract CreditTransfer

CurrencyExchangeRateMaster

CurrencyRateType
CustomerPartyMaster
CustomerReturn
DebitTransfer
FinancialCalendar

FinancialCalendar FinancialPartyMaster InspectDelivery InspectionOrder

InventoryAdjustment InventoryCount InventoryHold

InventoryHold Invoice ItemMaster LCLTaxReport

LCLTradeStatistics

Location

M3EDIAdvanceShipNotice

M3EDICarrierRoute M3EDIInventoryCount

M3EDIIIveilloryCol M3EDIInvoice M3EDIPickList

M3EDIPriceList

M3EDIPurchaseOrder

M3EDIRemittanceAdvice

M3EDISalesOrder M3EDIShipment

PayableTransaction PayFromPartyMaster

Person

ProductionOrder ProjectMaster

Promotion

PulseAlert

PulseNotification

PulseTask

PurchaseOrder

QualitySpecification

QualityTestMaster

Quote

ReceivableTransaction

ReceiveDelivery RemittanceAdvice RemitToPartyMaster Requisition SalesOrder

SecurityPermissionMaster

SecurityRoleMaster

ServiceOrder

ShipFromPartyMaster

Shipment

ShipToPartyMaster

SourceSystemGLMovement SourceSystemJournalEntry

SupplierInvoice SupplierPartyMaster

Transfer Workflow

AccountingBookDefinition

AccountingBookDefinition/DocumentID/ID	
CMNDIV.CCCONO CMNDIV.CCDIVI.; / @variationID	The field indicates the company and division, displayed as CONO_DIVI.
	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field indicates the logical ID of the system that is SOR for this noun instance.
AccountingBookDefinition/LastModificationDateTime CSYTAB.CTLMTS; /	The field indicates the date and time the object was last modified.
AccountingBookDefinition/LastModificationPerson/IDs/ID CSYTAB.CTCHID; /	The field indicates the ID of the person that entered/changed the recored.
@accountingEntity CSYTAB.CTCONO CSYTAB.CTDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
AccountingBookDefinition/DocumentDateTime CSYTAB.CTRGDT CSYTAB.CTRGTM.; /	The field indicates the date and time the object was created.
AccountingBookDefinition/Description CMNDIV.CCCONM; MNS100MI/GetBasicData	The field indicates the description.
AccountingBookDefinition/Name CMNDIV.CCTX15; MNS100MI/GetBasicData	The field indicates the name of the company.
AccountingBookDefinition/AccountingChartReference/ID CSYTAB.CTSTCO; CRS175MI/GetGeneralCode	The field indicates the Accounting Chart reference ID.
AccountingBookDefinition/AccountingChartReference/Name CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the AccountingChart name.
AccountingBookDefinition/FinancialCalendarReference/DocumentII	D/ID Set to "Financial Calendar".
AccountingBookDefinition/FinancialCalendarReference/Name	Set to "Financial Calendar".
AccountingBookDefinition/CurrencyCode CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the currency code.

AccountingChart

AccountingChart/IDs/ID	The field indicates the AssociatingChartStandard
@accountingEntity	The field indicates the AccountingChartStandard.
CSYTAB.CTCONO CSYTAB.CTDIVI.CTCONO	The field indicates the company and division.
CTDIVI; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760 AAA
@variationID	~ _
	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field in director the leasted ID of the constant that is CODY . W.
	The field indicates the logical ID of the system that is SOR for this noun instance.
AccountingChart/Status/Code	
@lietD	Set to 'Open'.
@listID	Set to 'AccountingChartStatus'.
AccountingChart/Name	
·	The field indicates the combination of <accountingentity>-AccountingChartStandard.</accountingentity>
	E.g 760 AAA-AccountingChartStandard
AccountingChart/AccountDisplayLength	
	The field indicates the AccountDisplayLength. Set to '10'
AccountingChart/DimensionSequence/SequencedDimension @sequence	
	The field indicates '1' to '7' (Dimension numbers).
AccountingChart/DimensionSequence/SequencedDimension/ListID CSYTAB.CTPARM; CRS175MI/GetGeneralCode	The field indicates the name for a specific accounting dimension.
AccountingChart/DimensionProfileSet/ID	
	The field set to 'DimensionProfileSetStandard'.
AccountingChart/DimensionProfileSet/DimensionProfile/ID	The field act to 'Dimension Profile Standard'
Accounting Chart/Dimension Profile Set/Dimension Profile/Dimension II	The field set to 'DimensionProfileStandard'.
AccountingChart/DimensionProfileSet/DimensionProfile/DimensionU CSYTAB.CTPARM; CRS175MI/GetGeneralCode	The field indicates the name for a specific accounting dimension.
	difference are manually a specime accounting difference.

AccountingChart/DimensionProfileSet/DimensionProfile/DimensionUsage/Usage The field is set to 'Optional'.

AccountingEntity

Accounting Entity/IDs/ID	
AccountingEntity/IDs/ID CMNDIV.CCCONO CMNDIV.CCDIVI.; MNS100MI/GetBasicData	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760_AAA
@variationID	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field indicates the logical ID of the system that is SOR for this noun instance.
AccountingEntity/LastModificationDateTime CMNDIV.CCLMTS; /	The field indicates when the record was last modifed in M3.
AccountingEntity/LastModificationPerson/IDs/ID CMNDIV.CCCHID; / @accountingEntity	The field indicates the user id who last modified the record in M3.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity.
AccountingEntity/DocumentDateTime CMNDIV.CCRGDT CMNDIV.CCRGTM.; /	The field indicates the date and time the record was created in M3.
AccountingEntity/Description CMNDIV.CCCONM; MNS100MI/GetBasicData	The field indicates the description of the M3 division.
AccountingEntity/Status/Code @listID	The field indicates the status. It is set to "Open".
AccountingEntity/Name	The field indicates the listID. It is set to "Generic Status".
CMNDIV.CCCONM; MNS100MI/GetBasicData	The field indicates the description of the M3 division.
AccountingEntity/ShortName CMNDIV.CCTX15; MNS100MI/GetBasicData	The field indicates the short name of the M3 division.
AccountingEntity/TaxID CMNDIV.CCVRNO; MNS100MI.GetBasicData CMNDIV.CCVRNL; MNS100MI.GetBasicData CMNDIV.CCCORG; MNS100MI.GetBasicData CMNDIV.CCCOR2; MNS100MI.GetBasicData XRUDIV.CCXIN2; CRRU01MI.GetDivisionRU XRUDIV.CCXKP2; CRRU01MI.GetDivisionRU.; /	If Country version (CSVN) is not FR or RU: Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". Tax declartion numner (VRNL) is displayed with @schemeName="TaxDeclarationNumber". Organization number 1 (CORG) is displayed with @schemeName="CountryIdentificationNumber". Organization number 2 (COR2) is displayed with @schemeName="CountryIdentificationNumber". If Country version (CSVN) is FR: Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". Tax declartion numner (VRNL) is displayed with @schemeName="CountryIdentificationNumber". If Country version (CSVN) is RU: INN code (XIN2) is displayed with @schemeName="TaxIdentificationNumber". If XIN2 is empty, Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". KPP code (XKP2) is displayed with @schemeName="TaxDeclarationNumber". If XKP2 is empty, Tax declartion numner (VRNL) is displayed with @schemeName="CountryIdentificationNumber". If Country version (CSVN) is not FR or RU: Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". Tax declartion numner (VRNL) is displayed with @schemeName="TaxDeclarationNumber". Organization number 1 (CORG) is displayed with @schemeName="TountryIdentificationNumber". Organization number 2 (COR2) is displayed with @schemeName="CountryIdentificationNumber". If Country version (CSVN) is FR: Vat registration number (VRNO) is displayed with @schemeName="CountryIdentificationNumber". If Country version (CSVN) is FR: Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". If Country version (CSVN) is FR: Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". If SchemeName="TountryIdentificationNumber". If Country version (CSVN) is FR: Vat registration number (VRNO) is displayed with @schemeName="TountryIdentificationNumber". If Country version (CSVN) is FR:
	If Country version (CSVN) is RU: INN code (XIN2) is displayed with

Infor May 26, 2023

_	4 -	
$\Lambda \wedge \wedge \wedge$	LINTIN	ngEntity
ALL.	,,,,,,,,,	IUEIIIIV

AccountingEntity AccountingEntity/AccountingChartReference/ID @accountingEntity	@schemeName="TaxIdentificationNumber". If XIN2 is empty, Vat registration number (VRNO) is displayed with @schemeName="TaxIdentificationNumber". KPP code (XKP2) is displayed with @schemeName="TaxDeclarationNumber". If XKP2 is empty, Tax declartion numner (VRNL) is displayed with @schemeName="CountryIdentificationNumber". Set to "AccountingChartStandard". The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI E.g. 760 AAA
AccountingEntity/Location/ID CMNDIV.CCCONO CMNDIV.CCDIVI.; MNS100MI/GetBasicData	The field indicates a division. This is an identity for a legal unit within a company group.
AccountingEntity/Location/Address/AddressLine CMNDIV.CCCOA1 CMNDIV.CCCOA2 CMNDIV.CCCOA3 CMNDIV.CCCOA4.; MNS100MI/GetBasicData	The field indicates address lines 1-4 for the M3 division.
AccountingEntity/Location/Address/CityName CMNDIV.CCTOWN; MNS100MI/GetBasicData	The field indicates the city.
AccountingEntity/Location/Address/CountrySubDivisionCode CMNDIV.CCECAR; MNS100MI/GetBasicData @listID	The field indicates the state/region/countrysubdivision. The field indicates an area, province or state within a country. Set to "Canadian Provinces" if the country is Canada. Set to "France - Departements" if the country is France. Set to "US States" if the country is United States.
	Set to "SubDivisions - <country code="">". E.g "SubDivisions - PH" if the country is not US, CA or FR. Set to "SubDivisions". If Country is not given.</country>
AccountingEntity/Location/Address/CountryCode CMNDIV.CCCSCD; MNS100MI/GetBasicData @listID	The field indicates a country. Set to "Countries".
AccountingEntity/Location/Address/PostalCode CMNDIV.CCPONO; MNS100MI/GetBasicData	The field indicates the postal code.
AccountingEntity/BaseCurrency CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the local currency of the country or division used.
AccountingEntity/FinancialCalendarReference/DocumentID/ID	Set to 'Financial Calendar'
@accountingEntity CMNDIV.CCDIVI; MNS100MI/GetBasicData	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIV E.g. 760_AAA

AccountingJournal

Association to compatible some and DID	
AccountingJournal/DocumentID/ID CSYTAB.CTSTKY; CRS175MI/GetGeneralCode	The field indicates an entry function within Financial Application Management (FAM).
	Constant value (STCO) is set to FEID (FAM function).
@accountingEntity CSYTAB.CTCONO CSYTAB.CTDIVI.; CRS175MI/GetGeneralCode	The field indicates the company and division, a combination of CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD for this object has been published.
@lid	The field indicates the logical ID of the system.
AccountingJournal/LastModificationDateTime	
CSYTAB.CTLMTS; /	The field indicates the date and time the object was changed.
AccountingJournal/LastModificationPerson/IDs/ID CSYTAB .CTCHID: /	The field indicates the last person who modified.
@accountingEntity	
CSYTAB.CTCONO CSYTAB.CTDIVI	The field indicates the company and division, displayed as CONO_DIVI.
AccountingJournal/DocumentDateTime CSYTAB.CTRGDT CSYTAB.CRRGTM.; /	The field indicates the date and time the object was created.
AccountingJournal/Description CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the description of the FAM function.
AccountingJournal/Name CSYTAB.CTTX15; CRS175MI/GetGeneralCode	The field indicates a name of the FAM function.
AccountingJournal/DocumentCode CSYTAB.CTPARM; CRS175MI/GetGeneralCode	The field indicates the FAM function, Module and Journal heading.

AdvanceShipNotice AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID For Process: MHEXRH.H1E0PA MHEXRH.H1TTYP MHEXRH.H1RIDN MHEXRH.H1REPN

PDNHEA.IHWHLO PDNHFA IHSUNO PDNHEA.IHSUDO PDNHEA.IHDNDT.; /

For Sync: MHEXRH.H1E0PA MHEXRH.H1WHLO MHEXRH.H1TTYP MHEXRH.H1RIDN MHEXRH.H1REPN.; /

@accountingEntity For Process:

MHEXRH.H1CONO CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

@location For Process:

MHEXRH.H1WHLO; /

For Sync:

MHEXRH.H1WHLO; MHS800MI/LstExpRec

@variationID

@lid

AdvanceShipNotice/AdvanceShipNoticeHeader/AlternateDocumentID/ID

MHEXRH.H1RIDN; MHS800MI/LstExpRec The field indicates the order number.

AdvanceShipNotice/AdvanceShipNoticeHeader/DisplayID

For Sync: For Sync:

MHEXRH.H1RIDN; MHS800MI/LstExpRec The field indicates the order number.

AdvanceShipNotice/AdvanceShipNoticeHeader/LastModificationDateTime

MHEXRH.H1LMTS; /

The field indicates the date and time the document was last modified.

The field indicates the date the record was last changed.

AdvanceShipNotice/AdvanceShipNoticeHeader/LastModificationPerson/IDs/ID

For Process For Process:

MHEXRH.H1CHID ; MHS800MI/GetExpRec document.

For Sync:

MHEXRH.H1CHID; / @accountingEntity

For Process: The field indicates the company and division, displayed as CONO DIVI. MHEXRH.H1CONO

May 26, 2023

It is a concatanenation of

The field indicates the advance ship notice ID.

For Process:

Partner (17) + Transaction type (2) + Order number (10) + Receiving number (10) without separator. The position of each field is determined by its maximum length, specified in the parenthesis. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID

except for the last one. The last field in the concatenation, in this case REPN, is trimmed if it does not consume the maximum length.

If the advance ship notice is for a purchase order with delivery note, the document ID is the concatenation of warehouse, supplier, delivery note, and delivery note date. This condition will also be possible only if the supplier in M3 has shipment advice (SHAC) set to 1 or 2.

If IEC Agreement Control Property is m3beDocumentIDSeparator = space: The field indicates the advance ship notice ID. It is a concatenation of Partner (E0PA) <17> + Transaction type (TTYP) <2> + Order number (RIDN) <10> + Receiving number (REPN) <10>. The number specified in brackets is the maximum length of each field. the position and concatenation of the fields are based on the field length. If the data does not consume the maximum length, the rest is filled-up with spaces except for the last field which is right trimmed.

Otherwise: If IEC Agreement Control Property

m3beDocumentIDSeparator = /: The field indicates the advance ship notice ID. It is a concatenation of Partner (E0PA) <17> + Warehouse (WHLO) <3> + Transaction type (TTYP) <2> + Order number (RIDN) <10> + Receiving number (REPN) <10>. The number specified in brackets is the maximum length of each field and the fields are

separated by /.

The field indicates the company and division, displayed as

CONO DIVI.

The field indicates the warehouse.

The field indicates the sequence number that identifies the number of times that the BOD has been published.

The field indicates the logical ID of the system.

For Process:

For Sync:

The field indicates the ID of the person who last modified the

The field indicates the ID of the person who last modified the record.

MHEXRH.H1CMND; MHS800MI/LstExpRec

For Sync: CMNDIV.CCCONO CMNDIV.CCDIVI.; / AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDateTime For Process: For Process: MHEXRH.H1RGDT The field indicates the date and time the document was created. MHEXRH.H1RGTM; MHS800MI/GetExpRec If purchase order is with delivery note, this field is the date and time PDNHEA.IHDNDT the delivery note is created. PDNHEA.IHDNTM; PPS360MI/GetHead.; / For Sync: The field indicates date and time the record is created. For Sync: MHEXRH.H1RGDT MHEXRH.H1RGTM.; MHS800MI/LstExpRec AdvanceShipNotice/AdvanceShipNoticeHeader/Note For Sync: For Sync: MHEXRH.H1USD1 The field indicates the user-defined fields. It is a concatenation of MHEXRH.H1USD2 USD1 <15> + USD2 <15> + USD3 <15> + USD4 <15> + USD5 <5> MHEXRH.H1USD3 separated by '/'. MHEXRH.H1USD4 MHEXRH.H1USD5.; MHS800MI/LstExpRec AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference @type For Process: For Process: MHEXRH.H1TTYP The field indicates the stock transaction type. If TTYP = 10, set @type='ProductionOrder'. If TTYP = 25 set @type= 'PurchaseOrder'. If TTYP = 30, set @type= For Sync: 'CustomerReturn' MHEXRH.H1TTYP; MHS800MI/LstExpRec If TTYP = 40, set @type ='Transfer'. If TTYP = 50, set @type= 'Transfer'. Set to 'Production' if Stock transaction type = 10. Set to 'PurchaseOrder' if Stock transaction type = 25. Set to 'CustomerReturn' if Stock transaction type = 30. Set to 'Transfer' if Stock transaction type = 40 or 50. AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/DocumentID/ID For Process: The field indicates the order number. MHEXRH.H1RIDN :/ For Sync: MHEXRH.H1RIDN; MHS800MI/LstExpRec @accountingEntity The field indicates the company and division, displayed as For Process: MHEXRH.H1CONO CONO DIVI. CMNDIV.CCDIVI.; / For Sync: CMNDIV.CCCONO CMNDIV.CCDIVI.; / @location For Sync: For Sync: MHEXRH.H1WHLO; MHS800MI/LstExpRec The field indicates the warehouse. AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/Facility/IDs/ID For Process: For Process: MHEXRH.H1FACI The field indicates the facility. ; MHS800MI/GetExpRec @accountingEntity For Process: For Process: MHEXRH.H1CONO The field indicates the company and division, displayed as CONO DIVI. CMNDIV.CCDIVI.; AdvanceShipNotice/AdvanceShipNoticeHeader/Status/Code For Process: For Process: MHEXRH.H1CMND; MHS800MI/GetExpRec The field indicates the status of the document. If CMND = '*ADD', set to'Open'.
If CMND = '*CHG', set to'Open'. PDNHEA.IHPUSL PDNHEA.IHPUST; PPS360MI/GetHead.; / If CMND = '*DLT', set to 'Deleted'.

If CMND = '*PRC', set to 'Partial'.

If CMND = '*CLS', set to 'Closed'. For Sync:

May 26, 2023

If the purchase order has delivery note, the status is the following:

-If PUSL and PUST are both 50, set status to 'Closed'

-If PUSL < 50 and PUST = 50, set status to 'Partial' -If PUSL and PUST = > 46 but < 50, set to 'Open

For Sync:

If CMND=*ADD or *CHG, set to Open. If CMND=*DLT, set to Cancelled. If CMND=*CLS, set to Closed. If CMND=*PRC, set to Partial.

@listID

For Sync:

Set to 'ShipmentStatus'.

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/ID

For Process: For Process:

MHEXRH.H1WHLO The field indicates the warehouse.

PDNHEA.IHWHLO.; / @accountingEntity

For Process: For Process:

MHEXRH.H1CONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/Address@type

or Process:

The field indicates the address type. Set to 'text'.

Display only if TTYP = 10 (ProductionOrder) or 40 (Transfer).

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/Address/AddressLine

For Process: For Process:

MHEXRH.H1ADR1 The field indicates the address line.

MHEXRH.H1ADR2 Display only if TTYP = 10 (ProductionOrder) or 40 (Transfer).

MHEXRH.H1ADR3

MHEXRH.H1ADR4.; MHS800MI/GetExpRec

@sequence

For Process:

The field indicates the address line sequence.

Display only if TTYP = 10 (Production Order) or 40 (Transfer).

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/Address/CountryCode

For Process: For Process:

MHEXRH.H1CSCD The field indicates the country code.

; MHS800MI/GetExpRec Display only if TTYP = 10 (ProductionOrder) or 40 (Transfer).

@listID

For Process:

The field indicates the coutry code list ID. Set to 'Countries'. Display only if TTYP = 10 (ProductionOrder) or 40 (Transfer).

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/Address/PostalCode

For Process: For Process:

MHEXRH.H1PONO; MHS800MI/GetExpRec The field indicates the postal code.

Display only if TTYP = 10 (ProductionOrder) or 40 (Transfer).

AdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMeasure

For Process: For Process:

MHEXRH.H1GRWE; MHS800MI/GetExpRec The field indicates the gross weight.

@unitCode

For Process: For Process:

CSYPAR.CPPARM The field indicates the general unit of measure for weight.

; CRS175MI/GetItemFreeFlds It is stored in M3 BE, program CRS703 General Units of Measure.

AdvanceShipNotice/AdvanceShipNoticeHeader/CountryOfOriginCode

For Process: For Process:

MHEXRH.H1CSCD; MHS800MI/GetExpRec The field indicates the country of origin.

For Sync: For Sync:

MHEXRH.H1CSCD; MHS800MI/LstExpRec The field indicates the suppliers country or the country where the

shipment is sent from.

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode

For Process: For Process:

MHEXRH.H1MODL; MHS800MI/GetExpRec The field indicates how the delivery is made.

PDNHEA.IHMODL; PPS360MI/GetHead.; / For Sync:

The field indicates the delivery method.

For Sync:

MHEXRH.H1MODL; MHS800MI/LstExpRec

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID

For Process: For Process:

MHEXRH.H1SUNO; MHS800MI/GetExpRec The field indicates the supplier.

Display only if TTYP = 25 (PurchaseOrder).

For Sync:

For Sync: The field indicates the supplier.

MHEXRH.H1SUNO: MHS800MI /LstExpRec

@accountingEntity

For Process:

MHEXRH.H1CONO

CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCDIVI.; /

CMNDIV.CCCONO

For Process:

The field indicates the accounting entity.

If SupplierShipFromCarrierRemitToMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

For Process:

The field indicates the accounting entity.

The field indicates the supplier name. Display only if TTYP = 25 (PurchaseOrder).

If ShipFromPartyMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI)

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Name

For Process:

MHEXRH.H1CONM; MHS800MI/GetExpRec

CIDMAS.IDSUNM; PPS360MI/GetHead.; /

For Sync: CIDMAS.IDSUNO;

CRS620MI/GetBasictData, MITWHL.MWWHNM; MMS005MI/GetWarehouse.; /

The field indicates the supplier's name for transaction type 25 (Purchases order). For transaction type 10, 40 and 50, the field

indicates the warehouse name.

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/ID

For Process:

MHEXRH.H1SUNO; .H1SUNO; MHS800MI/GetExpRec The field indicates the supplying warehouse.

Display only if TTYP = 50 (Transfer).

@accountingEntity

For Process:

MHEXRH.H1CONO

CMNDIV.CCDIVI.; /

For Process:

The field indicates the company and division, displayed as

CONO DIVI.

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address

@type

The field indicates the address type. Set to 'text'. Display only if TTYP = 25 (PurchaseOrder).

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/AddressLine

For Process:

MHEXRH.H1ADR1 MHEXRH.H1ADR2 MHEXRH.H1ADR3

MHEXRH.H1ADR4.; MHS800MI/GetExpRec

For Process:

The field indicates the address line. Display only if TTYP = 25 (PurchaseOrder).

For Sync:

The field indicates the address line.

For Sync:

MHEXRH.H1ADR1 MHEXRH.H1ADR2 MHEXRH.H1ADR3

MHEXRH.H1ADR4.; MHS800MI /LstExpRec

@sequence

For Process:

The field indicates the address line sequence. Display only if TTYP = 25 (PurchaseOrder).

For Sync:

The field indicates the address line sequence

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/CountryCode

For Process:

MHEXRH.H1CSCD

; MHS800MI/GetExpRec

The field indicates the country code. Display only if TTYP = 25 (PurchaseOrder).

For Sync:

MHEXRH.H1CSCD; MHS800MI/LstExpRec

@listID

The field indicates the country code.

For Process:

The field indicates the coutry code list ID. Set to 'Countries'.

Display only if TTYP = 25 (PurchaseOrder).

For Sync: Set to 'Countries'

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/PostalCode

For Process For Process:

MHEXRH.H1PONO; MHS800MI/GetExpRec The field indicates the postal code. Display only if TTYP = 25 (PurchaseOrder).

For Sync:

MHEXRH.H1CSCD; MHS800MI/LstExpRec For Sync:
The field indicates the country code.

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Name
For Sync:
For Sync:

MHEXRH.H1YREF; MHS800MI/LstExpRec The field indicates the supplier's contact person.

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Communication/DialNumber

For Sync: For Sync:

CIDMÁS.IDPHNO

CIDMAS.IDPHNO;

CIDMAS.IDPHN2;

CRS620MI/GetBasicData,

The field indicates the Supplier's phone number for transaction type 25 (Purchase Order). For transaction type not equal to 25, the field indicates the warehouse's phone number.

CRS620MI/GetBasicData, indicates the warehouse's phone number. MITWHL.MWPHNO:

MMS005MI/GetWarehouse.; /

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/PartyIDs/ID
For Sync:
For Sync:

MHEXRH.H1SUNO; MHS800MI/LstExpRec The field indicates the customer returning the goods. The field is

available for transaction type 30.

@accountingEntity

For Sync: For Sync

CMNDIV.CCCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI.

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Name
For Sync:
For Sync:

OCUSMA.OKCUNM; CRS610MI/GetBasicData

The field indicates the customer name. The field is available for

transaction type 30.

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/AddressLine

For Sync: For Sync:

MHEXRH.H1ADR1 The field indicates the address line.
MHEXRH.H1ADR2

MHEXRH.H1ADR3

MHEXRH.H1ADR4.; MHS800MI /LstExpRec

@sequence

For Sync:

The field indicates the address line sequence.

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnToShipFromParty/Location/Address/CountryCode

For Sync: For Sync:

MHEXRH.H1CSCD; MHS800MI/LstExpRec The field indicates the country code.

@listID

For Sync: Set to 'Countries'.

Advance Ship Notice / Advance Ship Notice Header / Return To Ship From Party/Location / Address / Postal Code to the property of the propert

For Sync: For Sync:

MHEXRH.H1PONO; MHS800MI /LstExpRec The field indicates the postal code.

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/PartyIDs/ID

For Process: For Process:

MHEXRH.H1SUNO; MHS800MI/GetExpRec The field indicates the customer.

Display only if TTYP = 30 (CustomerReturn).

@accountingEntity

For Process:

MHEXRH.H1CONO

For Process:
The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO_DIVI.

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Name
For Process:
For Process:

MHEXRH.H1CONM; MHS800MI/GetExpRec The field indicates the customer name.

Display only if TTYP = 30 (CustomerReturn).

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address

@type

For Process:

The field indicates the address type. Set to 'text'. Display only if TTYP = 30 (CustomerReturn).

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/AttentionOfName

For Process: For Process:

MHEXRH.H1YREF
The field indicates the customer's contact person.

; MHS800MI/GetExpRec
Display only if TTYP = 30 (CustomerReturn).

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/AddressLine

For Process: For Process:

MHEXRH.H1ADR1 The field indicates the address line.

MHEXRH.H1ADR2 Display only if TTYP = 30 (CustomerReturn).

MHEXRH.H1ADR3

MHEXRH.H1ADR4.; MHS800MI/GetExpRec

@sequence

For Process:

The field indicates the address line sequence. Display only if TTYP = 30 (CustomerReturn).

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/CountryCode

For Process:

MHEXRH.H1CSCD For Process:

; MHS800MI/GetExpRec The field indicates the country code.

Display only if TTYP = 30 (CustomerReturn).

@listID

For Process:

The field indicates the coutry code list ID. Set to 'Countries'.

Display only if TTYP = 30 (CustomerReturn)

AdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/PostalCode

For Process: For Process

MHEXRH.H1PONO; MHS800MI/GetExpRec The field indicates the postal code.

Display only if TTYP = 30 (CustomerReturn)

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/ID

MHEXRH.H1WHLO The field indicates the warehouse.

PDNHEA.IHWHLO.; /

The field indicates the warehouse ID.

For Sync: MHEXRH.H1WHLO; / @accountingEntity

For Process: The field indicates the company and division, displayed as

MHEXRH.H1CONO CONO DIVI. CMNDIV.CCDIVI.; /

For Sync:

CMNĎIV.CCCONO CMNDIV.CCDIVI.; /

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/Name

For Sync: For Sync:

MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse name

AdvanceShipNotice/AdvanceShipNoticeHeader/PriorityCode

For Process: For Process:

MHEXRH.H1PRIO The field indicates the priority.

; MHS800MI/GetExpRec

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode

For Process:

MHEXRH.H1TEDL: MHS800MI/GetExpRec The field indicates the delivery terms which define when the

responsibility for a delivery is transferred from the supplier to the customer.

PDNHEA.IHTEDL; PPS360MI/GetHead.; /

For Sync:

MHEXRH.H1TEDL; MHS800MI/LstExpRec

@listID

The field indicates the delivery terms.

For Process:

For Sync:

The field indicates the listID attribute. Set to 'Incoterms'.

For Sync: Set to 'Incoterms'

AdvanceShipNotice/AdvanceShipNoticeHeader/UserArea For Process:

1) MHEXRH.H1USD1

MHEXRH.H1USD2 MHEXRH.H1USD3 MHEXRH.H1USD4 MHEXRH.H1USD5; MHS800MI/GetExpRec

2) OOHEAD.OAORTP; OIS100MI/GetOrderHead MGHEAD.MGTRTP; MMS100MI/GetHead

3) CIDVEN.IISHAC; CRS620MI.GetBasicData

4) MHEXRH.H1TRSL: MHS800MI/GetExpRec.; / For Process:

1) User-defined field 1-5

The field indicates the user-defined fields 1-5.

If Property/NameValue = USD1, set @name='FreeField1'. If Property/NameValue = USD2, set @name='FreeField2'. If Property/NameValue = USD3, set @name='FreeField3'. If Property/NameValue = USD4, set @name='FreeField4'. If Property/NameValue = USD5, set @name='FreeField5'.

2) Order type

The field indicates the order type. If Property/NameValue = ORTP/

TRTP, set @name='OrderType'.

If TTYP = 30, use OIS100MI/GetHead ORTP where input is ORNO =

RIDN.

If TTYP = 40 or 50, use MMS100MI/GetHead TRTP where input is

TRNR = RIDN.

3) Shipment advice

The field indicates the shipment advice.

If Property/NameValue = SHAC, set @name='ShipmentAdvice'.

If SHAC = 0, set to 'Reported manually'. If SHAC = 1, set to 'Received via EDI' If SHAC = 2, set to 'Manual and delivery note'.

4) Lowest status

The field indicates lowest stock transaction status.

If Property/NameValue = TRSL, set @name='LowestStatus'.

5) ASN type

If AdvanceShipNoticeHeader/DocumentReference@type is

'CustomerReturn' and AdvanceShipNoticeHeader/ DocumentReference/DocumentID/ID is blank, AdvanceShipNoticeHeader/UserArea/Property/

NameValue@name='field.Type' is set to 2. This sets the ASN type in WMS to 'CustomerReturn'

AdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID

For Process MHEXRD.H2ITNO;

MHS800MI/LstExpRecDetail

MWOMAT.VMMTNO;

PMS100MI/LstMaterials

MWOCPN.VSCPNO; PMS090MI/LstCoProdReport.; /

For Sync:

MHEXRD.H2ITNO; MHS800MI/LstExpRecDetail

@accountingEntity For Process: MHEXRH.H1CONO CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

AdvanceShipNotice/AdvanceShipNoticeItem/Note

For Sync: MHEXRH.H1USD1 MHEXRH.H1USD2

MHEXRH.H1USD3 MHEXRH.H1USD4

MHEXRH.H1USD5.; MHS800MI/LstExpRec

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity

For Process: MHEXRD.H2TRQA;

MHS800MI/LstExpRecDetail

MWOCPN.VSORQA; PMS090MI/LstCoProdReport.; /

MITTRA.MTTRQA; MHS800MI/LstExpRecDetail

@unitCode

For Process:

MHEXRD.H2ALUN; MHS800MI/LstExpRecDetail

MWOCPN.VSMAUN; PMS090MI/LstCoProdReport.; /

MHEXRD.H2ALUN; MHS800MI/LstExpRecDetail

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity For Process

MHEXRD.H2TRQT;

MHS800MI/LstExpRecDetail

MWOMAT.VMREQT:

PMS100MI/LstMaterials.; /

For Sync:

MHEXRD.H2TRQT; MHS800MI/LstExpRecDetail

@unitCode For Process

For Process

For Sync:

MITMAS.MMUNMS; MHS800MI/LstExpRecDetail

For Sync: MHEXRD.H2UNMS; MHS800MI/LstExpRecDetail

AdvanceShipNotice/AdvanceShipNoticeItem/OwnershipCode

MHEXRD.H2RESP

; MHS800MI /LstExpRecDetail

AdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/DocumentID/ID

For Process:

MHEXRD.H2RIDN

; MHS800MI /LstExpRecDetail

For Process: The field indicates the item number. If the transtion type is for manufacturing order (TTYP = 10), this

element indicates the finished good or by-product or co-product.

For Sync: The field indicates the item number.

The field indicates the accounting entity.

If ItemMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

For Sync:

The field indicates the user-defined fields. It is a concatenation of USD1 <15> + USD2 <15> + USD3 <15> + USD4 <15> + USD5 <5>

separated by '/'.

The field indicates the shipped quantity in alternate unit of measure.

The field indicates the quantity in alternate unit of measure.

For Process: The field indicates the alternate unit of measure.

The field indicates the alternate unit of measurement.

For Process The field indicates the shipped quanrity in basic unit of measure.

For Sync:

The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.

For Process:

The field indicates the basic unit of measure.

For Sync:

The field indicates the basic unit of measure in which each item is recorded in inventory.

For Process:

The field indicates the person responsible for the item.

For Process

The field indicates the requisition order number.

Display only if TTYP = 40.

MHEXRD.H2RIDN: MHS800MI/LstExpRecDetail For Sync:

@accountingEntity

For Process: The field indicates the company and division, displayed as

MHEXRH.H1CONO CONO DIVI. CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

@location

For Sync: For Sync:

MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID

AdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/LineNumber For Process For Process:

MHEXRD.H2RIDL; MHS800MI/LstExpRecDetail The field indicates the order line number.

Display only if TTYP = 40.

For Sync:

MHEXRD.H2RIDL

MHEXRD.H2RIDX.; MHS800MI/LstExpRecDetail The field indicates the order line number and the order line suffix.

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/DocumentID/ID

For Process: For Process:

MHEXRD.H2RIDN The field indicates the purchase order number.

; MHS800MI /LstExpRecDetail Display only if TTYP = 25.

For Sync: For Sync:

The field indicates the order number for transaction type 25 MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail

(Purchase Order).

@accountingEntity For Process The field indicates the company and division, displayed as

MHEXRH.H1CONO CONO DIVI. CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

@location

For Sync:

MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/LineNumber

MHEXRD. H2RIDL For Process:

MHEXRD.H2PNLS.; MHS800MI/LstExpRecDetail The field indicates the concatenation of purchase order line number

and subnumber wherein the last 3 digits is the subnumber.

Display only if TTYP = 25.

For Sync:

The field indicates the order line number and purchase order line

The field indicates the order number for transaction type 40 (Transfer).

subnumber

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/SubLineNumber

For Process: For Process:

MHEXRD.H2PNLS The field indicates the purchase order line subnumber.

Display only if TTYP = 25. ; MHS800MI /LstExpRecDetail

AdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/DocumentID/ID

For Process: For Process:

MHEXRD.H2RIDN The field indicates the sales order number.

; MHS800MI /LstExpRecDetail Display only if TTYP = 30.

For Sync:

MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail The field indicates the order number for transaction type 30

(Customer Return).

For Process: The field indicates the company and division, displayed as

MHEXRH.H1CONO CONO DIVI. CMNDIV.CCDIVI.; /

For Sync:

@accountingEntity

CMNĎIV.CCCONO CMNDIV.CCDIVI.; /

MHEXRD.H2RIDL

@location

For Sync: For Sync:

MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID.

AdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/LineNumber

For Process: For Process:

MHEXRD.H2RIDL; MHS800MI/LstExpRecDetail The field indicates the sales order line number.

Display only if TTYP = 30. For Sync:

2) MHPRNS.J1SUDO;

MHEXRD.H2RIDX.: MHS800MI/LstExpRecDetail For Sync: The field indicates the order line number and the order line suffix. AdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/SubLineNumber For Process: MHEXRD.H2RIDX; MHS800MI/LstExpRecDetail The field indicates the sales order line suffix. Display only if TTYP = 30. AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference MHEXRD.H2TTYP; MHS800MI/LstExpRecDetail For Process: The field indicates the stock transaction type. If TTYP = 10, set @type='ProductionOrder'.

If TTYP = 25 set @type= 'PurchaseOrder'. If TTYP = 30, set @type= 'CustomerReturn'. If TTYP = 40, set @type ='Transfer'. If TTYP = 50, set @type= 'Transfer'. For Sync: Set to 'Production' if Stock transaction type = 10. Set to 'PurchaseOrder' if Stock transaction type = 25. Set to 'CustomerReturn' if Stock transaction type = 30. Set to 'Transfer' if Stock transaction type = 40 or 50 AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/DocumentID/ID For Process: For Process: MHEXRD.H2RIDN The field indicates the order number. MHEXRD.H2RIDI; MHS800MI/LstExpRecDetail If TTYP = 50 (Distribution Order), this is a concatenation of the order number (RIDN) and delivery number (RIDI) separated by '/'. MWOMAT.VMMFNO; PMS100MI/LstMaterials For Sync: The field indicates the order number for transaction type 10 MWOCPN.VSMFNO; PMS090MI/LstCoProdReport.; / (Production Order) or 50 (Transfer). For Sync: MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail @accountingEntity For Process: The field indicates the company and division, displayed as MHEXRH.H1CONO CONO_DIVI. CMNDIV.CCDIVI.; / For Sync: CMNDIV.CCCONO CMNDIV.CCDIVI.; / @location For Sync: For Sync: MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID. AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/LineNumber For Process: For Process: MHEXRD.H2RIDL The field indicates the order line number. MHEXRD.H2PNLS; If DocumentReference type='PurchaseOrder', concatenate RIDL and MHS800MI/LstExpRecDetail PNLS where PNLS is the last 3 digits. MWOMAT.VMMSEQ: If DocumentReference type='ProductionOrder' (TTYP =10), and the PMS100MI/LstMaterials item refers to a by-product, this element indicates the material sequence number. MWOCPN.VSOPNO; PMS090MI/LstCoProdReport If DocumentReference type='ProductionOrder' (TTYP =10), and the .; / item refers to a co-product, this element is a concatenation of the For Sync: operation number and autogenerated sequence number. MHEXRD.H2RIDL MHEXRD.H2RORX.; MHS800MI/LstExpRecDetail For Sync: If Transaction Type = 50 (Distribution Order) then display Order Line (RIDL) + line suffix (RORX) AdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/SubLineNumber For Process: For Process: MHEXRD.H2RIDX The field indicates the order line suffix. MHEXRD.H2PNLS.; MHS800MI/LstExpRecDetail If DocumentReference type='PurchaseOrder', use PNLS. Otherwise, use RIDX AdvanceShipNotice/AdvanceShipNoticeItem/UserArea For Process: For Process: 1) MHEXRD.H2USD1 1) User-defined field 1-5 MHEXRD.H2USD2 The field indicates the user-defined fields 1-5. If Property/NameValue = USD1, set @name='FreeField1'. MHEXRD.H2USD3 MHEXRD.H2USD4 If Property/NameValue = USD2, set @name='FreeField2'. MHEXRD.H2USD5; If Property/NameValue = USD3, set @name='FreeField3'. If Property/NameValue = USD4, set @name='FreeField4'. MHS850MI.LstExpRecDetail If Property/NameValue = USD5, set @name='FreeField5'.

MHS800MI.LstExpRecPacDet

3) MHPRNS.J1DNDT;

MHS800MI.LstExpRecPacDet

4) MHEXRH.H1REPN;

5) MPGRMT.GRDSTO MPGRMT.GRFLCD; PPS345MI.Get.; /

2) Delivery note

The field indicates the delivery note.

If Property/NameValue=SUDO, set @name='M3.DeliveryNote'

3) Delivery note date

The field indicates the delivery note date.

If Property/NameValue=DNDT, set @name='M3.DeliveryNoteDate'

4) Customer Return Receiving Number

The field indicates the customer return receiving number in M3.

If Property/NameValue=REPN, set

@name=='M3.CustomerReturnRecNum'. The value is retrieved from

the event data.

For Process:

For Process:

For Process:

Display only if TTYP = 10

Display only if TTYP = 10

product' if BYPR = 1.

5) If parameter Direct Putaway (DSTO) is 0, and Inspection Point (FLCD) is 1, 2, or 4 in the Goods Receiving Method of the purchase order, the value of of agreement control property m3beHoldCode will

be assigned to UserArea/Property/

NameValue@name='field.CONDITIONCODE' and the value of agreement control property m3beToLocation will be assigned to

UserArea/Property/NameValue@name='field.TOLOC'.

The field indicates the material sequence number.

The field indicates the component number.

This is used to assign a hold code and location in the integrating party when purchase order requires inspection.

AdvanceShipNotice/AdvanceShipNoticeItem/Reference

@sequence

For Process:

MWOMAT.VMMSEQ; PMS100MI/LstMaterials

AdvanceShipNotice/AdvanceShipNoticeItem/Reference/NameValue

MWOMAT.VMMTNO; PMS100MI/LstMaterials

@name For Process:

MWOMAT.VMBYPR; PMS100MI/LstMaterials

MHEXRD.H2RSCD; MHS800MI/LstExpRecDetail

AdvanceShipNotice/AdvanceShipNoticeItem/ReasonCode The field indicates the user-defined reason code that is used to

describe why the transaction was entered. AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/LotIDs/ID

MHEXRD.H2BANO; MHS800MI/LstExpRecDetail

For Process:

The field indicates the lot number.

Display if Lot control method (INDI) = 1 or 3 in MMS200MI

The field indicates if the component is a by-product. Set to 'By-

GetItmBasic with Item number (ITNO) as input.

For Sync:

The field indicates the lot number.

AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/SerialNumber

For Sync: For Sync:

MHEXRD.H2BANO; MHS800MI/LstExpRecDetail The field indicates the serial number.

AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/SerialNumber

For Process

MHEXRD.H2BANO; MHS800MI/LstExpRecDetail

For Process:

The field indicates the serial number.

Display if Lot control method (INDI) = 2 or 5 in MMS200MI

GetItmBasic with Item number (ITNO) as input.

AdvanceShipNotice/AdvanceShipNoticeItem/LineNumber

For Process: MHEXRD.H2RELI MHEXRD.H2RIDL MHEXRD.H2RIDX MHEXRD.H2PNLS;

MHS800MI/LstExpRecDetail

MWOCPN.VSOPNO; PMS090MI/LstCoProdReport.; /

MHEXRD.H2RELI; MHS800MI/LstExpRecDetail

For Process:

The field indicates the concatenation of line number and line suffix

wherein the last 3 digits is the line suffix.

Use Line number (RELI) for Transaction type = 30 (Customer

Return). Otherwise, use Order line (RIDL).

If DocumentReference type='PurchaseOrder' (TTYP =25), concatenate RIDL and PNLS where PNLS is the last 3 digits.

If DocumentReference type='ProductionOrder' (TTYP =10), and the

item refers to a co-product, this element is a concatenation of the operation number and autogenerated sequence number.

The field indicates the line number for customer order returns.

AdvanceShipNotice/AdvanceShipNoticeItem/Components/ItemID/ID

For Process:

MHEXRD.H2MTNO; MHS800MI/LstExpRecDetail

@accountingEntity

For Process:

For Process:

The field indicates the component number.

MHEXRH.H1CONO For Process:

CMNDIV.CCDIVI.; / The field indicates the company and division, displayed as

CONO DIVI.

AdvanceShipNotice/AdvanceShipNoticeUnit/TrackingID

For Process: For Process:

MHFRNS.J2PANR; MHS800Ml/LstExpRecPacDet

The field indicates the package number.

PFTRNS.INPACN; PPS360MI/LstPackage.; / @schemeName

For Process:

Set to 'PackageNumber' if element AdvanceShipNoticeUnit/

TrackingID refers to M3 Package Number (PANR).

AdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID

For Process: For Process:

MHFRNS.J2CAMU; MHS800MI/LstExpRecPacDet The field indicates the container.

For Sync: For Sync:

MHFRNS.J2PANR; MHS800MI/LstExpRecPacDet

The field indicates the package number.

AdvanceShipNotice/AdvanceShipNoticeUnit/CarrierParty/PartyIDs/ID

For Process:

MULEPNS: ISSUING: MUSSOOM!/LetExpDocPosDot

The field indicates the

MHFRNS.J2SUNO; MHS800MI/LstExpRecPacDet

The field indicates the forwarding agent.

Display only if TTYP = 25 and Supplier type (SUTY) = 5.

@accountingEntity

MHEXRH.H1CONO

CMNDIV.CCDIVI.; / The field indicates the company and division, displayed as CONO DIVI.

CMNDIV.CCDIVI.; / CONO DIVI.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipFromParty/PartyIDs/ID

For Process: For Process: For Process: MHFRNS.J2SUNO; MHS800MI/LstExpRecPacDet The field indicates the supplier number.

Display only if TTYP = 25 and Supplier type (SUTY) is not 5.

PFTRNS.INSUNO; PPS360MI/GetPackage.; /

@accountingEntity
For Process: For Process:

MHEXRH.H1CONO The field indicates the accounting entity.

CMNDIV.CCDIVI.: /

If SupplierShipFromCarrierRemitToMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

AdvanceShipNotice/AdvanceShipNoticeUnit/NetWeightMeasure

For Process: For Process:

MHFRNS.J2NEWE; MHS800MI/LstExpRecPacDet

The field indicates the net weight.

PFTRNS.IINEWE; PPS360MI/GetPackage.; /

@unitCode

For Process:

For Process: For Process:

CSYPAR.CPPARM
The field indicates the general unit of measure for weight.
; CRS175MI/GetItemFreeFlds
It is stored in M3 BE, program CRS703 General Units of Measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/GrossWeightMeasure

For Process: For Process:

MHFRNS.J2GRWE; MHS800MI/LstExpRecPacDet

The field indicates the gross weight.

PFTRNS.IIGRWE; PPS360MI/GetPackage.; /

@unitCode

For Process: For Process:

CSYPAR.CPPARM

The field indicates the general unit of measure for weight.

; CRS175MI/GetItemFreeFlds It is stored in M3 BE, program CRS703 General Units of Measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/TotalVolumeMeasure

For Process: For Process:

MHFRNS.J2VOL3; MHS800MI/LstExpRecPacDet

The field indicates the volume.

PFTRNS.INVOM3; PPS360MI/GetPackage.; /

@unitCode

For Process: For Process:

CSYPAR.CPPARM The field indicates the general unit of measure for volume.
; CRS175MI/GetItemFreeFlds It is stored in M3 BE, program CRS703 General Units of Measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/Item/ID/ID
For Process:

The field indicates the item number.

MHFRNS.J2ITNO; MHS800MI/LstExpRecPacDet

INITERNO.JZITNO, INITOOUDINI/ESIEXPRECEACDEL

PFTRNS.INITNO; PPS360MI/LstDetailByPack.; /

For Sync:

MHFRNS.J2ITNO; MHS800MI/LstExpRecPacDet

@accountingEntity
For Process:

CMNDIV.CCDIVI.: /

If ItemMaster is enabled in the BOD Processor Master AE tab, this is For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; / displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

The field indicates the accounting entity.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity

For Process For Process

MHFRNS.J2DLQA; MHS800MI/LstExpRecPacDet The field indicates the delivered quantity in alternate unit of measure.

PFTRNS.INRVQA; PPS360MI/LstDetailByPack.; /

The field indicates the delivered quantity.

For Sync:

MHFRNS.J2DLQT; MHS800MI/LstExpRecPacDet

@unitCode

For Process The field indicates the unit of measure.

MHFRNS.J2UNIT; MHS800MI/LstExpRecPacDet PFTRNS.INPUUN; PPS360MI/LstDetailByPack.; /

MHFRNS.J2UNIT; MHS800MI/LstExpRecPacDet

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedBaseUOMQuantity

For Process For Process

MHFRNS.J2DLQT; MHS800MI/LstExpRecPacDet The field indicates the delivered quantity in basic unit of measure.

@unitCode

For Process: For Process:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet For Process:

The field indicates the requisition order number.

Display only if TTYP = 40.

For Sync:

CONO DIVI.

For Sync:

The field indicates the order number for transaction type 40 (Transfer).

@accountingEntity The field indicates the company and division, displayed as For Process:

MHEXRH.H1CONO

CMNDIV.CCDIVI.; /

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/LineNumber

For Process: For Process:

The field indicates the requisition order line number. MHFRNS.J2RIDL; MHS800MI/LstExpRecPacDet Display only if TTYP = 40.

For Sync:

MHFRNS.J2RIDL MHFRNS.J2RIDX The field indicates the order line number and the order line suffix.

; MHS800MI/LstExpRecPacDet

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID

For Process: For Process:

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet The field indicates the purchase order number.

Display only if TTYP = 25. PFTRNS.INRIDN; PPS360MI/LstDetailByPack.; /

The field indicates the order number for transaction type 25 For Sync:

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet (Purchase Order).

@accountingEntity

For Process: The field indicates the company and division, displayed as

MHEXRH.H1CONO CONO DIVI.

CMNDIV.CCDIVI.; /

For Sync: CMNDIV.CCCONO CMNDIV.CCDIVI.;

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

For Process: For Process

MHFRNS.J2RIDL The field indicates the concatenation of purchase order line number

MHFRNS.J2RIDX; MHS800MI/LstExpRecPacDet and subnumber wherein the last 3 digits is the subnumber.

Display only if TTYP = 25.

PFTRNS.INRIDL

MHFRNS.J2RIDL

PFTRNS.INRIDX; PPS360MI/LstDetailByPack.; / For Sync:

The field indicates the order line number and the order line suffix. For Sync:

; MHS800MI/LstExpRecPacDet

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/SubLineNumber

For Process: For Process:

MHFRNS.J2RIDX; MHS800MI/LstExpRecPacDet The field indicates the purchase order line suffix.

Display only if TTYP = 25. PFTRNS.INRIDX; PPS360MI/LstDetailByPack.; /

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet For Process

The field indicates the sales order number.

Display only if TTYP = 30.

For Sync:

The field indicates the order number for transaction type 30

(Customer Return)

@accountingEntity

For Process: MHEXRH.H1CONO

CMNDIV.CCDIVI.; /

The field indicates the company and division, displayed as

CONO DIVI.

For Sync:

CMNDIV.CCCONO CMNDIV.CCDIVI.; /

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/LineNumber

For Process For Process:

MHFRNS.J2RIDL; MHS800MI/LstExpRecPacDet The field indicates the sales order line number.

Display only if TTYP = 30.

For Sync:

MHFRNS.J2RIDL For Sync:

MHFRNS.J2RIDX The field indicates the order line number and the order line suffix.

.; MHS800MI/LstExpRecPacDet

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber

For Process: For Process:

MHFRNS.J2RIDX; MHS800MI/LstExpRecPacDet The field indicates the sales order line suffix.

Display only if TTYP = 30.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference

@type

For Process: For Process:

MHEXRH.H1TTYP; MHS800MI/LstExpRecPacDet The field indicates the stock transaction type. If TTYP = 10, set @type='ProductionOrder'

If TTYP = 25 set @type= 'PurchaseOrder'. If TTYP = 30, set @type= MHEXRD.H2TTYP; MHS800MI/LstExpRecDetail

'CustomerReturn'

If TTYP = 40, set @type ='Transfer'. If TTYP = 50, set @type= 'Transfer'.

For Sync:

Set to 'Production' if Stock transaction type = 10. Set to 'PurchaseOrder' if Stock transaction type = 25. Set to 'CustomerReturn' if Stock transaction type = 30. Set to 'Transfer' if Stock transaction type = 40 or 50.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID For Process:

For Process:

MHFRNS.J2RIDN The field indicates the order number.

MHFRNS.J2DLIX.; MHS800MI/LstExpRecPacDet

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet

If TTYP = 50 (Distribution Order), this is a concatenation of the order

number (RIDN) and delivery number (DLIX) separated by '/'.

The field indicates the order number for transaction type 10

(Production Order) or 50 (Transfer).

@accountingEntity For Process

MHEXRH.H1CONO

CMNDIV.CCDIVI.; /

The field indicates the company and division, displayed as

CONO DIVI.

For Sync:

For Sync:

MHFRNS.J2RIDL

CMNDIV.CCCONO CMNDIV.CCDIVI.:

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/LineNumber

For Process:

MHFRNS.J2RIDL

The field indicates the order line number.

MHFRNS.J2RIDX.; MHS800MI/LstExpRecPacDet If TTYP =25, the field indicates the concatenation of purchase order

line number and subnumber wherein the last 3 digits is the

subnumber.

MHFRNS.J2RIDX .; MHS800MI/LstExpRecPacDet

AdvanceSnipNotice	For Sync:
	The field indicates the order line number and the order line suffix.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitIte	
For Process:	For Process:
MHFRNS.J2RIDX; MHS800MI/LstExpRecPacDet	The field indicates the order line suffix.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitIte	m/User∆rea
For Process:	For Process:
MPGRMT.GRDSTO	1.) If parameter Direct Putaway (DSTO) is 0, and Inspection Point
MPGRMT.GRFLCD;	(FLCD) is 1, 2, or 4 in the Goods Receiving Method of the purchase
PPS345MI.Get	order, the value of of agreement control property m3beHoldCode will
MUEDNO IODANO MUOCCOMUNICE DE DE C	be assigned to UserArea/Property/
MHFRNS.J2PANR; MHS800MI/LstExpRecPacDet	NameValue@name='field.CONDITIONCODE' and the value of
.; /	agreement control property m3beToLocation will be assigned to UserArea/Property/NameValue@name='field.TOLOC'.
	This is used to assign a hold code and location in the integrating party
	when purchase order requires inspection.
	Whom paronage order requires inspection.
	2.) The field indicates the package number if transaction type (TTYP)
	is 50. UserArea/Property/NameValue@name='field.ToID'
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitIte	
For Process:	For Process:
MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet	The field indicates the lot number.
DETENIS INDANO: DDS260MI/LatDatailByDook : /	Display if Lot control method (INDI) = 1 or 3 in MMS200MI
PFTRNS.INBANO; PPS360MI/LstDetailByPack.; /	GetItmBasic with Item number (ITNO) as input.
For Sync:	For Sync:
MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet	The field indicates the lot number.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitIte	m/SerializedLot/Lot/SerialNumber
For Sync:	For Sync:
MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet	The field indicates the serial number.
AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitIte	
For Process:	For Process:
MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet	The field indicates the serial number.
PFTRNS.INBANO; PPS360MI/LstDetailByPack.; /	Display if Lot control method (INDI) = 2 or 5 in MMS200MI GetItmBasic with Item number (ITNO) as input.
· · · · · · · · · · · · · · · · · · ·	Genumbasic with item number (11140) as input.
AdvanceShipNotice/AdvanceShipNoticeUnit/UserArea For Process:	For Process:
1) MHEXRD.H2USD1	1) User-defined field 1-5
MHEXRD.H2USD2	The field indicates the user-defined fields 1-5.
MHEXRD.H2USD3	If Property/NameValue = USD1, set @name='FreeField1'.
MHEXRD.H2USD4	If Property/NameValue = USD2, set @name='FreeField2'.
MHEXRD.H2USD5;	If Property/NameValue = USD3, set @name='FreeField3'.
MHS850MI.LstExpRecDetail	If Property/NameValue = USD4, set @name='FreeField4'.
O) MUDDNO MOUDO:	If Property/NameValue = USD5, set @name='FreeField5'.
2) MHPRNS.J1SUDO;	2) Delivery note
MHS800MI.LstExpRecPacDet	2) Delivery note The field indicates the delivery note
3) MHPRNS.J1DNDT;	The field indicates the delivery note. If Property/NameValue=SUDO, set @name='M3.DeliveryNote'
MHS800MI.LstExpRecPacDet	ii i Toporty/Marile value-0000, set whathe-180.DelivelyNote
; /	3) Delivery note date
•	The field indicates the delivery note date.
	If Property/NameValue=DNDT, set @name='M3.DeliveryNoteDate'

A (84 (//D . //D	
AssetMaster/IDs/ID FFASMA.FMASID, FMSBNO; FAS001MI/GetAsset	The field indicates the unique alpha-numeric ID of a fixed asset.
Occupation Fadita	It is a concatenation of Fixed asset ID (ASID) <10> + Subnumber (SBNO) <3> without separator.
@accountingEntity FFASMA.FMCONO, FMDIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD for this object has been published.
@lid	The field indicates the logical ID of the system.
AssetMaster/DisplayID FFASMA.FMASID, FMSBNO; FAS001MI/GetAsset	The field indicates the Fixed asset ID (ASID) and Subnumber (SBNO) with '-' as separator and no blanks (XXXXXXXXXXNNN).
	Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data.
AssetMaster/LastModificationDateTime FFASMA.FMLMDT; FAS001MI/GetAsset	The field indicates the date the record last was changed.
AssetMaster/LastModificationPerson/IDs/ID FFASMA.FMCHID; FAS001MI/GetAsset	The field indicates the User-ID of the person that last changed the fixed asset.
AssetMaster/LastModificationPerson/Name CMNUSR.JUNAME: MNS150MI/GetUserData	The field indicates the Name (NAME) of the User-ID (CHID).
AssetMaster/DocumentDateTime FFASMA.FMRGDT, FMRGTM; FAS001MI/GetAsset	The field indicates the date and time that the object was created.
AssetMaster/Description FFASMA.FMTXT1, FMTXT2; FAS001MI/GetAsset	The field indicates the fixed asset description.
AssetMaster/Note CSYTAB.CTTX15 CSYTAB.PARM FFASDM.FDVTAD FFASDM.FDVTAD FFASDM.FDVTDP FFASDM.FDVTDP FFASDM.FDDTTB FFASDM.FDDPBC FFASDM.FDSVAL FFASDM.FDSVAL FFASDM.FDSTPC FFASDM.FDHYAD FFASDM.FDDTLC FFASDM.FDDTLC FFASDM.FDDTLP FFASDM.FDFDAM; FAS002MI/Lst	The field indicates the following additional information related to a depreciation type (Asset Book): 1) Name (TX15) - Alpha 15. 2) Report type (RPTT) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-Economic, 1-Fiscal, 2-Technical and 3-Financial agreement. 3) Depreciation period range (DTPE) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-No depreciation, 1-Annual, 2-Biannual, 3-Quarterly, 4-Bimonthly and 5-Monthly. 4) External/internal transactions (EIA1) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 1-External and 2-Internal. 5) Depreciation at sales/scrap (DESS) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-Until sales/scrap date, 1-Until end of previous period, 2-Until end of previous fiscal year, 3-Until end of period, 4-Until end of fiscal year, 5-Until previous day of sales/scrap date and 6-Based on semi-annual adjustment. 6) Daily depreciation (DYDE) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-Calculated per period, 1-Calculated daily, number of days first year and 2-Calculated daily, number of days all years. 7) Stop value Percent(PER3) - Numeric 3,0. 8) Sales Accounting method (ACME) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-Different accounts for debit and credit and 1-Different account for gain and loss. 9) Value type basis (BVAT) - Numeric 2,0. 10) Value type cumulative depr YTD (ADTY) - Numeric 2,0. 11) Value type depr plan (VTDP) - Numeric 2,0. 12) Value type depr plan (VTDP) - Numeric 3,0 (YYYYPP). 14) Depreciation plan (DTTB) - Alpha 5. 15) Period type (DPBC) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 1-Acquisition period/date, 2-Manufacturing period/date, 3-Activation period/date, 4-Buidling permit period/date and 5-Revaluation date. 16) Depreciation share (NPE

ASSELIVIASLEI	
	20) Acquisition - depreciation adjustment (HYAD) - Numeric 1,0 + Description based on the value (only value in case of other than listed): 0-No adjustment, 1-Mid-Year, 2-Mid-Quarter and 3-Mid-Month. 21) Automatic change of depreciation method (DTLC) - Alpha 1 + Description based on the value (only value in case of other than listed): 0-No, 1-Yes, method 1, 2-Yes, method 2 and 3-Yes, method 3. 22) Digressive to linear transfer period (DTLP) - Numeric 6,0
	(YYYYPP). 23) Method for depreciation adjustment (FDAM) - Numeric 1,0 + Description based on the value (only value in case of other than
@noteID	listed): 0-No and 1-Yes.
	The field indicates the field name for the information related to an depreciation type (Asset Book): 1) Name (TX15): noteID="Name"
	2) Report type (RPTT): noteID="ReportType" 3) Depreciation period range (DTPE): noteID="DeprPeriodRange" 4) External/internal transactions (EIA1): noteID="ExternalInternalDepr' 5) Depreciation at sales/scrap (DESS): noteID="DeprSalesScrap" 6) Daily depreciation (DYDE): noteID="DailyDepr" 7) Stop value Percent(PER3): noteID="StopValuePercentage" 8) Sales Accounting method (ACME):
	noteID="SalesAccountingMethod"
	9) Value type basis (BVAT): noteID="ValueTypeBasis" 10) Value type cumulative depr (VTAD): pateID="ValueTypeDeprCymulative"
	noteID="ValueTypeDeprCumulative" 11) Value type cumulative depr YTD (ADTY):
	noteID="ValueTypeDeprThisYear"
	 12) Value type depr plan (VTDP): noteID="ValueTypeDeprPlan" 13) Last depreciation period (LPER): noteID="LastDeprPeriod" 14) Depreciation plan (DTTB): noteID="DeprPlan" 15) Period type (DPBC): noteID="PeriodType"
	16) Depreciation share (NPER): noteID="DeprShare" 17) Stop value (SVAL): noteID="StopValue"
	18) Below 0 (BELZ): noteID="BelowZero"
	19) Processing of remaining value (STPC):
	noteID="ProcessRemainingValue" 20) Acquisition - depreciation adjustment (HYAD):
	noteID="DeprAdjustmentAcquisition"
	21) Automatic change of depreciation method (DTLC): noteID="AutoChangeDeprMethod"
	22) Digressive to linear transfer period (DTLP):
	noteID="DigressiveToLinearTransferPeriod" 23) Method for depreciation adjustment (FDAM):
@type	noteID="MethodDeprAdjustment"
FFASDM.FDDPTP; FAS002MI/Lst	Set to "AssetBook" + "_" + value of field Depreciation type (DPTP), format "AssetBook nn".
AssetMaster/Status/Code FFASMA.FMFAST; FAS001MI/GetAsset	The field indicates the status of the Fixed asset.
	 Status 1-Normal fixed asset: Set to "Open" Status 3-Fixed asset under activation: Set to "Pending" Status 5-Preliminary fixed asset: Set to "Pending" Status 7-Budget fixed asset: Set to "Pending" Status 8-Fully depreciated fixed asset: Set to "Open" Status 9-Sold or disposed fixed asset: Set to "Closed"
	Note: Set to 'Deleted' for Replace_BOD for delated fixed asset (e.g. preliminary asset activated with same or different ID or rename of asset).
AssetMaster/Status/EffectiveDateTime FFASMA.FMRGDT, FMRGTM, FMSPER; FAS001MI/GetAsset	The field indicates the date and time depending on the status.
	If Status (FAST) is equal 9 and Sales period/date (SPER) not zero, set to Sales period/date (SPER), otherwise to Entry date and time (RGDT+RGTM).
AssetMaster/Status/ReasonCode FFASMA.FMFAST, FMSPER, FMCINO; FAS001MI/GetAsset	The field indicates the reason for the status codes related to the M3 process Status 1-Normal fixed asset: Set to "Normal" - Status 3-Fixed asset under activation: Set to "UnderActivation"
	 Status 5-Preliminary fixed asset: Set to o "Preliminary" Status 7-Budget fixed asset: Set to "Budget"
	 Status 8-Fully depreciated fixed asset: Set to "Depreciated" Status 9: a) If Sales period (SPER) not zero and Invoice number (CINO) not blank: Set to "Sold"
	b) If Sales period (SPER) not zero and Invoice number (CINO)

	blank: Set to "Disposed" c) If Sales period (SPER) zero and Invoice number (CINO) blank: Set to "Splitted/Divided"
AssetMaster/Name FFASMA.FMFADS; FAS001MI/GetAsset	The field indicates a shorter name of the fixed asset.
AssetMaster/AssetIDs/SerialNumber	TI C.I
FFASMA.FMSRNO; FAS001MI/GetAsset AssetMaster/ItemInstance/ItemID/ID	The field indicates the Serial number.
FFASMA.FMITNO; FAS001MI/GetAsset	The field indicates the item number.
@accountingEntity	The information is only included in case integration to equiment is used.
FFASMA.FMCONO, FMDIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
AssetMaster/ItemInstance/ServiceIndicator	Set to "false"
AssetMaster/ItemInstance/SerializedLot/SerialNumber FFASMA.FMBANO; FAS001MI/GetAsset	The field indicates the lot number.
	The information is only included in case integration to equiment is used.
AssetMaster/ItemInstance/SerializedLot/ProductionDate FFASMA.FFMPER: FAS001MI/GetAsset	The field indicates the date the asset was manufactured.
AssetMaster/ItemInstance/StorageLocation/IDs/ID	
FFASMA.FMLOC1; FAS001MI/GetAsset	The field indicates the location 1 of an asset, which enables you to keep track of assets.
	Note: Location 2 and 3 are currently not included.
AssetMaster/OwnedQuantity FFASMA.FMFAQT; FAS001MI/GetAsset	The field indicates the number of physical objects represented by the fixed asset.
AssetMaster/AcquisitionDateTime FFASMA.FMPPER; FAS001MI/GetAsset	The field indicates the date on which the fixed asset was purchased.
AssetMaster/CommissionDateTime FFASMA.FMAPER; FAS001MI/GetAsset	The field indicates from which period the fixed asset has been used.
AssetMaster/Cost/CurrencyExchangeRate/SourceCurrencyCode FFASMA.FMCUCD; FAS001MI/GetAsset	The field indicates the abbreviation for the currency.
AssetMaster/Cost/CurrencyExchangeRate/RateNumeric FFASMA.FMARAT; FAS001MI/GetAsset	The field indicates the exchange rate for the chosen currency.
AssetMaster/SoldScrapDateTime FFASMA.SPER; FAS001MI/GetAsset	The field indicates the Sales period/date for sold or disposed assets.
AssetMaster/FixedAsset/AssetBook/AssetBookCode FFASDM.FDDPTP; FAS002MI/Lst	The field indicates the Depreciation type that is connected to the
TI AGDIVI.I DDI TI , I AGGOZIVII/ESC	Fixed asset.
	One section of FixedAsset/AssetBook per depreciation type connected is included.
@aaaaunting/Futitu	Additional information about the Depreciation type per asset is sent as 'Note' information.
@accountingEntity FFASMA.FMCONO, FMDIVI; /	The field indicates the company and division, displayed as CONO DIVI.
AssetMaster/FixedAsset/AssetBook/Description CSYTAB.CTTX40; FAS002MI/LSt	The field indicates to the description of the Depreciation type.
AssetMaster/FixedAsset/AssetBook/PostingBookIndicator CSYTAB.CTPARM; FAS002MI/Lst	The field indicates if depreciation is to create updates in the general ledger (GL).
	Set to 'true' if transfer to FIM is selected, otherwise set to 'false'
AssetMaster/FixedAsset/AssetBook/AssetLife FFASDM.FDNOMT; FAS002MI/Lst	The field indicates the productive lifetime of the fixed asset, expressed in month.
AssetMaster/FixedAsset/AssetBook/DepreciationMethodCode FFASDM.FMDPMD; FAS002MI/Lst	The field indicates the depreciation method that is connected to the depreciation type.
@listID FFASDM.FMDPMD; FAS002MI/Lst	The field indicates the depreciation method in text: - If DPMD=1: Set to "LinearDepreciation - If DPMD=2: Set to "DecliningBalance - If DPMD=3: Set to "UserDefined" - If DPMD=4: Set to "MACRS_Formula" - If DPMD=5: Set to "MACRS_UserDefined" - If DPMD=6: Set to "RentalRevenuePercentage" - If DPMD=7: Set to "UsageBasedDepreciation"

	- If DPMD=8: Set to "FinancialAgreement"
AssetMaster/FixedAsset/AssetBook/DepreciationStatusCode	- If DPMD=9: Set to "OtherLocal"
FFASDM.FDFAST; FAS002MI/Lst	The field indicates the Depreciation Status If status 1: Set to "Depreciating" - If status 8: Set to "FullyDepreciated" - If status 9: Set to "NotDepreciated"
AssetMaster/Classification/Codes/Code	
FFASMA.FMACAT; FAS001MI/GetAsset	The field indicates the different classification codes of an asset: a) Fixed asset group (ACAT) using listID="FixedAssetGroup".
@sequence	Set to a sequence number for each code included.
@listID	The field indicates the field description of the different classification
	codes of an asset: a) Set to "FixedAssetGroup" for field ACAT.
@accountingEntity	
FFASMA.FMCONO, FMDIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
AssetMaster/UserArea	
FFASMA.FMSPYN, FMPYNO, FMCINO, FMLCNO, FMLCCO, FMPCDA, FMPHCN, FMPHSN, FMLRVD, FMINNO, FMAIT2-AIT7, FMVONO, FMVSER; FAS001MI/GetAsset	The field indicates the following additional information related to an asset: 1) Payee (SPYN): type=StringType and name "lcl.SupplierID"
	2) Accounting entity of SupplierID (CONO_DIVI): type=StringType and name "lcl.SupplierAE" - Note: Only included if "lcl.SupplierID" (SPYN) included.
	3) Payer (PYNO): type=StringType and name "lcl.CustomerID" 4) Accounting entity of CustomerID (CONO_DIVI): type=StringType and name "lcl.CustomerAE" - Note: Only included if
	"lcl.CustomerID" (PYNO) included. 5) Invoice number (CINO) for asset sold: type=StringType and name "lcl.InvoiceNo"
	6) Leasing agreement (LCNO): type=StringType and name "lcl.LeasingAgreement"
	7) Leasing company (LCCO): type=StringType and name "lcl.LeasingCompany"
	8) Last physical inventory date (PCDA): type=DateType and name "Icl.PhysicalInventoryLastDate"
	9) Physical inventory number (PHCN): type=IntegerType and name "Icl.PhysicalInventoryNo"
	10) Physical inventory run number (PHSN): type=IntegerType and name "Icl.PhysicalInventoryRunNo"
	11) Physical inventory text (PHCT): type=StringType and name "Icl.PhysicalInventoryText"
	12) Last revaluation date (LRVD): type=DateType and name "lcl.RevalutionLastDate" 13) Individual item number (INNO): type=StringType and name
	"Icl.IndividualItemNo" 14) Accounting dimension 2 (AIT2): type=StringType and name
	"Icl.Accounting dimension2" 15) Accounting dimension 3 (AIT3): type=StringType and name
	"Icl.Accounting dimension3" 16) Accounting dimension 4 (AIT4): type=StringType and name
	"Icl.AccountingDimension4"
	17) Accounting dimension 5 (AIT5): type=StringType and name "Icl.AccountingDimension5" 18) Accounting dimension 6 (AIT6): type=StringType and name
	"Icl.Accounting dimension6" 19) Accounting dimension 7 (AIT7): type=StringType and name
	"lcl.AccountingDimension7" 20) Voucher number (VONO): type=IntegerType and
	name="lcl.VoucherNo" 21) Voucher series (VSER): type=StringType and
	name="lcl.VoucherNoSeries"
	Attribute "sequence" is set to an incremental value for each NameValue included.
AssetMaster/AssetTypeCode FFASMA.FMFATP; FAS001MI/GetAsset @accountingEntity	The field indicates the type of equipment used to classify fixed assets
FFASMA.FMCONO, FMDIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
AssetMaster/CostCenterCode FFASMA.FMAIT2 - FMAIT7; FAS001MI/GetAsset	The field indicates an accounting identity in an accounting dimension The dimension used for Cost center is retrieved via the data translation (CRS881) defined on division level for: - Message: 'AssetMaster'

Assettituster	
	- Parent element: 'AssetMaster'
	- Element: 'CostCenterCode'
	The translation must be defined on division level:
	- M3 data (MVXD) should be left blank
	- Message data (MBMD) set to the accounting dimension to be used
	(value AIT2, AIT3, AIT4, AIT5, AIT6 or AIT7 allowed).
	Note: Field AIT2 used in case of no data translation found.
AssetMaster/BuiltYear	
FFASMA.FMBPER; FFAS001MI/GetAsset	The field indicates the year the asset was built.
	Retrieved from the Building permit date (BPER), position 1-4.
AssetMaster/WarrantyCoverage/CoverageByDate/ExpireDateTime FFASMA.FMWADT; FAS001MI/GetAsset	The field indicates the date the warranty expires.

7.1000111411041011	
AssetTransaction/AssetTransactionHeader/DocumentID/ID FFAHIS.FHASID, FHSBNO, FHVATP, FHRGDT, FHRGTM, FHTSTM; FAS220MI/GetFAHistoryDtl	The field indicates the unique key for the fixed asset history transaction.
@aaaauntiinu Futifu	It is a concatenation of the following fields (without separator): - Fixed asset ID(ASID) <10> + - Subnumber (SBNO) <3> + - Value type (VATP) <2> + - Entry date (RGDT) <8> + - Entry time (RGTM) <6> + - Time stamp (TSTM) <26>
@accountingEntity FFAHIS.FHCONO, FHDIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD for this object has been published.
@lid	The field indicates the logical ID of the system.
AssetTransaction/AssetTransactionHeader/DisplayID FFAHIS.FHASID, FHSBNO, FHVATP, FHVPER; FAS220MI/ GetFAHistoryDtl	The field indicates the Fixed asset ID (ASID), Subnumber (SBNO), Value type (VATP) and Value period (VPER) with '-' as separator (XXXXXXXXXXNNN-NN-YYYYPP).
	Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data.
AssetTransaction/AssetTransactionHeader/LastModificationDateTime FFAHIS.FHLMDT; FAS220MI/GetFAHistoryDtl	The field indicates the date the record last was changed.
AssetTransaction/AssetTransactionHeader/LastModificationPerson/IL	Os/ID
FFAHIS.String; FAS220MI/GetFAHistoryDtl @accountingEntity	The field indicates the User-ID of the person that last changed the fixed asset.
FFAHIS.FHCONO, FHDIVI; /	The field indicates the company and division, displayed as CONO DIVI.
AssetTransaction/AssetTransactionHeader/LastModificationPerson/N CMNUSR.JUNAME; MNS150MI/GetUserData	lame The field indicates the Name (NAME) of the User-ID (CHID).
AssetTransaction/AssetTransactionHeader/DocumentDateTime FFAHIS.FHRGDT, FHRGTM; FAS220MI/GetFAHistoryDtl	The field indicates the date and time that the object was created.
AssetTransaction/AssetTransactionHeader/Status/Code	Set to "Open".
	Note: Set to 'Deleted' for Replace_BOD for delated fixed asset transaction (preliminary asset activated with different ID, rename of asset or when moving to depreciation cumulative) and then retrieved from event data.
AssetTransaction/AssetTransactionHeader/Status/EffectiveDateTime FFAHIS.FHRGDT, FHRGTM; FAS220MI/GetFAHistoryDtl	The field indicates the entry date and entry time.
AssetTransaction/AssetTransactionHeader/Asset/ID FFAHIS.FHASID, FHSBNO; FAS220MI/GetFAHistoryDtl	The field indicates the unique alpha-numeric ID of a fixed asset.
	It is a concatenation of Fixed asset (ASID) <10> + Subnumber (SBNO) <3> without separator (Note: Same format as AssetMaster/ IDs/ID).
	Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data.
@accountingEntity FFAHIS.FHCONO, FHDIVI; /	The field indicates the company and division, displayed as CONO DIVI.
AssetTransaction/AssetTransactionHeader/Asset/Description FFASMA.FMTXT1, FMTXT2; FAS001MI/GetAsset	The field indicates the fixed asset description.
AssetTransaction/AssetTransactionHeader/InitializationIndicator	Set to 'true' in case the BOD is created via Initial load (EVS006).
AssetTransaction/AssetTransactionHeader/SupplierParty/PartyIDs/ID FFASMA.FMSPYN; FAS001MI/GetAsset @accountingEntity FFASMA.FMCONO, FMDIVI; /	The field indicated the Payee ID (SPYN) of a fixed asset.
	The field indicates the company and division, displayed as CONO DIVI.
AssetTransaction/AssetTransactionHeader/SupplierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicated the Name for the Payee of a fixed asset.
AssetTransaction/AssetTransactionHeader/UserArea FFAHIS.FHVPER; FAS002MI/GetFAHistoryDtl	The field indicates the following additional information related to an asset: 1) Finanical year (VPER, pos 1-4): type=IntegerType and name
Infor May 26, 202	"Icl.FiscalYear"

ASSELTIATISACTION	
	2) Financial period (VPER, pos 5-6): type=IntegerType and name "Icl.FiscalPeriod"
	Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data.
AssetTransaction/AssetTransactionLine/LineNumber	Set to '1' (currently one transaction per BOD is processed).
	Note: Also included for Replace BOD with Status/Code='Deleted'.
AssetTransaction/AssetTransactionLine/DocumentReference @type	Sat to "Sauraa Svatom JauraalEntry"
AssetTransaction/AssetTransactionLine/DocumentReference/Docum	Set to "SourceSystemJournalEntry".
FFAHIS.FHVPER, FHVSER, FHVONO; FAS220MI/GetFAHistoryDtl	The field indicates a concatenation of Year (VPER, pos 1-4) <4> + Voucher series number (VSER) <3> + Voucher number (VONO) <8> without separator. The data in Year always consumes maximum length, data in Voucher series number consumes between 1 and 3 positions (set to "" if empty), and if the data in Voucher number does not consume the maximum length, the rest is filled up with zeroes on the left side. E.g. 2019100001016 means Year=2019, Voucher series number=1 and
@accountingEntity FFHIS.FHCONO, FHDIVI; /	Voucher number=00001016 The field indicates the company and division, displayed as
	CONO_DIVI.
AssetTransaction/AssetTransactionLine/AssetBookCode FFAHIS.FHVATP; FAS220MI/GetFAHistoryDtl @accountingEntity	The field indicates the depreciation type for the fixed asset based on the value type (VATP). The value is retrieved via the data translation (CRS881) for: - Message: 'AssetTransaction' - Parent element: 'AssetTransactionLine' - Element: 'AssetBookCode' The translation must be defined on division level: - M3 data (MVXD) set to the applicable Value type (VATP) as 2 digits (e.g. value type 1 must be defined as 01). - Message data (MBMD) set to one of the following values (*): a) The related depreciation type (DPTP) as 2 digits (e.g. depreciation type 2 defined as 02). b) Set to '00' for value types applicable for all depreciation types. c) Set to 'AM' for value types related to depreciation base, depreciation this year and depreciation accumulated. d) Set to 'DP' for value types related to depreciation plan. Note: Element not created if no translation found (transaction not related to a depreciation type. (*) The value types that must be translated and the message data to be used are described in the Infor M3 CE Core Configuration Guide for Infor Localization Services Platform. Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data (data translation performed).
@accountingEntity FFAHIS.FHCONO, FHDIVI; /	The field indicates the company and division, displayed as CONO DIVI.
AssetTransaction/AssetTransactionLine/Amount FFAHIS.FHFAVC; FAS220MI/GetFAHistoryDtl	The field indicated the amount in foreign currency related to the activity of the asset. Note: Amounts related to e.g. depreciation are stored as positive values in M3 and must be reversed in the output. The indication for reverse sign is retrieved via the data translation (CRS881) for:
	 Message: 'AssetTransaction' Parent element: 'AssetTransactionLine' Element: 'ReverseSign' The translation must be defined on division level: M3 data (MVXD) set to the applicable Value type (VATP) as 2 digits (e.g. value type 1 must be defined as 01). The value types for which the amount sign must be reversed are described in the Infor M3 CE Core Configuration Guide for Infor Localization Services Platform. Message data (MBMD) set to 1 for reverse sign (reverse sign will not be done if any other value (e.g. 0) is used or if the Value type (VATP) is not found in the translation).
@currencyID FFAHIS.FHCUCD; FAS220MI/GetFAHistoryDtl	The field indicates the currency code related to the amount in foreign currency.

Infor May 26, 2023 29

Generic translation is used to translate CUCD according to ISO 4217.

AssetTransaction/AssetTransactionLine/BaseAmount

FFAHIS.FHFAVA; FAS220MI/GetFAHistoryDtl

The field indicated the amount in local currency related to the activity of the asset.

Note: Amounts related to e.g. depreciation are stored as positive values in M3 and must be reversed in the output. The indication for reverse sign is retrieved via the data translation (CRS881) for:

- Message: 'AssetTransaction'
- Parent element: 'AssetTransactionLine'
- Element: 'ReverseSign'

The translation must be defined on division level:

M3 data (MVXD) set to the applicable Value type (VATP) as 2 digits (e.g. value type 1 must be defined as 01). The value types for which the amount sign must be reversed are described in the Infor M3 CE Core Configuration Guide for Infor Localization Services Platform.
Message data (MBMD) set to 1 for reverse sign (reverse sign will not be done if any other value (e.g. 0) is used or if the Value type (VATP) is not found in the translation).

The field indicates the currency code related to the amount in local currency.

Generic translation is used to translate CUCD according to ISO 4217.

@currencyID

CMNDIV.CCLOCD; FAS220MI/GetFAHistoryDtl

AssetTransaction/AssetTransactionLine/AmountToFunctionalExchangeRate/RateNumeric

FGLEDG.EGARAT; FFAS220MI/GetFAHistoryDtl

The field indicates the exchange rate for the transaction when a voucher number is connected and already available in the General Ledger table (FGLEDG), otherwise no exchange rate is included.

AssetTransaction/AssetTransactionLine/Classification/Codes/Code

FFAHIS.FHMVCD; FAS220MI/GetFAHistoryDtl

The field indicates the different classification codes of an asset transaction:

- a) Recoding code (MVCD) using listID="RecodingCode" following values must be sent with a fix description per code:
- MVCD = 0: Set to 0-DefaultValue
- MVCD = 1: Set to 1-ExtraordinaryDeprMethod1
- MVCD = 2: Set to 2-ExtraordinaryDeprMethod2
- MVCD = 3: Set to 3-Recoded
- MVCD = 4: Set to 4-Split/Divide
- MVCD = 9: Set to 9-Reversed

Other values than above: Set to n-NotDefined (with n = value of field).

b) Detailed asset activity via data translation for the value type (VATP) using listID="DetailedAssetActivity".

The value is retrieved via the data translation (CRS881) for:

- Message: 'AssetTransaction'
- Parent element: 'AssetTransactionLine'
- Element: 'DetailedAssetActivity'

The translation must be defined on division level:

- M3 data (MVXD) set to the applicable Value type (VATP) as 2 digits (e.g. value type 1 must be defined as 01).
- Message data (MBMD) set to the Description are described in the Infor M3 CE Core Configuration Guide for Infor Localization Services Platform

Note: Set to 'NotDefined' in case of no data translation found. Note: Also included for Replace_BOD with Status/Code='Deleted' and then retrieved from event data (data translation performed).

Set to a sequence number for each code included.

The field indicates the field description of the different classification codes of an asset transaction:

- a) Set to "RecodingCode" for field MVCD.
- Set to "Detailed Asset Activity" for value from data translation for field VATP.

The field indicates the company and division, displayed as CONO DIVI.

@accountingEntity

@sequence

@listID

FFAHIS.FHCONO, FHDIVI; /

AssetTransaction/AssetTransactionLine/UserArea

FFAHIS.FHAIT1-7, FFAHIS.FHVONO, FFAHIS.FHVSER, FFAHIS.FHVDSC, FFAHIS.FHVATP, FFAHIS.FHZREV, FFAHIS.FHADSH, FFAHIS.FHUSSH, CSYTAB.CTTX40.-; FAS220MI/GetFAHistoryDtl

The field indicates the following additional information related to an asset:

- 1) Accounting dimension 1 (AIT1): type=StringType and name "lcl.AccountingDimension1"
- 2) Accounting dimension 2 (AIT2): type=StringType and name "lcl.AccountingDimension2"
- 3) Accounting dimension 3 (AIT3): type=StringType and name "lcl.AccountingDimension3"
- 4) Accounting dimension 4 (AIT4): type=StringType and name "lcl.AccountingDimension4"

- 5) Accounting dimension 5 (AIT5): type=StringType and name "Icl.AccountingDimension5"
- 6) Accounting dimension 6 (AIT6): type=StringType and name "lcl.AccountingDimension6"
- 7) Accounting dimension 7 (AIT7): type=StringType and name "Icl.AccountingDimension7"
- 8) Voucher number (VONO): type=IntegerType and name="lcl.VoucherNo"
- 9) Voucher series (VSER): type=StringType and name="Icl.VoucherNoSeries"
- 10) Voucher name (VDSC): type=StringType and name="lcl VoucherName"
- 11) Value type (VATP): type=IntegerType and name="lcl.ValueType" (2 digits)
 12) Value type description (TX40): type=StringType and
- name="lcl.ValueTypeDescription"
- 13) Zero revenue (ZREV): type=StringType and name="lcl.ZeroRevenue"
- 14) Share (ADSH): type=StringType and name="lcl.Share" (Note: Amount with 2 decimals)
- 15) Used share (USSH): type=StringType and name="Icl.UsedShare" (Note: Amount with 2 decimals)

DIIIOIWateriais	
BillOfMaterials/BillOfMaterialsHeader/DocumentID/ID	For Syring
For Sync: MPDHED.PHPRNO MPDHED.PHSTRT.; /	For Sync: The field indicates the document ID. It is a concatenation of Product number (PRNO) <15> + Product structure type (STRT) <3> without separator, he position of each field is determined by its maximum.
For Process: 1) MPDHED.PHPRNO MPDHED.PHSTRT	separator. he position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the ID except for the last one. The last field in the concatenation, in this case STRT, is trimmed if it does not
2) MPDMFD.MDMFPC MPDMFD.MDSTRT.; /	consume the maximum length.
	For Process: 1) The field indicates the product number (PRNO) <15>and structure type (STRT) <3> concatenated wthout separator. The position of each field is determined by its maximum length, specified in brackets. If PRNO does not consume the maximum length, the rest is filled up with spaces. STRT is trimmed if it is less than 3 characters.
	2) The field indicates the alternate product structure (MFPC) <15>and structure type (STRT) <3> concatenated without separator. The position of each field is determined by its maximum length, specified in brackets. If MFPC does not consume the maximum length, the rest is filled up with spaces. STRT is trimmed if it is less than 3 characters. This will be the ID if BOD is triggered from MPDMFD table.
@accountingEntity MPDHED.PHCONO CMNDIV.CCDIVI.; /	For Sync: The field indicates the company and division, displayed as CONO_DIVI.
@leastion	For Process: The field indicates the company and division, displayed as CONO_DIVI.
<pre>@location For Sync: MPDHED.PHFACI;/</pre>	For Sync: The field indicates the warehouse ID.
For Process: MPDHED.PHFACI; / @variationID	For Process: The field indicates the facility.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
BillOfMaterials/BillOfMaterialsHeader/DocumentID/RevisionID	
For Process: MPDVER.VRVRSN . /	For Process: The field indicates the product structure version.
BillOfMaterials/BillOfMaterialsHeader/DisplayID	
For Process: MPDHED.PHPRNO	For Process: The field indicates the product number.
BillOfMaterials/BillOfMaterialsHeader/LastModificationDateTime For Sync:	For Sync:
MPDHED.PHLMTS ; /	The field indicates the last modification date and time.
BillOfMaterials/BillOfMaterialsHeader/LastModificationPerson/IDs/ID	5.0
For Sync: MPDHED.PHCHID;/ @accountingEntity	For Sync: The field indicates the ID of the person who last modified the record.
For Sync: MPDHED.PHCONO CMNDIV.CCDIVI	For Sync: The field indicates the company and division, displayed as CONO_DIVI.
BillOfMaterials/BillOfMaterialsHeader/Description	
For Process:	For Process:
MITMAS.MMITDS; PDS001MI/Get MPDVER.VRTX40.; /	The field indicates the product structure description if nonversioned. The field indicates the product structure description if versioned.
BillOfMaterials/BillOfMaterialsHeader/Note	,
For Sync: MPDHED.PHPRTX	For Sync: The field indicates an optional text of at most 30 characters.
; PDS001MI /Get For Process:	For Process: The field indicates an optional text.
MPDHED.PHPRTX ; PDS001MI/Get	
BillOfMaterials/BillOfMaterialsHeader/Status/Code	

BIIIOTWateriais	
For Sync: MPDHED.PHSTAT ; PDS001MI/Get	For Sync: The field indicates the status of the record.
For Process: MPDHED.PHSTAT ; PDS001MI/Get	Set to 'Pending' if status is 10. Set to 'Open' if status is 20. Set to 'Closed' if status is 90. Set to 'Deleted' if the record is deleted.
	For Process: The field indicates the status (STAT) of the product. Set to 'Pending' if STAT = 10. Set to 'Open' if STAT = 20. Set to 'Deleted' if STAT = 90.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/ID	
For Sync: MPDHED.PHPRNO ; PDS001MI/Get	For Sync: The field indicates the product number.
For Process: 1) MPDHED.PHPRNO; PDS001MI.Get 2) MPDMAT.PMMTNO PDS002MI.LstComponent 3) MPDMFD.MDOTNO.; /	For Process: 1) The field indicates the product number. 2) The field indicates the by-product or co-product. 3) The field indicates the output item if BOD is triggered from MPDMFD table.
@accountingEntity For Sync: MPDHED.PHCONO CMNDIV.CCDIVI .; /	For Sync: The field indicates the company and division, displayed as CONO_DIVI.
For Process: MPDHED.PHCONO CMNDIV.CCDIVI.; /	For Process: The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/RevisionID For Process: MITMAS.MMECVE; MMS200MI/GetItmTech	For Process: The field indicates the revision number (edition) for an item or document.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/UPCID	
For Process:	For Process:
MITPOP.MPPOPN ; MMS025MI/LstAlias	The field indicates the alias number which is an alternative ID for an individual item.
	Display if Alias qualifier (ALWQ) is UPC.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/GTIN	F., D.,
For Process: MITPOP.MPPOPN ; MMS025MI/LstAlias	For Process: The field indicates the alias number which is an alternative ID for an individual item.
	Display if Alias qualifier (ALWQ) is GTIN.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/ServiceIndicator	For Process: Set to 'false'.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Description	
For Sync: MITMAS.MMITDS ; PDS001MI/Get	For Sync: The field indicates the item description.
For Process: MITMAS.MMITDS; PDS001MI/Get or MMS200MI.GetItmBasic.; /	For Process: The field indicates the item description.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Classification/Code	s/Code
For Sync:	For Sync:
1) MPDHED.PHUPCO PDS001MI/Get	Cost summation The field indicates the full cost summation. Set attribute listID to 'Cost Summation'.
2) MPDHED.PHPSET PDS001MI/Get	Pricing method The field indicates how the sales price for the kit item and the detail
3) MPDHED.PHFSCD PDS001MI/Get	lines are calculated. Set attribute listID to 'Pricing Method'.
4-8) CSYPAR.CPPARM CRS175MI/GetGeneralParm.; /	Set to 'Not used' if Pricing method is 0. Set to 'Cost price' if Pricing method is 1. Set to 'Price hierarchy' if Pricing method is 2.
For Process: 1) MITMAS.MMITGR;	Set to 'Line value/qty' if Pricing method is 3.
MMS200Ml.GetItmBasic 2) MITMAS.MMITCL;	Kit control The field indicates how a product can be used as a kit in a customer

MMS200MI.GetItmBasic 3) MITMAS.MMBUAR: MMS200MI.GetItmBasic 4) MITMAS.MMITTY; MMS200MI.GetItmBasic 5) MITMAS.MMTPCD; MMS200MI.GetItmBasic 6) MITMAS.MMPRGP; MMS200MI.GetItmBasic 7) MPDHED.PHUPCO; PDS001MI.Get 8) MPDHED.PHPSET; PDS001MI.Get 9) MPDHED.PHFSCD; PDS001MI.Get 10) MPDHED.PHSRCD; PDS001MI.Get 11) MPDHED.PHSCCD; PDS001MI.Get 12) MPDMAT.PMMSEQ; PDS002MI.LstComponent 13) MPDOPE POOPNO; PDS002MI.LstComponent 14) MPDOPE.POPLGR; PDS002MI.GetOperation .; /

@sequence

@listID

order and purchase order. Set attribute listID to 'Kit Control'.

Set to 'Not used' if Kit control is 0.

Set to 'Fixed structure' if Kit control is 1.

Set to 'Variable structure' if Kit control is 2.

Set to 'Attr control' if Kit control is 3.

4) Standard Structure type

Set attribute listID to 'Standard Structure Type'.

Set to 'true' if the structure type used by the product is equal to the standard product structure type (STPM) in CRS787.

Otherwise, set to 'false'.

5) Critical Structure type

Set attribute listID to 'Critical Structure Type'.

Set to 'true' if the structure type used by the product is equal to the critical product structure type (STCM) in CRS787.

Otherwise, set to 'false'

6) KIT Structure type

Set attribute listID to 'KIT Structure Type'.

Set to 'true' if the structure type used by the product is equal to the KIT product structure type (STTK) in CRS787.

Otherwise, set to 'false'.

7) SCP Structure type

Set attribute listID to 'SCP Structure Type'.

Set to 'true' if the structure type used by the product is equal to the SCP product structure type (STSP) in CRS787.

Otherwise, set to 'false'.

8) MAI Structure type

Set attribute listID to 'MAI Structure Type'

Set to 'true' if the structure type used by the product is equal to the MAI product structure type (STMA) in CRS787.

Otherwise, set to 'false'

For Process:

1) The field indicates the item group.

Set attribute listID to 'Item Groups'

2) The field indicates the product group.

Set attribute listID to 'Product Groups'.

3) The field indicates the business area.

Set attribute listID to 'Business Sectors'. 4) The field indicates the Item Type.

Set attribute listID to 'Item Types'.

5) The field indicates the item category.

Set attribute listID to 'Item Classes'.

6) The field indicates the procurement group.

Set attribute listID to 'Buying Groups'.

7) The field indicates the full cost summation. Set attribute listID to 'Cost Summation'

8) The field indicates the pricing method.

Set attribute listID to 'Pricing Method'.

9) The field indicates the kit control.

Set attribute listID to 'Kit Control'.

10) The field indicates the reservation level.

Set attribute listID to 'Reservation Level'.

11) The field indicates the statistics level.

Set attribute listID to 'Statistics Level'. 12) The field indicates the sequence number.

Set attribute listID to 'ERP Line Reference'.

13) The field indicates the operation number.

Set attribute listID to 'Operation Number'.

14) The field indicates the work center.

Set attribute listID to 'Work Center'.

For Sync:

The field indicates the sequence number for the ordering of elements within

a document.

For Process:

The field indicates the sequence number.

- 1) Set to 'Cost Summation' if Classification/Codes/Code = UPCO.
- 2) Set to 'Pricing Method' if Classification/Codes/Code = PSET.

	3) Set to 'Kit Control' if Classification/Codes/Code = FSCD. 4) Set to 'Standard Structure Type' 5) Set to 'Critical Structure Type' 6) Set to 'KIT Structure Type' 7) Set to 'SCP Structure Type' 8) Set to 'MAI Structure Type'
	For Process: 1) Set to 'Item Groups' if Clasification/Codes/Code = ITGR. 2) Set to 'Product Groups' if Clasification/Codes/Code = ITCL. 3) Set to 'Business Sectors' if Clasification/Codes/Code = BUAR. 4) Set to 'Item Types' if Clasification/Codes/Code = ITTY. 5) Set to 'Item Classes' if Clasification/Codes/Code = TPCD. 6) Set to 'Buying Groups' if Clasification/Codes/Code = PRGP. 7) Set to 'Cost Summation' if Clasification/Codes/Code = UPCO. 8) Set to 'Pricing Method' if Clasification/Codes/Code = PSET. 9) Set to IsitID to 'Kit Control' if Clasification/Codes/Code = SRCD. 10) Set to 'Reservation Level' if Clasification/Codes/Code = SRCD. 11) Set to 'Reservation Level' if Clasification/Codes/Code = MSEQ. 13) Set to 'Operation Number' if Clasification/Codes/Code = OPNO. 14) Set to 'Work Center' if Clasification/Codes/Code = PLGR.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Classification/De	escription
For Process: CSYTAB.CTTX40; CRS175MI/LstCodesByLng CRS175MI/GetGeneralCode.CTTX40; /	For Process: The field indicates the description. CRS175MI/LstCodesByLng is called for fields ITGR, ITCL, BUAR and ITTY. CRS175MI/GetGeneralCode is called for field PRGP.
@languageID For Process: CSYTAB.CTLNCD; CRS175MI/LstCodesByLng	For Process: The field indicates the language.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/HazardousMaterials	Applicable only for fields ITGR, ITCL and BUAR.
For Process: MITMAS.MMITNO	For Process: The field indicates the item number which is tagged as hazardous
; MMS200MI/GetItmBasic BillOfMaterials/BillOfMaterialsHeader/OutputItem/Type	material (HAZI = 1). If HAZI = 0, this field is blank.
For Process: MPDMAT	For Process: If OutputItem/Item/D/ID is PRNO, set to 'Product'.
.PMBYPR; PDS002MI/LstComponent	If OutputItem/ItemID/ID is BYPR: Set to 'By-product' if BYPR = 1. Set to 'Co-product' if BYPR = 2.
	If OutputItem/ItemID/ID is OTNO, set to 'Alternate Structure'.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/EffectiveTimePer	riod/StartDateTime
For Process: MPDMAT.PMFDAT; PDS002MI/LstComponent MPDMFD.MDFDAT.; /	For Process: The field indicates the start date.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/EffectiveTimePe	
For Process: MPDMAT.PMTDAT; PDS002MI/LstComponent MPDMFD.MDTDAT; PDS023MI/GetAltStructure .; PDS002MI/LstComponent	For Process: The field indicates the end date.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/LineNumber For Process: MPDMAT.PMELRF ; PDS002MI/LstComponent	For Process: The field indicates the external line reference.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/YieldPercent	
For Sync: MPDHED.PHEXPC ; PDS001MI/Get	For Sync: The field indicates the product's theoretical yield.
For Process: MPDHED.PHEXPC; PDS001MI.Get MPDVER.VREXPC; PDS028MI.GetVersion.; /	For Process: The field indicates the yield percentage (EXPC). If product is version managed, value is retrieved from PDS028. Otherwise, value is retrieved from PDS001. Set value to 100 if EXPC is blank or 0.
BillOfMaterials/BillOfMaterialsHeader/OutputItem/Yield	
For Sync: MPDHED.PHBAQT; PDS001MI/Get For Process:	For Sync: The field indicates the net outcome of the production process for each production batch.
MPDHED.PHBAQT;	For Process:
Infor	2022

PDS001MI.Get The field indicates the yield quantity (BAQT). If product is version managed, value is retrieved from PDS028. Otherwise, value is MPDVER.VRBAQT: PDS028MI.GetVersion.; /

For Sync:

For Process:

For Process:

retrieved from PDS001. Set value to 1 if BAQT is blank.

@unitCode For Sync:

MITMAS.MMUNMS; PDS001MI/Get The field indicates an alternate unit of measure.

For Process: For Process:

MITMAS.MMUNMS The field indicates the unit of measure.

; PDS001MI/Get

For Process:

BillOfMaterials/BillOfMaterialsHeader/OutputItem/ProducedBaseUOMQuantity

MPDHED.PHEOQT The field indicates the normal order quantity of each item/warehouse, : PDS001MI/Get that is the quantity that should be ordered when a requirement arises.

The quantity often refers to the economical quantity.

The quantity often refers to the economical quantity.

The field indicates the normal order quantity of each item/warehouse,

that is the quantity that should be ordered when a requirement arises.

@unitCode

For Process: For Process:

MITMAS.MMUNMS The field indicates the unit of measure. : PDS001MI/Get

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Quantity

For Process: MPDHED.PHEOQT; PDS001MI.Get

MPDMAT.PMCNQT;

PDS002MI.LstComponent.; / @unitCode

For Process: For Process: The field indicates the unit of measure.

MITMAS.MMUNMS; PDS001MI.Get MPDMAT.PMPEUN; PDS002MI.LstComponent

BillOfMaterials/BillOfMaterialsHeader/BillOfMaterialType

For Sync: For Sync:

MPDHED.PHPSCL; PDS001MI/Get The field indicates the product structure class.

For Process: For Process:

MPDPSC The field indicates the product structure class type (PCLT). Set to "Discrete" if PCLT = 00. .PCPCLT; PDS075MI/GetStructClass

Set to "Formula" if PCLT = 11. Set to "Routing" if PCLT = 12. Set to "Bulk Item" if PCLT = 13. Set to "Packaging Material" if PCLT = 14. Set to "Packaged Item" if PCLT = 15.

Call PDS001MI.Get to retrieve PSCL to be used as input to

PDS075MI.GetStructClass.

BillOfMaterials/BillOfMaterialsHeader/PhantomIndicator

For Process: For Process:

MITMAS.MMTPCD The field indicates if the object is a phantom item or not.

Set to '1' if TPCD = 2. ; MMS200MI /GetItmBasic

BillOfMaterials/BillOfMaterialsHeader/ParentBillOfMaterialsReference/DocumentID/ID For Process: For Process:

MPDHED.PHDWNO The field indicates a unique ID for the drawing used in designing the

; PDS001MI/Get

The drawing number is set per item and can also be used as a search

key in both the item file and product structures.

@accountingEntity

For Process:

For Process: For Process:

MPDHED.PHCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; CONO DIVI.

BillOfMaterials/BillOfMaterialsHeader/Name

For Process: For Process:

MITMAS.MMITDS The field indicates the name for each item. : PDS001MI/Get

BillOfMaterials/BillOfMaterialsHeader/UsageDescription

For Sync: The field indicates the product structure type.

MPDHED.PHSTRT; PDS001MI/Get

MPDHED.PHSTRT MPDMFD.MDSTRT.; /

BillOfMaterials/BillOfMaterialsHeader/EffectiveTimePeriod/StartDateTime

For Process: For Process:

MPDVER.VRFDAT; PDS028MI/GetVersion The field indicates the start date of the version.

BillOfMaterials/BillOfMaterialsHeader/EffectiveTimePeriod/EndDateTime

BillOfMaterials

For Process: MPDVER.VRTDAT; PDS028MI/GetVersion	For Process: The field indicates the end date of the version.
BillOfMaterials/BillOfMaterialsHeader/Location	
Dtype	For Sync:
	Set to 'Site'.
BillOfMaterials/BillOfMaterialsHeader/Location/ID	
For Sync: MPDHED.PHFACI ; PDS001MI/Get	For Sync: The field indicates the facility ID.
For Process: MPDHED.PMFACI MPDMFD.MDFACI.; / DaccountingEntity	For Process: The field indicates the facility used.
For Sync: MPDHED.PHCONO CMNDIV.CCDIVI .; /	For Sync: The field indicates the company and division, displayed as CONO_DIVI.
For Process: MPDHED.PHCONO CMNDIV.CCDIVI.; /	For Process: The field indicates the company and division, displayed as CONO_DIVI.
BillOfMaterials/BillOfMaterialsHeader/Location/Name	
For Process: CFACIL.CFFACN ; CRS008MI/Get	For Process: The field indicate the name of the facility.
BillOfMaterials/BillOfMaterialsHeader/Yield	
For Process: MPDHED.PHBAQT ; PDS001MI/Get	For Process: The field indicates the yield quantity (BAQT). Set value to '1' if BAQ is blank.
@unitCode For Process:	For Process:
MITMAS.MMUNMS ; PDS001MI/Get	The field indicates the unit of measure.
sillOfMaterials/BillOfMaterialsHeader/DrawingAttachment/FileNa	
For Sync: MPDHED.PHDWNO ; PDS001MI/Get	For Sync: The field indicates a unique ID for the drawing used in designing the item.
For Process: MPDHED.PHDWNO; PDS001MI/Get	For Process: The field indicates the drawing number.
BillOfMaterials/BillOfMaterialsHeader/UserArea	F D
For Process: 1) MPDHED.PHPCBO; PDS001MI/Get 2) MPDHED.PHVRNF; PDS001MI/Get.; /	For Process: 1) Percentage BoM The field indicates whether the BoM is based on percentages or quantity. Set attribute name to "PercentageBoM". Set to "true" if PCBO = 1. Set to "false" if PCBO = 0.
	2) Version Managed The field indicates if the product structure is managed by version. Versions may be applied to product structures that represent manufacturing processes. Set attribute name to "VersionManaged". Set to "true" if VRNF = 1. Set to "false" if VRNF = 0.
BillOfMaterials/BillOfMaterialsLine/LineNumber	For Syno:
For Sync: 1) MPDMAT.PMMSEQ / PDS002MI.LstCompnent 2) MPDSUM.PSSEQN / PDS102MI.PSSEQN /	For Sync: The field indicates the component sequence number. IF the product is a product variant, material details will be retrieved from PDS103MI.LstSumBOM.
PDS103MI.LstSumBOM.; / For Process: MPDMAT.PMELRF	For Process: The field indicates the external line reference (ELRF) or material sequence number (MSEQ).
or MPDMAT.PMMSEQ.; PDS002MI/LstComponent	Display MSEQ if ELRF is empty or blank.
BillOfMaterials/BillOfMaterialsLine/Description	Sopialy mode in early to onipty of blank.
For Sync: 1) MITMAS.MMITDS / MMS200MI.GetItmBasic 2) MPDSUM.PSITDS / PDS103MI.LstSumBOM.; /	For Sync: The field indicates the component name or description. IF the product is a product variant, material details will be retrieved from PDS103MI.LstSumBOM.
For Process:	For Process: The field indicates the component name or description.

BillOfMaterials

MITMAS.MMITDS; MMS200MI/GetItmBasic	
BillOfMaterials/BillOfMaterialsLine/Note	
For Sync: MPDMAT.PMFMT1; PDS002MI/LstComponent	For Sync: The field indicates optional text.
For Process: MPDMAT.PMFMT1; PDS002MI/LstComponent	For Process: The field is used to enter optional text.
BillOfMaterials/BillOfMaterialsLine/Status/Code	The field to decorate of the field to the fi
For Sync:	For Sync:
MITMAS.MMSTAT; PDS002MI/LstComponent	The field indicates the component status.
For Process: MPDMAT.PMSTAT; PDS001MI/Get	Set to 'Pending' if status is 05, 10 or 15. Set to 'Open' if status is 20, 30, 40, or 50. Set to 'Closed' if status is 80 or 90. Set to 'Deleted' if status is 99.
	For Process: The field indicates the item status (STAT). Set to 'Pending' if STAT = 10. Set to 'Open' if STAT = 20. Set to 'Deleted' if STAT = 90.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/ID	
For Sync: 1) MPDMAT.PMMTNO / PDS002MI.LstComponent 2) MPDSUM.PSMTNO / PDS103MI.LstSumBOM.PMMTNO ; /	For Sync: The field indicates a component number. IF the product is a product variant, material details will be retrieved from PDS103MI.LstSumBOM.
,	For Process:
For Process:	The field indicates a component number.
MPDMAT.PMMTNO; PDS002MI/LstComponent @accountingEntity	
MPDHED.PHCONO CMNDIV.CCDIVI.; /	For Sync: The field indicates the company and division, displayed as CONO_DIVI.
	For Process: The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/RevisionID	
For Sync: MPDHED.PMFECV; PDS002MI/LstComponent	For Sync: The field indicates the from revision number.
For Process: MPDMAT.PMFECV; PDS002MI/LstComponent	For Process: The field indicates the revision number (edition) for an item or document.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/UPCID	
For Process: MITPOP.MPPOPN ; MMS025MI/LstAlias	For Process: The field indicates the alias number which is an alternative ID for an individual item.
	Display if Alias qualifier (ALWQ) is UPC.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/GTIN	, , , , , , , , , , , , , , , , , , , ,
For Process: MITPOP.MPPOPN ; MMS025MI/LstAlias	For Process: The field indicates the alias number which is an alternative ID for an individual item.
	Display if Alias qualifier (ALWQ) is GTIN.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Description	
For Sync: 1) MITMAS.MMITDS / MMS200MI.GetltmBasic 2) MPDSUM.PSITDS / PDS103MI.LstSumBOM.; /	For Sync: The field indicates the component name or description. IF the product is a product variant, material details will be retrieved from PDS103MI.LstSumBOM.
For Process: MITMAS.MMITDS ; MMS200MI/GetItmBasic	For Process: The field indicates the material description.
BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Note	
For Sync: MPDMAT.PMFMT1; PDS002MI/LstComponent	For Sync: The field indicates an optional text of at most 30 characters.
For Process: MPDMAT.PMFMT1 ; PDS002MI/LstComponent	For Process: The field indicates an optional text.

BillOfMaterials BillOfMaterials/BillOfMaterialsLine/ConsumedItem/LineNumber For Sync: 1) MPDMAT.PMMSEQ / The field indicates the component sequence number. PDS002MI.LstCompnent IF the product is a product variant, material details will be retrieved 2) MPDSUM.PSSEQN / from PDS103MI.LstSumBOM. PDS103MI.LstSumBOM.; / For Process: For Process: The field indicates the material sequence number. MPDMAT.MMSEQ ; PDS002MI/LstComponent BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Status/Code For Sync: For Sync: MITMAS.MMSTAT; PDS002MI/LstComponent The field indicates the component status. Set to 'Pending' if status is 05, 10 or 15. For Process: MPDMAT.PMSTAT Set to 'Open' if status is 20, 30, 40, or 50. Set to 'Closed' if status is 80 or 90. ; PDS001MI/Get Set to 'Deleted' if status is 99. For Process: The field indicates the item status (STAT). Set to 'Pending' if STAT = 10. Set to 'Open' if STAT = 20. Set to 'Deleted' if STAT = 90. BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Name For Sync: For Sync: 1) MITMAS.MMITDS / The field indicates the component name or description. MMS200MI.GetItmBasic IF the product is a product variant, material details will be retrieved 2) MPDSUM.PSITDS / from PDS103MI.LstSumBOM. PDS103MI.LstSumBOM.MMITDS; MMS200MI/GetItmBasic For Process: For Process: The field indicates the material description. MITMAS.MMITDS ; MMS200MI/GetItmMeas BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Quantity For Sync: For Sync: 1) MPDMAT.PMCNQT / The field indicates the quantity of each component used in the bill of PDS002MI.LstComponent material/structure of a product. 2) MPDSUM.PSQTQT / IF the product is a product variant, material details will be retrieved from PDS103MI.LstSumBOM. PDS103MI.LstSumBOM.; / For Process: MPDMAT.PMCNQT The field indicates the quantity of each component used in the ; PDS002MI/LstComponent bill of material/structure of a product. @unitCode For Sync: For Sync: 1) MITMAS.MMUNMS / The field indicates the unit of measure that is used for an item PDS002MI.LstComponent quantity in a bill of material. 2) MPDSUM.PSPEUN / IF the product is a product variant, material details will be retrieved PDS103MI.LstSumBOM.; / from PDS103MI.LstSumBOM. For Process: For Process: MPDMAT.PMPEUN The field indicates the product engineering unit of measure. PDS002MI/LstComponent BillOfMaterials/BillOfMaterialsLine/ConsumedItem/BaseUOMQuantity For Process: .; PDS002MI/LstComponent The field indicates the quantity in basic unit of measure. @unitCode For Process: For Process: MITMAS.MMUNMS; PDS002MI/LstComponent The field indicates the basic unit of measure. BillOfMaterials/BillOfMaterialsLine/ConsumedItem/FixedQuantityIndicator For Process: For Process MPDMAT.PMFXCD; PDS002MI/LstComponent The field indicates the relation between the product's ordered quantity and the material's reserved quantity.

If FXCD = 1, set to true. Otherwise, set to false.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/EffectiveTimePeriod/StartDateTime

For Sync: For Sync: MPDMAT.PMFDAT; PDS002MI/LstComponent

The field indicates the start date for the system period.

For Process: For Process:

MPDMAT.PMFDAT; PDS002MI/LstComponent The field indicates the start date of the material.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/EffectiveTimePeriod/EndDateTime

MPDMAT.PMTDAT; PDS002MI/LstComponent The field indicates the date when the system period ends.

May 26, 2023

BillOfMaterials

For Process:

MPDMAT.PMTDAT; PDS002MI/LstComponent The field indicates the end date of the material.

BillOfMaterials/BillOfMaterialsLine/Substitutions

For Process: For Process:

MPDMAA.PAPREX; PDS013MI/LstAltMat The field indicates the priority of alternate material.

BillOfMaterials/BillOfMaterialsLine/Substitutions/Components/ItemID/ID

For Process: For Process:

MPDMAA.PAMTAL; PDS013MI/LstAltMat The field indicates the alternate material.

@accountingEntity For Process:

MPDHED.PHCONO The field indicates the accounting entity.

CMNDIV.CCDIVI.; / If ItemMaster is enabled in BOD Processor Master AE tab, this is

For Process

displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

BillOfMaterials/BillOfMaterialsLine/Substitutions/Components/Description

For Process: For Process:

The field indicates the alternate material name MITMAS.MMITDS; PDS013MI/LstAltMat

BillOfMaterials/BillOfMaterialsLine/Substitutions/Components/Quantity

For Process: For Process:

MPDMAA.PACNQT; PDS013MI/LstAltMat The field indicates the quantity.

@unitCode

For Process: For Process:

MPDMAA.PAPEUN; PDS013MI/LstAltMat The field indicates the unit of measure.

BillOfMaterials/BillOfMaterialsLine/DrawingPosition

The field indicates the drawing position.

MPDMAT.PMDWPO; PDS002MI/LstComponent

For Process:

MPDMAT.PMDWPO; PDS002MI/LstComponent

BillOfMaterials/BillOfMaterialsLine/OperationReference/DocumentID/ID

For Sync:

MPDMAT.PMOPNO The field indicates an operation number, which forms a unique ID for

PDS002MI/LstComponent an operation when combined with a product number.

MPDOPE.POOPNO

PDS002MI/LstOperation.; / The field indicates an operation number, which forms a unique ID for

an operation when combined with a product number. For Process:

MPDMAT PMOPNO: The operation number also indicates the order in which operations should be performed for a product. When an operation number has PDS002MI/LstComponent

MPDOPE.POOPNO; been entered on a material line in a product structure, it refers to the operation in which the material should first be used. PDS002MI/LstOperation.; /

BillOfMaterials/BillOfMaterialsLine/OperationReference/WorkCenterID

For Sync:

MPDÓPE.POPLGR; PDS002MI/LstOperation,

The field indicates a work center, which is a resource in which labor GetOperation operations are performed.

For Sync:

For Process:

5) Used in standard

For Process: For Process:

MPDOPE.POPLGR; PDS002MI/GetOperation, LstOperation The field indicates a work center, which is a resource in which labor

operations are performed

BillOfMaterials/BillOfMaterialsLine/UserArea

For Process: 1) MPDVER.VRVRSN;

PDS002MI/LstComponent

1) Version PDS028MI.GetVersion

The field indicates the version.

Set attribute name to 'Version'. 2) MPDMAT.PMSDCD;

The field indicates if the material and/or operation are used in MPDOPE.POSDCD; PDS002MI/LstOperation.; / standard. The code controls whether materials and operations should

be considered in estimate, requirements calculation and lead time

calculation of the product.

Set attribute name to 'UsedInStandard'. If SDCD = 1, set NameValue to true. If SDCD = 0, set NameValue to false.

May 26, 2023

BillOfResources

BillOfResources/BillOfResourcesHeader/DocumentID/ID MPDSRC.PVFACI MPDSRC.PVSTRT MPDSRC.PVSUFI. ; / @accountingEntity MPDSRC.PVCONO CMNDIV.CCDIVI.; / @variationID @lid	The field indicates the Bill of Resources ID. It is a concatenation of Facility (FACI) <3> + Product (PRNO) <15> + Product Structure Type (STRT) <3> + Service (SUFI) <20> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the ID except for the last one. The last field in the concatenation, in this case SUFI, is trimmed if it does not consume the maximum length. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the sequence number that identifies the number of times that the BOD has been published. The field indicates the logical ID of the system.
BillOfResources/BillOfResourcesHeader/DocumentID/RevisionID MPDSCF.CAECVE; MOS300MI/GetServiceFaci BillOfResources/BillOfResourcesHeader/LastModificationDateTime	The field indicates the revision number of the Bill of Resources.
MPDSRC.PVLMTS; /	The field indicates the date and time the record was last modified.
BillOfResources/BillOfResourcesHeader/LastModificationPerson/IDs. MPDSRC.PVCHID; MOS300MI/GetServiceFaci @accountingEntity	//D The field indicates the ID of the person who last modified the record.
MPDSRC.PVCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
BillOfResources/BillOfResourcesHeader/DocumentDateTime MPDSRC.PVRGDT MPDSRC.PVRGTM.; MOS300MI/GetServiceFaci	The field indicates the date and time the record was created.
BillOfResources/BillOfResourcesHeader/Description MPDSCF.CATX40; MOS300MI/GetServiceFaci	The field indicates the description of the Bill of Resources.
BillOfResources/BillOfResourcesHeader/Status/Code MPDSCF.CASTAT; MOS300MI /GetServiceFaci	The field indicates the status of the Bill of Resources. Set to "Pending" if status is 10. Set to "Open" if status is 20 or 30. Set to "Obsolete" if status is 90. Set to "Deleted" if record is deleted in MOS300.
BillOfResources/BillOfResourcesHeader/Status/ReasonCode MPDSCF.CARSCD; MOS300MI/GetServiceFaci	The field indicates the user-defined reason code that is used to describe why the transaction was entered.
BillOfResources/Operations/ID MPDOPE.POOPNO; MOS300MI/LstOpnoMtrl @accountingEntity MPDSRC.CACONO CMNDIV.CCDIVI.; /	The field indicates the operation number. The field indicates the company and division, displayed as CONO_DIVI.
BillOfResources/Operations/Description MPDOPE.POOPDS; PDS002MI/GetOperation	The field indicates the operation description.
BillOfResources/Operations/ConsumedItem/ItemID/ID MPDMAT.PMMTNO; PDS002MI/GetComponent @accountingEntity	The field indicates the component number.
MPDSRC.CACONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
BillOfResources/Operations/ConsumedItem/ItemID/RevisionID MPDMAT.PMFECV; PDS002MI/GetComponent	The field indicates the from revision number.
BillOfResources/Operations/ConsumedItem/Description MITMAS.MMITDS; PDS002MI/GetComponent	The field indicates the item description.
BillOfResources/Operations/ConsumedItem/Note MPDMAT.PMFMT1; PDS002MI/GetComponent	The field indicates optional text.
BillOfResources/Operations/ConsumedItem/LineNumber MPDMAT.PMMSEQ; MOS300MI/LstOpnoMtrl	The field indicates the sequence number.
BillOfResources/Operations/ConsumedItem/Status/Code MITMAS.MMSTAT; MMS200MI/GetItmBasic	The field indicates the item status. Set to "Pending" if status is 05, 10, or 15. Set to "Open" if status is 20, 30. or 40. Set to "DoNotReorder" if status is 50. Set to "Obsolete" if status is 80 or 90. Set to "Deleted" if status is 99.
BillOfResources/Operations/ConsumedItem/Name MITMAS.MMITDS; PDS002MI/GetComponent	The field indicates the item name.
BillOfResources/Operations/ConsumedItem/Quantity MPDMAT.PMCNQT; PDS002MI/GetComponent @unitCode	The field indicates the quantity of each component.
MPDMAT.PMPEUN; PDS002MI/GetComponent	The field indicates the unit of measure for the item quantity.

BillOfResources

BillOfResources/Operations/ConsumedItem/EffectiveTimePeriod/Sta	artDateTime
MPDMAT.PMFDAT; PDS002MI/GetComponent	The field indicates the validity start date.
BillOfResources/Operations/ConsumedItem/EffectiveTimePeriod/En	dDateTime
MPDMAT.PMTDAT; PDS002MI/GetComponent	The field indicates the validity end date.
BillOfResources/Operations/ConsumedItem/Location/ID	
MPDMAT.PMWHLO; PDS002MI/GetComponent	The field indicates the warehouse ID.
@accountingEntity	
MPDSRC.CACONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO_DIVI.
BillOfResources/Operations/SetupTimeDuration	
MPDOPE.POSETI; PDS002MI/GetOperation	The field indicates the time it normally takes for changes or preparations for a particular operation.
BillOfResources/Operations/RunTimeDuration	
MPDOPE.POPITI; PDS002MI/GetOperation	The field indicates the time it takes, per unit or batch, to perform a certain operation.
BillOfResources/Operations/RejectPercent	
MPDOPE.POSCPC; PDS002MI/GetOperation	The field indicates the scrap percentage for each labor operation.
BillOfResources/Operations/Tools/ResourceID/ID	
MPDOPE.POTOOL; PDS002MI/GetOperation	The field indicates a unique identity for a tool.
@accountingEntity	• • •
MPDSRC.CACONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
BillOfResources/Operations/WorkCenterReference/ID	
MPDOPE.POPLGR; PDS002MI/GetOperation	The field indicates the work center, a resource in which labor operations are performed.
@accountingEntity	'
MPDSRC.CACONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
BillOfResources/Operations/WorkCenterReference/Description	
MPDOPE.POOPDS; PDS002MI/GetOperation	The field indicates the operation description.

Dili i Oi ai tymastoi		
BillToPartyMaster/PartyIDs/ID		
OCUSMA.OKCUNO CRS610MI/GetBasicData	The field indicates the Customer number when triggered from OCUSMA (Customer) table. When triggered from OCUSAD (Customer Address) table, it is a concatenation of Customer number (CUNO) <10> + Address number (ADID) <6>. The position of each field is determined by its maximum length, specified in brackets. If CUNO does not consume the maximum length, the rest is filled up with spaces. ADID is trimmed if it is less than 6 characters.	
OCUSAD.OPCUNO+OCUSAD.OPADID CRS610MI/GetAddress.; /		
@accountingEntity OCUSMA.OKCONO		
OCUSMA.OKDIVI	The field indicates the accounting entity.	
.;/	If BillToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).	
@variationID	· · · · · · · · · · · · · · · · · · ·	
.;/	The field indicates the sequence number that identifies the number of times that the BOD has been published.	
@lid	·	
; / BillToPartyMaster/PartyIDs/TaxID	The field indicates the logical ID of the system.	
XRUCUS.OKXKPO; CRRU02MI /GetCustomerRU	The field indicates the tax ID.	
@schemeAgencyName	If Country Specific Version (CSVN) is 'RU', display the field OKPO code (XKPO).	
; <i>I</i>	Set to 'RU_OKPO' if TaxID is XKPO.	
BillToPartyMaster/LastModificationDateTime OCUSMA.OKLMTS; /	The field indicates the date and time the record was last modified.	
	The value is retrieved from the event data.	
BillToPartyMaster/LastModificationPerson/IDs/ID OCUSMA.OKCHID; /	The field indicates the user ID of the last person who modified the record.	
	The value is retrieved from the event data.	
@accountingEntity OCUSMA.OKCONO OCUSMA.OKDIVI	The field indicates the accounting entity, displayed as CONO_DIVI.	
• 1		
BillToPartyMaster/LastModificationPerson/Name CSYUSR.CRRENM; MNS150MI/GetUserData	The field indicate the name of the last person who modified the record.	
BillToPartyMaster/Name OCUSMA.OKCUNM CRS610MI/GetBasicdata	The field indicates the customer name.	
OCUSAD.OPCUNM		
CRS610MI/GetAddress.; / BillToPartyMaster/Location/Address		
@type	Set to 'text'.	
BillToPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF CRS610MI/GetBasicData	The field indicates the customer's contact person.	
OCUSAD.OPYREF CRS610MI/GetAddress.; /		
BillToPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4; CRS610MI/GetBasicData	The field indicates the address line.	
OCUSAD.OPCUA1 OCUSAD.OPCUA2 OCUSAD.OPCUA3 OCUSAD.OPCUA4; CRS610MI/GetAddress .: /		
@sequence	The field indicates the address line acquares	
; / BillToPartyMaster/Location/Address/CityName	The field indicates the address line sequence.	
OCUSMA.OKTOWN CRS610MI/GetBasicData	The field indicates the city name.	

The field indicates an area, province or state within a country.
Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
The field indicates the country code.
Sat to 'Countries'
Set to 'Countries'.
The field indicates the postal code.
Set to 'true'.
00.10 1140.
Set to 'false'
Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
Set to 'Communication Channels'.
Set to "Phone" if telephone number 1, telephone number 2 or
facsimile number.
Set to 'Communication Use Codes'
The field indicates the telephone 1, telephone number 2 or facsimile number.
The field indicates the e-mail address.
Set to 'false'.
The field indicates the contact ID.
The field indicates the accounting entity, displayed as CONO_DIVI.
The field indicates the payment term.
The field indicates the payment term.

BillToPartyMaster/PaymentTermCode OCUSMA.OKTEPY CCUDIV.OKTEPY; CRS610MI/GetOrderInfo	The field indicates the payment term.
.; CRS610MI/GetOrderInfo @listID	
	Set to 'Payment Term'.
BillToPartyMaster/PaymentMethodCode OCUSMA.OKPYCD; CRS610MI/GetFinancial	The field indicates the AR payment method. The payment method code is translated in CRS881 (e.g. Cash, Cheque). If no translation exist in CRS881, the following translation is followed based on the payment class: Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1. Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5. Set to 'Factoring' if payment class (PYCL) is 6.
BillToPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the status of the customer.
COUCHAI, CROUTOWINGELBASICBALA	Set to 'Pending' if status is 10. Set to 'Open' if status is 20. Set to 'Closed' if status is 90. Set to 'Deleted' if the BOD is triggered by deletion of customer or customer address record.
BillToPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP CRS610MI/GetBasicData	The field indicates the Classification.
2) OCUSMA.OKTEDL CCUDIV.OKTEDL CRS610MI/GetOrderInfo	 Customer Types The field indicates the type of customer. Set attribute listID to "Customer Types'.
3) OCUSMA.OKSDST CRS610MI/GetOrderInfo	 Incoterms The field indicates delivery terms, which indicate when the responsibility for the transport is transferred from supplier to customer. Set attribute listID to "Incoterms'.
	 District The field indicates the district the customer or payer belongs to. Set attribute listID to 'District'.
@sequence .; /	The field indicates the sequence number for the ordering of elements within a document.
@listID	a document.
.;1	The field indicates the Classification code listID. 1) Set to 'Customer Types' if Classification/Codes/Code is CUTP. 2) Set to 'Incoterms' if Classification/Codes/Code is TEDL. 3) Set to 'District' if Classification/Codes/Code is SDST.
BillToPartyMaster/CustomerParty/PartyIDs/ID OCUSMA .OKCUNO; CRS610MI/GetBasicData @accountingEntity	The field indicates the unique identification of the customer.
OCUSMA.OKCONO OCUSMA.OKDIVI	The field indicates the accounting entity.
.;/	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
BillToPartyMaster/CustomerParty/Name OCUSMA .OKCUNM; CRS610MI/GetBasicData	The field indicates the name of the record.
BillToPartyMaster/ShipToParty/PartyIDs/ID OCUSMA.OKCUNO; CRS610MI/GetBasicData @accountingEntity	The field indicates the unique identification of the customer.
OCUSMA.OKCONO OCUSMA.OKDIVI	The field indicates the accounting entity.
.; /	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
BillToPartyMaster/ShipToParty/Name	

OCUSMA .OKCUNM; CRS610MI/GetBasicData

The field indicates the name of the record.

C:	arr	ier	Pа	rty
V	411		ıu	ıty

CIDMAS_LIDENTS. SECONDING_COCKNO COMBON_COCCONO COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COMBON_COCCONO COCCONO COMBON_COCCONO COCCONO COCC	Carrier Farty	
CMNDIV.CCDIV If CarrierParty is enabled in 80D Processor Master AE tab, this is displayed as Company (COND). Otherwise, this is displayed as Company and Cond (SCAC), a four-test plant code that unjuxely identifies a forwarder. In Collina (COND). The field indicates the Standard Carrier Alpha Code (SCAC), a four-test plant code that unjuxely identifies a forwarder. In Collina (COND). The field indicates the date and time the record was last modified. In Collina (COND). The field indicates the last person who modified the record. In Collina (COND). The field indicates the accounting entity. If CarrierParty (COND). The field indicates the accounting entity. If CarrierParty (COND). The field indicates the accounting entity. If CarrierParty (COND). The field indicates the supplier name. In the field indicates the supplier name. In the field indicates the supplier name. In the field indicates the address line sequence. In the field indicates the address l	CarrierParty/PartyIDs/ID CIDMAS.IDSUNO; /	The field indicates the unique identity of a supplier with Supplier type (SUTY) = 5.
The field indicates the sequence number that identifies the number of times that the BOD has been published. The field indicates the logical ID of the system. The field indicates the logical ID of the system. The field indicates the text registration number of the supplier. The field indicates the text registration number of the supplier. The field indicates the Standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the Standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the address line sequence. The field indicates the address line sequence or	CMNDIV.CCDIVI	If CarrierParty is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as
The field indicates the logical ID of the system. The field indicates the tax registration number of the supplier. The field indicates the tax registration number of the supplier. The field indicates the tax registration number of the supplier. The field indicates the standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the Standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder. The field indicates the date and time the record was least modified. The field indicates the date and time the record was least modified. The field indicates the accounting entity. CINNAIN CCCONO CINNAIN CCCONO CINNAIN CCCONO CINNAIN CCCONO The field indicates the accounting entity. If CarrierParty is enabled in the BOD Processor Master AE tab, this is displayed as Company and Division (CONO DIVI). CarrierParty Name CIDIADS SALONE	DyariationID	The field indicates the sequence number that identifies the number of
CarrierParty/Location/Address/Country SubDivisionCode CIDADR SACCE (CRSEQOMICs Edited Supplier Country Is an address line sequence CIDADR SIDADR). CRSEQOMICs (CRSEQOMICs Edited Supplier). The field indicates the tax registration number of the supplier. CarrierParty/Location/Address/Country SubDivisionCode CIDADR SACCE. CRSEQOMI/LstAddresses The field indicates the Standard Carrier Alpha Code (SCAC), a four-tetter alpha code that uniquely identifies a forwarder. The field indicates the date and time the record was last modified. The field indicates the last person who modified the record. IDCHID: IDCHID	<u>D</u> lid	·
The field indicates the Standard Carrier Alpha Code (SCAC), a four-letter alpha code that uniquely identifies a forwarder.	CarrierParty/PartyIDs/TaxID CIDVEN.IITINO; CRS620MI/GetBasicData	
The field indicates the date and time the record was last modified.		The field indicates the Standard Carrier Alpha Code (SCAC), a four-
CarrierPartyLocation/Address/Country SubDivisionCode CIDADR SACORI, CRS620MI/LstAddresses The field indicates the address line sequence. The field indicates the address line. Company and Division (CONO) Divisio	CarrierParty/LastModificationDateTime CIDMAS IDI MTS: /	
CMNDIV.CCDIVI CMNDIV.CCDIVI If CarrierParty is enabled in the BOD Processor Master AE tab, this i displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). The field indicates the supplier name. ZarrierPartyLocation/Address Bype Set to "text". ZarrierPartyLocation/Address/AddressEline CIDADR SAADR1 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR4 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR4 CIDADR SAADR4 CIDADR SACDR1 ZarrierPartyLocation/Address/CityName CIDADR SACDR1 CIDADR SACDR3 CIDADR SACDR3 CIDADR SACDR3 ZarrierPartyLocation/Address/CityName CIDADR SACDR3 CIDADR SACDR3 CIDADR SACDR3 CIDADR SACDR3 CIDADR SACDR3 CIDADR SACDR3 ZarrierPartyLocation/Address/CountrySubDivisionCode CIDADR SACCR4 CIDADR SACCR5	CarrierParty/LastModificationPerson/IDs/ID CIDMAS	
displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). CIDMAS IDSUNM; CRS620MI/GetBasicData CarrierParty/Location/Address Bype Set to "text". The field indicates the supplier name. CIDADR SAADR1 CIDADR SAADR2 CIDADR SAADR3 CIDADR SAADR3 CIDADR SAADR4 : CRS620MI/GetBasicData Sequence The field indicates the address line. The field indicates the address line sequence. The field indicates the address line sequence. The field indicates the address line sequence. The field indicates the city name. CIDADR SAADR3 CIDADR SACTOWN; CRS620MI/LstAddresses The field indicates the city name. CIDADR SACTOWN; CRS620MI/LstAddresses The field indicates the area, province or state within the country. Set'to "Canadian Provinces" if the country is CA (Canada). Set'to "Canadian Provinces" if the country is FR (France). Set to "SubDivisions" and Country is FR (France). Set to "SubDivisions" if no Country is Specified. The field indicates the country code. Set to "SubDivisions" if no Country is specified. The field indicates the country code. Set to "SubDivisions" if no Country is specified. The field indicates the country code. Set to "SubDivisions" if no Country is specified. The field indicates the country code. Set to "SubDivisions" if no Country is specified. The field indicates the country code. The field indicates the country code. Set to "SubDivisions" if no Country is specified. The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.	CMNDIV.ČCCONO CMNDIV.CCDIVI	·
CIDMAS_IDSUMM; CRS620MI/GetBasicData ZarrierParty/Location/Address/AddressLine CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 ; CRS620MI/GetBasicData ZerrierParty/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses CIDADR.SATOWN; CRS620MI/LstAddresses The field indicates the address line sequence. ZarrierParty/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses CIDADR.SATOWN; CRS620MI/LstAddresses The field indicates the area, province or state within the country. ZerrierParty/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses CIDADR.SAECAR; CRS620MI/LstAddresses ZerrierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses CarrierParty/Location/Address/PostalCode CIDADR.SACSCD; CRS620MI/LstAddresses The field indicates the country code. ZerrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the postal code. ZerrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery recept 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.		displayed as Company (CONO). Otherwise, this is displayed as
Set to "text". The field indicates an address line. The field indicates the address line sequence. The field indicates the city name. The field indicates the city name. The field indicates the city name. The field indicates the address line sequence. The field indicates the city name. The field indicates the country is CA (Canada). Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "SubDivisions - Country Codes" for other countries. Set to "SubDivisions" if no Country is specified. CarrierParty/Location/Address/Country Code CIDADR.SACSCD; CRS620Mi/LstAddresses The field indicates the country code. Set to "Countries". The field indicates the postal code. CiDADR.SAPONO; CRS620Mi/LstAddresses The field indicates the postal code. CarrierParty/Contact/ID The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates the country code. The field indicates which of the following supplier references to be used: The field indicates which of the following supplier references to be used: The field indicates the country code. The field indicates the country code. The field indicates the country code. The field indicates the		The field indicates the supplier name.
CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 CIDADR.SAADR3 ; CRS620MI/GetBasicData Beequence The field indicates the address line sequence. The field indicates the city name. CIDADR.SATOWN; CRS620MI/LstAddresses The field indicates the city name. CIDADR.SAECAR; CRS620MI/LstAddresses The field indicates the area, province or state within the country. Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "Canadian Provinces" if the country is FR (France). Set to "SubDivisions" or "Country Code" for other countries. Set to "SubDivisions" if no Country is specified. CarrierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses The field indicates the country code. Set to "Countries". CarrierParty/Location/Address/PostalCode CIDADR.SACSCD; CRS620MI/LstAddresses The field indicates the postal code. CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstAddresses The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.		Set to "text"
The field indicates the address line sequence. The field indicates the didress line sequence. The field indicates the city name. The field indicates the area, province or state within the country. The field indicates the area, province or state within the country. Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country "countries".="" "subdivisions="" "subdivisions"="" (carrier="" -="" <country="" cid="" cid<="" city="" code.="" codes"="" contact="" countries="" countries.="" country="" field="" for="" id="" id)="" if="" indicates="" is="" no="" other="" party="" postal="" set="" specified.="" td="" the="" to=""><td>CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4.</td><td>The field indicates an address line.</td></country>	CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4.	The field indicates an address line.
CIDADR.SATOWN; CRS620MI/LstAddresses The field indicates the city name. CarrierParty/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses The field indicates the area, province or state within the country. Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "France - Departements" if the country is US (United States). Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions" if no Country to specified. CarrierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses DistID CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the country code. CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the postal code. CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.	; CRS620MI/GetBasicData Dsequence	The field indicates the address line sequence.
The field indicates the area, province or state within the country. Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "France - Departements" if the country is FR (France). Set to "SubDivisions - <country code="">" for other countries. Set to "SubDivisions" if no Country is specified. CarrierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses DistID Set to "Countries". CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the country code. Set to "Countries". CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the postal code. CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.</country>	CarrierParty/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses	The field indicates the city name.
Set?to "Canadian Provinces" if the country is CA (Canada), Set?to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country code="">" for other countries. Set to "SubDivisions" if no Country is specified. CarrierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates the postal code. CIDADR.SAPONO; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.</country>	CarrierParty/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses	·
CIDADR.SACSCD; CRS620MI/LstAddresses DistiD Set to "Countries". CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates the postal code. Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.		Set?to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country code="">" for other countries.</country>
CarrierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.	CIDADR.SACSCD; CRS620MI/LstAddresses	The field indicates the country code.
CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the postal code. CarrierParty/Contact/ID CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.	CarrierPartv/Location/Address/PostalCode	Set to "Countries".
CIDREF.IRRFTY; CRS620MI/LstSupplierRef The field indicates which of the following supplier references to be used: Alternatives 10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.	CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates the postal code.
10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial 35 = Agreement. It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.		
It is a contatenation of Rtp (RFTY) and Reference (RFID) with a separator (-) in between.		10 = Purchase 15 = Repair or subcontract 20 = Delivery receipt 25 = Claim 30 = Financial
• •		It is a contatenation of Rtp (RFTY) and Reference (RFID) with a
	@accountingEntity	

CarrierParty

CarrierParty	
CMNDIV.CCCONO CMNDIV.CCDIVI .; /	The field indicates the accounting entity. If CarrierParty is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
CarrierParty/Contact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the name of the person to be reached for issues regarding customer orders or purchase orders.
CarrierParty/Contact/Communication @preferredIndicator	
	Set to "false".
CarrierParty/Contact/Communication/ChannelCode	Set to "Phone" if Telephone number 1 (PHNO). Set to "Email" if E-mail address (EMAL).
@listID	Set to "Communication Channels".
0	Set to Communication Channels.
CarrierParty/Contact/Communication/UseCode	Set to "Office" if Telephone number 1 (PHNO) and if E-mail address (EMAL).
@listID	Set to "Communication Use Codes".
CarrierParty/Contact/Communication/DialNumber CIDREF.IRPHNO; CRS620MI/GetSupplierRef	The field indicates the telephone number of the supplier.
CarrierParty/Contact/Communication/URI CIDREF.IREMAL; CRS620MI/GetSupplierRef	The field indicates the e-mail address of the supplier.
CarrierParty/Contact/Communication/Preference/Indicator	Set to "false".
CarrierParty/UserArea CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status. Set attribute name to "M3Status". If STAT=05, set NameValue to 05 - Supplier template. If STAT=10, set NameValue to 10 - Preliminary. If STAT=20, set NameValue to 20 - Approved. If STAT=30, set NameValue to 30 - Stopped. If STAT=90, set NameValue to 90 - Deactivated.
CarrierParty/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the status. Set to "Closed" if status is 05. Set to "Pending" if status is 10. Set to "Open" if status is 20. Set to "Hold" if status is 30. Set to "Deleted" if status 90.

Catalog

Catalog/CatalogHeader/DocumentID/ID CSYTAB.CTSTKY; CRS175MI/GetGeneralCode	The field indicates the assortment ID where the constant value (STCO) is "ASCD"
@accountingEntity CMNDIV.CCCONO, CCDIVI; MNS100MI/GetBasicData	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
Catalog/CatalogHeader/LastModificationPerson/IDs/ID	
@accountingEntity	The field indicates the last person modification.
	The field indicates the company and division, displayed as CONO DIVI.
Catalog/CatalogHeader/Status/Code	TI 5 II: 5 1 1 1 15 15 15 15 15 15 15 15 15 15 1
@listID	The field indicates take Virtual field Catalog Status Code in the Event.
	Set to "Generic Status"
Catalog/CatalogHeader/Name CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the assortment name.
Catalog/CatalogLine/Item/ItemID/ID OASITN.OIITNO; CRS105MI/LstAssmItem	The field indicates the item number connected to the assortment.
Catalog/CatalogLine/TimePeriod/StartDateTime OASITN.OIFDAT; CRS105MI/LstAssmItem	The field indicates the date time.
Catalog/CatalogLine/TimePeriod/EndDateTime OASITN.OITDAT; CRS105MI/LstAssmItem	The field indicates the last validity date for a combination of item and assortment.
Catalog/CustomerSegment/CustomerSegment	
@orGroup	The field indicates internal counter for each customer number included in the assortment .
Catalog/CustomerSegment/Code OASCUS.OCCUNO; CRS105MI/LstAssmCust @listID	Set to "CustomerPartyMasterID".
	Set to "Customer segment criteria".
@accountingEntity CMNDIV.CCCONO, CCDIVI; MNS100MI/GetBasicData	The field indicates the company and division, displayed as CONO DIVI.
Catalog/CustomerSegment/TimePeriod/StartDateTime OASCUS.OCFDAT; CRS105/LstAssmCust	The field indicates the start date time.
Catalog/CustomerSegment/TimePeriod/EndDateTime OASCUS.OCTDAT; CRS105/LstAssmCust	The field indicates the end date time.
Catalog/CustomerSegment/TestValue OASCUS.OCCUNO; CRS105MI/LstAssmCust	The field indicates the customer number.
Catalog/CustomerSegment/TestOperator	Set to "equals".

ChartOfAccounts

Chartoraccounts	
ChartOfAccounts/IDs/ID FCHACC.EARITM; /	The field indicates the account ID.
@accountingEntity FCHACC.EACONO FCHACC.EADIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field indicates the logical ID of the system that is SOR for this noun instance.
ChartOfAccounts/LastModificationDateTime FCHACC.EALMDT; CRS630MI/GetAccountID	The field indicates the last modified date.
ChartOfAccounts/LastModificationPerson/IDs/ID FCHACC.EACHID; CRS630MI/GetAccountID	The field indicates the ID of the person that entered/changed the recored.
@accountingEntity FCHACC.EACONO FCHACC.EADIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
ChartOfAccounts/DocumentDateTime FCHACC.EARGDT; CRS630MI/GetAccountID	The field indicates the last modification date and time.
ChartOfAccounts/Description FCHACC.EATX40; CRS630MI/GetAccountID	The field indicates the description of the account.
ChartOfAccounts/Status/Code FCHACC.EALCCD; CRS630MI/GetAccountID	The field indicates the status.
	If status code (LCCD) is 0, set to 'Open'. If status code (LCCD) is 1, set to 'Closed'.
@listID	Set to 'ChartOfAccountsStatus'.
ChartOfAccounts/BaseChartOfAccounts/GLNominalAccount FCHACC.EAAITM: CRS630MI/GetAccountID	The field indicates the accounting identity.
ChartOfAccounts/BaseChartOfAccounts/EffectiveTimePeriod/St FCHACC.EAVFDT; CRS630MI/GetAccountID	
ChartOfAccounts/BaseChartOfAccounts/EffectiveTimePeriod/ErFCHACC.EAVTDT; CRS630MI/GetAccountID	ndDateTime The field indicates the end date and time.
ChartOfAccounts/BaseChartOfAccounts/AccountType FCHACC.EAAT01 FCHACC.EAAT02.; CRS630MI/GetAccountID @listID	If AT01 = 1, set to 'BalanceSheet'. If AT02 = 1, set to 'ProfitAndLoss'.
	Set to 'Account Types'.
ChartOfAccounts/BaseChartOfAccounts/CurrencyCode FCHACC.EACUCD; CRS630MI/GetAccountID @listID	The field indicates the currency code.
wisub	Set to 'Currency'.
ChartOfAccounts/BaseChartOfAccounts/Description FCHACC.EATX40; CRS630MI/GetAccountID @languageID	The field indicates the description of the account.
FCAIDL.ELLNCD; CRS630MI/GetAccountLng	The field indicates language code. E.g 'GB'
ChartOfAccounts/AccountingChartReference/ID	Set to 'AccountingChartStandard'.
@accountingEntity	The field indicates the company and division, displayed as
ChartOfAccounts/Name	CONO DIVI.
FCHACC.EATX15; CRS630MI/GetAccountID @languageID	The field indicates the name of the account.
FCĂIDL.ELLNCD; CRS630MI/GetAccountLng	The field indicates the language code. E.g. 'GB'.
ChartOfAccounts/ShortName FCHACC.EATX15; CRS630MI/GetAccountID @JanguageID	The field indicates the name of the account.
FCAIDL.ELLNCD; CRS630MI/GetAccountLng	The field indicates the language code. E.g. 'GB'.
ChartOfAccounts/DebitCreditFlag FTRSCD.FTX128; GLS030MI/GetAcntIdCtgry	The field indicates the debit or credit flag as defined in (GLS030) for the scenario 'CRS630BODDC' for the division or blank division. - If Category (X128) is 'ASSET', set to 'DEBIT'. - If Category (X128) is 'LIABILITY', set to 'CREDIT'. - If Category (X128) is 'REVENUE', set to 'CREDIT'. - If Category (X128) is 'COST', set to 'DEBIT'.
ChartOfAccounts/RevaluationIndicator FCHACC.EAAT06; CRS630MI/GetAccountID	If AT06 = 0, set to 'false'. Otherwise, set to 'true'.

ChartOfAccounts

ChartorAccounts	
ChartOfAccounts/Classification/Codes/Code FTRSCD.FTX128; GLS030MI/GetAcntIdCtgry @listID	The field indicates the account sub-type as defined in (GLS030) for the scenario 'CRS630BODSUBTYP' for the division or blank division. - If Category (X128) is 'ASSET', set to 'ASSET'. - If Category (X128) is 'LIABILITY', set to 'LIABILITY'. - If Category (X128) is 'EQUITY', set to 'EQUITY'. - If Category (X128) is 'REVENUE', set to 'REVENUE'. - If Category (X128) is 'EXPENSE', set to 'EXPENSE'.
<u></u>	Set to 'Account Sub-types'
ChartOfAccounts/DimensionProfileSet/ID	Set to 'DimensionProfileSetStandard'.
ChartOfAccounts/DimensionProfileSet/DimensionProfile/ID FCHACC.EAACR2 FCHACC.EAACR3 FCHACC.EAACR4 FCHACC.EAACR5 FCHACC.EAACR6 FCHACC.EAACR6 FCHACC.EAACR7.; CRS630MI/GetAccountID	The field indicates the Dimension profile ID.
ChartOfAccounts/DimensionProfileSet/DimensionProfile/Dimensi	ionUsage/ListID The field indicates the name for a specific accounting dimension.
ChartOfAccounts/DimensionProfileSet/DimensionProfile/DimensionProfile/DimensionProfileSet/DimensionProfile/DimensionProfileSet/DimensionProfile/DimensionProfileSet/Di	ionUsage/Usage If ACR = (0, 5, 6, 7, 8), set to 'Optional'. Otherwise, set to 'Mandatory'.

deDefinition/DocumentID/ID	
For Accounting Dimension: FCHACC.EAAITM; /	For Accounting Dimension: The field indicates an accounting identity in an accounting dimension
For AP Payment Methods: CSYTAB.CTSTKY; .	Accounting dimension (AITP) must be greater than 1 to generate th BOD.
For AR Payment Methods: CSYTAB.CTSTKY; /	For AP Payment Methods: The field indicates the payment method code.
For Capabilities: CCADEF.DECATY	STCO (Constant value) = PYME (Payment method - accounts payable).
CCADEF.DECABI.; / For Cost Centers:	For AR Payment Methods: The field indicates the payment method for Accounts Receivable.
FCHACC.EAAITM; / For Customer Discount Groups:	Constant value (STCO) = PYCD
CSYTAB.CTSTKY; / For Customer Groups:	For Capabilities: The field indicates the concatenation of Capability type and Capability.
CSYTAB.CTSTKY; /	For Cost Centers:
For Customer Statistics Identity 1: CSYTAB.CTSTKY; /	The field indicates the accounting identity in an accounting dimensi For Customer Discount Groups:
For Customs Statistics Number: CSYCSN.CKCSNO; /	The field indicates the discount group . STCO = DIGC.
For Delivery Terms: CSYTAB.CTSTKY; /	For Customer Groups: The field indicates the Item discount group.
For Dynamic Dimension: FCHACC.EAAITM; /	(STCO = CUCL) For Customer Statistics Identity 1: The field indicates a user-defined customer statistics accumulator.
For Equipment Classes: MIEQCL.QTEQCL; /	Constant Value (STCO) = FRE1
For Equipment Groups: MIEQGR.QGEQGR; /	For Customs Statistics Number: The field indicates the customs statistics number, which is used for regulating and calculating data for transactions to Intrastat.
For Equipment Meter: SINDMD.SBINNO; /	For Delivery Terms: The field indicates the code ID.
For Error Code 1s: CSYTAB.CTSTKY; /	For Dynamic Dimension:
For Error Code 2s: CSYTAB.CTSTKY; /	The field indicates value of an accounting identity in an accounting dimension. An accounting dimension is a part of the accounting strused to describe financial events in detail. M3 accounting strings contain seven dimensions.
For Error Code 3s: CSYTAB.CTSTKY; /	For Equipment Classes: The field indicates the equipment class.
For Feature Options: MPDFHE.PEFTID; /	For Equipment Groups: The field indicates the equipment group.
For Freight Terms: CSYTAB.CTSTKY	For Equipment Meter: The field indicates the number that identifies an individual item.
For General Code: CSYTAB.CTSTCO CSYSTS.CKECAR.; /	For Error Code 1s: The field indicates the Error Code 1.
For Harbor Airports: CSYTAB.CTSTKY; /	Constant value (STCO) = 'FCLA'
For Individual Item Groups:	For Error Code 2s: The field indicates the Error Code 2.
CSYTAB.CTSTKY; / For Inspection Result Values:	Constant value (STCO) = 'FCL2'
MPDIRV.PLRSIY+MPDIRV.PLEVAL+MPDIRV.PLSTRT+N .; /	MPDIRV.PLSUFFor Error Code 3s: The field indicates the Error Code 3.
For Item Discount Groups: CSYTAB.CTSTKY; /	Constant value (STCO) = 'FCL3'
For Item Free Field 1: CSYTAB.CTSTKY; /	For Feature Options: The field indicates the feature.

52 Infor May 26, 2023

For Service Order Types:

For Freight Terms: For Item Free Field 3: The field indicates the Freight Term. CSYTAB.CTSTKY; / For General Code: The field indicates the following when triggered from CSYTAB table: For Item Free Field 4: CSYTAB.CTSTKY; / Item group if Constant value (STCO) = ITGR Product group if Constant value (STCO) = ITCL For Item Free Field 5: Business area if Constant value (STCO) = BUAR Procurement group if Constant value (STCO) = PRGP CSYTAB.CTSTKY; / Country if Constant value (STCO) = CSCD District if Constant value (STCO) = SDST For Item Types: MITTTY.TYITTY; / The field indicates the State (ECAR) when triggered from CSYSTS For Miscellaneous Cost Types: table. ACUEXP.XPAMTY; / For Harbor Airports: The field indicates the Harbor/Airport ID. For Options: MPDOPT.PFOPTN; / Constant value (STCO) = HAFE For Payment Terms: CSYTAB.CTSTKY; / For Individual Item Groups: The field indicates the individual item group. For Points of Shipment: CSYTAB.CTSTKY; / Constant value (STCO) = 'INGR' For Price List Tables: For Inspection Result Values: OPLTMA.E5PLTB; / The field indicates the quality inspection result values. It is a concatenation of Result identity (RSIY) <15> + Expected value For Product Lines: (EVAL) <12> + Product structure type (STRT) <3> + Service (SUFI) <20> without separator. The position of each field is determined by its CRPDLN.PLPDLN; CRS099MI/GetProductLine maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to For Product Service Extend: SITCOM.USSVID all fields that are part of the ID except for the last one. The last field in the concatenation, in this case SUFI, is trimmed if it does not SSEITM.SRITNO.; / consume the maximum length. For Product Structure Classes: MPDPSC.PCPSCL; / For Item Discount Groups: The field indicates the item discount group. For Product Structure Types: CSYTAB.CTSTKY; / Constant value (STCO) = 'DIGI' For Purchase Order Types: For Item Free Field 1: MPORDT.OTORTY; / The field indicates the item user-defined field 1. Constant Value (STCO) = CFI1. For Routes: If ListID is set to 'Item Free Field 1', set 'MITMAS' as input to FILE. DROUTE.DRROUT; / For Item Free Field 3: For Sales Order Charges: The field indicates the item user-defined field 3. ODCHRG.USCRID; / Constant Value (STCO) = CFI3 For Sales Order Types: If ListID = 'Item Free Field 3', use 'MITMAS' as input in the field Table OOTYPE.OOORTP; [from event]/ (FILE). For Seasons: For Item Free Field 4: CSEAMA.HSSEA1; / The field indicates the item user-defined field 4. For Service Action: Constant Value (STCO) = CFI4 SMECOD.SOMECO; / If ListID = 'Item Free Field 4', use 'MITMAS' as input to FILE (Table). For Service Action Text: For Item Free Field 5: SMETXT.SMMTCO; / The field indicates the item user-defined field 5 code. For Service Assignment Type: Constant value (STCO) = 'CFI5' SASSTP.S1ASST; / Use 'MITMAS' as input for FILE if ListID is 'Item Free Field 5'. For Service Centers: MPDWCT.PPPLGR; / For Item Types: The field indicates the item type. For Service Error Cause: SERCOD.SNERCO For Miscellaneous Cost Types: The field indicates the Miscellaneous Cost Type. For Service Error Symptom: For Options: SERSYM.SLESCO; . The field indicates the option. For Payment Terms: For Service Managers: SSRESP.SCSRES; SOS100MI/LstServManager The field indicates the Payment Term.

nfor May 26, 2023 5.

Constant value (STCO) = 'TEPY'

SSTYPE.SKSOTP: /

For Service Qualification: CSYTAB.CTSTKY;/

For Service Types: CSYTAB.CTSTKY; /

For Stock Locations: MITPCE.MSWHLO MITPCE.MSWHSL.; /

For Supplier Invoice Authorized Users: FAPRCD.ENAPCD; /

For Transportation Methods: CSYTAB.CTSTKY; /

For Unit Codes: CSYTAB.CTSTKY; /

For VAT Codes: CSYTAB.CTSTKY; /

For Work Order Types: MMORDT.VQORTY; /

For Points of Shipment:

The field indicates the ID of a geographic location or a place, such as city, town or airport. STCO = EDES

For Price List Tables:

The field indicates the price list table.

For Product Lines:

The field indicates the Product Line.

For Product Service Extend:

The field indicates the service expense or service item extension.

For Product Structure Classes:

The field indicates the product structure class.

For Product Structure Types:

The field indicates the product structure type.

Constant value (STCO) = STRT

For Purchase Order Types:

The field indicates the purchase order type ID.

For Routes:

The field indicates the transportation route.

For Sales Order Charges:

The field indicates the unique ID of a charge.

For Sales Order Types:

The field indicates the order type which is a combined ID for settings that determine how the order is processed during order entry and in the processing flow.

For Seasons:

The field indicates the season.

For Service Action:

The field indicates the action performed for service order assignments or its service order lines.

For Service Action Text:

The field indicates the Service action text.

For Service Assignment Type:

The field indicates the ID of an assignment type. This is used to group service assignments of the same type.

For Service Centers:

This field indicates the Service Center.

For Service Error Cause:

The field indicates the service error cause.

For Service Error Symptom:

The field indicates the error symptom.

For Service Managers:

The field indicates who has the main responsibility for a service order. The service manager may be a person or a department head for one or more technicians.

For Service Order Types:

The field indicates the Service Order type.

For Service Qualification:

The field indicates the Service Qualification code.

Constant value (STCO) = QUNO

For Service Types:

The field indicates the service type.

Constant value (STCO) = 'STYP'

For Stock Locations:

The field indicates the concatenation of warehouse (WHLO) and

stock location (WHSL). WHLO and WHSL are concatenated without separator. WHLO has a maximum of 3 characters while WHSL has 10. If WHLO has less than 3 characters, it will be filled up with spaces to the right to consume the maximum length. If WHSL is less than 10 characters, it will be trimmed.

For Supplier Invoice Authorized Users:

The field indicates the user who can authorize a specific supplier invoice.

For Transportation Methods:

The field indicates the transportation method.

Contant value (STCO) = MODL

For Unit Codes:

The field indicates the unit of measure. Constant value (STCO) = UNIT

For VAT Codes:

The field indicates the VAT code ID.

Constant value (STCO) = 'VTCD'

For Work Order Types:

The field indicates the Work Order type.

For Accounting Dimension:

The field indicates the company and division, displayed as CONO DIVI.

For AP Payment Methods:

The field indicates the company and division, displayed as CONO DIVI.

For AR Payment Methods:

The field indicates the company and division, displayed as CONO DIVI.

For Capabilities:

The field indicates the company and division.

CONO_DIVI

For Cost Centers:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Groups:

The field indicates the company and division, displayed as CONO DIVI.

E.g. 760_AAA

For Customer Statistics Identity 1:

The field indicates the company and division, displayed as CONO DIVI.

For Customs Statistics Number:

The field indicates the company and division, displayed as CONO DIVI.

For Delivery Terms:

The field indicates the company and division, displayed as CONO DIVI.

For Dynamic Dimension:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Classes:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Groups:

The field indicates the company and division, displayed as

@accountingEntity

For Accounting Dimension: FCHACC.CONO FCHACC.DIVI.; /

For AP Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; .

For AR Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Capabilities: CCADEF.DECONO CMNDIV.CCDIVI.:/

For Cost Centers: FCHACC.EACONO FCHACC.EADIVI.; /

For Customer Discount Groups: CSYTAB.CTCONO

CSYTAB.CTDIVI.; /

For Customer Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customer Statistics Identity 1:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customs Statistics Number:

CSYCSN.CKCONO CMNDIV.CCDIVI.; /

For Delivery Terms: CSYTAB.CTCONO CMNDIV.CCDIVI.; /

For Dynamic Dimension: FCHACC.EACONO FCHACC.EADIVI.; /

For Equipment Classes: MIEQCL.QTCONO CMNDIV.CCDIVI.; /

For Equipment Groups: MIEQGR.QGCONO CMNDIV.CCDIVI.; /

For Equipment Meter: SINDMD.SBCONO SINDMD.SBDIVI.; /

For Error Code 1s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Error Code 2s: CSYTAB.CTCONO CYSTAB.CTDIVI.; /

For Error Code 3s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Feature Options: MPDFHE.PECONO CMNDIV.CCDIVI.; /

For Freight Terms: CSYTAB.CTCONO CMNDIV.CCDIVI.

For General Code: CSYTAB.CTCONO CSYTAB.CTDIVI

CSYSTS.CKCONO CMNDIV.CCDIVI.; /

For Harbor Airports: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Individual Item Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Inspection Result Values: MPDIRV.PLCONO CMNDIV.CCDIVI

For Item Discount Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 1: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 3: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 4: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 5: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Types: MITTTY.TYCONO MITTTY.TYDIVI.; /

For Miscellaneous Cost Types:

ACUEXP.XPCONO CMNDIV.CCDIVI.; /

For Options: MPDOPT.PFCONO CMNDIV.CCDIVI.; /

For Payment Terms: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

CONO DIVI.

For Equipment Meter:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 1s:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 2s:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 3s:

The field indicates the company and division, displayed as CONO_DIVI.

For Feature Options:

The field indicates the company and division, displayed as CONO DIVI.

For Freight Terms:

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780 ĀAA

For General Code:

The field indicates the company and division, displayed as CONO DIVI.

For Harbor Airports:

The field indicates the company and division, displayed as CONO DIVI.

For Individual Item Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Inspection Result Values:

The field indicates the company and division, displayed as CONO DIVI.

For Item Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 1:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 3:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 4:

The field indicates the company and division, displayed as CONO_DIVI.

For Item Free Field 5:

The field indicates the company and division, displayed as CONO DIVI.

For Item Types:

The field indicates the company and division, displayed as CONO DIVI.

For Miscellaneous Cost Types:

The field indicates the company and division, displayed as CONO DIVI.

For Options:

The field indicates the company and division.

CONO_DIVI

For Payment Terms:

The field indicates the company and division, displayed as CONO_DIVI.

May 26, 2023

For Points of Shipment: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Price List Tables: OPTLMA.E5CONO CMNDIV.CCDIVI.; /

For Product Lines: CRPDLN.PLCONO CRPDLN.PLDIVI.; /

For Product Service Extend: SITCOM.USCONO SITCOM.USDIVI

SSEITM.SRCONO SSEITM.SRDIVI.; /

For Product Structure Classes: MPDPSC.PCCONO CMNDIV.CCDIVI.; /

For Product Structure Types: CSYTAB.CTCONO CSYTAB.CTDIVI.: /

For Purchase Order Types: MPORDT.OTCONO CMNDIV.CCDIVI.; /

For Routes: DROUTE.DRCONO DROUTE.DRDIVI.; /

For Sales Order Charges: ODCHRG.USCONO ODCHRG.USDIVI.; /

For Seasons: CSEAMA.HSCONO CMNDIV.CCDIVI.; /

For Service Action: SMECOD.SOCONO SMECOD.SODIVI

.; /

For Service Action Text: SMETXT.SMCONO SMETXT.SMDIVI.; /

For Service Assignment Type: SASSTP.S1CONO CMNDIV.CCDIVI.; /

For Service Centers: MPDWCT.PPCONO CMNDIV.CCDIVI.; /

For Service Error Cause: SERCOD.SNCONO SERCOD.SNDIVI.; /

For Service Error Symptom:

For Service Managers: SSRESP.CONO + DIVI; /

For Service Order Types: SSTYPE.SKCONO SSTYPE.SKDIVI.; /

For Service Qualification: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Points of Shipment:

The field indicates the company and division, displayed as CONO DIVI.

For Price List Tables:

The field indicates the company and division, displayed as CONO DIVI.

For Product Lines:

The field indicates the company and division, displayed as $\ensuremath{\mathsf{CONO_DIVI}}$.

For Product Service Extend:

The field indicates the company and division, displayed as CONO DIVI.

For Product Structure Classes:

The field indicates the company and division.

CONO_DIVI

For Product Structure Types:

The field indicates the company and division, displayed as CONO DIVI.

For Purchase Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Routes:

The field indicates the company and division, displayed as CONO DIVI.

For Sales Order Charges:

The field indicates the company and division, displayed as CONO DIVI.

For Sales Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Seasons:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action Text:

The field indicates the company and division, displayed as CONO DIVI.

For Service Assignment Type:

The field indicates the company and division, displayed as CONO_DIVI.
E.g. 770 AAA

For Service Centers:

The field indicates the company and division, displayed as CONO DIVI.

For Service Error Cause:

The field indicates the company and division, displayed as CONO DIVI.

For Service Error Symptom:

The field indicates the company and division, displayed as CONO DIVI.

For Service Managers:

The field indicates the accounting entity for the Service Error Symptom.

For Service Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Service Qualification:

The field indicates the company and division, displayed as

For Service Types: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Stock Locations: MITPCE.MSCONO CMNDIV.CCDIVI.; /

For Supplier Invoice Authorized Users:

FAPRCD.ENCONO FAPRCD.ENDIVI.; /

For Transportation Methods:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Unit Codes: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For VAT Codes: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Work Order Types: MMORDT.VQCONO CMNDIV.CCDIVI.; /

@location

@variationID

For AP Payment Methods:

.; .

For Harbor Airports:

.; /

For Routes:

.; /

For Service Error Symptom:

.; .

CONO DIVI.

For Service Types:

The field indicates the company and division, displayed as CONO_DIVI.

For Stock Locations:

The field indicates the company and division, displayed as CONO DIVI.

For Supplier Invoice Authorized Users:

The field indicates the company and division.

CONO DIVI

For Transportation Methods:

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760 AAA

For Unit Codes:

The field indicates the company and division, displayed as CONO DIVI.

For VAT Codes:

The field indicates the company and division, displayed as CONO DIVI.

For Work Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Service Managers:

The field indicates the warehouse ID.

For Accounting Dimension:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For AP Payment Methods:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For AR Payment Methods:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Capabilities

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Cost Centers:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Customer Discount Groups:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Customer Groups:

The field indicates the sequence number.

For Customer Statistics Identity 1:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Customs Statistics Number:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Delivery Terms:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Dynamic Dimension:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Equipment Classes:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Equipment Groups:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Equipment Meter:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Error Code 1s:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Error Code 2s:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Error Code 3s:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Feature Options:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Freight Terms:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For General Code:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Harbor Airports:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Individual Item Groups:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Inspection Result Values:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Item Discount Groups:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Item Free Field 1:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Item Free Field 3:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Item Free Field 4:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Item Free Field 5:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Item Types:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Miscellaneous Cost Types:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Options:

The field indicates the sequence number that identifies the number of times that this BOD has been published.

For Payment Terms:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Points of Shipment:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Price List Tables:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Product Lines:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Product Service Extend:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Product Structure Classes:

The field indicates the sequence number that identifies the number of times that this BOD has been published.

For Product Structure Types:

This indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Purchase Order Types:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Routes:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Sales Order Charges:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Sales Order Types:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Seasons:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Action:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Action Text:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Service Assignment Type:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Centers:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Error Cause:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Error Symptom:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Managers:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Service Order Types:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

@lid

For AP Payment Methods:

.; .

For Harbor Airports:

.; /

For Routes:

.; /

For Service Error Symptom:

.; .

For Service Qualification:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Service Types:

The field indicates the sequence number that identifies the number of times the BOD has been published.

For Stock Locations:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Supplier Invoice Authorized Users:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Transportation Methods:

The field indicates the sequence number that identifies the number of times that this BOD has been published.

For Unit Codes:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For VAT Codes:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Work Order Types:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Accounting Dimension:

The field indicates the logical ID of the system.

For AP Payment Methods:

The field indicates the logical ID of the system.

For AR Payment Methods:

The field indicates the logical ID of the system.

For Capabilities:

The field indicates the logical ID of the system that is SOR for this noun instance.

For Cost Centers:

The field indicates the logical ID of the system.

For Customer Discount Groups:

The field indicates the logical ID of the system.

For Customer Groups:

The field indicates the logical ID of the system.

For Customer Statistics Identity 1:

The field indicates the logical ID of the system.

For Customs Statistics Number:

The field indicates the logical ID of the system.

For Delivery Terms:

The field indicates the logical ID of the system.

For Dynamic Dimension:

The field indicates the logical ID of the system.

For Equipment Classes:

The field indicates the logical ID of the system.

For Equipment Groups:

The field indicates the logical ID of the system.

For Equipment Meter:

The field indicates the logical ID of the system.

For Error Code 1s:

The field indicates the logical ID of the system.

Infor May 26, 2023 6⁻

For Error Code 2s:

The field indicates the logical ID of the system.

For Error Code 3s:

The field indicates the logical ID of the system.

For Feature Options:

The field indicates the logical ID of the system.

For Freight Terms:

The field indicates the logical ID of the system that is SOR for this noun instance.

For General Code:

The field indicates the logical ID of the system.

For Harbor Airports:

The field indicates the logical ID of the system.

For Individual Item Groups:

The field indicates the logical ID of the system.

For Inspection Result Values:

The field indicates the logical ID of the system.

For Item Discount Groups:

The field indicates the logical ID of the system.

For Item Free Field 1:

The field indicates the logical ID of the system.

For Item Free Field 3:

The field indicates the logical ID of the system.

For Item Free Field 4:

The field indicates the logical ID of the system.

For Item Free Field 5:

The field indicates the logical ID of the system.

For Item Types:

The field indicates the logical ID of the system.

For Miscellaneous Cost Types:

The field indicates the logical ID of the system.

For Options:

The field indicates the logical ID of the system.

For Payment Terms:

The field indicates the logical ID of the system.

For Points of Shipment:

The field indicates the logical ID of the system.

For Price List Tables:

The field indicates the logical ID of the system.

For Product Lines:

The field indicates the logical ID of the system.

For Product Service Extend:

The field indicates the logical ID of the system.

For Product Structure Classes:

The field indicates the logical ID of the system.

For Product Structure Types:

The field indicates the logical ID of the system.

For Purchase Order Types:

The field indicates the logical ID of the system.

For Routes:

The field indicates the logical ID of the system.

For Sales Order Charges:

The field indicates the logical ID of the system.

For Sales Order Types:

The field indicates the logical ID of the system.

For Seasons:

The field indicates the logical ID of the system.

For Service Action:

The field indicates the logical ID of the system.

For Service Action Text:

The field indicates the logical ID of the system.

For Service Assignment Type:

The field indicates the logical ID of the system.

For Service Centers:

The field indicates the logical ID of the system.

For Service Error Cause:

The field indicates the logical ID of the system.

For Service Error Symptom:

The field indicates the logical ID of the system.

For Service Managers:

The logical ID of the system that is SOR for this noun instance.

For Service Order Types:

The field indicates the logical ID of the system.

For Service Qualification:

The field indicates the logical ID of the system.

For Service Types:

The field indicates the logical ID of the system.

For Stock Locations:

The field indicates the logical ID of the system.

For Supplier Invoice Authorized Users:

The field indicates the logical ID of the system that is SOR for this noun instance.

For Transportation Methods:

The field indicates the logical ID of the system.

For Unit Codes:

The field indicates the logical ID of the system.

For VAT Codes:

The field indicates the logical ID of the system.

For Work Order Types:

The field indicates the logical ID of the system.

CodeDefinition/DisplayID

For Service Managers:

SSRESP.SCSRES; SOS100MI/LstServManager

For Service Managers:

The field indicates who has the main responsibility for a service order. The service manager may be a person or a department head for one or more technicians.

CodeDefinition/LastModificationDateTime

For AP Payment Methods:

CYSTAB.CTLMTS;

For Capabilities: CCADEF.DELMDT

: CBS004MI/Get For Cost Centers:

FCHACC.EALMTS ; CRS630MI/GetAccountID

For Customer Discount Groups:

CSYTAB.CTLMTS; /

For Customer Groups: CSYTAB.CTLMTS; /

For Customer Statistics Identity 1:

For AP Payment Methods:

The field indicates the date and time the record was last modified.

For Capabilities:

The field indicates the date and time the object was last modified.

For Cost Centers:

The field indicates the last modification date.

For Customer Discount Groups:

The field indicates the date and time the record was last modified.

For Customer Groups:

The field indicates the date and time the record was last modified.

For Customer Statistics Identity 1:

The field indicates the last modification date time.

May 26, 2023

CodeDefinition	
CSYTAB.CTLMTS; /	For Customs Statistics Number: The field indicates the last modification date.
For Customs Statistics Number: CSYCSN.CKLMDT; /	For Equipment Classes: The field indicates the date and time the record was last modified.
For Equipment Classes: MIEQCL.QTLMTS; /	For Equipment Groups: The field indicates the last modification date and time.
For Equipment Groups: MIEQGR.QGLMTS ; /	For Equipment Meter: The field indicates the last modification date.
For Equipment Meter: SINDMD.SBLMDT; /	For Error Code 1s: The field indicates the date and time the record was last modified.
For Error Code 1s: CSYTAB.CTLMTS	For Error Code 2s: The field indicates the date and time the record was last modified.
;/	For Error Code 3s: The field indicates the date and time the record was last modified.
For Error Code 2s: CSYTAB.CTLMTS	For Feature Options: The field indicates the date and time the object was last modified.
;/	For Freight Terms:
For Error Code 3s: CSYTAB.CTLMTS	The field indicates the date the object was last modified
;/	For Individual Item Groups: The field indicates when the most recent change was made to the record.
For Feature Options: MPDFHE.PELMTS; /	For Inspection Result Values: The field indicates the date and time the record was last modified.
For Freight Terms: CSYTAB.CTLMDT	For Item Discount Groups: The field indicates when the most recent change was made to the
For Individual Item Groups: CSYTAB.CTLMTS	record.
; / For Inspection Result Values:	For Item Free Field 1: The field indicates the last modification date and time.
MPDIRV.PLLMTS; /	For Item Free Field 3: The field indicates the last modification date.
For Item Discount Groups: CSYTAB.CTLMTS; /	For Item Free Field 4: The field indicates the last modification date.
For Item Free Field 1: CSYTAB.CTLMTS; /	For Item Free Field 5: The field indicates the last modification date and time.
For Item Free Field 3: CSYTAB.CTLMTS; /	For Item Types: The field indicates the last modification date and time.
For Item Free Field 4: CSYTAB.CTLMTS; /	For Miscellaneous Cost Types: The field indicates when the most recent change was made.
For Item Free Field 5: CSYTAB.CTLMTS; /	For Options: The field indicates the date and time the object was last modified.
For Item Types: MITTTY.TYLMDT; /	For Points of Shipment: The field indicates the date and time the record was last modified.
For Miscellaneous Cost Types: ACUEXP.XPLMTS; /	For Price List Tables: The field indicates the last modification date of the record.
For Options: MPDOPT.PFLMTS; /	For Product Lines: The field indicates the date and time the record was last modified.
For Points of Shipment: CSYTAB.CTLMTS; /	For Product Service Extend: The field indicates the date and time the record was last modified.
For Price List Tables: OPTLMA.E5LMDT; /	The value is retrieved from the event data.
For Product Lines: CRPDLN.PLLMTS; /	For Product Structure Classes: The field indicates the date and time the object was last modified.
For Product Service Extend: SITCOM.USLMTS	For Sales Order Charges: The field indicates the last modification date and time
SSEITM.SRLMTS	For Sales Order Types:

Infor May 26, 2023 64

The field indicates the last modification date and time. For Product Structure Classes: For Seasons: MPDPSC.PCLMTS; / The field indicates the last modification date and time. For Sales Order Charges: For Service Action: ODCHRG.USLMTS or The field indicates the last modification date of the record. ODCHRL.USLMTD.; / For Service Action Text: For Sales Order Types: The field indicates when the most recent change was made. OOTYPE.OOLMTS; [from event]/ For Service Assignment Type: The field indicates the date and time the record was last modified. For Seasons: CSEAMA.HSLMTS; / The value is retrieved from the event data. For Service Action: For Service Centers: SMECOD.SOLMDT The field indicates the date and time the record was last modified. ; SOS100MI/LstAction For Service Error Cause: For Service Action Text: The field indicates the last modification date and time of the record. SMETXT.SMLMTS; / For Service Error Symptom: For Service Assignment Type: The field indicates the last date and time modified. SASSTP.S1LMTS; / For Service Managers: The field indicates the LastModification date. For Service Centers: MPDWCT.PPLMTS For Service Order Types: The field indicates the last modification date and time. ; / For Service Error Cause: For Service Qualification: SERCOD.SNLMTS The field indicates the date and time the record was last modified. For Service Types: For Service Error Symptom: The field indicates when the most recent change was made. SERSYM.SLLMTS; . For Stock Locations: The field indicates the date and time the record was last modified. For Service Managers: SSRESP.SCLMDT; / For Supplier Invoice Authorized Users: For Service Order Types: The field indicates the date and time the object was last modified. SSTYPE.SKLMTS For Transportation Methods: The field indicates the date and time the object was last modified. For Service Qualification: CSYTAB.CTLMTS; / For Unit Codes: The field indicates the date and time the document was last modified. For Service Types: CSYTAB.CTLMTS; / For VAT Codes: The field indicates when the most recent change was made. For Stock Locations: MITPCE.MSLMTS; / For Work Order Types: The field indicates the last modification date and time. For Supplier Invoice Authorized Users: FAPRCD.ENLMTS; / For Transportation Methods: CSYTAB.CTLMTS; / For Unit Codes: CSYTAB.CTLMTS: / For VAT Codes: CSYTAB.CTLMTS; / For Work Order Types: MMORDT.VQLMTS; / CodeDefinition/LastModificationPerson/IDs/ID For AP Payment Methods: For AP Payment Methods: CYSTAB.CTCHID; . The field indicates the ID of the person who last modified the record.

For AR Payment Methods: CSYTAB.CTCHID; /

For Capabilities: CCADEF.DECHID : CBS004MI/Get

For AR Payment Methods:

The field indicates the user ID associated with the most recent change to the record.

For Capabilities:

The field indicates the ID of the person who last modified the record.

May 26, 2023

For Cost Centers: FCHACC.EACHID

; CRS630MI/GetAccountID

For Customer Discount Groups: CSYTAB.CTCHID; /

For Customer Groups: CSYTAB.CTCHID; /

For Customer Statistics Identity 1: CSYTAB.CTCHID; /

For Customs Statistics Number: CSYCSN.CKCHID; /

For Delivery Terms: CSYTAB.CTCHID; /

For Dynamic Dimension: FCHACC.EACHID; /

For Equipment Classes: MIEQCL.QTCHID; /

For Equipment Groups: MIEQGR.QGCHID; /

For Equipment Meter: SINDMD.SBCHID; /

For Error Code 1s: CSYTAB.CTCHID; /

For Error Code 2s: CSYTAB.CTCHID; /

For Error Code 3s: CSYTAB.CTCHID; /

For Feature Options: MPDFHE.PECHID; /

For Freight Terms: CSYTAB.CTCHID

For General Code: CSYTAB.CTCHID; /

For Harbor Airports: CSYTAB.CTCHID; /

For Individual Item Groups: CSYTAB.CTCHID; /

For Inspection Result Values: MPDIRV.PLCHID; /

For Item Discount Groups: CSYTAB.CTCHID; /

For Item Free Field 1: CSYTAB.CTCHID; /

For Item Free Field 3: CSYTAB.CTCHID; /

For Item Free Field 4: CSYTAB.CTCHID; /

For Item Free Field 5: CSYTAB.CTCHID; /

For Item Types: MITTTY.TYCHID; /

For Miscellaneous Cost Types: ACUEXP.XPCHID; /

For Cost Centers:

The field indicates the ID of the person who last modified the record.

For Customer Discount Groups:

The field indicates the ID of the person who last modified the record.

For Customer Groups:

The field indicates the ID of the person who last modified the record.

For Customer Statistics Identity 1:

The field indicates the person who last modified the document.

For Customs Statistics Number:

The field indicates the ID of the user that last updated the record.

For Delivery Terms:

The field indicates the ID of the person who last modified the record.

For Dynamic Dimension:

The field indicates the user ID associated with the most recent change to the record.

For Equipment Classes:

The field indicates the last person who modified.

For Equipment Groups:

The field indicates the ID of the person who last modified the record.

For Equipment Meter:

The field indicates the ID of the person who last modified the record.

For Error Code 1s:

The field indicates the ID of the person who last modified the record.

For Error Code 2s:

The field indicates the ID of the person who last modified the record.

For Error Code 3s:

The field indicates the ID of the person who last modified the record.

For Feature Options:

The field indicates the ID of the person who last modified the record.

For Freight Terms:

The field indicates the ID of the person who last modified the record.

For General Code:

The field indicates the last person who modified.

For Harbor Airports:

The field indicates the ID of the person who last modified the record.

For Individual Item Groups:

The field indicates the user ID of the person who last modified the record.

For Inspection Result Values:

The field indicates the ID of the person who last modified the record.

For Item Discount Groups:

The field indicates the user ID associated with the most recent change in the record.

For Item Free Field 1:

The field indicates the last modification person.

For Item Free Field 3:

The field indicates the person who last modified the document.

For Item Free Field 4:

The field indicates the person who last modified the document.

For Item Free Field 5:

The field indicates the ID of the user that last updated the record.

For Item Types:

The filed indicates the last modification person.

For Miscellaneous Cost Types:

For Options MPDOPT.PFCHID: /

For Payment Terms: CSYTAB.CTCHID; /

For Points of Shipment: CSYTAB.CTCHID; /

For Price List Tables: OPTLMA.E5CHID; /

For Product Lines: CRPDLN.PLCHID: /

For Product Service Extend: SITCOM.USCHID SSEITM.SRCHID SITCMD.UTCHID.; /

For Product Structure Classes: MPDPSC.PCCHID; /

For Product Structure Types:

For Purchase Order Types:

MPORDT.OTCHID; /

For Routes: DROUTE.DRCHID; /

CSYTAB.CTCHID; /

For Sales Order Charges: ODCHRG.USCHID or ODCHRL.USCHID.; /

For Sales Order Types: OOTYPE.OOCHID; [from event]/

For Seasons: CSEAMA.HSCHID; /

For Service Action: SMECOD.SOCHID; /

For Service Action Text: SMETXT.SMCHID; /

For Service Assignment Type: SASSTP.S1CHID; /

For Service Centers: MPDWCT.PPCHID; /

For Service Error Cause: SERCOD.SNCHID; /

For Service Error Symptom: SERSYM.SLCHID; .

For Service Managers: SSRESP.SCCHID: /

For Service Qualification: CSYTAB.CTCHID; /

For Service Types: CSYTAB.CTCHID; /

For Stock Locations: MITPCE.MSCHID; /

For Supplier Invoice Authorized Users:

FAPRCD.ENCHID: /

For Transportation Methods: CSYTAB.CTCHID; /

For Unit Codes:

The field indicates the user ID associated with the most recent change in the record.

For Options:

The field indicates the ID of the person who last modified the record.

For Payment Terms:

The field indicates the user ID associated with the most recent change in the record.

For Points of Shipment:

The field indicates the ID of the person who last modified the record.

For Price List Tables:

The field indicates the User ID of the person who last modified the record.

For Product Lines:

The field indicates the ID of the person who last modified the record.

For Product Service Extend:

The field indicates the user ID of the last person who modified the record. The value is retrieved from the event data.

For Product Structure Classes:

The field indicates the ID of the person who last modified the record.

For Product Structure Types:

The field indicates the ID of the person who last modified the record.

For Purchase Order Types:

The field indicates the user ID associated with the most recent change in the record.

For Routes:

The field indicates the ID of the person who last modified the record.

For Sales Order Charges:

The field indicates the ID of the person that entered/modified the record

For Sales Order Types:

The field indicates the last modification person.

For Seasons:

The field indicates the last modification person.

For Service Action:

The field indicates the ID of the person who last modified the record.

For Service Action Text:

The field indicates the user ID associated with the most recent change in the record.

For Service Assignment Type:

The field indicates the user ID of the last person who modified the record. The value is retrieved from the event data.

For Service Centers:

The field indicates the ID of the person who last modified the record.

For Service Error Cause:

The field indicates the ID of the person who last modified the record.

For Service Error Symptom:

The field indicates the ID of the person who last modified the record.

For Service Managers:

The field indicates the LastPerson modify.

For Service Qualification:

The field indicates the ID of the person who last modified the record.

For Service Types:

The field indicates the user ID associated with the most recent change.

For Stock Locations:

The field indicates the ID of the person who last modified the record

May 26, 2023 67

CSYTAB.CTCHID; /

For VAT Codes: CSYTAB.CTCHID; /

For Work Order Types: MMORDT.VQCHID; /

@accountingEntity

For AP Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; .

For AR Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Capabilities: CCADEF.DECONO CMNDIV.CCDIVI.; /

For Cost Centers: FCHACC.EACONO FCHACC.EADIVI.; /

For Customer Discount Groups:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customer Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customer Statistics Identity 1:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customs Statistics Number:

CSYCSN.CKCONO CMNDIV.CCDIVI.; /

For Delivery Terms: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Dynamic Dimension: FCHACC.EACONO FCHACC.EADIVI.; /

For Equipment Classes: MIEQCL.QTCONO CMNDIV.CCDIVI.; /

For Equipment Groups: MIEQGR.QGCONO CMNDIV.CCDIVI.; /

For Equipment Meter: SINDMD.SBCONO SINDMD.SBDIVI.; /

For Error Code 1s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Error Code 2s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Error Code 3s: CSYTAB.CTCONO

For Supplier Invoice Authorized Users:

The field indicates the ID of the person who last modified the record.

For Transportation Methods:

The field indicates the ID of the person who last modified the record.

For Unit Codes:

The field indicates the person who last modified the document.

For VAT Codes:

The field indicates the user ID associated with the most recent change.

For Work Order Types:

The field indicates the user that last changed the record.

For AP Payment Methods:

The field indicates the company and division, displayed as CONO DIVI.

For AR Payment Methods:

The field indicates the company and division, displayed as CONO_DIVI.

For Capabilities:

The field indicates the company and division.

CONO DIVI

For Cost Centers:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Groups:

The field indicates the company and division, displayed as CONO_DIVI.

E.g. 760_AAA

For Customer Statistics Identity 1:

The field indicates the company and division, displayed as CONO DIVI.

For Customs Statistics Number:

The field indicates the company and division, displayed as CONO_DIVI.

For Delivery Terms:

The field indicates the company and division, displayed as CONO DIVI.

For Dynamic Dimension:

The field indicates the company and division, displayed as CONO_DIVI.

For Equipment Classes:

The field indicates the company and division, displayed as CONO_DIVI.

For Equipment Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Meter:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 1s:

The field indicates the company and division, displayed as CONO_DIVI.

For Error Code 2s:

The field indicates the company and division, displayed as CONO_DIVI.

CSYTAB.CTDIVI.; /

For Feature Options: MPDFHE.PECONO CMNDIV.CCDIVI.; /

For Freight Terms: CSYTAB.CTCONO CSYTAB.CTDIVI.

For General Code: CSYTAB.CTCONO CSYTAB.CTDIVI

CSYSTS.CKCONO CMNDIV.CCDIVI.; /

For Harbor Airports: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Individual Item Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Inspection Result Values: MPDIRV.PLCONO CMNDIV.CCDIVI

For Item Discount Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.: /

For Item Free Field 1: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 3: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 4: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 5: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Types: MITTTY.TYCONO MITTTY.TYDIVI.; /

For Miscellaneous Cost Types:

ACUEXP.XPCONO CMNDIV.CCDIVI.; /

For Options:

MPDOPT.PFCONO CMNDIV.CCDIVI.; /

For Payment Terms: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Points of Shipment: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Price List Tables: OPTLMA.E5CONO CMNDIV.CCDIVI.; /

For Product Lines: CRPDLN.PLCONO CRPDLN.PLDIVI.; /

For Product Service Extend:

For Error Code 3s:

The field indicates the company and division, displayed as CONO DIVI.

For Feature Options:

The field indicates the company and division, displayed as CONO DIVI.

For Freight Terms:

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760 AAA

For General Code:

The field indicates the company and division, displayed as CONO DIVI.

For Harbor Airports:

The field indicates the company and division, displayed as CONO DIVI.

For Individual Item Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Inspection Result Values:

The field indicates the company and division, displayed as CONO DIVI.

For Item Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 1:

The field indicates the company and division, displayed as CONO_DIVI.

For Item Free Field 3:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 4:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 5:

The field indicates the company and division, displayed as CONO DIVI.

For Item Types:

The field indicates the company and division, displayed as CONO DIVI.

For Miscellaneous Cost Types:

The field indicates the company and division, displayed as CONO DIVI.

For Options:

The field indicates the company and division.

CONO DIVI

For Payment Terms:

The field indicates the company and division, displayed as CONO DIVI.

For Points of Shipment:

The field indicates the company and division, displayed as CONO DIVI.

For Price List Tables:

The field indicates the company and division, displayed as

CONO DIVI.

For Product Lines:

The field indicates the company and division, displayed as

CONO DIVI.

For Product Service Extend:

SITCOM.USCONO SITCOM.USDIVI

SSEITM.SRCONO SSEITM.SRDIVI

SITCMD.UTCONO SITCMD.UTDIVI.; /

For Product Structure Classes: MPDPSC.PCCONO CMNDIV.CCDIVI.; /

For Product Structure Types: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Purchase Order Types: MPORDT.OTCONO CMNDIV.CCDIVI.; /

For Routes: DROUTE.DRCONO DROUTE.DRDIVI.; /

For Sales Order Charges: ODCHRG.USCONO ODCHRG.USDIVI.; /

For Seasons: CSEAMA.HSCONO CMNDIV.CCDIVI.; /

For Service Action:

SMECOD

.SOCONO SODIVI

;/

For Service Action Text: SMETXT.SMCONO SMETXT.SMDIVI.; /

For Service Assignment Type: SASSTP.S1CONO CMNDIV.CCDIVI.; /

For Service Centers: MPDWCT.PPCONO CMNDIV.CCDIVI.; /

For Service Error Cause: SERCOD.SNCONO SERCOD.SNDIVI.; /

For Service Error Symptom: SERSYM.SLCONO SERSYM.SLDIVI.; .

For Service Managers: SSRESP.SCCONO SSRESP.SCDIVI.; /

For Service Order Types: SSTYPE.SKCONO SSTYPE.SKDIVI.; /

For Service Qualification: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Service Types: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Stock Locations: MITPCE.MSCONO

The field indicates the company and division, displayed as CONO DIVI.

For Product Structure Classes:

The field indicates the company and division. CONO DIVI

For Product Structure Types:

The field indicates the company and division, displayed as CONO DIVI.

For Purchase Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Routes:

The field indicates the company and division, displayed as CONO_DIVI.

For Sales Order Charges:

The field indicates the company and division, displayed as CONO DIVI.

For Sales Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Seasons:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action Text:

The field indicates the company and division, displayed as CONO DIVI.

For Service Assignment Type:

The field indicates the company and division, displayed as CONO DIVI. E.g. 770 AAA

For Service Centers:

The field indicates the company and division, displayed as CONO DIVI.

For Service Error Cause:

The field indicates the company and division, displayed as CONO DIVI.

For Service Error Symptom:

The field indicates the company and division, displayed as CONO DIVI.

For Service Managers:

The field indicates the company and division.

CONO_DIVI

For Service Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Service Qualification:

The field indicates the company and division, displayed as CONO_DIVI.

For Service Types:

The field indicates the company and division, displayed as CONO_DIVI.

For Stock Locations:

The field indicates the company and division, displayed as CONO_DIVI.

For Supplier Invoice Authorized Users: The field indicates the company and division. CONO DIVI

May 26, 2023

For Transportation Methods: For Supplier Invoice Authorized Users: The field indicates the company and division. FAPRCD.ENCONO FAPRCD.ENDIVI.; / AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760_AAA For Transportation Methods: CSYTAB.CTCONO For Unit Codes: CSYTAB.CTDIVI.; / The field indicates the company and division, displayed as CONO DIVI. For Unit Codes: CSYTAB.CTCONO For VAT Codes: CSYTAB.CTDIVI.; / The field indicates the company and division, displayed as CONO DIVI. For VAT Codes: CSYTAB.CTCONO For Work Order Types: CSYTAB.CTDIVI.; / The field indicates the company and division, displayed as CONO_DIVI. For Work Order Types: MMORDT.VQCONO CMNDIV.CCDIVI.; / CodeDefinition/LastModificationPerson/Name For Capabilities: For Capabilities: The field indicates the name of the person who last modified the CSYUSR.CRNAME ; MNS150MI/GetUserData CodeDefinition/EffectiveTimePeriod/StartDateTime For Accounting Dimension: For Accounting Dimension: FCHACC.EAVFDT; CRS630MI/GetAccountID The field indicates the Valid From Date. For Cost Centers: For Cost Centers: FCHACC.EAVFDT The field indicates the starting validity date. ; CRS630MI/GetAccountID For Seasons: For Seasons: The field indicates the first valid date. CSEAMA.HSSTDT; CRS912MI/GetSeason CodeDefinition/EffectiveTimePeriod/EndDateTime For Accounting Dimension: For Accounting Dimension: FCHACC.EAVTDT; CRS630MI/GetAccountID The field indicates the Valid To Date. For Cost Centers: For Cost Centers: FCHACC.EAVTDT The field indicates the valid to date. ; CRS630MI/GetAccountID For Seasons: For Seasons: The field indicates the last validity date of the record. CSEAMA.HSLVDT; CRS912MI/GetSeason CodeDefinition/Status/Code For Accounting Dimension: For Accounting Dimension: FCHACC.EALCCD; CRS630MI/GetAccountID The field indicates if the accounting entity is blocked from manual entry. For AP Payment Methods: Set to 'Open' if Blocked accounting identity (LCCD) is 0. Set to 'Closed' if Blocked accounting identity (LCCD) is 1. For Cost Centers: Set to 'Deleted' if record is deleted from CRS630. FCHACC.EALCCD ; CRS630MI/GetAccountID For AP Payment Methods: Set to 'Open'. For Harbor Airports: For AR Payment Methods: .; / Set to 'Open'. For Product Service Extend: SSEITM.SRSTAT; / For Capabilities: The field indicates the Status of the code id. For Routes: Set to 'Open'. .; / For Cost Centers: For Seasons: Set to 'Closed' if status is 1. CSEAMA.HSSTAT; CRS912MI/GetSeason Set to 'Deleted' if record is deleted. Otherwise, set to 'Open'. For Service Error Symptom: For Customer Discount Groups: Set to 'Open'. For Stock Locations: MITPCE.MSDEST; MMS010MI/GetLocation For Customer Groups: Set to 'Open'. For Customer Statistics Identity 1: Set to 'Open'.

```
For Customs Statistics Number:
Set to 'Open'.
For Delivery Terms:
Set to 'Open'.
For Dynamic Dimension:
Set to 'Open'.
For Equipment Classes:
Set to 'Open'.
For Equipment Groups:
Set to 'Open'.
For Equipment Meter:
Set to 'Open'.
For Error Code 1s:
Set to 'Open'.
For Error Code 2s:
Set to 'Open'.
For Error Code 3s:
Set to 'Open'.
For Feature Options:
Set to 'Open'.
Set to 'Deleted' if PDS055 record is deleted.
For Freight Terms:
The field indicates the status. Set to 'Open'.
For General Code:
Set to 'Open'.
For Harbor Airports:
Set to 'Open'.
For Individual Item Groups:
Set to 'Open'.
For Inspection Result Values:
Set to 'Open'.
For Item Discount Groups:
Set to 'Open'.
For Item Free Field 1:
Set to 'Open'.
For Item Free Field 3:
Set to 'Open'.
For Item Free Field 4:
Set to 'Open'.
For Item Free Field 5:
Set to 'Open'.
For Item Types:
Set to 'Open'.
For Miscellaneous Cost Types:
Set to 'Open'.
For Options:
The field indicates the status of the object. Set to 'Open'.
For Payment Terms:
Set to 'Open'.
For Points of Shipment:
Set to 'Open'.
For Price List Tables:
```

Infor May 26, 2023 72

Set to 'Open'.

For Product Lines:

Set to 'Open'.

For Product Service Extend:

The indicates the status (STAT) of the service expense.

Set to 'Preliminary', if service expense status is 10.

Set to 'Open' if service expense status is 20 and table SITCOM is triggered.

Set to 'Closed' if service expense status is 90.

For Product Structure Classes:

The field indicates the status of the object. Set to 'Open'.

For Product Structure Types:

Set to 'Open'.

For Purchase Order Types:

Set to 'Open'.

For Routes:

Set to 'Open'.

For Sales Order Charges:

Set to 'Open'.

For Sales Order Types:

Set to 'Open'.

For Seasons:

The field indicates the status (STAT).

If the status is 10, set to 'Pending'. If the status is 20, set to 'Open'.

If the status is 90, set to 'Closed'.

For Service Action:

Set to 'Open'.

For Service Action Text:

Set to 'Open'.

For Service Assignment Type:

The field indicate the status of the code id.

Set to 'Open'.

For Service Centers:

Set to 'Open'.

For Service Error Cause:

Set to 'Open'.

For Service Error Symptom:

Set to 'Open'.

For Service Managers:

The field indicates the Status of the code id.

Set to 'Open'

For Service Order Types:

Set to 'Open'.

For Service Qualification:

Set to 'Open'.

For Service Types:

Set to 'Open'.

For Stock Locations:

The field indicates the location's default status, which is proposed

when an item is placed at the location.

Set to 'Pending' if status is 1. Set to 'Open' if status is 2

Set to 'Closed' if status is 3.

For Supplier Invoice Authorized Users:

The field indicates the status of the code ID.

Set to 'Open'.

Set to 'Deleted' if record is deleted from the table.

For Transportation Methods: The field indicates the status of the object. Set to 'Open'. For Unit Codes: Set to 'Open'. For VAT Codes: Set to 'Open'. For Work Order Types: The field indicates the status of the code ID. Set to 'Open'. @listID For Cost Centers: Set to 'Code Definition Status'. For Feature Options: Set to 'Code Definition Status'. For Freight Terms: Set to 'Code Definition Status'. The field indicates the list ID for the status code. Set to 'Code Definition Status'. For Product Structure Classes: The field indicates the list ID for the status code. Set to 'Code Definition Status'. For Sales Order Charges: Set to 'Code Definition Status'. For Stock Locations: Set to 'Code Definition Status'. For Transportation Methods: The field indicates the list ID for the status code. Set to 'Code **Definition Status'** CodeDefinition/ReadOnlyIndicator For AP Payment Methods: For AP Payment Methods: Set to 'false'. .; . For AR Payment Methods: For Harbor Airports: Set to 'false'. For Routes: For Capabilities: Set to 'false'. .; / For Cost Centers: For Service Error Symptom: Set to 'false'. For Customer Discount Groups: Set to 'false'. For Customer Groups: Set to 'false'. For Customer Statistics Identity 1: Set to 'false'. For Customs Statistics Number: Set to 'false'. For Delivery Terms: Set to 'false', if the category is equals to Code. Set to 'true', if the category is equals to Dimension. For Equipment Classes: Set to 'false'. For Equipment Groups: Set to 'false'. For Equipment Meter: Set to 'false'. For Error Code 1s: Set to 'false'.

```
For Error Code 2s:
Set to 'false'.
For Error Code 3s:
Set to 'false'.
For Feature Options:
Set to 'false'.
For Freight Terms:
The field indicates that this instance is ReadOnly. Set to 'false'.
For General Code:
Set to 'false'.
For Harbor Airports:
Set to 'false'.
For Individual Item Groups:
Set to ' false'.
For Inspection Result Values:
Set to 'false'.
For Item Discount Groups:
Set to 'false'.
For Item Free Field 1:
Set to 'false'.
For Item Free Field 3:
Set to 'false'.
For Item Free Field 4:
Set to 'false'.
For Item Free Field 5:
Set to 'false'.
For Item Types:
Set to 'false', if category is equals to code.
Set to 'true', if category is equals to dimension.
For Miscellaneous Cost Types:
Set to 'false'.
For Options:
Set to 'false'.
For Payment Terms:
Set to 'false'.
For Points of Shipment:
Set to 'false'.
For Price List Tables:
Set to 'false'.
For Product Lines:
Set to 'false'.
For Product Service Extend:
Set to 'false'.
For Product Structure Classes:
The field indicates if the instance is ReadOnly. Set to 'false'.
For Product Structure Types:
Set to 'false'.
For Purchase Order Types:
The field indicates the read only indicator.
Set to 'false' if category is equals to Code.
Set to 'true' if category is equals to Dimension.
For Routes:
Set to 'false'.
```

For Sales Order Charges: Set to "false". For Sales Order Types: Set to 'false'. For Seasons: Set to 'false'. For Service Action: Set to 'false'. For Service Action Text: Set to 'false'. For Service Assignment Type: The field indicates that this instance is ReadOnly. Set to 'false'. For Service Centers: Set to 'false'. For Service Error Cause: Set to 'false'. For Service Error Symptom: Set to 'false'. For Service Managers: The field indicates that this instance is ReadOnly, default value is For Service Order Types: Set to 'false'. For Service Qualification: Set to 'false'. For Service Types: Set to 'false'. For Stock Locations: Set to 'false'. For Transportation Methods: The field indicates if the instance is ReadOnly. Set to 'false'. For Unit Codes: Set to 'false'. For VAT Codes: Set to 'false'. For Work Order Types: Set to 'false'. For Accounting Dimension: The field indicates the name of the accounting dimension as it is defined in CRS012, maximum length 10 characters, trimmed. For AP Payment Methods: Set to 'Payment Methods'. For AR Payment Methods: Set to 'Payment Methods'.

CodeDefinition/ListID

For Accounting Dimension:

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For AP Payment Methods:

.; .

For Dynamic Dimension:

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Harbor Airports:

.; /

For Routes:

.; /

For Service Error Symptom:

.; .

For Capabilities: Set to 'Capabilities'.

For Cost Centers: Set to 'Cost Centers'.

For Customer Discount Groups: Set to 'Customer Discount Groups'.

For Customer Groups: Set to 'Customer Groups'.

```
For Customer Statistics Identity 1:
Set to 'Customer Statistics Identity1'.
```

For Customs Statistics Number: Set to 'Customs Statistics Number'.

For Delivery Terms: Set to 'Incoterms'.

For Dynamic Dimension:

The field indicates the name of accounting dimension <10> which value is sent in DocumentID/ID element. Accounting dimension names can be seen from CRS012.

For Equipment Classes: Set to 'Equipment Classes'.

For Equipment Groups: Set to 'Equipment Groups'.

For Equipment Meter: Set to 'Equipment Meters'.

For Error Code 1s: Set to 'Error Code 1s'.

For Error Code 2s: Set to 'Error Code 2s'.

For Error Code 3s: Set to 'Error Code 3s'.

For Feature Options: Set to 'Style Features'.

For Freight Terms:

The field indicates the list ID for Freight Term. Set to 'Freight Terms'.

For General Code:

The field indicates the ListID.

If originDocument = 'CSYTAB'.

Set \dot{L} istID to 'Item Groups' if Constant value (STCO) = Item group (ITGR).

Set ListID to 'Product Groups' if Constant value (STCO) = Product group (ITCL).

Set ListID to 'Business Sectors' if Constant value (STCO) = Business area (BUAR).

Set ListID to 'Buying Groups' if Constant value (STCO) = Procurement group (PRGP).

Set ListID to 'Čountries' if Constant value (STCO) = Country (CSCD). Set ListID to 'District' if Constant value (STCO) = District (SDST).

If originDocument = 'CSYSTS'.

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to 'SubDivisions' if no country is specified.

For Harbor Airports: Set to 'Airports'.

For Individual Item Groups: Set to 'Individual Item Groups'.

For Inspection Result Values: Set to 'Inspection Result Values'.

For Item Discount Groups: Set to 'Item Discount Groups'.

For Item Free Field 1: Set to 'Item Free Field 1'.

For Item Free Field 3: Set to 'Item Free Field 3'.

For Item Free Field 4:

Set to 'Item Free Field 4'.

For Item Free Field 5: Set to 'Item Free Field 5'.

For Item Types: Set to 'Item Types'.

For Miscellaneous Cost Types: Set to 'Miscellaneous Cost Types'.

For Options: Set to 'Options'.

For Payment Terms: Set to 'Payment Term'.

For Points of Shipment: Set to 'Points Of Shipment'.

For Price List Tables: Set to 'Price List Tables'

For Product Lines: Set to 'Product Lines'.

For Product Service Extend: Set to 'Product Services Extended'.

For Product Structure Classes: The field indicates the ListID. Set to 'Product Structure Classes'.

For Product Structure Types: Set to 'Product Structure Types'.

For Purchase Order Types: Set to 'Purchase Order Types'.

For Routes: Set to 'Route Types'.

For Sales Order Charges: Set to 'Reasons for Charge'.

For Sales Order Types: Set to 'Sales Order Types'.

For Seasons: Set to 'Seasons'.

For Service Action: Set to 'Service Actions'.

For Service Action Text: Set to 'Service Action Texts'.

For Service Assignment Type: The indicates the list id. Set to 'Service Assignment Types'.

For Service Centers: Set to 'Service Centers'.

For Service Error Cause: Set to 'Service Error Causes'.

For Service Error Symptom: Set to 'Service Error Symptoms'.

For Service Managers: Set to 'Service Managers'

For Service Order Types: Set to 'Service Order Types'.

For Service Qualification: Set to 'Qualifications'.

For Service Types:

Set to 'Service Types'. For Stock Locations: Set to 'Stock Locations'. For Supplier Invoice Authorized Users: Set to 'Supplier Invoice Authorized Users'. For Transportation Methods: The field indicates the ListID. Set to 'Transportation Methods'. For Unit Codes: Set to 'Unit Codes'. For VAT Codes: Set to 'VAT Code'. For Work Order Types: Set to 'Work Order Types' CodeDefinition/CodeValue For Accounting Dimension: For Accounting Dimension: FCHACC.EAAITM; CRS630MI /GetAccountID The field indicates an accounting identity in an accounting dimension. For AP Payment Methods: For AP Payment Methods: CSYTAB.CTPARM; . The field indicates the Payment class. Set to 'Cash' if Payment class is 0. For AR Payment Methods: CSYTAB.CTPARM; CRS175MI/GetGeneralCode Set to 'Cheque' if Payment class is 1 Set to 'Cheque' if Payment class is 2. For Capabilities: Set to 'CreditCard/DebitCard/ElectronicFundsTransfer' if Payment CCADEF.DECATY Class is 3. CCADEF.DECABI.; / Set to 'BankDraft' if Payment class is 4. Set to 'DirectDeposit' if Payment class is 5. For Cost Centers: FCHACC.EAAITM For AR Payment Methods: The field indicates the Payment Class. Set to 'Cash' if Payment class is 0. For Customer Discount Groups: Set to 'Cheque' if Payment class is 1. CSYTAB.CTSTKY; / Set to 'Cheque' if Payment class is 2. If Payment Class is 3 and credit card (CRDC) is 1, Set to 'CreditCard/ For Customer Groups: DebitCard'. CSYTAB.CTSTKY; / If Payment Class is 3 and credit card (CRDC) is 0, Set to 'ElectronicFundsTransfer'. For Customs Statistics Number: Set to 'BankDraft' if Payment class is 4. Set to 'DirectDebit' if Payment class is 5. CSYCSN.CKCSNO; / For Delivery Terms: Use STCO = PYTP and STKY = value of PYTP (retrieved from 2nd CSYTAB.CTSTKY; / character of PARM field of CSYTAB table) as inputs. For Dynamic Dimension: For Capabilities: FCHÁCC.EAAITM; / The field indicates the concatenation of Capability type and Capability. For Equipment Classes: MIEQCL.QTEQCL; / For Cost Centers: The field indicates the accounting identity in an accounting dimension. For Equipment Groups: MIEQGR.QGEQGR; / For Customer Discount Groups: The field indicate the customer group. STCO = CUCL. For Equipment Meter: SINDMD.SBINNO; / For Customer Groups: For Error Code 1s: The field indicates the Item discount group. CSYTAB.CTSTKY; / (STCO = CUCL) For Error Code 2s: For Customer Statistics Identity 1: CSYTAB.CTSTKY; / The field indicates a user-defined customer statistics accumulator. Constant Value (STCO) = FRE1 For Error Code 3s: CSYTAB.CTSTKY; / For Customs Statistics Number: The field indicates the customs statistics number, which is used for For Feature Options: MPDFHE.PEFTID; / regulating and calculating data for transactions to Intrastat. For Delivery Terms: For Freight Terms: CSYTAB.CTSTKY The field indicates the code value. For General Code: For Dynamic Dimension: CSYTAB.CTSTCO The field indicates value of an accounting identity in an accounting

For Service Action Text:

For Service Assignment Type:

SMETXT.SMMTCO; SOS100MI.LstActTxt/

SASSTP.S1ASCA; SOS200MI/LstAssignmType

dimension, equal to DocumentID/ID element, More information about account identities can be retrieved by BE MI Transaction For Harbor Airports: CRS630MI.GetAccountID. CSYTAB.CTSTKY; / For Equipment Classes: For Individual Item Groups: The field indicates the equipment class. CSYTAB.CTSTKY; / For Equipment Groups: For Inspection Result Values: The field indicates the equipment group. MPDIRV.PLRSIY+MPDIRV.PLEVAL.; / For Equipment Meter: For Item Discount Groups: The field indicates the number that identifies an individual item. CSYTAB.CTSTKY; / For Error Code 1s: For Item Free Field 3: The field indicates the Error Code 1. CSYTAB.CTSTKY: / Constant value (STCO) = 'FCLA' For Item Free Field 4: CSYTAB.CTSTKY; / For Error Code 2s: The field indicates the Error Code 2. For Item Free Field 5: CSYTAB.CTSTKY; / Constant value (STCO) = 'FCL2' For Item Types: For Error Code 3s: MITTTY.TYITTY; / The field indicates the Error Code 3. For Miscellaneous Cost Types: Constant value (STCO) = 'FCL3' ACUEXP.XPAMTY; / For Feature Options: The field indicates the feature. For Options: MPDOPT.PFOPTN; / For Freight Terms: For Payment Terms: The field indicates the Freight Term. CSYTAB.CTSTKY; / For General Code: The field indicates the following when triggered from CSYTAB table: For Points of Shipment: CSYTAB.CTSTKY; / Item group if Constant value (STCO) = ITGR Product group if Constant value (STCO) = ITCL Business area if Constant value (STCO) = BUAR For Price List Tables: Procurement group if Constant value (STCO) = PRGP OPTLMA.E5PLTB; / Country if Constant value (STCO) = CSCD District if Constant value (STCO) = SDST For Product Lines: CRPDLN.PLPDLN; CRS099MI/GetProductLine The field indicates the State (ECAR) when triggered from CSYSTS For Product Service Extend: table. SITCOM.USITNO SSEITM.SRSVID.; / For Harbor Airports: The field indicates the Harbor/Airport ID. For Product Structure Classes: MPDPSC.PCPSCL; / Constant value (STCO) = HAFE For Product Structure Types: For Individual Item Groups: CSYTAB.CTSTKY; / The field indicates the individual item group. For Purchase Order Types: Constant value (STCO) = 'INGR' MPORDT.OTORTY; / For Inspection Result Values: For Routes: The field indicates the concatenation of Result identity (RSIY) + Expected value (EVAL) without separator. RSIY does not consume DROUTE.DRROUT; / the maximum length of 15, the rest is filled up with spaces. EVAL is For Sales Order Charges: trimmed if less than 12 characters. ODCHRG.USCRID ODCHRL.USCRID.; OIS030MI/LstOrderCharges, For Item Discount Groups: The field indicates the item discount group. LstOrderChrgLng For Sales Order Types: Constant value (STCO) = 'DIGI' OOTYPE.OOORTP; [from event]/ For Item Free Field 1: The field indicates the item user-defined field 1. For Seasons: CSEAMA.HSSEA1; / Constant Value (STCO) = CFI1. If ListID is set to 'Item Free Field 1', set 'MITMAS' as input to FILE. For Service Action: SMECOD.SOMECO; / For Item Free Field 3: The field indicates the item user-defined field 3.

May 26, 2023

(FILE).

Constant Value (STCO) = CFI3

If ListID = 'Item Free Field 3', use 'MITMAS' as input in the field Table

For Service Centers: MPDWCT.PPPLGR; /

For Service Error Cause: SERCOD.SNERCO

;/

For Service Error Symptom: SERSYM.SLESCO; .

For Service Managers:

SSRESP.SCSREŠ; SOS100MI/LstServManager

For Service Order Types: SSTYPE.SKSOTP; /

For Service Qualification: CSYTAB.CTSTKY;/

For Service Types: CSYTAB.CTSTKY; /

For Stock Locations: MITPCE.MSWHSL; /

For Supplier Invoice Authorized Users:

FAPRCD.ENAPCD; /

For Transportation Methods:

CSYTAB.CTSTKY; /

For Unit Codes: CSYTAB.CTSTKY; /

For VAT Codes: CSYTAB.CTSTKY; /

For Work Order Types: MMORDT.VQORTY; /

For Item Free Field 4:

The field indicates the item user-defined field 4.

Constant Value (STCO) = CFI4

If ListID = 'Item Free Field 4', use 'MITMAS' as input to FILE (Table).

For Item Free Field 5:

The field indicates the item user-defined field 5 code.

For Item Types:

The field indicates the item type.

For Miscellaneous Cost Types:

The field indicates the Miscellaneous Cost Type.

For Options:

The field indicates the option.

For Payment Terms:

The field indicates the Payment Term. If constant value (STCO) = 'TEPY' then display payment term.

For Points of Shipment:

The field indicates the ID of a geographic location or a place, such as city, town or airport.

STCO = EDES

For Price List Tables:

The field indicates the price list table.

For Product Lines:

The field indicates the Product Line code.

For Product Service Extend:

1) Service expense

The field indicates the service order system to handle for instance work hours, travel time, allowance etc.

2)Service item extension

The field indicates the item number, maintenance item number, equipment number.

For Product Structure Classes:

The field indicates the product structure class.

For Product Structure Types:

The field indicates the product structure type.

Constant value (STCO) = STRT

For Purchase Order Types:

The field indicates the purchase order type ID.

For Routes:

The field indicates the transportation route.

For Sales Order Charges:

The field indicates the unique ID of a charge.

For Sales Order Types:

The field indicates the order type which is a combined ID for settings that determine how the order is processed during order entry and in the processing flow.

For Seasons:

The field indicates the season.

For Service Action:

The field indicates the action performed for service order assignments or its service order lines

For Service Action Text:

The field indicates the Service action text.

For Service Assignment Type:

The field indicates the assignment category that the assignment type belongs to.

Set to 'Error report' if type is 01

Set to 'Service warranty' if type is 02

Set to 'On hold' if type is 03

Set to 'Installation' if type is 04

Set to 'Project/business' if type is 05

Set to 'Next visit' if type is 06

Set to 'Preventive maintenance' if type is 07

Set to 'Sales' if type is 08 Set to 'Other' if type is 09

Set to 'Return to fit' if type is 98

Set to 'Monitoring assignment' if type is 99

For Service Centers:

This field indicates the Service Center.

For Service Error Cause:

The field indicates the service error cause.

For Service Error Symptom:

The field indicates the error symptom.

For Service Managers:

The field indicates who has the main responsibility for a service order. The service manager may be a person or a department head for one or more technicians.

For Service Order Types:

The field indicates the Service Order type.

For Service Qualification:

The field indicates the Service Qualification code.

Constant value (STCO) = QUNO

For Service Types:

The field indicates the service type.

Constant value (STCO) = 'STYP'

For Stock Locations:

The field indicates the stock location.

For Supplier Invoice Authorized Users:

The field indicates the user who can authorize a specific supplier invoice.

For Transportation Methods:

The field indicates the transportation method.

Contant value (STCO) = MODL

For Unit Codes:

The field indicates the unit of measure.

Constant value (STCO) = UNIT

For VAT Codes:

The field indicates the VAT code ID.

Constant value (STCO) = 'VTCD'

For Work Order Types:

The field indicates the Work Order type.

For Accounting Dimension:

The field indicates the accounting dimension number, between 2 and

Set to 'AccountingDimension_'[accounting dimension number], e.g 'AccountingDimension_2' if accounting dimension number is equal to 2.

For AP Payment Methods:

The field indicates the company and division, displayed as CONO DIVI.

For AR Payment Methods:

The field indicates the company and division, displayed as CONO DIVI.

For Capabilities:

The field indicates the company and division.

CONO_DIVI

For Cost Centers:

@listID

For Accounting Dimension: FCHACC.EAAITP; /

@accountingEntity

For AP Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; .

For AR Payment Methods: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Capabilities: CCADEF.DECONO CMNDIV.CCDIVI.; /

For Cost Centers:

FCHACC.EACONO FCHACC.EADIVI.; /

For Customer Discount Groups:

CSYTAB.CTCONO CSYTAB.CTDIVI.;/

For Customer Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customer Statistics Identity 1:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customs Statistics Number:

CSYCSN.CKCONO CMNDIV.CCDIVI.; /

For Delivery Terms: CSYTAB.CTCONO CMNDIV.CCDIVI.; /

For Equipment Classes: MIEQCL.QTCONO CMNDIV.CCDIVI.; /

For Equipment Groups: MIEQGR.QGCONO CMNDIV.CCDIVI.; /

For Equipment Meter: SINDMD.SBCONO SINDMD.SBDIVI.; /

For Error Code 1s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Error Code 2s: CSYTAB.CTCONO CYSTAB.CTDIVI.:/

For Error Code 3s: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Feature Options: MPDFHE.PECONO CMNDIV.CCDIVI.: /

For Freight Terms: CSYTAB.CTCONO CMNDIV.CCDIVI.

For General Code: CSYTAB.CTCONO CSYTAB.CTDIVI

CSYSTS.CKCONO CMNDIV.CCDIVI.; /

For Harbor Airports: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Individual Item Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Discount Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 1: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

CSYTAB.CTDIVI.; /
For Item Free Field 3:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Customer Groups:

The field indicates the company and division, displayed as CONO DIVI.

E.g. 760_AAA

For Customer Statistics Identity 1:

The field indicates the company and division, displayed as CONO DIVI.

For Customs Statistics Number:

The field indicates the company and division, displayed as CONO DIVI.

For Delivery Terms:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Classes:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Equipment Meter:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 1s:

The field indicates the company and division, displayed as CONO_DIVI.

For Error Code 2s:

The field indicates the company and division, displayed as CONO DIVI.

For Error Code 3s:

The field indicates the company and division, displayed as CONO DIVI.

For Feature Options:

The field indicates the company and division, displayed as CONO DIVI.

For Freight Terms:

The field indicates the company and division. AccountingEntity for M3 is defaulted as a combination of CONO DIVI.

E.g. 780_AAA

For General Code:

The field indicates the company and division, displayed as CONO DIVI.

For Harbor Airports:

The field indicates the company and division, displayed as CONO DIVI.

For Individual Item Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Item Discount Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 1:

The field indicates the company and division, displayed as

CONO DIVI.

For Item Free Field 3:

CSYTAB.CTCONO CSYTAB.CTDIVI.; / For Item Free Field 4:

CSYTAB.CTCONO

CSYTAB.CTDIVI.; /

For Item Free Field 5: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Types: MITTTY.TYCONO MITTTY.TYDIVI.; /

For Miscellaneous Cost Types:

ACUEXP.XPCONO CMNDIV.CTDIVI.; /

For Options:

MPDOPT.PFCONO CMNDIV.CCDIVI.; /

For Payment Terms: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Points of Shipment: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Price List Tables: OPTLMA.E5CONO CMNDIV.CCDIVI.; /

For Product Lines: CRPDLN.PLCONO CRPDLN.PLDIVI.; /

For Product Service Extend: SITCOM.USCONO SITCOM.USDIVI

SSEITM.SRCONO SSEITM.SRDIVI.; /

For Product Structure Classes: MPDPSC.PCCONO CMNDIV.CCDIVI.; /

For Product Structure Types: CSYTAB.CTCONO

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Purchase Order Types: MPORDT.OTCONO CMNDIV.CCDIVI.; /

For Routes:

DROUTE.DRCONO DROUTE.DRDIVI.; /

For Sales Order Charges: ODCHRG.USCONO ODCHRG.USDIVI.; /

For Seasons: CSEAMA.HSCONO CMNDIV.CCDIVI.; /

For Service Action: SMECOD.SOCONO SMECOD.SODIVI

.; /

For Service Action Text: SMETXT.SMCONO SMETXT.SMDIVI.; /

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 4:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 5:

The field indicates the company and division, displayed as CONO DIVI.

For Item Types:

The field indicates the company and division, displayed as CONO DIVI.

For Miscellaneous Cost Types:

The field indicates the company and division, displayed as CONO_DIVI.

For Options:

The field indicates the company and division.

CONO DIVI

For Payment Terms:

The field indicates the company and division, displayed as CONO DIVI.

For Points of Shipment:

The field indicates the company and division, displayed as CONO DIVI.

For Price List Tables:

The field indicates the company and division, displayed as ${\sf CONO\ DIVI}.$

For Product Lines:

The field indicates the company and division, displayed as CONO DIVI.

For Product Service Extend:

The field indicates the company and division, displayed as CONO DIVI.

For Product Structure Classes:

The field indicates the company and division.

CONO DIVI

For Product Structure Types:

The field indicates the company and division, displayed as CONO DIVI.

For Purchase Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Routes:

The field indicates the company and division, displayed as CONO_DIVI.

For Sales Order Charges:

The field indicates the company and division, displayed as CONO DIVI.

For Sales Order Types:

The field indicates the company and division, displayed as CONO DIVI.

For Seasons:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action:

The field indicates the company and division, displayed as CONO DIVI.

For Service Action Text:

The field indicates the company and division, displayed as CONO_DIVI.

For Service Assignment Type:

SASSTP.S1CONO CMNDIV.CCDIVI.; /

For Service Centers: MPDWCT.PPCONO CMNDIV.CCDIVI.; /

For Service Error Cause: SERCOD.SNCONO SERCOD.SNDIVI.; /

For Service Managers: SSRESP.SCCONO SSRESP.SCDIVI.; /

For Service Order Types: SSTYPE.SKCONO SSTYPE.SKDIVI.; /

For Service Qualification: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Service Types: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Stock Locations: MITPCE.MSCONO CMNDIV.CCDIVI.; /

For Supplier Invoice Authorized Users:

FAPRCD.ENCONO FAPRCD.ENDIVI.; /

For Transportation Methods:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Unit Codes: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For VAT Codes: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Work Order Types: MMORDT.VQCONO CMNDIV.CCDIVI.; /

CodeDefinition/Name

For Accounting Dimension:

FCHACC.EATX15; CRS630MI/GetAccountID

For AP Payment Methods: CSYTAB.CTTX15; .

For AR Payment Methods: CSYTAB.CTTX15; /

For Capabilities: CCADEF.DETX15 ; CBS004MI/Get

For Cost Centers: FCHACC.EATX15

; CRS630MI/GetAccountID, LstAccountIDLng

For Customer Discount Groups:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Customer Groups:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Customer Statistics Identity 1:

For Service Assignment Type:

The field indicates the company and division, displayed as CONO DIVI.

For Service Centers:

The field indicates the company and division, displayed as CONO DIVI.

For Service Error Cause:

The field indicates the company and division, displayed as CONO_DIVI.

For Service Managers:

The field indicates the company and division.

CONO DIVI

For Service Order Types:

The field indicates the company and division, displayed as

CONO_DIVI.

For Service Qualification:

The field indicates the company and division, displayed as

CONO DIVI.

For Service Types:

The field indicates the company and division, displayed as

CONO_DIVI.

For Stock Locations:

The field indicates the company and division, displayed as

CONO DIVI.

For Supplier Invoice Authorized Users: The field indicates the company and division.

CONO DIVI

For Transportation Methods:

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.

E.g. 760_AAA

For Unit Codes:

The field indicates the company and division, displayed as

CONO_DIVI.

For VAT Codes:

The field indicates the company and division, displayed as

CONO_DIVI.

For Work Order Types:

The field indicates the company and division, displayed as

CONO DIVI.

For Accounting Dimension:

The field indicates the accounting dimension name.

For AP Payment Methods:

The field indicates the AP Payment Method name.

For AR Payment Methods:

The field indicates the AR Payment Method name.

For Capabilities:

The field indicates the capability name.

For Cost Centers:

The field indicates the name of the cost center.

For Customer Discount Groups:

The field indicates the discount group name.

For Customer Groups:

The field indicates the Customer group name.

For Customer Statistics Identity 1:

The field indicates the customer statistics identity name.

CSYTAB.CTTX15

; CRS175MI/GetGeneralCode

For Customs Statistics Number:

CSYCSN.CKTX15; CRS128MI/GetBasicData

For Delivery Terms:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Dynamic Dimension: FCHACC.EAAITM; /

For Equipment Classes:

MIEQCL.QTTX15; MMS252MI/Get

For Equipment Groups:

MIEQGR.QGTX15; MMS259MI/Get

For Equipment Meter:

SINDIV.SBMODC; SOS100MI/GetIndividual

For Error Code 1s:

CYSTAB.CTTX15; CRS175MI/GetGeneralCode

For Error Code 2s:

CYSTAB.CTTX15; CRS175MI/GetGeneralCode

For Error Code 3s:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Feature Options: MPDFHE.PETX10; PDS055MI/Get MPDFDS.QQTX10; PDS057MI/List.; /

For Freight Terms: CSYTAB.CTTX15

; CRS175MI/GetGeneralCode

For General Code: CSYTAB.CTTX15 CSYSTS.CKTX15 CRS175MI/LstCodesByLng CRS175MI/GetGeneralCode

.; /

For Harbor Airports: CSYTAB.CTTX15; /

For Individual Item Groups:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Inspection Result Values:

MPDIRV.PLTX15 ; PDS043MI /Get

For Item Discount Groups:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Item Free Field 1:

CSYTAB.CTTX15; CRS181MI/Get

For Item Free Field 3: CSYTAB.CTTX15 ; CRS183MI/Get

For Item Free Field 4: CSYTAB.CTTX15 ; CRS184MI/Get

For Item Free Field 5:

CSYTAB.CTTX15; CRS185MI/Get

For Item Types: MITTTY.TYTX15; /

For Miscellaneous Cost Types:

For Customs Statistics Number:

The field indicates the name of the customs statistics number.

For Delivery Terms:

The field indicates a name of the code.

For Dynamic Dimension:

The field indicates value of an accounting identity in an accounting dimension, equal to DocumentID/ID element. More information about account identities can be retrieved by BE MI Transaction

CRS630MI.GetAccountID.

For Equipment Classes:

The field indicates the equipment class name.

For Equipment Groups:

The field indicates the equipment group name.

For Equipment Meter:

The field indicates the model name of the individual item.

For Error Code 1s:

The field indicates the Error Code 1 name.

For Error Code 2s:

The field indicates the Error Code 2 name.

For Error Code 3s:

The field indicates the Error Code 3 name.

For Feature Options:

The field indicates the feature name.

For Freight Terms:

The field indicates the Freight Term name.

For General Code:

The field indicates the name of the code.

Call CRS175MI/LstCodesByLng if STCO = ITGR, ITCL, BUAR. Call CRS175MI/GetGeneralCode if STCO = PRGP, CSCD, SDST.

For Harbor Airports:

The field indicates the Harbor/Airport name.

For Individual Item Groups:

The field indicates the individual item group name.

For Inspection Result Values:

The field indicates the quality inspection result value name.

For Item Discount Groups:

The field indicates the item discount group name.

For Item Free Field 1:

The field indicates the item user-defined field 1 name.

For Item Free Field 3:

The field indicates the item user-defined field 3 name.

For Item Free Field 4:

The field indicates the item user-defined field 4 name.

For Item Free Field 5:

The field indicates the name of the item free field 5.

For Item Types:

The field indicates the item type name.

For Miscellaneous Cost Types:

The field indicates the Miscellaneous Cost Type name.

For Options:

The field indicates the name of the option.

For Payment Terms:

The field indicates the Payment Term name.

For Points of Shipment:

The field indicates the Point of Shipment (Place) name.

ACUEXP.XPTX15; COS160MI/Get

For Options: MPDOPT.PFTX15 ; PDS050MI/Get

For Payment Terms: CSYTAB.CTTX15

; CRS175MI/LstCodesByLng

For Points of Shipment: CSYTAB.CTTX15

; CRS175MI/GetGeneralCode

For Price List Tables: OPTLMA.E5TX15 ; OIS012MI/LstPriceLstTabl

For Product Lines:

CRPDLN.PLTX15; CRS099MI/GetProductLine

For Product Service Extend:

SSEITM.SRSVDS; SOS200MI/LstServiceExp

For Product Structure Classes: MPDPSC.PCTX15; PDS075MI/GetStuctClass

For Product Structure Types: CSYTAB.CTTX15; /

For Purchase Order Types: MPORDT.OTTX15; /

For Routes: DROUTE.DRTX15; /

For Sales Order Charges: ODCHRG.USCRD0

ODCHRL.USCRD0.; OIS030MI/LstOrderCharges, LstOrderChrgLng

LStorderonigling

For Seasons:

For Sales Order Types:

OOTYPE.OOTX15; OIS010MI/LstOrderTypes

CSEAMA.HSTX15; CRS912MI/GetSeason

For Service Action: SMECOD.SOTX15 ; SOS100MI/LstAction

For Service Action Text:

SMETXT.SMTX15; SOS100MI/LstActTxt

For Service Assignment Type: SASSTP.S1TX15; SOS200MI/LstAssignmType

For Service Centers:

MPDWCT.PPPLNM; PDS010MI/Get

For Service Error Cause: SERCOD.SNTX15; SOS100MI/LstErrCde

For Service Managers: SSRESP.SNL2; /

For Service Order Types:

SSTYPE.SKOTDE; SOS100MI /LstServOrdType

For Service Qualification: CSYTAB.CTTX15;/

For Service Types:

CSYTAB.CTTX15; CRS175MI/GetGeneralCode

For Stock Locations: MITPCE.MSSLDS

For Price List Tables:

The field indicates the price list table name.

For Product Lines:

The field indicates the Product Line name.

For Product Service Extend:

The field indicates the service expense name.

For Product Structure Classes:

The field indicates the name of the product structure class.

For Product Structure Types:

The field indicates the name of the product structure type.

For Purchase Order Types:

The field indicates the code name.

For Routes:

The field indicates the transportation route name.

For Sales Order Charges:

The field indicates the name of the charge to be printed on the external document.

For Sales Order Types: The field indicates the name.

For Seasons:

The field indicates the season name.

For Service Action:

The field indicates the service action name.

For Service Action Text:

The field indicates the Service action text name.

For Service Assignment Type: The field indicates the code name.

For Service Centers:

This field indicates the Service Center name.

For Service Error Cause:

The field indicates the service error cause name.

For Service Managers:

The field indicates the main responsible for a service order. It may contain up to 15 characters. This name is often displayed as a name in panels where the service manager code is displayed. The service manager can be a person or a department responsible for one or more technicians.

For Service Order Types:

The field indicates the Service Order type name.

For Service Qualification:

The field indicates the Service Qualification name.

For Service Types:

The field indicates the service type name.

For Stock Locations:

The field indicates the stock location name.

For Supplier Invoice Authorized Users:

The field indicates the name, retrieved from user record.

For Transportation Methods:

The field indicates the transportation method name.

For Unit Codes:

The field indicates the name of the unit of measure.

For VAT Codes:

The field indicates VAT code name.

MMS010MI/GetLocation

For Supplier Invoice Authorized Users:

FAPRCD.ENTX15; /

For Transportation Methods:

CSYTAB.CTTX15; CRS070MI/LstDelyMethod

For Unit Codes: CSYTAB.CTTX15; /

For VAT Codes: CSYTAB.CTTX15; /

For Work Order Types:

MMORDT.VQTX15; MOS120MI/Get

@languageID

For Accounting Dimension:

FCAIDL.ELLNCD; CRS630MI/LstAccountIDLng

For Cost Centers: FCAIDL.ELLNCD

; CRS630MI/LstAccountIDLng

For Delivery Terms: CSYTAB.CTLNCD; /

For Dynamic Dimension: .; CRS630MI/GetUserInfo

For Feature Options: MPDFDS.QQLNCD: PDS057MI/List

For Freight Terms: CSYTAB.CTLNCD

For General Code:

CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For Payment Terms:

CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For Sales Order Charges:

ODCHRL.USLNCD; OIS300MI/LstOrdrChrgLng

For Transportation Methods:

CSYTAB.CTLNCD; CRS070MI/LstDelyMethod

CodeDefinition/Description

For Accounting Dimension:

FCHACC.EATX40; CRS630MI/GetAccountID

For AP Payment Methods: CSYTAB.CTTX40; .

For AR Payment Methods: CSYTAB.CTTX40; /

For Capabilities: CCADEF.DETX40; CBS004MI/Get

For Cost Centers: FCHACC.EATX40

; CRS630MI/GetAccountID, LstAccountIDLng

For Customer Discount Groups:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Customer Groups:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Customer Statistics Identity 1:

CSYTAB.CTTX40

; CRS175MI/GetGeneralCode

For Customs Statistics Number:

CSYCSN.CKTX40; CRS128MI/GetBasicData

For Work Order Types:

The field indicates the Work Order type name.

For Accounting Dimension:

The field indicates the language code.

For Cost Centers:

The field indicates the language code.

For Delivery Terms:

The field indicates the language ID.

For Dynamic Dimension:

System Language from CRS012.

For Feature Options:

The field indicates the language for the feature name.

For Freight Terms:

The field indicates the language code for Freight Term name.

For General Code:

The field indicates the language code.

For Payment Terms:

The field indicates the language code for the Payment Term name.

For Sales Order Charges:

The field indicates the language that name of the charge is translated to. @language attribute is not displayed for non-language-specific

Name.

For Transportation Methods: The field indicates the language.

For Accounting Dimension:

The field indicates the accounting dimension description.

For AP Payment Methods:

The field indicates the AP Payment Method description.

For AR Payment Methods:

The field indicates the AR Payment Method description.

For Capabilities:

The field indicates the capability description.

For Cost Centers:

The field indicates the description of the cost center.

For Customer Discount Groups:

The field indicates the discount group description.

For Customer Groups:

The field indicates the Customer group description.

For Customer Statistics Identity 1:

The field indicates the customer statistics identity description.

For Customs Statistics Number:

The field indicates the description of the customs statistics number.

For Delivery Terms:

The field indicates the description.

For Delivery Terms:

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Dynamic Dimension: FCHACC.EAAITM; /

For Equipment Classes:

MIEQCL.QTTX40; MMS252MI/Get

For Equipment Groups:

MIEQGR.QGTX40; MMS259MI/Get

For Equipment Meter:

SINDIV.SBMODE; SOS100MI/GetIndividual

For Error Code 1s:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Error Code 2s:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Error Code 3s:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Feature Options: MPDFHE.PETX30; PDS055MI/Get MPDFDS.QQTX30; PDS057MI/List.; /

For Freight Terms: CSYTAB.CTPARM

; CRS175MI/GetGeneralCode

For General Code: CSYTAB.CTTX40 CSYSTS.CKTX40 CRS175MI/LstCodesByLng CRS175MI/GetGeneralCode

.; /

For Harbor Airports: CSYTAB.CTTX40; /

For Individual Item Groups:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Inspection Result Values:

MPDIRV.PLTX40; PDS043MI /Get

For Item Discount Groups:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Item Free Field 1:

CSYTAB.CTTX40; CRS181MI/Get

For Item Free Field 3: CSYTAB.CTTX40 ; CRS183MI/Get

For Item Free Field 4: CSYTAB.CTTX40 ; CRS184MI/Get

For Item Free Field 5:

CSYTAB.CTTX40; CRS185MI/Get

For Item Types: MITTTY.TYTX40; /

For Miscellaneous Cost Types: ACUEXP.XPTX40; COS160MI/Get

For Options: MPDOPT.PFTX30; PDS050MI/Get For Dynamic Dimension:

The field indicates value of an accounting identity in an accounting dimension, equal to DocumentID/ID element. More information about account identities can be retrieved by BE MI Transaction

CRS630MI.GetAccountID.

For Equipment Classes:

The field indicates the equipment class description.

For Equipment Groups:

The field indicates the equipment group description.

For Equipment Meter:

The field indicates the model description of the individual item.

For Error Code 1s:

The field indicates the Error Code 1 description.

For Error Code 2s:

The field indicates the Error Code 2 description.

For Error Code 3s:

The field indicates the Error Code 3 description.

For Feature Options:

The field indicates the feature description.

For Freight Terms:

The field indicates the Freight Term Description.

For General Code:

The field indicates the description of the code.

Call CRS175MI/LstCodesByLng if STCO = ITGR, ITCL, BUAR. Call CRS175MI/GetGeneralCode if STCO = PRGP, CSCD, SDST.

For Harbor Airports:

The field indicates the Harbor/Airport description.

For Individual Item Groups:

The field indicates the individual item group description.

For Inspection Result Values:

The field indicates the quality inspection result value description.

For Item Discount Groups:

The field indicates the item discount group description.

For Item Free Field 1:

The field indicates the item user-defined field 1 description.

For Item Free Field 3:

The field indicates the item user-defined field 3 description.

For Item Free Field 4:

The field indicates the item user-defined field 4 description.

For Item Free Field 5:

The field indicates the description of the item free field 5.

For Item Types:

The field indicates the item type description.

For Miscellaneous Cost Types:

The field indicates the Miscellaneous Cost Type description.

For Options:

The field indicates the description of the option.

For Payment Terms:

The field indicates the Payment Term text. It is a substring of the first

72 characters of field PARM.

For Points of Shipment:

The field indicates the Point of Shipment (Place) description.

For Price List Tables:

The field indicates the price list table description.

For Payment Terms: CSYTAB.CTPARM

; CRS175MI/LstCodesByLng

For Points of Shipment: CSYTAB.CTTX40

; CRS175MI/GetGeneralCode

For Price List Tables: OPTLMA.E5TX40

; OIS012MI/LstPriceLstTabl

For Product Lines:

CRPDLN.PLTX40; CRS099MI/GetProductLine

For Product Service Extend: 1) SSEITM.SRTEDS SOS200MI/LstServiceExp 2) SSEITM.SRFUDS

SOS200MI/LstServiceExp.; SOS200MI/LstServiceExp

For Product Structure Classes: MPDPSC.PCTX40

; PDS075MI/GetStuctClass

For Product Structure Types: CSYTAB.CTTX40; /

For Purchase Order Types: MPORDT.OTTX40; /

For Routes: DROUTE.DRTX40; /

For Sales Order Types:

OOTYPE.OOTX40; OIS010MI/LstOrderTypes

For Seasons:

CSEAMA.HSTX40; CRS912MI/GetSeason

For Service Action: SMECOD.SOTX40 ; SOS100MI/LstAction

For Service Action Text: SMETXT.SMTX40; /

For Service Assignment Type: SASSTP.S1TX40; SOS200MI/LstAssignmType

For Service Error Cause: SERCOD.SNTX40

For Service Error Symptom: SERSYM.SLTX15; SOS100MI.LstErrSym

For Service Managers: SSRESP.SNL1; /

For Service Qualification: CSYTAB.CTTX40;

For Service Types:

CSYTAB.CTTX40; CRS175MI/GetGeneralCode

For Supplier Invoice Authorized Users: FAPRCD.ENTX40; /

For Transportation Methods:

CSYTAN.CTPARM; CRS070MI/LstDelyMethod

For Unit Codes: CSYTAB.CTTX40; /

For VAT Codes: CSYTAB.CTTX40; /

For Product Lines:

The field indicates the Product Line description.

For Product Service Extend:

The field indicates the service expense description.

1) Description 1

The field indicates the description 1.

2) Description 2

The field indicates the description 2.

For Product Structure Classes:

The field indicates the description of the product structure class.

For Product Structure Types:

The field indicates the description of the product structure type.

For Purchase Order Types:

The field indicates the code description.

For Routes:

The field indicates the transportation route description.

For Sales Order Types:

The field indicates the description.

For Seasons:

The field indicates the season description.

For Service Action:

The field indicates the service action description.

For Service Action Text:

The field indicates the Service action text description.

For Service Assignment Type:

The field indicates the code description.

For Service Error Cause:

The field indicates the service error cause description.

For Service Error Symptom:

The field indicates the error symptom description.

The field contains 15 positions. When record updates the descriptions and names.

If no name is entered, the first 15 positions from the description field will automatically be proposed as the name.

For Service Managers:

The field indicates the main responsible for a service order. It may contain a maximum of 40 characters. The service manager can be a person or a department responsible for one or more technicians.

For Service Qualification:

The field indicates the Service Qualification description.

For Service Types:

The field indicates the service type description.

For Supplier Invoice Authorized Users:

The field indicates the user name, retrieved from user record.

For Transportation Methods:

The field indicates the description. This is a concatenation of Terms text 1 (TEL1) and Terms text 2 (TEL2) separated by a single space.

For Unit Codes:

The field indicates the description of the unit of measure.

For VAT Codes:

The field indicates VAT code description.

For Work Order Types:

The field indicates the Work Order type description.

For Work Order Types: MMORDT.VQTX40; MOS120MI/Get

@type

@languageID

For Accounting Dimension:

FCAIDL.ELLNCD; CRS630MI/LstAccountIDLng

For Cost Centers: FCAIDL.ELLNCD

; CRS630MI/LstAccountIDLng

For Dynamic Dimension: .; CRS630MI/GetUserInfo

For Feature Options: MPDFDS.QQLNCD; PDS057MI/List

For Freight Terms: CSYTAB.CTLNCD

For General Code:

CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For Payment Terms:

CSYTAB.CTLNCD; CRS175MI/LstCodesByLng

For Transportation Methods:

CSYTAB.CTLNCD; CRS070MI/LstDelyMethod

For Product Service Extend:

1) Set to '1' if the populated field is description 1. 2) Set to '2' if the populated field is description 2.

For Accounting Dimension:

The field indicates the language code.

For Cost Centers:

The field indicates the language code.

For Delivery Terms:

The field indicates the language ID.

For Dynamic Dimension:

System Language from CRS012.

For Feature Options:

The field indicates the language for the feature description.

For Freight Terms:

The field indicates the language code for Freight Term description.

For General Code:

The field indicates the language code.

For Payment Terms:

The field indicates the language code for Payment Term description.

For Transportation Methods: The field indicates the language.

CodeDefinition/Property

@sequence

For Feature Options: MPDVOF.PLSQNU: PDS056MI/List

For Product Service Extend:

1) SITCOM.USAM1U SITCOM.USAM2U SITCOM.USAM3U SITCOM.USAM4U SITCOM.USAM5U SITCOM.USLM6U

SOS400MI/LstltSrvSupplm 2) SITCOM.USLM1U SITCOM.USLM2U SITCOM.USLM3U SITCOM.USLM4U SITCOM.USLM5U

SITCOM.USLM6U SOS400MI/LstltSrvSupplm 3) SITCOM.USIM1U SITCOM.USIM2U SITCOM.USIM3U

SITCOM.USIM4U SITCOM.USIM5U

SITCOM.USIM6U SOS400MI/LstltSrvSupplm 4) SITCMD.UTI1BM

SITCMD.UTI2BM SITCMD.UTI3BM

SITCMD.UTI4BM

SITCMD.UTI5BM SITCMD.UTI6BM

SOS400MI/LstMtrByItm

For Equipment Meter:

The field indicates the sequence number of the name value. It is applicable only to Physical, Logical and Invoice meters.

For Feature Options:

The field indicates the sequence number for sorting.

For Options:

The field indicates the sequence number.

For Product Service Extend:

The field indicates the originDocument and table SITCOM or SITCMD.

1) Set to '1, 2, 3, 4, 5 or 6 if actual meter is use is populated.
2) Set to '1, 2, 3, 4, 5 or 6' if logical meter is use is populated.
3) Set to '1, 2, 3, 4, 5 or 6' if invoice meter is use is populated.
4) Set to '1, 2, 3, 4, 5 or 6' if invoice meter is use is populated.

For Product Structure Classes:

The field indicates the sequence number.

For Service Action Text:

The field indicates the sequence of the property.

.; /

CodeDefinition/Property/NameValue

For Customs Statistics Number:
1) CSYCSN.CKINYN
CRS128MI/GetBasicData
2) CSYCSN.CKSUPL
CRS128MI/GetBasicData
3) CSYCSN.CKSPFA
CRS128MI/GetBasicData.; /

For Customs Statistics Number:

1) Intrastat Generating

The field indicates if items belonging to the EU customs number are to be included in the basis for Intrastat accounting.

Set to 'true' if INYN = 1.

For Equipment Classes:

MIEQCL.QTEQCC; MMS252MI/Get

For Equipment Groups:

MIEQGR.QGEQGC; MMS259MI/Get

For Equipment Meter: 1)SINDMD.SBI1BM SOS100MI/GetMtrByInd

2)SINDMD.SBI2BM SOS100MI/GetMtrByInd

3)SINDMD.SBI3BM SOS100MI/GetMtrByInd

4)SINDMD.SBI4BM SOS100MI/GetMtrByInd

5)SINDMD.SBI5BM SOS100MI/GetMtrByInd

6)SINDMD.SBI6BM SOS100MI/GetMtrByInd

7)SINDMD.SBTMBM SOS100MI/GetMtrByInd

8)SINDMD.SBAMB1 SOS100MI/GetMtrByInd

9)SINDMD.SBAMB2 SOS100MI/GetMtrByInd

10)SINDIV.SAAM1U SOS100MI/GetIndividual

11)SINDIV.SAAM2U SOS100MI/GetIndividual

12)SINDIV.SAAM3U SOS100MI/GetIndividual

13)SINDIV.SAAM4U SOS100MI/GetIndividual

14)SINDIV.SAAM5U SOS100MI/GetIndividual

15)SINDIV.SAAM6U SOS100MI/GetIndividual

16)SINDIV.SALM1U SOS100MI/GetIndividual

17)SINDIV.SALM2U SOS100MI/GetIndividual

18)SINDIV.SALM3U SOS100MI/GetIndividual

19)SINDIV.SALM4U SOS100MI/GetIndividual

20)SINDIV.SALM5U SOS100MI/GetIndividual

21)SINDIV.SALM6U SOS100MI/GetIndividual

22)SINDIV.SAIM1U SOS100MI/GetIndividual

23)SINDIV.SAIM2U SOS100MI/GetIndividual

24)SINDIV.SAIM3U SOS100MI/GetIndividual Set to 'false' if INYN = 0.

Set attribute name to 'IntrastatGenerating'.

2) Supplementary UOM

The field indicates the supplementary unit of measure for a customs statistics number.

Set attribute name to 'SupplementaryUOM'.

3) Conversion Factor Supplementary UOM

The field indicates a recalculation factor for the supplementary unit of measure. It is used when a delivered or received quantity is to be recalculated to the supplementary unit of measure.

Set attribute name to 'ConversionFactorSupplementaryUOM'.

For Equipment Classes:

The field indicates the equipment class category. Set to 'Linear assets' if equipment class category is 02. Set to 'Fixed' if equipment class category is 03.

Set to 'Mobile' if equipment class category is 04.

For Equipment Groups:

The field indicates the equipment group category.

Set to 'Normal' if equipment group category is 00.

Set to 'Rent' if equipment group category is 01.

Set to 'Lease' if equipment group category is 02.

Set to 'Core' if equipment group category is 03.

Set to 'Used equipment' if equipment group category is 04.

Set to 'Simulation' if equipment group category is 05.

Set to 'Rebuild' if equipment group category is 06.

For Equipment Meter:

The field indicates the meter identifier.

For Feature Options:

1) The field indicates the feature group that can be used for selection and as additional information for a feature. The set groups X, Y and Z must be used for features that will be displayed in matrix form, where they represent the axes.

2) The field indicates the option which provides a selection that can be applied for the feature.

For Miscellaneous Cost Types: The field indicates the following:

1.) Unit of Measure

2.) Tax Code

3.) Set to 1 if registration number is required.

4.) Set to 1 if expense transactions require approval.

For Options:

The field indicates the grouping of options.

For Points of Shipment:

1) Country

The field indicates the country from which goods were sent.

2) Time zone

The field indicates the international time zone such as Central European (CET) or CET+1.

For Product Service Extend:

1) Actual meter (1-6) in use

The field indicates the meter details defined for the item or individual item. Set to attribute name to 'MeterIdentifier'.

2) Logical meter (1-6) in use

The field indicates the meter details defined for the item or individual item. Set to attribute name to 'MeterIdentifier'.

3) Invoice meter (1-6) in use

The field indicates the meter details defined for the item or individual item. Set to attribute name to 'MeterIdentifier'.

4) Invoice meter (1-6) in use

The field indicates the meter details defined for the item or individual item. Set to attribute name to 'BasedOnProductMeter' or 'BasedOnProductMeterTotal'.

5) Usage Period Type 1

25)SINDIV SAIM4U SOS100MI/GetIndividual

26)SINDIV.SAIM5U SOS100MI/GetIndividual

27)SINDIV.SAIM6U SOS100MI/GetIndividual.; /

For Feature Options: 1) MPDFHE.PEFGRP; PDS055MI/Get 2) MPDVOF.PLOPTN: PDS056MI/List .; /

For Miscellaneous Cost Types:

1.) ACUEXP.XPUNIT COS160MI/Get

2.) ACUEXP.XPTAXC COS160MI/Get

3.) ACUEXP.XPRNRQ COS160MI/Get

4.) ACUEXP.XPMAPE COS160MI/Get.; /

For Options: MPDOPT.PFOGRP ; PDS050MI/Get

For Points of Shipment: CSYTAB.CTPARM

; CRS175MI/GetGeneralCode

For Product Service Extend:

1) SITCOM.USAM1U SÍTCOM.USAM2U

SITCOM.USAM3U SITCOM.USAM4U

SITCOM.USAM5U

SITCOM.USLM6U

SOS400MI/LstltSrvSupplm

2) SITCOM.USLM1U

SITCOM.USLM2U

SITCOM.USLM3U

SITCOM.USLM4U SITCOM.USLM5U

SITCOM.USLM6U

SOS400MI/LstltSrvSupplm

3) SITCOM.USIM1U

SITCOM.USIM2U

SITCOM.USIM3U

SITCOM.USIM4U

SITCOM.USIM5U

SITCOM.USIM6U

SOS400MI/LstltSrvSupplm

4) SITCMD.UTI1BM SITCMD.UTI2BM

SITCMD.UTI3BM

SITCMD.UTI4BM

SITCMD.UTI5BM

SITCMD.UTI6BM

SITCMD.UTTMBM

SOS400MI/LstMtrByItm

5) SITCMD.UTAMB1

6) SITCMD.UTAMB2 SOS400MI/LstMtrByItm

7) SSEITM.SRSETP

8)SSEITM.SRSCOD

9)SSEITEM.SEERCO

10) SSEITEM.SRMECO

SÓS200MI.LstServiceExp

11) SITCOM.USMEIT

12)SITCOM.USINDC

SÓS400Mi.LstltmSrvSupplm.; /

The field indicates the usage period type 1. Set attribute name to 'UsagePeriodType1'.

6) Usage Period Type 2

The field indicates the usage period type 2. Set attribute name to 'UsagePeriodType2'

7) Service expense type

The field indicates the service expense type. Set to attribute name 'ServiceExpenseType'

8) Service expense category

The field indicates the service expense type. Set to attribute name 'ServiceExpenseCategory'.

9) Error cause

The field indicates the service expense category. Set to attibute name 'ServieErrorCause'.

10) Action

The field indicates the action. Set to attribute name

'ServiceErrorAction'.

11) Meter item

The field indicates the meter item. Set to attribute name 'MeterItem'.

12) Individual item management

The field indicates the individual item management. Set to attribute 'IndividualItemManagement'.

For Product Structure Classes:

The field indicates the product structure class type.

00 - Discrete

11 - Formula

12 - Routing

13 - Bulk item

14 - Packaging material

15 - Packaged item

For Seasons:

The field indicates the name value.

1)The field indicates the first order date for the season.

2)The field indicates the last date orders can be entered for the season.

For Service Action:

1) Item number

The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item

Set attribute name to 'ProductID'.

2) Individual item number

The field indicates a number that identifies an individual item Set attribute name to 'EquipmentID'.

3) Individual item group

The field indicates which group this individual item belongs to. Set attribute name to 'EquipmentGroup'.

4) Action class

The field indicates how to classify an action.

Set attribute name to 'ServiceActionClass'.

5) Qualification

The field indicates the code that describes the education, experience and other skills of the employees in a company.

Set attribute name to 'ServiceQualification'.

6) Planned work hours

The field indicates the time required to perform a service assignment. All time is considered except preparation time, travel time and finish

Set attribute name to 'PlannedWorkHours'.

For Service Action Text:

1) ProductID

The field indicates the item number. Set the attribute name to 'ProductID'.

2) EquipmentID

The field indicates the number that identifies an individual item. Set the attribute name to 'EquipmentID'

3) EquipmentGroup

The field indicates the individual item belongs to. Set the attribute name to 'EquipmentGroup'.

For Product Structure Classes:

MPDPSC.PCPCLT

; PDS075MI/GetStuctClass

For Seasons:

CSEAMA.HSFOED

CSEAMA.HSLOED.; CRS912MI/GetSeason

For Service Action:

1) SMECOD.SOITNO

2) SMECOD.SOINNO

3) SMECOD.SOINGR

4) SMECOD.SOMECL

5) SMECOD.SOQUNO

6) SMECOD.SOPLWT.; SOS100MI/LstAction

For Service Action Text:

1) SMETXT.SMITNO

SOS100MI.LstActTxt

2) SMETXT.SMIINO

SOS100MI.LstActTxt

3) SMETXT.SMINGR

SOS100MI.LstActTxt

4) SMETXT.SMQUNO

SOS100MI.LstActTxt

5) SMETXT.SMPLWT

SOS100MI.LstActTxt

6) SMETXT.SMMECO

SOS100MI.LstActTxt

7) SMETXT.SMMTX1-SMMTX4

SOS100MI.LstActTxt.; /

For Service Assignment Type:

SASSTP.S1PRIO

SASSTP.S1ASCL

SASSTP.S1APTM.; SOS200MI/LstAssignmType

For Service Centers:

- 1) MPDWCT.PPFACI
- 2) MPDWCT.PPDEPT
- 3) MPDWCT.PPREAR
- 4) MPDWCT.PPWHLO
- 5) MPDWCT.PPPLTP
- 6) MPDWCT.PPPLGT.

; PDS010MI/Get

For Service Error Cause:

- 1) SERCOD.SNITNO
- 2) SERCOD. SNINNO
- 3) SERCOD.SNINGR 4) SERCOD. SNQUNO
- 5) SERCOD. SNERCL
- 6) SERCOD. SNPLWT
- 7) SERCOD.SNOPRI.; SOS100MI/LstErrCde

For Service Error Symptom:

1) SERSYM.SLITNO

SOS100MI/LstErrSym

2) SERSYM.SLINNO SOS100MI/LstErrSym

3) SERSYM.SLINGR

SOS100MI/LstErrSym

4) SERSYM.SLERCO

SOS100MI/LstErrSym

5) SERSYM.SLQUNO SOS100MI/LstErrSym

6) SERSYM.SLSUFI SOS100MI/LstErrSym

7) SERSYM.SLPLWT

4) ServiceQualification

The field indicates the code that describes the education, experience and other skills of the employees in a company. Set the attribute name to 'ServiceQualification'.

5) PlannedWorkHours

The field indicates the time required to perform a service assignment. Set the attribute name 'PlannedQWorkHours'.

6) ServiceAction

The field indicates the service action. Set the attribute name to 'ServiceAction'.

7) ServiceAction1- ServiceAction4

The field indicates the optional text to describe an action taken on an individual item entry or reporting of a service assignment. Set attribute name to 'ServiceAction1-ServiceAction4'.

For Service Assignment Type:

The field indicates the value of one of the following assignment type properties: Priority, Assignment Class or Response time. Which properties value it is indicated by fields attribute @name.

For Service Centers:

1) Facility

The field indicates the the facility (FACI). Set attribute name to 'Facility'.

2) Department

The field indicates the name of the department. Set attribute name to 'Department'.

3) Area

The field indicates the level between work center and department. Set attribute name to 'Area'.

4) Warehouse

The field indicates the warehouse for the location. Set attribute name to 'Warehouse'.

5) Resource Type

The field indicates the type of resource a work center. Set the attribute name to 'ResourceType'.

Set to 'Operation', if the resource type is 1.

Set to 'Subcontract', if the resource type is 2.

Set to Subcontract, if the resource type is 2.

Set to 'Rough-cut W/C', if the resource type are 4 or 5.

Set to 'W/C Resource', if the resource type is 6.

Set to 'Maintenance W/C', if the resource type is 9.

6) Work Center Type

The field indicates the work center defined for consolidated facility which is used to group related work centers. Set attribute name to 'WorkCenterType'.

For Service Error Cause:

1) Item number

The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item

Set attribute name to 'ProductID'.

2) Individual item number

The field indicates a number that identifies an individual item Set attribute name to 'EquipmentID'.

3) Individual item group

The field indicates which group this individual item belongs to. Set attribute name to 'EquipmentGroup'.

4) Qualification

The field indicates the code that describes the education, experience and other skills of the employees in a company. Set attribute name to 'ServiceQualification'.

5) Error class

The field indicates similar error reasons. It is used for statistical purposes by indicating an error class. Set attribute name to 'ServiceErrorClass'.

6) Planned work hours

The field indicates the time required to perform a service assignment. All time is considered except preparation time, travel time and finish

SOS100MI/LstErrSym

8) SERSYM.SLETX1+SLETX2+SLETEX3+SLETEX4 SOS100MI/LstErrSym.; .

For Service Managers: SSRESP.SCRECT SSRESP.SCUSID SSRESP.SCRECM.String Decimal ; SOS100MI/LstServManager

For Service Order Types:

SSTYPE.SKASST

SKSOTK; SOS100MI /LstServOrdType

For Service Types:

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

For Stock Locations: 1) MITPCE.MSWHLO; 2) MITPCE.MSRESP MMS010MI/GetLocation 3) MITPCE.MSSLTP; MMS010MI/GetLocation 4) MITPCE.MSWHLT; MMS010MI/GetLocation 5) MITPCE.MSABFC; MMS010MI/GetLocation 6) MITPCE.MSPISE; MMS010MI/GetLocation 7) MITPCE.MSCMNG;

For Work Order Types:

MMS010MI/GetLocation.; /

MMORDT.VQMOTC; MOS120MI/Get

time.

Set attribute name to 'PlannedWorkHours'.

The field indicates the error cause priority.

Set attribute name to 'Priority'.

For Service Error Symptom:

1) Item number

The field indicates the item number (ITNO). Set attribute name to 'ProductID'.

2) Individual item number

The field indicates the individual item number (INNO). Set attribute name to 'EquipmentID'.

3) Individual item group

The individual item number (INGR). Set to attribute name to 'EquipmentGroupCode'.

4) Error cause

The field indicates the error cause (ERCO). Set to attribute name to 'ServiceErrorCauseCode'.

5) Qualification

The field indicates the qualification (QUNO). Set to attribute name to 'ServiceQualificationCode'.

The field indicates the service (SUFI). Set to attribute name to 'ServiceID'.

7) Planned work hours

The field indicates the planned work hours (PLWT). Set to attribute name to 'PlannedWorkHours'.

8) Error symptom text

The field indicates the error symptom text

(ETX1+ETX2+ETX3+ETX4). It is concatenation of error symptom text 1 + error symptom text 2 + error symptom text 3. Set to attribute name to 'ServiceErrorSymptomText'.

For Service Managers:

The field indicates the area/user/recipient.

For Service Order Types:

1) Service Assignment Type

The field indicates the ID of the assignment type.

Set attribute name to 'ServiceAssignmentType'.

2) Service Order Category

The field indicates the use of the service order type.

Set to 'Normal' if Service Order Category is 1.

Set to 'Credit order' if Service Order Category is 2.

Set to 'Agreement invoicing order' if Service Order Category 3.

Set to 'Quotation Order' is Service Order Category 4.

Set to 'Cash Order' if Service Order Category 5. Set to 'Adjustment order' if Service Order Category 6.

Set to 'Inhouse order' if Service Order Category 8.

Set to 'Preventative Service Order' if Service Order Category 9.

Set to 'Rental - debit' if Service Order Category S.

Set to 'Rental - credit' if Service Order Category C.

Set to 'Leasing - credit' if Service Order Category K. Set to 'Leasing - debit' if Service Order Category L.

Set attribute name to 'ServiceOrderCategory'.

For Service Types:

The field indicates the service classification.

For Stock Locations:

1) The field indicates the warehouse.

Set attribute name to 'Warehouse'.

2) The field indicates a unique user ID.

Set attribute name to 'Responsible'.

3) The field indicates the ID of a stock zone.

Set attribute name to 'StockZone'.

4) The field indicates the group of locations based on the

@name

For Service Error Symptom:

characteristics.

Set attribute name to 'LocationType'.

5) The field indicates the ABC class - frequency.

Set attribute name to 'ABCClass-Frequency'.

6) The field indicates the warehouse equipment.

Set attribute name to 'WarehouseEquipment' .

7) The field is set to 'true' if container management is used for the location. Otherwise, the field is set to 'false'.

Set attribute name to 'ContainerManagement'.

For Work Order Types:

The field indicates the category to which a user-defined work order type is connected.

Set to 'Simulation order' if Work Order Category is 01.

Set to 'Forecast order' if Work Order Category 05.

Set to 'Auto-report order' if Work Order Category 10.

Set to 'Normal order' if Work Order Category 20. Set to 'Claim order' if Work Order Category 30.

Set to 'Project order' if Work Order Category 40.

Set to 'Inspection order' if Work Order Category 50.

Set to 'Orders that are generated from sub-Works and included in a

work order network' if Work Order Category 60.

Set to 'Work order' if Work Order Category 70.

Set attribute name to 'WorkOrderCategory'.

For Customs Statistics Number:

- 1) Set to 'IntrastatGenerating' if Property/NameValue is INYN.
- 2) Set to 'SupplementaryUOM' if Property/NameValue is SUPL.
- 3) Set to 'ConversionFactorSupplementaryUOM' if Property/ NameValue is SPFA.

For Equipment Classes:

Set to 'EquipmentClassCategory'.

For Equipment Groups:

Set to 'EquipmentGroupCategory'.

For Equipment Meter:

Set to 'M1' if AM1U is not empty.

Set to 'M2' if AM2U is not empty.

Set to 'M3' if AM3U is not empty.

Set to 'M4' if AM4U is not empty.

Set to 'M5' if AM5U is not empty.

Set to 'M6' if AM6U is not empty.

Set to 'L1' if LM1U is not empty. Set to 'L2' if LM2U is not empty.

Set to 'L3' if LM3U is not empty.

Set to 'L4' if LM4U is not empty.

Set to 'L5' if LM5U is not empty.

Set to 'L6' if LM6U is not empty. Set to 'I1' if IM1U is not empty.

Set to 'I2' if IM2U is not empty.

Set to 'I3' if IM3U is not empty.

Set to 'I4' if IM4U is not empty. Set to 'I5' if IM5U is not empty.

Set to 'I6' if IM6U is not empty.

Set to 'BasedOnEquipmentMeterID' if I1BM/I2BM/I3BM/I4BM/I5BM/ I6BM is not empty.

Set to 'T1' if TMBM is not empty.

Set to 'UsagePeriodType1' if AMB1 is not empty.

Set to 'UsagePeriodType2' if AMB2 is not empty.

For Feature Options:

The field indicates the name attribute.

- 1) Set to 'StyleFeatureTypes' if Feature Group is published.
- 2) Set to 'StyleOption' if Option is published.

For Miscellaneous Cost Types:

The field is set to the following:

- 1.) 'BasicUnitOfMeasure'
- 2.) 'TaxCode'
- 3.) 'RegistrationNumberRequired'
- 4.) 'MandatoryApproval'

For Options:

Set to 'OptionGroups' if Option group is published.

For Points of Shipment:

- 1) Set to 'Country' for Country (CSCD).
- 2) Set to 'TimeZone' for Time Zone (TIZO).

For Product Service Extend:

- Set to 'MeterIdentifier'.
- 2) Set to 'MeterIdentifier'.
- 3) Set to 'MeterIdentifier'.
- 4) Set to 'BasedOnProductMeter' or 'BasedOnProductMeterTotal'.
- 5) Set to 'UsagePeriodType1'.
- 6) Set to 'UsagePeriodType2'.
- 7) Set to 'ServiceExpenseType'.
- 8) Set to 'ServiceExpenseCategory'.
- Set to 'Labor' if service expense category is 0.
- Set to 'Service kit' if service expense category is 1.
- Set to 'Travel time' if service expense category is 2.
- Set to 'Tool' if service expense category is 3.
- Set to 'Travel expenses' if service expense category is 4.
- Set to 'Per diem' if service expense category is 5.
- Set to 'Subcontract' if service expense category is 6.
- Set to 'Paid amount' if service expense category is 7.
- Set to 'Material' if service expense category is 8
- Set to 'Contract item' if service expense category is 9.
- 9) Set to 'ServieErrorCause'.
- 10) Set to 'ServiceErrorAction'.
- 11) Set to 'MeterItem'.
- 12) Set to 'IndividualItemManagement'.

For Product Structure Classes:

The field indicates the name attribute. Set to 'ClassType'.

For Seasons:

- 1)'FirstOrderDate'.
- 2)'LastOrderDate'.

For Service Action:

- 1) Set to 'ProductID' if Property/NameValue = ITNO
- 2) Set to 'EquipmentID' if Property/NameValue = INNO
- 3) Set to 'EquipmentGroup' if Property/NameValue = INGR
- 4) Set to 'ServiceActionClass' if Property/NameValue = MECL
- 5) Set to 'ServiceQualification' if Property/NameValue = QUNO
- 6) Set to 'PlannedWorkHours' if Property/NameValue = PLWT

For Service Action Text:

- 1) Set to 'ProductID'
- 2) Set to 'EquipmentID'.
- 3) Set to 'EquipmentGroup'.
- 4) Set to 'ServiceQualification'.
- 5) Set to 'PlannedWorkHours'.
- 6) Set to 'ServiceAction'.
- 7) Set to 'ServiceAction1-ServiceAction4'.

For Service Assignment Type:

Set to 'Priority' if property represents the value of Priority.

Set to 'AssignmentClass' if property represents the value of Assignment class.

Set to 'ResponseTime' if property represents the value of Response

For Service Centers:

- Set to 'Facility'.
 Set to 'Department'.
- 3) Set to 'Area'.
- 4) Set to 'Warehouse'.
- 5) Set to 'ResourceType'.
- 6) Set to 'WorkCenterType'.

For Service Error Cause:

- 1) Set to 'ProductID' if Property/NameValue = ITNO
- 2) Set to 'EquipmentID' if Property/NameValue = INNO
- 3) Set to 'EquipmentGroup' if Property/NameValue = INGR
- 4) Set to 'ServiceQualification' if Property/NameValue = QUNO
- 5) Set to 'ServiceErrorClass' if Property/NameValue = ERCL 6) Set to 'PlannedWorkHours' if Property/NameValue = PLWT
- 7) Set to 'Priority' if Property/NameValue = OPRI

For Service Error Symptom:

- 1) Set to 'ProductID'.
- 2) Set to 'EquipmentID'

@type

CodeDefinition/Property/Description

For Feature Options: 1) MPDOPT.PFTX30; PDS056MI/List 2) MPDOPT.PFTX15; PDS050MI/Get 3) MPDODS.QPTX30: PDS050MI/LstNameLanguage

For Service Error Symptom:

SERSYM.SLTX15; SOS100MI.LstErrSym

@type

@languagelD

For Feature Options: MPDODS.QPLNCD ; PDS050MI/LstNameLanguage 3) Set to 'EquipmentID'.

4) Set to 'ServiceErrorCauseCode'.

5) Set to 'ServiceQualificationCode'.

6) Set to 'ServiceID'.

7) Set to 'PlannedWorkHours'.

8) Set to 'ServiceErrorSymptom text'.

For Service Managers:

The field indicates the 'Area' / 'User' / 'Recipient'.

For Service Order Types:

1) Set to 'ServiceAssignmentType'.

2) Set to 'ServiceOrderCategory'.

For Service Types:

The field indicates the service classification description.

Set to 'Standard job' if service classification is 1.

Set to 'Ad hoc job' if service classification is 2.

Set to 'Preventive' if service classification is 3.

Set to 'Modification' if service classification is 4.

Set to 'Customer' if service classification is 5.

Set to 'Blanket work order' if service classification is 9.

For Stock Locations:

1) Set to 'Warehouse' if Property/NameValue = WHLO .

2) Set to 'Responsible' if Property/NameValue = RESP.

3) Set to 'StockZone' if Property/NameValue = SLTP.

4) Set to 'LocationType' if Property/NameValue = WHLT.

5) Set to 'ABCClass-Frequency' if Property/NameValue = ABFC.

6) Set to 'WarehouseEquipment' if Property/NameValue = PISE.

7) Set to 'ContainerManagement' if Property/NameValue = CMNG.

For Work Order Types:

Set to 'WorkOrderCategory'.

For Equipment Meter:

Set to 'Physical meter' if AM1U/AM2U/AM3U/AM4U/AM5U/AM6U is not empty.

Set to 'Logical meter' if LM1U/LM2U/LM3U/LM4U/LM5U/LM6U is not empty

Set to 'Invoice meter' if IM1U/IM2U/IM3U/IM4U/IM5U/IM6U is not empty.
Set to " if I1BM/I2BM/I3BM/I4BM/I5BM/I6BM is not empty.

Set to 'Total meter' if TMBM is not empty.

Set to "if AMB1/AMB2 is 0.

Set to 'Day' if AMB1/AMB2 is 1.

Set to 'Week' if AMB1/AMB2 is 2.

Set to 'Month' if AMB1/AMB2 is 3.

Set to 'Quart' if AMB1/AMB2 is 4.

Set to 'Year' if AMB1/AMB2 is 5.

For Product Service Extend:

The field indicates the originDocument and table SITCOM or SITCMD.

1) Set to 'Physical' if actual meter is 1, 2, 3, 4, 5, or 6.

2)Set to 'Logical' if actual meter is 1, 2, 3, 4, 5, or 6.

3) Set to 'Invoice' if actual meter is 1, 2, 3, 4, 5, or 6.

For Feature Options:

The field indicates the Option name and description.

1) Option description is published without any attribute.

2) Option name is published with attribute type='Short Name'.

3) Option description for different language/s is published with its corresponding languageID attribute.

For Service Error Symptom:

The field indicates the description.

ITNO = MMS200MI/Get/ITDS; INNO = SOS200MI/LstIndivItems/ MODE; ERCO = SOS100MI/LstErrCde/TX15; QUNO = CRS175MI/ GetGeneralCode/TX15 where STCO = QUNO;

For Feature Options:

The field indicates the description type attribute. Set to "Short Name" if Option name is published.

For Feature Options:

The field indicates the language for the option description. Use Option (OPTN) and Feature (FTID) as input to retrieve data.

ConfiguredAssetMaster

ConfiguredAssetMaster/IDs/ID	
For Serialized Item:	For Serialized Item:
MILOIN.LIITNO	The field indicates the primary key for the equipment master. It is a
MILOIN.LISERN.; /	concatenation of Item number (ITNO) <15> + Serial number (SERN)
For health date of the con-	<20> with slash (/) as a separator. The position of each field is
For Individual Item: SINDIV.SAINNO	determined by its maximum length, specified in brackets. ITNO and SERN are trimmed if the maximum length is not consumed.
;/	SERIN are unimitied if the maximum length is not consumed.
, 1	Ex. ITEM0001/SERN001
	EX. IT EMOCO MOET WOOT
	For Individual Item:
	The field indicates a number that identifies an individual item.
@accountingEntity	
For Serialized Item:	For Individual Item:
MILOIN.LICONO CMNDIV.CCDIVI.; /	The field indicates the company and division.
ONINDIV.OODIVI., /	If Master AE is enabled for the CustomerPartyMaster in the BOD
For Individual Item:	Processor, the attribute will only display the company (e.g., '770').
SINDIV.SACONO	Otherwise, it will display company and division (e.g., '770_AAA').
SINDIV.SADIVI	
; /	
@variationID	For Serialized Item:
	The field indicates the sequence number that identifies the number of
	times the BOD has been published.
	For Individual Item:
	The field indicates the sequence number that identifies the number of
	times that this BOD has been published.
@lid	The field indicates the logical ID of the system.
ConfiguredAssetMaster/DisplayID	The held indicates the logical ib of the system.
For Serialized Item:	For Serialized Item:
MILOIN.LIITNO	The field indicates the primary keys for the equipment master. It is a
MILOIN.LISERN.; /	concatenation of Item number (ITNO) <15> + Serial number (SERN)
·	<20> with slash (/) as a separator. The position of each field is
For Individual Item:	determined by its maximum length, specified in brackets. ITNO and
SINDIV.SAINNO	SERN are trimmed if the maximum length is not consumed.
. 1	Ex. ITEM0001/SERN001
; /	EX. ITEMIOUOT/SERINOUT
	For Individual Item:
	The field indicates a number that identifies an individual item.
ConfiguredAssetMaster/LastModificationDateTime	
For Serialized Item:	For Serialized Item:
MILOIN.LILMTS; /	The field indicates when the most recent change to the equipment
For Individual Item:	master was made.
SINDIV.SALMTS; /	For Individual Item:
ONVENTO, 7	The field indicates when the most recent change to the individual item
	record was made.
ConfiguredAssetMaster/LastModificationPerson/IDs/ID	
For Serialized Item:	For Serialized Item:
MILOIN.LICHID; /	The field indicates the user ID associated with the most recent
- 1 P. 1 19	change to the equipment master.
For Individual Item:	Fan Individual Hans
SINDIV.SACHID; /	For Individual Item: The field indicates the user ID associated with the most recent
	change to the individual item record.
@accountingEntity	gs to ano manifestal norm rooted.
For Serialized Item:	The field indicates the company and division, displayed as
MILOIN.LICONO	CONO_DIVI.
CMNDIV.CCDIVI.; /	
For Individual Itom:	
For Individual Item: SINDIV.SACONO	
SINDIV.SACONO SINDIV.SADIVI.; /	
ConfiguredAssetMaster/DocumentDateTime	
For Serialized Item:	For Serialized Item:
MILOIN.LIRGDT	The field indicates when the equipment master was created. It is a
MILOIN.LIRGTM.; /	concatenation of RGDT and RGTM.
E 1 8 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	F 1 P 1 P 1 P 1 P 1 P 1 P 1 P 1 P 1 P 1
For Individual Item: SINDIV.RGDT	For Individual Item: The field indicates when the individual item record was created. It is a
SINDIV.RGDT SINDIV.RGTM.; /	concatenation of RGDT and RGTM.
	COCOLORIGION OF TOOL FAIR TO THE

ConfiguredAssetMaster/Description
For Serialized Item:

Infor May 26, 2023 99

ConfiguredAssetMaster

For Serialized Item:

: MMS240MI/GetBasic The field indicates the description for the equipment.

For Individual Item: For Individual Item:

SINDIV.SAMODE The field indicates the description of the Individual item number.

; SOS100MI/GetIndividual

ConfiguredAssetMaster/Note

For Serialized Item: For Serialized Item:

MILOIN.LITXID The field indicates the text or note associated with the equipment. ; MMS240MI/GetBasic

@noteID

For Serialized Item: For Serialized Item:

MILOIN.LITXID The field indicates the noteID.

; MMS240MI/GetBasic

ConfiguredAssetMaster/Status/Code

For Serialized Item: For Serialized Item:

MILOIN.LISTAT The field indicates the status of the equipment. : MMS240MI/GetBasic

Set to "Pending" if status is 05, 10, 15, 40, or 89. For Individual Item: Set to "Open" if status is 20, 30, 50, 85, or 99.

Set to "Closed" if status is 80. SINDIV.SAISTS Set to "Deleted" if status is 90. ; SOS100MI/GetIndividual

For Individual Item:

The field indicates the status.

Set to "Pending" if status is 01. Set to "Open" if status is 10. Set to "InStore" if status is 11. Set to "InRepair" if status is 20.

Set to "ToBeRepaired" if status is 21,22,23 or 24.

Set to "InTransit" if status is 30. Set to "Withdrawn" if status is 40. Set to "Installed" if status is 50. Set to "Purchased" if status is 70. Set to "Deleted" if status is 90

ConfiguredAssetMaster/Name

For Individual Item: For Individual Item:

SINDIV.SAMODC The field indicates the name of the Individual item number.

SOS100MI/GetIndividual ConfiguredAssetMaster/CustomerParty/PartyIDs/ID

For Serialized Item: For Serialized Item:

MILOIN.LICUNO The field indicates the customer number. ; MMS240MI/GetBasic

For Individual Item:

For Individual Item: The field indicates the a unique ID for each customer. SINDIV.SACUPL

; SOS100MI/GetIndividual @accountingEntity

For Serialized Item: The field indicates the company and division, displayed as

MILOIN.LICONO CONO DIVI.

For Individual Item: SINDIV.SACONO SINDIV.SADIVI.; /

CMNDIV.CCDIVI.; /

ConfiguredAssetMaster/ItemInstance/ItemID/ID

For Serialized Item: For Serialized Item:

MILOIN.LIITNO; / The field indicates the item number for the equipment.

For Individual Item: For Individual Item:

SINDIV.SAITNO The field indicates the item number.

; SOS100MI/GetIndividual @accountingEntity

For Serialized Item: The field indicates the company and division, displayed as

MILOIN.LICONO CONO DIVI. CMNDIV.CCDIVI.; /

For Individual Item: SINDIV.SACONO SINDIV.SADIVI.; /

ConfiguredAssetMaster/ItemInstance/Description

For Serialized Item: For Serialized Item:

MITMAS.MMITDS The field indicates the item description for the equipment. ; MMS200MI/Get

ConfiguredAssetMaster/ItemInstance/SerializedLot/Lot/LotIDs/ID

For Serialized Item:

ConfiguredAssetMaster	
MILOIN.LISERN	For Serialized Item:
;/	The field indicates the unique serial number of each item.
For Individual Item:	For Individual Item:
SINDIV.SABANO ; SOS100MI/GetIndividual	The field indicates the lot number.
@accountingEntity	
SINDIV.SACONO	The field indicates the company and division, displayed as
SINDIV.SADIVI.; /	CONO_DIVI.
ConfiguredAssetMaster/ItemInstance/SerializedLot/Lot/SerialNumber For Serialized Item:	For Serialized Item:
MILOIN.LISERN	The field indicates the unique serial number of each item.
; /	<u> </u>
ConfiguredAssetMaster/ItemInstance/SerializedLot/SerialNumber	5 0 1 11 111
For Serialized Item: MILOIN.LISERN	For Serialized Item: The field indicates the unique serial number of each item.
;/	The field indicates the unique solid hamber of each term.
F 1 8 11 18	For Individual Item:
For Individual Item: SINDIV.SASERI	The field indicates the serial number, chassis number, identification number or the like for an individual item.
; SOS100MI/GetIndividual	number of the like for all individual item.
ConfiguredAssetMaster/PurchaseOrderReference/DocumentID/ID	
For Individual Item:	For Individual Item:
SINDIV.SAPUNO ; SOS100MI/GetIndividual	The field indicates the Purchase order number.
@accountingEntity	
For Individual Item:	For Individual Item:
SINDIV.SACONO SINDIV.SADIVI. /	The field indicates the company and division, displayed as
SINDIV.SADIVI.; /	CONO DIVI.
ConfiguredAssetMaster/PurchaseOrderReference/LineNumber For Individual Item:	For Individual Item:
SINDIV.SAPNLI	The field indicates the Purchase order line number.
; SOS100MI/GetIndividual	
ConfiguredAssetMaster/DocumentReference	
@type For Individual Item:	For Individual Item:
SINDIV.SARORC	The field indicates the reference order category (RORC).
; SOS100MI/GetIndividual	0.11 D. 1.12 0.1 17 1
	Set to "Production Order" if RORC = 1. Set to "Purchase Order" if RORC = 2.
	Set to "Sales Order" if RORC = 3.
	Set to "Requisition Order" if RORC = 4.
	Set to "Distribution Order" if RORC = 5. Set to "Work Order" if RORC = 6.
	Set to "Service Order" if RORC = 7.
	Set to "Project Order" if RORC = 8.
	Set to "Claim Order" if RORC = 9.
ConfiguredAssetMaster/DocumentReference/DocumentID/ID	Fau la dividual Haus
For Individual Item: SINDIV.SARORN	For Individual Item: The field indicates the reference order number.
; SOS100MI/GetIndividual	The field indicates the reference state number.
@accountingEntity	F 1 831 18
For Individual Item: SINDIV.SACONO	For Individual Item: The field indicates the company and division, displayed as
SINDIV.SADIVI.; /	CONO DIVI.
ConfiguredAssetMaster/DocumentReference/LineNumber	
For Individual Item:	For Individual Item:
SINDIV.SARORL ; SOS100MI/GetIndividual	The field indicates the reference order line number.
ConfiguredAssetMaster/DocumentReference/SubLineNumber	
For Individual Item:	For Individual Item:
SINDIV.SARORX	The field indicates the reference order line suffix.
; SOS100MI /GetIndividual	
ConfiguredAssetMaster/AcquisitionDateTime For Individual Item:	For Individual Item:
SINDIV.SAREDA	The field indicates the dates for the delivery to inventory for the
; SOS100MI/GetIndividual	individual lot.
ConfiguredAssetMaster/Classification/Codes/Code	4) M = 6 () = 0 ()
1) MILOMA.LMMFSN EQINFOMI/GetEquipment	Manufacturer Serial Number The field indicates the serial number assigned by the supplier, which
EQINI Olvii/GetEquipment	can either be the facility's own production center or information
2) MILOMA.LMMFDT	received from the supplier.
EQINFOMI/GetEquipment	Set attribute listID to "Manufacturer Serial Number".
3) SINDIV.SAINDA	2) Manufacturing Date
SOS100MI/GetIndividual	The field indicates, per lot/serial number, the date the identity was
Infor May 26, 202	

Infor May 26, 2023 101

ConfiguredAssetMaster 4 6 1

manufactured. The information can be used as basis for calculating 4) SINDIV SAGDT1 the expiration date. SOS100MI/GetIndividual Set attribute listID to "Manufacturing Date". 5) SINDIV.SAGDT2 3) Installation Date SOS100MI/GetIndividual The field indicates the date when equipment was installed at the customer site. 6) SINDIV.SAGDT3 Set attributes listID to "Installation Date". SOS100MI/GetIndividual .; / 4) Warranty date sales The field indicates the date on which the sales warranty of an individual item expires. Set attributes listID to "Sales Warranty Expire Date". 5) Warranty date supplier The field indicates the date on which the supplier warranty of an individual item expires. Set attributes listID to "Supplier Warranty Expire Date". 6) Workshop warranty expire date The field indicates the date the workshop warranty for an individual Set attribute listID to "Workshop Warranty Expire Date" @sequence The field indicates the sequence number for the ordering of elements a document. @listID 1) Set to "Manufacturer Serial Number" if Classification/Codes/Code = MFSN. 2) Set to "Manufacturing Date" if Classification/Codes/Code = MFDT. Set to "Installation Date" if Classification/Codes/Code = INDA.
 Set to "Sales Warranty Expire Date" if Classification/Codes/Code = GDT1. 5) Set to "Supplier Warranty Expire Date" if Classification/Codes/ Code = GDT2. 6) Set to "Workshop Warranty Expire Date" if Classification/Codes/ Code = GDT3 ConfiguredAssetMaster/ParentConfiguredAsset/IDs/ID For Individual Item: For Individual Item: SINDIV.SAMINO The field indicates the main individual item. ; SOS100MI/GetIndividual @accountingEntity For Individual Item: For Individual Item: SINDIV.SACONO The field indicates the company and division, displayed as SINDIV.SADIVI.; CONO DIVI. ConfiguredAssetMaster/UserArea For Individual Item: For Individual Item: 1) SINDIV.SACFE1 1) The field indicates the User-defined field 1 - individual item (CFE1).

SOS100MI/GetIndividual

2) SINDIV.SACFE2 SOS100MI/GetIndividual

3) SINDIV.SACFE3 SOS100MI/GetIndividual

4) SINDIV.SACFE4 SOS100MI/GetIndividual

5) SINDIV.SACFE5 SOS100MI/GetIndividual

6) SINDIV.SACFE6 SOS100MI/GetIndividual

7) SINDIV.SACFE7 SOS100MI/GetIndividual

8) SINDIV.SACFE8 SOS100MI/GetIndividual

9) SINDIV.SACFE9 SOS100MI/GetIndividual

10) SINDIV.SACFE0] SOS100MI/GetIndividual Set attribute name to "UserDefinedField1".

2) The field indicates the User-defined field 2 - individual item (CFE2). Set attribute name to "UserDefinedField2".

3) The field indicates the User-defined field 3 - individual item (CFE3). Set attribute name to "UserDefinedField3".

4) The field indicates the User-defined field 4 - individual item (CFE4). Set attribute name to "UserDefinedField4".

5) The field indicates the User-defined field 5 - individual item (CFE5). Set attribute name to "UserDefinedField5".

6) The field indicates the User-defined field 6 - individual item (CFE6). Set attribute name to "UserDefinedField6".

7) The field indicates the User-defined field 7 - individual item (CFE7). Set attribute name to "UserDefinedField7".

8) The field indicates the User-defined field 8 - individual item (CFE8). Set attribute name to "UserDefinedField8".

9) The field indicates the User-defined field 9 - individual item (CFE9). Set attribute name to "UserDefinedField9".

10) The field indicates the User-defined field 0 - individual item (CFE0). Set attribute name to "UserDefinedField0".

ConfiguredAssetMaster

11) SINDIV.SACFEA SÓS100MI/GetIndividual 11) The field indicates the User-defined field A - individual item (CFEA). 12) SINDIV.SACFEB Set attribute name to "UserDefinedFieldA". SÓS100MI/GetIndividual 12) The field indicates the User-defined field B - individual item Set attribute name to "UserDefinedFieldB".

ConfiguredAssetMaster/AssetTypeCode

For Serialized Item: MITMAS.MMINDI ; MMS200MI/Get

For Individual Item: SINDIV.SAINTY

; SOS100MI/GetIndividual

ConfiguredAssetMaster/DepartmentCode

For Serialized Item: MILOIN.LIPLGR ; MMS240MI/GetBasic

For Individual Item: SINDIV.SAINGR

; SOS100MI/GetIndividual

ConfiguredAssetMaster/SiteLocation/ID For Individual Item:

SINDIV.SALOCS ; SOS100MI/GetIndividual

@accountingEntity

For Individual Item:

SINDIV.SACONO

SINDIV.SADIVI.; /

ConfiguredAssetMaster/SiteLocation/Description

For Individual Item: SINDIV.SAAREA

; SOS100MI/GetIndividual

ConfiguredAssetMaster/ServiceAreaCode For Individual Item:

SINDIV.SAFCTN

; SOS100MI/GetIndividual

For Serialized Item:

The field indicates the asset type code for the equipment.

For Individual Item:

The field indicates the asset type code (INTY).

Set to "Normal" if AssetTypeCode = 0. Set to "Short-term rental" if AssetTypeCode = 3. Set to "Not used" if AssetTypeCode = 6. Set to "Long-term rental" if AssetTypeCode = 7. Set to "Stocked" if AssetTypeCode = 8. Set to "Temporary" if AssetTypeCode = 9.

For Serialized Item:

The field indicates the planning group/work center for the equipment.

For Individual Item:

The field indicates the individual item group.

For Individual Item:

The field indicates the location.

For Individual Item:

The field indicates the company and division, displayed as

CONO DIVI.

For Individual Item:

The field indicates the location description.

For Individual Item:

The field indicates the service function area.

ContactMaster

ContactMaster/IDs/ID	
CCUCON.CCCNPE ;/	The field indicates the contact.
@accountingEntity CCUCON.CCCONO CMNDIV.CCDIVI.; / @variationID	The field indicates the company and division, displayed as CONO_DIVI.
	This field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	This field indicates the logical ID of the system.
ContactMaster/LastModificationDateTime CCUCON.CCLMTS; /	The field indicates the date and time the record was last modified.
ContactMaster/LastModificationPerson/IDs/ID CCUCON.CCCHID ; CRS618MI/Get @accountingEntity	The field indicates the identity of the person who last changed the record.
CCUCON.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
ContactMaster/DocumentDateTime CCUCON.CCRGDT CCUCON.CCRGTM .; CRS618MI/Get	The field indicates the entry date and time of the record.
ContactMaster/Description CCUCON.CCTX40 ; CRS618MI/Get	The field indicates the description.
ContactMaster/Status/Code CCUCON.CCSTAT	The field indicates the status of the contact.
; CRS618MI/Get	Set to 'Pending' if STAT = 00, 10. Set to 'Open' if STAT = 10. Set to 'Closed' if STAT = 90.
ContactMaster/Name CCUCON.CCTX50 ; CRS618MI/Get	The field indicates the name.
ContactMaster/Title CCUCON.CCTITL ; CRS618MI/Get	The field indicates the title.
ContactMaster/SalutationPreferredName CCUCON.CCSALU ; CRS618MI/Get	The field indicates the salutation.
ContactMaster/GivenName CCUCON.CCNAMF ; CRS618MI/Get	The field indicates the given name or first name.
ContactMaster/MiddleName CCUCON.CCNAMM ; CRS618MI /Get	The field indicates the middle name.
ContactMaster/FamilyName CCUCON.CCNAMS ; CRS618MI/Get	The field indicates the surname or family name.
ContactMaster/SuffixName CCUCON.CCNAMX ; CRS618MI/Get	The field indicates the suffix name. The suffix appears after a person's full name and provides additional information about the person, for example an educational degree.
ContactMaster/JobTitle CCUCON.CCJTIT ; CRS618MI/Get	The field indicates the position or designation of a person within an organization.
ContactMaster/DepartmentName CCUCON.CCDEPT ; CRS618MI/Get	The field indicates the department.
ContactMaster/LanguageCode CCUCON.CCLHCD ; CRS618MI/Get	The field indicates the language.
ContactMaster/CommunicationDetail @preferredIndicator	Set to 'false'.
ContactMaster/CommunicationDetail/ChannelCode	Set to 'Phone' if Telephone number 1 and Telephone number 2. Set to 'EMail' if E-mail address.
@listID	Out to Lividii ii L-maii addross.

ContactMaster

Contactiviastei	
@lia4D	Set to 'Office' if Telephone number 1, Telephone number 2 or E-mail address.
@listID	Set to 'Communication Use Codes'.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2 .; CRS618MI/Get	The field indicates the telephone number.
ContactMaster/CommunicationDetail/Address	
@type	Set to 'text'.
ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1 CCUCON.CCCUA1 CCUCON.CCCUA1 CCUCON.CCCUA1 ;; CRS618MI/Get	The field indicates the address line.
@sequence	The field indicates the address line sequence.
ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN ; CRS618MI/Get	The field indicates the city.
ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR ; CRS618MI/Get @listID	nCode The field indicates an area, province or state within a country.
(misub	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD ; CRS618MI/Get @/listID	The field indicates the country code.
	Set to 'Countries'.
ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO ; CRS618MI/Get	The field indicates the postal code.
ContactMaster/CommunicationDetail/URI CCUCON.CCEMAL ; CRS618MI/Get	The field indicates the e-mail address.
ContactMaster/CommunicationDetail/DoNotEMailIndicator	Set to 'false' if ChannelCode = 'EMail'. Otherwise, set to 'true'.
ContactMaster/EmployerReference	Get to Taise ii Chamileloude - Liviaii . Otherwise, set to true .
@type CCUCON.CCERTP ; CRS618MI/Get	The employer reference type (ERTP) indicates if it is a customer, supplier, or 'other'.
	Set to 'Other' if ERTP = 0. Set to 'Customer' if ERTP = 1. Set to 'Supplier' if ERTP = 2.
ContactMaster/EmployerReference/DocumentID/ID CCUCON.CCEMRE ; CRS618MI/Get	The field indicates the customer or supplier who employs the contact.
@accountingEntity CCUCON.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
ContactMaster/UserArea	The field indicates the BODID from the sending application. Set attribute name to 'ProcessBODID'.
ContactMaster/GenderCode CCUCON.CCGEND ; CRS618MI/Get	The field indicates the gender (GEND).
	Set to 'NotSpecified' if GEND = 0.

Contract

JNO, is trimmed if it does not consume the maximum length. or Customer Order Contract Blanket Agreement: the field indicates the agreement number connected to a customer. The same of a customer number (CUNO) <10> + blanket
or Purchase Order Contract Blanket Agreement: the field indicates the agreement number connected to a supplier. It is a concatenation of supplier number (SUNO) <10> + agreement number (AGNB) <7> without separator. The position of each field is stermined by its maximum length, specified in brackets. If the data less not consume the maximum length, the rest is filled up with laces. This applies to all fields that are part of the document ID cept for the last one. The last field in the concatenation, in this case JNO, is trimmed if it does not consume the maximum length. For Customer Order Contract Blanket Agreement: The field indicates the agreement number connected to a customer. For a concatenation of customer number (CUNO) <10> + blanket
ne field indicates the agreement number connected to a supplier. It is a concatenation of supplier number (SUNO) <10> + agreement number (AGNB) <7> without separator. The position of each field is stermined by its maximum length, specified in brackets. If the data less not consume the maximum length, the rest is filled up with laces. This applies to all fields that are part of the document ID cept for the last one. The last field in the concatenation, in this case JNO, is trimmed if it does not consume the maximum length. For Customer Order Contract Blanket Agreement: Fine field indicates the agreement number connected to a customer. It is a concatenation of customer number (CUNO) <10> + blanket
ne field indicates the agreement number connected to a customer. s a concatenation of customer number (CUNO) <10> + blanket
preement number (AGNO) <7> + start date (STDT) <8) without parator. The position of each field is determined by its maximum ngth, specified in brackets. If the data does not consume the aximum length, the rest is filled up with spaces. This applies to all lids that are part of the document ID except for the last one. The st field in the concatenation, in this case CUNO, is trimmed if it does to consume the maximum length.
ne field indicates the company and division, displayed as DNO_DIVI.
ne field indicates the sequence number that identifies the number of nes that the BOD has been published.
or Purchase Order Contract Blanket Agreement: ne field indicates the logical ID of the system.
or Customer Order Contract Blanket Agreement: ne field indicates the logical ID.
or Purchase Order Contract Blanket Agreement: the field indicates the purchase order agreement number.
or Customer Order Contract Blanket Agreement: ne field indicates the doucment ID.
or Customer Order Contract Blanket Agreement: ne field indicates the last modification date and time.
or Customer Order Contract Blanket Agreement: ne field indicates the user who last changed the data.
or Customer Order Contract Blanket Agreement: ne field indicates the company and division, displayed as DNO DIVI.
or Purchase Order Contract Blanket Agreement: ne field indicates the agreement date.
or Customer Order Contract Blanket Agreement: ne field indicates the blanket agreement date.
or Purchase Order Contract Blanket Agreement: ne field indicates the name of the agreement.
or Customer Order Contract Blanket Agreement: the field indicates the description of the blanket agreement.
or Customer Order Contract Blanket Agreement: the field indicates the language.
or Purchase Order Contract Blanket Agreement: the field indicates the status of the agreement.

Contract

Contract	
For Customer Order Contract Blanket Agreement: OAGRHE.UYAGST; OIS060MI/GetCustBlkAgr	Set to 'Draft' if status is less than 20. Set to 'Open' if status in 20, 30, 40 Set to 'Completed' if status is 80. Set to 'Deleted' if status is 90 or if record is deleted in PPS100.
	For Customer Order Contract Blanket Agreement: The field indicates the status of the blanket agreement. Set to 'Draft' if status is 10.
	Set to 'Open' if status is 20. Set to 'Completed' if status is 80. Set to 'Deleted' if OIS060 record is deleted.
Contract/ContractHeader/Status/TimePeriod/StartDateTime	
For Purchase Order Contract Blanket Agreement: MPAGRH.AHFVDT; PPS100MI/GetAgrHead	For Purchase Order Contract Blanket Agreement: The field indicates the start date of the agreement's validity.
For Customer Order Contract Blanket Agreement: OAGRHE.UYSTDT; OIS060MI/GetCustBlkAgr	For Customer Order Contract Blanket Agreement: The field indicates the start date of the agreement's validity.
Contract/ContractHeader/Status/TimePeriod/EndDateTime	
For Purchase Order Contract Blanket Agreement: MPAGRH.AHUVDT; PPS100MI/GetAgrHead	For Purchase Order Contract Blanket Agreement: The field indicates the end date of the agreement's validity.
For Customer Order Contract Blanket Agreement: OAGRHE.UYLVDT; OIS060MI/GetCustBlkAgr	For Customer Order Contract Blanket Agreement: The field indicates the end date of the agreement's validity.
Contract/ContractHeader/CustomerParty/PartyIDs/ID For Customer Order Contract Blanket Agreement:	For Customer Order Contract Blanket Agreement: The field indicates the customer number.
OAGRHE.UYCUNO; OIS060MI/GetCustBlkAgr @accountingEntity	The field indicates the customer number.
	For Customer Order Contract Blanket Agreement:
	The field indicates the accounting entity. If CustomerPartyMaster is enabled in BOD Processor Master AE tab,
	this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Contract/ContractHeader/CustomerParty/Name For Customer Order Contract Blanket Agreement: OCUSMA.OKCUNM; CRS610MI/GetBasicData	For Customer Order Contract Blanket Agreement: The field indicates the customer name.
Contract/ContractHeader/CustomerParty/Location/Address	The field indicates the customer fiame.
@type	For Customer Order Contract Blanket Agreement:
	Set to 'text'
Contract/ContractHeader/CustomerParty/Location/Address/Attention	
For Customer Order Contract Blanket Agreement: OCUSMA.OKYREF; CRS610MI/GetBasicData	For Customer Order Contract Blanket Agreement: The field indicates the contact person.
Contract/ContractHeader/CustomerParty/Location/Address/Address	·
For Customer Order Contract Blanket Agreement: OCUSMA.OKCUA1 OKCUA2 OKCUA3	For Customer Order Contract Blanket Agreement: The field indicates the address line.
OKCUA4; CRS610MI/GetBasicData	
@sequence	For Customer Order Contract Blanket Agreement:
	The field indicates the address line sequence.
Contract/ContractHeader/CustomerParty/Location/Address/Cityl For Customer Order Contract Blanket Agreement: OCUSMA.OKTOWN; CRS610MI/GetBasicData	Name For Customer Order Contract Blanket Agreement: The field indicates the city name.
Contract/ContractHeader/CustomerParty/Location/Address/Cour	
For Customer Order Contract Blanket Agreement: OCUSMA.OKECAR; CRS610MI/GetBasicData @listID	For Customer Order Contract Blanket Agreement: The field indicates an area, province or state within a country.
	For Customer Order Contract Blanket Agreement:
	Set to 'Canadian Provinces' if the country is CA (Canada).
	Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
Contract/ContractHeader/CustomerParty/Location/Address/Cour	Set to "SubDivisions" if no country is specified.
For Customer Order Contract Blanket Agreement: OCUSMA.OKCSCD; CRS610MI/GetBasicData @listID	For Customer Order Contract Blanket Agreement: The field indicates the country code.
	For Customer Order Contract Blanket Agreement: Set to 'Countries'.
Contract/ContractHeader/CustomerParty/Location/Address/Post	alCode
For Customer Order Contract Blanket Agreement: OCUSMA.OKPONO; CRS610MI/GetBasicData	For Customer Order Contract Blanket Agreement: The field indicates the postal code.
Contract/ContractHeader/ShipToParty/Party/Ds/ID For Customer Order Contract Blanket Agreement:	

Contract

Goritiaet	
OAGRHE.UYCUNO UYADID; OIS060MI/GetCustBlkAgr	For Customer Order Contract Blanket Agreement: The field indicates the delivery customer. IF address number (ADID) is not blank, publish CUNO + ADID. It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the delivery customer code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.
@accountingEntity	For Customer Order Contract Blanket Agreement: The field indicates the accounting entity. If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Contract/ContractHeader/ShipToParty/Name For Customer Order Contract Blanket Agreement: OCUSMA.OKCUNM; CRS610MI/GetBasicData or GetAddress	For Customer Order Contract Blanket Agreement: The field indicates the customer name.
Contract/ContractHeader/ShipToParty/Location/Address @type	For Customer Order Contract Blanket Agreement: Set to 'text'
Contract/ContractHeader/ShipToParty/Location/Address/AttentionOff For Customer Order Contract Blanket Agreement: OCUSMA.OKYREF; CRS610MI/GetBasicData or GetAddress	Name For Customer Order Contract Blanket Agreement: The field indicates the contact person.
Contract/ContractHeader/ShipToParty/Location/Address/AddressLine For Customer Order Contract Blanket Agreement: OCUSMA.OKCUA1 OKCUA2 OKCUA3 OKCUA4; CRS610MI/GetBasicData or GetAddress @sequence	For Customer Order Contract Blanket Agreement: The field indicates the address line.
	For Customer Order Contract Blanket Agreement: The field indicates the address line sequence.
Contract/ContractHeader/ShipToParty/Location/Address/CityName For Customer Order Contract Blanket Agreement: OCUSMA.OKTOWN; CRS610MI/GetBasicData or GetAddress	For Customer Order Contract Blanket Agreement: The field indicates the city name.
Contract/ContractHeader/ShipToParty/Location/Address/CountrySubsection For Customer Order Contract Blanket Agreement:	DivisionCode For Customer Order Contract Blanket Agreement: The field indicates an area, province or state within a country.
@listID	For Customer Order Contract Blanket Agreement: Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
Contract/ContractHeader/ShipToParty/Location/Address/CountryCod For Customer Order Contract Blanket Agreement: OCUSMA.OKCSCD; CRS610MI/GetBasicData or GetAddress @listID	e For Customer Order Contract Blanket Agreement: The field indicates the country code.
October 4/October 4/10 and an incident To Douber 1/1 and the miles of Douber 10 and	For Customer Order Contract Blanket Agreement: Set to 'Countries'.
Contract/ContractHeader/ShipToParty/Location/Address/PostalCode For Customer Order Contract Blanket Agreement: OCUSMA.OKPONO; CRS610MI/GetBasicData or GetAddress	For Customer Order Contract Blanket Agreement: The field indicates the postal code.
Contract/ContractHeader/SupplierParty/PartyIDs/ID For Purchase Order Contract Blanket Agreement: CIDMAS.IDSUNO; PPS100MI/GetAgrHead @accountingEntity	For Purchase Order Contract Blanket Agreement: The field indicates the supplier number.
	For Purchase Order Contract Blanket Agreement: The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Contract/ContractHeader/SupplierParty/Name For Purchase Order Contract Blanket Agreement: CIDMAS.IDSUNM; CRS620MI/GetBasicData	For Purchase Order Contract Blanket Agreement: The field indicates the supplier name.
Infor May 26, 202	• • • • • • • • • • • • • • • • • • • •

Contract

Contract/ContractHeader/SupplierParty/Location		
@type For Purchase Order Contract Blanket Agreement: CIDADR	For Purchase Order Contract Blanket Agreement: The field indicates the type of address to use.	
.SAADTE; CRS620MI/LstAddresses	Set to 'Postal' if Address Type is 01. Set to 'Street' if Address Type is 02. Set to 'Pickup' if Address Type is 03. Set to 'Origin' if Address Type is 04. Set to 'Final' if Address Type is 05. Set to 'Bank' if Address Type is 10.	
Contract/ContractHeader/SupplierParty/Location/Name For Purchase Order Contract Blanket Agreement: CIDADR .SASUNM; CRS620MI/LstAddresses	For Purchase Order Contract Blanket Agreement: The field indicates the supplier name.	
Contract/ContractHeader/SupplierParty/Location/Address @type	For Purchase Order Contract Blanket Agreement:	
	Set to 'text'.	
Contract/ContractHeader/SupplierParty/Location/Address/AddressLin For Purchase Order Contract Blanket Agreement: CIDADR .SAADR1, SAADR2, SAADR3, SAADR3, SAADR4; CRS620MI/LstAddresses @sequence	ne For Purchase Order Contract Blanket Agreement: The field indicates the address line.	
	For Purchase Order Contract Blanket Agreement: The field indicates the address line sequence.	
Contract/ContractHeader/SupplierParty/Location/Address/CityName For Purchase Order Contract Blanket Agreement: CIDADR .SATOWN; CRS620MI/LstAddresses	For Purchase Order Contract Blanket Agreement: The field indicates the city name.	
Contract/ContractHeader/SupplierParty/Location/Address/Countr For Purchase Order Contract Blanket Agreement: CIDADR .SAECAR; CRS620MI/LstAddresses	bDivisionCode For Purchase Order Contract Blanket Agreement: The field indicates an area, province or state within a country.	
@listID	For Purchase Order Contract Blanket Agreement: Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>	
Contract/ContractHeader/SupplierParty/Location/Address/CountryCo For Purchase Order Contract Blanket Agreement: CIDADR .SACSCD; CRS620MI/LstAddresses @listID		
(Wisub	For Purchase Order Contract Blanket Agreement: Set to 'Countries'.	
Contract/ContractHeader/SupplierParty/Location/Address/PostalCode For Purchase Order Contract Blanket Agreement: CIDADR .SAPONO; CRS620MI/LstAddresses	For Purchase Order Contract Blanket Agreement: The field indicates the postal code.	
Contract/ContractHeader/UserArea For Purchase Order Contract Blanket Agreement: 1) MPAGRH.AHAGPT PPS100MI.GetAgrHead	For Purchase Order Contract Blanket Agreement: 1) Agreement priority The field indicates the priority of the agreement (AGPT). Set attribute name to 'AgreementPriority'.	
2) MPAGRH.AHCUCD PPS100MI.GetAgrHead.; /	Currency The field indicates the currency of the agreement (CUCD). Set attribute name to 'Currency'.	
Contract/ContractSchedule/EffectiveTimePeriod/StartDateTime For Purchase Order Contract Blanket Agreement: MPAGRL.AIFVDT; PPS100MI/LstAgrLine	The field indicates the date as from when the agreement line is valid.	
For Customer Order Contract Blanket Agreement: OAGRLN.UWSTDT; OIS060MI/LstCustBlkAgrLn		
Contract/ContractSchedule/EffectiveTimePeriod/EndDateTime For Purchase Order Contract Blanket Agreement: MPAGRL.AIUVDT; PPS100MI/LstAgrLine	The field indicates the last date the record is valid.	
For Customer Order Contract Blanket Agreement:		

Contract OAGRLN.UWFDAT: OIS060MI/LstCustBlkAarLn Contract/ContractSchedule/ContractPrice/Item/ItemID/ID For Purchase Order Contract Blanket Agreement: For Purchase Order Contract Blanket Agreement: MPAGRL.AIOBV1; PPS100MI/LstAgrLine The field indicates item number. For Customer Order Contract Blanket Agreement: For Customer Order Contract Blanket Agreement: OAGRLN.UWOBV1; OIS060MI/LstCustBlkAgrLn The field indicates @accountingEntity The field indicates the company and division, displayed as CONO DIVI Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/MinimumQuantity For Purchase Order Contract Blanket Agreement: The field indicates a limit for quantity dependent prices and discounts. MPAGPR.AJFRQT; PPS100MI/LstStgPrice For Customer Order Contract Blanket Agreement: OAGRPR.OLQTYL; OIS060MI/LstAgrLnPrice @unitCode For Purchase Order Contract Blanket Agreement: The field indicates the unit of mreasure. MPAGRL.AIPPUN; PPS100MI/LstAgrLine For Customer Order Contract Blanket Agreement: OAGRLN.UWSPUN; OIS060MI/LstCustBlkAgrLn Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/UnitPrice/Amount For Purchase Order Contract Blanket Agreement: The field indicates the agreed price when the limit value is reached MPAGPR.AJPUPR; PPS100MI/LstStgPrice For Customer Order Contract Blanket Agreement: OAGRPR.OLAGPR; OIS060MI/LstAgrLnPrice @currencyID For Purchase Order Contract Blanket Agreement: The field indicates the currency. MPAGRH.AHCUCD; PPS100MI/GetAgrHead For Customer Order Contract Blanket Agreement: OAGRLN.UWCUCD; OIS060MI/LstCustBlkAgrLn Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/UnitPrice/PerQuantity For Customer Order Contract Blanket Agreement: For Customer Order Contract Blanket Agreement: OAGRPR.OLSACD; OIS060MI/LstAgrLnPrice The field indiccates the quantity to which the sales price applies. @unitCode For Customer Order Contract Blanket Agreement: For Customer Order Contract Blanket Agreement: The field indicates the unit of mreasure. OAGRLN.UWSPUN; OIS060MI/LstCustBlkAgrLn Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/DiscountPercent For Purchase Order Contract Blanket Agreement: The field indicates the discount as a percentage. MPAGPR.AJDIP3; PPS100MI/LstStgPrice For Customer Order Contract Blanket Agreement: OAGRPR.OLDIPC; OIS060MI/LstAgrLnPrice Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/DiscountAmount For Customer Order Contract Blanket Agreement: For Customer Order Contract Blanket Agreement: OAGRPR.OLDIPR; OIS060MI/LstAgrLnPrice The field indicates the discount that the customer is to receive. @currencyID For Customer Order Contract Blanket Agreement: For Customer Order Contract Blanket Agreement: OAGRLN.UWCUCD; OIS060MI/LstCustBlkAgrLn The field indicates the currency. Contract/ContractSchedule/Status/Code For Purchase Order Contract Blanket Agreement: For Purchase Order Contract Blanket Agreement: MPAGRL.AISAGL; PPS100MI/LstAgrLine The field indicates the status of the agreement. Set to 'Open' if status in 20. For Customer Order Contract Blanket Agreement: Set to 'Completed' if status is 80. OAGRLN.UWAGST; OIS060MI/LstCustBlkAgrLn Set to 'Deleted' if status is 90. For Customer Order Contract Blanket Agreement: The field indicates the status of the blanket agreement. Set to 'Open' if status in 20. Set to 'Completed' if status is 80 Contract/ContractSchedule/AgreedQuantity For Purchase Order Contract Blanket Agreement: The field indicates the total agreed quantity of an agreement line.

MPAGRL.AIAGQT; PPS100MI/LstAgrLine

For Customer Order Contract Blanket Agreement: OAGRLN.UWAGQT; OIS060MI/LstCustBlkAgrLn

@unitCode For Purchase Order Contract Blanket Agreement: MPAGRL.AIPPUN; PPS100MI/LstAgrLine

For Customer Order Contract Blanket Agreement: OAGRLN.UWSPUN; OIS060MI/LstCustBlkAgrLn

The field indicates the unit of mreasure.

CreditTransfer/CreditTransferHeader/DocumentID/ID FPSUGH.P1PRPN + P1PYON, P1CNET; APS130MI/GetHead2	The field indicates the Payment proposal number (PRPN) and payment order number (PYON) that are key fields to M3 payment proposal. They are taken from Event together with M3 company and M3 division.
	PRPN is padded with zeros to lengh 10 and PYON is padded with zeros to length 5.
	Note 1: Some information retrieved in the CreditTransfer mapping depends on if the proposal is created for supplier payments in (APS130) or customer payments in (APS330). This is indicated via APS130Ml.GetHead2 and the output field 'Payment proposal type' (TPPR): - 0 = Supplier payments - 1 = Customer payments
	Note 2: The processing of the CreditTransfer BOD will be aborted in case of proposal for 'Corporate netting' (that is if field CNET = 1) as described in KB article 2174482.
@accountingEntity FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2	The field indicates the M3 BE Division where payment proposal belongs. M3 Division translated to accounting entity. = nounAE
@variationID ; -/-	The field indicates the Variation ID that is retrieved from the message manifest. Manifest element com:ionVariationId is used.
@lid ; -/-	The field indicates the Logical ID.
CreditTransfer/CreditTransferHeader/DisplayID FPSUGH.P1PRPN + P1PYON; APS130MI/GetHead2	The field indicates the Payment proposal number (PRPN) and payment order number (PYON).
	PRPN is padded with zeros to lengh 10 and PYON is padded with zeros to length 5.
CreditTransfer/CreditTransferHeader/DocumentDateTime FPSUGH.P1PRPD; APS130MI/GetHead2	The field indicates the Payment proposal date (PRPD) from the header.
CreditTransfer/CreditTransferHeader/Description CSYTAB.CTELET, CTDOCU; APS130MI/GetHead2	The field indicates the Electronic format (ELET) and if blank, Document format (DOCU) of the Payment method (PYME) of the proposal.
	Can be used as additional element in the detection setup for GEMS in case different formats/messages must be created for the same bank.
CreditTransfer/CreditTransferHeader/Status/Code FPSUGH.P1ACTO; APS130MI/GetHead2	Set to 'Open' for confirmed payment (action code 09) and copy of payment (action code 18). Set to 'Draft' for preliminary payment (action code 08).
CreditTransfer/CreditTransferHeader/AuthorizationID CBANAC.BCBKAG or	The field indicates the Bank agreement number (BKAG) of the company bank account.
XBRBAN.XCXAGN; APS130MI or	Exception if Country version (MNS100.CSVN) = BR (not used but left
APBR30MI/GetHead2 or GetHead	for future need): - Agreement number (XAGN) from APBR30MI.GetHead via same key as for APS130MI.GetHead2. Leading zeros added to length 13. No
CreditTransfer/CreditTransferHeader/BatchBookingIndicator CSYTAB.CTBBIN; APS130MI/GetHead2	output if no value retrieved. The field indicates the indicator for Batch booking (BBIN) as defined on the Payment method: - If Batch booking indicator (BBIN) = 0: Set to 'false' (default value). - If Batch booking indicator (BBIN) = 1: Set to 'true'. - If Batch booking indicator (BBIN) = 2: Set to 'true' if APS130MI.GetHead2.CUCD = APS130MI.GetHead2.BCUC, otherwise to 'false'
	Set internal grp indicator to 'true' when APS130MI.GetHead2.GRPP is equal to 1 or 2.
CreditTransfer/CreditTransferHeader/TotalTransactions	
; <i>-l</i> -	The field indicates the Number (counter) of occurrences of payment transaction (number of lines returned by transaction LstPayeeTotal3 with number of payments (NOPD) > 0) and amount to pay (CUAM) not 0.
CreditTransfer/CreditTransferHeader/InitiatingParty/PartyIDs/ID	The field indicates the ID's that are included as standard for the

CRS693MI/GetHead2

GetBasicData

@schemeName

-.-: -/-

@accountingEntity

FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2

CreditTransfer/CreditTransferHeader/InitiatingParty/PartyIDs/TaxID CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2

XRUDIV.CCXINN, CCXKPP

XMNDIV.CCCNPJ

CBANVA.BVBAVA.-; APS130MI

or

CRRU01MI

APBR30MI

CRS693MI/GetHeadAddress

GetDivisionRU

GetHead

GetBasicData

@schemeName

- . - : -/-

- ID 1: Customer number at financial institution (FICU) If the above value not exists: Company/divsion (CONO DIVI).

Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SEPA-CTMIX:

- ID 1: Value (BAVA) from CRS693 (*) for field (BVTP = 501).
 ID 2: Value (BAVA) from CRS693 (*) for field (BVTP = 502).
 ID 3: Value (BAVA) from CRS693 (*) for field (BVTP = 503). If none of the above fields are defined, standard value (FICU or

CONO DIVI) is included.

(*) Value (BAVA) from CRS693 is retrieved for the company's bank account using CRS693MI.GetBasicData with BKTP=01, BKID=APS130MI.GetHead2.BKID and BVTP as described above.

The field indicates the schemeNames used as standard:

- FICU with schemeName = 'BankPartyIdentification'
- CONO + DIVI without schemeName.

Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SEPA-CTMIX:

- ID 1: schemeName = 'CustomerNumber'.
- ID 2: schemeName = 'BankPartyIdentification'.
- ID 3: no schemeName.

The field indicates the Accounting entity (this is the translated M3 BE company and division).

The field indicates the TaxIDs included as standard with information from (MNS100):

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: Organization number 1 (CORG) of the company.
- TaxID 3: Organization number 2 (COR2) of the company.

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: Tax declaration number (VRNL) of the company.

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: CUC code (CBI identifier) (BAVA) of the company from CRS693MI.GetBasicData.BAVA for BKTP=01, BKID=APS130MI.GetHead2.BKID and BVTP=011.

Exception if Country version (MNS100.CSVN) = RU:

- TaxID 1: Payer INN (CRRU01.XIN2) without country code and if missing, VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: Payer KPP (CRRU01.XKP2) and if missing, Tax declaration number (VRNL) of the company.

Exception if Country version (MNS100.CSVN) = BR (not used but left for future need):

- TaxID 1: CNPJ/CPF (MNS100 - APBR30MI.GetHead.CNPJ) without country code.

The field indicates the schemeNames that are used as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = RU:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'TaxDeclarationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = BR (not used but left for future need): TaxID 1: schemeName 'TaxIdentificationNumber'.

CreditTransfer/CreditTransferHeader/InitiatingParty/Name

FPSUGH.P1CONM or P1COA1-P1COA4

XRUDIV.CCXFLN.-; APS130MI

CRRU01MI/GetHeadAddress

GetDivisionRU

The field indicates the Company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

Exception if Country version (MNS100.CSVN) = RU:

- Payer Name (CRRU01.XFLN) and if not existing, as standard (same as above).

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Name

FPSUGH.P1CONM or

P1COA1-P1COA4; APS130MI/GetHeadAddress

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address @type

-.-; -/-Set to 'text' if address information included.

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/AddressLine

FPSUGH.P1COA1-P1COA4; APS130MI/GetHeadAddress

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

@sequence -.-; -/-

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CityName

Set to sequence number of the address line: values 1-4.

FPSUGH.P1TOWN; APS130MI/GetHeadAddress

The field indicates the City name (TOWN) of company from (MNS100) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3)

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CountrySubDivisionCode

FPSUGH.P1ECAR; APS130MI/GetHeadAddress

The field indicates the Area/State code (ECAR) of company from (MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

@listID

-.-; -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/CountryCode

FPSUGH.P1CSCD; APS130MI/GetHeadAddress

The field indicates the Country code (CSCD) of company from

(MNS100)

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

Set to 'Countries'.

CreditTransfer/CreditTransferHeader/InitiatingParty/Location/Address/PostalCode

The field indicates the Postal code (PONO) of company from (MNS100) if available in M3 (also sent as part of AddressLine

@SequenceNumber = 3).

CreditTransfer/CreditTransferHeader/InitiatingParty/Contact/Name

CMNDIV.CCOREF; APS130MI/GetHeadAddress

FPSUGH.P1PONO; APS130MI/GetHeadAddress

The field indicates the Our reference (OREF) of the Division.

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/ID

FPSUGH.P1BKNO; APS130MI/GetHead2

The field indicates the Bank number (BKNO) of the company's bank.

@schemeName

@schemeName

-.-: -/-@accountingEntity Set to schemeName = 'BankPartyIdentification'.

FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2

The field indicates the Accounting entity (this is the translated M3 BE

company and division).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the VAT registration number (VRN2) of the company's bank (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

Set to schemeName = 'TaxIdentificationNumber'.

-.-; -/-CreditTransfer/CreditTransferHeader/ForwardingAgentParty/PartyIDs/BICID

CBANAC.BCSWBI or

CBANMA.BKSWIC .-; APS130MI or

CRS690MI/GetHead2 or

GetBasicData

The field indicates the Swift/BIC code (SWBI) of the company's bank account and if not existing, Swift code (SWIC) of the company's bank.

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Name

CBANMA.BKBKNM or BKBKA1-BKBKA4

XRUBAN.BKXFLN.-; CRS690MI

CRRU04MI/GetBasicData

GetBankRU

The field indicates the Bank name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

Exception if Country version (MNS100.CSVN) = RU:

- Payer's (Company's) Bank Name (CRRU04.XFLN (*)) and if not existing, as standard (same as above).

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04.

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Location name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank name (BKNM).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address

@type

Set to 'text' if address information included.

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/AddressLine

CBANMA.BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Bank address of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3

(BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence

Set to sequence number of the address line: values 1-4. -.-; -/-

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CityName

CBANMA.BKTOWN The field indicates the City name (TOWN) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine

@SequenceNumber = 3).

XRUBAN.BKXTWN.-; CRS690MI

@listID

-.-; -/-

CRRU04MI/GetBasicData

GetBankRU

Exception if Country version (MNS100.CSVN) = RU:

- Payer's (Company's) Bank Address = Town (CRRU04.XTWN (*)) and if not existing, as standard (same as above).

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CountrySubDivisionCode

CBANMA.BKECAR; CRS690MI/GetBasicData

The field indicates the Area/State code (ECAR) of company's bank

from (CRS690).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/CountryCode CBANMA.BKCSCD; CRS690MI/GetBasicData

The field indicates the Country code (CSCD) of company's bank from

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US

(CRS690)

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID Set to 'Countries' -.-; -/-

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/Location/Address/PostalCode

CBANMA.BKPONO; CRS690MI/GetBasicData

The field indicates the Postal code (PONO) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine

(CLSI+CLSN cut together) of the company's bank retrieved from the

bank account. If clearing system ID (CLSI) has not been defined, only

@SequenceNumber = 3).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/ClearingSystemMemberID The field indicates the Clearing system member identification

CBANAC.BCCLSI + BCCLSN

XRUBAN.BKXBIK .-; APS130MI

CRRU04MI/GetHead2

GetBankRU

clearing system number (CLSN) is used. Exception if Country version (MNS100.CSVN) = RU:

- BIK of Payer's bank (CRRU04.XBIK (*)) and if not existing, as

standard (same as above)

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04.

@schemeName

Set to schemaName = 'ClearingIdentificationNumber'. -.-; -/-

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/PartyIDs/ID

CBANAC.BCBBRN; APS130MI/GetHead2

The field indicates the Bank branch number (BBRN) of the company's

bank branch.

@schemeName

@accountingEntity

FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2

Set to schemeName = 'BankPartyIdentification'.

The field indicates the Accounting entity (this is the translated M3 BE

company and division).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/PartyIDs/BICID

CBANBR.BRSWIC; CRS691MI/GetBasicData

The field indicates the Swift code (SWIC) of the company's bank branch from (CRS691).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of company's bank based on on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank branch name (BKBM).

Alternative if generic translation not used: Bank branch name (BKBM).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Location name of company's bank branch based on on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address @type

Set to 'text' if address information included.

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/AddressLine

CBANBR.BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank address of company's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are usedCode E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4).

@sequence

-.-; -/-

Set to sequence number of the address line: values 1-4

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/CityName

CBANBR.BRTOWN; CRS691MI/GetBasicData

The field indicates the City name (TOWN) of company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/CountrySubDivisionCode

CBANBR.BRECAR; CRS691MI/GetBasicData

The field indicates the Area/State code (ECAR) of company's bank branch from (CRS691).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

@listID -.-; -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/CountryCode

CBANBR.BRCSCD; CRS691MI/GetBasicData

The field indicates the Country code (CSCD) of company's bank branch from (CRS691).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

Set to 'Countries'

CreditTransfer/CreditTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/PostalCode

CBANBR.BRPONO; CRS691MI/GetBasicData

The field indicates the Postal code (PONO) of the company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

CreditTransfer/CreditTransferPayment/ID

FPSUGH.P1PRPN + P1PYON; APS130MI/GetHead2

The field indicates the Payment proposal number (PRPN) and payment order number (PYON) followed by a sequence number for unique key for ID per payment date (format when maximum length

- Payment proposal number (PRPN) without leading zeros followed by '-'.
- Payment order number (PYON) without leading zeros followed by '-'.
- Sequence number added at the end of the ID without leading zeros.

@accountingEntity

FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2

Credit i alisiei	The field indicates the Accounting entity (this is the translated M3 BE company and division).
CreditTransfer/CreditTransferPayment/RequestedExecutionDateTime	· · · · · · · · · · · · · · · · · · ·
FPSUGD.P3PYDT; APS130MI	The field indicates the Payment date (PYDT), format YYYY-MM-DD.
CRS693MI	Exception if country code (after translation to ISO code) of the
APS130MI/LstInvByPayDate	company's bank is = CZ or SK: - If Payment method is defined with grouped payment = 0
GetBasicData	(APS130MI.GetHead2.GRPP) and
GetHead2	- Additional field (BVTP) = 610 in CRS693 for the company's bank account is set to "1" and
	- Electronic format (APS130MI.GetHead2.ELET) not = SEPA-CT or
	SEPA-CTMIX Set RequestedExecutionDateTime to payment proposal date
	(APS130MI.GetHead2.PRPD)
	If any of the above conditions are not met; process according to standard handling above (APS130MI.LstInvByPayDate.PYDT).
CSYTAB.CTPYTC; APS130MI/GetHead2	The field indicates the Type of payment and is set to depending on
	payment class: - Payment class 03-Bank transfer: Transfer code (PYTC) set on
	payment method, if blank set to 'TRF'.
	- Payment class 04-Draft: Set to 'TRF'.
CreditTransfer/CreditTransferPayment/DebtorParty/PartyIDs/ID CBANAC.BCFICU or FPSUGH.P1CONO + P1DIVI	The field indicates the ID's that are included for the Debtor party
or	(company):
CBANVA.BVBAVA; APS130MI	- ID 1: Customer number at financial institution (FICU). If the above value not exists: Company/divsion (CONO DIVI).
or	if the above value not exists. Company/division (CONO_DIVI).
CRS693MI/GetHead2	Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SEPA-CTMIX:
or	- ID 1: Value (BAVA) from CRS693 (*) for field (BVTP = 501).
GetBasicData	- ID 2: Value (BAVA) from CRS693 (*) for field (BVTP = 502).
	 ID 3: Value (BAVA) from CRS693 (*) for field (BVTP = 503). If none of the above fields are defined, standard value (FICU or
	CONO_DIVI) is included.
	(*) Value (BAVA) from CRS693 is retrieved for the company's bank
	account using CRS693MI.GetBasicData with BKTP=01,
@schemeName	BKID=APS130MI.GetHead2.BKID and BVTP as described above.
; -/-	The field indicates the schemeNames used as standard:
	FICU with schemeName = 'BankPartyIdentification'CONO + DIVI without schemeName.
	Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SEPA-CTMIX:
	- ID 1: schemeName = 'CustomerNumber'.
	- ID 2: schemeName = 'BankPartyIdentification'.
@accountingEntity	- ID 3: no schemeName.
FPSUGH.P1CONO + P1DIVI; APS130MI/GetHead2	The field indicates the Accounting entity (this is the translated M3 BE
CreditTransfer/CreditTransferPayment/DebtorParty/PartyIDs/TaxID	company and division).
CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2	The field indicates the TaxIDs included as standard with information
or XRUDIV.CCXINN, CCXKPP	from (MNS100): - TaxID 1: VAT registration number (VRN2) of the company (Note:
or	Country code (ISO country code from (CRS045) already added as
XMNDIV.CCCNPJ or	prefix if applicable) TaxID 2: Organization number 1 (CORG) of the company.
CBANVA.BVBAVA; APS130MI	- TaxID 2: Organization number 1 (CORG) of the company TaxID 3: Organization number 2 (COR2) of the company.
or	Execution if Country version (MNS100 CSV/N) = ED:
CRRU01MI	Exception if Country version (MNS100.CSVN) = FR: - TaxID 1: VAT registration number (VRN2) of the company (Note:
or	Country code (ISO country code from (CRS045) already added as
APBR30MI or	prefix if applicable) TaxID 2: Tax declaration number (VRNL) of the company.
CRS693MI/GetHeadAddress	, , , , , , , , , , , , , , , , , , ,
or	Exception if Country version (MNS100.CSVN) = IT: - TaxID 1: VAT registration number (VRN2) of the company (Note:
GetDivisionRU	Country code (ISO country code from (CRS045) already added as
or GetHead	prefix if applicable) TaxID 2: CUC code (CBI identifier) (BAVA) of the company from
or	CRS693MI.GetBasicData.BAVA for BKTP=01,
GetBasicData	BKID=APS130MI.GetHead2.BKID and BVTP=011.
	Exception if Country version (MNS100.CSVN) = RU:

@schemeName

-.-: -/-

- TaxID 1: Payer INN (CRRU01.XIN2) without country code and if missing, VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

- TaxID 2: Payer KPP (CRRU01.XKP2) and if missing, Tax declaration number (VRNL) of the company

Exception if Country version (MNS100.CSVN) = BR (not used but left for future need)

- TaxID 1: CNPJ/CPF (MNS100 - APBR30MI.GetHead.CNPJ) without country code.

The field indicates the schemeNames that are used as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
 TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = RU:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'TaxDeclarationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = BR (not used but left for future need):

TaxID 1: schemeName 'TaxIdentificationNumber'

CreditTransfer/CreditTransferPayment/DebtorParty/Name

FPSUGH.P1CONM or P1COA1-P1COA4

XRUDIV.CCXFLN.-; APS130MI

CRRU01MI/GetHeadAddress

GetDivisionRU

The field indicates the Company name based the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

Exception if Country version (MNS100.CSVN) = RU:

- Payer Name (CRRU01.XFLN) and if not existing, as standard (same as above).

CreditTransfer/CreditTransferPayment/DebtorParty/Location/Name

FPSUGH.P1CONM or

P1COA1-P1COA4; APS130MI/GetHeadAddress

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address @type

Set to 'text' if address information included.

CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address/AddressLine

FPSUGH.P1COA1-P1COA4; APS130MI/GetHeadAddress

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used, code G not available and the

				_		•	
(-	rΔ	М	IŤ	Γra	n	et.	Δľ
•							-

	fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.
	Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.
	Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).
@sequence ; -/-	Set to sequence number of the address line: values 1-4.
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address FPSUGH.P1TOWN; APS130MI/GetHeadAddress	
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address FPSUGH.P1ECAR; APS130MI/GetHeadAddress	c/CountrySubDivisionCode The field indicates the Area/State code (ECAR) of company from (MNS100).
	Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).
@listID ; -/-	Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address	·
FPSUGH.P1CSCD; APS130MI/GetHeadAddress	The field indicates the Country code (CSCD) of company from (MNS100).
@listID	Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.
; -/-	Set to 'Countries'.
CreditTransfer/CreditTransferPayment/DebtorParty/Location/Address FPSUGH.P1PONO; APS130MI/GetHeadAddress	s/PostalCode The field indicates the Postal code (PONO) of the company from (MNS100) if available in M3 (also sent as part of AddressLine
	@SequenceNumber = 3).
CMNDIV.CCOREF; APS130MI/GetHeadAddress	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division.
CMNDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. #/BBANID
CMNDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. */BBANID* The field indicates the Bank account number (BACN) of the company Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN.
CMNDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. */BBANID* The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed).
CMNDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. */BBANID* The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). **IBANID** The field indicates the International bank account number (IBAN) of the company.
CMNDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. */BBANID* The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). **IBANID** The field indicates the International bank account number (IBAN) of the company. **ICCurrencyCode**
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCCUCD; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. (BBANID) The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). EXBANID The field indicates the International bank account number (IBAN) of the company. EXCurrencyCode The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217.
CRINDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCCUCD; APS130MI/GetHead2 @listID; -/-	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. (BBANID) The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). (CurrencyCode) The field indicates the International bank account number (IBAN) of the company. (CurrencyCode) The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217. Set to 'Currencies'
CRINDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCCUCD; APS130MI/GetHead2 @listID; -/- CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBANA; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. (BBANID) The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). (BANID) The field indicates the International bank account number (IBAN) of the company. (CurrencyCode) The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217. Set to 'Currencies' (Name) The field indicates the Name (BANA) of the company's bank account.
CRINDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCCUCD; APS130MI/GetHead2 @listID; -/- CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBANA; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. (BBANID) The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). (BANID) The field indicates the International bank account number (IBAN) of the company. (CurrencyCode) The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217. Set to 'Currencies' (Name) The field indicates the Name (BANA) of the company's bank account.
CRONDIV.CCOREF; APS130MI/GetHeadAddress CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCCUCD; APS130MI/GetHead2 @listID; -/- CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBANA; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBANA; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccount CBANAC.BCBANA; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. **BBANID** The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). **IBANID** The field indicates the International bank account number (IBAN) of the company. **CurrencyCode** The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217. Set to 'Currencies' **Name** The field indicates the Name (BANA) of the company's bank account.
CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCBACN or BCBAF1; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCIBAN; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCCUCD; APS130MI/GetHead2 @listID; -/- CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCBANA; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCBANA; APS130MI/GetHead2 CreditTransfer/CreditTransferPayment/DebtorParty/FinancialAccounter CBANAC.BCBANA; APS130MI/GetHead2	@SequenceNumber = 3). The field indicates the Our reference (OREF) of the Division. **BBANID** The field indicates the Bank account number (BACN) of the company. Exception if Country version (MNS100.CSVN) = DK and APS130MI.GetHead2.CMBN = 23: - BBANID retrieved from APS130MI.GetHead2.BAF1 (see note below - Or if BAF1 = blank, from APS130MI.GetHead2.BACN. Otherwise retrieved from APS130MI.GetHead2.BACN as in standard. Comment to BAF1 when CMBN = 23: Old solution must be kept as same indicator used for BKTP-01 and 03. NB: Not included if IBAN of the company exists (only one FinancialAccount allowed). **//BANID** The field indicates the International bank account number (IBAN) of the company. **//CurrencyCode** The field indicates the Currency code (CUCD) of the company's bank account. Generic translation is used to translate CUCD according to ISO 4217. Set to 'Currencies' **//Name** The field indicates the Name (BANA) of the company's bank account. **//Type** The field indicates the code for currency account.

@schemeName

-.-; -/-

The field indicates the VAT registration number (VRN2) of the company's bank (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

Set to schemeName = 'TaxIdentificationNumber'.

CreditTransfer/CreditTransferPayment/FirstAgentParty/PartyIDs/BICID

CBANAC.BCSWBI or

CBANMA.BKSWIC.-; APS130MI or CRS690MI/GetHead2 or

GetBasicData

The field indicates the Swift/BIC code (SWBI) of the company's bank account and if not existing, Swift code (SWIC) of the company's bank.

CreditTransfer/CreditTransferPayment/FirstAgentParty/Name

CBANMA.BKBKNM or BKBKA1-BKBKA4

or

XRUBAN.BKXFLN.-; CRS690MI

or

CRRU04MI/GetBasicData

OI

GetBankRU

The field indicates the Bank name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

Exception if Country version (MNS100.CSVN) = RU:

- Payer's (Company's) Bank Name (CRRU04.XFLN (*)) and if not existing, as standard (same as above).

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04.

CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Location name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address @type

./۔ نہ ۔ ۔/۔

Set to 'text' if address information included.

Credit Transfer/Credit Transfer Payment/First Agent Party/Location/Address/Address Line Transfer/Credit Transfer Payment (No. 1997).

CBANMA.BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Bank address of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used.Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence

_ - -; -/-

Set to sequence number of the address line: values 1-4.

CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/CityName

CBANMA.BKTOWN

XRUBAN.BKXTWN.-; CRS690MI

or

CRRU04MI/GetBasicData

or

GetBankRU

The field indicates the City name (TOWN) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

Exception if Country version (MNS100.CSVN) = RU:

 - Payer's (Company's) Bank Address = Town (CRRU04.XTWN (*)) and if not existing, as standard (same as above).

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04.

Credit Transfer/Credit Transfer Payment/First Agent Party/Location/Address/Country SubDivision Code and the Control of the C

CBANMA.BKECAR; CRS690MI/GetBasicData

The field indicates the Area/State code (ECAR) of company's bank from (CRS690).

@listID

-.-; -/-

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.

CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/CountryCode

CBANMA.BKCSCD; CRS690MI/GetBasicData

The field indicates the Country code (CSCD) of company's bank from

(CRS690).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

Set to 'Countries'. -.-; -/-

CreditTransfer/CreditTransferPayment/FirstAgentParty/Location/Address/PostalCode CBANMA.BKPONO; CRS690MI/GetBasicData

The field indicates the Postal code (PONO) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine

(CLSI+CLSN cut together) of the company's bank retrieved from the

bank account. If clearing system ID (CLSI) has not been defined, only

@SequenceNumber = 3).

CreditTransfer/CreditTransferPayment/FirstAgentParty/ClearingSystemMemberID The field indicates the Clearing system member identification

CBANAC.BCCLSI + BCCLSN

XRUBAN.BKXBIK .-; APS130MI

CRRU04MI/GetHead2

GetBankRU

Exception if Country version (MNS100.CSVN) = RU:

clearing system number (CLSN) is used.

- BIK of Payer's bank (CRRU04.XBIK (*)) and if not existing, as

standard (same as above).

(*) APS130MI.GetHead2.BKNO must exist as key for CRRU04.

@schemeName

Set to schemaName = 'ClearingIdentificationNumber' -.-; -/-

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/PartyIDs/ID

FPSUGH.P1BBRN; APS130MI/GetHead2

The field indicates the Bank branch number (BBRN) of the company's

bank branch.

@schemeName -.-; -/-

Set to schemeName = 'BankPartvIdentification'.

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Party/Ds/BICID

CBANBR.BRSWIC; CRS691MI/GetBasicData

The field indicates the Swift code (SWIC) of the company's bank branch from (CRS691).

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank branch name (BKBM).

Alternative if generic translation not used: Bank branch name (BKBM).

Note: Address information retreived via APS130MI.GetHead2.BBRN.

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Location name of company's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address @type

-.-; -/-

Set to 'text' if address information included.

CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address/AddressLine

CBANBR.BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank address of company's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information. Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information. Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information. Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4). @seauence -.-; <u>-/</u>-Set to sequence number of the address line: values 1-4. CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address/CityName CBANBR.BRTOWN: CRS691MI/GetBasicData The field indicates the City name (TOWN) of company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3) CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address/CountrySubDivisionCode CBANBR.BRECAR; CRS691MI/GetBasicData The field indicates the Area/State code (ECAR) of company's bank branch from (CRS691). Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)). @listID Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US -.-; -/-States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements' CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address/CountryCode CBANBR.BRCSCD; CRS691MI/GetBasicData The field indicates the Country code (CSCD) of company's bank branch from (CRS691). Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1. @listID -.-; -/-Set to 'Countries'. CreditTransfer/CreditTransferPayment/FirstAgentParty/BranchParty/Location/Address/PostalCode The field indicates the Postal code (PONO) of the company's bank CBANBR.BRPONO; CRS691MI/GetBasicData branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3) CreditTransfer/CreditTransferPayment/Description CBANVA.BVBAVA.-; CRS693MI/GetBasicData The field indicates the Description of entries required by banks (company) Value (BAVA) from CRS693 is retrieved for the company's bank account using CRS693MI.GetBasicData with BKTP=01, BKID=APS130MI.GetHead2.BKID and BVTP=505. CreditTransfer/CreditTransferPayment/PaymentTransaction @sequence -.-; -/-The field indicates the Counter implemented within the BOD mapping (PaymentTransaction is created for each record returned by APS130MI.LstPayeeTotal3) CreditTransfer/CreditTransferPayment/PaymentTransaction/InstructionID FPSUGI.P2TEXT or The field indicates the Instruction ID that is set depending on the FPSUGD.P3PRPN + P3PYON + P3PDNB + P3SPYN.-; APS130MI/ Payment class used. LstPayInfByDoc or Payment class (APS130MI.GetHead2.PYCL) = 3: LstInvByPayDate - Internal ID (APS130MI.LstPayInfByDoc.TEXT where input.TAGG = InstructID). If not found, element not created. Payment class (APS130MI.GetHead2.PYCL) = 4: - Internal ID created as: Payment proposal number (PRPN), payment order number (PYON), document number (PDNB) and Payee (SPYN). - Payment proposal number (PRPN) is padded with zeros to length 10. - Payment document number (PYON) is padded with zeros to length - Document number (PDNB) is padded with zeros to length 5. - Payee (SPYN) is added at the end with '-' in front.

CreditTransfer/CreditTransferPayment/PaymentTransaction/TransactionID

FPSUGI.P2TEXT or The field indicates the Transaction ID (also called 'End-to-end ID') FPSUGD.P3PRPN + P3PYON + P3PDNB.-; APS130MI/LstPayInfByDoc that is set depending on the payment class used. or LstInvByPayDate

Payment class (APS130MI, GetHead2, PYCL) = 3:

- External ID (APS130MI.LstPayInfByDoc.TEXT where input.TAGG = EndToEndID).

If not found, element not created.

Payment class (APS130MI.GetHead2.PYCL) = 4:

- External ID created as: Payment proposal number (PRPN), payment order number (PYON) and document number (PDNB).
- Payment proposal number (PRPN) is padded with zeros to length
- Payment document number (PYON) is padded with zeros to length
- Document number (PDNB) is padded with zeros to length 5.

CreditTransfer/CreditTransferPayment/PaymentTransaction/PaymentPurposeCode

CBANAC.BCPPCO; APS130MI/LstPayeeTotal3 or GetHead2

The field indicates the Payment purpose code (PPCO) of the supplier's (TPPR=0) or customer's (TPPR=1) bank account and if not used (value = blank), retrieved from the company's bank account.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditTransferAgreement/CreditTransferType

@languageID

CSYTAB

CBANVA.BVBAVA .CTSLVC, CTSLCS and CTSLCE

; APS130MI

CRS693MI/GetHead2

GetBasicData

The field indicates the Service level code depending on setting on Payment method:

- If Service level code (SLVC) 0, 1, 2 or 3: Element not created on this level (instead handled on Payment level).
- If Service level code (SLVC) 4-SEPA extended control (transaction level): Set to Srv IvI cd - Std (SLCS) if SEPA payment (see (*) below), otherwise to Srv IvI cd - Exc (SLCE).
- (*) Extended control for SEPA payment included:
- If APS130MI.GetHead2.CUCD = EUR and
- If country APS130MI.GetHead2.SEPB = 1 (IBAN for SEPA country)
- If APS130MI.LstPayeeTotal3.SEPB = 1 (IBAN for SEPA country) for the supplier or customer.

Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SFPA-CTMIX:

Service level code retrieved according to the following priority: 1) Value (BAVA) from CRS693.GetBasicData with BKTP = 02 or 03 (see commment (a) below) for additional field (BVTP = 019).

- 2) Value (BAVA) from CRS693.GetBasicData with BKTP = 01 (see comment (b) below) for field (BVTP = 019).
- 3) If the above value not exists: From payment method.

(a) Value (BAVA) from CRS693 is retrieved for the supplier's bank account using CRS693MI.GetBasicData with ACHO= APS130MI.LstPayeeTotal3.SPYN,

BKID=APS130MI.LstPayeeTotal3.BKID and BVTP as described above and:

- BKTP set to 03 (supplier) in case TPPR = 0, first retrieved from company/division level and if not available, from company level.
- BKTP set to 02 (customer) in case TPPR = 1, retrieved from company level.

(b) Value (BAVA) from CRS693 is retrieved for the company's bank account using CRS693MI.GetBasicData with BKTP=01,

BKID=APS130MI.GetHead2.BKID and BVTP as described above. Retrieved from company division level

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditTransferAgreement/PriorityCode

CBANAC.BCPITY; APS130MI/LstPayeeTotal3

The field indicates the Priority code (PITY) of the supplier's or customer's bank account.

This code has to be translated:

- PITY = 01: 'NORMAL'
- PITY = 02: 'HIGH'
- PITY = 03: 'URGENT'
- PITY = 04: 'LOW'

Not included if value 00 (not used).

@listID -.-; -/-

Set to 'Priorities'.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditTransferAgreement/CategoryPurposeCode

CBANAC.BCCPCO; APS130MI/LstPayeeTotal3 The field indicates the Category purpose code (CPCO) of the

supplier's or customer's bank account.

NB: Exist also on 'CreditTransferPayment/CreditTransferAgreement' level where information from the company's bank account is retrieved.

CreditTransfer/CreditTransferPayment/PaymentTransaction/InstructedAmount

FPSUGS.P2CUAM: APS130MI/LstPaveeTotal3

@currencyID

FPSUGD.P3CUCD; APS130MI/LstInvByPayDate

The field indicates the Paid amount, currency (CUAM) of the document number (number of decimals for currency considerred in MI so must be adjusted to include 2 decimals).

The field indicates the Currency code (CUCD) of the invoice/payment.

Generic translation is used to translate CUCD according to ISO 4217.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty

@category
CBANAC. BCIBBN, BCIBIB, BCIBCN or XRUBAN.BKXCOR.-; APS130MI

CRRU04MI/GetHead2, LstPayeeTotal3

GetBankRU

The field indicates the sequence (category) of the intermediary party that is an agent (one or several) between the company's bank and supplier's bank.

Note that intermediary bank information is not available for customer bank accounts so in case of customer payments (TPPR=1), only company intermediary bank is included.

Standard handling:

The section 'IntermediaryFinancialParty' is created when one of the following fields are available (not blank) for the:

- 1) Company (APS130MI.GetHead2):
- Bank number (IBBN) or
- IBAN number (IBIB) or
- Bank account number (IBCN).
- => If found: Section created and @category set to 'Intermediary1'.
- 2) Supplier (APS130MI.LstPayeeTotal3) only in case of supplier payments (TPPR=0):
- Bank number (IBBN) or IBAN number (IBIB) or
- Bank account number (IBCN).
- => If found and:
- Available for company: Section created and @category set to 'Intermediary2'
- Not available for company: Section created and @category set to 'Intermediary1'.

Exception if Country version (MNS100.CSVN) = RU:

The section 'IntermediaryFinancialParty' is created (*) when the following field is available (not blank) for the:

1) Company (CRRU04MI. GetBankRU via

APS130MI.GetHead2.BKNO):

- 'Bank corresponding account' (XCOR).
- => If found: Section created and @category set to 'Intermediary1'.
- 2) Supplier (CRRU04MI.GetBankRU via

APS130MI.LstPayeeTotal3.BKNO) - only in case of supplier payments (TPPR=0):

- 'Bank corresponding account' (XCOR).
- => If found: Section created and @category set to 'Intermediary2'.
- (*) Only '/Name' and '/FinancialAccount/BBANID' included

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/PartyIDs/ID

CBANAC.BCIBBN; APS130MI/GetHead2, LstPayeeTotal3

The field indicates the Bank number (IBBN) of the Intermediary bank:

- If Company: Retrieved from APS130MI.GetHead2.
- If Supplier (only if TPPR=0): Retrieved from

APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

@schemeName -.-; -/-

Set to schemeName = 'BankPartyIdentification'.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the VAT registration number (VRN2) of the Intermediary bank retrieved from CRS690MI.GetBasicData via BKNO = IBBN from:

- If Company: Field IBBN retrieved from APS130MI.GetHead2.
- If Supplier (only if TPPR=0): Field IBBN retrieved from APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

Set to schemeName = 'TaxIdentificationNumber'.

@schemeName

-.-; -/-

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/PartyIDs/BICID

CBANAC.BCIBSW or CBANMA.BKSWIC.-; APS130MI or CRS690MI/ GetHead2, LstPayeeTotal3 or

GetBasicData

The field indicates the SWIFT/BIC code (IBSW or SWIC) of the Intermediary bank account and if blank, of the intermediary bank from: - If Company: Field IBSW from APS130MI.GetHead2 and if blank, field SWIC from CRS690MI.GetBasicData via BKNO = IBBN from APS130MI.GetHead2.

- If Supplier (only if TPPR=0): Field IBSW from

APS130MI.LstPaveeTotal3 and if blank, field SWIC from CRS690MI.GetBasicData via BKNO = IBBN from APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Name

CBANMA.BKBKNM or BKBKA1-BKBKA4

XRUBAN.BKXTXT.-: CRS690MI

CRRU04MI/GetBasicData

GetBankRU

The field indicates the Bank name of the intermediary bank (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

- Alternative if generic translation used and code A not available: Bank name (BKNM).
- Alternative if generic translation not used: Bank name (BKNM).
- (*) Field 'Bank number' (IBBN) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU: Bank Name (field XTXT from CRRU04MI:

- If Company: Via field BKNO from APS130MI.GetHead2.
- If Supplier (only if TPPR=0): Via field BKNO from APS130MI.LstPayeeTotal3

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Name

CBANMA.BKBKNM or

@sequence

BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Location name of the intermediary bank (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

- Alternative if generic translation used and code C not available: Location/Name not included.
- Alternative if generic translation not used: Bank name (BKNM).
- (*) Field 'Bank number' (IBBN) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Address/AddressLine

CBANMA.BKBKA1-BKBKA4; CRS690MI/GetBasicData

The field indicates the Bank address of the intermediary bank (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used.Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

- Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.
- Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.
- Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.
- Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).
- (*) Field 'Bank number' (IBBN) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Set to sequence number of the address line: values 1-4

- Element not created.

-.-; -/-

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Address/CityName CBANMA.BKTOWN; CRS690MI/GetBasicData

The field indicates the City (TOWN) of the intermediary bank (*) from

(*) Field 'Bank number' (IBBN) retrieved depending on type of

account:

- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Address/CountrySubDivisionCode

CBANMA.BKECAR; CRS690MI/GetBasicData

The field indicates the Area/State code (ECAR) of the intermediary bank (*) from (CRS690).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

- (*) Field 'Bank number' (IBBN) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

@listID -.-: -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Address/CountryCode

CBANMA.BKCSCD; CRS690MI/GetBasicData

The field indicates the Country code (CSCD) of the intermediary bank (*) from (CRS690).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

- (*) Field 'Bank number' (IBBN) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

@listID -.-; -/-

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/Location/Address/PostalCode

CBANMA.BKPONO; CRS690MI/GetBasicData

Set to 'Countries'

The field indicates the Postal code (PONO) of the intermediary bank (*) from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

- (*) Field 'Bank number' (IBBN) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/ClearingSystemMemberID

CBANAC.BCIBSI, BCIBSN; APS130MI/GetHead2, LstPayeeTotal3

The field indicates the Clearing system member identification (IBSI+IBSN cut together) of the intermediary bank (*) retrieved from the bank account. If clearing system ID (IBSI) has not been defined, only clearing system number (IBSN) is used.

- (*) Field 'Bank number' (IBBN) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

Set to schemaName = 'ClearingIdentificationNumber'

@schemeName

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/PartyIDs/ID

CBANAC.BCIBBB; APS130MI/GetHead2, LstPayeeTotal3

The field indicates the Bank branch number (IBBB) of the intermediary bank branch (*).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

@schemeName

<u>-.-;</u> -/-

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

Set to schemeName = 'BankPartyIdentification'.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/PartyIDs/BICID

CBANBR.BRSWIC; CRS691MI/GetBasicData

The field indicates the SWIFT/BIC code (SWIC) of the intermediary bank branch (*) from (CRS691).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Name @languageID

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of the intermediary bank branch (*) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

- Alternative if generic translation used and code A not available: Bank branch name (BKBM).
- Alternative if generic translation not used: Bank branch name (BKBM).
- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Location name of the intermediary bank branch (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description

of setup).

- Alternative if generic translation used and code C not available: Location/Name not included.

- Alternative if generic translation not used: Bank branch name (BKBM).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address @type

-.-; -/-

Set to 'text' if address information included

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address/AddressLine CBANBR.BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank address of the intermediary bank branch (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local ly for description of setup).

- Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.
- Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information.
- Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.
- Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4).
- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:

- If Company: From APS130MI.GetHead2.

- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

@sequence -.-: -/-

@listID

@listID

Set to sequence number of the address line: values 1-4

CBANBR.BRTOWN; CRS691MI/GetBasicData

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address/CityName The field indicates the City name (TOWN) of the intermediary bank branch (*) from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address/ CountrySubDivisionCode

CBANBR.BRECAR; CRS691MI/GetBasicData

The field indicates the Area/State code (ECAR) of the intermediary bank branch (*) from (CRS691).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address/CountryCode CBANBR.BRCSCD; CRS691MI/GetBasicData

The field indicates the Country code (CSCD) of the intermediary bank branch (*) from (CRS691).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Element not created.

Set to 'Countries'

CBANBR.BRPONO; CRS691MI/GetBasicData

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/BranchParty/Location/Address/PostalCode The field indicates the Postal code (PONO) of the intermediary bank branch (*) from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

- (*) Field 'Bank branch number' (IBBB) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.
- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/FinancialAccount/BBANID

CBANAC.BCIBCN

XRUBAN.BKXCOR.-; APS130MI

CRRU04MI/GetHead2, LstPayeeTotal3

or

GetBankRU

The field indicates the Bank account number (IBCN) of the intermediary bank (*).

NB: Not included if IBAN (field IBIB) of the intermediary bank exists (only one FinancialAccount allowed).

- (*) Field 'Bank account number' (IBCN) retrieved depending on type of account:
- If Company: From APS130MI.GetHead2.

- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU: Bank corresponding account (field XCOR from CRRU04MI: - If Company: Via field BKNO from APS130MI.GetHead2.

- If Supplier (only if TPPR=0): Via field BKNO from

APS130MI.LstPayeeTotal3.

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/FinancialAccount/IBANID

CBANAC.BCIBIB; APS130MI/GetHead2, LstPayeeTotal3

The field indicates the International bank account number (IBIB) of the intermediary bank (*).

(*) Field 'IBAN' (IBIB) retrieved depending on type of account:

- If Company: From APS130MI.GetHead2

- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

- Flement not created

CreditTransfer/CreditTransferPayment/PaymentTransaction/IntermediaryFinancialParty/FinancialAccount/Name

CBANAC.BCIBBD; APS130MI/GetHead2, LstPayeeTotal3

The field indicates the Name (IBBD) of the intermediary bank account(*).

(*) Field 'Bank account description' (IBBD) retrieved depending on type of account:

- If Company: From APS130MI.GetHead2.

- If Supplier (only if TPPR=0): From APS130MI.LstPayeeTotal3.

Exception if Country version (MNS100.CSVN) = RU:

Element not created.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/PartyIDs/ID

FPSUGS.P2OUCN, P2SPYN or

CBANAC.BCRENO.-; APS130MI/LstPayeeTotal3

The field indicates the IDs included as standard for the creditor party.

Information from Supplier (TPPR=0):

- ID 1: Payee number (SPYN).

- ID 2: Company's customer number at supplier (OUCN).

- ID 3: Recipient number (RENO) of supplier.

For ID 3 Recipient number (RENO), not included if following conditions have been met:

- Electronic format (APS130MI.GetHead2.ELET) = SE-BGL-GM, SE-BGF-GM, SE-PGL-GM or SE-PGF-GM

- Value = "9999999999"

Otherwise, process according to standard handling above.

Information from Customer (TPPR=1):

- ID 1: Payer number (PYNO sent as SPYN).

- ID 2: Company's supplier number at customer (CUSU sent as

OUCN).

The field indicates the schemeNames used as standard:

- ID 1: schemeName 'SupplierNumber'

- ID 2: schemeName 'CustomerNumber'

- ID 3: schemeName 'RecipientNumber'

already added as prefix if applicable).

already added as prefix if applicable)

or other signs between.

The field indicates the Accounting entity (this is the translated M3 BE company and division).

The field indicates the TaxIDs included as standard with information of supplier (from CRS620) or customer (from CRS610):
- TaxID 1: VAT registration number (VRN2) of the supplier or

customer (Note: Country code (ISO country code from (CRS045)

- TaxID 2: Organization number 1 (CORG) of the supplier.

- TaxID 3: Organization number 2 (COR2) of the supplier.

Exception if Country version (MNS100.CSVN) = FR: - TaxID 1: VAT registration number (VRN2) of the supplier or customer (Note: Country code (ISO country code from (CRS045)

@schemeName -.-; -/-

@accountingEntity

FPSUGS.P2CONO + P2DIVI; APS130MI/LstPayeeTotal3

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/PartyIDs/TaxID

CIDMAS.IDVRNO, IDCORG, IDCOR2

XRUSUP.IDXIN2, IDXKP2

XRUCUS.OKXIN2, OKXKP2

XIDADR.XACNPJ

XITSIN.XSXFCO

XITCIN.XCXFCO.-; APS130MI

CRRU03MI

CRRU02MI

CRIT24MI or

and if missing, VAT registration number (VRN2) of the supplier (Note: Country code (ISO country code from (CRS045) already added as

- TaxID 2: Organization number 1 (CORG) + Organization number 2

(COR2) of the supplier or customer concatenated without any blanks

Exception if Country version (MNS100.CSVN) = RU and Supplier payments (TPPR=0) XBR001MI - TaxID 1: Recipient INN (CRRU03.XIN2 (*)) without country code

CRIT10MI/LstPayeeTotal3

GetSupplierRU

GetCustomerRU

GetSupAddress

GetBasicData

or

GetBasicData

@schemeName

XIDADR.XAPJUR.-; -

XBR001MI/-

or

GetSupAddress

prefix if applicable).

- TaxID 2: Receipient KPP (CRRU03.XKP2 (*)) and if missing, Organization number 1 (CORG) of the supplier.

(*) Via APS130MI.LstPayeeTotal3.SPYN.

Exception if Country version (MNS100.CSVN) = RU and Customer payments (TPPR=1):

· TaxID 1: Recipient INN (CRRU02.XIN2 (*)) without country code and if missing, VAT registration number (VRN2) of the customer (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

- TaxID 2: Receipient KPP (CRRU02.XKP2 (*)) and if missing, Organization number 1 (CORG) of the customer.

(*) Via APS130MI.LstPayeeTotal3.SPYN.

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: VAT registration number (VRN2) of the supplier or customer (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

- If VAT registration number (VRN2) = blank:
 TaxID 2 for supplier (TPPR=0): Fiscal code (XFCO) from Italian supplier master (CRIT24), not created if if Fiscal code (XFCO) is blank or no record returned by CRIT24MI.

 - TaxID 2 for customer (TPPR=1): Fiscal code (XFCO) from Italian
- customer master (CRIT10), not created if if Fiscal code (XFCO) is blank or no record returned by CRIT10MI.

Exception if Country version (MNS100.CSVN) = BR and Supplier payments (TPPR=0) (not used but left for future need):

- TaxID 1: CNPJ/CPF (CRS622 - XBR001MI.GetSupAddress.CNPJ) without country code.

Retrieve from XBR001MI.GetSupAddress for the Payer (SPYN), Start date (STDT) = 'Date' from MBM initiator and Address type (ADTE) = 10, if not found try with Address type (ADTE) = 01.

Note: Not changed for customer payments (TPPR=1) as not used.

The field indicates the schemeNames that are used as standard:

- TaxID 1: schemeName = 'TaxIdentificationNumber'- TaxID 2: schemeName = 'CountryIdentificationNumber'
- TaxID 3: schemeName = 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = RU:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'TaxDeclarationNumber'

Following schemeNames are used as exception if Country version (MNS100.CSVN) = BR and Supplier payments (TPPR=0) (not used but left for future need):

- TaxID 1: schemeName 'TaxIdentificationNumber' if

XBR001MI.GetSupAddress.PJUR = 1 (CNPJ - company (juristic)).

- TaxID 1: schemeName 'NationalIdentityNumber' if

XBR001MI.GetSupAddress.PJUR = 2 (CPF - private person). Retrieve from XBR001MI.GetSupAddress for the Payer (SPYN), Start date (STDT) = 'Date' from MBM initiator and Address type (ADTE) = 10, if not found try with Address type (ADTE) = 01.

Note: Not changed for customer payments (TPPR=1) as not used.

Following schemeNames are used as exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'NationalIdentityNumber'

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Name

FPSUGS.P2SUNM or P2ADR1-P2ADR4

XRUSUP.IDXFLN.-; APS130MI

CRRU03MI

CRRU02MI/LstPayeeTotal3

or

The field indicates the Supplier or Customer name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' (if TPPR=0) or 'CUST' (if TPPR=1) or 'ALL' to a code string indicating how SUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Supplier or Customer name (SUNM) as mandatory information.

GetSupplierRU

GetCustomerRU

Alternative if generic translation not used: Supplier or Customer name (SUNM).

Exception if Country version (MNS100.CSVN) = RU and Supplier payments (TPPR=0):

- Recipient's (Payee's) Name (CRRU03.XFLN (*)) and if not existing, as standard (same as above).

(*) Via APS130MI.LstPayeeTotal3.SPYN.

(*) Via APS130MI.LstPayeeTotal3.SPYN.

Exception if Country version (MNS100.CSVN) = RU and Customer payments (TPPR=1):

 Recipient's (Payer's) Name (CRRU02.XFLN (*)) and if not existing, as standard (same as above).

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Name

FPSUGS.P2SUNM or

P2ADR1-P2ADR4; APS130MI/LstPayeeTotal3

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' (if TPPR=0) or 'CUST' (if TPPR=1) or 'ALL' to a code string indicating how SUNM and ADR1-ADR4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Supplier or Customer name (SUNM)

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address @type

Set to 'text' if address information included.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/AddressLine

FPSUGS.P2ADR1-P2ADR4; APS130MI/LstPayeeTotal3

The field indicates the Supplier's or Customer's address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' (if TPPR=0) or 'CUST' (if TPPR=1) or 'ALL' to a code string indicating how ADR1-ADR4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local ly for description of setup).

Alternative if generic translation used and code E not available: Supplier or Customer address line 2 (ADR2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Supplier or Customer address line 3 (ADR3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (ADR4) not included as not mandatory information.

Alternative if generic translation not used: Supplier or Customer address line 1-4 (ADR1-ADR4).

@sequence

-.-: -/-

Set to sequence number of the address line: values 1-4.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/CityName

FPSUGS.P2TOWN; APS130MI/LstPayeeTotal3

The field indicates the City name (TOWN) of supplier from (CRS620) or customer from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3)

Credit Transfer/Credit Transfer Payment/Payment Transaction/Creditor Party/Location/Address/Country SubDivision Code to the Contract of the Contract Country SubDivision Code to the Contract Code to the Contract Code to the Code to

FPSUGS.P2ECAR; APS130MI/LstPayeeTotal3

The field indicates the Area/State code (ECAR) of supplier from (CRS620) or customer from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

@listID

-.-; -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/CountryCode

FPSUGS.P2CSCD; APS130MI/LstPayeeTotal3

The field indicates the Country code (CSCD) of supplier from (CRS620) or customer from (CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

Set to 'Countries'. -.-; -/-

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/Location/Address/PostalCode

The field indicates the Postal code (PONO) of supplier from FPSUGS.P2PONO; APS130MI/LstPayeeTotal3

(CRS620) or customer from (CRS610) if available in M3 (also sent as

part of AddressLine @SequenceNumber = 3).

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/BBANID

CBANAC.BCBACN, BCBAF1

FPSUGD.P3IRE2.-; APS130MI/LstPayeeTotal3

LstInvByPayDate

The field indicates the Bank account number (BACN) of the supplier or customer.

Exception if Country version (MNS100.CSVN) = DK, Supplier payments (TPPR=0) and APS130MI.LstPayeeTotal3.CMBN = 22 or 23:

- BBANID retrieved from APS130MI.LstInvByPayDate.IRE2 (see note

- Or if IRE2 = blank, from APS130MI.LstPayeeTotal3.BAF1 - Or if BAF1 = blank, from APS130MI.LstPayeeTotal3.BACN. Otherwise retrieved from APS130MI.LstPayeeTotal3.BACN as in standard.

Comment to IRE2 when CMBN = 22 or 23: Payment document number (PDNB) is created per invoice so therefore possible to use IRE2 from invoice as bank account number.

NB: Not included if IBAN of the supplier or customer exists (only one FinancialAccount allowed).

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/IBANID

CBANAC.BCIBAN; APS130MI/LstPayeeTotal3

The field indicates the International bank account number (IBAN) of the supplier or customer.

CreditTransfer/CreditTransferPayment/PaymentTransaction/CreditorParty/FinancialAccount/Name

CBANAC.BCBANA; APS130MI/LstPayeeTotal3

The field indicates the Name (BANA) of the supplier's or customer's

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Party/Ds/ID

CBANAC.BCBKNO; APS130MI/LstPayeeTotal3

The field indicates the Bank number (BKNO) of the supplier's or

customer's bank.

@schemeName

@accountingEntity

FPSUGS.P2CONO + P2DIVI; APS130MI/LstPayeeTotal3

Set to schemeName = 'BankPartyIdentification'.

The field indicates the Accounting entity (this is the translated M3 BE

company and division)

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the VAT registration number (VRN2) of the supplier's or customer's bank (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

@schemeName -.-; -/-

Set to schemeName = 'TaxIdentificationNumber'.

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/BICID

CBANAC.BCSWBI or CBANMA.BKSWIC .-; APS130MI or CRS690MI/LstPayeeTotal3 or

The field indicates the Swift/BIC code (SWBI) of the supplier's or customer's bank account and if not existing, Swift code (SWIC) of the supplier's bank.

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Name

CBANMA.BKBKNM or BKBKA1-BKBKA4

CBANAC.BCBANA

XRUBAN.BKXFLN.-; CRS690MI

APS130MI

CRRU04MI/GetBasicData

LstPayeeTotal3

GetBankRU

The field indicates the Bank name of the supplier's or customer's

bank based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

If no name found above, Bank A/C name (BANA) for the Bank account ID (BKID) of the supplier or customer.

Exception if Country version (MNS100.CSVN) = RU:

- Recipient's (Payee's) Bank Name (CRRU04.XFLN (*)) and if not existing, Payee's bank name (CRS690.BKNM).

(*) APS130MI.LstPayeeTotal3.BKNO must exist as key for CRRU04.

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKBKA4: CRS690MI/GetBasicData

The field indicates the Location name of supplier's or customer's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank name (BKNM).

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address @type

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/AddressLine CBANMA.BKBKA1-BKBKA4; CRS690MI/GetBasicData

Set to 'text' if address information included.

The field indicates the Bank address of the supplier's or customer's bank based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate

'Country' (see the integration guide for Local.ly for description of

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence

@listID

-.-; -/-

CRRU04MI/GetBasicData

CRRU04MI/LstPayeeTotal3

-.-; <u>-/</u>-Set to sequence number of the address line: values 1-4.

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CityName

CBANMA.BKTOWN The field indicates the City name (TOWN) of supplier's or customer's

bank from (CRS690) if available in M3 (also sent as part of XRUBAN.BKXTWN.-; CRS690MI AddressLine @SequenceNumber = 3).

Exception if Country version (MNS100.CSVN) = RU: - Payer's (Company's) Bank Address = Town (CRRU04.XTWN (*)) GetBankRU

and if not existing, as standard (same as above).

(*) APS130MI.LstPayeeTotal3.BKNO must exist as key for CRRU04.

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountrySubDivisionCode

CBANMA.BKECAR; CRS690MI/GetBasicData The field indicates the Area/State code (ECAR) of supplier's or customer's bank from (CRS690).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountryCode

CBANMA.BKCSCD; CRS690MI/GetBasicData The field indicates the Country code (CSCD) of supplier's or

customer's bank from (CRS690).

Generic translation is used to translate CSCB to alpha-2 country code

according to ISO 3166-1.

@listID Set to 'Countries'

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/PostalCode

CBANMA.BKPONO; CRS690MI/GetBasicData The field indicates the Postal code (PONO) of supplier's or

customer's bank from (CRS690) if available in M3 (also sent as part

of AddressLine @SequenceNumber = 3)

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/ClearingSystemMemberID CBANAC.BCCLSI + BCCLSN

The field indicates the Clearing system member identification (CLSI+CLSN cut together) of the supplier's or customer's bank XRUBAN.BKXBIK .-; APS130MI retrieved from the bank account. If clearing system ID (CLSI) has not

been defined, only clearing system number (CLSN) is used.

Exception if Country version (MNS100.CSVN) = RU: GetBankRU

- BIK of Payer's bank (CRRU04.XBIK (*)) and if not existing, as

standard (same as above).

(*) APS130MI.LstPayeeTotal3.BKNO must exist as key for CRRU04.

@schemeName Set to schemaName = 'ClearingIdentificationNumber'

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/PartyIDs/ID

CBANAC.BCBBRN: APS130MI/LstPaveeTotal3

The field indicates the Bank branch number (BBRN) of the supplier's or customer's bank branch.

@schemeName

-.-: -/-

@accountingEntity

FPSUGS.P2CONO + P2DIVI; APS130MI/LstPayeeTotal3

Set to schemeName = 'BankPartyIdentification'.

The field indicates the Accounting entity (this is the translated M3 BE

company and division)

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/PartyIDs/BICID

CBANBR.BRSWIC; CRS691MI/GetBasicData The field indicates the Swift code (SWIC) of the supplier's or

customer's bank branch from (CRS691)

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of the supplier's or customer's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank branch name (BKBM).

Alternative if generic translation not used: Bank branch name (BKBM).

Note: Address information retreived via APS130MI.LstPayeeTotal3.BBRN

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Name

CBANBR.BRBKBM or

BRBKA1-BRBKA4; CRS691MI/GetBasicData

The field indicates the Location name of the supplier's or customer's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or

'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address @type

Set to 'text' if address information included

CBANBR.BRBKA1-BRBKA4; CRS691MI/GetBasicData

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/AddressLine The field indicates the Bank address of the supplier's or customer's bank branch based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local ly for description of setup).

Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4).

@sequence <u>-.-; -/-</u>

CBANBR.BRTOWN; CRS691MI/GetBasicData

Set to sequence number of the address line: values 1-4

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/CityName

The field indicates the City name (TOWN) of the supplier's or customer's bank branch from (CRS691) if available in M3 (also sent

as part of AddressLine @SequenceNumber = 3)

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/ **CountrySubDivisionCode**

CBANBR.BRECAR; CRS691MI/GetBasicData

The field indicates the Area/State code (ECAR) of the supplier's or customer's bank branch from (CRS691).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

@listID

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/CountryCode

CBANBR.BRCSCD; CRS691MI/GetBasicData

The field indicates the Country code (CSCD) of the supplier's or

customer's bank branch from (CRS691).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

Set to 'Countries' -.-; -/-

CreditTransfer/CreditTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/PostalCode CBANBR.BRPONO; CRS691MI/GetBasicData

The field indicates the Postal code (PONO) of the supplier's or customer's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

CreditTransfer/CreditTransferPayment/PaymentTransaction/ChargeBearerCode

CBANAC.BCCBCD; APS130MI/LstPayeeTotal3 or GetHead2

The field indicates the Charge bearer code (CBCD) of the supplier's or customer's bank account and if not used (value = 00), retrieved from the company's bank account.

This code has to be translated:

- CBCD = 01 - "Shared"

- CBCD = 02 - "Debtor"

- CBCD = 03 - "Creditor"

- CBCD = 04 - "ServiceLevel"

Not included if value 00 (not used) for both supplier's or customer's and company's bank accounts

CreditTransfer/CreditTransferPayment/PaymentTransaction/ExchangeContractReference/DocumentID/ID

FPSUGD.P3FECN; APS130MI/LstInvByPayDate

The field indicates the future rate agreement number, retrieved from the first invoice of a payment document.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RegulatoryReporting/Code

FPSUGS.P2TDCD FPSUGD.P3TDCD CBANVA.BVBAVA.-; APS130MI or CRS693MI/LstPayeeTotal3 or LstInvByPayDate or GetBasicData

The field indicates the Trade code (TDCD) of the payment (when split per trade code used), of the first invoice (if split not used) or standard code of the company's bank account.

Standard handling for Supplier payments (TPPR=0):

The Trade code is retrieved in the following order:

1) From payment = Trade code (TDCD) from LstPayeeTotal3 and if bĺank,

2) From first invoice = Trade code (TDCD) from LstInvByPayDate. 3 Default Trade code (BAVA) from CRS693MI.GetBasicData with CONO/DIVI from APS 130MI. GetHead2, BKTP=01 (Company) ACHO=blank, BKID=APS130MI.GetHead2.BKID and BVTP=031.

Standard handling for Customer payments (TPPR=1):

The Trade code is retrieved in the following order:

1 Default Trade code (BAVA) from CRS693MI.GetBasicData with CONO/DIVI from APS130MI.GetHead2, BKTP=01 (Company) ACHO=blank, BKID=APS130MI.GetHead2.BKID and BVTP=031

CreditTransfer/CreditTransferPayment/PaymentTransaction/RegulatoryReporting/Note

CSYTAB.CTTX40 FPLEDX.EPPEXI.-; APS130MI or APS251MI/LstPayeeTotal3 or LstInvByPayDate or LstInvInfo

The field indicates the Trade code description retrieved from (APS010) for the trade code included in the payment.

Standard handling for Supplier payments (TPPR=0):

If Trade code (TDCD) included:

1) From LstPayeeTotal3: Trade code description (TDCX) from LstPayeeTotal3.

2) From LstInvByPayDate (first record): Trade code description (TDCX) from LstInvByPayDate.

NB: The information is not included for Default Trade codes retrieved from (CRS693) - exception as described above for 'PaymentTransaction/RegulatoryReporting/Code'.

Exception if Country version (MNS100.CSVN) = NO for Supplier payments (TPPR=0):

If Trade code included (either from LstPayeeTotal3 and LstInvByPayDate), retrieve description via:

1) APS251MI.LstInvInfo with:

- CONO and DIVI = From APS130MI.GetHead2. Below values from the first invoice in LstInvByPayDate:

- SPYN, SUNO, SINO and INYR

Retrieve PEXI from records with PEXN = 557 and 558 (manual trade code desciption entered in APS100 for foreign suppliers where payment method defined with NADO not equal 10) and concatenate the information.

If not found.

Same as 1 and 2 above for standard.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/UnstructuredRemittanceText

FPSUGI.P2TEXT

FPSUGD.P3IRE1-P3IRE3 and P3TX51-P3TX55.-; APS130MI /

LstPayInfByDoc or LstInvByPayDate

The field indicates the Payment information (LstPayInfByDoc.TEXT where TAGG = blank, multiple records possible) as created in M3BE (indicated on payment method in CRS071 with user-defined settings in CRS485). If not found, element not created.

Not used for payment class 4 (element not created).

Exception if Country version (MNS100.CSVN) = AT: - If APS130MI.GetHead2.ELET = 'SEPA-CTMIX' and

APS130MI.LstPayeeTotal3.CPCO (Category purpose code) = 'TAXS': IRE1-IRE3 (blank) and TX51-TX55 for all invoices included in the payment (separator; + blank between each invoice).

Otherwise as standard (see above).

New record created per 1024 positions.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ **DocumentReference**

@type

-.-; -/-Set to Type of document reference depending on APL or ARL record.

For supplier payments (TPPR=0):

- If APS130MI.LstInvByPayDate.SCNO = blank: Noun =

- If APS130MI.LstInvByPayDate.SCNO # blank: Noun = Invoice.

For customer payments (TPPR=1):

- Noun = Invoice

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/

DocumentReference/DocumentID/ID

FPSUGD.P3SINO; APS130MI/LstInvByPayDate The field indicates the Supplier invoice number (SINO) that is supplier invoice number or

customer invoice number.

@accountingEntity

FPSUGD.P3CONO + P3ODIV; APS130MI/LstInvByPayDate

The field indicates the Accounting entity (this is the translated M3 BE

company and original division (ODIV))

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ RemittanceReferredDocumentAmounts/DiscountAppliedAmount

@currencyID

FPSUGD.P3CDCU; APS130MI/LstInvByPayDate

The field indicates the Cash discount amount currency (CDCU).

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ RemittanceReferredDocumentAmounts/DiscountAppliedBaseAmount

FPSUGD.P3CUCD; APS130MI/LstInvByPayDate

The field indicates the Currency code (CUCD) of the invoice/payment.

Generic translation is used to translate CUCD according to ISO 4217.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/

RemittanceReferredDocumentAmounts/RemittedAmount

FPSUGD.P3PYCU; APS130MI/LstInvByPayDate The field indicates the Paid amount, currency (PYCU) of the invoice

or credit note.

@currencvID FPSUGD.P3CUCD; APS130MI/LstInvByPayDate

The field indicates the Currency code (CUCD) of the invoice/payment.

Generic translation is used to translate CUCD according to ISO 4217.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/

RemittanceReferredDocumentAmounts/RemittedBaseAmount

FPSUGD.P3PYAM; APS130MI/LstInvByPayDate The field indicates the Paid amount, local (PYAM) of the invoice or

credit note.

@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the Local currency code (LOCD).

Generic translation is used to translate LOCD according to ISO 4217.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ RemittanceReferredDocumentAmounts/TaxAmount

FPLEDG.EPVTAM FSLEDG.ESVTAM

FPSUGD.P3VTAM .-: APS200MI or

ARS200MI or

APS130MI/GetInvTotInfo or

GetInvTotInfo or LstInvByPayDate The field indicates the VAT amount in foreign currency for the invoice (payment) and is as standard solution, only included when split payment is used for the payment method (only available for supplier payments (TPPR=0).

Exception if Country version (MNS100.CSVN) = RU and Supplier payments (TPPR=0):

The solution for CSVN = RU retrieve the information directly from the Accounts payable due to prepayment handling used (not available for split payment).

- Retrieve VAT amount (VTAM) from APS200MI.GetInvTotInfo via

@currencyID

FPLEDĞ.EPCUCD FSLEDG.ESCUCD FPSUGD.P3CUCD.-; APS200MI or ARS200MI or APS130MI/GetInvTotInfo or GetInvTotInfo or LstInvByPayDate ODIV, SPYN, SINO, INYR and SUNO from LstInvByPayDate.

Exception if Country version (MNS100.CSVN) = RU and Customer payments (TPPR=1):

The solution for CSVN = RU retrieve the information directly from the Accounts receivable.

- Retrieve VAT amount (VTAM) from ARS200MI.GetInvTotInfo via DIVI=ODIV, PYNO=SPYN, CINO=SINO, INYR and CUNO=SUNO from LstInvByPayDate.

The field indicates the currency code of the VAT amount in foreign currency for the invoice (payment) and is as standard solution only included when split payment is used for the payment method (only available for supplier payments (TPPR=0).

Exception if Country version (MNS100.CSVN) = RU and Supplier payments (TPPR=0):

The solution for CSVN = RU retrieve the information directly from the Accounts payable due to prepayment handling used (not available for split payment).

- Retrieve Currency code (CUCD) from APS200MI.GetInvTotInfo via ODIV, SPYN, SINO, INYR and SUNO from LstInvByPayDate.

Exception if Country version (MNS100.CSVN) = RU and Customer payments (TPPR=1):

The solution for CSVN = RU retrieve the information directly from the Accounts receivable.

- Retrieve Currency code (CUCD) from ARS200MI.GetInvTotInfo via DIVI=ODIV, PYNO=SPYN, CINO=SINO, INYR and CUNO=SUNO from LstInvByPayDate.

Generic translation is used to translate CUCD according to ISO 4217.

CreditTransfer/CreditTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/StructuredCreditorReference

CSYTAB.CTSCRA FPSUGD.P3IRE1-P3IRE3, P3PAIN XXVIIT.IIPAR1.-; APS130MI

XFI100MI/GetHead2 and LstInvByPayDate GetReference The field indicates the Invoice reference if used for the payment method (APS130MI.GetHead2.SCRA).

Supplier payments (TPPR=0):

- If value 0: No value to be included (tagg not created).
- If value 1: Invoice ref 1 (IRE1) included.
- If value 2: Invoice ref 1 and 2 (IRE1+IRE2) included.
- If value 3: Invoice ref 1, 2 and 3 (IRE1+IRE2+IRE3) included.
- If value 4: Parallel invoice number (PAIN) included.
- If value 9: See country exception below.

If value 1, 2, 3, 4 or 9 and no reference found for the invoice, tagg not created.

Customer payments (TPPR=1):

- If value 0: No value to be included (tagg not created).
- If value 4: Parallel invoice number (PAIN) included.

If value 4 and no reference found for the invoice, tagg not created.

Exception if Country version (MNS100.CSVN) = FI, Supplier payments (TPPR=0) and APS130MI.GetHead2.SCRA=9:

- Invoice reference (PAR1) with Reference type (output.TTU1) = 1 retrieved from XFI100MI.GetReference (see below).
- If no record found or other reference type (output TTU1), tagg not created.

Details for XFI100MI:

- DIVI, SUNO and SINO from APS130MI.LstInvByPayDate
- STCO = VIITE (domestic reference, see (*) below for comment)
- STKY and LNCD = blank
- (*) Comment to reference types used in Finland (for documentation only):
- STCO = VIITE: Other output.TTU1 = 2, 3, 5-7 exists but must not be included.
- STCO = INFOA: Is used for foreign reference (output.TTU1 = blank) exists but must not be included.

CreditTransfer/CreditTransferPayment/PaymentTransaction/Description

FPSUGD.P3TX51-P3TX55; APS130MI/GetInvLineText

The field indicates the Internal comment line 1-5 (TX51-TX55 without blanks) when single payments (grouped payments = 0-Not grouped) is used.

CreditTransfer/CreditTransferPayment/PaymentTransaction/Note FPSUGD.P3PRPN + P3PYON + P3PDNB + P3SPYN: APS130MI/

FPSUGD.P3PRPN + P3PYON + P3PDNB + P3SPYN; APS130MI/ LstInvByPayDate The field indicates the Note that is only used for country and/or format specific information.

Exception if Country version (MNS100.CSVN) = CZ and SK: Payment proposal number (PRPN), Payment order number (PYON),

Document number (PDNB) and Payee (SPYN) - format

11111111112222233333-ÁAAAAAÁAAÀ.

- Payment proposal number (PRPN) is padded with zeros to length 10.
- Payment document number (PYON) is padded with zeros to length 5.
- Document number (PDNB) is padded with zeros to length 5.
- Payee (SPYN) with separator '-' added in front.

CreditTransfer/CreditTransferPayment/CreditTransferAgreement/CreditTransferType

CSYTAB

or

CBANVA.BVBAVA.CTSLVC, CTSLCS and CTSLCE; APS130MI

or

CRS693MI/GetHead2

or

GetBasicData

The field indicates the Service level code depending on setting on Payment method:

- If Service level code (SLVC) 0-Not used and ELET = 'SEPA-CT': Set to 'SEPA'.
- If Service level code (SLVC) 0-Not used and other/blank ELET: Element not created.
- If Service level code (SLVC) 1-Standard value: Set to Srv Ivl cd Std (SLCS).
- If Service level code (SLVC) 2-Currency control: Set to Srv IvI cd Std (SLCS) if APS130MI.GetHead.CUCD = EUR, otherwise to Srv IvI cd Exc (SLCE).
- If Service level code (SLVC) 3-SEPA extended control (payment level): Set to Srv IvI cd - Std (SLCS) if only SEPA payments included (see (*) below), otherwise to Srv IvI cd - Exc (SLCE)
- If Service level code (SLVC) 4-SEPA extended control (transaction level): Element not created on this level (instead handled on PaymentTransaction level).
- (*) Extended control for only SEPA payments included in the CreditTransferPayment level:
- If APS130MI.GetHead2.CUCD = EUR and
- If country APS130MI.GetHead2.SEPB = 1 (IBAN for SEPA country) and
- If APS130MI.LstPayeeTotal3.SEPB = 1 (IBAN for SEPA country) for all suppliers or customers.

Exception if Electronic format (APS130MI.GetHead2.ELET) = SEPA-CT or SEPA-CTMIX:

Service level code retrieved according to the following priority:
1) Value (BAVA) from CRS693.GetBasicData with BKTP = 01 (see comment (a) below) for additional field (BVTP = 019).
2) If the above value not exists: From payment method.

(a) Value (BAVA) from CRS693 is retrieved for the company's bank account using CRS693MI.GetBasicData with BKTP=01, BKID=APS130MI.GetHead2.BKID and BVTP as described above. Retrieved from company/division level.

CreditTransfer/CreditTransferPayment/CreditTransferAgreement/PriorityCode

CBANAC.BCPITY; APS130MI/GetHead2

The field indicates the Priority code (PITY) of the company's bank account

This code has to be translated:

- PITY = 01: 'NORMAL'
- PITY = 02: 'HIGH'
- PITY = 03: 'URGENT'
- PITY = 04: 'LOW'

Not included if value 00 (not used).

@listID

-.-; -/-

Set to 'Priorities'.

CreditTransfer/CreditTransferPayment/CreditTransferAgreement/LocalInstrumentCode

CBANVA.BVBAVA.-; CRS693MI/GetBasicData

The field indicates the type of Payment required by banks (company) retrieved according to the following priority:

- 1) Value (BAVA) from CRS693 (*) for field (BVTP = 504).
- 2) Value (BAVA) from CRS693 (*) for field (BVTP = 601).
- (*) Value (BAVA) from CRS693 is retrieved for the company's bank account using CRS693MI.GetBasicData with BKTP=01, BKID=APS130MI.GetHead2.BKID and BVTP as described above.

CreditTransfer/CreditTransferPayment/CreditTransferAgreement/CategoryPurposeCode

CBANAC.BCCPCO; APS130MI/GetHead2

The field indicates the Category purpose code (CPCO) of the company's bank account.

NB: Exist also on 'CreditTransferPayment/PaymentTransation/ CreditTransferAgreement' level where information from the supplier's or customer's bank account is retrieved.

CurrencyExchangeRateMaster CurrencyExchangeRateMaster/IDs/ID The field indicates an ID. The ID is a concatenation of the fields CCURRA.CUCUCD CCURRA.CULOCD currency (CUCD), local currency (LOCD) and validity date (CUTD) CCURRA.CUCUTD where CUCD consists of 3 characters, LOCD 3 characters and CUTD .; CRS055MI/LstRatesPerType 8 characters. @accountingEntity CCURRA.CUCONO The field indicates the company and division. CCURRA.CUDIVI.; / @variationID The field indicates the variation ID. @lid The field indicates the logical ID. CurrencyExchangeRateMaster/LastModificationDateTime CCURRA.CUIDLMTS; The field indicates the date and time the record was last modified. CurrencyExchangeRateMaster/LastModificationPerson/IDs/ID CCURRA.CUCHID; / The field indicates the last person who modified. @accountingEntity CCURRA.CUCONO The field indicates the company and division, displayed as CCURRA.CUDIVI CONO DIVI. CurrencyExchangeRateMaster/DocumentDateTime CCURRA.CURGDT The field indicates the entry date and time when the record first was CCURRA.CURGTM.; CurrencyExchangeRateMaster/CurrencyExchangeRate/SourceCurrencyCode CCURRA.CUCUCD; CRS055MI/LstRatesPerType The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards CurrencyExchangeRateMaster/CurrencyExchangeRate/TargetCurrencyCode CCURRA.CULOCD; CRS055MI/LstRatesPerType The field indicates the currency relative to which the currency rate is given. Normally this is the local currency for the division. However, in an EMU installation in status 2, the rate is always stated towards the Monetary Union currency. CurrencyExchangeRateMaster/CurrencyExchangeRate/RateNumeric CCURRA.CUARAT; CRS055MI/LstRatesPerType The field indicates the exchange rate for the chosen currency. If Currency conversion method (DMCU) is set to Multiplication, the value is retrieved directly from the Exchange rate (ARAT). If Currency conversion method (DMCU) is set to Division, the value is computed as 1/Exchange rate (ARAT). Rate factor (RAFA) is considered in the computation. CurrencyExchangeRateMaster/CurrencyExchangeRate/SetDateTime CCURRA.CUCUTD; CRS055MI/LstRatesPerType The field indicates the date from which the registered data becomes valid. CurrencyExchangeRateMaster/CurrencyExchangeRate/EffectiveTimePeriod/StartDateTime CCURRA.CUCUTD; CRS055MI/LstRatesPerType The field indicates the start date from which the registered data becomes valid. CurrencyExchangeRateMaster/CurrencyExchangeRate/EffectiveTimePeriod/EndDateTime CCURRA.CUCUTD - 1day; CRS055MI/LstRatesPerType The field indicates the end date until which the registered data becomes valid. End date of the current record is determined by retrieving the CUTD value of the succeeding record minus 1 day. For the last record, set to December 31, 2099 (991231) by default CurrencyExchangeRateMaster/DecimalPlacesNumeric CSYTAB.YQDCCD; CRS175MI/GetGeneralCode The field indicates the number of decimal places to be used for the respective currency. Permitted values are 0-2. CurrencyExchangeRateMaster/CurrencyRateTypeReference/DocumentID/ID CCURRA.CUCRTP; CRS055MI/LstRatesPerType The field indicates the exchange rate type, such as variable rate, budget exchange rate, or rate used for group consolidation.

rate deviates more than the entered percentage.

The information is only relevant for the functions where manual entry

CurrencyExchangeRateMaster/Tolerance

CSYTAB.YQADPR; CRS175MI/GetGeneralCode

lists

Exchange rate types are used for budgeting and annual financial statements and can be connected to customers, suppliers, and price

The field indicates the accepted deviation when rate is entered or changed manually in connection with transaction entry. The information is entered as a percentage for each currency.

or change of currency rate is allowed.

A warning is displayed at entry of transactions if the manually entered

CurrencyRateType

CurrencyRateType/DocumentID/ID CSYTAB.CTSTKY; /	The field indicates the exchange rate type, such as variable rate, budget exchange rate, or rate used for group consolidation.
@accountingEntity CSYTAB.CTCONO CSYTAB.CTDIVI.; /	Constant value (STCO) = CRTP The field indicates the company and division, displayed as CONO DIVI.
@variationID	The field indicates the sequence number that identifies the number of times the BOD has been published.
@lid	The field indicates the logical ID of the system.
CurrencyRateType/LastModificationDateTime CSYTAB.CTLMTS; /	The field indicates when the most recent change to the exchange rate type was made.
CurrencyRateType/LastModificationPerson/IDs/ID CSYTAB.CTCHID; /	The field indicates the user ID associated with the most recent change to the exchange rate type.
@accountingEntity CSYTAB.CTCONO CSYTAB.CTDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
CurrencyRateType/DocumentDateTime CSYTAB.CTRGDT CSYTAB.CTRGTM.; /	The field indicates the creation date. It is a concatenation of RGDT and RGTM.
CurrencyRateType/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCode	The field indicates the description of the currency rate type.
CurrencyRateType/Status/Code	Set to "Open".
@listID	Set to "Currency Rate Type Status".
CurrencyRateType/Name CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the currency rate type description.
CurrencyRateType/ShortName CSYTAB.CTTX15; CRS175MI/GetGeneralCode	The field indicates the currency rate type name.

CustomerPartyMaster

<u>Customer Fartywaster</u>	
CustomerPartyMaster/PartyIDs/ID OCUSMA.OKCUNO; CRS610MI/GetBasicData	The field indicates the customer number.
@accountingEntity OCUSMA.OKCONO	The field indicates the accounting entity.
CMNDIV.CCDIVI.; /	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@variationID	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field indicates the logical ID of the system.
CustomerPartyMaster/PartyIDs/DisplayID OCUSMA.OKCUNO; CRS610MI/GetBasicData	The field indicates the customer number.
CustomerPartyMaster/PartyIDs/TaxID	TI (III II I I I I I I I I I I I I I I
OCUSMA.OKCORG OCUSMA.OKCOR2 OCUSMA.OKVRNO OCUSMA.OKVTCD CCUDIV.OKVTCD.; CRS610MI/GetFinancial	The field indicates the Organization number (CORG), Organization number 2 (COR2), VAT registration number (VRNO), VAT Code (VTCD).
@schemeName	Set to 'CountryIdentificationNumber2' if PartyIDs/TaxID is CORG. Set to 'CountryIdentificationNumber2' if PartyIDs/TaxID is COR2. Set to 'TaxIdentificationNumber' if PartyIDs/TaxID is VRNO. Set to 'VatCode' if PartyIDs/TaxID is VTCD.
CustomerPartyMaster/LastModificationDateTime OCUSMA.OKLMTS; /	The field indicates the date and time the object was last modified.
CustomerPartyMaster/LastModificationPerson/IDs/ID OCUSMA.OKCHID; /	The field indicates the User ID of the person who last modified the record.
@accountingEntity OCUSMA.OKCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity.
GNINETV.GGETVI., /	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
CustomerPartyMaster/LastModificationPerson/Name CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates the name of the person who last modified the record.
CustomerPartyMaster/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the customer name.
	NB: If the agreement control property 'm3beCustomerName' is activated (true) and the customer number (CUNO) is defined in the field 'M3 data' (MVXD) in the generic data translation 'CustomerName' (on division level), the customer name (CUNM) and address line 1 (CUA1) is concatenated with one blank between.
CustomerPartyMaster/Location/Address	
@type	Set to 'text'.
CustomerPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the customer's contact person.
CustomerPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2	The field indicates the address line.
OCUSMA.OKCUA3 OCUSMA.OKCUA4. ; CRS610MI/GetBasicData	NB: If the agreement control property 'm3beCustomerName' is activated (true) and the customer number (CUNO) is defined in the field 'M3 data' (MVXD) in the generic data translation 'CustomerName' (on division level), the address line 1 (CUA1) is instead populated as part of the Name.
@sequence	The field indicates the address line sequence.
	NB: See AddressLine above for comment about sequence number 1 (field CUA1).
CustomerPartyMaster/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the city name.
CustomerPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/GetBasicData	The field indicates an area, province or state within a country.
@listID	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).

CustomerPartyMaster

Oustonien artymaster	
	Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
CustomerPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/GetBasicData	The field indicates the country code.
@listID	Set to 'Countries'.
CustomerPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates the postal code.
CustomerPartyMaster/Location/Address/Preference/Indicator	Set to 'true'.
CustomerPartyMaster/Communication	out to true.
@preferredIndicator	Set to 'false'.
CustomerPartyMaster/Communication/ChannelCode	Set to Talse .
-	Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
CustomerPartyMaster/Communication/UseCode	Set to "Office" if telephone number 1, 2 or e-mail address.
@listID	Set to 'Communication Use Codes'.
CustomerPartyMaster/Communication/DialNumber	Set to Communication use codes.
OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO.; CRS610MI/GetBasicData	The field indicates the telephone number 1, telephone number 2 or facsimile number.
CustomerPartyMaster/Communication/URI	T. C.I.: P. 4. 4. 7. 11.
CEMAIL.CBEMAL; CRS610MI/GetBasicData CustomerPartyMaster/Communication/Preference/Indicator	The field indicates the e-mail address.
- Customerr artymaster/ Communication// Tereference/marcator	Set to 'false'.
CustomerPartyMaster/Contact/ID CCUCON.CCCNPE; CMS055MI/LstConnection @accountingEntity	The field indicates the contact ID.
OCUSMA.OKCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity.
GWINDIV.GGBTVI., /	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
CustomerPartyMaster/PaymentTermID OCUSMA.OKTEPY CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo	The field indicates the payment term.
CustomerPartyMaster/PaymentTermCode OCUSMA.OKTEPY CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo	The field indicates the payment term.
@listID	Set to 'Payment Term'
CustomerPartyMaster/PaymentMethodCode OCUSMA.OKPYCD; CRS610MI/GetFinancial	The field indicates the AR payment method. The payment method code is translated in CRS881 (e.g. Cash, Cheque). If no translation exist in CRS881, the following translation is followed based on the payment class: Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1. Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5. Set to 'Factoring' if payment class (PYCL) is 6.
CustomerPartyMaster/Description OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the customer name.
CustomerPartyMaster/UserArea/Property/NameValue 1) OCUSMA.OKCFC1 2) OCUSMA.OKCFC2 3) OCUSMA.OKCFC3 4) OCUSMA.OKCFC4	The field indicates a user-defined values but should be setup in CRS191. Set attribute name to "ItemFreeField1".
5) OCUSMA.OKCFC5 6) OCUSMA.OKCFC6 7) OCUSMA.OKCFC7 8) OCUSMA.OKCFC8 9) OCUSMA.OKCFC9 10) OCUSMA.OKCFC0.; CRS610MI/GetBasicData	2) The field indicates a user-defined values. Set attribute name to "ItemFreeField2".3) The field indicates a user-defined values but should be setup in CRS193.Set attribute name to "ItemFreeField3".

9) OCUSMA.OKPLTB

CRS610MI/GetOrderInfo

10) OCUSMA.OKTXAP CĆUDIV.OKTXAP

CRS610MI/GetFinancial

11) CSYTXL.TLTX60 CRS980MI/SItTxtBlock

CCUDIV.OKPLTB

CustomerPartyMaster 4) The field indicates a user-defined values but should be setup in CRS194 Set attribute name to "ItemFreeField4". 5) The field indicates a user-defined values but should be setup in CRS195. Set attribute name to "ItemFreeField5". 6) The field indicates a user-defined values but should be setup in Set attribute name to "ItemFreeField6". 7) The field indicates a user-defined values. Set attribute name to "ItemFreeField7". 8) The field indicates a user-defined values but should be setup in CRS198. Set attribute name to "ItemFreeField8". 9) The field indicates a user-defined values but should be setup in CRS199 Set attribute name to "ItemFreeField9". 10) The field indicates a user-defined values but should be setup in CRS190. Set attribute name to "ItemFreeField10". 11) The field indicates the BODID from the sending application. Set attribute name to "ProcessBODID" CustomerPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData The field indicates the status of the customer. Set to 'Pending' if status is 10 or 12. Set to 'Open' if status is 20. Set to 'Closed' if status is 90. If customer is deleted in CRS610, status is set to 'Deleted'. CustomerPartyMaster/CurrencyCode OCUSMA.OKCUCD; CRS610MI/GetBasicData The field indicates the currency code. @listID Set to 'Currency'. CustomerPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP The field indicates the Classification. CRS610MI/GetBasicData 1) Customer Types 2) OCUSMA.OKTEDL The field indicates the type of customer. CCUDIV.OKTEDL Set attribute listID to "Customer Types'. CRS610MI/GetOrderInfo 2) Incoterms 3) OCUSMA.OKSDST The field indicates delivery terms, which indicate when the CRS610MI/GetOrderInfo responsibility for the transport is transferred from supplier to customer. Set attribute listID to "Incoterms'. 4) OCUSMA.OKTINC CRS610MI/GetOrderInfo The field indicates the district the customer or payer belongs to. 5) OCUSMA.OKBLCD CRS610MI/GetFinancial Set attribute listID to 'District'. 6) OCUSMA.OKLHCD 4) VAT Included CRS610MI/GetBasicData Set to '1' if sales price include VAT. Set attribute listID to 'Vat Included'. 7) OCUSMA.OKCUCL CRS610MI/GetOrderInfo 5) Customer Stop The field indicates whether customer order entry and printing of 8) OCUSMA.OKDIGC picking lists should be blocked for a customer with this associated CCUDIV.OKDIGC payer. Set attribute listID to 'Customer Stop'. CRS610MI/GetOrderInfo

Alternatives:

Set to 'Not blocked' if 0. Set to 'Block partially' if 1. Set to 'Block CO' if 2. Set to 'Block CO EQM' if 3.

6) Language

The field is used for each customer to indicate which language should be used on external documents when corresponding with customers. Set attribute listID to 'Language'.

143

CustomerPartyMaster

12) OCUSMA OKFALO CRS610MI/GetBasicData

13) OCUSMA.OKULZO CRS610MI/GetOrderInfo

14) OCUSMA.OKFACI CRS610MI/GetOrderInfo

15) OCUSMA OKSPI M CRS610MI/GetOrderInfo

16) OCUSMA.OKAGCH CRS610MI/GetOrderInfo

17) OCUSMA.OKAGCT CRS610MI/GetOrderInfo

18) OCUSMA.OKMCOS CRS610MI/GetBasicData

19) OCUSMA.OKVTCD CĆUDIV.OKVTCD CRS610MI/GetFinancial

20) OCUSMA.OKPYCD CRS610MI/GetFinancial

@sequence

@listID

21) OCUSMA.OKMODL CRS610MI/GetOrderInfo.; / 7) Customer Groups

The field indicates the Customer Group. Set attribute listID to 'Customer Groups'.

8) Customer Discount Droups

The field indicates the Customer discount groups. Set attribute listID to 'Customer Discount Groups'.

9) Price List tables

The field indicates the Price list table. Set attribute listID to 'Price List tables'.

10) Tax Applicable

The field indicates the Tax applicable. Set attribute listID to 'Tax Applicable'.

Alternatives: Set to 'No' if 0.

Set to 'Yes' if 1.

Set to 'VAT Exempt' if 2.

11) Text

The field indicates the text. Set attribute listID to 'Text'.

12) EAN Location Code

The field indicates the EAN (European Article Numbering) code for a company. The code is issued by the local EAN organization. Set attribute listID to 'EAN Location Code'.

13) Unloading zone

The field indicates whether to divide a place of unloading into several different zones.

Set attribute listID to 'Unloading Zone'.

14) Facility

The field indicates the facility.

Set attribute listID to 'Site'.

15) Supply Model

The field indicates the supply model. Set attribute listID to 'Supply Model'.

16) Agreement check in order header

The field indicates how the blanket agreement is retrieved in the order head during CO entry.

Set attribute listID to 'Agreement Check-Order Header'.

17) Agreement check in order line

The field indicates how the blanket agreement is retrieved in the order line during CO entry.

Set attribute listID to 'Agreement Check-Order Line'.

18) Customer Order number mandatory

The field indicates if the customer's order number must be entered. Set attribute listID to 'CO Number Mandatory'.

19) VAT Code

The field indicates the VAT Code. Set attribute listID to 'VAT Code'.

20) AR Payment Method

The field indicates the AR payment method.

Set attribute listID to 'Payment Method'.

21) Transportation Method

The fields indcates the delivery method.

Set attribute listID to 'Transportation Method'.

The field indicates the sequence number for the ordering of elements within

a document.

The field indicates the Classification code listID.

- 1) Set to 'Customer Types' if Classification/Codes/Code is CUTP. 2) Set to 'Incoterms' if Classification/Codes/Code is TEDL.
- 3) Set to 'District' if Classification/Codes/Code is SDST.
- 4) Set to 'VAT Included' if Classification/Codes/Code is TINC.
- 5) Set to 'Customer Stop' if Classification/Codes/Code is BLCD. 6) Set to 'Language' if Classification/Codes/Code is LNCD.

	7) Set to 'Customer Group' if Classification/Codes/Code is CUCL.
	8) Set to 'Customer discount groups' if Classification/Codes/Code is DIGC.
	 9) Set to 'Price list tables' if Classification/Codes/Code is PLTB. 10) Set to 'Tax Applicable' if Classification/Codes/Code is CUTP. 11) Set to 'Text' if Classification/Codes/Code is TX60. 12) Set to 'EAN Location Code' if Classification/Codes/Code is EALO 13) Set to 'Unloading Zone' if Classification/Codes/Code is ULZO. 14) Set to 'Site' if Classification/Codes/Code is FACI. 15) Set to 'Supply Model' if Classification/Codes/Code is SPLM. 16) Set to 'Agreement Check-Order Header' if Classification/Codes/Code is AGCH. 17) Set to 'Agreement Check-Order Line' if Classification/Codes/Code is AGCT. 18) Set to 'CO Number Mandatory' if Classification/Codes/Code is
	MCOS. 19) Set to 'VAT Code' if Classification/Codes/Code is VTCD. 20) Set to 'Payment Method' if Classification/Codes/Code is PYCD 21) Set to 'Transportation Method' if Classification/Codes/Code is MODL.
CustomerPartyMaster/DefaultShipFromWarehouseLocation/ID OCUSMA.OKWHLO	The field indicates the default ship from werehouse (MILLO) when
CCUDIV.OKWHLO.; CRS610MI/GetOrderInfo @accountingEntity	The field indicates the default ship-from warehouse (WHLO) when shipping to this customer.
OCUSMA.OKCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity.
	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
CustomerPartyMaster/CustomerAccount/TotalCreditLimitAmount OCUSMA.OKCRLM OCUSMA.OKCRL2	The field indicates the highest credit limit for the customer.
OCUSMA.OKCRL3.; CRS610MI/GetFinancial	Use Credit limit 3 (CRL3) if value exists. If CRL3 is blank, use Credit limit 2 (CRL2) if value exists. If CRL3 and CRL2 is blank, use Credit limit (CRLM) if value exists.
@currencyID OCUSMA.OKCUCD CCUDIV.OKCUCD.; CRS610MI /GetFinancial	Set to 'Currency'.
CustomerPartyMaster/SalesPersonReference/IDs/ID 1) OCUSMA.OKSMCD CCUDIV.OKSMCD 2) OCUSMA.OKRESP.; CRS610MI/GetOrderInfo @accountingEntity	The field indicates the person responsible for sales to a customer. The field indicates who is responsible for the customer.
OCUSMA.OKCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity.

If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

CustomerPartyMaster/SalesPersonReference/Name

CSYTAB.CTTX40 CRS100MI/Get

OCUSMA.OKRESP MNS150/GetUserData 1) The field indicates the full name of the current identity.

2) The field indicates the responsible name.

CustomerPartyMaster/SalesPersonReference/SalesPersonRole

The field indicates the Sales person reference role.

Set 'External' if SMCD. Set 'Internal' if RESP.

Set to 'Sales Person Roles'.

@listID

CustomerReturn/CustomerReturnHeader/DocumentID/ID OCHEAD.OCREPN; /	The field indicates the receiving number of a customer return.
@accountingEntity OCHEAD.OCCONO	The field indicates the company and division, displayed as
OCHEAD.OCDIVI.; / @location	CONO_DIVI.
OCHEAD.OCWHLO; / @variationID	The field indicates the warehouse.
@lid	The field indicates the sequence number that identifies the number of times that the BOD has been published.
	The field indicates the logical ID of the system.
CustomerReturn/CustomerReturnHeader/AlternateDocumentID/ID OCHEAD.OCORNO; OIS390MI/GetHead @accountingEntity	The field indicates the customer order number.
OCHEAD.OCCONO OCHEAD.OCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
CustomerReturn/CustomerReturnHeader/DisplayID OCHEAD.OCREPN; OIS390MI/GetHead	The field indicates the receiving number which identifies a customer return.
CustomerReturn/CustomerReturnHeader/LastModificationDateTime OCHEAD OCLINE.OCLMTS	The field indicates when a change was last made to the record.
ODLMDT; /	If Timestamp (LMTS) is not available, use Change date (LMDT).
CustomerReturn/CustomerReturnHeader/LastModificationPerson/IDs. OCHEAD.OCCHID; / @accountingEntity	The field indicates the last person who modified.
OCHEAD.OCCONO OCHEAD.OCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
CustomerReturn/CustomerReturnHeader/DocumentDateTime OCHEAD.OCRGDT OCHEAD.OCRGTM.; /	The field indicates the document date and time.
CustomerReturn/CustomerReturnHeader/Description CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the transaction reason description.
CustomerReturn/CustomerReturnHeader/DocumentReference @type	
OCHEAD.OCRORC; OIS390MI/GetHead	 Set to 'ProductionOrder' if reference order category 1. Set to 'PurchaseOrder' if reference order category 2. Set to 'SalesOrder' if reference order category 3. Set to 'RequisitionOrder' if reference order category 4. Set to 'ServiceOrder' if reference order category 6. Set to 'ServiceOrder' if reference order category 7.
CustomerReturn/CustomerReturnHeader/DocumentReference/Document	
OCHEAD.OCORNO; OIS390MI/GetHead @accountingEntity OCHEAD.OCCONO	The field indicates the reference order number. The field indicates the company and division, displayed as
OCHEAD.OCDIVI.; / @location OCHEAD.OCWHLO; OIS390MI/GetHead	CONO_DIVI. The field indicates the warehouse.
CustomerReturn/CustomerReturnHeader/Status/Code	The field findicates the wateriouse.
OCHEAD .OCRESH; OIS390MI/GetHead	The field indicates the highest status (RESH) customer order return. Set to 'Open' if highest status - customer order return is equals to 11 and higest status - credit is equals to 2.
	Set to 'PartiallyReceived' if highest status - customer order return is equals to 12 , 13 and higest status - credit is equals to 2.
	Set to 'Received' if highest status - customer order return is equals to 22, 23, 33 and higest status - credit is equals to 2.
	Set to 'Credited' if highest status - customer order return is equals to 11, 12, 13, 22, 23, 33 and highest status - credit is equals to 2.
CustomerReturn/CustomerReturnHeader/CustomerParty/PartyIDs/ID OCHEAD.OCCUNO; OIS390MI/GetHead @accountingEntity	The field indicates the customer number.
OCHEAD.OCCONO OCHEAD.OCDIVI.; /	The field indicates the company and division.
55E. 5.55514, /	If Master AE is enabled for the CustomerPartyMaster in the BOD Processor, the attribute will only display the company (e.g., '770'). Otherwise, it will display company and division (e.g., '770 AAA').
CustomerReturn/CustomerReturnHeader/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the customer name.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/Ad@type	dress
	Set to 'text'.

CustomerReturn/CustomerReturnHeader/CustomerParty/Location/	
OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the contact person.
CustomerReturn/CustomerReturnHeader/CustomerParty/Location/ OCUSMA.OKCUA1 OCUSMA.OKCUA2	Address/AddressLine The field indicates the address line.
OCUSMA.OKCUA3 OCUSMA.OKCUA4.; CRS610MI/GetBasicData	
sequence	The field indicates the address line sequence.
ustomerReturn/CustomerReturnHeader/CustomerParty/Location// OCUSMA.OKTOWN; CRS610MI/GetBasicData	Address/CityName The field indicates the city name.
ustomerReturn/CustomerReturnHeader/CustomerParty/Location/ OCUSMA.OKECAR; CRS610MI/GetBasicData DistID	Address/CountrySubDivisionCode The field indicates a state or province within a country.
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
ustomerReturn/CustomerReturnHeader/CustomerParty/Location/ OCUSMA.OKCSCD; CRS610MI/GetBasicData DistID	Address/CountryCode The field indicates the country code.
	Set to 'Countries'.
ustomerReturn/CustomerReturnHeader/CustomerParty/Location// OCUSMA.OKPONO; CRS610MI/GetBasicData	Address/PostalCode The field indicates the postal code.
ustomerReturn/CustomerReturnHeader/ShipToParty/Location Otype	
	Set to 'Site'
ustomerReturn/CustomerReturnHeader/ShipToParty/Location/ID OOHEAD.OAFACI; OIS100MI/GetOrderHead	The field indicates the facility.
ustomerReturn/CustomerReturnHeader/ShipToParty/Location/Nar CFACIL.CFFACN; CRS008MI/Get	The field indicates the facility name.
ustomerReturn/CustomerReturnHeader/PayFromParty/PartyIDs/ID OCHEAD.OCPYNO; OIS390MI/GetHead accountingEntity	The field indicates the customer ID who receives the invoice.
OCHEAD.OCCONO OCHEAD.OCDIVI.; /	The field indicates the company and division.
CONLINE.CODIVI., /	If Master AE is enabled for the PayFromPartyMaster in the BOD Processor, the attribute will only display the company (e.g., '770'). Otherwise, it will display company and division (e.g., '770 AAA').
ustomerReturn/CustomerReturnHeader/PayFromParty/Location/N OCUSMA.OKCUNM; CRS610MI/GetBasicData	lame The field indicates the customer who receives the invoice.
ustomerReturn/CustomerReturnHeader/PayFromParty/Location/A @type	
triata ma uPatrium/Criata ma uPatrium/La adau/PariFua m Pautri/La aatia m/A	Set to 'text'.
ustomerReturn/CustomerReturnHeader/PayFromParty/Location/A OCUSMA.OKYREF; OIS100MI/GetAddress	The field indicates the contact person.
tustomerReturn/CustomerReturnHeader/PayFromParty/Location/A OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3	ddress/AddressLine The field indicates the address line.
OCUSMA.OKCUA4.; OIS100MI/GetAddress	
was to a supplied to the suppl	The field indicates the address line sequence.
ustomerReturn/CustomerReturnHeader/PayFromParty/Location/A OCUSMA.OKTOWN; OIS100MI/GetAddress	ddress/CityName The field indicates the city name.
ustomerReturn/CustomerReturnHeader/PayFromParty/Location/A OCUSMA.OKECAR; OIS100MI/GetAddress DistID	ddress/CountrySubDivisionCode The field indicates an area, province or state within a country.
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
tustomerReturn/CustomerReturnHeader/PayFromParty/Location/A OCUSMA.OKCSCD; OIS100MI/GetAddress DistID	The field indicates the country code.
customerReturn/CustomerReturnHeader/PayFromParty/Location/A	Set to 'Countries'.
OCUSMA.OKPONO; OIS100MI/GetAddress	The field indicates the postal code.
tustomerReturn/CustomerReturnHeader/TransportationTerm/Incot OOHEAD.OATEDL; OIS100MI/GetOrderHead DistID	termsCode The field indicates delivery terms.

Oddiomentetam	
O 4	Set to 'Incoterms'.
CustomerReturn/CustomerReturnHeader/PaymentTerm/Term/ID OOHEAD.OATEPY; OIS100MI/GetOrderHead	The field indicates the payment term.
CustomerReturn/CustomerReturnHeader/PaymentTerm/Term/Descrip CSYTAB.CTTX40; CRS175MI/GetGeneralCode	otion The field indicates the payment term description.
CustomerReturn/CustomerReturnHeader/PromisedReturnDateTime OCHEAD.OCEPDT; OIS390MI/GetHead	The field indicates the promised return date time.
CustomerReturn/CustomerReturnHeader/RequiredReturnDateTime OCHEAD.OCEPDT; OIS390MI/GetHead	The field indicates the required return date time.
CustomerReturn/CustomerReturnHeader/ReturnReasonCode OCHEAD.OCRSCD; OIS390MI/GetHead	The field indicates the transaction reason code.
CustomerReturn/CustomerReturnLine/LineNumber OCLINE.ODRELI; OIS390MI/LstLine	The field indicates a line number.
CustomerReturn/CustomerReturnLine/Description CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the transaction reason description.
CustomerReturn/CustomerReturnLine/DocumentReference	
@type OCLINE.ODRORC; OIS390MI/LstLine	1) Set to 'ProductionOrder' if reference order category 1. 2) Set to 'PurchaseOrder' if reference order category 2. 3) Set to 'SalesOrder' if reference order category 3. 4) Set to 'RequisitionOrder' if reference order category 4. 5) Set to 'ServiceOrder' if reference order category 6. 6) Set to 'ServiceOrder' if reference order category 7.
CustomerReturn/CustomerReturnLine/DocumentReference/Documer	ntID/ID
OCLINE.ODORNO; OIS390MI/LstLine	The field indicates the customer order number.
@accountingEntity OCHEAD.OCCONO OCHEAD.OCDIVI.; / @location	The field indicates the company and division, displayed as CONO_DIVI.
OCLINE.ODWHLO; OIS390MI/LstLine	The field indicates the warehouse.
CustomerReturn/CustomerReturnLine/DocumentReference/LineNum OCLINE.ODPONR; OIS390MI/LstLine	ber The field indicates line number.
CustomerReturn/CustomerReturnLine/DocumentReference/SubLinel	
OCLINE.ODPOSX; OIS390MI/LstLine	The field indicates subline number.
CustomerReturn/CustomerReturnLine/Status/Code OCLINE.ODREST; OIS390MI/GetLine	The field indicates the status (REST) customer order return. Set to 'Open' if status - customer order return is equals to 11 and status - credit is equals to 2.
	Set to 'PartiallyReceived' if status - customer order return is equals to 12, 13 and status - credit is equals to 2.
	Set to 'Received' if status - customer order return is equals to 22, 23, 33 and status - credit is equals to 2.
	Set to 'Credited' if status - customer order return is equals to 11, 12, 13, 22, 23, 33 and status - credit is equals to 2.
CustomerReturn/CustomerReturnLine/Item/Item/D/ID OCLINE.ODITNO; OIS390MI/LstLine	The field indicates the item number.
@accountingEntity OCHEAD.OCCONO OCHEAD.OCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
CustomerReturn/CustomerReturnLine/Item/Description MITMAS.MMFUDS; MMS200MI/GetItmBasic	The field indicates the description of the item.
CustomerReturn/CustomerReturnLine/Item/SerializedLot/Lot/LotIDs/I	·
OCLINE.ODBANO; OIS390MI/LstLine	The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item.
CustomerReturn/CustomerReturnLine/Item/SerializedLot/SerialNumb OCLINE.ODBANO; OIS390MI/LstLine	per The field indicates the unique serial number assigned by the manufacturer.
CustomerReturn/CustomerReturnLine/Quantity OCLINE.ODREQ1; OIS390MI/GetLine @unitCode	The field indicates the returned quantity.
OCLINE.ODUNMS; OIS390MI/GetLine	The field indicates the unit of measure.
CustomerReturn/CustomerReturnLine/BaseUOMQuantity OCLINE.ODREQ1; OIS390MI/GetLine @unitCode	The field indicates the quantity in basic unit of measure.
OCLINE.ODUNMS; OIS390MI/GetLine	The field indicates the basic unit of measure.
CustomerReturn/CustomerReturnLine/UnitPrice/Amount OCLINE.ODSAPR; OIS390MI/GetLine @currencyID	The field indicates the sales price.
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/UnitPrice/PerQuantity	

Customeriveturii	
OCLINE.ODSAPR; OIS390MI/GetLine	The field indicates the unit price.
@unitCode	·
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/ExtendedAmount	
1) OCLINE.ODSAPR	The field indicates the extended amount.
OIS390MI/GetLine	
2) OCLINE.ODREQ1	
OIS390MI/GetLine.; /	
@currencyID	
OCHEAD.OCCUCD; OIS390MI/GetHead	The field indicates the currency.
CustomerReturn/CustomerReturnLine/ExtendedBaseAmount	
1) OCLINE.ODCUPR	The field indicates the extended base amount.
OIS390MI/GetLine	
2) OCLINE.ODREQ1	
OIS390MI/GetLine.; /	
@currencyID	The field indicates the level currency
OCHEAD.OCCUCD; OIS390MI/GetLine	The field indicates the local currency.
CustomerReturn/CustomerReturnLine/TransportationTerm/Incote	
OOHEAD.OATEDL; OIS100MI/GetOrderHead	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
@listID	
	Set to 'Incoterms'.
CustomerReturn/CustomerReturnLine/ReturnReasonCode	
OCHEAD.OCRSCD; OIS390MI/GetLine	The field indicates the transaction reason code.

	•
	zeros to length 6. Exception if Country version (CSVN) = ES, Electronic format (ELET) = SEPA-DD and Payment class (PYCD) = 4: - Constant 'FSDD' + Remittance number (RMNB) padded with zeros
	to length 6 (format: FSDD NNNNNN).
DebitTransfer/DebitTransferHeader/DocumentDateTime FARREM.ERRMNDA; ARS300MI/GetHead2	The field indicates the Remittance date (RMDA) of the proposal.
DebitTransfer/DebitTransferHeader/Description CSYTAB.CTPARM (DSPYCD.FPELET, FPDOCU); ARS300MI/ GetHead2	The field indicates the Electronic format (ELET) and if blank, Document format (DOCU) from the Payment method (ARS300MI.GetHead2 retrieves PYCD from the first transaction (FARRED) included in the remittance proposal).
	Can be used as additional element in the detection setup for GEMS ir case different formats/messages must be created for the same bank.
DebitTransfer/DebitTransferHeader/Status/Code FARREM.ERACTO; ARS300MI/GetHead2	Set to 'Open' for confirmed payment (action code 09) and copy of payment (action code 18). Set to 'Draft' for preliminary payment (action code 08).
DebitTransfer/DebitTransferHeader/AuthorizationID CBANAC.BCBKAG; ARS300MI/GetHead2	The field indicates the Bank agreement number (BKAG) of the company's bank account.
DebitTransfer/DebitTransferHeader/TotalTransactions; -/-	The field indicates the Total number of payment transactions (counter).
DebitTransfer/DebitTransferHeader/InitiatingParty/PartyIDs/ID CBANAC.BCFICU or FARREM.ERCONO, ERDIVI; ARS300MI/ GetHead2	The field indicates the following ID's that are included for the Initiating party (company): - ID 1: Customer number at financial institution (FICU) ID 2: Creditor identifier number (CIDN). If non of the above values exists: Company/divsion (CONO_DIVI).
@schemeName ; -/-	Set to the following schemeNames used as standard: - FICU with schemeName = 'BankPartyIdentification' - CIDN with schemeName = 'CentralBankIdentificationNumber' - CONO + DIVI without schemeName.
@accountingEntity ; -/-	The field indicates the translated M3 BE company and division.
DebitTransfer/DebitTransferHeader/InitiatingParty/PartyIDs/TaxID CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2 CBANVA.BVBAVA; ARS300MI CRS693MI/GetHeadAddress GetBasicData	The field indicates the following TaxIDs included as standard with information from (MNS100): - TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable). - TaxID 2: Organization number 1 (CORG) of the company. - TaxID 3: Organization number 2 (COR2) of the company.
	Exception if Country version (MNS100.CSVN) = FR: - TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable) TaxID 2: Tax declaration number (VRNL) of the company. Exception if Country version (MNS100.CSVN) = IT: - TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as
@schemeName ; -/-	prefix if applicable) TaxID 2: CUC code (CBI identifier) (BAVA) of the company from CRS693MI.GetBasicData.BAVA for BKTP=01, BKID=ARS300MI.GetHead2.BKI2 and BVTP=011.

Set to the following schemeNames used as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

DebitTransfer/DebitTransferHeader/InitiatingParty/Name

FARREM.ERCONM

ERCOA1-COA4; ARS300MI/GetHeadAddress

The field indicates the Company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

DebitTransfer/DebitTransferHeader/InitiatingParty/Location/Name

FARREM.ERCONM

ERCOA1-COA4; ARS300MI/GetHeadAddress

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

$\label{lem:decomposition} Debit Transfer / Debit Transfer Header / Initiating Party / Location / Address \\ @type$

-.-; -/-

Set to 'text' if address information included.

DebitTransfer/DebitTransferHeader/InitiatingParty/Location/Address/AddressLine

FARREM.ERCOA1-COA4; ARS300MI/GetHeadAddress

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

@sequence

-.-; -/-

Set to sequence number of the address line: values 1-4.

Debit Transfer / Debit Transfer Header / Initiating Party / Location / Address / City Name

CMNDIV.CCTOWN; ARS300MI/GetHeadAddress

The field indicates the City name (TOWN) of company from (MNS100) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

Debit Transfer/Debit Transfer Header/Initiating Party/Location/Address/Country SubDivision Code

CMNDIV.CCECAR; ARS300MI/GetHeadAddress

The field indicates the Area/State code (ECAR) of company from (MNS100).

Generic translation is used to translate ECAR according to ISO 3166-2.

@listID

-.-; -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departments'.

Debit Transfer / Debit Transfer Header / Initiating Party/Location / Address/Country Code

CMNDIV.CCCSCD; ARS300MI/GetHeadAddress

The field indicates the Country code (CSCD) of company from (MNS100).

Generic translation is used to translate CSCD to alpha-2 country code

The field indicates the Bank number (BKNO) of the company's bank.

according to ISO 3166-2.

@listID

-.-; -/- Set to 'Countries'

DebitTransfer/DebitTransferHeader/InitiatingParty/Location/Address/PostalCode

CMNDIV.CCPONO; ARS300MI/GetHeadAddress

The field indicates the Postal code (PONO) of company from (MNS100) if available in M3 (also sent as part of AddressLine

@SequenceNumber = 3).

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/PartyIDs/ID

CBANAC.BCBKNO; ARS300MI/GetHead2

@schemeName

-.-; -/-

@accountingEntity
---; -/The field indicates the translated M3 BE company and division.

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the VAT registration number (VRN2) of the company's bank (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

Set to schemeName = 'BankPartyIdentification'.

@schemeName

-.-; -/- Set to schemeName = 'TaxIdentificationNumber'.

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/PartyIDs/BICID

CBANAC.BCSWBI or CBANMA.BKSWIC.-; ARS300MI or CRS690MI/ GetHead2 or GetBasicData The field indicates the Swift/BIC code (SWBI) of the company's bank account and if not existing, Swift code (SWIC) of the company's bank.

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Bank name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Location name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank name (BKNM)

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Address

@type

---; -/- Set to 'text' if address information included

Debit Transfer/Debit Transfer Header/Forwarding Agent Party/Location/Address/Address Line to the property of the property of

CBANMA.BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Bank address of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence

Set to sequence number of the address line: values 1-4.

DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Address/CityName

CBANMA.BKTOWN; CRS690MI/GetBasicData

Infor May 26, 2023 15.

(CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3) DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Address/CountrySubDivisionCode CBANMA.BKECAR; CRS690MI/GetBasicData The field indicates the Area/State code (ECAR) of company's bank from (CRS690). Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)). @listID Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US -.-; -/-States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departments' DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Address/CountryCode CBANMA.BKCSCD; CRS690MI/GetBasicData The field indicates the Country code (CSCD) of company's bank from (CRS690). Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166. @listID -.-; -/-Set to 'Countries' DebitTransfer/DebitTransferHeader/ForwardingAgentParty/Location/Address/PostalCode CBANMA.BKPONO; CRS690MI/GetBasicData The field indicates the Postal code (PONO) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3) DebitTransfer/DebitTransferHeader/ForwardingAgentParty/ClearingSystemMemberID CBANAC.BCCLSI + BCCLSN; ARS300MI /GetHead2 The field indicates the Clearing system member identification (CLSI+CLSN cut together) of the company's bank retrieved from the bank account. If clearing system ID (CLSI) has not been defined, only clearing system number (CLSN) is used. @schemeName Set to schemaName = 'ClearingIdentificationNumber'. -.-; -/-DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/PartyIDs/ID CBANAC.BCBBRN; ARS300MI/GetHead2 The field indicates the Bank branch number (BBRN) of the company's bank branch. @schemeName Set to schemeName = 'BankPartyIdentification'. -.-; -/-@accountingEntity The field indicates the translated M3 BE company and division -.-; -/-DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/PartyIDs/BICID CBANBR.BRSWIC; CRS691MI/GetBasicData The field indicates the Swift code (SWIC) of company's bank branch from (CRS691). DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/Name CBANBR.BRBKBM The field indicates the Bank branch name of company's bank based BRBKA1-BKA4; CRS691MI/GetBasicData on on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup). Alternative if generic translation used and code A not available: Bank branch name (BKBM). Alternative if generic translation not used: Bank branch name (BKBM). DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/Location/Name CBANBR.BRBKBM The field indicates the Bank branch name of company's bank based BRBKA1-BKA4; CRS691MI/GetBasicData on on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local ly for description of setup). Alternative if generic translation used and code A not available: Bank branch name (BKBM). Alternative if generic translation not used: Bank branch name (BKBM). DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/Location/Address @type Set to 'text' if address information included. -.-; -/-DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchParty/Location/Address/AddressLine The field indicates the Bank address of company's bank branch CBANBR.BRBKA1-BKA4; CRS691MI/GetBasicData based on the generic translation 'addressFieldType' (CRS881/882)

The field indicates the City name (TOWN) of company's bank from

Infor May 26, 2023 15

and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are usedCode E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and

			- 4 -	_		•	•	
	Δ	n	IT I	Γra	n	CI	יםי	۲
$\boldsymbol{\omega}$	┏	u		1 I A		31	•	ı

DebitTransfer/DebitTransferPayment/TotalTransactions; -/-	The field indicates the Total number of payment transactions (counter).
DebitTransfer/DebitTransferPayment/FirstAgentPaymentMethodCode; -/-	Set to value depending on payment class: - Payment class 04-Draft: Set to 'DD' Payment class 05-Direct Debiting: Set to 'DD'.
	Date used is depending on Payment class (PYCL): - If Payment class (PYCL) 04: Date = Due date (DUDT) If Payment class (PYCL) 05: Payment date (DTP5).
DebitTransfer/DebitTransferPayment/RequestedExecutionDateTime FARRED.R1DTP5, R1DUDT; ARS300MI/LstRemByPayer	The field indicates the Payment date (see below) - format YYYY-MM-DD.
@accountingEntity ; -/-	The field indicates the translated M3 BE company and division.
	The DebitTransferPayment level is created per Date (see below) and Sequence type (SQTP) using ARS300MI.LstRemByType where RMST (status) = 0: - If Payment class (PYCL) 04: Due date (DUDT). - If Payment class (PYCL) 05: Payment date (DTP5). NB: For non-SEPA messages, the Sequence type (SQTP) is blank so only one record per date is created.
DebitTransfer/DebitTransferPayment/ID FARRED.R1RMNB; ARS300MI/LstRemByPayer	The field indicates the Remittance number (RMNB) and Counter (sequence number): - Remittance number (RMNB) is padded with zeros to length 6 Counter (sequence number) is added at the end of the ID for unique key for ID per payment date (see below) and Sequence type (SQTP). Counter (sequence number) is padded with zeros to length 4 and is added with '-' in front.
DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchPar CBANBR.BRPONO; CRS691MI/GetBasicData	ty/Location/Address/PostalCode The field indicates the Postal code (PONO) of the company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
@listID ; -/-	according to ISO 3166. Set to 'Countries'.
DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchPar CBANBR.BRCSCD; CRS691MI/GetBasicData	The field indicates the Country code (CSCD) of company's bank branch from (CRS691). Generic translation is used to translate CSCD to alpha-2 country code
; -/- DebitTransfor/DebitTransforHeader/ForwardingAgentDerty/Prench Per	Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departments'.
@listID	Generic translation is used to translate ECAR according to ISO 3166-2.
DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchPar CBANBR.BRECAR; CRS691MI/GetBasicData	ty/Location/Address/CountrySubDivisionCode The field indicates the Area/State code (ECAR) of company's bank branch from (CRS691).
DebitTransfer/DebitTransferHeader/ForwardingAgentParty/BranchPar CBANBR.BRTOWN; CRS691MI/GetBasicData	· · · · · · · · · · · · · · · · · · ·
@sequence : -/-	1-4 (BKA1-BKA4). Set to sequence number of the address line: values 1-4.
	Address line 4 (BKA4) not included as not mandatory information. Alternative if generic translation not used: Bank branch address line
	Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information. Alternative if generic translation used and code J not available:
	Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.
	code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

CSYTAB.CTPARM (DSPYCD.FPBBIN); ARS300MI/GetHead2

The field indicates the Indicator for Batch booking (BBAN) as defined on the Payment method used:

- If Batch booking indicator (BBIN) = 0 or blank: Set to 'false' (default value).
- If Batch booking indicator (BBIN) = 1: Set to 'true'.
- If Batch booking indicator (BBIN) = 2: Set to 'true' if

ARS300MI.GetHead2.CUCD = ARS300MI.GetHead2.BCUC, otherwise to 'false'

DebitTransfer/DebitTransferPayment/CreditorParty/PartyIDs/ID

CBANAC.BCFICU or

BCCONO + BCDIVI; ARS300MI/GetHead2

The field indicates the following ID's included for the Creditor party

- ID 1: Customer number at financial institution (FICU).
- ID 2: Creditor identifier number (CIDN)

If non of the above values exists: Company/divsion (CONO_DIVI).

Set to the following schemeNames used as standard:

- FICU with schemeName = 'BankPartvIdentification'
- CIDN with schemeName = 'CentralBankIdentificationNumber'
- CONO + DIVI without schemeName.

@accountingEntity

@schemeName

-.-; -/-

-.-; -/-

DebitTransfer/DebitTransferPayment/CreditorParty/PartyIDs/TaxID

CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2 CBANVA.BVBAVA.-; ARS300MI

CRS693MI/GetHeadAddress

GetBasicData

The field indicates the translated M3 BE company and division.

The field indicates the following TaxIDs included as standard with information from (MNS100):

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: Organization number 1 (CORG) of the company.
- TaxID 3: Organization number 2 (COR2) of the company.

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: Tax declaration number (VRNL) of the company.

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: VAT registration number (VRN2) of the company (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).
- TaxID 2: CUC code (CBI identifier) (BAVA) of the company from CRS693MI.GetBasicData.BAVA for BKTP=01, BKID=ARS300MI.GetHead2.BKI2 and BVTP=011.

@schemeName

-.-: -/-

Set to the following schemeNames are used as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
 TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
 TaxID 2: schemeName 'CountryIdentificationNumber'

DebitTransfer/DebitTransferPayment/CreditorParty/Name

FARREM.ERCONM

ERCOA1-COA4; ARS300MI/GetHeadAddress

The field indicates the Company name based the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

DebitTransfer/DebitTransferPayment/CreditorParty/Location/Name FARREM.ERCONM

ERCOA1-COA4; ARS300MI/GetHeadAddress

The field indicates the Company name based the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

May 26, 2023

	Alternative if generic translation not used: Company name (CONM).
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address@type	
; <i>-</i> /-	Set to 'text' if address information included.
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address FARREM.ERCOA1-COA4; ARS300MI/GetHeadAddress	s/AddressLine The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).
	Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.
	Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.
	Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.
@aaguanaa	Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).
@sequence ; -/-	Set to sequence number of the address line: values 1-4.
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address CMNDIV.CCTOWN; ARS300MI/GetHeadAddress	s/CityName The field indicates the City name (TOWN) of the company from (MNS100) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address CMNDIV.CCECAR; ARS300MI/GetHeadAddress	s/CountrySubDivisionCode The field indicates the Area/State code (ECAR) of company from (MNS100).
@listID	Generic translation is used to translate ECAR according to ISO 3166-2.
; -/-	Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departments'.
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address CMNDIV.CCCSCD; ARS300MI/GetHeadAddress	s/CountryCode The field indicates the Country code (CSCD) of company from (MNS100).
@listID	Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166.
; -/-	Set to 'Countries'.
DebitTransfer/DebitTransferPayment/CreditorParty/Location/Address CMNDIV.CCPONO; ARS300MI/GetHeadAddress	s/PostalCode The field indicates the Postal code (PONO) of the company from (MNS100) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
DebitTransfer/DebitTransferPayment/CreditorParty/FinancialAccoun CBANAC.BCBACN; ARS300MI/GetHead2	t/BBANID The field indicates the Bank account number (BACN) of the company.
	NB: Not included if IBAN of the company exists (only one FinancialAccount allowed).
DebitTransfer/DebitTransferPayment/CreditorParty/FinancialAccoun CBANAC.BCIBAN; ARS300MI/GetHead2	The field indicates the International bank account number (IBAN) of the company.
DebitTransfer/DebitTransferPayment/CreditorParty/FinancialAccoun CBANAC.BCCUCD; ARS300MI/GetHead2	t/CurrencyCode The field indicates the Currency code (CUCD) of the company's bank account.
@listID	Generic translation is used to translate CUCD according to ISO 4217.
; -/- DebitTransfer/DebitTransferPayment/CreditorParty/FinancialAccoun	Set to 'Currency'. t/Name
CBANAC.BCBANA; ARS300MI/GetHead2	The field indicates the Name (BANA) of the company's bank account.
DebitTransfer/DebitTransferPayment/FirstAgentParty/PartyIDs/ID CBANAC.BCBKNO; ARS300MI/GetHead2 @schemeName	The field indicates the Bank number (BKNO) of the company's bank.
; -/-	Set to schemeName = 'BankPartyIdentification'.
Infor May 26, 20	22 15

@accountingEntity

· /

DebitTransfer/DebitTransferPayment/FirstAgentParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the translated M3 BE company and division.

The field indicates the VAT registration number (VRN2) of the

company's bank (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

@schemeName

-.-; -/-

Set to schemeName = 'TaxIdentificationNumber'

DebitTransfer/DebitTransferPayment/FirstAgentParty/PartyIDs/BICID

CBANAC.BCSWBI or CBANMA.BKSWIC.-; ARS300MI or CRS690MI/GetHead2 or GetBasicData

The field indicates the Swift/BIC code (SWBI) of the company's bank account and if not existing, Swift code (SWIC) of the company's bank.

DebitTransfer/DebitTransferPayment/FirstAgentParty/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Bank name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Location name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

 $\label{lem:decomposition} Debit Transfer Payment / First Agent Party / Location / Address \\ @type$

-.-; -/-

Set to 'text' if address information included.

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Address/AddressLine

CBANMA.BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Bank address of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used.Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence -.-; -/-

@listID

-.-: -/-

Set to sequence number of the address line: values 1-4.

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Address/CityName

CBANMA.BKTOWN; CRS690MI/GetBasicData

The field indicates the City name (TOWN) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Address/CountrySubDivisionCode

CBANMA.BKECAR; CRS690MI/GetBasicData

The field indicates the Area/State code (ECAR) of company's bank from (CRS690).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'.

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Address/CountryCode

CBANMA.BKCSCD; CRS690MI/GetBasicData

The field indicates the Country code (CSCD) of company's bank from

(CRS690).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166.

Set to 'Countries'

@listID

DebitTransfer/DebitTransferPayment/FirstAgentParty/Location/Address/PostalCode

CBANMA.BKPONO; CRS690MI/GetBasicData

The field indicates the Postal code (PONO) of company's bank from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

@Sequencervan

DebitTransfer/DebitTransferPayment/FirstAgentParty/ClearingSystemMemberID

CBANAC.BCCLSI + BCCLSN; ARS300MI/GetHead2

The field indicates the Clearing system member identification (CLSI+CLSN cut together) of the company's bank retrieved from the bank account. If clearing system ID (CLSI) has not been defined, only clearing system number (CLSN) is used.

@schemeName -.-; -/-

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/PartyIDs/ID CBANAC.BCBBRN; ARS300MI/GetHead2 The fiel

Set to schemaName = 'ClearingIdentificationNumber'.

The field indicates the Bank branch number (BBRN) of the company's

bank branch.

@schemeName

Set to schemeName = 'BankPartyIdentification'.

@accountingEntity
---; -/The field indicates the translated M3 BE company and division.

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/Party/Ds/BICID
CBANBR.BRSWIC; CRS691MI/GetBasicData
The field inc

The field indicates the Swift code (SWIC) of company's bank branch from (CRS691).

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/Name

CBANBR.BRBKBM

BRBKA1-BKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of company's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank branch name (BKBM).

Alternative if generic translation not used: Bank branch name (BKBM).

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/Location/Name

CBANBR.BRBKBM

BRBKA1-BKA4; CRS691MI/GetBasicData

The field indicates the Location name of company's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/Location/Address

@type

Set to 'text' if address information included.

DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty/Location/Address/AddressLine

CBANBR.BRBKA1-BKA4; CRS691MI/GetBasicData

The field indicates the Bank address of company's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Depitiransier	
@sequence	Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4).
; -/-	Set to sequence number of the address line: values 1-4.
DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty CBANBR.BRTOWN; CRS691MI/GetBasicData	y/Location/Address/CityName The field indicates the City name (TOWN) of company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty CBANBR.BRECAR; CRS691MI/GetBasicData	y/Location/Address/CountrySubDivisionCode The field indicates the Area/State code (ECAR) of company's bank branch from (CRS691).
Oli-AD	Generic translation is used to translate ECAR according to ISO 3166-2.
@listID ; -/-	Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departments'.
DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty CBANBR.BRCSCD; CRS691MI/GetBasicData	y/Location/Address/CountryCode The field indicates the Country code (CSCD) of company's bank branch from (CRS691).
@listID	Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166.
; -/-	Set to 'Countries'.
DebitTransfer/DebitTransferPayment/FirstAgentParty/BranchParty CBANBR.BRPONO; CRS691MI/GetBasicData	y/Location/Address/PostalCode The field indicates the Postal code (PONO) of the company's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
DebitTransfer/DebitTransferPayment/ChargeBearerCode CBANAC.BCCBCD; ARS300MI/GetHead2	The field indicates the Charge bearer code (CBCD) of the company's bank account.
	This code has to be translated: - CBCD = 01 - "Shared" - CBCD = 02 - "Debtor" - CBCD = 03 - "Creditor" - CBCD = 04 - "ServiceLevel" Not included if value 00 (not used).
	NB: Exists also under DebitTransferPayment/PaymentTransaction (retrieved from customer's bank account).
DebitTransfer/DebitTransferPayment/PaymentTransaction CSYTAB.CTPARM (DSPYCD.FPEGCD, FPQTAP, FPSBAG); ARS300MI/GetHead2	The field indicates the PaymentTransaction level within one Date (see above) and Sequence type (SQTP), is created depending on the group code used: - If Pmt class (PYCL) 04: Group code from ARS300MI.GetHead2.GRP2 (0 or 1). - If Pmt class (PYCL) 05: Group code from ARS300MI.GetHead2.GRP2 (0, 1 or 2).
	PaymentTransaction when Group code (GRP2) = 0 created per transaction from ARS300MI.LstRemByPayer where RMST (status) = 0.
	PaymentTransaction when Group code (GRP2) = 1 or 2 created (ARS300MI.LstRemByType where RMST (status) = 0) per: - Payee (PYNO) - Customer bank account (BKID) - Mandate (BKAG) NB: See (1) below Payment purpose code (PUPO)
	(1) Mandate (BKAG) must only be included as summary level if Electronic format (ELET) = SEPA-DD or if ARS300MI.GetHead2.SBAG of Payment method used = 1 (split per bank agreement).
DebitTransfer/DebitTransferPayment/PaymentTransaction/Instruc FARRED.R1RMNB, R1PYNO, R1CINO, R1DRRN FARRES.R3DENB; ARS300MI/LstRemByPayer and GetPayerTotal2	

Payment class (PYCL) = 04 and Electronic format (ELET) = SEPA-DD:

Case 1: Not grouped (Group code (ARS300MI.GetHead2.GRP2) = 0):

- RMNB + PYNO + DRRN or CINO with '-' as separator.

Case 2: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1):
- RMNB + PYNO + DRRN or CINO + DRRN or CINO etc with '-' and ',' but ',' between each invoice.

 If 35 characters exceeded, remove leading zeros for RMNB and DENB.

Payment class (PYCL) = 05 and Electronic format (ELET) = SEPA-DD.

Case 3: Not grouped (Group code (ARS300MI.GetHead2.GRP2) = 0):

- RMNB + PYNO + DENB + CINO with '-' as separator.

- If 35 characters exceeded, remove leading zeros for RMNB and DENB.

Case 4: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1 or 2):

- RMNB + PYNO + DENB + CINO + CINO etc with '-' as separator but ',' between each invoice.

- If 35 characters exceeded, remove leading zeros for RMNB and DENB.

DebitTransfer/DebitTransferPayment/PaymentTransaction/TransactionID

FARRED.R1RMNB, R1PYNO, R1CINO, R1DRRN FARRES.R3DENB.-; ARS300MI/LstRemByPayer and GetPayerTotal2

The field indicates the TransactionID created (*) depending on Payment class (PYCL), Group code (see below) and Electronic format (ELET).

(*) Temporary solution until new BE solution for ARS300 so setting defined in CRS485 can be used.

Payment class (PYCL) = 04 and Electronic format (ELET) = SEPA-DD:

Case 1: Not grouped (Group code (ARS300MI.GetHead2.GRP2 = 0): - RMNB + PYNO + DRRN or CINO with '-' as separator.

Case 2: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1):

- RMNB + PYNO + DRRN or CINO + DRRN or CINO etc with '-' and '.' but '.' between each invoice.

- If 35 characters exceeded, remove leading zeros for RMNB and DENB.

Payment class (PYCL) = 04 and Electronic format (ELET) not = SEPA-DD:

Case 3: Not grouped (Group code (ARS300MI.GetHead2.GRP2) = 0):
- DRRN and if not existing, CINO.

Case 4: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1):

- DRRN or CINO, DRRN or CINO etc with ',' as separator.

Payment class (PYCL) = 05 and Electronic format (ELET) = SEPA-DD or CH-DIRDEB:

Case 5: Not grouped (Group code (ARS300MI.GetHead2.GRP2) = 0).

- RMNB + PYNO + DENB + CINO with '-' as separator.

- If 35 characters exceeded, remove leading zeros for RMNB and DFNB

Case 6: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1 or 2):

- RMNB + PYNO + DENB + CINO + CINO etc with '-' as separator but ',' between each invoice.

- If 35 characters exceeded, remove leading zeros for RMNB and $\ensuremath{\mathsf{DENB}}$.

Payment class (PYCL) = 05 and Electronic format (ELET) not = SEPA-DD or CH-DIRDEB:

Case 7: Not grouped (Group code (ARS300MI.GetHead2.GRP2) = 0):

Case 8: Grouped (Group code (ARS300MI.GetHead2.GRP2) = 1 or 2):

- RMNB + PYNO with '-' as separator.

Debit Transfer/Debit Transfer Payment / Payment Transaction / Payment Purpose Code (Code) / Payment (Code)

FARRED.R1PUPO CBANAC.BCPPCO or FARREM.ERRMTY.-; ARS300MI The field indicates the Payment purpose code that is set depending on type of payment.

If Electronic format (ELET) = SEPA-DD (payment class 4 and 5): - Payment purpose code (PUPO) of the transaction.

- From Customer bank account (field PPCO), and if blank,
- From Company bank account (field PPCO).

or ARS300MI/LstRemByPayer or

GetPaverInfo or Otherwise not created. GetHead2 If Electronic format (ELET) # SEPA-DD and Payment class 4; Remittance type (RMTY) translated to the following values: GetHead2 - Remittance type (RMTY) = 1: Cash - Remittance type (RMTY) = 2: Advanced DebitTransfer/DebitTransferPayment/PaymentTransaction/DebitTransferAgreement/PriorityCode The field indicates the Priority code (PITY) of the customer's bank CBANAC.BCPITY; ARS300MI/GetPayerInfo account. This code has to be translated: - PITY = 01: 'NORMAL' - PITY = 02: 'HIGH' - PITY = 03: 'URGENT - PITY = 04: 'LOW' Not included if value 00 (not used). NB: Exists also under DebitTransferPayment/ DebitTransferAgreement (retrieved from the company's bank account). @listID Set to 'Priorities'. DebitTransfer/DebitTransferPayment/PaymentTransaction/DebitTransferAgreement/LocalInstrumentCode FARRED.R1QACE; ARS300MI/LstRemByPayer The field indicates the Acceptance code (QACE) for Payment class 4 and Electronic format (ELET) not SEPA-DD (otherwise not created): - If Acceptance code (QACÉ) = 0: Set to 'Not accepted' - If Acceptance code (QACE) = 1: Set to 'Accepted' - If Acceptance code (QACE) = 2: Set to 'Promissory Note' Retrieved from the first record included in the payment transaction (set per Payment method). Local IntrumentCode exists also under: - DebitTransferAgreement/LocalInstrumentCode. That level is not used for Electronic format (ELET) # (not equal) SEPA-DD. DebitTransfer/DebitTransferPayment/PaymentTransaction/DebitTransferAgreement/CategoryPurposeCode CBANAC.BCCPCO; ARS300MI/GetPayerInfo The field indicates the Category purpose code (CPCO) from the customer's bank account. NB: Exist also on 'DebitTransferPayment/DebitTransferAgreement' level where information from the company's bank account is retrieved. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/MandateID FARRED.R1BKAG; ARS300MI/LstRemByPayer The field indicates the Bank agreement number (BKAG) connected to the payment transaction. NB: Only created if Electronic format (ELET) = 'SEPA-DD' or if SBAG of Company bank account = 1 (split per bank agreement) DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/SignatureDate FDDAGR.DDVFDT; ARS450MI/LstAgrByCustNo The field indicates the Valid from date (VFDT). - First agreement having status "20, 30 or 80" retrieved with a valid "From Date" and "To date" compared to the payment date. NB: Retrieved using CUNO (PYNO) BKAG, BKID (Customer account), SDDS and BKI2 (Company account). If there is no agreement, search without BKI2 (Company account). NB: Only created if Electronic format (ELET) = 'SEPA-DD'. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentIndicator FARRED.R1AMRC; ARS300MI/LstRemByPayer The field indicates the Amendment indicator (AMRC) - Value is set to "false" if Amendment indicator (AMRC) is "blank", else set to "true". NB: Only created if Electronic format (ELET) = 'SEPA-DD'. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentDetail The field indicates the Amendment details, the section includes -.-; -/details about the reason for amendment of the mandate. - Only included if AmendmentIndicator above is "true". NB: Only created if Electronic format (ELET) = 'SEPA-DD' DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentDetail/OriginalMandateID The field indicates the Original mandate ID if Amendment indicator FDDAGR.DDBRAG; ARS450MI/GetBasicData (AMRC) = 01 and 06:

Infor May 26, 2023 16

leading and trailing spaces.

- Reference agreement number (BRAG) - position 18-32 and remove

GetBasicData

DebitTransfer NB: Only created if Electronic format (ELET) = 'SEPA-DD'. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentDetail/OriginalCreditorParty/PartyIDs/ID CBANVA.BVBAVA; CRS693MI/GetBasicData The field indicates the Original Creditor ID if Amendment indicator (AMRC) = 02 and 06:- Original Creditor ID (BAVA) from additional field 701 (CRS693 -BVTP) of the Company's bank account (BKID). NB: Only created if Electronic format (ELET) = 'SEPA-DD'. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentDetail/OriginalCreditorParty/Name CBANVA.BVBAVA; CRS693MI/GetBasicData The field indicates the Original Creditor name if Amendment indicator (AMRC) = 02, 03 and 06: - Original Creditor name (BAVA) from additional field 702 and/or 703 (CRS693 - BVTP) of the Company's bank account. NB: Only created if Electronic format (ELET) = 'SEPA-DD'. DebitTransfer/DebitTransferPayment/PaymentTransaction/MandateDetail/AmendmentDetail/OriginalDebtorParty/FinancialAccount/ **IBANID** The field indicates the IBAN of the Original Debtor Party if -.-: - /-Amendment indicator (AMRC) = 04 (*) or 05:
- Set to constant "SMNDA" (SMNDA = Same Mandate with a New Debtor Account). NB: Only created if Electronic format (ELET) = 'SEPA-DD'. (*) Changed handling for AMRC=4 from Rulebook 2016. DebitTransfer/DebitTransferPayment/PaymentTransaction/InstructedAmount FARRED.R1CUAM; ARS300MI/LstRemByPayer The field indicates the Payment amount (CUAM) of the document number This is the total amount of the invoices included in the payment @currencyID FARREM.ERCUCD; ARS300MI/LstRemByPayer The field indicates the Currency code (CUCD) of the invoice/payment. Generic translation is used to translate CUCD according to ISO 4217. DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/PartyIDs/ID FARRED.R1PYNO The field indicates the Party that owes an amount of money to the CBANVA.BVBAVA.-; ARS300MI Creditor, Payer number (PYNO). CRS693MI/LstRemByPayer GetBasicData To be taken according to priority: 1) Value (BAVA) from CRS693.GetBasicData (*) with BKTP=02 for field (BVTP = 511) 2) If the above value not exists: From payer number (PYNO) (*) Value (BAVA) from CRS693 is retrieved for the customer's bank account using CRS693MI.GetBasicData with BKTP=02, BKID=ARS300MI.GetHead2.BKI2 and BVTP. Exception if Country version (MNS100.CSVN) = SE: a) Additional ID if ELET = SE-BGAGRM and ÁRS300MI.GetPayerInfo.BAF1 = P: - Payer number (BAVA) from CRS693 for BVTP = 302. b) Additional ID if ELET = SE-PGAGRM and ÁRS300MI.GetPayerInfo.BAF1 = C: - Payer number (BAVA) from CRS693 for BVTP = 303. @schemeName Set to schemeName 'CustomerNumber' -.-; -/-Exception if Country version (MNS100.CSVN) = SE: - Set to schemeName 'BankPartyIdentification' @accountingEntity The field indicates the translated M3 BE company and division. -.-: -/-DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/PartyIDs/TaxID OCUSAD.OPVRNO OCUSMA.OKVRNO, OKCORG, OKCOR2 The field indicates the following TaxIDs included as standard with XITCIN.XCXFCO.-; ARS300MI information from (OIS002/CRS610): - TaxID 1: VAT registration number (VRN2) of the customer (Note: CRIT10MI/GetPayerInfo Country code (ISO country code from (CRS045) already added as prefix if applicable).

- TaxID 3: Organization number 2 (COR2) of the customer.

Exception if Country version (MNS100.CSVN) = FR: - TaxID 1: VAT registration number (VRN2) of the customer (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

- TaxID 2: Organization number 1 (CORG) of the customer.

- TaxID 2: Organization number 1 (CORG) + Organization number 2

May 26, 2023

@schemeName

-.-; -/-

(COR2) of the customer concatenated without any blanks or other signs between.

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: VAT registration number (VRN2) of the customer (Note: Country code (ISO country code from (CRS045) already added as prefix if applicable).

If VAT registration number (VRN2) = blank:

- TaxID 2: Fiscal code (XFCO) from Italian customer master (CRIT10).

NB: VAT registration number (VRN2) retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610).

Set to the following schemeNames used as standard:

- TaxID 1: schemeName = 'TaxIdentificationNumber'
- TaxID 2: schemeName = 'CountryIdentificationNumber'
- TaxID 3: schemeName = 'CountryldentificationNumber'

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName 'TaxIdentificationNumber'
 TaxID 2: schemeName 'CountryIdentificationNumber'

Exception if Country version (MNS100.CSVN) = IT:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'NationalIdentityNumber'

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Name

OCUSAD.OPCUNM, OPCUA1-CUA4 or FARREP.R2ADR1-ADR4.-; ARS300MI/GetPayerInfo

The field indicates the Customer name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM) as mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

NB: Information retrieved from (OIS002) if Address type (ADRT) and number (ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610)

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Name

OCUSAD.OPCUNM, OPCUA1-CUA4 or FARREP.R2ADR1-ADR4.-; ARS300MI/GetPayerInfo

The field indicates the Customer name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM) as mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

NB: Information retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610)

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address @type

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address/AddressLine

Set to 'text' if address information included.

OCUSAD.OPCUA1-CUA4 or FARREP.R2ADR1-ADR4.-; ARS300MI/GetPayerInfo

The field indicates the Customer's address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how ADR1-ADR4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of

Alternative if generic translation used and code E not available: Customer address line 2 (ADR2) as mandatory information.

May 26, 2023

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (ADR3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (ADR4) not included as not mandatory information.

Alternative if generic translation not used: Customer address line 1-4 (ADR1-ADR4).

NB: Information retrieved from (OIS002) if Address type

(ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610).

@sequence

-.-; -/-

Set to sequence number of the address line: values 1-4.

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address/CityName

OCUSAD.OPTOWN or

OCUSMA.OKTOWN.-; ARS300MI/GetPayerInfo

The field indicates the Čity name (TOWN) of customer from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

NB: Information retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number

(ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610).

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address/CountrySubDivisionCode

OCUSAD.OPECAR or

OCUSMA.OKECAR .-; ARS300MI/GetPayerInfo

The field indicates the Area/State code (ECAR) of customer from (MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/state' (CSCD-ECAR)).

NB: Information retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US

(CRS610).

States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address/CountryCode

OCUSAD.OPCSCD or

FARREP.R2CSCD.-; ARS300MI/GetPayerInfo

The field indicates the Country code (CSCD) of customer from (CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

NB: Information retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number (ARS300MI.GetHead2.ADID) defined for the payment me

(ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from

(CRS610).

@listID

@listID - -: -/-

Set to 'Countries'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/Location/Address/PostalCode

OCUSAD.OPPONO or

FARREP.R2PONO.-; ARS300MI/GetPayerInfo

The field indicates the Postal code (PONO) of customer from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

NB: Information retrieved from (OIS002) if Address type (ARS300MI.GetHead2.ADRT) and number

(ARS300MI.GetHead2.ADID) defined for the payment method used. If not defined or not existing, the information is retrieved from (CRS610).

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/FinancialAccount/BBANID

CBANAC.BCBACN; ARS300MI/GetPayerInfo

The field indicates the Bank account number (BACN) of the customer.

NB: Not included if IBAN of the customer exists (only one FinancialAccount allowed).

DebitTransfer/DebitTransferPayment/PaymentTransaction/DebtorParty/FinancialAccount/IBANID

CBANAC.BCIBAN; ARS300MI/GetPayerInfo

The field indicates the International bank account number (IBAN) of the customer.

Debit Transfer/Debit Transfer Payment/Payment Transaction/Debtor Party/Financial Account/Name

CBANAC.BCBANA: ARS300MI/GetPaverInfo

The field indicates the Name (BANA) of the customer's bank account.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/ID

CBANAC.BCBKNO; ARS300MI/GetPayerInfo

The field indicates the Bank number (BKNO) of the customer's bank.

@schemeName

-.-; -/-

Set to schemeName = 'BankPartyIdentification'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/TaxID

CBANMA.BKVRNO; CRS690MI/GetBasicData

The field indicates the VAT registration number (VRN2) of the customer's bank (Note: Country code (ISO country code from

(CRS045) already added as prefix if applicable).

@schemeName

-.-; -/-

Set to schemeName = 'TaxIdentificationNumber'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/PartyIDs/BICID

CBANAC.BCSWBI or CBANMA.BKSWIC .-; ARS300MI or CRS690MI/GetPayerInfo or

GetBasicData

The field indicates the Swift/BIC code (SWBI) of the customer's bank account and if not existing, Swift code (SWIC) of the customer's bank.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Bank name customer's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank name (BKNM).

Alternative if generic translation not used: Bank name (BKNM).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Name

CBANMA.BKBKNM or

BKBKA1-BKA4; CRS690MI/GetBasicData

The field indicates the Location name of customer's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank name (BKNM).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address @type

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/AddressLine CBANMA.BKBKA1-BKA4; CRS690MI/GetBasicData

Set to 'text' if address information included

The field indicates the Bank address of customerr's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local ly for description of setup).

Alternative if generic translation used and code E not available: Bank address line 2 (BKA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Bank address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank address line 1-4 (BKA1-BKA4).

@sequence

- -; -/-

-.-; -/-

Set to sequence number of the address line: values 1-4

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CityName

CBANMA.BKTOWN; CRS690MI/GetBasicData

The field indicates the City name (TOWN) of customer's bank from (CRS690) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3)

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountrySubDivisionCode

CBANMA.BKECAR; CRS690MI/GetBasicData

The field indicates the Area/State code (ECAR) of company from (MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

@listID

May 26, 2023

-.-; -/
Set to general value: 'Country Sub-divisions'; for ECAB = 'US': 'US

States'; for ECAB = 'CA': 'Canadian Provinces'; for ECAB = 'FR':

'France - Departements'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/CountryCode

CBANMA.BKCSCD; CRS690MI/GetBasicData

The field indicates the Country code (CSCD) of customer's bank from

(CRS690).

Generic translation is used to translate CSCB to alpha-2 country code

according to ISO 3166.

@listID

-.-; -/- Set to 'Countries'

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/Location/Address/PostalCode
CBANMA.BKPONO; CRS690MI/GetBasicData
The field indicates the Postal code (PONO) of section of the postal code (PONO) of section of the field indicates the Postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO) of section of the field indicates the postal code (PONO

The field indicates the Postal code (PONO) of supplier's bank from (CRS690) if available in M3 (also sent as part of AddressLine

@SequenceNumber = 3).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/ClearingSystemMemberID

CBANAC.BCCLSI + BCCLSN; ARS300MI/GetPayerInfo

The field indicates the Clearing system member identification (CLSI+CLSN cut together) of the customer's bank retreived from the bank account. If clearing system ID (CLSI) has not been defined, only clearing system number (CLSN) is used.

@schemeName

-.-; -/- Set to schemaName = 'ClearingIdentificationNumber'.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/PartyIDs/ID

The field indicates the Bank branch number (BBRN) of the customer's

bank branch.

@schemeName

- - · -/-

Set to schemeName = 'BankPartyIdentification'.

@accountingEntity -.-; -/-

The field indicates the translated M3 BE company and division.

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/PartyIDs/BICID

CBANBR.BRSWIC; CRS691MI/GetBasicData

CBANAC.BCBBRN; ARS300MI/GetPayerInfo

The field indicates the Swift code (SWIC) of customer's bank branch from (CRS691).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Name

CBANBR.BRBKBM

BRBKA1-BKA4; CRS691MI/GetBasicData

The field indicates the Bank branch name of customer's bank based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKNM and BKA1-BKA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Bank branch name (BKBM).

Alternative if generic translation not used: Bank branch name (BKBM).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Name

CBANBR.BRBKBM

BRBKA1-BKA4; CRS691MI/GetBasicData

The field indicates the Location name of customer's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKBM and BKA1-BKA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included.

Alternative if generic translation not used: Bank branch name (BKBM).

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address@type

---; -/- Set to 'text' if address information included

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/AddressLine
CBANBR.BRBKA1-BKA4; CRS691MI/GetBasicData
The field indicates the Bank address of customer's bank branch

The field indicates the Bank address of customer's bank branch based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'BANK' or 'ALL' to a code string indicating how BKA1-BKA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Bank branch address line 2 (BKA2) as mandatory information.

Alternative if generic translation used, code G not available and the fields for 'Postal code' and 'City' are empty: Bank branch address line 3 (BKA3) as mandatory information.

Alternative if generic translation used and code J not available:

Address line 4 (BKA4) not included as not mandatory information.

Alternative if generic translation not used: Bank branch address line 1-4 (BKA1-BKA4).

@sequence

Set to sequence number of the address line: values 1-4 -.-; -/-

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/CityName CBANBR.BRTOWN; CRS691MI/GetBasicData

The field indicates the City name (TOWN) of customer's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine

@SequenceNumber = 3)

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/

CountrySubDivisionCode

CBANBR.BRECAR; CRS691MI/GetBasicData

The field indicates the Area/State code (ECAR) of company from

(MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

Set to general value: 'Country Sub-divisions'; for ECAB = 'US': 'US States'; for ECAB = 'CA': 'Canadian Provinces'; for ECAB = 'FR':

'France - Departements'

DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/CountryCode

CBANBR.BRCSCD; CRS691MI/GetBasicData

The field indicates the Country code (CSCD) of customer's bank branch from (CRS691).

Generic translation is used to translate CSCB to alpha-2 country code

according to ISO 3166.

@listID -.-; -/-

@listID

-.-: -/-

Set to 'Countries'. DebitTransfer/DebitTransferPayment/PaymentTransaction/FinalAgentFinancialParty/BranchParty/Location/Address/PostalCode

CBANBR.BRPONO; CRS691MI/GetBasicData

The field indicates the Postal code (PONO) of the customer's bank branch from (CRS691) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

DebitTransfer/DebitTransferPayment/PaymentTransaction/ChargeBearerCode

CBANAC.BCCBCD; ARS300MI/GetPayerInfo

The field indicates the Charge bearer code (CBCD) of the customer's bank account.

This code has to be translated:

- CBCD = 01 - "Shared"

- CBCD = 02 - "Debtor"

- CBCD = 03 - "Creditor" - CBCD = 04 - "ServiceLevel"

Not included if value 00 (not used).

NB: Exists also under DebitTransferPayment (retrieved from the

company's bank account).

DebitTransfer/DebitTransferPayment/PaymentTransaction/RegulatoryReporting/Code

CBANVA.BVBAVA; CRS693MI/GetBasicData

The field indicates the Regulatory reporting code (in M3BE 'Trade code') only used for exception on Country version (CSVN) and Electronic format (ELET).

Exception if Country version (MNS100.CSVN) = IT and ELET = SEPA-DD:

- Default Trade code (BAVA) from CRS693MI.GetBasicData with CONO/DIVI from ARS300MI.GetHead2, BKTP=01 (Company), ACHO=blank, BKID=APS130MI.GetHead2.BKI2 and BVTP=031

DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/UnstructuredRemittanceText

FARRED.R1PYNO R1IVDT, R1DUDT R1CINO, R1DRRN R1CUAM

R1CUCD; ARS300MI/LstRemByPayer

The field indicates the Unstructured remittance text created (*) depending on Payment class (PYCL) and Number of invoices included. NB: For the moment only used (created) when Electronic format (ELET) = SEPA-DD or CH-DIRDEB.

(*) Temporary solution until new BE solution for ARS300 so setting defined in CRS485 can be used.

Payment class (PYCL) = 04:

Case 1: Maximum two invoices included:

- PYNO (only once) + DUDT + DRRN or CINO + CUAM + CUCD with

+ blank as field separator and '/' + blank as string separator (= between each invoice).

- DUDT with format YYYY.MMMM.DD.

- If 140 characters exceeded, truncate.

Case 2: More than two invoices included:

- DRRN or CINO with '/' + blank as string separator (= between each

- If 140 characters exceeded, truncate.

167 May 26, 2023

Payment class (PYCL) = 05: Case 3: Maximum two invoices included: - PYNO (only once) + IVDT + CINO + CUAM + CUCD with ',' + blank as field separator and '/' + blank as string separator (= between each invoice). - IVDT with format YYYY.MMMM.DD. - If 140 characters exceeded, truncate. Case 4: More than two invoices included: - CINO with '/' + blank as string separator (= between each invoice). - If 140 characters exceeded, truncate Debit Transfer/Debit Transfer Payment / Payment Transaction / Remittance Information / Structured Remittance Information / Transfer / Debit Transfer / Debit-.-; -/-The field indicates the Structured remittance information that is repeated for each invoice included. DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ **DocumentReference** @type Set to Noun = 'Invoice'. DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ DocumentReference/DocumentID/ID FARRED.R1CINO; ARS300MI/LstRembyPayer The field indicates the Customer invoice number (CINO). @accountingEntity The field indicates the translated M3 BE company and division. DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ RemittanceReferredDocumentAmounts/DiscountAppliedAmount FARRED.R1CDCU; ARS300MI/LstRemByPayer The field indicates the Cash discount amount currency (CDCU). @currencyID -.-; -/-The field indicates the Currency code (CUCD) of the invoice/payment. Generic translation is used to translate CUCD according to ISO 4217. DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ RemittanceReferredDocumentAmounts/RemittedAmount FARRED.R1CUAM; ARS300MI/LstRembyPayer The field indicates the Paid amount currency (CUAM). @currencyID The field indicates the Currency code (CUCD) of the invoice/payment. -.-; -/-Generic translation is used to translate CUCD according to ISO 4217. DebitTransfer/DebitTransferPayment/PaymentTransaction/RemittanceInformation/StructuredRemittanceInformation/ **StructuredCreditorReference** FARRED.R1DRRN The field indicates the Reference depending on the Payment class FARRED.R1PAIN.-; ARS300MI/LstRemByPayer - If Payment class (PYCL) = 04: Drawee reference number (DRRN) if existing. - If Payment class (PYCL) = 05: Parallel invoice number (PAIN) if existing. DebitTransfer/DebitTransferPayment/DebitTransferAgreement/DebitTransferType CSYTAB.CTPARM (DSPYCD.FPELET) The field indicates the Type set depending on electronic format FARREM.ERPYCL.-; ARS300MI/GetHead2 (ELET) and/or Payment class (PYCL) of the Payment method - Electronic format (ELET) = SEPA-DD: Set to 'SEPA' Otherwise not created. DebitTransfer/DebitTransferPayment/DebitTransferAgreement/PriorityCode CBANAC.BCPITY; ARS300MI/GetHead2 The field indicates the Priority code (PITY) of the company's bank This code has to be translated: - PITY = 01: 'NORMAL' - PITY = 02: 'HIGH' - PITY = 03: 'URGENT' - PITY = 04: 'LOW' Not included if value 00 (not used). NB: Exists also under DebitTransferPayment/ PaymentTransaction(DebitTransferAgreement (retrieved from customer's bank account). @listID Set to 'Priorities'. -.-; -/-DebitTransfer/DebitTransferPayment/DebitTransferAgreement/LocalInstrumentCode FARRED.R1SDDS; ARS300MI/GetHead2 The field indicates the Direct Debit scheme (SDDS) for Payment class 4 and 5 and Electronic format (ELET) = SEPA-DD or CH-DIRDEB (otherwise not created):

Infor May 26, 2023 16

If Direct Debit scheme (SDDS) = 1: Set to 'CORE'
If Direct Debit scheme (SDDS) = 2: Set to 'CORE' (*)
If Direct Debit scheme (SDDS) = 3: Set to 'B2B'

Retrieved from the first transaction as same for entire remittance.

(*) COR1 (SDDS=2) not allowed from Rulebook 2016.

Local IntrumentCode exists also under:

- PaymentTransaction/DebitTransferAgreement/LocalInstrumentCode That level is not used for Electronic format (ELET) = SEPA-DD as 'Direct debit scheme' (SDDS) is applicable for the entire remittance.

Debit Transfer/Debit Transfer Payment/Debit Transfer Agreement/Sequence Type Code

FARRED.R1SQTP; ARS300MI/LstRemByPayer

The field indicates the Sequence type (SQTP) code;

- If FRST: Set to 'First'.
- If RCUR: Set to 'Recurring'.
- If FNAL: Set to 'Final'.
- If OOFF: Set to 'One Off'

DebitTransfer/DebitTransferPayment/DebitTransferAgreement/CategoryPurposeCode

CBANAC.BCCPCO; ARS300MI/GetHead2

The field indicates the Category purpose code (CPCO) from the company's bank account.

NB: Exist also on 'DebitTransferPayment/PaymentTransation/ DebitTransferAgreement' level where information from the customer's bank account is retrieved.

FinancialCalendar

FinancialCalendar/FinancialCalendarID/ID	Sat to "Einanaial Calandar"
@accountingEntity	Set to "Financial Calendar".
CSYPER.CPCONO	The field indicates the company and division, displayed as
CSYPER.CPDIVI.; /	CONO_DIVI.
@variationID	The field indicates the assumes number that identifies the number of
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	times that the BOD has been published.
	The field indicates the logical ID of the system.
FinancialCalendar/Name	
	The field indicates the Financial Calendar name. It is a concatenation of CONO_DIVI + "- Financial Calendar".
FinancialCalendar/Status/Code	The field indicates the financial calendar status. Set to "Open".
FinancialCalendar/CalendarYear/Year	The hold indicates the infariour calculation status. Set to Sport.
CSYPER.CPYEA4; CRS910MI/Select	The field indicates the year.
	Agreement control properties m3beFromYear and m3beToYear is
	available to allow users to specify the year range.
	Default values are blank. Using the default values, all years in
	CRS910 in consideration with fields PETP and PTFA (if PETP !=
	PTFA, abort) will be published in the BOD.
FinancialCalendar/CalendarYear/Name	The Cold in disease the conse
CSYPER.CPYEA4; CRS910MI/Select	The field indicates the year. Agreement control properties m3beFromYear and m3beToYear is
	available to allow users to specify the year range.
	Default values are blank. Using the default values, all years in
	CRS910 in consideration with fields PETP and PTFA (if PETP !=
	PTFA, abort) will be published in the BOD.
FinancialCalendar/CalendarYear/EffectiveTimePeriod/StartDateTime	
CSYPER.CPFDAT; CRS910MI/Select	The field indicates the Financial Calendar start date.
FinancialCalendar/CalendarYear/EffectiveTimePeriod/EndDateTime CSYPER.CPTDAT; CRS910MI/Select	The field indicates the Financial Calendar end date.
FinancialCalendar/CalendarYear/Period/PeriodID	
CSYPER.CPPERI; CRS910MI/Select	The field indicates the period within the Fiscal Calendar year.
	ND: Deried 00 is greated as first period of each year to indicate the
	NB: Period 00 is created as first period of each year to indicate the opening balance period.
FinancialCalendar/CalendarYear/Period/Name	opening senance period.
CSYPER.CPTX15; CRS910MI/Select	The field indicates the period name.
,	
	NB: Set to "Opening balance period" for period 00.
FinancialCalendar/CalendarYear/Period/ShortName	T. C. I. C. A
CSYPER.CPTX15; CRS910MI/Select	The field indicates the period name.
	NB: Set to "OB period" for period 00.
FinancialCalendar/CalendarYear/Period/Status/Code	Set to "Open".
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/StartDat	·
CSYPER.CPFDAT; CRS910MI/Select	The field indicates the system period start date.
	NB: Set to the Start date from the period 01 for the opening balance period 00.
FinancialCalendar/CalendarYear/Period/EffectiveTimePeriod/EndDate	<u> </u>
CSYPER.CPTDAT; CRS910MI/Select	The field indicates the system period end date.
	NB: Set to the Start date from the period 01 for the opening balance period 00.
FinancialCalendar/CalendarYear/Period/PeriodTypeCode	
,,	Set to "Normal".
	ND O (A IA II A II A II A II A II A II A
	NB: Set to 'Adjustment' for the opening balance period 00.

FinancialPartyMaster

i manciair ai tymastei	
FinancialPartyMaster/PartyIDs/ID CBANMA.BKBKNO; CRS690MI/GetBasicData @accountingEntity	The field indicates the bank number.
	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
FinancialPartyMaster/PartyIDs/DisplayID .; CRS690MI/GetBasicData	The field indicates the bank number.
FinancialPartyMaster/PartyIDs/BICID CBANMA.BKSWIC; CRS690MI/GetBasicData	The field indicates the SWIFT/BIC code that can be defined on the bank account.
FinancialPartyMaster/LastModificationDateTime CBANMA.BKLMTS; [from event]/	The field indicates the last modification date and time.
FinancialPartyMaster/LastModificationPerson/IDs/ID CBANMA.BKCHID; [from event]/ @accountingEntity	The field indicates the last person who modified the record.
waccountingEntity	The field indicates the company and division, displayed as CONO DIVI.
FinancialPartyMaster/Name CBANMA.BKBKNM; CRS690MI/GetBasicData	The field indicates the bank name.
FinancialPartyMaster/Location/Address @type	Set to "text".
FinancialPartyMaster/Location/Address/AttentionOfName	COLLO TONE.
CBANMA.BKYREF BKYRE2; CRS690MI/GetBasicData	The field indicates the bank's contact person.
FinancialPartyMaster/Location/Address/AddressLine CBANMA.BKBKA1 BKBKA2 BKBKA3	The field indicates the address line.
BKBKA4; CRS690MI/GetBasicData	
@sequence	The field indicates the address line sequence.
FinancialPartyMaster/Location/Address/CityName CBANMA.BKTOWN; CRS690MI/GetBasicData	The field indicates the city name.
FinancialPartyMaster/Location/Address/CountrySubDivisionCode CBANMA.BKECAR; CRS690MI/GetBasicData @JistID	The field indicates an area, province or state within a country.
	Set to "Canadian Provinces" if the country is CA (Canada). Set to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country code="">" for other countries. Set to "SubDivisions" if no country is specified.</country>
FinancialPartyMaster/Location/Address/CountryCode CBANMA.BKCSCD; CRS690MI/GetBasicData	The field indicates the country code.
@listID	Set to "Countries".
FinancialPartyMaster/Location/Address/PostalCode CBANMA.BKPONO; CRS690MI/GetBasicData	The field indicates the postal code.
FinancialPartyMaster/Communication @sequence	
@preferredIndicator	The field indicates the communication sequence.
FinancialPartyMaster/Communication/ChannelCode	Set to "false".
manoan arymaccon communication chamboscae	Set to "Phone" if telephone number 1 or 2 or facsimile number or mobile. Set "Email" if email.
@listID	
FinancialPartyMaster/Communication/UseCode	Set to "Communication Channels".
and any matter desimilar reaction decoded	Set to "Office" if telephone number 1, telephone number 2 or e-mail address. Set to "Fax" if facsimile number.
@listID	
FinancialPartyMaster/Communication/DialNumber CBANMA.BKPHNO, BKPHN2 BKTFNO; CRS690MI/GetBasicData	Set to "Communication Use Codes". The field indicates the phone number.

FinancialPartyMaster

FinancialPartyMaster	
FinancialPartyMaster/Communication/URI CBANMA.BKEMAL; CRS690MI/GetBasicData	The field indicates the e-mail address.
FinancialPartyMaster/Communication/Preference/Indicator	Set to "false".
FinancialPartyMaster/BranchParty/PartyIDs/ID CBANBR.BRBBRN; CRS691MI/LstByNumber @accountingEntity	The fields indicates the bank branch code.
	The field indicates the company and division, displayed as CONO DIVI.
FinancialPartyMaster/BranchParty/PartyIDs/BICID CBANBR.BRSWIC; CRS691MI/LstByNumber	The field indicates the SWIFT/BIC code that can be defined on the bank account.
FinancialPartyMaster/BranchParty/Name CBANBR.BRBKBM; CRS691MI/LstByNumber	The field indicates the branch name.
FinancialPartyMaster/BranchParty/Location/Address	
@type	Set to "text".
FinancialPartyMaster/BranchParty/Location/Address/AttentionOfNan CBANBR.BRYREF BRYRE1; CRS691MI/LstByNumber	ne The field indicates the branch's contact person.
FinancialPartyMaster/BranchParty/Location/Address/AddressLine CBANBR.BRBKA1, BRBKA2, BRBKA3,	The field indicates the address line.
BRBKA4; CRS691MI/LstByNumber @sequence	The field indicates the address line sequence.
FinancialPartyMaster/BranchParty/Location/Address/CityName	The field findicates the address line sequence.
CBANBR.BRTOWN; CRS691MI/LstByNumber	The field indicates the city name.
FinancialPartyMaster/BranchParty/Location/Address/CountrySubDiv CBANBR.BRECAR; CRS691MI/LstByNumber @/listID	risionCode The field indicates an area, province or state within a country.
	Set to "Canadian Provinces" if the country is CA (Canada). Set to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country code="">" for other countries. Set to "SubDivisions" if no country is specified.</country>
FinancialPartyMaster/BranchParty/Location/Address/CountryCode CBANBR.BRCSCD; CRS691MI/LstByNumber	The field indicates the country code.
@listID	Set to "Countries".
FinancialPartyMaster/BranchParty/Location/Address/PostalCode CBANBR.BRPONO; CRS691MI/LstByNumber	The field indicates the postal code.
FinancialPartyMaster/BranchParty/Communication @sequence	- 1 6 11: 1:
@preferredIndicator	The field indicates the communication sequence. Set to "false".
FinancialPartyMaster/BranchParty/Communication/ChannelCode	Oct to faise .
	Set to "Phone" if telephone number 1 or 2 or facsimile number or mobile. Set "Email" if email.
@listID	Set to "Communication Channels".
FinancialPartyMaster/BranchParty/Communication/UseCode	Set to "Office" if telephone number 1, telephone number 2 or e-mail address. Set to "Fax" if facsimile number.
@listID	Set to "Communication Lles Codes"
FinancialPartyMaster/BranchParty/Communication/DialNumber CBANBR.BRPHNO, BRPHN2, BRTFNO; CRS691MI/LstByNumber	Set to "Communication Use Codes". The field indicates the phone number.
FinancialPartyMaster/BranchParty/Communication/URI CBANBR.BREMAL; CRS691MI/LstByNumber	The field indicates the e-mail address.
FinancialPartyMaster/BranchParty/Communication/Preference/Indica	ntor
	Set to "false".
FinancialPartyMaster/Status/Code CBANMA.CBSTAT; CRS692MI/GetBasicData	The field indicates the status. Set to "Pending" if status is 10. Set to "Open" if status is 20. Set to "Closed" if status is 90.

InspectDelivery

Inspectibelivery	
InspectDelivery/DocumentID/ID MPLIND.ICREPN; /	The field indicates the receiving number which is assigned automatically for each item received in goods receiving.
@accountingEntity MPLIND.ICCONO CMNDIV.CCDIVI.; / @location	The field indicates the company and division, displayed as CONO_DIVI.
MPLINE.IBWHLO; PPS330MI/ListPOTrans @variationID	The field indicates the warehouse.
	The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid	The field indicates the logical ID of the system.
InspectDelivery/LastModificationDateTime MPLIND.ICLMTS; /	The field indicates the date and time the record was last updated.
InspectDelivery/DocumentDateTime MPLIND.ICRGDT MPLIND.ICRGTM.; /	The field indicates the date and time the record was created.
InspectDelivery/DocumentReference/DocumentID/ID MPLIND.ICREPN; /	The field indicates the receiving number which is assigned automatically for each item received in goods receiving.
@accountingEntity MPLIND.ICCONO CMNDIV.CCDIVI.; / @location	The field indicates the company and division, displayed as CONO_DIVI.
MPLINE.IBWHLO; PPS330MI/ListPOTrans	The field indicates the warehouse.
InspectDelivery/DocumentReference/LineNumber MPLIND.ICPNLI; /	The field indicates the order line.
InspectDelivery/RejectedQuantity MPLINE.IBRJQA; PPS330MI/ListPOTrans	The field indicates the rejected quantity. This element is displayed if PPS330 PO status (PUOS) is 64 or 69.
@unitCode MPLINE.IBPUUN; PPS330MI/ListPOTrans	The field indicates the unit of measure in which the quantity of the purchase order is expressed.
InspectDelivery/AcceptedQuantity MPLINE.IBCAQA; PPS330MI/ListPOTrans	The field indicates the approved quantity. This element is displayed if PPS330 PO status (PUOS) is 60 or 65.
@unitCode MPLINE.IBPUUN; PPS330MI/ListPOTrans	The field indicates the unit of measure in which the quantity of the purchase order is expressed.
InspectDelivery/ReasonCode	The field indicates the rejection reason code. The value is retrieved from control property m3beRejectionReason with default value RR. Input to the control property should exist in M3 CRS090.
InspectDelivery/SupplierParty/PartyIDs/ID MPLINE.IBSUNO; PPS330MI/ListPOTrans @accountingEntity	The field indicates the supplier.
MPLIND.ICCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
InspectDelivery/PurchaseOrderReference/DocumentID/ID MPLIND.ICPUNO; / @accountingEntity	The field indicates the purchase order number.
MPLIND.ICCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
InspectDelivery/PurchaseOrderReference/LineNumber MPLIND.ICPNLI MPLIND.ICPNLS.; /	The field indicates the concatenation of purchase order line and subnumber where the last 3 digits indicates the subnumber.

InspectionOrder

InspectionOrder/InspectionOrderHeader/DocumentID/ID MMOOPS.QQMWNO, QQOPNO, QQACTS; MOS104MI/GetOpElement	Order number (MWNO) <10> + Operation number (OPNO) <4> + Task element number (ACTS) <3>. The position of each field is determined by its maximum length, specified in brackets. If the data
	does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case ACTS, is trimmed if it does not consume the maximum length.
@schemeName	The field indicates the scheme name.
@accountingEntity	The field indicates the company and division, displayed as CONO_DIVI.
@location	The field indicates the warehouse.
@variationID	
@lid	The field indicates the variation ID.
	The field indicates the logical ID of M3.
InspectionOrder/InspectionOrderHeader/LastModificationDateTime MMOOPS.QQLMTS; /	The field indicates the last modified date and time of the data.
InspectionOrder/InspectionOrderHeader/LastModificationPerson/IDs/II MMOOPS.QQCHID; MOS104MI/GetOpElement	D The field indicates the ID of the person that entered/changed the recored.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
InspectionOrder/InspectionOrderHeader/DocumentDateTime	The field indicates the date and time the decrease the second
MMOOPS.QQRGDT MMOOPS.QQRGTM.; MOS104MI/GetOpElement	The field indicates the date and time the document was created. These are set automatically and transformed to UTC time zone.
InspectionOrder/InspectionOrderHeader/UserArea	A) F104.
1) MMOOPS.QQFACI 2) MMOOPS.QQPRNO	Facility The field indicates the Facility (FACI).
3) MMOOPS.QQMWNO	Set attribute name to "Facility".
4) MMOOPS.QQOPNO.QQFACI, QQPRNO,QQMWNO,QQOPNO; MOS104MI/GetOpElement	2) Product
MOS104MI/GetOpElement	The field indicates the Product (PRNO). Set attribute name to "Product".
	3) Work order number The field indicates the Work Order Number (MWNO). Set attribute name to "WO number".
	Operation number The field indicates the Operation Nuumber (OPNO). Set attribute name to "Operation number".
InspectionOrder/InspectionOrderTask/LineNumber MMOOPS.QQACTS; MOS104MI/GetOpElement	The field indicates the inspection ID.
InspectionOrder/InspectionOrderTask/Description	
MMOOPS.QQACDS; MOS104MI/GetOpElement InspectionOrder/InspectionOrderTask/Note	The field indicates the operation element description.
MMOOPS.QQTXT1, QQTXT2; MOS104MI/GetOpElement	The field indicates the text. It is a concatenation of text line 1 (TXT1) <60> + text line 2 (TXT2) <60>. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case TXT2, is trimmed if it does not consume the maximum length.
InspectionOrder/InspectionOrderTask/Status/Code MMOOPS.QQSTMB; MOS104MI/GetOpElement	The field indicates the standard status (STMB) of the assignment
MMOOPS.QQSTMB, MOSTO4MI/GetOpElement	group.
	Set to "Accepted" if status is 40. Set to "Assigned" if status is 20, 21, 25, 30 or 31.
	Set to "Travel Started" if status is 41.
	Set to "Travel Stopped" if status is 42.
	Set to "Arrived on Site" if status is 44. Set to "Started" if status is 45.
	Set to "Stopped" if status is 80.
	Set to "Completed" if status is 89 or 90.
	Set to "Pending" if status is 46. Set to "Rejected" if status is 10, 19, 98 or 99.
InspectionOrder/InspectionOrderTask/Status/ReasonCode	
MMOOPS.QQSTMB; MOS104MI/GetOpElement	The field indicates the M3 status on assignment group.

InspectionOrder

MMQIRS.M7SPOS, M7INSI; MOS085MI/LstInsp

The field indicates the inspection line number. It is a concatenation of line number (SPOS) <10> + inspection ID (INSI) <15>. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case INSI, is trimmed if it does not consume the maximum length.

InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/Description

MMQIRS.M7IITX; MOS085MI/LstInsp

The field indicates the inspection description.

InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/Note

MMQIRS.M7REMK; MOS085MI/LstInsp

The field indicates the remarks.

InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/CreationDateTime

MMQIRS.M7TRDT, M7TRTM; MOS08MI/LstInsp

The field indicates the transaction date and time

In spection Order/In spection Order Task/In spection Order Task Line/Actual Completion Date Time Task Line/Actual Completion Date Ta

MMQIRS.M7RPDT; MOS085MI/LstInsp

The field indicates the reporting date.

In spection Order/In spection Order Task/In spection Order TaskLine/Test UOM Code

MMQIRS.M7RUOM; MOS085MI/LstInsp

The field indicates the unit of measure.

MMQIRS.M7RPRE; MOS085MI/LstInsp

The field indicates the reporting responsible

InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/Classification/Codes/Code

1) MMQIRS.M7RVAL MOS085MI.LstInsp

2) MMQIRS.M7RSIY

PDS041MI.Get.M7RVAL, M7RSIY; /

@listID

@sequence

The field indicates the classification code in the tassk line.

1) Reported Value

The field indicates the actual result of an inspection.

2) Result Identity

The field indicates a specific ID for a result.

- 1) Set to "Reported Value".
- 2) Set to "Result Identity".

The field indicates the sequence number.

InventoryAdjustment

inventoryAdjustment	
InventoryAdjustment/InventoryAdjustmentHeader/DocumentID/ID MITTRA.MTWHLO; /	The field indicates the warehouse for the adjusted inventory.
@accountingEntity MITTRA.MTCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MITTRA.MTWHLO; /	The field indicates the warehouse.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
InventoryAdjustment/InventoryAdjustmentHeader/LastModificationD MITTRA.MTLMTS; /	
InventoryAdjustment/InventoryAdjustmentHeader/DocumentDateTim MITTRA.MTRGDT MITTRA.MTRGTM.; /	The field indicates the date and time the record was created.
InventoryAdjustment/InventoryAdjustmentLine/LineNumber	Set to "1".
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/I MITWHL.MWWHLO; MMS005MI/GetWarehouse @accountingEntity	The field indicates the warehouse ID.
MITTRA.MTCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/i	Name
MITWHL.MWWHNM; MMS005MI/GetWarehouse InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/	The field indicates the warehouse name. Address
@type	Set to "text".
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/ACIADDR.OAADR1CIADDR.OAADR2CIADDR.OAADR3CIADDR.OAADR3CIADDR.OAADR4.; MMS005MI/GetWarehouse	
@sequence	The field indicates the address line sequence.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/	
CIADDR.OATOWN; MMS005MI/GetWarehouse InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation// CIADDR.OAECAR; MMS005MI/GetWarehouse	The field indicates the city name. Address/CountrySubDivisionCode The field indicates an area, province or state within a country.
@listID	Set?to "Canadian Provinces" if the country is CA (Canada). Set?to "France - Departements" if the country is FR (France). Set to "US States" if the country is US (United States). Set to "SubDivisions - <country code="">" for other countries. Set to "SubDivisions" if no country is specified.</country>
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation// CIADDR.OACSCD; MMS005MI/GetWarehouse @listID	Address/CountryCode The field indicates the country code.
InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/	Set to "Countries".
CIADDR.OAPONO; MMS005MI/GetWarehouse	The field indicates the postal code.
InventoryAdjustment/InventoryAdjustmentLine/Item/Item/ID/ID MITTRA.MTITNO; MWS070MI/GetStockTrans @accountingEntity MITTRA.MTCONO	The field indicates the item number. The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
InventoryAdjustment/InventoryAdjustmentLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItemMeas	The field indicates a supplementary description of the item.
InventoryAdjustment/InventoryAdjustmentLine/SerialNumber MITTRA.MTBANO; MWS070MI/GetStockTrans	The field indicates the lot number.
InventoryAdjustment/InventoryAdjustmentLine/Quantity MITTRA.MTTRQT; MWS070MI/GetStockTrans @unitCode	The field indicates the quantity.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the unit of measure.
InventoryAdjustment/InventoryAdjustmentLine/Facility/IDs/ID MITWHL.MWFACI; MMS005MI/GetWarehouse @accountingEntity	The field indicates the facility.
MITTRA.MTCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
InventoryAdjustment/InventoryAdjustmentLine/Facility/Name CFACIL.CFFACN ; CRS008MI/Get	The field indicates the facility name.

InventoryAdjustment

InventoryAdjustment/InventoryAdjustmentLine/TransactionDateTime
MITTRA.MTTRDT; MWS070MI/GetStockTrans

The field indicates the transaction date.

Infor May 26, 2023 177

InventoryCount

inventoryCount	
InventoryCount/InventoryCountHeader/DocumentID/ID	-
MITTKV.SVSTNB; / @accountingEntity	The field indicates the physical inventory number.
MITTKV.SVCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO_DIVI.
@location	
MITTKV.SVWHLO; / @variationID	The field indicates the warehouse.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the legical ID of the quotem
In ventors Countillar ventors Countille a deville and ID/ID	The field indicates the logical ID of the system.
InventoryCount/InventoryCountHeader/ItemID/ID MITTKV.SVITNO; MMS307MI/GetPhysInvVar	The field indicates the item number.
InventoryCount/InventoryCountHeader/WarehouseLocation/ID	
MITTKV.SVWHLO; MMS307MI/GetPhysInvVar	The field indicates the warehouse ID.
InventoryCount/InventoryCountHeader/TotalQuantity MITTKV.SVSTQI; MMS307MI/GetPhysInvVar	The field indicates the physical inventory quantity.
<pre>@unitCode MITTKV.SVUNMS; MMS307MI/GetPhysInvVar</pre>	The field indicates the basic unit of measure.
InventoryCount/InventoryCountLine/LineNumber	
MITTKV.SVSTRN; MMS307MI/GetPhysInvVar	The field indicates the physical inventory line.
InventoryCount/InventoryCountLine/Item/ItemID/ID	
MITTKV.SVITNO; MMS307MI/GetPhysInvVar @accountingEntity	The field indicates the item number.
MITTKV.SVCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
InventoryCount/InventoryCountLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItemMeas	The field indicates the name for each item.
InventoryCount/InventoryCountLine/Item/Classification/Codes/Code MITTKV.SVWHSL; MMS307MI/GetPhysInvVar	The field indicates the location. Set attribute listID to "Location".
@sequence	
@listID	Set to "1".
<u>wistib</u>	Set attribute listID to "Location" if Classification/Codes/Code = WHSL
InventoryCount/InventoryCountLine/Item/SerializedLot/Lot/LotIDs/ID MITTKV.SVBANO; MMS307MI/GetPhysInvVar	The field indicates the lot number.
InventoryCount/InventoryCountLine/SerialNumber	
MITTKV.SVBANO; MMS307MI/GetPhysInvVar	The field indicates the lot number.
InventoryCount/InventoryCountLine/Quantity MITTKV.SVSTQI; MMS307MI/GetPhysInvVar	The field indicates the physical inventory quantity.
@unitCode MITTKV.SVUNMS; MMS307MI/GetPhysInvVar	The field indicates the basic unit of measure.
InventoryCount/InventoryCountLine/Facility/IDs/ID MITTKV.SVFACI; MMS307MI/GetPhysInvVar	The field indicates the facility ID.
@accountingEntity	The Caldination to the comment of the Caldination o
MITTKV.SVCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
InventoryCount/InventoryCountLine/Status/Code MITTKV.SVSTAC; MMS307MI/GetPhysInvVar	Set to "Counted".
InventoryCount/InventoryCountLine/TransactionDateTime MITTKV.SVRGDT MITTKV.SVRGTM.; MMS307MI/GetPhysInvVar	The field indicates the transaction date time.
InventoryCount/InventoryCountLine/AdjustmentQuantity	
MITTKV.SVDFQT; MMS307MI/GetPhysInvVar @unitCode	The field indicates the difference in basic unit of measure.
MITTKV.SVUNMS; MMS307MI/GetPhysInvVar	The field indicates the basic unit of measure.
InventoryCount/InventoryCountLine/UserArea MITTKV.SVWHSL; MMS307MI/GetPhysInvVar	The field indicates the location.

InventoryHold

inventorymora	
InventoryHold/IDs/ID	
For ProcessInventoryHold: MITTRA.MTWHLO; /	For ProcessInventoryHold: The field indicates the warehouse ID.
For SyncInventoryHold: MITTRA.MTWHLO	For SyncInventoryHold: The field indicates the inventory hold ID.
MITTRA.MTWHSL MITTRA.MTITNO MITTRA.MTBANO	 If agreement control property m3beUniqueID = false, the field indicates the warehouse.
MITTRA.MTCAMU	2) If agreement control property m3beUniqueID = true, the element is a concatenation of Location (WHSL) <10>, Item number (ITNO) <15>, Lot number (BANO) <20> and Container (CAMU) <20>. The numbers specified in brackets is the maximum length of each field. The position and concatenation of the fields are based on the field length. If the data does not consume the maximum length, the rest is padded with trailing spaces except for the last populated field which is right trimmed.
@accountingEntity MITTRA.MTCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MITTRA.MTWHLO; /	The field indicates the warehouse ID.
@variationID @lid	For SyncInventoryHold: The field indicates the sequence number that identifies the number of times that the BOD has been published.
	The field indicates the logical ID of the system.
InventoryHold/LastModificationDateTime MITTRA.MTLMTS; /	The field indicates the date and time the record was last changed.
InventoryHold/DocumentDateTime For ProcessInventoryHold: MITTRA.MTRGDT MITTRA.MTRGTM.; MWS070MI/GetStockTrans	The field indicates the date and time the record was created.
For SyncInventoryHold: MITTRA.MTRGDT MITTRA.MTRGTM.; /	
InventoryHold/ItemInstance/ItemID/ID For ProcessInventoryHold: MITTRA.MTITNO ; MWS070MI/GetStockTrans	The field indicates the item number.
For SyncInventoryHold: MITTRA.MTITNO . /	
@accountingEntity MITTRA.MTCONO CMNDIV.CCDIVI.; /	For ProcessInventoryHold: The field indicates the company and division, displayed as CONO_DIVI.
	For SyncInventoryHold: The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
InventoryHold/ItemInstance/Description For ProcessInventoryHold: MITMAS.MMITDS ; MMS200MI/GetItemBasic	The field indicates the item description.
For SyncInventoryHold: MITMAS.MMITDS : MMS200MI/GetItmMeas	
InventoryHold/ItemInstance/SerialNumber For ProcessInventoryHold: MITTRA.MTBANO ; MWS070MI/GetStockTrans For SyncInventoryHold:	The field indicates the lot number.
MITTRA.MTBANÓ ; /	
InventoryHold/ItemInstance/SerializedLot/SerialNumber For ProcessInventoryHold: MITTRA.MTBANO ; MWS070MI/GetStockTrans	For ProcessInventoryHold: The field indicates the lot number.

InventoryHold

InventoryHold	
InventoryHold/ItemInstance/HoldCodes/Code For ProcessInventoryHold: MITTRA.MTTTYP; MWS070MI/GetStockTrans	For ProcessInventoryHold: If transaction type is 22 (Purchase Rejected) or 25 (Purchase Putaway) or 23 (Purchase Approved), the field is set from the value of agreement control property m3belnspectHoldCode. This is used in the WMS integration to set the 'from' hold code.
InventoryHold/WarehouseLocation/ID For ProcessInventoryHold: MITWHL.MWWHLO; MMS005MI/GetWarehouse	The field indicates the warehouse.
For SyncInventoryHold: MITTRA.MTWHLO; / @accountingEntity MITTRA.MTCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
InventoryHold/WarehouseLocation/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates the warehouse name.
InventoryHold/TransactionDateTime MITTRA.MTTRDT MITTRA.MTTRTM.; MWS070MI/GetStockTrans	The field indicates the transaction date and time.
InventoryHold/HoldCodes/Code For ProcessInventoryHold: MITTRA.MTSTAS MITTRA.MTTTYP.; MWS070MI/GetStockTrans For SyncInventoryHold: MITTRA.MTSTAS ; MWS070MI/GetStockTrans	For ProcessInventoryHold: The field indicates the balance ID status. Set to 'Under Inspection' if 1. Set to 'Approved' if 2. Set to 'Rejected' if 3. If transaction type is 22 (Purchase Rejected), the field is set from the value of agreement control property m3beRejectHoldCode. If transaction type is 25 (Purchase Putaway) or 23 (Purchase Approved), the field null. This is used in WMS integration to release or add a hold code to the inventory. For SyncInventoryHold: The field indicates the balance ID status. Set to 'Pending' if 1. Set to 'Open' if 2. Set to 'Closed' if 3.
InventoryHold/HoldQuantity MITTRA.MTTRQT ; MWS070MI/GetStockTrans @unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction. The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
InventoryHold/UserArea For ProcessInventoryHold: PFTRNS.INERCV; PPS360MI/LstDetByIntRecN	For ProcessInventoryHold: The field indicates the external receiving number from the purchase order's delivery note package.

Invoice @type

For Common Invoice:

CINHED.CIIVTP; INVBODMI/GetHeader

For Common Invoice:

The field indicates the information type (IVTP). a) Set to 'CreditMemo' if information type is 02 or 12.

b) Set to 'Prepaid' if information type is 04.

c) Set to 'CreditMemo' if information type is blank, 00 or 01 and

invoice amount (TAMT) is less than 0.

d) Set to 'Invoice' if information type is blank, 00, 01 or 03 and

extended invoice number (RXIN) is blank.

e) Set to 'DebitMemo' if information type is blank, 00 or 01 and extended invoice number (CINO) is not blank and invoice amount

(TAMT) is greater than or equal to 0.

Invoice/InvoiceHeader/DocumentID/ID

For Bill for Prepayment:

OOPINH.OHPPYN; OIS125MI/LstPrePayByCO

For Common Invoice: CINHED.CIINYR +

CICINO; INVBODMI/GetHeader

For Bill for Prepayment:

The field indicates the payment request number.

For Common Invoice:

The field indicates the invoice document ID.

It is a concatenation of Invoice Year (INYR) <4> + Invoice Number (CINO) <15> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case CINO, is trimmed if it does not consume the maximum length.

@accountingEntity

For Bill for Prepayment:

For Bill for Prepayment:

OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO

For Bill for Prepayment:

The field indicates the company and division.

For Common Invoice:

The field indicates the company and division, displayed as

CONO DIVI.

For Bill for Prepayment:

The field indicates the warehouse ID.

For Common Invoice:

OOHEAD.OAWHLO; OIS100MI/GetOrderHead

CINHED.CIWHLO; INVBODMI/GetHeader

@variationID

@lid

@location

For Common Invoice:

The field indicates the warehouse.

For Bill for Prepayment:

The field indicates the number of variation for the object

For Common Invoice:

The field indicates the sequence number that identifies the number of

times that the BOD has been published.

For Bill for Prepayment:

The field indicates the logical ID.

For Common Invoice:

The field indicates the logical ID of the system.

Invoice/InvoiceHeader/AlternateDocumentID/ID

For Bill for Prepayment:

For Common Invoice:

OOPINH.OHORNO; OIS125MI/LstPrePayByCO

For Bill for Prepayment:

The field indicates the Order number of the payment request is 01

else Invoice number.

CINHED.CIINPX + For Common Invoice: CIIVNO; INVBODMI/GetHeader

It is a concatenation of Invoice prefix (INPX) <6> + Invoice Number

(IVNO) <9>

Hyphen (-) is used as delimiter or separator between fields. If IVNO is

less than 9 then pad with leading zeroes.

@accountingEntity

@location

For Bill for Prepayment:

For Common Invoice:

OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO

For Bill for Prepayment:

The field indicates the company and division.

For Common Invoice:

The field indicates the company and division, displayed as

CONO_DIVI.

For Common Invoice:

For Bill for Prepayment:

The field indicates the warehouse

Invoice/InvoiceHeader/DisplayID

For Bill for Prepayment:

CINHED.CIWHLO; INVBODMI/GetHeader

OOPINH.OHPPYN; OIS125MI/LstPrePayByCO

For Common Invoice:

The field indicates the invoice number.

The field indicates the payment request number.

For Common Invoice: CINHED.CICINO; INVBODMI/GetHeader

181 May 26, 2023

Invoice/InvoiceHeader/LastModificationDateTime	
For Bill for Prepayment: OOPINH.OHDTPR; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the last modification date.
For Common Invoice: CINHED.CILMTS; /	For Common Invoice: The field indicates the most recent date and time a change was made to the record.
Invoice/InvoiceHeader/LastModificationPerson/IDs/ID	
For Common Invoice: CINHED.CICHID; / @accountingEntity	For Common Invoice: The field indicates the ID of the user that last updated the record.
For Common Invoice: CINHED.CICONO CINHED.CIDIVI.; /	For Common Invoice: The field indicates the company and division, displayed as CONO_DIVI.
Invoice/InvoiceHeader/LastModificationPerson/Name	
For Common Invoice: CMNUSR.JUTX40; MNS150MI/GetUserData	For Common Invoice: The field indicates the name of the user that last updated the record.
Invoice/InvoiceHeader/DocumentDateTime	
For Bill for Prepayment: OOPINH.OHRGDT + OHRGTM; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the document date and time
For Common Invoice: CINHED.CIIVDT; INVBODMI/GetHeader	For Common Invoice: The field indicates the invoice date.
Invoice/InvoiceHeader/Description	For Dill for December 1
For Bill for Prepayment: OOPINH.OHPYRE; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the request reference number.
For Common Invoice: CINHED.CIRXIN; INVBODMI/GetHeader @languageID	For Common Invoice: The field indicates the extended invoice number reference (RXIN).
For Bill for Prepayment: OOPINH.OHLNCD; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the language.
Invoice/InvoiceHeader/Note	
For Bill for Prepayment: OOPINH.OHIDAT; OIS125MI/LstPrePayByCO / LstFinPayByIVNO	For Bill for Prepayment: The field indicates the Text 1 and Text 2.
For Common Invoice: CSYTXH.THTX60; CRS980MI/SltTxtBlock	For Common Invoice: The field indicates the note in the header.
@noteID For Common Invoice:	For Common Invoice:
CINTXT.CITXID CITXVR; INVBODMI/SelTexts	The field indicates the header note ID. It is a concatenation of Text ID (TXID) <13> + Text Block (TXVR) <10> without separator. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the NoteID except for the last one. The last field in the concatenation, in this case TXVR, is trimmed if it does not consume the maximum length.
@type	For Common Invaion
For Common Invoice: CINTXT.CITXPR CIIBTC; INVBODMI/SelTexts	For Common Invoice: The field indicates the note type (TXPR) and text category (IBTC) Set to 'Pre-Text' if TXPR is 1 + the text category (IBTC) with separator '_'.
	 Set to 'Post-Text' if TXPR is 2 + the text category (IBTC) with separator '_'.
	NB: The text category (IBTC) including separator '_' is only added if the control property 'm3beTextCategory' has been activated (true), default value is false.
@languageID	
For Common Invoice: CINTXT.CILNCD; INVBODMI/SelTexts	For Common Invoice: The field indicates the language of the note.
Invoice/InvoiceHeader/DocumentReference	The held indicates the fallydage of the flote.
@type For Common Invoice:	For Bill for Prepayment:
CINDRE.CIDRTP; INVBODMI/SelDocReference	Set to 'SalesOrder'
	For Common Invoice: The field indicates the document reference type. IF DRTP is not 'TransportDocument', publish DRTP.
Invoice/InvoiceHeader/DocumentReference/DocumentID/ID	Car Dill far Drangumant
For Bill for Prepayment: OOPINH.OHCOIV; OIS125MI/LstPrePayByCO	For Bill for Prepayment: This field indicates the customer order number.
For Common Invoice: CINDRE.CIDIDN; INVBODMI/SelDocReference @accountingEntity	For Common Invoice: The field indicates the document reference number.
© 3-,	For Bill for Prepayment: The field indicates the company and division.

(Planation	For Common Invoice: The field indicates the company and division, displayed as CONO_DIVI.
@location For Common Invoice:	For Common Invoice:
CINHED.CIWHLO; INVBODMI/GetHeader	The field indicates the warehouse.
	NB: Not populated for Document type 'SupplierInvoice'.
Invoice/InvoiceHeader/DocumentReference/LineNumber	For Common Invoice
For Common Invoice:	For Common Invoice: The field indicates the line number.
Invoice/InvoiceHeader/DocumentReference/SubLineNumber	
For Common Invoice: CINDRE.CIDLSN: INVBODMI/SelDocReference	For Common Invoice: The field indicates the sub-line number.
Invoice/InvoiceHeader/PrePaymentInvoiceIndicator	
For Common Invoice:	For Common Invoice:
CINHED.ICIVTP; INVBODMI/GetHeader	The field indicates if the invoice is an advance invoice. If invoice type (IVTP) = 3, set to 'true', otherwise, set to 'false'.
Invoice/InvoiceHeader/ExtendedAmount	
For Bill for Prepayment: OOPINH.OHIVAM; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the extended amount (IVAM - (VTA1 + VTA2))
For Common Invoice: CINHED.ICEXTA; INVBODMI/GetHeader	For Common Invoice: The field indicates the total order value before Discount and excluding VAT and Charges in transaction currency. In case of correction invoice - method 1, the field indicates the difference for total order value.
@currencyID For Bill for Prepayment:	For Bill for Prepayment:
OOPINH.OHCUCD; OIS125MI/LstPrePayByCO	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/ExtendedBaseAmount	The flora findicates the transaction currency.
For Common Invoice:	For Common Invoice:
CINHED.CIEXLA; INVBODMI/GetHeader	The field indicates the total order value before Discount and excluding
	VAT and Charges in local currency. In case of correction invoice - method 1, the field indicates the difference for total order value.
@currencyID	difference for total order value.
For Common Invoice: CINHED.CILOCD: INVBODMI/GetHeader	For Common Invoice:
Invoice/InvoiceHeader/ExtendedReportAmount	The field indicates the local currency.
For Common Invoice:	For Common Invoice:
CINHED.CIEXLA	The field indicated the 'ExtendedBaseAmount' converted to Reporting
CIRCUC CIRCUD	currency of the base country and exchange rate as indicated in the
CIRCUE	invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the
CIRCUF	currency.
CIDCCD; INVBODMI/GetHeader	The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID	
For Common Invoice: CINHED.CIRCUD: INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/PreSubunitRoundedTotalAmount	The field indicated the reporting outlettey.
For Common Invoice:	For Common Invoice:
CINHED.CITAMT	The field indicates the amount before rounding-off.
CIROAM; INVBODMI/GetHeader	IF ROAM > 0 then Total Amount (TAMT) - rounding-off (ROAM). IF ROAM < 0 then Total Amount (TAMT) + rounding-off (ROAM)
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceHeader/SubunitRoundingAmount	
For Common Invoice:	For Common Invoice:
CINHED.CIROAM; INVBODMI/GetHeader @currencyID	The field indicates the rounding-off amount.
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceHeader/TotalAmount	Can Dill fan Dranay maant
For Bill for Prepayment: OOPINH.OHIVAM; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the amount including taxes, charges and allowances in local currency. Payment request amount.
For Common Invoice: CINHED.CITAMT; INVBODMI/GetHeader	anomanoes in local carrettey. I ayment request amount.

For Common Invoice: The field indicates the invoice total in transaction currency. @currencyID For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHCUCD; OIS125MI/LstPrePayByCO The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader For Common Invoice: The field indicates the transaction currency. Invoice/InvoiceHeader/TotalBaseAmount For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHIVAM; OIS125MI/LstPrePayByCO The field indicates the amount including taxes, charges and allowances in local currency. Payment request amount. For Common Invoice: CINHED.CITOLA; INVBODMI/GetHeader For Common Invoice: The field indicates the invoice total in local currency. @currencvID For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHCUCD; OIS125MI/LstPrePayByCO The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader For Common Invoice: The field indicates the local currency. Invoice/InvoiceHeader/TotalReportAmount For Common Invoice: For Common Invoice: CINHED.CITOLA The field indicated the 'TotalBaseAmount' converted to Reporting CIRCUD currency of the base country and exchange rate as indicated in the **CIRCUC** invoice header table (CINHED). The amount is presented with 2 **CIRCUE** decimals but rounded to the number of decimals (DCCD) for the CIRCUF CIDCCD; INVBODMI/GetHeader The report amount is required by some countries for the electronic invoice sent to the authorities. @currencyID For Common Invoice: For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader The field indicated the reporting currency. Invoice/InvoiceHeader/PrePayment/PaidAmount For Common Invoice: For Common Invoice: CINPRE.CIAMTC; INVBODMI/SelPrepayments The field indicates the advance invoice amount. @currencyID For Common Invoice: For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader The field indicates the transaction currency. Invoice/InvoiceHeader/PrePayment/PaymentReferenceText For Common Invoice: For Common Invoice: CINPRE.CIA200; INVBODMI/SelPrepayments The field indicates the advance invoice text. Invoice/InvoiceHeader/PrePayment/DocumentReference @type For Common Invoice: Set to 'Invoice' Invoice/InvoiceHeader/PrePayment/DocumentReference/DocumentID/ID For Common Invoice: For Common Invoice: CINPRE.CIYEA + The field indicates the customer invoice number. It is a concatenation of Invoice Year (YEA4) <4> + Invoice Number CIEXIN; INVBODMI/SelPrepayments (EXIN) <14> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the PrePayment document ID except for the last one. The last field in the concatenation, in this case EXIN, is trimmed if it does not consume the maximum length. @accountingEntity For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. @location For Common Invoice: For Common Invoice: CINHED.CIWHLO; INVBODMI/GetHeader The field indicates the warehouse of the Advance (prepayment) invoice if existing in (CMS500) Invoice/InvoiceHeader/SupplierParty/PartyIDs/ID For Bill for Prepayment: For Bill for Prepayment: CMNDIV.CCCONO + CCDIVI; MNS100MI/GetBasicData The field indicates a company and division. For Common Invoice: For Common Invoice: CINHED.CICONO + The field indicates the company and division. CIDIVI: / @accountingEntity For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO The field indicates the company and division.

	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/SupplierParty/PartyIDs/TaxID	
For Bill for Prepayment: CMNDIV.CCVRNL; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates the Tax ID of the company
For Common Invoice: 1) CINPTY.CIVRNO 2) CINPTY CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININO	For Common Invoice: The field indicates the following Tax IDs of the supplier. 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryldentificationNumber (CORG). 4) CountryldentificationNumber (COR2). 5) CountryldentificationNumber (COR4). 6) National Identity Number (NINO). 7) National Identity Number (NIN2).
@schemeName	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceHeader/SupplierParty/Name For Bill for Prepayment: CMNDIV.CCCONM; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates the name of the company.
For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty	For Common Invoice: The field indicates the company/division name.
Invoice/InvoiceHeader/SupplierParty/Location/Name	
For Bill for Prepayment: CMNDIV.CCWHLO; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates the warehouse ID.
For Common Invoice: CINHED.CIWHLO; INVBODMI/GetHeader	For Common Invoice: The field indicates the warehouse.
Invoice/InvoiceHeader/SupplierParty/Location/Address @type	Cot to House
Invaire // mysical leader/Cumplier Portry/Leastion/Address/Attention/CAI	Set to 'text'.
Invoice/InvoiceHeader/SupplierParty/Location/Address/AttentionOfNa For Bill for Prepayment: CMNDIV.CCOREF; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates the person who the customer may contact regarding customer.
For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: The field indicates the contact name.
Invoice/InvoiceHeader/SupplierParty/Location/Address/AddressLine For Bill for Prepayment: CMNDIV.COA1, COA2,	For Bill for Prepayment: The field indicates address line for each company.
COA3, COA4; MNS100MI/GetBasicData	For Common Invoice: The field indicates the address line.
COA3, COA4; MNS100MI/GetBasicData For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	For Common Invoice:
COA3, COA4; MNS100MI/GetBasicData For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3	For Common Invoice:
COA3, COA4; MNS100MI/GetBasicData For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	For Common Invoice: The field indicates the address line. For Bill for Prepayment:
COA3, COA4; MNS100MI/GetBasicData For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	For Common Invoice: The field indicates the address line. For Bill for Prepayment: The field indicates an incremental number For Common Invoice:
COA3, COA4; MNS100MI/GetBasicData For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty @sequence Invoice/InvoiceHeader/SupplierParty/Location/Address/CityName For Bill for Prepayment:	For Common Invoice: The field indicates the address line. For Bill for Prepayment: The field indicates an incremental number For Common Invoice: The field indicates the address line sequence. For Bill for Prepayment: The field indicates the city in an address. For Common Invoice: The field indicates the city name.

Infor May 26, 2023 185

CINPTY.CIECAR; INVBODMI/GetParty

	For Common Invoice: The field indicates an area, province or state within a country.
@listID	For Bill for Prepayment: The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'
	For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceHeader/SupplierParty/Location/Address/CountryCode For Bill for Prepayment:	For Bill for Prepayment:
CMNDIV.CCCSCD; MNS100MI/GetBasicData	The field indicates a country.
For Common Invoice: CINPTY.CICSCD; INVBODMI/GetParty @/listID	For Common Invoice: The field indicates the country code.
	Set to 'Countries'.
Invoice/InvoiceHeader/SupplierParty/Location/Address/PostalCode For Bill for Prepayment: CMNDIV.CCPONO; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates a postal code for a specific address.
For Common Invoice: CINPTY.CIPONO; INVBODMI/GetParty	For Common Invoice: The field indicates the postal code.
Invoice/InvoiceHeader/SupplierParty/Contact/Name	The field indicates the postal code.
For Bill for Prepayment: CMNDIV.CCOREF; MNS100MI/GetBasicData	For Bill for Prepayment: The field indicates the person who the customer may contact regarding customer.
For Common Invoice: .; MNS100MI/GetBasicData	For Common Invoice: The field indicates the contact name.
Invoice/InvoiceHeader/SupplierParty/Contact/Communication	
@sequence	For Common Invoice: The field indicates the contact sequence number.
@preferredIndicator	For Common Invoice: Set to 'false'.
Invoice/InvoiceHeader/SupplierParty/Contact/Communication/Channe	
	For Common Invoice: Set to "Phone" if telephone number is 1, 2, facsimile number or mobile.
@listID	For Common Invoice: Set to "Communication Channels".
Invoice/InvoiceHeader/SupplierParty/Contact/Communication/UseCod	
rr	For Common Invoice: Set to "Office" if telephone number is 1 or 2.
@listID	Set to "Fax" if facsimile number.
	For Common Invoice: Set to "Communication Use Codes".
Invoice/InvoiceHeader/SupplierParty/Contact/Communication/DialNum For Common Invoice:	For Common Invoice:
.; MNS100MI/GetBasicData	The field indicates the phone number.
Invoice/InvoiceHeader/SupplierParty/Contact/Communication/Prefere	nce/Indicator For Common Invoice: Set to 'false'.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty	For Common Invoice:
	For Common Invoice: The section is populated in case a fiscal representive (party type 'SupplierTaxRep') is connect to the invoice. NB: The SupplierParty/TaxRepresentativeParty' is only populated if the control property 'm3beSupplierTaxRep' has been activated (true), default value is false.

default value is false. Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/PartyIDs/ID

For Common Invoice: CINPTY.CISUNO; INVBODMI/GetParty For Common Invoice:

The field indicates the Internal supplier number (SUNO) connected to the Fiscal representative in (TXS030).

Infor May 26, 2023

IIIVOICE	
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/PartyID	
For Common Invoice: CINPTY.CIVRNO, CICORG, CICOR2, CIVRNL; INVBODMI/GetParty	For Common Invoice: The field indicates the Tax IDs of the fiscal representative (internal
Clive 11. Clivitino, Clooks, Clooks, Clivitine, livibodivil/Getraity	supplier).
	- VAT registration number (VRNO)
	- Organization number 1 (CORG)
	 Organization number 2 (COR2) Tax declaration number (VRNL) - M3BE exception for Hungary
	using (COR2)
@schemeName	For Common Invoice:
	Set to:
	- 'TaxIdentificationNumber' for VAT registration number (VRNO)
	 'CountryIdentificationNumber' for Organization number 1 (CORG) 'CountryIdentificationNumber' for Organization number 2 (COR2)
	- 'TaxDeclarationNumber' for Tax declaration number (VRNL)
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Name	
For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty	For Common Invoice: The field indicates the Name (NAME) of the fiscal representative
City 11.0ivAvic, iivbobivii/Get arty	(internal supplier) retrieved from address type 01.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Location	on/Address
@type	For Common Invoice:
	Set to 'text'.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Location	
For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3	For Common Invoice: The field indicates the Address (CUA1-CUA4) of the fiscal
CICUA4; INVBODMI/GetParty	representative (internal supplier) retrieved from address type 01.
@sequence	
	For Common Invoice: The field indicates the address line sequence.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Locatio	
For Common Invoice:	For Common Invoice:
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the City (TOWN) of the fiscal representative (internal supplier) retrieved from address type 01.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Locatio	
For Common Invoice:	For Common Invoice:
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates the Area/State (ECAR) of the fiscal representative (internal supplier) retrieved from address type 01.
@listID	(Internal supplier) retrieved from address type or.
	For Common Invoice:
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Location For Common Invoice:	n/Address/CountryCode For Common Invoice:
CINPTY.CICSCD; INVBODMI/GetParty	The field indicates the Country (CSCD) of the fiscal representative
	(internal supplier) retrieved from address type 01.
@listID	For Common Invoice:
	Set to 'Countries'.
Invoice/InvoiceHeader/SupplierParty/TaxRepresentativeParty/Location For Common Invoice:	n/Address/PostalCode For Common Invoice:
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the Postal code (PONO) of the fiscal
	representative (internal supplier) retrieved from address type 01.
Invoice/InvoiceHeader/SupplierParty/SalesContact/Name For Bill for Prepayment:	For Bill for Prepayment:
CMNDIV.CCOREF; MNS100MI/GetBasicData	The field indicates the person who the customer may contact
	regarding customer.
Invoice/InvoiceHeader/CustomerParty/PartyIDs/ID	For Bill for Dronovment
For Bill for Prepayment: OOPINH.OHCUNO; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the unique identification of a customer. It can
COT INT. COTOCINO, CIC 125MI/LEST TOT BYBYCO	contain up to ten positions, and is alphanumeric.
For Common Invoice: CINPTY.CICUNO; INVBODMI/GetParty	For Common Invoice:
GINT 11.GIGGING, INVEGDINI/GELFAILY	The field indicates the customer number.
@schemeName	For Common Invoice.
	For Common Invoice: Set to 'CustomerNumber'.
@accountingEntity	
For Bill for Prepayment: OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the accounting entity.
OOI IIIII.OHOONOTOHDIVI, OIO120WI/ESTETERAYBYOO	If CustomerPartyMaster is enabled in BOD Processor Master AE tab,
	this is displayed as Company (CONO). Otherwise, this is displayed as
Infor May 26, 203	this is displayed as Company (CONO). Otherwise, this is displayed

	Company and Division (CONO_DIVI).
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/CustomerParty/PartyIDs/TaxID For Common Invoice: 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININO. 7) CINPTY.CININ2.; INVBODMI/GetParty @schemeName	For Common Invoice: The field indicates the following Tax IDs of the customer: 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryIdentificationNumber (CORG). 4) CountryIdentificationNumber (COR2). 5) CountryIdentificationNumber (COR4). 6) National Identity Number (NINO). 7) National Identity Number (NIN2).
<u> </u>	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceHeader/CustomerParty/Name For Common Invoice:	For Common Invoice:
CINPTY.CINAME; INVBODMI/GetParty	The field indicates the customer name.
Invoice/InvoiceHeader/CustomerParty/Location/Address	
@type	For Common Invoice: Set to 'text'.
Invoice/InvoiceHeader/CustomerParty/Location/Address/AttentionOff	lame
For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: The field indicates the contact name.
Invoice/InvoiceHeader/CustomerParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty @sequence	For Common Invoice: The field indicates the address lines.
	For Common Invoice: The field indicates the address line sequence.
Invoice/InvoiceHeader/CustomerParty/Location/Address/CityName For Common Invoice:	For Common Invoice:
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
Invoice/InvoiceHeader/CustomerParty/Location/Address/CountrySubs For Common Invoice:	DivisionCode For Common Invoice:
CINPTY.CIECAR; INVBODMI/GetParty @listID	The field indicates an area, province or state within a country.
	For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'States' if CountryCode is MX (Mexico) Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceHeader/CustomerParty/Location/Address/CountryCode For Common Invoice:	
CINPTY.CICSCD; INVBODMI/GetParty @listID	For Common Invoice: The field indicates the country code.
	For Common Invoice: Set to 'Countries'.
Invoice/InvoiceHeader/CustomerParty/Location/Address/PostalCode For Common Invoice: CINPTY.CIPONO; INVBODMI/GetParty	For Common Invoice: The field indicates the postal code.
Invoice/InvoiceHeader/CustomerParty/Communication/ChannelCode	For Common Invoice:
@listID	Set to 'Email' in case of EMAL.
	For Common Invoice: Set to 'Communication Channels'.
Invoice/InvoiceHeader/CustomerParty/Communication/UseCode	For Common Invoice:
@listID	Set to 'Office'.

	For Common Invoice:
	Set to 'Communication Use Codes'.
Invoice/InvoiceHeader/CustomerParty/Communication/URI	
For Common Invoice:	For Common Invoice:
CINPTY.CIEMAL; INVBODMI/GetParty	The field indicates the email address of the customer for the email
	type 01-Customer in (CRS111).
Invoice/InvoiceHeader/CustomerParty/Communication/Preference	5 O
	For Common Invoice: Set to 'false'.
Invoice/InvoiceHeader/CustomerParty/Contact/ID	Get to Taise.
For Common Invoice:	For Common Invoice:
OCUSCO.CCNPE; CMS055MI/LstByCustomer	The field indicates the contact ID.
@accountingEntity	
	For Common Invoice:
	The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/CustomerParty/Contact/Name	OCNO_BIVI.
For Common Invoice:	For Common Invoice:
CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication	
@preferredIndicator	
	For Common Invoice:
	Set to 'false'.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Cha	
	For Common Invoice: Set to "Phone" if telephone number is 1, 2, facsimile number or
	mobile.
	Set to "EMail" if e-mail address.
@listID	
	For Common Invoice: Set to "Communication Channels".
Invoice/InvoiceHeader/CustomerPorty/Contact/Communication/Hea	
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Use	For Common Invoice:
	Set to "Office" if telephone number is 1 or 2.
	Set to "Fax" if facsimile number.
@listID	5 0 I I
	For Common Invoice: Set to "Communication Use Codes".
For Common Invoice:	For Common Invoice:
CCUCON.CCPHNO	The field indicates the telephone number.
CCPHN2; CRS618MI/Get	
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Add	ress
@type	For Common Invoice:
	Set to 'text'.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Add	
For Common Invoice:	For Common Invoice:
CCUCON.CCCUA1	The field indicates the address lines.
CCCUA2	
CCCUA3	
CCCUA4; CRS618MI/Get @sequence	
@ocque.noc	For Common Invoice:
	The field indicates the address sequence number.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Add	ress/CityName
For Common Invoice:	For Common Invoice:
CCUCON.CCTOWN; CRS618MI/Get	The field indicates the city name.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Add	
For Common Invoice:	For Common Invoice:
CCUCON.CCECAR; CRS618MI/Get @listID	The field indicates an area, province or state within a country.
<u></u>	For Common Invoice:
	Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Add	
For Common Invoice:	For Common Invoice:
CCUCON.CCCSCD; CRS618MI/Get	The field indicates the country code.
@listID	•
	For Common Invoice:
	Set to 'Countries'.

Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Address	ess/PostalCode
For Common Invoice:	For Common Invoice:
CCUCON.CCPONO; CRS618MI/Get	The field indicates the postal code.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/URI For Common Invoice:	For Common Invoice:
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the email address.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/HTML	PreferredIndicator
	For Common Invoice:
In the state of th	Set to 'false'.
Invoice/InvoiceHeader/CustomerParty/Contact/Communication/Preference	rence/Indicator For Common Invoice:
	Set to 'false'.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/PartyIDs/ID	
For Common Invoice:	For Common Invoice:
CBANAC.BCBKNO; CRS692MI/GetBankAccount	The field indicates the bank number (BKNO) of the company's bank
	account. The RemitToParty block is published for all payment class except 0-Cash.
@schemeName	5,65 pt 0 Gusti.
	For Common Invoice:
@accounting Futitus	Set to 'BankPartyIdentification'.
@accountingEntity	For Common Invoice:
	The field indicates the Accounting entity (this is the translated M3 BE
	company and division).
Invoice/InvoiceHeader/RemitToParty/FinancialParty/PartyIDs/BICID	
For Common Invoice:	For Common Invoice:
CBANAC.BCSWBI CBANMA.BKSWIC.; CRS692MI/GetBankAccount	The field indicates the SWIFT code of the company's bank account (SWBI). If SWBI is not provided, SWIFT code of the company's bank
CDANNIA.DROWIC., CROO92MI/GetDankAccount	(SWIC) is published.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/Name	, , ,
For Common Invoice:	For Common Invoice:
CBANMA.BKBKNM; CRS690MI/GetBasicData	The field indicates the bank name of the company's bank account.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/ClearingSystemN	
For Common Invoice: CBANAC.BCCLSI	For Common Invoice: The field indicates the system clearing ID. It is a concatenation of
BCCLSN; CRS692MI/GetBankAccount	Clearing System ID (CLSI) + Clearing System number (CLSN)
	without separator.
	All fields are trimmed if it does not consume the maximum length.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/BranchParty/Party	
For Common Invoice: CBANBR.BRSWIC; CRS692MI/GetBankAccount	For Common Invoice: The field indicates SWIFT code of the company's bank branch.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialAccoun	· ·
For Common Invoice:	For Common Invoice:
CBANAC.BCBACN; CRS692MI/GetBankAccount	The field indicates the Bank Account Number of the company.
Invoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialAccoun	t/IBANID
For Common Invoice:	For Common Invoice:
CBANAC.BCIBAN; CRS692MI/GetBankAccount	The field indicates the International Bank Account number of the
Invoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialAccoun	company. t/CurrencyCode
For Common Invoice:	For Common Invoice:
CBANAC.BCCUCD; CRS692MI/GetBankAccount	The field indicates the currency of the bank.
@listID	
	For Common Invoice: Set to 'Currency'.
Invoice/InvoiceHeader/StructuredCreditorReference	Oct to Currency.
For Common Invoice:	For Common Invoice:
CINHED.CIPAIN; INVBODMI/GetHeader	The field indicates the Parallel invoice number (PAIN) of type 1
O and a small a small	(number created by M3BE using setting in CMS090).
@schemeName For Common Invoice:	For Common Invoice:
CINHED.CIRNRU; INVBODMI/GetHeader	The field indicates the Reference number rule (RNRU), for example
	OCR or KID, of the parallel invoice number.
Invoice/InvoiceHeader/ReasonCode	
	For Bill for Prepayment:
	The field indicates the reason code.
	If PPYT = 01, set to 'Prepay'; If PPYT = 02, set to 'FinalPP'
Invoice/InvoiceHeader/PaymentTerm/Description	,
For Common Invoice:	For Common Invoice:
CINPTE.CITEL1 + CITEL2; INVBODMI/SelPaymentTerms	The field indicates the payment term description. It is a concatenation
	of Text1 (TEL1) + Text2 (TEL2) with ' ' as separator. All fields are
Invoice/InvoiceHeader/PoumentTerm/Note	trimmed if it does not consume the maximum length.
Invoice/InvoiceHeader/PaymentTerm/Note For Common Invoice:	
. c. Johnnon myoloc.	

CINPTE.CITX15; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the payment term short description.
Invoice/InvoiceHeader/PaymentTerm/PaymentTermCode	
For Common Invoice: CINPTE.CITEPY; INVBODMI/SelPaymentTerms @accountingEntity	For Common Invoice: The field indicates the payment term code.
waccounting Emity	For Common Invoice: The field indicates the company and division, displayed as
nvoice/InvoiceHeader/PaymentTerm/Term/ID	CONO DIVI.
For Bill for Prepayment: OOPINH.OHTEPY; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the payment term.
For Common Invoice: CINPTE.CITEPY; INVBODMI/SelPaymentTerms @accountingEntity	For Common Invoice: The field indicates the payment term code.
gaccountingEntity	For Bill for Prepayment: The field indicates the company and division.
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/PaymentTerm/Term/Description For Bill for Prepayment: CSYTAB.CTPARM; CRS175MI/GetGeneralCode	For Bill for Prepayment: The field indicates the payment term description.
For Common Invoice: CINPTE.CITEL1 + CITEL2; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with ' ' as separator. All fields are trimmed if it does not consume the maximum length.
Invoice/InvoiceHeader/PaymentTerm/Term/EffectiveDateTime	
For Bill for Prepayment: OOPINH.OHRQDT; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the requested date. The request date will be used when calculating the due date.
For Common Invoice: CINPTE.CIIVDT; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the invoice date.
Invoice/InvoiceHeader/PaymentTerm/Term/DueDateTime	E D'II (D
For Bill for Prepayment: OOPINH.OHDUDT; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the date the invoice is due for payment.
For Common Invoice: CINPTE.CIDUDT; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the invoice due date.
Invoice/InvoiceHeader/PaymentTerm/Term/Amount For Common Invoice:	For Common Invoice:
CINPTE.CIAMTC; INVBODMI/SelPaymentTerms @currencyID	The field indicates the amount in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/PaymentTerm/Term/BaseAmount	The flora findicates the transaction carronay.
For Common Invoice: CINPTE.CIAMTC; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the amount in local currency.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader Invoice/InvoiceHeader/PaymentTerm/Term/ReportAmount	The field indicates the local currency.
For Common Invoice:	For Common Invoice:
CINPTE.CIAMLC	The field indicated the 'PaymentTerm/Term/BaseAmount' converted
CINHED.CIRCUC CINHED.CIRCUD	to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/SelPaymentTerms	(DCCD) for the currency. The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader Invoice/InvoiceHeader/PaymentTerm/Discount/ID	The field indicated the reporting currency.
For Common Invoice: CINPTE.CITECD; INVBODMI/SelPaymentTerms	For Common Invoice: The field indicates the cash discount ID. If cash discount date1 (CDT1) is not 0, it is a concatenation of TECD
	+ '-' + '1'. If cash discount date2 (CDT2) is not 0, it is a concatenation of TECD
	+ '-' + '2'. If cash discount date3 (CDT3) is not 0, it is a concatenation of TECD + '-' + '3'.

Invoice Invoice/InvoiceHeader/PaymentTerm/Discount/Description For Common Invoice: For Common Invoice: CINPTE.CITEL3 + The field indicates the cash discount text. It is a concatenation of Text1 (TEL3) + Text2 (TEL4) with ' ' as separator. All fields are trimmed if it does not consume the maximum length. CITEL4; INVBODMI/SelPaymentTerms Invoice/InvoiceHeader/PaymentTerm/Discount/DueDateTime For Common Invoice: For Common Invoice: The field indicates the cash discount date 1 to 3. CINPTE.CICDT1 CICDT2 CICDT3; INVBODMI/SelPaymentTerms Invoice/InvoiceHeader/PaymentTerm/Discount/AmountBasisCode For Common Invoice: For Common Invoice: CINPTE.CIGRNT; INVBODMI/SelPaymentTerms The field indicates the cash discount method. Set to 'TotalAmount' if cash discount method (GRNT) is 1 Set to 'ExtendedPretaxAmount' if cash discount method (GRNT) is 2. @listID For Common Invoice: Set to 'Amount Basis' Invoice/InvoiceHeader/PaymentTerm/Discount/DiscountPercent For Common Invoice: For Common Invoice: CINPTE.CICDP1 The field indicates the cash discount percentage 1 to 3. CICDP2 Format: 1% = 1.000. CICDP3; INVBODMI/SelPaymentTerms Invoice/InvoiceHeader/PaymentMethodCode For Common Invoice: For Common Invoice: CINHED.CIPYCD The field indicates the Payment method translated to the standard CICRDC; INVBODMI/GetHeader Infor Payment Method code. Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class is 1 or 2. Set to 'ElectronicFundsTransfer' if payment class is 3 and credit card indicator (CRDC) is 0. Set to 'CreditCard/DebitCard' if payment class is 3 and credit card indicator (CRDC) is 1. Set to 'BankDraft' if payment class is 4 Set to 'DirectDebit' if payment class is 5 Set to 'Factoring' if payment class is 6. @listID For Common Invoice: Set to 'Payment Methods' Invoice/InvoiceHeader/Tax For Common Invoice: For Common Invoice: .; INVBODMI/GetTaxDetails If Tax type (TXTB) = 'SalesTax' then block must be created per field VTID, VTI2, VTI3, VTI4 and VTI5. SelHeaderTax Else if Tax type (TXTB) = 'Perception' then block must be created per field VTID. Otherwise, as is. @sequenceNumber For Common Invoice: For Common Invoice: CINVTD.CITAXS; INVBODMI/SelHeaderTax The field indicates the sequence number. @type For Common Invoice: CINVTD.CITXTB: INVBODMI/GetTaxDetails The field indicates the tax type. The values can be 'SalesTax', 'VAT' or 'Perception'. @subType For Common Invoice: For Common Invoice: CINVTD.CITSAB; INVBODMI/GetTaxDetails Create this attribute only if Tax method (TATM) = 2. The field indicates the standard tax code based on the Invoice translation 'TaxsubType' (CRS881/882). Alternative if generic translation not used: Actual value of TSAB. Invoice/InvoiceHeader/Tax/ID For Bill for Prepayment: For Bill for Prepayment: The field indicates the VAT Code.

OOPINH.OHVTCD; OIS125MI/LstPrePayByCO

For Common Invoice: CINVTD.CIVTCD

CISETC CITAXC; INVBODMI/GetTaxDetails

@accountingEntity

For Common Invoice:

The field indicates the VAT/Tax code. IF Tax type (TXTB) = 'Perception', publish service tax calculation

code (SETC).

Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/

address (TAXC).

Otherwise, publish VAT code (VTCD).

For Bill for Prepayment:

The field indicates the company and division.

For Common Invoice:

May 26, 2023

IIIVOICE	The field indicates the company and division, displayed as
	The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/Tax/TaxJurisdicationCodes/Code	
For Common Invoice:	For Common Invoice:
CINVTD.CITAJ1; INVBODMI/GetTaxDetails	The field indicates the Tax juridisction code.
	Create this element only if Tax method (TATM) = 2.
Invoice/InvoiceHeader/Tax/BasisAmount	For Order and Investory
For Common Invoice: CINVTD.CIBASA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the basis amount of the tax in transaction currency.
@currencyID	The hold maledate are paste amount of the tax in transaction earliersy.
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Tax/BasisTaxAuthorityAmount	The field indicates the transaction currency.
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA	The field indicated the 'Tax/BasisBaseAmount' converted to Tax
CINHED.CIIBT1 CINHED.CIIBT2	authority currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The
CINHED.CIIBT4	amount is presented with 2 decimals but rounded to the number of
CINHED.CIIBT5	decimals (IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the
Con loadol	currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD).
	The amount in tax authority currency is required by some countries
	for the electronic invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIIBT1; INVBODMI/GetHeader	The field indicated the Tax authority currency (IBT1) of the base
- <u> </u>	country as indicated in the invoice header table (CINHED).
Invoice/InvoiceHeader/Tax/BasisBaseAmount	5 0
For Common Invoice: CINVTD.CIBALA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the basis amount of the tax in local currency.
@currencyID	,
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/Tax/BasisReportAmount	The field findicates the local currency.
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA CINHED.CIRCUC	The field indicated the 'Tax/BasisBaseAmount' converted to Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails	(DCCD) for the currency. The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	Fan Camman Invaira
For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/Tax/Calculation/RateNumeric	
For Common Invoice:	For Common Invoice:
CINVTD.CIVTP1 CITAR1; INVBODMI/GetTaxDetails	The field indicates the VAT/Tax rate converted to decimal. Format: 1.00 (for 1%)
,	
	If Tax method (TATM) = 2, use TAR1. Otherwise, use VTP1.
Invoice/InvoiceHeader/Tax/Exemption/ID	Otherwise, use vii i.
For Common Invoice:	For Common Invoice:
CINVTD.CIVTCD CISETC	The field indicates the VAT/Tax exemption code.
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code
	(SETC).
	Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC).
	Otherwise, publish VAT code (VTCD).
@accountingEntity	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceHeader/Tax/Exemption/Description	For Common Invaine
For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption description.
Invoice/InvoiceHeader/Tax/Exemption/Amount	The note indicated the vitt exemption description.
For Common Invoice:	For Common Invoice:
CINVTD.CITXEA; INVBODMI/GetTaxDetails	The field indicates the exemption amount in transaction currency.
@currencyID	

Invoice	
For Common Invoice:	For Common Invoice: The field indicates the transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Tax/Exemption/BaseAmount	The field indicates the transaction currency.
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL; INVBODMI/GetTaxDetails	The field indicates the exemption amount in local currency.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceHeader/Tax/Exemption/ReportAmount	
For Common Invoice: CINVTD.CITXEL	For Common Invoice: The field indicated the 'Tax/Exemption/BaseAmount' converted to
CINVID.CITAEL CINHED.CIRCUC	Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE CINHED.CIRCUF	presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Tax/Description	
For Bill for Prepayment:	For Bill for Prepayment:
CSYTAB.CTTX40; CRS175MI/Get	The field indicates VAT code description.
For Common Invoice:	For Common Invoice:
CINVTD.CITX40; INVBODMI/GetTaxDetails	The field indicates the VAT description.
Invoice/InvoiceHeader/Tax/TaxAuthorityAmount For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Tax/BaseAmount' converted to Tax authority
CINHED.CIIBT1 CINHED.CIIBT2	currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The amount is
CINHED.CIIBT4	presented with 2 decimals but rounded to the number of decimals
CINHED.CIIBT5	(IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the
Geti leadel	currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD).
	The amount in tax authority currency is required by some countries
@currencyID	for the electronic invoice sent to the authorities.
For Common Invoice:	For Common Invoice:
CINHED.CIIBT1; INVBODMI/GetHeader	The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Invoice/InvoiceHeader/Tax/Amount	country do indicated in the involse heads. table (onthick).
For Bill for Prepayment:	For Bill for Prepayment:
OOPINH.OHVTA1 + OHVTA2; OIS125MI/LstPrePayByCO	This field indicates the tax amount.
For Common Invoice:	For Common Invoice:
CINVTD.CITXAM; INVBODMI/GetTaxDetails	The field indicates the VAT amount in transaction currency.
@currencyID For Bill for Prepayment:	For Bill for Prepayment:
OINVOH.UHCUCD; OIS350MI/GetInvHead	The field indicates the abbreviation for the currency. The abbreviation
For Common Invaion	should follow ISO standards.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice:
	The field indicates the transaction currency.
Invoice/InvoiceHeader/Tax/BaseAmount	
For Common Invoice: CINVTD.CITXAL; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT amount in local currency.
@currencyID	The hold indicated the V/T amount in local carrolley.
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceHeader/Tax/ReportAmount For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Tax/BaseAmount' converted to Reporting
CINHED.CIRCUC	currency of the base country and exchange rate as indicated in the
CINHED.CIRCUD CINHED.CIRCUE	invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the
CINHED.CIRCUF	currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader @currencyID	invoice sent to the authorities.
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Tay/WithholdIndicator	

Infor May 26, 2023 194

Invoice/InvoiceHeader/Tax/WithheldIndicator

For Common Invoice: CINHVT.CIVTI2, CINVTD.CIVTCD, CINVTD.CITATM.; INVBODMI/ SelHeaderTax, GetTaxDetails	For Common Invoice: The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where the VAT rate 2 (VTP2) is set to a negative rate for the tax to be withheld.
	VAT codes applicable to withheld tax must be defined 'Business Message Data Translation. Display' (CRS881) for: - Business message (BMSG) = Invoice - Parent element (ELMP) = Tax - Data element (ELMD) = WithheldIndicator The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for example VAT code 1 must be defined as 01).
	NB: The WithheldIndicator is only applicable to divisions using Tax method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.
Invoice/InvoiceHeader/Charge/ID	
For Common Invoice: CINCRG.CICRID; INVBODMI/SelCharges @accountingEntity	For Common Invoice: The field indicates the charge ID.
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/Charge/Description	
For Common Invoice: CINCRG.CICRDO; INVBODMI/SelCharges	For Common Invoice: The field indicates the charge description.
Invoice/InvoiceHeader/Charge/Amount For Common Invoice:	For Common Invoice:
CINCRG.CIAMTC; INVBODMI/SelCharges @currencyID	The field indicates the amount in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Charge/BaseAmount	The field fidicates the transaction currency.
For Common Invoice:	For Common Invoice:
CINCRG.CIAMLC; INVBODMI/SelCharges @currencyID	The field indicates the amount in local currency.
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/Charge/ReportAmount	
For Common Invoice:	For Common Invoice:
CINCRG.CIAMLC	The field indicated the 'Charge/BaseAmount' converted to Reporting
CINHED.CIRCUC CINHED.CIRCUD	currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2
CINHED.CIRCUE	decimals but rounded to the number of decimals (DCCD) for the
CINHED.CIRCUF	currency.
CINHED.CIDCCD; INVBODMI/SelCharges GetHeader	The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Charge/Tax	
@type For Common Invoice: CINVTD.CITXTB; INVBODMI/GetTaxDetails	For Common Invoice: If Tax type (TXTB) = 'SalesTax' then block must be created per field VTID, VTI2, VTI3, VTI4 and VTI5. Else if Tax type (TXTB) = 'Perception' then block must be created per field VTID. Otherwise, as is.
@subType	
For Common Invoice: CINVTD.CITSAB; INVBODMI/GetTaxDetails	For Common Invoice: Create this attribute only if Tax method (TATM) = 2.
	The field indicates the standard tax code based on the Invoice translation 'TaxsubType' (CRS881/882).
	Alternative if generic translation not used: Actual value of TSAB.
Invoice/InvoiceHeader/Charge/Tax/ID	
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the header charge VAT/Tax code.
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC).
	Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD).

IIIVOICE	
@accountingEntity	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/Charge/Tax/TaxJurisdicationCodes/Code	
For Common Invoice: CINVTD.CITAJ1; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the Tax juridisction code.
	Create this element only if Tax method (TATM) = 2.
Invoice/InvoiceHeader/Charge/Tax/BasisAmount	
For Common Invoice: CINVTD.CIBASA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the basis amount of the tax in transaction currency.
@currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Charge/Tax/BasisTaxAuthorityAmount	
For Common Invoice: CINVTD.CIBALA CINHED.CIIBT1 CINHED.CIIBT2 CINHED.CIIBT4 CINHED.CIIBT5 CINHED.CIIBT5	For Common Invoice: The field indicated the 'Tax/BasisBaseAmount' converted to Tax authority currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (IBT5) for the currency.
GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base) currency (LOCD).
@currencyID	The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Invoice/InvoiceHeader/Charge/Tax/BasisBaseAmount For Common Invoice:	For Common Invoice:
CINVTD.CIBALA; INVBODMI/GetTaxDetails @currencyID	For Common Invoice: The field indicates the basis amount of the tax in local currency.
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Charge/Tax/BasisReportAmount For Common Invoice: CINVTD.CIBALA CINHED.CIRCUC CINHED.CIRCUD CINHED.CIRCUE CINHED.CIRCUE CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails GetHeader @currencyIncomplexions	For Common Invoice: The field indicated the 'Charge/Tax/BasisBaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities.
For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/Charge/Tax/Calculation/RateNumeric	
For Common Invoice: CINVTD.CIVTP1 CITAR1; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT/Tax rate converted to decimal. Format: 1.00 (for 1%)
	If Tax method (TATM) = 2, use TAR1. Otherwise, use VTP1.
Invoice/InvoiceHeader/Charge/Tax/Exemption/ID For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT/Tax exemption code.
CITAXC; INVBODMI/GetTaxDetails @accountingEntity	If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD).
	For Common Invoice: The field indicates the company and division, displayed as CONO_DIVI.
Invoice/InvoiceHeader/Charge/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption description.
Invoice/InvoiceHeader/Charge/Tax/Exemption/Amount For Common Invoice:	

Invoice	
CINVTD.CITXEA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the exemption amount in transaction currency.
@currencyID For Common Invoice:	Ear Common Invaiga:
CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Charge/Tax/Exemption/BaseAmount	For Common Invaion
For Common Invoice: CINVTD.CITXEL; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the exemption amount in local currency.
@currencyID	
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/Charge/Tax/Exemption/ReportAmount	The note indicates the local currency.
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL	The field indicated the 'Charge/Tax/Exemption/BaseAmount'
CINHED.CIRCUC CINHED.CIRCUD	converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount
CINHED.CIRCUE	is presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails	(DCCD) for the currency. The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Charge/Tax/Description	
For Common Invoice: CINVTD.CITX40; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT description.
Invoice/InvoiceHeader/Charge/Tax/TaxAuthorityAmount	The field findicates the VAT description.
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL CINHED.CIIBT1	The field indicated the 'Tax/BaseAmount' converted to Tax authority currency (IBT1) of the base country and exchange rate (IBT7) as
CINHED.CIIBT1 CINHED.CIIBT2	indicated in the invoice header table (CINHED). The amount is
CINHED.CIIBT4	presented with 2 decimals but rounded to the number of decimals
CINHED.CIIBT5 CINHED.CIIBT7; INVBODMI/GetTaxDetails	(IBT5) for the currency.
GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the
	currency differ to the Invoice currency (CUCD) and Local (base) currency (LOCD).
	currency (LOOD).
	The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
@currencyID	
For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base
C. W. Z.D. C. ID. 1.1, INVESTIGATION	country as indicated in the invoice header table (CINHED).
Invoice/InvoiceHeader/Charge/Tax/Amount For Common Invoice:	For Common Invoice:
For Common invoice: CINHED.CITXAM; INVBODMI/GetHeader	For Common Invoice: The field indicates the VAT amount in transaction currency.
@currencyID	•
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Charge/Tax/BaseAmount	,·
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL; INVBODMI/GetTaxDetails @currencyID	The field indicates the VAT amount in local currency.
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Charge/Tax/ReportAmount	The field indicates the local currency.
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Charge/Tax/BaseAmount' converted to
CINHED.CIRCUC CINHED.CIRCUD	Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails	(DCCD) for the currency. The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	For Common Invoice:
For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/Charge/Tax/WithheldIndicator	· · · · · · · · · · · · · · · · · · ·
For Common Invoice:	For Common Invoice: The field indicates that the tax is withheld and is defined by using a
	For Common Invoice: The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where
For Common Invoice: CINCRG.CIVTI2, CINVTD.CITATM.; INVBODMI/	The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where the VAT rate 2 (VTP2) is set to a negative rate for the tax to be
For Common Invoice: CINCRG.CIVTI2, CINVTD.CITATM.; INVBODMI/	The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where

IIIVOICE	
	Message Data Translation. Display' (CRS881) for: - Business message (BMSG) = Invoice - Parent element (ELMP) = Tax - Data element (ELMD) = WithheldIndicator The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for example VAT code 1 must be defined as 01).
	NB: The WithheldIndicator is only applicable to divisions using Tax method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.
Invoice/InvoiceHeader/Allowance/ID	For Common Invoice:
@accountingEntity	Set to 'Order total discount'.
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/Allowance/Amount	
For Common Invoice: CINDIS.CIAMTC; INVBODMI/SelHeadDiscount @currencyID	For Common Invoice: The field indicates the amount in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Allowance/BaseAmount	
For Common Invoice: CINDIS.CIAMLC; INVBODMI/SelHeadDiscount @currencyID	For Common Invoice: The field indicates the amount in local currency.
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/Allowance/ReportAmount	
For Common Invoice:	For Common Invoice:
CINDIS.CIAMLC	The field indicated the 'Allowance/BaseAmount' converted to Reporting currency of the base country and exchange rate as
CINHED.CIRCUC CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/SelHeadDiscount	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	Fan Camanan Invaina
For Common Invoice:CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/Allowance/Tax	
@type	Fan Camanan Invaina
For Common Invoice: CINVTD.CITATM; INVBODMI/GetTaxDetails	For Common Invoice: If Tax type (TXTB) = 'SalesTax' then block must be created per field
CITY TD. CITATIVI, INVIDODIVII/GETTAXDELAIIS	VTID, VTI2, VTI3, VTI4 and VTI5.
SelHeadDiscTax	Else if Tax type (TXTB) = 'Perception' then block must be created per
	field VTID.
@cubTupe	Otherwise, as is.
@subType For Common Invoice:	For Common Invoice:
CINVTD.CITSAB; INVBODMI/GetTaxDetails	Create this attribute only if Tax method (TATM) = 2.
	The field indicates the standard tax code based on the Invoice translation 'TaxsubType' (CRS881/882).
	Alternative if generic translation not used: Actual value of TSAB.
Invoice/InvoiceHeader/Allowance/Tax/ID	For Common Invoice
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the header discount VAT/Tax code.
CITAXC; INVBODMI/GetTaxDetails	IF Tax type (TXTB) = 'Perception', publish service tax calculation
	code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD).
@accountingEntity	, ,
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/Allowance/Tax/TaxJurisdicationCodes/Code	
For Common Invoice: CINVTD.CITAJ1; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the Tax juridisction code.
	Create this element only if Tax method (TATM) = 2.
	. , ,

Invoice/InvoiceHeader/Allowance/Tax/BasisAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CIBASA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in transaction currency.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceHeader/Allowance/Tax/BasisTaxAuthorityAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA	The field indicated the 'Tax/BasisBaseAmount' converted to Tax
CINHED.CIIBT1	authority currency (IBT1) of the base country and exchange rate
CINHED.CIIBT2	(IBT7) as indicated in the invoice header table (CINHED). The
CINHED.CIIBT4	amount is presented with 2 decimals but rounded to the number of
CINHED.CIIBT5	decimals (IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	Amount in currency of Tay outbority (IDT1) is only if the currency
Getneadel	Amount in currency of Tax authority (IBT1) is only if the currency differ to the Invoice currency (CUCD) and Local (base) currency
	(LOCD).
	The amount in tax authority currency is required by some countries
@augranauID	for the electronic invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIIBT1; INVBODMI/GetHeader	
CINTED.CIIDTT, INVOODIVII/Getheadel	The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Investigation (Investigation of the Investigation o	country as indicated in the invoice header table (Charles).
Invoice/InvoiceHeader/Allowance/Tax/BasisBaseAmount	For Common Invoice:
For Common Invoice: CINVTD.CIBALA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the basis amount of the tax in local currency.
@currencyID	The field findicates the basis amount of the tax in local currency.
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceHeader/Allowance/Tax/BasisReportAmount	The hold indicates the transaction currency.
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA	The field indicated the 'Allowance/Tax/BasisBaseAmount' converted
CINHED.CIRCUC	to Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Allowance/Tax/Calculation/RateNumeric	F 0
For Common Invoice:	For Common Invoice: The field indicates the VAT rate converted to decimal.
CINVTD.CIVTP1	Format: 1.00 (for 1%)
CITAR1; INVBODMI/GetTaxDetails	Format. 1.00 (101 178)
	If Tax method (TATM) = 2, use TAR1.
	Otherwise, use VTP1.
Invoice/InvoiceHeader/Allowance/Tay/Evemption/ID	Otherwise, use VTP1.
Invoice/InvoiceHeader/Allowance/Tax/Exemption/ID	
For Common Invoice:	For Common Invoice:
For Common Invoice: CINVTD.CIVTCD	For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC).
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC).
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD).
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice:	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice:	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice:	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice:
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Allowance/Tax/Exemption/BaseAmount	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice: The field indicates the transaction currency.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Allowance/Tax/Exemption/BaseAmount For Common Invoice:	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice: The field indicates the transaction currency.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Allowance/Tax/Exemption/BaseAmount For Common Invoice: CINVTD.CITXEL; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice: The field indicates the transaction currency.
For Common Invoice: CINVTD.CIVTCD CISETC CITAXC; INVBODMI/GetTaxDetails @accountingEntity Invoice/InvoiceHeader/Allowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails Invoice/InvoiceHeader/Allowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Invoice/InvoiceHeader/Allowance/Tax/Exemption/BaseAmount For Common Invoice:	For Common Invoice: The field indicates the VAT exemption code. If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. For Common Invoice: The field indicates the VAT exemption description. For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice: The field indicates the transaction currency.

CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice:
To the state of th	The field indicates the local currency.
Invoice/InvoiceHeader/Allowance/Tax/Exemption/ReportAmount For Common Invoice: CINVTD.CITXEL CINHED.CIRCUC CINHED.CIRCUD CINHED.CIRCUE CINHED.CIRCUE CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails GetHeader @currencyID For Common Invoice:	For Common Invoice: The field indicated the 'Allowance/Tax/Exemption/BaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities. For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceHeader/Allowance/Tax/Description For Common Invoice: CINVTD.CITX40; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT description.
Invoice/InvoiceHeader/Allowance/Tax/TaxAuthorityAmount For Common Invoice: CINVTD.CITXAL CINHED.CIIBT1 CINHED.CIIBT2 CINHED.CIIBT4 CINHED.CIIBT5 CINHED.CIIBT5 CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	For Common Invoice: The field indicated the 'Tax/BaseAmount' converted to Tax authority currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (IBT5) for the currency. Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD). The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Invoice/InvoiceHeader/Allowance/Tax/Amount For Common Invoice: CINHED.CITXAM; INVBODMI/GetHeader @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the VAT amount in transaction currency. For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceHeader/Allowance/Tax/BaseAmount For Common Invoice: CINVTD.CITXAL; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the VAT amount in local currency. For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/Allowance/Tax/ReportAmount For Common Invoice: CINVTD.CITXAL CINHED.CIRCUC CINHED.CIRCUD CINHED.CIRCUE CINHED.CIRCUE CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails GetHeader @currencyID For Common Invoice:	For Common Invoice: The field indicated the 'Allowance/Tax/BaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities. For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader Invoice/InvoiceHeader/Allowance/Tax/WithheldIndicator For Common Invoice: CINDVT.CIVTI2, CINVTD.CIVTCD, CINVTD.CITATM.; INVBODMI/ SelHeadDiscTax, GetTaxDetails	The field indicated the reporting currency. For Common Invoice: The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where the VAT rate 2 (VTP2) is set to a negative rate for the tax to be withheld.
	VAT codes applicable to withheld tax must be defined 'Business Message Data Translation. Display' (CRS881) for: - Business message (BMSG) = Invoice - Parent element (ELMP) = Tax - Data element (ELMD) = WithheldIndicator The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for example VAT code 1 must be defined as 01).

NB: The WithheldIndicator is only applicable to divisions using Tax

Invoice/InvoiceHeader/UserArea

For Common Invoice:

CINBUA.CIDFVA;

CINBUA.CIDFNA;

CINBUA.CIDFTY

CINHED.CIRCUE;

CINHED.CIACDT;

CINHED.CIROLC

CINHED.CITOLA; INVBODMI/SelUserArea;

INVBODMI/GetHeader

method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.

For Common Invoice:

The field indicates additional information (DFVA) for the invoice.

The following information is created as standard when applicable for the invoice:

- 1) Shipment issue date with attribute 'name' = "Icl.ShipmentIssueDate".
- 2) E-invoice format with attribute 'name' = 'lcl.Pattern'.
- 3) Customer's purchase order date with attribute 'name' = "lcl.CustomerPurchaseOrderDate".
- 4) Invoice class used as sub invoice type with attribute 'name' = "lcl.SubInvoiceType".
- 5) Payment method with attribute 'name' = "Icl.PaymentMethod".
- 6) E-invoice category from (CRS075) with attribute 'name' = "lcl.CategoryIndicator"
- 7) Email address of type 15-User defined AR from (CRS111) with attribute 'name' = "Icl.CustomerReference".

The attribute sequence (SEQC) and attribute type (DFTY) are set to value from MI - SelUserArea.

The following information is only created for specific Country Versions when applicable for the invoice:

- 1) Italy: Administration reference from (CRIT10) with attribute 'name' = "lcl.AdditionalReference'
- 2) Mexico: Property number from (ARS120 or FAS130) with attribute 'name' = "Icl.PropertyNumber".

The attribute sequence (SEQC) and attribute type (DFTY) are set to value from MI - SelUserArea.

The following other information is created when entered in:

- 1) E-invoice Additional Information. Open (CMS525) or
- 2) Settings E-invoice (CMS520)

The information that can be used is described in the M3 configuration guide for the integration to Localization Services.

The attribute name (DFNA), attribute sequence (SEQC) and attribute type (DFTY) are set to value from MI - SelUserArea.

The following information from the invoice header (CINHED) is added in UserArea using INVBODMI - GetHeader (attribute 'sequence' set to the last number from INVBODMI - SelUserArea +1 for each information outputted):

- 1) Report currency, exchange rate (RCUE) is populated in case Report currency (RCUD) is used (not blank), value sent with 6 decimals. The attribute 'name' is set to 'lcl.ReportExchangeRate', attribute 'type is set to 'DecimalType' and attribute 'sequence' to +1. 2) Accounting date (ACDT) is populated in case not blank/null. The attribute 'name' is set to 'lcl.AccountingDate', attribute 'type is set to
- 'DateType' and attribute 'sequence' to +1.
 3) Rounding-off in local currency (ROLC) is populated in case not 0. The attribute 'name' is set to 'lcl.SubunitRoundingBaseAmount', attribute 'type is set to 'AmountType', attribute 'currencyID' set to Local currency (LOCD) and attribute 'sequence' to +1.
- 4) Invoice total in local currency before rounding-off is populated in case rounding-off in local currency (ROLC) is not 0. The attribute 'name' is set to 'lcl.PreSubunitRoundingBaseAmount', attribute 'type is set to 'AmountType', attribute 'currencyID' set to Local currency (LOCD) and attribute 'sequence' to +1.
- If Rounding-off in local currency (ROLC) > 0 then Total Amount in local currency (TOLA) Rounding-off (ROLC).
- If Rounding-off in local currency (ROLC) < 0 then Total Amount in local currency (TOLA) + Rounding-off (ROLC).

Invoice/InvoiceHeader/Status/Code

For Bill for Prepayment:

OINVOH.UHINST; OIS350MI/GetInvHead

For Common Invoice: CINHED.CIRVST; INVBODMI/GetHeader For Bill for Prepayment: Set to 'Proforma'

For Common Invoice:

Set to "Void" if reversal status (RVST) = 90, otherwise set to "Open".

NB: The status code "Void" is only used in case the feature feature ID = 2183649 has been activated in CMS975 in M3BE (see (*) below):
- If the feature is not actived (FEAT=0): Only status code "Open" is

- If the feature is not actived (FEAT=0): Only status code "Open" is used regardless the reversal status of the invoice in M3BE.
- If the feature is activated (FEAT=1): Invoice with reversal status 90-Reversed will get status code "Void", otherwise status code "Open" is used.

THE OLD THE OL	(*) Retrieved from CMS975MI.Get with field NCRN = 2183649.
	Reversal status (RVST) indicates if the invoice voucher has been reversed in (GLS900), the following values are used: - blank: The invoice voucher has not been reversed, status code "Open" is used 20: The invoice voucher has been reversed with a new accounting date, status code "Open" is used 90: The invoice voucher has been reversed (cancelled), status code
	"Void" is used.
Invoice/InvoiceHeader/Status/EffectiveDateTime For Common Invoice: CINHED.CIRGDT + CIRGTM; INVBODMI/GetHeader	For Common Invoice: The field indicates the date and time that the object was created. This date is set automatically. It is a concatenation of creation date (RGDT) <8> + creation time (RGTM) <6>. E.g. 2018-12-13T05:09:04.903Z
Invoice/InvoiceHeader/Status/ArchiveIndicator	For Common Invoice: Set to 'false'.
Invoice/InvoiceHeader/CurrencyExchangeRate/SourceCurrencyCode For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction/foreign currency code.
Invoice/InvoiceHeader/CurrencyExchangeRate/SourceUnitBaseNume	
For Common Invoice: CINHED.CIRAFA; INVBODMI/GetHeader	For Common Invoice: The field indicates the rate factor (RAFA) defined in (CRS055/MFS055) of the transaction currency (CUCD) to the local currency. - If Rate factor = 1: Set to "1000" - If Rate factor = 2: Set to "100" - If Rate factor = 3: Set to "10" - If Rate factor = 4-7: Set to "1"
Invoice/InvoiceHeader/CurrencyExchangeRate/TargetCurrencyCode For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency code.
Invoice/InvoiceHeader/CurrencyExchangeRate/TargetUnitBaseNumer For Common Invoice: CINHED.CIRAFA; INVBODMI/GetHeader	For Common Invoice: The field indicates the rate factor (RAFA) defined in (CRS055/MFS055) of the transaction currency (CUCD) to the local currency. - If Rate factor = 1-4: Set to "1" - If Rate factor = 5: Set to "10" - If Rate factor = 6: Set to "100" - If Rate factor = 7: Set to "1000"
Invoice/InvoiceHeader/CurrencyExchangeRate/RateNumeric For Common Invoice: CINHED.CIRAIN; INVBODMI/GetHeader	For Common Invoice: The field indicates the exchange rate.
Invoice/InvoiceHeader/CurrencyExchangeRate/SetDateTime For Common Invoice: CINHED.CIIVDT; INVBODMI/GetHeader	For Common Invoice: The field indicates the exchange rate date.
Invoice/InvoiceHeader/ShipToParty/PartyIDs/ID For Common Invoice: CINPTY.CICUNO; INVBODMI/GetParty	For Common Invoice: The field indicates the delivery customer. IF address number (ADID) is not blank, publish CUNO + ADID. It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the delivery customer code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.
@schemeName	For Common Invoice: Set to 'CustomerNumber'.
@accountingEntity	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/ShipToParty/PartyIDs/TaxID For Common Invoice: 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININO; INVBODMI/GetParty	For Common Invoice: The field indicates the following Tax IDs of the ShipTo customer: 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryldentificationNumber (CORG). 4) CountryldentificationNumber (COR2). 5) CountryldentificationNumber (COR4). 6) National Identity Number (NINO). 7) National Identity Number (NIN2).

11140100	
@schemeName	
	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed.
	5) Set to 'CountryldentificationNumber' if COR4 is displayed.6) Set to 'NationalIdentityNumber: if NINO is displayed.7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceHeader/ShipToParty/Name	5.0
For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty @languageID	For Common Invoice: The field indicates the delivery customer name.
For Common Invoice: CINHED.CILNCD: INVBODMI/GetHeader	For Common Invoice: The field indicates the language.
Invoice/InvoiceHeader/ShipToParty/Location/Address @type	The hold maleatee the language.
	For Common Invoice: Set to 'text'.
Invoice/InvoiceHeader/ShipToParty/Location/Address/AttentionOfNa	
For Common Invoice:	For Common Invoice:
CINPTY.CIYREF; INVBODMI/GetParty	The field indicates the contact name.
Invoice/InvoiceHeader/ShipToParty/Location/Address/AddressLine For Common Invoice:	For Common Invoice:
CINPTY.CICUA1 CICUA2 CICUA3	The field indicates the address lines.
CICUA4; INVBODMI/GetParty @sequence	
S4	For Common Invoice:
	The field indicates the address line sequence.
Invoice/InvoiceHeader/ShipToParty/Location/Address/CityName For Common Invoice:	For Common Invoice:
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
nvoice/InvoiceHeader/ShipToParty/Location/Address/CountrySubDi	
For Common Invoice: CINPTY.CIECAR; INVBODMI/GetParty © <i>listID</i>	For Common Invoice: The field indicates an area, province or state within a country.
5 • •	For Common Invoice:
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'States' if CountryCode is MX (Mexico)
	Set to 'SubDivisions - Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.
Invoice/InvoiceHeader/ShipToParty/Location/Address/CountryCode	der to oubbivisions if no obtainly is specified.
For Common Invoice:	For Common Invoice:
CINPTY.CICSCD; INVBODMI/GetParty @ <i>listID</i>	The field indicates the country code.
	For Common Invoice: Set to 'Countries'.
Invoice/InvoiceHeader/ShipToParty/Location/Address/PostalCode	5.0
For Common Invoice: CINPTY.CIPONO; INVBODMI/GetParty	For Common Invoice: The field indicates the postal code.
nvoice/InvoiceHeader/ShipToParty/Communication	•
@preferredIndicator	For Common Invoice: Set to 'false'.
Invoice/InvoiceHeader/ShipToParty/Communication/ChannelCode	Cotto Talos.
	For Common Invoice: Set to 'Phone' if telephone number or facsimile number. Set to 'Email' if email address.
@listID	For Common Invoice:
	Set to 'Communication Channels'.
nvoice/InvoiceHeader/ShipToParty/Communication/UseCode	For Common Invaion
	For Common Invoice: Set to "Office" if telephone number. Set to "Fax" if facsimile number. Set to 'Office' if email address.
@listID	For Common Invoice: Set to 'Communication Use Codes'.
Invoice/InvoiceHeader/ShipToParty/Communication/DialNumber	
For Common Invoice: CINPTY.CIPHNO CITFNO; INVBODMI/GetParty	For Common Invoice: The field indicates the telephone number (PHNO) or fax number (TFNO) of the delivery customer.
Infor May 26, 20	1923

Invoice/InvoiceHeader/ShipToParty/Communication/URI For Common Invoice: For Common Invoice: CINPTY.EMAL; INVBODMI/GetParty The field indicates the email address of the customer for the email type 01-Customer in (CRS111). Invoice/InvoiceHeader/ShipToParty/Communication/Preference/Indicator For Common Invoice: Set to 'false'. Invoice/InvoiceHeader/ShipToParty/Contact/ID For Common Invoice: For Common Invoice: OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact ID. @accountingEntity For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceHeader/ShipToParty/Contact/Name For Common Invoice: For Common Invoice: CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name. Invoice/InvoiceHeader/ShipToParty/Contact/Communication @preferredIndicator For Common Invoice: Set to 'false'. Invoice/InvoiceHeader/ShipToParty/Contact/Communication/ChannelCode For Common Invoice: Set to "Phone" if telephone number is 1, 2, facsimile number or mobile. Set to "EMail" if e-mail address. @listID For Common Invoice: Set to 'Communication Channels' Invoice/InvoiceHeader/ShipToParty/Contact/Communication/UseCode For Common Invoice: Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number. @listID For Common Invoice: Set to "Communication Use Codes". Invoice/InvoiceHeader/ShipToParty/Contact/Communication/DialNumber For Common Invoice: For Common Invoice: CCUCON.CCPHNO The field indicates the telephone number. CCPHN2; CRS618MI/Get Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/AddressLine For Common Invoice: For Common Invoice: CCUCON.CCCUA1 The field indicates the address lines. CCCUA2 CCCUA3 CCCUA4; CRS618MI/Get @sequence For Common Invoice: The field indicates the address sequence number. Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CityName For Common Invoice: For Common Invoice: CCUCON.CCTOWN; CRS618MI/Get The field indicates the city name. Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CountrySubDivisionCode For Common Invoice: For Common Invoice: CCUCON.CCECAR; CRS618MI/Get The field indicates an area, province or state within a country. @listID For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CountryCode For Common Invoice: For Common Invoice: CCUCON.CCCSCD; CRS618MI/Get The field indicates the country. @listID For Common Invoice: Set to 'Countries' Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/PostalCode For Common Invoice: For Common Invoice: The field indicates the postal code. CCUCON.CCPONO; CRS618MI/Get Invoice/InvoiceHeader/ShipToParty/Contact/Communication/URI For Common Invoice: For Common Invoice: CCUCON.CCEMAL; CRS618MI/Get The field indicates the email address.

Invoice/InvoiceHeader/ShipToParty/Contact/Communication/HTMLPreferredIndicator For Common Invoice: Set to 'false' Invoice/InvoiceHeader/ShipToParty/Contact/Communication/Preference/Indicator For Common Invoice: Set to 'false'. Invoice/InvoiceHeader/BillToParty/PartyIDs/ID For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHCUNO; OIS125MI/LstPrePayByCO The field indicates the person/business who is the recipient of the For Common Invoice: CINPTY.CICUNO; INVBODMI/GetParty For Common Invoice: The field indicates the invoice recipient customer. @schemeName For Common Invoice: Set to 'CustomerNumber'. @accountingEntity For Bill for Prepayment: For Bill for Prepayment: OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO The field indicates the accounting entity. If BillToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI). For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceHeader/BillToParty/PartyIDs/TaxID For Bill for Prepayment: For Bill for Prepayment: OCUSMA.UHTAXC; CRS610MI/GetFinancial The field indicates Tax ID For Common Invoice: For Common Invoice: 1) CINPTY.CIVRNO The field indicates the following Tax IDs of the BilTo customer: 2) CINPTY.CIVRNL 1) VAT Registration number (VRNO). 3) CINPTY.CICORG 2) Tax declaration number (VRNL). 4) CINPTY.CICOR2 3) CountryldentificationNumber (CORG). 5) CINPTY.CICOR4 4) Country Identification Number (COR2). 5) CountryldentificationNumber (COR4). 6) CINPTY.CININO 7) CINPTY.CININ2.; INVBODMI/GetParty 6) National Identity Number (NINO). 7) National Identity Number (NIN2). @schemeName For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryldentificationNumber' if CORG is displayed. 4) Set to 'CountryldentificationNumber' if COR2 is displayed. 5) Set to 'CountryldentificationNumber' if COR4 is displayed.
6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed. Invoice/InvoiceHeader/BillToParty/PartyIDs/EndPointID For Common Invoice: For Common Invoice: CINPTY.CIEPID; INVBODMI/GetParty The field indicates the endpoint ID. @schemeID For Common Invoice: For Common Invoice: CINPTY.CISCHI; INVBODMI/GetParty The field indicates the scheme ID Invoice/InvoiceHeader/BillToParty/Name For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHCUN2; CRS610MI/GetBasicData The field indicates the invoice receiver, which is used as complementary information to the customer number on panels and For Common Invoice: documents. CINPTY.CINAME; INVBODMI/GetParty For Common Invoice: The field indicates the invoice recipient customer name Invoice/InvoiceHeader/BillToParty/Location/Address @type Set to 'text'. Invoice/InvoiceHeader/BillToParty/Location/Address/AttentionOfName For Bill for Prepayment: For Bill for Prepayment: OINVOH.OKYREF; OIS100MI/GetAddress The field indicates the invoice receiver, which is used as complementary information to the customer number on panels and For Common Invoice: documents. CINPTY.CIYREF; INVBODMI/GetParty For Common Invoice: The field indicates the contact name. Invoice/InvoiceHeader/BillToParty/Location/Address/AddressLine For Bill for Prepayment: For Bill for Prepayment: OOADRE.ODCUA1, The field indicate an Address Line

ODCUA3.

ODCUA4; OIS100MI

/GetAddress

For Common Invoice:

The field indicates the address lines.

For Common Invoice:

CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty

@sequence

For Bill for Prepayment:

The field indicates an incremental number

For Common Invoice:

The field indicates the address line sequence.

Invoice/InvoiceHeader/BillToParty/Location/Address/CityName

For Bill for Prepayment:

OOADRE.ODTOWN: OIS100MI

/GetAddress

For Bill for Prepayment:

The field indicates the City in an address

For Common Invoice:

The field indicates the city name.

For Common Invoice:

CINPTY.CITOWN; INVBODMI/GetParty

Invoice/InvoiceHeader/BillToParty/Location/Address/CountrySubDivisionCode

For Bill for Prepayment:

OOADRE.ODECAR; OIS100MI

/GetAddress

For Bill for Prepayment:

The field indicates an area, province or state within a country

For Common Invoice: For Common Invoice:

CINPTY.CIECAR; INVBODMI/GetParty

@listID

The field indicates an area, province or state within a country.

For Bill for Prepayment:

The field indicates the list ID depending on the country:

- Canada has list ID 'Canadian Provinces - France has list ID 'France - Departements'

- United States has list ID 'US States'

- Other countries have list ID 'SubDivisions - [country code]'

For Common Invoice:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

Invoice/InvoiceHeader/BillToParty/Location/Address/CountryCode

For Bill for Prepayment: OOADRE.ODCSCD; OIS100MI

/GetAddress

For Bill for Prepayment: The field indicates a country

For Common Invoice:

The field indicates the country code.

For Common Invoice:

CINPTY.CICSCD; INVBODMI/GetParty

@listID

Set to 'Countries'.

Invoice/InvoiceHeader/BillToParty/Location/Address/PostalCode

For Bill for Prepayment:

OOADRE.ODPONO; OIS100MI

/GetAddress

For Bill for Prepayment:

The field indicates a postal code for a specific address

For Common Invoice:

The field indicates the postal code.

Invoice/InvoiceHeader/BillToParty/Location/Status/Code

For Bill for Prepayment:

For Common Invoice:

OCUSMA.OKSTAT; CRS610MI/GetBasicData

CINPTY.CIPONO; INVBODMI/GetParty

For Bill for Prepayment:

The field indicates the status of the customer.

If M3 status is 10, set to "Pending" If M3 status is 20, set to "Open" If M3 status is 90, set to "Closed

Invoice/InvoiceHeader/BillToParty/Communication/ChannelCode

For Common Invoice:

Set to 'Email' if email address.

For Common Invoice:

Set to 'Communication Channels'.

Invoice/InvoiceHeader/BillToParty/Communication/UseCode

For Common Invoice:

Set to 'Office' if email address.

@listID

@listID

For Common Invoice: Set to 'Communication Use Codes'.

May 26, 2023

Invoice/InvoiceHeader/BillToParty/Communication/URI For Common Invoice: For Common Invoice: CINPTY.EMAL; INVBODMI/GetParty The field indicates the email address of the invoice recipient for the email type: - 12-Invoice recipient and if not found, - 11-Payer and if not found, - 01-Customer in (CRS111) Invoice/InvoiceHeader/BillToParty/Communication/Preference/Indicator For Common Invoice: Set to 'false'. Invoice/InvoiceHeader/BillToParty/Contact/ID For Common Invoice: For Common Invoice: OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact ID @accountingEntity For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceHeader/BillToParty/Contact/Name For Common Invoice: For Common Invoice: CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name Invoice/InvoiceHeader/BillToParty/Contact/Communication @preferredIndicator For Common Invoice: Set to 'false'. Invoice/InvoiceHeader/BillToParty/Contact/Communication/ChannelCode For Common Invoice: Set to "Phone" if telephone number is 1, 2, facsimile number or Set to "EMail" if e-mail address. @listID For Common Invoice: Set to 'Communication Channels'. Invoice/InvoiceHeader/BillToParty/Contact/Communication/UseCode For Common Invoice: Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number. @listID For Common Invoice: Set to "Communication Use Codes" Invoice/InvoiceHeader/BillToParty/Contact/Communication/DialNumber For Common Invoice: For Common Invoice: CCUCON.CCPHNO The field indicates the telephone number. CCPHN2; CRS618MI/Get Invoice/InvoiceHeader/BillToParty/Contact/Communication/Address/AddressLine For Common Invoice: For Common Invoice: CCUCON.CCCUA1 The field indicates the address lines. CCCUA2 CCCUA3 CCCUA4; CRS618MI/Get @sequence For Common Invoice: The field indicates the sequence number. Invoice/InvoiceHeader/BillToParty/Contact/Communication/Address/CityName For Common Invoice: For Common Invoice: The field indicates the city name. CCUCON.CCTOWN; CRS618MI/Get Invoice/InvoiceHeader/BillToParty/Contact/Communication/Address/CountrySubDivisionCode For Common Invoice: For Common Invoice: CCUCON.CCECAR; CRS618MI/Get The field indicates an area, province or state within a country. @listID For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. Invoice/InvoiceHeader/BillToParty/Contact/Communication/Address/CountryCode For Common Invoice: For Common Invoice: CCUCON.CCCSCD; CRS618MI/Get The field indicates the country. @listID For Common Invoice: Se to 'Countries'. Invoice/InvoiceHeader/BillToParty/Contact/Communication/Address/PostalCode For Common Invoice: For Common Invoice: CCUCON.CCPONO; CRS618MI/Get The field indicates the postal code.

invoice	
Invoice/InvoiceHeader/BillToParty/Contact/Communication/URI For Common Invoice: CCUCON.CCEMAL; CRS618MI/Get	For Common Invoice: The field indicates the email address.
Invoice/InvoiceHeader/BillToParty/Contact/Communication/HTMLPre	ferredIndicator For Common Invoice:
	Set to 'false'.
Invoice/InvoiceHeader/BillToParty/Contact/Communication/Preference	e/Indicator
·	For Common Invoice:
La distribution de l'Octobre De la l'Octobre De l'Octobre	Set to 'false'.
Invoice/InvoiceHeader/PayFromParty/PartyIDs/ID For Bill for Prepayment: OOPINH.OHPYNO; OIS125MI/LstPrePayByCO	The field indicates the person/business who has paid or will pay the invoice.
For Common Invoice: CINPTY.CICUNO; INVBODMI/GetParty @schemeName	
	For Common Invoice:
@accountingEntity	Set to 'CustomerNumber'.
For Bill for Prepayment: OOPINH.OHCONO+OHDIVI; OIS125MI/LstPrePayByCO	For Bill for Prepayment: The field indicates the accounting entity. If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as
	Company and Division (CONO_DIVI).
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/PayFromParty/PartyIDs/TaxID	
For Common Invoice: 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININO	For Common Invoice: The field indicates the following Tax IDs of the PayFrom customer: 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryldentificationNumber (CORG). 4) CountryldentificationNumber (COR2). 5) CountryldentificationNumber (COR4). 6) National Identity Number (NINO).
@schemeName	7) National Identity Number (NIN2).
	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceHeader/PayFromParty/Name	
For Bill for Prepayment: OCUSMA.UHCUNM; CRS610MI/GetBasicData	For Bill for Prepayment: The field indicates the customer name.
For Common Invoice:	For Common Invoice:
CINPTY.CINAME; INVBODMI/GetParty Invoice/InvoiceHeader/PayFromParty/Location	The field indicates the payer name.
@type	
	For Bill for Prepayment: Set to 'type'
Invoice/InvoiceHeader/PayFromParty/Location/Address @type	Set to type
<i>₩</i>	For Common Invoice: Set to 'text'.
Invoice/InvoiceHeader/PayFromParty/Location/Address/AttentionOfN	
For Bill for Prepayment: OCUSMA.UHCUNM; CRS610MI/GetBasicData	For Bill for Prepayment: The field indicates the customer name.
For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: The field indicates the contact name.
Invoice/InvoiceHeader/PayFromParty/Location/Address/AddressLine	
For Bill for Prepayment: OOADRE.ODCUA1,	For Bill for Prepayment: The field indicates the address line.
ODCUA2,	For Common Invoice:
ODCUA3, ODCUA4; OIS100MI /GetAddress	For Common Invoice: The field indicates the address lines.
For Common Invoice:	
1.6	20

CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty

@sequence

For Bill for Prepayment:

The field indicates a incremental number.

For Common Invoice:

The field indicates the address line sequence.

Invoice/InvoiceHeader/PayFromParty/Location/Address/CityName

For Bill for Prepayment:

OOADRE.ODTOWN; OIS100MI

/GetAddress

For Bill for Prepayment:

The field indicates the city in an address.

For Common Invoice:

The field indicates the city name.

For Common Invoice:

CINPTY.CITOWN; INVBODMI/GetParty

Invoice/InvoiceHeader/PayFromParty/Location/Address/CountrySubDivisionCode

For Bill for Prepayment: OOADRE.ODECAR; OIS100MI

/GetAddress

For Bill for Prepayment: The field indicates the state.

For Common Invoice:

The field indicates an area, province or state within a country.

For Common Invoice: CINPTY.CIECAR; INVBODMI/GetParty

@listID

For Bill for Prepayment:

The field indicates the list ID depending on the country:

- Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States'

- Other countries have list ID 'SubDivisions - [country code]'

For Common Invoice:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

Invoice/InvoiceHeader/PayFromParty/Location/Address/CountryCode

For Bill for Prepayment:

OOADRE.ODCSCD; OIS100MI

/GetAddress

The field indicates the country code.

For Common Invoice:

CINPTY.CICSCD; INVBODMI/GetParty

@listID

Set to 'Countries'.

Invoice/InvoiceHeader/PayFromParty/Location/Address/PostalCode

For Bill for Prepayment:

For Common Invoice:

OOADRE.ODPONO; OIS100MI

/GetAddress

For Bill for Prepayment:

The field indicates the postal code

For Common Invoice:

The field indicates the postal code.

CINPTY.CIPONO; INVBODMI/GetParty

Invoice/InvoiceHeader/PayFromParty/Communication/ChannelCode

For Common Invoice:

Set to "EMail" if email address.

@listID

For Common Invoice:

Set to 'Communication Channels'.

Invoice/InvoiceHeader/PayFromParty/Communication/UseCode

For Common Invoice:

Set to "Office" if email address.

@listID

For Common Invoice:

Set to "Communication Use Codes".

Invoice/InvoiceHeader/PayFromParty/Communication/URI

For Common Invoice:

CINPTY.CIEMAL; INVBODMI/GetParty

For Common Invoice:

The field indicates the email address of the payer for the email type

11-Payer and if not found, 01-Customer in (CRS111).

Invoice/InvoiceHeader/PayFromParty/Communication/Preference/Indicator

For Common Invoice:

Set to 'false'.

Invoice/InvoiceHeader/PayFromParty/FinancialParty/PartyIDs/BICID

For Common Invoice:

CBANAC.BCSWBI

CBANMA.BKSWIC.; CRS692MI/GetBankAccount

For Common Invoice:

The field indicates the SWIFT code of the customer's bank account (SWBI). If SWBI is not provided, SWIFT code of the customer's bank

(SWIC) is published.

May 26, 2023

11110100	
Invoice/InvoiceHeader/PayFromParty/FinancialParty/ClearingSystemM For Common Invoice: CBANAC.BCCLSI BCCLSN; CRS692MI/GetBankAccount	MemberID For Common Invoice: The field indicates the system clearing ID. It is a concatenation of Clearing System ID (CLSI) + Clearing System number (CLSN) without separator. All fields are trimmed if it does not consume the maximum length.
Invoice/InvoiceHeader/PayFromParty/FinancialParty/BranchParty/Part For Common Invoice: CBANBR.BRSWIC; CRS692MI/GetBankAccount	tyIDs/BICID For Common Invoice: The field indicates SWIFT code of the customer's bank branch.
Invoice/InvoiceHeader/PayFromParty/FinancialParty/FinancialAccoun For Common Invoice: CBANAC.BCBACN; CRS692MI/GetBankAccount	
Invoice/InvoiceHeader/PayFromParty/FinancialParty/FinancialAccoun For Common Invoice: CBANAC.BCIBAN; CRS692MI/GetBankAccount	t/IBANID For Common Invoice: The field indicates the International Bank Account number of the custome/payer.
Invoice/InvoiceHeader/ShipFromParty/PartyIDs/ID For Common Invoice: CINPTY.; INVBODMI/GetParty @accountingEntity	For Common Invoice: The field indicates the warehouse. For Common Invoice: The field indicates the company and division, displayed as
Invoice/InvoiceHeader/ShipFromParty/PartyIDs/TaxID For Common Invoice: 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININO; INVBODMI/GetParty	For Common Invoice: The field indicates the following Tax IDs of the ShipFrom: 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryIdentificationNumber (CORG). 4) CountryIdentificationNumber (COR2). 5) CountryIdentificationNumber (COR4). 6) National Identity Number (NINO). 7) National Identity Number (NINO).
@schemeName	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceHeader/ShipFromParty/Name For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty	For Common Invoice: The field indicates the warehouse name.
Invoice/InvoiceHeader/ShipFromParty/Location @type	For Common Invoice: Set to 'Warehouse'
Invoice/InvoiceHeader/ShipFromParty/Location/ID For Common Invoice: CINPTY:; INVBODMI/GetParty @accountingEntity	For Common Invoice: The field indicates the warehouse.
	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceHeader/ShipFromParty/Location/Address @type	For Common Invoice: Set to 'text'.
Invoice/InvoiceHeader/ShipFromParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty @sequence	
Invoice/InvoiceHeader/ShipFromParty/Location/Address/CityName For Common Invoice:	The field indicates the address line sequence. For Common Invoice:
CINPTY.CITOWN; INVBODMI/GetParty Invoice/InvoiceHeader/ShipFromParty/Location/Address/CountrySuble For Common Invoice: CINPTY.CIECAR; INVBODMI/GetParty @listID	The field indicates the city name.

IIIVOICE	
	For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'States' if CountryCode is MX (Mexico) Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceHeader/ShipFromParty/Location/Address/CountryCode	
For Common Invoice: CINPTY.CICSCD; INVBODMI/GetParty	For Common Invoice: The field indicates the country code.
@listID	For Common Invoice:
	Set to 'Countries'.
Invoice/InvoiceHeader/ShipFromParty/Location/Address/PostalCode For Common Invoice:	For Common Invoice:
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the postal code.
Invoice/InvoiceHeader/ExtendedPretaxAmount For Common Invoice: CINHED.CIEPAM; INVBODMI/GetHeader @currencyID	For Common Invoice: The field indicates the gross total order value in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice:
Invoice/InvoiceHeader/ExtendedPretaxBaseAmount For Common Invoice: CINHED.CIEPLA; INVBODMI/GetHeader @currencyID For Common Invoice:	For Common Invoice: For Common Invoice: The field indicates the gross total order value in local currency. For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceHeader/ExtendedPretaxReportAmount For Common Invoice: CINHED.CIEPLA CIRCUC CIRCUD CIRCUB CIRCUE CIRCUF CIRCUF CIDCCD; INVBODMI/GetHeader	For Common Invoice: The field indicated the 'ExtendedPretaxBaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/SubTotalAmount	·
For Common Invoice: CINHED.CISUTA; INVBODMI/GetHeader @currencyID	For Common Invoice: The field indicates the sum of the TotalPretaxAmount for all the order lines in the transaction currency.
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceHeader/SubTotalBaseAmount	
For Common Invoice: CINHED.CISTLA; INVBODMI/GetHeader	For Common Invoice: The field indicates the sum of the TotalPretaxAmount for all the order lines in local currency.
@currencyID For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
Invoice/InvoiceHeader/SubTotalReportAmount For Common Invoice: CINHED.CISTLA CIRCUC CIRCUD CIRCUB CIRCUE CIRCUF CIDCCD; INVBODMI/GetHeader	For Common Invoice: The field indicated the 'SubTotalBaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceHeader/Classification/Codes/Code For Common Invoice: CINHED.CIRXIN CIIVTP CITEDL; INVBODMI/GetHeader	For Common Invoice: The field indicates different classifications for the invoice: Sequence 1: - Set to 'Original' if RXIN is blank and IVTP is 00, 02, 03 or 04 Set to 'Corrective' if RXIN is not blank and IVTP is 00 or 01 Set to 'Summary' if RXIN is blank and IVTP is 01. Sequence 2: - The field indicates the delivery term (TEDL) of the invoice and is populated for all invoices except summary invoices (see InvoiceLine).

IIIVUICE	
@sequence	
@li-4ID	For Common Invoice: The field indicates the classification sequence number.
@listID	For Common Invoice:
	Set to 'InvoiceClass' for sequence = 1.
	Set to 'Incoterms' for sequence = 2.
Invoice/InvoiceHeader/Reference/NameValue	•
For Common Invoice:	For Common Invoice:
CINHED.CICUSU; INVBODMI/GetHeader	The field indicates the supplier number of the customer.
@name	
- Others	For Common Invoice: Set to 'ExternalSupplierNumber'.
@type	For Common Invoice:
	Set to 'StringType'.
Invoice/InvoiceHeader/SalesPersonReference/IDs/ID	V /1
For Common Invoice:	For Common Invoice:
CINHED.CISMCD; INVBODMI/GetHeader	The field indicates the sales person ID.
@accountingEntity	
	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceHeader/SalesPersonReference/Name	For Occurred Invarian
For Common Invoice: :: CRS100MI/Get	For Common Invoice: The field indicates the sales person name.
,	The field indicates the sales person name.
Invoice/InvoiceHeader/Correction/OriginalDocumentID/ID	For Common Invaion
For Common Invoice: CINHED.CIRYEA +	For Common Invoice:
CINNED.CIRTEA + CIRXIN; INVBODMI/GetHeader	The field indicates the original invoice number in case of corrective invoice.
Citoxiia, iiaabobixii/Geti leadei	It is a concatenation of Invoice Year (RYEA) <4> + Invoice Number
	(RXIN) <15> without separator. The position of each field is
	determined by its maximum length, specified in brackets. If the data
	does not consume the maximum length, the rest is filled up with
	spaces. This applies to all fields that are part of the original document
	ID except for the last one. The last field in the concatenation, in this
@aaaaunting/Futitus	case RXIN, is trimmed if it does not consume the maximum length.
@accountingEntity	For Common Invoice:
	The field indicates the company and division, displayed as CONO_DIVI.
@location	_
For Common Invoice:	For Common Invoice:
CINHED.CIWHLO; INVBODMI/GetHeader	The field indicates the warehouse of the Original invoice if existing in
 	(CMS500).
Invoice/InvoiceHeader/Correction/ReasonCode	F O Invasions
For Common Invoice: CINHED.CIFRSC	For Common Invoice: The field indicates the (finance) reason code for the correction.
FQRADF.EAESFV; INVBODMI/GetHeader	The field indicates the (finance) reason code for the correction.
TXS035MI/GetAddField	For credit notes (Invoice@type=CreditMemo) where no reason code
17.0000Mill Contact ford	can be connected (field FRSC is blank), a default code can be
	defined in (TXS035) using transaction type 7-Electronic invoices with
	additional field number 550 defined with length 10 and numeric
	cleared. The base country should be set to the base country of the
	invoice, that is from the Tax representative party or Supplier (division)
@liastD	party.
@listID	For Common Invoice:
	For Common Invoice: Set to 'Invoice Correction Reasons'.
@accountingEntity	Set to IIIVoice Correction (Ceasons).
,	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO_DIVI.
Invoice/InvoiceLine/LineNumber	
For Bill for Prepayment:	For Bill for Prepayment:
Increment integer starting with 1; /	Increment integer starting with 1.
	5 0
For Common Invoice:	For Common Invoice:
CINLIN.CILINU; INVBODMI/SelLines	The field indicates the line number.
Invoice/InvoiceLine/Description For Common Invoice:	For Common Invoice:
CINLIN.CIA200; INVBODMI/SelLines	For Common Invoice: The field indicates the invoice reference text.
	THE HEIGHNUCALES THE HIVOIDE FEICHCHE LEXL.
Invoice/InvoiceLine/Note For Rill for Prepayment:	For Rill for Prenayment
For Bill for Prepayment: N/A.Various; OIS350MI/LstInvLineByTyp	For Bill for Prepayment: This contains concatenated values of the following: company,
1.47 a. various, Otoobolvii/Estitivelilosy 1 yp	division, year, invoice prefix, invoice number, information type, order
	2.11.0.011, jour, intoice profix, intoice fluidber, information type, order

For Common Invoice:

CSYTXL.TLTX60: CRS980MI/SIITxtBlock

For Common Invoice:

For Common Invoice:

The field indicates the line note.

number, delivery number, warehouse, invoice reference.

The field indicates the line note ID. It is a concatenation of Text ID

does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the NotelD except for the last one. The last field in the concatenation, in this case TXVR, is

(TXID) <13> + Text Block (TXVR) <10> without separator. If the data

@noteID

@type

For Common Invoice:

CINTXT.CITXID

CITXVR; INVBODMI/SelTexts

trimmed if it does not consume the maximum length.

The field indicates the note type.

@languageID

For Common Invoice:

For Common Invoice:

CINTXT.CILNCD; INVBODMI/SelTexts

CINTXT.CITXPR; INVBODMI/SelTexts

Invoice/InvoiceLine/DocumentReference @type

For Common Invoice:

CINDRE.CIDRTP; INVBODMI/SelDocReference

Invoice/InvoiceLine/DocumentReference/DocumentID/ID

For Bill for Prepayment:

ODLINE.UBORNO; OIS350MI/LstInvLineByTyp

For Common Invoice:

CINDRE.CIDIDN; INVBODMI/SelDocReference

@accountingEntity

For Bill for Prepayment:

-.-: -/-

@location

For Bill for Prepayment:

Invoice/InvoiceLine/DocumentReference/LineNumber For Bill for Prepayment:

Increment integer starting with 1. .; N/A/

For Common Invoice:

CINDRE.CIDIDN; INVBODMI/SelDocReference

Invoice/InvoiceLine/DocumentReference/SubLineNumber For Common Invoice:

CINDRE.CIDLSN; INVBODMI/SelDocReference

Invoice/InvoiceLine/Item/ItemID/ID

For Bill for Prepayment:

ODLINE.UBITNO: OIS350MI/LstDelLine

For Common Invoice:

CINLIN.CIITNO

CIICSNO; INVBODMI/SelLines

For Common Invoice:

Set to 'Pre-Text' if TXPR is 1. Set to 'Post-Text' if TXPR is 2.

For Common Invoice:

The field indicates the language of the note

For Common Invoice:

The field indicates the document reference type. IF DRTP is not 'TransportDocument', publish DRTP

For Bill for Prepayment:

The field indicates a unique identity for a customer order.

Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type

For Common Invoice:

The field indicates the document reference number.

For Bill for Prepayment:

The field indicates a division. This is an identity for a legal unit within

a company group.

Division is a key value in the financial system in M3.

One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes.

For Common Invoice:

The field indicates the company and division, displayed as

CONO DIVI.

For Bill for Prepayment:

The field indicates the warehouse ID.

Warehouse is a stock zone which is used to distinguish different geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock

locations and items are connected to the warehouse.

For Bill for Prepayment:

Increment integer starting with 1.

For Common Invoice:

The field indicates the reference line number.

For Common Invoice:

The field indicates the reference subline number.

For Bill for Prepayment:

The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual

For Common Invoice:

The field indicates the item number (ITNO) or the Customs statistical number (CSNO) that can in some cases be used as an alternative item number.

In case both numbers exist for the line, the Item number (ITNO) is included as the first ItemID/ID.

@schemeName

May 26, 2023

For Common Invoice: Set to 'Supplier' in case of Custom statistical number (CSNO), otherwise not included. @accountingEntity For Bill for Prepayment: For Bill for Prepayment: The field indicates a division. This is an identity for a legal unit within a company group. Division is a key value in the financial system in M3. One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes. For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceLine/Item/ItemID/RevisionID For Bill for Prepayment: The field indicates the revision number (edition) for an item or MITMAS.MMECVE: MMS200MI/GetItmTech document. For Common Invoice: CINLIN.CIECVE; INVBODMI/SelLines Invoice/InvoiceLine/Item/UPCID For Bill for Prepayment: For Bill for Prepayment: MITPOP.MPPOPN; MMS025MI/LstAlias Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods. For Common Invoice: Alias qualifier = UPC CINLIN.CIUPCI; INVBODMI/SelLines For Common Invoice: The field indicates the alias number that corresponds to GTIN-12 and UCC-12. It is a 12-digit number used for identifying goods. Do not create this element if value of UPCI exceeds the max length of Invoice/InvoiceLine/Item/GTIN For Bill for Prepayment: For Bill for Prepayment: MITPOP MPPOPN; MMS025MI/LstAlias The Global Trade Item Number is a 14-digit number which includes various EAN/UCC numbering structures. For Common Invoice: Alias qualifier = GTIN CINLIN.CIGTIN; INVBODMI/SelLines For Common Invoice: The field indicates the alias number that corresponds to Global Trade Item Number. It is a 14-digit number which includes various EAN/ UCC numbering structures. Do not create this element if value of GTIN exceeds the max length of @schemeName For Common Invoice: For Common Invoice: CINLIN.CIGTIS; INVBODMI/SelLines The field indicates the GTIN scheme name. Set to the value of field GTIS. Invoice/InvoiceLine/Item/ServiceIndicator For Common Invoice: Set to 'false'. Invoice/InvoiceLine/Item/Description For Bill for Prepayment: For Bill for Prepayment: MITMAS.MMITDS; MMS200MI/Get ItmBasic The field indicates the name for each item. For Common Invoice: For Common Invoice: CINLIN.CIITDS: INVBODMI/SelLines The field indicates the item name. @languagelD For Common Invoice: For Common Invoice: CINHED.CILNCE; INVBODMI/GetHeader The field indicates the language Invoice/InvoiceLine/Item/Note For Common Invoice: For Common Invoice: CSYTXH.THTX60; CRS980MI/SLITxtBlock The field indicates the item note. @noteID For Common Invoice: For Common Invoice: CINTXT.CITXID The field indicates the line note ID. It is a concatenation of Text ID (TXID) <13> + Text Block (TXVR) <10> without separator. If the data CITXVR; INVBODMI/SelTexts does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the NoteID except for the last one. The last field in the concatenation, in this case TXVR, is trimmed if it does not consume the maximum length. @type For Common Invoice: For Common Invoice: CINTXT.CITXPR; INVBODMI/SelTexts The field indicates the note type. Set to 'Pre-Text' if TXPR is 1. Set to 'Post-Text' if TXPR is 2.

@languagelD

For Common Invoice:

CINTXT.CILNCD; INVBODMI/SelTexts

Invoice/InvoiceLine/Item/Classification/Codes/Code

For Bill for Prepayment:

- 1) MITMAS
- 2) MITMAS
- 3) MITMAS
- 4) MITMAS
- 5) MITMAS
- 6) MITMAS
- 7) MITMAS
- 8) MITMAS.MMITGR

MMITCL

MMBUAR

MMITTY

MMTPCD

MMPRGP

MMDIGI

MMCHCD; MMS200MI

MMS200MI

MMS200MI

MMS200MI

MMS200MI MMS200MI

MMS200MI

MMS200MI/GetItmBasic

GetItmBasic

GetItmBasic

GetItmBasic

GetItmBasic GetItmBasic

GetItmPrice

GetItmBasic

For Common Invoice:

1) MITMAS. MMITGR

MMS200MI.GetItmBasic

2) MITMAS.MMITCL

MMS200MI.GetItmBasic

3) MITAS.MMBUAR MMS200MI.GetItmBasic

4)MITMAS.MMITTY

MMS200MI.GetItmBasic

5) MITMAS.MMTPCD

MMS200MI.GetItmBasic

6) MITMAS.MMPRGP

MMS200MI.GetItmBasic

7) MITMAS.MMDIGI

MMS200MI.GetItmPrice

8) MITMAS.MMCHCD

MMS200MI.GetItmBasic

9) CINLIN.CICCSNO

INVBODMI.SelLines

10) CINLIN.CICCSNO

INVBODMI.SelLines

.; /

For Common Invoice:

The field indicates the language of the note

For Bill for Prepayment:

1)Item group

The field indicates the item group.

2) Product group

The field indicates the product group.

3) Business area

The field indicates the business area.

4) Item type

The item type is mandatory and cannot be changed after the item is created. The only time an item type can be changed is when you copy template items.

The functions connected to the item type include:

-A template item that contains default values for creating items.

-A numbering rule for assigning the correct item number

-A warehouse/item type to set the item/warehouse records generated when you create an item.

-An alias/item type that is used to set the alias numbers generated when you create an item.

5) Item category

The field indicates the item category.

Alternatives

00 = Normal item

02 = Phantom item

03 = Subcontracted item

04 = Tool

05 = Fixed machine

07 = Repairable item

08 = Recyclable item

11 = Extended Catalog Item (ECI)

12 = Non-coded Extended Catalog Item

13 = Non-material item

6) Procurement grp

The field indicates the procurement group for an item.'

7) Item discount group

Item discount groups are entered per item in M3 and may be used as a control object for calculating customer order line discounts.

8) Configuration code

The field indicates if the item is configured when ordered or configured as a maintenance item.

For Common Invoice:

The field indicates the following:

1)Item group

The field indicates the item group.

2) Product group

The field indicates the product group.

3) Business area

The field indicates the business area.

4) Item type

The item type is mandatory and cannot be changed after the item is created. The only time an item type can be changed is when you copy template items.

5) Item category

The field indicates the item category.

Alternatives

00 = Normal item

02 = Phantom item

03 = Subcontracted item

04 = Tool

05 = Fixed machine

07 = Repairable item

08 = Recyclable item

11 = Extended Catalog Item (ECI)

12 = Non-coded Extended Catalog Item

13 = Non-material item

6) Procurement Group

The field indicates the procurement group for an item.

7) Item discount group

Item discount groups are entered per item in M3 and may be used as a control object for calculating customer order line discounts.

8) Configuration code

The field indicates if the item is configured when ordered or configured as a maintenance item.

9) Custom statistical number

May 26, 2023

	The field indicates the custom statistical number.
	10) Custom statistical number
@	The field indicates the custom statistical number for Local.ly
@sequence	For Common Invoice:
	The filed indicates the sequence number.
@listID	
	For Common Invoice:
	Set to:
	1)item Groups
	2)Product Groups 3)Business Sectors
	4)Item Types
	5)Item Category
	6)Procurement Groups
	7) Item Discount Groups
	8) Configuration Code 9) Customs Statistical Number
	10) CommodityCodes
nvoice/InvoiceLine/Item/Classification/Description	10) Commonly Codes
For Bill for Prepayment:	For Bill for Prepayment:
CSYTAB.CTTX40; CRS175MI/LstCodesByLng	The field indicates a description of the classification.
, ,	It is retrieved from table CSYTAB (generic description), table
	CSLGHN (language-specific description) or hardcoded.
nvoice/InvoiceLine/Item/SerializedLot/Lot/LotIDs/ID	
For Bill for Prepayment:	For Bill for Prepayment:
OOLINE.OBBANO; OIS100MI/GetLine	The field indicates the lot number, which is an ID of a manufactured
For Common Invoices	or purchased quantity of an item. All units included in a lot have the
For Common Invoice: MITTRA.MTBANO; MWS070MI/LstTransByOrder	same characteristics.
WITT TO V.WIT DAVIG, WIWOOV OWIN EST TAILS BY OTHER	Serial numbers can be used for lot numbering.
	For Common Invoice:
	The field indicates the lot number. Lot number is displayed when the
	lot number indicator (INDI) is 1, 3, 4 or 5.
nvoice/InvoiceLine/Item/SerializedLot/Lot/Quantity	
For Common Invoice:	For Common Invoice:
MITTRA.MTTRQA; MWS070MI/LstTransByOrder	The field indicates the transaction quantity.
@unitCode For Common Invoice:	For Common Invoice:
CINLIN.CISPUN; INVBODMI/SelLines	The field indicates the unit of measure.
nvoice/InvoiceLine/Item/SerializedLot/Lot/BaseUOMQuantity	
For Common Invoice:	For Common Invoice:
MITTRA.MTTRQT; MWS070MI/LstTransByOrder	The field indicates the quantity in basic unit of measure.
@unitCode	5 O
For Common Invoice: CINLIN.CIUNMS; INVBODMI/SelLines	For Common Invoice: The field indicates the base unit of measure.
nvoice/InvoiceLine/Item/SerializedLot/Lot/SerialNumber	The hold indicated the pace and of medicare.
For Bill for Prepayment:	For Bill for Prepayment:
OOLINE.OBSERN; OIS100MI/GetLine	The field indicates the unique serial number of each item.
	Lot number and lot/serial number can also be used.
nvoice/InvoiceLine/Item/SerializedLot/SerialNumber	5 Dill (D
For Bill for Prepayment:	For Bill for Prepayment:
OOLINE.OBSERN; OIS100MI/GetLine	The field indicates the unique serial number of each item.
For Common Invoice:	Lot number and lot/serial number can also be used.
MITTRA.MTBANO; MWS070MI/LstTransByOrder	·
·	For Common Invoice:
	The field indicates the serial number. Serial number is displayed
	when the lot number indicator (INDI) is 2.
nvoice/InvoiceLine/ShipmentDateTime	For Common Invoice:
For Common Invoice: CINLIN.CIDLDT; INVBODMI/SelLines	For Common Invoice: The field indicates the shipment date.
·	The hold indicated the dilipinotit date.
TVOICE/INVOICEI INE/COUNTRYCHTURINGOAE	
	For Common Invoice:
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines	For Common Invoice: The field indicates the country of origin.
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines	The field indicates the country of origin.
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines	The field indicates the country of origin. For Common Invoice:
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines DistiD	The field indicates the country of origin.
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines DistID nvoice/InvoiceLine/Quantity	The field indicates the country of origin. For Common Invoice:
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines DistID	The field indicates the country of origin. For Common Invoice: Set to "Countries". For Bill for Prepayment:
For Common Invoice: CINLIN.CIORCO; INVBODMI/SelLines DistID nvoice/InvoiceLine/Quantity For Bill for Prepayment: ODLINE.UBQTY5; OIS350MI/GetDelLine	The field indicates the country of origin. For Common Invoice: Set to "Countries". For Bill for Prepayment: The field indicates the invoiced quantity in a basic U/M for the delivery line.
CINLIN.CIORCO; INVBODMI/SelLines @listID Invoice/InvoiceLine/Quantity For Bill for Prepayment:	The field indicates the country of origin. For Common Invoice: Set to "Countries". For Bill for Prepayment: The field indicates the invoiced quantity in a basic U/M for the delivery

@unitCode

transferred to the invoiced quantity on the order line and to the

invoiced quantity on the delivery line.

Delivered quantity on the order line is reduced by the transferred

delivered quantity on the delivery line.

For Common Invoice:

The field indicates the invoice quantity in alternate unit of measure.

For Bill for Prepayment: For Bill for Prepayment: -.-; OIS350MI/GetDelLine

The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All

balance information for the current item is always stored in this unit.

For Common Invoice:

The field indicates the alternate unit of measure.

Invoice/InvoiceLine/BaseUOMQuantity

CINLIN.CISPUN; INVBODMI/SelLines

For Common Invoice:

For Bill for Prepayment: For Bill for Prepayment: ODLINE.UBQTY4; OIS350MI/GetDelLine

Quantity of an invoice line

For Common Invoice: For Common Invoice:

CINLIN.CIIVQT; INVBODMI/SelLines The field indicates the invoice quantity in basic unit of measure.

@unitCode For Bill for Prepayment: For Bill for Prepayment:

-.-; OIS350MI/GetDelLine The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All For Common Invoice: balance information for the current item is always stored in this unit.

CINLIN.CIUNMS; INVBODMI/SelLines

For Common Invoice: The field indicates the base unit of measure.

Invoice/InvoiceLine/UnitPrice/Amount

For Bill for Prepayment: For Bill for Prepayment: ODLINE.UBSAPR; OIS350MI/GetDelLine The field indicates the invoice amount in the local currency.

For Common Invoice: For Common Invoice:

CINLIN.CISAPR; INVBODMI/SelLines The field indicates the unit price in transaction currency.

@currencyID

For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHCUCD; -/-The field indicates the abbreviation for the currency. The abbreviation

should follow ISO standards.

For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Example:

GBP British pounds USD United States dollars SEK Swedish kronor.

For Common Invoice:

The field indicates the transaction currency.

Invoice/InvoiceLine/UnitPrice/BaseAmount

For Bill for Prepayment: For Bill for Prepayment: ODLINE.UBSAP1; OIS350MI/GetDelLine unit price in local currency.

For Common Invoice: For Common Invoice:

CINLIN.CIPRIL; INVBODMI/SelLines The field indicates the unit price in local currency.

@currencvID

For Bill for Prepayment: For Bill for Prepayment: CMNDIV.CCLOCD; -/-The field indicates the abbreviation for the currency. The abbreviation

should follow ISO standards. For Common Invoice:

CINHED.CILOCD; INVBODMI/GetHeader Example: GBP British pounds

USD United States dollars SEK Swedish kronor.

For Common Invoice: The field indicates the local currency.

Invoice/InvoiceLine/UnitPrice/ReportAmount

FQRADF.EAESFV

TXS035MI/GetAddField

GetHeader;

For Common Invoice: For Common Invoice: CINLIN.CIPRIL The field indicated the "UnitPrice/BaseAmount" converted to CINHED.CIRCUC Reporting currency of the base country and exchange rate as CINHED.CIRCUD indicated in the invoice header table (CINHED). The amount is CINHED.CIRCUE presented with 6 decimals but rounded to the number of price decimals defined in TXS035 - field 551 (value 0-6) and if not existing, CINHED.CIRCUF

CINHED.CINPRD from the invoice header (NPRD) for the currency.

The report amount is required by some countries for the electronic

.-; INVBODMI/SelLines invoice sent to the authorities.

The alterntive field 551 can be defined in (TXS035) using transaction type 7-Electronic invoices with additional field set to length 1 and

217 May 26, 2023

	numeric selected. The base country should be set to the base country of the invoice, that is from the Tax representative party or Supplier (division) party. Note that 6 decimals will be used in case the field is set to a higher number.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/UnitPrice/PerQuantity	
For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UBSAPR; OIS350MI/GetDelLine	The field indicates the quantity to which the sales price applies. Sales
	price quantity is defined for each item and is expressed in the item
For Common Invoice:	unit of measure.
CINLIN.CISACD; INVBODMI/SelLines	Fan Camanan Invisias
	For Common Invoice:
@unitCodo	The field indicates the per quantity.
@unitCode For Rill for Prenayment:	For Rill for Drangyment
For Bill for Prepayment: ODLINE.UBSPUN; OIS350MI/GetDelLine	For Bill for Prepayment: The field indicates the sales price U/M
ODENIAE.ODON ON, ONOSOUNI/OCIDENINE	The held indicates the sales price O/NI
For Common Invoice:	For Common Invoice:
CINLIN.CIUNMS; INVBODMI/SelLines	The field indicates the sales price unit of measure.
Invoice/InvoiceLine/PurchaseOrderReference/SubLineNumber	
For Bill for Prepayment:	For Bill for Prepayment:
ODHEAD.UACUNO; /	0
Invoice/InvoiceLine/ExternalDocumentReference	<u> </u>
@type For Common Invoice:	For Common Invoice:
CINDRE.CIDRTP; INVBODMI/SelDocReference	The field indicates the document reference type.
SHADIKE. SHDIKIT, HAV DODIVII/OGIDOGIAGIGICIUG	IF DRTP is 'TransportDocument: and TXEI is '1', publish DRTP.
Invoice/InvoiceLine/ExternalDocumentReference/DocumentID/ID	is the separation and the to 1, publish bittle
For Common Invoice:	For Common Invoice:
CINDRE.CIDIDN; INVBODMI/SelDocReference	The field indicates the external document reference number.
·	The note indicates the external document reletence number.
Invoice/InvoiceLine/ExternalDocumentReference/LineNumber	For Common Invoice:
For Common Invoice: CINDRE.CIDLIN; INVBODMI/SelDocReference	The field indicates the external document reference line number.
·	The held indicates the external document reference line number.
Invoice/InvoiceLine/ExtendedAmount	For Pill for Drong/monty
For Bill for Prepayment:	For Bill for Prepayment:
OINVOH.UHAMT2; OIS350MI/GetInvHead	Display AMT2 if IVTP = '31'.
For Common Invoice:	For Common Invoice:
CINLIN.CIEXTA; INVBODMI/SelLines	The field indicates the extended amount in transaction currency.
@currencyID	The hold indicates the extended amount in transaction currency.
For Bill for Prepayment:	For Bill for Prepayment:
OINVOH.UHCUCD; -/-	The field indicates the abbreviation for the currency. The abbreviation
, .	should follow ISO standards.
For Common Invoice:	
CINHED.CICUCD; INVBODMI/GetHeader	Example:
	GBP British pounds
	USD United States dollars
	SEK Swedish kronor.
	For Common Invoice:
	The field indicates the transaction currency.
Invoice/InvoiceLine/ExtendedBaseAmount	
For Bill for Prepayment:	For Bill for Prepayment:
OINVOL.UHIIVLA; OIS350MI/LstInvLine	Display AMT1 if IVTP = '31'.
For Occurrent Involves	F O
For Common Invoice:	For Common Invoice:
CINLIN.CIEXLA; INVBODMI/SelLines	The field indicates the extended amount in local currency.
@currencyID	For Pill for Pronovment
For Bill for Prepayment: CMNDIV.CCLOCD; -/-	For Bill for Prepayment:
GIVINDIV.GGEOGD, -/-	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
For Common Invoice:	SHOULU TOHOW ISO STATILIATUS.
CINHED.CILOCD; INVBODMI/GetHeader	Example:
ON AT IED. OILOOD, HAV DODIVII/OCH ICAUCI	GBP British pounds
	USD United States dollars
	SEK Swedish kronor.
	SER SWOODINGTON.
	For Common Invoice:
	The field indicates the local currency.
Invoice/InvoiceLine/ExtendedReportAmount	
For Common Invoice:	For Common Invoice:
CINLIN.CIEXLA	The field indicated the 'ExtendedBaseAmount' converted to Reporting
CINHED.CIRCUC	currency of the base country and exchange rate as indicated in the
CINHED.CIRCUD	invoice header table (CINHED). The amount is presented with 2
	, , ,

Invoice CINHED.CIRCUE decimals but rounded to the number of decimals (DCCD) for the CINHED.CIRCUF currency CINHED.CIDCCD.-; INVBODMI/SelLines The report amount is required by some countries for the electronic GetHeader invoice sent to the authorities. @currencyID For Common Invoice: For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader The field indicated the reporting currency. Invoice/InvoiceLine/TotalAmount For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHAMT2; OIS350MI/GetInvHead Display AMT2 if IVTP = '31'. Should include + charge, - invoice allowance, + extended amount. For Common Invoice: CINLIN.CITAMT; INVBODMI/SelLines For Common Invoice: The field indicates the total amount in transaction currency. @currencyID For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHCUĆD: -/-The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Example: GBP British pounds **USD United States dollars** SEK Swedish kronor. For Common Invoice: The field indicates the transaction currency. Invoice/InvoiceLine/TotalBaseAmount For Bill for Prepayment: For Bill for Prepayment: OINVOL.ONIVLA; OIS350MI/LstInvLine Display AMT1 if IVTP = '31'. For Common Invoice: For Common Invoice: CINLIN.CITOLA; INVBODMI/SelLines The field indicates the total amount in local currency. @currencyID For Bill for Prepayment: For Bill for Prepayment: CMNDIV.CCLOCD; -/-The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader Example: GBP British pounds USD United States dollars SEK Swedish kronor. For Common Invoice: The field indicates the local currency. Invoice/InvoiceLine/TotalReportAmount For Common Invoice: For Common Invoice: CINLIN.CITOLA The field indicated the 'TotalBaseAmount' converted to Reporting CINHED.CIRCUC currency of the base country and exchange rate as indicated in the CINHED.CIRCUD invoice header table (CINHED). The amount is presented with 2 CINHED.CIRCUE decimals but rounded to the number of decimals (DCCD) for the CINHED.CIRCUF CINHED.CIDCCD.-; INVBODMI/SelLines The report amount is required by some countries for the electronic GetHeader invoice sent to the authorities. @currencvID For Common Invoice: For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader The field indicated the reporting currency.

Invoice/InvoiceLine/OpenItemIndicator

Invoice/InvoiceLine/Tax For Common Invoice:

CINVTD.CITATM; INVBODMI/GetTaxDetails

SelLines

@sequenceNumber For Common Invoice:

CINVTD.CITAXS; INVBODMI/SelHeaderTax

For Common Invoice:

CINVTD.CITXTB; INVBODMI/SelHeaderTax

For Common Invoice:

Set to 'false'.

For Common Invoice:

If Tax type (TXTB) = 'SalesTax' then block must be created per field

VTID, VTI2, VTI3, VTI4 and VTI5.

Else if Tax type (TXTB) = 'Perception' then block must be created per

field VTID Otherwise, as is.

For Common Invoice:

The field indicates the sequence number.

For Common Invoice:

If Tax type (TXTB) = 'SalesTax' then block must be created per field

VTID, VTI2, VTI3, VTI4 and VTI5.

Else if Tax type (TXTB) = 'Perception' then block must be created per field VTID.

Otherwise, as is.

@subType

May 26, 2023

Invoice	
For Common Invoice: CINVTD.CITSAB; INVBODMI/GetTaxDetails	For Common Invoice: Create this attribute only if Tax method (TATM) = 2.
	The field indicates the standard tax code based on the Invoice translation 'Taxsubtype' (CRS881/882).
	Alternative if generic translation not used: Actual value of TSAB.
Invoice/InvoiceLine/Tax/ID For Bill for Prepayment: OINVOL.ONVTCD; OIS350MI/GetInvLine	For Bill for Prepayment: The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply.
For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT/Tax code.
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/address (TAXC). Otherwise, publish VAT code (VTCD).
@accountingEntity For Bill for Prepayment: .; -/-	For Bill for Prepayment: The field indicates a division. This is an identity for a legal unit within a company group. Division is a key value in the financial system in M3. One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes.
	For Common Invoice: The field indicates the company and division, displayed as CONO_DIVI.
@location For Bill for Prepayment: .; -/-	For Bill for Prepayment: The field indicates the warehouse ID.
	Warehouse is a stock zone which is used to distinguish different geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock locations and items are connected to the warehouse.
Invoice/InvoiceLine/Tax/TaxJurisdicationCodes/Code	
For Common Invoice: CINVTD.CITAJ1; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the Tax juridisction code.
	Create this element only if Tax method (TATM) = 2.
Invoice/InvoiceLine/Tax/BasisAmount For Common Invoice: CINVTD.CIBASA; INVBODMI/GetTaxDetails @currencyID	For Common Invoice: The field indicates the basis amount of the tax in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/Tax/BasisTaxAuthorityAmount For Common Invoice: CINVTD.CIBALA CINHED.CIIBT1 CINHED.CIIBT2 CINHED.CIIBT4 CINHED.CIIBT5 CINHED.CIIBT5 CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	For Common Invoice: The field indicated the 'Tax/BasisBaseAmount' converted to Tax authority currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (IBT5) for the currency. Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD). The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Invoice/InvoiceLine/Tax/BasisBaseAmount For Common Invoice: CINVTD.CIBALA; INVBODMI/GetTaxDetails @currencyID For Common Invoice:	For Common Invoice: The field indicates the basis amount of the tax in local currency.
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/Tax/BasisReportAmount For Common Invoice: CINVTD.CIBALA	For Common Invoice: The field indicated the 'Tax/BasisBaseAmount' converted to
Infor May	v 26 2023 22

IIIVOICE	
CINHED.CIRCUC	Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	F 0
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/Tax/Calculation/RateNumeric	
For Common Invoice:	For Common Invoice:
CINVTD.CIVTP1	The field indicates the VAT rate converted to decimal.
CITAR1; INVBODMI/GetTaxDetails	Format: 1.00 (for 1%)
	If Tax method (TATM) = 2, use TAR1.
	Otherwise, use VTP1.
Invoice/InvoiceLine/Tax/Exemption/ID	
For Common Invoice:	For Common Invoice:
CINVTD.CIVTCD	The field indicates the VAT exemption code
CISETC	The hold indicated the V/TI exemption code
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code
,	(SETC).
	Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/
	address (TAXC).
	Otherwise, publish VAT code (VTCD).
@accountingEntity	5 0 1 .
	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceLine/Tax/Exemption/Description	Fan Oamana Installant
For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption description.
·	The field indicates the VAT exemption description.
Invoice/InvoiceLine/Tax/Exemption/Amount	Fan Camanan Invesions
For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the exemption amount in transaction currency.
@currencyID	The field indicates the exemption amount in transaction currency.
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/Tax/Exemption/BaseAmount	,
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL; INVBODMI/GetTaxDetails	The field indicates the exemption amount in local currency.
@currencyID	· · · · · · · · · · · · · · · · · · ·
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/Tax/Exemption/ReportAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL	The field indicated the 'Tax/Exemption/BaseAmount' converted to
CINHED.CIRCUC	Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE CINHED.CIRCUF	presented with 2 decimals but rounded to the number of decimals
CINHED.CIDCCD; INVBODMI/GetTaxDetails	(DCCD) for the currency. The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	invoice som to the additionate.
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/Tax/Description	· · · · · · · · · · · · · · · · · · ·
For Common Invoice:	For Common Invoice:
CINVTD.CITX40; INVBODMI/GetTaxDetails	The field indicates the VAT description.
Invoice/InvoiceLine/Tax/TaxAuthorityAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Tax/BaseAmount' converted to Tax authority
CINHED.CIIBT1	currency (IBT1) of the base country and exchange rate (IBT7) as
CINHED.CIIBT2	indicated in the invoice header table (CINHED). The amount is
CINHED.CIIBT4	presented with 2 decimals but rounded to the number of decimals
CINHED.CIIBT5	(IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails	Amount in currency of Tax authority (IRT1) is only populated if the
GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD).
	oditorioy (2005).
	The amount in tax authority currency is required by some countries
	for the electronic invoice sent to the authorities.
	for the diedactine invoice cont to the dutionales.
@currencyID	ior the distribution involce cont to the duthornics.
@currencyID For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	

	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
nvoice/InvoiceLine/Tax/Amount	,
For Common Invoice: CINHED.CITXAM; INVBODMI/GetHeader @currencyID	For Common Invoice: The field indicates the VAT amount in transaction currency.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
nvoice/InvoiceLine/Tax/BaseAmount	,
For Common Invoice: CINVTD.CITXAL; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT amount in local currency.
@currencyID For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
nvoice/InvoiceLine/Tax/ReportAmount	,
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Tax/BaseAmount' converted to Reporting
CINHED.CIRCUC CINHED.CIRCUD	currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2
CINHED.CIRCUE	decimals but rounded to the number of decimals (DCCD) for the
CINHED.CIRCUF	currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	For Common Invoice:
For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/Tax/WithheldIndicator	The field indicated the reporting currency.
For Common Invoice: CINLIN.CIVTI2, CINVTD.CIVTCD, CINVTD.CITATM.; INVBODMI/ SelHeaderTax, GetTaxDetails	For Common Invoice: The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where the VAT rate 2 (VTP2) is set to a negative rate for the tax to be withheld.
	VAT codes applicable to withheld tax must be defined 'Business Message Data Translation. Display' (CRS881) for: - Business message (BMSG) = Invoice - Parent element (ELMP) = Tax - Data element (ELMD) = WithheldIndicator The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for example VAT code 1 must be defined as 01).
	NB: The WithheldIndicator is only applicable to divisions using Tax method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.
nvoice/InvoiceLine/InvoiceCharge/ID	
For Bill for Prepayment: OOLINE.OBCRID; OIS100MI/LstConnCOCharge	For Bill for Prepayment: The field indicates the unique ID of a charge.
For Common Invoice: CINCRG.CICRID; INVBODMI/SelCharges	For Common Invoice: The field indicates the charge ID.
@accountingEntity	For Common Invoice: The field indicates the company and division, displayed as CONO_DIVI.
nvoice/InvoiceLine/InvoiceCharge/Description	
For Bill for Prepayment: OOLINE.OBCRD0; OIS100MI/LstConnCOCharge	For Bill for Prepayment: The field indicates the charge description
For Common Invoice: CINCRG.CICRDO; INVBODMI/SelCharges	For Common Invoice: The field indicates the charge description.
nvoice/InvoiceLine/InvoiceCharge/Amount	
For Bill for Prepayment: OINVOH.UHAMT2; OIS350MI/GetInvHead	For Bill for Prepayment: Get all Records with IVTP = 67, 60, 65. The fields indicates the Charge Amount
For Common Invoice: CINCRG.CIAMTC; INVBODMI/SelCharges	For Common Invoice: The field indicates the amount in transaction currency.
@currencyID	
For Bill for Prepayment: OINVOH.UHCUCD; -/-	For Bill for Prepayment: The field indicates the abbreviation for the currency. The abbreviatior should follow ISO standards.
For Common Invoice:	Example:

	SEK Swedish kronor.
	For Common Invoice:
	The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceCharge/BaseAmount For Bill for Prepayment:	For Bill for Prepayment:
OINVOL.ONIVLA; OIS350MI/LstInvLine	Get all Records with IVTP = 67, 60, 65. The fields indicates the
OHAVOE.OHAVEA, OHOOOOMI/ESHINVEIHO	Charge Amount
For Common Invoice:	•
CINCRG.CIAMLC; INVBODMI/SelCharges	For Common Invoice:
MaurranaulD	The filed indicates the amount in local currency.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/InvoiceCharge/ReportAmount	
For Common Invoice:	For Common Invoice:
CINCRG.CIAMLC	The field indicated the 'InvoiceCharge/BaseAmount' converted to
CINHED.CIRCUC	Reporting currency of the base country and exchange rate as
CINHED.CIRCUD CINHED.CIRCUE	indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/SelCharges	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/InvoiceCharge/Calculation/RateNumeric	For Bill for Dronouments
For Bill for Prepayment: OOLINE.OBCRFA; OIS100MI/LstConnCOCharge	For Bill for Prepayment: The field indicates the calculation factor that is used to calculate the
OCENIC.OBON A, OIO TOOM/ESICOTITIO OTALIGO	charge amount. The field is used in combination with calculation
	method 1-5. A charge is calculated by multiplying the calculation
	factor and the base selected in the Calculation method field. The
	calculation is made when the customer order is invoiced.
Invoice/InvoiceLine/InvoiceCharge/ReasonCode	E D''I (D
For Bill for Prepayment: OOLINE.OBCRD0; OIS100MI/LstConnCOCharge	For Bill for Prepayment: The field indicates the name or description of the charge to be printed
OOLINE.OBCRDO, OIS 100MI/ESICOTITICOCHAIge	on the external document.
Invoice/InvoiceLine/InvoiceCharge/Tax	STEELS STATE WOODS TO STATE OF
@type	
For Common Invoice:	For Common Invoice:
CINVTD.CITATM; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'SalesTax' then block must be created per field
	VTID, VTI2, VTI3, VTI4 and VTI5. Else if Tax type (TXTB) = 'Perception' then block must be created per
	field VTID.
	Otherwise, as is.
@subType	
For Common Invoice:	For Common Invoice:
CINVTD.CITSAB; INVBODMI/GetTaxDetails	Create this attribute only if Tax method (TATM) = 2.
	The field indicates the standard tax code based on the Invoice
	translation 'TaxsubType' (CRS881/882).
	Alternative if generic translation not used: Actual value of TSAB.
Invoice/InvoiceLine/InvoiceCharge/Tax/ID	
For Common Invoice: CINVTD.CIVTCD	For Common Invoice: The field indicates the line charge VAT / Tax code.
CISETC	The field findicates the line charge VAT / Tax code.
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code
,	(SETC).
	Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/
	address (TAXC).
@accountingEntity	Otherwise, publish VAT code (VTCD).
Gaccounting	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceLine/InvoiceCharge/Tax/TaxJurisdicationCodes/Code	
For Common Invoice:	For Common Invoice:
CINVTD.CITAJ1; INVBODMI/GetTaxDetails	The field indicates the Tax juridisction code.
	Create this element only if Tax method (TATM) = 2.
Invoice/InvoiceLine/InvoiceCharge/Tax/BasisAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CIBASA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in transaction currency.
@currencyID For Common Invoice:	
I OF COMMINGER MYCHOG.	

CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceCharge/Tax/BasisTaxAuthorityAmount	,
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA	The field indicated the 'Tax/BasisBaseAmount' converted to Tax
CINHED.CIIBT1	authority currency (IBT1) of the base country and exchange rate
CINHED.CIIBT2	(IBT7) as indicated in the invoice header table (CINHED). The
CINHED.CIIBT4	amount is presented with 2 decimals but rounded to the number of
CINHED.CIIBT5	decimals (IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails	Amount in currency of Tay authority (IDT1) is only nanulated if the
GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base) currency (LOCD).
	The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CIIBT1; INVBODMI/GetHeader	The field indicated the Tax authority currency (IBT1) of the base
	country as indicated in the invoice header table (CINHED).
Invoice/InvoiceLine/InvoiceCharge/Tax/BasisBaseAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CIBALA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in local currency.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the transaction currency.
·	The field indicates the transaction editericy.
Invoice/InvoiceLine/InvoiceCharge/Tax/BasisReportAmount For Common Invoice:	For Common Invoice:
CINVTD.CIBALA	The field indicated the 'InvoiceCharge/Tax/BasisBaseAmount'
CINHED.CIRCUC	converted to Reporting currency of the base country and exchange
CINHED.CIRCUD	rate as indicated in the invoice header table (CINHED). The amount
CINHED.CIRCUE	is presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/InvoiceCharge/Tax/Calculation/RateNumeric	
For Common Invoice:	For Common Invoice:
CINVTD.CIVTP1	The field indicates the VAT rate converted to decimal.
CITAR1; INVBODMI/GetTaxDetails	Format: 1.00 (for 1%)
	If Tax method (TATM) = 2, use TAR1. Otherwise, use VTP1.
Invoice/InvoiceLine/InvoiceCharge/Tax/Exemption/ID	,
For Common Invoice:	For Common Invoice:
CINVTD.CIVTCD	The field indicates the VAT/Tax exemption code.
CISETC	·
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation cod
	(SETC).
	Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/
	address (TAXC).
@accountingEntity	Otherwise, publish VAT code (VTCD).
@accountingEntity	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceLine/InvoiceCharge/Tax/Exemption/Description	
For Common Invoice:	For Common Invoice:
CINVTD.CIT102; INVBODMI/GetTaxDetails	The field indicates the VAT exemption description.
Invoice/InvoiceLine/InvoiceCharge/Tax/Exemption/Amount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXEA; INVBODMI/GetTaxDetails	The field indicates the exemption amount in transaction currency.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceCharge/Tax/Exemption/BaseAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL; INVBODMI/GetTaxDetails	The field indicates the exemption amount in local currency.
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/InvoiceCharge/Tax/Exemption/ReportAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL	The field indicated the 'InvoiceCharge/Tax/Exemption/BaseAmount'
Infor May 26, 20)23

CINHED.CIRCUC converted to Reporting currency of the base country and exchange CINHED.CIRCUD rate as indicated in the invoice header table (CINHÉD). The amount CINHED.CIRCUE is presented with 2 decimals but rounded to the number of decimals CINHED.CIRCUF (DCCD) for the currency. The report amount is required by some countries for the electronic CINHED.CIDCCD.-; INVBODMI/GetTaxDetails GetHeader invoice sent to the authorities. @currencyID For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader For Common Invoice: The field indicated the reporting currency. Invoice/InvoiceLine/InvoiceCharge/Tax/Description For Common Invoice: For Common Invoice: CINVTD.CITX40; INVBODMI/GetTaxDetails The field indicates the VAT description. Invoice/InvoiceLine/InvoiceCharge/Tax/TaxAuthorityAmount For Common Invoice: For Common Invoice: CINVTD.CITXAL The field indicated the 'Tax/BaseAmount' converted to Tax authority CINHED.CIIBT1 currency (IBT1) of the base country and exchange rate (IBT7) as CINHED.CIIBT2 indicated in the invoice header table (CINHED). The amount is CINHED.CIIBT4 presented with 2 decimals but rounded to the number of decimals CINHED.CIIBT5 (IBT5) for the currency. CINHED.CIIBT7.-; INVBODMI/GetTaxDetails Amount in currency of Tax authority (IBT1) is only populated if the GetHeader currency differ to the Invoice currency (CUCD) and Local (base) currency (LOCD). The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities. @currencyID For Common Invoice: For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED). Invoice/InvoiceLine/InvoiceCharge/Tax/Amount For Common Invoice: For Common Invoice: CINVTD.CITXAM; INVBODMI/GetTaxDetails The field indicates the VAT amount in transaction currency. @currencyID For Common Invoice: For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader The field indicates the transaction currency. Invoice/InvoiceLine/InvoiceCharge/Tax/BaseAmount For Common Invoice: For Common Invoice: CINVTD.CITXAL; INVBODMI/GetTaxDetails The field indicates the VAT amount in local currency. @currencyID For Common Invoice: For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader The field indicates the local currency. Invoice/InvoiceLine/InvoiceCharge/Tax/ReportAmount For Common Invoice: For Common Invoice: CINVTD.CITXAL The field indicated the 'InvoiceCharge/Tax/BaseAmount' converted to CINHED.CIRCUC Reporting currency of the base country and exchange rate as CINHED.CIRCUD indicated in the invoice header table (CINHED). The amount is CINHED.CIRCUE presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. CINHED.CIRCUF CINHED.CIDCCD.-; INVBODMI/GetTaxDetails The report amount is required by some countries for the electronic GetHeader invoice sent to the authorities. @currencyID For Common Invoice: For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader The field indicated the reporting currency Invoice/InvoiceLine/InvoiceCharge/Tax/WithheldIndicator For Common Invoice: For Common Invoice: CINCRG.CIVTI2, CINVTD.CIVTCD, CINVTD.CITATM.; INVBODMI/ The field indicates that the tax is withheld and is defined by using a VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where SelCharges, GetTaxDetails the VAT rate 2 (VTP2) is set to a negative rate for the tax to be withheld. VAT codes applicable to withheld tax must be defined 'Business Message Data Translation. Display' (CRS881) for: - Business message (BMSG) = Invoice - Parent element (ELMP) = Tax - Data element (ELMD) = WithheldIndicator The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for example VAT code 1 must be defined as 01). NB: The WithheldIndicator is only applicable to divisions using Tax method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.

Invoice/InvoiceLine/InvoiceAllowance/ID
For Bill for Prepayment:

For Bill for Prepayment: For Bill for Prepayment: Constant = "Allowance".; / Constant = 'Allowance'

For Common Invoice: Set to 'Discount per line' @accountingEntity For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceLine/InvoiceAllowance/Amount For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHAMT2; OIS350MI/GetInvHead Display data if IVTP = 32,33,34. The fields indicates the Allowance Amount in foreign For Common Invoice: CINLND.CIAMTC; INVBODMI/SelLineDiscount For Common Invoice: The field indicates the amount in transaction currency. @currencvID For Bill for Prepayment: For Bill for Prepayment: OINVOH.UHCUĆD; -/-The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards. For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader Example: GBP British pounds USD United States dollars SEK Swedish kronor. For Common Invoice: The field indicates the transaction currency Invoice/InvoiceLine/InvoiceAllowance/BaseAmount For Bill for Prepayment: For Bill for Prepayment: OINVOL.ONIVLA; OIS350MI/LstInvLine Display data if IVTP = 32,33,34. The fields indicates the Allowance Amount in local currency. For Common Invoice: CINLND.CIAMLC; INVBODMI/SelLineDiscount For Common Invoice: The field indicates the amount in local currency. @currencyID For Bill for Prepayment: For Bill for Prepayment: CMNDIV.CCLOCD; OIS350MI/GetInvHead The field indicates the currency For Common Invoice: For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader The field indicates the local currency Invoice/InvoiceLine/InvoiceAllowance/ReportAmount For Common Invoice: For Common Invoice: CINLND.CIAMLC The field indicated the 'InvoiceAllowance/BaseAmount' converted to CINHED.CIRCUC Reporting currency of the base country and exchange rate as CINHED.CIRCUD indicated in the invoice header table (CINHED). The amount is CINHED.CIRCUE presented with 2 decimals but rounded to the number of decimals CINHED.CIRCUF (DCCD) for the currency. CINHED.CIDCCD.-; INVBODMI/SelLineDiscount The report amount is required by some countries for the electronic GetHeader invoice sent to the authorities. @currencyID For Common Invoice: For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader The field indicated the reporting currency Invoice/InvoiceLine/InvoiceAllowance/Tax @type For Common Invoice: For Common Invoice: CINVTD.CITATM; INVBODMI/GetTaxDetails If Tax type (TXTB) = 'SalesTax' then block must be created per field VTID, VTI2, VTI3, VTI4 and VTI5. SelLineDisc Else if Tax type (TXTB) = 'Perception' then block must be created per field VTID. Otherwise, as is. @subType For Common Invoice: For Common Invoice: CINVTD.CITSAB; INVBODMI/GetTaxDetails Create this attribute only if Tax method (TATM) = 2. The field indicates the standard tax code based on the Invoice translation 'TaxsubType' (CRS881/882). Alternative if generic translation not used: Actual value of TSAB. Invoice/InvoiceLine/InvoiceAllowance/Tax/ID For Common Invoice: For Common Invoice: CINVTD.CIVTCD; INVBODMI/GetTaxDetails The field indicates the line discount VAT code. @accountingEntity

The field indicates the company and division, displayed as CONO DIVI. Invoice/InvoiceLine/InvoiceAllowance/Tax/TaxJurisdicationCodes/Code

For Common Invoice: For Common Invoice:

CINVTD.CITAJ1; INVBODMI/GetTaxDetails The field indicates the Tax juridisction code.

May 26, 2023

For Common Invoice:

	Create this element only if Tax method (TATM) = 2.
Invoice/InvoiceLine/InvoiceAllowance/Tax/BasisAmount For Common Invoice: CINVTD.CIBASA; INVBODMI/GetTaxDetails @currencyID For Common Invoice:	For Common Invoice: The field indicates the basis amount of the tax in transaction currency. For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/BasisTaxAuthorityAmount For Common Invoice: CINVTD.CIBALA CINHED.CIIBT1 CINHED.CIIBT2 CINHED.CIIBT4 CINHED.CIIBT5 CINHED.CIIBT5 CINHED.CIIBT7; INVBODMI/GetTaxDetails GetHeader	For Common Invoice: The field indicated the 'Tax/BasisBaseAmount' converted to Tax authority currency (IBT1) of the base country and exchange rate (IBT7) as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (IBT5) for the currency. Amount in currency of Tax authority (IBT1) is only populated if the currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD).
@currencyID	The amount in tax authority currency is required by some countries for the electronic invoice sent to the authorities.
For Common Invoice: CINHED.CIIBT1; INVBODMI/GetHeader	For Common Invoice: The field indicated the Tax authority currency (IBT1) of the base country as indicated in the invoice header table (CINHED).
Invoice/InvoiceLine/InvoiceAllowance/Tax/BasisBaseAmount	For Common Invoice:
For Common Invoice: CINVTD.CIBALA; INVBODMI/GetTaxDetails @currencyID	The field indicates the basis amount of the tax in local currency.
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/BasisReportAmount	The field findicates the transaction currency.
For Common Invoice: CINVTD.CIBALA CINHED.CIRCUC CINHED.CIRCUD CINHED.CIRCUE CINHED.CIRCUE CINHED.CIRCUF CINHED.CIDCCD; INVBODMI/GetTaxDetails GetHeader	For Common Invoice: The field indicated the 'InvoiceAllowance/Tax/BasisBaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the currency. The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Calculation/RateNumeric	The field indicated the reporting currency.
For Common Invoice: CINVTD.CIVTP1 CITAR1; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT/Tax rate converted to decimal. Format: 1.00 (for 1%)
	If Tax method (TATM) = 2, use TAR1. Otherwise, use VTP1.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/ID For Common Invoice: CINVTD.CIVTCD CISETC	For Common Invoice: The field indicates the VAT/Tax exemption code.
CITAXC; INVBODMI/GetTaxDetails	If Tax type (TXTB) = 'Perception', publish service tax calculation code (SETC). Else if Tax type (TXTB) = 'SalesTax', publish Tax code customer/ address (TAXC). Otherwise, publish VAT code (VTCD).
@schemeName	For Common Invoice: The field indicates the company and division, displayed as CONO DIVI.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/Description For Common Invoice: CINVTD.CIT102; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT exemption description.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/Amount For Common Invoice: CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the exemption amount in transaction currency. For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/BaseAmount For Common Invoice: CINVTD.CITXEL; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the exemption amount in local currency.
Infor May 26, 202	3 27

Infor

11170100	
@currencyID	
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/ReportAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXEL	The field indicated the 'InvoiceAllowance/Tax/Exemption/
CINHED.CIRCUC	BaseAmount' converted to Reporting currency of the base country
CINHED.CIRCUD	and exchange rate as indicated in the invoice header table (CINHED).
CINHED.CIRCUE	The amount is presented with 2 decimals but rounded to the number
CINHED.CIRCUF	of decimals (DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	For Common Invaion
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/Description	For Common Invaion
For Common Invoice: CINVTD.CITX40; INVBODMI/GetTaxDetails	For Common Invoice: The field indicates the VAT description.
@languagelD	The field findicates the VAT description.
For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UBORNO: /	0
Invoice/InvoiceLine/InvoiceAllowance/Tax/TaxAuthorityAmount	<u> </u>
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'Tax/BaseAmount' converted to Tax authority
CINHED.CIIBT1	currency (IBT1) of the base country and exchange rate (IBT7) as
CINHED.CIIBT2	indicated in the invoice header table (CINHED). The amount is
CINHED.CIIBT4	presented with 2 decimals but rounded to the number of decimals
CINHED.CIIBT5	(IBT5) for the currency.
CINHED.CIIBT7; INVBODMI/GetTaxDetails	•
GetHeader	Amount in currency of Tax authority (IBT1) is only populated if the
	currency differ to the Invoice currency (CUCD) and Local (base)
	currency (LOCD).
	The amount in tax authority currency is required by some countries
@augramaudD	for the electronic invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIIBT1; INVBODMI/GetHeader	The field indicated the Tax authority currency (IBT1) of the base
GIN IED.GIIDTT, INVOCOMI/Gett leadel	country as indicated in the invoice header table (CINHED).
Invoice/InvoiceLine/InvoiceAllowance/Tax/Amount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXAM; INVBODMI/GetTaxDetails	The field indicates the VAT amount in transaction currency.
@currencyID	The field managed and to the amount in a discourse out only in
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/BaseAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
@currencyID	·
For Common Invoice:	For Common Invoice:
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/InvoiceAllowance/Tax/ReportAmount	
For Common Invoice:	For Common Invoice:
CINVTD.CITXAL	The field indicated the 'InvoiceAllowance/Tax/BaseAmount' converted
CINHED.CIRCUC	to Reporting currency of the base country and exchange rate as
CINHED.CIRCUD	indicated in the invoice header table (CINHED). The amount is
CINHED.CIRCUE	presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/GetTaxDetails	The report amount is required by some countries for the electronic
GetHeader	invoice sent to the authorities.
@currencyID	For Common Invaion
For Common Invoice: CINHED.CIRCUD; INVBODMI/GetHeader	For Common Invoice: The field indicated the reporting currency.
	The note indicated the reporting outlettey.
Invoice/InvoiceLine/InvoiceAllowance/Tax/WithheldIndicator	For Common Invaion:
For Common Invoice:	For Common Invoice: The field indicates that the tax is withheld and is defined by using a
CINLND.CIVTI2, CINVTD.CIVTCD, CINVTD.CITATM.; INVBODMI/ SelLineDiscount, GetTaxDetails	VAT code (VTCD) with VAT method (VATT) 2-Combined VAT where
Golding Discount, Oct Landetails	the VAT rate 2 (VTP2) is set to a negative rate for the tax to be
	withheld.
	VAT codes applicable to withheld tax must be defined 'Business
	Managa Data Translation, Display! (CDS991) for:

VAT codes applicable to withheld tax must be defined 'Business Message Data Translation. Display' (CRS881) for:

- Business message (BMSG) = Invoice

- Parent element (ELMP) = Tax

- Data element (ELMD) = WithheldIndicator
The VAT code(s) is defined in (CRS882) and field 'M3 data' (MVXD) and must include the leading zero in case of only one digit used (for

III VOICE	example VAT code 1 must be defined as 01).
	·
	NB: The WithheldIndicator is only applicable to divisions using Tax method 1-VAT and is populated if the control property 'm3beWithheldTax' has been activated (true), default value is false.
Invoice/InvoiceLine/InvoiceAllowance/AdjustmentTypeCode @listID	mosevitament rax ride seem dentated (trac), dendati value le talee.
For Bill for Prepayment: ODLINE.UBPONR; /	For Bill for Prepayment: 0
Invoice/InvoiceLine/InvoiceAllowance/RateCurrency @listID	
For Bill for Prepayment: OINVOH.UHCUCD; /	For Bill for Prepayment: 0
nvoice/InvoiceLine/OrderCommission/SalesPerson/ID	
@schemeName For Bill for Prepayment: ODLINE.UBDCOS; /	For Bill for Prepayment:
nvoice/InvoiceLine/OrderCommission/Amount	
@currencyID For Bill for Prepayment:	For Bill for Prepayment:
ODHEAD.UACUNO; /	0
nvoice/InvoiceLine/Classification/Codes/Code	
For Common Invoice: CINLIN.CITEDL; INVBODMI/SelLines	For Common Invoice: The field indicates different classifications for the invoice:
C	Sequence 1:
	 The field indicates the delivery term (TEDL) of the invoice and is populated for summary invoices (see InvoiceHeader for other
	invoices).
Dsequence	For Common Invoice
	For Common Invoice: The field indicates the classification sequence number.
DlistID	
	For Common Invoice: Set to 'Incoterms' for sequence = 1.
nvoice/InvoiceLine/UserArea	
For Common Invoice:	For Common Invoice:
OIDTRL.OTICDN; CMS135MI/Lst	 The field indicates the import declaration number. This is for the following source transaction:
	OI20-CustomerOrder with transaction type (TTYP) 31
	CO20-MaintenanceOrder with transaction type (TTYP) 41 and 61 SO20-Rental Agreement with transaction type (TTYP) 71
	Set attribute sequence to an incremental value.
	Set attribute type to 'IntegerType'. Set attribute name to 'Icl.CustomsFormNumber'.
nvoice/InvoiceLine/RequestedDeliveryDate	
For Common Invoice: CINLIN.CIDWDZ; INVBODMI/SelLines	For Common Invoice: The field indicates the requested delivery date.
nvoice/InvoiceLine/CustomerParty/PartyIDs/ID	,,,
For Bill for Prepayment:	For Bill for Prepayment:
OINVOH.UHCUNO; OIS350MI/GetInvHead	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.
For Common Invoice:	
CINPTY.CICUNO; INVBODMI/GetParty	For Common Invoice: The field indicates the customer number.
@schemeName	For Order to the control of the cont
	For Common Invoice: Set to 'CustomerNumber'.
DaccountingEntity	
For Bill for Prepayment: ; -/-	For Bill for Prepayment: 0
.,,	•
	For Common Invoice: The field indicates the company and division, displayed as
	CONO DIVI.
nvoice/InvoiceLine/CustomerParty/PartyIDs/TaxID	
For Bill for Prepayment: OINVOL.ONVTCD; OIS350MI/GetInvLine	For Bill for Prepayment: The field indicates a VAT code. The VAT code controls what VAT
SHAV SELONVI OD, GIGGGGINI/OGUNVEING	method and VAT rate to apply.
For Common Invoice:	
1) CINPTY.CIVRNO 2) CINPTY.CIVRNL	For Common Invoice: The field indicates the following Tax IDs of the customer:
3) CINPTY.CICORG	1) VAT Registration number (VRNO).
4) CINPTY.CICOR2 5) CINPTY.CICOR4	Tax declaration number (VRNL). CountryIdentificationNumber (CORG).
6) CINPTY.CININO	CountryIdentificationNumber (COR2).
7) CINPTY.CININ2.; INVBODMI/GetParty	5) CountryIdentificationNumber (COR4).

IIIVOICE	
@schemeName	6) National Identity Number (NINO). 7) National Identity Number (NIN2).
wschemename	For Common Invoice: 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceLine/CustomerParty/Name For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UNCÚN1; OIS350MI/GetDelLine	The field indicates the name of the customer.
For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty	For Common Invoice: The field indicates the customer name.
Invoice/InvoiceLine/CustomerParty/Location/Address @type	
	For Common Invoice: Set to 'text'.
Invoice/InvoiceLine/CustomerParty/Location/Address/AttentionOfNat	
For Bill for Prepayment: OOHEAD.OARESP; OIS100MI/GetHead	For Bill for Prepayment: Responsible name
For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: The field indicates the contact name.
Invoice/InvoiceLine/CustomerParty/Location/Address/AddressLine For Bill for Prepayment: OCUSMA.Various; OIS100MI	For Bill for Prepayment: Address line
OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	For Common Invoice: The field indicates the address lines.
For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	
@sequence	For Common Invoice: The field indicates the address line sequence.
Invoice/InvoiceLine/CustomerParty/Location/Address/CityName	
For Bill for Prepayment: OCUSMA.OKTOWN; OIS100MI OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	For Bill for Prepayment: The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
For Common Invoice: CINPTY.CITOWN; INVBODMI/GetParty	For Common Invoice: The field indicates the city name.
Invoice/InvoiceLine/CustomerParty/Location/Address/CountrySubDiv	visionCode
For Bill for Prepayment: OCUSMA.OKECAR; OIS100MI	For Bill for Prepayment: The field indicates the customer responsible. The retrieval is based
OIS100MI CRS610MI/GetLineAddress/GetAddress/GetBasicData	on hierarchy. It will be retrieved first in table OADRE, if not exists it will retrieve on OCUSAD else OCUSMA
For Common Invoice: CINPTY.CIECAR; INVBODMI/GetParty	For Common Invoice: The field indicates an area, province or state within a country.
@listID	For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceLine/CustomerParty/Location/Address/CountryCode For Bill for Prepayment: OCUSMA.OKCSCD; OIS100MI OIS100MI	For Bill for Prepayment: The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it
CRS610MI/GetLineAddress/GetAddress/GetBasicData For Common Invoice:	will retrieve on OCUSAD else OCUSMA For Common Invoice:
CINPTY.CICSCD; INVBODMI/GetParty @listID	The field indicates the country code.
	For Common Invoice: Set to 'Countries'.
Invoice/InvoiceLine/CustomerParty/Location/Address/PostalCode For Bill for Prepayment: OCUSMA.OKPONO; OIS100MI	For Bill for Prepayment: The field indicates the customer responsible. The retrieval is based

Invoice on hierarchy. It will be retrieved first in table OADRE, if not exists it CRS610MI/GetLineAddress/GetAddress/GetBasicData will retrieve on OCUSAD else OCUSMA For Common Invoice: For Common Invoice: CINPTY.CIPONO; INVBODMI/GetParty The field indicates the postal code. Invoice/InvoiceLine/CustomerParty/Contact/ID For Bill for Prepayment: For Bill for Prepayment: The field indicates the unique identification of a customer. It can OCUSCO.CCCUNO; CMS055MI/LstByCustomer contain up to ten positions, and is alphanumeric. For Common Invoice: OCUSCO.CCCNPE; CMS055MI/LstByCustomer For temporary customers (customer type 9), the customer number must be within a defined range where only customers with customer type 9 can be entered. For Common Invoice: The field indicates the contact ID. @accountingEntity For Bill for Prepayment: For Bill for Prepayment: For Common Invoice: The field indicates the company and division, displayed as CONO DIVI. @lid For Bill for Prepayment: For Bill for Prepayment: CMS055MI/LstByCustomer The field indicates the name of the customer's contact. Invoice/InvoiceLine/CustomerParty/Contact/Name For Common Invoice: For Common Invoice: CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name Invoice/InvoiceLine/CustomerParty/Contact/Communication @sequence For Common Invoice: The field indicates the sequence number. @preferredIndicator For Common Invoice: Set to 'false'. Invoice/InvoiceLine/CustomerParty/Contact/Communication/ChannelCode For Common Invoice: Set to "Phone" if telephone number is 1, 2, facsimile number or mobile Set to "EMail" if e-mail address. @listID For Common Invoice: Set to 'Communication Channels' Invoice/InvoiceLine/CustomerParty/Contact/Communication/UseCode For Common Invoice: Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number. @listID For Common Invoice: Set to "Communication Use Codes" Invoice/InvoiceLine/CustomerParty/Contact/Communication/DialNumber For Bill for Prepayment: For Bill for Prepayment: CCUCON Various; CRS618MI/Get The field indicates the telephone number of the customer. For Common Invoice: For Common Invoice: CCUCON.CCPHNO The field indicates the telephone number. CCPHN2; CRS618MI/Get Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address @type For Common Invoice: Set to 'text'.

Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/AddressLine

For Bill for Prepayment: For Bill for Prepayment:

CCUCON. Various; CRS618MI/Get The field indicate an Address Line

For Common Invoice: For Common Invoice: The field indicates the address lines.

CCUCON.CCCUA1

CCCUA2

CCCUA3

CCCUA4; CRS618MI/Get

@sequence

For Common Invoice:

The field indicates the address sequence number.

Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CityName

For Bill for Prepayment:

May 26, 2023

Invoice CCUCON.OKTOWN: CRS618MI/Get For Bill for Prepayment: The field indicates the city in an address. The information is For Common Invoice: mandatory when address formatting is used, and when a city is an CCUCON.CCTOWN; CRS618MI/Get address element used in the formatting rule. Address formatting rules are defined for each country. For Common Invoice: The field indicates the city name. Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CountrySubDivisionCode CCUCON.CCECAR; CRS618MI/Get For Bill for Prepayment: The field indicates an area, province or state within a country For Common Invoice: The field indicates an area, province or state within a country. @listID For Common Invoice: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Get For Bill for Prepayment: The field indicates a country For Common Invoice: The field indicates the country code. @listID For Common Invoice: Set to 'Countries'. Invoice/InvoiceLine/CustomerParty/Contact/Communication/Address/PostalCode CCUCON.CCPONO; CRS618MI/Get For Bill for Prepayment: The field indicates a postal code for a specific address. The postal code is an address element that can be part of an address line if address formatting rules are used. For Common Invoice: The field indicates the postal code. Invoice/InvoiceLine/CustomerParty/Contact/Communication/URI CCUCON.CCEMAL; CRS618MI/Get For Bill for Prepayment: The field indicates an e-mail address for the customer, supplier, etc. entered. For Common Invoice: The field indicates the email address Invoice/InvoiceLine/CustomerParty/Contact/Communication/HTMLPreferredIndicator For Bill for Prepayment: For Bill for Prepayment: Constant = 'true'.; N/A/ Constant = 'true' For Common Invoice: Set to 'false'. Invoice/InvoiceLine/CustomerParty/Contact/Communication/Preference/Sequence For Bill for Prepayment: For Bill for Prepayment: Constant = '1'.; N/A/ Constant = '1' Invoice/InvoiceLine/CustomerParty/Contact/Communication/Preference/Indicator For Bill for Prepayment: For Bill for Prepayment: Constant = 'true'.; N/A/ Constant = 'true' For Common Invoice: Set to 'false'. Invoice/InvoiceLine/SalesOrderReference/DocumentID/ID For Bill for Prepayment: For Bill for Prepayment: ODLINE.ONORNO; OIS350MI/GetDelLine The field indicates a unique identity for a customer order. For Common Invoice: Different order number series can be used, which are controlled by an CINDRE.CIDIDN; INVBODMI/SelDocReference assigned order type. Number series are connected to an order type

For Common Invoice:

The field indicates the customer order number. @accountingEntity

For Bill for Prepayment: For Bill for Prepayment:

For Common Invoice:

May 26, 2023

	The field indicates the company and division, displayed as
@location	CONO_DIVI.
For Bill for Prepayment:; -/-	For Bill for Prepayment: 0
, <i>-,-</i>	·
For Common Invoice: CINLIN.CIWHLO; INVBODMI/SelLines	For Common Invoice: The field indicates the warehouse.
Invoice/InvoiceLine/SalesOrderReference/DocumentDateTime	The field indicates the warehouse.
For Bill for Prepayment: OOHEAD.OAORDT: OIS100MI/GetHead	For Bill for Prepayment: Document date
Invoice/InvoiceLine/SalesOrderReference/LineNumber	Document date
For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UBPONR; OIS350MI/GetDelLine	This field indicates the line number
For Common Invoice: CINDRE.CIDIDN; INVBODMI/SelDocReference	For Common Invoice: The field indicates the customer order line number.
Invoice/InvoiceLine/SalesOrderReference/SubLineNumber	
For Bill for Prepayment: ODLINE.UBPOSX; OIS350MI/GelDelLine	For Bill for Prepayment: The field indicates a sequence number within a line number. The
·	suffix is used in kit order handling. The kit order line has the suffix 00,
For Common Invoice: CINDRE.CIDLSN; INVBODMI/SelDocReference	and the suffix of the detail lines may vary from 01 to 99.
ON DIVELOIDED IN, INVESTIGATION CONTROL OF THE CONT	For Common Invoice:
Invoice/InvoiceLine/ExtendedCost/Amount	The field indicates the customer order subline number.
For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UBDCOS; OIS350MI/GetDelLine	This field indicates the Extended Cost . (Issued cost amount found in
For Common Invoice:	OIS356/F).
CINLIN.CIDCOL; INVBODMI/SelLines	For Common Invoice:
@currencyID	The field indicates the extended cost in transaction currency.
For Bill for Prepayment: OINVOH.UHCUCD; -/-	For Bill for Prepayment: The field indicates the abbreviation for the currency. The abbreviation
Olivon.oncood, 4-	should follow ISO standards.
For Common Invoice: CINHED.CICUCD; INVBODMI/GetHeader	Example:
ON TEB. 01000B, INVESTIMING OUT 10000	GBP British pounds
	USD United States dollars SEK Swedish kronor.
	For Common Invoice: The field indicates the transaction currency.
Invoice/InvoiceLine/ExtendedCost/ReportAmount	
For Common Invoice: CINLIN.CIDCOS	For Common Invoice: The field indicated the 'ExtendedCost/BaseAmount' converted to
CINHED.CIRCUC	Reporting currency of the base country and exchange rate as
CINHED.CIRCUD CINHED.CIRCUE	indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/SelLines GetHeader	The report amount is required by some countries for the electronic invoice sent to the authorities.
@currencyID For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/ExtendedCost/BaseAmount	
For Bill for Prepayment: ODLINE.UHIVAM; OIS350MI/GetDelLine	For Bill for Prepayment: This field indicates the Extended Cost Converted to local currency
·	,
For Common Invoice: CINLIN.CIDCOS; INVBODMI/SelLines	For Common Invoice: The field indicates the extended cost in local currency.
@currencyID	For Common Invoice:
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
Invoice/InvoiceLine/Rebate	
@type	For Common Invoice:
	If IVTP = 69 then set to 'Supplier'.
Invoice/InvoiceLine/Rebate/Amount	If IVTP = 37 then set to 'Customer'.
For Common Invoice:	For Common Invoice:
CINLIN.CIREB1; INVBODMI/SelLines @currencyID	The field indicates the rebate amount in transaction currency.
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.

Invoice/InvoiceLine/Rebate/BaseAmount

For Common Invoice:

CINLIN.CIREBL; INVBODMI/SelLines

@currencyID

For Common Invoice:

CINHED.CILOCD; INVBODMI/GetHeader

Invoice/InvoiceLine/Rebate/ReportAmount

For Common Invoice: CINLIN.CIREBL CINHED.CIRCUC CINHED.CIRCUD CINHED.CIRCUE CINHED.CIRCUF

CINHED.CIDCCD.-; INVBODMI/SelLines

GetHeader

@currencyID

For Common Invoice:

CINHED.CIRCUD; INVBODMI/GetHeader

Invoice/InvoiceLine/ShipToParty/PartyIDs/ID

For Bill for Prepayment:

OOHEAD.OADECU; OIS100MI/GetLineAddress GetLine

For Common Invoice:

CINPTY.CICUNO; INVBODMI/GetParty

@schemeName

@accountingEntity

For Bill for Prepayment:

-.-; -/-

Invoice/InvoiceLine/ShipToParty/PartyIDs/TaxID

For Bill for Prepayment:

OCUSMA.UHVRNO; CRS610MI/GetFinancial

For Common Invoice:

- 1) CINPTY.CIVRNO
- 2) CINPTY.CIVRNL
- 3) CINPTY.CICORG
- 4) CINPTY.CICOR2
- 5) CINPTY.CICOR4
- 6) CINPTY.CININO
- 7) CINPTY.CININ2.; INVBODMI/GetParty

@schemeName

Invoice/InvoiceLine/ShipToParty/Name

For Bill for Prepayment:

ODLINE.UNCUN1; OIS350MI/GetDelLine

For Common Invoice:

CINPTY.CINAME; INVBODMI/GetParty

For Common Invoice:

The field indicates the rebate amount in local currency.

For Common Invoice:

The field indicates the local currency.

For Common Invoice:

The field indicated the 'Rebate/BaseAmount' converted to Reporting currency of the base country and exchange rate as indicated in the invoice header table (CINHED). The amount is presented with 2 decimals but rounded to the number of decimals (DCCD) for the

The report amount is required by some countries for the electronic

invoice sent to the authorities.

For Common Invoice:

The field indicated the reporting currency.

For Bill for Prepayment:

If ADRT = 1 consists of two data then display in InvoiceLine. Display field if ADRT = '1' (Delivery address). The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric. The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.

For Common Invoice:

The field indicates the delivery customer.

IF address number (ADID) is not blank, publish CUNO + ADID. It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the delivery customer code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.

For Common Invoice:

Set to 'CustomerNumber'.

For Bill for Prepayment:

For Common Invoice:

The field indicates the company and division, displayed as

CONO DIVI.

For Bill for Prepayment:

The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply.

For Common Invoice:

The field indicates the following Tax IDs of the ShipTo customer:

- 1) VAT Registration number (VRNO).
- 2) Tax declaration number (VRNL).3) CountryIdentificationNumber (CORG).
- 4) CountryIdentificationNumber (COR2).
- 5) CountryIdentificationNumber (COR4).6) National Identity Number (NINO).7) National Identity Number (NIN2).

For Common Invoice:

- 1) Set to 'TaxIdentificationNumber' if VRNO is displayed.
- 2) Set to 'TaxDeclarationNumber' if VRNL is displayed.
- 3) Set to 'CountryldentificationNumber' if CORG is displayed.
- 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryldentificationNumber' if COR4 is displayed.
- 6) Set to 'NationalIdentityNumber: if NINO is displayed.
- 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.

For Bill for Prepayment:

The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.

For Common Invoice:

The field indicates the delivery customer name.

May 26, 2023

@languagelD

For Common Invoice:

CINHED.CILNCD; INVBODMI/GetHeader The field indicates the language.

Invoice/InvoiceLine/ShipToParty/Location/Address

@type

For Common Invoice:

For Bill for Prepayment:

For Common Invoice:

Set to 'text'.

Invoice/InvoiceLine/ShipToParty/Location/Address/AttentionOfName

For Bill for Prepayment: OCUSMA. Various; OIS100MI

OIS100MI

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Common Invoice:

The field indicates the contact name.

will retrieve on OCUSAD else OCUSMA

CINPTY.CIYREF; INVBODMI/GetParty Invoice/InvoiceLine/ShipToParty/Location/Address/AddressLine

For Bill for Prepayment: OCUSMA. Various; OIS100MI

For Common Invoice:

OIS100MI

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Common Invoice:

CINPTY.CICUA1 CICUA2 CICUA3

CICUA4; INVBODMI/GetParty

@sequence

For Bill for Prepayment:

The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it

The field indicates the customer responsible. The retrieval is based

on hierarchy. It will be retrieved first in table OADRE, if not exists it

will retrieve on OCUSAD else OCUSMA

For Common Invoice:

The field indicates the address lines.

For Common Invoice:

The field indicates the address line sequence

Invoice/InvoiceLine/ShipToParty/Location/Address/CityName

For Bill for Prepayment:

OCUSMA.OKŤOWN; OIS100MI

OIS100MI

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Bill for Prepayment:

The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it

will retrieve on OCUSAD else OCUSMA

For Common Invoice:

CINPTY.CITOWN; INVBODMI/GetParty

For Common Invoice:

The field indicates the city name.

Invoice/InvoiceLine/ShipToParty/Location/Address/CountrySubDivisionCode

For Bill for Prepayment:

OCUSMA.OKĖCAR; OIS100MI

OIS100MI

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Bill for Prepayment:

The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it

will retrieve on OCUSAD else OCUSMA

For Common Invoice:

CINPTY.CIECAR; INVBODMI/GetParty

For Common Invoice:

The field indicates an area, province or state within a country.

@listID

For Common Invoice:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

Invoice/InvoiceLine/ShipToParty/Location/Address/CountryCode

For Bill for Prepayment:

OCUSMA.OKĊSĆD; OIS100MI

OIS100MI

@listID

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Bill for Prepayment:

The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it

will retrieve on OCUSAD else OCUSMA

For Common Invoice:

CINPTY.CICSCD; INVBODMI/GetParty @listID

For Common Invoice:

The field indicates the country code.

For Common Invoice: Set to 'Countries'.

Invoice/InvoiceLine/ShipToParty/Location/Address/PostalCode

For Bill for Prepayment: OCUSMA.OKPONO; OIS100MI

OIS100MI

CRS610MI/GetLineAddress/GetAddress/GetBasicData

For Bill for Prepayment:

The field indicates the customer responsible. The retrieval is based on hierarchy. It will be retrieved first in table OADRE, if not exists it

will retrieve on OCUSAD else OCUSMA

For Common Invoice: For Common Invoice: CINPTY.CIPONO; INVBODMI/GetParty

The field indicates the postal code.

Invoice/InvoiceLine/ShipToParty/Location/Address/Preference/Indicator

For Common Invoice:

Set to 'false'.

Invoice/InvoiceLine/ShipToParty/Communication/ChannelCode

For Common Invoice:

Set to 'Phone

May 26, 2023

	For Common Invoice: Set to 'Communication Channels'.
Invoice/InvoiceLine/ShipToParty/Communication/UseCode	
, ,	For Common Invoice:
	Set to 'Office', If PHNO.
@listID	Set to 'Fax', If TFNO.
@nou2	For Common Invoice:
	Set to 'Communication Use Codes'.
Invoice/InvoiceLine/ShipToParty/Communication/DialNumber	
For Common Invoice: CINPTY.; INVBODMI/GetParty	For Common Invoice: The field indicates the telephone number (PHNO) or fax number.
CINFIT., INVEODINI/GetFaity	The field indicates the telephone number (PHNO) or fax number (TFNO) of the delivery customer.
Invoice/InvoiceLine/ShipToParty/Communication/Preference/Indica	
,	For Common Invoice:
	Set to 'false'.
Invoice/InvoiceLine/ShipToParty/Contact/ID	For Pill for Pronouments
For Bill for Prepayment: OCUSCO.CCCUNO; CMS055MI/LstByCustomer	For Bill for Prepayment: Display field if ADRT = '1' (Delivery address)
OCCOOLS OCCOONS	Biopiay nois in ABTO (Boilvery againsts)
For Common Invoice:	For Common Invoice:
OCUSCO.CCCNPE; CMS055MI/LstByCustomer @accountingEntity	The field indicates the contact ID.
For Bill for Prepayment:	For Bill for Prepayment:
.; -/-	0
	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO_DIVI.
@location	For Dill for Drong recent
For Bill for Prepayment:	For Bill for Prepayment: 0
Invoice/InvoiceLine/ShipToParty/Contact/Name	0
For Bill for Prepayment:	For Bill for Prepayment:
OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the name of the customer's contact.
For Common Invoice:	For Common Invoice:
CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
Invoice/InvoiceLine/ShipToParty/Contact/Communication	
@preferredIndicator	For Common Invoice:
	Set to 'false'.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Channel	
•	For Common Invoice:
	Set to "Phone" if telephone number is 1, 2, facsimile number or
	mobile. Set to "EMail" if e-mail address.
@listID	ost to Email it o mail address.
	For Common Invoice:
	Set to 'Communication Channels'.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/UseCode	e For Common Invoice:
	Set to "Office" if telephone number is 1, 2 or e-mail address.
@listID	
	For Common Invoice: Set to "Communication Use Codes".
Invoice/InvoiceLine/ShipToParty/Contact/Communication/DialNum	
For Bill for Prepayment:	For Bill for Prepayment:
CCUCON.Various; CRS618MI/Get	The field indicates the telephone number of the customer.
For Common Invaion	For Common Invaion
For Common Invoice: CCUCON.CCPHNO	For Common Invoice: The field indicates the telephone number.
CCPHN2; CRS618MI/Get	The hold indicates the telephone number.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Address	/CityName
For Common Invoice:	For Common Invoice:
CCUCON.CCTOWN; CRS618MI/Get	The field indicates the city name.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Address. For Common Invoice:	/ CountrySubDivisionCode For Common Invoice:
CCUCON.CCECAR; CRS618MI/Get	The field indicates an area, province or state within a country.
@listID	
	For Common Invoice:
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	, - (-

	Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Address/Comm	
For Common Invoice:	For Common Invoice:
CCUCON.CCCSCD; CRS618MI/Get @listID	The field indicates the country code.
	For Common Invoice: Set to 'Countries'.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Address/Po	ostalCode
For Common Invoice:	For Common Invoice:
CCUCON.CCPONO; CRS618MI/Get	The field indicates the postal code.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/URI CCUCON.CCEMAL; CRS618MI/Get	For Bill for Prepayment: The field indicates an e-mail address for the customer, supplier, etc. entered.
	For Common Invoice: The field indicates the email address.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/HTMLPrefe	
	For Common Invoice:
	Set to 'false'.
Invoice/InvoiceLine/ShipToParty/Contact/Communication/Preference	/Indicator
• •	For Common Invoice:
	Set to 'false'.
Invoice/InvoiceLine/ShipFromParty/PartyIDs/ID	
For Common Invoice:	For Common Invoice:
CINPTY.; INVBODMI/GetParty @accountingEntity	The field indicates the warehouse ID.
wassounding_many	For Common Invoice:
	The field indicates the company and division, displayed as
	CONO DIVI.
Invoice/InvoiceLine/ShipFromParty/PartyIDs/TaxID	
For Common Invoice:	For Common Invoice:
1) CINPTY.CIVRNO	The field indicates the following Tax IDs of the ShipTo customer:
2) CINPTY CICORC	1) VAT Registration number (VRNO).
3) CINPTY.CICORG 4) CINPTY.CICOR2	Tax declaration number (VRNL). CountryldentificationNumber (CORG).
5) CINPTY.CICOR4	4) CountryIdentificationNumber (COR2).
6) CINPTY.CININO	5) CountryIdentificationNumber (COR4).
7) CINPTY.CININ2.; INVBODMI/GetParty	6) National Identity Number (NINO).
.	7) National Identity Number (NIN2).
@schemeName	For Common Invoice:
	Set to 'TaxIdentificationNumber' if VRNO is displayed.
	Set to 'TaxDeclarationNumber' if VRNL is displayed.
	Set to 'CountryIdentificationNumber' if CORG is displayed.
	4) Set to 'CountryldentificationNumber' if COR2 is displayed.
	Set to 'CountryldentificationNumber' if COR4 is displayed.
	6) Set to 'NationalIdentityNumber: if NINO is displayed.
	7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
Invoice/InvoiceLine/ShipFromParty/Name	For Common Invoices
For Common Invoice: CINPTY.CINAME; INVBODMI/GetParty	For Common Invoice: The field indicates the warehouse name.
•	THE BOIL HIMIOGICS THE WAIGHOUSE HAIHE.
Invoice/InvoiceLine/ShipFromParty/Location @type	
<i>⊝</i> 7 <i>F</i> −	For Common Invoice:
	Set to 'Warehouse'.
Invoice/InvoiceLine/ShipFromParty/Location/ID	
For Common Invoice:	For Common Invoice:
CINPTY.; INVBODMI/GetParty	
	The field indicates the warehouse.
Invoice/InvoiceLine/ShipFromParty/Location/Address	The field indicates the warehouse.
Invoice/InvoiceLine/ShipFromParty/Location/Address @type	
	For Common Invoice:
@type	For Common Invoice: Set to 'text'.
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNar	For Common Invoice: Set to 'text'. me
@type	For Common Invoice: Set to 'text'.
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNair For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: Set to 'text'. me For Common Invoice:
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNair For Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty	For Common Invoice: Set to 'text'. me For Common Invoice:
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNation Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty Invoice/InvoiceLine/ShipFromParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3	For Common Invoice: Set to 'text'. me For Common Invoice: The field indicates the contact name.
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNation Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty Invoice/InvoiceLine/ShipFromParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	For Common Invoice: Set to 'text'. me For Common Invoice: The field indicates the contact name. For Common Invoice:
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNation Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty Invoice/InvoiceLine/ShipFromParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3	For Common Invoice: Set to 'text'. me For Common Invoice: The field indicates the contact name. For Common Invoice: The field indicates the address lines.
@type Invoice/InvoiceLine/ShipFromParty/Location/Address/AttentionOfNation Common Invoice: CINPTY.CIYREF; INVBODMI/GetParty Invoice/InvoiceLine/ShipFromParty/Location/Address/AddressLine For Common Invoice: CINPTY.CICUA1 CICUA2 CICUA3 CICUA4; INVBODMI/GetParty	For Common Invoice: Set to 'text'. me For Common Invoice: The field indicates the contact name. For Common Invoice:

Invoice/InvoiceLine/ShipFromParty/Location/Address/CityName	
For Common Invoice:	For Common Invoice:
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
Invoice/InvoiceLine/ShipFromParty/Location/Address/CountrySubDiv	,
For Common Invoice:	For Common Invoice:
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country.
@listID	5.0
	For Common Invoice:
	Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
Invoice/InvoiceLine/ShipFromParty/Location/Address/CountryCode	
For Common Invoice:	For Common Invoice:
CINPTY.CICSCD; INVBODMI/GetParty	The field indicates the country code.
@listID	
	For Common Invoice:
Invesion / Invesional in a / Chin Fuo no Porte / Invesion / Address / Posta I Code	Set to 'Countries'.
Invoice/InvoiceLine/ShipFromParty/Location/Address/PostalCode For Common Invoice:	For Common Invoice:
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the postal code.
Invoice/InvoiceLine/PricingAmount/UnitPretaxAmount	
For Common Invoice:	For Common Invoice:
CINLIN.CIUPAM; INVBODMI/SelLines	The field indicates the net price of the item.
@currencyID	·
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/PricingAmount/TotalPretaxAmount	
For Common Invoice:	For Common Invoice:
CINLIN.CITPTA; INVBODMI/SelLines	The field indicates the amount of order line after line discount
@currencyID	deducted, line charge included but VAT excluded (foreign).
For Common Invoice:	For Common Invoice:
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Invoice/InvoiceLine/PricingAmount/TotalPretaxBaseAmount	
For Common Invoice:	For Common Invoice:
CINLIN.CITPLA; INVBODMI/SelLines	The field indicates the amount of order line after line discount
	deducted, line charge included but VAT excluded (local).
@currencyID	5 O
For Common Invoice: CINHED.CILOCD; INVBODMI/GetHeader	For Common Invoice: The field indicates the local currency.
	The field indicates the local currency.
Invoice/InvoiceLine/PricingAmount/TotalPretaxReportAmount For Common Invoice:	For Common Invoice:
CINLIN.CITPLA	The field indicated the 'PricingAmount/TotalPretaxBaseAmount'
CINHED.CIRCUC	converted to Reporting currency of the base country and exchange
CINHED.CIRCUD	rate as indicated in the invoice header table (CINHED). The amount
CINHED.CIRCUE	is presented with 2 decimals but rounded to the number of decimals
CINHED.CIRCUF	(DCCD) for the currency.
CINHED.CIDCCD; INVBODMI/SelLines	The report amount is required by some countries for the electronic
GetHeader @currencyID	invoice sent to the authorities.
For Common Invoice:	For Common Invoice:
CINHED.CIRCUD; INVBODMI/GetHeader	The field indicated the reporting currency.
Invoice/InvoiceLine/Reference/NameValue	
For Bill for Prepayment:	For Bill for Prepayment:
ODLINE.UBORNO; OIS350MI/GetDelLine	The field indicates a unique identity for a customer order.
	Different and a mumb an action and be seed at 11 to 11
	Different order number series can be used, which are controlled by an assigned order type. Number series are connected to an order type.
@name	assigned order type. Inditibet series are confidented to all order type.
For Bill for Prepayment:	For Bill for Prepayment:
; -/-	Constant = 'Sales Order'
@type	
For Bill for Prepayment:	For Bill for Prepayment:
; -/-	Constant = ' StringType'
@unitCode	For Bill for Drangyments
For Bill for Prepayment:; -/-	For Bill for Prepayment: 0
, -/- @currencyID	V
For Bill for Prepayment:	For Bill for Prepayment:
OINVOH.UHCUCD; -/-	The field indicates the abbreviation for the currency. The abbreviation
	should follow ISO standards.
	Evernley
	Example: GBP British pounds
	סטוווט ועס prilian pourius

@accountingEntity
For Bill for Prepayment:
-.-; -/-

USD United States dollars SEK Swedish kronor.

For Bill for Prepayment: The field indicates a division. This is an identity for a legal unit within a company group.

Division is a key value in the financial system in M3.

One division may consist of several facilities. Facilities are used in material and production management and for purchasing purposes.

<u>ItemMaster</u>

ILETTIMASIET	
ItemMaster/ItemMasterHeader/ItemID/ID 1) MITMAS.MMITNO	1) The field indicates the item number.
2) MITPOP.MPPOPN; MMS025MI/LstAlias.; /	2) The field indicates the alias for the customer's item number for alias category (ALWT) 6. The field indicates the alias for the manufacturer's item number for alias category (ALWT) 4. The field indicates the alias for the supplier's item number for alias category (ALWT) 5.
@schemeName	Set to 'Customer' for alias category (ALWT) 6. Set to 'Manufacturer' for alias category (ALWT) 4. Set to 'Supplier' for alias category (ALWT) 5.
@schemeAgencyID MITPOP.MPE0PA; MMS025MI/LstAlias	The field indicates the customer for alias category (ALWT) 6, manufacturer for alias category (ALWT) 4 and supplier for alias category (ALWT) 5.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@variationID	If SupplierShipFromCarrierRemitToMaster_MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@lid ; /	The field indicates the logical ID of the system.
ItemMaster/ItemMasterHeader/ItemID/RevisionID MITMAS.MMECVE ; MMS200MI/GetItmTech	The field indicates the revision number (edition) for an item or document.
ItemMaster/ItemMasterHeader/DisplayID MITMAS.MMITNE ; MMS200MI/GetItmBasic	The field indicates the extended item number, which is a prolonged item number used in lists, sorting, viewing information, etc.
ItemMaster/ItemMasterHeader/UPCID MITPOP.MPPOPN ; MMS025MI/LstAlias	The field indicates the alias number which is an alternative ID for an individual item.
	Display if Alias qualifier (ALWQ) is UPC.
ItemMaster/ItemMasterHeader/GTIN MITPOP.MPPOPN ; MMS025MI/LstAlias	The field indicates the alias number which is an alternative ID for an individual item.
@aahamaNama	Display if Alias qualifier (ALWQ) is GTIN, EA08, EA13 or DU14.
@schemeName MITPOP.MPALWQ	The field indicates the alias qualifier.
; MMS025MI/LstAlias	Set to 'GTIN-8' if ALWQ = EA08. Set to 'GTIN-13' if ALWQ = EA13. Set to 'GTIN-14' if ALWQ = DU14. Do not display if ALWQ is GTIN.
ItemMaster/ItemMasterHeader/LastModificationPerson/IDs/ID MITMAS.MMCHID; / @accountingEntity	The field indicates the user who last changed the data.
MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
ItemMaster/ItemMasterHeader/ServiceIndicator MTEINF.UICFMA; CMS474MI/GetUdefContent	The field indicates the service indicator. Set to 'true' for service item, 'false' for non-service item.
	Use the following input values: ITNO = <itno> UDFT = 1 CFMG = BOD CFMF = MROSERV</itno>
ItemMaster/ItemMasterHeader/Description 1) MITMAS.MMFUDS; MMS200MI/GetItmBasic	The field indicates a supplementary description of the item.
2) MITMAS.MMITDS;	2) The field indicates the item name.
MMS200MI/GetItmBasic	 The field indicates the language specific item description with attribute languageID (LNCD).
3) MITLAD.MDFUDS; MMS200MI/LstItemDescLang	,

4) MITLAD.MDITDS; MMS200MI/LstItemDescLang.; /

@type

@languageID

MITLAD.MDLNCD

; MMS200MI/LstItemDescLang

ItemMaster/ItemMasterHeader/PartyDescription

1) OCUSIT.ORITDS; OIS005MI/Get

2) OCUSIT.ORTEDS; OIS005MI/Get

3) MITVEN.IFSITD; PPS040MI/GetItemSupplier

3) MITVEN.IFSITT; PPS040MI/GetItemSupplier.; / @partyType

@partyID

MITPOP.MPE0PA; MMS025MI/LstAlias

@partyAccountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /

@type

ItemMaster/ItemMasterHeader/Classification @type

ItemMaster/ItemMasterHeader/Classification/Codes/Code

 MITMAS.MMITGR
 MMS200MI/GetItmBasic

2) MITMAS.MMITCL MMS200MI/GetItmBasic

3) MITMAS.MMBUAR MMS200MI/GetItmBasic

4) MITMAS.MMITTY MMS200MI/GetItmBasic

5) MITMAS.MMTPCD MMS200MI/GetItmBasic

6) MITMAS.MMPRGP MMS200MI/GetItmBasic

7) MITMAS.MMDIGI MMS200MI/GetItmPrice

8) MITMAS.MMCHCD MMS200MI/GetItmBasic

9) MITMAS.MMRUID MMS200MI/GetItmBasic

10) MITMAS.MMPDLN MMS200MI/GetItmBasic

11) MITTRS.MTCMMC MWS001MI/GetItem

12) MITMAS.MMITNO/ MITMAS.MMHDPR/ MITMAS.MMTPLI MMS200MI/GetItmBasic 4) The field indicates the language specific item name with attribute languageID (LNCD).

Set to 'ShortName' if Description = ITDS.

The field indicates the language ID of the description.

1) The field indicates the customer's item name if @partyType='Customer' and @type='ShortName'.

2) The field indicates the customer's item description if @partyType='Customer' and @type='Description'.

3) The field indicates the supplier's item name if @partyType='Supplier' and @type='ShortName'.

4) The field indicates the supplier's item description if @partyType='Supplier' and @type='Description'.

Set to 'Customer' for alias category (ALWT) 6. Set to 'Supplier' for alias category (ALWT) 5.

The field indicates the customer if alias category (ALWT) is 6. The field indicates the supplier if alias category (ALWT) is 5.

The field indicates the accounting entity.

If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

1) Set to "ShortName" if PartyDescription = customer's item name (ITDS) or supplier's item name (SITD).

Set to "Description" if PartyDescription = customer's item description (TEDS) or supplier's item description (SITT).

Set to 'InventoryCharacteristics' if Classification/Codes/Code@listID='Styles'.

1) Item group

The field indicates the item group. Set attribute listID to 'Item Groups'.

2) Product group

The field indicates the product group. Set attribute listID to 'Product Groups'.

3) Business area

The field indicates the business area which is used to group information for budgeting and statistical purposes. Set attribute listID to 'Business Sectors'.

4) Item type

The field indicates the item type, which determines an item's life cycle. Set attribute listID to 'Item Types'.

5) Item category

The field indicates the item category that best represents the characteristics of each item.

Set attribute listID to 'Item Classes'.

Alternatives:

00 = Normal item 02 = Phantom item

03 = Subcontracted item

04 = Tool

05 = Fixed machine 07 = Repairable item

08 = Recyclable item

11 = Extended Catalog Item (ECI)12 = Non-coded Extended Catalog Item

13 = Non-material item

6) Procurement group

The field indicates the procurement group for an item, which is used to facilitate selections by grouping similar items together.

Set attribute listID to 'Buying Groups'.

- 13) MMODMA.HHSECH MMS016MI/Get
- 14) MITMAS.MMHIE1-MMHIE5 MMS200MI/GetItmBasic
- 15) MITMAS.MMACRF MMS200MI/GetItmPrice
- 16) MITMAS.MMGRP1-MMGRP5 MMS200MI/GetItmBasic
- 17) MHIMAS.RAIFIN MHS001MI/LstIntltmVialtm
- 18) MITMAS.MMQMGP MMS200MI/GetItmBasic
- 19) MITMAS.MMPDCC MMS200MI/GetItmBasic
- 20) MITMAS.MMSAPR MMS200/GetItmPrice
- 21) MITMAS.MMINDI MMS200MI/GetItmBasic
- 22) MITMAS.MMBACD MMS200MI/GetItmBasic
- 23) MITMAS.MMACTI MMS200MI/GetItmBasic
- 24) MITMAS.MMEXPD MMS200MI/GetItmBasic
- 25) MITMAS.MMSUME MMS200MI/GetItmBasic
- 26) MITMAS.MMATMN MMS200MI/GetItmBasic
- 27) MITPOP.MPPOPN; MMS025MI/LstAlias
- 28) MITMAS.MMTECR; MMS200MI/GetItmBasic
- 29) MITMAS.MMEXCA; MMS200MI/GetItmBasic
- 30) MITMAS.MMCCI1; MMS200MI/GetItmBasic
- 31) MITMAS.MMCRI1; MMS200MI/GetItmBasic
- 32) MITTRS.MTCMCL; MWS001MI/GetItem
- 33) MITTRS.MTUNNN; MWS001MI/GetItem
- 34) MITHAZ.MHHAZC; CRS212/Lst
- 35) MITMAS.MMATMO; MMS200MI.GetItemBasic
- 36) MPGRMT.GRFLCD; PPS345MI.Get
- 37) MITMAS.MMQACD; MMS200MI.GetItemBasic.; /

7) Item discount group

The field indicates the Item discount group which may be used as a control object for calculating customer order line discounts. Set attribute listID to 'Item Rebate Groups'.

8) Configuration code

The field indicates if the item is configured when ordered or configured as a maintenance item. Set attribute listID to 'Configuration Code'.

Alternatives:

0 = No

1 = Yes

- 2 = Yes, as a family item from which product variants with item numbers are created.
- 3 = No. The item is a product variant with the item number of the family item.
- 4 = The item is a maintenance item. Regulates the item costing.
- 5 = The item is a maintenance item. Queries can be answered in order to provide a better planned work order.

9) Ruleset ID

The field indicates the identification of the ruleset in PCM (Product Configuration Management) to use when the product is configured. Set attribute listID to 'Configured Ruleset'.

10) Product line

The field indicates the product line. Set attribute listID to 'Product Line'.

11) Commodity code

The field indicates the freight commodity code Set attribute listID to 'Commodity Codes'.

12) Styles

The field indicates the Style item number. For Style, retrieve from ITNO. For SKU, retrieve from HDPR; if HDPR is blank use TPLI. Set attribute listID to 'Styles'.

13) Season control

The field indicates whether the season is checked during customer order entry. This sets how the item is processed during entry. Set attribute listID to 'Season Control'.

14) Hierarchy level 1 - 5

The field indicates item hierarchy, which groups items vertically in a way that describes a company's business. Item hierarchy provides a flexible and logical way to search for items and to group items for statistics and control purposes.

Set attribute listID to 'Item Hierarchy'

15) Accounting control object

The field indicates the user-defined accounting control object. Set attribute listID to 'Accounting Control Object'.

16) Search group 1-5

The field indicates the search group, which is a user-defined field and can be used as a complement to the item hierarchies. The purpose of the search group is to allow a horizontal search. Set attribute listID to 'Search Group'.

17) Interface item

The field indicates the interface item number. Set attribute listID to 'Interface Item'.

18) Quality group

The field provides a way to classify items that have similar quality specification.

Set attribute listID to 'Quality Groups'.

19) Number of Price decimal places

The field indicates how many decimal places for prices. Set attribute listID to 'Number of Price Decimal Places'.

20) Sales price

The field indicates the sales price. Set attribute listID to 'Sales Price'.

21) Lot control method

The field indicates if and how lot control is to be applied for each item. Set attribute listID to 'Lot Control Method'.

Alternatives:

0 = set to Not used

1 = set to Lot not defined

2 = set to Lot no.= Ser no

3 = set to In lot master

5 = set to Serial no. spec

22) Lot numbering method

The field indicates how the serial or lot number is created.

Set attribute listID to 'Lot Numbering Method'.

Alternatives:

0 = set to Manual entry

1 = set to Auto YYMM, seq

2 = set to Auto YY, seq

3 = set to Auto, seq no

4 = set to Man, receiv no

5 = set to Auto order no

6 = set to Auto YYMMDD seg

7 = set to Numbering rule

8 = set to Simple mand

9 = set to Simple optl

23) Active or catch weight item

The field indicates whether the item is active or catch weight item.

Set attribute listID to 'Active or Catch Weight Item'.

Alternatives:

0 = set to Normal item

1 = set to Active item

2 = set to Catch weight 1

3 = set to Catch weight 2

4 = set to Catch weight 3

24) Expiration date method

The field indicates how the expiration date is calculated.

Set attribute listID to 'Expiration Date Method'.

Alternatives:

0 = set to No expiry date

1 = set to Receiving date

2 = set to Production date

3 = set to Receiving date - update all warehouses

4 = set to Production date - update all warehouses

25) Sublot controlled

The field indicates if the item is sublot controlled.

Set attribute listID to 'Sublot Controlled'.

Alternatives:

0 = set to false

1 = set to true

26) Attribute managed

The field indicates whether the item is processed using attribute control.

Set attribute listID to 'Attribute Managed'.

Alternatives:

0 = set to No

1 = set to Yes, always dsp

2 = set to Yes, dsp stock rec

3 = set to Yes, only if error

27) Alias number

The field indicates the alias number depending on the alias category (ALWT) used.

Set attribute listID to 'Popular Number' if ALWT = 1.

Set attribute listID to 'Ref No - External Database' if ALWT = 3.

Set attribute listID to 'Assortment' if ALWT = 7.

Set attribute listID to 'EDI Partner's Item Number' if ALWT = 9.

28) Core terms

The field indicates the ID of the terms for the core return.

Set attribute listID to 'Core Terms'.

29) Exchangeable

The field indicates if the item is available as part of a core exchange program.

Set attribute listID to 'Exchangeable'.

Alternatives:

0 = false

1 = set to Supplier remanufacturing.

2 = set to Internal remanufacturing.

30) Core charge - item number

The field indicates the item used on the core charge line when entering customer orders.

Set attribute listID 'Core Charge Item Number'.

31) Core remanufacturing - item number

The field indicates the item used by default for a core return on Customer return module. This is used in the internal remanufacturing process when the core return is used as a raw material in the finished product. The item number used preferably has a prefix indicating its similarity to the other item in the same acceptance group. Set attribute listID 'Core Remanufacturing Item Number'.

32) Commodity class

The field indicates a rating that is assigned to products based on their value and shipping characteristics, such as density and how the freight is packaged. The commodity class is printed on the bill of lading documents for less than truckload shipments. Set attribute listID to 'Commodity Classes'.

33) UN number

The field indicates the identity/number of the item in question in the summary of the most common transported goods, prepared by the UN experts commission. The UN number is used for identification of transport documents.

Set attribute listID to 'UN Number'.

34) Danger class

The field indicates the danger class for the item and describes how the item is considered dangerous.

Set attribute listID to 'Danger Classes'.

35) Attribute Model

The field indicates the ID of an attribute model.

36) Inspection Point

The field indicates when the inspection must be done. In M3, the field is found inside the goods receiving method.

If value:

0 - set element to Never

1 - set element to Before put away

2 and 4 - set element to After put away

3 and 5 - set element to Receipt then QI Set attribute listID to 'Inspection Point'.

37) Inspection Code

The field indicates if item should be quality inspected. Set to true if value is not 0, otherewise, the element is set to false. Set attribute listID to 'Inspection Code'.

The field indicates the classification code sequence attribute. This is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in case of multi-level codes.

For Classification/Codes/Code = POPN with ALWT = 1 and 7 this element is mapped to MMS025MI.LstAlias SEQN. For the rest, the sequence number is auto-generated.

- 1) Set to 'Item Groups' if Classification/Codes/Code = ITGR.
- 2) Set to 'Product Groups' if Classification/Codes/Code = ITCL.
- 3) Set to 'Business Sectors' if Classification/Codes/Code = BUAR.
- 4) Set to 'Item Types' if Classification/Codes/Code = ITTY
- 5) Set to 'Item Classes' if Classification/Codes/Code = TPCD.
- 6) Set to 'Buying Groups' if Classification/Codes/Code = PRGP.
 7) Set to 'Item Rebate Groups if Classification/Codes/Code = DIGI.
- 8) Set to 'Configuration Code' if Classification/Codes/Code = CHCD.
- 9) Set to 'Configured Ruleset' if Classification/Codes/Code = RUID.
- 10) Set to 'Product Line' if Classification/Codes/Code = PDLN.
- 11) Set to 'Commodity Codes' if Classification/Codes/Code = CMMC.
- 12) Set to 'Styles' if Classification/Codes/Code = ITNO/HDPR/TPLI with CHCD = 2 or 3.
- 13) Set to 'Season Control' if Classification/Codes/Code = SECH.
- 14) Set to 'Item Hierarchy' if Classification/Codes/Code = HIE1-HIE5.
- 15) Set to 'Accounting Control Object' if Classification/Codes/Code = ACRF.
- 16) Set to 'Search Group' if Classification/Codes/Code = GRP1-

@sequence

MITPOP.MPSEQN; MMS025MI/LstAlias

@listID

ILEITIMASIEI	
	GRP5. 17) Set to 'Interface Item' if Classification/Codes/Code = IFIN. 18) Set to 'Quality Group' if Classification/Codes/Code = QMGP. 19) Set to 'Number of Price Decimal Places' if Classification/Codes/Code = PDCC. 20) Set to 'Sales Price' if Classification/Codes/Code = SAPR. 21) Set to 'Lot Control Method' if Classification/Codes/Code = INDI. 22) Set to 'Lot Numbering Method' if Classification/Codes/Code = BACD. 23) Set to 'Active or Catch Weight Item' if Classification/Codes/Code = ACTI. 24) Set to 'Expiration Date Method' if Classification/Codes/Code = EXPD. 25) Set to 'Sublot Controlled' if Classification/Codes/Code = SUME. 26) Set to 'Attribute Managed' if Classification/Codes/Code = ATMN. 27) Set to 'Popular Number' if Classification/Codes/Code = POPN and ALWT = 1. Set to 'Ref No - External Database' if Classification/Codes/Code = POPN and ALWT = 3. Set to 'Assortment' if Classification/Codes/Code = POPN and ALWT = 7.
	Set to 'EDI Partner's Item Number' if Classification/Codes/Code = POPN and ALWT = 9. 28) Set attribute listID to 'Core Terms' if Classification/Codes/Code = TECR. 29) Set attribute listID to 'Exchangeable' if Classification/Codes/Code = EXCA. 30) Set attribute listID 'Core Charge Item Number' if Classification/Codes/Code = CCI1. 31) Set attribute listID 'Core Remanufacturing Item Number' if Classification/Codes/Code = CRI1. 32) Set to 'Commodity Classes' if Classification/Codes/Code = CMLC. 33) Set to 'UN Number' if Classification/Codes/Code = HAZC. 35) Set to 'Attribute Model' if Classification/Codes/Code = ATMO.
ItemMaster/ItemMasterHeader/Classification/Description CSYTAB.CTTX40; CRS175MI/LstCodesByLng CRS175MI.GetGeneralCode.; /	The field indicates the classification code description. If Constant value (STCO) = CHCD: Set to 'Item is not configured' if CHCD = 0. Set to 'Item is configured if CHCD = 1. Set to 'Item is configured as a family item from which product variants with item numbers are created' if CHCD = 2. Set to 'Item is not configured, it is a product variant with the item number of the family item' if CHCD = 3. Set to 'Item is not configured, it is a maintenance item. Regulates the item costing' if CHCD = 4. Set to 'Item is not configured, it is a maintenance item. Possibility to answer inquiries to get a better maintenance order proposal' if CHCD = 5. The call to CRS175MI.LstCodesByLng is applicable only for fields ITGR, ITCL, BUAR and ITTY. The call to CRS175MI.GetGeneralCode is applicable only for fields
@languageID CYSTAB.CTLNCD ; CRS175MI/LstCodesByLng	The call to CRS175Mi.GetGeneralCode is applicable only for fields PRGP, DIGI and ACRF. The field indicates the classification code description language ID. The call to CRS175Mi.LstCodesByLng is applicable only for fields ITGR, ITCL, BUAR and ITTY.
ItemMaster/ItemMasterHeader/Specification/ID MTEINF.UICMFM : CMS474MI/LstUdefContent	The field indicates the CustomerFreeField field
ItemMaster/ItemMasterHeader/Specification/Property/NameValue MTEINF .UICMFA UICMFN	The field indicates the value of the CustomFreeField
UICMFD	

	The field indicates whether the item is hazardous. Set to 'true' if Danger indicator (HAZI) = 1. Otherwise, set to 'false'.
ItemMaster/ItemMasterHeader/HazardousMaterial/ID	and the second section of the second section for the second section se
MITMAS.MMITNO	The field indicates the item number which is tagged as hazardous
; MMS200MI/GetItmBasic	material (HAZI = 1). If HAZI = 0, this field is blank.
ItemMaster/ItemMasterHeader/Type MITMAS.MMTPCD; MMS200MI/CottlemPeoile	Set to 'MRO' if Item Category (TPCD) = 4, 5, 7.
MMS200MI/GetItmBasic MTEINF.UICFMF;	4 = Tool
CMS474MI/GetUdefContent	5 = Fixed machine
MTEINF.UICFMA; CMS474MI/GetUdefContent.; /	7 = Repairable item
OWO-7 HIVII/Getodelcontent., /	Set to 'MRO' regardless of the TPCD value if CMS474MI.GetUdefContent CFMF = EAMITEM and CFMA = Y.
ItemMaster/ItemMasterHeader/PackagingItem/PackagingCode MITAUN.PACT; MMS200MI/GetItmBasic @JistID	This field indicates the Alternative unit of measure packaging code
<u> </u>	Set to 'm3.AlternativeUnitOfMeasurePackagingCode'
ItemMaster/ItemMasterHeader/TrackingIndicator	The field in director and sale and a second bound for the ideas in
MITMAS.MMSTCD ; MMS200MI/GetItmBasic	The field indicates whether the stock kept for the item is accounted in inventory.
,	Set to 'true' if Inventory accounting (STCD) = 1. Otherwise, set to 'false'.
	0 = No.
	1 = Yes, the item is inventory accounted.
	2 = No, the item is not inventory accounted, but it is planned as demand in the material planning process in (MMS080 - Material Plan.
	Open).
	3 = No, the item is not inventory accounted, but it is planned as a
	function number. A function number is a dummy number for items that can replace each other. So material planning for the item is done
	on the function number level instead of the item level.
ItemMaster/ItemMasterHeader/ItemStatus/Code MITMAS.MMSTAT	The field indicates the item status.
; MMS200MI/GetItmBasic	Set to 'Pending' if Status (STAT) = 10, 15.
	Set to 'Open' if Status (STAT) = 20, 30, 40.
	Set to 'DoNotReorder' if Status (STAT) = 50. Set to 'Obsolete' if Status (STAT) = 80, 90.
	Set to 'Deleted' if Status (STAT) = 99.
	If item is deleted in MMS001, status is set to 'Deleted'.
ItemMaster/ItemMasterHeader/ItemStatus/Description	-
MITMAS.MMSTAT ; MMS200MI/GetItmBasic	The field indicates the item status description.
, MINIO200IMI/Gettinbasic	Set to 'Preliminary Item' if Status (STAT) = 10.
	Set to 'Replacement Item' if Status (STAT) = 15. Set to 'Released Item' if Status (STAT) = 20.
	Set to 'Alternate Items Available' if Status (STAT) = 30.
	Set to 'Low Turnover Item' if Status (STAT) = 40.
	Set to 'Discontinued Item' if Status (STAT) = 50 Set to 'Not Carried' if Status (STAT) = 80.
	Set to 'No Longer Stocked' if Status (STAT) = 90.
Was the state of t	Set to 'Item Number Changed' if Status (STAT) = 99.
ItemMaster/ItemMasterHeader/BaseUOMCode MITMAS.MMUNMS	The field indicates the unit in which each item is recorded in
; MMS200MI/GetItmBasic	inventory, even if alternate inventory units of measure are used. All
	balance information for the current item is always stored in this unit.
ItemMaster/ItemMasterHeader/BaseUOMPrecision MITMAS.MMDCCD	The field indicates how many decimal places are to be used in
; MMS200MI/GetItmBasic	connection with processing quantities.
, MINIOZUUMI/GETTIIIDASIC	DCCD = 0 will be displayed as 0.
	DCCD = 1 will be displayed as 0.1. DCCD = 2 will be displayed as 0.01.
	DCCD = 2 will be displayed as 0.01. DCCD = 3 will be displayed as 0.001.
	DCCD = 4 will be displayed as 0.0001.
	DCCD = 5 will be displayed as 0.00001.
ItemMaster/ItemMasterHeader/StorageUOMCode	
ItemMaster/ItemMasterHeader/StorageUOMCode MITMAS.MMUNMS	DCCD = 5 will be displayed as 0.00001. DCCD = 6 will be displayed as 0.000001. The field indicates the unit in which each item is recorded in
	DCCD = 5 will be displayed as 0.00001. DCCD = 6 will be displayed as 0.000001. The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All
MITMAS.MMUNMS	DCCD = 5 will be displayed as 0.00001. DCCD = 6 will be displayed as 0.000001. The field indicates the unit in which each item is recorded in

ItemMaster/ItemMasterHeader/SalesUOMCode MITMAS.MMALUN; MMS200MI/GetItmBasic	The field indicates the default unit of measure when the item is picked up for sales.
ItemMaster/ItemMasterHeader/SalesPriceUOMCode MITMAS.MMSPUN; MMS200MI/GetItmBasic	The field indicates the sales price unit of measure. This is the unit of measure on which the item price is based.
ItemMaster/ItemMasterHeader/LastModificationDateTime MITMAS.MMLMTS :/	The field indicates the date and time the object was last modified.
ItemMaster/ItemMasterHeader/AlternateUOMCode MITAUN.MUALUN	The field indicates the alternate unit of measure.
; MMS200MI/LstltmAltUnitMs	Display if Alternate U/M type (AUTP) = 1 (Alternate quantity U/M).
@listID MITAUN.MUAUSC MULGUN ; MMS200MI MMS200MI/LstItmAltUnitMs LstItmAltUnitMS	if AUSC = 1 set to 'm3.CatchWeightStandardUnitOfMeasure' if LGUN = 1 set to 'm3.LogisticUnitOfMeasure'
ItemMaster/ItemMasterHeader/AlternateUOM/UOMCode MITAUN.MUALUN ; MMS200MI/LstItmAltUnitMs	The field indicates the alternate unit of measure.
@listID	Display if Alternate U/M type (AUTP) = 1 (Alternate quantity U/M).
MITAUN.MUAUSC MULGUN ; MMS200MI MMS200MI/LstltmAltUnitMs LstltmAltUnitMS	if AUSC = 1 set to 'Catch Weigt Standard UOM' if LGUN = 1 set to 'Logistic UOM'
ItemMaster/ItemMasterHeader/AlternateUOM/UOMPrecision MITAUN.MUDCCD; MMS200MI/LstltmAltUnitMs	The field indicates how many decimal places are to be used in connection with processing quantities. DCCD = 0 will be displayed as 0. DCCD = 1 will be displayed as 0.1. DCCD = 2 will be displayed as 0.01. DCCD = 3 will be displayed as 0.001. DCCD = 4 will be displayed as 0.0001. DCCD = 5 will be displayed as 0.00001. DCCD = 6 will be displayed as 0.00001.
ItemMaster/ItemMasterHeader/UOMCodeConversion/FromUOMPacket MITMAS.MMUNMS ; MMS200MI/GetItmBasic	age/UOMCode The field indicates the basic unit of measure. +Al694
ItemMaster/ItemMasterHeader/UOMCodeConversion/RateNumeric MITAUN.MUCOFA ; MMS200MI/LstItmAltUnitMs	The field indicates a factor that is used to convert a basic U/M to an alternate U/M.
ItemMaster/ItemMasterHeader/UOMCodeConversion/ToUOMPackage MITAUN.MUALUN ; MMS200MI/LstltmAltUnitMs	Display if Alternate U/M type (AUTP) = 1 (Alternate quantity U/M). a/UOMCode The field indicates an alternate unit of measure (U/M) for the basic U/M for an item.
, MINI-0200MI/LStittinAitOffitivis	Display if Alternate U/M type (AUTP) = 1 (Alternate quantity U/M).
ItemMaster/ItemMasterHeader/SerialControlIndicator MITMAS.MMINDI ; MMS200MI/GetItmBasic	The field indicates if and how serial control is to be applied for each item.
	Set to 'false' if Lot control method (INDI) = 0, 1, 3. Set to 'true' if Lot control method (INDI) = 2, 5.
ItemMaster/ItemMasterHeader/LotControlIndicator MITMAS.MMINDI ; MMS200MI/GetItmBasic	The field indicates if and how lot control is to be applied for each item.
	Set to 'false' if Lot control method (INDI) = 0. Set to 'true' if Lot control method (INDI) = 1, 2, 3, 5.
ItemMaster/ItemMasterHeader/ConfiguredItemIndicator MITMAS.MMCHCD ; MMS200MI/GetItmBasic	The field indicates if the item is configured when ordered or configured as a maintenance item.
	Set to 'false' if Configuration code (CHCD) = 0, 3, 4, 5. Set to 'true' if Configuration code (CHCD) = 1, 2.
ItemMaster/ItemMasterHeader/ConfiguratorRuleModel MITMAS.MMRUID; MMS200MI/GetItmBasic	The field indicates the identification of the ruleset in PCM (Product Configuration Management) to use when the product is configured. Set attribute listID to 'Configured Ruleset'.

ItemMaster/ItemMasterHeader/CatchWeightIndicator

MITMAS.MMACTI ; MMS200MI/GetItmBasic The field indicates whether this is a catch weight item.

Set to "false" if Active or catch weight item (ACTI) = 0, 1. Set to "true" if Active or catch weight item (ACTI) = 2, 3, 4.

ItemMaster/ItemMasterHeader/AuxiliaryQuantityIndicator

MITMAS.MMCWUN; MMS200MI/GetItmBasic

If field CWUN not empty set to 'true'

ItemMaster/ItemMasterHeader/AuxiliaryQuantitySpecification/AuxiliaryUOMCode

MITMAS.MMALUN; MMS200MI/GetItmBasic @listID

The field Indficates the CatchWeight std unit of measure code

If field CWUN not empty set to 'm3.CatchWeightUnitOfMeasure'

ItemMaster/ItemMasterHeader/UserArea

1) MITMAS.MMCHCD; MMS200MI/GetItmBasic

2) MITMAH.HMOPTX MITMAH.HMOPTY MITMAH.HMOPTZ; MMS019MI/Get

3) MITMAH.HMSQNX MITMAH.HMSQNY MITMAH.HMSQNZ; MMS019MI/Get

4) MITMAH.HMTX15 MITMAH.HMTY15 MITMAH.HMTZ15 MMS019MI/Get

5) MMODFE.HUFTID; MMS017MI/List MITMAH.HMFTIX MITMAH.HMFTIY MITMAH.HMFTIZ; MMS019MI/Get

6) MPDFHE.PETX30 MMS017MI/List

7) MITMAS.MMCFI1-MMCFI5; MMS200MI/GetItmBasic

8) MMODMA.HHFM01-HHFM20; MMS016MI/Get

9) MTEINF.UICFMA; CMS474MI/GetUdefContent

10) MITMAS.MMQACD; MMS200MI/GetItmBasic

11) MITMAS.MMFRE3; MMS200MI/GetItmPrice

12) MITMAS.MMFRE4; MMS200MI/GetItmPrice 13) MITTRS.MTA001 - MITTRS.MTA001; MWS001MI/GetItem.; / The field indicates additional information that is not captured in OAGIS. The information are defined in UserArea/Property which are determined by different name attributes.

This is used to identify if the Item is Style or SKU with their corresponding details such as feature, options and option sequence number.

1) The field indicates if the item is a style or SKU. Set NameValue = Style if Configuration code (CHCD) = 2. Set NameValue = SKU if Configuration code (CHCD) = 3. Set @name='StyleItemType'.

2) The field indicates the option.

Set @name='StyleOptionX' if NameValue = OPTX. Set @name='StyleOptionY' if NameValue = OPTY. Set @name='StyleOptionZ' if NameValue = OPTZ.

3) The field indicates the option sequence number. Set @name='StyleOptionXSequence' if NameValue = SQNX. Set @name='StyleOptionYSequence' if NameValue = SQNY. Set @name='StyleOptionZSequence' if NameValue = SQNZ.

4) The field indicates the option description. Set Description = TX15 if NameValue = OPTX. Set Description = TY15 if NameValue = OPTY. Set Description = TZ15 if NameValue = OPTZ.

5) The field indicates the feature.

Set @name='StyleFeatureX' if Feature group (FGRP) = X or NameValue = FTIX.

Set @name='StyleFeatureY' if Feature group (FGRP) = Y or NameValue = FTIY.

Set @name='StyleFeatureZ' if Feature group (FGRP) = Z or NameValue = FTIZ.
Set @listID='Style Features'.

6) The field indicates the feature description.

7) The field indicates user-defined field for the item. Set @name='ItemFreeField1'-'ItemFreeField5' if NameValue = CFI1-CFI5.

8) The field indicates freely defined style information. Set @name='StyleFreeField1' - 'StyleFreeField20' if NameValue = FM01-FM20.

9) The field indicates a custom field to determine if the item is to be consumed by EAM or not.

Use the following input values:

ITNO = <ITNO> UDFT = 1 CFMG = BOD CFMF = EAMItem

If CFMA = Y, set to true. Otherwise, set to false.

The field indicates if the item should be quality inspected.
 @name="eam.InspectionRequiredIndicator" if NameValue = QACD.

If QACD = 0, set to false. Otherwise, set to true.

11) The field indicates item statistics field, which can be used for accumulation of sales statistics information for an item.

Set @name='m3.ltemStatisticsIdentity3' if NameValue = FRE3.

	12) The field indicates item statistics field, which can be used for accumulation of sales statistics information for an item. Set @name='m3.ItemStatisticsIdentity4' if NameValue = FRE4.
	13) The field indicates the transportation information user-defined fields.
	Set @name='m3.TransportData1' to 'm3.TransportData5'.
ItemMaster/ItemMasterHeader/SellableIndicator MITMAS.MMSALE ; MMS200MI/GetItmBasic	The field indicates if the item is a sales item. Set to 'false' if Sales item (SALE) = 0. Set to 'true' if Sales item (SALE) = 1, 2.
	 0 = No, customer orders/service orders may not be entered. 1 = Yes, customer orders/service orders may be entered. 2 = Yes, but customer orders/service orders may only be entered if the item is a component in a KIT.
ItemMaster/ItemMasterHeader/PackagingUnit/ID MITAUN.M9PACT; MMS200MI/LstItmAltUnitsMS	This represent the packaging code
ItemMaster/ItemMasterHeader/PackagingUnit/UnitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the packaging unit of measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/WidthMeas	
MITMAS.MMIWID ; MMS200MI/GetItmBasic @unitCode	The field indicates the item width.
CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for width. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/LengthMeadITMAS.MMILEN ; MMS200MI/GetItmBasic @unitCode	asure The field indicates the item length.
CSYPAR.CPPARM : CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for length. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/HeightMea MITMAS.MMIHEI ; MMS200MI/GetItmBasic	· -
@unitCode CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for height. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/NetWeightMeasure MITMAS.MMNEWE ; MMS200MI/GetItmTech @unitCode	The field indicates the item net weight per basic U/M.
CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for weights. It is stored in M3 BE, program CRS703 General Units of Measure.
ItemMaster/ItemMasterHeader/PackagingUnit/GrossWeightMeasure	
MITMAS.MMGRWE ; MMS200MI/GetltmTech	The field indicates the item weight per basic U/M including the weight of any product packaging material.
	The information is used when creating packages for transportation purposes, and should not include the transportation packaging material such as transportation boxes, pallets, containers etc.
@unitCode CSYPAR.CPPARM	The field indicates the general unit of measure for weights.
; CRS175MI/GetItemFreeFlds	It is stored in M3 BE, program CRS703 General Units of Measure.
<pre>ItemMaster/ItemMasterHeader/PackagingUnit/TotalVolumeMeasure MITMAS.MMVOL3 ; MMS200MI/GetItmTech</pre>	The field indicates the item volume per basic U/M including any product packaging material.
@unitCode CSYPAR.CPPARM	The field indicates the general unit of measure for volumes.
; CRS175MI/GetItemFreeFlds ItemMaster/ItemMasterHeader/ProcurementParameters/Procurement	It is stored in M3 BE, program CRS703 General Units of Measure.
MITMAS.MMMABU; MMS200MI/GetItmBasic	The field indicates whether the item is manufactured in-house or purchased. Set to 'Manufacture' if Make/by code (MABU) = 1
	Set to 'Maridiacture' ir Make/by code (MABO) = 1 Set to 'Purchase' if Make/by code (MABU) = 2
ItemMaster/ItemMasterHeader/SupplierItemSpecifics/SupplierParty/F 1) MITMAS.MMSUNO; MMS200MI/GetItmPrice	
2) MITVEN.IFSUNO ; PPS040MI.LstItemSupplier.; /	The field indicates the supplier number for the item/supplier combination.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab,

	this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ItemMaster/ItemMasterHeader/SupplierItemSpecifics/UserArea	, , , , , , , , , , , , , , , , , , ,
1) MITVEN.IFUCA1 ; PPS040MI/LstItemSupplier	The field indicates additional information that is not captured in OAGIS. The information are defined in UserArea/Property which are determined by different name attributes.
2) MITVEN.IFUCA2 ; PPS040MI/LstItemSupplier	This is used to identify the data for a specific supplier and item
3) MITVEN.IFUCA3 ; PPS040MI/LstItemSupplier	combination. 1) The field indicates a user defined field 1. Set @name to 'UserDefinedField1'.
4) MITVEN.IFUCA4 ; PPS040MI/LstItemSupplier	The field indicates a user defined field 2. Set @name to 'UserDefinedField2'.
5) MITVEN.IFUDN1 ; PPS040MI/LstItemSupplier	The field indicates a user defined field 3. Set @name to 'UserDefinedField3'.
6) MITVEN.IFUCU1; PPS040MI/LstItemSupplier.; /	The field indicates a user defined field 4. Set @name to 'UserDefinedField4'.
	5) The field indicates a user defined numeric 1. Set @name to 'UserDefinedNumeric1'.
	6) The field indicates a user defined unit 1. Set @name to 'UserDefinedUnit1'.
	7) The field indicates the item supplier connection indicator. Set NameValue to 'true' if supplier is from PPS040, Otherwise, set to 'false' if supplier is from MMS001/H. Set @name to 'SupplierItemConnectIndicator'.
ItemMaster/ItemMasterHeader/Supercedes/Components/ItemID/ID MITALT.MAALIT; MITALT/LstItemRelation	The field indicates the related item number.
	Display if Replacement type (RPTY) is 1 (Complete replacement), 2 (Replaced) or 8 (Replaced).
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ItemMaster/ItemMasterHeader/Supercedes/Components/Note MITALT.MACNDN; MITALT/LstItemRelation	The field indicates the conditions for the replacement.
	Display if Replacement type (RPTY) is 1 (Complete replacement) or 2 (Replaced).
@type	Set to 'Condition'
ItemMaster/ItemMasterHeader/Substitutions	
@EffectiveDateTime MITALT.MASTDT ; MMS020MI/LstItemRelation	The field indicates the start date when the substitution becomes valid.
@Туре	Set to 'InterchangeableWithRestrictions' if Replacement type (RPTY) is 3.
	Set to 'FullyInterchangeable' if Replacement type (RPTY) is 4.
ItemMaster/ItemMasterHeader/Substitutions/Components/ItemID MITALT.MAALIT ; MMS020MI/LstItemRelation	The field indicates a related item. A related item can replace an item that is out of stock or has been deleted.
	Display if Replacement type (RPTY) is 3 (Interchangeable with restrictions) or 4 (Fully interchangeable).
ItemMaster/ItemMasterHeader/Substitutions/Components/ItemID/ID	, , , , , , , , , , , , , , , , , , , ,
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ItemMaster/ItemMasterHeader/AddOns/ItemID/ID MITALT.MAALIT; MMS020MI/LstItemRelation	The field indicates th related item.
@accountingEntity	Display if Replacement type (RPTY) is 7 (Accessory) or 9 (Upselling).
MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

ItemMaster/ItemLocation/Classification @type

ItemMaster/ItemLocation/Classification/Codes/Code

- 1) MITBAL.MBABCD; MMS200MI/GetItmWhsBasic
- 2) MITFAC.MPORCO; MMS200MI/GetItmFac
- 3) MITBAL.MBRESP; MMS200MI/GetItmWhsBasic
- 4) MITBAL.MBBUYE; MMS200MI/GetItmWhsBasic
- 5) MITFAC.M9CSNO; MMS200MI/GetItmFac
- 6) MITWHL.MWCSCD; MMS200MI/SelltemWhsByltm
- 7) MITBAL.MBSUNO; MMS200MI/GetItmWhsBasic
- 8) MITBAL.MBWHSL; MMS200MI/GetItmWhsBasic
- 9) MITBAL.MBDPLO; MMS200MI/GetItmWhsBasic
- 10) MITBAL.MBDDLO; MMS200MI/GetItmWhsBasic
- 11) MITBAL.MBCOMG; MMS200MI/GetItmWhsBasic
- 12) MITFAC.M9ALTS; MMS200MI/GetItmFac
- 13) MITBAL.MBIPLA; MMS200MI/GetItmWhsBasic
- 14) MITBAL.MBVTCS; MMS200MI/GetItmWhsBasic
- 15) MITBAL.MBSAEL; MMS200MI/GetItmWhsBasic .:/

Set to 'Customs Statistical Number' if Classification/Codes/Code@listID is 'Customs Statistical Number' and 'Countries'.

The field indicates the classification code in the item location level.

1) ABC Code

The field indicates a code, usually A, B or C, used to group items according to how they affect the total sales volume. Set attribute listID to 'ABC Codes'.

2) Country of Origin

The field indicates the item's country of origin. Set attribute listID to 'Country Of Origin'.

3) Responsible

The field indicates the person responsible for acquisition of each item. Set attribute listID to 'Planner'.

4) Buyer

The field indicates the buyer normally responsible for purchasing. Set attribute listID to 'Buyer'.

5) Customs statistical number

The field indicates the customs statistics number, which is specified for each item/facility. It is used in printouts of various shipping documents, such as the unit document. It is also used for regulating and calculating data for transactions to INTRASTAT, the trade statistics of the EU. This is also known as the HTS code. Set attribute listID to 'Customs Statistical Number'.

6) Country

The field indicates the country of the warehouse. Set attribute listID to 'Countries'.

7) Supplier

The field indicates the supplier considered as the main supplier for the item.

Set attribute listID to 'Supplier'.

8) Location

The field indicates the default location that is proposed upon receipt, issue etc.

Set attribute listID to 'Location'.

9) Pack location

The field indicates the location normally used for packing operations. Set attribute listID to 'Pack Location'.

10) Dock location

The field indicates the location normal docking location used for packaged goods ready to be shipped.

Set attribute listID to 'Dock Location'.

11) Container management

The field indicates how containers are managed.

Set attribute listID to 'Container Management'.

Alternatives:

0 = Not used

1 = Used. No verf

2 = Used. Verf

3 = Used. Verf, lot

4 = As 1 + one loc 5 = As 2 + one loc

6 = As 3 + one loc

7 = Container for packages

12) Alternate structure

The field indicates if alternate structures may be created for the item in PDS023.

Set @listID to 'Alternate Structure'.

If ALTS = 1, set to true. Otherwise, set to false.

13) Inventory Planned

The field indicates if an item should be considered as not stocked or stocked.

Set attribute listID to 'Inventory Planned'.

itemwaster	
	Alternatives: [Blank] = Not used 10 = Not stocked 20 = To be stocked 30 = Stocked
	14) Sales VAT code The field indicates the VAT code to be used for sold items. Set attribute listID to 'Sales VAT Code'.
@sequence	15) Sales TIme The field indicates the standard number of days from the production date to the last sales date.
;, <i>I</i>	The field indicates the classification sequence attribute. This is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in the case of multi-level codes.
@listID .; /	 Set to 'ABC Codes' if Classification/Codes/Code = ABCD. Set to 'Country Of Origin' if Classification/Codes/Code = ORCO. Set to 'Planner' if Classification/Codes/Code = RESP. Set to 'Buyer' if Classification/Codes/Code = BUYE. Set to 'Customs Statistical Number' if Classification/Codes/Code = CSNO.
	 6) Set to 'Countries' if Classification/Codes/Code = CSCD. 7) Set to 'Supplier' if Classification/Codes/Code = SUNO. 8) Set to 'Location' if Classification/Codes/Code = WHSL. 9) Set to 'Pack Location' if Classification/Codes/Code = DPLO. 10) Set to 'Dock Location' if Classification/Codes/Code = DDLO. 11) Set to 'Container Management' if Classification/Codes/Code = COMG. 12) Set to 'Alternate Structure' if Classification/Codes/Code = ALTS. 13) Set to 'Inventory Planned' if Classification/Codes/Code = IPLA. 14) Set to 'Sales VAT Code' if Classification/Codes/Code = SAEL. 15) Set to 'Sales Time' if if Classification/Codes/Code = SAEL.
ItemMaster/ItemLocation/Classification/Description	T. 6.11: E. A. H. 1: E. C. 1: C.
CSYTAB.CTTX40 ; CRS175MI/GetGeneralCode	The field indicates the classification description. The call to CRS175Ml.GetGeneralCode is applicable only for fields
ItemMaster/ItemLocation/MaximumLotSizeBaseUOMQuantity MITBAL.MBMOQT ; MMS200MI/GetItmWhsBasic	ABCD and ORCO. The field indicates the maximum order quantity, which is the maximum allowed order quantity for each combination of item/ warehouse.
	The information is used at calculation of batch size in connection with requirement calculation.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the maximum lot size basic unit of measure.
ItemMaster/ItemLocation/MinimumLotSizeBaseUOMQuantity MITBAL.MBLOQT ; MMS200MI/GetltmWhsBasic	The field indicates minimum order quantity, which is the minimum order quantity allowed for each combination of item/warehouse.
0. 110	The information is used at calculation of batch size in connection with requirements calculation, but only if it is greater than zero.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the minimum lot size basic unit of measure.
ItemMaster/ItemLocation/LotSizeMultipler MITBAL.MBUNMU; MMS200MI/GetItmWhsBasic	The field indicates the order multiple quantity. It is used in order to avoid the need to break up packages.
ItemMaster/ItemLocation/LeadTimeDuration MITBAL.MBLEAT ; MMS200MI/GetItmWhsBasic	The field indicates the lead time for each item. This is the time required to meet a requirement from the time acquisition activities are started to the time the requirement is fulfilled.
ItemMaster/ItemLocation/QualityInspectionLeadTimeDuration MITBAL.MBLEA2 ; MMS200MI/GetItmWhsBasic	The field indicates the time normally required for goods receipt, quality inspection and put-away. Inspection lead time is not allowed for direct put-away. It is mainly used for purchased items and is thus always entered via the current goods receiving method.
ItemMaster/ItemLocation/ItemStatus/Code MITBAL.MBSTAT ; MMS200MI/GetItmWhsBasic	The field indicates the item-warehouse status. This is the status that the system verifies for transactions.
	Set to 'Pending' if Status (STAT) = 10. Set to 'Open' if Status (STAT) = 20.
Infor May 26	

Infor May 26, 2023 25.

ItemMaster

	Set to 'DoNotReorder' if Status (STAT) = 50. Set to 'Obsolete' if Status (STAT) = 80, 90.
ItemMaster/ItemLocation/ItemStatus/Description MITBAL.MBSTAT	The field indicates the item-warehouse status description.
; MMS200MI/GetItmWhsBasic	Set to 'Preliminary Item' if Status (STAT) = 10. Set to 'Released Item' if Status (STAT) = 20. Set to 'Discontinued Item' if Status (STAT) = 50. Set to 'Not Carried' if Status (STAT) = 80. Set to 'No Longer Stocked' if Status (STAT) = 90.
ItemMaster/ItemLocation/ItemValue/UnitValue/Amount 1) MITFAC.M9UCOS; MMS200MI/GetItmFac	The field indicates the monetary value of the item.
2) MITFAC.M9AAPR; MMS200MI/GetItmFac.; /	 Standard cost The field indicates the standard cost expressed in the item cost quantity, calculated per item/facility.
	2) Average cost The field indicates the average cost saved per item/facility in the local currency. The average cost is the cost of items issued from stock. This cost is calculated using the moving weighted average cost method.
@currencyID CMNDIV.CCLOCD ; MNS100MI/GetBasicData	The field indicates the unit value currency ID.
ItemMaster/ItemLocation/ItemValue/UnitValue/BaseAmount 1) MITFAC.M9UCOS MMS200MI/GetItmFac	The field indicates the monetary amount used for consolidation at the company/division level.
2) MITFAC.M9AAPR MMS200MI/GetItmFac.; /	Standard cost The field indicates the standard cost expressed in the item cost quantity, calculated per item/facility.
	2) Average cost The field indicates the average cost saved per item/facility in the local currency. The average cost is the cost of items issued from stock. This cost is calculated using the moving weighted average cost method. It is updated using the acquisition cost for each positive inventory transaction in M3.
@currencyID CMNDIV.CCLOCD ; MNS100MI/GetBasicData	The field indicates the unit value currency ID.
ItemMaster/ItemLocation/ItemValue/UnitValue/PerQuantity MITFAC.M9COCD ; MMS200MI/GetItmFac	The field indicates the default item cost quantity per item/facility. The item cost quantity is always entered in the basic unit of measure of the item.
@unitCode MITMAS.MMCPUN ; MMS200MI/GetItmBasic	The field indicates the per quantity unit of measure.
ItemMaster/ItemLocation/ItemValue/CostingMethodCode MITFAC.M9VAMT ; MMS200MI/GetItmFac	The field indicates the inventory accounting method that defines how the cost of an item is determined per item/facility.
@liatD	Set to 'Standard' if Inventory accounting method (VAMT) = 1. Set to 'WeightedAverage' if Inventory accounting method (VAMT) = 2.
@listID .; /	Set to 'Costing Methods' if Inventory accounting method (VAMT) = 1 or 2.
ItemMaster/ItemLocation/UserArea MITBAL MITWHL.MBWHSL MBSAEL ; MMS200MI MMS200MI/GetItmWhsBasic GetItmWhsBasic	1.The field indicates the default location that is proposed upon receipt, issue, etc. Set attribute name to 'eam.DefaultBin' if NameValue = Location (WHSL). 2.The field indicates the number of days from Production date to the last Sales date. NameValue = WBSAEL name = 'Sales time in days'
ItemMaster/ItemLocation/ShelfLifeDuration MITBAL.MBSLDY ; MMS200MI/GetItmWhsBasic	The field indicates the number of days shelf life for a lot or serial number measured from the production date to expiration date.
ItemMaster/ItemLocation/WarehouseLocation/ID MITBAL.MBWHLO ; MMS200MI/SelltemWhsByltm	The field indicates the warehouse.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO_DIVI).

ItemMaster

ItemMaster/ItemLocation/WarehouseLocation/Name MITWHL.MWWHNM ; MMS200MI/GetItmWhsBasic	The field indicates the warehouse name.
temMaster/ItemLocation/Location @type	
	Set to 'Site'.
temMaster/ItemLocation/Location/ID MITBAL.MBFACI; MM200MI/SelltemWhsByItm	The field indicates the facility.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.: /	The field indicates the accounting entity. This is displayed as Company and Division (CONO DIVI).
temMaster/ItemLocation/Location/Description	
CFACIL.CFFACN; MMS200MI/GetItmFac	The field indicates the facility name.
ItemMaster/ItemLocation/ProcurementParameters/ProcurementMet MITBAL.MBPUIT; MMS200MI/GetItmWhsBasic	The field indicates how acquisition is performed for requirements (immediate or planned) for each item/warehouse.
	Set to 'Manufacture' if Acquisition code (PUIT) = 1. Set to 'Purchase' Acquisition code (PUIT) = 2. Set to 'Transfer' Acquisition code (PUIT) = 3. Set to 'Maintenance' Acquisition code (PUIT) = 6.
temMaster/ItemLocation/ProcurementParameters/OrderPointQuanti	ty
MITBAL.MBREOP; MMS200MI/GetItmWhsBasic @unitCode	The field indicates the reorder point. When the on-hand balance is equal to or below the level displayed in this element, a planned order is automatically created.
MITMAS.MMUNMS : MMS200MI/GetItmBasic	The field indicates the reorder point unit of measure.
temMaster/ItemLocation/ProcurementParameters/OrderPointBaseU	OMQuantity
MITBAL.MBREOP; MMS200MI/GetItmWhsBasic	The field indicates the reorder point. When the on-hand balance is equal to or below the level displayed in this element, a planned order is automatically created.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the reorder point unit of measure.
temMaster/ItemLocation/ProcurementParameters/SafetyStockQuan	titv
MITBAL.MBSSQT; MMS200MI/GetItmWhsBasic	The field indicates the safety stock. This is a buffer quantity which is only used during unexpected circumstances such as increased demand, difficulties in delivery, etc.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the safety stock unit of measure.
temMaster/ItemLocation/ProcurementParameters/SafetyStockBase	JOMQuantity
MITBAL.MBSSQT; MMS200MI/GetItmWhsBasic	The field indicates the safety stock. This is a buffer quantity which is only used during unexpected circumstances such as increased demand, difficulties in delivery, etc.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the safety stock unit of measure.
ItemMaster/ItemLocation/ProcurementParameters/EOQQuantity MITBAL.MBEOQT; MMS200MI/GetItmWhsBasic	The field indicates the Economic Order Quantity (EOQ). It is a type of fixed-order quantity that determines the amount of an item to be purchased or manufactured at one time.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the EOQ unit of measure.
temMaster/ItemLocation/ProcurementParameters/EOQBaseUOMQu	antity
MITBAL.MBEOQT; MMS200MI/GetItmWhsBasic	The field indicates the Economic Order Quantity (EOQ). It is a type of fixed-order quantity that determines the amount of an item to be purchased or manufactured at one time.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the Economic Order Quantity (EOQ) unit of measure.
temMaster/ItemLocation/SupplierItemSpecifics/SupplierParty/Partyl	
MITBAL.MBSUNO; MMS200MI/GetItmWhsBasic	The field indicates the supplier number.
@accountingEntity MITMAS.MMCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
	. , , , , , , , , , , , , , , , , , , ,

ItemMaster

Iterrivaster	
; MMS200MI/GetItmWhsBasic	The field indicates minimum order quantity, which is the minimum order quantity allowed for each combination of item/warehouse.
	The information is used at calculation of batch size in connection with requirements calculation, but only if it is greater than zero.
@unitCode	
MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the minimum lot size unit of measure.
ItemMaster/ItemLocation/SalesParameters/OrderIncrementQuantity	
MITBAL.MBTOMU; MMS200MI/GetItmWhsBasic	The field indicates the quantity by which an order can be increased.
@unitCode	
MITMAS.MMUNMS	The field indicates the issue multiple unit of measure.
; MMS200MI/GetItmBasic	

LCLTaxReport/TaxReportHeader/DocumentID/ID	
For Supplier Tax: FTAXR1.R1JBNO, R1JBDT, R1JBTM; APS430MI/GetTaxHead	For Supplier Tax: The field indicates the Job number (JBNO), date (JBDT and time (JBTM) from tax report header (or MBM event data) concatenated without space or separator.
	For VAT Periodic: The field indicates the VAT run number (VRUN) from MBM event data.
@accountingEntity For Supplier Tax:; -/-	For Supplier Tax: The field indicates the Accounting entity.
@variationID	For VAT Periodic: The field indicates the Company/Division from MBM event data.
For Supplier Tax:; -/-	For Supplier Tax: The field indicates the Variation ID.
@lid	For VAT Periodic: The field indicates the variationId.
For Supplier Tax:; -/-	For Supplier Tax: The field indicates the Logical ID.
	For VAT Periodic: The field indicates the automatic generation of ID from the system.
LCLTaxReport/TaxReportHeader/DisplayID	5 0 " T
For Supplier Tax: FTAXR1.R1JBNO, R1JBDT, R1JBTM; APS430MI/GetTaxHead	For Supplier Tax: The field indicates the Job number (JBNO), date (JBDT and time (JBTM) from tax report header (or MBM event data).
For VAT Periodic: FVATHE.VHVERN; TXS100MI/GetHeadInfo	For VAT Periodic: The field indicates the VAT electronic report number (VERN)
LCLTaxReport/TaxReportHeader/DocumentDateTime	
For Supplier Tax: FTAXR1.R1TODT; APS430MI/GetTaxHead	For Supplier Tax: The field indicates the Tax order date (TODT) entered when proposal created.
For VAT Periodic: FVATHE.VHERCD; TXS100MI/GetHeadInfo	For VAT Periodic: The field indicates the Reporting date (ERCD) from report header.
LCLTaxReport/TaxReportHeader/Description	
For Supplier Tax: FTAXR1.R1LITX, R1RMDS; APS430MI/GetTaxHead	For Supplier Tax: The field indicates the Report text (LITX) if not blank or the Name (RMDS) entered when proposal created.
	The information can be used as additional detection value in case different message formats are used for the same country.
	For VAT Periodic: The field indicates the Report template (VRTM) from MBM event data
LCLTaxReport/TaxReportHeader/Status/Code FQRADF.EAESFV; TXS035MI/GetAddField	For Supplier Tax: Set to "Open" or "Draft" depending on if a Productive or Test report is
	sent: - If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 1:
	"Draft". - If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 0 or if (ESAF) 522 is missing or other value: "Open"
	(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD.
	For VAT Periodic: Set to "Open" or "Draft" depending on if a Productive or Test report is
	sent: - If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 1: "Draft". If additional field (ESAF) = 523 exists (*) and value (ESFV) set to 0.
	- If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 0 or if (ESAF) 522 is missing or contains other value: "Open"
	(*) Value in TXS035 for type (TYPE) = 2 and base country (FBSC)
LOLT Deposit To-Deposit Local CERT Collection To the Collection CERT COLLec	from report header.
LCLTaxReport/TaxReportHeader/EffectiveTimePeriod/StartDateTime For VAT Periodic: FVATRH.RHFVTD; TXS100MI/GetHeadInfo	from report header.

For VAT Periodic

FVATRH.RHTVTD; TXS100MI/GetHeadInfo

LCLTaxReport/TaxReportHeader/InitiatingParty/PartyIDs/ID

For Supplier Tax:

FTAXR1.R1CONO, R1DIVI; APS430MI/GetTaxHead

For VAT Periodic:

FQRADF.EAESFV; TXS035MI/GetAddField

@accountingEntity

For Supplier Tax:

-.-; -/-

LCLTaxReport/TaxReportHeader/InitiatingParty/PartyIDs/TaxID

For Supplier Tax:

CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2

FQRADF.EAESFV.-; MNS100MI

TXS035MI/GetBasicData

GetAddField

For VAT Periodic: FQRADF.EAESFV FVATHE.VHOVRN

; TXS035MI or TXS100MI/GetAddField or

GetHeadInfo

@schemeName

For Supplier Tax:

-.-: -/-

LCLTaxReport/TaxReportHeader/InitiatingParty/Name

For Supplier Tax:

CMNDIV.CCCONM, CCCOA1-COA4; MNS100MI/GetBasicData

For VAT Periodic:

FVATHE.VHCONM; TXS100MI/GetHeadInfo

For VAT Periodic:

The field indicates the VAT date - To (TVTD) from report header.

For Supplier Tax:

The field indicates the Company and division concatenated without space or separator.

For VAT Periodic:

The field indicates the ID (external or internal) of the initiating party: - If report field (ESAF) = 514 for the base country (FBSC) in report header and type (TYPE) = 2 exist: External ID from (ESFV) in)TXS035) and if not existing:

- Internal ID - Company (CONO) and Division (DIVI).

For Supplier Tax:

The field indicates the Accounting entity.

For VAT Periodic:

The field indicates the Company/Division from MBM event data

For Supplier Tax:

The field indicates the standard TaxID's included:

- TaxID 1: Tax ID of company (ESFV) from (TXS035) with additional field (ESAF) = 509, type (TYPE) = 6 and Base country = MNS100.CSCD and if not found from VAT registration number (VRNO) from MNS100.

- TaxID 2: Organization number 1 (CORG) from MNS100.
- TaxID 3: Organization number 2 (COR2) from MNS100.

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: Tax declaration number (VRNL) from MNS100.

For VAT Periodic:

The field indicates the following TaxID is included as standard: - TaxID 1: Tax number from 1) Report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 509 and base country (FBSC) of the report header and if not defined from 2) VAT Registration number (OVRN) from Report header (ISO country code added in M3BE (*) so no adjustment needed).

For Supplier Tax:

The field indicates the standard schemeName included:

- TaxID 1: schemeName "TaxIdentificationNumber"
 TaxID 2: schemeName "CountryIdentificationNumber"
- TaxID 3: schemeName "CountryIdentificationNumber"

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName "CountryIdentificationNumber"

For VAT Periodic:

The following schemeName is included as standard:

- TaxID 1: schemeName "TaxIdentificationNumber"

For Supplier Tax:

The field indicates the Company name (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

For VAT Periodic:

The field indicates the Company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Name

For Supplier Tax:

CMNDIV.CCCONM, CCCOA1-COA4; MNS100MI/GetBasicData

FOR VAT Periodic: FVATHE.VHCONM FVATHE.VHCOA1 FVATHE.VHCOA2 FVATHE.VHCOA3

FVATHE.VHCOA4.; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Location name (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

For VAT Periodic:

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address@type

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address/AddressLine

For Supplier Tax:

CMNDIV.CCCOA1-COA4; MNS100MI/GetBasicData

For VAT Periodic: FVATHE.VHCOA1 FVATHE.VHCOA2 FVATHE.VHCOA3

FVATHE.VHCOA4.; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Company address (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For VAT Periodic:

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

@sequence

For Supplier Tax:

-.-; -/-

For VAT Periodic:

The field indicates the sequence number of the address line: values

1-4

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address/CityName

For Supplier Tax:

For Supplier Tax:

CMNDIV.CCTOWN; MNS100MI/GetBasicData

The field indicates the City (TOWN) of company (from MNS100).

For VAT Periodic: For VAT Periodic:

FVATHE.VHTOWN; TXS100MI/GetHeadInfo The field indicates the city from the report header.

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address/CountrySubDivisionCode

CMNDIV.CCECAR; MNS100MI/GetBasicData

For Supplier Tax: The field indicates the Area/State code (ECAR) of company (from

MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/

state" (CSCD-ECAR)).

For VAT Periodic:

The field indicates the state (ECAR) from the division.

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/

state" (CSCD-ECAR)).

@listID

-.-; -/-

For Supplier Tax:

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" :

"France - Departements".

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces";

for ECAR = "FR" : "France - Departements"

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address/CountryCode

For Supplier Tax:

For Supplier Tax:

CMNDIV.CCCSCD; MNS100MI/GetBasicData The field indicates the Country code (CSCD) of company (from

MNS100).

For VAT Periodic:

FVATRH.RHFBSC; TXS100MI/GetHeadInfo

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

For VAT Periodic:

The field indicates the country code (FBSC) from report header.

Generic translation is used to translate FBSC (BSCD) to alpha-2

country code according to ISO 3166-1.

@listID

For Supplier Tax:

Set to "Countries".

-.-; -/-

LCLTaxReport/TaxReportHeader/InitiatingParty/Location/Address/PostalCode

For Supplier Tax: CMNDİV.CCPONO; MNS100MI/GetBasicData For Supplier Tax:

The field indicates the Postal code (PONO) of company (from

MNS100).

For VAT Periodic:

FVATHE.VHPONO; TXS100MI/GetHeadInfo

For VAT Periodic:

The field indicates the postal code (PONO) from report header.

LCLTaxReport/TaxReportHeader/InitiatingParty/Communication/Address

For Supplier Tax:

For Supplier Tax:

-.-; -/-

The field indicates the Communication/Address section that is only

created if Country version (CSVN) = FR.

@type

For Supplier Tax: -.-: -/-

For Supplier Tax:

Set to "text" if address information included

LCLTaxReport/TaxReportHeader/InitiatingParty/Communication/Address/AddressLine

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - Mailing address (ESFV) from

additional field (ESAF) = 003 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

@seauence For Supplier Tax:

-.-: -/-

For Supplier Tax:

The field indicates the sequence number of the address line: value 1

(only one address line included).

LCLTaxReport/TaxReportHeader/InitiatingParty/Communication/Address/CityName

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - City name (ESFV) from

additional field (ESAF) = 004 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD.

LCLTaxReport/TaxReportHeader/InitiatingParty/Communication/Address/PostalCode

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - Postal code (ESFV) from

additional field (ESAF) = 005 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the Contact information created depending on

setup.

Case 1: If additional field (ESAF) = 500 for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD exist in (TXS035): Information retrieved from CRS618MI with Contact ID (CNPE) = $\frac{1}{2}$

TXS035MI.ESFV.

Case 2: Otherwise, limited information retrieved from MNS100MI.

Case 3: Email address from TXS035MI and additional field (ESAF) = 501+502 for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD in case additional field (ESAF) = 500 is missing.

Case 4: Website from TXS035MI and additional field (ESAF) = 503 for the type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

(Case number included below as clarification, case 3 and 4 only for

applicable elements.)

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/ID

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Contact ID of the company.

Case 1: Contact ID (ESFV) from additional field (ESAF) = 500 in

(TXS035) and if found in CRS618.

Case 2: Not created.

For VAT Periodic:

The field indicates the contact ID (ESFV) from additional field (ESAF) ="500" for the type (TYPE) = 2 in (TXS035) and for the Base country

(FBSC) of the report header.

For Supplier Tax:

The field indicates the accounting entity of the Contact ID.

Case 1: Accounting entity.

Case 2: Not created.

For VAT Periodic:

The field indicates the Company/Division from MBM event data.

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Name

For Supplier Tax: CCUCON.CCTX50

@accountingEntity
For Supplier Tax:

-.-; -/-

CMNDIV.CCOREF.-; CRS618MI

CCUCON.CCTX50; CRS618MI/Get

MNS100MI/Get GetBasicData

For VAT Periodic:

For Supplier Tax:

The field indicates the the Contact name of the company.

Case 1: Contact name (TX50) from (CRS618) via additional field

(ESAF) = 500 in (TXS035).

Case 2: Contact name from Our reference (OREF) in (MNS100).

For VAT Periodic:

The field indicates the contact name (TX50) from (CRS618) for the contact ID (CNPE) from additional field (ESAF) ="500" for the type (TYPE) = 2 in (TXS035) and for the Base country (FBSC) of the report header.

If the additional field "500" is missing, Contact name from Our reference (OREF) in (MNS100)

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication

@sequence

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to the sequence number of communication details.

For VAT Periodic:

The field indicates the sequence number of the contact information:

values 1-4.

@preferredIndicator

For Supplier Tax:

For Supplier Tax: -.-; -/-Set to "false".

For VAT Periodic: Set to "false"

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/ChannelCode

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the type of Channel code.

Case 1 and 2: Set to "Phone" in case of 'DailNumber' (for PHNO,

PHN2 and TFNO).

Case 1 and 3: Set to "Email" in case of 'URI' (for EMAL from CRS618

or from TXS035MI with ESAF=501+502.).

Case 4: Set to "Website" in case of 'URI' (for ESFV from TXS035MI

with ESAF=503).

For VAT Periodic:

Set to "Phone" in case of 'DialNumber' and to "Email" in case of "URI".

@listID

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "Communication Channels".

For VAT Periodic:

Set to "Communication Channels"

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/UseCode

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the the type of Use code.

Case 1 and 2: Set to "Office" in case of 'DailNumber' (for PHNO and

Case 1 and 2: Set to "Fax" in case of 'DailNumer (for TFNO).

Case 1, 3 and 4: Set to 'Office' in case of 'URI' (for EMAL and ESFV

from TXS035MI with ESAF=501+502 and 503).

For VAT Periodic:

Set to "Office" for Phone numbers (PHNO and PHN2) in case of

'DialNumber'

Set to "Office" for E-mail address (EMAL/EMA8) in case of 'URI'. Set to "Fax" for Fax number (TFNO) in case of 'DialNumber'.

For Supplier Tax: For Supplier Tax:

Set to "Communication Use Codes". -.-; -/-

For VAT Periodic:

Set to "Communication Use Codes"

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/DialNumber

For Supplier Tax:

@listID

CCUCON.CCPHNO, CCPHN2

CMNDIV.CCPHNO, CCPHN2, CCTFNO.-; CRS618MI

MNS100MI/Get GetBasicData

For VAT Periodic: CCUCON.CCPHNO CCUCON.CCPHN2 **FVATHE.VHPHNO**

FVATHE.VHPHN2 CMNDIV.CCTFNO.; CRS618MI or TXS100MI MNS100MI/Get or

GetHeadInfo GetBasicData For Supplier Tax:

The field indicates the Dail number for the contact person of the

company.

Case 1: Telephone number 1 (PHNO) and 2 (PHN2) from (CRS618) via additional field (ESAF) = 500 in (TXS035) and Fax number

(TFNO) from (MNS100).

Case 2: Telephone number 1 (PHNO) and 2 (PHN2) from (MNS100) and Fax number (TFNO) from (MNS100).

For VAT Periodic:

The field indicates the telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618).

- If the additional field "500" is missing, Telephone number 1 (PHNO)

and Telephone number 2 (PHN2) from report header.

Fax number (TFNO) from (MNS100).

${\it LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address} \\ @type$

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address/AddressLine

For Supplier Tax:

CCUCON.CCCUA1-CUA4; CRS618MI/Get

For VAT Periodic: CCUCON.CCCUA1 CCUCON.CCCUA2 CCUCON.CCCUA3

CCUCON.CCCUA4.; CRS618MI/Get

For Supplier Tax:

The field indicates the address of the contact person of the company.

Case 1: Address of the contact person of the company from (CRS618) via additional field (ESAF) = 500 in (TXS035) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

Case 2: Not included.

For VAT Periodic:

The field indicates the address of the contact person of the company from (CRS618) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Supplier Tax:

Set to the Sequence number of the address line: values 1-4.

For VAT Periodic:

The field indicates the sequence number of the address line: values 1-4.

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address/CityName

CCUCON.CCTOWN; CRS618MI/Get

@seauence

-.-: -/-

For Supplier Tax:

For Supplier Tax:

The field indicates the City of the contact person of the company.

Case 1: City (TOWN) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Case 2: Not included.

For VAT Periodic:

The field indicates the city (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and

when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address/CountrySubDivisionCode

CCUCON.CCECAR; CRS618MI/Get

For Supplier Tax:

The field indicates the Area/State of the contact person of the company.

Case 1: Area/state (ECAR) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR).

Case 2: Not included.

For VAT Periodic:

The field indicates the area/state (ECAR) of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR).

@listID

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements".

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address/CountryCode

CCUCON.CCCSCD; CRS618MI/Get

For Supplier Tax:

The field indicates the Country of the contact person of the company.

Case 1: Country (CSCD) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

Case 2: Not included.

For VAT Periodic:

The field indicates the country code (CSCD) of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

For Supplier Tax:

Set to "Countries".

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Address/PostalCode

CCUCON.CCPONO; CRS618MI/Get

For Supplier Tax:

The field indicates the Postal code of the contact person of the company.

Case 1: Postal code of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Case 2: Not included.

For VAT Periodic:

The field indicates the postal code (PONO) of the contact in (CRS618).

LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/URI

For Supplier Tax: CCUCON.CCEMAL

FQRADF.EAESFV.-; CRS618MI TXS035MI/Get

LstBaseCountry

For VAT Periodic: CCUCON.CCEMAL

FVATHE.VHEMA8.; CRS618MI or

TXS100MI/Get or GetHeadInfo For Supplier Tax:

The field indicates the E-mail address of the contact person of the company as well as the Website of the company.

Case 1: E-mail address (EMAL) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Case 3: If the additional field ESFV=500 is missing, retreived from additional field ESAF=501+502 in (TXS035).

For VAT Periodic:

Case 4: Retreived from additional field "503" in (TXS035). For VAT Periodic: The field indicates the e-mail address (EMAL) of the contact in (CRS618). If the additional field "500" is missing, retrieved from e-mail (EMA8) from report header. LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/HTMLPreferredIndicator For Supplier Tax: For Supplier Tax: -.-; -/-Set to constant = "true". For VAT Periodic: Set to 'true' LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Preference/Sequence For Supplier Tax: For Supplier Tax: -.-; -/-Set to constant = "1". For VAT Periodic: Set to '1' LCLTaxReport/TaxReportHeader/InitiatingParty/Contact/Communication/Preference/Indicator For Supplier Tax: For Supplier Tax: -.-; -/-Set to "false". For VAT Periodic: Set to "false" LCLTaxReport/TaxReportHeader/InitiatingParty/UserArea For Supplier Tax: For Supplier Tax: FQRADF.EAESFV; TXS035MI/GetAddField The field indicates the APE code and main activity of the company for Country version (CSVN) = FR: - NameValue = @name="lcl.APECode and @listID="APE": APE code (ESFV) from additional field (ESAF) = 001 (*) in (TXS035). - Description: Main activity of Facility (ESFV) from additional field (ESAF) = 008 (*) in (TXS035). Ex: <UserArea> <Property> <NameValue name="lcl.APECode" listID="APE">1051B</ NameValue> <Description>Manufacture of butter</Description> </Property> </UserArea> (*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD. LCLTaxReport/TaxReportHeader/DeclaringParty/PartyIDs/ID For Supplier Tax: For Supplier Tax: FTAXR1.R1CONO, R1DIVI; APS430MI/GetTaxHead The field indicates the Company and Division concatenated without space or separator. For VAT Periodic: FQRADF.EAESFV; TXS035MI/GetAddField For VAT Periodic: The field indicates the ID (external or internal) of the declaring party: - If report field (ESAF) = 515 for the base country (FBSC) in report header and type (TYPE) = 2 exist: External ID from (ESFV) in)TXS035) and if not existing: - If report field (ESAF) = 514 for the base country (FBSC) in report header and type (TYPE) = 2 exist: External ID from (ESFV) in)TXS035) and if not existing: - Internal ID - Company (CONO) and Division (DIVI). @accountingEntity For Supplier Tax: For Supplier Tax: -.-; -/-The field indicates the Accounting entity. For VAT Periodic: The field indicates the Company/Division from MBM event data LCLTaxReport/TaxReportHeader/DeclaringParty/PartyIDs/TaxID For Supplier Tax: For Supplier Tax: CMNDIV.CCVRNO, CCVRNL, CCCORG, CCCOR2 The field indicates the standard TaxID included: - TaxID 1: Tax ID of company (ESFV) from (TXS035) with additional field (ESAF) = 509, type (TYPE) = 6 and Base country = $\frac{1}{2}$ FQRADF.EAESFV .-: MNS100MI TXS035MI/GetBasicData MNS100.CSCD and if not found from VAT registration number (VRNO) from MNS100. - TaxID 2: Organization number 1 (CORG) from MNS100. GetAddField - TaxID 3: Organization number 2 (COR2) from MNS100.

FVATHE.VHOVRN.; TXS035MI or TXS100MI/GetAddField or GetHeadInfo

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: Tax declaration number (VRNL) from MNS100.

For VAT Periodic:

The field indicates the following TaxID is included as standard: - TaxID 1: Tax number from 1) Report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 509 and base country (FBSC) of the report header and if not defined from 2) VAT Registration number (OVRN) from Report header (ISO country code added in M3BE (*) so no adjustment needed).

@schemeName

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the standard schemeName included:

- TaxID 1: schemeName "TaxIdentificationNumber"
 TaxID 2: schemeName "CountryIdentificationNumber"
- TaxID 3: schemeName "CountryIdentificationNumber"

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: schemeName "CountryIdentificationNumber"

For VAT Periodic:

The following schemeName is included as standard:

- TaxID 1: schemeName "TaxIdentificationNumber"

LCLTaxReport/TaxReportHeader/DeclaringParty/Name

For Supplier Tax:

CMNDIV.CCCONM, CCCOA1-COA4; MNS100MI/GetBasicData

For VAT Periodic:

FVATHE.VHCONM; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Company name (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

For VAT Periodic:

The field indicates the company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Name

For Supplier Tax:

CMNDIV.CCCONM, CCCOA1-COA4; MNS100MI/GetBasicData

For VAT Periodic: **FVATHE.VHCONM** or

VHCOA1-VHCOA4; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Location name (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

For VAT Periodic:

The field indicates the location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address @type

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address/AddressLine

For Supplier Tax:

CMNDIV.CCCOA1-COA4; MNS100MI/GetBasicData

For VAT Periodic:

FVATHE.VHCOA1-VHCOA4; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Company address (from MNS100) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For VAT Periodic:

The field indicates the company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

For VAT Periodic:

The field indicates the Sequence number of the address line: values 1-4.

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address/CityName

For Supplier Tax:

For Supplier Tax:

@sequence

-.-; -/-

CMNDIV.CCTOWN; MNS100MI/GetBasicData

For Supplier Tax:

The field indicates the City (TOWN) of company (from MNS100).

For VAT Periodic:

FVATHE.VHTOWN; TXS100MI/GetHeadInfo

For VAT Periodic:

The field indicates the city (TOWN) from the report header.

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address/CountrySubDivisionCode

CMNDIV.CCECAR; MNS100MI/GetBasicData

For Supplier Tax:

The field indicates the Area/State code (ECAR) of company (from MNS100).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR)).

For VAT Periodic:

The field indicates the State (ECAR) from the division.

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR)).

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements".

@listID

For Supplier Tax:

-.-; -/-

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces";

for ECAR = "FR" : "France - Departements"

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address/CountryCode

For Supplier Tax:

For Supplier Tax: CMNDIV.CCCSCD; MNS100MI/GetBasicData

The field indicates the Country code (CSCD) of company (from

MNS100).

For VAT Periodic:

FVATRH.RHFBSC; TXS100MI/GetHeadInfo

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

For VAT Periodic:

The field indicates the country code (FBSC) from report header.

Generic translation is used to translate FBSC (BSCD) to alpha-2

country code according to ISO 3166-1.

@listID

For Supplier Tax:

Set to "Countries"

LCLTaxReport/TaxReportHeader/DeclaringParty/Location/Address/PostalCode

For Supplier Tax:

CMNDIV.CCPONO; MNS100MI/GetBasicData

For VAT Periodic:

FVATHE.VHPONO; TXS100MI/GetHeadInfo

For Supplier Tax:

The field indicates the Postal code (PONO) of company (from

MNS100).

For VAT Periodic:

The field indicates the Postal code (PONO) from report header

LCLTaxReport/TaxReportHeader/DeclaringParty/Communication/Address

For Supplier Tax:

-.-; -/-

@type

For Supplier Tax:

For Supplier Tax: The field indicates the Communication/Address section that is only

created if Country version (CSVN) = FR.

For Supplier Tax:

Set to "text" if address information included.

LCLTaxReport/TaxReportHeader/DeclaringParty/Communication/Address/AddressLine

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - Mailing address (ESFV) from

additional field (ESAF) = 003 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

@sequence

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to sequence number of the address line: value 1 (only one

address line included).

LCLTaxReport/TaxReportHeader/DeclaringParty/Communication/Address/CityName

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - City name (ESFV) from

additional field (ESAF) = 004 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

LCLTaxReport/TaxReportHeader/DeclaringParty/Communication/Address/PostalCode

For Supplier Tax:

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Postal address - Postal code (ESFV) from

additional field (ESAF) = 005 (*) in (TXS035).

NB: Only created for Country version (CSVN) = FR.

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact

For Supplier Tax: -.-; -/-

For Supplier Tax:

The field indicates the Contact information created depending on

Case 1: If additional field (ESAF) = 500 for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD exist in (TXS035): Information retrieved from CRS618MI with Contact ID (CNPE) =

TXS035MI.ESFV.

Case 2: Otherwise, limited information retrieved from MNS100MI.

Case 3: Email address from TXS035MI and additional field (ESAF) = 501+502 for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD in case additional field (ESAF) = 500 is missing.

Case 4: Website from TXS035MI and additional field (ESAF) = 503 for the type (TYPE) = 6 and Base country (BSCD) =

MNS100MI.CSCD.

(Case number included below as clarification, case 3 and 4 only for applicable elements.)

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/ID

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Contact ID of the contact person of the company.

Case 1: Contact ID (ESFV) from additional field (ESAF) = 500 in (TXS035) and if found in CRS618.

Case 2: Not created.

For VAT Periodic:

The field indicates the contact ID (ESFV) from additional field (ESAF) ="500" for the type (TYPE) = 2 in (TXS035) and for the Base country (FBSC) of the report header.

@accountingEntity

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the accounting entity of the Contact ID.

Case 1: Accounting entity.

Case 2: Not created.

For VAT Periodic:

The field indicates the company/Division from MBM event data.

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Name

For Supplier Tax: CCUCON.CCTX50

CMNDIV.CCOREF.-; CRS618MI

MNS100MI/Get GetBasicData

For VAT Periodic:

CCUCON.CCTX50; CRS618MI/Get

For Supplier Tax:

The field indicates the Contact name of the contact person of the company.

Case 1: Contact name (TX50) from (CRS618) via additional field (ESAF) = 500 in (TXS035).

Case 2: Contact name from Our reference (OREF) in (MNS100).

For VAT Periodic:

The field indicates the contact name (TX50) from (CRS618) for the contact ID (CNPE) from additional field (ESAF) ="500" for the type (TYPE) = 2 in (TXS035) and for the Base country (FBSC) of the report header.

If the additional field "500" is missing, Contact name from Our reference (OREF) in (MNS100).

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication

@sequence

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to sequence number of communication details.

For VAT Periodic:

The field indicates the Sequence number of the contact information:

values 1-4.

@preferredIndicator

For Supplier Tax:

-.-; -/-

For Supplier Tax: Set to "false".

For VAT Periodic: Set to "false"

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/ChannelCode

For Supplier Tax:

For Supplier Tax:

-.-; -/-

The field indicates the type of Channel code.

Case 1 and 2: Set to "Phone" in case of 'DailNumber' (for PHNO, PHN2 and TFNO).

Case 1 and 3: Set to "Email" in case of 'URI' (for EMAL from CRS618 or from TXS035MI with ESAF=501+502.).

Case 4: Set to "Website" in case of 'URI' (for ESFV from TXS035MI

with ESAF=503).

For VAT Periodic:

Set to "Phone" in case of 'DialNumber' and to "Email" in case of "URI".

@listID

For Supplier Tax:

-.-: -/-

For Supplier Tax:

Set to "Communication Channels".

For VAT Periodic:

Set to "Communication Channels"

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/UseCode

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the type of Use code.

Case 1 and 2: Set to "Office" in case of 'DailNumber' (for PHNO and

Case 1 and 2: Set to "Fax" in case of 'DailNumer (for TFNO).

Case 1, 3 and 4: Set to 'Office' in case of 'URI' (for EMAL and ESFV

from TXS035MI with ESAF=501+502 and 503).

For VAT Periodic:

Set to "Office" for Phone numbers (PHNO and PHN2) in case of

'DialNumber'.

Set to "Office" for E-mail address (EMAL/EMA8) in case of 'URI'. Set to "Fax" for Fax number (TFNO) in case of 'DialNumber'.

For Supplier Tax:

Set to "Communication Use Codes".

For VAT Periodic:

Set to "Communication Use Codes"

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/DialNumber

For Supplier Tax:

For Supplier Tax:

@listID

-.-; -/-

CCUCON.CCPHNO, CCPHN2

CMNDIV.CCPHNO, CCPHN2, CCTFNO.-; CRS618MI

MNS100MI/Get GetBasicData

For VAT Periodic: CCUCON.CCPHNO CCUCON.CCPHN2 **FVATHE.VHPHNO**

FVATHE.VHPHN2 CMNDIV.CCTFNO.; CRS618MI or TXS100MI MNS100MI/Get or

GetHeadInfo GetBasicData For Supplier Tax:

The field indicates the Dail number of the contact person of the

company.

Case 1: Telephone number 1 (PHNO) and 2 (PHN2) from (CRS618) via additional field (ESAF) = 500 in (TXS035) and Fax number

(TFNO) from (MNS100).

Case 2: Telephone number 1 (PHNO) and 2 (PHN2) from (MNS100)

and Fax number (TFNO) from (MNS100).

For VAT Periodic:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618).

- If the additional field "500" is missing, Telephone number 1 (PHNO)

and Telephone number 2 (PHN2) from report header.

Fax number (TFNO) from (MNS100).

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address @tvpe

For Supplier Tax: -.-; -/-

For Supplier Tax:

Set to "text" if address information included

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address/AddressLine

For Supplier Tax:

CCUCON.CCCUA1-CUA4; CRS618MI/Get

For Supplier Tax:

The field indicates the Address of the contact person of the company.

For VAT Periodic: CCUCON.CCCUA1 CCUCON.CCCUA2 CCUCON.CCCUA3

CCUCON.CCCUA4.; CRS618MI/Get

Case 1: Address of the contact person of the company from (CRS618) via additional field (ESAF) = 500 in (TXS035) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

Case 2: Not included.

For VAT Periodic:

The field indicates address of the contact person of the company from (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

For VAT Periodic:

The field indicates the Sequence number of the address line: values 1-4.

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address/CityName

CCUCON.CCTOWN; CRS618MI/Get

@sequence

For Supplier Tax:

For Supplier Tax:

The field indicates the City of the contact person of the company.

Case 1: City (TOWN) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Case 2: Not included.

For VAT Periodic:

The field indicates the city (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address/CountrySubDivisionCode

CCUCON.CCECAR; CRS618MI/Get

For Supplier Tax:

The field indicates the Area/state of the contact person of the company.

Case 1: Area/state (ECAR) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR).

Case 2: Not included.

For VAT Periodic:

The field indicates area/state (ECAR) of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR).

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"

@listID

For Supplier Tax:

-.-; -/-

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces";

for ECAR = "FR" : "France - Departements"

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address/CountryCode

CCUCON.CCCSCD; CRS618MI/Get

For Supplier Tax:

The field indicates the Country of the contact person of the company.

Case 1: Country (CSCD) of the contact person in (CRS618) via

additional field (ESAF) = 500 in (TXS035).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

Case 2: Not included.

For VAT Periodic:

The field indicates the country code (CSCD) of the contact in

(CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Supplier Tax: Set to "Countries".

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Address/PostalCode

CCUCON.CCPONO; CRS618MI/Get

For Supplier Tax:

The field indicates the Postal code of the contact person of the

company.

Case 1: Postal code of the contact person in (CRS618) via additional

field (ESAF) = 500 in (TXS035).

Case 2: Not included.

For VAT Periodic:

For Supplier Tax:

The field indicates the Postal code (PONO) of the contact in

(CRS618)

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/URI

For Supplier Tax: CCUCON.CCEMAL

FQRADF.EAESFV.-; CRS618MI TXS035MI/Get

LstBaseCountry

The field indicates the E-mail address of the contact person of the company as well as the Website of the company.

> Case 1: E-mail address (EMAL) of the contact person in (CRS618) via additional field (ESAF) = 500 in (TXS035).

For VAT Periodic: CCUCON.CCEMAL

FVATHE.VHEMA8.; CRS618MI or

TXS100MI/Get or GetHeadInfo

Case 3: If the additional field ESFV=500 is missing, retreived from

additional field ESAF=501+502 in (TXS035).

Case 4: Retreived from additional field "503" in (TXS035).

For VAT Periodic:

The field indicates the e-mail address (EMAL) of the contact in

(CRS618).

If the additional field "500" is missing, retrieved from e-mail (EMA8)

from report header.

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/HTMLPreferredIndicator

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to constant = "true".

For VAT Periodic:

Set to 'true'

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Preference/Sequence

For Supplier Tax: -.-; -/-

For Supplier Tax: Set to constant = "1".

For VAT Periodic:

Set to '1'

LCLTaxReport/TaxReportHeader/DeclaringParty/Contact/Communication/Preference/Indicator

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "false".

For VAT Periodic: Set to "false"

LCLTaxReport/TaxReportHeader/DeclaringParty/UserArea

For Supplier Tax:

For Supplier Tax:

The field indicates the APE code and main activity of the company for Country version (CSVN) = FR:

- NameValue = @name="lcl.APECode and @listID="APE": APE code (ESFV) from additional field (ESAF) = 001 (*) in (TXS035).

- Description: Main activity of Facility (ESFV) from additional field (ESAF) = 008 (*) in (TXS035).

Ex:

<UserArea>

<Property>

<NameValue name="Icl.APECode" listID="APE">1051B</

NameValue>

<Description>Manufacture of butter

</Property>

</UserArea>

(*) Value in TXS035 for type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD.

LCLTaxReport/TaxReportHeader/Party

For VAT Periodic:

For Supplier Tax:

For VAT Periodic:

@role

FQRADF.ESFV; TXS035MI/GetAddField

FQRADF.EAESFV; TXS035MI/GetAddField

For VAT Periodic:

Party created depending on information defined in TXS035 (*):

1) Party with role="Agent" created when:

Additional field (ESAF) = 570, 571, 572 and/or 573 defined.

2) Party with role="Recipient" created when:

- Additional field (ESAF) = 563 and/or 564 defined.

(*) TXS035 for type (TYPE) = 2 and base country (FBSC) from report header.

For Supplier Tax:

The field indicates the role of the party. One party per role is created with information depending on setup:

- Party with role@"SoftwareVendor" created if additional field (ESAF):
 576 for Party/Contact information from CRS618MI.
- 578 for Party/Name and Location from CRS610MI.
- Party with role@"Auditor" created if additional field (ESAF): 581 for Party/Contact information from CRS618MI.

- 583 for Party/Name and Location from CRS610MI.

Information retrieved from CRS618MI with Contact ID (CNPE) = TXS035MI.ESFV for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD.

Information retrieved from CRS610MI with Customer ID (CUNO) = TXS035MI.ESFV for the type (TYPE) = 6 and Base country (BSCD) = MNS100MI.CSCD.

For VAT Periodic:

Role of party depending on information defined in TXS035 (*):

- Additional field (ESAF) = 570, 571, 572 and/or 573 defined: Set to
- Additional field (ESAF) = 563 and/or 564 defined: Set to "Recipient".

(*) TXS035 for type (TYPE) = 2 and base country (FBSC) from report header.

LCLTaxReport/TaxReportHeader/Partv/PartvIDs/ID

FQRADF.EAESFV; TXS035MI/GetAddField

For Supplier Tax:

The field indicates the Customer ID (CUNO) from (TXS035/CRS610).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the ID of the Party from report field (ESFV in TXS035 (*):

- 1) Party with role="Agent":
- External ID from field (ESAF) = 572, if not existing from:
- Internal ID from field (ESAF) = 573.
- 2) Party with role="Recipient":
- External ID from field (ESAF) = 563, if not existing from:
- Internal ID from field (ESAF) = 564.

(*) TXS035 for type (TYPE) = 2 and base country (FBSC) from report header.

@accountingEntity

For Supplier Tax:

-.-; -/-

LCLTaxReport/TaxReportHeader/Party/Name

For Supplier Tax:

OCUSMA.OKCUNM, OKCUA1-CUA4; CRS610MI/GetBasicData

For VAT Periodic:

OCUSMA.OKCUNM; CRS610MI/GetBasicData

For Supplier Tax:

The field indicates the Accounting entity.

For Supplier Tax:

The field indicates the Party name from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Name (CUNM) as mandatory information.

Alternative if generic translation not used: Name (CUNM).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the name of the internal customer (*) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code A and B indicate 'Customer name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM).

Alternative if generic translation not used: Customer name (CUNM).

- (*) Created depending on information defined in TXS035:
- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).
- Additional field (ESÁF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

LCLTaxReport/TaxReportHeader/Party/Location/Name

For Supplier Tax:

OCUSMA.OKCUNM, OKCUA1-CUA4; CRS610MI/GetBasicData

For VAT Periodic: OCUSMA.OKCUNM OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3

OCUSMA.OKCUA4.; CRS610MI/GetBasicData

For Supplier Tax:

The field indicates the Location name from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Name (CUNM).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the location name of the internal customer (*) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

- (*) Created depending on information defined in TXS035:
- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).
- Additional field (ESAF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

LCLTaxReport/TaxReportHeader/Party/Location/Address @type

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/Party/Location/Address/AttentionOfName

For VAT Periodic:

OCUSMA.OKYREF; CRS610MI/GetBasicData

For VAT Periodic:

The field indicates the Your reference (YREF) of the internal customer (*) from (CRS610).

(*) Created depending on information defined in TXS035:
- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).

- Additional field (ESÁF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

LCLTaxReport/TaxReportHeader/Party/Location/Address/AddressLine

For Supplier Tax:

OCUSMA.OKCUA1-CUA4; CRS610MI/GetBasicData

For VAT Periodic: OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3

OCUSMA.OKCUA4.; CRS610MI/GetBasicData

For Supplier Tax:

The field indicates the Address from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates address of the internal customer (*) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Customer address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Customer address line 1-4 (CUA1-CUA4).

(*) Created depending on information defined in TXS035:
- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).

 Additional field (ESAF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

For VAT Periodic:

The field indicates the Sequence number of the address line: values 1-4

LCLTaxReport/TaxReportHeader/Party/Location/Address/CityName

For Supplier Tax:

@sequence
 For Supplier Tax:

-.-; -/-

OCUSMA.OKTOWN; CRS610MI/GetBasicData

For VAT Periodic:

OCUSMA.OKTOWN; CRS610MI/GetBasicDAta

For Supplier Tax:

The field indicates the City (TOWN) from (CRS610).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the city name (TOWN) of the internal customer (*) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

(*) Created depending on information defined in TXS035:

- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).

- Additional field (ESAF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

LCLTaxReport/TaxReportHeader/Party/Location/Address/CountrySubDivisionCode

For Supplier Tax:

OCUSMA.OKECAR; CRS610MI/GetBasicData

For VAT Periodic:

OCUSMA.OKECAR; CRS610MI/GetBasicDAta

For Supplier Tax:

The field indicates the Area/State code (ECAR) from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/state" (CSCD-ECAR)).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates area/State code (ECAR) of the internal customer (*) from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR)).

(*) Created depending on information defined in TXS035:

- Ádditional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).

- Additional field (ESÁF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements".

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departments".

LCLTax Report/Tax Report Header/Party/Location/Address/Country Code

OCUSMA.OKCSCD; CRS610MI/GetBasicData

For Supplier Tax:

The field indicates the Country code (CSCD) from CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the country code (CSCD) of the internal customer (*) from (CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

(*) Created depending on information defined in TXS035:

- Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO).

 Additional field (ESAF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).

Set to "Countries".

@listID

@listID

-.-; -/-

For Supplier Tax:

For Supplier Tax:

LCLTaxReport/TaxReportHeader/Party/Location/Address/PostalCode

OCUSMA.OKPONO; CRS610MI/GetBasicData

For Supplier Tax:

The field indicates the Postal code (PONO) from (CRS610).

NB: Created if additional field (ESAF) 578 or 583 defined in (TXS035) and customer found in (CRS610).

For VAT Periodic:

The field indicates the Postal code (PONO) of the internal customer

LCLIARREPOIL	
•	(*) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).
	(*) Created depending on information defined in TXS035: - Additional field (ESAF) = 573 defined (role="Agent"): Contains Customer no (CUNO). - Additional field (ESAF) = 564 defined (role="Recipient"): Contains Customer no (CUNO).
LCLTaxReport/TaxReportHeader/Party/Contact/ID FQRADF.EAESFV; TXS035MI/GetAddField	For Supplier Tax: The field indicates the Contact ID (CNPE) from (TXS035/CRS618).
	NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).
	For VAT Periodic: The field indicates the contact ID of the Party from report field (ESFV in TXS035 (*): 1) Party with role="Agent": - External ID from field (ESAF) = 570, if not existing from: - Internal ID from field (ESAF) = 571.
	(*) TXS035 for type (TYPE) = 2 and base country (FBSC) from report header.
@accountingEntity For Supplier Tax:; -/-	For Supplier Tax: The field indicates the Accounting entity.
LCLTaxReport/TaxReportHeader/Party/Contact/Name For Supplier Tax: CCUCON .CCTX50; CRS618MI/Get	For Supplier Tax: The field indicates the Contact name (TX50) from (CRS618).
For VAT Periodic: CCUCON.CCTX50; CRS618MI/Get	NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).
	For VAT Periodic: The field indicates the contact name (TX50) from (CRS618) for the contact ID (CNPE) from TXS035 (*): 1) Party with role="Agent": - Additional field (ESAF) = 571.
	(*) TXS035 for type (TYPE) = 2 and base country (FBSC) from report header.
LCLTaxReport/TaxReportHeader/Party/Contact/Communication	
@sequence For Supplier Tax:; -/- @preferredIndicator For Supplier Tax:; -/-	For Supplier Tax: Set to sequence number of communication details.
	For VAT Periodic: Set to sequence= 1-3 depending on information included.
	NB: The details for Party/Contact/Communication created depending on information defined in TXS035: - Additional field (ESAF) = 571 defined (role="Agent"): Contains Contact ID (CNPE).
	For Supplier Tax: Set to "false".
	For VAT Periodic: Set to "false"
LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Cha For Supplier Tax:	nnelCode For Supplier Tax:
; -/-	The field indicates the type of Channel code.
	Set to "Phone" in case of 'DailNumber' (for PHNO and PHN2).
	Set to "Email" in case of 'URI' (for EMAL).
	NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).
@listID	For VAT Periodic: Set to "Phone" in case of 'DialNumber' and to "Email" in case of 'URI'.
For Supplier Tax:	Set to "Communication Channels".

Infor May 26, 2023 276

LCLTax Report/Tax Report Header/Party/Contact/Communication/Use Code

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the type of Use code.

Set to "Office" in case of 'DailNumber' (for PHNO and PHN2).

Set to 'Office' in case of 'URI' (for EMAL).

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).

For VAT Periodic:

Set to "Office" for Phone numbers (PHNO and PHN2) in case of

'DialNumber'.

Set to "Office" for E-mail address (EMAL) in case of 'URI'.

Set to "Communication Use Codes".

@listID For Supplier Tax:

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/DialNumber

For Supplier Tax:

CCUCON.CCPHNO, CCPHN2; CRS618MI/Get

For VAT Periodic: CCUCON.CCPHNO

CCUCON.CCPHN2.; CRS618MI/Get

For Supplier Tax:

The field indicates the Telephone number 1 (PHNO) and 2 (PHN2)

from (CRS618).

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035)

and contact found in (CRS618).

For VAT Periodic:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618).

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address

@type

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

For VAT Periodic: Set to 'text'.

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address/AddressLine

For Supplier Tax:

CCUCON.CCCUA1-CUA4; CRS618MI/Get

For VAT Periodic: CCUCON.CCCUA1 CCUCON.CCCUA2 CCUCON.CCCUA3

CCUCON.CCCUA4.; CRS618MI/Get

For Supplier Tax:

The field indicates the Address of the contact person of the company

from (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate

'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).

For VAT Periodic:

The field indicates address of the contact in (CRS618) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H indicate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (CUA2).

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code J not available: Address line 4 (CUA4) not included as not mandatory information.

@sequence

For Supplier Tax:

-.-: -/-

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

For VAT Periodic:

The field indicates the Sequence number of the address line: values 1.4

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address/CityName

CCUCON.CCTOWN; CRS618MI/Get

For Supplier Tax:

The field indicates the City (TOWN) of the contact person in (CRS618)

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).

For VAT Periodic:

The field indicates the city (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address/CountrySubDivisionCode

CCUCON.CCECAR; CRS618MI/Get

For Supplier Tax:

The field indicates the Area/state (ECAR) of the contact person in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR).

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).

For VAT Periodic:

The field indicates area/state (ECAR) of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR).

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements"

For VAT Periodic:

The field indicates the general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR" : "France - Departements"

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address/CountryCode

CCUCON.CCCSCD; CRS618MI/Get

For Supplier Tax:

The field indicates the Country (CSCD) of the contact person in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618).

For VAT Periodic:

The field indicates the country code (CSCD) of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

@listID

-.-; -/-

@listID

-.-: -/-

For Supplier Tax:

For Supplier Tax:

Set to "Countries".

LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Address/PostalCode

CCUCON.CCPONO; CRS618MI/Get

For Supplier Tax:

The field indicates the Postal code of the contact person in (CRS618).

NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035)

@currencyID

and contact found in (CRS618). For VAT Periodic: The field indicates the Postal code (PONO) of the contact in (CRS618) LCLTaxReport/TaxReportHeader/Party/Contact/Communication/URI CCUCON.CCEMAL; CRS618MI/Get For Supplier Tax: The field indicates the E-mail address (EMAL) of the contact person in (CRS618). NB: Created if additional field (ESAF) 576 or 581 defined in (TXS035) and contact found in (CRS618). For VAT Periodic: The field indicates the e-mail address (EMAL) of the contact in (CRS618) LCLTaxReport/TaxReportHeader/Party/Contact/Communication/HTMLPreferredIndicator For Supplier Tax: For Supplier Tax: -.-; -/-Set to constant = "true". For VAT Periodic: Set to 'true' LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Preference/Sequence For Supplier Tax: For Supplier Tax: Set to constant = "1" -.-; -/-LCLTaxReport/TaxReportHeader/Party/Contact/Communication/Preference/Indicator For Supplier Tax: For Supplier Tax: Set to "false". LCLTaxReport/TaxReportHeader/AuthorizationCode For Supplier Tax: For Supplier Tax: FQRADF.EAESFV; TXS035MI/LstBaseCountry The field indicates the Authorization code from report field (ESFV in TXS035) for type TYPE) = 6, field (ESAF) = 512 and Base country For VAT Periodic: (BSCD) = MNS100MI.CSCD. FQRADF.EAESFV; TXS035MI/GetAddField For VAT Periodic: The field indicates the authorization code from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 512 and base country (FBSC) from report header. LCLTaxReport/TaxReportHeader/AuthenticationCode For Supplier Tax: For Supplier Tax: FQRADF.EAESFV; TXS035MI/LstBaseCountry The field indicates the Authentication code from report field (ESFV in TXS035) for type TYPE) = 6, field (ESAF) = 511 and Base country For VAT Periodic: (BSCD) = MNS100MI.CSCD. FQRADF.EAESFV; TXS035MI/GetAddField For VAT Periodic: The field indicates the authentication code from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 511 and base country (FBSC) from report header LCLTaxReport/TaxReportHeader/TotalTaxBasisAmount For VAT Periodic: For VAT Periodic: FQRADF.EAESFV; TXS035MI/GetAddField The field indicates the TotalTaxBasisAmount (AC02) depending on Report type: - Report type 1: Not populated (not used for this type of report for the moment). Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 1 must be used. @currencyID For VAT Periodic: For VAT Periodic: FVATHE.VHCUCD; TXS100MI/GetHeadInfo The field indicates the currency code (CUCD) from Report header. Generic translation is used to translate CUCD according to ISO 4217. LCLTaxReport/TaxReportHeader/TotalTaxAuthorityAmount For VAT Periodic: For VAT Periodic: FQRADF.EAESFV; TXS035MI/GetAddField The field indicates the TotalTaxAuthorityAmount (AC03) depending on Report type: - Report type 1: Not populated (not used for this type of report for the

Infor May 26, 2023 27

moment).

default report type 1 must be used.

Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used.

Lourakneport	
For VAT Periodic: FVATHE.VHCUCD; TXS100MI/GetHeadInfo	For VAT Periodic: The field indicates the currency code (CUCD) from Report header.
	Generic translation is used to translate CUCD according to ISO 4217.
LCLTaxReport/TaxReportHeader/TotalAmount For VAT Periodic: FQRADF.EAESFV; TXS035MI/GetAddField	For VAT Periodic: The field indicates the TotalAmount (AC01) depending on Report type - Report type 1: Not populated (not used for this type of report for the moment).
	Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 1 must be used.
@currencyID For VAT Periodic: FVATHE.VHCUCD; TXS100MI/GetHeadInfo	For VAT Periodic: The field indicates the currency code (CUCD) from Report header.
	Generic translation is used to translate CUCD according to ISO 4217.
LCLTaxReport/TaxReportHeader/NumberOfLines For Supplier Tax:; -/-	For Supplier Tax: The field indicates the counter for Number of TaxReportLines included.
	For VAT Periodic: The field indicates the calculated number of line (TaxReportLine) in the report.
ECLTaxReport/TaxReportLine/LineNumber For Supplier Tax:; -/- For VAT Periodic: FQRADF.EAESFV FVTUDL.V2UK01.; TXS035MI and TXS100MI/GetAddField and LstVATUserDef	For Supplier Tax: The field indicates the standard solution to create section TaxReportLine: - Create one TaxReportLine per Supplier (SUNO) - NB: MI can return one or several records per Supplier (SUNO) so TaxReportLine must be created when new Supplier (SUNO).
	NB: Any other structure/solution required will be handled (when added) as exception depending on Country version (MNS100.CSVN).
	NB: LineNumber not created, only used for comment about structure.
	(*) Reporting method (ESTR) not available via APS430MI.GetTaxHead, to be added in case required.
	For VAT Periodic: The field indicates the Structure: TaxReportLine created depending on report type (*) selected: - If report type = 1: Created per record in TXS100MI.LstVATUserDef.
	Line number (LNID = UK01 with leading zeros removed if sent) created depending on report type (*) selected: - If report type = 1: LineNumber always created (mandatory) If report type = 2 or 3: LineNumber only created if Line ID (LNID = UK01) is not zero (needed for some formats to indicate type of record to be created), otherwise not created.
	(*) Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. - If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 1 must be used.
LCLTaxReport/TaxReportLine/CustomerParty For VAT Periodic: .; TXS035MI and TXS100MI/GetAddField and LstVATUserDef	For VAT Periodic: Customer party created in case report type 2 or 3 selected and Customer/Supplier code (CVOP = UKnn) = 1.
	Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 1 must be used.
	Customer party name and address via TXS035 setting (optional, only if information from OIS002).
LCLTaxReport/TaxReportLine/SupplierParty	For VAT Periodic: Supplier party created in case report type 2 or 3 selected and Customer/Supplier code (CVOP) = 0 or 2 If CVOP (UKnn) = 0: Information from TXS040 must be used. (*) - If CVOP (UKnn) = 2: Information from CRS620 must be used.

Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 1 must be used.

(*) Must be discussed with Christina F how to handle CVOP=0, ev new setting in BE to decide.

Supplier party name and address via TXS035 setting (mandatory (if address information needed), information from CRS622).

LCLTaxReport/TaxReportLine/SupplierParty/PartyIDs/ID

For Supplier Tax:

FTAXR2.R2SUNO; APS430MI/LstTaxTotSupSer

@schemeName

For Supplier Tax:

-.-: -/-

@accountingEntity

For Supplier Tax:

LCLTaxReport/TaxReportLine/SupplierParty/PartyIDs/TaxID

For Supplier Tax:

CIDMAS.IDVRNO, IDCORG, IDCOR2 CIDVEN.IITINO .-; CRS620MI/GetBasicData

For Supplier Tax:

For Supplier Tax:

For Supplier Tax:

For Supplier Tax:

The field indicates the standard TaxID included:

The field indicates the Supplier number (SUNO).

The field indicates the schemeName used as standard:

- TaxID 1: VAT registration number (VRNO). - TaxID 2: Organization number 1 (CORG).

The field indicates the Accounting entity.

- schemeName "SupplierNumber"

- TaxID 3: Organization number 2 (COR2).

Exception if Country version (MNS100.CSVN) = FR:

- TaxID 1: Organization number 1 (CORG) + Organization number 2 (COR2) concatenated without any blanks or other signs between.

Exception if Country version (MNS100.CSVN) = US:

- TaxID 1: Tax ID for supplier (TINO).

@schemeName

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the standard schemeName included:

- TaxID 1: schemeName "TaxIdentificationNumber" TaxID 2: schemeName "CountryIdentificationNumber"
- TaxID 3: schemeName "CountryIdentificationNumber"

Exception if Country version (MNS100.CSVN) = FR: - TaxID 1: schemeName "CountryIdentificationNumber"

Exception if Country version (MNS100.CSVN) = US: - TaxID 1: schemeName "TaxIdentificationNumber"

LCLTaxReport/TaxReportLine/SupplierParty/Name

For Supplier Tax:

CIDADR.SASUNM, SAADR1-ADR4 CIDMAS.IDSUNM .-; CRS620MI

CRS620MI/LstAddresses

GetBasicData

For Supplier Tax:

The field indicates the Supplier name (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' or 'ALL' to a code string indicating how SUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Name (SUNM) as mandatory information.

Alternative if generic translation not used: Name (SUNM).

(*) Comment about address information used:

- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address). Alternative if no record found: Name (SUNM) from CRS620MI.GetBasicData.
- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Alternative if no record found: Name (SUNM) from CRS620MI.GetBasicData.

LCLTaxReport/TaxReportLine/SupplierParty/Location/Name

For Supplier Tax:

CIDADR.SASUNM, SAADR1-ADR4 CIDMAS.IDSUNM.-; CRS620MI

CRS620MI/LstAddresses

GetBasicData

For Supplier Tax:

The field indicates the Supplier location name (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' or 'ALL' to a code string indicating how SUNM and ADR1-ADR4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available:

Location/Name not included as not mandatory information.

Alternative if generic translation not used: Name (SUNM).

(*) Comment about address information used:

- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address). Alternative if no record found: Name (SUNM) from CRS620MI.GetBasicData.
- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Alternative if no record found: Name (SUNM) from CRS620MI.GetBasicData.

LCLTaxReport/TaxReportLine/SupplierParty/Location/Address@type

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to "text" if address information included.

LCLTaxReport/TaxReportLine/SupplierParty/Location/Address/AddressLine

For Supplier Tax:

CIDADR.SAADR1-ADR4; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the Supplier address (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' or 'ALL' to a code string indicating how ADR1-ADR4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (ADR2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (ADR3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (ADR4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (ADR1-ADR4).

- (*) Comment about address information used:
- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address).
- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Postal address sent as "Communication/Address".

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

@sequence

For Supplier Tax:

LCLTaxReport/TaxReportLine/SupplierParty/Location/Address/CityName
For Supplier Tax:

CIDADR.SATOWN; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the City (TOWN) (*).

- (*) Comment about address information used:
- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address).
- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Postal address sent as "Communication/Address".

LCL Tax Report/Tax Report Line/Supplier Party/Location/Address/Country SubDivision Code

For Supplier Tax:

CIDADR.SAECAR; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the Area/State code (ECAR) (*).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR)).

- (*) Comment about address information used:
- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address).
- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Postal address sent as "Communication/Address".

@listID

For Supplier Tax:

-.-; -/-

For Supplier Tax:

Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements".

LCLTaxReport/TaxReportLine/SupplierParty/Location/Address/CountryCode

For Supplier Tax:

CIDADR.SACSCD; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the Country code (CSCD) (*).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

(*) Comment about address information used:

- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address).

- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Postal address sent as "Communication/Address".

@listID

For Supplier Tax:

For Supplier Tax: Set to "Countries".

LCLTaxReport/TaxReportLine/SupplierParty/Location/Address/PostalCode

For Supplier Tax:

CIDADR.SAPONO; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the Postal code (PONO) (*).

(*) Comment about address information used:

- Standard: Information retrieved from last record with Address type (ADTE) = 2 (Street address) and if not found, from last record with Address type (ADTE) = 1 (Postal address).

- Exception if Country version (MNS100.CSVN) = FR: Information retrieved from last record with Address type (ADTE) = 2 (Street address). Postal address sent as "Communication/Address".

LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address

For Supplier Tax:

-.-; -/-

@type

For Supplier Tax:

The field indicates the Communication/Address section that is only created if Country version (CSVN) = FR and information with Address type (ADTE) = 1 (Postal address) exists.

For Supplier Tax:

Set to "text" if address information included.

LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address/AddressLine

For Supplier Tax:

For Supplier Tax:

CIDADR.SAADR1-ADR4; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the Supplier address (*) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' or 'ALL' to a code string indicating how ADR1-ADR4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E not available: Address line 2 (ADR2) as mandatory information.

Alternative if generic translation used and code G not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (ADR3) as mandatory information.

Alternative if generic translation used and code J not available: Address line 4 (ADR4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (ADR1-ADR4).

(*) Information retrieved from last record with Address type (ADTE) = 1 (Postal address).

NB: Only created for Country version (CSVN) = FR.

For Supplier Tax:

Set to sequence number of the address line: values 1-4.

LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address/CityName

For Supplier Tax:

For Supplier Tax:

@sequence

CIDADR.SATOWN; CRS620MI/LstAddresses

For Supplier Tax:

The field indicates the City (TOWN) (*).

NB: Only created for Country version (CSVN) = FR.

(*) Information retrieved from last record with Address type (ADTE) = 1 (Postal address) LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address/CountrySubDivisionCode For Supplier Tax: For Supplier Tax: CIDADR.SAECAR; CRS620MI/LstAddresses The field indicates the Area/State code (ECAR) (*). NB: Only created for Country version (CSVN) = FR. Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to "Country code-Area/ state" (CSCD-ECAR)). (*) Information retrieved from last record with Address type (ADTE) = 1 (Postal address). @listID For Supplier Tax: For Supplier Tax: - . - : -/-Set to general value: "Country Sub-divisions"; for ECAR = "US": "US States"; for ECAR = "CA": "Canadian Provinces"; for ECAR = "FR": "France - Departements" LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address/CountryCode For Supplier Tax: For Supplier Tax: CIDADR.SACSCD; CRS620MI/LstAddresses The field indicates the Country code (CSCD) (*). NB: Only created for Country version (CSVN) = FR. Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1. (*) Information retrieved from last record with Address type (ADTE) = 1 (Postal address). @listID For Supplier Tax: For Supplier Tax: Set to "Countries" LCLTaxReport/TaxReportLine/SupplierParty/Communication/Address/PostalCode For Supplier Tax: For Supplier Tax: CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the Postal code (PONO) (*). NB: Only created for Country version (CSVN) = FR. (*) Information retrieved from last record with Address type (ADTE) = (Postal address) LCLTaxReport/TaxReportLine/SupplierParty/UserArea For Supplier Tax: For Supplier Tax: FTAXR2.R2AVCD The field indicates the Activity description of the supplier that is only CSYTAB.CTTX40.-; APS430MI created for Country version (CSVN) = FR: CRS175MI/LstTaxTotSupSer - NameValue = @name="lcl.APECode and @listID="APE": Set to GetGeneralCode 'Not used'. - Description: Activity description (TX40 from CRS175MI.GetGeneralCode (*)) of Activity code (AVCD from APS430MI.LstTaxTotSupSer). NB: If Activity code (AVCD) is missing, no UserArea must be created. Ex: <UserArea> <Property> <NameValue name="Icl.APECode" listID="APE">Not used</ <Description>Consultant/Description> </Property> </UserArea> (*) CRS175MI with: - CONO = APS430MI.LstTaxTotSupSer.CONO - DIVI = blank - STCO = 'AVCD' - STKY = APS430MI.LstTaxTotSupSer.ACVD LCLTaxReport/TaxReportLine/FATCAIndicator For Supplier Tax: For Supplier Tax: FTAXR2.R2AVCD; APS430MI/LstTaxTotSupSer The field indicates the Activity code (AVCD) = "FTC": Set to 'true', otherwise 'false'. NB: Only created for Country version (CSVN) = US. LCLTaxReport/TaxReportLine/TotalTaxBasisAmount For VAT Periodic: For VAT Periodic: FQRADF.EAESFV The field indicates the TotalTaxBasisAmount (AC02) depending on FVTUDL.V2AC02.; TXS035MI Report type (1): TXS100MI/GetAddField - Report type 1: Amount per line (record). See comment (2) below for

Let\/ATLlearDef

reverse sign.

- (1) Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 2 must be used.
- (2) Reverse sign depending on format (3) used:
- If format (ESFV) = VAT100 or MTD: The amount sign must be reversed for records having the following Line ID (UK01): 1, 2, 3, 6 and 8
- (3) Format from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 539 and base country (FBSC) from report header.

For VAT Periodic:

The field indicates the currency code (CUCD) from Report header.

Generic translation is used to translate CUCD according to ISO 4217.

@currencyID

For VAT Periodic:

FVATHE.VHCUCD; TXS100MI/GetHeadInfo

LCLTaxReport/TaxReportLine/TotalTaxAuthorityAmount

For VAT Periodic: FQRADF.EAESFV

FVTUDL.V2AC03.; TXS035MI TXS100MI/GetAddField LstVATUserDef For VAT Periodic:

The field indicates the TotalTaxAuthorityAmount (AC03) depending on Report type (1):

- Report type 1: Amount per line (record). See comment (2) below for reverse sign.
- (1) Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 2 must be used.
- (2) Reverse sign depending on format (3) used:
- If format (ESFV) = VAT100 or MTD: The amount sign must be reversed for records having the following Line ID (UK01): 1, 2, 3, 6 and 8.
- (3) Format from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 539 and base country (FBSC) from report header.

For VAT Periodic:

The field indicates the currency code (CUCD) from Report header.

Generic translation is used to translate CUCD according to ISO 4217.

@currencyID

For VAT Periodic:

FVATHE.VHCUCD; TXS100MI/GetHeadInfo

LCLTaxReport/TaxReportLine/TotalAmount

For VAT Periodic: FQRADF.EAESFV

FVTUDL.V2AC01.; TXS035MI TXS100MI/GetAddField LstVATUserDef For VAT Periodic

The field indicates the TotalAmount (AC01) depending on Report type (1):

- Report type 1: Amount per line (record). See comment (2) below for reverse sign.
- (1) Report type from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 521 and base country (FBSC) from report header. If field (ESAF) = 521 not found or other value than 1, 2 and 3 used, default report type 2 must be used.
- (2) Reverse sign depending on format (3) used:
- If format (ESFV) = VAT100 or MTD: The amount sign must be reversed for records having the following Line ID (UK01): 1, 2, 3, 6 and 8
- (3) Format from report field (ESFV in TXS035) for type TYPE) = 2, field (ESAF) = 539 and base country (FBSC) from report header.

For VAT Periodic:

The field indicates the currency code (CUCD) from Report header.

Generic translation is used to translate CUCD according to ISO 4217.

@currencyID

For VAT Periodic:

FVATHE.VHCUCD; TXS100MI/GetHeadInfo

LCLTaxReport/TaxReportLine/TransactionSummary

For Supplier Tax:

-.-; -/-

For Supplier Tax:

The field indicates the TransactionSummary section that is created depending on Country version (MNS100.CSVN):

If CSVN = FR

- APS430MI.LstTaxTotSupSer (several records per supplier returned): Create one TransactionSummary per Box ID (BOXI), must be summarized in case several records returned with the same Box ID.

LOLIUXICPOIT	
	If CSVN = US: - APS430MI.LstTaxTotSupSer (one record per supplier returned): Create one TransactionSummary per Amount field (PA01-PA08, PA10 and PA13-PA14) with amount not equal zero.
	For VAT Periodic: Design for report type 2 and 3 to be added.
	Details must be clarified with Local.ly how amounts must be sent (standard to be found including use of @type that require BE changes).
	Solution for reverse amount on line level required (BE changes for setting and handling in MI-transaction (new transaction or additional fields). This will also affect amount elements on levels above.
LCLTaxReport/TaxReportLine/TransactionSummary/Type	,
For Supplier Tax: CSYTAB.CTBOXI FTAXR2.R2PA01-PA14; APS430MI/LstTaxTotSupSer	For Supplier Tax: The field indicates the type required for US and FR, created depending on Country version (MNS100.CSVN):
	If CSVN = FR: - @type set to Box identity (field BOXI).
	If CSVN = US: - @type set to 1-8 for Payment amount field PA01-PA08 @type set to A for Payment amount field PA10 @type set to B-C for Payment amount field PA13-PA14.
LCLTaxReport/TaxReportLine/TransactionSummary/Amount	
For Supplier Tax: FTAXR2.R2PYAM, R2PA01-PA14; APS430MI/LstTaxTotSupSer	For Supplier Tax: The field indicates the amount to be reported and is created depending on Country version (MNS100.CSVN): - If CSVN = FR: Amount from field PYAM If CSVN = US: Amount from field PA01-PA08, PA10 and PA13-
	PA14.
@currencyID For Supplier Tax: CMNDIV.CCLOCD; MNS100MI/GetBasicData	For Supplier Tax: The field indicates the Local curreny (LOCD) of the reporting division.
	Generic translation is used to translate CUCD (LOCD) according to ISO 4217.
LCLTaxReport/TaxReportLine/NumberOfTransactions	For VAT Periodic: The field indicates the number of transactions.
LCLTaxReport/TaxReportLine/TaxReportLineDetail	
LOLI ANTOPOR LINES I ANTOPOR LINES CLAIM	For VAT Periodic: Created in case report type 3 selected.
	Must be analyzed and discussed with Christina if we should use detail table where invoice details are stored or if template must be defined for key values with Invoice number etc.
@sequence	•
	For VAT Periodic: The field indicates the counter of line detail.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/TransactionID	For VAT Periodic: The field indicates the invoice number.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/EffectiveDateTin	me
	For VAT Periodic: The field indicates the Invoice date.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/PostDateTime	
	For VAT Periodic: The field indicates the accounting date.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/CountryOfOrigin	_
	For VAT Periodic: The field indicates the From/To country.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/Tax	For VAT Periodic: Design for report type 2 and 3 to be added.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/Tax/ID	For VAT Periodic: The field indicates the VAT code.
LOUTSUBSUS SHITTER BOOK AND TO SHITTER BOOK AND TO SHITTER SHITTER BOOK AND THE SHITTER SHITTE	THE HEID HIDICALES THE VAT CODE.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/Correction	For VAT Periodic: Details must be checked.
LCLTaxReport/TaxReportLine/TaxReportLineDetail/Correction/Trans	
LOL LAXIVEPOLU LAXIVEPOLILINE/ LAXIVEPOLILINEDELAN/CONTECTION/ LIANSACTIONID	

For VAT Periodic:
The field indicates the original invoice number (object &OCIN stored as alpha field 3 - to be decided).
- Used in ES-340.

LCLTradeStatistics

LCLTradeStatistics/TradeStatisticsHeader/DocumentID/ID

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHESSU; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

CTXTSH.CHVRNL; TXS300MI/GetHead

@accountingEntity For Intrastat Extrastat:

CMNDIV.CCCONO, CCDIVI; MNS100MI/GetBasicData

@variationID

For Intrastat Extrastat:

@lid

For Intrastat Extrastat:

-.-; -/-

LCLTradeStatistics/TradeStatisticsHeader/LastModificationDateTime

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHLMDT; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

CTXTSH.CHLMDT; TXS300MI/GetHead

The field indicates the Proposal number from report header (TXS130/

B).

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the TAX declaration number used of the acutal run (e.g report number), setup in CRS165 TX/0 (tax declaration number).

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the accounting entity (CONO + DIVI) without

schemeName from MNS100.

For Intrastat Extrastat:

Set to CONO + DIVI without schemeName. From MNS100

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Variation ID from the manifest

(getManifestInfo('com:ionVariationId')).

For Intrastat Extrastat:

Set to (getManifestInfo('com:ionVariationId')) from the manifest.

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the LID from the system (IONToolbox.getSenderLogicalID(myMap)).

For Intrastat Extrastat:

Set to (IONToolbox.getSenderLogicalID(myMap)) from the system.

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Last modification date (LMDT) from

GetHeadInfo time set to 00:00:00 as it is not given if LMDT is empty -

>Timestamp from the Event (LMTS).

For Intrastat Extrastat:

The field indicates the Last modification date from

TXS300MI GetHead Last modification date (LMDT) time set to

00:00:== since the this information is not stored in M3

LCLTradeStatistics/TradeStatisticsHeader/LastModificationPerson/IDs/ID

For Intrastat Extrastat:

For EU Sales Purchase:

FQRHEA.EHCHID; TXS130MI /GetHeadInfo

For Intrastat Extrastat:

CTXTSH.CHCHID; TXS300MI + MNS150/GetHead, GetUserData

@accountingEntity

For Intrastat Extrastat: For EU Sales Purchase:

CMNDIV.CMCONO+CMDIVI; MNS100/GetBasicData

For Intrastat Extrastat:

CMNDIV.CCCONO, CCDIVI; MNS100/GetBasicData

For EU Sales Purchase: The field indicates the User-ID (CHID) from report header.

For Intrastat Extrastat:

For Intrastat Extrastat: The field indicates the User-ID from TXS300MI GetHead

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Accounting entity (Company and division) from

MNS100

For Intrastat Extrastat:

The field indicates the Company and division from

MNS100MI GetBasicData

LCLTradeStatistics/TradeStatisticsHeader/LastModificationPerson/Name

For Intrastat Extrastat: For EU Sales Purchase:

CMNUSR.JUNAME; MNS150/GetUserData

For Intrastat Extrastat:

CTXTSH.CHRENM; TXS300MI/GetHead

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Name (NAME) of the user that issued the report (taken from MNS150) via CHID of the report header).

For Intrastat Extrastat:

The field indicates the Contact person for

TXS300MI GetHead RENM

LCLTradeStatistics/TradeStatisticsHeader/DocumentDateTime

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHRGDT/EHRGTM; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

CTXTSH.CHRGDT, CHRGTM; TXS300MI/GetHead

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Date when the report was issued, taken from

the report head transaction

For Intrastat Extrastat:

LCLTradeStatistics/TradeStatisticsHeader/Status/Code

For Intrastat Extrastat: For EU Sales Purchase:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstaseCountry

The field indicates the when the report was issued, talken from the report head transaction

For Intrastat Extrastat:

For EU Sales Purchase:

Set to 'Open' or 'Draft' depending on if a Productive or Test report is sent:

- If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 1: 'Draft'.
- If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 0 or if (ESAF) 522 is missing: 'Open'
- (*) Value in TXS035 for type (TYPE) = 1 and base country (BSCD) from report header.

Note:

- actionCode='Add' used for both new report and copy.
- actionCode='Replace' to be added when copy flag (CPPL) in MBM initiator has been clarified and corrected (now always set to 0 even of copy).

For Intrastat Extrastat:

Set to 'Open' or 'Draft' depending on if a Productive or Test report is sent:

- If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 1: 'Draff'
- If additional field (ESAF) = 522 exists (*) and value (ESFV) set to 0 or if (ESAF) 522 is missing: 'Open'
- (*) Value in TXS035 for type (TYPE) = 3 and base country (BSCD) from report header.

Note:

- actionCode='Add' used for new report.
- actionCode='Replace' used for resend report in CRS600 (MessageCopy = 1 in MBMEvent).

LCLTradeStatistics/TradeStatisticsHeader/ReportType

For Intrastat Extrastat: For EU Sales Purchase:

-.-; -/-

For Intrastat Extrastat: CTXTSH.CHECTP

CTXTSD.CDECTP.-; TXS300MI/GetHead/LstLine

For Intrastat Extrastat: For EU Sales Purchase: Set to constant 'EUSales'.

For Intrastat Extrastat:

Set to 'Intrastat' if ECTP = 1 or 2 and to 'Extrastat' if ECTP = 4 or 5.

NB: The value is retrieved from the first line (TXS300MI.LstLine) if not indicated on the header (that is if TXS300MI.GetHead.ECTP equal 0).

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/PartyIDs/ID

For Intrastat Extrastat:
For EU Sales Purchase:
FQRHEA.EHCONO,EHDIVI
FQRADF.EAESFV.-; TXS130MI/
TXS035MI/GetHeadInfo/
LstBaseCountry

For Intrastat Extrastat:

CMNDIV.CCCONO, CCDIVI FQRADF.EAESFV.-; MNS100MI/

TXS035MI/GetBasicData/

LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the ID (external or internal) of the initiating party:

- If report field (ESAF) = 514 for the base country (BSCD) in report header and type (TYPE) = 1 exist: External ID from (ESFV) in)TXS035) and if not existing:
- Internal ID Company (CONO) and Division (DIVI).

For Intrastat Extrastat:

The field indicates the ID (external or internal) of the initiating party:

- If report field (ESAF) = 514 for the base country (BSCD) in report header and type (TYPE) = 3 exist: External ID from (ESFV) in (TXS035) and if not existing:
- Internal ID Company (CONO) and Division (DIVI).

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/PartyIDs/TaxID

For Intrastat Extrastat:

For EU Sales Purchase: FQRHEA.EHOVRN,EHVRNL CMNDIV.CMCORG,CMCOR2

FQRADF.EAESFV.-; TXS130MI/MNS100MI/TXS035MI/GetHeadInfo/GetBasicData/LstBaseCountry

For Intrastat Extrastat:

CMNDIV.CCVRNL, CCCORG, CCCOR2 CTXTSH.CHVRIN.-; MNS100MI/TXS300MI/GetBasicData/GetHead

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the TaxID's included as standard depending on the value for 'Type of TaxID' defined as report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 526 and base country (BSCD) of the report header (see (*) below).

- TaxID 1: VAT Registration number 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 509 and base country (BSCD) of the report header and if not defined from 2) VAT registration number (OVR2) from Report header (ISO country code added in MI so no adjustment needed).
- TaxID 2: Tax declaration number from 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 510 and base country (BSCD) of the report header and if not defined from 2) Report header (VRNL).

- TaxID 3: Organization number 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 517 and base country (BSCD) of the report header and if not defined from 2) Organization number 1 (CORG) of the company from (MNS100).
- TaxID 4: Organization number 2 (COR2) of the company from (MNS100).
- (*) If report field 526-Type of TaxID set to:
- 1: Only TaxID 2 is included.
- 2: Only TaxID 1 is included.
- 3: Only TaxID 3 is included.
- 4: Only TaxID 4 is included.
- 0 or other value (not 1-4) or not defined: All TaxIDs are included in order TaxID 1, TaxID 2, TaxID 3 and TaxID 4.

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: VAT Registration number (OVR2) from Report header (ISO country code added in MI so no adjustment needed).
- TaxID 2: Tax declaration number from Report header (VRNL). NB: No other TaxID's included.
- (*) If report field 526-Type of TaxID set to:
- 1: Only TaxID 2 is included.
- 2: Only TaxID 1 is included.
- 0 or other value (not 1-2) or not defined: All TaxIDs are included in order TaxID 1 and TaxID 2.
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

The field indicates the following TaxID's that are included as standard:

- TaxID 1: VAT Registration number internal (VRI2) from Report header (ISO country code added in MI so no adjustment needed).
 TaxID 2: Tax declaration number from 1) Report field (ESFV in
- TXS035) for type TYPE) = 1, field (ESAF) = 510 and base country (BSCD) of the report header and if not defined from 2) the division (MNS100 and VRNL).
- TaxID 3: Organization number 1 (CORG) of the company from (MNS100).
- TaxID 4: Organization number 2 (COR2) of the company from (MNS100).

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: VAT Registration number internal (VRI2) from Report header (ISO country code added in M3BE so no adjustment needed).
 - TaxID 2: Tax declaration number from the division (MNS100 and VRNL).
- NB: No other TaxID's included
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

For EU Sales Purchase:

Set to the following schemeNames as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'TaxDeclarationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'
- TaxID 4: schemeName 'CountryIdentificationNumber'

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

For Intrastat Extrastat:

The field indicates the the following schemeNames that are included as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'TaxDeclarationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'
- TaxID 4: schemeName 'CountryIdentificationNumber'

@schemeID

For Intrastat Extrastat: For EU Sales Purchase:

-.-; -/-

@schemeName

For Intrastat Extrastat: For Intrastat Extrastat:

-.-; -/-

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Name

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCONM, EHCOA1-EHCOA4; TXS130MI/GetHeadInfo

For Intrastat Extrastat:
OSUSAD.OPCONM, OPCOA1-COA4
OCUSMA.OKCONM, OKCOA1-COA4

CMNDIV.CCCONM, CCCOA1-COA4 .-; TXS300MI/GetHeadAddress

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

For Intrastat Extrastat:

The field indicates the Company name from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Name

For Intrastat Extrastat:

For EU Sales Purchase:

FQRHEA.EHCONM, EHCOA1-EHCOA4; TXS130MI/GetHeadInfo

For Intrastat Extrastat: OSUSAD.OPCONM, OPCOA1-COA4

OCUSMA.OKCONM, OKCOA1-COA4

CMNDIV.CCCONM, CCCOA1-COA4 .-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

For Intrastat Extrastat:

The field indicates the Location name from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

${\it LCLT rade Statistics/Trade Statistics Header/Initiating Party/Location/Address} \\ @type$

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to 'text' if address information included

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Address/AddressLine

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCOA1, EHCOA2,EHCOA3,EHCOA4; TXS130MI/ GetHeadInfo

For Intrastat Extrastat: OSUSAD.OPCOA1-COA4 OCUSMA.OKCOA1-COA4

CMNDIV.CCCOA1-COA4.-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E or F not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code I or J not available: Address line 4 (COA4) included.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For Intrastat Extrastat:

The field indicates the Company address from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used.

Street and Building number (sequence 1 and if needed 2): - Code E and F indicate 'Street and Building number

Alternative if generic translation used and code E or F not available: Company address line 2 (COA2) as mandatory information.

Postal code and City (sequence 3):
- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Country (sequence 4):

- Code I and J indicate 'Country'

Alternative if generic translation used and code I or J not available: Address line 4 (COA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4.

@sequence

For Intrastat Extrastat:

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Address/CityName

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHTOWN; TXS130MI/GetHeadInfo

For Intrastat Extrastat: OCUSAD.OPTOWN OCUSMA.OKTOWN

CMNDIV.CCTOWN.-; TXS300MI/GetHeadAddress

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the City (TOWN) from the report header.

For Intrastat Extrastat:

The field indicates the City (TOWN) from the report header MI if available in M3 (also sent as part of AddressLine @SequenceNumber

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Address/CountrySubDivisionCode

For Intrastat Extrastat: For EU Sales Purchase: FQRHEA.EHECAR FQRADF.EAESFV .-; TXS130MI / TXS035MI/GetHeadInfo /

LstBaseCountry

For Intrastat Extrastat: OCUSAD.OPECAR OCUSMA.OKECAR

CMNDIV.CCECAR .-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the State (ECAR) from the report header.

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = CZ in report header:

- If report field (ESAF) = 100 for type (TYPE) = 1 exist: additional field value for 'Municipality' from (ESFV) in (TXS035).

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = PL in report header:

- If report field (ESAF) = 020 for type (TYPE) = 1 exist: additional field value for 'Province' ('State') from (ESFV) in (TXS035).
- If report field (ESAF) = 030 for type (TYPE) = 1 exist: additional field value for 'District' from (ESFV) in (TXS035).
- If report field (ESAF) = 040 for type (TYPE) = 1 exist: additional field value for 'Community' ('Municipality') from (ESFV) in (TXS035).

For Intrastat Extrastat:

The field indicates the Area/State code (ECAR) from the report header MI.

Generic translation (blank division) is used to translate ECAR

@listID

For Intrastat Extrastat:

-.-; -/-

according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the

Base country (BSCD) = CZ in report header:

- If report field (ESAF) = 100 for type (TYPE) = 1 exist:

@listID='Municipalities'.

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the

Base country (BSCD) = PL in report header:

- If report field (ESAF) = 020 for type (TYPE) = 1 exist: @listID='States'

- If report field (ESAF) = 030 for type (TYPE) = 1 exist:

@listID='Districts'.

- If report field (ESAF) = 040 for type (TYPE) = 1 exist:

@listID='Municipalities'.

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

according to ISO 3166-1.

For Intrastat Extrastat:

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Address/CountryCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRHEA.EHCSCD; TXS130MI/GetHeadInfo The field indicates the Country code (CSCD) from report header.

For Intrastat Extrastat: OCUSAD.OPCSCD

OCUSMA.OKCSCD CMNDIV.CCCSCD.-; TXS300MI/GetHeadAddress

The field indicates the Country code (CSCD) from the report header

Generic translation is used to translate CSCD to alpha-2 country code

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: Set to 'Countries'

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Location/Address/PostalCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRHEA.EHPONO; TXS130MI/GetHeadInfo The field indicates the Postal code (PONO) from report header.

For Intrastat Extrastat: For Intrastat Extrastat:

OCUSAD.OPPONO The field indicates the Postal code (PONO) from the report header MI

OCUSMA.OKPONO if available in M3 (also sent as part of AddressLine

CMNDIV.CCPONO.-; TXS300MI/GetHeadAddress @SequenceNumber = 3)

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/ID

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCNPE; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

FQRADF.EAESFV; TXS300MI/GetHeadAddress @accountingEntity

For Intrastat Extrastat:

For Intrastat Extrastat:

CTXTSH.CCCONO, CCDIVI; TXS300MI/GetHeadAddress

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Contact ID (CNPE) from the report header.

For Intrastat Extrastat:

The field indicates the Contact ID (CNPE) from the report header MI.

For Intrastat Extrastat: For Intrastat Extrastat:

The field indicates the Company and division from the report header

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Name

For Intrastat Extrastat: For EU Sales Purchase:

CCUCON.CCTX50

CMNDIV.CMOREF .-; CRS618MI/MNS100/Get/GetBasicData

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Contact name (TX50) from (CRS618) for the

contact ID (CNPE) from the report header.

For Intrastat Extrastat: CCUCON.XXTX50

CMNDIV.CCOREF.-; CRS618MI/MNS100MI/Get/GetBasicData

If the Contact ID (CNPE) of the report header is missing, Contact

name from Our reference (OREF) in (MNS100).

For Intrastat Extrastat:

The field indicates the Contact name (TX50) from (CRS618) for the

contact ID (CNPE) from the report header MI.

If the Contact ID (CNPE) of the report header MI is missing, Contact name from Our reference (OREF) in (MNS100)

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication

@seauence

For Intrastat Extrastat: For Intrastat Extrastat:

-.-: -/-For EU Sales Purchase:

Set to sequence number of contact/communication.

For Intrastat Extrastat:

The field indicates the Counter set in mapping depending on

information included.

@preferredIndicator

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'false'

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/ChannelCode For Intrastat Extrastat: For Intrastat Extrastat:

For EU Sales Purchase: -.-: -/-

Set to 'Phone' in case of 'DailNumber', to 'EMail' in case of 'URI' contains email address or to 'Website' in case of URI contains web

address

For Intrastat Extrastat:

The field indicates the Channel code.

- Set to 'Phone' for PHNO, PHN2 and TFNO (DailNumber). - Set to 'Email' for EMAL (when URI contains email address).

- Set to 'WebSite' for EMAL (when URI contains web site).

@listID

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'Communication Channels'. -.-; -/-

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/UseCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: -.-; -/-

Set to 'Office' for PHNO and PHN2 in case of 'DailNumber'.

Set to 'Fax' for TFNO in case of 'DailNumber'. Set to 'Office' for EMAL if URI contains email adress.

For Intrastat Extrastat: The field indicates the Use code.

- Set to 'Office' for PHNO and PHN2 (DailNumber).

- Set to 'Fax' for TFNO (DailNumber).

- Set to 'Office' for EMAL and ESFV=URI (URI).

@listID

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'Communication Use Codes'

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/DialNumber For Intrastat Extrastat:

For EU Sales Purchase: CCUCON.CCPHNO,CCPHN2

FQRHEA.EHPHNO,EHPHN2, EHTFNO.-; CRS618MI/TXS130MI/Get/

GetHeadInfo

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618) and the and Fax

number (TFNO) from the report header.

For Intrastat Extrastat: CCUCON.CCPHNO, CCPHN2

OCUSAD.OPPHNO, OPTFNO

OCUSMA OKPHNO, OKPHN2, OKTFNO

CMNDIV.CCPHNO, CCPHN2, CCTFNO.-; CRS618MI

TXS300MI/Get GetHeadAddress If the Contact ID (CNPE) of the report header is missing, Telephone number 1 (PHNO), Telephone number 2 (PHN2) and Fax number

(TFNO) from report header.

For Intrastat Extrastat:

The field indicates the Telephone number 1 (PHNO) and Telephone number 2 (PHN2) of the contact in (CRS618) and if the Contact ID (CNPE) of the report header is missing, from the report header MI.

Faxnumber (TFNO) from the report header MI.

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address

@type

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'text' if address information included -.-; -/-

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address/AddressLine

For Intrastat Extrastat: For Intrastat Extrastat: CCUCON.CCCUA1-CCCUA4; CRS618MI/Get

For EU Sales Purchase:

The field indicates the Address of the contact person of the company

from (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or

'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate

'Country' (see the integration guide for Local.ly for description of setup)

Alternative if generic translation used and code E or F not available: Address line 2 (CUA2).

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) not included as not mandatory information.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

The field indicates the Address of company's contact person in (CRS618) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

- Code E and F indicate 'Street and Building number,

Alternative if generic translation used and code E or F not available: Address line 2 (CUA2) as mandatory information.

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3) as mandatory information.

Country (sequence 4):

- Code I and J indicate 'Country'.

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4.

For Intrastat Extrastat:

For EU Sales Purchase:

Set to sequence number of the address line: values 1-4

@sequence

For Intrastat Extrastat: For Intrastat Extrastat:

..-; -/-@languageID

For Intrastat Extrastat: For EU Sales Purchase:

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address/CityName

For Intrastat Extrastat:

CCUCON.CCTOWN; CRS618MI/Get

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the city of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

For Intrastat Extrastat:

The field indicates the City (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address/CountrySubDivisionCode

For Intrastat Extrastat:

CCUCON.CCECAR; CRS618MI/Get

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the area/state of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR).

For Intrastat Extrastat:

The field indicates the Area/State of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat: For Intrastat Extrastat:

For EU Sales Purchase: .-; -/-Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US

States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR' :

'France - Departements'

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address/CountryCode

For Intrastat Extrastat: For Intrastat Extrastat: CCUCON.CCCSCD; CRS618MI/Get For EU Sales Purchase:

The field indicates a country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

For Intrastat Extrastat:

The field indicates the country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: -.-; -/-Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Address/PostalCode

For Intrastat Extrastat: For Intrastat Extrastat: CCUCON.CCPONO; CRS618MI/Get For EU Sales Purchase:

The field indicates a postal code of the contact in (CRS618).

For Intrastat Extrastat:

The field indicates the postal code of the contact in (CRS618).

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/URI

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

CCUCON.CCEMAL The field indicates an e-mail address of the contact in (CRS618).

FQRHEA.EHEMA8, EHURL8.-; CRS618MI/TXS130MI/Get/GetHeadInfo

For Intrastat Extrastat:

CCUCON.CCEMAL FQRADF.EAESFV.-; CRS618MI/TXS300MI/Get/GetHeadAddress If the Contact ID (CNPE) of the report header is missing, retreived

from E-mail address (EMA8) from the report header.

URL address (URLB) from the report header if existing.

For Intrastat Extrastat:

The field indicates the e-mail address of the contact in (CRS618).

If the Contact ID (CNPE) of the report header MI is missing, retreived

from E-mail address (EMA8) from the report header MI.

URL address (URLB) from the report header MI if existing.

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/HTMLPreferredIndicator

For Intrastat Extrastat: For Intrastat Extrastat:

For EU Sales Purchase: -.-; -/-Set to constant = 'true'.

For Intrastat Extrastat:

Set to constant = 'true' in case of ChannelCode = Email or WebSite

(URI)

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Preference/Sequence

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: Set to constant = '1'. -.-: -/-

LCLTradeStatistics/TradeStatisticsHeader/InitiatingParty/Contact/Communication/Preference/Indicator

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: Set to 'false'.

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/PartyIDs/ID

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the External ID of the Recipient (receiving) party from report field (ESFV in TXS035) for type TYPE) = 1 and base

country (BSCD) from report header in following order: - External ID from field (ESAF) = 563, if not existing from

- Internal customer ID from field (ESAF) = 564

NB: Recipient party is only created If either report field (ESAF) 563 or

564 found.

For Intrastat Extrastat:

The field indicates the ID of the Recipient (receiving) party from report field (ESFV in TXS035) for type TYPE) = 3 and base country (BSCD) from report header in following order:

- External ID from field (ESAF) = 563, if not existing from
- Internal customer ID from field (ESAF) = 564

NB: Recipient party is only created If either report field (ESAF) 563 or 564 found.

- If only 563 existing, only PartyIDs/ID created.
- If 564 existing, Name and Location information created.

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Name

For Intrastat Extrastat: For EU Sales Purchase:

OCUSMA.OKCUNM: CRS610MI/GetBasicData

For Intrastat Extrastat:

OCUSMA.OKCUNM, OKCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat:

The field indicates the Name of the internal customer (recipient) from (CRS610) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code A and B indicate 'Customer name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM).

Alternative if generic translation not used: Customer name (CUNM).

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Name

For Intrastat Extrastat:

For EU Sales Purchase:

OCUSMA.OKCUNM,OKCUA1,OKCUA2,OKCUA3,OKCUA4; CRS610MI/(recipient) from (CRS610) based on the generic translation

GetBasicData

For Intrastat Extrastat:

OCUSMA.OKCUNM, OKCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat:

The field indicates the Location name of the internal customer (recipient) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address

@type

-.-; -/-

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to 'text' if address information included.

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/AttentionOfName

For Intrastat Extrastat:

OCUSMA.OKYREF; CRS610MI/GetBasicData

For Intrastat Extrastat:

The field indicates the Your reference (YREF) of the internal customer (recipient) from (CRS610).

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/AddressLine

For Intrastat Extrastat:

For EU Sales Purchase:

OCUSMA.OKCUA1,OKCUA2,OKCUA3,OKCUA4; CRS610MI/

GetBasicData

For Intrastat Extrastat:

OCUSMA.OKCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Address of the internal customer (recipient) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E or F not available: Customer address line 2 (CUA2).

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (CUA3).

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

Alternative if generic translation not used: Customer address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

The field indicates the Address of the internal customer (recipient) from (CRS610) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

- Code E and F indicate 'Street and Building number.

Alternative if generic translation used and code E or F not available: Customer address line 2 (CUA2).

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (CUA3).

Country (sequence 4):

- Code I and J indicate 'Country'.

Alternative if generic translation used and code I or J not available:

Address line 4 (CUA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Customer address line 1-4

(CUA1-CUA4).

@sequence

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/CityName

For Intrastat Extrastat:

For Intrastat Extrastat: OCUSMA.OKTOWN; CRS610MI/GetBasicDAta For EU Sales Purchase:

The field indicates the City name (TOWN) of the internal customer (recipient) from (CRS610) if available in M3 (also sent as part of

AddressLine @SequenceNumber = 3).

For Intrastat Extrastat:

For Intrastat Extrastat:

The field indicates the City (TOWN) of the internal customer (recipient) from (CRS610) if available in M3 (also sent as part of

AddressLine @SequenceNumber = 3)

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/CountrySubDivisionCode

For Intrastat Extrastat: OCUSMA.OKECAR; CRS610MI/GetBasicDAta

The field indicates the Area/State code (ECAR) of the internal

customer (recipient) from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

@listID

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'.

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/CountryCode

For Intrastat Extrastat:

For EU Sales Purchase: OCUSMA.OKCSCD

FQRHEA.EHBSCD.-; CRS610MI TXS130MI/GetBasicData

TXS300MI/GetBasicData

GetHeadInfo

GetHead

@listID

-.-: -/-

For Intrastat Extrastat:

The field indicates the Country code (CSCD) of the internal customer

(recipient) from (CRS610).

If no internal customer (recipient) exist (= field 564 missing or customer not found), the field is set to the Base country (BSCD) for

the report.

For Intrastat Extrastat: OCUSMA.OKCSCD

Generic translation is used to translate CSCD to alpha-2 country code CTXTSH.CHBSCD.-; CRS610MI

according to ISO 3166-1.

Can be used as additional element in the detection setup for GEMS in

case declaration in other country (fiscal representative used) must be

created for the same accounting entity (that is CONO and DIVI).

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/Location/Address/PostalCode

For Intrastat Extrastat: For Intrastat Extrastat:

The field indicates the Postal code (PONO) of the internal customer OCUSMA.OKPONO; CRS610MI/GetBasicData

(recipient) from (CRS610) if available in M3 (also sent as part of

AddressLine @SequenceNumber = 3).

LCLTradeStatistics/TradeStatisticsHeader/RecipientParty/BranchParty/PartyIDs/ID

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the External branch ID of the Recipient (receiving) party from report field (ESFV in TXS035) for type TYPE) = 1 and base

country (BSCD) from report header in following order:

- External Branch ID from field (ESAF) = 566.

For Intrastat Extrastat:

The field indicates the Branch ID of the Recipient (receiving) party from report field (ESFV in TXS035) for type TYPE) = 3 and base country (BSCD) from report header in following order:
- External Branch ID from field (ESAF) = 566

LCLTradeStatistics/TradeStatisticsHeader/Party @role

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the type of party:

- @role = 'Agent' if report field (ESAF) = 570, 571, 572 or 573 found in (TXS035) for type TYPE) = 1 and base country (BSCD) from report header.
- @role = 'SoftwareVendor' if report field (ESAF) = 577 (*) found in (TXS035) for type TYPE) = 1 and base country (BSCD) from report header.
- (*) Additional handling for field 575, 576 and 578 to be implemented later if requested.

For Intrastat Extrastat:

The field indicates the type of party:

- @role = 'Agent' if report field (ESAF) = 570, 571, 572 or 573 found in (TXS035) for type TYPE) = 3 and base country (BSCD) from report header

LCLTradeStatistics/TradeStatisticsHeader/Party/PartyIDs/ID

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the ID of the External party from report field (ESFV in TXS035) for type TYPE) = 1 and base country (BSCD) from report header in following order:

For Party with @role = 'Agent':

- External ID from field (ESAF) = 572, if not existing from
- Internal customer ID from field (ESAF) = 573

For Party with @role = 'SoftwareVendor':

- External ID from field (ESAF) = 577.

For Intrastat Extrastat:

The field indicates the ID of the External party from report field (ESFV in TXS035) for type TYPE) = 3 and base country (BSCD) from report header in following order:

- External ID from field (ESAF) = 572, if not existing from
- Internal customer ID from field (ESAF) = 573

LCLTradeStatistics/TradeStatisticsHeader/Party/PartyIDs/TaxID

For Intrastat Extrastat: For EU Sales Purchase:

OCUSMA.VRNO,

CORG, COR2; CRS610MI/GetFinancial

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the TaxIDs of the External party retrieved via the Internal customer ID from report field 573 for @role = 'Agent' (ESFV in TXS035) for type TYPE) = 1 and base country (BSCD) from report header:

The field indicates the TaxID's included as standard:

- TaxID 1: VAT Registration number (VRNO) (must be entered in correct format including prefix if applicable).
- TaxID 2: Organization number 1 (CORG).
- TaxID 3: Organization number 2 (COR2).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

For EU Sales Purchase:

Set to the following schemeNames as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = LU (*):

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- TaxID 3: schemeName 'TaxDeclarationNumber'

(*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

@schemeName

For Intrastat Extrastat: For EU Sales Purchase:

-.-; -/-

NB: The information is currently only included for Party with @role = 'Agent'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Name

For Intrastat Extrastat:

For EU Sales Purchase:

OCUSMA.OKCUNM,OKCUA1,OKCUA2,OKCUA3,OKCUA4; CRS610MI/The field indicates the Name of the internal customer (external party)

GetBasicData

from (CRS610) based on the generic translation

For Intrastat Extrastat:

OCUSMA.OKCUNM, OKCCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat: For EU Sales Purchase:

I/The field indicates the Name of the internal customer (external party from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code A and B indicate 'Customer name' (see the

integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM).

Alternative if generic translation not used: Customer name (CUNM).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Name of the internal customer (external party) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code A and B indicate 'Customer name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM).

Alternative if generic translation not used: Customer name (CUNM).

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Name

For Intrastat Extrastat:

For EU Sales Purchase:

OCUSMA.OKCUNM,OKCUA1,OKCUA2,OKCUA3,OKCUA4; CRS610MI/The field indicates the Location name of the internal customer GetBasicData (external party) from (CRS610) based on the generic translatic

For Intrastat Extrastat:

OCUSMA.OKCUNM, OKCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Location name of the internal customer (external party) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Location name of the internal customer (external party) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and CUA1-CUA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address@type

For Intrastat Extrastat:

-.-; -/-

For Intrastat Extrastat: For EU Sales Purchase:

Set to 'text' if address information included.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

Set to 'text' if address information included.

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/AttentionOfName

For Intrastat Extrastat: For EU Sales Purchase:

For Intrastat Extrastat: For EU Sales Purchase:

OCUSMA.OKYREF: CRS610MI/GetBasicData

The field indicates the Your reference (YREF) from (CRS610).

NB: The information is currently only included for Party with @role = 'Agent'.

@languageID

For Intrastat Extrastat: For Intrastat Extrastat:

OCUSMA.OKYREF; CRS610MI/GetBasicData

For Intrastat Extrastat: For Intrastat Extrastat:

The field indicates the Your reference (YREF) from (CRS610).

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/AddressLine

For Intrastat Extrastat: For EU Sales Purchase:

OCUSMA.OKCUA1,OKCUA2,OKCUA3,OKCUA4; CRS610MI/

GetBasicData

For Intrastat Extrastat:

OCUSMA.OKCUA1-OKCUA4; CRS610MI/GetBasicData

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Address of the internal customer (external party) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E or F not available: Customer address line 2 (CUA2).

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (CUA3).

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

Alternative if generic translation not used: Customer address line 1-4 (CUA1-CUA4).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Address of the internal customer (external party) from (CRS610) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

Code E and F indicate 'Street and Building number.
 Alternative if generic translation used and code F or F not available.

Alternative if generic translation used and code E or F not available: Customer address line 2 (CUA2).

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Customer address line 3 (CUA3).

Country (sequence 4):

- Code I and J indicate 'Country'.

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Customer address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to sequence number of the address line: values 1-4.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4.

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/CityName

For Intrastat Extrastat: OCUSMA.OKTOWN; CRS610MI/GetBasicDAta

@sequence

-.-: -/-

For Intrastat Extrastat:

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the City name (TOWN) of the internal customer (external party) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

Infor May 26, 2023 30°

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the City (TOWN) of the internal customer (external party) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/CountrySubDivisionCode

For Intrastat Extrastat:

OCUSMA.OKECAR; CRS610MI/GetBasicDAta

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Area/State code (ECAR) of the internal customer (external party) from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Area/State code (ECAR) of the internal customer (external party) from (CRS610).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/CountryCode

For Intrastat Extrastat:

For Intrastat Extrastat:

@listID

-.-; -/-

OCUSMA.OKCSCD; CRS610MI/GetBasicData

For Intrastat Extrastat:
For EU Sales Purchase:

The field indicates the Country code (CSCD) of the internal customer (external party) from (CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Country code (CSCD) of the internal customer (external party) from (CRS610).

Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.

For Intrastat Extrastat: For EU Sales Purchase: Set to 'Countries'.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat: Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Location/Address/PostalCode

For Intrastat Extrastat:

For Intrastat Extrastat:

@listID

-.-: -/-

OCUSMA.OKPONO; CRS610MI/GetBasicData

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Postal code (PONO) of the internal customer (external party) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3).

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the Postal code (PONO) of the internal customer (external party) from (CRS610) if available in M3 (also sent as part of AddressLine @SequenceNumber = 3)

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/ID

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Contact ID of the External party from report field (ESFV in TXS035) for type TYPE) = 1 and base country (BSCD) from report header in following order:

- External contact ID from field (ESAF) = 570, if not existing from
- Internal contact ID from field (ESAF) = 571.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Contact ID of the External party from report field (ESFV in TXS035) for type TYPE) = 3 and base country (BSCD) from report header in following order:

- External contact ID from field (ESAF) = 570, if not existing from
- Internal contact ID from field (ESAF) = 571.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Name

For Intrastat Extrastat:

CCUCON.CCTX50; CRS618MI/Get

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Contact name (TX50) from (CRS618) for the contact ID (CNPE) from additional field (ESAF) ='571' for the type (TYPE) = 1 in (TXS035) and for the Base country (BSCD) of the report header.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Contact name (TX50) from (CRS618) for the contact ID (CNPE) from additional field (ESAF) ='571' for the type (TYPE) = 3 in (TXS035) and for the Base country (BSCD) of the report header

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication @sequence

For Intrastat Extrastat:

@preferredIndicator For Intrastat Extrastat:

-.-; -/-

-.-; -/-

For Intrastat Extrastat:

For EU Sales Purchase:

Set to the sequence number of the communication details.

For Intrastat Extrastat:

The field indicates the counter set in mapping depending on

information included.

For Intrastat Extrastat:

For EU Sales Purchase:

Set to 'false'.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

Set to 'false'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/ChannelCode

For Intrastat Extrastat:

-.-; -/-

For Intrastat Extrastat:

For EU Sales Purchase:

Set to 'Phone' in case of 'DailNumber' and to 'EMail' in case of 'URI'.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the Channel code.

- Set to 'Phone' for PHNO, PHN2 and TFNO (DailNumber).

- Set to 'Email' for EMAL (when URI contains email address).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to 'Communication Channels'.

NB: The information is currently only included for Party with @role =

@listID

For Intrastat Extrastat:

'Agent'.

For Intrastat Extrastat:

Set to 'Communication Channels'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/UseCode

For Intrastat Extrastat:

-.-: -/-

For Intrastat Extrastat: For EU Sales Purchase:

Set to 'Office' for PHNO and PHN2 in case of 'DailNumber'.

Set to 'Fax' for TFNO in case of 'DailNumber'. Set to 'Office' for EMAL if URI contains email adress.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the Use code

- Set to 'Office' for PHNO and PHN2 (DailNumber).

- Set to 'Fax' for TFNO (DailNumber).

- Set to 'Offce' for EMAL (URI).

@listID

For Intrastat Extrastat:

For Intrastat Extrastat: For EU Sales Purchase:

Set to 'Communication Use Codes'.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

Set to 'Communication Use Codes'

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/DialNumber

For Intrastat Extrastat: CCUCON.CCPHNO, CCPHN2; CRS618MI/Get

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618).

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618)

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/Address @type

For Intrastat Extrastat:

-.-: -/-

For Intrastat Extrastat:

For EU Sales Purchase:

Set to 'text' if address information included.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

Set to 'text' if address information included.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/Address/AddressLine

For Intrastat Extrastat:

CCUCON.CCCUA1-CCCUA4; CRS618MI/Get

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Address of the contact person of the external

party (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate

'Country' (see the integration guide for Local.ly for description of

Alternative if generic translation used and code E or F not available:

Address line 2 (CUA2).

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Address of the contact person of the external party (CRS618) based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

- Code E and F indicate 'Street and Building number.

Alternative if generic translation used and code E or F not available: Address line 2 (CUA2).

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3).

Country (sequence 4):

- Code I and J indicate 'Country'.

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to sequence number of the address line: values 1-4.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/Address/CityName

For Intrastat Extrastat:

For Intrastat Extrastat:

@sequence

CCUCON.CCTOWN; CRS618MI/Get

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the city of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the City (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

LCLT rade Statistics/Trade Statistics Header/Party/Contact/Communication/Address/Country SubDivision Code

For Intrastat Extrastat:

CCUCON.CCECAR; CRS618MI/Get

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the area/state of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR).

NB: The information is currently only included for Party with @role = 'Agent'.

For Intrastat Extrastat:

The field indicates the Area/State of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat: For EU Sales Purchase:

@listID

For Intrastat Extrastat:

-.-; -/-

-.-; -/-

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/Address/CountryCode

For Intrastat Extrastat: For Intrastat Extrastat: CCUCON.CCCSCD; CRS618MI/Get For EU Sales Purchase:

The field indicates a country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID
For Intrastat Extrastat: For Intrastat Extrastat:

For EU Sales Purchase: Set to 'Countries'.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat: Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/Address/PostalCode

For Intrastat Extrastat: For Intrastat Extrastat: CCUCON.CCPONO; CRS618MI/Get For EU Sales Purchase:

The field indicates a postal code of the contact in (CRS618).

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the postal code of the contact in (CRS618).

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/URI

For Intrastat Extrastat: For Intrastat Extrastat:

CCUCON.CCEMAL; CRS618MI/Get For EU Sales Purchase:

The field indicates an e-mail address of the contact in (CRS618).

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

The field indicates the e-mail address of the contact in (CRS618).

LCLTradeStatistics/TradeStatisticsHeader/Party/Contact/Communication/HTMLPreferredIndicator

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase:

Set to constant = 'true' in case of email.

NB: The information is currently only included for Party with @role =

'Agent'.

For Intrastat Extrastat:

Set to constant = 'true' in case of ChannelCode = Email (URI).

LCLTradeStatistics/TradeStatisticsHeader/Party/Description

For Intrastat Extrastat:

For Intrastat Extrastat:

The field indicates the Job title (JTIT) from (CRS618) for the contact ID (CNPE) from additional field (ESAF) ='571' for the type (TYPE) = 1 in (TXS035) and for the Base country (BSCD) of the report header.

LCLTradeStatistics/TradeStatisticsHeader/InterchangeAgreementID

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase: The field indicates the Agreement ID from report field (ESFV in

FQRHEA.EHYEA4; TXS130MI/GetHeadInfo

TXS035) for type TYPE) = 1, field (ESAF) = 513 and base country (BSCD) from report header. For Intrastat Extrastat: The field indicates the Agreement ID from report field (ESFV in TXS035) for type TYPE) = 3, field (ESAF) = 513 and base country (BSCD) from report header. LCLTradeStatistics/TradeStatisticsHeader/AuthorizationCode For Intrastat Extrastat: For Intrastat Extrastat: FQRADF.EAESFV; TXS035MI/LstBaseCountry For EU Sales Purchase: The field indicates the Authorization code from report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 512 and base country (BSCD) from report header. For Intrastat Extrastat: The field indicates the Authorization code from report field (ESFV in TXS035) for type TYPE) = 3, field (ESAF) = 512 and base country (BSCD) from report header. LCLTradeStatistics/TradeStatisticsHeader/AuthenticationCode For Intrastat Extrastat: For Intrastat Extrastat: FQRADF.EAESFV; TXS035MI/LstBaseCountry For EU Sales Purchase: The field indicates the Authentication code from report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 511 and base country (BSCD) from report header. For Intrastat Extrastat: The field indicates the Authentication code from report field (ESFV in TXS035) for type TYPE) = 3, field (ESAF) = 511 and base country (BSCD) from report header. LCLTradeStatistics/TradeStatisticsHeader/NumberOfDeclarations For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: -.-; -/-Set to hardcoded to 1. For Intrastat Extrastat: Set to 1 In M3 there is a 1:1 relation 1 declaration per report LCLTradeStatistics/TradeStatisticsDeclaration/ID For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: FQRHEA.EHESNO FQRSUG.UGCRRN.-; TXS130MI/GetHeadInfo The field indicates the Unique number set in M3 (CRS165 - 64/C) to identify 1 specific declaration: - If TXS130MI.GetHeadInfo.CORR = 0 (First): Set to ESNO. For Intrastat Extrastat: CTXTSH.CHVRNL: TXS300MI/GetHead - If TXS130MI.GetHeadInfo.CORR = 1 (Corrective): Set to CRRN. For Intrastat Extrastat: The field indicates the TAX declaration number used of the acutal run (e.g reportnumber), setup in CRS165 TX/0 (tax declaration number). @accountingEntity For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: FQRHEA.EHCONO,EHDIVI; TXS130MI/GetHeadInfo The field indicates the Accounting entity (Company and divison) from Transaction header. For Intrastat Extrastat: CTXTSH.CHCONO, CHDIVI; TXS300MI/GetHead The field indicates the Company and divison from Transaction header @lid For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: -.-; -/-The field indicates the LID from IONToolbox.getSenderLogicalID(myMap). For Intrastat Extrastat: Set to (IONToolbox.getSenderLogicalID(myMap)) from the system. LCLTradeStatistics/TradeStatisticsDeclaration/DocumentDateTime For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: FQRHEA.EHRGDT,EHRGTM; TXS130MI/GetHeadInfo The field indicates the Date of issue, taken from the the header transaction. For Intrastat Extrastat: CTXTSH.CHRGTM, CHRGDT; TXS300MI/LstLine For Intrastat Extrastat: The field indicates the Date and time of issue, taken from the the header transaction. LCLTradeStatistics/TradeStatisticsDeclaration/Year For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

Infor May 26, 2023 307

The field indicates the Year from EU-sales report header.

For Intrastat Extrastat:

CTXTSH.CHRPER: TXS300MI/GetHead

For Intrastat Extrastat:

The field indicates the first 4 positions in RPER represent Report

LCLTradeStatistics/TradeStatisticsDeclaration/PeriodID

For Intrastat Extrastat: For EU Sales Purchase: FQRHEA.EHPERI

FQRADF.EAESFV.-; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

For Intrastat Extrastat:

@schemeName

CTXTSH.CHRPER; TXS300MI/GetHead

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Report period from the report header. The value depends on the Period type defined as additional field (ESAF) = 520 (*) in (TXS035):

- If value (ESFV) = M (Monthly) or if 520 missing: Period retreived from (PERI).
- If value (ESFV) = Q (Quarterly): Period retreived from (ESAR).
- If value (ESFV) = Y (Yearly): PeriodID not included.

(*) Value in TXS035 for type (TYPE) = 1 and base country (BSCD) from report header.

For Intrastat Extrastat:

The field indicates the last 2 positions in RPER represnt report month.

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Period ID, the value depends on the Period type defined as additional field (ESAF) = 520 (*) in (TXS035): - If value (ESFV) = M (Monthly) or if 520 missing: schemeName =

- If value (ESFV) = Q (Quarterly): schemeName = 'Quarter'.
- If value (ESFV) = Y (Yearly): Not included.

(*) Value in TXS035 for type (TYPE) = 1 and base country (BSCD) from report header.

For Intrastat Extrastat: Set to 'Month'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/PartyIDs/ID For Intrastat Extrastat: For EU Sales Purchase: FQRHEA.EHCONO,EHDIVI FQRADF.EAESFV .-: TXS130MI/ TXS035MI/GetHeadInfo/ LstBaseCountry

For Intrastat Extrastat: CMNDIV.CCCONO, CCDIVI FQRADF. EAESFV .-; MNS100MI/ TXS035MI/GetBasicData/ LstBaseCountry

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the ID (external or internal) of the declaring party: - If report field (ESAF) = 515 for the base country (BSCD) in report header and type (TYPE) = 1 exist: External ID from (ESFV) in)TXS035) and if not exsting:

- If report field (ESAF) = 514 for the base country (BSCD) in report header and type (TYPE) = 1 exist: External ID from (ESFV) in)TXS035) and if not existing:
- Internal ID Company (CONO) and Division (DIVI).

For Intrastat Extrastat:

The field indicates the ID (external or internal) of the declaring party: - If report field (ESAF) = 515 for the base country (BSCD) in report header and type (TYPE) = 3 exist: External ID from (ESFV) in)TXS035) and if not exsting:

- If report field (ESAF) = 514 for the base country (BSCD) in report header and type (TYPE) = 3 exist: External ID from (ESFV) in)TXS035) and if not existing:

- Internal ID - Company (CONO) and Division (DIVI)

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/PartyIDs/TaxID

For Intrastat Extrastat: For EU Sales Purchase: FQRHEA.EHOVRN,EHVRNL CMNDIV.CMCORG,CMCOR2

FQRADF.EAESFV.-; TXS130MI/MNS100MI/TXS035MI/GetHeadInfo/ GetBasicData/LstBaseCountry

For Intrastat Extrastat:

CMNDIV.CCVRNL, CCCORG, CCCOR2 CTXTSH.CHVRIN.-; MNS100MI/TXS300MI/GetBasicData/GetHead

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the TaxID's included as standard depending on the value for 'Type of TaxID' defined as report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 526 and base country (BSCD) of the report header (see (*) below).

- TaxID 1: VAT Registration number 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 509 and base country (BSCD) of the report header and if not defined from 2) VAT registration number (OVR2) from Report header (ISO country code added in MI so no adjustment needed).

- TaxID 2: Tax declaration number from 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 510 and base country (BSCD) of the report header and if not defined from 2) Report header (VRNL)

- TaxID 3: Organization number 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 517 and base country (BSCD) of the report header and if not defined from 2) Organization number 1 (CORG) of the company from (MNS100).

- TaxID 4: Organization number 2 (COR2) of the company from (MNS100).

@schemeName

For Intrastat Extrastat:

- (*) If report field 526-Type of TaxID set to:
- 1: Only TaxID 2 is included.
- 2: Only TaxID 1 is included.
- 3: Only TaxID 3 is included.
- 4: Only TaxID 4 is included.
- 0 or other value (not 1-4) or not defined: All TaxIDs are included in order TaxID 1, TaxID 2, TaxID 3 and TaxID 4.

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: VAT Registration number (OVR2) from Report header (ISO country code added in M3BE so no adjustment needed)
- TaxID 2: Tax declaration number from Report header (VRNL). NB: No other TaxID's included.
- (*) If report field 526-Type of TaxID set to:
- 1: Only TaxID 2 is included.
- 2: Only TaxID 1 is included.
- 0 or other value (not 1-2) or not defined: All TaxIDs are included in order TaxID 1 and TaxID 2.
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

The field indicates the TaxID's are included as standard:

- TaxID 1: VAT Registration number internal (VRI2) from Report header (ISO country code added in MI so no adjustment needed).
- TaxID 2: Tax declaration number from 1) Report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 510 and base country (BSCD) of the report header and if not defined from 2) the division (MNS100 and VRNL).
- TaxID 3: Organization number 1 (CORG) of the company from (MNS100).
- TaxID 4: Organization number 2 (COR2) of the company from (MNS100).

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: VAT Registration number internal (VRI2) from Report header (ISO country code added in M3BE so no adjustment needed). - TaxID 2: Tax declaration number from the division (MNS100 and VRNL).
- NB: No other TaxID's included.
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

For EU Sales Purchase:

Set to the following schemeNames as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber'
 TaxID 2: schemeName 'TaxDeclarationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'
- TaxID 4: schemeName 'CountryIdentificationNumber'

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

For Intrastat Extrastat:

The field indicates the schemeNames are included as standard:

- TaxID 1: schemeName 'TaxIdentificationNumber' TaxID 2: schemeName 'TaxDeclarationNumber'
- TaxID 3: schemeName 'CountryIdentificationNumber'
- TaxID 4: schemeName 'CountryIdentificationNumber'

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR (*):

- TaxID 1: schemeName 'TaxIdentificationNumber'
- TaxID 2: schemeName 'CountryIdentificationNumber'
- (*) Country version (MNS100.CSVN) cannot be used due to Fiscal representative.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Name

For Intrastat Extrastat:

For EU Sales Purchase:

FQRHEA.EHCONM, EHCOA1-EHCOA4; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

OSUSAD.OPCONM, OPCOA1-COA4 OCUSMA.OKCONM, OKCOA1-COA4

CMNDIV.CCCONM, CCCOA1-COA4 .-; TXS300MI/GetHeadAddress

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Company name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

For Intrastat Extrastat:

The field indicates the Company name from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Company name (CONM) as mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Name

For Intrastat Extrastat:

For EU Sales Purchase:

FQRHEA.EHCONM, EHCOA1-EHCOA4; TXS130MI/GetHeadInfo

For Intrastat Extrastat:

OSUSAD.OPCONM, OPCOA1-COA4 OCUSMA.OKCONM, OKCOA1-COA4

CMNDIV.CCCONM, CCCOA1-COA4 .-; TXS300MI/GetHeadAddress

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Location name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

For Intrastat Extrastat:

The field indicates the Location name from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CONM and COA1-COA4 fields are used. Code C and D indicate 'Location name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code C not available: Location/Name not included as not mandatory information.

Alternative if generic translation not used: Company name (CONM).

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Address @type

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to 'text' if address information included

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Address/AddressLine

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCOA1-EHCOA4; TXS130MI/GetHeadInfo

For Intrastat Extrastat: OSUSAD.OPCOA1-COA4 OCUSMA.OKCOA1-COA4

CMNDIV.CCCOA1-COA4.-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Company address based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate 'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E or F not available: Company address line 2 (COA2) as mandatory information.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Alternative if generic translation used and code I or J not available: Address line 4 (COA4) not included as not mandatory information.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

For Intrastat Extrastat:

The field indicates the Company address from the report header MI based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how COA1-COA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

- Code E and F indicate 'Street and Building number

Alternative if generic translation used and code E or F not available: Company address line 2 (COA2) as mandatory information.

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Company address line 3 (COA3) as mandatory information.

Country (sequence 4):

- Code I and J indicate 'Country'

Alternative if generic translation used and code I or J not available: Address line 4 (COA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Company address line 1-4 (COA1-COA4).

@sequence

For Intrastat Extrastat:

-.-: -/-

For Intrastat Extrastat:

Set to sequence number of the address line: values 1-4.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Address/CityName

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHTOWN; TXS130MI/GetHeadInfo

For Intrastat Extrastat: OCUSAD.OPTOWN OCUSMA.OKTOWN

CMNDIV.CCTOWN.-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the City (TOWN) from report header.

The field indicates the City (TOWN) from the report header MI if available in M3 (also sent as part of AddressLine @SequenceNumber

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Address/CountrySubDivisionCode

For Intrastat Extrastat: For EU Sales Purchase: FQRHEA.EHECAR

FQRADF.EAESFV.-; TXS130MI /

TXS035MI/GetHeadInfo /

LstBaseCountry

For Intrastat Extrastat: OCUSAD.OPECAR OCUSMA.OKECAR

CMNDIV.CCECAR.-; TXS300MI/GetHeadAddress

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the State (ECAR) from the report header.

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CŠCD-ECAR)).

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = CZ in report header:

- If report field (ESAF) = 100 for type (TYPE) = 1 exist: additional field value for 'Municipality' from (ESFV) in (TXS035).

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = PL in report header:

- If report field (ESAF) = 020 for type (TYPE) = 1 exist: additional field value for 'Province' ('State') from (ESFV) in (TXS035).
- If report field (ESAF) = 030 for type (TYPE) = 1 exist: additional field
- value for 'District' from (ESFV) in (TXS035).

 If report field (ESAF) = 040 for type (TYPE) = 1 exist: additional field value for 'Community' ('Municipality') from (ESFV) in (TXS035).

For Intrastat Extrastat:

The field indicates the Area/State code (ECAR) from the report header MI.

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': 'France - Departements'.

@listID

For Intrastat Extrastat:

-.-; -/-

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the

Base country (BSCD) = CZ in report header:

- If report field (ESAF) = 100 for type (TYPE) = 1 exist:

@listID='Municipalities'.

Additional value if ISO code (CRS045MI.GetBasicData.IISO) of the

Base country (BSCD) = PL in report header:

- If report field (ESAF) = 020 for type (TYPE) = 1 exist:

@listID='States'.

- If report field (ESAF) = 030 for type (TYPE) = 1 exist:

@listID='Districts'.

- If report field (ESAF) = 040 for type (TYPE) = 1 exist:

@listID='Municipalities'.

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'.

LCL Trade Statistics/Trade Statistics Declaration/Declaring Party/Location/Address/Country Code

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRHEA.EHCSCD; TXS130Ml/GetHeadInfo

The field indicates the Country code (CSCD) from report header.

For Intrastat Extrastat: Generic translation is used to translate CSCD to alpha-2 country code

OCUSAD.OPCSCD according to ISO 3166-1.
OCUSMA.OKCSCD

CMNDIV.CCCSCD.-; TXS300MI/GetHeadAddress For Intrastat Extrastat:

The field indicates the Country code (CSCD) from the report header

MI.

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: ---; -/- Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Location/Address/PostalCode

For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: For EU Sales Purchase:

FQRHEA.EHPONO; TXS130MI/GetHeadInfo

The field indicates the Postal code (PONO) from report header.

For Intrastat Extrastat: For Intrastat Extrastat:

OCUSAD.OPPONO The field indicates the Postal code (PONO) from the report header MI

OCUSMA.OKPONO if available in M3 (also sent as part of AddressLine

CMNDIV.CCPONO.-; TXS300MI/GetHeadAddress @SequenceNumber = 3)

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/ID

For Intrastat Extrastat:
For EU Sales Purchase:
For EU Sales Purchase:
For EU Sales Purchase:
For EU Sales Purchase:

FQRHEA.EHCNPE; TXS130MI/GetHeadInfo

The field indicates the Contact ID (CNPE) from the report header.

For Intrastat Extrastat: For Intrastat Extrastat:

FQRADF.EAESFV; TXS300MI/GetHeadAddress

The field indicates the Contact ID (CNPE) from the report header MI.

@accountingEntity

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSH.CHCONO, CHDIVI; TXS300MI/GetHead The field indicates the Company and divison from Transaction header

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Name

For Intrastat Extrastat:
For EU Sales Purchase:
For EU Sales Purchase:
For EU Sales Purchase:

CCUCON.CCTX50 The field indicates the Contact name (TX50) from (CRS618) for the

CMNDIV.CMOREF.-; CRS618MI/MNS100/Get/GetBasicData contact ID (CNPE) from the report header.

For Intrastat Extrastat: If the Contact ID (CNPE) of the report header is missing, Contact

CCUCON.XXTX50 name from Our reference (OREF) in (MNS100).

CMNDIV.CCOREF.-; CRS618MI/MNS100/Get/GetBasicData

For Intrastat Extrastat:

The field indicates the Contact name (TX50) from (CRS618) for the contact ID (CNPE) from the report header MI.

If the Contact ID (CNPE) of the report header MI is missing, Contact

name from Our reference (OREF) in (MNS100).

LCLT rade Statistics/Trade Statistics Declaration/Declaring Party/Contact/Communication

@sequence

For Intrastat Extrastat: For Intrastat Extrastat:

-.-; -/- For EU Sales Purchase:

Set to sequence number of contact/communication.

For Intrastat Extrastat:

@preferredIndicator

For Intrastat Extrastat: For Intrastat Extrastat:

Set to 'false'

information included.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/ChannelCode

For Intrastat Extrastat:

For Intrastat Extrastat: For EU Sales Purchase:

-.-; -/-

Set to 'Phone' in case of 'DailNumber', to 'EMail' in case of 'URI' contains email address or to 'Website' in case of URI contains web address.

The field indicates the counter set in mapping depending on

For Intrastat Extrastat:

The field indicates the Channel code.

- Set to 'Phone' for PHNO, PHN2 and TFNO (DailNumber). - Set to 'Email' for EMAL (when URI contains email address). - Set to 'WebSite' for EMAL (when URI contains web site).

@listID

For Intrastat Extrastat:

For Intrastat Extrastat:

Set to 'Communication Channels'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/UseCode

For Intrastat Extrastat: -.-; -/-

For Intrastat Extrastat: For EU Sales Purchase:

Set to 'Office' for PHNO and PHN2 in case of 'DailNumber'.

Set to 'Fax' for TFNO in case of 'DailNumber' Set to 'Office' for EMAL if URI contains email adress.

For Intrastat Extrastat:

The field indicates the Use code.

- Set to 'Office' for PHNO and PHN2 (DailNumber).

- Set to 'Fax' for TFNO (DailNumber).

- Set to 'Office' for EMAL and ESFV=URI (URI).

@listID

-.-<u>;</u> -/-

For Intrastat Extrastat:

For Intrastat Extrastat: Set to 'Communication Use Codes'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/DialNumber

For Intrastat Extrastat:

For EU Sales Purchase:

CCUCON.CCPHNO,CCPHN2

FQRHEA.EHPHNO,EHPHN2, EHTFNO.-; CRS618MI/TXS130MI/Get/

GetHeadInfo

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Telephone number 1 (PHNO) and Telephone

number 2 (PHN2) of the contact in (CRS618) and the and Fax

number (TFNO) from the report header.

For Intrastat Extrastat:

CCUCON.CCPHNO, CCPHN2 OCUSAD OPPHNO, OPTFNO

OCUSMA.OKPHNO, OKPHN2, OKTFNO

CMNDIV.CCPHNO, CCPHN2, CCTFNO.-; CRS618MI

TXS300MI/Get GetHeadAddress If the Contact ID (CNPE) of the report header is missing, Telephone number 1 (PHNO), Telephone number 2 (PHN2) and Fax number (TFNO) from report header.

For Intrastat Extrastat:

The field indicates the Telephone number 1 (PHNO) and Telephone number 2 (PHN2) of the contact in (CRS618) and if the Contact ID (CNPE) of the report header is missing, from the report header MI.

Faxnumber (TFNO) from the report header MI.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address

@type

For Intrastat Extrastat:

For EU Sales Purchase:

For Intrastat Extrastat: For EU Sales Purchase:

Set to 'text' if address information included

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address/AddressLine

For Intrastat Extrastat:

For EU Sales Purchase:

CCUCON.CCCUA1, CCCUA2, CCCUA3, CCCUA4; CRS618MI/Get

For Intrastat Extrastat:

CCUCON.CCCUA1-CCCUA4; CRS618MI/Get

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Address of the contact person of the company

from (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used. Code E and F indicate 'Street and Building number, code G and H incidate 'Postal code and City' and code I and J indicate

'Country' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code E or F not available: Address line 2 (CUA2).

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3)

Alternative if generic translation used and code I or J not available:

Address line 4 (CUA4) included.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat:

The field indicates the Address of company's contact person in (CRS618) based on the generic translation

'addressFieldType' (CRS881/882) and 'Address type' = 'COMP' or 'ALL' to a code string indicating how CUA1-CUA4 fields are used.

Street and Building number (sequence 1 and if needed 2):

- Code E and F indicate 'Street and Building number,

Alternative if generic translation used and code E or F not available: Address line 2 (CUA2) as mandatory information.

Postal code and City (sequence 3):

- Code G and H incidate 'Postal code and City'.

Alternative if generic translation used and code G or H not available and the fields for 'Postal code' and 'City' are empty: Address line 3 (CUA3) as mandatory information.

Country (sequence 4):

- Code I and J indicate 'Country'.

Alternative if generic translation used and code I or J not available: Address line 4 (CUA4) included.

See the integration guide for Local.ly for description of setup.

Alternative if generic translation not used: Address line 1-4 (CUA1-CUA4).

For Intrastat Extrastat: For EU Sales Purchase:

Set to sequence number of the address line: values 1-4.

@sequence

For Intrastat Extrastat: For EU Sales Purchase:

-; -/-

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address/CityName

For Intrastat Extrastat:

CCUCON.CCTOWN; CRS618MI/Get

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the city of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country.

For Intrastat Extrastat:

The field indicates the City (TOWN) of the contact in (CRS618).

The information is mandatory when address formatting is used, and when a city is an address element used in the formatting rule. Address formatting rules are defined for each country

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address/CountrySubDivisionCode

For Intrastat Extrastat:

CCUCON.CCECAR; CRS618MI/Get

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the area/state of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR).

For Intrastat Extrastat:

The field indicates the Area/State of the contact in (CRS618).

Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/ state' (CSCD-ECAR)).

For Intrastat Extrastat:

For EU Sales Purchase:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR':

'France - Departements'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address/CountryCode

For Intrastat Extrastat:

For Intrastat Extrastat:

@listID

-.-; -/-

CCUCON CCCSCD: CRS618MI/Get For Intrastat Extrastat:

For FU Sales Purchase:

The field indicates a country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

For Intrastat Extrastat:

The field indicates the country of the contact in (CRS618).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

CCUCON.CCEMAL

For Intrastat Extrastat: For Intrastat Extrastat: Set to 'Countries' -.-; -/-

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Address/PostalCode

For Intrastat Extrastat: For Intrastat Extrastat:

CCUCON.CCPONO; CRS618MI/Get For EU Sales Purchase:

The field indicates a postal code of the contact in (CRS618).

For Intrastat Extrastat:

The field indicates the postal code of the contact in (CRS618).

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/URI

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

CCUCON.CCEMAL The field indicates an e-mail address of the contact in (CRS618).

FQRHEA.EHEMA8, EHURL8.-; CRS618MI/TXS130MI/Get/GetHeadInfo

If the Contact ID (CNPE) of the report header is missing, retreived from E-mail address (EMA8) from the report header.

For Intrastat Extrastat:

FQRADF.EAESFV.-; CRS618MI/TXS300MI/Get/GetHeadAddress URL address (URLB) from the report header if existing.

For Intrastat Extrastat:

The field indicates the e-mail address of the contact in (CRS618).

If the Contact ID (CNPE) of the report header MI is missing, retreived

from E-mail address (EMA8) from the report header MI.

URL address (URLB) from the report header MI if existing.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/HTMLPreferredIndicator

For Intrastat Extrastat: For Intrastat Extrastat:

-.-; -/-For EU Sales Purchase: Set to constant = 'true'.

For Intrastat Extrastat:

Set to constant = 'true' in case of ChannelCode = Email or WebSite

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Preference/Sequence

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: <u>-.-;</u> -/-Set to constant = '1'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclaringParty/Contact/Communication/Preference/Indicator

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: Set to 'false'. .-: -/-

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationFunction/Code

For Intrastat Extrastat: For EU Sales Purchase:

For EU Sales Purchase: The field indicates the function of the report:

FQRHEA.EHCORR; TXS130MI/GetHeadInfo - If TXS130MI.GetHeadInfo.CORR = 0 (First): Set to 'Original'.

- If TXS130MI.GetHeadInfo.CORR = 1 (Corrective): Set to 'Corrected'.

For Intrastat Extrastat:

FORADF

CTXTSH.EAESFV CHOTDN; TXS035MI

TXS300MI/LstBaseCountry

GetHead

For Intrastat Extrastat:

The field indicates the function of the report.

The processing depends on if the feature ID = 2246027 has been

activated or not in CMS975 (*):

If the feature is not actived (FEAT=0): Code depends on the report field (ESAF) = 523 in (TXS035) for type (TYPE) = 3 and BSCD of the

report header: - If value (ESFV) = O: Set to 'Original'. - If value (ESFV) = R: Set to 'Replaced'. - If value (ESFV) = N: Set to 'Nil return'

Set to 'Original' if report field (ESAF) 523 is missing or other value (ESFV) used.

NB: Value 'Deleted' and 'Corrected' not included at the moment.

If the feature is activated (FEAT=1): Code will be set as indicated

Set to translated value (ESFV) if field (ESAF) = 523 in (TXS035) for type (TYPE) = 3 and BSCD of the report header.

- If value (ESFV) = O: Set to 'Original'.
- If value (ESFV) = R: Set to 'Replaced'.
- If value (ESFV) = N: Set to 'Nil return'.

If Original tax declaration no. (OTDN) is blank:

- Set to default 'Original'.

If Original tax declaration no. (OTDN) is NOT blank:

- Set to default 'Replaced'.

NB: Value, 'Deleted' and 'Corrected' are not included.

(*) Retrieved from CMS975MI.Get with field NCRN = 2246027.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationFunction/PreviousDeclarationID

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHESNO; TXS130MI/GetHeadInfo

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Previous report number (ESNO) in case of 'Corrective report' (TXS130MI.GetHeadInfo.CORR = 1). In this case, the report number from field ESNO is sent in this element and the new report number from field CRRN is sent as report

number in TradeStatisticsDeclaration/ID.

@accountingEntity

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCONO, EHDIVI; TXS130MI/GetHeadInfo

For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Accounting entity (Company and division) from report header.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationTypeCode

For Intrastat Extrastat:

For Intrastat Extrastat:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For Intrastat Extrastat:

The field indicates the type or level of details in the declaration for Import/Arrival (ECTP = 1 or 4 (*)) from report field (ESAF) = 524 in (TXS035) for type (TYPE) = 3 and BSCD of the report header:

- If value (ESFV) = D: Set to 'Detailed'.If value (ESFV) = E: Set to 'Extended'.
- If value (ESFV) = S: Set to 'Standard'.
- If value (ESFV) = X: Set to 'Simplified'.

Set to 'Detailed' if report field (ESAF) 524 is missing or other value (ESFV) used.

Type or level of details in the declaration for Export/Dispatch (ECTP = 2 or 5 (*)) from report field (ESAF) = 525 in (TXS035) for type (TYPE)

- = 3 and BSCD of the report header:
- If value (ESFV) = D: Set to 'Detailed'.
- If value (ESFV) = E: Set to 'Extended'.
- If value (ESFV) = S: Set to 'Standard'. - If value (ESFV) = X: Set to 'Simplified'.

Set to 'Detailed' if report field (ESAF) 525 is missing or other value

(ESFV) used.

NB: Value 'Fiscal' and 'Very detailed' not included at the moment.

(*) NB: The value is retrieved from the first line (TXS300MI.LstLine) if not indicated on the header (that is if TXS300MI.GetHead.ECTP equal 0)

LCLTradeStatistics/TradeStatisticsDeclaration/DirectionCode

For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSH.CHECTP; TXS300MI/GetHead

For Intrastat Extrastat:

For Intrastat Extrastat:

The field indicates the direction code of the report.

- If ECTP = 1 or 4 set to 'Arrival'.
- If ECTP = 2 or 5 set to 'Dispatch'.

NB: The element is not included if DirectionCode is indicated on the line (that is if TXS300MI.GetHead.ECTP equal 0)

LCLTradeStatistics/TradeStatisticsDeclaration/CurrencyCode

For Intrastat Extrastat: For EU Sales Purchase:

FQRHEA.EHCUCD; TXS130MI/GetHeadInfo

For Intrastat Extrastat: CTXTSD.CDFSCU; TXS300MI/LstLine For Intrastat Extrastat: For EU Sales Purchase:

The field indicates the Currency taken from the report header.

Generic translation is used to translate CUCD according to ISO 4217.

For Intrastat Extrastat:

The field indicates the Fiscal currency from declaration line.

Generic translation is used to translate CUCD according to ISO 4217.

The field indicates the Total amount, accumulated in the mapping.

LCLTradeStatistics/TradeStatisticsDeclaration/TotalBaseAmount

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For FU Sales Purchase:

FQRLIN.ELACAM; TXS130MI/LstAmountEUSales The field indicates the Total amount (reporting currency), calculated

(summarize lines) in the mapping.

For Intrastat Extrastat:

@currencyID

CTXTSD.CDFSVL; TXS300MI/LstLine

For Intrastat Extrastat:

For Intrastat Extrastat:

For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRHEA.EHCUCD; TXS130MI/GetHeadInfo The field indicates the Currency taken from the report header.

For Intrastat Extrastat: Generic translation is used to translate CUCD according to ISO 4217.

CTXTSD.CDFSCU: TXS300MI/LstLine

For Intrastat Extrastat:

The field indicates the Fiscal currency on declaration line.

Generic translation is used to translate FSCU according to ISO 4217.

LCLTradeStatistics/TradeStatisticsDeclaration/TotalStatisticalValueAmount

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDSSVL; TXS300MI/LstLine The field indicates the Statistical value, accumulated in the mapping

@currencyID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDFSCU; TXS300MI/LstLine The field indicates the Statistical value currency from the declaration

Generic translation is used to translate CUCD according to ISO 4217.

LCLTradeStatistics/TradeStatisticsDeclaration/TotalNetWeightMeasure

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDECNW; TXS300MI/LstLine The field indicates the Net weight, accumulated in the mapping.

@unitCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: Set to 'KG'.

LCLTradeStatistics/TradeStatisticsDeclaration/NumberOfDeclarationLines

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

-.-; TXS130MI/LstAmountEUSales The field indicates the Number of lines, counted from

LstAmountEUSales number of lines in TXS130MI.

For Intrastat Extrastat:

CTXTSD.-; TXS300MI/LstLine For Intrastat Extrastat:

The field indicates the number of lines, count LstLines in TXS300MI.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/LineNumber

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: CTXTSD.CDRRLN; TXS300MI/LstLine

The field indicates the Line number in declaration.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/LineType

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

The field indicates the Internal counter in the mapping.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For FLI Sales Purchase:

FQRLIN.ELSERV; TXS130MI/LstAmountEUSales The field indicates the Line type if LSTAmountEUSale SERV = 2

Value "InternalTransfer" otherwise leave blank.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Commodity/CommodityCode For Intrastat Extrastat: For Intrastat Extrastat:

For Intrastat Extrastat: For Intrastat Extrastat:

The field indicates the Commodity code (CSNO) of transaction. CTXTSD.CDCSNO; TXS300MI/LstLine

If value is *ERROR, convert to 99999999 (8 digits)

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Commodity/AdditionalGoodsCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDECCC; TXS300/LstLine The field indicates the Consumption code - trade stat (ECCC) of

transaction.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Commodity/Description

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CSYCSN.CKTX40; CRS128MI/GetBasicData The field indicates the Commodity description (TX40) from CRS128.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/DestinationCountryCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELFTCO; TXS130MI/LstAmountEUSales The field indicates the Destination country according to ISO-std.

For Intrastat Extrastat:

CTXTSD.CDCSCD; TXS300MI/LstLine

Generic translation is used to translate FTCO to alpha-2 country code

according to ISO 3166-1.

For Intrastat Extrastat:

The field indicates the Goods destination country code, country to

where the manufactured goods is destinated to go to

a) If TXS300MI.GetHead.ECTP = 2 or 5 (Dispatch): Country code

(CSCD) of Export/Dispatch.

b) If TXS300MI.GetHead.ECTP = 0:

- TXS300MI.LstLine.ECTP = 2 or 5 (Dispatch): Country code (CSCD)

of Export/Dispatch.

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: -.-; -/-Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/DispatchCountryCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDCSCD; TXS300MI/LstLine The field indicates the Country from where the goods were

dispatched.

a) If TXS300MI.GetHead.ECTP = 1 or 4 (Arrival): Country code

(CSCD) of Import/Arrival.

b) If TXS300MI.GetHead.ECTP = 0:

- TXS300MI.LstLine.ECTP = 1 or 4 (Arrival): Country code (CSCD) of

Import/Arrival.

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: Set to 'Countries'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/CountryOfOriginCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDORCO; TXS300MI/LstLine The field indicates the Country of origin (ORCO) according to

declaration line.

Generic translation is used to translate ORCO to alpha-2 country

code according to ISO 3166-1.

@listID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/CountrySubDivisionCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDECAR; TXS300MI/LstLine The field indicates the State (ECAR) according to declaration line.

> Generic translation (blank division) is used to translate ECAR according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (BSCD(CSCD)-ECAR)).

@listID

For Intrastat Extrastat:

CTXTSH.CHECTP

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

Set to general value: 'Country Sub-divisions'; for ECAR = 'US': 'US States'; for ECAR = 'CA': 'Canadian Provinces'; for ECAR = 'FR': -.-: -/-

'France - Departements'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/DirectionCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELCVOP; TXS130MI/LstAmountEUSales The field indicates the direction of goods based on the type of party

(as no other information available in M3 function TXS130): - Type of party (CVOP) = 1 (Customer): Set to 'Dispatch' - Type of party (CVOP) = 2 (Supplier): Set to 'Arrival'

CTXTSD.CDECTP.-; TXS300MI/GetHead/LstLine For Intrastat Extrastat:

The field indicates the direction code of the report.

- If ECTP = 1 or 4 set to 'Arrival'.

- If ECTP = 2 or 5 set to 'Dispatch'.

NB: The element is not included if DirectionCode is indicated on the header (that is if TXS300MI.GetHead.ECTP not equal 0)

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/NetWeightMeasure

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDECNW; TXS300MI/Lstline The field indicates the Net weight from the declaration line.

@unitCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: Set to 'KG'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/SupplementaryUOMQuantity

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDECQT; TXS300MI/LstLine The field indicates the Supplementary Quantity.

@unitCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDSUPL; TXS300MI/LstLine The field indicates the Supplementary unit of measure code.

Generic translation is used to translate SUPL according to X-12 EDI

standard.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/BaseAmount

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELACAM, ELCACA; TXS130MI/LstAmountEUSales The field indicates the Recorded amount (ACAM) of the report line or

in case of correction (field CORP not 0):

- Correct original amount (CACA) and if this amount = 0, manual For Intrastat Extrastat: CTXTSD.CDFSVL; TXS300MI/LstLine

correction amount (ACAM).

For Intrastat Extrastat:

The field indicates the Fiscal value on declaration line.

@currencyID

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELCUCD; TXS130MI/LstAmountEUSales The field indicates the Currency code (CUCD) of the report line.

For Intrastat Extrastat:

CTXTSD.CDFSCU; TXS300MI/LstLine

Generic translation is used to translate CUCD according to ISO 4217.

For Intrastat Extrastat:

The field indicates the Fiscal currency on declaration line.

Generic translation is used to translate FSCU according to ISO 4217.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/CurrencyCode

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELCUCD; TXS130MI/LstAmountEUSales The field indicates the Currency code (CUCD) of the report line.

Generic translation is used to translate CUCD according to ISO 4217.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/StatisticalValueAmount

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDSSVL; TXS300MI/Lstline The field indicates the Statistical value from the declaration line

@currencyID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDFSCU: TXS300MI/Lstline The field indicates the Currency for statistical value from the declaration line in M3 statistical value = Fiscal value

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/StatisticalProcedureCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDCSNO/ The field indicates the Labour code (ECLC) from declaration line.

CDECLC; TXS300MI CRS128MI/LstLine GetBasicData

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base

country (BSCD) = AT (*):

- First 5 positions from (CRS240) - field description (TX40) of the TST

Business type (VRCD) from the declaration line.

(*) Country version (MNS100.CSVN) cannot be used due to Fiscal

representative.

Exception if ISO code (CRS045MI.GetBasicData.IISO) of the Base

country (BSCD) = FR:

- Get value from field TST Business type (VRCD) from declaration line

NB: Exception to ISO code(Exception if ISO code

(CRS045MI.GetBasicData.IISO) of the Base country (BSCD) = FR is only applicable if the agreement control property 'm3beFrance' is activated (true), default value is false

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/NatureOfTransaction

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDVRCD; TXS300MI/LstLine The field indicates the Bussiness type from declaration line.

Exception if BSCD = FR:

- Get value from field Labor Code (ECLC) from declaration line

NB: Exception to BSCD = FR is only applicable if the agreement control property 'm3beFrance' is activated (true), default value is false.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/TransportationMethodCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDVRDL: TXS300MI/LstLine The field indicates the Transportation method based on the value of

field 'Transportation method' (VRDL):

- If VRDL = 1: Set to 'Sea' - If VRDL = 2: Set to 'Rail' - If VRDL = 3 Set to 'Road' - If VRDL = 4: Set to 'Air' - If VRDL = 5: Set to 'Post' - If VRDL = 7: Set to 'Fixed'

- If VRDL = 8: Set to 'Inland Waterway' - If VRDL = 9: Set to 'Own Propulsion'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/TransportationTerm/IncotermsCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

The field indicates the Transportation term from declaration line CTXTSD.CDECDT; TXS300MI/ListLine

(CSYTSD.ECDT set to CSYECT.ECDT and if blank to

CSYECT.TEDL).

Valid codes are to be found at http://usaavwmydaydb2/Console/

Browse/86

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/TransportationTerm/LocationCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: -.-; -/-Set to default value '1'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/PortOfLoadUnloadCode For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDHAFE; TXS300MI/LstLine The field indicates the Harbour/airport

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/CustomsPreferenceCode

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDCPRI/CDCPRE; TXS300MI/LstLine The field indicates the preference code, provided by the autorities,

valid for import from a certain country and a certain product:

If GetHead.ECTP <> 0:

- If import declaration: Value retrieved from CPRI. - If export declaration: Value retrieved from CPRE.

If GetHead.ECTP = 0, ECTP from LstLine must be checked. If LstLine.ECTP = 1 or 4, retrieve value from then CPRI. Else if LstLine.ECTP = 2 or 5, then CPRE must be used.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/ExternalReferenceID

For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat: For Intrastat Extrastat:

CTXTSD.CDUNST; TXS300MI/LstLine The field indicates the Separation number.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Party

@role

For Intrastat Extrastat: For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELCVOP; TXS130MI/LstAmountEUSales The field indicates the type of party: @role = 'Customer' (if CVOP = 1)

or 'Supplier' (if CVOP = 2).

For Intrastat Extrastat:

CTXTSH.CHECTP

CTXTSD.CDECTP.; TXS300MI/GetHead/LstLine The field indicates the role of the party (line value used and if ECTP =

0, value from header):

For Intrastat Extrastat:

- If ECTP = 1 or 4: Set to 'Supplier' - If ECTP = 2 or 5: Set to 'Customer'

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Party/PartyIDs/TaxID

For Intrastat Extrastat: For Intrastat Extrastat: For FU Sales Purchase For EU Sales Purchase:

FQRLIN.ELYVRN; TXS130MI/LstAmountEUSales The field indicates the Your VAT registration number (YVRN) of the

For Intrastat Extrastat:

@schemeName

CTXTSD.CTVRNO; TXS300MI/LstLines

report line.

For Intrastat Extrastat:

The field indicates the VAT registration number (VRNO) of

transaction.

For Intrastat Extrastat: For Intrastat Extrastat: --: -/- For EU Sales Purchase:

Set to schemeName = 'TaxIdentificationNumber'

For Intrastat Extrastat:

Set to schemeName='TaxIdentificationNumber'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Party/Name

For Intrastat Extrastat: For EU Sales Purchase: OCUSMA.OKCUNM

CIDMAS.IDSUNM.-; CRS610MI/ CRS620MI/GetBasicData For Intrastat Extrastat:
For EU Sales Purchase:

The field indicates the Name of Customer or Supplier if BSCD=ES

(no address translation used):

- If CVOP = 1 (Customer): Customer name (CUNM) from (CRS610)

via Report line.CUNO=CUNO.

The field indicates the Customer name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'CUST' or 'ALL' to a code string indicating how CUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Customer name (CUNM) as mandatory information.

Alternative if generic translation not used: Customer name (CUNM).

 If CVOP = 2 (Supplier): Supplier name (SUNM) from (CRS620) via Report line.CUNO=SUNO.

The field indicates the Supplier name based on the generic translation 'addressFieldType' (CRS881/882) and 'Address type' = 'SUPP' or 'ALL' to a code string indicating how SUNM and ADR1-ADR4 fields are used. Code A and B indicate 'Company name' (see the integration guide for Local.ly for description of setup).

Alternative if generic translation used and code A not available: Supplier name (SUNM) as mandatory information.

Alternative if generic translation not used: Supplier name (SUNM).

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Party/Location/Address/CountryCode

For Intrastat Extrastat:
For EU Sales Purchase:
For EU Sales Purchase:
For EU Sales Purchase:

FQRLIN.ELFTCO; TXS130MI/LstAmountEUSales

The field indicates the country code from the VAT registration number

of the reporter. Retrieve first two characters from YVRN only.

@listID
For Intrastat Extrastat:
For EU Sales Purchase:
---; -/Set to 'Countries'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/TriangulationIndicator
For Intrastat Extrastat:
For Intrastat Extrastat:

For EU Sales Purchase: For EU Sales Purchase: FQRLIN.ELTRIA; TXS130MI/LstAmountEUSales The field indicates the indicator if the line is a triangulation scenario:

- If TRIA = 1 set to 'true' if TRIA = 0 set to 'false'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/ServiceIndicator

For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELSERV; TXS130MI/LstAmountEUSales

The field indicates the indicator if the line is a service:

- If SERV = 1 set to 'true' else set to 'false'.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/NumberOfConsignments

For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELNINV; TXS130MI/LstAmountEUSales The field indicates the Number of invoices (NINV).

LCLT rade Statistics/Trade Statistics Declaration/Declaration Line/Correction/Year

For Intrastat Extrastat: For EU Sales Purchase: For EU Sales Purchase: For EU Sales Purchase:

FQRLIN.ELYEA4; TXS130MI/LstAmountEUSales

The field indicates the Correction year, only created if Correction

period (CORP) not 0: Year (YEA4) from report line.

Exception for manual correction:

As Year (YEA4) is missing in case of manual correction, the value is

Infor May 26, 2023 32:

retrieved from CORP: If field CORP not = 0 and YEAR = 0:

Position 1-4 from field CORP used.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Correction/PeriodID

For Intrastat Extrastat:

For EU Sales Purchase:

FQRLIN.ELPERI,ELQUAR,ELYEA4

FQRADF.EAESFV.-; TXS130MI/TXS035MI/LstAmountEUSales/

LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Correction period ID, only created if Correction period (CORP) not 0. Period from report line, the value depends on the Period type defined as additional field (ESAF) = 520 (*) in

- If value (ESFV) = M (Monthly) or if 520 missing: Period retreived from (PERI).
- If value (ESFV) = Q (Quarterly): Period retreived from (QUAR).
- If value (ESFV) = Y (Yearly): PeriodID not included.

(*) Value in TXS035 for type (TYPE) = 1 and base country (BSCD) from report header.

Exception for manual correction:

As Period (PERI) and Quarter (QUAR) are missing in case of manual correction, the value is retrieved from CORP: If field CORP not = 0 and YEAR = 0:

- If value (ESFV) = M (Monthly) or if 520 missing: Position 5-6 from field CORP used.
- If value (ESFV) = Q (Quarterly): Position 5-6 from field CORP retrieved and translated to Quarter as following:
- Position 5-6 in range 01-03: Set PeriodID to 01.
- Position 5-6 in range 04-06: Set PeriodID to 02.
- Position 5-6 in range 07-09: Set PeriodID to 03.
- Position 5-6 in range 10-12: Set PeriodID to 04.

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the schemeName for the Correction period ID, only created if Correction period (CORP) not 0. The value depends on the Period type defined as additional field (ESAF) = 520 (*) in (TXS035): - If value (ESFV) = M (Monthly) or if 520 missing: schemeName =

'Month'

- If value (ESFV) = Q (Quarterly): schemeName = 'Quarter'.
- If value (ESFV) = Y (Yearly): Not included.

(*) Value in TXS035 for type (TYPE) = 1 and base country (BSCD) from report header.

LCLTradeStatistics/TradeStatisticsDeclaration/DeclarationLine/Correction/CorrectionBaseAmount

For Intrastat Extrastat:

@schemeName

-.-; -/-

For Intrastat Extrastat:

For EU Sales Purchase:

For EU Sales Purchase:

FQRLIN.ELBACA; TXS130MI/LstAmountEUSales

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Correction amount, only created if Correction period (CORP) not 0. There are two types of corrections:

- Automatic correction: Original invoice amount (BACA) from the report line included (the correct original amount (CACA) is sent as DeclarationLine/BaseAmount, difference calculated by GEMS if requested by message).
- Manual correction: No original invoice amount exists (BACA = 0) so value set to 0 (correction amount sent as DeclarationLine/ BaseAmount).

@currencyID

For Intrastat Extrastat:

For EU Sales Purchase:

FQRLIN.ELCUCD; TXS130MI/LstAmountEUSales

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the Currency of the correction amount, only created if Correction period (CORP) not 0. Currency code of the report line.

Generic translation is used to translate CUCD according to ISO 4217.

LCLTradeStatistics/TradeStatisticsDeclaration/UserArea

For Intrastat Extrastat:

For EU Sales Purchase:

FQRADF.EAESFV; TXS035MI/LstBaseCountry

For Intrastat Extrastat:

For EU Sales Purchase:

The field indicates the specific information required for some country versions.

The following information is included as 'UserArea/Property/ NameValue':

a) If ISO code (CRS045MI.GetBasicData.IISO) of the Base country (BSCD) in report header = 'PL': Post office name: From report field (ESFV in TXS035) for type TYPE) = 1, field (ESAF) = 050 with @name 'lcl.PostOfficeName'.

Location	
@type	For Warehouse:
	The field indicates the location type. Set to 'Warehouse' if information
	is retrieved from MITWHL(Warehouse) table .
	For Facility: Set to 'Site'.
Location/ID	- w .
For Warehouse: MITWHL.MWWHLO; /	For Warehouse: The field indicates the warehouse ID.
For Facility: CFACIL.CFFACI; /	For Facility: The field indicates the facility.
@accountingEntity For Warehouse: MITWHL.MWCONO MITWHL.MWDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
For Facility: CFACIL.CFCONO CFACIL.CFDIVI.; /	
@variationID	For Warehouse: The field indicates the sequence number that identifies the number of times that this BOD has been published.
	For Facility: The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
Location/DisplayID	
For Facility: CFACIL.CFFACI; /	For Facility: The field indicates the facility.
Location/LastModificationDateTime	
For Warehouse: MITWHL.MWLMTS; /	For Warehouse: The field indicates the date and time the record was last modified.
For Facility: CFACIL.CFLMTS; /	For Facility: The field indicates date and time the record was last modified.
Location/LastModificationPerson/IDs/ID For Warehouse:	For Warehouse:
MITWHL.MWCHID; /	The field indicates the last person who modified.
For Facility: CFACIL.CFCHID; /	For Facility: The field indicates the ID of the person who last modified the record.
@accountingEntity For Warehouse:	The field indicates the company and division, displayed as
MITWHL.MWCONO MITWHLMWDIVI .; /	CONO_DIVI.
For Facility: CFACIL.CFCONO CFACIL.CFDIVI.; /	
Location/Name	For Warehouse:
For Warehouse: MITWHL.MWWHNM; MMS005MI/GetWarehouse	For Warehouse: The field indicates warehouse name.
For Facility: CFACIL.CFFACN ; CRS008MI/Get	For Facility: The field indicates the name of the facility.
Location/Address @tvne	
@type	For Warehouse: Set to 'text'.
Location/Address/AddressLine	
For Warehouse: CIADDR. OAADR1	For Warehouse: The field indicates the address line.
CIADDR. OAADR2 CIADDR. OAADR3	
CIADDR. OAADR4.; MMS005MI/GetWarehouse @sequence	
<u>. </u>	For Warehouse: The field indicates the address line sequence.

Infor May 26, 2023

Location

Location	
Location/Address/CityName	
For Warehouse:	For Warehouse:
CIADDR.OATOWN; MMS005MI/GetWarehouse	The field indicates the city name.
Location/Address/CountrySubDivisionCode For Warehouse:	For Warehouse:
CIADDR.OAECAR: MMS005MI/GetWarehouse	The field indicates an area, province or state within a country.
@listID	,
	For Warehouse:
	Set to 'Canadian Provinces' if the country is CA (Canada).
	Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
Location/Address/CountryCode	
For Warehouse:	For Warehouse:
CIADDR.OACSCD; MMS005MI/GetWarehouse	The field indicates the country code.
@listID	For Warehouse:
	Set to 'Countries'.
Location/Address/PostalCode	
For Warehouse:	For Warehouse:
CIADDR.OAPONO; MMS005MI/GetWarehouse	The field indicates the postal code.
Location/Description	F . W . I
For Warehouse: MITWHL.MWWHNM; MMS005MI/GetWarehouse	For Warehouse: The field indicates warehouse name.
IVII I VVIIL.IVIVVVVIINIVI, IVIIVIOUUDIVII/GELVVARENOUSE	The field findicates wateriouse flame.
For Facility:	For Facility:
CFACIL.CFFACN; CRS008MI/Get	The field indicates the name of the facility.
Location/ParentLocation/ID	
For Warehouse:	For Warehouse:
MITWHL.MWFACI; MMS005MI/GetWarehouse @accountingEntity	The field indicates the facility.
For Warehouse:	For Warehouse:
MITWHL.MWCONO	The field indicates the company and division, displayed as
MITWHL.MWDIVI.; /	CONO_DIVI.
Location/ParentLocation/Name	F 14/ 1
For Warehouse: CFACIL.CFFACN; CRS008MI/Get	For Warehouse: The field indicates the name of the facility.
Location/Classification/Codes/Code	The held indicates the harne of the facility.
For Warehouse:	For Warehouse:
1) MITWHL.MWHTY;	The field indicates the classification code value.
MMS005MI/GetWarehouse	4) 14/ 1
2) MITWHL.MWWHSY;	 Warehouse type The field indicates the grouping of warehouses of the same type. It
MMS005MI/GetWarehouse	also determines whether the warehouse balance should be
	accumulated by facility level.
3) MITWHL.MWPHNO;	Set attribute listID to 'Location Type'.
MMS005MI/GetWarehouse	2) Warehouse subtype
4) MITWHL.MWCOMA;	The field indicates the warehouse subtype, and is used to
MMS005MI/GetWarehouse	differentiate warehouses within each type.
	Set attribute listID to 'Location Sub Type'.
5) MITWHL.MWSDES; MMS005MI/CotWorehouse	2) Tolonhono number
MMS005MI/GetWarehouse	 Telephone number The field indicates the warehouse's telephone number that is printed
6) MITWHL.MWLNCD;	on the freight document in the dispatch routine.
MMS005MI/GetWarehouse	Set attribute listID to 'Phone'.
ZV MITVAU II. MIA/DECC	A) Communication 11
7) MITWHL.MWRESP; MMS005MI/GetWarehouse	Communication address The field indicates the sender's address printed on digital documents
www.coocivii/Getyvareficuse	(purchase orders, and such) issued from this warehouse.
8) MITWHL.MWTWSL;	Set attribute listID to 'Communication Address'.
MMS005MI/GetWarehouse	5) Di
O) MITWILL MW/CDVN:	5) Place of loading The field indicates the ID of the geographic leastion, or place, for the
9) MITWHL.MWCDYN; MMS005MI/GetWarehouse.; /	The field indicates the ID of the geographic location, or place, for the transportation loading operation.
2 2 3 3 11 3 11 3 11 3 11 3 11 3	Set attribute listID to 'Place Of Load'.
For Facility:	
CFACIL.CFWHLO	6) Language The field indicates the language in which external documents are to
; CRS008MI/Get	The field indicates the language in which external documents are to be printed.
	Set attribute listID to 'Language'.
	7) Responsible The field indicates a unique user ID
	The field indicates a unique user ID.

Infor May 26, 2023 324

Set attribute listID to 'Responsible'.

Location

	8) To location The field indicates a destination location for a stock transaction. Set attribute listID to 'To Location'.
	 Cross-dock Set to '1' if cross-docking is activated. Set attribute listID to 'Cross-dock'.
@sequence	For Facility: The field indicates the main warehouse. Set attribute listID to 'Main Warehouse'.
wsequence .	For Warehouse: The field indicate the sequence number.
@listID	For Facility: The field indicates the sequence number.
Wisub	For Warehouse: The field indicates the classification code listID.
	 Set to 'Location Type' if Classification/Codes/Code = WHTY. Set to 'Location Sub Type' if Classification/Codes/Code = WHSY. Set to 'Phone' if Classification/Codes/Code = PHNO. Set to 'Communication Address' if Classification/Codes/Code = COMA. Set to 'Place Of Load' if Classification/Codes/Code = SDES. Set to 'Language' if Classification/Codes/Code = LNCD. Set to 'Responsible' if Classification/Codes/Code = RESP. Set to 'To Location' if Classification/Codes/Code = TWSL. Set to 'Cross-dock' if Classification/Codes/Code = CDYN.
	For Facility: Set to 'Main Warehouse' if Classification/Codes/Code = WHLO.
Location/TimeZone/TimeZoneOffset For Warehouse: CITZON.TZTGMT ; MMS005MI/GetWarehouse	For Warehouse: The field indicates the number of hours and minutes by which the current time zone deviates from UTC (Universal Time Coordinated). Note that UTC replaces Greenwich Mean Time (GMT).
	You should enter any time zone that is earlier than UTC with a minus sign after the number of hours.
Location/TimeZone/TimeZoneDaylightStartDate For Warehouse: CITZON.TZVFDT ; MMS005MI/GetWarehouse	For Warehouse: The field indicates the date when Daylight Saving Time takes effect or ends.
	When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect. When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.
Location/TimeZone/TimeZoneDaylightEndDate For Warehouse: CITZON.TZVTDT ; MMS005MI/GetWarehouse	For Warehouse: The field indicates the date when Daylight Saving Time takes effect or ends.
	When applied on the Northern hemisphere, it describes the date when Daylight Saving Time takes effect. When applied on the Southern hemisphere, it describes the date when Daylight Saving Time ends.
Location/TimeZone/Description For Warehouse: CITZON.TZTX40 ; MMS005MI/GetWarehouse	For Warehouse: The field indicates the description of the current identity.
Location/Status/Code	For Warehouse: Set to 'Open'. Set to 'Deleted' if MMS005 record is deleted.
@lia4D	For Facility: Set to 'Open'. Set to 'Deleted' if CRS008 record is deleted.
@listID	Set to 'Location Status'.

M3EDIAdvanceShipNotice

M3EDIAdvanceShipNotice/TradingPartnerID

The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.

The translated value in CRS881/882 will be displayed in MEC.

@schemeName

The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID

MHEXRH.H1E0PA MHEXRH.H1WHLO MHEXRH.H1TTYP MHEXRH.H1RIDN MHEXRH.H1REPN.; /

The documentID value is a concatenation of various M3 fields retrieved from the eventData. The fields are the Partner, Warehouse, Transaction Type, Order number and Receiving Number.

If IEC Agreement Control Property is m3beDocumentIDSeparator = space: The field indicates the advance ship notice ID. It is a concatenation of Partner (E0PA) <17> + Transaction type (TTYP) <2> + Order number (RIDN) <10> + Receiving number (REPN) <10>. The number specified in brackets is the maximum length of each field, the position and concatenation of the fields are based on the field length. If the data does not consume the maximum length, the rest is filled-up with spaces except for the last field which is right trimmed.

Otherwise: If IEC Agreement Control Property

m3beDocumentIDSeparator = /: The field indicates the advance ship notice ID. It is a concatenation of Partner (E0PA) <17> + Warehouse (WHLO) <3> + Transaction type (TTYP) <2> + Order number (RIDN) <10> + Receiving number (REPN) <10>. The number specified in brackets is the maximum length of each field and the fields are separated by /.

@accountingEntity CMNDIV.CCCONO

CMNDIV.CCDIVI.; / @location

MHEXRH.H1WHLO; MHS800MI/LstExpRec

@variationID

The field indicates the company and division, displayed as CONO DIVI.

The field indicates the warehouse.

The field indicates the sequence number that identifies the number of times that the BOD has been published.

@lid

The field indicates the logical ID of the system.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/AlternateDocumentID/ID

MHEXRH.H1RIDN; MHS800MI/LstExpRec

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DisplayID

MHEXRH.H1RIDN; MHS800MI/LstExpRec

The field indicates the order number. The field indicates the order number.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDateTime MHEXRH.H1RGDT

MHEXRH.H1RGTM.; MHS800MI/LstExpRec

The field indicates date and time the record is created.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/Note

MHEXRH.H1USD1 MHEXRH.H1USD2 MHEXRH.H1USD3 MHEXRH.H1USD4 The field indicates the user-defined fields. It is a concatenation of USD1 <15> + USD2 <15> + USD3 <15> + USD4 <15> + USD5 <5> separated by '/'.

MHEXRH.H1USD5.; MHS800MI/LstExpRec

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference @type

MHEXRH.H1TTYP; /

Set to 'Production' if Stock transaction type = 10. Set to 'PurchaseOrder' if Stock transaction type = 25. Set to 'CustomerReturn' if Stock transaction type = 30.

Set to 'Transfer' if Stock transaction type = 40 or 50.

Stock transaction type (TTYP) value is retrieved from the event data.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/DocumentID/ID

MHEXRH.H1RIDN; MHS800MI/LstExpRec

The field indicates the order number.

@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /

The field indicates the company and division, displayed as

CONO DIVI.

@location

MHEXRH.H1WHLO; MHS800MI/LstExpRec The field indicates the warehouse.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/Status/Code

MHEXRH.H1CMND; MHS800MI/LstExpRec

If CMND="*ADD', '*CHG' then set Status Code='Open' If CMND= '*DLT' then set Status Code = 'Canceled' If CMND="*CLS' then set Status Code='Closed'

@listID Set to 'ShipmentStatus'.

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/CountryOfOrigin

MHEXRH.H1CSCD; MHS800MI/LstExpRec

The field indicates the supplier's country or the country where the shipment is sent from.

May 26, 2023

M3EDIAdvanceShipNotice

CMNDIV.CCCONO

CMNDIV.CCDIVI.; /

M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/Note

M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode MHEXRH.H1MODL; MHS800MI/LstExpRec The field indicates the delivery method M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID MHEXRH.H1SUNO; MHS800MI /LstExpRec The field indicates the supplier. @accountingEntity CMNDIV.CCCONO The field indicates the accounting entity. CMNDIV.CCDIVI.; M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Name CIDMAS.IDSUNO; The field indicates the supplier's name for transaction type 25 CRS620MI/GetBasictData, (Purchases order). For transaction type 10, 40 and 50, the field MITWHL.MWWHNM: indicates the warehouse name. MMS005MI/GetWarehouse.; / M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/AddressLine MHEXRH.H1ADR1 The field indicates the address line. MHEXRH.H1ADR2 MHEXRH.H1ADR3 MHEXRH.H1ADR4.; MHS800MI /LstExpRec @sequence The field indicates the address line sequence M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/CountryCode MHEXRH.H1CSCD; MHS800MI/LstExpRec The field indicates the country code. @listID Set to 'Countries' M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Location/Address/PostalCode MHEXRH.H1CSCD; MHS800MI/LstExpRec The field indicates the country code. M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Name MHEXRH.H1YREF; MHS800MI/LstExpRec The field indicates the supplier's contact person. M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/Contact/Communication/DialNumber CIDMAS.IDPHNO The field indicates the Supplier's phone number for transaction type CIDMAS.IDPHN2; 25 (Purchase Order). For transaction type not equal to 25, the field CRS620MI/GetBasicData, indicates the warehouse's phone number. MITWHL.MWPHNO; MMS005MI/GetWarehouse.; / M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/PartyIDs/ID MHEXRH.H1SUNO; MHS800MI/LstExpRec The field indicates the customer returning the goods. The field is available for transaction type 30. @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CONO DIVI CMNDIV.CCDIVI.; / M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData The field indicates the customer name. The field is available for transaction type 30 M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/AddressLine MHEXRH.H1ADR1 The field indicates the address line. MHEXRH.H1ADR2 MHEXRH.H1ADR3 MHEXRH.H1ADR4.; MHS800MI /LstExpRec @sequence The field indicates the address line sequence M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/CountryCode MHEXRH.H1CSCD; MHS800MI/LstExpRec The field indicates the country code. @listID Set to 'Countries' M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ReturnFromShipToParty/Location/Address/PostalCode MHEXRH.H1PONO; MHS800MI /LstExpRec The field indicates the postal code M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/ID MHEXRH.H1WHLO; / The field indicates the warehouse ID. The value of this element is retrieved from the eventData. @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipToParty/Location/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse name M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode MHEXRH.H1TEDL; MHS800MI/LstExpRec The field indicates the delivery terms. @listID Set to 'Incoterms' M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID MHEXRD.H2ITNO; MHS800MI/LstExpRecDetail The field indicates the item number. @accountingEntity

May 26, 2023

The field indicates the accounting entity.

M3EDIAdvanceShipNotice The field indicates the user-defined fields. It is a concatenation of USD1 <15> + USD2 <15> + USD3 <15> + USD4 <15> + USD5 <5> MHEXRD H2USD2 MHEXRD.H2USD3 separated by '/'. MHEXRD.H2USD4 MHEXRD.H2USD5.; MHS800MI/LstExpRecDetail M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity MITTRA.MTTRQA; MHS800MI/LstExpRecDetail The field indicates the quantity in alternate unit of measure. @unitCode MHEXRD.H2ALUN; MHS800MI/LstExpRecDetail The field indicates the alternate unit of measurement. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity MHEXRD.H2TRQT; MHS800MI/LstExpRecDetail The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction. @unitCode MITMAS.MMUNMS; MHS800MI/LstExpRecDetail The field indicates the basic unit of measure in which each item is recorded in inventory M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/DocumentID/ID MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail The field indicates the order number for transaction type 40 (Transfer). @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. @location MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/RequisitionReference/LineNumber MHEXRD.H2RIDL The field indicates the order line number and the order line suffix. MHEXRD.H2RIDX.; MHS800MI/LstExpRecDetail M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/DocumentID/ID MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail The field indicates the order number for transaction type 25 (Purchase Order). @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. @location MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/LineNumber MHEXRD.H2RIDL The field indicates the order line number and purchase order line MHEXRD.H2PNLS.; MHS800MI/LstExpRecDetail subnumber M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/DocumentID/ID MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail The field indicates the order number for transaction type 30 (Customer Return). @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. @location MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SalesOrderReference/LineNumber MHEXRD.H2RIDL The field indicates the order line number and the order line suffix. MHEXRD.H2RIDX.; MHS800MI/LstExpRecDetail M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference @tvpe MHEXRD.H2TTYP; MHS800MI/LstExpRecDetail Set to 'Production' if Stock transaction type = 10. Set to 'PurchaseOrder' if Stock transaction type = 25 Set to 'CustomerReturn' if Stock transaction type = 30. Set to 'Transfer' if Stock transaction type = 40 or 50 M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/DocumentID/ID MHEXRD.H2RIDN; MHS800MI/LstExpRecDetail The field indicates the order number for transaction type 10 (Production Order) or 50 (Transfer). @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. @location MHEXRD.H2WHLO; MHS800MI/LstExpRecDetail The field indicates the warehouse ID. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/LineNumber MHEXRD.H2RIDL If Transaction Type = 50 (Distribution Order) then display Order Line MHEXRD.H2RIDX.; MHS800MI/LstExpRecDetail (RIDL) + line suffix (RIDX) M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/LotIDs/ID MHEXRD.H2BANO; MHS800MI/LstExpRecDetail The field indicates the lot number. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/SerialNumber MHEXRD.H2BANO; MHS800MI/LstExpRecDetail The field indicates the serial number. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/LineNumber MHEXRD.H2RELI; MHS800MI/LstExpRecDetail The field indicates the line number for customer order returns M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID

Infor May 26, 2023 328

The field indicates the package number.

The field indicates the item number.

MHFRNS.J2PANR; MHS800MI/LstExpRecPacDet

MHFRNS.J2ITNO; MHS800MI/LstExpRecPacDet

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ItemID/ID

M3EDIAdvanceShipNotice

@accountingEntity

CMNDIV.ČCCONO

The field indicates the accounting entity.

CMNDIV.CCDIVI.; /

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity

MHFRNS.J2DLQT; MHS800MI/LstExpRecPacDet

The field indicates the delivered quantity.

@unitCode

MHFRNS.J2UNIT; MHS800MI/LstExpRecPacDet

The field indicates the unit of measure.

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet The field indicates the order number for transaction type 40 (Transfer).

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet The field indicate @accountingEntity

CMNDIV.CCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/RequisitionReference/LineNumber

MHFRNS.J2RIDL The field indicates the order line number and the order line suffix.

MHFRNS.J2RIDX

.; MHS800MI/LstExpRecPacDet

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet

The field indicates the order number for transaction type 25

(Purchase Order).

@accountingEntity

CMNDIV.CCCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

MHFRNS.J2RIDL The field indicates the order line number and the order line suffix.

MHFRNS.J2RIDX

.; MHS800MI/LstExpRecPacDet

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet

The field indicates the order number for transaction type 30

(Customer Return).

@accountingEntity

CMNDIV.CCCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SalesOrderReference/LineNumber

MHFRNS.J2RIDL The field indicates the order line number and the order line suffix.

MHFRNS.J2RIDX

.; MHS800MI/LstExpRecPacDet

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference

@type

MHEXRH.H1TTYP; / Set to 'Production' if Stock transaction type = 10.

Set to 'PurchaseOrder' if Stock transaction type = 25. Set to 'CustomerReturn' if Stock transaction type = 30. Set to 'Transfer' if Stock transaction type = 40 or 50.

The value of TTYP is retrieved from the event data.

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID

MHFRNS.J2RIDN; MHS800MI/LstExpRecPacDet

The field indicates the order number for transaction type 10

(Production Order) or 50 (Transfer).

@accountingEntity

CMNDIV.CCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI.

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/DocumentReference/LineNumber

MHFRNS.J2RIDL MHFRNS.J2RIDX The field indicates the order line number and the order line suffix.

.; MHS800MI/LstExpRecPacDet

MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet

The field indicates the lot number.

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/SerialNumber

MHFRNS.J2BANO; MHS800MI/LstExpRecPacDet

The field indicates the serial number.

M3EDICarrierRoute/TradingPartnerID	
@schemeName	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
<u>wschemename</u>	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
M3EDICarrierRoute/DocumentID/ID	
For Standard: DCONSI.DACONN; MYS500MI/GetHead	For Standard: The field indicates the Shipment Number.
For Delivery: MHDISH.OQDLIX MHDISH.OQCONN.; MYS500MI MWS410MI/GetHead GetHead	For Delivery: The field indicates the delivery number if shipment does not exist. Else, the field indicates the shipment number.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location For Standard: DCONSI.DASDES; DRS100MI/GetShipment	For Standard: The field indicates the place of loading.
@variationID	For Delivery: The field indicates the warehouse.
@lid	The field indicates the number of times this BOD has been published.
	The field indicates the logical ID of the system.
M3EDICarrierRoute/DisplayID For Standard: DCONSI.DACONN; MYS500MI/GetHead	For Standard: The field indicates the Shipment Number
For Delivery: MHDISH.OQDLIX; MYS500MI/GetHead	For Delivery: The field indicates the Delivery number.
M3EDICarrierRoute/DocumentDateTime For Standard: DCONSI.DARGDT DCONSI.DARGTM.; DRS100MI/GetShipment For Delivery: MHDISH.OQTRDT MHDISH.OQTRTM.; MWS410MI/GetHead	This field indicates the transaction date and time.
M3EDICarrierRoute/TrackingID	
For Delivery: MHDISH.OQETRN.OQETRN; MWS410/GetHead	For Delivery: The field indicates the external tracking ID
M3EDICarrierRoute/ActualShipDateTime For Standard: DCONSI.DADSDT DCONSI.DADSHM.; DRS100MI/GetShipment For Delivery: MHDISH.OQDSDT	This field indicates the departure date and time.
MHDISH.OQDSHM.; MWS410MI/GetHead	
M3EDICarrierRoute/ScheduledDeliveryDateTime For Delivery:	For Delivery:
MMW442.OQSHD4 MMW442.OQSHD4.; MWS410MI/GetHead	The field indicates the scheduled delivery date and time.
M3EDICarrierRoute/ScheduledShipDateTime For Standard: DCONSI.DADSDT DCONSI.DADSHM.; DRS100MI/GetShipment	For Standard: This field indicates the scheduled ship date.
M3EDICarrierRoute/RequiredShipDateTime For Delivery: MHDISH.OQDSDT MHDISH.OQDSHM.; MWS410MI/GetHead	For Delivery: This field indicates the departure date and time.
M3EDICarrierRoute/PointOfLoadingCode For Standard: DCONSI.DASDES; DRS100MI/GetShipment	For Standard: This field indicates the Point of Loading
For Delivery: MHDISH.OQSDES; MWS410MI/GetHead	For Delivery: The field indicates the Place of loading.
M3EDICarrierRoute/TransportationMethodCode For Standard: DCONSI.DAMMDL; DRS100MI/GetShipment	For Standard: This field indicates the main delivery method at the delivery level.

MISEDICATIETROUTE	
For Delivery: MHDISH.OQMODF MHDISH.OQMODL.; MWS410MI/GetHead @listID	For Delivery: The field indicates the delivery method.
8 1302	For Standard: Set to 'TransportationMethods'.
M3EDICarrierRoute/GrossWeightMeasure For Standard: DCONSI.DAGRW2; DRS100MI/GetShipment	The field indicates the gross weight of all items in the delivery.
For Delivery: MHDISH.OQGRW2; MWS410MI/GetHead @unitCode	
CSYPAR.CPPARM; CRS175MI/GetItemFreeFlds	For Standard: The field indicates the general unit of measure for all weights within a company.
	For Delivery: The field indicates the unit code.
M3EDICarrierRoute/TotalVolumeMeasure	
For Standard: DCONSI.DAWM32; DRS100MI/GetShipment @unitCode	For Standard: The field indicates the total volume of all items in the shipment.
For Standard: CSYPAR.CPPARM; CRS175MI/GetItemFreeFlds	For Standard: The field indicates the general unit of measure for volume.
M3EDICarrierRoute/DeclaredValueAmount ODLINE.UBLNAM; MYS500MI/LstStatNo @currencyID	The field indicates the shipment declared value amount.
For Delivery: ODHEAD.UACUCD; MYS500MI/LstStatNo	The field indicates the currency.
M3EDICarrierRoute/Container/ContainerID For Standard: DCONSI.DAE0B4; DRS100MI/GetShipment	The field indicates the container number for the Delivery.
For Delivery: DCONSI.DAE0B4; MWS410MI/GetHead	
M3EDICarrierRoute/Container/SealID For Standard: DCONSI.DASEAL; DRS100MI/GetShipment	This field indicates the seal number.
For Delivery: DCONSI.DASEAL; MWS410MI/GetHead	
M3EDICarrierRoute/Status/Code	
For Standard:	For Standard:
DCONSI.DACSTL DCONSI.DACLOS.; DRS100MI/GetShipment	Set to 'InTransit' if lowest status is 60 (Shipment is reported) and
For Delivery:	shipment is closed. Set to 'Staged' if lowest status is 60 (Shipment is reported) and shipment is open.
MHDISH.OQPGRS MHDISH.OQCONN.; MWS410MI/GetHead	Set to 'Canceled' if lowest status is 90 (Shipment is canceled.
	For Delivery: Set to 'Open' if delivery status is 00, 01, 02, 03, 05, 50. Set to 'InTransit' if delivery status is 60, 65, 90 and shipment is empty. Set to 'Staged' if delivery status is 60, 65, 90 and there is a shipment. Set to 'Shipped' if delivery status is 95.
M3EDICarrierRoute/CarrierParty/PartyIDs/ID	5 O
For Standard: DCONSI.DAFWNO; DRS100MI/GetShipment	For Standard: This field indicates the forwarder.
For Delivery: MHDISH.OQFWNO; MWS410MI/GetHead	Value can be translated in CRS881. Translations in division level will be prioritized.
	For Delivery: This field indicates the carrier.
	Value can be translated in CRS881. Translation in Division level will be prioritized.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDICarrierRoute/CarrierParty/Name	
CIDMAS.IDSUNM; CRS620MI/GetBasicData	For Standard: The field indicates supplier name.
	For Delivery:

	The field indicates supplier name, most often the supplier's company
MOEDIO - mi - Danta /Danta Ota - //D	name.
M3EDICarrierRoute/RouteStop/ID For Standard:	For Standard:
MHDISH.OQDLIX; DRS100MI/LstByDelivery	This field indicates the delivery number.
For Delivery: MHDISH.OQDLIX; MYS500MI/GetHead	For Delivery: The field indicates the Delivery number.
M3EDICarrierRoute/RouteStop/NetWeightMeasure MHDISH.OQNEW2; MWS410MI/GetHead @unitCode	The field indicates the total net weight of all items in the delivery
CSYPAR.CPPARM; CRS175MI/GetItemFreeFlds	The field indicates the unit code.
M3EDICarrierRoute/RouteStop/GrossWeightMeasure MHDISH.OQGRW2; MWS410MI/GetHead @unitCode	The field indicates the total gross weight of all items in the delivery.
CSYPAR.CPPARM; CRS175MI/GetItemFreeFlds	The field indicates the unit code.
M3EDICarrierRoute/RouteStop/TotalVolumeMeasure MHDISH.OQVM32; MWS410MI/GetHead @unitCode	The field indicates the total volume of all items in the delivery.
CSYPAR.CPPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for volume.
M3EDICarrierRoute/RouteStop/StopDetail/StopPackages/Quantity MFTRNS.OSPANR; MWS410MI/LstPackages @unitCode	The field indicates the number of packages in the delivery.
MITPAC.M4PACK; MMS050MI/GetPackaging	The field indicates the packaging type.
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/PartyIDs/ID MHDISH.OQCONA .; MWS410MI/LstAdr	For Standard: The field indicates the consignee.
	Value can be translated in CRS881. Translations in division level will be prioritized.
	For Delivery: The field indicates the consignee.
	Value can be translated in CRS881. Translation in Division level will be prioritized.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Name OCUSAD.OPCUNM; MWS410MI/LstAdr	The field indicates the ship to party name.
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/ID	
MHDISH.OQCONA MHDISH.OQCOAA.; MWS410MI/LstAdr	The field indicates the consignee and consignee address. If consignee address is not available, only the consignee will be displayed.
@accountingEntity CMNDIV.CCCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/Add OCUSAD.OPCUA1 OCUSAD.OPCUA2	Tress/AddressLine The field indicates the address line.
OCUSAD.OPCUA3 OCUSAD.OPCUA4.; MWS410MI/LstAdr	
@sequence	The field indicates the address line sequence.
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/Add	ress/CityName
OCUSAD.OPTOWN; MWS410MI/LstAdr M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/Add	The field indicates the city name.
OCUSAD.OPECAR; MWS410MI/LstAdr @listID	The field indicates an area, province or state within a country.
	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/Add OCUSAD.OPCSCD; MWS410MI/LstAdr	
@listID	Set to "Countries".
M3EDICarrierRoute/RouteStop/StopDetail/ShipToParty/Location/Add OCUSAD.OPPONO; MWS410MI/LstAdr	
M3EDICarrierRoute/RouteStop/StopDetail/ShipmentReference/Docume For Standard: MHDISH.OQDLIX; DRS100MI/LstByDelivery	·

For Delivery: MHDISH.OQDLIX; MYS500MI/GetHead For Delivery:

The field indicates the Delivery number.

@accountingEntity CMNDIV.CCCONO

CMNDIV.CCDIVI.; / @location

For Standard:

DCONSI.DASDES; DRS100MI/GetShipment

For Delivery:

MHDISH.OQSDES; MWS410MI/GetHead

@lid

The field indicates the Place of loading

The field indicates the place of loading.

The field indicates the logical ID of the system.

M3EDICarrierRoute/RouteStop/StopDetail/ShipFromParty/PartyIDs/ID

For Standard:

DCONSI.DASDES; DRS100MI/GetShipment

For Delivery:

MHDISH.OQSDES; MWS410MI/GetHead

@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.;

M3EDICarrierRoute/UserArea/Property/NameValue

MHDISH.OQCONA; MWS410MI/GetHead

@name

CONO_DIVI.

For Standard:

For Delivery:

The field indicates the place of loading.

For Delivery: The field indicates the Place of loading.

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

The field indicates the translated value of the consignee.

For Standard:

Set to "EDITradingPartnerID".

For Delivery:

Set to "EDITradingPartnerID".

Set to "M3EDICarrierRouteDelivery"

M3EDICarrierRoute/UserArea/Property/Description

For Standard:

Set to "Customer from OrderHeader".

For Delivery:

Set to "Customer from OrderHeader".

Set to "M3EDI Mapping Variant"

May 26, 2023

M3EDIInventorvCount

M3EDIINVentoryCount	
M3EDIInventoryCount/InventoryCountHeader/DocumentID/ID	
MITTKH.SHSTNB; /	The field indicates the Physical Inventory number. The values is retrieved from the event fields.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MITTKH.SHWHLO; /	The field indicates the warehouse. The values is retrieved from the event fields.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical id of the system.
M3EDIInventoryCount/InventoryCountHeader/WarehouseLocation/ID MITTKH.SHWHLO; /	The field indicates the warehouse. The values is retrieved from the event fields.
M3EDIInventoryCount/InventoryCountLine/LineNumber MITTKV.SVSTRN; MMS307MI/LstPhysInvVar	The field indicates the Physical inventory number.
M3EDIInventoryCount/InventoryCountLine/Item/ItemID/ID MITTKV.SVITNO; MMS307MI/LstPhysInvVar @accountingEntity	The field indicates the item number.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInventoryCount/InventoryCountLine/Item/UPCID MITPOP.MPPOPN; MMS025MI/GetAlias	The field indicates the alias number. This value is retrieved from the Item/Alias file with alias category (ALWT) = 02 and alias qualifier (ALWQ) = UPC
M3EDIInventoryCount/InventoryCountLine/Item/EPCID MITPOP.MPPOPN; MMS025MI/GetAlias	The field indicates the alias number. This value is retrieved from the Item/Alias file with alias category (ALWT) = 02 and alias qualifier (ALWQ)= EA13
M3EDIInventoryCount/InventoryCountLine/Item/Description MITTKV.SVITNO; MMS307MI/LstPhysInvVar	The field indicates the item name.
M3EDIInventoryCount/InventoryCountLine/Item/SerializedLot/Lot/Lot/ MITTKV.SVBANO; MMS307MI/LstPhysInvVar	Ds/ID The field indicates the lot number.
M3EDIInventoryCount/InventoryCountLine/Quantity MITTKV.SVSTQI; MMS307MI/LstPhysInvVar @unitCode	The field indicates the counted quantity
MITTKV.SVUNMS; MMS307MI/LstPhysInvVar	The field indicates the unit of measure.
M3EDIInventoryCount/InventoryCountLine/Facility/IDs/ID MITTKV.SVFACI; MMS307MI/LstPhysInvVar @accountingEntity	The field indicates the facility
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInventoryCount/InventoryCountLine/Status/Code	Set to "Counted".
M3EDIInventoryCount/InventoryCountLine/TransactionDateTime MITTKV.SVRGDT MITTKV.SVRGTM.; MMS307MI/LstPhysInvVar	The field indicates the transaction date and time.
M3EDIInventoryCount/InventoryCountLine/AdjustmentQuantity MITTKV.SVDFQT; MMS307MI/LstPhysInvVar	The field indicates the quantity variance.
@unitCode MITTKV.SVUNMS; MMS307MI/LstPhysInvVar	The field indicates the unit of measure.

M3EDIINVOICE	
M3EDIInvoice	
@type CINHED.CIIVTP; INVBODMI/GetHeader	The field indicates the information type (IVTP). Set to 'CreditMemo' if information type is 02 or 12. Set to 'Prepaid' if information type is 04.
	Set to 'Invoice' if information type is blank, 00, 01 or 03 and extended invoice number (RXIN) is blank. Set to 'CreditMemo' if information type is blank, 00 or 01 and extended invoice number is not blank and invoice amount is less than
	 Set to 'DebitMemo' if information type is blank, 00 or 01 and extended invoice number (CINO) is not blank and invoice amount (TAMT) is greater than or equal to 0.
M3EDlInvoice/TradingPartnerID	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
@schemeName	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
M3EDIInvoice/InvoiceHeader/DocumentID/ID	
CINHED.CIINYR + CICINO; INVBODMI/GetHeader	The field indicates the invoice document ID. It is a concatenation of Invoice Year (INYR) <4> + Invoice Number (CINO) <15> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case CINO, is trimmed if it does not consume the maximum length.
@accountingEntity	The field indicates the company and division, displayed as CONO_DIVI.
@location CINHED.CIWHLO; INVBODMI/GetHeader @variationID	The field indicates the warehouse.
@lid	The field indicates the sequence number that identifies the number of times that the BOD has been published.
	The field indicates the logical ID of the system.
M3EDIInvoice/InvoiceHeader/AlternateDocumentID/ID CINHED.CIINPX +	It is a concatenation of Invoice prefix (INPX) <6> + Invoice Number
CIIVNO; INVBODMI/GetHeader	(IVNO) <9>. Hyphen (-) is used as delimiter or separator between fields. If IVNO is less than 9 then pad with leading zeroes.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
@location CINHED.CIWHLO; INVBODMI/GetHeader	The field indicates the warehouse.
M3EDIInvoice/InvoiceHeader/DisplayID CINHED.CICINO; INVBODMI/GetHeader	The field indicates the invoice number.
M3EDIInvoice/InvoiceHeader/LastModificationDateTime CINHED.CILMDT; INVBODMI/GetHeader	The field indicates the last modification date.
M3EDIInvoice/InvoiceHeader/DocumentDateTime CINHED.CIIVDT; INVBODMI/GetHeader	The field indicates the invoice date.
M3EDIInvoice/InvoiceHeader/Description CINHED.CIRXIN; INVBODMI/GetHeader	The field indicates the extended invoice number reference.
M3EDIInvoice/InvoiceHeader/Note CSYTXH.THTX60; CRS980MI/SltTxtBlock @noteID	The field indicates the note in the header.
CINTXT.CITXID CITXVR; INVBODMI/SelTexts	The field indicates the header note ID. It is a concatenation of Text ID (TXID) <13> + Text Block (TXVR) <10> without separator. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the NoteID except for the last one. The last field in the concatenation, in this case TXVR, is trimmed if it does not consume the maximum length.
@type CINTXT.CITXPR; INVBODMI/SelTexts	The field indicates the note type. Set to 'Pre-Text' if TXPR is 1. Set to 'Post-Text' if TXPR is 2.
@languageID CINTXT.CILNCD; INVBODMI/SelTexts	The field indicates the language of the note.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1

MISEDIIIIVOICE	
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: languageCode
M3EDIInvoice/InvoiceHeader/DocumentReference	
@type CINDRE.CIDRTP; INVBODMI/SelDocReference	The field indicates the document reference type.
CINDRE.CIDRIF, INVEODIVII/Selbockeleletice	IF DRTP is not 'TransportDocument', publish DRTP.
M3EDIInvoice/InvoiceHeader/DocumentReference/DocumentID/ID	II BITTI IO NOT TIANOPOREDOGAMONE, PABIGIT BITTI
CINDRE.CIDIDN; INVBODMI/SelDocReference	The field indicates the document reference number.
@accountingEntity	
	The field indicates the company and division, displayed as
	CONO_DIVI.
M3EDIInvoice/InvoiceHeader/DocumentReference/LineNumber	The field in disease the line around an
CINDRE.CIDIDN; INVBODMI/SelDocReference	The field indicates the line number.
M3EDIInvoice/InvoiceHeader/DocumentReference/SubLineNumber CINDRE.CIDLSN; INVBODMI/SelDocReference	The field indicates the sub-line number.
	The field indicates the sub-line number.
M3EDlInvoice/InvoiceHeader/ExtendedAmount CINHED.ICEXTA; INVBODMI/GetHeader	The field indicates the total order value before Discount and excluding
ONVIED.IOEXTA, IIVV DODIMI/Octi Icadei	VAT and Charges in transaction currency.
	In case of correction invoice - method 1, the field indicates the
	difference for total order value.
@currencyID	The field in disease the transport of the same of the
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/ExtendedBaseAmount	
CINHED.CIEXLA; INVBODMI/GetHeader	The field indicates the total order value before Discount and excluding
	VAT and Charges in local currency.
	In case of correction invoice - method 1, the field indicates the difference for total order value.
@currencyID	difference for total order value.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	·
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/PreSubunitRoundedTotalAmount	Data element. Currency
CINHED.CITAMT	The field indicates the amount before rounding-off.
CIROAM; INVBODMI/GetHeader	IF ROAM > 0 then Total Amount (TAMT) - rounding-off (ROAM).
,	IF ROAM < 0 then Total Amount (TAMT) + rounding-off (ROAM)
@currencyID	T. C. I
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/SubunitRoundingAmount	
CINHED.CIROAM; INVBODMI/GetHeader	The field indicates the rounding-off amount.
@currencyID	The field indicates the transaction assures
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	1/O. O

	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/TotalAmount CINHED.CITAMT; INVBODMI/GetHeader	
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the invoice total in transaction currency. The field indicates the transaction currency.
CINTED.CICOCD, INVEODIVII/Getheadel	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: 0
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/TotalBaseAmount CINHED.CITOLA; INVBODMI/GetHeader @currencyID	The field indicates the invoice total in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/PrePayment/PaidAmount CINPRE.CIAMTC; INVBODMI/SelPrepayments @currencyID	The field indicates the advance invoice amount.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/PrePayment/PaymentReferenceText CINPRE.CIA200; INVBODMI/SelPrepayments	The field indicates the advance invoice text.
M3EDIInvoice/InvoiceHeader/PrePayment/DocumentReference	
@type	
	Set to 'Invoice'
M3EDIInvoice/InvoiceHeader/PrePayment/DocumentReference/DocumentRe	mentID/ID The field indicates the customer invoice number.
@accountingEntity	The field indicates the company and division, displayed as
	CONO_DIVI.
CINHED.CICONO +	The field indicates the company and division.
	The field indicates the company and division.
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic
CINHED.CICONO +	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O
CINHED.CICONO + CIDIVI; /	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic
CINHED.CICONO + CIDIVI; /	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID The field indicates the company and division, displayed as
@accountingEntity	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID
@accountingEntity	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID The field indicates the company and division, displayed as CONO DIVI.
@accountingEntity @accountingEntity M3EDIInvoice/InvoiceHeader/SupplierParty/PartyIDs/TaxID 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID The field indicates the company and division, displayed as CONO DIVI. The field indicates the following Tax IDs of the supplier. 1) VAT Registration number (VRNO).
@accountingEntity @accountingEntity M3EDIInvoice/InvoiceHeader/SupplierParty/PartyIDs/TaxID 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID The field indicates the company and division, displayed as CONO DIVI. The field indicates the following Tax IDs of the supplier. 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL).
@accountingEntity M3EDlInvoice/InvoiceHeader/SupplierParty/PartyIDs/TaxID 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL	The field indicates the company and division. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID The field indicates the company and division, displayed as CONO DIVI. The field indicates the following Tax IDs of the supplier. 1) VAT Registration number (VRNO).

MISEDIIIIVOICE	
7) CINPTY.CININ2.; INVBODMI/GetParty	6) National Identity Number (NINO).7) National Identity Number (NIN2).
@schemeName	 Set to 'TaxIdentificationNumber' if VRNO is displayed. Set to 'TaxDeclarationNumber' if VRNL is displayed. Set to 'CountryIdentificationNumber' if CORG is displayed. Set to 'CountryIdentificationNumber' if COR2 is displayed. Set to 'CountryIdentificationNumber' if COR4 is displayed. Set to 'NationalIdentityNumber: if NINO is displayed. Set to 'NationalIdentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceHeader/SupplierParty/Name CINPTY.CINAME; INVBODMI/GetParty	The field indicates the company/division name.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Name CINHED.CIWHLO; INVBODMI/GetHeader	The field indicates the warehouse.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address @type	Set to 'text'.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Atter	
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Add CINPTY.CICUA1, CICUA2, CICUA3, CICUA4; INVBODMI/GetParty @sequence	
	The field indicates the address line sequence.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Cityle CINPTY.CITOWN: INVBODMI/GetParty	Name The field indicates the city name.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Cou	ntrySubDivisionCode
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country. If CountryCode is specified, the value of [CountryCode]- [SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can
	require more characters in ISO 3166 standard. E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
@listID	Data element: AreaState Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries.</country>
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Cou.	Set to "SubDivisions" if no Country is specified.
CINPTY.CICSCD; INVBODMI/GetParty	The field indicates the country code.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode
@listID	Set to 'Countries'.
M3EDIInvoice/InvoiceHeader/SupplierParty/Location/Address/Post CINPTY.CIPONO; INVBODMI/GetParty	
### 17:50 Greet, https://www.det.arty ####################################	The field indicates the contact name.
M3EDIInvoice/InvoiceHeader/SupplierParty/Contact/Communicatio @preferredIndicator	on
M3FDllnvoice/InvoiceHeader/SunnlierParty/Contact/Communication	Set to 'false'.
M3EDIInvoice/InvoiceHeader/SupplierParty/Contact/Communication	Set to "Phone" if telephone number is 1, 2, facsimile number or mobile.
@listID	Set to "Communication Channels".
1.1	0000

M3EDIInvoice/InvoiceHeader/SupplierParty/Contact/Communication/UseCode Set to "Office" if telephone number is 1 or 2. Set to "Fax" if facsimile number. @listID Set to "Communication Use Codes". M3EDIInvoice/InvoiceHeader/SupplierParty/Contact/Communication/DialNumber .; MNS100MI/GetBasicData The field indicates the phone number. M3EDIInvoice/InvoiceHeader/SupplierParty/Contact/Communication/Preference/Indicator Set to 'false'. M3EDIInvoice/InvoiceHeader/CustomerParty/PartyIDs/ID CINPTY.CICUNO; INVBODMI/GetParty The field indicates the customer number. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): CustomerParty Data element: PartyID @schemeName Set to 'CustomerNumber'. @accountingEntity The field indicates the company and division, displayed as CONO DIVI. M3EDIInvoice/InvoiceHeader/CustomerParty/PartyIDs/TaxID 1) CINPTY.CIVRNO The field indicates the following Tax IDs of the customer: 2) CINPTY.CIVRNL 1) VAT Registration number (VRNO). 3) CINPTY.CICORG 2) Tax declaration number (VRNL) 4) CINPTY.CICOR2 3) CountryldentificationNumber (CORG). 5) CINPTY.CICOR4 4) CountryIdentificationNumber (COR2). 6) CINPTY.CININO 5) CountryldentificationNumber (COR4). 7) CINPTY.CININ2.; INVBODMI/GetParty 6) National Identity Number (NINO). 7) National Identity Number (NIN2). @schemeName 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. 2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryldentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryldentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed. M3EDIInvoice/InvoiceHeader/CustomerParty/Name CINPTY.CINAME; INVBODMI/GetParty The field indicates the customer name M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address @type Set to 'text'. M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/AttentionOfName CINPTY.CIYREF; INVBODMI/GetParty The field indicates the contact name M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/AddressLine CINPTY.CICUA1, CICUA2, CICUA3, The field indicates the address lines. CICUA4; INVBODMI/GetParty @sequence The field indicates the address line sequence M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/CityName CINPTY.CITOWN; INVBODMI/GetParty The field indicates the city name. M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/CountrySubDivisionCode CINPTY.CIECAR; INVBODMI/GetParty The field indicates an area, province or state within a country.

If CountryCode is specified, the value of [CountryCode]-[SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.

E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.

It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: O Parent element(s): Generic Data element: AreaState @listID Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/CountryCode CINPTY.CICSCD; INVBODMI/GetParty The field indicates the country code. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode @listID Set to 'Countries' M3EDIInvoice/InvoiceHeader/CustomerParty/Location/Address/PostalCode CINPTY.CIPONO; INVBODMI/GetParty The field indicates the postal code M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact ID. @accountingEntity The field indicates the company and division, displayed as CONO DIVI M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name. M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication @sequence The field indicates the sequence number. @preferredIndicator Set to 'false' M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/ChannelCode Set to "Phone" if telephone number is 1, 2, facsimile number or mobile. Set to "EMail" if e-mail address M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/UseCode Set to 'Communication Channels'. @listID Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number. M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/DialNumber CCUCON.CCPHO The field indicates the telephone number. CCPHN2; CRS618MI/Get M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/Address @type Set to "Communication Use Codes" M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/AddressLine CCUCON.CCCUA1 The field indicates the address lines. CCCUA2 CCCUA3 CCCUA4; CRS618MI/Get @sequence The field indicates the address sequence number. M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/CityName CCUCON.CCTOWN; CRS618MI/Get The field indicates the city name. M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication/Address/CountrySubDivisionCode CCUCON.CCECAR; CRS618MI/Get The field indicates an area, province or state within a country. If CountryCode is specified, the value of [CountryCode]-[SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard. E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic

	I/O: O
	Parent element(s): Generic
	Data element: AreaState
@listID	
	Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication CCUCON.CCCSCD; CRS618MI/Get	on/Address/CountryCode The field indicates the country code.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: CountryCode
@listID	Bata demant. Country Code
	Set to 'Countries'.
M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication	on/Address/PostalCode
CCUCON.CCPONO; CRS618MI/Get	The field indicates the postal code.
M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication	on/URI
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the email address.
M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication	on/HTMLPreferredIndicator
	Set to 'false'.
M3EDIInvoice/InvoiceHeader/CustomerParty/Contact/Communication	on/Preference/Indicator
	Set to 'false'.
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/PartyIDs	/BICID
CBANAC.BCSWBI	The field indicates the SWIFT code of the company's bank account
CBANMA.BKSWIC.; CRS692MI/GetBankAccount	(SWBI). If SWBI is not provided, SWIFT code of the company's bank
	(SWIC) is published.
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Clearing	
CBANAC.BCCLSI	The field indicates the system clearing ID. It is a concatenation of
BCCLSN; CRS692MI/GetBankAccount	Clearing System ID (CLSI) + Clearing System number (CLSN)
	without separator. All fields are trimmed if it does not consume the maximum length.
MOEDIL ' II ' II I ID '(T. D. 4 /E' '- ID - 4 /D I. D	
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/BranchP CBANBR.BRSWIC; CRS692MI/GetBankAccount	The field indicates SWIFT code of the company's bank branch.
·	
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialCBANAC.BCBACN; CRS692MI/GetBankAccount	The field indicates the Bank Account Number of the company.
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	
	The field indicates the International Bank Account number of the
CBANAC BCIBAN: CRS692MI/GetBankAccount	
CBANAC.BCIBAN; CRS692MI/GetBankAccount	
	company.
	company. IAccount/CurrencyCode
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company.
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only.
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia CBANAC.BCCUCD; CRS692MI/GetBankAccount	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financia CBANAC.BCCUCD; CRS692MI/GetBankAccount	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialCBANAC.BCCUCD; CRS692MI/GetBankAccount @listID	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/FinancialCBANAC.BCCUCD; CRS692MI/GetBankAccount @listID	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount @listID M3EDIInvoice/InvoiceHeader/PaymentTerm/Description	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are
M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount @listID M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation
@listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount @listID M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length.
### M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount ###################################	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with ' ' as separator. All fields are
### ### ### ### ### ### ### ### ### ##	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with ' ' as separator. All fields are trimmed if it does not consume the maximum length.
### ### ### ### ### ### ### ### ### ##	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length.
@listID @listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note CINPTE.CITX15; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerms	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length. The field indicates the payment term short description. The field indicates the payment term code.
@listID @listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note CINPTE.CITX15; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerms	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length. The field indicates the payment term short description. The field indicates the payment term code. The field indicates the company and division, displayed as
@listID @listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note CINPTE.CITX15; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/PaymentTermCode CINPTE.CITX15; INVBODMI/SelPaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerms @accountingEntity	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length. The field indicates the payment term short description. The field indicates the payment term code.
@listID @listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note CINPTE.CITX15; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/PaymentTermCode CINPTE.CITX15; INVBODMI/SelPaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerms @accountingEntity M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/ID	IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length. The field indicates the payment term short description. The field indicates the payment term code. The field indicates the company and division, displayed as CONO DIVI.
@listID @listID M3EDIInvoice/InvoiceHeader/RemitToParty/FinancialParty/Financial CBANAC.BCCUCD; CRS692MI/GetBankAccount M3EDIInvoice/InvoiceHeader/PaymentTerm/Description CINPTE.CITEL1 CITEL2; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/Note CINPTE.CITX15; INVBODMI/SelPaymentTerms M3EDIInvoice/InvoiceHeader/PaymentTerm/PaymentTermCode CINPTE.CITX15; INVBODMI/SelPaymentTerm/PaymentTermCode CINPTE.CITEPY; INVBODMI/SelPaymentTerms @accountingEntity	company. IAccount/CurrencyCode The field indicates the currency of the bank. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency Set to 'Currency'. The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with '' as separator. All fields are trimmed if it does not consume the maximum length. The field indicates the payment term short description. The field indicates the payment term code. The field indicates the company and division, displayed as

	The field indicates the company and division, displayed as CONO_DIVI.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/Description	
CINPTE.CITEL1 + CITEL2; INVBODMI/SelPaymentTerms	The field indicates the payment term description. It is a concatenation of Text1 (TEL1) + Text2 (TEL2) with ' ' as separator. All fields are trimmed if it does not consume the maximum length.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/EffectiveDateTime CINPTE.CIIVDT; INVBODMI/SelPaymentTerms	The field indicates the invoice date.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/DueDateTime CINPTE.CIDUDT; INVBODMI/SelPaymentTerms	The field indicates the invoice due date.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/Amount CINPTE.CIAMTC; INVBODMI/SelPaymentTerms	The field indicates the amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic I/O: O Parent element(s): Generic
M3EDIInvoice/InvoiceHeader/PaymentTerm/Term/BaseAmount CINPTE.CIAMTC; INVBODMI/SelPaymentTerms	Data element: Currency The field indicates the amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/PaymentTerm/Discount/ID CINPTE.CITECD; INVBODMI/SelPaymentTerms	The field indicates the cash discount ID. If cash discount date1 (CDT1) is not 0, it is a concatenation of TECD + '-' + '1'.
	If cash discount date2 (CDT2) is not 0, it is a concatenation of TECD + '-' + '2'. If cash discount date3 (CDT3) is not 0, it is a concatenation of TECD
	+ '-' + '3'.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Discount/Description CINPTE.CITEL3 + CITEL4; INVBODMI/SelPaymentTerms	The field indicates the cash discount text. It is a concatenation of Text1 (TEL3) + Text2 (TEL4) with ' ' as separator. All fields are trimmed if it does not consume the maximum length.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Discount/DueDateTime CINPTE.CICDT1 CICDT2 CICDT3; INVBODMI/SelPaymentTerms	The field indicates the cash discount date 1 to 3 .
M3EDIInvoice/InvoiceHeader/PaymentTerm/Discount/AmountBasisCo	nde
CINPTE.CIGRNT; INVBODMI/ŠelPaymentTerms	The field indicates the cash discount method. Set to 'TotalAmount' if cash discount method (GRNT) is 1. Set to 'ExtendedPretaxAmount' if cash discount method (GRNT) is 2.
@listID 	Set to 'Amount Basis'.
M3EDIInvoice/InvoiceHeader/PaymentTerm/Discount/DiscountPercen CINPTE.CICDP1 CICDP2 CICDP3; INVBODMI/SelPaymentTerms	The field indicates the cash discount percentage 1 to 3. Format: 1% = 1.000.
M3EDIInvoice/InvoiceHeader/PaymentMethodCode CINHED.CIPYCD; INVBODMI/GetHeader	The field indicates the Payment method translated to the standard Infor Payment Method code. Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class is 1 or 2. Set to 'ElectronicFundsTransfer' if payment class is 3 and credit card indicator (CRDC) is 0. Set to 'CreditCard/DebitCard' if payment class is 3 and credit card indicator (CRDC) is 1. Set to 'BankDraft' if payment class is 4 Set to 'DirectDebit' if payment class is 5
@listID	Set to 'Factoring' if payment class is 6.

2, 3 or 4. on, displayed as tax in transaction currency y. 32. ly.
on, displayed as tax in transaction currency y. 32. ly.
on, displayed as tax in transaction currency y. 32. ly.
tax in transaction currency y. 32. ly.
tax in transaction currency y. 32. ly.
tax in transaction currency y. 32. ly.
y. 32. ly.
y. 32. ly.
ly.
ly.
tax in local currency.
32.
ly.
to decimal.
le.
on, displayed as
scription.
in transaction currency.
y.
32.
ly.
in local currency.
32.
ly.

M3EDIInvoice/InvoiceHeader/Tax/Amount	The field indicates the VAT amount in transaction currency
CINVTD.CITXAM; INVBODMI/GetTaxDetails @currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the VAT amount in transaction currency. The field indicates the transaction currency.
CINTED.CICOCD; INVBODMI/Getneader	·
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/ID CINCRG.CICRID; INVBODMI/SelCharges	The field indicates the charge ID.
@accountingEntity	The field indicates the company and division, displayed as
M3EDIInvoice/InvoiceHeader/Charge/Description	CONO DIVI.
CINCRG.CICRDO; INVBODMI/SelCharges	The field indicates the charge description.
M3EDIInvoice/InvoiceHeader/Charge/Amount CINCRG.CIAMTC; INVBODMI/SelCharges @currencyID	The field indicates the amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/BaseAmount CINCRG.CIAMLC; INVBODMI/SelCharges @currencyID	The field indicates the amount in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/Tax/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails	The field indicates the header charge VAT code.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/Charge/Tax/BasisAmount	33
CINVTD.CIBASA; INVBODMI/GetTaxDetails @currencyID	The field indicates the basis amount of the tax in transaction currency
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic I/O: O

	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/Tax/BasisBaseAmount CINVTD.CIBALA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
######################################	The field indicates the VAT rate converted to decimal. Format: 1.00 (for 1%)
M3EDIInvoice/InvoiceHeader/Charge/Tax/Exemption/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails DaccountingEntity	The field indicates the VAT exemption code.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/Charge/Tax/Exemption/Description CINVTD.CIT102; INVBODMI/GetTaxDetails	The field indicates the VAT exemption description.
M3EDIInvoice/InvoiceHeader/Charge/Tax/Exemption/Amount CINVTD.CITXEA; INVBODMI/GetTaxDetails ®currencyID	The field indicates the exemption amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/Tax/Exemption/BaseAmount CINVTD.CITXEL; INVBODMI/GetTaxDetails @currencyID	The field indicates the exemption amount in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/Tax/Description CINVTD.CITX40: INVBODMI/GetTaxDetails	The field indicates the VAT description.
M3EDIInvoice/InvoiceHeader/Charge/Tax/Amount CINHED.CITXAM; INVBODMI/GetHeader	The field indicates the VAT amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Charge/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the VAT amount in local currency. The field indicates the local currency.
ON NIED. OILOOD, HAVBODIVII/GEU IEAUEI	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic

	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Allowance/ID	Set to 'Order total discount'.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/Allowance/Amount CINDIS.CIAMTC; INVBODMI/SelHeadDiscount @currencyID	The field indicates the amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Allowance/BaseAmount	,
CINDIS.CIAMLC; INVBODMI/SelHeadDiscount @currencyID	The field indicates the amount in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Allowance/Tax/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails	The field indicates the header discount VAT code.
@accountingEntity	The field indicates the reader discount VAT code. The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/Allowance/Tax/BasisAmount CINVTD.CIBASA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Allowance/Tax/BasisBaseAmount CINVTD.CIBALA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Allowance/Tax/Calculation/RateNumeric CINVTD.CIVTP1; INVBODMI/GetTaxDetails	The field indicates the VAT rate converted to decimal. Format: 1.00 (for 1%)
M3EDIInvoice/InvoiceHeader/Allowance/Tax/Exemption/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails	The field indicates the VAT exemption code.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/Allowance/Tax/Exemption/Description CINVTD.CIT102; INVBODMI/GetTaxDetails	The field indicates the VAT exemption description.
M3EDIInvoice/InvoiceHeader/Allowance/Tax/Exemption/Amount	

CINIVED CITYER INIVERDANI/CotToy/Dataila	The field indicates the exemption amount in transaction assumence.
CINVTD.CITXEA; INVBODMI/GetTaxDetails DcurrencyID	The field indicates the exemption amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
### ### ### ### ######################	The field indicates the exemption amount in local currency.
OcurrencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
12EDIImvoice/ImvoiceHeader/Allewanes/Tov/Dear-windian	Data element: Currency
ISEDIInvoice/InvoiceHeader/Allowance/Tax/Description CINVTD.CITX40; INVBODMI/GetTaxDetails	The field indicates the VAT description.
I3EDIInvoice/InvoiceHeader/AIIowance/Tax/Amount CINHED.CITXAM; INVBODMI/GetHeader OcurrencyID	The field indicates the VAT amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
//3EDIInvoice/InvoiceHeader/Allowance/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
©currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
//3EDIInvoice/InvoiceHeader/UserArea	A) The field is disease the obliners of
CINBUA.CIDFVA; INVBODMI/SelUserArea	The field indicates the shipment issue date. Set attribute sequence to the field value of sequence (SEQC).
	Set attribute type to the field value of data type (DFTY).
	Set attribute name to 'lcl.ShipmentIssueDate', field data name
	(DFNA).
	2) The field indicates the customer's purchase order date.
	Set attribute sequence to the field value of sequence (SEQC).
	Set attribute type to the field value of data type (DFTY).
	Set attribute name to 'lcl.CustomerPurchaseOrderDate', field data name (DFNA).
	3) The field indicates the payment method.
	Set attribute sequence to the field value of sequence (SEQC).
	Set attribute type to the field value of data type (DFTY). Set attribute name to 'lcl.PaymentMethod', field data name (DFNA).
	4) The field indicates if this is an original invoice or a copy.
	Set to 'Original' if element MSGCOPY in Event Data is equal to 0
	Set to 'Copy' if element MSGCOPY in Event Data is equal to 1
	Set to 'Copy' if element MSGCOPY in Event Data is equal to 1 Set attribute sequence to the next number.

	Set to 'Open'
M3EDIInvoice/InvoiceHeader/Status/EffectiveDateTime	- Social Open
CINHED.CIRGDT,	The field indicates the date and time that the object was created. This
CDRGTM; INVBODMI/GetHeader	date is set automatically. It is a concatenation of creation date
	(RGDT) <8> + creation time (RGTM) <6>.
	E.g.
M3EDIInvoice/InvoiceHeader/Status/ArchiveIndicator	2018-12-13T05:09:04.903Z
more involced involced reductivo tatas in a final cattor	Set to 'false'
M3EDIInvoice/InvoiceHeader/CurrencyExchangeRate/SourceCurrence	
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction/foreign currency code.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
M3EDIInvoice/InvoiceHeader/CurrencyExchangeRate/TargetCurrenc	Data element: Currency
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceHeader/CurrencyExchangeRate/RateNumeric CINHED.CIRAIN; INVBODMI/GetHeader	The field indicates the exchange rate.
M3EDIInvoice/InvoiceHeader/CurrencyExchangeRate/SetDateTime CINHED.CIIVDT: INVBODMI/GetHeader	The field indicates the exchange rate date.
M3EDIInvoice/InvoiceHeader/ShipToParty/PartyIDs/ID	The held indicates the exchange rate date.
CINPTY.CICUNO; INVBODMI/GetParty	The field indicates the delivery customer. IF address number (ADID) is not blank, publish CUNO + ADID.
	It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with
	spaces. This applies to all fields that are part of the delivery customer code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.
	The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD.
	Msg std: M3EDI
	Vers: 1
	Message: Generic
	I/O: O
Out to walk we	Parent element(s): ShipToParty Data element: PartyID
@schemeName @accountingEntity	Set to 'CustomerNumber'.
<u> </u>	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/ShipToParty/PartyIDs/TaxID	
1) CINPTY.CIVRNO	The field indicates the following Tax IDs of the ShipTo customer:
2) CINPTY CIOCRO	1) VAT Registration number (VRNO).
3) CINPTY.CICORG	2) Tax declaration number (VRNL).
4) CINPTY.CICOR2 5) CINPTY.CICOR4	CountryIdentificationNumber (CORG). CountryIdentificationNumber (COR2).
6) CINPTY.CININO	5) CountryIdentificationNumber (COR2).
7) CINPTY.CININ2.; INVBODMI/GetParty	6) National Identity Number (NINO).
	7) National Identity Number (NIN2).
@schemeName	Set to 'TaxIdentificationNumber' if VRNO is displayed.
	2) Set to 'TaxDeclarationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed.

	4) Set to 'CountryldentificationNumber' if COR2 is displayed.
	5) Set to 'CountryIdentificationNumber' if COR4 is displayed.
	6) Set to 'NationalIdentityNumber: if NINO is displayed.7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceHeader/ShipToParty/Name	1) Set to NationalidentityNumber. II NINZ is displayed.
CINPTY.CINAME; INVBODMI/GetParty @JanguageID	The field indicates the delivery customer name.
CINHED.CILNCD; INVBODMI/GetHeader	The field indicates the language.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: languageCode
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address @type	
	Set to 'text'.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/Attention CINPTY.CIYREF; INVBODMI/GetParty	OfName The field indicates the contact name.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/AddressL	
CINPTY.CICUA1, CICUA2, CICUA3, CICUA4; INVBODMI/GetParty	The field indicates the address lines.
@sequence	The field indicates the address line sequence.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/CityName CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/CountryS	•
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]-
	[SubDivisionCode] can be translated in CRS881/882. It can be
	necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: AreaState
@listID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/CountryCCINPTY.CICSCD; INVBODMI/GetParty	
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: CountryCode
@listID	
	Set to 'Countries'.
M3EDIInvoice/InvoiceHeader/ShipToParty/Location/Address/PostalCoc CINPTY.CIPONO; INVBODMI/GetParty	de The field indicates the postal code.
M3EDIInvoice/InvoiceHeader/ShipToParty/Communication @preferredIndicator	
	Set to 'false'.
M3EDIInvoice/InvoiceHeader/ShipToParty/Communication/ChannelCo	<i>de</i> Set to 'Phone
@listID	
	Set to 'Communication Channels'.

M3EDIInvoice/InvoiceHeader/ShipToParty/Communication/UseCode Set to "Office" if telephone number. Set to "Fax" if facsimile number. @listID Set to 'Communication Use Codes'. M3EDIInvoice/InvoiceHeader/ShipToParty/Communication/DialNumber CINPTY.; INVBODMI/GetParty The field indicates the telephone number (PHNO) or fax number (TFNO) of the delivery customer. M3EDIInvoice/InvoiceHeader/ShipToParty/Communication/Preference/Indicator Set to 'false' M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact ID. @accountingEntity The field indicates the company and division, displayed as CONO DIVI M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Name The field indicates the contact name CCUCON.CCTX50; CRS618MI/Get M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication @sequence The field indicates the sequence number. @preferredIndicator Set to 'false'. M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/ChannelCode Set to "Phone" if telephone number is 1, 2, facsimile number or mobile. Set to "EMail" if e-mail address. @listID Set to 'Communication Channels' M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/UseCode Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number. @listID Set to "Communication Use Codes". M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/DialNumber CCUCON.CCPHO The field indicates the telephone number. CCPHN2; CRS618MI/Get M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address Set to 'text'. M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/AddressLine CCUCON.CCCUA1 The field indicates the address lines. CCCUA2 CCCUA3 CCCUA4; CRS618MI/Get @sequence The field indicates the address sequence number M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CityName CCUCON.CCTOWN; CRS618MI/Get The field indicates the city name. M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CountrySubDivisionCode CCUCON.CCECAR; CRS618MI/Get The field indicates an area, province or state within a country. If CountryCode is specified, the value of [CountryCode]-[SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard. E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: AreaState @listID Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Get

The field indicates the country code. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic 1/O: O Parent element(s): Generic Data element: CountryCode @listID M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Address/PostalCode CCUCON CCPONO; CRS618MI/Get The field indicates the postal code M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/URI CCUCON.CCEMAL; CRS618MI/Get The field indicates the email address. M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/HTMLPreferredIndicator Set to 'false' M3EDIInvoice/InvoiceHeader/ShipToParty/Contact/Communication/Preference/Indicator Set to 'false'. M3EDIInvoice/InvoiceHeader/BillToParty/PartyIDs/ID CINPTY.CICUNO; INVBODMI/GetParty The field indicates the invoice recipient customer. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): BillToParty Data element: PartyID @schemeName Set to 'CustomerNumber'. @accountingEntity The field indicates the company and division, displayed as CONO DIVI M3EDIInvoice/InvoiceHeader/BillToParty/PartyIDs/TaxID 1) CINPTY.CIVRNO The field indicates the following Tax IDs of the BilTo customer: 2) CINPTY.CIVRNL 1) VAT Registration number (VRNO). 3) CINPTY.CICORG 2) Tax declaration number (VRNL). 4) CINPTY.CICOR2 3) CountryldentificationNumber (CORG). 4) CountryIdentificationNumber (COR2). 5) CINPTY.CICOR4 6) CINPTY.CININO 5) CountryIdentificationNumber (COR4). 7) CINPTY.CININ2.; INVBODMI/GetParty 6) National Identity Number (NINO). 7) National Identity Number (NIN2). @schemeName 1) Set to 'TaxIdentificationNumber' if VRNO is displayed. Set to 'TaxDeclarationNumber' if VRNL is displayed.
 Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryldentificationNumber' if COR2 is displayed. 5) Set to 'CountryldentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed. M3EDIInvoice/InvoiceHeader/BillToParty/PartyIDs/EndPointID CINPTY.CIEPID; INVBODMI/GetParty The field indicates the endpoint ID. @schemeID CINPTY.CISCHI; INVBODMI/GetParty The field indicates the scheme ID M3EDIInvoice/InvoiceHeader/BillToParty/Name CINPTY.CINAME; INVBODMI/GetParty The field indicates the invoice recipient customer name. M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address @type Set to 'text'. M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/AttentionOfName CINPTY.CIYREF; INVBODMI/GetParty The field indicates the contact name. M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/AddressLine CINPTY.CICUA1, CICUA2, CICUA3, The field indicates the address lines. CICUA4; INVBODMI/GetParty @sequence The field indicates the address line sequence. M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/CityName CINPTY.CITOWN; INVBODMI/GetParty The field indicates the city name.

M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/CountrySu	
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]- [SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic I/O: O Parent element(s): Generic
OV. IIB	Data element: AreaState
@listID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/CountryCo	ode The field indicates the country code.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
@listID	Data element: CountryCode
M3EDIInvoice/InvoiceHeader/BillToParty/Location/Address/PostalCod	Set to 'Countries'.
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the postal code.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer @accountingEntity	The field indicates the contact ID.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication @sequence	
©preferredIndicator	The field indicates the sequence number.
	Set to 'false'.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Cha	Set to "Phone" if telephone number is 1, 2, facsimile number or mobile. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Use	Set to "Office" if telephone number is 1, 2 or e-mail address. Set to "Fax" if facsimile number.
@listID	Set to "Communication Use Codes".
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Dial CCUCON.CCPHO CCPHN2; CRS618MI/Get	Number The field indicates the telephone number.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Add @sequence	dress/AddressLine
	The field indicates the sequence number.
M3EDlInvoice/InvoiceHeader/BillToParty/Contact/Communication/Add CCUCON.CCTOWN; CRS618MI/Get	The field indicates the city name.
M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Add CCUCON.CCECAR; CRS618MI/Get	Iress/CountrySubDivisionCode The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]-[SubDivisionCode] can be translated in CRS881/882. It can be

necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.

E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.

It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: AreaState

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Address/CountryCode

CCUCON.CCCSCD; CRS618MI/Get

The field indicates the country code.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: CountryCode

@listID

@listID

Se to 'Countries'

M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Address/PostalCode

CCUCON.CCPONO; CRS618MI/Get

The field indicates the postal code.

M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/URI

CCUCON.CCEMAL; CRS618MI/Get

The field indicates the email address.

M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/HTMLPreferredIndicator Set to 'false'

M3EDIInvoice/InvoiceHeader/BillToParty/Contact/Communication/Preference/Indicator Set to 'false'

M3EDIInvoice/InvoiceHeader/PayFromParty/PartyIDs/ID

CINPTY.CICUNO; INVBODMI/GetParty

The field indicates the person/business who has paid or will pay the

The value can be translated in CRS881/882.

It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD.

Msg std: M3EDI

Vers: 1

Message: Generic

I/O: O

Parent element(s): PayFromParty

Data element: PartyID

Set to 'CustomerNumber'.

The field indicates the company and division, displayed as CONO DIVI.

M3EDIInvoice/InvoiceHeader/PayFromParty/PartyIDs/TaxID

1) CINPTY.CIVRNO

@schemeName

@accountingEntity

- 2) CINPTY.CIVRNL
- 3) CINPTY.CICORG 4) CINPTY.CICOR2
- 5) CINPTY.CICOR4
- 6) CINPTY.CININO
- 7) CINPTY.CININ2.; INVBODMI/GetParty
- @schemeName

- The field indicates the following Tax IDs of the PayFrom customer:
- 1) VAT Registration number (VRNO).
- 2) Tax declaration number (VRNL)
- 3) CountryIdentificationNumber (CORG).
- 4) CountryIdentificationNumber (COR2). 5) CountryldentificationNumber (COR4).
- 6) National Identity Number (NINO).
- 7) National Identity Number (NIN2)
- 1) Set to 'TaxIdentificationNumber' if VRNO is displayed.
- 2) Set to 'TaxDeclarationNumber' if VRNL is displayed.
- 3) Set to 'CountryldentificationNumber' if CORG is displayed.
- 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryldentificationNumber' if COR4 is displayed.

May 26, 2023

	Set to 'NationalldentityNumber: if NINO is displayed. Set to 'NationalldentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceHeader/PayFromParty/Name CINPTY.CINAME: INVBODMI/GetParty	The field indicates the payer name.
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address	The field malestate and payer manner
@type	Set to 'text'.
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address/Attention CINPTY.CIYREF; INVBODMI/GetParty	ionOfName The field indicates the contact name.
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address/Address CINPTY.CICUA1, CICUA2, CICUA3, CICUA4; INVBODMI/GetParty @sequence	ssLine The field indicates the address lines.
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address/CityNa	The field indicates the address line sequence.
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address/Countric CINPTY.CIECAR; INVBODMI/GetParty	rySubDivisionCode The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]- [SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic I/O: O Parent element(s): Generic Data element: AreaState
@listID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDIInvoice/InvoiceHeader/PayFromParty/Location/Address/Countri CINPTY.CICSCD; INVBODMI/GetParty	- · · · · · · · · · · · · · · · · · · ·
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
@listID	Data element: CountryCode
	Set to 'Countries'.
M3EDlInvoice/InvoiceHeader/PayFromParty/Location/Address/Postal CINPTY.CIPONO; INVBODMI/GetParty	Code The field indicates the postal code.
M3EDIInvoice/InvoiceHeader/PayFromParty/FinancialParty/PartyIDs/ECBANAC.BCSWBICCBANMA.BKSWIC.; CRS692MI/GetBankAccount	The field indicates the SWIFT code of the customer's bank account (SWBI). If SWBI is not provided, SWIFT code of the customer's bank (SWIC) is published.
	The element is displayed if the payment class (PYCL) of the payment method (PYCD) is 5-Direct debiting.
M3EDIInvoice/InvoiceHeader/PayFromParty/FinancialParty/ClearingS CBANAC.BCCLSI BCCLSN; CRS692MI/GetBankAccount	ystemMemberID The field indicates the system clearing ID. It is a concatenation of Clearing System ID (CLSI) + Clearing System number (CLSN) without separator. All fields are trimmed if it does not consume the maximum length.
	The element is displayed if the payment class (PYCL) of the payment method (PYCD) is 5-Direct debiting.
M3EDIInvoice/InvoiceHeader/PayFromParty/FinancialParty/BranchPa CBANBR.BRSWIC; CRS692MI/GetBankAccount	
	The element is displayed if the payment class (PYCL) of the payment method (PYCD) is 5-Direct debiting.

M3EDIInvoice/InvoiceHeader/PayFromParty/FinancialParty/FinancialACBANAC.BCBACN; CRS692MI/GetBankAccount	Account/BBANID The field indicates the Bank Account Number of the customer/payer.
	The element is displayed if the payment class (PYCL) of the payment method (PYCD) is 5-Direct debiting.
M3EDIInvoice/InvoiceHeader/PayFromParty/FinancialParty/FinancialACBANAC.BCIBAN; CRS692MI/GetBankAccount	Ccount/IBANID The field indicates the International Bank Account number of the customer/payer.
	The element is displayed if the payment class (PYCL) of the payment method (PYCD) is 5-Direct debiting.
M3EDIInvoice/InvoiceHeader/ShipFromParty/PartyIDs/ID CINPTY.; INVBODMI/GetParty	The field indicates the warehouse.
	The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD.
	Msg std: M3EDI Vers: 1
	Message: Generic I/O: O
	Parent element(s): ShipFromParty Data element: PartyID
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDlInvoice/InvoiceHeader/ShipFromParty/PartyIDs/TaxID 1) CINPTY.CIVRNO 2) CINPTY.CIVRNL 3) CINPTY.CICORG 4) CINPTY.CICOR2 5) CINPTY.CICOR4 6) CINPTY.CININO 7) CINPTY.CININ2.; INVBODMI/GetParty	The field indicates the following Tax IDs of the ShipFrom: 1) VAT Registration number (VRNO). 2) Tax declaration number (VRNL). 3) CountryIdentificationNumber (CORG). 4) CountryIdentificationNumber (COR2). 5) CountryIdentificationNumber (COR4). 6) National Identity Number (NINO).
@schemeName	7) National Identity Number (NIN2).1) Set to 'TaxIdentificationNumber' if VRNO is displayed.
	2) Set to 'TaxtueritinationNumber' if VRNL is displayed. 3) Set to 'CountryIdentificationNumber' if CORG is displayed. 4) Set to 'CountryIdentificationNumber' if COR2 is displayed. 5) Set to 'CountryIdentificationNumber' if COR4 is displayed. 6) Set to 'NationalIdentityNumber: if NINO is displayed. 7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceHeader/ShipFromParty/Name CINPTY.CINAME; INVBODMI/GetParty	The field indicates the Company name field in the address of type 1 (Final destination or goods receiving address) connected to the warehouse (MNS095).
M3EDIInvoice/InvoiceHeader/ShipFromParty/Location @type	
M3EDIInvoice/InvoiceHeader/ShipFromParty/Location/ID	Set to 'Warehouse'
CINPTY.; INVBODMI/GetParty @accountingEntity	The field indicates the warehouse.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDlInvoice/InvoiceHeader/ShipFromParty/Location/Address @type	Set to 'text'.
M3EDIInvoice/InvoiceHeader/ShipFromParty/Location/Address/Addr	
@sequence	The field indicates the address line sequence.
M3EDlInvoice/InvoiceHeader/ShipFromParty/Location/Address/CityNaCINPTY.CITOWN; INVBODMI/GetParty	ame The field indicates the city name.
M3EDIInvoice/InvoiceHeader/ShipFromParty/Location/Address/Count CINPTY.CIECAR; INVBODMI/GetParty	rySubDivisionCode The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]- [SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.

@currencyID

CINHED.CILOCD; INVBODMI/GetHeader

E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: AreaState @listID Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. M3EDIInvoice/InvoiceHeader/ShipFromParty/Location/Address/CountryCode CINPTY.CICSCD; INVBODMI/GetParty The field indicates the country code. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode @listID Set to 'Countries'. M3EDIInvoice/InvoiceHeader/ShipFromParty/Location/Address/PostalCode CINPTY.CIPONO; INVBODMI/GetParty The field indicates the postal code M3EDIInvoice/InvoiceHeader/ExtendedPretaxAmount CINHED.CIEPAM; INVBODMI/GetHeader The field indicates the gross total order value in transaction currency. @currencyID CINHED.CICUCD; INVBODMI/GetHeader The field indicates the transaction currency. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency M3EDIInvoice/InvoiceHeader/ExtendedPretaxBaseAmount CINHED.CIEPLA; INVBODMI/GetHeader The field indicates the gross total order value in local currency. @currencyID CINHED.CILOCD; INVBODMI/GetHeader The field indicates the local currency. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency M3EDIInvoice/InvoiceHeader/SubTotalAmount CINHED.CISUTA; INVBODMI/GetHeader The field indicates the sum of the TotalPretaxAmount for all the order lines in the transaction currency. @currencyID CINHED.CICUCD; INVBODMI/GetHeader The field indicates the transaction currency. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency M3EDIInvoice/InvoiceHeader/SubTotalBaseAmount CINHED.CISTLA; INVBODMI/GetHeader The field indicates the sum of the TotalPretaxAmount for all the order

Infor May 26, 2023 35

lines in local currency.

MISEDIIIIVOICE	
	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceHeader/Classification/Codes/Code	Bata dement. Currency
CINHED.CIRXIN,	Set to 'Original' if RXIN is blank and IVTP is 00, 02, 03 or 04.
CIIVTP; INVBODMI/GetHeader	Set to 'Corrective' if RXIN is not blank and IVTP is 00 or 01.
	Set to 'Summary' if RXIN is blank and IVTP is 01.
@sequence	
@#-4ID	The field indicates the classification sequence number.
@listID	Set to 'InvoiceClass'
MOEDIlmusias //musias II and an //Deference /Nomes Value	Set to invoice class
M3EDIInvoice/InvoiceHeader/Reference/NameValue CINHED.CICUSU; INVBODMI/GetHeader	The field indicates the supplier number of the customer.
@name	The field indicates the supplier number of the customer.
what the second	Set to 'ExternalSupplierNumber'.
@type	***
	Set to 'StringType'.
M3EDIInvoice/InvoiceHeader/SalesPersonReference/IDs/ID	
CINHED.CISMCD; INVBODMI/GetHeader	The field indicates the sales person ID.
@accountingEntity	T. C. I
	The field indicates the company and division, displayed as CONO DIVI.
MOEDIllowsia a llowa in a llow de u/O al a Dama au Dafanana a /Nama	CONO DIVI.
M3EDIInvoice/InvoiceHeader/SalesPersonReference/Name .: CRS100MI/Get	The field indicates the sales person name.
·	The field indicates the sales person fiame.
M3EDIInvoice/InvoiceHeader/Correction/OriginalDocumentID/ID CINHED.CIRXIN; INVBODMI/GetHeader	The field indicates the original invoice number in case of corrective
CINTIED: CITXIIN, INVEODIMI/Geti leadel	invoice.
@schemeName	involoc.
	Set to 'CommercialInvoice'.
@accountingEntity	
	The field indicates the company and division, displayed as
	CONO_DIVI.
M3EDIInvoice/InvoiceHeader/Correction/ReasonCode CINHED.CIFRSC; INVBODMI/GetHeader	The field indicates the reason code for the correction
@accountingEntity	The field indicates the reason code for the correction
@adddaning_naty	The field indicates the company and division, displayed as
	CONO DIVI.
M3EDIInvoice/InvoiceHeader/InvoiceHeader/M3EDICorrection/Origin	allnvoiceDateTime
CINHED.CIIVDT; INVBODMI/GetHeader	The field indicates the date when the original Invoice was issued
M3EDIInvoice/InvoiceLine/LineNumber	
CINLIN.CILINU; INVBODMI/SelLines	The field indicates the line number.
M3EDIInvoice/InvoiceLine/Description	
CINLIN.CIA200; INVBODMI/SelLines	The field indicates the invoice reference text.
M3EDIInvoice/InvoiceLine/Note	
CSYTXL.TLTX60; CRS980MI/SIITxtBlock	The field indicates the line note.
@notelD	The field indicates the live seets ID It is a second of CT 100
CINTXT.CITXID	The field indicates the line note ID. It is a concatenation of Text ID
CITXVR; INVBODMI/SelTexts	(TXID) <13> + Text Block (TXVR) <10> without separator. If the data does not consume the maximum length, the rest is filled up with
	spaces. This applies to all fields that are part of the NoteID except for
	the last one. The last field in the concatenation, in this case TXVR, is
	trimmed if it does not consume the maximum length.
@type	g
CINTXT.CITXPR; INVBODMI/SelTexts	The field indicates the note type.
	Set to 'Pre-Text' if TXPR is 1.
@languageID	Set to 'Post-Text' if TXPR is 2.
CINTXT.CILNCD; INVBODMI/SelTexts	The field indicates the language of the note.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: languageCode

Infor May 26, 2023 35

M3EDIInvoice/InvoiceLine/DocumentReference

MOLDINIVOICC	
@type CINDRE.CIDRTP; INVBODMI/SelDocReference	The field indicates the document reference type. IF DRTP is not 'TransportDocument', publish DRTP.
M3EDIInvoice/InvoiceLine/DocumentReference/DocumentID/ID CINDRE.CIDIDN; INVBODMI/SelDocReference	The field indicates the document reference number.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDlInvoice/InvoiceLine/DocumentReference/LineNumber CINDRE.CIDIDN: INVBODMI/SelDocReference	The field indicates the reference line number.
M3EDIInvoice/InvoiceLine/DocumentReference/SubLineNumber CINDRE.CIDLSN; INVBODMI/SelDocReference	The field indicates the reference subline number.
M3EDIInvoice/InvoiceLine/Item/Item/D/ID CINLIN.CIITNO; INVBODMI/SelLines @schemeName	The field indicates the item number.
@accountingEntity	Set to 'Supplier'.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/Item/ItemID/RevisionID CINLIN.CIECVE; INVBODMI/SelLines	The field indicates the revision number (edition) for an item or document.
M3EDIInvoice/InvoiceLine/Item/CustomerItemID/ID CINLIN.CIPOPN; INVBODMI/SelLines @schemeName	The field indicates the Customer alias number (Category 06)
@accountingEntity	Set to 'Customer'.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/Item/UPCID CINLIN.CIUPCI; INVBODMI/SelLines	The field indicates the alias number that corresponds to GTIN-12 and UCC-12. It is a 12-digit number used for identifying goods.
M3EDIInvoice/InvoiceLine/Item/GTIN CINLIN.CIGTIN; INVBODMI/SelLines	The field indicates the alias number that corresponds to Global Trade Item Number. It is a 14-digit number which includes various EAN/ UCC numbering structures.
M3EDIInvoice/InvoiceLine/Item/ServiceIndicator	Set to 'false'.
M3EDIInvoice/InvoiceLine/Item/Description CINLIN.CIITDS; INVBODMI/SelLines	The field indicates the item name.
@languageID CINHED.CILNCD; INVBODMI/GetHeader	The field indicates the language.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: languageCode
M3EDIInvoice/InvoiceLine/Item/Note CSYTXH.THTX60; CRS980MI/SLITxtBlock	The field indicates the item note.
@noteID CINTXT.CITXID CITXVR; INVBODMI/SelTexts	The field indicates the line note ID. It is a concatenation of Text ID (TXID) <13> + Text Block (TXVR) <10> without separator. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the NoteID except for the last one. The last field in the concatenation, in this case TXVR, is trimmed if it does not consume the maximum length.
@type CINTXT.CITXPR; INVBODMI/SelTexts	The field indicates the note type. Set to 'Pre-Text' if TXPR is 1. Set to 'Post-Text' if TXPR is 2.
@languageID CINTXT.CILNCD; INVBODMI/SelTexts	The field indicates the language of the note.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: languageCode

M3EDIInvoice/InvoiceLine/Item/Classification/Codes/Code 1) MITMAS. MMITGR The field indicates the following: MMS200MI.GetItmBasic 1)Item group 2) MITMAS.MMITCL The field indicates the item group. MMS200MI.GetItmBasic 2) Product group 3) MITAS.MMBUAR The field indicates the product group. MMS200MI.GetItmBasic 3) Business area 4)MITMAS.MMITTY The field indicates the business area. MMS200MI.GetItmBasic 4) Item type 5) MITMAS.MMTPCD The item type is mandatory and cannot be changed after the item is MMS200MI.GetItmBasic created. The only time an item type can be changed is when you 6) MITMAS.MMPRGP copy template items. MMS200MI.GetItmBasic 5) Item category The field indicates the item category. 7) MITMAS.MMDIGI MMS200MI.GetItmPrice Alternatives 8) MITMAS.MMCHCD 00 = Normal item 02 = Phantom item MMS200MI.GetItmBasic 9) CINLIN.CICCSNO 03 = Subcontracted item INVBODMI.SelLines 04 = Tool 05 = Fixed machine 10) CINLIN.CICCSNO INVBODMI.SelLines 07 = Repairable item 08 = Recyclable item .; / 11 = Extended Catalog Item (ECI) 12 = Non-coded Extended Catalog Item 13 = Non-material item 6) Procurement Group The field indicates the procurement group for an item. 7) Item discount group Item discount groups are entered per item in M3 and may be used as a control object for calculating customer order line discounts. 8) Configuration code The field indicates if the item is configured when ordered or configured as a maintenance item. 9) Custom statistical number The field indicates the custom statistical number. 10) Custom statistical number The field indicates the custom statistical number for Local ly @listID Set to: 1)item Groups 2)Product Groups 3) Business Sectors 4)Item Types 5)Item Category 6)Procurement Groups 7) Item Discount Groups 8) Configuration Code 9) Customs Statistical Number 10) CommodityCodes M3EDIInvoice/InvoiceLine/Item/SerializedLot/Lot/LotIDs/ID MITTRA.MTBANO; MWS070MI/LstTransByOrder The field indicates the lot number. Lot number is displayed when the lot number indicator (INDI) is 1, 3, 4 or 5. M3EDIInvoice/InvoiceLine/Item/SerializedLot/Lot/Quantity MITTRA.MTTRQA; MWS070MI/LstTransByOrder The field indicates the transaction quantity. @unitCode CINLIN.CISPUN; INVBODMI/SelLines The field indicates the unit of measure. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: ÙÓMCode M3EDIInvoice/InvoiceLine/Item/SerializedLot/Lot/BaseUOMQuantity MITTRA.MTTRQT; MWS070MI/LstTransByOrder The field indicates the quantity in basic unit of measure. @unitCode CINLIN.CIUNMS; INVBODMI/SelLines The field indicates the base unit of measure. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O

	Parent element(s): Generic Data element: UOMCode
M3EDIInvoice/InvoiceLine/Item/SerializedLot/SerialNumber	
MITTRA.MTBANO; MWS070MI/LstTransByOrder	The field indicates the serial number. Serial number is displayed when the lot number indicator (INDI) is 2.
M3EDIInvoice/InvoiceLine/ShipmentDateTime CINLIN.CIDLDT: INVBODMI/SelLines	The field indicates the shipment date.
M3EDIInvoice/InvoiceLine/CountryOfOriginCode CINLIN.CIORCO; INVBODMI/SelLines	The field indicates the country of origin.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic
@lictD	Data element: CountryCode
@listID	Set to 'Countries'.
M3EDIInvoice/InvoiceLine/Quantity CINLIN.CIIVQS; INVBODMI/SelLines @unitCode	The field indicates the invoice quantity in alternate unit of measure.
CINLIN.CISPUN; INVBODMI/SelLines	The field indicates the alternate unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDIInvoice/InvoiceLine/BaseUOMQuantity	
CINLIN.CIIVQT; INVBODMI/SelLines @unitCode CINLIN.CIUNMS; INVBODMI/SelLines	The field indicates the invoice quantity in basic unit of measure. The field indicates the base unit of measure.
CINEIN.CIONING, INVECEDIMI/GEILINES	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDIInvoice/InvoiceLine/UnitPrice/Amount CINLIN.CISAPR; INVBODMI/SelLines	The field indicates the unit price in transaction currency.
@currencylD CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/UnitPrice/BaseAmount CINLIN.CIPRIL; INVBODMI/SelLines	The field indicates the unit price in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/UnitPrice/PerQuantity CINLIN.CISACD; INVBODMI/SelLines	The field indicates the per quantity.
@unitCode CINLIN.CIUNMS; INVBODMI/SelLines	

M3EDIIIIvoice	The field indicates the sales price unit of measure.
	·
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDIInvoice/InvoiceLine/ExternalDocumentReference	
@type CINDRE.CIDRTP; INVBODMI/SelDocReference	The field indicates the document reference type. IF DRTP is 'TransportDocument: and TXEI is '1', publish DRTP.
M3EDIInvoice/InvoiceLine/ExternalDocumentReference/Documen CINDRE.CIDIDN; INVBODMI/SelDocReference	tID/ID The field indicates the external document reference number.
M3EDIInvoice/InvoiceLine/ExtendedAmount CINLIN.CIEXTA; INVBODMI/SelLines	The field indicates the extended amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/ExtendedBaseAmount CINLIN.CIEXLA; INVBODMI/SelLines	The field indicates the extended amount in local currency.
<pre>@currencyID CINHED.CILOCD; INVBODMI/GetHeader</pre>	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: 0
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/TotalAmount	Data element. Currency
CINLIN.CITAMT; INVBODMI/SelLines @currencyID	The field indicates the total amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/TotalBaseAmount CINLIN.CITOLA; INVBODMI/SelLines	The field indicates the total amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
M3EDIInvoice/InvoiceLine/OpenItemIndicator	Data element: Currency
·	Set to 'false'.
M3EDIInvoice/InvoiceLine/Tax @sequenceNumber	
CINVTD.CITAXS; INVBODMI/SelHeaderTax	The field indicates the sequence number.
@type CINVTD.CITXTB; INVBODMI/SelHeaderTax	If Tax type (TXTB) = 'SalesTax' then block must be created per field
	VTID, VTI2, VTI3, VTI4 and VTI5.

	Else if Tax type (TXTB) = 'Perception' then block must be created per
	field VTID. Otherwise, as is.
M3EDIInvoice/InvoiceLine/Tax/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails	The field indicates the VAT code.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/Tax/BasisAmount CINVTD.CIBASA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/Tax/BasisBaseAmount CINVTD.CIBALA; INVBODMI/GetTaxDetails @currencyID	The field indicates the basis amount of the tax in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/Tax/Calculation/RateNumeric CINVTD.CIVTP1; INVBODMI/GetTaxDetails	The field indicates the VAT rate converted to decimal.
M3EDIInvoice/InvoiceLine/Tax/Exemption/ID	Format: 1.00 (for 1%)
CINVTD.CIVTCD; INVBODMI/GetTaxDetails @accountingEntity	The field indicates the VAT exemption code.
	The field indicates the company and division, displayed as CONO DIVI.
M3EDlInvoice/InvoiceLine/Tax/Exemption/Description CINVTD.CIT102; INVBODMI/GetTaxDetails	The field indicates the VAT exemption description.
M3EDIInvoice/InvoiceLine/Tax/Exemption/Amount CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID	The field indicates the exemption amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/Tax/Exemption/BaseAmount CINVTD.CITXEL; INVBODMI/GetTaxDetails	The field indicates the exemption amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/Tax/Description CINVTD.CITX40; INVBODMI/GetTaxDetails	The field indicates the VAT description.
M3EDIInvoice/InvoiceLine/Tax/Amount CINHED.CITXAM; INVBODMI/GetHeader @currencyID	The field indicates the VAT amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	

MOLDIIIIVOICC	
	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
ON WILE SEE SE, HAVE SEEM CONTINUES.	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/ID	The field indicates the above ID
CINCRG.CICRID; INVBODMI/SelCharges	The field indicates the charge ID.
@accountingEntity	The field indicates the company and division, displayed as
	CONO DIVI.
M3EDIInvoice/InvoiceLine/InvoiceCharge/Description	
CINCRG.CICRDO; INVBODMI/SelCharges	The field indicates the charge description.
M3EDIInvoice/InvoiceLine/InvoiceCharge/Amount	
CINCRG.CIAMTC; INVBODMI/SelCharges	The field indicates the amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
Cital IEB. Cloddb, IIAA BODWI/Octi Icadci	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/BaseAmount	
CINCRG.CIAMLC; INVBODMI/SelCharges	The filed indicates the amount in local currency.
@currencyID	
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	1/0: 0
	Parent element(s): Generic Data element: Currency
MOSEDHaveire //aveire Line //aveire Charge /Tav/ID	Data element. Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails	The field indicates the line charge VAT code.
@accountingEntity	The hold indicates the line ordings VAT code.
<u></u>	The field indicates the company and division, displayed as
	CONO DIVI.
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/BasisAmount	
CINVTD.CIBASA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in transaction currency.
@currencyID	The field indicates the transaction currency
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/BasisBaseAmount	Zam domain duranty
CINVTD.CIBALA; INVBODMI/GetTaxDetails	The field indicates the basis amount of the tax in local currency.

@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/Calculation/RateNumerio	
CINVTD.CIVTP1; INVBODMI/GetTaxDetails	The field indicates the VAT rate converted to decimal. Format: 1.00 (for 1%)
######################################	The field indicates the VAT exemption code.
DaccountingEntity	
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/Exemption/Description	The field in disease the MAT connection description
CINVTD.CIT102; INVBODMI/GetTaxDetails M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/Exemption/Amount	The field indicates the VAT exemption description.
CINVTD.CITXEA; INVBODMI/GetTaxDetails	The field indicates the exemption amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
## 13 Property of the Control of	The field indicates the exemption amount in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
######################################	The field indicates the VAT description.
#3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/Amount CINVTD.CITXAM; INVBODMI/GetTaxDetails	The field indicates the VAT amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
GINTIED.GIGGGD, INVEGENIAGGI	·
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceCharge/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
@c <i>urrencyID</i> CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O ¯
	Parent element(s): Generic

MISEDIIIIAOICE	0-44-10:
@accountingEntity	Set to 'Discount per line'
	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Amount CINLND.CIAMTC; INVBODMI/SelLineDiscount	The field indicates the amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/BaseAmount CINLND.CIAMLC; INVBODMI/SelLineDiscount	The field indicates the amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails @accountingEntity	The field indicates the line discount VAT code.
<u>saccounting_naty</u>	The field indicates the company and division, displayed as CONO DIVI.
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/BasisAmount CINVTD.CIBASA; INVBODMI/GetTaxDetails @currencyID	The field indicates the basis amount of the tax in transaction currence
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/BasisBaseAmount CINVTD.CIBALA; INVBODMI/GetTaxDetails @currencyID	The field indicates the basis amount of the tax in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Calculation/RateNun CINVTD.CIVTP1; INVBODMI/GetTaxDetails	•
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/ID CINVTD.CIVTCD; INVBODMI/GetTaxDetails @accountingEntity	The field indicates the VAT exemption code. The field indicates the company and division, displayed as
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/Descripti	CONO DIVI.
CINVTD.CIT102; INVBODMI/GetTaxDetails	The field indicates the VAT exemption description.
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/Amount CINVTD.CITXEA; INVBODMI/GetTaxDetails @currencyID	The field indicates the exemption amount in transaction currency.
CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.

MOLDIIIIVOICC	
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Exemption/BaseA	
CINVTD.CITXEL; INVBODMI/GetTaxDetails @currencyID	The field indicates the exemption amount in local currency.
CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Description CINVTD.CITX40; INVBODMI/GetTaxDetails	The field indicates the VAT description.
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/Amount CINVTD.CITXAM; INVBODMI/GetTaxDetails	The field indicates the VAT amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/InvoiceAllowance/Tax/BaseAmount CINVTD.CITXAL; INVBODMI/GetTaxDetails	The field indicates the VAT amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/UserArea OIDTRL.OTICDN; CMS135MI/Lst	1) The field indicates the import declaration number. This is for the
	following source transaction: Ol20-CustomerOrder with transaction type (TTYP) 31
	CO20-MaintenanceOrder with transaction type (TTYP) 41 and 61
	SO20-Rental Agreement with transaction type (TTYP) 71
	Set attribute sequence to an incremental value. Set attribute type to 'IntegerType'.
	Set attribute name to 'lcl.CustomsFormNumber'.
M3EDlInvoice/InvoiceLine/RequestedDeliveryDate CINLIN.CIDWDZ; INVBODMI/SelLines	The field indicates the requested delivery date.
M3EDIInvoice/InvoiceLine/CustomerParty/PartyIDs/ID CINPTY.CICUNO; INVBODMI/GetParty	The field indicates the customer number.
	The value can be translated in CRS881/882.
	It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD.
	Msg std: M3EDI
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): CustomerParty
@schemeName	Data element: PartyID
	Set to 'CustomerNumber'.
Infor	2022

Accounting Entity	
@accountingEntity	The field indicates the company and division, displayed as
	CONO DIVI.
M3EDIInvoice/InvoiceLine/CustomerParty/PartyIDs/TaxID	
1) CINPTY.CIVRNO	The field indicates the following Tax IDs of the customer:
2) CINPTY.CIVRNL	1) VAT Registration number (VRNO).
3) CINPTY.CICORG	2) Tax declaration number (VRNL).
4) CINPTY.CICOR2	3) CountryIdentificationNumber (CORG).
5) CINPTY.CICOR4	4) CountryldentificationNumber (COR2).
6) CINPTY.CININO	5) CountryldentificationNumber (COR4).
7) CINPTY.CININ2.; INVBODMI/GetParty	6) National Identity Number (NINO).
	7) National Identity Number (NIN2).
@schemeName	
	Set to 'TaxIdentificationNumber' if VRNO is displayed.
	Set to 'TaxDeclarationNumber' if VRNL is displayed.
	3) Set to 'CountryldentificationNumber' if CORG is displayed.
	4) Set to 'CountryIdentificationNumber' if COR2 is displayed.
	5) Set to 'CountryIdentificationNumber' if COR4 is displayed.
	6) Set to 'NationalIdentityNumber: if NINO is displayed.
	7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceLine/CustomerParty/Name	T. 6.11: P. 4. 41
CINPTY.CINAME; INVBODMI/GetParty	The field indicates the customer name.
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address	
@type	Set to 'text'.
880 F.D.U	
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/Attentio	
CINPTY.CIYREF; INVBODMI/GetParty	The field indicates the contact name.
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/Addres	
CINPTY.CICUA1, CICUA2, CICUA3,	The field indicates the address lines.
CICUA4; INVBODMI/GetParty	
@sequence	The field indicates the address line assurance
	The field indicates the address line sequence.
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/CityNar	
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/Country	
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]-
	[SubDivisionCode] can be translated in CRS881/882. It can be
	necessary because this field is limited to 2 characters in M3 but can
	require more characters in ISO 3166 standard.
	E. a. for the Maxison state Ovintana Boo IMV DOI son he translated to
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to
	'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: AreaState
@listID	Bata domoni. A dabtato
©	Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/Country	vCode
CINPTY.CICSCD; INVBODMI/GetParty	The field indicates the country code.
•	•
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
@lietD	Data element: CountryCode
@listID	Set to 'Countries'.
MOPPH water flow is a line to the same and t	
M3EDIInvoice/InvoiceLine/CustomerParty/Location/Address/PostalC	
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the postal code.
M3EDIInvoice/InvoiceLine/CustomerParty/Contact/ID	
OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the contact ID.

he field indicates the contact name. the field indicates the sequence number. tet to 'false'. nelCode tet to "Phone" if telephone number is 1, 2, facsimile number or
net to 'false'.
net to 'false'.
nelCode
nobile.
et to "EMail" if e-mail address.
et to 'Communication Channels'.
ode
tet to "Office" if telephone number is 1, 2 or e-mail address. tet to "Fax" if facsimile number.
tet to "Communication Use Codes".
<i>lumber</i> he field indicates the telephone number.
The field intellection are telephone maniper.
ess
et to 'text'.
ess/AddressLine
he field indicates the address lines.
he field indicates the address sequence number.
ess/CityName
he field indicates the city name.
ess/CountrySubDivisionCode The field indicates an area, province or state within a country.
CountryCode is specified, the value of [CountryCode]-
SubDivisionCode] can be translated in CRS881/882. It can be
ecessary because this field is limited to 2 characters in M3 but can equire more characters in ISO 3166 standard.
.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
can be defined on the company level only.
/lsg std: ION /ers: 1
lessage: Generic
O: O larent element(s): Generic
ata element: AreaState
etto 'Canadian Provinces' if the country is CA (Canada).
etto 'France - Departements' if the country is FR (France).
et to 'US States' if the country is US (United States). tet to 'SubDivisions - <country code="">' for other countries.</country>
et to "SubDivisions" if no Country is specified.
ess/CountryCode he field indicates the country code.
he value can be translated in CRS881/882.
can be defined on the company level only.
Isg std: ION
'ers: 1 lessage: Generic
0: 0
arent element(s): Generic lata element: CountryCode
·
tet to 'Countries'.
ess/PostalCode he field indicates the postal code.
no nora maioatos tro postal GUGE.
the field indicates the email address.

	Set to 'false'.
M3EDIInvoice/InvoiceLine/CustomerParty/Contact/Communication/	
wiseDimvoice/invoiceEme/customerFarty/contact/communication//	Set to 'false'.
M3EDIInvoice/InvoiceLine/SalesOrderReference/DocumentID/ID	
CINDRE.CIDIDN; INVBODMI/SelDocReference @accountingEntity	The field indicates the customer order number.
	The field indicates the company and division, displayed as
@location	CONO_DIVI.
CINLIN.CIWHLO; INVBODMI/SelLines	The field indicates the warehouse.
M3EDIInvoice/InvoiceLine/SalesOrderReference/LineNumber CINDRE.CIDIDN; INVBODMI/SelDocReference	The field indicates the customer order line number.
M3EDIInvoice/InvoiceLine/SalesOrderReference/SubLineNumber CINDRE.CIDLSN; INVBODMI/SelDocReference	The field indicates the customer order subline number.
M3EDIInvoice/InvoiceLine/Rebate	
@type	If IVTP = 69 then set to 'Supplier'.
	If IVTP = 37 then set to Supplier.
M3EDIInvoice/InvoiceLine/Rebate/Amount	
CINLIN.CIREB1; INVBODMI/SelLines	The field indicates the rebate amount in transaction currency.
@currencyID CINHED.CICUCD; INVBODMI/GetHeader	The field indicates the transaction currency
CINNED.CICOCD, INVECTIVINGENERALE	The field indicates the transaction currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIInvoice/InvoiceLine/Rebate/BaseAmount	Data clotherit. Ourierley
CINLIN.CIREBL; INVBODMI/SelLines	The field indicates the rebate amount in local currency.
@currencyID CINHED.CILOCD; INVBODMI/GetHeader	The field indicates the local currency.
	The value can be translated in CDC004/002
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
M3EDIInvoice/InvoiceLine/ShipToParty/PartyIDs/ID	·
CINPTY.CICUNO; INVBODMI/GetParty	The field indicates the delivery customer.
	IF address number (ADID) is not blank, publish CUNO + ADID.
	It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is
	determined by its maximum length, specified in brackets. If the data
	does not consume the maximum length, the rest is filled up with
	spaces. This applies to all fields that are part of the delivery customer
	code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.
	The value can be translated in CRS881/882.
	It can be defined on the division or company level. Translation that is
	defined on the division level is primarily selected. If there is no
	translation on division level, translation on the company level is
	considered by the BOD.
	Msg std: M3EDI
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): ShipToParty
@schemeName	Data element: PartyID
	Set to 'CustomerNumber'.
M3EDIInvoice/InvoiceLine/ShipToParty/PartyIDs/TaxID	The field indicates the following Tay IDs of the Chief's queternous
1) CINPTY.CIVRNO 2) CINPTY.CIVRNL	The field indicates the following Tax IDs of the ShipTo customer: 1) VAT Registration number (VRNO).
3) CINPTY.CICORG	2) Tax declaration number (VRNL).
4) CINPTY.CICOR2	3) CountryldentificationNumber (CORG).
5) CINPTY CININO	4) CountryIdentificationNumber (COR2).
6) CINPTY.CININO	5) CountryldentificationNumber (COR4).
Infor May 26, 2	, ,

7) CINIDTY CINING : INV/DODMI/CatDoub.	6) National Identity Number (NINO).
7) CINPTY.CININ2.; INVBODMI/GetParty	7) National Identity Number (NINO).
@schemeName	, ,
	Set to 'TaxIdentificationNumber' if VRNO is displayed.
	Set to 'TaxDeclarationNumber' if VRNL is displayed.
	Set to 'CountryldentificationNumber' if CORG is displayed.
	4) Set to 'CountryldentificationNumber' if COR2 is displayed.
	5) Set to 'CountryldentificationNumber' if COR4 is displayed.
	6) Set to 'NationalIdentityNumber: if NINO is displayed.
	7) Set to 'NationalIdentityNumber: if NIN2 is displayed.
M3EDIInvoice/InvoiceLine/ShipToParty/Name	T. C. I. P. A. W. J. P.
CINPTY.CINAME; INVBODMI/GetParty @languageID	The field indicates the delivery customer name.
CINHED.CILNCD; INVBODMI/GetHeader	The field indicates the language.
OINTIED. OIENOD, IIVVDODIVII/OCTICAGO	The held indicates the language.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: languageCode
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address	Bata dismont. language code
@type	
٩	Set to 'text'.
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/AttentionOf	
CINPTY.CIYREF; INVBODMI/GetParty	The field indicates the contact name.
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/AddressLin	
CINPTY.CICUA1, CICUA2, CICUA3,	The field indicates the address lines.
CICUA4; INVBODMI/GetParty	The held maleates the address into.
@sequence	
<u> </u>	The field indicates the address line sequence.
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/CityName	
CINPTY.CITOWN; INVBODMI/GetParty	The field indicates the city name.
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/CountrySub	DivisionCode
CINPTY.CIECAR; INVBODMI/GetParty	The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]-
	[SubDivisionCode] can be translated in CRS881/882. It can be
	necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.
	require more characters in 130 3100 standard.
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to
	'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: AreaState
@listID	
-	Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/CountryCod	
CINPTY.CICSCD; INVBODMI/GetParty	The field indicates the country code.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
@listID	Data element: CountryCode
whou b	Set to 'Countries'.
MIZEI)IINVOICO/INVOICOI INO/Shin I ADartu/I Acation/Address/Daatai/Sada	
M3EDIInvoice/InvoiceLine/ShipToParty/Location/Address/PostalCode CINPTY CIPONO: INVBODMI/GetParty	
CINPTY.CIPONO; INVBODMI/GetParty	The field indicates the postal code.
	The field indicates the postal code.

M3EDIInvoice/InvoiceLine/ShipToParty/Communication/ChannelCod	
@listID	Set to 'Phone
M3EDIInvoice/InvoiceLine/ShipToParty/Communication/UseCode	Set to 'Communication Channels'.
·	Set to 'Office', If PHNO. Set to 'Fax', If TFNO.
@listID	Set to 'Communication Use Codes'.
M3EDIInvoice/InvoiceLine/ShipToParty/Communication/DialNumber CINPTY.; INVBODMI/GetParty	The field indicates the telephone number (PHNO) or fax number (TFNO) of the delivery customer.
M3EDIInvoice/InvoiceLine/ShipToParty/Communication/Preference/I	<i>ndicator</i> Set to 'false'.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer @accountingEntity	The field indicates the contact ID.
	The field indicates the company and division, displayed as CONO_DIVI.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication	
@sequence	The field indicates the sequence number.
@preferredIndicator	Set to 'false'.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Cha	
	mobile. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Use	
@listID	Set to "Office" if telephone number is 1, 2 or e-mail address.
MATRIC CONTRACTOR OF THE CONTR	Set to "Communication Use Codes".
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Dial CCUCON.CCPHO CCPHN2; CRS618MI/Get	The field indicates the telephone number.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Add CCUCON.CCTOWN; CRS618MI/Get	ress/CityName The field indicates the city name.
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Add	
CCUCON.CCECAR; CRS618MI/Get	The field indicates an area, province or state within a country.
	If CountryCode is specified, the value of [CountryCode]- [SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard.
	E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard.
	It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic
0.11.415	Parent element(s): Generic Data element: AreaState
@listID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Add CCUCON.CCCSCD; CRS618MI/Get	ress/CountryCode The field indicates the country code.
CCCCON.CCCCCD, CROUTOWIFGEL	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O

@listID Set to 'Countries'. M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Address/PostalCode CCUCON.CCPONO; CRS618MI/Get The field indicates the postal code. M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/URI CCUCON.CCEMAL; CRS618MI/Get The field indicates the email address. M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/HTMLPreferredIndicator Set to 'false' M3EDIInvoice/InvoiceLine/ShipToParty/Contact/Communication/Preference/Indicator Set to 'false'. M3EDIInvoice/InvoiceLine/ShipFromParty/PartyIDs/ID CINPTY:; INVBODMI/GetParty The field indicates the warehouse ID. The value can be translated in CRS881/882. It can be defined on the division or company level. Translation that is defined on the division level is primarily selected. If there is no translation on division level, translation on the company level is considered by the BOD. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipFromParty Data element: PartyID @accountingEntity The field indicates the company and division, displayed as CONO DIVI. M3EDIInvoice/InvoiceLine/ShipFromParty/Name CINPTY.CINAME; INVBODMI/GetParty The field indicates the warehouse name. M3EDIInvoice/InvoiceLine/ShipFromParty/Location @type Set to 'Warehouse'. M3EDIInvoice/InvoiceLine/ShipFromParty/Location/ID CINPTY.; INVBODMI/GetParty The field indicates the warehouse. M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address @type Set to 'text' M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address/AddressLine CINPTY.CICUA1, CICUA2, CICUA3, The field indicates the address lines. CICUA4; INVBODMI/GetParty @sequence The field indicates the address line sequence M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address/CityName CINPTY.CITOWN; INVBODMI/GetParty The field indicates the city name. M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address/CountrySubDivisionCode CINPTY.CIECAR; INVBODMI/GetParty The field indicates an area, province or state within a country. If CountryCode is specified, the value of [CountryCode]-[SubDivisionCode] can be translated in CRS881/882. It can be necessary because this field is limited to 2 characters in M3 but can require more characters in ISO 3166 standard. E.g. for the Mexican state Quintana Roo 'MX-RO' can be translated to 'ROO' for CountrySubDivisionCode to comply to ISO 3166 standard. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: AreaState @listID Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address/CountryCode CINPTY.CICSCD; INVBODMI/GetParty The field indicates the country code.

Parent element(s): Generic Data element: CountryCode

Infor May 26, 2023 37

The value can be translated in CRS881/882.

It can be defined on the company level only.

Msg std: ION

Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: CountryCode

@listID

Set to 'Countries'.

M3EDIInvoice/InvoiceLine/ShipFromParty/Location/Address/PostalCode

CINPTY.CIPONO; INVBODMI/GetParty

The field indicates the postal code.

M3EDIInvoice/InvoiceLine/PricingAmount/UnitPretaxAmount

CINLIN.CIUPAM; INVBODMI/SelLines

CINHED.CICUCD; INVBODMI/GetHeader

@currencyID

The field indicates the net price of the item.

The field indicates the transaction currency.

The value can be translated in CRS881/882.

It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic

Data element: Currency

M3EDIInvoice/InvoiceLine/PricingAmount/TotalPretaxAmount

CINLIN.CITPTA; INVBODMI/SelLines

The field indicates the amount of order line after line discount deducted, line charge included but VAT excluded (foreign).

@currencyID

CINHED.CICUCD; INVBODMI/GetHeader

The field indicates the transaction currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION

Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: Currency

M3EDIInvoice/InvoiceLine/PricingAmount/TotalPretaxBaseAmount

CINLIN.CITPLA; INVBODMI/SelLines

The field indicates the amount of order line after line discount deducted, line charge included but VAT excluded (local).

@currencyID

CINHED.CILOCD; INVBODMI/GetHeader

The field indicates the local currency.

The value can be translated in CRS881/882.

It can be defined on the company level only.

Msg std: ION

Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic

Data element: Currency

M3EDIInvoice/InvoiceLine/PricingAmount/TotalPretaxReportAmount

CINHED.CILOCD; INVBODMI/GetHeader

The field indicates the local currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION

Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: Currency

May 26, 2023

M3EDIPickList

M2EDIBiokl int/TradingPortporID	
M3EDIPickList/TradingPartnerID	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
@schemeName	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPickList/PickListHeader/DocumentID/ID	
MHPICL.H5DLIX MHPICL.H5PLSX.; MHS810MI/LstPickList @accountingEntity	The field indicates the Delivery number and Picklist suffix separated by '/'.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPickList/PickListHeader/AlternateDocumentID/ID MHPICL.H5CUOR; MHS810MI/LstPickList @schemeName	The field indicates the customer's order number.
<u></u>	set to 'Customer'.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.: /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPickList/PickListHeader/DocumentDateTime MHPICL.H5RGDT MHPICL.H5RGTM.; MHS810MI/LstPickList	The field indicates the entry date and time.
M3EDIPickList/PickListHeader/RouteID MHPICL.H5ROUT; MHS810MI/LstPickList	The field indicates the route.
M3EDIPickList/PickListHeader/WeightMeasure MHPICL.H5GRWE; MHS810MI/LstPickList @unitCode	The field indicates the gross weight.
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
M3EDIPickList/PickListHeader/VolumeMeasure MHPICL.H5VOL3; MHS810MI/LstPickList @unitCode	The field indicates the volume.
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the unit code.
M3EDIPickList/PickListHeader/TransportationTerm/IncotermsCode MHPICL.H5TEDL; MHS810MI/LstPickList	The field indicates the delivery term.
M3EDIPickList/PickListHeader/TransportationMethodCode MHPICL.H5MODL; MHS810MI/LstPickList	The field indicates the delivery method.
M3EDIPickList/PickListHeader/PlannedShipDateTime MHPICL.H5DSDT MHPICL.H5DSHM.; MHS810MI/LstPickList	The field indicates the planned departure date and time.
M3EDIPickList/PickListHeader/ShipFromParty/Location/ID MHPICL.H5WHLO; MHS810MI/LstPickList @accountingEntity	The field indicates the warehouse.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPickList/PickListHeader/ShipToParty/PartyIDs/ID MHPICA.H7CUNO; MHS810MI/LstPickListAdr	The field indicates the customer.
@accountingEntity	The value is retrieved from address type 01 (ADRT = 01).
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPickList/PickListHeader/ShipToParty/Name MHPICA.H7CUNM; MHS810MI/LstPickListAdr	The field indicates the customer name.
	The value is retrieved from address type 01 (ADRT = 01).
M3EDIPickList/PickListHeader/ShipToParty/Location/Address @type	set to 'text'.
M3EDIPickList/PickListHeader/ShipToParty/Location/Address/Addres	
M3EDIFICKLISUFICKLISUHEADEI/SIIIPTOFAITY/LOCALIOII/ADDIFESS/ADDIFES MHPICA.H7ADR1	The field indicates the address line.
MHPICA.H7ADR2 MHPICA.H7ADR3 MHPICA.H7ADR4.; MHS810MI/LstPickListAdr	The value is retrieved from address type 01 (ADRT = 01).
@sequence	The field indicates the address line assurers
	The field indicates the address line sequence.
M3FDIPickl ist/Pickl istHeader/ShinToParty/l ocation/Address/CityNa	me
M3EDIPickList/PickListHeader/ShipToParty/Location/Address/CityNa MHPICA.H7TOWN; MHS810MI/LstPickListAdr	The field indicates the city name. The value is retrieved from address type 01 (ADRT = 01).

M3EDIPickList

WISEDIPICKLIST	
MHPICA.H7ECAR; MHS810MI/LstPickListAdr	The field indicates an area, province or state within a country.
@liestD	The value is retrieved from address type 01 (ADRT = 01).
@listID	Set to 'US States' if CSCD = US.
	Set to 'Canadian Provinces" if CSCD = CA.
	Set to 'France - Departements'if CSCD = FR.
	Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIPickList/PickListHeader/ShipToParty/Location/Address/Count	
MHPICA.H7CSCD; MHS810MI/LstPickListAdr	The field indicates the country code.
	The value is retrieved from address type 01 (ADRT = 01).
@listID	Set to 'Countries'.
M3EDIPickList/PickListHeader/ShipToParty/Location/Address/Posta	
MHPICA.H7PONO; MHS810MI/LstPickListAdr	The field indicates the postal code.
	The value is retrieved from address type 01 (ADRT = 01).
M3EDIPickList/PickListHeader/SupplierParty/PartyIDs/ID	
OCUSMA.OKCUSU; MWS410Ml/ĠetHead @accountingEntity	The field indicates the supplier number at customer.
CMNDIV.CCCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
M3EDIPickList/PickListLine/LineNumber	
	The field indicates the pick list line number.
M3EDIPickList/PickListLine/DocumentReference	
@type MHPICD.H6TTYP; MHS10MI/LstPickDetail	The field indicates the transaction type.
	If TTYP = 11, set to 'ProductionOrder'.
	If TTYP = 31, set to 'Foddodionordor'.
	If TTYP = 41, set to 'Transfer'.
	If TTYP = 51, set to 'Transfer'.
	If TTYP= 61, set to 'WorkOrder'. If TTYP = 71, set to 'ServiceOrder'.
MOEDID: LLI: -4/D: -LLi: -4/ in -/D/D	II TITP = 71, set to ServiceOrder.
M3EDIPickList/PickListLine/DocumentReference/DocumentID/ID MHPICD.H6RIDN; MHS10MI/LstPickDetail	The field indicates the reference order number.
@accountingEntity	
CMNDIV.CCCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; / M3EDIPickList/PickListLine/DocumentReference/LineNumber	CONO_DIVI.
MHPICD.H6RIDL; MHS10MI/LstPickDetail	The field indicates the reference order line number.
M3EDIPickList/PickListLine/DocumentReference/SubLineNumber MHPICD.H6RIDX; MHS10MI/LstPickDetail	The field indicates the reference order line suffix.
M3EDIPickList/PickListLine/Item/ItemID/ID	
MHPICD.H6ITNO; MHS10MI/LstPickDetail	The field indicates the item number.
@accountingEntity	
CMNDIV.CCCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO DIVI.
M3EDIPickList/PickListLine/Item/UPCID	
MITPOP.MPPOPN; MMS025MI/LstAlias	The field indicates the alias number which is an alternative ID for an
	individual item. This value is retrieved from Item. Connect Alias
	Number (MMS025) in M3 with alias category (ALWT) = 02 and alias
MOEDIDiald in 4/Diald in 4/ in - //4 /EDOID	qualifier (ALWQ) = UPC.
M3EDIPickList/PickListLine/Item/EPCID MITPOP.MPPOPN; MMS025MI/LstAlias	The field indicates the alias number which is an alternative ID for an
IVITT OF TVILLY INTO INTO INTO INTO INTO INTO INTO INTO	individual item. This value is retrieved from Item. Connect Alias
	Number (MMS025) in M3 with alias category (ALWT) = 02 and alias qualifier (ALWQ)= EA13.
M3EDIPickList/PickListLine/Item/GTIN	quanto (ALVIX) - LATO.
MITPOP.MPPOPN	The field indicates the alias number which is an alternative ID for an
; MMS025MI/LstAlias	individual item. This value is retrieved from Item. Connect Alias
, MINICOZOWII/ LOU MINICO	Number (MMS025) in M3 with alias category (ALWT) = 02.
	Display if Alias qualifier (ALWQ) is GTIN, EA08, UPC, EA13 or DU1
@schemeName	Display if Alias qualifier (ALTTA) is OTHY, LAUG, OF G, LATS OF DUT
MITPOP.MPALWQ	The field indicates the alias qualifier.
; MMS025MI/LstAlias	Set to 'EA08' if alias qualifier (ALWQ) is EA08
, mmodeown Log mad	Set to 'UPC' if alias qualifier (ALWQ) is UPC
	Set to 'EA13' if alias qualifier (ALWQ) is EA13
	Set to 'DU14' if alias qualifier (ALWQ) is DU14 Do not publish if alias qualifier (ALWQ) is GTIN
M3EDIPickList/PickListLine/Item/Classification/Codes/Code	25 St passion it aliae qualifor (richtig) to OTH
MHPICD.H6WHSL; MHS10MI/LstPickDetail	The field indicates the location if @listID is 'Location'.
Infor May 26, 20	-

M3EDIPickList

@listID	
	If set to 'Location' then Classification/Codes/Code indicates the location.
M3EDIPickList/PickListLine/Item/Packaging/ID	
MHPICD.H6PACT; MHS10MI/LstPickDetail	The field indicates the packaging.
M3EDIPickList/PickListLine/SerializedLot/Lot/LotIDs/ID	
MHPICD.H6BANO; MHS10MI/LstPickDetail	The field indicates the lot number.
M3EDIPickList/PickListLine/SerializedLot/Lot/Quantity	
MHPICD.H6ALQT; MHS10MI/LstPickDetail	The field indicates the allocated quantity.
@unitCode	
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the item's basic unit of measure.
M3EDIPickList/PickListLine/Quantity	
MHPICD.H6ALQT; MHS10MI/LstPickDetail	The field indicates the allocated quantity.
@unitCode	
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the item's basic unit of measure.

M3EDIPriceList

MOLDII HOCLIST	
M3EDIPriceList/TradingPartnerID	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
@schemeName	The field indicates the trading partner ID schemeName. The value is
	retrieved from field RRD2 in CRS949/J.
M3EDIPriceList/PriceListHeader/DocumentID/ID OPRRED.SQRPID; /	The field indicates the ID used to identify a report in the report generator for sales price list.
@accountingEntity CMNDIV.CCCONO CCDIVI: /	The field indicates the company and division.
@variationID	
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
M3EDIPriceList/PriceListHeader/DocumentDateTime	The field indicates the logical ib of the system.
OPRRED.SQSTDT; OIS530MI/GetHead	The field indicates the start date.
M3EDIPriceList/PriceListHeader/CurrencyCode	The hold indicates the start date.
OPRRED.SQCUCD; OIS530MI/GetHead	The field indicates the currency code.
M3EDIPriceList/PriceListHeader/PublisherParty/PartyIDs/ID	The field indicates the division. The values is retrieved from MBMInit.
CMNDIV.CCDIVI; / @accountingEntity	The field indicates the division. The values is retrieved from MBMinit.
CMNDIV.CCCONO	The field indicates the company and division.
CCDIVI; /	· ,
M3EDIPriceList/PriceListHeader/CustomerParty/PartyIDs/ID OPRRED.SQCUNO; OIS530MI/GetHead	The field indicates the customer number.
@accountingEntity CMNDIV.CCCONO	The field indicates the company and division.
CCDIVI; /	The held indicates the company and division.
M3EDIPriceList/PriceListLine/Item/ItemID/ID OPRLRP.SWITNO; OIS530MI/LstLine	The field indicates the item number.
@accountingEntity	The field indicates the item number.
CMNDIV.ČCCOŃO CCDIVI: /	The field indicates the company and division.
M3EDIPriceList/PriceListLine/Item/CustomerItemID/ID	
MITPOP.MPPOPN; MMS025MI/GetAlias	The field indicates the customer's item number. This value is retrieved from the Item/Alias file with alias category (ALWT) = 6 and partner (E0PA) same as the customer.
@accountingEntity CMNDIV.CCCONO CCDIVI: /	The field indicates the company and division.
M3EDIPriceList/PriceListLine/Item/UPCID	
MITPOP.MPPOPN; MMS025MI/GetAlias	The field indicates the alias number. This value is retrieved from the Item/Alias file with alias category (ALWT) = 02 and alias qualifier (ALWQ) = UPC
M3EDIPriceList/PriceListLine/Item/EPCID	
MITPOP.MPPOPN; MMS025MI/GetAlias	The field indicates the alias number. This value is retrieved from the Item/Alias file with alias category (ALWT) = 02 and alias qualifier (ALWQ)= EA13
M3EDIPriceList/PriceListLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItmBasic	The field indicates the item's name.
M3EDIPriceList/PriceListLine/Item/Specification/Property/Effectiv	
OPRLRP.SWPSFD; OIS530MI/LstLine	The field indicates the sales price start date.
M3EDIPriceList/PriceListLine/Item/Specification/Property/Effectiv OPRLRP.SWPSTD; OIS530MI/LstLine	eTimePeriod/EndDateTime The field indicates the sales price end date.
M3EDIPriceList/PriceListLine/UnitPrice/Amount OPRLRP.SWSAPR; OIS530MI/LstLine	The field indicates the sales price.
@currencyID OPRLRP.SWPSCU; OIS530MI/LstLine	The field indicates the sales price currency code.
M3EDIPriceList/PriceListLine/UnitPrice/PerQuantity	The field indicates the sales price sufferior code.
OPRLRP.SWSACD; OIS530MI/LstLine @unitCode	The field indicates the sales price quantity.
OPRLRP.SWSPUN; OIS530MI/LstLine	The field indicates the sales price quantity unit of measure.
M3EDIPriceList/PriceListLine/PriceBreak/DiscountAmount OPRLRP.SWDIA1 - SWDIA6; OIS530MI/LstLine	The field indicates the discount amount.
@currencyID OPRLRP.SWCUC3; OIS530MI/LstLine	The field indicates the currency code.
M3EDIPriceList/PriceListLine/PriceBreak/DiscountPercent	The lielu iliuloates the cuttericy code.
OPRLRP.SWDIP1 - SWDIP6; OIS530MI/LstLine	The field indicates discount percentage.

MOLDII dicilascoraci	
M3EDIPurchaseOrder/TradingPartnerID	The field indicates the trading wants of ID. The value is nationed from
@schemeName	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
goonemename	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentID/ID MPHEAD.IAPUNO; PPS200MI/GetHead	The field indicates the Purchase Order number.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MPHEAD.IAWHLO; PPS200MI/GetHead @variationID	The field indicates the warehouse.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentID/RevisionID	<u> </u>
MPHEAD.IAREVN; PPS200MI/GetHead	The field indicates a revision. By using the revision number, it is possible to ascertain which purchase order lines are connected to a certain revision by updating them with the revision number.
M3EDIPurchaseOrder/PurchaseOrderHeader/DisplayID MPHEAD.IAPUNO; PPS200MI/GetHead	The field indicates the Purchase Order number.
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentDateTime MPHEAD.IAPUDT; PPS200MI/GetHead	The field indicates when the purchase order was placed.
M3EDIPurchaseOrder/PurchaseOrderHeader/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt	The field indicates the notes or remarks.
M3EDIPurchaseOrder/PurchaseOrderHeader/Status/Code MPHEAD.IAPUSL; PPS001MI/GetHeadBasic	The field indicates the following status of the Purchase Order Head: 15-Open 20-Open 25-Open 31-Open 32-Open 33-Open 35-Open 40-Open 45-Open 50-Recevied 51-Received 60-Received 64-Received 65-Received 67-Received 69-Received 89-Received 70-Partially Received 80-Invoiced
M3EDIPurchaseOrder/PurchaseOrderHeader/CustomerParty/PartyIDs CMNDIV.CCCONO CMNDIV.CCDIVI.; /	90-Invoiced 99-Canceled
	Company (CONO) and Division (DIVI). The value of this field can be translated in programs CRS881/882.
M3EDIPurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerCo CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates a description of the current identity.
M3EDIPurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerCo	ontact/Communication/ChannelCode Set to 'EMail' if URI or email is not empty.
M3EDIPurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerCo CMNUSR.JUPHNO; MNS150MI/GetUserData	The field indicates the Buyer phone number.
M3EDIPurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerCo CEMAIL.CBEMAL; CRS111MI/Get	ontact/Communication/URI The field indicates an e-mail address of the buyer.
M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/PartyIDs/ MPHEAD.IASUNO; PPS200MI/GetHead	The field indicates the unique identity of a supplier.
@accountingEntity	The value of this field can be translated in programs CRS881/882.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Name CIDMAS.IDSUNM; PPS200MI/GetAddresses	The field indicates the name of the supplier.
Infor May 26, 202	23 3

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address

@type

Set to 'text'

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/AttentionOfName

MPHEAD.IAYRE1; PPS200MI/GetHead The field indicates the supplier reference

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/AddressLine MPPOAD.ADADR1 The field indicates an address line.

MPPOAD.ADADR2 MPPOAD.ADADR3

MPPOAD.ADADR4.; PPS200MI/GetAddresses

@sequence The field indicates the address line sequence

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/CityName MPPOAD.ADTOWN; PPS200MI/GetAddresses The field indicates the city name.

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/CountrySubDivisionCode

MPPOAD.ADECAR; PPS200MI/GetAddresses The field indicates a state or province within a country.

@listID

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/CountryCode

MPPOAD.ADCSCD; PPS200MI/GetAddresses The field indicates a country.

The value can be translated in CRS881/882.

It can be defined on the division or on the company level.

Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: CountryCode

@listID

Set to 'Countries'

M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address/PostalCode

MPPOAD.ADPONO; PPS200MI/GetAddresses The field indicates a postal code

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/PartyIDs/ID

MPPOAD.ADADK2; PPS200MI/GetAddresses

The field indicates the destination warehouse.

The value can be translated in CRS881/882.

It can be defined on the division or on the company level.

Msg std: M3EDI

Vers: 1

Message: Generic

I/O: O

Parent element(s):ShipToParty

Data element: PartyID

CMNDIV.CCCONO CMNDIV.CCDIVI.;

The field indicates the company and division, displayed as

CONO DIVI

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Name

MPPOAD.ADCONM; PPS200MI/GetAddresses

The field indicates the name of the company

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/ID

MPPOAD.ADADK2; PPS200MI/GetAddresses

The field indicates the destination warehouse.

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address

@type

Set to 'text'.

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/AddressLine The field indicates an address line.

MPPOAD.ADADR1

@accountingEntity

MPPOAD.ADADR2 MPPOAD.ADADR3

MPPOAD.ADADR4.; PPS200MI/GetAddresses @sequence

The field indicates the address line sequence

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CityName

MPPOAD.ADTOWN; PPS200MI/GetAddresses The field indicates the city name.

M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CountrySubDivisionCode

MPPOAD.ADECAR; PPS200MI/GetAddresses

The field indicates a state or province within a country.

@listID

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).

May 26, 2023

Set to 'SubDivisions - < Country Code>' for other countries. Set to "SubDivisions" if no Country is specified M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CountryCode MPPOAD.ADCSCD; PPS200MI/GetAddresses The field indicates a country. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode @listID Set to 'Countries' M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/PostalCode MPPOAD.ADPONO; PPS200MI/GetAddresses The field indicates a postal code M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/PartyIDs/ID MPHEAD.IASUNO: PPS200MI/GetHead The field indicates the unique identity of a supplier. The value of this field can be translated in programs CRS881/882. @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location @type Set to 'Distribution Center' if the warehouse type of the destination warehouse is set as Distribution Center. M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/ID MPHEAD.IAWHLO; PPS200MI/GetHead The field indicates the destination warehouse. @accountingEntity CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI. M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address @type Set to 'text'. M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/AddressLine CIADDR.OAADR1 The field indicates the address line CIADDR OAADR2 CIADDR.OAADR3 CIADDR.OAADR4.; MMS005MI/GetWarehouse @sequence The field indicates the address line sequence M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CityName CIADDR.OATOWN; MMS005MI/GetWarehouse The field indicates the city name. M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CountrySubDivisionCode CIADDR.OAECAR; MMS005MI/GetWarehouse The field indicates a state or province within a country. @listID Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CountryCode CIADDR.OACSCD; MMS005MI/GetWarehouse The field indicates a country. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode @listID Set to 'Countries M3EDIPurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/PostalCode CIADDR.OAPONO; MMS005MI/GetWarehouse The field indicates a postal code M3EDIPurchaseOrder/PurchaseOrderHeader/ContractReference/DocumentID/ID MPHEAD.IAOURR; PPS200MI/GetHead The field indicates the contract/agreement number. M3EDIPurchaseOrder/PurchaseOrderHeader/ExtendedAmount MPHEAD.IACOAM; PPS200MI/GetHead The field indicates total order amount. @currencyID MPHEAD.IACUCD; PPS200MI/GetHead

May 26, 2023 38

M3EDIPurchaseOrder	
	The field indicates currency used.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element:Currency
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead	The field indicates the payee.
@accountingEntity	The value of this field can be translated in programs CRS881/882.
CMNDIV.CCCONO CMNDIV.CCDIVI.: /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Name MPPOAD.ADCONM; PPS200MI/GetAddresses	The field indicates the invoice receiver name.
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Ac @type	
	Set to 'text'.
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/AdMPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4; PPS200MI/GetAddresses	ddress/AddressLine The field indicates the invoice receiver address.
@sequence	The field indicates the address line sequence.
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Ad MPPOAD.ADTOWN; PPS200MI/GetAddresses	· · · · · · · · · · · · · · · · · · ·
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Ad	ddress/CountrySubDivisionCode
MPPOAD.ADECAR; PPS200MI/GetAddresses @listID	The field indicates a state or province within a country.
<u></u>	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Ac MPPOAD.ADCSCD; PPS200MI/GetAddresses	ddress/CountryCode The field indicates a country.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
@listID	Data element: CountryCode
- MOSEDID:::::abaaa Oudau/D:::abaaa Oudau/Iaadau/D:!!Ta Daub//Iaadau/A	Set to 'Countries'.
M3EDIPurchaseOrder/PurchaseOrderHeader/BillToParty/Location/AdMPPOAD.ADPONO; PPS200MI/GetAddresses	The field indicates a postal code.
M3EDIPurchaseOrder/PurchaseOrderHeader/TransportationTerm/Ind MPHEAD.IATEDL; PPS200MI/GetHead	CotermsCode The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID	Set to 'Incoterms'.
M3EDIPurchaseOrder/PurchaseOrderHeader/TransportationTerm/From MPHEAD.IATEAF; PPS200MI/GetHead	
M3EDIPurchaseOrder/PurchaseOrderHeader/PaymentTerm/Payment MPHEAD.IATEPY; PPS200MI/GetHead	
@listID	Set to 'Payment Term'.
M3EDIPurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/De. CSYTAB.CTPARM; PPS200MI/GetHead	scription The field indicates the description of the payment term.
M3EDIPurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Am MPHEAD.IACOAM; PPS200MI/GetHead @currencyID	
MPHEAD.IACUCD; PPS200MI/GetHead	
Infor May 26, 20	23

MISEDIPUICHASEOLUEI	
	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the division or on the company level.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element:Currency
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge	
@type MPOEXP.IVEXTY; PPS215MI/LstPOCharges	The field indicates the type of charge the costing element represents. If EXTY = 2, set to 'External charge'. Only external costing elements are included
@sequence MPOEXP.IVCDSE; PPS215MI/LstPOCharges	The field indicates the sequence number of the costing element.
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge/ID	
MPOEXP.IVCEID; PPS215MI/LstPOCharges	The field indicates the costing element. Only external costing elements are Included. Only costing elements with operators different than 15, 16, 77, 90 and 91 are added included. Costing elements with distribution method = 3 are not included.
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge/Desc MPCELE.INTX30; PPS280MI/GetElement	cription 1) Set to 'Order discount'. 2) The field indicates the costing element description.
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge/Amo	
1) MPHEAD.IAODAM; PPS200MI/GetHead	The field indicates the order total discount. The field indicates the costing element amount. CEVA + CEVJ.
2) MPOEXP.IVCEVA	
MPOEXP.IVCEVJ;	
PPS215MI/LstPOCharges.; /	
@currencyID MPHEAD.IACUCD; PPS200MI/GetHead MPOEXP.IVCUCD;	The field indicates the currency.
PPS215MI/LstPOCharges.; /	
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge/Reas	
MPOEXP.IVEXIC; PPS215MI/LstPOCharges	1) Set to 'Order discount'.
	 The field indicates if charges connected to a purchase order can be invoiced one time or several times. This field is only valid for external charges. If EXIC = 1, set to 'Only once'.
	If EXIC = 2, set to 'Several times'.
	Attribute list ID is set to 'Charge Invoicing'.
@listID	C C
	Set to 'Charge Invoicing' if DistributedCharge/ReasonCode is mapped to EXIC.
M3EDIPurchaseOrder/PurchaseOrderHeader/DistributedCharge/Gros	s WeightIndicator Set to 'false'.
M3EDIPurchaseOrder/PurchaseOrderHeader/Reference	
@sequence	The field indicates the sequence number
M2EDIDurahaan Orday/Durahaan Orday/Landay/Dafayyan Alayy	The field indicates the sequence number.
M3EDIPurchaseOrder/PurchaseOrderHeader/Reference/NameValue MBMTRD.TDMBMD; CRS881MI/GetTransIData	The field contains the ISASender and ISAReceiver data. Translation is available in CRS881. (Sequence 1) MSTD Message Standard should be set to M3EDI.
	MVRS Message Version should be set to 1 BMSG Business Message should be set to PurchaseOrder IBOB Inbound or Outbound Message should be set to O ELMP Parent Element should be set to PurchaseOrderHeader ELMD Data Element should be set to ISA MVXD Movex Data should be set to ISASender
	EXTP External Partner should be populated with the Supplier Number. If it does not find one, then it should look for the default one that has a Blank External Partner.
@name	(Sequence 2) Same data as above except for MVXD Movex Data should be set to ISAReceiver
@name	The field is set to 'ISASender' for Sequence 1 and 'ISAReceiver' for Sequence 2.
Infor May 26, 202	23 3

@type	Set to 'StringType'.
M3EDIPurchaseOrder/PurchaseOrderHeader/RequestedShipDate MPHEAD.IADWDT; PPS200MI/GetHead	
######################################	The field indicates when the purchase order was placed.
M3EDIPurchaseOrder/PurchaseOrderHeader/UserArea MPHEAD.IAPUST	The field indicates the following:
MPHEAD.IAPUSL MPHEAD.IANTAM MPHEAD.IACMCO	Purchase Order Highest Status Attribute Name is set to 'HighestStatus'.
MPHEAD.IANOLN MPHEAD.IABREM	Purchase Order Lowest Status Attribute Name is set to 'LowestStatus'.
8) MPHEAD.IAUCA1-IAUCA0 MPHEAD.IAUDN1-IAUDN6	3.) Net order value Attribute Name is set to 'SubTotalAmount'.
MPHEAD.IAUID1-IAUID3 MPHEAD.IAUCT1; PPS200MI/GetHead	4.) Media profile Attribute Name is set to 'MediaProfile'.
CUDFLD.FDTX15; CMS082/LstFields CUDFLV.FVTX40;	5.) Number of order lines. Attribute Name is set to 'OrderLineCount'.
CMS083/LstValues	6.) Order Value Gross Attribute Name is set to 'GrossTotalAmount'.
.; PPS001MI PPS001MI PPS200MI PPS200MI	7.) If the document is printed for the first time, the field is set to Original, else, Copy. Attribute Name is set to 'Purchase Order Print'.
PPS200MI PPS200MI	User-defined field The field indicates a user-defined field for displaying and storing you own information.
PPS200MI/GetHeadBasic GetHeadBasic GetHead GetHead GetHead GetHead GetHead	Set attribute name to 'm3. <m3 be="" field="">-<cms082 tx15="">'. Description is retrieved from CMS083 TX40. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS08 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.</cms082></m3>
GetHead	
#I3EDIPurchaseOrder/PurchaseOrderHeader/RFQReference/Docu MPHEAD.IAOURR; PPS200MI/GetHead	The field indicates the supplier quotation number.
//3EDIPurchaseOrder/PurchaseOrderHeader/Classification/Codes 1) MPHEAD.IAPOTC PPS200MI/GetHead	s/Code 1) Purchase Order category The field indicates purchase order category.
2) MPHEAD.IAORTY PPS200MI/GetHead	Set attribute listID to 'Purchase Order Categories'.
FF3ZUUWI/GetHeau	Z) Older type
3) CIDVEN.IIDCSM	Order type The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'.
3) CIDVEN.IIDCSM CRS620MI/GetBasicData 4) MPHEAD.IAAGNT PPS200MI/GetHead.; 1) PPS200MI 2) PPS200MI	The field indicates the purchase order type.
3) CIDVEN.IIDCSM CRS620MI/GetBasicData 4) MPHEAD.IAAGNT PPS200MI/GetHead.; 1) PPS200MI 2) PPS200MI 3) CRS620MI 4) PPS200MI/1) GetHead 2) GetHead 3) GetBasicData	The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'. 3) Discount calculation method The discount calculation method used. Set to 'Total discount' if value is 0. Set to 'Chain discount' if value is 1. Set attribute listID to 'Discount Calculation Method'. 4) Agent The field indicates the agent's number.
3) CIDVEN.IIDCSM CRS620MI/GetBasicData 4) MPHEAD.IAAGNT PPS200MI/GetHead.; 1) PPS200MI 2) PPS200MI 3) CRS620MI 4) PPS200MI/1) GetHead 2) GetHead 3) GetBasicData 4) GetHead	The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'. 3) Discount calculation method The discount calculation method used. Set to 'Total discount' if value is 0. Set to 'Chain discount' if value is 1. Set attribute listID to 'Discount Calculation Method'. 4) Agent
3) CIDVEN.IIDCSM CRS620MI/GetBasicData 4) MPHEAD.IAAGNT PPS200MI/GetHead.; 1) PPS200MI 2) PPS200MI 3) CRS620MI 4) PPS200MI/1) GetHead 2) GetHead 3) GetBasicData 4) GetHead 2) Sequence	The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'. 3) Discount calculation method The discount calculation method used. Set to 'Total discount' if value is 0. Set to 'Chain discount' if value is 1. Set attribute listID to 'Discount Calculation Method'. 4) Agent The field indicates the agent's number. Set attribute listID to 'Agent'. The field indicates the sequence number. 1) Set to 'Purchase Order Categories'. 2) Set to 'Purchase Order Types'. 3) Set to 'Discount Calculation Method'.
3) CIDVEN.IIDCSM CRS620MI/GetBasicData 4) MPHEAD.IAAGNT PPS200MI/GetHead.; 1) PPS200MI 2) PPS200MI 3) CRS620MI 4) PPS200MI/1) GetHead 2) GetHead 3) GetBasicData	The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'. 3) Discount calculation method The discount calculation method used. Set to 'Total discount' if value is 0. Set to 'Chain discount' if value is 1. Set attribute listID to 'Discount Calculation Method'. 4) Agent The field indicates the agent's number. Set attribute listID to 'Agent'. The field indicates the sequence number. 1) Set to 'Purchase Order Categories'. 2) Set to 'Purchase Order Types'.

2) MPORDT, OTTX15 PPS095MI/LstOrderType Set t 3) CIDMAS.IDSUNM CRS620MI.GetBasicData.; 1) PPS200MI 2) PPS200MI 3) CRS620MI/1) GetHead 3) CRS620MI/1) GetHead 2) GetHead 3) GetBasicData 3) GetBasicData 3) GetBasicData 3) GetBasicData 3) GetBasicData 3) The ### ### ### ### ### ### ### ### ### #	
PPS095MI/LstOrderType	o 'Consignment usage order' if PO category is 26. o 'Delivery schedule(rolling)' if PO category is 30. o 'Delivery schedule (time limiting)' if PO category is 40. o 'Repair order' if PO category is 60. o 'Warranty repair' if PO category is 65. o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. he field indicates the order type name. he field indicates the agent's name. field indicates a valid supplier number for the supplier that should give the payment. Payee is entered only if the supplier and the reare not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
Set t	o 'Delivery schedule(rolling)' if PO category is 30. o 'Delivery schedule (time limiting)' if PO category is 40. o 'Repair order' if PO category is 60. o 'Warranty repair' if PO category is 65. o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. he field indicates the order type name. he field indicates the agent's name. field indicates a valid supplier number for the supplier that should give the payment. Payee is entered only if the supplier and the he are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
3) CIDMAS.IDSUNM CRS620MI.GetBasicData.; 1) PPS200MI Set tt 2) PPS200MI 3) CRS620MI/1) GetHead 3) CRS620MI/1) GetHead 2) GetHead 3) GetBasicData 2) Ti 3) Ti M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The receipaye @accountingEntity CMNDIV.CCCONO CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstLine MSEDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 31-C 33-C 35-C 50-R 64-R 65-R 69-R 70-P 75-R 80-IR	o 'Delivery schedule (time limiting)' if PO category is 40. o 'Repair order' if PO category is 60. o 'Warranty repair' if PO category is 65. o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. he field indicates the order type name. he field indicates the agent's name. field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the he are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
CRS620MI GetBasicData; 1) PPS200MI	o 'Repair order' if PO category is 60. o 'Warranty repair' if PO category is 65. o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. ne field indicates the order type name. ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the re are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
2) PPS200MI 3) CRS620MI/1) GetHead 3) GetBasicData 2) Tit 2) Tit 3) Tit M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The receipaye @accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstLine/Note MSYTXH.THTX40; PPS200MI/LstLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 31-C 32-C 31-C 31-C 32-C 31-C 31-C 32-C 31-C 31-C 31-C 31-C 31-C 31-C 31-C 31	o 'Warranty repair' if PO category is 65. o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. ne field indicates the order type name. ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should tive the payment. Payee is entered only if the supplier and the se are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks.
3) CRS620MI/1) GetHead Set t 2) GetHead Set t 3) GetBasicData Set t 3) GetBasicData Set t 3) Tri ### M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/Party/Ds/ID ### M9HEAD.IAPRSU; PPS200MI/GetHead The receipayse ### @accountingEntity CMNDIV.CCCONO The CON ### CON ### M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber ### MPLINE.IBPNLI; PPS200MI/LstLine The ### M3EDIPurchaseOrder/PurchaseOrderLine/Note ### MSYTXH.THTX40; PPS200MI/LstLine The ### M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code ### M9LINE.IBPUST; PPS200MI/LstLine The ### M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code ### M9LINE.IBPUST; PPS200MI/LstLine The ### 15-CC 20-C 25-CC 31-CC 32-CC 40-CC 45-CC 40-CC	o 'Subcontract' if PO category is 70. o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. ne field indicates the order type name. ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should tive the payment. Payee is entered only if the supplier and the se are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
2) GetHead 3) GetBasicData Set t 3) GetBasicData Set t Set t 2) TH 3) TH ### M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/Party/Ds/ID MPHEAD.IAPRSU; PPS200MI/GetHead The rece paye ###################################	o 'Loan' if PO category is 80. o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. ne field indicates the order type name. ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should tive the payment. Payee is entered only if the supplier and the seare not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
3) GetBasicData Set t Set t Set t 2) Th 3) Th M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The receip paye @accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine MSEDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 31-C 40-C 50-R 60-R 60-R 60-R 70-P 75-R 60-R 75-R 60-R 75-R 60-R	o 'Exchange' if PO category is 85. o 'Freight' if PO category is 90. ne field indicates the order type name. ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should tive the payment. Payee is entered only if the supplier and the se are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks.
Set t 2) TH 3) TH M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The rece paye @accountingEntity CMNDIV.CCONO CMNDIV.CCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 31-C 32-C 33-C 40-C 45-C 45-C 45-C 45-C 45-C 45-C 45-C 45	o 'Freight' if PO category is 90. The field indicates the order type name. The field indicates the agent's name. The field indicates a valid supplier number for the supplier that should live the payment. Payee is entered only if the supplier and the see are not the same legal entity. The field indicates the company and division, displayed as a self of DIVI. The field indicates the purchase order line number. The field indicates the notes or remarks. The field indicates the following status of the Purchase Order Head: The field indicates the following status of the Purchase Order Head:
2) The 33 Telephore 33 Telephore 33 Telephore 34 Telephore 35 Telephore 36 Telephore 37 Telepho	ne field indicates the agent's name. field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the se are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID	field indicates the agent's name. field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the er are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The receivage paye paye @accountingEntity The CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber The M9EDIPurchaseOrder/PurchaseOrderLine/Note The MSYTXH.THTX40; PPS200MI/LstHeadTxt The M9EDIPurchaseOrder/PurchaseOrderLine/Status/Code The MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 33-C 33-C 40-C 45-C 50-R 60-R 64-R 65-R 69-R 69-R 69-In 75-R 80-Ir 80-Ir	field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the see are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MPHEAD.IAPRSU; PPS200MI/GetHead The receivage paye paye @accountingEntity The CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber The M9EDIPurchaseOrder/PurchaseOrderLine/Note The MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code The MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 33-C 33-C 40-C 45-C 50-R 60-R 64-R 65-R 69-R 69-R 70-P 75-R 80-Ir 80-Ir	field indicates a valid supplier number for the supplier that should ive the payment. Payee is entered only if the supplier and the see are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
@accountingEntity CMNDIV.CCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 35-C 40-C 40-C 40-C 40-C 40-C 40-C 40-C 40	ive the payment. Payee is entered only if the supplier and the see are not the same legal entity. field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head: Open
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 35-C 40-C 50-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
@accountingEntity The CMNDIV.CCCONO The CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 20-C 25-C 31-C 25-C 31-C 25-C 31-C 25-C 31-C 25-C 31-C 25-C 31-C 31-C 31-C 31-C 31-C 31-C 31-C 31	field indicates the company and division, displayed as IO DIVI. field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
CMNDIV.CCDIVI.; / CON M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber MPLINE.IBPNLI; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 33-C 35-C 40-C 45-C 50-R 60-R 60-R 60-R 70-P 75-R 80-Ir	field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber The M9LINE.IBPNLI; PPS200MI/LstLine The M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code The MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 62-R 69-R 70-P 75-R 80-Ir	field indicates the purchase order line number. field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
MPLINE.IBPNLI; PPS200MI/LstLine M3EDIPurchaseOrder/PurchaseOrderLine/Note	field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M3EDIPurchaseOrder/PurchaseOrderLine/Note MSYTXH.THTX40; PPS200MI/LstHeadTxt The M3EDIPurchaseOrder/PurchaseOrderLine/Status/Code The MPLINE.IBPUST; PPS200MI/LstLine 15-C 20- 0 25-C 31-C 32-C 33-C 33-C 40-C 45-C 50-R 51-R 60-R 69-R 70-P 75-R 80-Ir 80-Ir	field indicates the notes or remarks. field indicates the following status of the Purchase Order Head:
M9EDIPurchaseOrder/PurchaseOrderLine/Status/Code MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 33-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	field indicates the following status of the Purchase Order Head:
MPLINE.IBPUST; PPS200MI/LstLine The 15-C 20-C 25-C 31-C 32-C 33-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir)pen
15-C 20- C 25-C 31-C 32-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R)pen
20- 0 25- C 31- C 32- C 33- C 35- C 40- C 45- C 50- R 51- R 60- R 64- R 65- R 69- R 70- P 75- R	
25-C 31-C 32-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R	Open
31-C 32-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R	
32-C 33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R	
33-C 35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
35-C 40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
40-C 45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
45-C 50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
50-R 51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
51-R 60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	
60-R 64-R 65-R 69-R 70-P 75-R 80-Ir	lecevied
64-R 65-R 69-R 70-P 75-R 80-Ir	leceived
65-R 69-R 70-P 75-R 80-Ir	leceived
69-R 70-P 75-R 80-Ir	deceived
70-P 75-R 80-Ir	leceived
75-R 80-Ir	leceived
80-Ir	artially Received
	leceived
11-68	nvoiced
	nvoiced
	nvoiced
99-C M3EDIPurchaseOrder/PurchaseOrderLine/Item/ItemID/ID	anceled
	field indicates the item number.
@accountingEntity	
	field indicates the company and division, displayed as
	IO DIVI.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/UPCID	
	field contains the UPC code which has an alias qualifier of UPC
	MS025.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/GTIN	6 11
	field contains the UPC code which has an alias qualifier of EA13
	MS025
M3EDIPurchaseOrder/PurchaseOrderLine/Item/ServiceIndicator MTEINF.UICFMA; CMS474MI/GetUDefContent Set t	o 'true' if the item is a service item. Otherwise, set to 'false'.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/Description	o ado a dio nom io a convicto nom. Otherwise, set to laise.
•	field indicates the description of an item in a purchase order.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/Classification/Codes/Code	
1.) MPLINE.IBFSCD The	field indicates the following:
PPS200MI/GetLine	-
	t control
2).MITVEN.IFSITE The	field indicates the kit control. Set attribute type and listID to 'KIT'.
PPS040MI/GetItemSupplier	nela indicates the kit control. Set attribute type and listib to Kin.
2) So	ineld indicates the kit control. Set attribute type and listib to Kit .
	upplier item number
	upplier item number field indicates the supplier item number in the purchase order
	upplier item number
3) Co	upplier item number field indicates the supplier item number in the purchase order Set attribute type and listID to 'Supplier Item Code'.

MSEDIPUICIIASEOIUEI	
@sequence	The field indicates the item's country of origin. Set attribute type and listID to 'Country of Origin'.
	The field indicates the sequence number.
@listID	Set to 'KIT'. Set to 'Supplier Item Code'
	3.) Seto to 'Country of Origin'.
M3EDIPurchaseOrder/PurchaseOrderLine/Quantity MPLINE.IBORQA; PPS200MI/LstLine	The field indicates the ordered quantity .
@unitCode MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the unit of measure (U/M) in which the purchase price is expressed.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
M3EDIPurchaseOrder/PurchaseOrderLine/QuantityDistribution/Proje	Data element: UOMCode
MPLINE.IBPROJ; PPS200MI/LstLine2	The field indicates the unique ID for a project.
@accountingEntity MPHEAD.IACONO	The field indicates the company and division, displayed as
MPHEAD.IADIVI.; /	CONO DIVI.
M3EDIPurchaseOrder/PurchaseOrderLine/QuantityDistribution/Proje	
CSEAMA.HSTX40; CRS912MI/GetSeason	The field indicates the season description. Retrieve Season Control (SEAG) from PPS095MI.LstOrderType. If SEAG = 2, call CRS912MI.GetSeason.
M3EDIPurchaseOrder/PurchaseOrderLine/QuantityDistribution/Proje	,
M3EDIPurchaseOrder/PurchaseOrderLine/BaseUOMQuantity MPLINE.IBORQT; PPS200MI/LstLine	The field indicates the quantity.
@unitCode MITMAS.MMUNMS; PPS200MI/LstLine	The field indicates the basic unit of measure (U/M).
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION
	Vers: 1 Message: Generic
	I/O: O Parent element(s): Generic
M3EDIPurchaseOrder/PurchaseOrderLine/UnitPrice/Amount MPLINE.IBPUPR; PPS200MI/LstLine	Data element: UOMCode The field indicates the purchase price.
@currencylD MPHEAD.IACUCD; PPS200MI/GetHead	The field indicates the currency.
WILLIAD.IAGGOD, 11 GZOOWI/Geti lead	·
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: Currency
M3EDIPurchaseOrder/PurchaseOrderLine/UnitPrice/PerQuantity	Data dictricit. Currency
MPLINE.IBCPUC MPLINE.IBPUCD.; PPS200MI/1) GetHead	The field indicates the purchase price quantity.
2) LstLine @unitCode	
MPLINE.IBPPUN; PPS200MI/LstLine	The field indicates the purchase price unit of measure.
M3EDIPurchaseOrder/PurchaseOrderLine/ExtendedAmount MPLINE.IBLNAM; PPS200MI/LstLine	The field indicates the line amount.
@currencyID MPHEAD.IACUCD; PPS200MI/GetHead	The field indicates currency used.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1
	Message: Generic I/O: O

WISEDIFUICIIASEOIGEI	
	Parent element(s): Generic Data element: Currency
M3EDIPurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBTIHM.; PPS200MI/LstLine	The field indicates the delivery date and time.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/PartyIDs/ID MPPOAD.ADADK2; PPS200MI/GetDelAddress	The field indicates the destination warehouse.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Name MPPOAD.ADCONM; PPS200MI/GetDelAddress	The field indicates the name of the company.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MPPOAD.ADADK2; PPS200MI/GetDelAddress	The field indicates the destination warehouse.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr @type	
MOSPIE AL COLLA PARTICIPATA DE LA CALLA DE	Set to 'text'.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr MPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4.; PPS200MI/GetDelAddress	ess/AddressLine The field indicates an address line.
@sequence	The field indicates the sequence number.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr	ess/CityName
MPPOAD.ADTOWN; PPS200MI/GetDelAddress	The field indicates the city name.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr MPPOAD.ADECAR; PPS200MI/GetDelAddress	ess/CountrySubDivisionCode The field indicates a state or province within a country.
@listID	The field indicates a state of province within a country.
	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries.</country>
	Set to "SubDivisions" if no Country is specified.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr MPPOAD.ADCSCD; PPS200MI/GetDelAddress @listID	The field indicates a country.
M2EDID: wahaaa Ordar/D: wahaaa Ordari ina (Shin Ta Dartu/) aaatia n/Addw	Set to 'Countries'.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Addr MPPOAD.ADPONO; PPS200MI/GetDelAddress	The field indicates a postal code.
M3EDIPurchaseOrder/PurchaseOrderLine/TransportationTerm/Incoter MPLINE.IBTEDL; PPS200MI/LstLine	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID	
M2EDID: wahaaa Orday/D: wahaaa Orday lina/Diatrib: stadCharga	Set to 'Incoterms'.
M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge @type MPOEXP.IVEXTY; PPS215MI/LstPOCharges	The field indicates the type of charge the costing element represents. If EXTY = 2, set to 'External charge'.
@sequence	Only external costing elements are included.
MPOEXP.IVCDSE; PPS215MI/LstPOCharges	The field indicates the sequence number of the costing element.
M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/ID MPOEXP.IVCEID; PPS215MI/LstPOCharges	The field indicates the costing element. Only external charges are Included. Only costing elements with operators different than 15, 16, 77, 90 and 91 are added included. Costing elements with distribution method = 3 are included.
M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/Descript MPCELE.INTX30; PPS280MI/GetElement	-
M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/Amount 1) MPLINE.IBODI1 MPLINE.IBODI2	The field indicates the costing element description. 1) The field indicates the discount and/or the confirmed discount and/or internal charges and/or external charges.

MPLINE.IBODI3
MPLINE.IBCFD1
MPLINE.IBCFD2
MPLINE.IBCFD3
MPLINE.IBINEP
MPLINE.IBEXEP;
PPS200MI.GetHead
2) MPOEXP.IVCEVA
MPOEXP.IVCEVJ;
PPS215MI/LstPOCharges..; /

2) The field indicates the costing element amount.

@currencyID

MPHEAD.IACUCD; PPS200MI/GetHead MPOEXP.IVCUCD; PPS215MI/LstPOCharges.; / The field indicates the currency.

M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/ReasonCode

MPOEXP.IVEXIC; PPS215MI/LstPOCharges

- 1) For description 'Order discount 1', reason code = 'General Order Discount'.
- 2) For description 'Order discount 2'- if reference type in the header (HeadOURT) is 1 and reference number (HeadOURR) is not empty, reason code = 'AgreementHeader ' + iHeadOURR. Else if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementHeader '+ iLineOURR. Else if reference type in the header (HeadOURT) is not 1, reason code = 'Manual Discount'.
- 3) For description 'Order discount 3'- if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine '+ iLineOURR. Else if reference type in the line (LineOURT) is not 1, reason code = 'Manual Discount'.
- 4.) For description 'Confirmed discount 1', reason code = 'General Order Discount'.
- 5.) For description 'Confirmed discount 2'- if reference type in the header (HeadOURT) is 1 and reference number (HeadOURR) is not empty, reason code = 'AgreementHeader ' + iHeadOURR. Else if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine '+ iLineOURR. Else if reference type in the header (HeadOURT) is not 1, reason code = 'Manual Discount'.
- 6.) For description'Confirmed discount 3'- if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine '+ iLineOURR. Else if reference type in the line (LineOURT) is not 1, reason code = 'Manual Discount'.
- 7.) For description 'Charge Type' and amount internal charge (INEP), reason code = 'Internal Charges'.
- 8.) For description 'Charge Type' and amount external charge (EXEP), reason code = 'External Charges'.
- 9) The field indicates if charges connected to a purchase order can be invoiced one time or several times. This field is only valid for external charges.

If EXIC = 1, set to 'Only once'.

If EXIC = 2, set to 'Several times'.

Attribute list ID is set to 'Charge Invoicing'.

Set to 'Charge Invoicing' if DistributedCharge/ReasonCode is mapped to EXIC.

M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/GrossWeightIndicator

Set to 'false'

M3EDIPurchaseOrder/PurchaseOrderLine/FreightClassification/Codes/Code

MPLINE.IBMODL; PPS200MI/LstLine @sequence

The field indicates the delivery method.

MPLINE.IBPNLI; PPS200MI/LstLine The field indicates the purchase order line number. M3EDIPurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentID/ID

MPLINE.IBPLPN; PPS200MI/LstLine

The field indicates the reference Planned Purchase Order number.

@accountingEntity

@listID

CMNDIV.CCCONO

The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI.

M3EDIPurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber

MPLINE.IBPLPS; PPS200MI/LstLine

The field indicates the Planned Purchase order subnumber.

M3EDIPurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime

WIJEDIF UI CHASEOTUEI	
MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBTIHM.; PPS200MI/LstLine	The field indicates the delivery date and time.
M3EDIPurchaseOrder/PurchaseOrderLine/ReceivedQuantity	
MPLINE.IBRVQA; PPS200MI/LstLine @unitCode	The field indicates the received quantity
MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the unit of measure of the received quantity
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic
	I/O: O Parent element(s): Generic Data element: UOMCode
### ### ##############################	
DunitCode MITMAS.MMUNMS; PPS200MI/LstLine	The field indicates the basic unit of measure (U/M).
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1
	Message: Generic I/O: O Parent element(s): Generic
	Data element: UOMCode
// // // // // // // // // // // // //	
MPLINE.IBORQA MPLINE.IBRVQA.; PPS200MI/LstLine	The field indicates the pending quantity which is the difference of Ordered Quantity and Received Quantity.
MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the pending quantity unit of measure.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
	Data element: UOMCode
M3EDIPurchaseOrder/PurchaseOrderLine/OpenBaseUOMQuantity MPLINE.IBORQT MPLINE.IBRVQT.; PPS200MI/LstLine	The field indicates the pending quantity in basic unit of measure.
@unitCode MITMAS.MMUNMS; PPS200MI/LstLine	The field indicates the basic unit of measure (U/M).
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1 Message: Generic I/O: O
#25DIDurahaan Ordan/Durahaan Ordan ina/Salaa Ordan Dafananaa/Daa	Parent element(s): Generic Data element: UOMCode
######################################	The field indicates the reference sales order number.
MPLINE.IBRORL; PPS200MI/LstLine	The field indicates the reference sales order line.
// // // // // // // // // // // // //	The field indicates the buyer.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
######################################	The field indicates the number of the subline. The subline elements will be populated for kit components.
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Qu MPDMAT.PMCNQT; PDS002MI/LstKitItems @unitCode	rantity The field indicates the quantity of each component used in the kit.

MPDMAT.PMPEUN; PDS002MI/LstKitItems	The field indicates the unit of measure that is used for an item quantity in a component of a kit.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: UOMCode
######################################	seUOMQuantity The field indicates the quantity of each component used in the kit.
MPDMAT.PMPEUN; PDS002MI/LstKitItems	The field indicates the unit of measure that is used for an item quantity in a component of a kit.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: ION Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Pa MPLINE.IBPNLI; PPS200MI/LstLine	rentLineNumber The field indicates the purchase order line number.
######################################	The hold indicated the parendos order line fluthber.
MPLINE.IBPUST MPLINE.IBPUSL	The fields indicate the following:
4) MPLINE.IBUCA1-IBUCA0 MPLINE.IBUDN1-IBUDN6	Purchase Order Line Highest Status Attribute Name is set to 'HighestStatus'.
MPLINE.IBUID1-IBUID3 MLINE.IBUCT1; PPS200MI/LstLine	2.) Purchase Order Line Lowest Status Attribute Name is set to 'LowestStatus'.
CUDFLD.FDTX15; CMS082/LstFields	4) User-defined field
CUDFLV.FVTX40; CMS083/LstValues.; PPS200MI	The field indicates a user-defined field for displaying and storing you own information.
PPS200MI/LstLine	Set attribute name to 'm3. <m3 be="" field="">-<cms082 tx15="">'. Description is retrieved from CMS083 TX40. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS08 Name (TX15) is the default Gen. Decimal CRS082 TX15 should be</cms082></m3>
LstLine	changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.
M3EDIPurchaseOrder/PurchaseOrderLine/ContractReference/Docum	
MPLINE.IAOURR; PPS200MI/LstLine	The field indicates the contract/agreement number.
#13EDIPurchaseOrder/PurchaseOrderLine/UnitQuantityConversionFa MITAUN.MUCOFA; MMS200MI/LstltmAltUnitMs	ctor The field indicates the conversion factor.
######################################	The field indicates the unique identity of a supplier.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
######################################	The field indicates the unique identity of a supplier.
M3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location Dtype	Set to 'Pickup' if address type is 3.
//3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Nat CIDADR.SASUNM; PPS200MI/GetAddrPerDate	
//3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Ad Dtype	
12EDIDurchasoOrdor/DurchasoOrdorl ina/SummliarDarty// acctic=/Ad	Set to 'text'.
### ITEM PROPERTY OF THE PROPERTY IN THE PROPERTY IN THE PROPERTY OF THE PROPERTY IN THE PR	The field indicates the address line.
M3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Ad	
CIDADR.SATOWN; PPS200MI/GetAddrPerDate M3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Add	
CIDADR.SAECAR; PPS200MI/GetAddrPerDate @ <i>listID</i>	The field indicates the state.

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified.

M3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CountryCode

CIDADR.SACSCD; PPS200MI/GetAddrPerDate

@listID

The field indicates the country code.

Set to 'Countries'.

M3EDIPurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/PostalCode

CIDADR.SAPONO; PPS200MI/GetAddrPerDate

The field indicates the postal code.

M3EDIPurchaseOrder/PurchaseOrderLine/ShipFromParty/PartyIDs/ID

MPHEAD.IASUNO; PPS200MI/GetHead

The field indicates the unique identity of a supplier.

The value can be translated in CRS881/882.

It can be defined on the division or on the company level.

Msg std: M3EDI

Vers: 1

Message: Generic

I/O: O

Parent element(s): ShipFromParty

Data element: PartyID

@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.;/

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIPurchaseOrder/PurchaseOrderLine/ProductionOrderReference/DocumentID/ID

MPLINE.; PPS200MI/LstLine

The field indicates the reference manufacturing order.

M3EDIPurchaseOrder/PurchaseOrderLine/Classification/Codes/Code

1) MPLINE.IBOTOD PPS200MI/GetLine

2) MPLINE.IBSORN PPS200MI/GetLine

3) MHIAUN.RFAUTP MMS200MI/LstltmAltUnitMs

4) MHIAUN.RFDMCF MMS200MI/LstltmAltUnitMs

5) MPLINE.IBWHLO PPS200MI/GetLine

6) MPLINE.IBSRCD PPS200MI/GetLine

7) MPLINE.IBPSET PPS200MI/GetLine

8) MPLINE.IBTAXC PPS200MI/LstLine2

9) MPLINE.IBVTCD PPS200MI/LstLine

10) MPLINE.IBPIAD PPS200MI/LstLine

11) MPLINE.IBHAFE PPS200MI/LstLine CSYTAB.CTTX40 CRS175MI/GetGeneralCode CSYTAB.CTTX15 CRS175MI/GetGeneralCode

12) MPLINE.IBSDES PPS200MI/LstLine CSYTAB.CTTX40 MMS008MI/GetPlace CSYTAB.CTTX15 MMS008MI/GetPlace

13) MPLINE.IBCIAD PPS200MI/LstLine

14) MPLINE.IBCDES PPS200MI/LstLine.: /

1) Part of order total discount

The field indicates the part of order total discount. Set attribute listID to 'Part of order total discount'.

2) Supplier order number

The field indicates the number that the supplier assigns to his order. The order number is normally specified per purchase order when these are confirmed.

Set attribute listID to 'Supplier Order Number'.

3) Alternate U/M type

The field indicates the alternate unit of measure type. Set attribute listID to 'Alternate U/M type'.

Set to 'Alternate quantity U/M' if AUTP is 1. Set to 'Alternate price U/M' is AUTP is 2.

Set to 'Alternate price U/M' is AUTP is 2.
Set to "Supplementary INTRASTAT U/M based on net weight." if

AUTP is 3. Set to 'Comparison price' if AUTP is 7.

4) Coversion form

The field indicates the conversion form. Set listID attribute to 'Conversion form'.

5) Warehouse

The field indicates the warehouse. Set listID attribute to 'Location'.

6) Reservation level

The field indicates how the inventory reservation should be performed

Set attribute listID to 'Reservation Level'. Display only if Kit control (FSCD) is greater than 0.

7) Pricing Method

The field indicates how the sales price for the kit item and the detail lines are calculated. Set attribute listID to 'Pricing Level'. Display only if Kit control (FSCD) is greater than 0.

8) Tax code

The field indicates the tax code. Set attribute listID to 'Tax Code'.

9) Vat code

The field indicates the VAT code. Set attribute listID to 'VAT Code'.

10) Pickup address

The field indicates the pickup address. Set attribute listID to 'Pickup Address'.

@sequence

@listID

11) Harbor/Airport

The field indicates the ID of the harbor or airport. Set attribute listID to 'Harbor Airports'. The field indicates the Harbor/Airpot description. Set attribute listID to 'Harbor Airports Description'. The field indicates the Harbor/Airpot name. Set attribute listID to 'Harbor Airports Name'.

12) Place of loading

The field indicates the ID of the place of loading. Set attribute listID to 'Place Of Load'. The field indicates the Place of load description. Set attribute listID to 'Place Of Load Description'. The field indicates the Place of load name. Set attribute listID to 'Place Of Load Name'.

13) Confirmed pickup address

The field indicates the confirmed pickup address. Set attribute listID to 'Confirmed Pickup Address'.

14) Confirmed place of loading

The field indicates the ID of the confirmed place of loading. Set attribute listID to 'Confirmed Place Of Load'.

The field indicates the sequence number.

- 1) Set to 'Part of order total discount'.
- 2) Set to 'Supplier Order Number'.
- 3) Set to 'Alternate U/M type'.
- 4) Set to 'Conversion form'.
- 5) Set to 'Location'.
- 6) Set to 'Reservation Level'.
- 7) Set to 'Pricing Level'.
- 8) Set to 'Tax Code' if Classification/Codes/Code is TAXC.
- 9) Set to 'VAT Code' if Classification/Codes/Code is VTCD.
- 10) Set to 'Pickup Address' if Classification/Codes/Code is PIAD.11) Set to 'Harbor Airports' if Classification/Codes/Code is HAFE.
- Set to 'Harbor Airports Description' if Classification/Codes/Code is TX40.

Set to 'Harbor Airports Name' if Classification/Codes/Code is TX15. 12) Set to 'Place Of Load' if Classification/Codes/Code is SDES. Set to 'Place Of Load Description' if Classification/Codes/Code is TX40.

Set to 'Place Of Load Name' if Classification/Codes/Code is TX15.

13) Set to 'Confirmed Pickup Address' if Classification/Codes/Code is CIAD.

14) Set to 'Confirmed Place Of Load' if Classification/Codes/Code is CDES.

M3EDIPurchaseOrder/PurchaseOrderLine/DropShipIndicator MPLINE.IBGETY: PPS200MI/LstLine

The field is set to 'true' if purchase order line is generated from a customer order direct delivery. Otherwise, the field is set to 'false'.

M3EDIRemittanceAdvice

M3EDIRemittanceAdvice/TradingPartnerID

- 1. FPSUGH.P1BKID,
- 2. FPSUGD.P3SPYN;

The field indicates the trading partner ID. The value of the element reflects as the partner in MEC. Max length is 15 char. The value is retrieved from Rcvr ref data 1 (RRD1) in Std Document. Connect Media Ctrl Object CRS949/J.

1. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is not activated and the BOD is triggered from Document number 500 or 504 (Program=='APS161PF' OR Program=='APS141PF'), TradingPartnerID will be set to Company's bank account ID. 2. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is activated and the BOD is triggered from Document number 520 (Program=='APS162PF'), TradingPartnerID will be set to Payee.

The value can be translated in CRS881/882.

It can be defined on the company level only.

In this case, TradingPartnerID element will still be populated with the original M3 value of the trading partner ID, and the translation will be used as External partner value when retrieving the translation of any other translatable field, e.g. currency.

Msg std: M3EDI

Vers: 1

Message: Generic

I/O: I

Parent element(s): Generic Data element: TradingPartnerID

External partner: [empty]

M3 data: [trading partner ID translation]

Message data: [original M3 value of the trading partner ID]

The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.

- 1. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is not activated and the BOD is triggered from Document number 500 or 504 (Program=='APS161PF' OR Program=='APS141PF'), this field will be set to the payment method
- 2. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is activated and the BOD is triggered from Document number 520 (Program=='APS162PF'), this field will not be published.

@schemeName

1. FPSUGH.P1PYME;

M3EDIRemittanceAdvice/RemittanceAdviceHeader/DocumentID/ID

1. FPSUGH.P1PRPN, FPSUGH.P1PYON 2. FPSUGH.P1PRPN,

FPSUGH.P1PYON, FPSUGD.P3SPYN;

The field indicates the unique number:

- 1. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is not activated and the BOD is triggered from Document number 500 or 504 (Program=='APS161PF' OR Program=='APS141PF'), ID will be set to a supplier payment proposal concatenated with the payment order. One BOD will be triggered per payment proposal and payment order, one payment order per payment method if following conditions are fulfilled:
- a) payment method has payment class 3
- b) company's bank account ID and payment method are configured in CRS945 Connect Media Ctrl Object for document number 500 or 504. c) company's bank account ID and payment methods media is configured in CRS949 (CRS945->Related Ctrl+12->Media with Media=MBMEVENT and RecipientReference3=M3EDIBOD There could be multiple payees in the same BOD.
- 2. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is activated and the BOD is triggered from Document number 520 (Program=='APS162PF'), ID will be set to a supplier payment proposal concatenated with the payment order and payee. There will be one BOD for each payee in the payment proposal if following conditions are fulfilled:
- a) payment method has payment class 3
- b) payee is configured in CRS945 Connect Media Ctrl Object for document number 520
- c) payees media is configured in CRS949 (CRS945 -> Related Ctrl+12 -> Media with Media=MBMEVENT and RecipientReference3=M3EDIBOD

The BOD is triggered from APS130 -> Related Ctrl+8 Preliminary/copy.

Document number is connected to Printer file in CRS928 like this: 500 to APS161PF, 504 to APS141PF, 520 to APS162PF.

The field indicates the company and division, displayed as CONO_DIVI.

@accountingEntity FPSUGH.CONO FPSUGH.DIVI; @variationID

M3EDIRemittanceAdvice

The field indicates the sequence number that identifies the number of times that the BOD has been published. @lid The field indicates the logical id of the system. M3EDIRemittanceAdvice/RemittanceAdviceHeader/DocumentDateTime FPSUGH.P1PRPD; APS130MI/GetHead The field indicates the payment proposal date M3EDIRemittanceAdvice/RemittanceAdviceHeader/Status/Code FPSUGH.P1PYST; APS130MI/GetHead The field indicates the status. If the status (PYST) is equal to 9, set status to 'Open' M3EDIRemittanceAdvice/RemittanceAdviceHeader/FinancialParty/PartyIDs/ID FPSUGH.P1BKNO; APS130MI/GetHead The field indicates the bank number of the company. M3EDIRemittanceAdvice/RemittanceAdviceHeader/FinancialParty/FinancialAccount/ID FPSUGH.P1BKID; APS130MI/GetHead The field indicates the Company's bank account ID. M3EDIRemittanceAdvice/RemittanceAdviceHeader/FinancialParty/FinancialAccount/AccountIDs/ID FPSUGH.P1BAF1; APS130MI/GetHead The field indicates the Company's bank account number. M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/PartyIDs/ID FPSUGD.P3SPYN; APS130MI/LstInvByPayee The field indicates the payee. @accountingEntity FPSUGH.CONO The field indicates the accounting entity. FPSUGH.DIVI; If RemitToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData The field indicates the name of the payee. M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Name FPSUGS.F2SUNM; APS130MI/GetPayeeTotal The field indicates the name on the payee's address M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Address/AddressLine FPSUGS.F2ADR1-F2ADR1; APS130MI/GetPayeeTotal The field indicates the address line 1-4 of the payee's address. @sequence Set to sequence number 1-4 for each address line available. M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Address/CityName FPSUGS.F2TOWN; APS130MI/GetPayeeTotal The field indicates the city of the payee's address M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Address/CountrySubDivisionCode FPSUGS.F2ECAR; APS130MI/GetPayeeTotal The field indicates the state code of the payee's address. FPSUGS.F2CSCD; APS130MI/GetPayeeTotal Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Address/CountryCode FPSUGS.F2CSCD; APS130MI/GetPayeeTotal The field indicates the country code of the payee's address. @listID Set to 'Countries'. M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Location/Address/PostalCode FPSUGS.F2PONO; APS130MI/GetPayeeTotal The field indicates the postal code (PONO) of the payee's (SPYN) address M3EDIRemittanceAdvice/RemittanceAdviceHeader/PaymentMethodCode FPSUGH.P1PYME; APS130MI/GetHead The field indicates the payment method. Only payment methods with payment class 3 = Bank transfer/credit card are supported. M3EDIRemittanceAdvice/RemittanceAdviceHeader/TotalAmount 1. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is 1. FPSUGH.P1CUAM 2. FPSUGD.P3PYCU; 1. APS130MI/GetHead not activated and the BOD is triggered from Document number 500 or 504 (Program=='APS161PF' OR Program=='APS141PF'), this field 2. APS130MI/LstInvByPayee/ will be set to payment proposal+payment proposal order's total amount. 2. When Feature ID=2243983 in CMS975 Feature list. Open in M3 is activated and the BOD is triggered from Document number 520 (Program=='APS162PF'), this field will be set to sum of all line amounts for all invoices with positive amounts belonging to the payee. @currencyID FPSUGH.P1CUCD; APS130MI/GetHead The field indicates the currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

1/0:0

Parent element(s): Generic Data element: Currency

M3EDIRemittanceAdvice/RemittanceAdviceHeader/UserArea

M3EDIRemittanceAdvice

WISEDIREIIIILLATICEAUVICE	
	If nameValue@name = 'Purchase Order Print', the field indicates whether the document is printed for the first time or not. If it is printed for the fist time, the value of the field is 'Original', otherwise, 'Copy'.
	Tor the list time, the value of the field is Original, otherwise, Copy.
M3EDIRemittanceAdvice/RemittanceAdviceLine/LineNumber	The field in director the line according
	The field indicates the line number.
M3EDIRemittanceAdvice/RemittanceAdviceLine/DocumentRefere @type	ence
	Set to 'SupplierInvoice'
	2. Set to 'PurchaseOrder'.
M3EDIRemittanceAdvice/RemittanceAdviceLine/DocumentRefere	ence/DocumentID/ID
1. FPSUGD.P3SINO	1. The field indicates the supplier's invoice number.
2. FPLEDX.EPPEXI; 1. APS130MI/LstInvByPayee	2. The field indicates the purchase order number.
2. APS251MI/GetInvInfo	The purchase order number is the 11th to 20th character of the value
	in the field PEXI if GL information number (PEXN) = 402.
M3EDIRemittanceAdvice/RemittanceAdviceLine/DocumentRefere	
FPSUGD.P3IVDT; APS130MI/LstInvByPayee	The field indicates the supplier invoice date.
M3EDIRemittanceAdvice/RemittanceAdviceLine/RemitToParty/Fi	· · · · · · · · · · · · · · · · · · ·
FPSUGD.P3BKID; APS130MI/LstInvByPayee	The field indicates the supplier's bank account ID.
M3EDIRemittanceAdvice/RemittanceAdviceLine/PaymentAmount	
FPSUGD.P3PYCU; APS130MI/LstInvByPayee	The field indicates the payment amount due.
@currencyID	The field indicates the payment amount due.
FPSUGH.P1CUCD; APS130MI/LstInvByPayee	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
	•

M3EDISalesOrder

MOLDIGAICSOIACI	
M3EDISalesOrder/TradingPartnerID	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
@schemeName	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
M3EDISalesOrder/SalesOrderHeader/DocumentID/ID OOHEAD.ORNO; OIS100MI/GetOrderHead	The field indicates the Customer Order Number
@accountingEntity CONO+DIVI; -/	The field indicates the company and division
@location .WHLO; -/ @variationID	The field indicates the location/warehouse
.; -/	The field indicates the number of variation for the object
@lid .; -/	The field indicates the logical ID
M3EDISalesOrder/SalesOrderHeader/AlternateDocumentID/ID OOHEAD.CUOR; OIS100MI/GetOrderHead	The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents.
@schemeName .; Fixed value = "Customer"/	Customer is published.
M3EDISalesOrder/SalesOrderHeader/DisplayID OOHEAD.OAORNO; /	The field indicates the document ID.
M3EDISalesOrder/SalesOrderHeader/LastModificationDateTime .[from event]; -/	This indicates the last modification date and time of the BOD
M3EDISalesOrder/SalesOrderHeader/DocumentDateTime OOHEAD.ORDT; OIS100MI/GetOrderHead	This indicates the date and time of the sales order.
M3EDISalesOrder/SalesOrderHeader/Note OSYTXH.TX60; OIS100MI/LstHeadTxt	The field indicates the remarks or notes.
@type .; Fixed value = "Pre-Text", "Post-Text", "Text"/	For Pre-text field, 'Pre-Text' is published. For Post-Text field, 'Post-text' is published. And for Text field, 'Text' is published
M3EDISalesOrder/SalesOrderHeader/Status/Code OOHEAD.ORSL; OIS100MI/GetOrderHead	The field indicates the customer orders lowest status, M3 BE field ORSL. It is translated according to: 22, 23, 24, 29, 33, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Deleted
M3EDISalesOrder/SalesOrderHeader/Status/EffectiveDateTime OOHEAD.ORDT; OIS100MI/GetOrderHead	99= Canceled If Status is equal to 'Approved' or 'In Process', the Order Date field is published. If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken. Default filled with the UTC number of the Date and Time when the BOD is published.
M3EDISalesOrder/SalesOrderHeader/Status/ReasonCode OOHEAD.OAOBLC; 0IS100MI/GetOrderHead	The field indicates the customer order stop. 1) If OBLC = 1 then set to 'CreditLimit 1'. 2) If OBLC = 2 then set to 'CreditLimit 2'. 3) If OBLC = 3 then set to 'CreditLimit 3'. 4) If OBLC = 4 then set to 'CreditLimit 4'. 5) If OBLC = 5 then set to 'Connected to LOC'. 6) If OBLC = 6 then set to 'Credit limit'. 7) If OBLC = 7 then set to 'Manually set stop'. 8) If OBLC = 8 then set to 'Manually set stop'. 9) If OBLC = 9 then set to 'Manually released order'.
@listID .;/	Set to 'M3 Hold Reasons'.
M3EDISalesOrder/SalesOrderHeader/Status/ArchiveIndicator .; Value = "TRUE" or "FALSE/	If the Sales Order is deleted and the Order Status is equal to 'Closed or 'Released', 'true' is published. Otherwise, 'false' is published.
M3EDISalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OOHEAD.CUNO; OIS100MI/GetOrderHead	The field indicates the customer identity.
	The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic
Infor May 26.2	

M3EDISalesOrder

IC. C. Departed element(s); CustomerParty Date element Party(D Date Party(D		
### MSEDISalesOrder/SalesOrder/Header/CustomerPartyPartyIbs/TaxID OCUSMA_CNND_CRS610MIGGEffinancial The field indicates the company and division The field indicates the VAT registration number OCUSMA_CNND_CRS610MIGGEffinancial The field indicates the VAT registration number The field indicates the Customer name OCUSMA_CNND_CRS610MIGGEfficationerPartyLocation/Address Aftertion/OName MSEDISalesOrder/SalesOrderHeader/CustomerPartyLocation/Address Aftertion/OName MSEDISalesOrder/SalesOrderHeader/CustomerPartyLocation/Address Aftertion/OName MSEDISalesOrder/SalesOrderHeader/CustomerPartyLocation/Address Aftertion/OName July sequence The field indicates the Address fields (4 fields) MSEDISalesOrder/SalesOrderHeader/CustomerPartyLocation/Address/Clythame The field indicates the sequence number The field indicates the country code The field indicates the country code The field		Parent element(s): CustomerParty
M3EDISales Order/Sales Order/Reader/CustomerParty/Party/Ds/TaxiD COUSMA CUMM, CR8510Mil/GetBasicData M3EDISales Order/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/Sales Order/Reader/CustomerParty/Location/Address/City/Ame COUSMA COVIN, CR8510Mil/GetBasicData M3EDISales Order/Sales Order/Reader/CustomerParty/Location/Address/CustomerP		,
M3EDIsates Order/Sales Order/teader/Customer Party/Location/Address/Attention/ORAme The field indicates the Customer name	M3EDISalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/TaxID	· •
M3EDISalesOrder/SalesOrder/Header/CustomerPartyl.coation/Address/AutorionOfMame The filed indicates the Outsomer Order Responsible M3EDISalesOrder/SalesOrder/Header/CustomerPartyl.coation/Address/AddressI/me COUSMA_CUAI-CUAI-CHAI-CRS610Mi/GetBasicData The filed indicates the Address fileds (4 fields) The filed indicates the Sequence number M3EDISalesOrder/SalesOrder/Header/CustomerPartyl.coation/Address/City/Jame OCUSMA_CSCO_CRS610Mi/GetBasicData The filed indicates the sequence number M3EDISalesOrder/SalesOrder/Header/CustomerPartyl.coation/Address/City/Jame OCUSMA_CSCO_CRS610Mi/GetBasicData The filed indicates the Stet ID depending on the country: - Canada has its ID Canading Provinces - France has list ID Can	M3EDISalesOrder/SalesOrderHeader/CustomerParty/Name	· ·
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/AddressLine OCUSMA_CUAL-CUA, CRS610MUGetBasicData The field indicates the sequence member M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/City/Name OCUSMA_CRS610MUGetBasicData The field indicates the sequence number M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CustomerData/Substitution (Customer Party/Location/Address/CustomerData/Substitution) The field indicates the state The field indicates the Country Code. M3EDISalesOrder/SalesOrder/Header/CustomerParty/Location/Address/Posts/Code The field indicates the Country Code. M3EDISalesOrder/SalesOrder/Header/CustomerParty/Contact/Name Cucyon Concystes Corder-Header/CustomerParty/Contact/Name Cucyon Concystes Corder-Header/CustomerParty/Contact/Name Cucyon Concystes Corder-Header/CustomerParty/Contact/Name Cucyon Concystes Corder-Header/CustomerParty/Party/Ds/ID OHEAD OACONO ODHEAD OACONO ODHEAD OACONO ODHEAD OACONO ODHE	M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Addres	ss/AttentionOfName
### SEDISales Order/Reder/CustomerParty/Location/Address/City/bame OCUSMA CND, CR8610MIGetBasicData The field indicates the Step The field indicates the Sequence number ### SEDISales Order/Reder/CustomerParty/Location/Address/Country/SubDivisionCode OCUSMA CRRC (RS810MIGEtBasicData OSUSMA CRRC, RCR810MIGEtBasicData The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'Prance - Departments' - United States has list ID 'States' - United States has list ID 'Canadian Provinces' - France has list ID 'Canadian Provinces' - United States has list ID 'Country Sub-Britan Provinces' - United States has list ID '	·	·
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CityName OCUSMA_COCUSMA_COCK_CR8610MI/GetBasicData	@sequence	
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CountrySubDivisionCode COUSMA_CSCD; CRS610MI/GetBasicData	M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Addres	ss/CityName
OCUSMA_ECAP; CRS610MI/GetBasicData OCUSMA_CSCD; CRS610MI/GetBasicData The filed indicates the state ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'Trance - Departments' - United States has list ID 'States' - France has list ID 'States' - France has list ID 'States' - Other countries have list ID 'Country Sub-divisions' - Other countries have list ID 'Country Sub-divisions' - When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: - Other countries have list ID 'Country Sub-divisions' - Other countries have list ID 'SubDivisions - [country code]' M3ED/SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/Country/Code OCUSMA_CSCD; CRS610MI/GetBasicData The filed indicates the Country Code on the company level only. M3ED/SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/PostatCode OCUSMA_CSCD; CRS610MI/GetBasicData M3ED/SalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO_CCCNPE; CMS055MI/LstByCustomer @secountingEntity OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO_CCNPE; CMS055MI/LstByCustomer @secountingEntity OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/SupplierParty/Party/Ds/ID OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/SupplierParty/Party/Ds/ID OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/SupplierParty/Party/Ds/ID OCHEAD_OACONO+OADIV: / M3ED/SalesOrder/SalesOrderHeader/SupplierParty/Party/Ds/ID OCHEAD_OADIVI: / M3ED/SalesOrder/SalesOrderHeader/SupplierParty/Party/Ds/ID OCHEAD_	·	·
The field indicates the list ID depending on the country: - Canada has list ID "Canadian Provinces' - France has list ID "France - Departements' - United States has list ID "US States' - When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: - Other countries have list ID "Country Sub-divisions' - Other countries have list ID "Country Sub-divisions' - Other countries have list ID "Country Sub-divisions' - Other countries have list ID "SubDivisions - [country code]' M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CountryCode - The field indicates the CountryCode. The value can be translated in CRS881/882. It can be defined on the company level only. Vers: - Other countries have list ID "SubDivisions - [country code]' The value can be translated in CRS881/882. It can be defined on the company level only. Vers: - Other country code - The field indicates the CountryCode. The value can be translated in CRS881/882. It can be defined on the company level only. Vers: - Other country code - The field indicates the Country Code. Wiscountry Code - Parent element(s): Generic - Data element: Country Code - Set to "Country Code - The field indicates the Postal code - The field indicates the Postal code - The field indicates the contact ID - OCUSANA PONO; CRS616MI/GetBasicData - The field indicates the contact ID - The field indicates the contact ID - The field indicates the contact ID - The field indicates the contact person - The field indicates the Custom	OCUSMA.ECAR; CRS610MI/GetBasicData	
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Address/CountryCode OCUSMA.CSCD; CRS610MI/GetBasicData		 Canada has list ID 'Canadian Provinces' France has list ID 'France - Departements' United States has list ID 'US States' When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: Other countries have list ID 'Country Sub-divisions' When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated:
OCUSMA CSCD; CRS610MI/GetBasicData The field indicates the CountryCode. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O/O Parent element(s). Generic Data element: CountryCode ### M3EDISales Order/Sales Order/Header/CustomerParty/Location/Address/PostalCode OCUSMA.PONO; CRS610MI/GetBasicData ### M3EDISales Order/Sales OrderHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEntify OCHEAD.OACONO+OADIVI: / The field indicates the contact ID ### M3EDISales Order/Sales Order/BasicOrder/Party/Contact/Name CCUCON.CCTX50; CRS615MI/Cet ### The field indicates the contact ID ### The field indicates the contact person ### The field indicates the customer person ### The field indicates the customer person	M3EDISalesOrder/SalesOrderHeader/CustomerParty/Location/Addres	
It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O/O Parent element(s): Generic Data element: CountryCode @istID		The field indicates the CountryCode.
Set to 'Countries'. Set to 'Countries'. Set to 'Countries'. M3ED/SalesOrder/SalesOrder/Leader/CustomerParty/Location/Address/PostalCode OCUSMA.PONO; CRS610MI/GetBasicData The field indicates the Postal code The field indicates the contact ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer COUCON.CCTXCO; CCNPE; CMSO55MI/LstByCustomer The field indicates the contact ID COUCON.CCTXCO; CCNPE; CMSO55MI/LstByCustomer The field indicates the contact ID COUCON.CCTXS0; CRS618MI/Get The field indicates the contact person The field indicates the concatenated values of Company and Division. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Vers: 1 Message: Generic I/O: O Parent element: PartyID PartyID Data element: PartyID Data		Msg std: ION Vers: 1 Message: Generic I/O:O Parent element(s): Generic
OCUSMA.PONO; CRS610MI/GetBasicData M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer @accountingEntity OHEAD.OACONO+OADIVI; / The field indicates the contact ID The field indicates the company and division, displayed as CONO DIVI. M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OACONO OOHEAD.OACONO OOHEAD.OADIVI.; / The field indicates the contact person The field in	@listID ∴ -/	Set to 'Countries'.
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEnitity OOHEAD.OACONO+OADIVI; / The field indicates the contact ID M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OACONO OOHEAD.OACONO OOHEAD.OACONO OOHEAD.OADIVI.; / The field indicates the contact person The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Wers: 1 MascalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID		ss/PostalCode
M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/Name CUUCON.CCTX50; CRS618MI/Get M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OACONO OOHEAD.OACONO OOHEAD.OADIVI.; / The field indicates the contact person The field indicates the contact person The field indicates the contact person The field indicates the concatenated values of Company and Division. The field indicates the concatenated values of Company and Division. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The field indicates the Customer shipping address code. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID	M3EDISalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer	
CCUCON.CCTX50; CRS618MI/Get M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OACONO OOHEAD.OADIVI.; / The field indicates the concatenated values of Company and Division. The field indicates the concatenated values of Company and Division. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The field indicates the Customer shipping address code. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID		
M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OADIVI.; / The field indicates the concatenated values of Company and Division. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The field indicates the Customer shipping address code. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID		The field indicates the contact person
The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty Data element: PartyID M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The field indicates the Customer shipping address code. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID	M3EDISalesOrder/SalesOrderHeader/SupplierParty/PartyIDs/ID OOHEAD.OACONO	The field indicates the concatenated values of Company and Division.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OOHEAD.ADID; OIS100MI/GetAddress The field indicates the Customer shipping address code. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID	COLIEND.ONDIVI., /	It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): SupplierParty
It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID		•
		It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty
	@accountingEntity	,

M3EDISalesOrder	= -
.CONO+DIVI; -/	The field indicates the company and division
M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/TaxID OCUSMA.VRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Name OCUSAD OCUSMA.CUNM; OIS100MI/GetAddress	The field indicates the Customer identity.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/	AttentionOfName
OCUSAD OCUSMA.YREF	The field indicates the Customer responsible
YREF & YRE1; OIS100MI/GetAddress	
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/ OCUSAD OCUSMA.CUA1-CUA4; OIS100MI/GetAddress	AddressLine The field indicates the Address fields (4 fields).
@sequence .; Line sequence/	The field indicates the line sequence of the address.
., Line sequence/ M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/	•
OCUSAD OCUSMA.TOWN; OIS100MI/GetAddress	The field indicates the City.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/	
OCUSAD OCUSMA.ECAR; OIS100MI/GetAddress	The field indicates the state.
@listID Ocusad	The field indicates the list ID depending on the country:
OCUSMA.CSCD; OIS100MI/GetAddress	- Canada has list ID 'Canadian Provinces'
	 France has list ID 'France - Departements' United States has list ID 'US States'
	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	not activated: - Other countries have list ID 'Country Sub-divisions'
	When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	activated:
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/	- Other countries have list ID 'SubDivisions - [country code]' CountryCode
OCUSAD	The field indicates the CountryCode.
OCUSMA.CSCD; OIS100MI/GetAddress	The value can be translated in CDC004/000
	The value can be translated in CRS881/882. It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O:O
	Parent element(s): Generic
@listID	Data element: CountryCode
	Set to 'Countries'.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address/ OCUSAD	PostalCode The field indicates the Postal code.
OCUSMA.PONO; OIS100MI/GetAddress	
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEntity	The field indicates the contact ID
gaccounting Emity	The field indicates the company and division, displayed as CONO DIVI.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OOLINE.WHLO; OIS100MI/GetOrderHead	The field indicates the warehouse.
	The value can be translated in CDS001/000
	The value can be translated in CRS881/882. It can be defined on the division or on the company level.
	Msg std: M3EDI
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): ShipFromParty
@accountingEntity	Data element: PartyID
.CONO+DIVI; -/	The field indicates the company and division
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Name MITWHL.WHNM; MMS005/GetWarehouse	The field indicates the warehouse name
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/Addres MITWHL.ADR1, ADR2,	ss/AddressLine The field indicates the Address fields (4 fields)
ADR3, ADR4; MMS005/GetWarehouse	The held maleates the Madress helds (Thelds)

MOLDIGAICSOLACI	
MITWHL.TOWN; MMS005/GetWarehouse	The field indicates the City
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location	
MITWHL.ECAR; MMS005/GetWarehouse	The field indicates the state
@ <i>listID</i> MITWHL.CSCD; MMS005/GetWarehouse	The field indicates the list ID depending on the country:
WITT VITE. GOOD, WINGGOOD GOLVARONGAGO	- Canada has list ID 'Canadian Provinces'
	- France has list ID 'France - Departements'
	- United States has list ID 'US States'
	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3
	not activated:
	 Other countries have list ID 'Country Sub-divisions'
	2. When Feature ID=2275202 in CMS975 Feature list. Open in M3
	activated:
	- Other countries have list ID 'SubDivisions - [country code]'
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location MITWHL.CSCD; MMS005/GetWarehouse	n/Address/CountryCode The field indicates the CountryCode.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	1/0:0
	Parent element(s): Generic
O	Data element: CountryCode
DlistID .; -/	Set to 'Countries'.
M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Locatior	
MITWHL.PONO; MMS005/GetWarehouse	The field indicates the Postal code
M3EDISalesOrder/SalesOrderHeader/ContractReference/Docu	
OOHEAD.OAAGNO; OIS100MI/GetOrderHead	The field indicates the blanket agreement number in the customer
MOS DIO - 1 - 2 O und - 1/0 - 1 - 2 O und - 1/1 - 2 d - 1/5 und - 1/4 und -	order header.
M3EDISalesOrder/SalesOrderHeader/ExtendedAmount	The field indicates the Cross Order Value
OOHEAD.BRAM+IRAM; OIS100MI/GetOrderValue ©currencyID	The field indicates the Gross Order Value.
OOHEAD.CUCD; OIS100MI/GetOrderHead	The field indicates the currency of the Gross Order Value.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderHeader/TotalAmount	The field indicates the Tetal value
OOHEAD.TOPY+ITOP; OIS100MI/GetOrderValue	The field indicates the Total value
@c <i>urrencyID</i> OOHEAD.CUCD; OIS100MI/GetOrderHead	The field indicates the currency of the Total value.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderHeader/BillToParty/PartyIDs/ID	
OOHEAD.INRC; OIS100MI/GetOrderHead	The field indicates the Invoice Recipient.
	The value can be translated in CDC004/000
	The value can be translated in CRS881/882.
	It can be defined on the division or on the company level. Msg std: M3EDI
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): BillToParty
	Data element: PartyID
@accountingEntity .CONO+DIVI; -/	·
U.U.N.U.1+1.11\/1. =/	The field indicates the company and division
M3EDISalesOrder/SalesOrderHeader/BillToParty/Name	The field indicates the invoice reginient
M3EDISalesOrder/SalesOrderHeader/BillToParty/Name OCUSAD	The field indicates the invoice recipient.
M3EDISalesOrder/SalesOrderHeader/BillToParty/Name	The field indicates the invoice recipient.

The field indicates the Customer responsible. OCUSMA.YREF-YRE1: OIS100MI /GetAddress M3EDISalesOrder/SalesOrderHeader/BillToParty/Location/Address/AddressLine The field indicates the Address fields (4 fields) for (Invoice recipient). OCUSAD OCUSMA.CUA1-CUA4; OIS100MI /GetAddress @seauence The field indicates the sequence number of the address line .; Line sequence/ M3EDISalesOrder/SalesOrderHeader/BillToParty/Location/Address/CityName OCUSAD The field indicates the City (Invoice recipient). OCUSMA.TOWN; OIS100MI /GetAddress M3EDISalesOrder/SalesOrderHeader/BillToParty/Location/Address/CountrySubDivisionCode The field indicates the state **OCUSAD** OCUSMA.ECAR; OIS100MI /GetAddress @listID **OCUSAD** The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' OCUSMA.CSCD: OIS100MI /GetAddress - France has list ID 'France - Departements' - United States has list ID 'US States' 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: Other countries have list ID 'Country Sub-divisions' 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is - Other countries have list ID 'SubDivisions - [country code]' M3EDISalesOrder/SalesOrderHeader/BillToParty/Location/Address/CountryCode **OCUSAD** The field indicates the CountryCode (invoice recipient). OCUSMA.CSCD; OIS100MI The value can be translated in CRS881/882. /GetAddress It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: CountryCode @listID <u>.;</u> -/ Set to 'Countries'. M3EDISalesOrder/SalesOrderHeader/BillToParty/Location/Address/PostalCode OCUSAD The field indicates the Postal code (Invoice recipient). OCUSMA.PONO; OIS100MI /GetAddress M3EDISalesOrder/SalesOrderHeader/BillToParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer The field indicates the contact ID @accountingEntity OOHEAD.OACONO+OADIVI; / The field indicates the company and division, displayed as CONO DIVI M3EDISalesOrder/SalesOrderHeader/BillToParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get The field indicates the Our reference person number 1 and number 2. M3EDISalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/ID OOHEAD.PYNO; OIS100MI/GetOrderHead The field indicates the Payer. The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): PayFromParty Data element: PartyID @accountingEntity .CONO+DIVI; -/ The field indicates the company and division M3EDISalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/TaxID OCUSMA.VRNO; CRS610MI/GetFinancial The field indicates the Tax ID M3EDISalesOrder/SalesOrderHeader/PayFromParty/Name OCUSMA.CUNM; CRS610MI/GetBasicData The field indicates the Customer name (Payer) M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Address/AttentionOfName OCUSMA.YREF; CRS610MI/GetBasicData The field indicates the Customer responsible M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Address/AddressLine OCUSMA.CUA1-CUA4; CRS610MI/GetBasicData The field indicates the Address fields (4 fields) for (Payer) @sequence .; Line sequence/ The field indicates the sequence number of the address line

OCUSMA.TOWN; CRS610MI/GetBasicData	s/CityName The field indicates the City (Payer)
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Addres OCUSMA.ECAR; CRS610MI/GetBasicData	
@listID	The field indicates the state
OCUSMA.CSCD; CRS610MI/GetBasicData	The field indicates the list ID depending on the country:
	- Canada has list ID 'Canadian Provinces'
	 France has list ID 'France - Departements' United States has list ID 'US States'
	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	not activated:
	- Other countries have list ID 'Country Sub-divisions'
	2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	activated:
	- Other countries have list ID 'SubDivisions - [country code]'
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Addres OCUSMA.CSCD; CRS610MI/GetBasicData	s/CountryCode The field indicates the CountryCode.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O:O
	Parent element(s): Generic
@listID	Data element: CountryCode
;;-/	Set to 'Countries'.
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Addres	s/PostalCode
OCUSMA.PONO; CRS610MI/GetBasicData	The field indicates the Postal code (Payer)
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Location/Status/	
OCUSMA.STAT; CRS610MI/GetBasicData	The field indicates the customer status, M3 BE field STAT.
	It is translated according to:
	10, 11 or 12 = Pending
	20 = Open 90 = Closed
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Contact/ID	90 - Gloseu
OCUSCO.CCCNPE; CMSO55MI/LstByCustomer	The field indicates the contact ID
@accountingEntity OCUSCO.CONO+DIVI; /	The field indicates the company and division, displayed as
	CONO_DIVI.
M3EDISalesOrder/SalesOrderHeader/PayFromParty/Contact/Name	
CCUCON.CCTX50; CRS618MI/Get	The field indicates the Our reference person number 1 and number 2
M3EDISalaa Orday/Salaa Orday Haaday/Tyanan aytatia n Taym/Inaa tayma/	(Payer)
M3EDISalesOrder/SalesOrderHeader/TransportationTerm/IncotermsOOHEAD.TEDL; OIS100MI/GetOrderHead	The field indicates delivery terms, which define when the
COTIE/D.TEBE, GIOTOUMI/OStordomicad	responsibility for a delivery is transferred from the supplier to the
	customer.
	marshinTransfort ocation/ID
M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.CCDELT; CRS065MI/GetDelyTerm	The field indicates the delivery terms.
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. IntershipTransferLocation/Description
CSYTAB.CCDELT; CRS065MI/GetDelyTerm	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date.
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to:
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.'
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. IntershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.'
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. IntershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.'
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw	The field indicates the delivery terms. IntershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode M3EDISalesOrder/SalesOrderHeader/DistributedCharge/Description OOCHRG.CRDO; OIS100MI	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode M3EDISalesOrder/SalesOrderHeader/DistributedCharge/Description	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID The field indicates the payment term description The field indicates the charge description: Line Charge
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode M3EDISalesOrder/SalesOrderHeader/DistributedCharge/Description OOCHRG.CRDO; OIS100MI	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID The field indicates the payment term description The field indicates the charge description: Line Charge Order Discount
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode M3EDISalesOrder/SalesOrderHeader/DistributedCharge/Description OOCHRG.CRDO; OIS100MI	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID The field indicates the payment term description The field indicates the charge description: Line Charge Order Discount Service Charge
CSYTAB.CCDELT; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOw CSYTAB.TX40; CRS065MI/GetDelyTerm M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OOHEAD.TEPY; OSI100MI/GetOrderHead M3EDISalesOrder/SalesOrderHeader/PaymentTerm/Term/Description CSYTAB.PARM; CRS175MI/GetGeneralCode M3EDISalesOrder/SalesOrderHeader/DistributedCharge/Description OOCHRG.CRDO; OIS100MI	The field indicates the delivery terms. InershipTransferLocation/Description The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Set to: If ID = 1: 'The buyer assumes liability when the goods leave the supplier's inventory.' If ID = 2: 'The buyer assumes liability when the goods are received at the buyer's transport address.' If ID = 3: 'The buyer assumes liability when the goods are received at the buyer's final address.' The field indicates the payment term ID The field indicates the payment term description The field indicates the charge description: Line Charge Order Discount

OOHEAD.ODAM+IDAM The field indicates the distributed amount for the ff: OHEAD.EXAM+IXAM Line Charge OOCHRG.PBAM Order Discount OOHEAD.ROAM+IROA; OIS100MI Service Charge **Header Charges** /GetLineChrgTot GetOrderValue Rounding off GetOrderValue LstOrderCharges GetOrderValue @currencyID OOCHRG.CUCD; OIS100MI/LstOrderCharges The field indicates the currency. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency M3EDISalesOrder/SalesOrderHeader/DistributedCharge/ReasonCode OOCHRG.CRD0; OIS100MI/LstOrderCharges The field indicates the charge description: Line Charge Order Discount Service Charge Header Charges Rounding off @listID Set to 'Reasons for Charge'. M3EDISalesOrder/SalesOrderHeader/DistributedCharge/CalculationMethodCode The field indicates how a charge is to be calculated or entered for OOCHRG.CRME; OIS100MI/LstConnCOCharge each item charge. Alternatives 0 = Amount, no calculation is made 1 = Calculation factor * gross price 2 = Calculation factor * net price 2 = Calculation factor * gross weight 4 = Calculation factor * net weight 5 = Calculation factor * volume 6 = Amount per quantity M3EDISalesOrder/SalesOrderHeader/DistributedCharge/GrossWeightIndicator .; FIXED VALUE = 'FALSE"/ Always filled with 'false'. M3EDISalesOrder/SalesOrderHeader/DistributedTax/ID .; Fixed Value = "Tax"/ The field has a fixed value of 'Tax' M3EDISalesOrder/SalesOrderHeader/DistributedTax/Description .; Fixed Value = "Tax"/ The field has a fixed value of 'Tax' M3EDISalesOrder/SalesOrderHeader/DistributedTax/Amount MPHEAD.VTAM+IVTA; OIS100MI/GetOrderValue The field indicates the Tax amount @currencyID MPHEAD.CUCD; OIS100MI/GetOrderValue The field indicates the currency. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Currency M3EDISalesOrder/SalesOrderHeader/EarliestDeliveryDateTime OOHEAD.FDED; OIS100MI/GetOrderHead The field indicates the Earliest Delivery Date, the first valid delivery date for a customer order. 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: The field is not published. 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is First/last date (the first part) in OIS100/E M3EDISalesOrder/SalesOrderHeader/RequiredDeliveryDateTime 1.OOHEAD.RLDT+RLHM The field indicates the Requested Delivery Date and Time when the 2.OOHEAD.RLDZ+RLHZ.; OIS100MI/GetOrderHead customer wants the delivery to arrive at the final destination. 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: Second Req delivery dt in OIS100/E, fields OOHEAD.RLDT+RLHM are used 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is

	activated: First Req delivery dt in OIS100/E, fields OOHEAD.RLDZ+RLHZ are used
M3EDISalesOrder/SalesOrderHeader/PaymentMethodCode OOHEAD.OAPYCD; OIS100MI/GetOrderHead	The field indicates the AR payment method.
	When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: M3 AR payment method (PYCD) value is published directly as it is
	defined in CRS076. 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated:
	The value can be translated in CRS881/882. (e.g. Cash, Cheque). It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: ARPaymentMethod
	If translation in CRS881 equals to 'CreditCard/DebitCard/ ElectronicFundsTran', the value published is 'CreditCard/DebitCard/ ElectronicFundsTransfer'.
	If no translation exist in CRS881, or translation is the same as M3 value, the following translation is published based on the payment class:
	Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1.
	Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5.
M3EDISalesOrder/SalesOrderHeader/UserArea/Property/NameValue	Cot to Birotiposit ii paymont class (t 102) to c.
@name CUDFLD.FDTX15;.; CMS082MI/LstFields	Hardcode the SalesOrderHeader/UserArea with the following valuas first oNamerValuename = "M3EDISalesOrderAcknowledge";
	2) User-defined free field name Attribute name set to "m3. <m3 be="" field="">-<cms082 tx15="">". User-defined free fields are only added if control property 'm3beAddFreeFields' is set to 'true' in MeC Administration for this mapping. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for</cms082></m3>
M3EDISalesOrder/SalesOrderHeader/UserArea/Property/Description	fields UDN1-UDN6.
CUDFLV.FVTX40;.; CMS083MI/LstValues	Hardcode the SalesOrderHeader/UserArea with the following valuas first oNameValueDescription = "M3EDI "M3EDI Mapping Variant";
	2) User-defined free field Description
	Description is retrieved from CMS083 TX40.
	User-defined free fields are only added if control property 'm3beAddFreeFields' is set to 'true' in MeC Administration for this
	mapping.
	Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.
M3EDISalesOrder/SalesOrderHeader/PricingRequiredIndicator	
;; FIXED VALUE = 'FALSE/ M3EDISalesOrder/SalesOrderHeader/SalesPersonReference/IDs/ID OOHEAD.SMCD; OIS100MI/GetOrderHead	Always filled with 'false'. The field indicates the Salesman
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
M3EDISalesOrder/SalesOrderHeader/SalesPersonReference/Name	
CSYTAB.TX15; CRS100MI/Get M3EDISalesOrder/SalesOrderHeader/Classification/Codes/Code	The field indicates the Name of Salesperson
1) OOHEAD.OAPYCD OIS100MI/GetOrderHead.; /	When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: The field is not published.
Infor May 26, 20:	1) The field is not published.

	When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated: AR Payment Method The field indicates the AR Payment method as it is defined in
@coguenee	CRS076 without translation.
@sequence	When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: The field is not published. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated:
	The field indicates the sequence number.
@listID	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated:
	1) The field is not published. 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated:
	Set to 'Payment Methods' if Classification/Codes/Code = PYCD.
M3EDISalesOrder/SalesOrderHeader/ExtendedPretaxAmount OOHEAD.ORVA+IRVA; OIS100MI/GetOrderValue @currencyID	The field indicates the pre-tax amount.
OOHEAD.CUCD; OIS100MI/GetOrderHead	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderHeader/SubTotalAmount OOHEAD.TOAM+ITOA; OIS100MI/GetOrderValue @currencyID	The field indicates the sub-total amount.
OOHEAD.CUCD; OIS100MI/GetOrderValue	The field indicates the currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic I/O: O Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderHeader/OrderTypeCode OOHEAD.OAORTP; OIS100MI/GetOrderHead	The field indicates the customer order type
M3EDISalesOrder/SalesOrderLine/LineNumber OOLINE.PONR; OIS100MI/LstLineBOD	The field indicates the Order Line number
M3EDISalesOrder/SalesOrderLine/Description OOLINE.OBTEDS; OIS100MI/LstLineBOD	The field indicates a description.
M3EDISalesOrder/SalesOrderLine/Note OSYTXL.TX40; OIS100MI/LstLineTxt	The field indicates the remarks or notes.
@type .; Fixed value = "Pre-Text", "Post-Text"/	For Pre-text field, 'Pre-Text' is published. For Post-Text field, 'Post-text' is published.
M3EDISalesOrder/SalesOrderLine/DocumentReference	text to published.
@type	Set to 'CustomerPurchaseOrder' if Customer's order number (CUOR) is existing in the order line.
M3EDISalesOrder/SalesOrderLine/DocumentReference/DocumentID/ OOLINE.OBCUOR; OIS100MI/LstLineBOD	The field indicates the Customer's order number if
@accountingEntity	DocumentReference@type='CustomerPurchaseOrder'.
MOEDICalas Ouday/Calas Ouday/ in a /Danning / Danning /	The field indicates the concatenated value of company and division.
M3EDISalesOrder/SalesOrderLine/DocumentReference/LineNumber OOLINE.OBCUPO; OIS100MI/GetLine	The field indicates the Customer's order line number if DocumentReference@type='CustomerPurchaseOrder'.
M3EDISalesOrder/SalesOrderLine/Status/Code OOLINE.ORST; OIS100MI/LstLineBOD	The field indicates the customer order lines status, M3 BE field ORST It is translated according to: 22, 23, 24, 29, 33, 34, 39, 44 or 49 = Approved 26, 27, 36, 37, 46 or 47 = PartiallyShipped 66, 67 or 69 = Shipped 77 or 79 = Invoiced

	90 = Deleted 99= Canceled
M3EDISalesOrder/SalesOrderLine/Status/EffectiveDateTime	or Janosia
OOHEAD.ORDT; OIS100MI/GetOrderHead	If Status is equal to 'Approved' or 'In Process', the Order Date field is
	published.
	If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken.
	Default filled with the UTC number of the Date and Time when the
	BOD is published.
M3EDISalesOrder/SalesOrderLine/Status/ArchiveIndicator	
.; Value = "TRUE" or "FALSE/	If the Sales Order Line is deleted or the Sales Order is deleted and the Order Status is equal to 'Closed' or 'Released', 'true' is published.
	Otherwise, 'false' is published.
M3EDISalesOrder/SalesOrderLine/Item/ItemID/ID	,
OOLINE.ITNO; OIS100MI/LstLineBOD	The field indicates the Item Number
@accountingEntity .CONO+DIVI: -/	The field indicates the company and division
M3EDISalesOrder/SalesOrderLine/Item/CustomerItemID/ID	The field indicates the company and division
OOLINE.ITNO; OIS100MI/GetLine	The field indicates the Alias number
@schemeName	
MITPOP.POPN; /	Set to 'Customer'
@accountingEntity .CONO+DIVI; -/	The field indicates the company and division
M3EDISalesOrder/SalesOrderLine/Item/UPCID	• •
.; MMS025MI/LstAlias	The field indicates the UPCID
M3EDISalesOrder/SalesOrderLine/Item/Description OOLINE.ITDS; OIS100MI/LstLineBOD	The field indicates the Item description
M3EDISalesOrder/SalesOrderLine/Item/SerialNumber	The field fidicates the field description
OOLINE.BANO; OIS100MI/LstLineBOD	The field indicates the Serial number
M3EDISalesOrder/SalesOrderLine/Item/SerializedLot/Lot/LotIDs/ID	The field indicates the let number
OOLINE.BANO; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/Quantity	The field indicates the lot number.
OOLINE.ORQA; OIS100MI/LstLineBOD	The field indicates the Quantity for Order line (in alternate Unit of
	Measure)
@unitCode OOLINE.ALUN; OIS100MI/LstLineBOD	The field indicates the base unit of measure.
OCENTESTY, ONO TOOMINESTEINOBOB	The hold indicates the base unit of medicale.
	The value can be translated in CRS881/882.
	It can be defined on the company level only. Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/BaseUOMQuantity	Bata dement. Odwoode
OOLINE.ORQT; OIS100MI/LstLineBOD	The field indicates the Quantity for Order line (in Basic Unit of
	Measure)
@unitCode MITMAS.UNMS; MMS200MI/GetItmBasic	The field indicates the base unit of measure.
MITMAS.UNMS; MMS200MI/GetttmBasic	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
Machicala Audau/Cala Audaul in a // In it Built - / A 4	Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/UnitPrice/Amount OOLINE.SAPR; OIS100MI/LstLineBOD	The field indicates the unit sales price amount.
@currencyID	·
OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	It can be defined on the company level only. Msg std: ION
	It can be defined on the company level only. Msg std: ION Vers: 1
	It can be defined on the company level only. Msg std: ION
	It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic
MOEDICales Ouday/Cales Ouday/ in a // In it Duiss // Duis	It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O
M3EDISalesOrder/SalesOrderLine/UnitPrice/BaseAmount OOLINE.SAAM/ORQT; OIS100MI/LstLineBOD	It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic

Modelicaciaci	
OOLINE.LOCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderLine/UnitPrice/PerQuantity	The field in disease the according to which the color origin and its Octo-
OOLINE.SACD; OIS100MI/LstLineBOD	The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the item
	unit of measure.
@unitCode	unit of measure.
OOLINE.SPUN; OIS100MI/LstLineBOD	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic I/O: O
	Parent element(s): Generic
	Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/ExtendedAmount	Data cicinchi. Gowlood
OOLINE.GLAM; OIS100MI/LstLineBOD	The field indicates the gross line amount
@currencyID	· ·
OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: I
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderLine/ExtendedBaseAmount	
OOLINE.SAAM; OIS100MI/LstLineBOD	The field indicates the net line amount in local currency.
@currencyID	
OOLINE.LOCD; OIS100MI/LstLineBOD	The field indicates the local currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderLine/TotalAmount	
OOLINE.NLAM; OIS100MI/LstLineBOD	The field indicates the Net Line Amount
@currencyID	
OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	TI I D D D D D D D D D D D D D D D D D D
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency
M3EDISalesOrder/SalesOrderLine/RequiredDeliveryDateTime	
OOLINE.DWDZ+DWHZ; OIS100MI/LstLineBOD	The field indicates the Requested Delivery date
,	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	not activated:
	Req delivery dt in OIS101/F, fields OOLINE.DWDZ+DWHZ are used
	but time is rendered incorrectly to T12:00:00.000Z
	2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	activated:
	Req delivery dt in OIS101/F, fields OOLINE.DWDZ+DWHZ are used
	and time is rendered correctly
M3EDISalesOrder/SalesOrderLine/ShipToParty/PartyIDs/ID	
OOHEAD.ADID; OIS100MI/GetLineAddress	The field indicates the Customer shipping address code.
	the state of the s

The value can be translated in CRS881/882. It can be defined on the division or on the company level. Msg std: M3EDI Vers: 1 Message: Generic I/O: O Parent element(s): ShipToParty Data element: PartyID @accountingEntity .CONO+DĪVI; -/ The field indicates the company and division M3EDISalesOrder/SalesOrderLine/ShipToParty/PartyIDs/TaxID OCUSMA.VRNO; CRS610MI/GetFinancial The field indicates the Tax ID M3EDISalesOrder/SalesOrderLine/ShipToParty/Name The field indicates the Customer name. **OOADRE OCUSAD** OCUSMA.CUNM; OIS100MI /GetLineAddress M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/AttentionOfName The field indicates the Customer responsible. OOADRE **OCUSAD** OCUSMA.YREF-YRE1; OIS100MI /GetLineAddress M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/AddressLine **OOADRE** The field indicates the Address fields (4 fields). **OCUSAD** OCUSMA.CUA1-CUA4; OIS100MI /GetLineAddress @sequence .; Line segunce/ The field indicates the address line sequence number. M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/CityName OOADRE The field indicates the City. **OCUSAD** OCUSMA.TOWN; OIS100MI /GetLineAddress M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/CountrySubDivisionCode OOADRE The field indicates the state OCUSAD OCUSMA.ECAR; OIS100MI /GetLineAddress @listID **OOADRE** The field indicates the list ID depending on the country: **OCUSAD** - Canada has list ID 'Canadian Provinces' OCUSMA.ESCD; OIS100MI - France has list ID 'France - Departements' /GetLineAddress - United States has list ID 'US States' 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: - Other countries have list ID 'Country Sub-divisions' 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated: Other countries have list ID 'SubDivisions - [country code]' M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/CountryCode **OOADRE** The field indicates the CountryCode. OCUSAD OCUSMA.ESCD; OIS100MI The value can be translated in CRS881/882. It can be defined on the company level only. /GetLineAddress Msg std: ION Vers: 1 Message: Generic $I/\Omega \cdot \Omega$ Parent element(s): Generic Data element: CountryCode M3EDISalesOrder/SalesOrderLine/ShipToParty/Location/Address/PostalCode **OOADRE** The field indicates the Postal Code. **OCUSAD** OCUSMA.PONO; OIS100MI /GetLineAddress M3EDISalesOrder/SalesOrderLine/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer The field indicates the contact ID @accountingEntity OOHEAD.OACONO+OADIVI; / The field indicates the company and division, displayed as CONO DIVI. M3EDISalesOrder/SalesOrderLine/ShipToParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get The field indicates the Customer responsible. M3EDISalesOrder/SalesOrderLine/TransportationTerm/IncotermsCode OOLINE.TEDL; OIS100MI/LstLineBOD

	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
M3EDISalesOrder/SalesOrderLine/TransportationTerm/PlaceOfOwne CSYTAB.TX40; CRS065MI/GetDelyTerm	
	Alternatives 1 = The buyer assumes liability when the goods leave the supplier's
	inventory.
	 2 = The buyer assumes liability when the goods are received at the buyer's transport address. 3 = The buyer assumes liability when the goods are received at the
	buyer's final address.
M3EDISalesOrder/SalesOrderLine/PaymentTerm/Term/ID OOLINE.TEPY; OIS100MI/LstLineBOD	The field indicates the payment term
M3EDISalesOrder/SalesOrderLine/PaymentTerm/Term/Description CSYTAB.TX40; CRS175MI/GetGeneralCode	The field indicates the payment term description
M3EDISalesOrder/SalesOrderLine/DistributedCharge/Description .; Fixed value = "Discount"/	Set to 'Discount'
M3EDISalesOrder/SalesOrderLine/DistributedCharge/Amount OOLINE.DIA1 DIA2 DIA3 DIA4	The field indicates the discount amount
DIA5 DIA6; OIS100MI/LstLineBOD	
@currencyID OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1
	Message: Generic I/O: I
M3EDISalesOrder/SalesOrderLine/DistributedCharge/Calculation/Rat OOLINE.DIP1	Parent element(s): Generic Data element: Currency
	Parent element(s): Generic Data element: Currency eNumeric
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode	Parent element(s): Generic Data element: Currency TeNumeric The field indicates the discount percentage
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD	Parent element(s): Generic Data element: Currency TeNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1'
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode	Parent element(s): Generic Data element: Currency ReNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3'
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode	Parent element(s): Generic Data element: Currency ReNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5'
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode .; Fixed value = "Discount"/	Parent element(s): Generic Data element: Currency ReNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5' 'Discount 6' The field indicates the discount reason code. Depending on which discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 6' The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 6' The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 6' The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 6' The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 6' The field indicates the discount reason code.
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode .; Fixed value = "Discount"/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/CalculationMetal.; Fixed value = ""/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/GrossWeightIn	Parent element(s): Generic Data element: Currency PeNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5' 'Discount 6' The field indicates a fixed value of blank dicator
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode .; Fixed value = "Discount"/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/CalculationMet; Fixed value = ""/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/GrossWeightIne; Fixed value = "False"/	Parent element(s): Generic Data element: Currency PeNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5' 'Discount 6' PhodCode The field indicates a fixed value of blank
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode .; Fixed value = "Discount"/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/CalculationMetal.; Fixed value = ""/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/GrossWeightIn	Parent element(s): Generic Data element: Currency ReNumeric The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5' 'Discount 6' ModCode The field indicates a fixed value of blank dicator The field indicates a fixed value of False The field indicates the Planned departure date + time 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: Departure date in OIS101/I, but incorrect fields are used: OOLINE.CODT+COHM 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
OOLINE.DIP1 DIP2 DIP3 DIP4 DIP5 DIP6; OIS100MI/LstLineBOD M3EDISalesOrder/SalesOrderLine/DistributedCharge/ReasonCode .; Fixed value = "Discount"/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/CalculationMeta.; Fixed value = ""/ M3EDISalesOrder/SalesOrderLine/DistributedCharge/GrossWeightInd.; Fixed value = "False"/ M3EDISalesOrder/SalesOrderLine/PromisedShipDateTime 1.OOLINE.CODT+COHM; 2.OOLINE.DSDT+DSHM.CODT+COHM; 1.OIS100MI.GetLine;	Parent element(s): Generic Data element: Currency **ReNumeric** The field indicates the discount percentage The field indicates the discount reason code. Depending on which discount is applied, set to one of the following values: 'Discount 1' 'Discount 2' 'Discount 3' 'Discount 4' 'Discount 5' 'Discount 6' **HodCode** The field indicates a fixed value of blank* **dicator** The field indicates a fixed value of False The field indicates the Planned departure date + time 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is not activated: Departure date in OIS101/I, but incorrect fields are used: OOLINE.CODT+COHM

activated: Conf dely dt in OIS101/I, fields OOLINE.CODZ+COHZ are used and time is rendered correctly M3EDISalesOrder/SalesOrderLine/PurchaseOrderReference/DocumentID/ID 1. OOOREF.OORIDN; OIS100MI/GetLine2 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is 2. OOLINE.OBRORN; OIS100MI/LstLineBOD.; / not activated: The fields indicates the batch order number. 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated: The fields indicates the reference to the purchase order number Ref order no in OIS101/F. This element should be filled if the line type (OOLINE.OBLTYP) is 1 (=An order line that creates a purchase order. Delivery is made from stock.) or 2 (=A purchase order is created for the order line, with delivery address according to the customer order. Direct delivery from supplier to customer.) A line type is specified in 'CO Type. Open' (OIS010), and it is proposed by default when the customer order type is used during customer order entry. M3EDISalesOrder/SalesOrderLine/PurchaseOrderReference/LineNumber 1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is 2. OOLINE.OBRORL; OIS100MI/LstLineBOD.; / not activated: The fields is not published. 2. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is activated: The fields indicates the reference to the purchase order line number Ref order line in OIS101/F. This element should be filled if the line type (OOLINE.OBLTYP) is 1 (=An order line that creates a purchase order. Delivery is made from stock.) or 2 (=A purchase order is created for the order line, with delivery address according to the customer order. Direct delivery from supplier to customer.) A line type is specified in 'CO Type. Open' (OIS010), and it is proposed by default when the customer order type is used during customer order M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/LineNumber OOLINE.POSX; OIS100MI/LstLineBOD The field indicates the subline number M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/Item/ItemID/ID OOLINE.ITNO; OIS100MI/LstLineBOD The field indicates the Item Number M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/Item/Description MITMAS.ITDS; MMS200MI/GetItmBasic The field indicates the Item description M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/Item/SerialNumber OOLINE.SERN; OIS100MI/LstLineBOD The field indicates the Serial number M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.BANO; OIS100MI/LstLineBOD The field indicates the lot number. M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/Quantity OOLINE.ORQA; OIS100MI/LstLineBOD The field indicates the Quantity for Order line (in Basic Unit of Measure) @unitCode OOLINE.ALUN; OIS100MI/LstLineBOD The field indicates the base unit of measure. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: UOMCode M3EDISalesOrder/SalesOrderLine/SalesOrderSubLine/BaseUOMQuantity OOLINE.ORQT; OIS100MI/LstLineBOD The field indicates the Quantity for Order line (in Basic Unit of Measure) @unitCode MITMAS.UNMS; MMS200MI/GetItmBasic The field indicates the base unit of measure. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic

M3EDISalesOrder/SalesOrderLine/UserArea/Property/NameValue

CUDFLD.FDTX15;.; CMS082MI/LstFields

User-defined free field Name

Parent element(s): Generic Data element: UOMCode

Attribute name is set to "m3.<M3 BE field>-<CMS082 TX15>". User-defined free fields are only added if control property

Infor May 26, 2023 408

I/O: O

MITWHL.PONO; MMS005/GetWarehouse	The field indicates the postal code.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/Address/F	
@listID	Data element: CountryCode Set to 'Countries'.
	I/O:O Parent element(s): Generic
	Vers: 1 Message: Generic
	It can be defined on the company level only. Msg std: ION
IVII I VVITL.COCD, IVIIVIOUUS/GELVVAIEITUUSE	The value can be translated in CRS881/882.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/Address/OMITWHL.CSCD; MMS005/GetWarehouse	
	When Feature ID=2275202 in CMŚ975 Feature list. Open in M3 is activated: Other countries have list ID 'SubDivisions - [country code]'
	not activated: - Other countries have list ID 'Country Sub-divisions' 2. When Facture ID=2375300 in CMS075 Facture list. Open in M3 is
	1. When Feature ID=2275202 in CMS975 Feature list. Open in M3 is
	- France has list ID 'France - Departements' - United States has list ID 'US States'
MITWHL.CSCD; MMS005/GetWarehouse	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces'
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/Address/CMITWHL.ECAR; MMS005/GetWarehouse @listID	CountrySubDivisionCode The field indicates the state
MITWHL.TOWN; MMS005/GetWarehouse	The field indicates the city where the warehouse is located.
MITWHL.ADR1, ADR2, ADR3, ADR4; MMS005/GetWarehouse M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/Address/0	The field indicates the warehouse address line
MITWHL.WHNM; MMS005/GetWarehouse M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/Address/A	
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Name	•
	Parent element(s): ShipFromParty Data element: PartyID
	Message: Generic I/O:O
	Msg std: M3EDI Vers: 1
	The value can be translated in CRS881/882. It can be defined on the company and on division level.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/PartyIDs/ID OOLINE.WHLO; OIS100MI/LstLineBOD	The field indicates the warehouse where the item is from.
M3EDISologOvdov/SologOvdovi inc/Shin Fugur Book /Book 4Bo-//B	RushIndicator = 'false' if PRIO != 1
OOLINE.OBPRIO; OIS100MI/LstLineBOD	Boolean that tells if an order is a rush order. Turn this on for order lines having order priority equal 1. RushIndicator = 'true' if PRIO = 1
OOHEAD.OFNO; OIS100MI/GetOrderHead M3EDISalesOrder/SalesOrderLine/RushIndicator	The field indicates the quote number
M3EDISalesOrder/SalesOrderLine/QuoteReference/DocumentID/ID	order line.
M3EDISalesOrder/SalesOrderLine/ContractReference/DocumentID/ID OOLINE.OBAGNO; OIS100MI/LstLineBOD	The field indicates the blanket agreement number in the customer
	Elements are excluded. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.
CUDFLV.FVTX40;.; CMS083MI/LstValues	User-defined free field description: Description is retrieved from CMS083 TX40. User-defined free fields are only added if control property 'm3beAddFreeFields' is set to 'true' in MeC Administration for this mapping and the line is a normal line or a KIT header. KIT components are excluded.
M3EDISalesOrder/SalesOrderLine/UserArea/Property/Description	fields UDN1-UDN6.
	mapping and the line is a normal line or a KIT header. KIT components are excluded. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDNA UDNA.
	'm3beAddFreeFields' is set to 'true' in MeC Administration for this

WIJEDISalesOluei	
OOLINE.ALQT+PLQT; OIS100MI/LstLineBOD @unitCode	The field indicates the quantity of Allocated and Picked items.
MITMAS.UNMS; MMS200MI/GetItmBasic	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: I
	Parent element(s): Generic Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/OpenBaseUOMQuantity	
OOLINE.ORQT- ALQT- PLQT-DLQT-IVQT; OIS100MI/LstLineBOD	The field indicates the open quantity (not yet allocated items).
@unitCode	
MITMAS.UNMS; MMS200MI/GetItmBasic	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
M2EDISolooOvdov/SolooOvdov/ inc/ShinnodOverdite	Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/ShippedQuantity OOLINE.DLQT+IVQT; OIS100MI/LstLineBOD	The field indicates the quantity of delivered and invoiced items.
@unitCode .; MMS200MI/GetItmBasic	The field indicates the base unit of measure.
	T
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: ÙÓMCode
M3EDISalesOrder/SalesOrderLine/ShippedBaseUOMQuantity OOLINE.DLQT+IVQT; OIS100MI/LstLineBOD	The field indicates the quantity of delivered and invoiced items.
@unitCode MITMAS.UNMS; MMS200MI/GetItmBasic	The field indicates the base unit of measure.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic Data element: UOMCode
M3EDISalesOrder/SalesOrderLine/PricingAmount/UnitBaseAmount OOLINE.SAPR; OIS100MI/LstLineBOD	The field indicates the sales price for each sales price quantity.
@currencyID	maisates and sales price for sales price qualitity.
OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O Parent element(s): Generic
	Data element: Currency
//3EDISalesOrder/SalesOrderLine/PricingAmount/UnitPretaxAmount	!
OOLINE.NEPR; OIS100MI/LstLineBOD	The field indicates the net price.
@currencyID OOLINE.CUCD; OIS100MI/LstLineBOD	The field indicates the currency.
	The value can be translated in CRS881/882.
	It can be defined on the company level only.
	Msg std: ION
	Vers: 1
	Message: Generic
	I/O: O
	Parent element(s): Generic
	Data element: Currency

OOLINE.NLAM; OIS100MI/LstLineBOD

@currencyID

OOLINE.CUCD; OIS100MI/LstLineBOD

The field indicates the net amount The field indicates the currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic I/O: O

Parent element(s): Generic Data element: Currency

M3EDISalesOrder/SalesOrderLine/PricingAmount/TotalPretaxBaseAmount

OOLINE.SAAM; OIS100MI/LstLineBOD

@currencyID

OOLINE.LOCD; OIS100MI/LstLineBOD

The field indicates the line amount in local currency

The field indicates the currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1 Message: Generic

I/O: O

Parent element(s): Generic Data element: Currency

M3EDISalesOrder/SalesOrderLine/PricingAmount/UnitTotalAmount

OOLINE.NEPR; OIS100MI/LstLineBOD

@currencyID

OOLINE.CUCD; OIS100MI/LstLineBOD

The field indicates the Net Line Amount (as well as currency)

The field indicates the currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1 Message: Generic I/O: O

Parent element(s): Generic Data element: Currency

M3EDISalesOrder/SalesOrderLine/ProjectReference/ID

OOLINE.OBPROJ; OIS100MI/LstLineBOD

@accountingEntity

.; /

The field indicates the project number.

The field indicates the company and division, displayed as CONO DIVI.

M3EDISalesOrder/SalesOrderLine/DropShipIndicator

OOLINE.OPLTYP; OIS100MI/LstLineBOD

The field indicates if the item should generate a purchase order and if the goods shall be shipped directly to the customer. Set to 'true' if LTYP = 1 or 2 (order line that creates a purchase, manufacturing or distribution order), and Ref order no (OIS101/F) not equals to

'????????.

M3EDIShipment M3EDIShipment/TradingPartnerID	
	The field indicates the trading partner ID. The value is retrieved from field RRD1 in CRS949/J.
@schemeName	The field indicates the trading partner ID schemeName. The value is retrieved from field RRD2 in CRS949/J.
M3EDIShipment/ShipmentHeader/DocumentID/ID	
For Shipment: DCONSI.DACONN; DRS100MI/LstShipment	For Shipment: The field indicates a shipment number, which is the unique identity used to identify a shipment.
For Delivery: MHDISH.OQDLIX; MWS410MI/GetHead	For Delivery: The field indicates the delivery number. This unique ID for the delivery is created or updated automatically during order line entry.
0	Several order numbers can be attached to the same delivery number if allowed by the dispatch policy (MWS010).'
@accountingEntity For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI .; /	
@location For Shipment: MHPICH.PIWHLO; DRS100MI/LstShipPickList	For Shipment: The field indicates the Warehouse
For Delivery: MHDISH .OQWHLO; MWS410MI/GetHead	For Delivery: This field indicates the warehouse location.
@variationID	For Shipment: The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	For Delivery: The field indicates the sequence number that identifies the number of times that the BOD has been published.
and	For Shipment: The field indicates the logical ID of the system.
	For Delivery: The field indicates the logical ID of the system.
M3EDIShipment/ShipmentHeader/DisplayID	·
For Delivery: MHDISH.OQDLIX; MWS410MI/GetHead	For Delivery: This field indicates the delivery number
M3EDIShipment/ShipmentHeader/LastModificationDateTime	This field indicates the delivery flumber
For Shipment: DCONSI.DALMTS; DRS100MI/LstShipment	For Shipment: The field indicates the last date and time the record is modified.
M3EDIShipment/ShipmentHeader/LastModificationPerson/IDs/ID	
For Shipment: DCONSI.DACHID; DRS100MI/LstShipment @accountingEntity	For Shipment: The field indicates the ID of the person who last modified the record.
For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /	For Shipment: The field indicates the company and division, displayed as CONO DIVI.
M3EDIShipment/ShipmentHeader/DocumentDateTime	
For Shipment: DCONSI.DARGDT DCONSI.DARGTM.; DRS100MI/GetShipment	For Shipment: The field indicates the record's entry date and time. It is a concatenation of entry date (RGDT) <8> + entry time (RGTM) <6>.
For Delivery: MHDISH.OQTRDT MHDISH.OQTRTM.; MWS410MI/GetHead	For Delivery: The field indicates the document date and time.
M3EDIShipment/ShipmentHeader/DocumentReference	
@type For Delivery: MHDISH.OQRORC; MWS410MI/GetHead	For Delivery: The field indicates the reference order category.
	1 - ProductionOrder2 - PurchaseOrder3 - SalesOrder4 - RequisitionOrder5 - DistributionOrder

May 26, 2023 412 Infor

M3EDIShipment 6 - WorkOrder 7 - ServiceOrder 8 - ProjectOrder 9 - ClaimOrder M3EDIShipment/ShipmentHeader/DocumentReference/DocumentID/ID For Delivery: For Delivery: **MHDISH** The field indicates the reference order number. .OQRIDN; MWS410MI/GetHead @accountingEntity For Delivery: For Delivery: MHDISH.OQCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI CONO_DIVI. M3EDIShipment/ShipmentHeader/Status/Code For Shipment: For Shipment: DCONSI.DACSTL; DRS100MI/LstShipment The field indicates the status of the Shipment. For Delivery: 00 - Open MHDISH.OQPGRS; MWS410MI/GetHead 10 - Open 20 - Allocated 30 - Allocated 40 - Staged 50 - Loaded 60 - Shipped 90 - Cancelled For Delivery: The field indicates the status of a delivery. 00 -> 59 Open 60 -> 89 Staged 90 -> 95 Shipped M3EDIShipment/ShipmentHeader/ShipUnitQuantity For Delivery For Delivery: MWS410MI/GetHead The field indicates the ship unit quantity M3EDIShipment/ShipmentHeader/WarehouseLocation/ID For Shipment: For Shipment: DCONSI.DAWHLO; DRS100MI/LstShipment The field indicates the warehouse ID. For Delivery: Warehouse is a stock zone which is used to distinguish different MHDISH.OQWHLO; MW410MI/GetHead geographical locations within a company. The warehouse is used as a planning level for material and production. Stock zones, stock locations and items are connected to the warehouse. For Delivery: The field indicates the location. @accountingEntity The field indicates the company and division, displayed as For Shipment: DCONSI.DACONO CONO DIVI. DCONSI.DADIVI.; / For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; / M3EDIShipment/ShipmentHeader/WarehouseLocation/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse description. M3EDIShipment/ShipmentHeader/WarehouseLocation/Address/AddressLine CIADDR.OAADR1 For Shipment:

CIADDR.OAADR2 The field indicates an address line. A maximum of 36 characters may

CIADDR.OAADR3 be used.

CIADDR.OAADR4.; MMS005MI/GetWarehouse

For Delivery:

The field indicates the address line. @sequence

For Shipment

The field indicates the address line sequence.

For Delivery:

Auto generated sequence number for the address line.

M3EDIShipment/ShipmentHeader/WarehouseLocation/Address/CityName

CIADDR.OATOWN; MMS005MI/GetWarehouse The field indicates the city name.

M3EDIShipment/ShipmentHeader/WarehouseLocation/Address/CountrySubDivisionCode CIADDR.OAECAR; MMS005MI/GetWarehouse For Shipment:

The field indicates an area, province or state within a country.

@listID

For Delivery:

The field indicates an area, province or state within a country

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

M3EDIShipment/ShipmentHeader/WarehouseLocation/Address/CountryCode

CIADDR.OACSCD; MMS005MI/GetWarehouse

For Shipment:

The field indicates the country code.

For Delivery:

The field indicates the Country code (CSCD) of company from

(MNS100).

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

Set to "Countries"

M3EDIShipment/ShipmentHeader/WarehouseLocation/Address/PostalCode

CIADDR.OAPONO; MMS005MI/GetWarehouse

For Shipment:

The field indicates the postal code.

For Delivery:

The field indicates the postal code

M3EDIShipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID

For Shipment:

DCONSI.DAROUT; DRS100MI/LstShipment

For Delivery:

MHDISH.OQROUT; MWS410MI/GetHead

For Shipment:

The field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region, such as southeast Germany

Routes are used to:

- Coordinate transportation to several customers along a road or within a specified area
- Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination.

For Delivery:

The field indicates the transportation route. A route is determined by a loading place with one or more unloading locations. The unloading locations can be located in a geographical area or region, such as southeast Germany.

Routes are used to:

- Coordinate transportation to several customers along a road or within a specified area
- Distinguish orders needing special handling, such as special deliveries to be made with a company vehicle. In this case, the route can vary every time depending on where the order's destination.

The field indicates the company and division, displayed as CONO DIVI.

@accountingEntity

For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /

For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/RouteDay

For Delivery:

MHDISH.OQDEWD; MWS410MI/GetHead

For Delivery:

The field indicates the day of the week when delivery is made to a customer. This information is specified in the order header for a standing order, but can be changed for each individual order line.

Alternatives

- 1 = Mondays
- 2 = Tuesdays
- 3 = Wednesdays
- 4 = Thursdays
- 5 = Fridays
- 6 = Saturdays
- 7 = Sundays.

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/RequiredShipDateTime

For Delivery For Delivery

MHDISH.OQDTDT The field indicates the requested departure date/time of the delivery

OQDTHM; MWS410MI/GetHead

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/PlannedShipDateTime

For Shipment: For Shipment:

DCONSI.DARDDT The field indicates the planned route departure date and time. It is a DCONSI.DARDTM.; DRS100MI/GetShipment

concatenation of planned departure date (RDDT) <8> + planned

departure time (RDTM) <4>

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/PlannedDeliveryDateTime

For Shipment: For Shipment:

DCONSI.DAPWDT The field indicates the forwarder's planned arival date and time. It is a DCONSI.DAPWHM.; DRS100MI/GetShipment

concatenation of planned arrival date (PWDT) <8> + planned arrival

time (PWHM) <4>

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/CarrierParty/Party/Ds/ID

For Shipment: The field indicates the forwarding agent who can be used for the DCONSI.DAFWNO; DRS100MI/GetShipment

transport.

MHDISH.OQFWNO; MWS410MI/GetHead

@accountingEntity

For Shipment: The field indicates the company and division, displayed as

DCONSI.DACONO CONO DIVI. DCONSI.DADIVI.;

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/CarrierParty/Name

CIDMAS.IDSUNM; CRS620MI/GetBasicData

The field indicates the Fowarder's name.

For Delivery:

The field indicates supplier name, most often the supplier's company

name.

M3EDIShipment/ShipmentHeader/CarrierRouteReference/RouteStop/CarrierParty/SCAC

CIDMAS.IDFWSC: CRS620MI/GetBasicData For Shipment:

The field indicates the forwarder SCAC.

For Delivery:

The field indicates the SCAC code for the Vendor

M3EDIShipment/ShipmentHeader/CarrierRouteReference/MasterBillOfLadingID

For Delivery: For Delivery:

DDOCUX.DBMBOL; MWS410MI/GetHead The field indicates the master bill of lading ID

M3EDIShipment/ShipmentHeader/ActualShipDateTime

For Shipment: For Shipment:

DCONSI.DADFDT The field indicates the departure date. DCONSI.DADFHM

DCONSI.DADSDT

If field actual departure date (DFDT) is not empty, the element DCONSI.DADSHM.; DRS100MI/GetShipment displays actual departure date (DFDT) and time (DFHM). Else,

departure date (DSDT) and time (DSHM) are displayed.

MHDISH.OQDSDT For Delivery:

OQDSHM; MWS410MI/GetHead The field indicates the actual departure date/time of the delivery.

M3EDIShipment/ShipmentHeader/ScheduledDeliveryDateTime

For Shipment: For Shipment:

DCONSI.DAARDT The field indicates the Planned Route Departure Date and Time

DCONSI.DAARHM DCONSI.DARDDT

For Delivery:

If planned route departure date (RDDT) is blank, arrival date (ARDT)

DCONSI.DARDTM.; DRS100MI/GetShipment and time (ARHM) are displayed in this element.

For Delivery: For Delivery:

MHDISH.OQDEDA The field indicates the estimated date and time of arrival at the place

MHDISH.OQDLTM.; / of unloading for outbound deliveries.

M3EDIShipment/ShipmentHeader/ActualDeliveryDateTime

For Shipment: For Shipment:

DCONSI.DAARDT The field indicates when a transfer from the subsidiary company has

DCONSI.DAARHM.; DRS100MI/GetShipment arrived to the parent company.

For Delivery: For Delivery:

MITTRA.MTRGDT The field indicates the date/time the goods were delivered. MTRGTM; MWS070MI/LstTransByOrder

M3EDIShipment/ShipmentHeader/EstimatedWeightMeasure

For Shipment: For Shipment:

DCONSI.DAGWTE; DRS100MI/GetShipment The field indicates the Estimated Gross Weight. @unitCode

For Shipment: For Shipment:

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds The field indicates the general unit of measure for all weights within a

company.

@sequence

M3EDIShipment/ShipmentHeader/LoadingWeightMeasure	
For Shipment: DCONSI.DAGRW2; DRS100MI/GetShipment @unitCode	For Shipment: The field indicates the Packed Gross Weight
For Shipment: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: The field indicates the general unit of measure for all weights within a company.
M3EDIShipment/ShipmentHeader/NetWeightMeasure	
For Delivery: MHDISH.OQNEWE; MWS410MI/GetHead @unitCode	For Delivery: The field indicates the total weight of all items in the delivery.
For Delivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Delivery: The field indicates the general unit of measure for all weights within a company.
M3EDIShipment/ShipmentHeader/GrossWeightMeasure	
For Shipment: DCONSI.DAGRWE; DRS100MI/GetShipment	For Shipment: The field indicates the Gross Weight
For Delivery: MHDISH.OQGRW2; MWS410MI/GetHead @unitCode	For Delivery: The field indicates the gross weight of all items in the delivery.
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
M3EDIShipment/ShipmentHeader/TotalVolumeMeasure	
For Shipment: DCONSI.DAVLME; DRS100MI/GetShipment	For Shipment: The field indicates the Estimated Volume
For Delivery: MHDISH.OQVM32; MWS410MI/GetHead @unitCode	For Delivery: The field indicates the volume of all items in the delivery.
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: The field indicates the general unit of measure for all volumes within a company.
	For Delivery: The field indicates the unit code.
M3EDIShipment/ShipmentHeader/TransportationMethodCode	
For Shipment: CSYTAB.CTPARM; CRS070MI/GetDelyMethod	For Shipment: The field indicates how the delivery is made.
For Delivery: MDDADV.OVTRCA; MWS410MI/GetHead	For Delivery: The field indicates transportation equipment which is the unique code identifying a specific mode of transportation.
	The code may for instance be the license number of a truck, the flight number of an aircraft etc.
M3EDIShipment/ShipmentHeader/ShipFromParty/PartyIDs/ID	
For Shipment: MHPICH.PIWHLO; DRS100MI/LstShipPicklist	For Shipment: The field indicates the warehouse where the delivery is shipped from.
For Delivery:	For Delivery:
OCUSMA.OKCUSU; CRS610MI/GetBasicData	The field indicates the supplier number at customer. The field is only used as a search key in the customer file.
@schemeName	For Delivery: Text set to 'Supplier'.
@accountingEntity	
For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
M3EDIShipment/ShipmentHeader/ShipFromParty/Name	
For Shipment: MITWHL.MWWHNM: MMS005MI/GetWarehouse	For Shipment: The field indicates the warehouse description.
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/ID	The held indicates the warehouse description.
For Delivery: MHDISH.OQWHLO; MWS410MI/GetHead	For Delivery: This field indicates the Ship From Warehouse
@accountingEntity For Delivery:	For Delivery:
MHDISH.OQCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/Address	
CIADDR.OAADR1 CIADDR.OAADR2	The field indicates an address line. A maximum of 36 characters may be used.
CIADDR.OAADR3	
CIADDR.OAADR4.; MMS005MI/GetWarehouse	

	For Shipment: The field indicates the address line sequence.
	·
	For Delivery: Auto generated sequence number for the address line.
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/Address/ CIADDR.OATOWN: MMS005MI/GetWarehouse	CityName The field indicates the city name.
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/Address/	
CIADDR.OAECAR; MMS005MI/GetWarehouse	For Shipment: The field indicates an area, province or state within a country.
@lietID	For Delivery: The field indicates an area, province or state within a country
@listID	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/Address/0	
CIADDR.OACSCD; MMS005MI/GetWarehouse	For Shipment: The field indicates the country code.
	For Delivery: The field indicates the countrycode Generic translation is used to translate CSCD to alpha-2 country code according to ISO 3166-1.
@listID	For Shipment: Set to "Countries".
	For Delivery: Set to 'Countries'.
M3EDIShipment/ShipmentHeader/ShipFromParty/Location/Address/l	PostalCode
CIADDR.OAPONÓ; MMS005MI/GetWarehouse	For Shipment: The field indicates the postal code.
	For Delivery: The field indicates the Postal Code.
M3EDIShipment/ShipmentHeader/CarrierParty/PartyIDs/ID For Shipment: DCONSI.DAFWNO; DRS100MI/LstShipment	The field indicates the forwarding agent who can be used for the transport.
For Delivery: MHDISH.OQFWNO; MWS410MI/GetHead @accountingEntity For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /	
M3EDIShipment/ShipmentHeader/CarrierParty/PartyIDs/SCACID	
For Shipment: CIDMAS.IDFWSC; CRS620MI/GetBasicData	For Shipment: The field indicates the forwarder SCAC.
M3EDIShipment/ShipmentHeader/CarrierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name, most often the supplier's company
M3EDIShipment/ShipmentHeader/CarrierParty/SCAC For Delivery:	name. For Delivery:
.; CRS620MI/GetBasicData	The field indicates the SCAC code for the Vendor
M3EDIShipment/ShipmentHeader/FreightTermCode	For Polivene
For Delivery: CSYTAB.CTPARM; CRS065MI/GetDelyTerm	For Delivery: The field indicates the payer of the freight cost.
	If field RCPY = 0, the element is set to Sender pays
	If field RCPY = 1, the element is set to Recipient pays
	If field RCPY = 2, the element is set to Prepaid
	If field RCPY = 3, the element is set to Collect

For Delivery:

DCONSI.DAWHLO: MWS410MI/GetHead The field indicates the warehouse ID.

@accountingEntity

For Delivery:

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/PartyIDs/TaxID

For Delivery: For Delivery

CIDMAS.IDVRNO; CRS620MI/GetBasicData The field indicates the VAT registration number.

@schemeName

For Delivery:

Set to 'TaxIdentificationNumber' if TaxID is VRNO.

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Name

For Delivery: For Delivery:

MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse description

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/ID

For Shipment: For Shipment:

MHPICH.PIWHLO; DRS100MI/LstShipPicklist The field indicates the warehouse where the delivery is shipped from.

@accountingEntity

For Shipment: For Shipment:

DCONSI.DACONO The field indicates the company and division, displayed as

DCONSI.DADIVI.; CONO DIVI.

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Name For Shipment:

For Shipment: MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse description

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address

@type

For Delivery: Set to 'text'

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/AddressLine

For Shipment: The field indicates an address line. A maximum of 36 characters may

CIADDR.OAADR1 CIADDR.OAADR2 CIADDR.OAADR3

CIADDR.OAADR4.; MMS005MI/GetWarehouse

For Delivery: CIADDR.OAADR1 CIADDR.OAADR2

CIADDR.OAADR3 CIADDR.OAADR4.; MWS410MI/GetAdr

@sequence

For Shipment:

The field indicates the address line sequence.

For Delivery:

Auto generated sequence number for the address line.

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CityName

For Shipment: The field indicates the city in an address.

CIADDR.OATOWN; MMS005MI/GetWarehouse

For Delivery

CIADDR.OATOWN; MWS410MI/GetAdr

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountrySubDivisionCode

For Shipment: For Shipment:

CIADDR.OAECAR; MMS005MI/GetWarehouse The field indicates an area, province or state within a country.

For Delivery: For Delivery:

CIADDR.ECAR; MWS410MI/GetAdr The field indicates an area, province or state within a country.

The field indicates the Area/State code (ECAR) of company from

(MNS100).

Generic translation (blank division) is used to translate ECAR

according to ISO 3166-2 (M3 data set to 'Country code-Area/

state' (CSCD-ECAR)).

@listID For Shipment:

Set to 'Canadian Provinces' if the country is CA (Canada).

Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States)

Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

For Delivery:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France).

Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountryCode

For Shipment: For Shipment:

CIADDR.OACSCD; MMS005MI/GetWarehouse The field indicates a country.

For Delivery:

For Delivery: CIADDR.CSCD; MWS410MI/GetAdr The field indicates a country.

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Shipment: Set to "Countries".

For Delivery: Set to 'Countries'

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/PostalCode

For Shipment: For Shipment:

CIADDR.OAPONO; MMS005MI/GetWarehouse The field indicates a postal code for a specific address.

For Delivery: For Delivery:

CIADDR.PONO; MWS410MI/GetAdr The field indicates a postal code for a specific address.

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Communication

@preferredIndicator

For Delivery: Set to 'false'

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Communication/ChannelCode

For Delivery:

Set to "Phone" if telephone number or facsimile number.

Set to "EMail" if e-mail address.

@listID

For Delivery:

Set to 'Communication Channels'

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Communication/UseCode

For Delivery:

Set to "Office" if telephone number or e-mail.

Set to "Fax" if facsimile number.

@listID

For Delivery:

OQCOAA; MWS410MI/LstAdr

For Delivery:

Set to 'Communication Use Codes'

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Communication/DialNumber

For Delivery For Delivery:

CIDMAS.IDPHNO CIDMAS.IDPHN2

The field indicates the telephone number or facsimile number.

CIDMAS.IDTFNO.; CRS620MI/GetBasicData

M3EDIShipment/ShipmentHeader/ReturnToShipFromParty/Communication/URI

For Delivery:

The field indicates the e-mail address. CEMAIL.CBEMAL; CRS111MI/Get

M3EDIShipment/ShipmentHeader/ShipToParty/PartyIDs/ID

For Shipment: For Shipment:

MHDISH The field indicates the consignee's ID.

.OQCONA; MWS410MI/LstAdr

For Delivery: For Delivery: The field indicates the consignee's ID, which depends on the MHDISH

delivery's order category. If Address ID (COAA) is blank, .OQCONA ShipToPartyID = CONA else ShipToPartyID = CONA+COAA. CONA OQCOAA; MWS410MI/LstAdr and COAA will be concatenated without separator. CONA has exactly

10 characters while COAA can have maximum of 6. **

@accountingEntity MHDISH.OQCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI.

M3EDIShipment/ShipmentHeader/ShipToParty/Name

For Shipment: CIADDR

OOADRE.OAWHNM The field indcates the ship to name. ODCUNM; MWS410MI/LstAdr

For Delivery:

This is the Ship To Name.***

M3EDIShipment/ShipmentHeader/ShipToParty/Location/ID

For Shipment: For Shipment:

MHDISH.OQCONA The field indicates the consignee's ID, which depends on the MHDISH.OQCOAA.; MWS410MI/LstAdr delivery's order category. If Address ID (COAA) is blank,

ShipToPartyID = CONA else ShipToPartyID = CONA+COAA. CONA

and COAA will be concatenated without separator. CONA has exactly

MHDISH OQCONA 10 characters while COAA can have maximum of 6.

M3EDIShipment For Delivery: The field indicates the consignee's ID, which depends on the delivery's order category. If Address ID (COAA) is blank, ShipToPartyID = CONA else ShipToPartyID = CONA+COAA. CONA and COAA will be concatenated without separator. CONA has exactly 10 characters while COAA can have maximum of 6. *** @accountingEntity For Delivery: For Delivery: MHDISH.OQCONO The field indicates the company and division, displayed as CONO DIVI CMNDIV.CCDIVI.; / M3EDIShipment/ShipmentHeader/ShipToParty/Location/Address/AddressLine The field indicates the address line. For Shipment: CIADDR CIADDR CIADDR **CIADDR OCUSAD OCUSAD OCUSAD** OCUSAD.OAADR1 OAADR2 OAADR3 OAADR4 OPADR1 OPADR2 OPADR3 OPADR4 ; MWS410MI/LstAdr For Delivery: CIADDR.OAADR1 CIADDR.OAADR2 CIADDR.OAADR3 CIADDR.OAADR4 OCUSAD.OPADR1 OCUSAD.OPADR2 OCUSAD.OPADR3 OCUSAD.OPADR4.; MWS410MI/LstAdr @sequence For Delivery: Auto generated sequence number for the address line. M3EDIShipment/ShipmentHeader/ShipToParty/Location/Address/CityName For Shipment: The field indicates the city name. CIADDR OCUSAD.OATOWN **OPTOWN** ; MWS410MI/LstAdr For Delivery: CIADDR.OATOWN OCUSAD.OPTOWN.; MWS410MI/LstAdr M3EDIShipment/ShipmentHeader/ShipToParty/Location/Address/CountrySubDivisionCode For Shipment: The field indicates an area, province or state within a country CIADDR OCUSAD.OAECAR OPECAR; MWS410MI/LstAdr For Delivery: CIADDR.OAECAR

OCUSAD.OPECAR.; MWS410MI/LstAdr

@listID

For Delivery:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

M3EDIShipment/ShipmentHeader/ShipToParty/Location/Address/CountryCode

For Shipment: For Shipment:

CIADDR The field indicates a country.

OCUSAD.OACSCD

OPCSCD; MWS410MI/LstAdr For Delivery: The field indicates a country.***

For Delivery:

OCUSAD.OPCSCD.; MWS410MI/LstAdr

@listID

.; MRS001MI/GetFieldInfo

For Shipment: Set to 'Countries'.

For Delivery:

The field indicates the list ID

M3EDIShipment/ShipmentHeader/ShipToParty/Location/Address/PostalCode

For Shipment: For Shipment:

CIADDR The field indicates a postal code.

OCUSAD

For Delivery:

.OAPONO OPPONO; / The field indicates a postal code for a specific address. ****

For Delivery: CIADDR.OAPONO

OCUSAD.OPPONO.;

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/ID

For Delivery: For Delivery:

MHDISH.OQADVI; MWS410MI/GetHead The field indicates the Ship-Via address ID. This is the address the

transport is shipped through before it arrives at the final address.

@accountingEntity

For Delivery:

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/Address/AddressLine

For Delivery: For Delivery:

CISHVI.ILADR1

ILADR2

The field indicates the address lines of the Ship-Via address.

ILADR3

ILADR4: MWS410MI/GetAdr

@sequence

For Delivery:

Auto generated sequence number for the address line.

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/Address/CityName

For Delivery:

For Delivery:

The field indicates the city name of the Ship-Via address. CISHVI.ILTOWN; MWS410MI/GetAdr

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/Address/CountrySubDivisionCode For Delivery:

CISHVI.ILECAR; MWS410MI/GetAdr The field indicates the state in the Ship-Via address.

@listID

For Delivery:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/Address/CountryCode

For Delivery: For Delivery:

CISHVI.ILCSCD: MWS410MI/GetAdr The field indicates the country code in the Ship-Via address.

@listID

For Delivery: Set to 'Countries'.

M3EDIShipment/ShipmentHeader/ShipToParty/Location/LogisticsLocation/Address/PostalCode

For Delivery: For Delivery:

CISHVI.ILPONO; MWS410MI/GetAdr The field indicates the postal code in the Ship-Via address.

M3EDIShipment/ShipmentHeader/RequiredDeliveryDateTime

For Delivery:

For Delivery: OOHEAD.ÓARLDZ The fields indicates the date and time when the customer wants the

OOHEAD.OARHDZ.; OIS100MI/GetOrderHead delivery to arrive at the final destination.

This is displayed only if Reference order category (RORC) is 3

concatenation of planned departure date (RDDT) <8> + planned

(Customer order)

departure time (RDTM) <4>.

M3EDIShipment/ShipmentHeader/ScheduledShipDateTime

For Shipment: For Shipment: DCONSI.DADSDT The field indicates the planned route departure date and time. It is a

DCONSI.DADSHM DCONSI.DARDDT

DCONSI.DARDTM.; DRS100MI/GetShipment

If planned route departure date (RDDT) is blank, departure date (DSDT) and time (DSHM) are displayed in this element. For Delivery:

MHDISH.OQDSDT

OQDSHM; MWS410MI/GetHead For Delivery: The field indicates the actual ship date. It is updated at stock issue.

M3EDIShipment/ShipmentHeader/PlannedDeliveryDateTime

OQDTHM; MWS410MI/GetHead

For Delivery: For Delivery

MHDISH.OQDTDT The field indicates the Requested Delivery Date and Time

M3EDIShipment/ShipmentHeader/PriorityCode

For Delivery: For Delivery:

MHDISH.OQPRIO; MWS410MI/GetHead The field indicates the priority of the delivery.

M3EDIShipment/ShipmentHeader/DestinationCountryCode

For Shipment: For Shipment:

MHDISH.; MWS410MI/GetHead The field indicates the Destination Country Code.

For Delivery

For Delivery: MHDISH.OQCSCD; MWS410MI/GetHead The field indicates the country.

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.

@listID

For Delivery:

; MRS001Mi/GetFieldInfo The field indicates the list ID.

M3EDIShipment/ShipmentHeader/TransportationTerm/IncotermsCode

For Shipment: For Shipment:

MHDISH.; MWS410MI/GetHead The field indicates the Delivery Terms.

For Delivery: For Delivery:

MHDISH.MQTEDL; MWS410MI/GetHead The field indicates delivery terms, which define when the

responsibility for a delivery is transferred from the supplier to the

customer.

@listID For Delivery:

@schemeName

For Shipment: .; MRS001MI/GetFieldInfo Set to 'Incoterms'.

For Delivery:

The field indicates the list ID.

M3EDIShipment/ShipmentHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/ID

For Shipment: For Shipment:

MIDTLE.; CRS065MI/GetDelyTerm The field indicates the goods responsibility.

M3EDIShipment/ShipmentHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/Description

For Delivery For Delivery:

CSYTAB.CTPARM; CRS065MI/GetDelyTerm The field indicates when the liability for a delivery is transferred from

the supplier to the buyer.

M3EDIShipment/ShipmentHeader/TrackingID

DDOCUX.DBNBOL.; MWS410MI/GetHead

For Shipment: For Shipment:

DCONSI.; DRS100MI/GetShipment The field indicates transport identity.

For Delivery: For Delivery:

MHDISH.OQERTN -The field indicates the external identification, or the forwarder's MDDADV.OVE0BH identification, of a delivery note, bill of lading, or package. You can

use this number to track deliveries or packages using the forwarder's

ID instead of the M3 ID.

-The field indicates the trailer registration number if attribute

schemeName is set to 'TrailerRegistrationNumber'.

-The field indicates the bill of lading if attribute schemeName is set to

'BillOfLading'.

For Delivery:

Set to 'TrailerRegistrationNumber' if element TrackingID refers to

trailer registration number.

Set to 'BillOfLading' if element TrackingID refers to bill of lading.

M3EDIShipment/ShipmentHeader/UserArea

MHDISH/CPAALI.CKPAAL; MWS410MI/CRS886MI/GetHead/CnvPtr

For Delivery:

Translate ISASENDER using call to CRS881.

Then call the API CRS881MI_GetTranslData again with the following

input

TRQF = 0MSTD = M3EDI MVRS = 1

BMSG = Invoice

IBOB = '0'

ELMP = InvoiceHeader

ELMD = ISA EXTP = CONA MVXD= 'ISAReceiver'

MBMD = GetTranslated ISASender

Then fill the userArea with the following values for the Sender

oNameValue = GetTranslated ISASenderi; oNamerValuename = 'EDITradingPartnerID';

oNameValueDescription = 'Customer from OrderHeader';

Then fill the userArea with the following values for the Receiver

oNameValue = GetTranslated ISAReceiver; oNamerValuename = 'EDITradingPartnerID';

oNameValueDescription = 'Customer from OrderHeader';

NameValue@name='Shipment Delivery Print' is set to 'Original' when

it is the first time to print the Shipment Delivery, otherwise, the

element is set to 'Copy'

M3EDIShipment/ShipmentHeader/SpecializedLogisticHeader/Reference/NameValue

For Delivery: For Delivery:

.; CRS620MI/GetBasicData The field indicates the External Supplier Number @name

Set to 'ExternalSupplierNumber'.

M3EDIShipment/ShipmentHeader/CustomerParty/PartyIDs/ID

For Shipment: For Shipment:

OCUSMA.CUNO; MWS410MI/LstAdr The field indicates the consignee.

For Delivery: For Delivery:

OCUSMA.OKCUNO; CRS610MI/GetBasicData The field indicates the customer party ID.

@accountingEntity

For Shipment: For Shipment:

CMNDIV.CCCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO DIVI.

For Delivery:

For Delivery:

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentHeader/CustomerParty/Name

For Shipment: The field indicates the customer name.

OCSUMA.CUNM; MWS410MI/LstAdr

For Delivery: OCSUMA.OKCUNM; CRS610MI/GetBasicData

M3EDIShipment/ShipmentHeader/CustomerParty/Location/Address/AddressLine

For Shipment: The field indicates the address line

OCUSMA.ADR1/ADR2/ADR3/ADR4; MWS410/LstAdr

For Delivery: OCUSMA.ÓKCUA1

OKCUA2 OKCUA3

OKCUA4; CRS610MI/GetBasicData

@sequence

M3EDIShipment/ShipmentHeader/CustomerParty/Location/Address/CityName

For Shipment: The field indicates the city name.

OCUSMA.TOWN; MWS410/LstAdr

For Delivery:

OCUSMA. OKTOWN; CRS610MI/GetBasicData

M3EDIShipment/ShipmentHeader/CustomerParty/Location/Address/CountrySubDivisionCode

For Shipment: The field indicates an area, province or state within a country

OCUSMA.ECAR; MWS410/LstAdr

For Delivery:

OCUSMA.OKECAR; CRS610MI/GetBasicData

@listID

For Delivery:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

The field indicates the address line sequence

M3EDIShipment/ShipmentHeader/CustomerParty/Location/Address/CountryCode

For Shipment: For Shipment:

OCUSMA.CSCD; MWS410/LstAdr This field indicates the CountryCode. CSCD from array ADRT=10. Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1. For Delivery OCUSMA.ÓKCSCD; CRS610MI/GetBasicData

For Delivery:

This field indicates the CountryCode. @listID

> For Delivery: Set to 'Countries'.

M3EDIShipment/ShipmentHeader/CustomerParty/Location/Address/PostalCode

For Shipment: For Shipment:

OCUSMA.PONO; MWS410/LstAdr This field idicates the PostalCode. PONO from array ADRT=10

For Delivery: For Delivery:

OCUSMA.OKPONO; CRS610MI/GetBasicData This field idicates the PostalCode.

M3EDIShipment/ShipmentHeader/SupplierParty/PartyIDs/ID

CMNDIV.DIVI; MWS410MI/GetHead This fields indicates the supplierPartys ID using

CRS881MI GetTranslData.**

@accountingEntity

For Delivery:

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentHeader/SupplierParty/Name

CMNDIV.NAME; MWS410MI/LstAdr For Shipment:

This field indicates the name of the supplier.

For Delivery:

This field indicates the name of the supplier. ADRT = 01 NAME from

MWS410MI LstAdr

M3EDIShipment/ShipmentHeader/SupplierParty/Location/Address/AddressLine

CMNDIV.ADR1/ADR2/ADR3/ADR4; MWS410MI/LstAdr The field indicates the address line

@sequence

The field indicates the address line sequence.

M3EDIShipment/ShipmentHeader/SupplierParty/Location/Address/CityName

CMNDIV.TOWN; MWS410MI/LstAdr The field indicates the city name.

 ${\it M3EDIShipment/ShipmentHeader/SupplierParty/Location/Address/CountrySubDivisionCode}$

CMNDIV.ECAR; MWS410MI/LstAdr

@listID

@listID

The field indicates an area, province or state within a country

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

M3EDIShipment/ShipmentHeader/SupplierParty/Location/Address/CountryCode

CMNDIV.CSCD; MWS410MI/LstAdr Thies Field indicates the country code CSCD from ADRT=01

Generic translation is used to translate CSCD to alpha-2 country code

according to ISO 3166-1.***

For Delivery:

Set to 'Countries'

M3EDIShipment/ShipmentHeader/SupplierParty/Location/Address/PostalCode

CMNDIV.PONO; MWS410MI/LstAdr The field indicates the Postal code in an address retreive from PONO

in array for ADRT=01

M3EDIShipment/ShipmentItem/ItemID/ID

For Shipment: For Shipment:

MFTRNS.MQITNO; MWS410MI/LstItem The field indicates the Item Number.

For Delivery:

For Delivery: MFTRNS.OSITNO; MWS423MI/LstContents

The field indicates the item number within the Shipment.

@accountingEntity

For Shipment: The field indicates the company and division, displayed as

DCONSI.DACONO CONO DIVI.

DCONSI.DADIVI.; /

For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

M3EDIShipment/ShipmentItem/CustomerItemID/ID

For Delivery: For Delivery:

MITPOP.MPPOPN; MMS025MI/LstAlias The field indicates the customer's item ID.

In M3, this is the alias number (POPN) with alias category (ALWT) =

06

@accountingEntity

For Delivery: For Delivery:

MHDISH.OQCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; /

CONO DIVI.

For Delivery:

MOLDIOMPINCIA	
M3EDIShipment/ShipmentItem/UPCID MITPOP.MPPOPN; MMS025MI/LstAlias	Correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods. Alias qualifier = UPC
M3EDIShipment/ShipmentItem/EPCID	<u> </u>
For Shipment: MITPOP.MPPOPN; MMS025MI/LstAlias	For Shipment: The field indicates the item's EAN number.
· · · · · · · · · · · · · · · · · · ·	The field findicates the fleth's EAN fluttiber.
M3EDIShipment/ShipmentItem/GTIN For Delivery: MITPOP.MPPOPN; MMS025MI/LstAlias	For Delivery: The Global Trade Item Number is a 14-digit number which includes various EAN/UCC numbering structures. Alias qualifier = GTIN
@schemeName	For Delivery: The field is set to: 1.) EA08 = for alias with qualifier EA08 2.) EA13 = for alias with qualifier EA13 3.)DU14 = for alias with qualifier DU14
M3EDIShipment/ShipmentItem/Description	e./peri lerande war quanner peri
For Shipment: MFTRNS.MQITDS; MWS410MI/Lstltem	For Shipment: The field indicates the description of the Item.
For Delivery: MITMAS.MMITDS; MWS423MI/LstContents	For Delivery: The field indicates the item description.
M3EDIShipment/ShipmentItem/Classification/Codes/Code	note melocico elo tom docomptoni
For Delivery: OOLINE.OBORST; OIS100MI/GetLine (@listID	For Delivery: The field indicates the customer order line status.
	For Delivery: Set to 'Customer Order Line Status'.
M3EDIShipment/ShipmentItem/Packaging/ID MHDISH.OQETRN; MWS410MI/GetHead	For Shipment: The field indicates the extenal tracking number.
	For Delivery: This indicates the external tracking number
M3EDIShipment/ShipmentItem/OrderQuantity For Delivery: MGLINE/OOLINE.MRTRQTOB/ORQT; MWS411MI/OIS100MI/ GetDeliveryLine/GetLine	For Delivery: The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction. If feature toggle 2244883 is active and RORC= 3 populate with value from OOLINE.ORQT. If feature toggle off, Populate with MWS411_LstContent_TRQT.
@unitCode	IIIII III Lataanan Lata
For Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	For Delivery: This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
M3EDIShipment/ShipmentItem/CustomerPurchaseOrderReference For Delivery:	For Delivery:
OOLINE.OBCUOR; OIS100MI/GetLine	The field indicates the customer purchase order number.
M3EDIShipment/ShipmentItem/ShippedQuantity For Shipment: MFTRNS.MQTRQT; MWS410MI/LstItem	For Shipment: The field indicates the Delivered Quantity.
For Delivery: MFTRNS.OSDLQT; MWS423MI/LstContents	For Delivery: The field indicates the delivered quantity, expressed in the item's basic U/M.
@unitCode For Shipment: MITMAS.MMUNMS; MMS410MI/LstItem	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
For Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	
M3EDIShipment/ShipmentItem/ShippedBaseUOMQuantity For Shipment: MFTRNS.MQDLQT; MWS410MI/LstItem	For Shipment: The field indicates the Delivered Quantity.
For Delivery: MFTRNS.OSDLQT; MWS423MI/LstContents	For Delivery: The field indicates the delivered quantity, expressed in the item's basic U/M.
@unitCode For Shipment: MITMAS.MMUNMS; MMS410MI/LstItem	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

M3EDIShipment MITMAS.MMUNMS: MWS423MI/LstContents M3EDIShipment/ShipmentItem/LoadingWeightMeasure For Delivery: For Delivery: MFTRNS.ÓSNEWE; MWS423MI/LstContents The field indicates the net weight. @unitCode For Delivery: The field indicates the unit code. M3EDIShipment/ShipmentItem/PurchaseOrderReference/DocumentID/ID For Delivery: For Delivery: MFTRNS.OSRIDN; MWS423MI/LstContents The field indicates the purchase order number. This field is displayed only if RORC=2. @accountingEntity For Delivery: For Delivery: MHDISH.OQCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI.; / CONO_DIVI. @location For Delivery: For Delivery: MGLINE.MRWHLO; MWS411MI/GetDeliveryLine The field indicates the warehouse ID. M3EDIShipment/ShipmentItem/PurchaseOrderReference/LineNumber For Delivery: For Delivery: MFTRNS.OSRIDL; MWS423MI/LstContents The field indicates the order line number. M3EDIShipment/ShipmentItem/PurchaseOrderReference/SubLineNumber For Delivery: For Delivery: MFTRNS.OSRIDX; MWS423MI/LstContents The field indicates the line suffix. M3EDIShipment/ShipmentItem/SalesOrderReference/DocumentID/ID For Shipment: For Shipment: MHDISH.MQRIDN; MWS410MI/GetHead The field indicates an order number. For Delivery: For Delivery: MFTRNS.OSRIDN; MWS423MI/LstContents The field indicates the sales order number. This field is displayed only if RORC=3. @accountingEntity For Shipment: The field indicates the company and division, displayed as DCONSI.DACONO CONO DIVI. DCONSI.DADIVI.; / For Delivery: MHDISH.OQCONO CMNDIV.CCDIVI.; / @location For Shipment: For Shipment: MHDISH.OQWHLO; MWS410MI/GetHead The field indicates the warehouse. For Delivery: For Delivery: MGLINE.MRWHLO; MWS411MI/GetDeliveryLine The field indicates the warehouse ID. M3EDIShipment/ShipmentItem/SalesOrderReference/LineNumber For Delivery: For Delivery: MFTRNS.OSRIDL; MWS423MI/LstContents The field indicates the order line number M3EDIShipment/ShipmentItem/SalesOrderReference/SubLineNumber For Delivery: For Delivery: MFTRNS.OSRIDX; MWS423MI/LstContents The field indicates the line suffix M3EDIShipment/ShipmentItem/DocumentReference @type For Delivery: For Delivery: MFTRNS.ÓSRORC; MWS423MI/LstContents The field indicates the reference order category. 1 - ProductionOrder 2 - PurchaseOrder 3 - SalesOrder 4 - RequisitionOrder 5 - DistributionOrder 6 - WorkOrder 7 - ServiceOrder 8 - ProjectOrder 9 - ClaimOrder

M3EDIShipment/ShipmentItem/DocumentReference/DocumentID/ID

For Delivery:

MFTRNS.ÓSRIDN

MFTRNS.OSCUOR.; MWS423MI/LstContents

@accountingEntity For Delivery:

MHDISH.OQCONO CMNDIV.CCDIVI

For Delivery:

The field indicates the M3 order number and/or the customer's order

If the document ID refers to customer's order number (CUOR), this

number.

For Delivery:

The field indicates the company and division, displayed as

field is set to CustomerPurchaseOrder.

CONO DIVI.

.; / M3EDIShipment/ShipmentItem/DocumentReference/LineNumber	
For Delivery: MFTRNS.OSRIDL; MWS423MI/LstContents	For Delivery: The field indicates the order line number.
M3EDIShipment/ShipmentItem/DocumentReference/SubLineNumber	The field indicates the order line number.
For Delivery:	For Delivery:
MFTRNS.OSRIDX; MWS423MI/LstContents	The field indicates the line suffix.
M3EDIShipment/ShipmentItem/SerializedLot/ItemQuantity	
For Shipment:	This field indicates the delivered quantity, expressed in the item's
MFTRNS.MQTRQT; MWS410MI/Lstltem	basic U/M.
For Delivery:	
MFTRNS.OSDLQT; MWS423MI/LstContents	
@unitCode	The field indicates the unit is which each item is uppounded in
For Shipment: MITMAS.MMUNMS; MWS410MI/LstItem	The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
For Delivery: MITMAS.MMUNMS; MWS423MI/LstContents	
M3EDIShipment/ShipmentItem/SerializedLot/Lot/Lot/IDs/ID	
For Shipment:	The field indicates the lot number.
MITTRA.MTBANO; MWS070MI/LstTransByOrder	The field findicates the fet fidings.
For Delivery:	
MITTRA.MŤBANO MWS070MI/LstTransByOrder	
or MFTRNS.OSBANO;	
MWS423MI/LstContents.MTBANO; MWS070MI or	
MWS423MI/LstTransByOrder or	
LstContents	
M3EDIShipment/ShipmentItem/SerializedLot/SerialNumber	
For Shipment: MITTRA.MTBANO; MWS070MI/LstTransByOrder	The field indicates the lot number.
For Delivery: MITTRA.MTBANO MWS070MI/LstTransByOrder	
or MFTRNS.OSBANO; MWS423MI/LstContents.; MWS070 or	
MWS423/LstTransByOrder or	
LstContents	
M3EDIShipment/ShipmentItem/SerializedLot/ProductionDate MILOMA.MFDT; MMS235MI/GetItmLot	The field indicates, per lot/serial number, the date the item is manufactured
M3EDIShipment/ShipmentItem/SerializedLot/ExpiryDate	
MILOMA.EXPI; MMS235MI/GetItmLot	The field indicates the last usage date for the current item and lot
M3EDIShipment/ShipmentItem/LineNumber	For Shipment: The field indicates the line number.
	For Delivery: The field indicates the line number
M3EDIShipment/ShipmentItem/WeightMeasure	
For Delivery:	For Delivery:
MFTRNS.OSNEWE; MWS423MI/LstContents @unitCode	The field indicates the net weight.
For Delivery:	For Delivery:
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within company.
M3EDIShipment/ShipmentItem/SpecializedLogisticItem/Reference/Nam OCUSMA.OKCUSU; MWS410MI/GetHead	neValue The field indicates the supplier number at customer. The field is only used as a search key in the customer file.
@name	Cat to IF stamped Counties to the state of t
	Set to 'ExternalSupplierNumber' when Our supplier number at customer (CUSU) field is populated.
M3EDIShipment/ShipmentItem/SpecializedLogisticItem/VIN	tation (0000) hold to populated.
nondrighter to original and tell supportant and control of the support of the sup	For Delivery:

M3EDISnipment	
For Shipment: MHDISH.OQDLIX; DRS100MI/LstByDelivery	For Shipment: The field indicates the delivery number. This unique ID for the delivery is created or updated automatically during order line entry.
For Delivery: MPTRNS.ORSSCC; MWS410MI/GetPackage	For Delivery: The field indicates the serial shipment container code if attribute schemeName is set to 'SSCC'.
@schemeName	For Delivery: Set to 'SSCC' if Tracking ID refers to serial shipment container code.
M3EDIShipment/ShipmentUnit/ContainerID For Delivery: MPTRNS.ORPANR; MWS423MI/LstPackDel	For Delivery: The field indicates the package number.
M3EDIShipment/ShipmentUnit/SealID	The field findicates the package number.
For Shipment:	For Shipment:
DCONSI.DASEAL; DRS100MI/GetShipment	The field indicates the Seal Number.
M3EDIShipment/ShipmentUnit/NetWeightMeasure For Shipment: MHDISH.OQNEW2; MWS410MI/GetHead	For Shipment: The field indicates the total weight of all items entered on the customer order.
For Delivery: MFTRNS.OSNEWE; MWS410MI/GetPackage	The information is based on the respective items' net weight in for outstanding and allocated quantities on the order lines.
	For Delivery: The field indicates the total weight of all items entered on the customer order.
	The information is based on the respective items' net weight in (MMS001/F) for outstanding and allocated quantities on the order lines.
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
M3EDIShipment/ShipmentUnit/GrossWeightMeasure	
For Shipment: MHDISH.OQGRW2; MWS410MI/GetHead	The field indicates the total weight for all items that have been entered on the order.
For Delivery: MFTRNS.OSGRW2; MWS410MI/GetPackage @unitCode	The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity
CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
M3EDIShipment/ShipmentUnit/TotalVolumeMeasure For Shipment: MHDISH.OQVM32; MWS410MI/GetHead	The field indicates the volume for each item in the item file or for undelivered order lines for a customer order.
For Delivery: MPTRNS.ORVOL3; MWS410MI/GetPackage	The latter is calculated automatically by accumulating the remaining quantity of each order line with the volume of the item.
@unitCode CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For Shipment: The field indicates the general unit of measure for all volumes within a company.
	For Delivery: The field indicates the unit code.
M3EDIShipment/ShipmentUnit/ShippingMaterial/ID	
For Delivery: MPTRNS.ORPACT; MWS410MI/GetPackage @accountingEntity	For Delivery: The field indicates the packaging.
	For Delivery: The field indicates the company and division, displayed as CONO_DIVI.
M3EDIShipment/ShipmentUnit/ShipmentUnitContainer @type For Delivery:	For Delivery:
MPTRNS.ORPACT; MWS410MI/GetPackage	The field indicates the packaging of the inner package.
M3EDIShipment/ShipmentUnit/ShipmentUnitContainer/ContainerID For Shipment: MPTRNS.ORPANR; MWS410MI/LstPackages	For Shipment: This field indicates the identity of a package. A package can be
For Delivery: MPTRNS.ORPANR; MWS423MI/LstPackDel	packed in another package. For Delivery: The field indicates the inner package number.
M3EDIShipment/ShipmentUnit/ShipmentUnitContainer/ShippingMate	The field indicates the inner package number.
For Shipment:	·

MPTRNS.ORPACT: MWS410MI/LstPackages For Shipment:

@accountingEntity

For Shipment: CMNDIV.CCCONO CMNDIV.CCDIVI.; /

For Shipment:

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/ItemID/ID

MFTRNS.OSITNO; MWS423MI/LstContents

For Shipment:

The field indicates the item number which is a unique ID for an individual item. Items are entered and maintained in Item Master. Item number can consist up to 15 alphanumeric characters.

For Delivery:

The field indicates the item number.

The field indicates the ID of the packaging

@accountingEntity For Shipment: DCONSI.DACONO DCONSI.DADIVI.; /

The field indicates the company and division, displayed as CONO DIVI.

For Delivery:

MHDISH.OQCONO CMNDIV.CCDIVI.; /

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/UPCID

For Delivery MITPOP.MPPOPN; MMS025MI/LstAlias For Delivery: Correspond to GTIN-12 and UCC-12. This is a 12-digit number used

for identifying goods. Alias qualifier = UPC

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/GTIN

For Delivery:

@schemeName

MITPOP.MPPOPN; MMS025MI/LstAlias

For Delivery:

The Global Trade Item Number is a 14-digit number which includes

various EAN/UCC numbering structures.

Alias qualifier = GTIN

For Delivery:

The field is set to:

1.) EA08 = for alias with qualifier EA08 2.) EA13 = for alias with qualifier EA13 3.)DU14 = for alias with qualifier DU14

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/Classification/Codes/Code

For Delivery

OOLINE.OBORST; OIS100MI/GetLine

@listID

For Delivery:

The field indicates the customer order line status.

For Delivery:

Set to 'Customer Order Line Status'.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/ShippedQuantity

MFTRNS.OSDLQT; MWS423MI/LstContents

For Shipment:

The field indicates the delivered quantity, expressed in the item's

basic U/M.

For Delivery:

The field indicates quantity delivered expressed in an alternate U/M.

@unitCode For Shipment:

MFTRNS.OSUNMS; MWS423MI/LstContents

The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

For Delivery:

MITMAS.MMUNMS; MWS423MI/LstContents

MFTRNS.OSNEWE; MWS423MI/LstContents

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/EstimatedWeightMeasure

The field indicates the net weight

For Delivery:

For Shipment:

The field indicates the total weight of all items entered on the

customer order.

The information is based on the respective items' net weight in (MMS001/F) for outstanding and allocated quantities on the order

lines

@unitCode

For Shipment:

MFTRNS.OSWEUN; MWS423MI/LstContents

For Shipment:

The field indicates the general unit of measure for all weights within a

company.

For Delivery:

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

For Delivery:

The field indicates the unit code

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/LoadingWeightMeasure

For Shipment:

MPTRNS.ORGRWE: MWS423MI/LstContents For Shipment:

For Delivery:

MFTRNS.ÓSGRWE; MWS423MI/LstContents The basis for this calculation is the gross weight of each item in the

item file multiplied by the quantity

The field indicates the total weight of the item.

For Delivery:

The field indicates the total weight for all items that have been

entered on the order.

The basis for this calculation is the gross weight of each item in the

item file multiplied by the quantity

@unitCode

CSYTAB.CTPARM: CRS175MI/GetItemFreeFlds

For Shipment:

The field indicates the general unit of measure for all weights within a

company.

For Delivery:

The field indicates the unit code.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID

For Delivery For Delivery:

MFTRNS.OSRIDN; MWS423MI/LstContents The field indicates the purchase order number. This is displayed only

if RORC=2.

@accountingEntity

For Delivery:

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

CONO DIVI.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

For Delivery: For Delivery:

MFTRNS.ÓSRIDL; MWS423MI/LstContents The field indicates the purchase order line number.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/SubLineNumber

For Delivery: For Delivery:

MFTRNS.OSRIDL; MWS423MI/LstContents The field indicates the purchase order subline number.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID

For Shipment: For Shipment:

MHDISH.OQRIDN: MWS423MI/LstContents The field indicates an order number where item is connected to.

For Delivery: For Delivery:

MITALO.MQRIDN; MWS423MI/LstContents The field indicates the sales order number. This is displayed only if

RORC=3.

CONO DIVI.

@accountingEntity For Shipment:

DCONSI.DACONO

DCONSI.DADIVI.; /

For Delivery:

MHDISH.OQCONO CMNDIV.CCDIVI.; /

@location

For Shipment: For Shipment:

MHDISH.OQWHLO; MWS410MI/GetHead The field indicates the warehouse

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/LineNumber

For Shipment: For Shipment:

MHDISH.OQRIDL; MWS423MI/LstContents The field indicates an order line where item is connected to.

For Delivery: For Delivery:

MITALO.MQRIDL; MWS423MI/LstContents The field indicates the order line number.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber

For Shipment: For Shipment:

MHDISH.OQRIDX; MWS423MI/LstContents The field indicates an order line suffix where item is connected to.

For Delivery For Delivery:

MITALO.MQRIDX; MWS423MI/LstContents The field indicates the line suffix.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference @type

For Delivery:

For Delivery:

MFTRNS.OSRORC: MWS423MI/LstContents The field indicates the reference order category.

1 - ProductionOrder

2 - PurchaseOrder

3 - SalesOrder

4 - RequisitionOrder

5 - DistributionOrder

6 - WorkOrder

7 - ServiceOrder 8 - ProjectOrder

9 - ClaimOrder

If the document ID refers to customer's order number (CUOR), this field is set to CustomerPurchaseOrder. M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID For Delivery: For Delivery: MFTRNS. ÓSRIDN The field indicates the M3 order number and/or the customer's order MFTRNS.OSCUOR.; MWS423MI/LstContents number @accountingEntity For Delivery: For Delivery: MHDISH.OQCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI CONO DIVI. M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/LineNumber For Delivery: For Delivery: MFTRNS.OSRIDL; MWS423MI/LstContents The field indicates the order line number. M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/SubLineNumber For Delivery: For Delivery: MFTRNS.OSRIDX; MWS423MI/LstContents The field indicates the line suffix. M3EDIShipment/ShipmentUnit/ShipmentUnitItem/UserArea For Shipment: For Shipment: If translated take from MWS410MI GetHEAD CONA > MHDISH/CPAALI.CKPAAL; MWS410MI/CRS886MI/GetHead/CnvPtr CRS886MI CnvPtr Keyfield PCTG = 11 and PAAC = 11 oNameValue For Delivery: = iUserArea CONA; MFTRNS. ÓSPANR; MWS423MI/LstContents oNameValue = iCONA; oNamerValuename = 'EDITradingPartnerID'; oNameValueDescription = 'Customer from OrderHeader'; if NO translation found take from MWS410MI GetHead CONA oNameValue = iCONA; oNamerValuename = 'EDITradingPartnerID'; oNameValueDescription = 'Customer from OrderHeader'; Property/NameValue set to package number Property/NameValue@Name set to 'Internal package number' Property/NameValue@type set to blank Property/NameValue@listID set to blank Property/Description set to 'Package number within delivery' M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/Lot/LotIDs/ID For Shipment: The field indicates the lot number. MITTRA.MTBANO; MWS070MI/LstTransByOrder For Delivery MFTRNS.OSBANO; MWS423MI/LstContents M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/Lot/CountryOfOriginCode For Delivery: For Delivery: The field indicates the Country code (CSCD) CIADDR.OACSCD; MMS005MI/GetWarehouse M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/ProductionDate MILOMA.MFDT; MMS235MI/GetItmLot The field indicates, per lot/serial number, the date the item is manufactured M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/ExpiryDate MILOMA.EXPI; MMS235MI/GetItmLot The field indicates the last usage date for the current item and lot M3EDIShipment/ShipmentUnit/ShipmentUnit/tem/SerializedLot/SpecializedLogisticsItem/ManufacturingReferenceNumber For Delivery: For Delivery: MILOMA.RORN; MMS235MI/GetItmLot The field indicated the reference order number M3EDIShipment/ShipmentUnit/UserArea For Delivery: For Delivery: MHDISH.OQCONA The fields indicate the following: MPTRNS.ORPAII .: MWS410MI 1.) Consignee Attribute name is set to 'EDITradingPartnerID'. MWS410MI/GetHead Description is set to 'Customer from OrderHeader'. GetPackage 2.) Payment Method Attribute name is set to 'ShippingMethodofPayment'. Attribute type is set to 'StringType'. Description is set to 'Shipping Method of Payment'. 3.) Included in Package Attribute name is set to 'IncludedInPackageNumber'.

M3EDIShipment/ShipmentUnit/SpecializedLogisticUnit/Reference/NameValue

@name

The field indicates the supplier number at customer. The field is only used as a search key in the customer file.

Attribute type is set to 'StringType'.

Description is set to ' Package where the current package is packed'.

OCUSMA.OKCUSU; MWS410MI/GetHead

For Shipment: Set to 'ExternalSupplierNumber' when Our supplier number at customer (CUSU) field is populated.

For Delivery: Set to 'ExternalTrackingNumber'.

PayFromPartyMaster

PayFromPartyMaster/PartyIDs/ID OCUSMA.OKCUNO; CRS610MI/GetBasicData	This field indicates the customer number.
@accountingEntity OCUSMA.OKCONO	The field indicates the accounting entity.
OCUSMA.OKDIVI.; /	If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed a
@variationID	Company and Division (CONO_DIVI). The field indicates the sequence number that identifies the number of times that this BOD has been published.
@lid .; /	The field indicates the logical ID of the system that is SOR for this noun instance.
PayFromPartyMaster/PartyIDs/DisplayID OCUSMA.OKCUNO; CRS610MI/GetBasicData	This field indicates the customer number.
PayFromPartyMaster/PartyIDs/TaxID OCUSMA.OKVTCD; CRS610MI/GetFinancial @schemeAgencyName	The field indicates the VAT Code to use for the customer.
PayFromPartyMaster/PartyIDs/BICID XRUBAN.BKXBIK: CRRU04MI/GetBankRU	The field indicates the name of the entity that created the ID. If CSVN = RU, display BIK code.
PayFromPartyMaster/LastModificationPerson/IDs/ID OCUSMA.OKCHID; /	The field indicates the ID of the person that entered/changed the recored.
@accountingEntity OCUSMA.OKCONO	The field indicates the accounting entity.
OCUSMA.OKDIVI.; /	If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed a Company and Division (CONO DIVI).
PayFromPartyMaster/Name OCUSMA.OKCUNM ; CRS610MI /GetBasicData	The field indicates the customer name.
PayFromPartyMaster/Location/Address @type	Set to 'text'.
PayFromPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the customer's contact person.
PayFromPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4. ; CRS610MI/GetBasicData	The field indicates the address lines for the customer address.
@sequence	The field indicates the Address Line sequence. E.g Sequence = '1'
PayFromPartyMaster/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the city name.
PayFromPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/GetBasicData @listID	The field indicates an area, province or state within a country.
;,1	The field indicates the country subdivision code listID. Set to 'Canadian Provinces' if the country is Canada. Set to 'France - Departements' if the country is France. Set to 'US States' if the country is United States. Set to 'SubDivisions - <country code="">'. E.g 'SubDivisions - PH' if the country is not US, CA or FR. Set to 'SubDivisions'. If Country is not given.</country>
PayFromPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/GetBasicData @listID	The field indicates the country code.
:; <i>I</i>	Set to 'Countries'.
PayFromPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates the postal code.
PayFromPartyMaster/Location/Address/Preference/Indicator .; / PayFromPartyMaster/Communication	Set to 'true'.
PayFromPartyMaster/Communication @preferredIndicator	Set to 'false'.
PayFromPartyMaster/Communication/ChannelCode	550 to 10100 .

PayFromPartyMaster Telephone number 1 to 'Phone' Telephone number 2 to 'Phone' Facsimile number to Fax E-Mail address to 'EMail' @listID Set to 'Communication Channels' PayFromPartyMaster/Communication/UseCode The field indicates the code identifying usage of the contact point. Telephone number 1 to 'Office' Telephone number 2 to 'Office' Facsimile number to 'Fax' E-Mail address to 'Office' @listID Set to 'Communication Use Codes' PayFromPartyMaster/Communication/DialNumber The field indicates the telephone or facsimile number of the contact. PayFromPartyMaster/Communication/URI The field indicates an e-mail address for the contact PayFromPartyMaster/Communication/Preference/Indicator Set to 'false' PayFromPartyMaster/Contact/ID @accountingEntity OCUSMA OKCONO The field indicates the accounting entity. OCUSMA.OKDIVI.; / If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). PayFromPartyMaster/PaymentTermID OCUSMA.OKTEPY The field indicates the payment term. CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo PayFromPartyMaster/PaymentTermCode OCUSMA.OKTEPY The field indicates the payment term. CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo @listID Set to 'Payment Term'. PayFromPartyMaster/PaymentMethodCode OCUSMA.OKPYCD; CRS610MI/GetFinancial The field indicates the AR payment method. The payment method code is translated in CRS881 (e.g. Cash, Cheque). If no translation exist in CRS881, the following translation is followed based on the payment class: Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1. Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5. Set to 'Factoring' if payment class (PYCL) is 6. PayFromPartyMaster/FinancialParty/Contact/Communication/DialNumber OCUSMA. OKPHNO If CSVN = RU, display Telephone number 1 (PHNO) and Telephone OCUSMA.OKPHN2. number 2 (PHN2). CRS610MI/GetBasicData PayFromPartyMaster/FinancialParty/FinancialAccount/BBANID CBANAC.CCFIAN; CRS692MI/LstByAccHolder If CSVN = RU, display Financial Institution. Get the highest Bank Priority (CBPY) PayFromPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData The field indicates the status of the customer. If M3 status is 10, set element to 'Pending'. If M3 status is 20, set element to 'Open'. If M3 status is 90, set element to 'Closed' PayFromPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP The field indicates the Classification. CRS610MI/GetBasicData 1) Customer Types 2) OCUSMA.OKTEDL The field indicates the type of customer. Set attribute listID to "Customer Types'. CCUDIV OKTEDI CRS610MI/GetOrderInfo 3) OCUSMA.OKSDST The field indicates delivery terms, which indicate when the

Infor May 26, 2023 434

customer.

Set attribute listID to "Incoterms'.

responsibility for the transport is transferred from supplier to

CRS610MI/GetOrderInfo

.; /

PayFromPartyMaster

@listID

@sequence

.; /

PayFromPartyMaster/BillToParty/PartyIDs/ID

OCUSMA.OKPYNO CCUDIV.OKPYNO: CRS610M/GetOrderInfo

OCUSMA.OKINRC CCUDIV.OKINRC; CRS610MI/GetFinancial.; CRS610MI CRS610MI BODCSSMI/GetFinancial GetOrderInfo LstBillToParty

@accountingEntity OCUSMA.OKCONO OCUSMA.OKDIVI.; /

PayFromPartyMaster/BillToParty/Name OCUSMA.OKCUNM; BODCSSMI/LstBillToParty 3) District

The field indicates the district the customer or payer belongs to.

Set attribute listID to 'District'.

The field indicates the sequence number for the ordering of elements within

a document.

E.g Sequence = '1'

The field indicates the Classification code listID.

If Customer type has value, set listID to 'Customer Types'. If Delivery terms has value, set listID to 'Incoterms'.

If District field has value, set listID to 'District'.

The field indicates a list of customer records from M3 BE that is the

invoice recipient.

The field indicates the accounting entity.

If BillToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

The field indicates the name.

May 26, 2023 435

- ayabicitanicaction	
PayableTransaction/PayableTransactionHeader/DocumentID/ID FPLEDG.EPYEA4, EPJRNO, EPJSNO; -/-	The field indicates concatenated fields Year (YEA4, 4 digits), Journal number (JRNO, 7 digits) and Journal sequence number (JSNO, 7 digits) for the Invoice (TRCD = 40) or the Payment or Adjustement (TRCD = 50) transactions from the event data.
O	Value populated will have a fixed length of 18 digits (4+7+7) with JRNO and JSNO padded with zeros (2019/1/1: Document ID/ID = 201900000010000001).
<pre>@accountingEntity FPLEDG.EPCONO, FPLEDG.EPDIVI; @variationID</pre>	The field indicates the company and division, displayed as CONO_DIVI.
@lid	The field indicates the sequence number that identifies the number of times that this BOD has been published.
	The field indicates the logical ID of the system.
PayableTransaction/PayableTransactionHeader/AlternateDocumentID FPLEDX.EPPEXI, FPLEDG.EPSINO; APS251MI, APS200MI/Lstinvinfo, GetInvTotInfo	The field indicates the Supplier invoice number, original invoice number (PEXI) in case of split due date or supplier invoice number (SINO).
@cake.maNama	If APS251MI returns a record from table FPLEDX with info category (SEXN) = 416, use additional information (PEXI) = Original invoice number, else use Supplier invoice number (SINO).
@schemeName	Set to 'CommercialInvoice'.
@accountingEntity FPLEDG.EPCONO, FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO DIVI.
PayableTransaction/PayableTransactionHeader/DisplayID FPLEDG.EPSINO ; APS200MI/GetInvoice	The field indicates the Supplier invoice number.
PayableTransaction/PayableTransactionHeader/LastModificationDate FPLEDG.EPLMTS;	e Time The field indicates the date and time the record was last modified.
PayableTransaction/PayableTransactionHeader/LastModificationPers FPLEDG.EPCHID; APS200MI/GetInvTotInfo	
@accountingEntity FPLEDG.EPCONO, FPLEDG.EPDIVI:	The field indicates the company and division, displayed as CONO DIVI.
PayableTransaction/PayableTransactionHeader/DocumentDateTime FPLEDG.EPACDT ; -/-	The field indicates the accounting date (ACDT) from the event data of the invoice (TRCD = 40) or the payment (TRCD = 50).
PayableTransaction/PayableTransactionHeader/Description FPLEDG.EPTDSC; APS200MI/GetInvoice	The field indicates the description of the transaction based on the Transaction code (TRCD) from the event data with Transaction description added if available (separator 'blank' / 'blank' added between): - If TRCD = 40: Set to 'Supplier invoices - AP' / Value of TDSC if not blank - If TRCD = 50: Set to 'Payments - AP' / Value of TDSC if not blank
PayableTransaction/PayableTransactionHeader/Status/Code FPLEDG.EPPCUA, EPCUAM, EPIVTP, EPRECO, EPPYST; APS200MI/GetInvTotInfo / GetInvoice	The field indicates the status of the payable transaction: - Set to 'Paid': Reconciliation code (RECO) = 9 and Invoice amount (CUAM) != 0 or Reconciliation code (RECO) = 9 and Invoice amount (CUAM) = 0 Set to 'PartialPaid': Reconciliation code (RECO) != 9 and Paid amount (PCUA) != 0 and < Invoice amount (CUAM) Set to 'UnappliedCash': Reconciliation code (RECO) != 9 and Invoice type (IVTP) = AP (on account payment) Set to 'Applied': Reconciliation code (RECO) = 9 and Invoice type (IVTP) = AP (on account payment) Set to 'Void': Reconciliation code (RECO) = 9 and Payment status (PYST) = 4 (reversed/cancelled) Set to 'Open': For all other conditions.
PayableTransaction/PayableTransactionHeader/Status/EffectiveDateTransactionHeader/Status/EffectiveDateTrans; APS200MI/GetInvTotInfo / LstInvoiceTrans	·

PayableTransaction APS200MI.GetInvTotInfo. - If Status/Code = 'Open' or 'Void': Set to Invoice date (IVDT) from APS200MI.GetInvTotInfo. PayableTransaction/PayableTransactionHeader/Status/ReasonCode FPLEDG.EPAPRV; APS200MI/GetInvoice The field indicates the reason code for status 'Open'. Set to 'Unapproved' if APRV =0. Set to 'Approved' if APRV =1. PayableTransaction/PayableTransactionHeader/SupplierParty/PartyIDs/ID FPLEDG.EPSUNO The field indicates the supplier. ; APS200MI/GetInvoice @accountingEntity FPLEDG.EPCONO, The field indicates the accounting entity. FPLEDG.EPDIVI; If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). PayableTransaction/PayableTransactionHeader/SupplierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData The field indicates the supplier name. PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address The field indicates the address type. Set to 'text'. PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/AddressLine CIDADR.SAADR1, The field indicates the address lines using address type 01-Postal CIDADR.SAADR2, address CIDADR.SAADR3, CIDADR.SAADR4; CRS620MI/LstAddresses @sequence The field indicates the address line sequence number. PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses The field indicates the city using address type 01-Postal address. PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses The field indicates the country subdivision code using address type 01-Postal address. @listID The field indicates the country subdivision code listID. Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified. PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses The field indicates the country code using address type 01-Postal address. @listID The field indicates the country code list ID. Set to 'Countries' PayableTransaction/PayableTransactionHeader/SupplierParty/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses The field indicates the postal code using address type 01-Postal address PayableTransaction/PayableTransactionHeader/RemitToParty/PartyIDs/ID FPLEDG.EPSPYN The field indicates the payee. ; APS200MI/GetInvoice @accountingEntity FPLEDG. EPCONO. The field indicates the accounting entity. If RemitToPartyMaster is enabled in BOD Processor Master AE tab, FPLEDG.EPDIVI; this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). PayableTransaction/PayableTransactionHeader/RemitToParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData The field indicates the payee name. Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO) PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address The field indicates the address type. Set to 'text'.

$\label{lem:payable} \textit{PayableTransaction} \textit{Header/RemitToParty/Location/Address/AddressLine} \\ \textbf{PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/AddressLine} \\ \textbf{PayableTransaction} \\ \textbf{Payable$

CIDADR.SAADR1, CIDADR.SAADR2, The field indicates the address line using address type 01-Postal

address.

CIDADR.SAADR3, CIDADR.SAADR4; CRS620MI/LstAddresses

Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO).

@sequence

The field indicates the address line sequence number.

PayableTransaction/PayableTransactionHeader/RemitToParty/Location/Address/CityName

CIDADR.SATOWN; CRS620MI/LstAddresses

	_	4 =
ロハソハト	IAIranca	ATIAN
Pavau	121131154	
. uyun	leTransa	

	The field indicates the city using address type 01-Postal address.
	Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO).
PayableTransaction/PayableTransactionHeader/RemitToParty/Locatio CIDADR.SAECAR; CRS620MI/LstAddresses	n/Address/CountrySubDivisionCode The field indicates the country subdivision code using address type 01-Postal address.
	Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO).
@listID	The field indicates the country subdivision code listID.
	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
PayableTransaction/PayableTransactionHeader/RemitToParty/Locatio CIDADR.SACSCD; CRS620MI/LstAddresses	n/Address/CountryCode The field indicates the country code using address type 01-Postal address.
@listID	Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO).
	The field indicates the country code list ID. Set to 'Countries'.
PayableTransaction/PayableTransactionHeader/RemitToParty/Locatio CIDADR.SAPONO; CRS620MI/LstAddresses	n/Address/PostalCode The field indicates the postal code using address type 01-Postal address.
	Payee (SPYN) from APS200MI.GetInvoice as used as input to CRS620MI.GetAddress - field Supplier number (SUNO).
PayableTransaction/PayableTransactionHeader/PayableStyle FPLEDG.EPCUAM, EPIVTP; APS200MI/GetInvTotInfo / LstInvoiceTrans	invoice (TRCD=40, that is transaction from MI output) and: - If Invoice type (IVTP) = AP: 'CreditMemo' - If Invoice type (IVTP) = 'blank' and amount (CUAM) is positive: 'CreditMemo' - If Invoice type (IVTP) = 'blank', amount (CUAM) is 0.00, Status/ Code='Void' and amount (CUAM) of the first record for the invoice number (*) is positive (reversed credit note): 'CreditMemo' - If Invoice type (IVTP) = LC, SI or SP: 'Miscellaneous' - If Invoice type (IVTP) = CP, PF, PI, PR or RC: 'PrePaid' (Might be changed) For all other Invoice types (IVTP): 'Invoice'
	(*) That is from APS200MI.LstInvoiceTrans with: - CONO/DIVI from event data - SPYN and SUNO from event data or GetInvTotInfo - SINO and INYR from from event data GetInvTotInfo - TRCD set to '40'
PayableTransaction/PayableTransactionHeader/PayableStyleCategory FPLEDG.EPTRCD, EPSLOP; APS200MI/GetInvoice	The field indicates if the transaction is related to an Invoice, Payment or Adjustment: - If Transaction code (TRCD) = 40: 'I' - If Transaction code (TRCD) = 50 and: - Accounting option (SLOP) = 18 or 20-99: 'A' - For all other cases: 'P'
PayableTransaction/PayableTransactionHeader/InvoiceReference/Doc FPLEDG.EPSINO; APS200MI/GetInvTotInfo @accountingEntity	cumentID/ID The field indicates the invoice reference number.
FPLEDG.EPCONO, FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO_DIVI.
PayableTransaction/PayableTransactionHeader/ExtendedAmount FPLEDG.EPCUAM, FGLEDG.EGCUAM; APS200MI/GetInvTotInfo	The field indicates Invoice amount (CUAM - sign reversed) minus Tax amount (TXCU - sign not reversed) in foreign currency. Amount of 0.00 is presented without minus sign.
@currencyID	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
FGLEDG.EGACAM; APS200MI/GetInvTotInfo	The field indicates Invoice amount (ACAM - sign reversed) minus Tax amount (TXAM - sign not reversed) in local currency.
PayableTransaction/PayableTransactionHeader/ExtendedBaseAmoun FGLEDG.EGACAM; APS200MI/GetInvTotInfo	t The field indicates Invoice amount (ACAM - sign reversed) minus Tax amount (TXAM - sign not reversed) in local currency. Amount of 0.00

	is presented without minus sign.
	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID CMNDIV.CCLOCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/TotalAmount FGLEDG.EGCUAM ; APS200MI/GetInvTotInfo	The field indicates the invoice amount (CUAM - sign reversed) in foreign currency. Amount of 0.00 is presented without minus sign.
	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID FGLEDG.EGCUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/TotalBaseAmount FGLEDG.EGACAM; APS200MI/GetInvTotInfo	The field indicates Invoice amount (ACAM - sign reversed) in local currency. Amount of 0.00 is presented without minus sign.
	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID CMNDIV.CCLOCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/BasisAmount FGLEDG.EGCUAM ; APS200MI/GetInvTotInfo	The field indicates the VAT/Tax base amount (TBCU - sign not reversed) in foreign currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 11 and VAT account type (field AT04) = 3 to 9.
@augrapadD	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID FGLEDG.EGCUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/BasisBaseAmou FGLEDG.EGACAM; APS200MI/GetInvTotInfo	Int The field indicates the VAT/Tax base amount (TBAM - sign not reversed) in local currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 41 and VAT account type (field AT04) = 3 to 9.
	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID CMNDIV.CCLOCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/Amount FGLEDG.EGCUAM ; APS200MI/GetInvTotInfo	The field indicates the VAT/Tax amount (TXCU - sign not reversed) if foreign currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 41 and VAT account type (field AT04) = 1 or 2.
	The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.
@currencyID FGLEDG.EGCUCD; APS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
PayableTransaction/PayableTransactionHeader/Tax/BaseAmount FGLEDG.EGACAM; APS200MI/GetInvTotInfo	The field indicates the VAT/Tax amount (TXAM - sign not reversed) i local currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 41 and VAT account type (field AT04) = 1 or 2.

PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountAllowedAmount

@currencyID

CMNDIV.CCLOCD ; APS200MI/GetInvTotInfo

Infor May 26, 2023 439

The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'.

The field indicates the abbreviation for the local currency.

The abbreviation should follow ISO standards.

FPCASH.PCCDAM; APS200MI/GetCashDiscInfo The field indicates the allowed Cash discount (CDA1 - sign reversed) for an invoice in foreign currency using cash discount rate 1. Retrieved using Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) from APS200MI.GetInvTotInfo. The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'. @currencyID FPLEDG.EPCUCD; APS200MI/GetCashDiscInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountAllowedBaseAmount FPCASH.PCCDAM; APS200MI/GetCashDiscInfo The field indicates the allowed Cash discount (LDA1 - sign reversed) for an invoice in local currency (converted from cash discount foreign currency) using cash discount rate 1. Retrieved using Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) from ARS200MI.GetInvTotInfo. The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'. @currencyID CMNDIV.CCLOCD; APS200MI/GetCashDiscInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards. PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenAmount FPLEDG.EPCUAM The field indicated the total cash discount amount taken (CDCU - sign ; APS200MI/GetInvTotInfo not reversed) in foreign currency that is the sum of the transactions in table FSLEDG with Transaction code (field TRCD) = 50 and the Account option (field SLOP) = 18. Note that the Split payment transaction (field SPAR) parameter on the payment FAM function (e.g. AP20) needs to be set to 1-Several pmt trans in AR/AP or else cash discounts cannot be detected. @currencyID FPLEDG.EPCUCD; APS200MI/GetCashDiscInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards. PayableTransaction/PayableTransactionHeader/DiscountStatus/DiscountTakenBaseAmount FGLEDG.EGACAM The field indicated the total cash discount amount taken (CDAM -; APS200MI/GetInvTotInfo sign not reversed) in local currency that is the sum of the transactions in table FSLEDG with Transaction code (field TRCD) = 50 and the Account option (field SLOP) = 18. Note that the Split payment transaction (field SPAR) parameter on the payment FAM function (e.g. AP20) needs to be set to 1-Several pmt trans in AR/AP or else cash discounts cannot be detected. @currencyID CMNDIV.CCLOCD; APS200MI/GetCashDiscInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/PayableAmount FPLEDG.EGCUAM The field indicates the Outstanding amount (OCUA - sign not ; APS200MI/GetInvTotInfo reversed) in foreign currency. The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'. @currencyID FPLEDG.EPCUCD; APS200MI/GetInvTotInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/PayableBaseAmount FGLEDG.EGACAM The field indicates the Outstanding amount (OAMT - sign not : APS200MI/GetInvTotInfo reversed) in local currency. The amount is set to 0.00 if transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and Status/Code = 'Void'. @currencyID CMNDIV.CCLOCD; APS200MI/GetInvTotInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards. PayableTransaction/PayableTransactionHeader/PaidAmount FPLEDG.EPCUAM The field indicates the paid amount (sign not reversed) in foreign ; APS200MI/GetInvTotInfo currency calculated as: - Paid amount (PCUA) minus

; APS200MI/GetCashDiscInfo

@currencyID

- Write-Off (WRCU) @currencyID FPLEDG.EPCUCD; APS200MI/GetInvTotInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/PaidBaseAmount FGLEDG.EGACAM The field indicates the paid amount (sign not reversed) in local ; APS200MI/GetInvTotInfo currency calculated as: - Paid amount (PAMT) minus - Cash discount taken (CDAM) minus - Write-Off (WRAM) @currencyID The field indicates the abbreviation for the local currency. CMNDIV.CCLOCD; APS200MI/GetInvTotInfo The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/PaymentMethodCode CSYTAB CTPARM The field indicates the payment class of the payment method from the ; CRS175MI/GetGeneralCode invoice (TRCD=40) or payment (TRCD=50) using APS200MI.GetInvoice. First Payment method AP is read (STKY = PYME), then the payment type connected to the method is read. Set the following if Payment class (PYCL) in payment type is: - 0: Set to 'Cash' - 1: Set to 'Cheque' - 3: Set to 'CreditCard' if Credit card (CRCD) = 1 or to 'ElectronicFundsTransfer' if CRCD != 1). - 4: Set to 'BankDraft - 5: Set to 'DirectDebit' Everything else is set to 'Cash'. PayableTransaction/PayableTransactionHeader/CurrencyExchangeRate/SourceCurrencyCode FPLEDG.EPCUCD; APS200MI/GetInvTotInfo The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/CurrencyExchangeRate/TargetCurrencyCode CMNDIV.CCLOCD; APS200MI/GetInvTotInfo The field indicates the local currency, that is, the basic currency used by the division. The local currency is defined per division. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/CurrencyExchangeRate/RateNumeric FPLEDG.EPARAT; APS200MI/GetInvTotInfo The field indicates the exchange rate for the chosen currency. The rate may be entered with up to six decimal places. The result, however, will be displayed with two decimal places PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/ID FPLEDG.EPTEPY; CRS175MI/GetGeneralCode The field indicates the payment term. FPLEDG.EPCONO, The field indicates the company and division, displayed as FPLEDG.EPDIVI; CONO DIVI. PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCode The field indicates the payment term description (position 1-72 characters of field PARM) of the payment term (TEPY) PayableTransaction/PayableTransactionHeader/PaymentTerm/Term/DueDateTime FPLEDG.EPDUDT The field indicates the date the invoice is due for payment according APS200MI/GetInvTotInfo to payment term. PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/ID FPLEDG.EPTECD; APS200MI/GetInvTotInfo The field indicates the cash discount term (TECD), created per Cash discount term (TECD) and level (1-3) of discount percentage used. Example: (TECD, '-' + level). PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCode The field indicates the description (position 1-72 of field PARM) of the cash discount term (TECD) PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/EffectiveDateTime FPCASH.PCCDT1, PCCDT2, PCCDT3; APS200MI/GetCashDiscInfo The field indicates the cash discount date. PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/Amount FPCASH.PCCDAM The field indicates the cash discount (CDA1-CDA3 - sign reversed) -; APS200MI/GetCashDiscInfo foreign currency. @currencyID FGLEDG.EGCUCD; APS200MI/GetCashDiscInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards PayableTransaction/PayableTransactionHeader/PaymentTerm/Discount/BaseAmount FPCASH.PCCDAM The field indicates the cash discount (LDA1-LDA3 - sign reversed) -

- Cash discount taken (CDCU) minus

Infor May 26, 2023 44

local currency (converted from Cash discount - foreign currency)

CMNDIV.CCLOCD: APS200MI/GetCashDiscInfo

The field indicates the abbreviation for the local currency.

The abbreviation should follow ISO standards.

PayableTransaction/PayableTransactionHeader/UserArea

FPLEDG.EPPYME FPLEDG.EPTRCD FPLEDG.EPSLOP FPLEDG.EPCUAM FPLEDG.EPCUCD

FGLEDG.EGACAM CMNDIV.CCLOCD .-; APS200MI/GetInvoice / GetInvTotInfo

The field indicates specific values required by an integration:
1) Payment method (PYME) of the Invoice (TRCD=40) or the Payment (TRCD=50):

- Property name = 'Icl.PaymentMethod' and Property type = 'StringType'
- 2) Type of adjustment when element 'PayableStyleCategory' = 'A':
- Property name = 'lcl.AdjustmentType' and Property type = 'StringType'

NameValue set to:

- 'DiscountTaken' when Transaction code (TRCD) = 50 and:
- Accounting option (SLOP) = 18.
- 'WriteOff' when Transaction code (TRCD) = 50 and:
- Accounting option (SLOP) = 20-99.
- 3) Write-off amount in foreign currency (WRCU sign not reversed):
- Property name = 'Icl.WriteOffAmount' and Property type = AmountType and CurrencyID = (CUCD)
- 4) Write-off amount in local currency (WRAM sign not reversed):
- Property name = 'lcl.WriteOffBaseAmount' and Property type = AmountType and CurrencyID = (LOCD)
- 5) Unique ID set to Year (YEA4), Journal number (JRNO 7 digits) and Journal sequence number (JSNO 7 digits). Required for the integration to Local.ly as DocumentID/ID for SupplierInvoice is not unique.
- Property name = 'm3 UniqueID' and Property type = 'IntegerType'

PayableTransaction/PayableTransactionLine/LineNumber

-.-; -/-

Set to 1.

Note: PayableTransactionLine is created for records with transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)) and (TRCD) = 50 (that is PayableStyleCategory = P (Payment) and A (Adjustment)) to output amount of the transaction that triggers the BOD.

PayableTransaction/PayableTransactionLine/UserArea

FGLEDG.EGCUAM FGLEDG.EGCUCD FGLEDG.EGACAM CMNDIV.CCLOCD; GLS200MI / APS200MI/GetVoucherLine / GetInvTotInfo

The field indicates the amount of the invoice, payment or adjustment for the transaction that has triggered the BOD.

- 1) Foreign currency amount (CUAM):
- Property name = Icl.Amount and Property type = Amount ype and CurrencyID = (CUCD)
- 2) Local currency amount (ACAM):
- Property name = 'Icl.BaseAmount' and Property type = AmountType and CurrencyID = (LOCD)

The amount sign is reversed for transactions with transaction code (TRCD) = 40 (that is PayableStyleCategory = I (Invoice)).

GLS200MI.GetVoucherLine via:

- CONO/DIVI from event data
- YEA4 from event data
- VSER/VONO from APS200MI.GetInvoice
- JRNO/JSNO from event data

Person

Person/ID CMNUSR.JUUSID; /	The field indicates the person ID.
@accountingEntity CMNUSR.JUCONO	The field indicates the company and division, displayed as
CMNUSR.JUDIVI.; / @variationID	CONO_DIVI.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
Person/DisplayID CMNUSR.JUUSID; MNS150MI/GetUserData	The field indicates the display id.
Person/Name	The field indicates the name.
Person/Description CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates the description.
Person/LanguageCode CMNUSR.JULANC; MNS150MI/GetUserData	The field indicates the language code.
Person/Communication @preferredIndicator	, ,
gpreren camaroator	Set to "false".
Person/Communication/ChannelCode	Set to "Phone" if telephone number or cellular telephone number. Set to "EMail" if e-mail address.
@listID	Set to "Communication Channels".
Person/Communication/UseCode	Set to "Mobile(Office)" if or cellular telephone number. Set to "Office" if telephone number or e-mail address.
@listID	Set to "Communication Use Codes" .
Person/Communication/DialNumber CEAEMP.EAPHNO CEAEMP.EACAPH.; CRS530MI /LstEmployee	The field indicates the user's telephone number and mobile number.
Person/Communication/URI CEMAIL.CBEMAL; CRS111MI/Get	The field indicates the e-mail address.
Person/Communication/Preference/Sequence	The field indicates the sequence number.
Person/Communication/Preference/Indicator	Set to "false".
Person/PersonnelReference/ID CEAEMP.CBEMNO; CRS530MI/LstEmployee	The field indicates the reference employee number.
@accountingEntity CMNUSR.JUCONO CMNUSR.JUDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Person/PersonnelReference/Name CEAEMP.CBEMNM: CRS530MI/LstEmployee	The field indicates the reference employee name.
Person/SecurityUser/ID	
CMNUSR.JUEUID; MNS150MI/GetUserData Person/Classification	The field indicates the user ID.
@type CMNUSR.JUUSTP; MNS150MI/GetUserData	The field indicates the user type.
Person/Classification/Codes/Code 1) CMNUSR.JUWHLO 2) CMNUSR.JUDCFM 3) CMNUSR.JUDTFM.; MNS150MI /GetUserData	The field indicates the classification code. 1) The field indicates the user's default warehouse in M3. 2) The field indicates the user's decimal format in M3. 3) The field indicates the user's date format in M3.
@sequence	The field indicates the classification code sequence.
@listID	The field indicates the list ID. 1) Set to "Warehouse". 2) Set to "Decimal Format". 3) Set to "Date Format".
Person/Status/Code CMNUSR.JUUSTA.; MSN150MI/GetUserData	The field indicates the user status (USTA). Set to "Pending", if the user status is 10. Set to "Open", if the user status is 20. Set to "Closed", if the user status is 90.

ProductionOrder

The field indicates the production order number. It is a concatenation of Facility (FACI) '-' + Product (PRNO)+ '-' + Manufacturing order number (MFNO). All field are trimmed of spaces and it uses hyphen (-) as delimiter or separator between fields. E.g. A01-ProductNo-400001
The field indicates the company and division, displayed as CONO_DIVI.
The field indicates the manufacturing order number.
The field indicates the product description.
The field indicates the status (WHST) of the Production order. Set to 'Planned' if status is 10. Set to 'Released' if status is 20. Set to 'Active' if status is 40, 50 or 60. Set to 'Stopped' if status is 25,26 45, 46, 55, 56, 65 or 66. Set to 'Completed' if status is 80. Set to 'Closed' if status is 90. Set to 'Deleted' if PMS100 record is deleted.
The field indicates the ordered quantity in the basic unit of measure (U/M).
The field indicates the basic unit of measure.
The field indicates the ordered quantity in alternate unit of measure. The field indicates the alternate unit of measure.
DateTime
The field indicates the actual start date. DateTime The field indicates the actual finish date.
rtDateTime The field indicates the planned start date and time. It is a concatenation of start date (STDT) <10> + start time (MSTI) <4>. E.g. 2018-12-13T05:09:04.903Z
The field indicates the planned finish date and time. It is a concatenation of start date (FIDT) <10> + start time (MFTI) <4>. E.g. 2018-12-13T05:09:04.903Z
The field indicates the Facility. Set attribute name to "Facility".
The field indicates the operation number, which forms a unique ID for an operation when combined with a product number.
//D The field indicates the operation number, which forms a unique ID for an operation when combined with a product number.
/NextID The field indicates the next operations ID.
/Description The field indicates the operation description.
/ConsumedItem/ItemID/ID The field indicates the component number. The field indicates the accounting entity
The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
/ConsumedItem/Description The field indicates the component description.
/O = = = = = = = = // i= = N = = = = = =
/ConsumedItem/LineNumber The field indicates the sequence number.

ProductionOrder If BYPR = 1, set to "By-Product". If BYPR = 2, set to "Co-Product". If BYPR = 3, set to "Product" ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/ConsumedItem/Quantity MWOMAT.VMCNQT; PMS100MI /LstMaterials The field indicates the quantity of an included item used for the Bill of Material or a product. @unitCode MWOMAT.VMPEUN; PMS100MI /LstMaterials The field indicates the unit of measure that is used for an item quantity in a bill of material. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/ConsumedItem/Location Set to "Warehouse". ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/ConsumedItem/Location/ID MWOMAT.VMWHLO; PMS100MI /LstMaterials The field indicates the warehouse. @accountingEntity MWOHED. VHCONO The field indicates the company and division, displayed as MWOHED.VHDIVI.; / CONO DIVI. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/Output/tem/ItemID/ID MWOHED.VHPRNO; / The field indicates the product number. @accountingEntity MWOHED. VHCONO The field indicates the accounting entity. MWOHED.VHDIVI.; / If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Description The field indicates the item description. MWOOPE.VOITDS: PMS100MI/LstOperations If OPNO does not exist, data is retrieved from PMS100MI/Get. MITMAS.MMITDS; PMS100MI/Get.; / ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/Output/tem/Type Set to "Product" ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/LineNumber The field indicates the incremental value starting with 1. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/ProducedBaseUOMQuantity MWOOPE.VOMAQT; The field indicates the manufactured quantity in the basic unit of PMS100MI/LstOperations measure. MWOHED.VHMAQT; If OPNO does not exist, data is retrieved from PMS100MI/Get. PMS100MI/Get.; / @unitCode MITMAS.VHUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/OrderBaseUOMQuantity MWOOPE.VOORQT; The field indicates the ordered quantity in the basic unit of measure. PMS100MI/LstOperations If OPNO does not exist, data is retrieved from PMS100MI/Get. MWOHED.VHORQT; PMS100MI/Get.; / @unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Rejection/RejectBaseUOMQuantity MWOOPE.VOSCQT; PMS100MI/LstOperations The field indicates the total scrapped quantity for the order in the basic unit of measure or in the manufacturing unit of measure. @unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure. ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Costing @rateCode 1) Set to 'Labor' if Actual run time (UMAT) is not blank.

1) MWOOPE.VOUMAT;

PMS100MI/LstOperations

2) MWOOPE VOUPIT;

PMS100MI/GetOperation.; /

@type

2) Set to 'Machine' if Used machine run time (UPIT) is not blank.

Set to 'Actual'.

ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/Costing/CostTime

1) MWOOPE.VOUMAT;

PMS100MI/LstOperations 2) MWOOPE/VOUPIT;

PMS100MI.GetOperation.; /

1) Actual run time

The field indicates the accumulated reported man-hours used to process a piece or lot using the operation.

2) Use Machine run time

The field indicates the accumulated reported machine/process time used to process a piece or lot using the operation.

ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/OutputItem/PlannedRejectQuantity The field indicates the planned scrap quantity. This is calculated

MWOOPE.VOORQT

MWOOPE.VOSCPC.; PDS100MI/LstOperations, GetOperations

@unitCode

MITMAS.MMUNMS; MMS200MI/GetItmBasic

using Order quantity (ORQT) multiplied by Scrap percentage (SCPC).

The field indicates the basic unit of measure.

ProductionOrder/ProductionOrderDetail/BillOfResources/Operations/WorkCenterID

May 26, 2023

ProductionOrder

MWOOPE.VOPLGR; PMS100MI/LstOperations

The field indicates the work center.

ProjectMaster

1 TOJECTINASTEI	
ProjectMaster/ID BPROJS.LAPROJ; / @accountingEntity	The field indicates project number.
	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
ProjectMaster/Description BPROJS.LATX40; POS100MI/LstElement1	The field indicates the description.
ProjectMaster/ProjectManagerPerson/IDs/ID BPROJS.LAMPLE: /	The field indicates the project manager.
ProjectMaster/Status/Code BPROJS.LAELST; POS100MI/LstElement1	The field indicates the status project element (ELST). Set to "Draft" if the status project element is 0 to 9 and 10 to 79. Set to "Closed" if the status project element is 99. Set to "Deleted" if project is deleted.
ProjectMaster/UserArea 1.BPROJS.LAELNO; POS100MI/LstElement1 2.BPROJS.LALEVL; POS100MI/LstElement1	The field indicates additional information that is not captured in OAGIS. The information are defined in UserArea/Property/ NameValue which are determined by different name attributes. This is used to identify the Project Element, Level in Structure, Position, and Personnel ID of the project manager.
3.BPROJS.LAPOSI; POS100MI/LstElement1 4. CEAEMP.EAEMNO; CRS530MI/SelUserID.; /	1) Project The field indicates the project element. Set attribute name to "m3.ProjectElement". 2) Lowest level The field indicates the lowest level. Set attribute name to "m3.ElementLevel". 3) Position number The field indicates the position number. Set attribute name to "m3.ElementPosition".
ProjectMaster/ProjectElement/ID	Employee number The field indicates the employee number. Set attribute name to "PersonnelID".
BPROJS.LAELNO; POS100MI/LstElement1	The field indicates the project element.
ProjectMaster/ProjectElement/Description BPROJS.LATX40; POS100MI/LstElement1	The field indicates the project element description.
ProjectMaster/ProjectElement/Status/Code BPROJS.LAELST; POS100MI/LstElement1	The field indicates the status project element (ELST). Set to "Draft", if the status project element is 0 to 9 and 10 to 79. Set to "Closed", if the status project element is 99.
ProjectMaster/ProjectElement/ParentElement/ID BPROJS.LACIEN; POS100MI/LstElement1	The field indicates the parent element.
ProjectMaster/ProjectElement/ParentElement/UserArea 1.BPROJS.LALEVL; POS100MI/LstElement1 2.BPROJS.LAPOSI; POS100MI/LstElement1.; /	The field indicates additional information that is not captured in OAGIS. The information are defined in UserArea/Property/ NameValue which are determined by different name attributes. This is used to identify the Level in Structure and Position. 1) Lowest level The field indicates the lowest level. Set attribute name "m3.ElementLevel". 2) Position The field indicates the position. Set attribute name "m3.ElementPosition".

Promotion

1 10111011011	
Promotion/IDs/ID OPROMH.FZPIDE; /	The field indicates the sales promotion code.
@accountingEntity OPROMH.FZCONO OPROMH.FZDIVI.; /	The field indicates the accounting entity displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of
@lid	times that the BOD has been published.
	The field indicates the logical ID of the system.
Promotion/DisplayID OPROMH.FZPIDE; /	The field indicates a sales promotion code.
Promotion/LastModificationDateTime OPROMH.FZLMDT; OIS840MI/GetPromHead	The field indicates the last modification date.
Promotion/LastModificationPerson/IDs/ID OPROMH.FZCHID; OIS840MI/GetPromHead	The field indicates the user ID of the person who last modified the record.
@accountingEntity OPROMH.FZCONO OPROMH.FZDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Promotion/Description OPROMH.FZTX40; OIS840MI/GetPromHead	The field indicates the description of the promotion.
Promotion/Status/Code OPROMH.FZPROS; OIS840MI/GetPromHead	The field indicates the status of the promotion. Set to 'Open' if status is 00, 10, or 20. Set to 'Closed' if status is 90. Set to 'Deleted' if the record is no longer existing in M3.
Promotion/Name OPROMH.FZTX15; OIS840MI/GetPromHead	The field indicates the name of the promotion.
Promotion/EffectiveTimePeriod/StartDateTime OPROMH.FZFVDT; OIS840MI/GetPromHead	The field indicates the valid start date of the promotion.
Promotion/EffectiveTimePeriod/EndDateTime OPROMH.FZLVDT; OIS840MI/GetPromHead	The field indicates the valid end date of the promotion.
Promotion/ItemQualification/PromotionItem/ItemID/ID OPROML.FLITNR; OIS840MI/LstPromLine @accountingEntity	The field indicates the item number that is part of the promotion.
OPROMH.FZDIVI.; /	The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Promotion/ItemQualification/EffectiveTimePeriod/StartDateTime OPROML.FLFVDT; OIS840MI/LstPromLine	The field indicates the valid start date of the item promotion.
Promotion/ItemQualification/EffectiveTimePeriod/EndDateTime OPROML.FLLVDT; OIS840MI/LstPromLine	The field indicates the valid end date of the item promotion.
Promotion/CustomerQualification/CustomerParty/PartyIDs/ID OPROMC.FBCUNO; OIS840MI/LstPromCust	The field indicates the customer number that is linked to the promotion.
@accountingEntity OPROMH.FZCONO OPROMH.FZDIVI.; /	The field indicates the accounting entity. If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Promotion/OffInvoice/DiscountAmount OPROML.FLDIAM; OIS840MI/LstPromLine	The field indicates the discount amount offered during the promotion period. The promotion's discount can either be entered as a fixed amount or as a percentage.
@currencyID OPROML.FLCUCD; OIS840MI/LstPromLine	The field indicates the currency of the discount amount.
Promotion/OffInvoice/DiscountPercent OPROML.FLDISP; OIS840MI/LstPromLine	The field indicates the discount percentage to be assigned. If the discount is assigned as an amount, this field is left blank.
Promotion/OffInvoice/Description	Set to 'Discount Percentage' if DiscountPercent is populated.

PulseAlert

PulseAlert/Description	
CMAILB CBMSGT: /	

The field indicates the alert text. The field consists of 2 parts.

- Set to 'M3 BE application message: ', if Hardcoded text.
 The field indicates the Application message from M3 BE.
- The field indicates the M3 BE application messages are categorized in Ming.le and Activity Deck as 'M3BE app msg'.

PulseAlert/DistributionPerson/PersonReference/IDs/ID

CMAILB.CBREC2; /

The field indicate the user id of the application message receiver in M3 BE.

PulseNotification

PulseNotification/Description CMAILB.CBMSGT; /

The field indicates the the 2 parts notification text.

1) Set to 'M3 BE application message: ', if hardcoded text.

2) Application message from M3 BE

PulseNotification/DistributionPerson/PersonReference/IDs/ID CMAILB.CBREC2; /

The field indicates the user id of the application message receiver in $\ensuremath{\mathsf{M3}}$ BE.

Infor May 26, 2023 450

PulseTask

PulseTask/Description	1
CMAILB CBMSGT: /	

The field indicates the alert text. The field consists of 2 parts.

- Set to 'M3 BE application message: ', if Hardcoded text.

 The field indicates the Application message from M3 BE.

The field indicates the M3 BE application messages are categorized in Ming.le and Activity Deck as 'M3BE app msg'.

PulseTask/DistributionPerson/PersonReference/IDs/ID

CMAILB.CBREC2; N/A/

The field indicates the person reference.

PurchaseOrder/PurchaseOrderHeader/DocumentID/ID MPHEAD.IAPUNO: /	The field indicates the purchase order number.
@accountingEntity	·
MPHEAD.IACONO MPHEAD.IADIVI	The field indicates the company and division, displayed as CONO_DIVI.
;/	GONO_BIVI.
@Jocation MPHEAD.IAWHLO; /	The field indicates the warehouse.
@variationID	The field indicates the warehouse.
⊗1:-1	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
PurchaseOrder/PurchaseOrderHeader/DocumentID/RevisionID MPLINE.IBREVN; PPS200MI/GetHead	The field indicates the revision number.
PurchaseOrder/PurchaseOrderHeader/DisplayID	
MPHEAD.IAPUNO ;/	The field indicates the purchase order number.
PurchaseOrder/PurchaseOrderHeader/LastModificationDateTime	The field indicates when the last shapes was made to the Divisions
MPHEAD.IALMTS :/	The field indicates when the last change was made to the Purchase Order.
PurchaseOrder/PurchaseOrderHeader/LastModificationPerson/IDs/ID	
MPHEAD.IACHID	The field indicates the user ID associated with the last change made
;/	to the Purchase Order.
@accountingEntity MPHEAD.IACONO	The field indicates the company and division, displayed as
MPHEAD.IADIVI.; /	CONO DIVI.
PurchaseOrder/PurchaseOrderHeader/DocumentDateTime MPHEAD.IAPUDT	The field indicates the purchase order date.
; PPS200MI/GetHead PurchaseOrder/PurchaseOrderHeader/Note	
MSYTXL.TLTX60 ; PPS200MI/LstHeadTxt	The field indicates the notes or remarks.
@type	The field indicates the mate time
.; PPS200MI/LstHeadTxt	The field indicates the note type. If TYTR=1, set to "Pre-text".
	If TYTR=2, set to "Post-text".
	If TYTR=3, do not display attribute type.
PurchaseOrder/PurchaseOrderHeader/Status/Code	The field indicates the lawest status of the numbers and a
MPHEAD.IAPUSL ; PPS200MI/GetHead	The field indicates the lowest status of the purchase order. Set to 'Open' if lowest status is 15, 20, 25, 31,32, 33, 35, 40 or 45.
,	Set to 'Received' if lowest status is 50, 51, 60, 64, 65, 69 or 75.
	Set to 'PartiallyReceived' if lowest status is 70.
	Set to 'Invoiced' if lowest status is 80, 85 or 90. Set to 'Canceled' if lowest is status 99.
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/I	
CMNUSR.JUTX40 ; MNS150MI/GetUserData	The field indicates the buyer's contact name.
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/C	Communication
@preferredIndicator	Set to 'false'.
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/C	
Turonuocorucini uronuocorucinicuucinouotomen urtyibuyeroonuubk	Set to "Phone" if telephone number 1 or facsimile number.
O.V. vID	Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/	
	Set to "Office" if telephone number 1 or e-mail address.
Oli-AID	Set to "Fax" if facsimile number.
@listID	Set to "Communication Use Codes".
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/	
CMNUSR.JUPHNO CMNUSR.JUTFNO.; MNS150MI/GetUserData	The field indicates the telephone number or facsimile number.
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/C	Communication/URI
CEMAIL.CBEMAL	The field indicates the e-mail address.
; CRS111MI/Get	Demonstration /Durfacence - //
PurchaseOrder/PurchaseOrderHeader/CustomerParty/BuyerContact/C	Communication/Preference/Indicator Set to 'false'.
PurchaseOrder/PurchaseOrderHeader/SupplierParty/PartyIDs/ID	
MPHEAD.IASUNO	The field indicates the unique identity of a supplier.
; PPS200MI/GetHead	
@accountingEntity MPHEAD.IACONO	

PurchaseOrder	
MPHEAD.IADIVI .; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Name CIDMAS.IDSUNM : PPS200MI/GetAddresses	The field indicates the supplier name.
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Addres. @type	
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Addres.	Set to 'text'.
MPHEAD.IAYRE1 ; PPS200MI/GetHead	The field indicates the name of the person to be contacted for issues regarding purchase orders.
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address MPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4 .; PPS200MI/GetAddresses @sequence	s/AddressLine The field indicates the address line.
	The field indicates the address line sequence.
<pre>PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address MPPOAD.ADTOWN ; PPS200MI/GetAddresses</pre>	s/CityName The field indicates the city name.
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address MPPOAD.ADSECA ; PPS200MI/GetAddresses @listID	s/CountrySubDivisionCode The field indicates an area, province or state within a country.
(LISTID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address MPPOAD.ADCSCD ; PPS200MI/GetAddresses	
@listID	Set to 'Countries'.
PurchaseOrder/PurchaseOrderHeader/SupplierParty/Location/Address MPPOAD.ADPONO : PPS200MI/GetAddresses	
PurchaseOrder/PurchaseOrderHeader/ShipToParty/PartyIDs/ID MPPOAD.ADADK2 ; PPS200MI/GetAddresses	The field indicates the warehouse.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI . /	The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Name MPPOAD.ADCONM ; PPS200MI/GetAddresses	The field indicates the delivery receiver name.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/ID MPPOAD.ADADK2 ; PPS200MI/GetAddresses	The field indicates the warehouse.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates the warehouse name.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address @type	Set to 'text'.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/MPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4 .; PPS200MI/GetAddresses @sequence	The field indicates the address line.
Boundary Outland Double Control of the Control of t	The field indicates the address line sequence.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/ MPPOAD.ADTOWN ; PPS200MI/GetAddresses	CityName The field indicates the city name.
PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/ MPPOAD.ADDECA ; PPS200MI/GetAddresses @listID	/CountrySubDivisionCode The field indicates an area, province or state within a country.

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified. PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/CountryCode MPPOAD.ADCSCD The field indicates a country code. ; PPS200MI/GetAddresses @listID Set to 'Countries' PurchaseOrder/PurchaseOrderHeader/ShipToParty/Location/Address/PostalCode MPPOAD.ADPONO The field indicates the postal code. PPS200MI/GetAddresses PurchaseOrder/PurchaseOrderHeader/ShipFromParty/PartyIDs/ID The field indicates the ShipFromParty ID. MPHEAD.IASUNO ; PPS200MI/GetHead @accountingEntity MPHEAD.IACONO The field indicates the accounting entity MPHEAD.IADIVI If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI). PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location @type CSYTAB.CTPARM; MMS006MI/Get Set to 'Distribution Center' if the warehouse type of the warehouse is set as a distribution center. PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/ID MPHEAD.IAWHLO The field indicates the warehouse ; PPS200MI/GetHead @accountingEntity MPHEAD. ĪACONO The field indicates the company and division, displayed as MPHEAD.IADIVI CONO DIVI. PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address Set to 'text' PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/AddressLine CIADDR.OAADR1 The field indicates the address line CIADDR.OAADR2 CIADDR.OAADR3 CIADDR.OAADR4; MMS005MI/GetWarehouse MPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4; PPS200MI/GetAddresses @sequence The field indicates the address line sequence PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CityName CIADDR.OATOWN; The field indicates the city name. MMS005MI/GetWarehouse MPPOAD.ADTOWN; PPS200MI/GetAddresses.; / PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CountrySubDivisionCode CIADDR.OAECAR: The field indicates an area, province or state within a country. MMS005MI/GetWarehouse MPPOAD.ADECAR; PPS200MI/GetAddresses @listID Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified. PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/CountryCode CIADDR.OACSCD: The field indicates a country code. MMS005MI/GetWarehouse

MPPOAD.ADCSCD;

PPS200MI/GetAddresses.; /

@listID

PurchaseOrder/PurchaseOrderHeader/ShipFromParty/Location/Address/PostalCode

CIADDR.OAPONO: The field indicates a postal code.

May 26, 2023

Set to 'Countries

MMS005MI/GetWarehouse MPPOAD.ADPONO: PPS200MI/GetAddresses.; /

PurchaseOrder/PurchaseOrderHeader/ContractReference/DocumentID/ID

MPHEAD.IAOURR The field indicates the reference number. Display if Reference type

; PPS200MI/GetHead (OURT) is 1 (Agreement number).

PurchaseOrder/PurchaseOrderHeader/ExtendedAmount

MPHEAD.IACOAM ; PPS200MI/GetHead The field indicates total order cost.

@currencyID

MPHEAD.IACUCD The field indicates currency. ; PPS200MI/GetHead

PurchaseOrder/PurchaseOrderHeader/BillToParty/Name

MPPOAD ADCONM The field indicates the invoice receiver name ; PPS200MI/GetAddresses

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address

@type

Set to 'text'.

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/AddressLine

MPPOAD.ADADR1 The field indicates the invoice receiver address.

MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4

.; PPS200MI/GetAddresses

@sequence

The field indicates the address line sequence

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/CityName

MPPOAD.ADTOWN; PPS200MI/GetAddresses The field indicates the invoice receiver city name.

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/CountrySubDivisionCode

MPPOAD.ADECAR; PPS200MI/GetAddresses The field indicates an area, province or state within a country.

@listID

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/CountryCode

MPPOAD.ADCSCD; PPS200MI/GetAddresses

The field indicates the invoice receiver country code.

@listID Set to 'Countries'.

PurchaseOrder/PurchaseOrderHeader/BillToParty/Location/Address/PostalCode

MPPOAD.ADPONO; PPS200MI/GetAddresses The field indicates the invoice receiver postal code.

PurchaseOrder/PurchaseOrderHeader/TransportationTerm/IncotermsCode

The field indicates the delivery terms.

MPHEAD.IATEDL

; PPS200MI/GetHead

The value can be translated in CRS881/882.

Msg std: ION Vers: 1

Message: Generic

I/O: 0

Parent element(s): Generic Date element: IncotermsCode

@listID Set to 'Incoterms'.

PurchaseOrder/PurchaseOrderHeader/TransportationTerm/IncotermsText

MPHEAD.IATEL1: PPS200MI/GetHead CSYTAB.CTPARM; CRS065MI/GetDelyTerm.; / The field indicates the terms text, which is usually printed on external

documents as explanatory text.

If terms text from PO header is blank, map this element to

CRS065MI.GetDelyTerm TEL1 and TEL2.

If TEL1 does not consume the maximum field length of 36 and TEL2

is not empty, leave a space between TEL1 and TEL2.

If TEL2 does not consume the maximum field length of 36, right trim. If TEL1 does not consume the maximum field length of 36 and TEL2

is empty, right trim TEL1

PurchaseOrder/PurchaseOrderHeader/TransportationTerm/FreightTermCode

MPHEAD.IATEAF The field indicates the freight terms.

; PPS200MI/GetHead

PurchaseOrder/PurchaseOrderHeader/PaymentTerm/PaymentTermCode

MPHEAD.IATEPY The field indicates the payment terms.

; PPS200MI/GetHead @listID

Set to 'Payment Term'.

PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/ID

MPHEAD.IATEPY The field indicates the payment terms.

May 26, 2023

: PPS200MI/GetHead	
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Description	7
CSYTAB.CTPARM ; PPS200MI/GetHead	The field indicates the payment description.
PurchaseOrder/PurchaseOrderHeader/PaymentTerm/Term/Amount MPHEAD.IACOAM ; PPS200MI/GetHead	The field indicates the total order cost.
@currencyID MPHEAD.IACUCD ; PPS200MI/GetHead	The field indicates the currency.
PurchaseOrder/PurchaseOrderHeader/DistributedCharge	
@type MDOEYD IVEYTY: DDS245MI/LetDOCherges	The field indicates the type of charge the coating element represents
MPOEXP.IVEXTY; PPS215MI/LstPOCharges	The field indicates the type of charge the costing element represents If EXTY = 0, set to 'No charge'. If EXTY = 1, set to 'Internal charge'. If EXTY = 2, set to 'External charge'.
<pre>@sequence MPOEXP.IVCDSE; PPS215MI/LstPOCharges</pre>	The field indicates the sequence number of the costing element.
PurchaseOrder/PurchaseOrderHeader/DistributedCharge/ID MPOEXP.IVCEID; PPS215MI/LstPOCharges	The field indicates the costing element.
PurchaseOrder/PurchaseOrderHeader/DistributedCharge/Description	<u> </u>
MPCELE.INTX30; PPS280MI/GetElement	Set to 'Order discount'. The field indicates the costing element description.
PurchaseOrder/PurchaseOrderHeader/DistributedCharge/Amount	4) The field indicates the and the literature
1) MPHEAD.IAODAM; PPS200MI/GetHead	The field indicates the order total discount. The field indicates the costing element amount. CEVA + CEVJ.
2) MPOEXP.IVCEVA MPOEXP.IVCEVJ; PPS215MI/LstPOCharges.; /	
@currencylD	
MPHEAD.IACUCD; PPS200MI/GetHead MPOEXP.IVCUCD;	The field indicates the currency.
PPS215MI/LstPOCharges.; /	
PurchaseOrder/PurchaseOrderHeader/DistributedCharge/ReasonCode MPOEXP.IVEXIC; PPS215MI/LstPOCharges	 Set to 'Order discount'. The field indicates if charges connected to a purchase order can be invoiced one time or several times. This field is only valid for external charges. If EXIC = 1, set to 'Only once'. If EXIC = 2, set to 'Several times'.
@listID	Attribute list ID is set to 'Charge Invoicing'. Set to 'Charge Invoicing' if DistributedCharge/ReasonCode is mappe
	to EXIC.
PurchaseOrder/PurchaseOrderHeader/DistributedCharge/GrossWeigh	tIndicator Set to 'false'.
PurchaseOrder/PurchaseOrderHeader/RequestedShipDateTime MPHEAD.IADWDT PRES200MI/CotHood	The field indicates requested delivery date.
; PPS200MI/GetHead PurchaseOrder/PurchaseOrderHeader/PromisedDeliveryDateTime	
MPHEAD.IADWDT ; PPS200MI/GetHead	The field indicates promised delivery date.
PurchaseOrder/PurchaseOrderHeader/OrderDateTime MPHEAD.IAPUDT : PPS200MI/GetHead	The field indicates purchase order date.
PurchaseOrder/PurchaseOrderHeader/UserArea	
1) MPHEAD.IAPUST; PPS001MI/GetHeadBasic	Highest status The field indicates the highest status.
2) MPHEAD.IAPUSL; PPS001MI/GetHeadBasic	Set attribute name to 'HighestStatus'. 2) Lowest status
3) MPHEAD.IANTAM;	The field indicates the lowest status. Set attribute name to 'LowestStatus'.
PPS200MI/GetHead 4) MPHEAD.IACMCO;	3) Net order value The field indicates the net order value.
PPS200MI/GetHead	Set attribute name to 'SubTotalAmount'.
5) MPHEAD.IANOLN; PPS200MI/GetHead	Media profile The field indicates the media profile. Set attribute page to 'Media Profile'.
6) MPHEAD.IABRAM; PPS200MI/GetHead	Set attribute name to 'MediaProfile'. 5) Line count
Infor May 26, 202	3

7) CIDMAS.IDCFI4; CRS620MI/GetBasicData

8) MPHEAD.IAUCA1-IAUCA0 MPHEAD.IAUDN1-IAUDN6 MPHEAD.IAUID1-IAUID3 MPHEAD.IAUCT1; PPS200MI/GetHead CUDFLD.FDTX15; CMS082/LstFields CUDFLV.FVTX40; CMS083/LstValues.; / The field indicates the number of purchase order lines. Set attribute name to 'OrderLineCount'.

6) Gross total value

The field indicates the gross total value. Set attribute name to 'GrossTotalAmount'.

7) Supplier user-defined field 4

The field indicates user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'.

8) User-defined field

The field indicates a user-defined field for displaying and storing your own information

Set attribute name to 'm3.<M3 BE field>-<CMS082 TX15>'.

Description is retrieved from CMS083 TX40.

Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.

PurchaseOrder/PurchaseOrderHeader/RFQReference/DocumentID/ID

MPHEAD.IAOURR ; PPS200MI/GetHead @accountingEntity

MPHEAD.IACONO MPHEAD.IADIVI The field indicates the reference number. Display if Reference type (OURT) is 3 (Supplier quotation number).

The field indicates the company and division, displayed as CONO_DIVI.

PurchaseOrder/PurchaseOrderHeader/Classification/Codes/Code

1) MPHEAD.IAPOTC PPS200MI/GetHead

2) MPHEAD.IAORTY PPS200MI/GetHead

3) CIDVEN.IIDCSM CRS620MI/GetBasicData

4) MPHEAD.IAAGNT PPS200MI/GetHead.; / 1) Purchase Order category

The field indicates purchase order category. Set attribute listID to 'Purchase Order Categories'.

2) Order type

The field indicates the purchase order type. Set attribute listID to 'Purchase Order Types'.

3) Discount calculation method The discount calculation method used. Set to 'Total discount' if value is 0. Set to 'Chain discount' if value is 1.

Set attribute listID to 'Discount Calculation Method'.

4) Agent

The field indicates the agent's number. Set attribute listID to 'Agent'.

The field indicates the sequence number.

1) Set to 'Purchase Order Categories'.

2) Set to 'Purchase Order Types'.

3) Set to 'Discount Calculation Method'.

4) Set to 'Agent'.

The field indicates the company and division, displayed as CONO_DIVI.

@accountingEntity

@sequence

@listID

MPHEAD.IACONO MPHEAD.IADIVI

PurchaseOrder/PurchaseOrderHeader/Classification/Description

1) MPHEAD.IAPOTC PPS200MI/GetHead

2) MPORDT.OTTX15 PPS095MI/LstOrderType

3) CIDMAS.IDSUNM CRS620MI.GetBasicData.; /

1) Purchase Order Category

Set to 'Inquiry' if PO category is 10.

Set to 'Purchase Order' if PO category is 20.
Set to 'Consignment order' if PO category is 25.

Set to 'Consignment usage order' if PO category is 26. Set to 'Delivery schedule(rolling)' if PO category is 30.

Set to 'Delivery schedule(time limiting)' if PO category is 40.

Set to 'Repair order' if PO category is 60. Set to 'Warranty repair' if PO category is 65. Set to 'Subcontract' if PO category is 70. Set to 'Loan' if PO category is 80.

Set to 'Loan' if PO category is 80. Set to 'Exchange' if PO category is 85. Set to 'Freight' if PO category is 90.

2) The field indicates the order type name.

3) The field indicates the agent's name.

PurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID

MPHEAD.IAPRSU

The field indicates the payee.

PurchaseOrder	
; PPS200MI/GetHead	
@accountingEntity	
MPHEAD.IACONO	The field indicates the accounting entity.
MPHEAD.IADIVI	If RemitToPartyMaster is enabled in BOD Processor Master AE tab,
.; /	this is displayed as Company (CONO). Otherwise, this is displayed as
	Company and Division (CONO DIVI).
PurchaseOrder/PurchaseOrderLine/LineNumber	
MPLINE.IBPNLI	The field indicates the purchase order line concatenated with the
MPLINE.IBPNLS.; PPS200MI/LstLine	purchase ordeline subnumber.
PurchaseOrder/PurchaseOrderLine/Note	
MSYTXL.TLTX60	The field indicates the notes or remarks.
; PPS200MI/LstLineTxt	
@type	
:; PPS200MI/LstHeadTxt	The field indicates the note type.
,	If TYTR=1, set to "Pre-text".
	If TYTR=2, set to "Post-text".
	If TYTR=3, do not display attribute type.
PurchaseOrder/PurchaseOrderLine/Status/Code	ii i i i i vo, do not diopidy ditiribato typo.
	The field indicates the fellowing status of the Durchass Order line.
MPLINE.IBPUST	The field indicates the following status of the Purchase Order line:
; PPS200MI/LstLine	Set to 'Open' if the PO line is 15, 20, 25, 31, 32, 33, 35, 40 or 45.
	Set to 'Received' if the PO line is 50, 51, 60, 64, 65, 69 or 75.
	Set to 'PartiallyReceived' if the PO line is 70.
	Set to 'Invoiced' if the PO line is 80, 85 or 90.
	Set to 'Canceled' if the PO line is 99.
PurchaseOrder/PurchaseOrderLine/Item/ItemID/ID	
MPLINE.IBITNO	The field indicates the item number.
MPLINE.IBSITE.; PPS200MI/LstLine	
	The field indicates the supplier's item number if @schemeName is set
	to 'Supplier'.
@schemeName	
	Set to 'Supplier' if Item ID is a supplier's item number.
@schemeAgencyID	
MPLINE.IBSUNO; PPS200MI/LstLine	The field indicates the supplier.
@accountingEntity	
MPHEAD.IACONO	The field indicates the company and division, displayed as
MPHEAD.IADIVI	CONO_DIVI.
.; /	
PurchaseOrder/PurchaseOrderLine/Item/ItemID/RevisionID	
MPLINE.IBECVE	The field indicates the revision number of an item or document.
; PPS200MI/LstLine	
PurchaseOrder/PurchaseOrderLine/Item/GTIN	
MITPOP.MPPOPN	The field indicates the alias number.
; MMS025MI	Use the following as inputs:
/GetAlias	Alias category (ALWT) = 2
	Alias qualifier (ALWQ) = EA13
PurchaseOrder/PurchaseOrderLine/Item/ServiceIndicator	
MTEINF.UICFMA	The field indicates the value of service indicator.
; CMS474MI/GetUdefContent	Use the following as input:
,	UDFT = 1
	ITNO = <item number=""></item>
	CFMG = BOD
	CFMF = MROSERV'
	Set to 'true' if CFMA is Y. Otherwise, set to 'false'.
PurchaseOrder/PurchaseOrderLine/Item/Description	
MPLINE.IBPITT	The field indicates the purchase order item description.
: PPS200MI/GetLineX	The hold indicates the parchase order item description.
PurchaseOrder/PurchaseOrderLine/Item/PartyDescription	The field indicates the summitted items described as
MITVEN.IFSITT; PPS040MI/GetItemSupplier	The field indicates the supplier's item description.
@partyType	Catta ICumulian
@nortyAccountingEntity	Set to 'Supplier'.
@partyAccountingEntity MDHEAD IACONO	The field indicates the company and division displayed as
MPHEAD IADIV	The field indicates the company and division, displayed as
MPHEAD.IADIVI	CONO_DIVI.
;/	
PurchaseOrder/PurchaseOrderLine/Item/Classification	
@type	4) Cotto II/ITI if Oloosifi - 4: /O1 /O1 : FOOD : 11
	1) Set to 'KIT' if Classification/Codes/Code is FSCD with value of
	greater than 0.
	2) Set to 'Supplier Item Code' if Classification/Codes/Code is SITE.
	3) Set to 'Item Description' if Classification/Codes/Code is FUDS.
	Set to 'Item Name' if Classification/Codes/Code is ITDS.
	5) Set to 'PO Item Name' if Classification/Codes/Code is PITD.
	6) Set to 'Packaging' if if Classification/Codes/Code is PACT.
	7) Set to 'Manufacturer if Classification/Codes/Code is PROD.
	8) Set to 'Country Of Origin' if Classification/Codes/Code is ORCO.
Infor May 2	26, 2023 45

MPLINE.IBPUPR

@currencyID

MPLINE.IBCPPR.; PPS200MI/LstLine

PurchaseOrder/PurchaseOrderLine/Item/Classification/Codes/Code 1) MPLINE.IBFSCD Kit control PPS200MI/GetLine The field indicates the kit control. Set attribute type and listID to 'KIT'. 2) MPLINE.IBSITE 2) Supplier item number PPS200MI/LstLine The field indicates the supplier item number in the purchase order line. Set attribute type and listID to 'Supplier Item Code'. 3) MITMAS.MMFUDS MMS200MI/GetItmBasic The field indicates the item number description. Set attribute type and 4) MITMAS.MMITDS listID to 'Item Description'. PPS200MI/LstLine 4) Item name The field indicates the item number name. Set attribute type and listID 5) MPLINE.IBPITD PPS200MI/GetLine to 'Item Name'. 6)MPLINE.IBPACT 5) Purchase order item name The field indicates the purchase order item name. Set attribute type PPS200MI/LstLine and listID to 'PO Item Name'. 7) MPLINE.IBPROD PPS200MI/LstLine 6) Packaging The field indicates the packaging. Set attribute type and listID to 8) MPLINE.IBORCO 'Packaging'. PPS200MI/LstLine2 7) Manufacturer The field indicates the manufacturer. Set attribute type and listID to 'Manufacturer'. 8) Country of origin The field indicates the item's country of origin. Set attribute type and listID to 'Country of Origin'. @sequence The field indicates the sequence number. @listID 1) Set to 'KIT' if Classification/Codes/Code is FSCD with value of greater than 0. 2) Set to 'Supplier Item Code' if Classification/Codes/Code is SITE. 3) Set to 'Item Description' if Classification/Codes/Code is FUDS. 4) Set to 'Item Name' if Classification/Codes/Code is ITDS 5) Set to 'PO Item Name' if Classification/Codes/Code is PITD. 6) Set to 'Packaging' if Classification/Codes/Code is PACT. 7) Set to 'Manufacturer if Classification/Codes/Code is PROD. 8) Set to 'Country Of Origin' if Classification/Codes/Code is ORCO. PurchaseOrder/PurchaseOrderLine/Item/Classification/Description CSYTAB.CTTX40; CRS045MI/GetBasicData The field indicates the full name of the country. The field is only available if Classification/Codes/Code@listID is 'Country of Origin' PurchaseOrder/PurchaseOrderLine/Quantity MPLINE.IBORQA The field indicates the ordered quantity in alternate unit of measure if MPLINE.IBCFQA.; PPS200MI/LstLine Confirmed quantity (CFQA) is less than 1. Otherwise, the confirmed quantity (CFQA) is displayed. @unitCode MPLINE.IBPUUN The field indicates the purchase order unit of measure. PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/QuantityDistribution/ProjectReference/ID MPLINE.IBPROJ: PPS200MI/LstLine2 The field indicates the unique ID for a project. @accountingEntity MPHEAD. IACONO The field indicates the company and division, displayed as MPHEAD.IADIVI.; / CONO DIVI. PurchaseOrder/PurchaseOrderLine/QuantityDistribution/ProjectReference/Description CSEAMA.HSTX40; CRS912MI/GetSeason The field indicates the season description. Retrieve Season Control (SEAG) from PPS095MI.LstOrderType. If SEAG = 1 or 2, call CRS912MI. GetSeason. PurchaseOrder/PurchaseOrderLine/QuantityDistribution/ProjectReference/ProjectElement/ID MPLINE.IBELNO; PPS200MI/LstLine2 The field indicates an element which is part of a project structure. PurchaseOrder/PurchaseOrderLine/BaseUOMQuantity The field indicates the ordered quantity in basic unit of measure if MPLINE.IBORQA MPLINE.IBCFQA.; PPS200MI/LstLine Confirmed quantity (CFQA) is less than 1. Otherwise, Confirmed quantity (CFQT) is displayed. @unitCode MPLINE.IBUNMS The field indicates the basic unit of measure. ; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/UnitPrice/Amount

Infor May 26, 2023 45

(CPPR) is displayed.

The field indicates the purchase price (PUPR) if Confirmed purchase

price (CPPR) is less than 1. Otherwise, Confirmed purchase price

PurchaseOrder	
MPHEAD.IACUCD ; PPS200MI/GetHead	The field indicates the currency.
PurchaseOrder/PurchaseOrderLine/UnitPrice/PerQuantity MPLINE.IBCPUC MPLINE.IBPUCD.; PPS200MI/LstLine	The field indicates the unit price per quantity. Display Confirmed purchase price quantity if value is greater than 0. I not, Purchase price quantity (PUCD) should be checked. If PUCD is less than 1, then the value of the element will be set to 1. If more Thant 1, then the value of PUCD will be displayed.
@unitCode MPLINE.IBPPUN ; PPS200MI/LstLine	The field indicates the purchase price unit of measure.
PurchaseOrder/PurchaseOrderLine/ExtendedAmount MPLINE.IBLNAM or IBLNA2; PPS200MI/LstLine	The field indicates the Line amount in order currency. If the item is confirmed, LNA2 is published else LNAM is published.
@currencyID MPHEAD.IACUCD ; PPS200MI/GetHead	The field indicates the currency.
PurchaseOrder/PurchaseOrderLine/TotalAmount MPLINE.IBLNAM MPLINE.IBEXEP .; PPS200MI/GetLine	The field indicates the total amount. If External charge (EXEP) is not 0, Line amount in order currency (LNAM) + EXEP is displayed. Otherwise, LNAM is displayed.
@currencyID MPHEAD.IACUCD ; PPS200MI/GetHead	The field indicates the currency.
PurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine	The field indicates the requested delivery date and time.
PurchaseOrder/PurchaseOrderLine/ShipToParty/PartyIDs/ID MPPOAD.ADADK2 ; PPS200MI/GetDelAddress	The field indicates the delivery address.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; /	The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Name MPPOAD.ADCONM ; PPS200MI/GetDelAddress	The field indicates the delivery receiver name.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MPLINE.IBWHLO ; PPS200MI/LstLine	The field indicates the warehouse. If Generation reference (GETY) = 24 (from CO direct delivery), this element will not be displayed.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; /	The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates the warehouse name.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address@type	
	Set to 'text'.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/AMPPOAD.ADADR1 MPPOAD.ADADR2 MPPOAD.ADADR3 MPPOAD.ADADR4 .; PPS200MI/GetDelAddress	The field indicates the address line.
@sequence	The field indicates the address line sequence.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/OMPPOAD.ADTOWN; PPS200MI/GetDelAddress	CityName The field indicates the delivery address city.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/C MPPOAD.ADECAR; PPS200MI/GetDelAddress @listID	CountrySubDivisionCode The field indicates the delivery address state.
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/C MPPOAD.ADCSCD ; PPS200MI/GetDelAddress	
@listID	Set to 'Countries'

i ulcilaseoluei	
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/Address/PomPPOAD.ADPONO : PPS200MI/GetDelAddress	ostalCode The field indicates the delivery address postal code.
PurchaseOrder/PurchaseOrderLine/TransportationTerm/IncotermsCo	ode
MPLINE.IBTEDL; PPS200MI/LstLine	The field indicates the delivery terms.
	The value can be translated in CRS881/882.
	Msg std: ION
	Vers: 1 Message: Generic
	I/O: O
	Parent element(s): Generic
@listID	Date element: IncotermsCode
	Set to 'Incoterms'.
PurchaseOrder/PurchaseOrderLine/TransportationTerm/IncotermsTe	
MPLINE.IBTEL1; PPS200MI/LstLine	The field indicates the terms text, which is usually printed on external documents as explanatory text.
CSYTAB.CTPARM;	If terms text from PO line is blank, map this element to
CRS065MI/GetDelyTerm.; /	CRS065MI.GetDelyTerm TEL1 and TEL2.
	If TEL1 does not consume the maximum field length of 36 and TEL2 is not empty, leave a space between TEL1 and TEL2.
	If TEL2 does not consume the maximum field length of 36, right trim.
	If TEL1 does not consume the maximum field length of 36 and TEL2 is empty, right trim TEL1.
PurchaseOrder/PurchaseOrderLine/DistributedCharge	is empty, right unit TEET.
@type	
MPOEXP.IVEXTY; PPS215MI/LstPOCharges	The field indicates the type of charge the costing element represents. If EXTY = 0, set to 'No charge'.
	If EXTY = 0, set to 'No charge'.
	If EXTY = 2, set to 'External charge'.
@sequence MPOEXP.IVCDSE; PPS215MI/LstPOCharges	The field indicates the sequence number of the costing element.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/ID	
MPOEXP.IVCEID; PPS215MI/LstPOCharges	The field indicates the costing element.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Description	Cat to the fallowing.
MPCELE.INTX30; PPS280MI/GetElement	Set to the following: 1) 'Order discount 1'
	2) 'Order discount 2'
	3) 'Order discount 3' 4) 'Confirmed discount 1'
	5) 'Confirmed discount 2'
	6) 'Confirmed discount 3'
	7) 'Charge Type' 8) 'Charge Type'
	9) The field indicats the costing element description.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Amount	N= 2
1) MPLINE.OBODI1 MPLINE.OBODI2	 The field indicates the discount and/or the confirmed discount and/or internal charges and/or external charges.
MPLINE.OBODI3	of internal charges and/of external charges.
MPLINE.OBCFD1	2) The field indicates the costing element amount.
MPLINE.OBCFD2 MPLINE.OBCFD3	
MPLINE.OBINEP	
MPLINE.OBEXEP;	
PPS200MI/GetLine.; / @currencyID	
MPHEAD.IACUCD;	The field indicates the currency.
PPS200MI/GetHead MPOEXP.IVCUCD:	
PPS215MI/LstPOCharges.; /	
PurchaseOrder/PurchaseOrderLine/DistributedCharge/ReasonCode	
MPOEXP.IVEXIC; PPS215MI/LstPOCharges	For description 'Order discount 1', reason code = 'General Order Discount'.
	2) For description 'Order discount 2'- if reference type in the header (HeadOURT) is 1 and reference number (HeadOURR) is not empty, reason code = 'AgreementHeader - ' + iHeadOURR. Else if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementHeader - '+ iLineOURR. Else if reference type in the header (HeadOURT) is not 1, reason code =

Infor May 26, 2023 461

reference type in the header (HeadOURT) is not 1, reason code = 'Manual Discount'.

3) For description 'Order discount 3'- if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine - '+ iLineOURR. Else if reference type

	in the line (LineOURT) is not 1, reason code = 'Manual Discount'.
	4.) For description 'Confirmed discount 1', reason code = 'General Order Discount'.
	5.) For description 'Confirmed discount 2'- if reference type in the header (HeadOURT) is 1 and reference number (HeadOURR) is not empty, reason code = 'AgreementHeader - ' + iHeadOURR. Else if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine - '+ iLineOURR. Else if reference type in the header (HeadOURT) is not 1, reason code = 'Manual Discount'.
	6.) For description'Confirmed discount 3'- if reference type in the line (LineOURT) is 1 and reference number (LineOURR) is not empty, reason code = 'AgreementLine - '+ iLineOURR. Else if reference type in the line (LineOURT) is not 1, reason code = 'Manual Discount'.
	7.) For description 'Charge Type' and amount internal charge (INEP), reason code = 'Internal Charges'.
	8.) For description 'Charge Type' and amount external charge (EXEP), reason code = 'External Charges'.
	9) The field indicates if charges connected to a purchase order can be invoiced one time or several times. This field is only valid for external charges. If EXIC = 1, set to 'Only once'. If EXIC = 2, set to 'Several times'. Attribute list ID is set to 'Charge Invoicing'.
@listID	Set to 'Charge Invoicing' if DistributedCharge/ReasonCode is mapped to EXIC.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/GrossWeightIn	
PurchaseOrder/PurchaseOrderLine/Reference/NameValue MPLINE.IBETRF; PPS200MI/LstLine	The field represents a reference code for standard text which is to be printed on external PO and quotation request documents. Set attribute name to 'ExternalInstruction'.
@name	
PurchaseOrder/PurchaseOrderLine/FreightClassification/Codes/Code	Set to 'ExternalInstruction' if NameValue is ETRF.
MPLINE.IBMODL; PPS200MI/LstLine	The field indicates the delivery method.
	The field indicates the delivery method.
	The value can be translated in CRS881/882. Msg std: ION
	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic
	The value can be translated in CRS881/882. Msg std: ION Vers: 1
	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIll MPLINE.IBPLPN; PPS200MI/LstLine	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIl	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIle MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIle MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI _; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. T The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIII MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIle MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date is displayed (DWDT) with time (TIHM).
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIII MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode MPLINE.IBPUUN; PPS200MI/LstLine	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date is displayed (DWDT) with time (TIHM).
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIle MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date is displayed (DWDT) with time (TIHM).
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentII MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .;/ PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode MPLINE.IBPUUN; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedBaseUOMQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode MPLINE.IBRVQA; PPS200MI/LstLine @unitCode MPLINE.IBPUUN; PPS200MI/LstLine	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date is displayed (DWDT) with time (TIHM). The field indicates the received quantity. The field indicates the purchase order unit of measure.
PurchaseOrder/PurchaseOrderLine/RequisitionReference/DocumentIII MPLINE.IBPLPN; PPS200MI/LstLine @accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; / PurchaseOrder/PurchaseOrderLine/RequisitionReference/LineNumber MPLINE.IBPLPS; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT MPLINE.IBDWDT MPLINE.IBDWDT MPLINE.TIHM.; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode MPLINE.IBPUUN; PPS200MI/LstLine PurchaseOrder/PurchaseOrderLine/ReceivedBaseUOMQuantity MPLINE.IBRVQA; PPS200MI/LstLine @unitCode @unitCode @unitCode @unitCode @unitCode @unitCode	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Date element: TransportationMethodCode D/ID The field indicates the planned purchase order. The field indicates the company and division, displayed as CONO_DIVI. The field indicates the subnumber of the planned purchase order. The field indicates the confirmed delivery date (CODT) and time (TIHM), if the field CODT is not empty, else, Requested delivery date is displayed (DWDT) with time (TIHM). The field indicates the received quantity. The field indicates the purchase order unit of measure.

PulchaseOrder	
@unitCode	difference of Ordered quantity (ORQA) and Received quantity (RVQA).
MPLINE.IBPUUN; PPS200MI/LstLine	The field indicates the purchase order unit of measure.
PurchaseOrder/PurchaseOrderLine/OpenBaseUOMQuantity	The field indicates the managinar accountity in basic unit of managinar
MPLINE.IBCFQA MPLINE.IBORQA	The field indicates the remaining quantity in basic unit of measure. This is the difference of Confirmed quantity (CFQT) and Received
MPLINE.IBRVQA.; PPS200MI/LstLine	quantity (RVQT). If Confirmed quantity (CFQA) is less than 1, then the value is the difference of Ordered quantity (ORQT) and Received quantity (RVQT).
@unitCode MPLINE.IBPUUN: PPS200MI/LstLine	The field indicates the basic unit of measure.
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/DocumentID	
MPLINE.IBRORN; PPS200MI/LstLine	The field indicates the reference order number. The element will be displayed only if reference order category is 3.
PurchaseOrder/PurchaseOrderLine/SalesOrderReference/LineNumber MPLINE.IBRORL; PPS200MI/LstLine	. The field indicates the reference order line. The element will be displayed only if reference order category is 3.
PurchaseOrder/PurchaseOrderLine/BuyerParty/PartyIDs/ID MPLINE.IBBUYE; PPS200MI/LstLine	The field indicates the buyer.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI . /	The field indicates the company and division, displayed as CONO_DIVI.
··, / PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/LineNumb	per
MPLINE.IBPNLI MPLINE.IBPNLS.; PPS200MI/LstLine	The field indicates the line number and the subline number. The element is only valid for KIT items.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Note MSYTXL.TLTX60 ; PPS200MI/LstLineTxt	The field indicates the notes or remarks.
@type .; PPS200MI/LstLineTxt	The field indicates the note type.
., TT OZOOWI/LStEINETAL	If TYTR=1, set to "Pre-text".
	If TYTR=2, set to "Post-text".
	If TYTR=3, do not display attribute type.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Document @type MPLINE.IBRORC; PPS200MI/LstLine	The field indicates the reference order category (RORC).
	Set to 'ProductionOrder' if RORC = 1.
	Set to 'PurchaseOrder' if RORC = 2. Set to 'SalesOrder' if RORC = 3.
	Set to 'Transfer' if RORC = 4.
	Set to 'Transfer' if RORC = 5.
	Set to 'ServiceOrder' if RORC = 6.
	Set to 'ServiceOrder' if RORC = 7. Set to 'ProjectOrder' if RORC = 8.
	Set to 'ClaimOrder' if RORC = 9.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Document MPLINE.IBRORN; PPS200MI/LstLine	tReference/DocumentID/ID The field indicates the reference order number.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .:/	The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Document	
MPLINE.IBRORL MPLINE.IBRORX.; PPS200MI/LstLine	The field indicates concatenation of reference order line and line suffix. The last 3 digits is line suffix.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Document MPLINE.IBRORX; PPS200MI/LstLine	tReference/SubLineNumber The field indicates the line suffix.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Item/ MPLINE.IBITNO ; PPS200MI/LstLine	D/ID The field indicates the item number/component of a kit.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI .; /	The field indicates the company and division, displayed as CONO_DIVI.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/GTIN MITPOP.MPPOPN	The field indicates the alias number.
; MMS025MI /GetAlias	Use the following as inputs: Alias category (ALWT) = 2 Alias qualifier (ALWQ) = EA13
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Desc MITMAS.MMITDS ; PPS200MI/LstLine	
Infor	

PurchaseOrder PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Classification/Codes/Code 1) MPI INF IBSITE 1) Supplier item number PPS200MI/LstLine The field indicates the supplier item number in the purchase order 2) MPLINE.IBCOLO Set attribute listID to 'Supplier Item Code'. PPS200MI/GetLine The field indicates the color of the product. 3) MPLINE.IBSIZE PPS200MI/GetLine Set attribute listID to 'Color'. 4) MPLINE.IBCHCS The field indicates the size of the product. Set attribute listID to 'Size'. PPS200MI/GetLine 5) MPLINE.IBHDPR 4) Characteristics The field indicates the characteristics of the product. PPS200MI/GetLine Set attribute listID to 'Characteristics'. 6) MITMAS.MMITDS PPS200MI/GetLine 5) Main product The field indicates the main product. 7) MPLINE.IBPITD Set attribute listID to 'Main Product'. PPS200MI/GetLine 8) OOHEAD.OACUOR The field indicates the item number name. Set attribute listID to 'Item Name'. OIS100MI/GetLine or GetOrderHead.; / 7) Purchase order item name The field indicates the purchase order item name. Set attribute listID to 'PO Item Name'. 8) Customer's order number The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents. Set attribute listID to 'Customers Order Number' Display only if PPS200MI/LstLine RORC = 3 (SalesOrder). @seauence The field indicates the sequence number. @listID 1) Set to 'Supplier Item Code' if Classification/Codes/Code is SITE. 2) Set to 'Color' if Classification/Codes/Code is COLO. 3) Set to 'Size' if Classification/Codes/Code is SIZE. 4) Set to 'Characteristics' if Classification/Codes/Code is CHCS. 5) Set to 'Main Product' if Classification/Codes/Code is HDPR. 6) Set to 'Item Name' if Classification/Codes/Code is ITDS 7) Set to 'PO Item Name' if Classification/Codes/Code is PITD. 8) Set to 'Customers Order Number' if Classification/Codes/Code is **CUOR** PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Item/Classification/Description MPDOPT.PFTX30; PDS050MI/Get The field indicates the option (Color, Size, Characteristics) description.

Use values of COLO, SIZE or CHCS as input to OPTN.

PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Quantity

MPLINE.IBORQA **IBCFQA**

; PPS200MI/LstLine

@unitCode

MPLINE.IBPUUN

; PPS200MI/LstLine

The field indicates the ordered quantity in alternate unit of measure if Confirmed quantity (CFQA) is less than 1. Otherwise, CFQA is

displayed.

The field indicates the alternate unit of measure.

PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/BaseUOMQuantity

MPLINE.IBORQT OR

IBCFQT

; PPS200MI/LstLine

@unitCode

MPLINE.IBUNMS

; PPS200MI/LstLine

The field indicates the ordered quantity in basic unit of measure if Confirmed quantity (CFQA) is less than 1. Otherwise, CFQA is

The field indicates the basic unit of measure.

PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/UnitPrice/Amount

MPLINE.IBPUPR

MPLINE.IBCPPR.; PPS200MI/LstLine

@currencvID MPHEAD.IACUCD PPS200MI/GetHead

The field indicates the purchase price (PUPR) if Confirmed purchase price (CPPR) is less than 1. Otherwise, Confirmed purchase price (CPPR) is displayed.

The field indicates the currency.

PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/UnitPrice/PerQuantity

MPLINE.IBCPUC

MPLINE.IBPUCD.; PPS200MI/LstLine

The field indicates the unit price per quantity.

Display Confirmed purchase price quantity if value is greater than 0. If not, Purchase price quantity (PUCD) should be checked. If PUCD is

May 26, 2023

PurchaseOrder	
@unitCode	less than 1, then the value of the element will be set to 1. If more Thant 1, then the value of PUCD will be displayed.
MPLINE.IBPPUN ; PPS200MI/LstLine	The field indicates the purchase price unit of measure.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/ParentLin	neNumber
MPLINE.IBPNLI ; PPS200MI/LstLine	The field indicates the purchase order line concatenated with three zeroes.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/UserArea	
1) MITMAS.MMCFl3; MMS200MI/GetItmBasic	 User-defined field 3 - item The field indicates the item user-defined field. This is used for custom report templates as well as for displaying and storing your own
2) MPLINE.IBUCA1-IBUCA0 MPLINE.IBUDN1-IBUDN6	information. Set attribute name to 'ItemFreeField 3'.
MPLINE.IBUID1-IBUID3	2) User-defined field
MLINE.IBUCT1; PPS200MI/LstLine	The field indicates a user-defined field for displaying and storing your own information.
CUDFLD.FDTX15;	Set attribute name to 'm3. <m3 be="" field="">-<cms082 tx15="">'.</cms082></m3>
CMS082/LstFields	Description is retrieved from CMS083 TX40.
CUDFLV.FVTX40; CMS083/LstValues.; /	Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.
PurchaseOrder/PurchaseOrderLine/UserArea	
1) MPLINE.IBPUST PPS200MI/LstLine	Highest status The field indicates the purchase order line highest status. Set attribute name to 'HighestStatus'.
2) MPLINE.OBPUSL	
PPS200MI/LstLine	2) Lowest status
3) MPLINE.IBOEND	The field indicates the purchase order line lowest status. Set attribute name to 'LowestStatus'.
PPS200MI/GetLine	name to Lowestotatus.
	3) Flagged as completed
4) MITMAS.MMCFI3 MMS200MI/GetItmBasic	The field indicates if flag is completed. Set attribute name to 'eam.ActiveFlag'. Set value to 'false' is OEND is 1. Otherwise, set value to 'true'.
5) MPLINE.IBUCA1-IBUCA0	
MPLINE.IBUDN1-IBUDN6	4) User-defined field 3 - item
MPLINE.IBUID1-IBUID3 MLINE.IBUCT1;	The field indicates the item user-defined field. This is used for custom report templates as well as for displaying and storing your own
PPS200MI/LstLine	information. Set attribute name to 'ItemFreeField 3'.
CUDFLD.FDTX15;	
CMS082/LstFields	5) User-defined field
CUDFLV.FVTX40; CMS083/LstValues.; /	The field indicates a user-defined field for displaying and storing your own information.
CIVISOOS/ESTV alues., /	Set attribute name to 'm3. <m3 be="" field="">-<cms082 tx15="">'.</cms082></m3>
	Description is retrieved from CMS083 TX40. Elements are not displayed if value of UDN1-UDN6 is 0 and CRS082 Name (TX15) is the default Gen. Decimal. CRS082 TX15 should be changed if the value 0 is intended to be displayed in the BOD for fields UDN1-UDN6.
PurchaseOrder/PurchaseOrderLine/ContractReference/DocumentID/I	D
MPLINE.IBOURR ; PPS200MI/LstLine	The field indicates the reference number. Display if Reference type (OURT) is 1 (Agreement number).
PurchaseOrder/PurchaseOrderLine/UnitQuantityConversionFactor MITUAN.MUCOFA ; MMS200MI/LstltmAltUnitMs	The field indicates the conversion factor.
PurchaseOrder/PurchaseOrderLine/SupplierParty/PartyIDs/ID MPLINE.IBSUNO ; PPS200MI/LstLine	The field indicates the unique identity of a supplier.
@accountingEntity MPHEAD.IACONO	The field indicates the accounting entity.
MPHEAD.IADIVI	If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
PurchaseOrder/PurchaseOrderLine/SupplierParty/Name MPPOAD.ADCONM; PPS200MI/GetAddress	The field indicates the supplier name.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location	
@type CIDADR.SAADTE; CRS620MI/GetAddrPerDate	The field indicates the address type. Set to 'Pickup' if ADTE = 3.
	SupplierParty/Location elements will only be displayed if ADTE = 3. Location information will be retrieved from Confirmed pickup address (CIAD). If CIAD is blank, it will be retrieved from Pickup address (PIAD).

PurchaseOrder	
CIDADR.SASUNM; CRS620MI/GetAddrPerDate	The field indicates the supplier name connected to the address.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address @type	Cat to House
Burnels and Outland Burnels and Outland in a 10 compliant Point of the anti-	Set to 'text'.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/ACIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4.; CRS620MI/GetAddrPerDate @sequence	The field indicates the address lines.
	The field indicates the address line sequence number.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CIDADR.SATOWN; CRS620MI/GetAddrPerDate	CityName The field indicates the city in an address.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CCIDADR.SAECAR; CRS620MI/GetAddrPerDate @listID	CountrySubDivisionCode The field indicates an area, province or state within a country.
	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/CCIDADR.SACSCD; CRS620MI/GetAddrPerDate @listID	CountryCode The field indicates the country.
	Set to 'Countries'.
PurchaseOrder/PurchaseOrderLine/SupplierParty/Location/Address/FCIDADR.SAPONO; CRS620MI/GetAddrPerDate	PostalCode The field indicates the postal code.
PurchaseOrder/PurchaseOrderLine/ShipFromParty/PartyIDs/ID MPLINE.IBSUNO ; PPS200MI/LstLine	The field indicates the unique identity of a supplier.
@accountingEntity MPHEAD.IACONO MPHEAD.IADIVI	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as
.;/	this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
PurchaseOrder/PurchaseOrderLine/ProductionOrderReference/Documents	mentID/ID The field indicates the reference order number. Display if Reference order category (RORC) is 1 (Manufacturing order).
PurchaseOrder/PurchaseOrderLine/Classification	
@type	Set to "Harbor Airports" for HAFE, TX40 and TX15. Set to "Place Of Load" for PIAD, TX40 and TX15.
PurchaseOrder/PurchaseOrderLine/Classification/Codes/Code	Social Flado of Essay for Flads, factor and factor.
1) MPLINE.IBOTOD PPS200MI/GetLine	Part of order total discount The field indicates the part of order total discount. Set attribute listID to 'Part of order total discount'.
2) MPLINE.IBSORN PPS200MI/GetLine	2) Supplier order number
3) MHIAUN.RFAUTP PPS200MI/GetLine	The field indicates the number that the supplier assigns to his order. The order number is normally specified per purchase order when these are confirmed. Set attribute listID to 'Supplier Order Number'.
4) MHIAUN.RFDMCF PPS200MI/GetLine	3) Alternate U/M type
5) MPLINE.IBWHLO PPS200MI/GetLine	The field indicates the alternate unit of measure type. Set attribute listID to 'Alternate U/M type'. Set to 'Alternate quantity U/M' if AUTP is 1. Set to 'Alternate price U/M' is AUTP is 2.
6) MPLINE.IBSRCD PPS200MI/GetLine	Set to "Supplementary INTRASTAT U/M based on net weight." if AUTP is 3. Set to 'Comparison price' if AUTP is 7.
7) MPLINE.IBPSET PPS200MI/GetLine	4) Conversion form The field indicates the conversion form.
8) MPLINE.IBGTNF PPS200MI/GetLine	Set listID attribute to 'Conversion form'.
9) MPLINE.IBHDPR PPS200MI/GetLine	5) Warehouse The field indicates the warehouse. Set listID attribute to 'Location'.
10) MPLINE.IBCOLO PPS200MI/GetLine	6) Reservation level The field indicates how the inventory reservation should be performed.
11) MPLINE.IBSIZE PPS200MI/GetLine	Set attribute listID to 'Reservation Level'. Display only if Kit control (FSCD) is greater than 0.

12) MPLINE.IBCHCS PPS200MI/GetLine

13) MPLINE.IBPNLI + IBPNLS PPS200MI/GetLine

14) MPLINE.IBGETY PPS200MI/GetLine

15)MPLINE.IBPACT PPS200MI/LstLine

16) MPLINE.IBPROD PPS200MI/LstLine

17) OOHEAD.OACUOR OIS100MI/GetLine or GetOrderHead

18) MPLINE.IBTAXC PPS200MI/LstLine2

19) MPLINE.IBVTCD PPS200MI/LstLine

20) MPLINE.IBPIAD PPS200MI/LstLine

21) MPLINE.IBHAFE PPS200MI/LstLine CSYTAB.CTTX40 CRS175MI/GetGeneralCode CSYTAB.CTTX15 CRS175MI/GetGeneralCode

22) MPLINE.IBSDES PPS200MI/LstLine CSYTAB.CTTX40 MMS008MI/GetPlace CSYTAB.CTTX15 MMS008MI/GetPlace

23) MPLINE.IBCIAD PPS200MI/LstLine

24) MPLINE.IBCDES PPS200MI/LstLine

7) Pricing Method

The field indicates how the sales price for the kit item and the detail lines are calculated. Set attribute listID to 'Pricing Level'. Display only if Kit control (FSCD) is greater than 0.

8) Complete flag

The field indicates if the GT Nexus completed flag. Set attribute listID to 'Flag Complete'. Set to value to 'true' if GTNF is 1. Set to value to 'false' if GTNF is 0.

9) Main product

The field indicates the main product. Set attribute listID to 'Main Product'.

10) Color

The field indicates the color of the product.

Set attribute listID to 'Color'.

The field indicates the size of the product. Set attribute listID to 'Size'.

12) Characteristics

The field indicates the characteristics of the product.

Set attribute listID to 'Characteristics'.

13) Purchase order line/Purchase order line subnumber

The field indicates which subline number the current line number was splitted to.

Set attribute listID to 'Split to PurchaseOrderLine'.

14) General reference

The field indicates the general reference.

Set attribute listID to 'General Reference'.

15) Packaging

The field indicates the packaging.

Set attribute type and listID to 'Packaging'.

16) Manufacturer

The field indicates the manufacturer.

Set attribute type and listID to 'Manufacturer'.

17) Customer's order number

The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents. Set attribute listID to 'Customers Order Number'.

Display only if PPS200MI/LstLine RORC = 3 (SalesOrder).

18) Tax code

The field indicates the tax code.

Set attribute listID to 'Tax Code'.

19) Vat code

The field indicates the VAT code.

Set attribute listID to 'VAT Code'.

20) Pickup address

The field indicates the pickup address.

Set attribute listID to 'Pickup Address'.

21) Harbor/Airport

The field indicates the ID of the harbor or airport.

Set attribute listID to 'Harbor Airports'.

The field indicates the Harbor/Airport description.

Set attribute listID to 'Harbor Airports Description'.

The field indicates the Harbor/Airport name.

Set attribute listID to 'Harbor Airports Name'.

22) Place of loading

The field indicates the ID of the place of loading.

Set attribute listID to 'Place Of Load'.

The field indicates the Place of load description.

Set attribute listID to 'Place Of Load Description'.

The field indicates the Place of load name.

Set attribute listID to 'Place Of Load Name'.

23) Confirmed pickup address

The field indicates the confirmed pickup address.

467 May 26, 2023

@sequence

@listID

Set attribute listID to 'Confirmed Pickup Address'.

24) Confirmed place of loading

The field indicates the ID of the confirmed place of loading. Set attribute listID to 'Confirmed Place Of Load'.

The field indicates the sequence number.

- 1) Set to 'Part of order total discount'.
- 2) Set to 'Supplier Order Number'.
- 3) Set to 'Alternate U/M type'.
- 4) Set to 'Conversion form'.
- 5) Set to 'Location'.
- 6) Set to 'Reservation Level'.
- 7) Set to 'Pricing Level'.
- 8) Set to 'Flag Complete'.
- 9) Set to 'Main Product'.
- 10) Set to 'Color'.
- 11) Set to 'Size'.
- 12) Set to 'Characteristics'.
- 13) Set to 'Split to PurchaseOrderLine' .
- 14) Set to 'General Reference'.
- 15) Set to 'Packaging' if Classification/Codes/Code is PACT.
- 16) Set to 'Manufacturer if Classification/Codes/Code is PROD.
- 17) Set to 'Customers Order Number' if Classification/Codes/Code is CUOR.
- 18) Set to 'Tax Code' if Classification/Codes/Code is TAXC.
- 19) Set to 'VAT Code' if Classification/Codes/Code is VTCD.
- 20) Set to 'Pickup Address' if Classification/Codes/Code is PIAD.
- 21) Set to 'Harbor Airports' if Classification/Codes/Code is HAFE. Set to 'Harbor Airports Description' if Classification/Codes/Code is TX40.

Set to 'Harbor Airports Name' if Classification/Codes/Code is TX15. 22) Set to 'Place Of Load' if Classification/Codes/Code is SDES. Set to 'Place Of Load Description' if Classification/Codes/Code is TX40.

Set to 'Place Of Load Name' if Classification/Codes/Code is TX15. 23) Set to 'Confirmed Pickup Address' if Classification/Codes/Code is CIAD.

24) Set to 'Confirmed Place Of Load' if Classification/Codes/Code is CDES.

PurchaseOrder/PurchaseOrderLine/Classification/Description

1) MPDOPT.PFTX30 PDS050MI/Get

2) CSYTAB.CTTX40 CRS175MI/GetGeneralCode

3) CSYTAB.CTTX40 CRS030M/.GetBasicData 1) The field indicates the option (Color, Size, Characteristics) description.

Use values of COLO, SIZE or CHCS as input to OPTN.

- 2) The field indicates the Tax Code description.
- 3) The field indicates the VAT Code description.

PurchaseOrder/PurchaseOrderLine/DropShipIndicator

MPLINE.IBGETY; PPS200MI/GetLine

The field is set to true if the PO line is generated from a customer order direct delivery (GETY = 24). Otherwise, the field is set to false.

QualitySpecification

Quanty Specification	
QualitySpecification/QualitySpecificationHeader/SpecificationID/ID MPDIID.PIINSI MPDIID.PISTRT MPDIID.PISUFI.; /	The field indicates the unique inspection ID. It is a concatenation of Inspection identity (INSI) <15> + Product structure type (STRT) <3> + Service (SUFI) <20> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with
	spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case SUFI, is trimmed if it does not consume the maximum length.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; / @variationID	The field indicates the company and division, displayed as CONO_DIVI.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
QualitySpecification/QualitySpecificationHeader/Description MPDIID.PITX40; PDS040MI/Get	The field indicates that inspection description.
QualitySpecification/QualitySpecificationHeader/Note MPDIID.PITXID; CRS980MI/SeITxtBlocks @noteID	The field indicates the text block.
?CSYTXH.?THTXID? ?CSYTXH.?THTXVR ?CSYTXL.??TLLINO?.; CRS980MI/SelTxtBlocks	The field indicates the text ID of the text block. It is a concatenation of ?Text identity? (TXID?) <13> + ?Text block? (TXVR?) <10> + ? Line number? (LINO?) <3> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case LINO?, is trimmed if it does not consume the maximum length. Text block (TXVR?) is an optional identity for texts that can be entered for most objects in M3 with a maximum of 10 positions. For each block an optional text can be stored.
CSYTXH.LNCD; CRS980MI/SelTxtBlocks QualitySpecification/QualitySpecificationHeader/EffectiveTimePeriod	The field indicates the language of the text block. //StartDateTime
MPDIID.PIVFDT; PDS040MI/Get	The field indicates the effectivity start date.
QualitySpecification/QualitySpecificationHeader/EffectiveTimePeriod MPDIID.PIVTDT; PDS040MI/Get	The field indicates the effectivity end date.
QualitySpecification/QualitySpecificationHeader/Name MPDIID.PITX15; PDS040MI/Get	The field indicates the inspection name.
QualitySpecification/QualitySpecificationLine/LineNumber MPDIIL.PJSPOS; PDS041MI/Lst	The field indicates the line number.
QualitySpecification/QualitySpecificationLine/Note CSYTXL.TLTX60; CRS980MI/SelTxtBlocks @noteID	The field indicates the text block.
?CSYTXH.?THTXID? ?CSYTXH.??THTXVR ?CSYTXL.??TLLINO?.; CRS980MI/SelTxtBlocks	The field indicates the text ID of the text block. It is a concatenation of ?Text identity? (TXID?) <13> + ?Text block? (TXVR?) <10> + ? Line number? (LINO?) <3> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this cast LINO?, is trimmed if it does not consume the maximum length. Text block (TXVR?) is an optional identity for texts that can be entered for most objects in M3 with a maximum of 10 positions. For each block an optional text can be stored.
@languagelD CSYTXH.LNCD; CRS980MI/SelTxtBlocks	The field indicates the language of the text block.
QualitySpecification/QualitySpecificationLine/QualityTest/IDs/ID MPDIIL.PJRSIY; PDS041MI/Lst	The field indicates a specific ID for a Quality Inspection Result.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
QualitySpecification/QualitySpecificationLine/QualityTest/Description MPDIIL.PJTX40; PDS041MI/Lst	-
QualitySpecification/QualitySpecificationLine/QualityTest/ValueLimit MPDIIL.PJEVAL,	/Limit The field indicates the value of:
PJRBFR, PJRBTO,	Expected value
PJEAFR, PJEATO, PJAAFR, PJAATO, PJAATR; PDS041MI/Lst	Range value (Minimum and Maximum) External limit (ExternalMinimum and ExternalMaximum) Alarm limit (AlarmMinimum and AlarmMaximum) Trand limit
QualitySpecification/QualitySpecificationLine/QualityTest/ValueLimit MPDIIL.PJEVAL,	Trend limit //ValueOperator

QualitySpecification

PJOPE1, PJOPE2, PJOPE3, PJOPE4, PJOPE5, PJOPE6, PJOPE7; PDS041MI/Lst

The field indicates the operators.

Set to "Target" if EVAL is set.
Set to "Minimum" if operator is OPE1.
Set to "Maximum" if operator is OPE2.
Set to "ExternalMinimum" if operator is OPE3.
Set to "ExternalMaximum" if operator is OPE4.
Set to "AlarmMinimum" if operator is OPE5.
Set to "AlarmMaximum" if operator is OPE6.
Set to "ExternalTarget" if operator is OPE7.

QualityTestMaster

QualityTestMaster/IDs/ID MPDIRE.PKRSIY, PKSTRT, PKSUFI; PDS042MI/Get	The field indicates a specific ID for a Quality Inspection Result. It is a concatenation of Result Identity (RSIY) <15> + Product structure type (STRT) <3> + Service (SUFI) <20> without separator. The position of each field is determined by its maximum length, specified in brackets. If it is the last field with data in the ID, it is trimmed. Otherwise, it is filled-up with spaces to consume the maximum length.
@accountingEntity	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
QualityTestMaster/LastModificationDateTime MPDIRE.PKLMTS; /	The field indicates the date and time the record was last modified. The value is retrieved from the event data.
QualityTestMaster/LastModificationPerson/IDs/ID MPDIRE.PKCHID; /	The field indicates the user ID of the last person who modified the record. The value is retrieved from the event data.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
QualityTestMaster/DocumentDateTime MPDIRE.PKRGDT MPDIRE.PKRGTM.; /	The field indicates the record's entry date and time.
QualityTestMaster/Description MPDIRE.PKTX40; PDS042MI/Get	The field indicates the description.
QualityTestMaster/Note MPDIRE.PKTX60; CRS980MI/SItTxtBlock @noteID	The field indicates the notes.
?CSYTXH.?THTXID? ?CSYTXH.??THTXVR ?CSYTXL.??TLLINO?.; CRS980MI/SltTxtBlock	The field indicates note ID. It is a concatenation of ?Text identity? (TXID?) <13> + ?Text block? (TXVR?) <10> + ?Line number? (LINO?) <3> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the document ID except for the last one. The last field in the concatenation, in this case LINO?, is trimmed if it does not consume the maximum length. Text block (TXVR?) is an optional identity for texts that can be entered for most objects in M3 with a maximum of 10 positions. For each block an optional text can be stored.
@languageID CSYTXH.LNCD; CRS980MI/SltTxtBlock	The field indicates the language of the notes.
QualityTestMaster/TestValueTypeCode MPDIRE.PKRSTE; PDS042MI/Get	The field indicates the Result type (RSTE), how a result is entered: 1 = Numeric result with limit 2 = Alphanumeric result with limit 3 = Numeric result in a table 4 = Alphanumeric result in a table
QualityTestMaster/SignificantDigits MPDIRE.PKDCCD; PDS042MI/Get	The field indicates the number of decimals.
QualityTestMaster/ValueLimit/Limit MPDIRE.PKEVAL, PKRBFR, PKRBTO, PKEAFR, PKEATO, PKAAFR, PKAATO, PKAATR; PDS042MI/Lst	The field indicates the value of:
QualityTestMaster/ValueLimit/ValueOperator MPDIRE.PKEVAL, PKOPE1, PKOPE2, PKOPE3, PKOPE4, PKOPE5, PKOPE6, PKOPE7; PDS042MI/Lst	The field indicates the operators. Set to "Target" if EVAL is set. Set to "Minimum" if operator is OPE1. Set to "Maximum" if operator is OPE2. Set to "ExternalMinimum" if operator is OPE3. Set to "ExternalMaximum" if operator is OPE4. Set to "AlarmMinimum" if operator is OPE5. Set to "AlarmMaximum" if operator is OPE6. Set to "ExternalTarget" if operator is OPE7.

Quote/QuoteHeader/DocumentID/ID OOQUOH.OFORNO ; OIS100MI/GetQuot	The field indicates the sales quotation order number.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@variationID	The field indicates the sequence number that identifies the number of
@lid	times that the BOD, for this object has been published.
Quote/QuoteHeader/AlternateDocumentID/ID	The field indicates the logical ID of the system.
1) OOHEAD.OACUOR; OIS100MI/GetHead 2) OXHEAD.OAORNO; OIS275MI/GetTmpOrderStat.; /	The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents.
·	The field indicates the temporary customer order number created in Batch Customer Order module in M3.
@schemeName	The field indicates a fixed value 'Customer'
@accountingEntity OOQUOH.QFCONO	The field indicates the company and division.
OOQUOH.QFDIVI.; /	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760_AAA
Quote/QuoteHeader/LastModificationDateTime OOHEAD	The field indicates when a change was made to the record.
OOQUOH.OALMTS QFLMDT; /	If Timestamp (LMTS) is not available, use Change date (LMDT).
Quote/QuoteHeader/LastModificationPerson/IDs/ID OOHEAD OOQOUH.OACHID QFCHID; /	The field indicates the ID of the person who last modified the record.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
Quote/QuoteHeader/DocumentDateTime OOQUOH.QFRGDT OOQUOH.QFRGTM .; OIS100MI/GetQuot	The field indicates the date and time the document was created.
Quote/QuoteHeader/Note OSYTXH.THTX60; OIS100MI/LstHeadText @noteID	The field indicates the note.
OSYTXH.THTXVR; OIS100MI/LstHeadText	The field indicates the note ID.
@use CSYTXH.THTXEI; CRS980MI/LstTxtBlocks	The field indicates the internal or external text indicator. If TXEI is 0 or 1, set to 'External'. If TXEI is 2, set to 'Internal'.
@type	The field indicates the type of note. If Type of text (TYTR) = 1, set to 'Pre-text'. If Type of text (TYTR) = 2, set to 'Post-text'. If Type of text (TYTR) = 3, set to 'Text'.
Quote/QuoteHeader/Status/Code OOQUOH.QFSTAT	The field indicates the quote status.
; OIS100MI/GetQuot	10 - Unapproved 20 - Open 30 - Lost 40 - Open 50 - Accepted 60 - Awarded 90 - Deleted
Quote/QuoteHeader/CustomerParty/PartyIDs/ID OQUOH.OFCUNO ; OIS100MI/GetQuot	The field indicates the customer.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the accounting entity.
	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
Quote/QuoteHeader/CustomerParty/Name OCUSMA.OKCUNM ; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.

Quote/QuoteHeader/CustomerParty/Location/Address @type	
	The field indicates the address type. Set to 'text'.
Quote/QuoteHeader/CustomerParty/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4 .; CRS610MI/GetBasicData	The field indicates an address line.
@sequence	The field indicates the address line sequence number.
Quote/QuoteHeader/CustomerParty/Location/Address/CityName OCUSMA.OKTOWN : CRS610MI/GetBasicData	The field indicates the city.
Quote/QuoteHeader/CustomerParty/Location/Address/CountrySubDiv OCUSMA.OKECAR ; CRS610MI/GetBasicData @listID	risionCode The field indicates the country subdivision code.
<u>9</u>	The field indicates the country subdivision code listID.
	Set to 'US States' if country is US. Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR. Else, set to 'SubDivisions - <country>'. Retrieve country using CRS610MI/GetBasicData CSCD.</country>
Quote/QuoteHeader/CustomerParty/Location/Address/CountryCode OCUSMA.OKCSCD ; CRS610MI/GetBasicData @listID	The field indicates the country code.
	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteHeader/CustomerParty/Location/Address/PostalCode OCUSMA.OKPONO ; CRS610MI/GetBasciData	The field indicates a postal code for a specific address.
	The postal code is an address element that can be part of an address line if address formatting rules are used.
Quote/QuoteHeader/CustomerParty/Communication @preferredIndicator	Set to 'false'.
Quote/QuoteHeader/CustomerParty/Communication/ChannelCode	Set Telephone number 1 to 'Phone'. Set Telephone number 2 to 'Phone'. Set Facsimile number to'Fax'.
@listID	Set E-Mail address to EMail'.
Ouate/OuateHanday/CuatemayParty/Communication/HanCada	Set to 'Communication Channels'.
Quote/QuoteHeader/CustomerParty/Communication/UseCode	Set Telephone number 1 to 'Office'. Set Telephone number 2 to 'Office'. Set Facsimile number to 'Fax'. Set E-Mail address to 'Office'.
@listID	Set to 'Communication Use Codes'.
Quote/QuoteHeader/CustomerParty/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO.; CRS610MI/GetBasicData	The field indicates the telephone and facsimile transmission number of the customer. PHNO - Telephone no 1 PHN2 - Telephone no 2 TFNO - Facsimile number
Quote/QuoteHeader/CustomerParty/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData	The field indicates the customer's e-mail address.
Quote/QuoteHeader/CustomerParty/Communication/Preference/Indica	ator Set to false.
Quote/QuoteHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE ; CMS055MI/LstByCustomer	The field indicates the customer contact id.
	Use CUNO and ADRT=0 as input.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI E.g. 760_AAA
Quote/QuoteHeader/CustomerParty/Contact/Name CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.

@preferredIndicator	Set to 'false'.
Quote/QuoteHeader/CustomerParty/Contact/Communication/Channe	
, , , , , , , , , , , , , , , , , , ,	Set Telephone number 1 to 'Phone'.
	Set Telephone number 2 to 'Phone'.
	Set E-Mail address to'EMail'.
DlistID	
	Set to 'Communication Channels'.
Quote/QuoteHeader/CustomerParty/Contact/Communication/UseCo	de
•	Set Telephone number 1 to 'Office'.
	Set Telephone number 2 to 'Office'.
	Set E-Mail address to 'Office'.
@listID	
	Set to 'Communication Use Codes'.
Quote/QuoteHeader/CustomerParty/Contact/Communication/DialNu	mber
CCUCON.OKPHNO	The field indicates the telephone number of the customer contact.
CCUCON.OKPHN2	PHNO - Telephone no 1
.; CRS618MI/Get	PHN2 - Telephone no 2
Quote/QuoteHeader/CustomerParty/Contact/Communication/URI	
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the customer contact's e-mail address.
Quote/QuoteHeader/CustomerParty/Contact/Communication/Prefere	ence/Indicator Set to false.
2	UEL IU 1013C.
Quote/QuoteHeader/ShipToParty/PartyIDs/ID	The field indicates the ship to party. If Address ID (ADID) is 11.1.1.
OOHEAD.OADECU; OIS100MI/GetAddress	The field indicates the ship to party. If Address ID (ADID) is blank in the order header, ShipToPartyID = DECU else ShipToPartyID =
OIO IUUIVII/GEIAUUIESS	DECU+ADID. DECU and ADID will be concatenated without
OOHEAD.OAADID;	separator. DECU has exactly 10 characters while ADID can have
OIS100MI/GeOrdertHead.	maximum of 6.
:/	maximum or o.
@accountingEntity	
OOQUOH.QFCONO	The field indicates the accounting entity.
OOQUOH.QFDIVI.; /	ů,
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab,
	this is displayed as Company (CONO), e.g. 760. Otherwise, this is
	displayed as Company and Division (CONO_DIVI), e.g. 760_AAA.
Quote/QuoteHeader/ShipToParty/Name	
OOADRE.ODCUNM;	The field indicates the customer name, which is used as
OIS100MI/GetAddress	complementary information to the customer number on panels and
	documents.
OCUSAD.OPCUNM;	MOLET BOARD AND AND AND AND AND AND AND AND AND AN
CRS610MI/GetAddress.; /	If ShipToParty/PartyIDs/ID = DECU, use CRS610MI GetBasicData
	with CUNO = DECU as input.
	If ShipToParty/PartyIDs/ID = DECU+ADID, use CRS610MI
	GetAddress with CUNO = DECU, ADRT=1 and ADIDas inputs.
Quote/QuoteHeader/ShipToParty/Location/Address	
@type	
5n ·	The field indicates the address type. Set to 'text'.
Quote/QuoteHeader/ShipToParty/Location/Address/AddressLine	
OOADRE.ODCUA1	The field indicates the address line.
OOADRE.ODCUA2	maiotico tro addicoo into.
OOADRE.ODCUA3	If ShipToParty/PartyIDs/ID = DECU, use OIS100MI GetAddress for
OOADRE.ODCUA4;	Location/Address elements.
OIS100MI/GetAddress	
	If ShipToParty/PartyIDs/ID = DECU+ADID, use CRS610MI
OCUSAD.OPCUA1	GetAddress with CUNO=DECU, ADRT=1 and ADID for Location/
OCUSAD.OPCUA2	Address elements.
OCUSAD.OPCUA3	
OCUSAD.OPCUA4;	
CRS610MI/GetAddress	
.; /	
<u>@</u> sequence	The field indicates the address line sequence number.
Quote/QuoteHeader/ShipToParty/Location/Address/CityName	The hold indicates the address line sequence number.
Quote/QuoteHeader/Snip1oParty/Location/Address/CityName OOADRE.ODTOWN:	The field indicates the city.
OIS100MI/GetAddress	The hold indicates the city.
CIC TOOIVII/ OCUMUNICOS	
OCUSAD.OPTOWN;	
CRS610MI/GetAddress	
J. 123 . Olili, God (adi 000	
.; /	
.;/ Quote/QuoteHeader/ShipToPartv/Location/Address/CountrvSubDivi	sionCode
.;/ Quote/QuoteHeader/ShipToParty/Location/Address/CountrySubDivis OOADRE.ODECAR:	
.;/ Quote/QuoteHeader/ShipToParty/Location/Address/CountrySubDivision OOADRE.ODECAR; OIS100MI/GetAddress	sionCode The field indicates the country subdivision code.
OOADRE.ODECAR;	

CRS610MI/GetAddress.; /	
@listID	The field indicates the country subdivision code listID.
	The field indicates the country subdivision code listib.
	Set to 'US States' if country is US.
	Set to 'Canadian Provinces' if country is CA.
	Set to 'France - Departements' if country is FR. Else, set to 'SubDivisions - <country>'. Retrieve country using</country>
	OIS100MI/GetAddress or CRS610MI/GetAddress CSCD.
Quote/QuoteHeader/ShipToParty/Location/Address/CountryCode	
OOADRE.ODCSCD;	The field indicates the country code.
OIS100MI/GetAddress	
OCUSAD.OPCSCD;	
CRS610MI/GetAddress .; /	
@listID	
Ouata/Ouatallanday/Ohin Ta Payty/l anatian/Address/DagtalCada	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteHeader/ShipToParty/Location/Address/PostalCode OOADRE.ODPONO:	The field indicates a postal code for a appoint address
OUADRE.ODPONO; OIS100MI/GetAddress	The field indicates a postal code for a specific address.
Old Tourin/Get/Address	The postal code is an address element that can be part of an address
OCUSAD.OPPONO;	line if address formatting rules are used.
CRS610MI/GetAddress.; /	
Quote/QuoteHeader/ShipToParty/Communication @preferredIndicator	
wp. o.c., cumuloutor	Set to 'false'.
Quote/QuoteHeader/ShipToParty/Communication/ChannelCode	
• •	Set to 'Phone' if Telephone number 1.
- W - W-	Set to 'Fax' if Facsimile number.
@listID	Set to 'Communication Channels'.
Quote/QuoteHeader/ShipToParty/Communication/UseCode	Oct to Communication Chambers.
Quote/Quoterreader/3mp10Farty/Communication/oseCode	Set to 'Office' if the field Telephone number 1.
	Set to 'Fax' if the Facsimile number.
@listID	Out to 10 annumination Has Out to 1
Quote/QuoteHeader/ShipToParty/Communication/DialNumber	Set to 'Communication Use Codes'
OOADRE.OPPHNO	The field indicates the telephone/telefax number of the customer.
OOADRE.OPTFNO	PHN0 is phone numbers.
.; OIS100MI/GetAddress	TFNO is fax number.
Quote/QuoteHeader/ShipToParty/Contact/ID	
OCUSCO.CCCNPE	The field indicates the customer contact id.
; CMS055MI/LstByCustomer	Use CUNO=DECU and ADRT=1 as input.
@accountingEntity	Ose CONO-DECO and ADIXI-1 as input.
OOQUOH.QFCONO	The field indicates the company and division.
OOQUOH.QFDIVI.; /	
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI E.g. 760 AAA
Quote/QuoteHeader/ShipFromParty/Location	W
@type	4) 0 11 114 1
	1) Set to 'Warehouse' 2) Set to 'Site'
Quote/QuoteHeader/ShipFromParty/Location/ID	2) OGLIO OIIG
Quote/QuoteHeader/Snip+romParty/Location/ID 1) OOHEAD.OAWHO	The field indicates the warehouse.
2) OOHEAD.OAFACI.; OIS100MI/GetOrderHead	The hold indicates the walchouse.
@accountingEntity	
OOQUOH.QFCONO	The field indicates the company and division.
OOQUOH.QFDIVI.; /	Accounting Entity for M3 is defaulted as a combination of CONO. DN//
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI E.g. 760 AAA
Quote/QuoteHeader/ShipFromParty/Location/Name	
MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates the warehouse name.
Quote/QuoteHeader/ShipFromParty/Location/Address	
@type	Set to 'text'.
Quote/QuoteHeader/ShipFromParty/Location/Address/AddressLine	
CIADDR.OAADR1	The field indicates the warehouse address.
CIADDR.OAADR2	
CIADDR.OAADR3	
CIADDR.OAADR4	
.; CRS235MI/Get @sequence	
@ssqus.100	The field indicates the address line number.
Infor May 26, 20	023 47
100 / V	46.1

Quote/QuoteHeader/ShipFromParty/Location/Address/CityName CIADDR.OATOWN; CRS235MI/Get	The field indicates the city.
Quote/QuoteHeader/ShipFromParty/Location/Address/CountrySubDiv CIADDR.OAECAR; CRS235MI/Get	·
@listID	The field indicates the country subdivision code listID.
	Set to 'US States' if country is US.
	Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR.
	Else, set to 'SubDivisions - <country>'. Retrieve country using</country>
	MMS005MI/GetWarehouse CSCD.
Quote/QuoteHeader/ShipFromParty/Location/Address/CountryCode CIADDR.OACSCD; CRS235MI/Get @listID	The field indicates the country.
	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteHeader/ShipFromParty/Location/Address/PostalCode CIADDR.OAPONO; CRS235MI/Get	The field indicates the postal code.
Quote/QuoteHeader/ShipFromParty/Communication @preferredIndicator	
Out to 10 and a 11 and a 110 bits Fire and Points 10 and a 10 and	Set to 'false'.
Quote/QuoteHeader/ShipFromParty/Communication/ChannelCode @listID	Set Telephone number to 'Phone'.
<u> </u>	Set to 'Communication Channels'.
Quote/QuoteHeader/ShipFromParty/Communication/UseCode	Set Telephone number to 'Office'.
@listID	Set to 'Communication Use Codes'.
Quote/QuoteHeader/ShipFromParty/Communication/DialNumber MITWHL.MWPHNO; MMS005MI/GetWarehouse	The field indicates the telephone number.
Quote/QuoteHeader/ShipFromParty/Communication/Preference/Indic	ator Set to false.
Quote/QuoteHeader/ShipFromParty/Contact/ID MITWHL.MWRESP; MMS005MI/GetWarehouse @accountingEntity	The field indicates the warehouse responsible.
waccounting Emity	The field indicates the company and division, displayed as CONO DIVI.
Quote/QuoteHeader/ExtendedAmount	
OOHEAD.OANTAM ; OIS100MI/GetOrderHead	The field indicates the net order value, including any discounts, expressed in the domestic currency.
	No charges is included in the amount.
@currencyID	The field indicates the abbreviation for the currency. The abbreviation
OOHEAD.OACUCD ; OIS100MI/GetOrderHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
Quote/QuoteHeader/TotalAmount OOHEAD.OATOPY : OIS100MI/GetOrderValue	The field indicates the total amount.
@currencyID	· · · · · · · · · · · · · · · · · ·
OOHEAD.OACUCD ; OIS100MI/GetOrderHead	The field indicates the abbreviation for the currency. The abbreviation should follow ISO standards.
Quote/QuoteHeader/BillToParty/PartyIDs/ID OOHEAD.OAINRC ; OIS100MI/GetOrderHead	The field indicates the number of the customer who receives the invoice.
	The information is specified for each payer in the customer file. It is copied to the order header via the payer used when entering new
@accountingEntity	orders.
OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the accounting entity.
	If BillToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
Quote/QuoteHeader/BillToParty/Name OCUSMA.OKCUNM ; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
	Use CUNO = INRC as input
Quote/QuoteHeader/BillToParty/Location/Address @type	
<i>-</i>	The field indicates the address type. Set to 'text'.

\sim			4	
11		\sim	•	^
w	u	u	L	C

OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4 .; CRS610MI/GetBasicData	The field indicates the address line.
@sequence	The field indicates the address line assurance assurance
Quote/QuoteHeader/BillToParty/Location/Address/CityName OCUSMA.OKTOWN ; CRS610MI/GetBasicData	The field indicates the address line sequence number. The field indicates the city.
Quote/QuoteHeader/BillToParty/Location/Address/CountrySubDivisio OCUSMA.OKECAR ; CRS610MI/GetBasicData @/listID	nCode The field indicates the country subdivision code.
<u>@113412</u>	The field indicates the country subdivision code listID.
	Set to 'US States' if country is US. Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR. Else, set to 'SubDivisions - <country>'. Retrieve country using CRS610MI/GetBasicData CSCD.</country>
Quote/QuoteHeader/BillToParty/Location/Address/CountryCode OCUSMA.OKCSCD ; CRS610MI/GetBasicData	The field indicates the country.
@listID	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteHeader/BillToParty/Location/Address/PostalCode OCUSMA.OKPONO ; CRS610MI/GetBasciData	The field indicates the postal code.
Quote/QuoteHeader/BillToParty/Contact/ID OCUSCO.CCCNPE ; CMS055MI/LstByCustomer	The field indicates the customer contact id.
•	Use CUNO=INRC and ADRT=3 as input.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division.
OOQUUT.QI DIVI.,7	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760_AAA
Quote/QuoteHeader/PayFromParty/PartyIDs/ID OOHEAD.OAPYNO ; OIS100MI/GetOrderHead	The field indicates the person/business who has paid or will pay the invoice.
	The payer is specified when an invoice should be sent somewhere other than to the customer placing the order.
	For order and sales statistics, the payer is used as a statistic ID. For total statistics, the payer is one of the key IDs.
@accountingEntity OOQUOH.QFCONO	The field indicates the accounting entity.
OOQUOH.QFDIVI.; /	If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
Quote/QuoteHeader/PayFromParty/Name OCUSMA.OKCUNM ; CRS610MI/GetBasicData	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
	Use CUNO = PYNO as input.
Quote/QuoteHeader/PayFromParty/Location	
@type	Set to 'text'.
Quote/QuoteHeader/PayFromParty/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4 .; CRS610MI/GetBasicData	The field indicates an address line.
@sequence	The field indicates the address line sequence number.
Quote/QuoteHeader/PayFromParty/Location/Address/CityName	·
OCUSMA.OKTOWN ; CRS610MI/GetBasicData	The field indicates the city.

; CRS610MI/GetBasicData	
@listID	The field indicates the country subdivision code listID.
	Set to 'US States' if country is US. Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR. Else, set to 'SubDivisions - <country>'. Retrieve country using CRS610MI/GetBasicData CSCD.</country>
Quote/QuoteHeader/PayFromParty/Location/Address/CountryCode OCUSMA.OKCSCD ; CRS610MI/GetBasicData @listID	The field indicates a country.
	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteHeader/PayFromParty/Location/Address/PostalCode OCUSMA.OKPONO ; CRS610MI/GetBasciData	The field indicates the postal code.
Quote/QuoteHeader/PayFromParty/Contact/ID OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the customer contact id.
Raccounting Entity	Use CUNO=PYNO and ADRT=4 as input.
@accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division.
Quote/QuoteHeader/TransportationTerm/IncotermsCode OOHEAD.OATEDL; OIS100MI/GetOrderHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
@listID	Set to 'Incoterms'.
Quote/QuoteHeader/TransportationMethodCode OAHEAD.OAMODL; OIS100MI/GetOrderHead @ <i>listID</i>	The field indicates the transportation method.
	Set to 'Transportation Methods'.
Quote/QuoteHeader/DistributedCharge/Description OOCHRG.OECRDO; OIS100MI /LstOrderCharges	The field indicates the header charge description.
Quote/QuoteHeader/DistributedCharge/Amount OOCHRG.OEPBAM; OIS100MI /LstOrderCharges @currencyID	The field indicates the header charge amount.
OOCHRG.OECUCD; OIS100MI/LstOrderCharges	The field indicates the Currency
Quote/QuoteHeader/DistributedCharge/ReasonCode OOCHRG.OECRD0; OIS100MI/LstOrderCharges @listID	The field indicates the header charge description.
	Set to "Reasons for Charge".
Quote/QuoteHeader/DistributedCharge/GrossWeightIndicator	Set to "false".
Quote/QuoteHeader/DistributedTax @type	Set to 'VAT' if tax method is 1 or 4. Set to 'Sales Tax' if tax method is 2 or 3.
Quote/QuoteHeader/DistributedTax/ID	Set to 'Tax'.
Quote/QuoteHeader/DistributedTax/Description	Set to 'Tax'.
Quote/QuoteHeader/DistributedTax/Amount OOHEAD.OAVTAM; OIS100MI/GetOrderValue @currencyID	The field indicates the Tax amount
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the currency
Quote/QuoteHeader/RFQReference/DocumentID/ID OOHEAD.OAOFNO; OIS100MI/GetOrderHead	The field indicates a reference to the quotation number belonging to a customer order, service order or agreement.
@accountingEntity OOQUOH.OFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division.
Quote/QuoteHeader/PaymentMethodCode OAHEAD.OAPYCD; OIS100MI/GetOrderHead	The field indicates the payment method code. The payment method code is translated in CRS881.
Quote/QuoteHeader/EffectiveTimePeriod/EndDateTime OOQUOH.QFGIDT ; OIS100MI/GetQuot	The field indicates how long a quotation is valid.
Quote/QuoteHeader/UserArea	

Quote	
2) OOQUOH.QFFFI1 / OIS100MI.GetQuot	 Set attribute name to 'AttentionOfName'. Set attribute name to 'QuoteFreeField1'.
3) OOQUOH.QFFFI2 / OIS100MI.GetQuot	3) Set attribute name to 'QuoteFreeField2'.4) Set attribute name to 'QuoteFreeField3'.
4) OOQUOH.QFFFI3 / OIS100MI.GetQuot	5) Set attribute name to 'QuoteFreeField4'.6) Set attribute name to 'QuoteFreeField5'.
5) OOQUOH.QFFFI4 / OIS100MI.GetQuot	7) Set attribute name to 'QuoteFreeField6'.
6) OOQUOH.QFFFI5 / OIS100MI.GetQuot	
7) OOQUOH.QFFFI6 / OIS100MI.GetQuot.; /	
Quote/QuoteHeader/RequiredDeliveryDateTime OAHEAD.OARLDZ+OARLHZ; OIS100MI/GetOrderHead	The field indicates the required delivery date time.
Quote/QuoteHeader/ExpectedDeliveryDate	·
OOHEAD.OARLDZ; OIS100MI/GetOrderHead	The field indicates the date the customer wants the delivery to arrive at the final destination.
	The information is expressed in the time zone of the unloading location at the final destination.
	If the loading and unloading locations are in different time zones, this date can be different from what applies for the local time zone.
Quote/QuoteHeader/Charge/Description	TI 6 11: P 4 4 4 1 1 2 P
OOCHRG.OECRDO; OIS100MI /LstOrderCharges	The field indicates the charge description: If Line Charge
/Latoruer Orlanges	Order Discount
	Service Charge
	Header Charges Rounding off
Quote/QuoteHeader/Charge/Amount	rounding on
OOCHRG.OEPBAM	The field indicates the distributed amount for the ff:
OOHEAD.ODAM	Line Charge
OHEAD.OAEXAM OOHEAD.OAROAM.; OIS100MI	Order Discount Service Charge
/LstOrderCharges	Header Charges
GetLineChrgTot	Rounding off
GetOrderValue GetOrderValue	
@currencyID OOCHRG.OECUCD; OIS100MI/LstOrderCharges	The field indicates the Currency
Quote/QuoteHeader/Charge/ReasonCode	The field indicates the outrolley
OOCHRG.OECRD0; OIS100MI/LstOrderCharges	The field indicates the charge description:
	Header Charges
	Line Charge Order Discount
	Service Charge
	Rounding off
@listID	The field indicates the change description.
OOCHRG.OECRD0; OIS100MI/LstOrderCharges	The field indicates the charge description: Line Charge
	Order Discount
	Service Charge
	Header Charges Rounding off
Quote/QuoteHeader/Charge/GrossWeightIndicator	Rounding on
	Set to 'false'.
Quote/QuoteHeader/Classification/Codes/Code 1) OAHEAD.OAORTP	1) Order Type
OIS100MI/GetOrderHead	The field indicates the Order type.
2) OOQUOH.QFORCD	2) Quotation reason
OIS100MI/GetQuot	The field indicates why a quotation was given to a customer or why it
3) 000H0H 0FBVC4	did not result in an order.
3) OOQUOH.QFBVC1 OIS100MI/GetQuot	3) Follow-up activity 1
STO TOOMIN OCTORUOT	The field indicates which follow-up activity to be performed for a
4) OOQUOH. QFBVC2	quotation.
OIS100MI/GetQuot	1) Follow up activity 2
5) OOHEAD.OAFRE1	Follow-up activity 2 The field indicates which follow-up activity to be performed for a
OIS100MI/GetOrderHead.; /	quotation.
	5) Statistics Identity 1 Customer
	The field indicates a user-defined customer statistics accumulator.
@listID	Set attribute listID to 'Customer Statistics Identity1'.
wiisab	

Quote	
	1) Set to 'Order Types'. 2) Set to 'Quotation Reasons'. 3) Set to 'Follow-up Activity 1'. 4) Set to 'Follow-up Activity 2'.
Quote/QuoteHeader/SalesPersonReference/IDs/ID OOHEAD.OASMCD; OIS100MI/GetOrderHead	The field indicates the person responsible for sales to a customer.
@accountingEntity OOQUOH.OFCONO OOQUOH.QFDIVI.: /	The field indicates the company and division.
Quote/QuoteHeader/SalesPersonReference/Name CSYTAB.CTTX40; CRS100MI/Get	The field indicates the sales person full name.
Quote/QuoteLine/LineNumber OOHEAD.OAPONR ; OIS100MI/LstLineBOD	The field indicates the line number, defining each line in a customer order. A line number is assigned automatically when entering order lines.
Quote/QuoteLine/Note OSYTXL.TLTX60; OIS100MI/LstLineText	The field indicates the note.
@noteID OSYTXL.TLTXVR; OIS100MI/LstHeadText	The field indicates the note ID.
@use CSYTXL.TLTXEI; CRS980MI/LstTxtBlocks	The field indicates the internal or external text indicator. If TXEI is 0 or 1, set to 'External'. If TXEI is 2, set to 'Internal'.
@type	If Type of text (TYTR) = 1, set to 'Pre-text'. If Type of text (TYTR) = 2, set to 'Post-text'. If Type of text (TYTR) = 3, set to 'Text'.
Quote/QuoteLine/Status/Code OOQUOH.QFSTAT; OIS100MI/GetQuot	The field indicates the quote status.
	10 - Unapproved 20 - Open 30 - Lost 40 - Open 50 - Accepted 60 - Awarded 90 - Deleted
Quote/QuoteLine/Item/ItemID/ID OOLINE.OBITNO ; OIS100MI/LstLineBOD	The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item.
@accountingEntity OOQUOH.OFCONO OOQUOH.OFDIVI.: /	The field indicates the company and division.
Quote/QuoteLine/Item/Description OOLINE.OBITDS ; OIS100MI/LstLineBOD	The field indicates the name for each item.
Quote/QuoteLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/LstLineBOD	The field indicates the lot number.
Quote/QuoteLine/Item/SerializedLot/ProductionDate OOLINE.OBORQA ; OIS100MI/LstLineBOD	The field indicates the ordered quantity in an alternate unit of measure.
Quote/QuoteLine/Quantity @unitCode OOLINE.OBALUN ; OIS100MI/LstLineBOD	The field indicates an alternate unit of measure (U/M) for the basic U/M for an item. An unlimited number of alternate U/Ms may be defined for each item.
Quote/QuoteLine/BaseUOMQuantity OOLINE.OBORQT ; OIS100MI/LstLineBOD	The field indicates the ordered quantity in basic unit of measure.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the basic unit of measure.
Quote/QuoteLine/UnitPrice/Amount OOLINE.OBSAPR OIS100MI/ListLineBOD	The field indicates the sales price for each sales price quantity.
; OIS100MI/LstLineBOD	If no value is specified in the sales price quantity, the sales price per unit applies.
	The sales price per unit is calculated as: Price per unit= Sales price/ Sales price quantity.
@currencyID OOLINE.OBCUCD ; OIS100MI/LstLineBOD	The field indicates the abbreviation for the currency.
Quote/QuoteLine/UnitPrice/PerQuantity OOLINE.OBSACD	
Info	00 0000

Quote	
; OIS100MI/LstLineBOD	The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the item unit of measure.
@unitCode OOLINE.OBSPUN : OIS100MI/LstLineBOD	The field indicates the sales price U/M.
Quote/QuoteLine/ExtendedAmount .; OIS100MI/LstLineBOD	The field indicates the gross line amount.
@currencyID OOLINE.OBCUCD ; OIS100MI/LstLineBOD	The field indicates the abbreviation for the currency.
Quote/QuoteLine/ExtendedBaseAmount .; OIS100MI/LstLineBOD	The field indicates the line amount in local currency.
@currencyID OOHEAD.OALOCD ; OIS100MI/LstLineBOD	The field indicates the local currency.
Quote/QuoteLine/TotalAmount .; OIS100MI/LstLineBOD	The field indicates the net line amount.
@currencyID OOLINE.OBCUCD : OIS100MI/LstLineBOD	The field indicates the currency.
Quote/QuoteLine/RequiredDeliveryDateTime OOLINE.OBDWDZ+ OBDWHZ; OIS100MI/LstLineBOD	The field indicates the Requested Delivery date
Quote/QuoteLine/ShipToParty/PartyIDs/ID OOLINE.OBDECU; OIS100MI/LstLineBOD OOADRE.ODADID; OIS100MI/GetLineAddress.	The field indicates the ship to party. If Address ID (ADID) is blank in the order line, ShipToPartyID = DECU else ShipToPartyID = DECU+ADID. DECU and ADID will be concatenated without separator. DECU has exactly 10 characters while ADID can have maximum of 6.
; / @accountingEntity OOQUOH.QFCONO OOQUOH.QFDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
Quote/QuoteLine/ShipToParty/Name OOADRE.ODCUNM; OIS100MI/GetLineAddress	The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
OCUSAD.OPCUNM; CRS610MI/GetAddress.; /	If ShipToParty/PartyIDs/ID = DECU, use CRS610MI GetBasicData with CUNO = DECU as input.
	If ShipToParty/PartyIDs/ID = DECU+ADID, use CRS610MI GetAddress with CUNO = DECU, ADRT=1 and ADID as inputs.
Quote/QuoteLine/ShipToParty/Location/Address/AddressLine OOADRE.ODCUA1	The field indicates the address line.
OOADRE.ODCUA2 OOADRE.ODCUA3 OOADRE.ODCUA4;	If ShipToParty/PartyIDs/ID = DECU, use OIS100MI GetAddress for Location/Address elements.
OIS100MI/GetLineAddress OCUSAD.OPCUA1 OCUSAD.OPCUA2 OCUSAD.OPCUA3 OCUSAD.OPCUA4; CRS610MI/GetAddress ;,/	If ShipToParty/PartyIDs/ID = DECU+ADID, use CRS610MI GetAddress with CUNO=DECU, ADRT=1 and ADID for Location/Address elements.
@sequence	The field indicates the address line sequence number.
Quote/QuoteLine/ShipToParty/Location/Address/CityName OOADRE.ODTOWN; OIS100MI/GetLineAddress	The field indicates the city.
OCUSAD.OPTOWN; CRS610MI/GetAddress .; /	
Quote/QuoteLine/ShipToParty/Location/Address/CountrySubDivis OOADRE.ODECAR; OIS100MI/GetLineAddress	sionCode The field indicates the country subdivision code.
OCUSAD.OPECAR; CRS610MI/GetAddress.; /	
Orto rown occurations., /	2000

Oliveto	
@listID	The field indicates the country subdivision code listID.
	Set to 'US States' if country is US. Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR. Else, set to 'SubDivisions - <country>'. Retrieve country using OIS100MI/GetAddress or CRS610MI/GetAddress CSCD.</country>
Quote/QuoteLine/ShipToParty/Location/Address/CountryCode OOADRE.ODCSCD; OIS100MI/GetLineAddress	The field indicates the country code.
OCUSAD.OPCSCD; CRS610MI/GetAddress ;; /	
@listID	The field indicates the country code listID. Set to 'Countries'.
Quote/QuoteLine/ShipToParty/Location/Address/PostalCode OOADRE.ODPONO; OIS100MI/GetLineAddress	The field indicates a postal code for a specific address.
OCUSAD.OPPONO; CRS610MI/GetAddress.; /	The postal code is an address element that can be part of an address line if address formatting rules are used.
Quote/QuoteLine/ShipToParty/Communication @preferredIndicator	Sat to 'false'
Quote/QuoteLine/ShipToParty/Communication/ChannelCode	Set to 'false'.
@listID	Set to 'Phone' if Telephone number 1. Set to 'Fax' if Facsimile number.
	Set to 'Communication Channels'.
Quote/QuoteLine/ShipToParty/Communication/UseCode	Set to 'Office' if the field Telephone number 1. Set to 'Fax' if the Facsimile number.
@listID	Set to 'Communication Use Codes'
Quote/QuoteLine/ShipToParty/Communication/DialNumber	The field indicates the telephone/telefax number of the customer. PHN0 is phone numbers. TFNO is fax number.
Quote/QuoteLine/ShipToParty/Communication/Preference/Indicator	Set to 'false'.
Quote/QuoteLine/PromisedDeliveryDateTime OOLINE.OBCODZ OOLINE.OBCOHZ .; OIS100MI/LstLineBOD	The field indicates the confirmed delivery date and time.
Quote/QuoteLine/QuoteSubLine/LineNumber OOLINE.OBPOSX; OIS100MI/LstLineBOD	The field indicates the subline number
Quote/QuoteLine/QuoteSubLine/Note OSYTXL.TLTX60; OIS100MI/LstLineText @noteID	The field indicates the remarks or notes.
OSYTXL.TLTXVR; OIS100MI/LstHeadText @use	The field indicates the note ID.
CSYTXL.TLTXEI; CRS980MI/LstTxtBlocks	The field indicates the internal or external text indicator. If TXEI is 0 or 1, set to 'External'. If TXEI is 2, set to 'Internal'.
@type	The field indicates the note type. For Pre-text field, 'Pre-Text' is published. For Post-Text field, 'Post-text' is published. And for Text field, 'Text' is published
Quote/QuoteLine/QuoteSubLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLineBOD @accountingEntity	The field indicates the Item Number
OOQUOH.OFCONO, OOQUOH.QFDIVI.: /	The field indicates the company and division.
Quote/QuoteLine/QuoteSubLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItmBasic	The field indicates the Item description
Quote/QuoteLine/QuoteSubLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/LstLineBOD	The field indicates the lot number.
Quote/QuoteLine/QuoteSubLine/Quantity OOLINE.OBORQA; OIS100MI/LstLineBOD @unitCode	The field indicates the Quantity for Orderline in Basic Unit of Measure
OOLINE.OBALUN; OIS100MI/LstLineBOD	The field indicates the currency.
Quote/QuoteLine/QuoteSubLine/BaseUOMQuantity Infor May 26, 20	23 483
May 26 20	48

Quote	
OOLINE.OBORQT; OIS100MI/LstLineBOD	The field indicates the Quantity for Orderline (in Basic Unit of Measure).
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the currency.
Quote/QuoteLine/ShipFromParty/Location	······································
@type	
	Set to 'Warehouse'.
Quote/QuoteLine/ShipFromParty/Location/ID	T. 611: P. 4. W.
OOLINE.OBWHLO : OIS100MI/LstLineBOD	The field indicates the warehouse.
@accountingEntity	
OOQUOH.OFCONO,	The field indicates the company and division.
OOQUOH.QFDIVI.; /	
Quote/QuoteLine/Charge/Amount	-
OOLINE.OBDIA1 OOLINE.OBDIA2	The field indicates the discount amount
OOLINE.OBDIA3	
OOLINE.OBDIA4	
OOLINE.OBDIA5	
OOLINE.OBDIA6	
.; OIS100MI/LstLineBOD	
Quote/QuoteLine/Charge/Calculation/RateNumeric OOLINE.OBDIP1	The field indicates the discount percentage
OOLINE.OBDIP2	The field indicates the discount percentage
OOLINE.OBDIP3	
OOLINE.OBDIP4	
OOLINE OPPIPS - OIS 100M// att in a POP	
OOLINE.OBDIP6.; OIS100MI/LstLineBOD	
Quote/QuoteLine/Charge/ReasonCode	The field indicates the Discount as reason code
Quote/QuoteLine/PricingAmount/UnitBaseAmount	
OOLINE.OBSAPR; OIŠ100MI/LstLineBOD	The field indicates the sales price for each sales price quantity.
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
Quote/QuoteLine/PricingAmount/UnitPretaxAmount	The field indicates the currency
OOLINE.OBNEPR; OIS100MI/LstLineBOD	The field indicates the net price.
@currencyID	,
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
Quote/QuoteLine/PricingAmount/TotalPretaxAmount	
OOLINE.OBNLAM; OIS100MI/LstLineBOD	The field indicates the net amount
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the currency
Quote/QuoteLine/PricingAmount/TotalPretaxBaseAmount	The hold indicates the surroincy
OOLINE.OBSAAM; OIS100MI/LstLineBOD	The field indicates the line amount in local currency
@currencyID	
OOLINE.OBLOCD; OIS100MI/LstLineBOD	The field indicates the currency
Quote/QuoteLine/PricingAmount/UnitTotalAmount	
OOLINE.OBNEPR; OIŠ100MI/LstLineBOD	The field indicates the Net Line Amount (as well as currency)
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
COLINE.ODOUGD. OIG IUUIVII/LÕLLIIICDUD	THE HEIGHNICALES THE CAHEHOV

ReceivableTransaction/ReceivableTransactionHeader/DocumentID/ID	
FSLEDG.ESYEA4, ESJRNO, ESJSNO; -/-	The field indicates concatenated fields Year (YEA4, 4 digits), Journal number (JRNO, 7 digits) and Journal sequence number (JSNO, 7 digits) and Journal sequence number (JSNO, 7 digits) for the Jacobs (JSNO, 7 digits) for t
	digits) for the Invoice (TRCD = 10) or the Payment/Adjustement (TRCD = 20) transactions from the event data.
	Value populated will have a fixed length of 18 digits (4+7+7) with JRNO and JSNO padded with zeros (2019/1/1: Document ID/ID = 201900000010000001).
@accountingEntity FSLEDG.ESCONO, ESDIVI; -/-	The field indicates the company and division from the event data.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIV E.g. 760_AAA
@variationID	
; -/- @lid	The field indicates the sequence number that identifies the number of times that this BOD has been published.
⊕na ; -/-	The field indicates an information with logical ID.
ReceivableTransaction/ReceivableTransactionHeader/AlternateDocun	
FSLEDX.ESSEXI FSLEDG.ESCINO FSLEDG.ESIVTP; ARS251MI, ARS200MI/LstInvInfo, GetInvTotInfo	The field indicates the invoice number, original invoice number (SEXI) in case of split due date or invoice number (CINO).
	If ARS251MI returns a record from table FSLEDX with info category (SEXN) = 227 or 228, use additional information (SEXI) = Original invoice number, else use Invoice number (CINO).
	Note: The information is not included for On-Account payment (that is IVTP=AP).
@schemeName; -/- @accountingEntity FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvTotInfo	The field indicates the alternate document ID scheme name. Set to 'CommercialInvoice'.
	Note: The information is not included for On-Account payment (that is IVTP=AP).
	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIV E.g. 760 AAA
ReceivableTransaction/ReceivableTransactionHeader/DisplayID FSLEDG.ESCINO; ARS200MI/GetInvoice	The field indicates the invoice number (CINO).
ReceivableTransaction/ReceivableTransactionHeader/LastModificatio FSLEDG.ESLMTS; ARS200MI/GetInvTotInfo	nDateTime The field indicates the date the record was last modified.
ReceivableTransaction/ReceivableTransactionHeader/LastModificatio FSLEDG.ESCHID; ARS200MI/GetInvoice	nPerson/IDs/ID The field indicates the ID of the person that entered/changed the recored.
@accountingEntity FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvoice	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVIE.g. 760 AAA
ReceivableTransaction/ReceivableTransactionHeader/DocumentDate	
FSLEDG.ESACDT; -/-	The field indicates the accounting date (ACDT) from the event data of the invoice (TRCD = 10) or the payment (TRCD = 20).
ReceivableTransaction/ReceivableTransactionHeader/Description	The field indicates the description of the transaction has a distribution
FSLEDG.ESTDSC; ARS200MI/GetInvoice	The field indicates the description of the transaction based on the Transaction code (TRCD) from the event data with Transaction description added if available (separator 'blank' / 'blank' added
	between):If TRCD = 10: Set to 'Customer invoices - AR' / Value of TDSC if no blank
	- If TRCD = 20: Set to 'Payments received - AR' / Value of TDSC if not blank
ReceivableTransaction/ReceivableTransactionHeader/Status/Code	
FSLEDG.ESCUAM, ESIVTP, ESIIST, ESRECO; ARS200MI/GetInvTotInfo / GetInvoice	The field indicates the status of the receivable transaction: - Set to 'Paid' if: Reconciliation code (RECO) = 9 and Invoice amount

- (CUAM) != 0 and = Paid amount (PCUA) or Reconciliation code (RECO) = 9, Invoice amount (CUAM) = 0 and Interest invoice block (IIST) !=8 (zero invoice).
- Set to 'PartialPaid' if: Reconciliation code (RECO) != 9 and Paid
- amount (PCUA) != 0 and < Invoice amount (CUAM)
 Set to 'UnappliedCash' if: Reconciliation code (RECO) != 9 and Invoice type (IVTP) = AP (on account payment)
- Set to 'Applied' if: Reconciliation code (RECO) = 9 and Invoice type (IVTP) = AP (on account payment)

@accountingEntity

Neceivable Hallsaction	
	 Set to 'Void' if: Reconciliation code = 9, Interest invoice block (IIST) 8 and Transaction code (TRCD) = 10 (reversed invoice) Set to 'Open': For all other conditions
ReceivableTransaction/ReceivableTransactionHeader/Status/Effection FSLEDG.ESDTP5, ESIVDT; ARS200MI/GetInvTotInfo / GetInvoice	veDateTime The field indicates the date of the status code set: - If Status/Code = 'Paid', 'PartialPaid', 'Applied' or UnappliedCash': Set to Payment date (DTP5) If Status/Code = 'Open' or 'Void': Set to Invoice date (IVDT).
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart	
FSLEDG.ESCUNO; ARS200MI/GetInvoice	The field indicates the unique identification of a customer. It can contain up to ten positions, and is alphanumeric.
O	For temporary customers (customer type 9), the customer number must be within a defined range where only customers with customer type 9 can be entered.
@accountingEntity FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvoice	The field indicates the accounting entity.
	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKCUNM; CRS610MI/GetBasicData	ty/Name The field indicates the customer name, which is used as complementary information to the customer number on panels and documents.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart@type	ty/Location/Address
; -/-	Set to 'text'.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKYREF; CRS610MI/GetBasicData	ty/Location/Address/AttentionOfName The field indicates the customer's contact person as defined in CRS610 as your reference 1.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKCUA1, OKCUA2, OKCUA3, OKCUA4; CRS610MI/ GetBasicData @sequence	ty/Location/Address/AddressLine The field indicates the address lines.
; -/-	The field indicates the sequence number of an address.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKTOWN; CRS610MI/GetBasicData	ty/Location/Address/CityName The field indicates the city.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKECAR; CRS610MI/GetBasicData	ty/Location/Address/CountrySubDivisionCode The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics.
	When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
@listID ; -/-	Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States. Set list ID to 'Country Sub-divisions' if the country 's SubDivisions- [CountryCode]'.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKCSCD; CRS610MI/GetBasicData	ty/Location/Address/CountryCode The field indicates a country.
@lietD	Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
@listID : -/-	Set to 'Countries'.
ReceivableTransaction/ReceivableTransactionHeader/CustomerPart OCUSMA.OKPONO; CRS610MI/GetBasicData	
	The postal code is an address element that can be part of an address line if address formatting rules are used.
ReceivableTransaction/ReceivableTransactionHeader/PayFromParty FSLEDG.ESPYNO; ARS200MI/GetInvoice	r/PartyIDs/ID The field indicates the person/business who has paid or will pay the invoice.

Infor May 26, 2023 485

The payer is specified when an invoice should be sent somewhere

For order and sales statistics, the payer is used as a statistic ID. For

other than to the customer placing the order.

total statistics, the payer is one of the key IDs.

FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvoice	The field indicates the accounting entity.
	If PayFromPartyMaster is enabled in BOD Processor Master AE tab,
	this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO_DIVI), e.g. 760_AAA
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa	rty/Name
OCUSMA.OKCUNM; CRS610MI/GetBasicData ReceivableTransaction/ReceivableTransactionHeader/PayFromPa	The field indicates the name of the payer.
@type	
; -/- Paccivable Transaction/Paccivable Transaction Hander/PayEromPa	Set to 'text'.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the payer's contact person as defined in (CRS610) as Your reference 1.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKCUA1, OKCUA2, OKCUA3, OKCUA4; CRS610MI/ GetBasicData	arty/Location/Address/AddressLine The field indicates the address of the payer.
@sequence ; -/-	The field indicates the sequence number of an address.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKTOWN; CRS610MI/GetBasicData	nrty/Location/Address/CityName The field indicates the city.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKECAR; CRS610MI/GetBasicData	arty/Location/Address/CountrySubDivisionCode The field indicates an area, province or state within a country. The information is used for addresses, U.S. sales tax and for trade statistics.
© li-up	When editing addresses, the information is validated when state is used as an address element according to the address formatting rule, used for the country to which the address applies. Address formatting rules are stated for each country.
@listID ; -/-	Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States. Set list ID to 'Country Sub-divisions' if the country 's SubDivisions-[CountryCode]'.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKCSCD; CRS610MI/GetBasicData	rty/Location/Address/CountryCode The field indicates a country.
@listID	Countries are entered and assigned a three-character country code. These country codes are used as selection criteria and such.
; -/-	Set to 'Countries'.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa OCUSMA.OKPONO; CRS610MI/GetBasicData	arty/Location/Address/PostalCode The field indicates a postal code for a specific address.
	The postal code is an address element that can be part of an address line if address formatting rules are used.
ReceivableTransaction/ReceivableTransactionHeader/PayFromPa @listID	rty/Contact/Communication/Address/CountrySubDivisionCode
; -/-	Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States. Set list ID to 'Country Sub-divisions' if the country 's SubDivisions- [CountryCode]'.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTell CSYTAB.CTSTKY; ARS200MI/GetInvTotInfo	rm/Term/ID The field indicates a key value, which is a value included in the group of items displayed in this panel.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTel @accountingEntity	rm/PaymentTermCode
FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvTotInfo	The field indicates the company and division. Accounting Entity for M3 is defaulted as a combination of CONO. DIVI
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI E.g. 760 AAA
ReceivableTransaction/ReceivableTransactionHeader/PaymentTell CSYTAB.CTPARM; CRS175MI/GetGeneralCode	rm/Term/Description The field indicates the description (position 1-72 characters of field PARM) of the payment term (TEPY).
ReceivableTransaction/ReceivableTransactionHeader/PaymentTell FSLEDG.ESDUDT; ARS200MI/GetInvTotInfo	
ReceivableTransaction/ReceivableTransactionHeader/PaymentTel FSLEDG.ESTECD; ARS200MI/GetInvTotInfo	· · ·

11CCCIVADIC ITAIISACTION	
CSYTAB.PARM; CRS175MI/GetGeneralCode	The field indicates the description (position 1-72 of field PARM) of the cash discount term (TECD).
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm. FSCASH.ESCDT1, ESCDT2, ESCDT3; ARS200MI/GetCashDiscInfo	/Discount/EffectiveDateTime The field indicates the cash discount date.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm. FSCASH.ESCDAM; ARS200MI/GetCashDiscInfo	
@currencyID FSCASH.PCCUCD; ARS200MI/GetCashDiscInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/PaymentTerm. FSCASH.ESCDAM; ARS200MI/GetCashDiscInfo	/Discount/BaseAmount The field indicates the cash discount - local currency (converted from Cash discount - foreign currency)
@currencyID CMNDIV.CCLOCD; ARS200MI/GetCashDiscInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/ReceivableSty FSLEDG.ESIVTP, ESPYRS; ARS200MI/GetInvTotInfo	The field indicates the type of receivable transaction based on the invoice (TRCD=10, that is transaction from MI output) and: - If Invoice type (IVTP) = AP or CN: 'CreditMemo' - If Invoice type (IVTP) = DI, GP, LC, PP, SI or UN: 'Miscellaneous' - If Invoice type (IVTP) = 'blank', Payment class (PYCL) (*) = 4 (Draft) and Remittance status (PYRS) => 10: 'Miscellaneous' For all other Invoice types (IVTP): 'Invoice'
	(*) Payment class (PYCL) as retrieved for 'PaymentMethodCode'.
ReceivableTransaction/ReceivableTransactionHeader/ReceivableSty FSLEDG.ESTRCD, ESIVTP, ESSLOP; ARS200MI/GetInvoice	 Interview of the transaction is related to an Invoice, Payment or Adjustment: Set to 'I': If Transaction code (TRCD) = 10. Set to 'A: If Transaction code (TRCD) = 20 and: Invoice type (IVTP) = BB and Accounting option (SLOP) = 15 Invoice type (IVTP) = DN and Accounting option (SLOP) = 16 Invoice type (IVTP) = blank and Accounting option (SLOP) = 18 or 20-99 Set to 'P': For all other cases (default value).
ReceivableTransaction/ReceivableTransactionHeader/InvoiceRefere	
FSLEDG.ESINYR, FSLEDX.ESSEXI, FSLEDG.ESCINO; ARS251MI, ARS200MI/LstInvInfo, GetInvTotInfo	The field indicates the invoice reference number. Concatenate invoice year (INYR) retrieved from FSLEDG table before additional information (SEXI) in case of split due date or invoice number (CINO)
	If ARS251MI returns a record from table FSLEDX with info category (SEXN) = 227 or 228, use additional information (SEXI) = Original invoice number, else use Invoice number (CINO).
	NB: The reference is only included in case the invoice is created using one of the following FAM functions (*): AR20, CO20, FA50, MF01, Ol20, PO20 or SO20. (*) Retrieved from GLS200MI.GetVoucherHead using as input, the
@accountingEntity	output values from ARS200MI.GetInvTotInfo.
FSLEDG.ESCONO, ESDIVI; ARS200MI/GetInvTotInfo	The field indicates the company and division. AccountingEntity for M3 is defaulted as a combination of CONO_DIVI
	E.g. 760 AAA
ReceivableTransaction/ReceivableTransactionHeader/ExtendedAmo FSLEDG.ESCUAM, FGLEDG.EGCUAM; ARS200MI/GetInvTotInfo	The field indicates Invoice currency amount minus tax currency amount.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/ExtendedBase FGLEDG.EGACAM; ARS200MI/GetInvTotInfo	eAmount The field indicates Invoice local amount minus tax local amount
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@D	(invoice)) and states edge void, set amount to e.co.
@currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.

FSLEDG.ESCUAM; ARS200MI/GetInvTotInfo	The field indicates Invoice foreign amount.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/TotalBase FGLEDG.EGACAM; ARS200MI/GetInvTotInfo	seAmount The field indicates Invoice local amount
,	
@currencyID	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Tax/Bas FGLEDG.EGCUAM; ARS200MI/GetInvTotInfo	The field indicates the VAT/Tax base amount in foreign currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 11 and VAT account type (field AT04) = 3 to 9.
@ourrenovID	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Tax/Bas FGLEDG.EGACAM; ARS200MI/GetInvTotInfo	The field indicates the VAT/Tax base amount in local currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 11 and VAT account type (field AT04) = 3 to 9.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Tax/Amount FGLEDG.EGCUAM; ARS200MI/GetInvTotInfo	The field indicates the VAT/Tax amount in foreign currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 11 and VAT account type (field AT04) = 1 or 2.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Tax/BaseAmou FGLEDG.EGACAM; ARS200MI/GetInvTotInfo	The field indicates the VAT/Tax amount in local currency that is the sum of the transactions in table FGLEDG with Transaction code (field TRCD) = 11 and VAT account type (field AT04) = 1 or 2.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Discount FSCASH.ESCDAM; ARS200MI/GetCashDiscInfo	ntStatus/DiscountAllowedAmount The field indicates the allowed cash discount for an invoice in foreign currency using cash discount rate 1.
	Retrieved using Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) from ARS200MI.GetInvTotInfo.
	If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00.
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/Discoun	ntStatus/DiscountAllowedBaseAmount

The field indicates the allowed cash discount for an invoice in local currency (converted from cash discount - foreign currency) using cash discount rate 1. Retrieved using Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) from ARS200MI.GetInvTotInfo. If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00. @currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards ReceivableTransaction/ReceivableTransactionHeader/DiscountStatus/DiscountTakenAmount FSLEDG.ESCUAM; ARS200MI/GetInvTotInfo The field indicated the total cash discount amount taken in foreign currency that is the sum of the transactions in table FSLEDG with Transaction code (field TRCD) = 20 and the Account option (field SLOP) = 18. Note that the Split payment transaction (field SPAR) parameter on the payment FAM function (e.g. AR30) needs to be set to 1-Several pmt trans in AR/AP or else cash discounts cannot be detected. @currencyID FSLEDG.ESCUCD: ARS200MI/GetInvTotInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards. Receivable Transaction / Receivable Transaction Header / Discount Status / Discount Taken Base AmountFGLEDG.EGACAM; ARS200MI/GetInvTotInfo The field indicated the total cash discount amount taken in local currency that is the sum of the transactions in table FSLEDG with Transaction code (field TRCD) = 20 and the Account option (field SLOP) = 18.Note that the Split payment transaction (field SPAR) parameter on the payment FAM function (e.g. AR30) needs to be set to 1-Several pmt trans in AR/AP or else cash discounts cannot be detected. @currencvID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards. ReceivableTransaction/ReceivableTransactionHeader/ReceivableAmount FSLEDG.ESCUAM; ARS200MI/GetInvTotInfo The field indicates outstanding amount in foreign currency. If status code = Applied, UnappliedCash, Paid or PartialPaid, set OCUA else set CUAM. If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00. @currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo The field indicates the abbreviation for the foreign currency. The abbreviation should follow ISO standards. ReceivableTransaction/ReceivableTransactionHeader/ReceivableBaseAmount FGLEDG.EGACAM; ARS200MI/GetInvTotInfo The field indicates outstanding amount in local currency. If status code = Applied, UnappliedCash, Paid or PartialPaid, set OAMT else set ACAM If transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and status code = Void, set amount to 0.00. @currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo The field indicates the abbreviation for the local currency. The abbreviation should follow ISO standards. ReceivableTransaction/ReceivableTransactionHeader/ReceivedAmount FSLEDG.ESCUAM: ARS200MI/GetInvTotInfo The field indicates the Paid amount in foreign currency calculated as: - Paid amount (PCUA) minus - Cash discount taken (CDCU) minus - Write-Off (WRCU) minus - Bill back (BBCU) minus - Debit note (DNCU) @currencvID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo The field indicates the abbreviation for the foreign currency.

ReceivableTransaction/ReceivableTransactionHeader/ReceivedBaseAmount

FGLEDG.EGACAM; ARS200MI/GetInvTotInfo

The field indicates the Paid amount in local currency calculated as:

Paid amount (PAMT) minus

The abbreviation should follow ISO standards.

- Cash discount taken (CDAM) minus

- Write-Off (WRAM) minus

- Bill back (BBAM) minus

- Debit note (DNAM)

@currencyID

CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the local currency.

The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/PaymentMethodCode

CSYTAB.CTPARM; CRS175MI/GetGeneralCode

The field indicates the payment class of the payment method from the invoice (TRCD=10) or payment (TRCD=20) using

ARS200MI.GetInvoice.

First Payment method AR is read (STKY = PYCD), then the payment type connected to the method is read. Set the following if Payment class (PYCL) in payment type is:

- 0: Set to 'Cash'

- 1: Set to 'Cheque'

- 2: Set to 'Cheque'

- 3: Set to 'CreditCard' (if the credit card flag is set on the payment

method) or 'ElectronicFundsTransfer' - 4: Set to 'BankDraft'

- 5: Set to 'DirectDebit'

- 6: Set to 'Factoring'

Everything else is set to 'Cash'

ReceivableTransaction/ReceivableTransactionHeader/WriteOff/Amount

FSLEDG.ESCUAM; ARS200MI/GetInvTotInfo

The field indicates the write-off amount in foreign currency done aginst the invoice, that is transactions in table FSLEDG with Accounting option (field SLOP) = 20 to 98.

@currencvID

FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the foreign currency.

The abbreviation should follow ISO standards

ReceivableTransaction/ReceivableTransactionHeader/WriteOff/BaseAmount The field indicates the write-off amount in local currency done aginst

FGLEDG.EGACAM; ARS200MI/GetInvTotInfo

the invoice, that is transactions in table FSLEDG with Accounting option (field SLOP) = 20 to 98.

@currencyID

CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the local currency.

The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/WriteOff/ReasonCode

FSLEDG.ESTDSC; ARS200MI/GetInvoice

The field indicates the transaction description of this transaction from the user-defined accounting options for manual payments.

The description allows for a more detailed voucher description.

@listID

-.-; -/-@accountingEntity Set to 'Write Off Reasons'.

FSLEDG.ESCONO, ESDIVI; -/-

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI.

E.g. 760_AAA

ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/SourceCurrencyCode

FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo

The field indicates the abbreviation for the currency.

The abbreviation should follow ISO standards

ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/SourceUnitBaseNumeric

.; CRS055MI/GetBasicData

The field indicates the rate factor (RAFA) defined in (CRS055/ MFS055) of the transaction currency (CUCD) to the local currency.

- If Rate factor = 1: Set to '1000'

- If Rate factor = 2: Set to '100'

- If Rate factor = 3: Set to '10'

If Rate factor = 4-7: Set to '1'

ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/TargetCurrencyCode

CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo

The field indicates the local currency, that is, the basic currency used by the division. The local currency is defined per division.

The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionHeader/CurrencyExchangeRate/TargetUnitBaseNumeric

.; CRS055MI/GetBasicData

The field indicates the rate factor (RAFA) defined in (CRS055/ MFS055) of the transaction currency (CUCD) to the local currency.

- If Rate factor = 1-4: Set to '1'

- If Rate factor = 5: Set to '10'

- If Rate factor = 6: Set to '100'

- If Rate factor = 7: Set to '1000'

ReceivableTransaction/ReceivableTransactionHeader/CurrencyExch FSLEDG.ESARAT; ARS200MI/GetInvTotInfo	angeRate/RateNumeric The field indicates the exchange rate (6 decimals) for the transaction currency as entered in M3BE.
ReceivableTransaction/ReceivableTransactionHeader/MiscAdjustme FSLEDG.ESCUAM; ARS200MI/GetInvTotInfo	The field indicates miscellaneous adjustments in foreign currency done as: - Rounding off (transaction with SLOP = 99) transaction (ROCU) plus - Bill back (BBCU) plus
@currencyID FSLEDG.ESCUCD; ARS200MI/GetInvTotInfo	 Debit note (DNCU) The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/MiscAdjustme FGLEDG.EGACAM; ARS200MI/GetInvTotInfo	
@currencyID CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo	The field indicates the abbreviation for the local currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionHeader/BaseCurrency	
@type	Set 1st amount to "ExtendedAmount", 2nd amount to "TotalAmount", 3rd amount to "ReceivableAmount", 4th amount to "ReceivedAmount"
ReceivableTransaction/ReceivableTransactionHeader/BaseCurrency FGLEDG.EGACAM; ARS200MI/GetInvTotInfo @currencyID	Amount/Amount The field indicates the base currency amount.
CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates currency used in the base currency amount
ReceivableTransaction/ReceivableTransactionHeader/UserArea FSLEDG.ESPYCD, ESTRCD, ESIVTP, ESSLOP; ARS200MI/GetInvoid	ce The field indicates specific values required by an integration (currently only for Local.ly as indicated by prefix 'lcl.').
	Payment method (PYCD) of the Invoice (TRCD = 10) or the Payment (TRCD = 20): - Propery name = 'Icl.PaymentMethod' and Property type = 'StringType'
	Type of adjustment when element 'ReceivableStyleCategory' = 'A': - Property name = 'Icl.AdjustmentType' and Property type = 'StringType' NameValue set to: - 'MiscAdjustments' when Transaction code (TRCD) = 20 and: - Invoice type (IVTP) = BB and Accounting option (SLOP) = 15 Invoice type (IVTP) = DN and Accounting option (SLOP) = 16 Invoice type (IVTP) = blank and Accounting option (SLOP) = 99 'DiscountTaken' when Transaction code (TRCD) = 20 and: - Invoice type (IVTP) = blank and Accounting option (SLOP) = 18 'WriteOff' when Transaction code (TRCD) = 20 and: - Invoice type (IVTP) = blank and Accounting option (SLOP) = 20-98
ReceivableTransaction/ReceivableTransactionLine/LineNumber ; -/-	Set to 1.
	Note: ReceivableTransactionLine is created for records with transaction code (TRCD) = 10 (that is ReceivableStyleCategory = I (Invoice)) and (TRCD) = 20 (that is ReceivableStyleCategory = P (Payment) and A (Adjustment)) to output amount of the transaction that triggers the BOD.
ReceivableTransaction/ReceivableTransactionLine/Amount FGLEDG.EGCUAM; GLS200MI/GetVoucherLine	The field indicates the foreign currency amount of the invoice, payment or adjustment for the transaction that has triggered the BOD The amount sign is reversed for transactions with transaction code (TRCD) = 20 (that is ReceivableStyleCategory = P (Payment) and A (Adjustment)).
@currencyID FGLEDG.EGCUCD; GLS200MI/GetVoucherLine	The field indicates the abbreviation for the foreign currency.
	The abbreviation should follow ISO standards.
ReceivableTransaction/ReceivableTransactionLine/BaseAmount FGLEDG.EGACAM; GLS200MI/GetVoucherLine	The field indicates the local currency amount of the invoice, payment or adjustment for the transaction that has triggered the BOD. The amount sign is reversed for transactions with transaction code (TRCD) = 20 (that is ReceivableStyleCategory = P (Payment) and A (Adjustment)).

@currencyID

CMNDIV.CCLOCD; ARS200MI/GetInvTotInfo

The abbreviation should follow ISO standards.

ReceivableTransaction/ReceivableTransactionLine/UserArea FGLEDG.EGARAT, EGCUAM; GLS200MI/GetVoucherLine

The field indicates additional information for the line and is only populated if Country Version (CSVN) = MX-Mexico, Currency conversion method (DMCU) = 1-Multiplication (see note 2) and the control property 'm3beMXPayment' has beed activated (true), default value is false.

The following information is included for a payment, that is ReceivableStyleCategory = P:

The field indicates the abbreviation for the local currency.

- a) Exchange rate (with 8 decimals) of the payment (ARAT, see Note 1) with attribute name = 'lcl.PaymentExchangeRate'.
- The attribute 'type is set to 'DecimalType' and attribute 'sequence' to
- b) Base amount (with 2 decimals) of the payment (calculated as CUAM*ARAT (see Note 1 and 2)) with attribute name = 'lcl.PaymentBaseAmount'.
- The attribute 'type is set to 'AmountType', attribute 'currencyID' set to Local currency (LOCD) and attribute 'sequence' to +1.
- c) Exchange rate (with 6 decimals) of the payment (ARAT, see Note 3) with attribute name = 'm3_PaymentExchangeRate'.
- The attribute 'type is set to 'DecimalType' and attribute 'sequence' to +1.

(Note 1) Exchange rate must be sent in relation 1:1 (for USD, Mexico must use rate factor (RAFA) 4=1:1 with the exchange rate as stated from the government but recommended for other currencies when possible).

(Note 2) Mexico must use Currency conversion method (DMCU) 1=Multiplication for the division .

(Note 3) Exchange rate as stored in M3BE (included for information purpose).

ReceiveDelivery

ReceiveDelivery/ReceiveDeliveryHeader/DocumentID/ID

For Standard:

MPLIND.ICREPN; PPS200MI/GetLineTrans The field indicates the receiving number for each item received in

goods receiving.

For Standard:

CONO_DIVI.

For Warehouse:

For Standard:

For Warehouse:

For Standard:

For Warehouse:

For Standard:

For Warehouse:

noun instance.

For Warehouse:

For Standard:

For Warehouse:

For Standard:

For Warehouse:

For Warehouse:

For Standard:

For Warehouse:

For Standard:

For Warehouse: MHDISH.OQDLIX

; MWS410MI/GetHead

For Warehouse: The field indicates the receiving number which is assigned

The field indicates the company and division.

The field indicates the warehouse location.

The field indicates the warehouse locaiton.

times the BOD has been published.

times that this BOD has been published.

The field indicates the logical ID of the system.

automatically for each item received in goods receiving.

The field indicates the company and division, displayed as

The field indicates the sequence number that identifies the number of

The field indicates the sequence number that identifies the number of

The field indicates the logical id of the system that is SOR for this

The field indicates the user who makes the goods receipt. User id is

The field indicates the ID of the person who last modified the record.

The field indicates the date and time the record was created.

The field indicates the receiving number which is assigned

automatically for each item received in goods receiving

The field indicates the last modification date and time.

The field indicates the last date and time modified

retrieved from event data field 'owner'.

The field indicates the company and division.

@accountingEntity For Standard:

MPLIND.ICCONO CMNDIV.CCDIVI

For Warehouse: MHDISH.OQCONO CMNDIV.CCDIVI

@location

For Standard:

MPLIND.ICWHLO; PPS200MI/GetLineTrans

For Warehouse: MHDISH.OQWHLO ; MWS410MI/GetHead

@variationID

For Warehouse:

.; /

@lid

For Warehouse:

ReceiveDelivery/ReceiveDeliveryHeader/DisplayID

For Warehouse: MHDISH.OQDLIX ; MWS410MI/GetHead

For Standard: MPLIND.ICLMTS; /

For Warehouse:

MHDISH.OQLMTS; / ReceiveDelivery/ReceiveDeliveryHeader/LastModificationPerson/IDs/ID

For Warehouse: MHDISH.OQCHID: /

@accountingEntity For Warehouse: MHDISH.OQCONO

CMNDIV.CCDIVI

ReceiveDelivery/ReceiveDeliveryHeader/DocumentDateTime For Standard:

For Warehouse:

MITTRA.MTRGDT MITTRA.MTRGTM.; MWS070MI/LstTransByOrder

MPLIND.ICTRDT; PPS200MI/GetLineTrans

ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference @type

ReceiveDelivery/ReceiveDeliveryHeader/LastModificationDateTime

For Warehouse MHDISH.OQRORC ; MWS410MI/GetHead For Standard:

Set to 'AdvanceShipNotice'.

For Warehouse:

The field indicates the document reference type.

Set to 'Transfer' if RORC = 4 or 5.

The field indicates the receipt date.

ReceiveDelivery ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference/DocumentID/ID For Standard: For Standard: MPLIND.ICSUDO; PPS200MI/GetLineTrans The field indicates the unique number to a purchase order. For Warehouse: For Warehouse: MHDISH.OQRIDN The field indicates the unique number that is assigned to a ; MWS410MI/GetHead distribution or requisition order when it is created. @accountingEntity For Standard: For Standard: MPLIND.ICCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI CONO DIVI. For Warehouse: For Warehouse: The field indicates the company and division. MHDISH.OQCONO CMNDIV.CCDIVI ReceiveDelivery/ReceiveDeliveryHeader/Status/Code For Standard: For Standard: MPLIND.ICPUOS; PPS200MI/GetLineTrans The field indicates the purchase order status (PUOS). Set to 'Received' if purchase order status is 50, 51, 70 or 75. For Warehouse: Set to 'Deleted' if BOD is triggered from MPLIND_DELETE rule. MHDISH.OQPGRS ; MWS410MI/GetHead For Warehouse: The field indicates the status of the receipt transaction. Set to 'Received' if PGRS = 75 or 90. ReceiveDelivery/ReceiveDeliveryHeader/Status/EffectiveDateTime For Standard: For Standard: MPLIND.ICRGDT The field indicates the entry date and entry time. MPLIND.ICRGTM.; PPS200MI/GetLineTrans For Warehouse: For Warehouse: The field indicates the receipt date and time. MHDISH.OQRCDT MHDISH.OQRCTM MWS410MI/GetHead ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/ID For Standard: The field indicates the warehouse ID. MPLIND.ICWHLO; PPS200MI/GetLineTrans For Warehouse: MHDISH .OQWHLO; MWS410MI/GetHead @accountingEntity For Standard: For Standard: MPLIND.ICCONO The field indicates the company and division, displayed as CMNDIV.CCDIVI CONO DIVI. For Warehouse: For Warehouse: The field indicates the company and division. MHDISH.OQCONO CMNDIV.CCDIVI ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Name For Warehouse: For Warehouse: MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse description ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address @type For Warehouse: Set to 'text'. ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address/AddressLine For Warehouse: For Warehouse: The field indicates the location address.

CIADDR.OAADR1 CIADDR.OAADR2 CIADDR.OAADR3

.; MMS005MI/GetWarehouse

@sequence

CIADDR.OAADR4

For Warehouse: For Warehouse:

.; / The field indicates the address line sequence number.

ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address/CityName

For Warehouse: For Warehouse:

CIADDR.OATOWN The field indicates the city.

; MMS005MI/GetWarehouse

ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address/CountrySubDivisionCode

ReceiveDeliverv

For Warehouse: CIADDR.OAECAR

; MMS005MI/GetWarehouse

@listID

For Warehouse:

The field indicates the country subdivision code.

For Warehouse:

Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States

Set list ID to 'Country Sub-divisions' if the country 's SubDivisions-

[CountryCode]'

ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address/CountryCode

For Warehouse: For Warehouse:

CIADDR.OACSCD The field indicates the country code.

; MMS005MI/GetWarehouse

@listID

For Warehouse: Set to 'Countries'

ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/Address/PostalCode

For Warehouse: For Warehouse:

CIADDR.OAPONO The field indicates the postal Code.

; MMS005MI/GetWarehouse

ReceiveDelivery/ReceiveDeliveryHeader/CarrierRouteReference/DocumentID/ID

For Warehouse: For Warehouse:

MHDISH.OQROUT The field indicates the transportation route. A route is determined by a ; MWS410MI/GetHead

loading place with one or more unloading locations.

@accountingEntity For Warehouse: For Warehouse:

MHDISH.OQCONO The field indicates the company and division.

CMNDIV.CCDIVI

ReceiveDelivery/ReceiveDeliveryHeader/ActualShipDateTime

For Warehouse: For Warehouse:

MHDISH.OQDSDT The field indicates the shipment date and time.

MHDISH.OQDSHM .; MWS410MI/GetHead

ReceiveDelivery/ReceiveDeliveryHeader/ActualDeliveryDateTime

For Warehouse: For Warehouse:

MITTRA.MTTRDT The field indicates the date/time the goods were delivered.

MITTRA.MTTRTM .; MWS070MI/LstTransByOrder

ReceiveDelivery/ReceiveDeliveryHeader/NetWeightMeasure

For Warehouse: For Warehouse:

MHDISH.OQNEWE The field indicates the total weight of all items in the delivery.

; MWS410MI/GetHead @unitCode

For Warehouse: For Warehouse:

CSYTAB.CTPARM The field indicates the general unit of measure for all weights within a

; CRS175MI/GetItemFreeFlds company

ReceiveDelivery/ReceiveDeliveryHeader/GrossWeightMeasure For Warehouse: For Warehouse:

MHDISH.OQGRW2 The field indicates the gross weight of all items in the delivery.

: MWS410MI/GetHead

@unitCode For Warehouse: For Warehouse:

CSYTAB.CTPARM The field indicates the general unit of measure for all weights within a

; CRS175MI/GetItemFreeFlds company.

ReceiveDelivery/ReceiveDeliveryHeader/TotalVolumeMeasure

For Warehouse: For Warehouse: The field indicates the volume of all items in the delivery.

MHDISH.OQVM32 ; MWS410MI/GetHead

@unitCode For Warehouse: For Warehouse:

CSYTAB.CTPARM The field indicates the general unit of measure for all volume within a

; CRS175MI/GetItemFreeFlds company

ReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/PartyIDs/ID

For Standard: For Standard:

MPLINE.IBSUNO; PPS200MI/GetLine The field indicates the supplier.

For Warehouse: For Warehouse:

MITWHL The field indicates the unique identity of a supplier. .MWSUNO: MMS005MI/GetWarehouse

@accountingEntity

For Standard: The field indicates the accounting entity.

MPLIND.ICCONO CMNDIV.CCDIVI If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, .; /

ReceiveDelivery

For Warehouse: MHDISH.OQCONO CMNDIV.CCDIVI

this is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

ReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/Name

For Warehouse:

CIDMAS.IDSUNM; CRS620MI

/GetBasicData

For Warehouse:

For Standard:

The field indicates the supplier name.

The field indicates the contact name.

ReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/Contact/Name

For Standard

CIDREF.IRYRE1; PPS200MI/GetHead

ReceiveDelivery/ReceiveDeliveryHeader/CarrierParty/PartyIDs/ID

For Warehouse: MHDISH.OQFWNO ; MWS410MI/GetHead

@accountingEntity For Warehouse:

> MHDISH.OQCONO CMNDIV.CCDIVI

.: /

For Warehouse:

For Warehouse:

transport.

The field indicates the accounting entity.

If CarrierParty is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as

The field indicates the forwarding agent who can be used for the

Company and Division (CONO DIVI).

ReceiveDelivery/ReceiveDeliveryHeader/CarrierParty/Name

For Standard:

MPLIND.ICCARN; PPS200MI/GetLineTrans

For Warehouse: CIDMAS.IDSUNM

; CRS620MI/GetBasicData

For Standard:

The field indicates the carrier name.

For Warehouse:

The field indicates supplier name, most often the supplier's company

name.

ReceiveDelivery/ReceiveDeliveryHeader/ReceivedDateTime

For Standard:

MPLIND.ICTRDT; PPS200MI/GetLineTrans

For Warehouse: MHDISH.OQRCDT

MHDISH OORCTM

The field indicates the transaction date.

For Warehouse:

The field indicates the receive date and time.

.; MWS410MI/GetHead

ReceiveDelivery/ReceiveDeliveryHeader/BillOfLadingID For Standard:

MPLIND.ICBOLN; PPS200MI/GetLineTrans

MHDISH.OQNBOL ; MWS410MI/GetHead

For Warehouse:

For Standard:

The field indicates the bill of lading

The field indicates the number of the delivery's bill of lading.

ReceiveDelivery/ReceiveDeliveryHeader/Container/ContainerID

For Standard:

MPLIND.ICCAMU; PPS200MI/GetLineTrans

For Standard:

The field indicates the container ID

ReceiveDelivery/ReceiveDeliveryHeader/DeliverToParty/Location/Description

For Standard: MPPOAD.ADNAM; PPS200MI/GetDelAddress, For Standard:

The field indicates the location description.

GetAddress

For Warehouse:

For Warehouse: MITWHL.MWWHNM ; MMS005MI/GetWarehouse

The field indicates the warehouse description.

ReceiveDelivery/ReceiveDeliveryHeader/ReceivingLocation/ID

For Standard:

MPLIND.ICWHSL; PPS200MI/GetLineTrans

For Standard:

The field indicates the location warehouse.

For Warehouse: For Warehouse: MHDISH.OQCONA

; MWS410MI/GetHead

@accountingEntity For Warehouse:

MHDISH.OQCONO CMNDIV.CCDIVI.;

The field indicates the consignee.

For Warehouse: The field indicates the company and division.

ReceiveDelivery/ReceiveDeliveryHeader/UserArea

For Standard:

CIDMAS.IDCFI4; CRS620MI/GetBasicData

For Standard:

1) Supplier user-defined field 4

The field indicates user-defined text that can be used for selecting

reports or for individual information.

Set attribute name to 'SupplierFreeField4'

ReceiveDelivery/ReceiveDeliveryHeader/UserArea/Property/NameValue

ReceiveDeliverv

MHDISH.QQINOU; /Event Data

@name

For Warehouse:

The field indicates Direction filed

For Warehouse: Set to "Direction"

ReceiveDelivery/ReceiveDeliveryItem/ItemID/ID

For Standard:

MPLINE.IBITNO; PPS200MI/GetLine

The field indicates the item number.

For Warehouse: MHDISL.URITNO; MWS410MI/LstItem MITTRA.MTITNO;

MWS070MI.LstTransByOrder.; /

@accountingEntity

For Standard: MPLIND.ICCONO

CMNDIV.CCDIVI

For Warehouse:

MHDISH.OQCONO

CMNDIV.CCDIVI

ReceiveDelivery/ReceiveDeliveryItem/ServiceIndicator

For Standard: MTEINF.UICFMA; CMS474MI/GetUdefContent

For Warehouse:

.; /

ReceiveDelivery/ReceiveDeliveryItem/Description

For Standard:

MPLINE.IBPITT; PPS200MI/GetLineX

For Warehouse:

MITMAS.MMITDS ; MWS410MI/LstItem

ReceiveDelivery/ReceiveDeliveryItem/HazardousMaterial/ID

For Warehouse: MITMAS.MMITNO

; MMS200MI/GetItmBasic

ReceiveDelivery/ReceiveDeliveryItem/OrderQuantity

For Standard: MPLINE.IBORQA; PPS200MI/GetLine

For Warehouse:

MGLINE.MRTRQT: MWS411MI/GetDeliveryLine

MGLINE.MRTRQT

MGLINE.MRTRQA;

MMS100MI/GetLine.; /

@unitCode

For Standard:

MPLINE.IBPUUN; PPS200MI/GetLine

For Warehouse: MITMAS.MMUNMS;

MWS423MI/LstContents

MGLINE.MRALUN; MMS100MI/GetLine.;

ReceiveDelivery/ReceiveDeliveryItem/OrderBaseUOMQuantity

For Warehouse: MGLINE.MRTRQT;

MWS411MI/GetDeliveryLine MMS100MI/GetLine.; /

@unitCode

For Warehouse:

For Warehouse:

MITMAS.MMUNMS ; MMS200MI/GetItmBasic

ReceiveDelivery/ReceiveDeliveryItem/ShippedQuantity For Standard

MPLIND.ICRPQA; PPS200MI/GetLineTrans

For Standard:

The field indicates the accounting entity.

If ItemMaster_MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO_DIVI).

For Warehouse:

The field indicates the company and division.

For Standard:

Set to 'true' if service item. Set to 'false' if non-service item.

For Warehouse: Set to 'false'.

For Standard:

The field indicates the item description of purchase order.

For Warehouse:

The field indicates the item description.

For Warehouse:

The field indicates the item number which is tagged as hazardous

material

(HAZI = 1). If HAZI = 0, this field is blank.

For Standard:

The field indicates the order quantity.

For Warehouse:

The field indicates the quantity.

For TTYP = 40, use TRQT only when TRQA is 0.

For Standard:

The field indicates the unit of measure.

For Warehouse:

The field indicates the unit of measure.

Use UNMS if OrderQuantity is TRQT. Use ALUN if OrderQuantity is TRQA

For Warehouse:

The field indicates the quantity, in the basic unit of measure, for the

planned or actual transaction.

For Warehouse:

This field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

For Standard:

The field indicates shipped quantity.

For Warehouse:

ReceiveDeliverv

MFTRNS.OSDLQT The field indicates the delivered quantity, expressed in the item's : MWS423MI/LstContents

basic U/M.

@unitCode

For Standard:

MPLINE.IBPUUN; PPS200MI/GetLine

For Standard: The field indicates the unit of measure.

For Warehouse:

MITMAS.MMUNMS The field indicates the unit in which each item is recorded in ; MMS200MI/GetItmBasic inventory, even if alternate inventory units of measure are used. All

balance information for the current item is always stored in this unit.

ReceiveDelivery/ReceiveDeliveryItem/ShippedBaseUOMQuantity

For Warehouse: For Warehouse:

MFTRNS.OSDLQT The field indicates the delivered quantity, expressed in the item's : MWS423MI/LstContents

basic U/M.

For Warehouse:

@unitCode

For Warehouse: MITMAS.MMUNMS

The field indicates the unit in which each item is recorded in ; MMS200MI/GetItmBasic inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/DocumentID/ID

For Standard: For Standard:

MPLIND.ICPUNO; PPS200MI/GetLineTrans The field indicates the purchase order number.

@accountingEntity

For Standard: For Standard:

MPLIND.ICCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI CONO DIVI.

@location

For Standard: For Standard:

MPLIND.ICWHLO; PPS200MI/GetLineTrans The field indicates the warehouse ID.

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/LineNumber

For Standard:

MPLIND.ICPNLI The field indicates the purchase order reference line number.

MPLINE.ICPNLS.; PPS200MI/GetLineTrans

It is a concatenation of purchase order line (PNLI) and purchase

order line subnumber (PNLS).

The position of purchase order line subnumber is determined by its

lenath.

If the length of purchase order line subnumber is 0 then the value is

If the length of purchase order line subnumber is 1 then the value is

00 + purchase order line subnumber (PNLS).

If the length of purchase order line subnumber is 2 then the value is 0

purchase order line subnumber (PNLS).

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/SubLineNumber

For Standard: For Standard:

MPLIND.ICPNLS; PPS200MI/GetLineTrans The field indicates the purchase order line subnumber.

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/Quantity

For Standard: For Standard:

MPLINE.IBORQA; PPS200MI/GetLine The field indicates the order quantity.

@unitCode

For Standard: For Standard:

MPLINE.IBPUUN; PPS200MI/GetLine The field indicates the unit of measure.

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/DocumentID/ID

For Standard: For Standard:

MPLINE.IBRORN; PPS200MI/GetLine The field indicates the customer's reference order number.

@accountingEntity

For Standard: For Standard:

MPLIND.ICCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI CONO DIVI.

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/DocumentDateTime For Standard: For Standard:

OOHEAD.OACUDT; OIS100MI/GetOrderHead The field indicates the customer's purchase order date.

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/LineNumber

For Standard: For Standard:

MPLINE.IBRORL; PPS200MI/GetLine The field indicates the customer's reference order number.

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/SubLineNumber

For Standard: For Standard:

MPLINE.IBRORX; PPS200MI/GetLine The field indicates the customer order sub-line number.

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/Quantity

For Standard: For Standard:

OOLINE.OBORQT; OIS100MI/GetLine The field indicates the customer order quantity.

@unitCode For Standard:

ReceiveDelivery

OOLINE.OBALUN: OIS100MI/GetLine For Standard:

The field indicates the customer order quantity unit of measure.

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference

@type

For Warehouse: For Warehouse:

MFTRNS.OSRORC The field indicates the document reference type. Set to 'Transfer'.

; MWS423MI/LstContents

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/DocumentID/ID

For Warehouse: For Warehouse: MFTRNS.OSRIDN; The field indicates the document reference order number.

MWS070MI/LstContents MWS070MI/LstTransByOrder.; /

@accountingEntity

For Warehouse: For Warehouse:

MHDISH.OQCONO The field indicates the company and division.

CMNDIV.CCDIVI

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/LineNumber

For Warehouse: For Warehouse:

MFTRNS.OSRIDL: MWS070MI/LstContents MWS070MI/LstTransByOrder.; / The field indicates the document reference line number.

ReceiveDelivery/ReceiveDeliveryItem/Status/Code

For Standard: For Standard:

MPLIND.ICPUOS; PPS200MI/GetLineTrans The field indicates the purchase order status (PUOS).

Set to 'Received' if purchase order status is 50, 51, 70 or 75. Set to 'Deleted' if BOD is triggered from MPLIND_DELETE rule.

For Warehouse: MITMAS.MMSTAT

; MMS200MI/GetItmBasic

For Warehouse:

The field indicates the status of the item.

10 - Pending 15 - Pending 20 - Open 30 - Open

40 - Open 50 - DoNotReorder 80 - Obsolete 90 - Obsolete 99 - Deleted

ReceiveDelivery/ReceiveDeliveryItem/ReceivedQuantity

For Standard:

MPLIND.ICRVQA; PPS200MI/GetLineTrans

For Standard:

This indicates the received quantity.

The field indicates the received quantity.

For Warehouse: MFTRNS.OSDLQT;

MWS423MI/LstContents

MGLINE.MRRPQA MGLINE.MRRPQT:

MMS100MI.GetLine.; /

For Warehouse:

For TTYP = 40, use RPQT only if RPQA is 0.

@unitCode

For Standard:

MPLINE.IBPUUN; PPS200MI/GetLine

For Standard:

This indicates the received quantity unit of measure.

For Warehouse: For Warehouse:

MITMAS.MMUNMS; MWS423MI/LstContents MGLINE.MRALUN: MMS100MI.GetLine.; /

The field indicates the received quantity unit of measure.

ReceiveDelivery/ReceiveDeliveryItem/ReceivedBaseUOMQuantity

For Standard:

For Warehouse:

MFTRNS.OSDLQT;

MWS423MI/LstContents MGLINE.MRRPQT;

MPLIND.ICRPQT; PPS200MI/GetLineTrans

For Standard:

The field indicates the received quantity in basic unit of measure.

For Warehouse:

The field indicates the received quantity.

MMS100MI.GetLine.; / @unitCode

For Standard:

For Standard:

MITMAS.MMUNMS; MMS200MI/Get The field indicates the basic unit of measure.

For Warehouse: For Warehouse:

MITMAS.MMUNMS The field indicates the received quantity unit of measure.

; MWS423MI/LstContents

ReceiveDelivery/ReceiveDeliveryItem/UserArea

For Standard:

ReceiveDelivery

ReceiveDelivery	- A
MITTRA.MTWHSL; MWS070MI/LstTransByOrder	For Standard: 1) Location The field indicates the location. Set attribute name to 'eam.Bin'. Retrieve REPN value from Event Data and compare it to MWS070MI/ LstTransByOrder REPN to identify the correct WHSL to display. Call PPS330MI ListPOTrans to check PO status (PUOS). Set TTYP = 20 if PUOS = 50/51. Set TTYP = 22 if PUOS = 64. Set TTYP = 25 if PUOS = 70/75.
ReceiveDelivery/ReceiveDeliveryItem/SerializedLot/ItemQuantity For Warehouse: MFTRNS.OSDLQT ; MWS423MI/LstContents @unitCode	For Warehouse: The field indicates the delivered quantity, expressed in the item's basic U/M.
For Warehouse: MITMAS.MMUNMS ; MMS200MI/GetItmBasic	For Warehouse: The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used. All balance information for the current item is always stored in this unit.
ReceiveDelivery/ReceiveDeliveryItem/SerializedLot/Lot/LotIDs/ID MITTRA.MTBANO; MWS070MI/LstTransByOrder	For Standard: The field indicates the lot number. Set TTYP = 25, RIDN = PUNO, RIDL = PNLI, RIDX = PNLS and ITNO. To Retrieve REPN value from Event Data and compare it to MWS070MI/LstTransByOrder REPN to identify the correct BANO to display.
	For Warehouse: The field indicates the lot number.
ReceiveDelivery/ReceiveDeliveryItem/LineNumber For Standard: MPLIND.ICPNLI MPLINE.ICPNLS.; PPS200MI/GetLineTrans For Warehouse:	For Standard: The field indicates the purchase order reference line number. It is a concatenation of purchase order line (PNLI) and purchase order line subnumber (PNLS).
MHDISL.URRIDL; MWS411MI/LstDeliveryLine MITTRA.MTRIDL; MWS070MI.LstTransByOrder.; /	The position of purchase order line subnumber is determined by its length. If the length of purchase order line subnumber is 0 then the value is 000. If the length of purchase order line subnumber is 1 then the value is
	00 + purchase order line subnumber (PNLS). If the length of purchase order line subnumber is 2 then the value is 0 + purchase order line subnumber (PNLS). For Warehouse: The field indicates the line number.
ReceiveDelivery/ReceiveDeliveryUnit/TrackingID For Warehouse: MPTRNS.ORPANR ; MWS410MI/LstPackageLine	For Warehouse: The field indicates the package number.
ReceiveDelivery/ReceiveDeliveryUnit/ContainerID For Warehouse: MPTRNS.ORCAMU ; MWS410MI/LstPackageLine	For Warehouse: The field indicates the container.
ReceiveDelivery/ReceiveDeliveryUnit/CarrierParty/Name For Standard: MPLIND.ICCARN; PPS200MI/GetLineTrans	For Standard: The field indicates the name of the carrier used.
ReceiveDelivery/ReceiveDeliveryUnit/ShipFromParty/PartyIDs/ID For Standard: MPLINE.IBSUNO; PPS200MI/GetLine @accountingEntity	For Standard: The field indicates the unique identity of a supplier.
For Standard: MPLIND.ICCONO CMNDIV.CCDIVI .; /	For Standard: The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as
ReceiveDelivery/ReceiveDeliveryUnit/ShipmentDateTime For Standard:	Company and Division (CONO_DIVI). For Standard:
MPLIND.ICSMDT; PPS200MI/GetLineTrans ReceiveDelivery/ReceiveDeliveryUnit/Status/Code	The field indicates the shipment date.

ReceiveDeliverv

For Warehouse For Warehouse:

MPTRNS.ORNEWE The field indicates the total weight of all items entered on the ; MWS410MI/LstPackageLine customer order. The information is based on the respective items' net

weight in (MMS001/F) for outstanding and allocated quantities on the

order lines.

@unitCode For Warehouse: For Warehouse:

CSYTAB.CTPARM The field indicates the unit code.

; CRS175MI/GetItemFreeFlds

ReceiveDelivery/ReceiveDeliveryUnit/GrossWeightMeasure

For Warehouse: For Warehouse:

MPTRNS.ORGRW2 The field indicates the total weight for all items that have been ; MWS410MI/LstPackageLine

entered on the order. The basis for this calculation is the gross weight

of each item in the item file multiplied by the quantity

@unitCode

For Warehouse: For Warehouse:

CSYTAB.CTPARM The field indicates the unit code.

; CRS175MI/GetItemFreeFlds

ReceiveDelivery/ReceiveDeliveryUnit/TotalVolumeMeasure

For Warehouse: For Warehouse:

MPTRNS.ORVOL3 The field indicates the volume for each item in the item file or for ; MWS410MI/LstPackageLine

undelivered order lines for a customer order. The latter is calculated automatically by accumulating the remaining quantity of each order

line with the volume of the item.

@unitCode

For Warehouse: For Warehouse:

The field indicates the unit code. CSYTAB.CTPARM

; CRS175MI/GetItemFreeFlds

ReceiveDelivery/ReceiveDeliveryUnit/Container/ContainerID

For Standard: For Standard:

MPLIND.ICCAMU; PPS200MI/GetLineTrans The field indicates the container ID.

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ItemID/ID

For Standard: For Standard:

MPLINE.IBITNO; PPS200MI/GetLine The field indicates the item number.

@accountingEntity

For Standard: For Standard:

MPLIND.ICCONO The field indicates the accounting entity.

CMNDIV.CCDIVI If ItemMaster_MAE is enabled in BOD Processor Master AE tab, this

is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/Description

For Standard: For Standard:

MPLINE.IBPITT; PPS200MI/GetLineX The field indicates the description of an item in a purchase order.

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/OrderQuantity

For Standard: For Standard:

The field indicates the order quantity. MPLINE.IBORQA; PPS200MI/GetLine

@unitCode

For Standard: For Standard:

MPLINE.IBPUUN; PPS200MI/GetLine The field indicates the unit of measure.

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ShippedQuantity

For Standard: For Standard:

The field indicates shipped quantity. MPLIND.ICRPQA; PPS200MI/GetLineTrans

@unitCode

For Standard: For Standard:

MPLINE.IBPUUN: PPS200MI/GetLine The field indicates the unit of measure.

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/Status/Code

For Standard: For Standard:

MPLIND.ICPUOS; PPS200MI/GetLineTrans The field indicates the purchase order status (PUOS).

Set to 'Received' if purchase order status is 50, 51, 70 or 75. Set to 'Deleted' if BOD is triggered from MPLIND DELETE rule.

ReceiveDelivery/ReceiveDeliveryUnit/ReceiveDeliveryUnitItem/ReceivedQuantity

For Standard: For Standard:

MPLIND.ICRVQA; PPS200MI/GetLineTrans This indicates the received quantity. @unitCode

For Standard:

For Standard: MPLINE.IBPUUN; PPS200MI/GetLine This indicates the received quantity unit of measure.

RemitToPartyMaster

Neithici or artywaster	
RemitToPartyMaster/PartyIDs/ID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
@accountingEntity CIDMAS.IDCONO	The field indicates the accounting entity.
CIDMAS.IDDIVI.; /	If RemitToPartyMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
RemitToPartyMaster/PartyIDs/DisplayID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
RemitToPartyMaster/PartyIDs/TaxID CIDMAS.IDCORG; CRS620MI/GetBasicData	The field indicates the supplier's organization number.
RemitToPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
RemitToPartyMaster/LastModificationDateTime CIDMAS.IDLMTS; /	The field indicates the date and time the record was last modified.
RemitToPartyMaster/LastModificationPerson/IDs/ID CIDMAS.IDCHID; /	The field indicates the last person who modified the record.
@accountingEntity CIDMAS.IDCONO CIDMAS.IDDIVI.; /	The field indicates the accounting entity.
GIDINAS.IDDIVI., /	If RemitToPartyMaster is enabled in the BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
RemitToPartyMaster/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates supplier name.
RemitToPartyMaster/Location @type	
CIDADR.SAADTE; CRS620MI/LstAddresses	The field indicates the address type (ADTE).
	Set to 'Postal' if ADTE is 1.
	Set to 'Street' if ADTE is 2.
	Set to 'Pickup' if ADTE is 3.
	Set to 'Origin' if ADTE is 4.
	Set to 'Final' if ADTE is 5. Set to 'Bank' if ADTE is 10.
RemitToPartyMaster/Location/Name	Set to Bank II ADTE IS 10.
CIDADR.SASUNM; CRS620MI/LstAddresses	The field indicates the address name.
RemitToPartyMaster/Location/Address @type	Cat to libraria
RemitToPartyMaster/Location/Address/AddressLine	Set to 'text'.
CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4	The field indicates the address line.
.; CRS620MI/LstAddresses @sequence	
	The field indicates the address line sequence.
RemitToPartyMaster/Location/Address/CityName CIDADR.SATOWN; CRS620MI/LstAddresses	The field indicates the city name.
RemitToPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses @/listID	The field indicates an area, province or state within a country.
	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
RemitToPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses @JistID	The field indicates the country code.
	Set to "Countries".
RemitToPartyMaster/Location/Address/PostalCode CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates the postal code.
RemitToPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT; CRS620MI/LstAddresses	The field indicates the valid from date of the address.
RemitToPartyMaster/Contact/ID CIDREF.IRRFTY	

RemitToPartyMaster CRS620MI/LstSupplierRef The field indicates the field indicates the Reference type (RFTY) and CIDREF.IRRFID Reference (RFID) CRS620MI/LstSupplierRef.; / It is a concatenation of Reference Type (RFTY) < 2 > +'-'+ Reference (RFID) < 10 >. The position of each field is determined by its maximum length, specified in brackets. @accountingEntity CIDMAS.IDCONO The field indicates the company and division, displayed as CIDMAS.IDDIVI.; / CONO DIVI. RemitToPartyMaster/Contact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef The field indicates the name of the contact. RemitToPartyMaster/Contact/Communication @preferredIndicator Set to 'false'. RemitToPartyMaster/Contact/Communication/ChannelCode Set to "Phone" if telephone number 1. Set to "EMail" if e-mail address. @listID Set to "Communication Channels". RemitToPartyMaster/Contact/Communication/UseCode Set to "Office" if telephone number 1 or email address. Set to "Fax" if facsimile number. @listID Set to "Communication Use Codes". RemitToPartyMaster/Contact/Communication/DialNumber 1)CIDREF.IRPHNO The field indicates the dial number 1) Telephone 1 CRS620MI/LstSupplierRef 2)CIDREF.IRTFNO The field indicates the telephone 1 of the contact. CRS620MI/LstSupplierRef 2) Facsimile The field indicates the facsimile number of the contact. RemitToPartyMaster/Contact/Communication/URI The field indicates the e-mail address RemitToPartyMaster/Contact/Preference/Indicator Set to 'false' RemitToPartyMaster/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/LstByAccHolder2 The field indicates the bank number. @accountingEntity CIDMAS.IDCONO The field indicates the accounting entity. CIDMAS.IDDIVI.; / RemitToPartyMaster/FinancialParty/BranchParty/PartyIDs/BICID CBANAC.BCBBRN; CRS692MI/LstByAccHolder2 The field indicates the bank branch identity. RemitToPartyMaster/FinancialParty/FinancialAccount/ID CBANAC.BCBKID; CRS692MI/LstByAccHolder2 The field indicates the bank account identity. RemitToPartyMaster/FinancialParty/FinancialAccount/BBANID The field indicates the bank account number that is not in the format CBANAC.BCBACN; CRS692MI/LstByAccHolder2 IBAN (e.g. Basic Bank Account Number) RemitToPartyMaster/FinancialParty/FinancialAccount/IBANID CBANAC.BCIBAN; CRS692MI/LstByAccHolder2 The field indicates the international bank account number. RemitToPartyMaster/FinancialParty/FinancialAccount/Name CBANAC.BCBANA; CRS692MI/LstByAccHolder2 The field indicates the bank account name RemitToPartyMaster/UserArea CIDMAS.IDSTAT; CRS620MI/GetBasicData The field indicates the status (STAT) of the supplier. If status is 05, set the NameValue '05 - Supplier template'. Set attribute name to 'M3Status'. If status is 10, set the NameValue '10 - Preliminary'. Set attribute name to 'M3Status' If status is 20, set the NameValue '20 - Approved'. Set attribute name to 'M3Status'. If status is 30, set the NameValue '30 - Stopped'. Set attribute name to 'M3Status' If status is 90, set the NameValue '90 - Deactivated'. Set attribute name to 'M3Status'. RemitToPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData The field indicates the status (STAT) of the supplier. Set to 'Closed' if status is 05. Set to 'Pending' if status is 10. Set to 'Open' if the status is 20. Set to 'Hold' if the status is 30. Set to 'Deleted' if the status is 90. Set to 'Deleted' if the record is deleted from CRS620. RemitToPartyMaster/Classification/Codes/Code

Infor May 26, 2023 503

The field indicates the buyer.

CIDVEN.IIBUYE; CRS620MI/GetBasicData

@listID

RemitToPartyMaster

The field indicates the classification code listID

1) Set to 'Buyer' if Classification/Codes/Code is BUYE.

RemittanceAdvice

RemittanceAdvice/RemittanceAdviceHeader/DocumentID/ID FPSUGH.P1PRPN: /	The field indicates the unique number that is assigned to a supplier
	payment proposal when it is created.
@accountingEntity FPSUGH.CONO	The field indicates the company and division, displayed as
FPSUGH.DIVI.; / @variationID	CONO_DIVI.
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical id of the system.
RemittanceAdvice/RemittanceAdviceHeader/DocumentReference @type	
	Set to "ExpenseType".
RemittanceAdvice/RemittanceAdviceHeader/DocumentReference/Doc FPSUGH.P1PRPN; APS130MI/GetHead	cumentID/ID The field indicates the payment proposal number.
@accountingEntity	The field indicates the payment proposal number.
FPSUGH.CONO FPSUGH.DIVI.; /	The field indicates the logical id of the system.
RemittanceAdvice/RemittanceAdviceHeader/Status/Code	
FPSUGH.P1PYST; APS130MI/GetHead	The field indicates the status. If the status (PYST) is equal to 9, set status to "Open".
RemittanceAdvice/RemittanceAdviceHeader/RemitToParty/PartyIDs/I	
FPSUGD.P3SPYN; APS130MI/LstlnvByPayee @accountingEntity	The field indicates the payee.
@	The field indicates the accounting entity.
	If RemitToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
RemittanceAdvice/RemittanceAdviceHeader/PaymentMethodCode	
FPSUGH.P1PYME; APS130MI/GetHead	The field indicates the payment method.
RemittanceAdvice/RemittanceAdviceLine/LineNumber	The field indicates the line number.
RemittanceAdvice/RemittanceAdviceLine/DocumentReference	
@type	Set to "ExpenseReport".
RemittanceAdvice/RemittanceAdviceLine/DocumentReference/DocumentRe	mentID/ID
FPSUGD.P3SINO; APS130Ml/LstInvByPayee	The field indicates the supplier's invoice number.
RemittanceAdvice/RemittanceAdviceLine/PaymentAmount FPSUGD.P3PYCU; APS130MI/LstInvByPayee	The field indicates the payment amount due.
@currencyID FPSUGH.P1CUCD; APS130MI/LstInvByPayee	The field indicates the currency.

Requisition

110 di Sition	
Requisition/RequisitionHeader/DocumentID/ID MPOPLP.POPLPN; PPS170MI/GetPlannedPO	The field indicates the planned order.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MPOPLP.POWHLO; /	The field indicates the warehouse location.
@variationID	The field indicates the sequence number. Sequence number is an
@lid	internal number to ensure documents are processed in correct order.
	The field indicates the logical ID of the system that is SOR for this noun instance.
Requisition/RequisitionHeader/LastModificationDateTime MPOPLP.POLMTS; /	The field indicates the last modified date and time of the data.
Requisition/RequisitionHeader/LastModificationPerson/IDs/ID MPOPLP.POCHID; /	The field indicates the ID of the person that entered/changed the recored.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Requisition/RequisitionHeader/DocumentDateTime MPOPLP.PORGDT MPOPLP.PORGTM : DDS470MI/CetPlennedDO	The field indicates the date and time the document was created.
MPOPLP.PORGTM.; PPS170MI/GetPlannedPO Requisition/RequisitionHeader/DocumentReference	These are set automatically and transformed to UTC time zone.
@type MPOPLP.PORORC; PPS170MI/GetPlannedPO	The field indicates the origin of the reference order number.
	Set to 'Normal Order' if RORC = 0 Set to 'Manufacturing order' if RORC = 1 Set to 'Purchase order' if RORC = 2 Set to 'Customer order' if RORC = 3 Set to 'Requisition order' if RORC = 4 Set to 'Distribution order' if RORC = 5 Set to 'Work order' if RORC = 6 Set to 'Service order' if RORC = 7 Set to 'Project order' if RORC = 8 Set to 'Claim order' if RORC = 9
Requisition/RequisitionHeader/DocumentReference/DocumentID/ID MPOPLP.PORORN; PPS170MI/GetPlannedPO @accountingEntity	The field indicates a reference order number.
MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Requisition/RequisitionLine/LineNumber MPOPLP.POPLPS; PPS170MI/LstPlannedPO	The field indicates a subnumber which is set automatically when the planned order is created. The subnumber is used internally by the system.
Requisition/RequisitionLine/DocumentReference/DocumentID/ID MPOPLP.PORORN; PPS170MI/GetPlannedPO	The field indicates a reference order number.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Requisition/RequisitionLine/Status/Code MPOPLP.POPSTS; PPS170MI/GetPlannedPO	The field indicates the status of the planned order.
	Set to 'Pending" if PSTS = 00, 05. Set to "Open" if PSTS = 10, 15, 20, 30, 40, 50, 55. Set to "Approved" if PSTS = 60.
Requisition/RequisitionLine/Item/Item/D/ID MPOPLP.POITNO; PPS170MI/GetPlannedPO	The field indicates the item number (for Maintenance, the item number or equipment number), which is a unique ID for an individual item.
@accountingEntity MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
Requisition/RequisitionLine/Quantity MPOPLP.POPPQT; PPS170MI/GetPlannedPO	The field indicates the quantity that has been calculated to cover a future requirement. The quantity is expressed in purchase order unit of measure
@unitCode MPOPLP.POPUUN; PPS170MI/GetPlannedPO	The field indicates the unit of measure (U/M) in which the quantity on the purchase order is expressed.
	The purchase order U/M can be the alternate U/M or the item's

Requisition

110 4 410 1110 11	
	standard purchase U/M, if an alternate does exist. If there is no standard purchase U/M, the item's basic U/M is used.
Requisition/RequisitionLine/BaseUOMQuantity MPOPLP.POTRQT; PPS170MI/GetPlannedPO	The field indicates the quantity in the basic unit of measure for the planned or actual transaction.
@unitCode MPOPLP.POUNMS; PPS170MI/GetPlannedPO	The field indicates the unit in which each item is recorded in inventory.
Requisition/RequisitionLine/UnitPrice/Amount MPOPLP.POPUPR; PPS170MI/GetPlannedPO	The field indicates the purchase price for one unit.
@currencyID MPOPLP.POCUCD; PPS170MI/GetPlannedPO	The field indicates the currency.
Requisition/RequisitionLine/UnitPrice/PerQuantity MPOPLP.POPUCD; PPS170MI/GetPlannedPO	The field indicates the unit price per quantity. If PUCD is is less than 1, then the value of the element will be set to 1. If more thant 1, then the value of PUCD will be displayed.
@unitCode MPOPLP.POPPUN; PPS170MI/GetPlannedPO	The field indicates the purchase price unit of measure.
Requisition/RequisitionLine/ExtendedAmount MPOPLP.POPUPR MPOPLP.POPPQT.; PPS170MI/GetPlannedPO	The field indicates gross Line amount in order currency before any discounts or charges or taxes are applied. It is calculated as Purchase price for one unit*Planned quantity.
@currencyID MPOPLP.POCUCD; PPS170MI/GetPlannedPO	The field indicates the currency.
Requisition/RequisitionLine/ExtendedBaseAmount MPOPLP.POPUPR; PPS170MI/GetPlannedPO	The field indicates the sales price expressed in the service order's currency or the agreement price in the agreement's currency.
@currencyID CMNDIV.CCLOCD; PPS170MI/GetPlannedPO	The field indicates the local currency, that is, the basic currency used by the division.
Requisition/RequisitionLine/RequiredDeliveryDateTime MPOPLP.PODLDT; PPS170MI/GetPlannedPO	The field indicates the planned delivery date.
Requisition/RequisitionLine/UserArea/Property/NameValue MPOPLP.POPLP2; PPS170MI/GetPlannedPO @name	The field indicates the SubNumber-order proposal.
	Set to 'Proposal sub-number'.
Requisition/RequisitionLine/SupplierParty/PartyIDs/ID MPOPLP.POSUNO; PPS170MI/GetPlannedPO @accountingEntity	The field indicates the unique identity of a supplier.
MPOPLP.POCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.

SalesOrder/SalesOrderHeader/DocumentID/ID OOHEAD.OAORNO: /	The field indicates the Customer Order Number.
@accountingEntity	
OOHEAD.OACONO+OADIVI; / @location	The field indicates the company and division, displayed as CONO_DIVI.
OOHEAD.OAWHLO; / @variationID	The field indicates the location/warehouse.
@lid	The field indicates the number of variation for the object
	The field indicates the logical ID
SalesOrder/SalesOrderHeader/AlternateDocumentID/ID OOHEAD.OACUOR OAORNO; OIS100MI OIS275MI/GetHead GetTmpOrderStat	The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents. The field indicates the temporary customer order number created in Batch Customer Order module in M3.
@schemeName	The field indicates a fixed value 'Customer'
SalesOrder/SalesOrderHeader/LastModificationDateTime	This indicates the last modification date and time of the BOD. The value is retrieved from the event date and time.
SalesOrder/SalesOrderHeader/LastModificationPerson/IDs/ID OOHEAD.OACHID; OIS100MI/GetOrderHead @accountingEntity	The field indicates the ID of the user (CHID) who was the last to change the sales order.
OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/LastModificationPerson/Name CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates the Name (NAME) of the user who was the last to change the sales order.
SalesOrder/SalesOrderHeader/DocumentDateTime OOHEAD.OAORDT; OIS100MI/GetOrderHead	This indicates the date and time of the sales order.
SalesOrder/SalesOrderHeader/Note OSYTXH.THTX40; OIS100MI/LstHeadTxt	The field indicates the remarks or notes.
@type	The field indicates a fixed value: for Pre-text field, 'Pre-Text' . for Post-Text field, 'Post-text', and for Text field, 'Text' is published.
SalesOrder/SalesOrderHeader/DocumentReference @type	Set to 'Quote' if quote id is not blank.
SalesOrder/SalesOrderHeader/DocumentReference/DocumentID/ID OOHEAD.OAOFNO; OIS100MI/GetOrderHead	The field indicates the quote id.
@accountingEntity OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/Status/Code OOHEAD.OAORSL; OIS100MI/GetOrderHead	The field indicates the customer orders lowest status, M3 BE field ORSL. It is translated according to: 22,23,24,26,27,29 = Approved 33,34,36,37,39,44,46,47,49 = Allocated 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Deleted 99 = Canceled
SalesOrder/SalesOrderHeader/Status/EffectiveDateTime OOHEAD.OAORDT; OIS100MI/GetOrderHead	The field indicates the document date. If Status is equal to 'Approved' or 'In Process', the Order Date field is published. If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken. Default filled with the UTC number of the Date and Time when the BOD is published.
SalesOrder/SalesOrderHeader/Status/ReasonCode OOHEAD.OAOBLC; 0IS100MI/GetOrderHead @listID	The field indicates the customer order stop. 1) If OBLC = 1 then set to 'CreditLimit 1'. 2) If OBLC = 2 then set to 'CreditLimit 2'. 3) If OBLC = 3 then set to 'CreditLimit 3'. 4) If OBLC = 4 then set to 'CreditLimit 4'. 5) If OBLC = 5 then set to 'Connected to LOC'. 6) If OBLC = 6 then set to 'Credit limit'. 7) If OBLC = 7 then set to 'Manually set stop'. 8) If OBLC = 8 then set to 'Manually released order'.

SalesOluei	
	Set to 'M3 Hold Reasons'.
SalesOrder/SalesOrderHeader/Status/ArchiveIndicator	
	Set to 'true' if order status is 77. Set to 'false if order status is 99.
Salas Orday/Salas OrdayHaaday/Cuata may Bayty/Bayty/Da/ID	Set to Taise it order status is 99.
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OOHEAD.OACUNO; OIS100MI/GetOrderHead @accountingEntity	The field indicates the customer identity.
OOHEAD.OACONO+ OADIVI: /	The field indicates the accounting entity.
J. D. IV., 7	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO_DIVI), e.g. 760_AAA.
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the VAT registration number
SalesOrder/SalesOrderHeader/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the Customer name
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address@type	
шіуре	The field indicates a fixed value of 'text'
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/AOOHEAD.OARESP; CRS610MI/GetBasicData	
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/	· · · · · · · · · · · · · · · · · · ·
OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKOCUA3	The field indicates the Address fields (4 fields).
OCUSMA.OKOCUA4.; CRS610MI/GetBasicData @sequence	
	The field indicates the sequence number.
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/	
OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the City.
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/GOCUSMA.OKECAR; CRS610MI/GetBasicData	CountrySubDivisionCode The field indicates the state.
@listID	The field indicates the list ID depending on the country:
	- Canada has list ID 'Canadian Provinces'
	- France has list ID 'France - Departements'
	- United States has list ID 'US States'
0.1.0.1.0.1.0.1.0.1.111.101.10	- Other countries have list ID 'SubDivisions - [country code]'
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/ OCUSMA.OKCSCD; CRS610MI/GetBasicdata @listID	The field indicates the CountryCode
<u> </u>	The field indicates the list ID
SalesOrder/SalesOrderHeader/CustomerParty/Location/Address/l	PostalCode
OCUSMA.OKPONO; CRS610MI/GetBasicData	The field indicates the Postal code
SalesOrder/SalesOrderHeader/CustomerParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer	The field indicates the contact ID
@accountingEntity OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/CustomerParty/Contact/Name	
OCUSCO.CCTX50; CMSO55MI/LstByCustomer	The field indicates the contact person
SalesOrder/SalesOrderHeader/SupplierParty/Communication/Dial	
OOADRE OPPING	The field indicates the telephone/telefax number of the customer.
OOADRE.OPPHN2 OOADRE.OPTFNO	PHN0 and PHN2 is phone numbers. TFNO is fax number.
.; OIS100MI/GetAddress	TI NO IS IAX HUMBEL.
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID	
OOHEAD.OADECU +	The field indicates the Customer shipping address code
OAADID; OIS100MI/GetAddress	
@accountingEntity OOHEAD.OACONO+	The field indicates the accounting entity
OADIVI; /	The field indicates the accounting entity.
Ondivi, /	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderHeader/ShipToParty/Name	
OCUSAD .OPCUNM; OIS100MI/GetAddress	The field indicates the Customer identity.
SalesOrder/SalesOrderHeader/ShipToParty/Location	
@type	The field indicates a fixed value of 'text'

SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Attention OCUSAD.OPYREF; OIS100MI/GetAddress	onOfName The field indicates the customer's contact person.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Address OCUSAD.OPCUA1 OCUSAD.OPCUA2 OCUSAD.OPCUA3 OCUSAD.OPCUA4 .; OIS100MI/GetAddress @sequence	
	The field indicates the line sequence of the address.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/CityNam OCUSAD .OPTOWN; OIS100MI/GetAddress	The field indicates the City.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Country OCUSAD .OPECAR; OIS100MI/GetAddress @listID	/SubDivisionCode The field indicates the state.
	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Country OCUSAD .OPCSCD; OIS100MI/GetAddress @listID	The field indicates the CountryCode.
Color Oudew/Color Oudew/less-to-/Okin To Bonda // Color Oudew/Color Oudew/Colo	The field indicates the list ID
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/PostalCOCUSAD OPPONO; OIS100MI/GetAddress	The field indicates the Postal code.
SalesOrder/SalesOrderHeader/ShipToParty/Communication @preferredIndicator	
Solo Oudov/Solo Oudov/Loodov/Shin To Bouts/Communication/Shanne/	Set to 'false'.
SalesOrder/SalesOrderHeader/ShipToParty/Communication/ChannelO	Set to 'Phone' if Telephone number 1. Set to 'Phone' if Telephone number 2. Set to 'Fax' if Facsimile number. Set to 'Email' if Email address.
@listID	Set to 'Communication Channels'.
SalesOrder/SalesOrderHeader/ShipToParty/Communication/UseCode	Set to Communication Ghamlers.
@listID	Set to 'Office' if the field Telephone number 1. Set to 'Office' if the field Telephone number 2. Set to 'Fax' if the Facsimile number. Set to 'Office' if the E-mail address.
	Set to 'Communication Use Codes'
SalesOrder/SalesOrderHeader/ShipToParty/Communication/Preference	
Soloo Oudou/Soloo Oudoul loo dou/Shin To Bouts/Contoot/ID	Set to 'false'.
SalesOrder/SalesOrderHeader/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEntity	The field indicates the contact ID
	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/ShipToParty/Contact/Name OCUSCO.CCCNPE; CMSO55MI/LstByCustomer	The field indicates the contact name.
SalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OOLINE.OBWHLO; OIS100MI/GetOrderHead @accountingEntity	The field indicates the warehouse
OOHEAD.OACONO+ OADIVI; /	The field indicates the company and division, displayed as CONO_DIVI.
SalesOrder/SalesOrderHeader/ShipFromParty/Name MITWHL.MWWHNM; MMS005/GetWarehouse	The field indicates the warehouse name
SalesOrder/SalesOrderHeader/ShipFromParty/Location @type	1) Set to 'Warehouse' 2) Set to 'Site'
SalesOrder/SalesOrderHeader/ShipFromParty/Location/ID 1) OOHEAD.OAWHO 2) OOHEAD.OAFACI.; OIS100MI/GetOrderHead	The field indicates the warehouse. The field indicates the facility.
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address @type	The field indicates a fixed value 'text'

<u> </u>	
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/MITWHL.MWADR1 MITWHL.MWADR2 MITWHL.MWADR3 MITWHL.MWADR4: MMS005MI/CetWarehouse	AddressLine The field indicates the Address fields (4 fields)
MITWHL.MWADR4.; MMS005MI/GetWarehouse	OV. N
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/ MITWHL.MWTOWN; MMS005MI/GetWarehouse	CityName The field indicates the City
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/ MITWHL.MWECAR; MMS005MI/GetWarehouse @listID	CountrySubDivisionCode The field indicates the Area
	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/MITWHL.MWCSCD; MMS005MI/GetWarehouse	CountryCode The field indicates the CountryCode
@listID	The field in disease the Bet ID
SalesOrder/SalesOrderHeader/ShipFromParty/Location/Address/MITWHL.MWPONO: MMS005MI/GetWarehouse	The field indicates the list ID (PostalCode The field indicates the Postal code
SalesOrder/SalesOrderHeader/ContractReference/DocumentID/ID	
OOHEAD.OAAGNO; OIS100MI/GetOrderHead @accountingEntity	The field indicates the agreement number.
	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/ExtendedAmount OOHEAD.OABRAM; OIS100MI/GetOrderValue @currencyID	The field indicates the Gross Order Value
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the Currency of the Gross Order Value
SalesOrder/SalesOrderHeader/TotalAmount OOHEAD.OATOPY+OAITOP; OIS100MI/GetOrderValue @currencyID	The field indicates the Total value
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the Currency of the Total value
SalesOrder/SalesOrderHeader/BillToParty/PartyIDs/ID OOHEAD.OAINRC; OIS100MI/GetOrderHead	The field indicates the Invoice Recipient
@accountingEntity OOHEAD.OACONO+ OADIVI; /	The field indicates the accounting entity.
	If BillToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
SalesOrder/SalesOrderHeader/BillToParty/Name OCUSAD.OPCUNM; OIS100MI /GetAddress	The field indicates the invoice recipient.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address @type	The field indicates a fixed value of 'text'
Salas Ordar/Salas Ordar Handar/Bill To Barty/Logation / Address / Atta	
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Atte OCUSAD .OPYREF+OPYRE1; OIS100MI /GetAddress	The field indicates the customer's contact person.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Add	ressl ine
OCUSAD.OPCUA1 OCUSAD.OPCUA2 OCUSAD.OPCUA3 OCUSAD.OPCUA4.; OIS100MI /GetAddress	The field indicates the Address fields (4 fields) for (Invoice recipient).
@sequence	The field indicates the sequence number of the address line
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/City OCUSAD .OPTOWN; OIS100MI	·
/GetAddress	
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Cou OCUSAD .OPECAR; OIS100MI	IntrySubDivisionCode The field indicates the Area
/GetAddress	
@listID	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'

SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Count	
OCUSAD	The field indicates the CountryCode (invoice recipient).
.OPCSCD; OIS100MI /GetAddress	
@listID	-
	The field indicates the list ID
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Postal OCUSAD	Code The field indicates the Postal code (Invoice recipient).
OPPONO; OIS100MI	The hold indicates the Fostal code (involce recipienty.
/GetAddress	
SalesOrder/SalesOrderHeader/BillToParty/Contact/ID	
OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEntity	The field indicates the contact ID
OOHEAD.OACONO+OADIVI: /	The field indicates the company and division, displayed as
	CONO_DIVI.
SalesOrder/SalesOrderHeader/BillToParty/Contact/Name OCUSCO.CCTX50; CMSO55MI/LstByCustomer	The field indicates the Our reference person number 1 and number 2.
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/ID	
OOHEAD.OAPYNO; OIS100MI/GetOrderHead	The field indicates the Payer
@accountingEntity OOHEAD.OACONO+	The field indicates the accounting entity.
OADIVI; /	The field indicates the accounting entity.
	If PayFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO_DIVI), e.g. 760_AAA.
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderHeader/PayFromParty/Name	THE HOLD HIGHOUSES THE TRATES
OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the Customer name (Payer)
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address	
@type	The field indicates a fixed value 'text'
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Att	
OCUSMA.OKYREF; CRS610MI/GetBasicData	The field indicates the customer's contact person.
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Ad OCUSMA.OKCUA1- OKCUA4; CRS610MI/GetBasicData	dressLine The field indicates the Address fields (4 fields) for (Payer)
@sequence	The field indicates the sequence number of the address line
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Cit	·
OCUSMA.OKTOWN; CRS610MI/GetBasicData	The field indicates the City (Payer)
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Co OCUSMA.OKECAR; CRS610MI/GetBasicData @JistID	The field indicates the state
@c2	The field indicates the list ID depending on the country:
	- Canada has list ID 'Canadian Provinces'
	- France has list ID 'France - Departements'
	 - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Co	
OCUSMA.OKCSCD; CRS610MI/GetBasicData @/listID	The field indicates the CountryCode
-	The field indicates the list ID
SalesOrder/SalesOrderHeader/PayFromParty/Location/Address/Po- OCUSMA.OKPONO; CRS610MI/GetBasicData	stalCode The field indicates the Postal code (Payer)
SalesOrder/SalesOrderHeader/PayFromParty/Location/Status/Code	· · · ·
OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the customer status, M3 BE field STAT.
·	It is translated according to:
	10, 11 or 12 = Pending
	20 = Open 90 = Closed
SalesOrder/SalesOrderHeader/PayFromParty/Contact/ID	UU OIUGUU
OCUSCO.CCCNPE; CMSO55MI/LstByCustomer	The field indicates the contact ID
@accountingEntity	
OCUSCO.CONO+DIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/PayFromParty/Contact/Name	OONO_DIVI.
OCUSCO.CCTX50; CMSO55MI/LstByCustomer	The field indicates the Our reference person number 1 and number 2 (Payer)
SalesOrder/SalesOrderHeader/TransportationTerm/IncotermsCode OOHEAD.OATEDL; OIS100MI/GetOrderHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.

	Set to 'Incoterms'.
SalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOwnership	
CSYTAB.CCDELT; CRS065MI/GetDelyTerm	The field indicates the delivery terms.
SalesOrder/SalesOrderHeader/TransportationTerm/PlaceOfOwnership	
CSYTAB.CTTX40; CRS065MI/GetDelyTerm	The field indicates when the liability for a delivery is transferred from
	the supplier to the buyer. The date on which liability is transferred is
	defined as the delivery date.
	Alternatives
	1 = The buyer assumes liability when the goods leave the supplier's
	inventory.
	2 = The buyer assumes liability when the goods are received at the
	buyer's transport address.
	3 = The buyer assumes liability when the goods are received at the buyer's final address.
SalesOrder/SalesOrderHeader/TransportationMethodCode	24) 5. 5 mm daa. 666.
OOHEAD.OAMODL; OIS100MI/GetOrderHead	The field indicates the delivery method code
DistID	,
	The field indicates the ListID 'Transportation Methods'
SalesOrder/SalesOrderHeader/PaymentTerm/PaymentTermCode	
OOHEAD.OATEPY; OSI100MI/GetOrderHead	The field indicates the payment term ID
DlistID	
	Set to 'Payment Term'.
Sales Order/Sales Order Header/Payment Term/Term/ID	T. 6.11: 1: 4 4
OOHEAD.OATEPY; OSI100MI/GetOrderHead	The field indicates the payment term ID
@accountingEntity OOHEAD.OACONO+	The field indicates the company and division, displayed as
OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/PaymentTerm/Term/Description	
OOHEAD.OATXPY; CRS175MI/GetGeneralCode	The field indicates the payment term description
SalesOrder/SalesOrderHeader/DistributedCharge/Description	
OOCHRG.OECRDO; OIS100MI	The field indicates the charge description:
/LstOrderCharges	Line Charge
	Order Discount
	Service Charge
	Header Charges
	Rounding off
SalesOrder/SalesOrderHeader/DistributedCharge/Amount	
OOLICH.PBAM	The field indicates the distributed amount for the ff:
OOHEAD.ODAM+IDAM	Line Charge
OHEAD.EXAM+IXAM	Order Discount
OOCHRG.PBAM	Service Charge
OOHEAD.ROAM+IROA.; OIS100MI	Header Charges
/GetLineChrgTot	Rounding off
GetOrderValue	· ·
GetOrderValue	
LstOrderCharges	
GetOrderValue	
DcurrencyID	
OOCHRG.OECUCD; OIS100MI/LstOrderCharges	The field indicates the Currency
SalesOrder/SalesOrderHeader/DistributedCharge/ReasonCode	
OOCHRG.OECRD0; OIS100MI/LstOrderCharges	The field indicates the charge description:
-	Line Charge
	Order Discount
	Service Charge
	Header Charges
	Rounding off
DistID	Sat to 'Deacons for Charge'
Salos Ordor/Salos Ordor Hoador/Distributed Charge / Calculation ##a44-a44	Set to 'Reasons for Charge'.
GalesOrder/SalesOrderHeader/DistributedCharge/CalculationMethodO OOCHRG.OECRME; OIS100MI/LstConnCOCharge	The field indicates how a charge is to be calculated or entered for
	each item charge.
	Alternatives
	0 = Amount, no calculation is made
	1 = Calculation factor * gross price
	2 = Calculation factor * net price
	2 = Calculation factor * net price 3 = Calculation factor * gross weight
	2 = Calculation factor * net price 3 = Calculation factor * gross weight 4 = Calculation factor * net weight
	2 = Calculation factor * net price 3 = Calculation factor * gross weight
alesOrder/SalesOrderHeader/DistributedCharge/GrossWeightIndicat	2 = Calculation factor * net price 3 = Calculation factor * gross weight 4 = Calculation factor * net weight 5 = Calculation factor * volume 6 = Amount per quantity.
SalesOrder/SalesOrderHeader/DistributedCharge/GrossWeightIndicat	2 = Calculation factor * net price 3 = Calculation factor * gross weight 4 = Calculation factor * net weight 5 = Calculation factor * volume 6 = Amount per quantity.

	Set to 'VAT' if tax method is 4. Set to 'Sales Tax' if tax method is 3.
SalesOrder/SalesOrderHeader/DistributedTax/ID	Set to 'Tax'.
SalesOrder/SalesOrderHeader/DistributedTax/Description	The field has a fixed value of 'Tax'
SalesOrder/SalesOrderHeader/DistributedTax/Amount OOHEAD.OAVTAM+OAIVTA; OIS100MI/GetOrderValue @currencyID	The field indicates the Tax amount
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the currency
SalesOrder/SalesOrderHeader/EarliestDeliveryDateTime OOHEAD.OAFDDT; OIS100MI/GetOrderHead	The field indicates the Earliest Delivery Date.
SalesOrder/SalesOrderHeader/RequiredDeliveryDateTime OOHEAD.OARLDT & OARLHM; OIS100MI/GetOrderHead	The field indicates the Requested Delivery Date and Time
SalesOrder/SalesOrderHeader/PaymentMethodCode OOHEAD.OAPYCD; OIS100MI/GetOrderHead	The field indicates the AR payment method. The payment method code is translated in CRS881 (e.g. Cash, Cheque). If no translation exist in CRS881, the following translation is followed based on the payment class: Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1. Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5.
SalesOrder/SalesOrderHeader/UserArea OOHEAD.OAYREF; OIS100MI/GetOrderHead	1) The field indicates the customer's contact person. Set attribute name to 'AttentionOfName'. 2) The field indicates the BODID from the sending application.
	Set attribute name to 'ProcessBODID'.
SalesOrder/SalesOrderHeader/PricingRequiredIndicator	Set to 'false'.
SalesOrder/SalesOrderHeader/SalesPersonReference/IDs/ID OOHEAD.OASMCD; OIS100MI/GetOrderHead @accountingEntity OOHEAD.OACONO+ OADIVI; /	The field indicates the Salesman The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/SalesPersonReference/Name CSYTAB.CTTX15; CRS100MI/Get	The field indicates the Name of Salesperson
SalesOrder/SalesOrderHeader/Classification/Codes/Code 1) OOHEAD.OARESP OIS100MI/GetHead 2) OOHEAD.OAPROJ OIS100MI/GetHead 3) OOHEAD.OAELNO OIS100MI/GetHead 4) OOHEAD.OASPLM OIS100MI/GetHead 5) OOHEAD.OAFRE1 OIS100MI/GetOrderHead 6) OOHEAD.OAPYCD OIS100MI/GetOrderHead.; /	1) CO Resp The field indicates the CO responsible. Set attribute listID to 'Responsible'. 2) Project number The field indicates the project number. Set attribute listID to 'Project Numbers'. 3) Project element The field indicates the project element number. Set attribute listID to 'Project Elements'. 4) Supply model The field indicates the supply model. Set attribute listID to 'Supply Model'. 5) Statistics Identity 1 Customer The field indicates a user-defined customer statistics accumulator. Set attribute listID to 'Customer Statistics Identity1'.
@sequence @listID	6) AR Payment Method The field indicates the AR Payment method. The field indicates the sequence number. 1) Set to 'Responsible' if Classification/Codes/Code = RESP. 2) Set to 'Project Numbers' if Classification/Codes/Code = PROJ. 3) Set to 'Project Elements' if Classification/Codes/Code = ELNO. 4) Set to 'Supply Model' if Classification/Codes/Code = SPLM. 5) Set to 'Customer Statistics Identity1' if Classification/Codes/Code =

	FRE1. 6) Set to 'Payment Methods' if Classification/Codes/Code = PYCD.
SalesOrder/SalesOrderHeader/ExtendedPretaxAmount	· · · · · ·
OOHEAD.OAORVA+OAIRVA; OIS100MI/GetOrderValue @currencyID	The field indicates the pre-tax amount.
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the currency.
SalesOrder/SalesOrderHeader/SubTotalAmount OOHEAD.OANTAM+ OAINTA; OIS100MI/GetOrderValue @currencyID	The field indicates the sub-total amount.
OOHEAD.OACUCD; OIS100MI/GetOrderValue	The field indicates the currency.
SalesOrder/SalesOrderHeader/OrderTypeCode	The field indicates the quaternay and automa
OOHEAD.OAORTP; OIS100MI/GetOrderHead SalesOrder/SalesOrderLine/LineNumber	The field indicates the customer order type
OOLINE.OBPONR; OIS100MI/LstLineBOD SalesOrder/SalesOrderLine/Description	The field indicates the Order Line number
OOLINE.OBTEDS; OIS100MI/LstLineBOD	The field indicates a description.
SalesOrder/SalesOrderLine/Note OSYTXL .TLTX40; OIS100MI/LstLineTxt	The field indicates the remarks or notes.
@type	For Pre-text field, 'Pre-Text' is published. For Post-Text field, 'Post-text' is published.
SalesOrder/SalesOrderLine/Status/Code OOLINE.OBORST; OIS100MI/LstLineBOD	The field indicates the customer order lines status, M3 BE field ORST. It is translated according to: 22,23,24,26,27,29 = Approved 33,34,36,37,39,44,46,47,49 = Allocated 66, 67 or 69 = Shipped 77 or 79 = Invoiced 90 = Deleted 99 = Canceled
SalesOrder/SalesOrderLine/Status/EffectiveDateTime OOHEAD.OAORDT; OIS100MI/GetOrderHead	The field indicates the status date. If Status is equal to 'Approved' or 'In Process', the Order Date field is published. If Status is equal to 'Closed' or 'Canceled', the transaction time of the last entry in Sales Order History is taken. Default filled with the UTC number of the Date and Time when the BOD is published.
SalesOrder/SalesOrderLine/Status/ArchiveIndicator	The field indicates the status of the line. If the Sales Order Line is deleted or the Sales Order is deleted and the Order Status is equal to 'Closed' or 'Released', 'true' is published. Otherwise, 'false' is published.
SalesOrder/SalesOrderLine/Item OOLINE.TEPY; OIS100MI/LstLineBOD	The field indicates the payment term
SalesOrder/SalesOrderLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLineBOD @accountingEntity	The field indicates the Item Number
OOHEAD.OACONO+	The field indicates the accounting entity.
OADIVI; /	If ItemMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
SalesOrder/SalesOrderLine/Item/Description OOLINE.OBITDS: OIS100MI/LstLineBOD	The field indicates the Item description
SalesOrder/SalesOrderLine/Item/SerializedLot/Lot/LotIDs/ID OOLINE.OBBANO; OIS100MI/LstLineBOD	The field indicates the lot number.
SalesOrder/SalesOrderLine/Quantity OOLINE.OBORQA; OIS100MI/LstLineBOD	The field indicates the Quantity for order line in alternate Unit of Measure.
@unitCode OOLINE.OBALUN; OIS100MI/LstLineBOD	The field indicates the alternate Unit of Measure.
SalesOrder/SalesOrderLine/BaseUOMQuantity OOLINE.OBORQT; OIS100MI/LstLineBOD	The field indicates the Quantity for order line in Basic Unit of Measure.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
Sales Order/Sales OrderLine/UnitPrice/Amount OOLINE.OBSAPR; OIS100MI/LstLineBOD	The field indicates the unit sales price amount.
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the currency
SalesOrder/SalesOrderLine/UnitPrice/BaseAmount OOLINE.OBSAAM/ OBORQT; OIS100MI/LstLineBOD	The field indicates the unit base price amount

<u>Jaics Oraci</u>	
@currencyID OOLINE.OBLOCD; OIS100MI/LstLineBOD	The field indicates the currency
SalesOrder/SalesOrderLine/UnitPrice/PerQuantity OOLINE.OBSACD; OIS100MI/LstLineBOD	The field indicates the quantity to which the sales price applies. Sales price quantity is defined for each item and is expressed in the Sales price Unit of Measure.
@unitCode OOLINE.OBSPUN; OIS100MI/LstLineBOD	The field indicates the Sales price Unit of Measure.
SalesOrder/SalesOrderLine/ExtendedAmount OOLINE.OBGLAM; OIS100MI/LstLineBOD	The field indicates the gross line amount
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/ExtendedBaseAmount OOLINE.OBSAAM; OIS100MI/LstLineBOD @currencyID	The field indicates the net line amount in local currency.
OOLINE.OBLOCD; OIS100MI/LstLineBOD	The field indicates the local currency.
SalesOrder/SalesOrderLine/TotalAmount OOLINE.OBNLAM; OIS100MI/LstLineBOD @currencyID	The field indicates the Net Line Amount
OOLINÉ.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/RequiredDeliveryDateTime OOLINE.OBDWDZ+ OBDWHZ; OIS100MI/LstLineBOD	The field indicates the Requested Delivery date
SalesOrder/SalesOrderLine/ShipToParty/PartyIDs/ID OOHEAD.OADECU + OAADID; OIS100MI/GetLineAddress	The field indicates the Customer shipping address code
@accountingEntity OOHEAD.OACONO+ OADIVI: /	The field indicates the accounting entity.
OADIVI; /	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.
SalesOrder/SalesOrderLine/ShipToParty/PartyIDs/TaxID OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the Tax ID
SalesOrder/SalesOrderLine/ShipToParty/Name OOADRE .ODCUNM; OIS100MI /GetLineAddress	The field indicates the Customer name.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address @type	The field indicates a five divelve blood
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/Attention/OADRE .ODYREF+ODYRE1; OIS100MI /GetLineAddress	The field indicates a fixed value 'text' tionOfName The field indicates the customer's contact person.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/AddresOADRE.ODCUA1 OOADRE.ODCUA2 OOADRE.ODCUA3 OOADRE.ODCUA4.; OIS100MI /GetLineAddress @sequence	PessLine The field indicates the Address fields (4 fields).
<u> </u>	The field indicates the address line sequence number.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/CityNet OOADRE .ODTOWN; OIS100MI /GetLineAddress	ame The field indicates the City.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/Count OOADRE .ODECAR; OIS100MI /GetLineAddress	trySubDivisionCode The field indicates the Area.
@listID	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States has list ID 'US States' - Other countries have list ID 'SubDivisions - [country code]'
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/Count OOADRE .ODESCD; OIS100MI /GetLineAddress	The field indicates the CountryCode.
SalesOrder/SalesOrderLine/ShipToParty/Location/Address/Posta OOADRE .ODPONO; OIS100MI	ICode The field indicates the Postal Code.

SalesOrder	
/GetLineAddress	
SalesOrder/SalesOrderLine/ShipToParty/Communication	
@preferredIndicator	0-44- 16-11
0-10	Set to 'false'.
SalesOrder/SalesOrderLine/ShipToParty/Contact/ID OCUSCO.CCCNPE; CMSO55MI/LstByCustomer @accountingEntity	The field indicates the contact ID
OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderLine/ShipToParty/Contact/Name OCUSCO.CCTX50; CMSO55MI/LstByCustomer	The field indicates the Customer responsible.
SalesOrder/SalesOrderLine/ShipToParty/Contact/Communication/F	Preference/Indicator Set to 'false'.
SalesOrder/SalesOrderLine/TransportationTerm/IncotermsCode	Set to Taise .
OOLINE.OBTEDL; OIS100MI/LstLineBOD	The field indicates delivery terms, which control when transport responsibility shifts from supplier to customer.
@listID	Set to 'Incoterms'
SalesOrder/SalesOrderLine/TransportationTerm/PlaceOfOwnership	
CSYTAB.CTTX40; CRS065MI/GetDelyTerm	The field indicates when the liability for a delivery is transferred from the supplier to the buyer. The date on which liability is transferred is defined as the delivery date. Alternatives 1 = The buyer assumes liability when the goods leave the supplier's inventory. 2 = The buyer assumes liability when the goods are received at the buyer's transport address. 3 = The buyer assumes liability when the goods are received at the buyer's final address.
SalesOrder/SalesOrderLine/TransportationMethodCode OOHEAD.OAMODL; OIS100MI/GetOrderHead	The field indicates the delivery method code
@listID	The field indicates the ListID 'Transportation Methods'
SalesOrder/SalesOrderLine/PaymentTerm/PaymentTermCode OOLINE.OBTEPY; OIS100MI/LstLineBOD @listID	The field indicates the payment term
	Set to 'Payment Term'.
SalesOrder/SalesOrderLine/PaymentTerm/Term/ID OOLINE.OBTEPY; OIS100MI/LstLineBOD	The field indicates the payment term
SalesOrder/SalesOrderLine/PaymentTerm/Term/Description CSYTAB.CTTX40; CRS175MI/GetGeneralCode	The field indicates the payment term description
SalesOrder/SalesOrderLine/DistributedCharge/Description	Set to 'Discount'.
SalesOrder/SalesOrderLine/DistributedCharge/Amount OOLINE.OBDIA1 OOLINE.OBDIA2 OOLINE.OBDIA3 OOLINE.OBDIA4 OOLINE.OBDIA5 OOLINE.OBDIA6	The field indicates the discount amount
.; OIS100MI/LstLineBOD @currencyID	
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/DistributedCharge/Calculation/RateNumOOLINE.OBDIP1 OOLINE.OBDIP2 OOLINE.OBDIP3 OOLINE.OBDIP4 OOLINE.OBDIP5 OOLINE.OBDIP6.; OIS100MI/LstLineBOD	meric The field indicates the discount percentage
SalesOrder/SalesOrderLine/DistributedCharge/ReasonCode	
	The field indicates the Discount as reason code
SalesOrder/SalesOrderLine/DistributedCharge/CalculationMethodC	Code The field indicates a fixed value of blank
SalesOrder/SalesOrderLine/DistributedCharge/GrossWeightIndicat	tor The field indicates a fixed value of False
SalesOrder/SalesOrderLine/PromisedShipDateTime	
OOLINE.OBDSDT+ OBDSHM; OIS100MI/LstLineBOD	The field indicates the departure date and time.
SalesOrder/SalesOrderLine/PromisedDeliveryDateTime OOLINE.OBCODZ+ OBCOHZ; OIS100MI/LstLineBOD	The field indicates the Confirmed delivery date and time.
SalesOrder/SalesOrderLine/PurchaseOrderReference/DocumentID/	ID .

SalesOrder	
OOLINE.OBRORN; OIS100Mi/LstLineBOD	The fields indicates the reference to the purchase order number. This should be filled if the OOLINE.OBLTYP is 1 or 2
SalesOrder/SalesOrderLine/PurchaseOrderReference/LineNumber OOLINE.OBRORL; OIS100Mi/LstLineBOD	The fields indicates the reference to the purchase order number. This should be filled if the OOLINE.OBLTYP is 1 or 2
SalesOrder/SalesOrderLine/SalesOrderSubLine/LineNumber OOLINE.OBPOSX; OIS100MI/LstLineBOD	The field indicates the subline number
SalesOrder/SalesOrderLine/SalesOrderSubLine/Note .; OIS100MI/LstLineTxt	The field indicates the remarks or notes.
@type	The field indicates the note type. For Pre-text field, 'Pre-Text' is published. For Post-Text field, 'Post-text' is published. And for Text field, 'Text' is published
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/ItemID/ID OOLINE.OBITNO; OIS100MI/LstLineBOD	The field indicates the Item Number
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/Description MITMAS.MMITDS; MMS200MI/GetItmBasic	The field indicates the Item description
SalesOrder/SalesOrderLine/SalesOrderSubLine/Item/SerializedLot/Lo	· · · · · · · · · · · · · · · · · · ·
SalesOrder/SalesOrderLine/SalesOrderSubLine/Quantity OOLINE.OBORQA; OIS100MI/LstLineBOD	The field indicates the Quantity for order line in alternate Unit of Measure.
@unitCode OOLINE.OBALUN; OIS100MI/LstLineBOD	The field indicates the alternate Unit of Measure.
SalesOrder/SalesOrderLine/SalesOrderSubLine/BaseUOMQuantity OOLINE.OBORQT; OIS100MI/LstLineBOD @unitCode	The field indicates the Quantity for order line in Basic Unit of Measure
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/ContractReference/DocumentID/ID OOLINE.OBAGNO; OIS100MI/LstLineBOD @accountingEntity	The field indicates the agreement number.
	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderLine/QuoteReference/DocumentID/ID OOHEAD.OAOFNO; OIS100MI/GetOrderHead @accountingEntity	The field indicates the quote number.
OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderLine/ShipFromParty/PartyIDs/ID OOLINE.OBWHLO; OIS100MI/LstLineBOD	The field indicates the warehouse where the item is from.
SalesOrder/SalesOrderLine/ShipFromParty/Name MITWHL.MWWHNM; MMS005MI/GetWarehouse	The field indicates the warehouse name.
SalesOrder/SalesOrderLine/ShipFromParty/Location @type	Sat to "Marahausa"
SalesOrder/SalesOrderLine/ShipFromParty/Location/ID OOLINE.OBWHLO; OIS100MI/GetOrderHead	Set to 'Warehouse' The field indicates the warehouse
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/Addres MITWHL.MWDR1, MWADR2, MWADR3, MWADR4; MMS005MI/GetWarehouse	ssLine The field indicates the warehouse address line
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/CityNa MITWHL.MWTOWN: MMS005MI/GetWarehouse	nme The field indicates the city where the warehouse is located.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/Counts MITWHL.MWECAR; MMS005MI/GetWarehouse @JistID	·
wisub	The field indicates the list ID depending on the country: - Canada has list ID 'Canadian Provinces' - France has list ID 'France - Departements' - United States list ID 'S States'
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/Count MITWHL.MWCSCD; MMS005MI/GetWarehouse	- Other countries have list ID 'SubDivisions - [country code]' ryCode The field indicates the country code.
SalesOrder/SalesOrderLine/ShipFromParty/Location/Address/Postal MITWHL.MWPONO; MMS005MI/GetWarehouse	
SalesOrder/SalesOrderLine/SupplierParty/Communication/ChannelC	ode
	Set to 'Phone' if Telephone number 1. Set to 'Phone' if Telephone number 2. Set to 'Fax' if Facsimile number.
@listID	Set to 'Email' if Email address.
SalesOrder/SalesOrderLine/SupplierParty/Communication/DialNumb	Set to 'Communication Channels'.

SalesOrder	
OOADRE.OPPHNO OOADRE.OPPHN2 OOADRE.OPTFNO	The field indicates the telephone/telefax number of the customer. PHN0 and PHN2 is phone numbers. TFNO is fax number.
.; OIS100MI/GetAddress	
SalesOrder/SalesOrderLine/PriceOverrideIndicator OOLINE.OBPRMO; OIS100MI/LstLineBOD	The field indicates that the order line was priced manually. Set to 'true' if PRMO = 8 Set to 'false' if PRMO != 8
SalesOrder/SalesOrderLine/AllocatedQuantity	
OOLINE.OBALQT+ OBPLQT; OIS100MI/LstLineBOD @unitCode	The field indicates the quantity of Allocated and Picked items in Basic Unit of Measure.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/AllocatedBaseUOMQuantity	
OOLINE.OBALQT+ OBPLQT; OIS100MI/LstLineBOD	The field indicates the quantity of Allocated and Picked items in Basic Unit of Measure.
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/OpenQuantity	The held indicates the basic offic of Measure.
OOLINE.OBORQT-OBALQT-OBPLQT-OBDLQT-OBIVQT; OIS100MI/ LstLineBOD @unitCode	The field indicates the open quantity (not yet allocated items) in Basic Unit of Measure.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/OpenBaseUOMQuantity OOLINE.OBORQT-OBALQT-OBPLQT-OBDLQT-OBIVQT; OIS100MI/ LstLineBOD @unitCode	The field indicates the open quantity (not yet allocated items) in Basic Unit of Measure.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/ShippedQuantity OOLINE.OBDLQT+ OBIVQT; OIS100MI/LstLineBOD @unitCode	The field indicates the quantity of delivered and invoiced items in Basic Unit of Measure.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/ShippedBaseUOMQuantity	
OOLINE.OBDLQT+ OBIVQT; OIS100MI/LstLineBOD @unitCode	The field indicates the quantity of delivered and invoiced items in Basic Unit of Measure.
MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the Basic Unit of Measure.
SalesOrder/SalesOrderLine/ExtendedCost/Amount OOLINE.OBUCOS; OIS100MI/LstLineBOD	The field indicates the cost price
@currencyID OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the currency of the cost price
SalesOrder/SalesOrderLine/Classification/Codes/Code	The field findicates the currency of the cost price
1) OOLINE.OBPIDE/ OIS100MI.GetLine2	1) Promotion The field indicates the promotion code.
2) OOLINE.OBJDCD/	Set attribute listID to 'Promotion Code'.
OIS100MI.LstLine	2) Joint delivery
	The field indicates the joint delivery code.
3) OOLINE.OBCUOR/	Set attribute listID to 'Joint Delivery Code'.
OIS100MI.LstLine.; /	Customer order number The field indicates the customer's order number. Set attribute listID to 'Customer's Order Number'.
@sequence	The field indicates the sequence number
@listID	The field indicates the sequence number.
<u></u>	 Set to 'Promotion Code' if Classification/Codes/Code = PIDE. Set to 'Joint Delivery Code' if Classification/Codes/Code = JDCD. Set to 'Customer's Order Number' if Classification/Codes/Code = CUOR.
SalesOrder/SalesOrderLine/PricingAmount/UnitBaseAmount OOLINE.OBSAPR; OIS100MI/LstLineBOD @currencyID	The field indicates the sales price for each sales price quantity.
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/PricingAmount/UnitPretaxAmount OOLINE.OBNEPR; OIS100MI/LstLineBOD @currencyID	The field indicates the net price.
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/PricingAmount/TotalPretaxAmount OOLINE.OBNLAM; OIS100MI/LstLineBOD @currencyID	The field indicates the net amount
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the currency
SalesOrder/SalesOrderLine/PricingAmount/TotalPretaxBaseAmount OOLINE.OBSAAM; OIS100MI/LstLineBOD	The field indicates the line amount in local currency
Infor May 26, 202	•

@currencyID OOLINE.OBLOCD; OIS100MI/LstLineBOD	The field indicates the currency
SalesOrder/SalesOrderLine/PricingAmount/UnitTotalAmount	The hold maloutes the currency
OOLINE.OBNEPR; OIS100MI/LstLineBOD @currencyID	The field indicates the Net Line Amount (as well as currency)
OOLINE.OBCUCD; OIS100MI/LstLineBOD	The field indicates the Currency
SalesOrder/SalesOrderLine/ItemConfiguration/ConfigurationCompo OOHEAD.OAORNO; /	nent/ConfiguratorLinks/HeaderID The field indicates the customer order number.
@accountingEntity OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderLine/ItemConfiguration/ConfigurationCompo	nent/ConfiguratorLinks/ConfigurationID
OOLINE.OACONO + OACFIN + OAECVS ; OIS100MI/LstLineBOD	The field indicates the configuration ID. It is a concatenation of Company (CONO) * 1000000000000 + Configuration number (CFIN) *100 + Simulation number (ECVS).
@accountingEntity OOHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderLine/ProjectReference/ID OOLINE.OBPROJ; OIS100MI/LstLineBOD @accountingEntity	The field indicates the project number.
	The field indicates the company and division, displayed as CONO_DIVI.
SalesOrder/SalesOrderLine/ProjectReference/ProjectElement/ID OOLINE.OBELNO; OIS100MI/LstLineBOD	The field indicates the project element number.
SalesOrder/SalesOrderLine/DropShipIndicator	тте ней інивалез ше ргојев стептент питрет.
OOLINE.OPLTYP; OIS100MI/LstLineBOD	The field indicates if the item should generate a purchase order and if the goods shall be shipped directly to the customer. Set to TRUE if LTYP = 1 or 2,also the Element Purchase order reference should be filled.
SalesOrder/SalesOrderSchedule/LineNumber OOLINE.OBPONR; /	The field indicates the order line number.
SalesOrder/SalesOrderSchedule/Quantity	The field indicates the order line number.
OOLINE.ORQT, ALQTY, DLQT, IVQT; /	The field indicates the computed quantity in Basic Unit of Measure. Open quantity = ORQT - ALQT - DLQT - IVQT Allocated quantity = ALQT Shipped quantity = DLQT Invoiced quantity = IVQT
@unitCode MITMAS.MMUNMS; MMS200MI/GetItmBasic	The field indicates the basic Unit of Measure.
SalesOrder/SalesOrderSchedule/Status/Code	
OOLINE.OBORST; OIS100MI/LstLineBOD	The field indicates the customer orders lowest status. It is translated according to: 22 = Approved 33 = Allocated 66 = Shipped 77 = Invoiced 90 = Deleted 99 = Canceled
	These status codes contain two positions. When the status is higher than 20, the first position indicates how far a partial quantity has progressed in the earliest stage of the order flow. The second positior indicates how far a partial quantity has progressed in the latest stage of the order flow. 2 = Approved 3, 4 = Allocated 6 = Shipped 7 = Invoiced 9 = Canceled
SalesOrder/SalesOrderSchedule/ShipToParty/Communication/UseC	
. ,	Set to 'Office' if the field Telephone number 1.
	Set to 'Office' if the field Telephone number 2. Set to 'Fax' if the Facsimile number.
	Set to 'Office' if the E-mail address.

SecurityPermissionMaster

SecurityPermissionWaster	
SecurityPermissionMaster/IDs/ID CMNPSU.KSFNID CMNPSU.KSROLL CMNPSU.KSCONO CMNPSU.KSDIVI.; / @variationID	The field indicates the Permission ID which is a concatenation of the fields Function (FNID), Role (ROLL), Company (CONO), Division (DIVI). The field indicates the sequence number that identifies the number of
@lid	times that the BOD has been published. The field indicates the logical ID of the system.
SecurityPermissionMaster/LastModificationDateTime CMNPSU.KSLMTS; /	The field indicates the date and time the record was last modified.
SecurityPermissionMaster/LastModificationPerson/IDs/ID CMNPSU.KSCHID; /	The field indicates the user id who last modified the record in M3.
SecurityPermissionMaster/DocumentDateTime CMNPSU.KSRGDT CMNPSU.KSRGTM.; /	The field indicates the date and time the record was created in M3.
SecurityPermissionMaster/Description MVXCON.COMSG; SES400MI/Get	The field indicates the Description retrieved from standard program name (from MVXCON table).
SecurityPermissionMaster/Status/Code	Set to 'Open' when record exist in M3. Set to 'Deleted' when record is deleted from M3 or status is changed from 20 ('Active') to 10 ('Preliminary') in M3.
@listID	Set to 'Generic Status'.
SecurityPermissionMaster/Name CMNPSU.KSFNID; /	The field indicates the function defined in M3 MNS110. It contains information about which program to use.
SecurityPermissionMaster/PermissionDetails/PropertyCode CMNFNP.JSPGM; AUTCHKMI/SelFncRolePerm	The field indicates the M3 program and the permitted option. The value is unique throughout the BOD. E.g. <propertycode>PPS010.Update Goods Responsibility<!-- PropertyCode--></propertycode>
SecurityPermissionMaster/PermissionDetails/Description CMNFNP.JPGM MVXCON.COMSG.; AUTCHKMI/SelFncRolePerm	The field indicates the permitted option description, which is concatenated of M3 program (PGNM) + Program description (TX40) + Option category (VALU) + description (DESC). In some cases the same Program can be accessed in multiple ways, for example using Related options and Function keys. In such cases description for all possible ways will be accumulated. E.g. Description>PPS010 / Supplier. Connect Transp Lead Times / Related option 14 + Function key F14 (Update Goods Responsibility)

SecurityRoleMaster

SecurityRoleMaster/IDs/ID CMNROL.KRROLL; /	This is the M3 role id.
SecurityRoleMaster/LastModificationDateTime CMNROL.KRLMTS; /	This is when the record was last modifed in M3.
SecurityRoleMaster/LastModificationPerson/IDs/ID CMNROL.KRCHID; /	This is the user id who last modified the record in M3.
SecurityRoleMaster/DocumentDateTimeCMNROL.KRRGDT + KRRGTM; /	This is when the record was created in M3.
SecurityRoleMaster/Description CMNROL.KRTX40; /	This the M3 role description.
SecurityRoleMaster/Status/Code	
	Set to 'Open' when record exist in M3. Set to 'Deleted' when record is deleted from M3.
@listID	Set to 'Generic Status'
SecurityRoleMaster/Name CMNROL.KRTX15; /	This the M3 role name.
SecurityRoleMaster/SecurityPermission/ID CMNPSU.FNID+ROLL+CONO+DIVI; SES400MI/LstAuthByRole	Permission ID is concatenated from M3 fields Function + Role + Company + Division
@lid	This is the M3 logical id.
SecurityRoleMaster/SecurityPermission/Description MVXCON.COMSG + CMNPSU.KSROLL + CMNPSU.KSCONO + CMNPSU.KSDIVI.; SES400MI.GetFieldHeading + SES400MI.LstAuthByRole/	Description is concatenated from standard program name (from MVXCON table) + Role name + Company + Division (from CMNPSU table)

ServiceC	rder
@tvpe	

For Service Order: Set to "FieldService"

The field indicates the work order number.

The field indicates the service order number.

The field indicates the company and division

The field indicates the company and division, displayed as

For Work Order:

For Service Order:

For Work Order:

For Service Order:

CONO DIVI.

For Work Order:

ServiceOrder/ServiceOrderHeader/DocumentID/ID

For Work Order:

MMOHED.QHMWNO; MOS100MI/Get

For Service Order:

SSHEAD.SDORNO; SOS100MI/GetHead

@accountingEntity For Work Order:

MMOHED.QHCONO+QHDIVI; /

For Service Order: SSHEAD.CONO

SSHEAD.DIVI.; /GetHead

@location

For Work Order: MMOHED.QHWHLO; /

For Service Order:

SSHEAD.SDFACI; /GetHead

@variationID

@lid

For Service Order: The field indicates the warehouse.

For Work Order:

The field indicates the variation ID

The field indicates the warehouse

For Service Order:

The field indicates the sequence number that identifies the number of

times that the BOD has been published.

For Work Order:

The field indicates the list ID

For Service Order:

The field indicates the logical ID of the system.

ServiceOrder/ServiceOrderHeader/AlternateDocumentID/ID

For Work Order:

MMOHED.QHIORN; MOS100MI/Get

For Service Order:

@schemeName

SSHEAD.SDCUOR; SOS100MI/GetHead

@accountingEntity

ServiceOrder/ServiceOrderHeader/DisplayID

For Work Order:

MMOHED.QHMWNO; MOS100MI/Get

For Service Order:

SSHEAD.SDORNO; SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/LastModificationDateTime

For Work Order:

MMOHED.QHLMDT; MOS100MI/Get

For Service Order:

SSHEAD.SDLMDT + time(); SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/LastModificationPerson/IDs/ID

For Work Order:

MMOHED.QHCHID; MOS100MI/Get

For Service Order:

SSHEAD.SDCHID; SOS100MI/GetHead

@accountingEntity For Work Order:

For Service Order:

MMOHED.QHCONO+QHDIVI; /

SSHEAD.CONO

SSHEAD.DIVI.; /GetHead ServiceOrder/ServiceOrderHeader/LastModificationPerson/Name

For Work Order:

CMNUSR.JUNAME; MNS150MI/GetUserData

For Work Order:

The field indicates the interface order number

For Service Order:

The field indicates the customers order reference.

For Service Order: Set to 'Service'.

For Work Order:

The field indicates the company and divison

For Work Order:

The field indicates the work order number.

For Service Order:

The field indicates the display ID.

For Work Order:

The field indicates the last date when the Service order (work order)

was changed.

For Service Order:

The field indicates the last modification date and time.

For Work Order:

The field indicates the user id who last changed the record

For Service Order:

The field indicates the last modification person.

For Work Order:

The field indicates the company and division.

For Service Order:

The field indicates the company and division, displayed as

CONO DIVI.

For Work Order: The field indicates the name of the person

ServiceOrder/ServiceOrderHeader/DocumentDateTime For Work Order For Work Order: MMOHED.QHRGDT + QHRGTM; MOS100MI/Get The field indicates the entry date and time when the record first was For Service Order: SSHEAD.SDOSDT; SOS100MI/GetHead For Service Order: The field indicates the document date and time. ServiceOrder/ServiceOrderHeader/Description For Work Order: For Work Order: MMOHED .QHTX40 + QHTXT1 + QHTXT2; MOS100MI/Get The field indicates the description on the work order header For Service Order: For Service Order:

SSHEAD.SDDLRM; SOS100MI/GetHead ServiceOrder/ServiceOrderHeader/Note

For Work Order: For Work Order: MSYTXH.THTX60; CRS980MI/SItTxtBlock The field indicates the text

For Service Order: For Service Order:

OSYTXH.THTX60; SOS200MI/LstSOText The field indicates the notes. @noteID

For Work Order: For Work Order: MSYTXH.THTXVR; CRS980MI/LstTxtBlockS

The field indicates the note ID

For Service Order: For Service Order: OSYTXH.THTXVR The field indicates the text block and text ID.

OSYTXH.THXID.; SOS200MI/LstSOText @use

For Service Order: For Service Order:

OSYTXH.THTXEI; SOS200MI/LstSOText The field indicates the note is external or internal text.

@type For Service Order: For Service Order:

OSYTXH.THTYTX; SOS200MI/LstSOText The field indicates the type of note:

1 - Pre-text 2 - Post-text 3 - General text @languageID

For Work Order: For Work Order:

MSYTXH.THLNCD; CRS980MI/LstTxtBlockS The field indicates the note's language

For Service Order: For Service Order:

OSYTXH.THLNCD; SOS200MI/LstSOText The field indicates the language used for the notes.

ServiceOrder/ServiceOrderHeader/DocumentReference @type

For Work Order: For Work Order: MMOHED.QHRORC; MOS100MI/Get The field indicates the document reference type.

Alternatives: For Service Order: 1 = ProductionOrder

SSHEAD.SDRORC; SOS100MI/GetHead 2 = PurchaseOrder 3 = SalesOrder 4 = RequisitionOrder

5 = DistributionOrder 6 = WorkOrder 7 = ServiceOrder 8 = ProjectOrder 9 = ClaimOrder

For Service Order:

For Work Order:

The field indicates the following reference order type (RORC) Set to 'ProductionOrder', if reference order type is 1. Set to 'PurchaseOrder', if reference order type is 2. Set to 'SalesOrder', if reference order type is 3. Set to 'RequisitionOrder', if reference order type is 4. Set to 'DistributionOrder', if reference order type is 5. Set to 'WorkOrder', if reference order type is 6. Set to 'ServiceOrder', if reference order type is 7.

Set to 'ProjectOrder', if reference order type is 8.

The field indicates the service order description

ServiceOrder/ServiceOrderHeader/DocumentReference/DocumentID/ID

For Work Order: For Work Order:

MMOHED.QHRORN; MOS100MI/Get The field indicates the document reference number.

For Service Order: For Service Order:

SSHEAD.SDRORN; SOS100MI/GetHead The field indicates the reference order number. @accountingEntity

For Work Order:

MMOHED.QHCONO+QHDIVI; / The field indicates the company and division

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI .: /GetHead CONO DIVI.

@location

For Work Order: For Work Order:

MMOHED.QHWHLO; / The field indicates the warehouse

ServiceOrder/ServiceOrderHeader/DocumentReference/LineNumber

For Work Order:

MMOHED.QHRORL; MOS100MI/Get

SSHEAD.SDRORL; SOS100MI/GetHead

For Service Order:

ServiceOrder/ServiceOrderHeader/DocumentReference/Facility/IDs/ID

For Work Order:

MMOHED.QHFACI; MOS100MI/Get

For Service Order: SSHEAD.SDFACI; SOS100MI/GetHead

@accountingEntity

For Work Order:

MMOHED.QHCONO+QHDIVI; /

ServiceOrder/ServiceOrderHeader/DocumentReference/Facility/Name

CFACIL.CFFACN; CRS008MI/Get

The field indicates the facility name

The field indicates the facility name.

ServiceOrder/ServiceOrderHeader/DocumentReference/SubLineNumber

For Service Order

SSHEAD.SDRORX; SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/PriorityCode For Work Order:

MMOHED.QHPRIO; MOS100MI/Get

For Service Order:

SSHEAD.SDOPRI; SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/Status/Code For Work Order:

MMOHED.QHWHST; MOS100MI/Get

For Service Order:

SSHEAD.SDORST; SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/Status/EffectiveDateTime

For Work Order:

MMOHED.QHRGDT + QHRGTM; MOS100MI/Get

For Service Order:

SSHEAD.SDRGDT; SOS100MI/GetHead

ServiceOrder/ServiceOrderHeader/Status/ReasonCode For Work Order:

MMOHED.QHWHST; MOS100MI/Get

For Service Order:

SSHEAD.SDORST; SOS100MI/GetHead

@listID

For Work Order:

MMOHED.QHWHST; MOS100MI/Get

For Work Order:

The field indicates the document reference line number

For Service Order: The field indicates the reference order line number.

For Work Order:

The field indicates the facility ID

For Service Order:

The field indicates the facility.

For Work Order:

The field indicates the company and division

For Service Order:

The field indicates the company and divison

For Work Order:

For Service Order:

For Service Order:

The field indicates the reference order line subline number.

For Work Order:

The field indicates the priority of the order

For Service Order:

The field indicates the priority of the order

The field indicates the standard status on work order header

Alternatives: 80, 94=Closed

For Work Order:

20=Open 30, 34, 35, 36, 37, 38, 40, 50, 60, 70=Approved

98=Invoiced 98=Hold 10=Pending

85,89, 90,95,96=Completed

The field indicates the status of the service order (ORST). Set to 'Approved', if the service order status are 30, 31, 32,33,34,

35,36,37,39,40,41,42,43,44,45,50,53,54,58 and 59. Set to 'Hold', if the service order status is 49. Set to 'Completed', if the service order status is 60.

Set to 'Invoiced', if the service order status is 80.

For Service Order:

Set to 'Service Order Status'.

For Work Order:

The field indicates the entry date and time when the record first was

For Service Order:

The field indicates the status effective date and time.

For Work Order:

The field indicates the M3 status on work order header

For Service Order:

The field indicates the service type status.

For Work Order:

The field indicates the M3 status on work order header

ServiceOrder Alternatives: 10=Preliminary 20=Definite 30=Order started/previous operation not started 34=Previous operation ready to start 35=Previous operation's dispatch list configured 36=Previous operation started 37-Previous operation partially reported 38=Previous operation stopped 40=Ready to begin/preceeding operation complete 50=Dispatch list configured 60=Started 70-Partially reported 80,94,98,99=Stopped 85,89=Flagged as completed, work order not closed 90,95,96,97=Finish marked ServiceOrder/ServiceOrderHeader/CustomerParty/PartyIDs/ID For Work Order: For Work Order: MMOHED.QHCUNO; EQINFOMI/GetMaintCO The field indicates the customer number For Service Order: For Service Order: SSHEAD.SDCUNO; SOS100MI/GetHead The field indicates the customer number. @accountingEntity For Work Order: For Work Order: MMOHED.QHCONO+QHDIVI; / The field indicates the accounting entity. If CustomerPartyMaster is enabled in BOD Processor Master AE tab, For Service Order: this is displayed as Company (CONO). Otherwise, this is displayed as SSHEAD.CONO Company and Division (CONO_DIVI). SSHEAD.DIVI.; /GetHead For Service Order: The field indicates the company and division, displayed as CONO DIVI. ServiceOrder/ServiceOrderHeader/CustomerParty/PartyIDs/TaxID For Service Order: For Service Order: The field indicates the tax ID of the customer. OCUSMA.OKVRNO; CRS610MI/GetFinancial ServiceOrder/ServiceOrderHeader/CustomerParty/Name For Work Order: For Work Order: OCUSMA.OKCUNM; CRS610MI/GetBasicData The field indicates the customer name For Service Order: For Service Order: SSADRE.HBCUNM; SOS100MI/LstSOAddr The field indicates the customer name. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/ID For Service Order: For Service Order: SSADRE.HBADID; SOS100MI/LstSOAddr The field indicates the location ID. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address @type For Service Order: Set to 'text'. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AttentionOfName For Service Order: For Service Order: SSADRE.HBYREF; SOS100MI/LstSOAddr The field indicates the contact person for the cusrtomer. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AddressLine For Work Order: For Work Order: OCUSMA.OKCUA1, OKCUA2, This is the delivery address for the customer, from customer address, adress type 2, CUA2-CUA3-CUA4 OKCUA3. OKCUA4: CRS610MI/GetBasicData For Service Order: For Service Order: SSADRE.HBCUA1 The field indicates the address line. SSADRE.HBCUA2 SSADRE.HBCUA3 SSADRE.HBCUA4.; SOS100MI/LstSOAddr @sequence For Work Order: The field indicates the address id/seq of the the customer For Service Order: The field indicates the address line sequence

ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CitySubDivisionName

For Work Order: For Work Order:

OCUSMA.OKECAR; CRS610MI/GetBasicData The field is used for subdivision or state code.

ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CityName

For Work Order: For Work Order:

OCUSMA.OKTOWN; CRS610MI/GetBasicData The field indicates the city of the the customer

For Service Order: For Service Order:

SSADRE.HBTOWN; SOS100MI/LstSOAddr The field indicates the city name.

For Service Order:

CCUCON.CCPHNO

ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CountrySubDivisionCode For Work Order: For Work Order: OCUSMA.OKECAR; CRS610MI/GetBasicData The field is used for subdivision or state code For Service Order: For Service Order: SSADRE.HBECAR; SOS100MI/LstSOAddr The field indicates an area, province or state within a country. @listID For Work Order: Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States. Set list ID to 'Country Sub-divisions' if the country 's SubDivisions-[CountryCode]'. For Service Order: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CountryCode For Work Order: For Work Order: OCUSMA.OKCSCD; CRS610MI/GetBasicData The field indicates the Country code for the the cusrtomer For Service Order: For Service Order: SSADRE.HBCSCD; SOS100MI/LstSOAddr The field indicates the country code. @listID For Work Order: Set to 'Countries' For Service Order: Set to 'Countries ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/PostalCode For Work Order: For Work Order: OCUSMA.OKPONO; CRS610MI/GetBasicData The field indicates the postal code for the the cusrtomer For Service Order: For Service Order: SSADRE.HBPONO; SOS100MI/LstSOAddr The field indicates the postal code. ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/ID For Work Order: For Work Order: CCUCON.CCCNPE; COS119MI/LstByOrder The field indicates the contact name For Service Order: For Service Order: OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact person. @accountingEntity For Work Order: For Work Order: MMOHED.QHCONO+QHDIVI; / The field indicates the company and division For Service Order: For Service Order: The field indicates the company and division, displayed as SSHEAD.CONO SSHEAD.DIVI.; /GetHead CONO DIVI ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Name For Service Order: For Service Order: CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name. ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Communication @preferredIndicator For Service Order: Set to 'false'. ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Communication/ChannelCode For Service Order: The field indicates the channel code Phone, Fax or EMail. @listID For Service Order: Set to "Communication Channels". ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Communication/UseCode For Service Order: Set to "Office" if telephone number 1, telephone number 2 or e-mail Set to "Fax" if facsimile number. Set to "Mobile" if mobile number. @listID For Service Order: Set to "Communication Use Codes". ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Communication/DialNumber

Infor May 26, 2023 527

For Service Order:

The field indicates the phone number.

CCDHN2: CDS618MI/Cot	
CCPHN2; CRS618MI/Get	nication/IDI
ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/Commu For Service Order:	Inication/URI For Service Order:
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the e-mail address.
ServiceOrder/ServiceOrderHeader/ShipToParty/PartyIDs/ID	
For Service Order:	For Service Order:
SSADRE.HBCUNO	The field indicates the ship to party ID.
SSADRE.HBADID. ; SOS100MI/GetHead	
@accountingEntity	
For Service Order:	For Service Order:
SSHEAD.CONO	The field indicates the company and division, displayed as
SSHEAD.DIVI.; /GetHead	CONO_DIVI.
ServiceOrder/ServiceOrderHeader/ShipToParty/PartyIDs/TaxID For Service Order:	For Service Order:
OCUSMA.OKVRNO; CRS610MI/GetFinancial	The field indicates the tax ID of the customer.
ServiceOrder/ServiceOrderHeader/ShipToParty/Name	
For Service Order:	For Service Order:
SSADRE.HBCUNM; SOS100MI/LstSOAddr	The field indicates the ship to party name.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/ID	
For Work Order:	For Work Order:
OJADID.ADID; MOS100./GetWoAddress	The field indicates the location id
For Service Order:	For Service Order:
SSADRE.HBADID; SOS100MI/LstSOAddr	The field indicates the location ID.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Name	
For Work Order:	For Work Order:
ACUORA.OACUNM; EQINFOMI/GetROCAddress	The field indicates the location name
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address @type	
e, pr	For Work Order:
	Set to 'text'
	For Sandas Order
	For Service Order: Set to 'text'.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/	
For Work Order:	For Work Order:
ACUORA.OAYREF; EQINFOMI/GetROCAddress	The field indicates the reference number or contact person of a
For Service Order:	customer.
SSADRE.HBYREF; SSADRE/LstSOAddr	For Service Order:
	The field indicates the reference person.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/	AddressLine
For Work Order:	For Work Order:
ACUORA.OACUA1, OACUA2, OACUA3, OACUA4; EQINFOMI/ GetROCAddress	The field indicates the address line.
Geti (OOAddiess	For Service Order:
For Service Order:	The field indicates the address line.
SSADRE.HBCUA1	
SSADRE.HBCUA2 SSADRE.HBCUA3	
SSADRE.HBCUA3; SOS100MI/LstSOAddr	
@sequence	
	For Work Order:
	The field indicates the sequential number
	For Service Order:
	The field indicates the address line sequence.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/	
For Work Order:	For Work Order:
ACUORA.OATOWN; EQINFOMI/GetROCAddress	The field indicates the city
For Service Order:	For Service Order:
SSADRE.HBTOWN; SOS100MI/LstSOAddr	The field indicates the city name.
ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/	
For Work Order:	For Work Order:
ACUORA.OAECAR; EQINFOMI/GetROCAddress	The field indicates the state
For Service Order:	For Service Order:
SSADRE.HBECAR; SOS100MI/LstSOAddr	The field indicates an area, province or state within a country.
@listID	
	For Work Order:
	Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France.
	Set list ID to 'US States' if the country is United States.
	in the state of th

ServiceOrder Set list ID to 'Country Sub-divisions' if the country 's SubDivisions-[CountryCode]'. For Service Order: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CountryCode For Work Order: For Work Order: ACUORA.OACSCD; EQINFOMI/GetROCAddress The field indicates the Country code For Service Order: For Service Order: SSADRE.HBCSCD; SOS100MI/LstSOAddr The field indicates the country code. @listID For Work Order: Set to 'Countries For Service Order: Set to 'Countries' ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/PostalCode For Work Order: For Work Order: ACUORA.OAPONO; EQINFOMI/GetROCAddress The field indicates the postal code For Service Order: For Service Order: The field indicates the postal code SSADRE.HBPONO; SOS100MI/LstSOAddr ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/ID For Service Order: For Service Order: OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact person ID. @accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; /GetHead CONO DIVI. ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Name For Service Order: For Service Order: CCUCON.CCTX50; CRS618MI/Get The field indicates the contact person name ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication @preferredIndicator For Service Order: Set to 'false' ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/ChannelCode For Service Order: The field indicates the channel code Phone, Fax or EMail. @listID For Service Order: Set to "Communication Channels". ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/UseCode For Service Order: Set to "Office" if telephone number 1, telephone number 2 or e-mail address Set to "Fax" if facsimile number. Set to "Mobile" if mobile number. @listID For Service Order: Set to "Communication Use Codes" ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/CountryDialing For Service Order: The field indicates the phone number. ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/DialNumber For Service Order: For Service Order: CCUCON.CCPHNO The field indicates the phone number. CCUCON.CCPHN2 ; CRS618MI/Get ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/URI For Service Order: For Service Order: CCUCON.CCEMAL; CRS618MI/Get The field indicates the e-mail address ServiceOrder/ServiceOrderHeader/ShipToParty/Contact/Communication/Preference/Indicator For Service Order: Set to 'false'

Infor May 26, 2023 52

For Work Order:

The field indicates the product number and lot number

ServiceOrder/ServiceOrderHeader/ConfiguredAsset/ID

MMOHED.QHPRNO + QHBANO; MOS100MI/Get

For Work Order:

@accountingEntity

For Work Order:	For Work Order:
MMOHED.QHCONO + QHDIVI; / ServiceOrder/ServiceOrderHeader/Classification/Codes/Code	The field indicates the company and division
For Work Order: ACUORH.OHPRRF ACUORH.OHYREF ACUORH.OHVREF ACUORH.OHAAGN ACUORH.OHAAGN ACUORH.OHAOTY MMOHED.QHRSCD MMOHED.QHRSCD MMOHED.QHRESP ACUORH.OHACWA.; EQINFOMI.GetMaintCO.PRRF EQINFOMI.GetMaintCO.TEDL EQINFOMI.GetMaintCO.TEDL EQINFOMI.GetMaintCO.CUOR EQINFOMI.GetMaintCO.AAGN EQINFOMI.GetMaintCO.AAGN EQINFOMI.GetMaintCO.AOTY MOS100.Get.RSCD MOS100.Get.RSCD MOS100.Get.RESP EQINFOMI.GetMainCOLine.ACWA/	For Work Order: The field indicates the price list The field indicates the transportation method The field indicates the reference number or contact person of a customer. The field indicates the customer order number. The field indicates the agreement number The field indicates the agreement o.rder type The field indicates the reason code. The field indicates the person responsible. The field indicates the claim warranty.
@sequence	For Work Order:
O.V. VID	The field indicates the sequential number
@listID	For Work Order: The field indicates the list ID 'Price List' The field indicates the list ID 'Transportation Method' The field indicates the list ID 'Customer Reference' The field indicates the list ID 'Customer Order Number' The field indicates the listID 'Agreement Number' The field indicates the listID 'Agreement Order Type' The field indicates the 'Reason Code' The field indicates the 'Responsible' The field indicates the ListID 'Claim Warranty'
ServiceOrder/ServiceOrderHeader/ReportedDateTime For Work Order:	For Work Order:
MMOHED.QHRPDT; MOS100MI/Get	The field indicates the reporting date
For Service Order: SSHEAD.SDPMDT SSHEAD.SDPMTM.; SOS100MI/GetHead	For Service Order: The field indicates the reported date and time.
ServiceOrder/ServiceOrderHeader/ChangeDateTime	For Coming Order
For Service Order: SSHEAD.SDLMDT+TIME(); SOS100mi/GetHead	For Service Order: The field indicates the change date and time.
ServiceOrder/ServiceOrderHeader/FailureDateTime For Work Order: MMOHED.QHBRDT+QHBRTI; MOS100MI/Get	For Work Order: The field indicates the breakdown date and time
For Service Order: SSHEAD.SDPMDT SSHEAD.SDPMTM.; SOS100MI/GetHead	For Service Order: The field indicates the error reporting date and time.
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/StartDateTime For Work Order: MMOHED.QHSTDT + QHMSTI; MOS100MI/Get	For Work Order: The field indicates the planned start date and time
For Service Order: SSHEAD.SDRQSD SSHEAD.SDRQST. ; SOS100MI/GetHead	For Service Order: The field indicates the planned start date and time.
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/EndDateTime For Work Order: MMOHED.QHFIDT + QHMFTI; MOS100MI/Get	The field indicates the planned finish date and time.
For Service Order: SSHEAD.SDRQFD SSHEAD.SDRQFT.; SOS100MI/GetHead	
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/StartDateTime For Service Order: SSHEAD.SDCSDT SSHEAD.SDCSTM.; SOS100MI/GetHead	For Service Order: The field indicates the actual start date and time.
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/EndDateTime For Service Order:	For Service Order:
SSHEAD.SDCFDA SSHEAD.SDCFTM.; SOS100MI/GetHead	The field indicates the actual finish date and time.
ServiceOrder/ServiceOrderHeader/Facility/IDs/ID	

For Work Order: For Work Order: MMOHED.QHFACI: MOS100MI/Get The field indicates the facility code @accountingEntity For Work Order: For Work Order: The field indicates the company and division MMOHED.QHCONO + QHDIVI; / ServiceOrder/ServiceOrderHeader/Facility/Name For Work Order: For Work Order: The field indicates the facility name CFACIL.CFFACN; CRS008MI/Get ServiceOrder/ServiceOrderHeader/PreventiveMaintenanceID For Work Order: For Work Order: MMOHED.QHSUFI + QHSTRT; MOS100MI/Get The field indicates the service id for scheduled/preventive services (only populated if scheduled service) @accountingEntity For Work Order: For Work Order: MMOHED.QHCONO+QHDIVI; / The field indicates the company and division ServiceOrder/ServiceOrderHeader/SupervisorID For Service Order: For Service Order: SSHEAD.SDSRES; SOS100MI/GetHead The field indicates the service manager. ServiceOrder/ServiceOrderHeader/ProjectReference For Service Order: For Service Order: SSHEAD.SDPROJ; SOS100MI/GetHead The field indicates the project reference id ServiceOrder/ServiceOrderHeader/ProjectReference/ID For Work Order: For Work Order: ACOURH.OHAPRS; EQINFOMI/GetMaintCO The field indicates the project ID For Service Order: For Service Order: SSHEAD.SDPROJ; SOS100MI/GetHead The field indicates the project reference id . @accountingEntity For Work Order: For Work Order: MMOHED.QHCONO+WHDIVI; / The indicates the company and division For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; /GetHead CONO DIVI. ServiceOrder/ServiceOrderHeader/ProjectReference/ProjectElement/ID For Work Order: For Work Order: ACUORH.OHELNO; EQINFOMI/GetMaintCO The field indicates the project element ID For Service Order: For Service Order: SSHEAD.SDELNO; SOS100MI/GetHead The field indicates project structure. The element can refer to an activity a subproject or a main project. ServiceOrder/ServiceOrderHeader/UserArea/Property/NameValue For Work Order: For Work Order: MMOHED.QHCFI1+QHCFI2+QHCFI3+QHCFI4+QHCFI5,PRNO,MWNO;The field indicates the user defined fields 1 to 5 and Product Number and WorkOrder Number MOS100MI/Get @name For Work Order: Set to "ItemFreeField1" Set to "ItemFreeField2" Set to "ItemFreeField3" Set to "ItemFreeField4" Set to "ItemFreeField5"set to "Product" if it is Product Number ."WO Number"if it is WorkOrder Number ServiceOrder/ServiceOrderHeader/SalesPersonReference/IDs/ID For Service Order: For Service Order: SSHEAD.SDSMCD; SOS100MI/GetHead The field indicates the sales person ID. @accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as CONO DIVI. SSHEAD.DIVI.; /GetHead ServiceOrder/ServiceOrderHeader/SalesPersonReference/Name For Service Order: For Service Order: CMNUSR.JUTX15; MNS150MI/GetUserData The field indicates the sales person name ServiceOrder/ServiceOrderHeader/PreferredEngineerPerson/ID For Service Order: For Service Order: SSHEAD.SDTECH; SOS100MI/GetHead The field indicates the preffered engineer person. @accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; /GetHead CONO DIVI. ServiceOrder/ServiceOrderHeader/PreferredEngineerPerson/Name For Service Order: For Service Order: CEAEMP.EAEMNM; CRS530MI/LstEmployee The field indicates the name of the service engineer ServiceOrder/ServiceOrderHeader/PreferredEngineerPerson/Status/Code

For Service Order For Service Order:

CEAEMP.EAACEM; CRS530MI/LstEmployee The field indicates the status of the employee. Set to 'Open', if status of the employee is 1. Set to 'Terminated', if status of the employee is 0.

ServiceOrder/ServiceOrderHeader/SiteLocation/ID

For Work Order: For Work Order:

MMOHED.QHADID; MOS100MI/Get The field indicates the key to the delivery address, made up by

ADID, ADRR, ADRT from MOS100MI-get

For Service Order:

SSADRE.HBADID; SOS100MI/LstSOAddr For Service Order:

The field indicates the delivery address code.

@accountingEntity

For Work Order: For Work Order:

MMOHED.QHCONO+QHDIVI; / The field indicates the company and division

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

CONO DIVI. SSHEAD.DIVI.; /GetHead

ServiceOrder/ServiceOrderHeader/SiteLocation/Name

For Work Order: For Work Order:

MOADDR.OYCUNM; EQINFOMI/GetROCAddress The field indicates the customer name

For Service Order: For Service Order:

SSADRE.HBCUNM; SOS100MI/LstSOAddr The field indicates the name of the equipment address.

ServiceOrder/ServiceOrderHeader/SiteLocation/Address

@type

For Work Order: Set to 'text'

For Service Order: Set to 'text'.

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/AttentionOfName

For Work Order: For Work Order:

ACUORA.OAYREF; EQINFOMI/GetROCAddress The field indicates the contact number or name

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/AddressLine

For Work Order: For Work Order:

ACUORA.OACUA1, OACUA2, OACUA3, This is the delivery address for the customer, from customer address,

OACUA4; EQINFOMI/GetROCAddress adress type 2, CUA2-CUA3-CUA4

For Service Order: For Service Order:

SSADRE.HBCUA1 SSADRE.HBCUA2 SSADRE.HBCUA3

SSADRE.HBCUA4.; SOS100MI/LstSOAddr

@sequence

For Work Order:

The field indicates the sequential number

The field indicates the address line.

For Service Order:

The field indicates the address line sequence.

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CitySubDivisionName

For Work Order: For Work Order:

ACUORA.OAECAR; EQINFOMI/GetROCAddress The field is used for subdivision or state code.

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CityName

For Work Order: For Work Order:

ACUORA.OATOWN; EQINFOMI/GetROCAddress The field indicates the city of the the customer

For Service Order: For Service Order:

SSADRE.HBTOWN; SOS100MI/LstSOAddr The field indicates the city name.

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CountrySubDivisionCode

For Service Order: For Service Order:

The field indicates an area, province or state within a country. SSADRE.HBECAR; SOS100MI/LstSOAddr

@listID

For Service Order:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no country is specified

ServiceOrder/ServiceOrderHeader/SiteLocation/Address/CountryCode

For Work Order: For Work Order:

ACUORA.OACSCD; EQINFOMI/GetROCAddress The field indicates the Country code for the the cusrtomer

For Service Order: For Service Order:

SSADRE.HBCSCD; SOS100MI/GetSOAddress The field indicates the country code.

@listID

ent.
A11C.
art date-time
art date-time.
it date-time.
nd date-time
00
as
1

ServiceOrder	For Service Order:
Openia Onda (Openia Openia Ope	The field indicates the address line sequence.
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/C For Service Order:	ityName For Service Order:
SSADRE.HBTOWN; SOS100MI/LstSOAddr	The field indicates the city name.
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/C	
For Service Order: SSADRE.HBECAR; SOS100MI/LstSOAddr	For Service Order: The field indicates an area, province or state within a country.
@listID	
	For Service Order: Setto 'Canadian Provinces' if the country is CA (Canada).
	Setto 'France - Departements' if the country is FR (France).
	Set to 'US States' if the country is US (United States).
	Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no country is specified.</country>
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/C	
For Service Order:	For Service Order:
SSADRE.HBCSCD; SOS100MI/LstSOAddr @listID	The field indicates the country code.
	For Service Order:
Our is a Coule of Cours is a Coule of London Bull To Book of London Address of B	Set to 'Countries'.
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/P	ostalCode For Service Order:
SSADRE.HBPONO; SOS100MI/LstSOAddr	The field indicates postal code.
ServiceOrder/ServiceOrderHeader/BillToParty/Contact/ID	F 0 : 0 !
For Service Order: OCUSCO.CCCNPE; CMS055MI/LstByCustomer	For Service Order: The field indicates the contact person's ID.
@accountingEntity	The hold indicates the contact persons in.
For Service Order:	For Service Order:
SSHEAD.CONO SSHEAD.DIVI.; /GetHead	The field indicates the company and division, displayed as CONO DIVI.
ServiceOrder/ServiceOrderHeader/BillToParty/Contact/Name	
For Service Order:	For Service Order:
CCUCON.CCTX50; CRS618MI/Get ServiceOrder/ServiceOrderHeader/BillToParty/Contact/Communica	The field indicates the name of the contact person name.
@preferredIndicator	auon
<u> </u>	For Service Order:
ServiceOrder/ServiceOrderHeader/BillToParty/Contact/Communication	Set to 'false'.
ServiceOrder/ServiceOrderneader/biii i Oranty/Contact/Confiniumica	For Service Order:
	Set to "Phone" if telephone number 1 or 2 or facsimile number or
	mobile. Set to "EMail" if e-mail address.
@listID	
	For Service Order: Set to "Communication Channels".
ServiceOrder/ServiceOrderHeader/BillToParty/Contact/Communication	
For Service Order:	For Service Order:
CCUCON.CCPHNO CCPHN2; CRS618MI/Get	The field indicates the telephone number.
ServiceOrder/ServiceOrderHeader/BillToParty/Contact/Communication	ation/URI
For Service Order:	For Service Order:
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the e-mail address.
ServiceOrder/ServiceOrderHeader/PayFromParty/PartyIDs/ID For Work Order:	For Work Order:
ACUORH.OHPYNO; EQINFOMI/GetMaintCO	The field indicates the payer ID
For Comico Ordon	For Comice Order
For Service Order: SSHEAD.SDPYNO; SOS100MI/GetHead	For Service Order: The field indicates the customer number who receives the invoice.
@accountingEntity	
For Work Order: MMOHED.QHCONO+QHDIVI; /	For Work Order: The field indicates the accounting entity.
	If CustomerPartyMaster is enabled in BOD Processor Master AE tab,
For Service Order:	this is displayed as Company (CONO). Otherwise, this is displayed as
SSHEAD.CONO SSHEAD.DIVI.; /GetHead	Company and Division (CONO_DIVI).
55	For Service Order:
	The field indicates the company and division, displayed as
ServiceOrder/ServiceOrderHeader/PayFromParty/Name	CONO DIVI.
For Service Order:	For Service Order:
SSADRE.HBCUNM; SOS100MI/LstSOAddr	The field indicates the name of the invoice recepient.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address	s
@type	

<u>OCI VICCOI dCI</u>	
	For Service Order: Set to 'text'.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/	
For Service Order:	For Service Order:
SSADRE.HBYREF; SOS100MI/LstSOAddr	The field indicates the attention of name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/	
For Service Order: SSADRE.HBCUA1	For Service Order:
SSADRE.HBCUA2	The field indicates the address line.
SSADRE.HBCUA3	
SSADRE.HBCUA4.; SOS100MI/LstSOAddr	
@sequence	For Service Order:
	The field indicates the address line sequence.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/	CityName
For Service Order:	For Service Order:
SSADRE.HBTOWN; SOS100MI/LstSOAddr	The field indicates the city name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/ For Service Order:	For Service Order:
SSADRE.HBECAR; SOS100MI/LstSOAddr	The field indicates an area, province or state within a country.
@listID	5 0 : 01
	For Service Order: Set to 'Canadian Provinces' if country is Canada.
	Set to 'France - Departements' if country is France.
	Set to 'US States' if country is United States.
	Set to 'SubDivisions - [country code]' if other countries. Set to "SubDivisions" if no country is specified.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/	
For Service Order:	For Service Order:
SSADRE.HBCSCD; SOS100MI/LstSOAddr	The field indicates the country code.
@listID	For Service Order:
	Set to 'Countries'.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/	PostalCode PostalCode
For Service Order:	For Service Order:
SSADRE.HBPONO; SOS100MI/LstSOAddr	The field indicates the postal code.
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/ID For Service Order:	For Service Order:
OCUSCO.CCCNPE; CMS055MI/LstByCustomer	The field indicates the contact person ID.
@accountingEntity	For Comition Coders
	For Service Order: The field indicates the company and division, displayed as
	CONO DIVI.
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Name	
For Service Order:	For Service Order:
CCUCON.CCTX50; CRS618MI/Get	The field indicates the contact name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Communic@preferredIndicator	Lation
.	For Service Order:
	Set to 'false'.
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Communic	cation/ChannelCode For Service Order:
	The field indicates the channel code Phone, Fax or EMail.
@listID	5.0.
	For Service Order: Set to "Communication Channels".
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Communic	
ociviocoraci/ociviocoraci/roadci// ayrroini arty/ociriadaoonimani	For Service Order:
	Set to "Office" if telephone number 1, telephone number 2 or e-mail
	address. Set to "Fax" if facsimile number.
	Set to "Mobile" if mobile number.
@listID	
	For Service Order: Set to "Communication Use Codes".
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Communic	
33. 1.333. activities in the control of the control	For Service Order:
	The field indicates the phone number.
ServiceOrder/ServiceOrderHeader/PayFromParty/Contact/Communic	
For Service Order: CCUCON.CCPHNO	For Service Order: The field indicates the telephone number.
CCUCON.CCPHN2.	The held indicates the telephone hulliber.
; CRS618MI/Get	
Service Order/Service Order Header/Pay From Party/Contact/Communication (Communication From Party) and the Communication (Communicati	cation/URI

ServiceOrder	
For Service Order:	For Service Order:
CCUCON.CCEMAL; CRS618MI/Get	The field indicates the e-mail address.
ServiceOrder/ServiceOrderHeader/PaymentTerm/PaymentTermCode For Service Order:	For Service Order:
SSHEAD.SDTEPY; SOS100MI/GetHead	The field indicates the payment term code.
@listID	Fan Camilian Ordani
	For Service Order: Set to 'Payment Term'.
ServiceOrder/ServiceOrderHeader/PaymentTerm/Term/ID	Cotto i aymont roim.
For Work Order:	For Work Order:
ACUORH.OHTEPY; EQINFOMI/GetMaintCO	The field indicates the payment term
For Service Order:	For Service Order:
SSHEAD.SDTEPY; SOS100MI/GetHead	The field indicates the payment term id.
@accountingEntity For Work Order:	For Work Order:
MMOHED.QHCONO+QHDIVI; /	The indicates the company and division
· · · · · · · · · · · · · · · · · · ·	
	For Service Order: The field indicates the company and division, displayed as
	CONO DIVI.
ServiceOrder/ServiceOrderHeader/PaymentTerm/Term/Description	
For Service Order:	For Service Order:
CSYTAB.CTTX15; CRS175MI/GetGeneralCode	The field indicates the payment term description.
ServiceOrder/ServiceOrderHeader/ServiceMaterialGroup/EstimatedW For Work Order:	arehouseLocation/ID For Work Order:
MMOMAT.QMFWHL; MOS100MI/GetMtrl	The field indicates the warehouse
ServiceOrder/ServiceOrderHeader/ServiceOtherGroup/Classification/	
For Work Order: ACUSMIS.IMAIST; COS150MI/Get	For Work Order: The field indicates the transaction status
@listID	The field indicates the transaction status
	For Work Order:
	Set to 'Transaction Status'
ServiceOrder/ServiceOrderLine/LineNumber For Work Order:	For Work Order:
MMOOPE.QOOPNO; EQINFOMI/SelWorkOrderOp	The field indicates the operation number
	·
For Service Order: SSJOBH.SEJOBN	For Service Order: The field indicates the line number.
SSJOBH.SEJBSX.; SOS500MI/LstAssignmPerSO	The field indicates the fine number.
ServiceOrder/ServiceOrderLine/Description	
For Work Order:	For Work Order:
MMOOPE.QOOPDS; MOS100MI/GetOp	The field indicates the description of the line
For Service Order:	For Service Order:
SSHEAD.SDDLRM; SOS100MI/GetHead	The field indicates the error symptom description.
ServiceOrder/ServiceOrderLine/Note	Fau Mark Orden
For Work Order: MMOOPE.QOTXT1 + QOTXT2; MOS100MI/GetOp	For Work Order: The field indicates the notes of the line
·	
For Service Order:	For Service Order:
OSYTXL.TLTX60; SOS200MI/LstSOText @use	The field indicates the service order line note.
For Service Order:	For Service Order:
OSYTXL.TLTXEI; SOS200MI/LstSOText	The field indicates the external or internal text.
@type For Service Order:	For Service Order:
OSYTXL.TLTYTX; SOS200MI/LstSOText	The field indicates the type of text.
@languageID For Service Order:	For Service Order:
OSYTXL.TLLNCD; SOS200MI/LstSOText	The field indicates the language for service order line note,
ServiceOrder/ServiceOrderLine/DocumentReference	
@type	Fan Camilia Ordani
	For Service Order: The field indicates the reference order number (RORN).
	Set to 'ProductionOrder', if reference order number is 1.
	Set to 'PurchaseOrder', if reference order number is 2.
	Set to 'SalesOrder', if reference order number is 3. Set to 'RequisitionOrder', if reference order number is 4.
	Set to 'DistributionOrder', if reference order number is 4.
	Set to 'WorkOrder', if reference order number is 6.
	Set to 'ServiceOrder', if reference order number is 7. Set to 'ProjectOrder', if reference order number is 8.
ServiceOrder/ServiceOrderLine/DocumentReference/DocumentID/ID	Oct to 1 rejectoraci, il reletence oraci manibel is 0.
For Service Order:	For Service Order:
SSHEAD.SDRORN; SOS100MI/GetHead	The field indicates the reference order number.

For Service Order:

OCUSCO.CCCNPE; CMS055MI/LstByCustomer

@accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; /GetHead CONO DIVI. ServiceOrder/ServiceOrderLine/DocumentReference/Facility/IDs/ID For Service Order: For Service Order: SSHEAD.SDFACI; SOS100MI/GetHead The field indicates the facility. @accountingEntity For Service Order: The field indicates the company and division ServiceOrder/ServiceOrderLine/DocumentReference/Facility/Name For Service Order For Service Order: CFACIL.CFFACN; CRS008MI/Get The field indicates the faclity name. ServiceOrder/ServiceOrderLine/DocumentReference/SubLineNumber For Service Order: For Service Order: SSHEAD.SDRORX; SOS100MI/LstSOAssignm The field indicates the the reference order sub-line number ServiceOrder/ServiceOrderLine/ShipToParty/PartyIDs/ID For Service Order: For Service Order: SSADRE.HBCUNO The field indicates the ship to party ID. SSADRE.HBADID.; SOS100MI/GetHead @accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; /GetHead CONO DIVI. ServiceOrder/ServiceOrderLine/ShipToParty/PartyIDs/TaxID For Service Order: For Service Order: The field indicates the tax ID. OCUSMA.OKVRNO; CRS610MI/GetFinancial ServiceOrder/ServiceOrderLine/ShipToParty/Name For Service Order: For Service Order: SSADRE.HBCUNM; SOS100MI/LstSOAddr The field indicates the customer name. ServiceOrder/ServiceOrderLine/ShipToParty/Location/Name For Service Order: For Service Order: The field indicates the ship to party name SSADRE.HBCUNM; SOS100MI/LstSOAddr ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address For Service Order: Set to 'text'. ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/AttentionOfName For Service Order: For Service Order: SSADRE.HBYREF; SSADRE/LstSOAddr The field indicates the attention of name. ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/AddressLine For Service Order: For Service Order: SSADRE.HBCUA1 The field indicates the address line SSADRE.HBCUA2 SSADRE.HBCUA3 SSADRE.HBCUA4.; SOS100MI/LstSOAddr @sequence For Service Order: The field indicates the address line sequence. ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/CityName For Service Order: For Service Order: The field indicates the city name SSADRE.HBTOWN; SOS100MI/LstSOAddr ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/CountrySubDivisionCode For Service Order: For Service Order: SSADRE.HBECAR; SOS100MI/LstSOAddr The field indicates an area, province or state within a country. @listID For Service Order: Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no country is specified ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/CountryCode For Service Order: For Service Order: SSADRE.HBCSCD: SOS100MI/LstSOAddr The field indicates the country code. @listID For Service Order: Set to 'Countries' ServiceOrder/ServiceOrderLine/ShipToParty/Location/Address/PostalCode For Service Order: For Service Order: SSADRE.HBPONO; SOS100MI/LstSOAddr The field indicates the postal code. ServiceOrder/ServiceOrderLine/ShipToParty/Contact/ID

Infor May 26, 2023 537

For Service Order:

The field indicates the contact person ID.

@accountingEntity
For Service Order: For S

For Service Order: For Service Order:
SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO DIVI

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Name

For Service Order: For Service Order:

CCUCON.CCTX50; CRS618MI/Get

The field indicates the contact person name.

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication

@preferredIndicator

@listID

For Service Order: Set to 'false'.

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/ChannelCode

For Service Order:

Set to "Phone" if telephone number 1 or 2 or facsimile number or

mobile.

Set to "EMail" if e-mail address.

For Service Order:

Set to "Communication Channels"

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/UseCode

For Service Order:

Set to "Office" if telephone number 1, telephone number 2 or e-mail

address.

Set to "Fax" if facsimile number. Set to "Mobile" if mobile number.

@listID For Service Order:

Set to "Communication Use Codes".

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/DialNumber

For Service Order: For Service Order:

CCUCON.CCPHNO The field indicates the phone number.

CCPHN2; CRS618MI/Get

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/Address/AddressLine

For Service Order: For Service Order:

CCUCON.CCCUA1, CCCUA2, CCCUA3, CCCUA4; CRS618MI/Get

The field indicates the address line

@sequence

For Service Order:

The field indicates the sequence number of the address line

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/Address/CityName

For Service Order: For Service Order: CCUCON.CCTOWN; CRS618MI/Get The field indicates the city

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/Address/PostalCode
For Service Order:
For Service Order:

CCUCON.CCPONO; CRS618MI/Get The field indicates postal code

ServiceOrder/ServiceOrderLine/ShipToParty/Contact/Communication/URI

For Service Order: For Service Order:

CCUCON.CCEMAL; CRS618MI/Get

The field indicates the e-mail address.

ServiceOrder/ServiceOrderLine/ProjectReference/ID

For Service Order: For Service Order:

SSJOBH.SEPROJ; SOS100MI/GetAssignm

The field indicates the project reference ID.

@accountingEntity

For Service Order:

The field indicates the company and divison

ServiceOrder/ServiceOrderLine/OperationID/ID

For Work Order: For Work Order:

MMOOPE.QOOPNO; MOS100MI/GetOp The field indicates the operation number

For Service Order: For Service Order:

SSJOBH.SEESCO; SOS100MI/GetAssignm

The field indicates the service on the operation ID.

@accountingEntity

SSJOBH.SETRTI SSJOBH.SEFITM.

@location

For Work Order: For Work Order:

MMOHED.QHCONO+QHDIVI; / The field indicates the company and division

For Service Order:

The field indicates the company and division, displayed as

CONO_DIVI.

For Work Order: For Work Order:

MMOOPE.QOWHLO; / The field indicates the warehouse

ServiceOrder/ServiceOrderLine/EstimatedDuration

For Service Order: For Service Order: SSJOBH.SEPRTM For Service Order: The field indicates

SJOBH.SEPRTM The field indicates the estimated duration on when to finish the

SSJOBH.SEWOTM assignment.

· SOSSOOMI/LatAccignmPorSO	
; SOS500MI/LstAssignmPerSO ServiceOrder/ServiceOrderLine/ReportedDateTime	
For Work Order:	For Work Order:
MMOOPE.QORPDT + QORTM1; MOS100MI/GetOp	The field indicates the reporting date and time
For Service Order:	For Service Order:
SSJOBH.SEPMDT SSJOBH.SEPMTM	The field indicates the reported date and time.
.; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/CompletionDateTime	
For Service Order:	For Service Order:
SSJOBH.SERFDJ	The field indicates the completion date and time.
SSJOBH.SERFTJ.; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/MeterRecording/RecordedMeasure For Work Order:	For Work Order:
MILOMN.MNMVAO; MMS241MI/LstMeters	The field indicates the meter value
@unitCode	
For Work Order:	For Work Order:
MILOMN.MNMESO; MMS241MI/LstMeters	The field indicates the meter
ServiceOrder/ServiceOrderLine/Failure/Problem/ID	For Work Order:
For Work Order: MMOOPE.QOFCLA	For Work Order: The field indicates the problem code.
MMOSER.SEITNO.; MOS100MI.GetOp.FCLA	
MOS057MI.Lst.ITNO/	
ServiceOrder/ServiceOrderLine/Failure/Problem/Type	
For Work Order:	For Work Order:
MMOSER.SEMAIN; MOS057MI/Lst	The field is used to indicate the main service error report when several error reports exist for the same reference order.
ServiceOrder/ServiceOrderLine/Failure/Problem/Note	
For Work Order:	For Work Order:
MMOSER.SETXL1 + SETXL2; MOS057MI/GetText	The field indicates the problem notes.
@author For Work Order:	For Work Order:
MMOSER.SEREPR; MOS057MI/Lst	The field indicates the user ID of the person that reported the record.
@entryDateTime	' '
For Work Order:	For Work Order:
MMOSER.SERGDT + SERGTM; MOS057MI/Lst	The field indicates the failure date.
ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/ID For Work Order:	For Work Order:
MMOOPE.QOFCLA	The field indicates the symptom code
MMOSER.SEFCLA.; MOS100MI.GetOp.FCLA	
MOS057MI.Lst.FCLA/	For Service Order:
For Service Order:	The field indicates the Failure/Problem/Symptom/ID.
SSJOBH.SEESCO; SOS100MI/GetAssignm	
ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/Descriptio	n
For Service Order:	For Service Order:
SERSYM.SLTX15; SOS100MI/LstErrSym	The field indicates the description of the problem.
ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/Note For Work Order:	For Work Order:
MMOSER.SETXL3 + SETXL4; MOS057MI/GetText	The field indicates the symptom notes
,	
For Service Order:	For Service Order:
SSJOBH.SEETX1 SSJOBH.SEETX2	The field indicates the notes for the sympton or problem.
SSJOBH.SEETX3	
SSJOBH.SEETX4.; SOS100MI/GetAssignm	
ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/UserArea/	
For Work Order:	For Work Order: The field indicates the date and time the equipment broke down
MMOSER.SEBRDT + SEBRTI; MOS057MI/Lst ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/ID	The field indicates the date and time the equipment broke down.
For Work Order:	For Work Order:
MMOOPE.QOFCL2; MOS057MI/Lst	The field indicates the problem cause code
For Coming Order	
For Service Order: SSJOBH.SEERCO; SOS100MI/GetAssignm	For Service Order: The field indicates the Failure/Problem/Cause/ID.
ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/Description	The held indicates the Fallatett Tobletti/Gade/ID.
For Service Order:	For Service Order:
SERCOD.SNTX15; SOS100MI/LstErrCde	The field indicates the error code description.
ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/Note	
For Work Order:	For Work Order:
MMOSER.SETXL5 + SETXL6; MOS057MI/Lst	The field indicates the problem cause notes
ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/ID	

For Work Order:

MMOOPE.QOFCL3: MOS100MI.GetOp.FCLA3

MOS057MI.Lst.FCLA3/

For Work Order:

The field indicates the remedy code

For Service Order: SSJOBH.SEMTCO For Service Order:

The field indicates the OEM codes identified on the operation to

correct the problem.

SEMECO; SOS100MI/GetAssignm ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/Description

For Service Order:

SSJOBH.SETX15; SOS100MI/LstActTxt

For Service Order:

The field indicates the action text.

@languageID For Work Order:

MMOSER.SETXL7 + SETXL8; MOS057MI/GetText

For Work Order:

The field indicates the remedy description

ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/Note

For Work Order:

MMOSER.SETXL9 + SETXL0; MOS057MI/GetText

For Work Order:

For Service Order:

The field indicates the repair comment text.

For Service Order: SSJOBH.SEMTX1 SSJOBH.SEMTX2

SSJOBH.SEMTX3 SSJOBH.SEMTX4 .; SOS100MI/GetAssignm The field indicates the actions text description.

@status

For Work Order: MMOSER.SESTAT; MOS057MI/Lst For Work Order:

The field indicates the status of the error report

ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/UserArea/Property/NameValue

For Work Order:

MMOSER.SEMRDT + SEMRTI, MMOSER.SEEQDT + SEEQTI,

MMOSER.SESTAT.; MOS057MI/Lst

For Work Order:

The field indicates the date the object was ready to be put back in

operation after a failure.

The field indicates the available date and time. The field indicates the service report status.

@name

For Work Order:

Set to "CompletionDateTime". Set to "AvailableDateTime". Set to "ServiceReportStatus"

ServiceOrder/ServiceOrderLine/Status/Code

For Work Order:

MMOOPE.QOWOST; MOS100MI/GetOp

For Service Order:

SSJOBH.SEJBST; SOS100MI/GetAssignm

For Work Order:

The field indicates the standard status on work order line

Alternatives: 80=Closed 20=Open

30, 34, 35, 36, 37, 38, 40, 50, 60, 70=Approved

10=Pending 89, 90=Completed

For Service Order:

The field indicates the assignment status (JBST).

Set to 'Approved', if the service order status are 30, 31, 32 ,33 ,34 ,

35,36,37,39,40,41,42,43,44,45,50,53,54,58 and 59. Set to 'Hold', if the service order status is 49.

Set to 'Completed', if the service order status are 60 or 85.

Set to 'Invoiced', if the service order status is 80.

ServiceOrder/ServiceOrderLine/Status/ReasonCode

For Work Order:

@listID

MMOOPE.QOWOST; MOS100MI/GetOp

For Work Order:

For Service Order: Set to 'Service Order Status'

The field indicates the M3 status code on work order line

For Service Order:

SSJOBH.SEJBST; SOS100MI/GetAssignm

For Service Order:

The field indicates the assignment status.

@name For Work Order:

MMOOPE.QOWOST; MOS100MI/GetOp

For Work Order:

The field indicates the M3 status on work order line

Alternatives: 10=Preliminary 20=Definite

30=Order started/previous operation not started

34=Previous operation ready to begin 35=Preceding operation scheduled 36=Preceding operation started 37-Preceding operation partially reported 38=Preceding operation stopped

40=Ready to begin/preceding operation complete

50=Scheduled

ServiceOrder	
	60=Started
	70-Partially reported
	80=Stopped 89=Flagged as completed, work order not closed
	90=Flagged as completed
ServiceOrder/ServiceOrderLine/ActivityTemplateCode	
For Work Order:	For Work Order:
MMOOPE.QOSUFI, QOSTRT; MOS100MI/GetOp	The field indicates the ActivityTemplate ID
ServiceOrder/ServiceOrderLine/ServiceTypeCode	
For Work Order:	For Work Order:
MMOOPE.QOSTYP; MOS300MI/GetBasic	The field indicates the service type code
For Service Order:	For Service Order:
SSJOBH.SEASST; SOS500MI/LstAssignmPerSO	The field indicates the assignment type.
ServiceOrder/ServiceOrderLine/CoverageTypeCode	For Comite Order
For Service Order: SSJOBH.SECTNO	For Service Order: The field indicates the agreement number and agreement type.
SSJOBH.SEAGTP.; SOS100MI/GetAssignm	The hold indicates the agreement hamber and agreement type.
ServiceOrder/ServiceOrderLine/ConfiguredAsset/ID	
For Work Order:	For Work Order:
MMOOPE.QOPRNO + QOBANO; MOS100MI/GetOp	The field indicates the equipment ID (PRNO + BANO)
For Service Order:	For Service Order:
SSJOBH.SEINNO; SOS500MI/LstAssignmPerSO	The field indicates the individual item number.
@accountingEntity	5 W 10 I
For Work Order: MMOOPE.QOCONO+QODIVI; /	For Work Order: The field indicates the company and division
IVIIVICOI L. WOODINO I WODINI, /	The hold indicates the company and division
For Service Order:	For Service Order:
SSHEAD.CONO	The field indicates the company and division, displayed as
SSHEAD.DIVI.; / @Jocation	CONO_DIVI.
For Work Order:	For Work Order:
MMOOPE.QOWHLO; /	The field indicates the warehouse
ServiceOrder/ServiceOrderLine/ConfiguredAsset/Description	
For Work Order:	For Work Order:
MILOIN.LIALII; MMS240MI/GetBasic	The field indicates the Equipment description.
For Service Order:	For Service Order:
SSJOBH.SEMODE; SOS100MI/GetAssignm	The field indicates the equipment description.
ServiceOrder/ServiceOrderLine/EstimatedDownTimeDuration	Fan Wards Ondarn
For Work Order: MMOOPE.QODOWT; MOS100MI/GetOp	For Work Order: The field indicates the estimated downtime of the equipment.
ServiceOrder/ServiceOrderLine/CustomerTimePeriod/StartDateTime	The hold indicates the commuted downtains of the equipment.
For Service Order:	For Service Order:
SSJOBH.SERQSD	The field indicates the customer requested start date and time.
SSJOBH.SERQST.; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/CustomerTimePeriod/EndDateTime For Service Order:	For Service Order:
SSJOBH.SERQFD	The field indicates the customer requested end date and time.
SSJOBH.SERQFT.; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/StartDateTime	
For Work Order:	For Work Order:
MMOOPE.QOSTDT + QOMSTI; MOS100MI/GetOp	The field indicates the Planned Start DateTime.
For Service Order:	For Service Order:
SSJOBH.SEPSDJ	The field indicates the planned start date and time.
SSJOBH.SEPSTJ.; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/EndDateTime	For Work Order
For Work Order: MMOOPE.QOFIDT + QOMFTI; MOS100MI/GetOp	For Work Order: The field indicates the Planned End DateTime.
5. 2. 2. 2	
For Service Order:	For Service Order:
SSJOBH.SEPFDJ SSJOBH.SEPFTJ.; SOS500MI/LstAssignmPerSO	The field indicates the planned end date and time.
ServiceOrder/ServiceOrderLine/ActualTimePeriod/StartDateTime	
For Work Order:	For Work Order:
MMOOPE.QORSDT + QORSTI; MOS100MI/GetOp	The field indicates the Actual Start DateTime.
For Comitoe Ordon	For Coming Order
For Service Order: SSJOBH.SERSDJ	For Service Order: The field indicates the actual start date and time.
SSJOBH.SERSTJ.	The hold indicated the dotadi start date and time.
; SOS500MI/LstAssignmPerSO	
ServiceOrder/ServiceOrderLine/ActualTimePeriod/EndDateTime	

For Work Order:

ServiceOrder MMOOPE.QOREFD + QORFTI; MOS100MI/GetOp For Work Order: The field indicates the the actual finish date time. For Service Order: SSJOBH.SERFDJ For Service Order: SSJOBH.SERFTJ. The field indicates the actual end date and time. ; SOS500MI/LstAssignmPerSO ServiceOrder/ServiceOrderLine/PlannedTravelTimePeriod/Duration For Service Order For Service Order SSJOBH.SETRTI; SOS500MI/LstAssignmPerPO The field indicates the planned travel time duration ServiceOrder/ServiceOrderLine/SupplierParty/PartyIDs/ID For Work Order For Work Order: MMOOPE.QOSUNO; MOS100MI/GetOp The field indicates the supplier number on the operation @accountingEntity For Work Order: For Work Order: MMOOPE.QOCONO+QODIVI; / The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI). ServiceOrder/ServiceOrderLine/SupplierParty/Name For Work Order For Work Order: The field indicates the supplier name CIDMAS.IDSUNM; CRS620MI/GetBasicData ServiceOrder/ServiceOrderLine/RequiredServiceSkills/Code For Service Order: For Service Order: SSJOBH.SEQUNO; SOS500MI/LstAssignmPerSO The field indicates the required service skills. @accountingEntity For Work Order: For Work Order: MMOOPE.QOCONO+QODIVI; / The field indicates the company and division For Service Order: The field indicates the company and divison @location For Work Order: For Work Order: MMOOPE.QOWHLO:/ The field indicates the warehouse ServiceOrder/ServiceOrderLine/RequiredServiceSkills/Name For Work Order: For Work Order: MMOOPE.QOPLGR; MOS100MI/GetOp The field indicates the RequiredServiceSkills/Workcewnter from operation For Service Order: CSYTAB.CTTX15; CRS175MI/GetGeneralCode For Service Order: The field indicates the required service skills name. ServiceOrder/ServiceOrderLine/CustomerCallReference/DocumentID/ID For Service Order: For Service Order: SSHEAD.SDYREF; SOS100MI/GetHead The field indicates the customer call reference. @accountingEntity For Service Order: For Service Order: SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.; / CONO DIVI. ServiceOrder/ServiceOrderLine/AssignmentGroup/LineNumber For Work Order: For Work Order: MMOOPS.QQACTS, ACTT; MOS104MI/LstOpElement The field indicates the assignment line and operation element For Service Order: For Service Order: SSJOBH SFORNO The field indicates the operation element/assignment line. SSJOBH.SEJOBN SSJOBH.SEJBSX. ; SOS500MI/LstAssignmPerSO ServiceOrder/ServiceOrderLine/AssignmentGroup/ActivityEngineerPerson/IDs/ID The field indicates the employee number. For Work Order: MMOOPS.QQEMNO; MOS104MI/GetOpElement For Service Order: SSJOBH.SETECH; SOS500MI/LstAssignmPerSO @accountingEntity For Work Order: For Work Order:

MMOOPS.QQCONO+QQDIVI; / The field indicates the company and division

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as SSHEAD.DIVI.: CONO DIVI

ServiceOrder/ServiceOrderLine/AssignmentGroup/ActivityEngineerPerson/Name

For Work Order: For Work Order:

MMOOPS.QQEMNM; MOS104MI/LstOperElement The field indicates the employee name

For Service Order: For Service Order:

CEAEMP.EAEMNM; CRS530MI/LstEmployee The field indicates the employee name

ServiceOrder/ServiceOrderLine/AssignmentGroup/Status/Code

For Work Order:

MMOOPS.QQSTMB; MOS104MI/GetOpElement

The field indicates the standard status of the assingment group

Alternatives: 40=Accepted

For Work Order:

For Service Order:

SSJOBH.SEJBST; SOS100MI/GetAssignm

20, 21, 25, 30, 31=Assigned

41,8A-Travel Started 42,8B=Travel Stopped 44,8C=Arrived on Site

45=Started 80=Stopped 89, 90=Completed 46=Pending

10, 19, 98,99=Rejected

For Service Order:

The field indicates the assignment status (JBST).

Set to 'Assigned', if the assignment status are 35, 36, 37 or 39.

Set to 'Started', if the assignment status are 40 or 41.

Set to 'Completed', if the assignment status are 42, 43, 60, 80 or 85.

Set to 'Started', if the assignment status are 44 or 45. Set to 'Stopped', if the assignment status is 49.

Set to 'Started', if the assignment status is 50, 53, 54, 58 or 59. Set to 'Completed', if the assignment status are 60 or 85.

ServiceOrder/ServiceOrderLine/AssignmentGroup/Status/ReasonCode

For Work Order:

MMOOPS.QQSTMB; MOS104MI/GetOpElement

For Work Order: The field indicates the M3 status code on assignment group

For Service Order:

SSJOBH.SEJBST; SOS100MI/GetAssignm

For Service Order: The field indicates

The field indicates the assignment status.

55JOBH.SE. **@name**

For Work Order:

MMOOPS.QQSTMB; MOS104MI/GetOpElement

For Work Order:

The field indicates the M3 status on assignment group

Alternatives:

10=Declined by emloyee 19=To be reallocated

20=Assignment assigned to employee 21=Temporary reallocation status

25=Sent to device 30=Queued for dispatch 31=On the technician's device 40=Accepted by employee 41=Travel Started 42=Travel Stopped 44=Arrived on Site 45=Operation Started 46=Stopped/Pending

89=Finished 90=Complete

98=Cancellation Notification 99=Canceled 8A=Travel Back Started

80=Stopped/Run disturbance

8B=Travel Back Stopped 8C=Arrived at Depot

ServiceOrder/ServiceOrderLine/AssignmentGroup/AcceptedDateTime

For Service Order: STSHIS.SYCDJS

STSHIS.SYCTJS.; SOS400MI/LstAssignStsHis

For Service Order:

The field indicates the date and time the assignment accepted date

and time.

ServiceOrder/ServiceOrderLine/AssignmentGroup/RejectionDatetime

For Service Order: STSHIS.SYCDJS+ For Service Order:

The field indicates the date and time the assignment got rejected

SYCTJS; SOS400MI/LstAssignStsHis

Service Order/Service Order Line/Assignment Group/Planned Time Period/Start Date Time

For Work Order: For Work Order:

For Service Order: SSJOBH.SEPSDJ SSJOBH.SEPSTJ. For Service Order:

The field indicates the planned start date and time.

; SOS500MI/LstAssignmPerSO

ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTimePeriod/EndDateTime

For Work Order: For Work Order:

MMOOPE.QOFIDT + QOMFTI; MOS100MI/GetOp

The field indicates the planned finish date time

For Service Order:

For Service Order:

SSJOBH.SEPFTJ. The field indicates the planned end date and time.

; SOS500MI/LstAssignmPerSO

ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/StartDateTime

The field indicates the actual start date time For Work Order:

MMOOPE.QORSDT + QORSTI; MOS100MI/GetOp

For Service Order: SSJOBH.SERSDW SSJOBH.SERSTW.

; SOS500MI/LstAssignmPerSO

ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/EndDateTime

The field indicates the the actual finish date time.

MMOOPE.QORSFD + QORFTI; MOS100MI/GetOp

For Service Order: SSJOBH.SERFDW SSJOBH SERETW

; SOS500MI/LstAssignmPerSO

ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTravelTimePeriod/Duration

For Service Order: For Service Order:

SSJOBH.SETRTI; SOS500MI/LstAssignmPerSO The field indicates the planned travel time duration

ServiceOrder/ServiceOrderLine/AssignmentGroup/Note

For Work Order: For Work Order:

MMOOPS.QQACDS, QQACTR, QQCATY; MOS104MI/LstOpElement The field indicates the description, work element and capability type

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/LineNumber

For Work Order: For Work Order:

MMOMAT.QMMSEQ; EQINFOMI/LstWorkOrdMtrl The field indicates the material line sequense number

For Service Order: For Service Order: SSLINE.SFJOBN The field indicates the material line group line number.

SSLINE.SFJBSX SSLINE.SFPONR SSLINE.SFPOSX.

; SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialEngineerPerson/IDs/ID

For Service Order: For Service Order:

SSLINE.SFTECH; SOS100MI/LstLine The field indicates the technician.

@accountingEntity

For Service Order: For Service Order:

The field indicates the company and division, displayed as SSHEAD.CONO

SSHEAD.DIVI.; / CONO DIVI.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialEngineerPerson/Name For Service Order: For Service Order

CEAEMP.EAENMN; CRS530MI/LstEmployee The field indicates the company / division number.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Status/Code

For Work Order:

MMOMAT.QMWMST; MOS100MI/GetMtrl The field indicates the standard status of the service material group

Alternatives:

20, 30, 60, 70, 80=Open 10, 13, 14, 90=Invoice For Service Order: SSLINE.SFORST; SOS100MI/LstLine

94=Canceled

For Work Order:

For Service Order:

The field indicates the material status code (ORST).

Set to 'Open', if material status code are 22, 23, 24, 25, 26, 32, 33, 34, 35, 36, 42, 43, 44, 45, 46, 52, 53, 54, 55, 56, 62, 63, 64, 65 or 66.

Set to 'Invoiced', if material status code is 77.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Status/ReasonCode

For Work Order: For Work Order

MMOMAT.QMWMST; MOS100MI/GetMtrl The field indicates the M3 status code on service material group

For Service Order:

For Service Order: SSLINE.SFORST; SOS100MI/LstLine The field indicates the material status code.

@name

For Work Order: For Work Order:

MMOMAT.QMWMST; MOS100MI/GetMtrl The field indicates the M3 status on service material group

Alternatives: 10=Preliminary

20=Item is discontinued and replacement is conditional

14=Item is discontinued at this warehouse

20=Definite

30=Material issue without picking list (kanban) 60=Requisition created but not allocated

ServiceOrder 70=Requisition created and allocated 80=Requisition created and picking list printed 90=Material issue reported and flagged as completed 94=Material line status flagged as deleted ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Note For Work Order: For Work Order: MMOMAT.QMFMT1; MOS100MI/GetMtrl The field indicates the text For Service Order: For Service Order: OSYTXL.TLTX60; SOS200MI/LstSOText The field indicates the text. @use For Service Order: For Service Order: OSYTXL.TLTXEI; SOS200MI/LstSOText The field indicates the external or internal ID. @type For Service Order: For Service Order: OSYTXL.TLTYTX; SOS200MI/LstSOText The field indicates the type of text. @languageID For Service Order: For Service Order: OSYTXL.TLLNCD; SOS200MI/LstSOText The field indicates the language used for the notes. ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/CreationDateTime For Work Order: The field indicates the entry date time. MMOMAT.QMRGDT + QMRGTM; MOS100MI/GetMtrl For Service Order: SSLINE.SFRGDT SSLINE.SFRGTM. SOS100MI/LstLine ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/InvoiceDateTime For Service Order: For Service Order: SSLINE.SFLIDT; SOS100MI/LstLine The field indicates the invoice date and time. ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialItem/ItemID/ID For Work Order: For Work Order: MMOMAT.QMMTNO; MOS100MI/GetMtrl The field indicates the material id/item number. For Service Order: For Service Order: SSLINE.SFITNO; SOS100MI/LstLine The field indicates the material item. @accountingEntity For Work Order: For Work Order: MMOMAT.QMCONO+QMDIVI; / The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is For Service Order: displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). SSHEAD.CONO SSHEAD.DIVI.: / For Service Order: The field indicates the company and division, displayed as CONO DIVI. ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialItem/Description For Work Order: For Work Order: MITMAS.MMITDS: MMS200MI/Get The field indicates thename of the material For Service Order: For Service Order: SSLINE.SFITDS; SOS100MI/LstLine The field indicates the material item description. ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Classification/Codes/Code For Work Order: For Work Order: MHILIN.G2OEND The field indicates the item category MMOMAT.QMIORL The field indicates the interface order line MMOMAT.QMWHSL The field indicates the stock location MMOMAT.QMPRMO The field indicates the price origin The field indicates the claim warranty MMOMAT.ACWA MMOMAT.MAUP The field indicates if the sales price is manually updated MMOMAT.BANO The field indicates serial or lot number of the item MMOMAT.SPMT.; MMS200MI.Get.TPCD The field indicates the issue method

MOS100MI.GetMtrl.IORL
MOS100MI.GetMtrl.WHSL
MOS100MI.GetMtrl.PRMO
MOS100MI.GetMtrl.ACWA

For Service Order:
Set to 'Material'.

For Service Order:

MOS100MI.GetMtrl.MAUP MOS100MI.GetMtrl.BANO MOS100MI.GetMtrl.SPMT/

SSLINE.SFSCOD; SOS100MI/LstLine

@sequence

For Work Order:

The field indicates the sequence number starting with 1.

@listID

For Service Order:

The field indicates the service material group sequence.

For Work Order:

The field indicates the listID 'Item Category' The field indicates the listID 'Interface Order Line' The field indicates the lisID 'Stock Location' The field indicates the list ID 'Price Origin' The field indicates the list ID 'Claim Warranty' The field indicates the list ID 'Manual Update' The field indicates the list ID 'Lot Number'

The field indicates the list ID 'Issue Method'

For Service Order:

Set to 'Service Expense Category'.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/PartyIDs/ID

For Work Order: For Work Order:

MMOMAT.QMCUNO + QMADID; MOS100MI/GetMtrl The field indicates the delivery address for the material (if populated)

Else take from WO header

For Service Order: SSADRE.HBCUNO

For Service Order:

SSADRE.HBADID. The field indicates the delivery address for the material.

; SOS100MI/GetHead

@accountingEntity

For Work Order: For Work Order:

MMOMAT.QMCONO+QMDIVI; / The field indicates the accounting entity.

If ShipToPartyMaster is enabled in BOD Processor Master AE tab, For Service Order: this is displayed as Company (CONO). Otherwise, this is displayed as

SSHEAD.CONO Company and Division (CONO DIVI). SSHEAD.DIVI.; /

For Service Order: The field indicates the company and division, displayed as

CONO DIVI.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/PartyIDs/TaxID For Service Order:

For Service Order: OCUSMA.OKVRNO; CRS610MI/GetFinancial The field indicates the tax ID

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Name

For Work Order:

OCUSAD.OPCUNM; CRS610MI.GetAddress.CUNM The field indicates the company location name for delivery address

CRS530MI.LstAddress.CUNM MOS272MI.GetAddressByld.CUNM

For Service Order: The field indicates the service material group name.

CRS300MI.GetShipVia.CUNM MOS156MI.Get.CUNM

EQINFOMI.GetMCOAddress.CUNM/

For Service Order:

SSADRE.HBCUNM; SOS100MI/LstSOAddr

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/ID

For Work Order For Work Order

MMOMAT.QMADRR+QMADRT+QMADID+QMLTYP; MOS100MI/ The field indicates the address file, address type and address ID

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Name

For Work Order:

The field indicates the locatio name

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address

@type

For Work Order: Set to 'text'

For Service Order: Set to 'text'.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/AttentionOfName

For Work Order: For Work Order:

OCUSAD.OPYREF; CRS610MI.GetAddress.YREF The field indicates the attention / contact name

CRS530MI.LstAddress.YREF

MOS272MI.GetAddressByld.YREF For Service Order: MOS156MI.Get.YREF

The field indicates the attention pf name. EQINFOMI.GetMCOAddress.YREF/

For Service Order:

SSADRE.HBYREF; SSADRE/LstSOAddr

CRS530MI.LstAddress.CUA1+CUA2+CUA3+CUA4

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/AddressLine

For Work Order:

OCUSAD.OPCUA1 + OPCUA2 + OPCUA3 + OPCUA4; The field indicates the address line. CRS610MI.GetAddress.CUA1+CUA2+CUA3+CUA4

MOS272MI.GetAddressByld.CUA1+CUA2+CUA3+CUA4 CRS300MI.GetShipVia.ADR1+ADR2+ADR3+ADR4

MOS156MI.Get.CUA1+CUA2+CUA3+CUA4

EQINFOMI.GetMCOAddress.CUA1+CUA2+CUA3+CUA4/

For Service Order: SSADRE.HBCUA1 SSADRE.HBCUA2 SSADRE.HBCUA3

SSADRE.HBCUA4.; SOS100MI/LstSOAddr

@sequence

For Work Order:

For Service Order:

The field indicates the address line.

The field indicates the address line sequence number

For Service Order:

The field indicates the address line sequence

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CityName

For Work Order:

OCUSAD.OPTOWN; CRS610MI.GetAddress.TOWN

CRS530MI.LstAddress.TOWN MOS272MI.GetAddress.TOWN CRS300MI.GetShipVia.TOWN MOS156MI.Get.TOWN

EQINFOMI.GetMCOAddress.TOWN/

For Service Order:

SSADRE.HBTOWN; SOS100MI/LstSOAddr

For Work Order:

The field indicates the city of the address

For Service Order:

The field indicates the city name.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CountrySubDivisionCode

For Work Order: For Work Order:

OCUSAD.OPECAR; CRS610MI.GetAddress.ECAR The field is used for subdivision or state code

CRS530MI.LstAddress.ECAR MOS272MI.GetAddress.ECAR

CRS300MI.GetShipVia.ECAR MOS156MI.Get.ECAR

EQINFOMI.GetMCOAddress.ECAR/

For Service Order:

SSADRE.HBECAR; SOS100MI/LstSOAddr

@listID

For Work Order:

For Service Order:

Set list ID to 'Canadian Provinces' if the country is Canada. Set list ID to 'France - Departements' if the country is France. Set list ID to 'US States' if the country is United States.

The field indicates an area, province or state within a country.

Set list ID to 'Country Sub-divisions' if the country 's SubDivisions-

[CountryCode]'.

For Service Order:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no country is specified.

The field indicates the country code.

The field indicates the country code of the address

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/CountryCode For Work Order:

For Work Order:

OCUSAD.OPCSCD; CRS610MI.GetAddress.CSCD

CRS530MI.LstAddress.CSCD MOS272MI.GetAddressByID.CSCD CRS300MI.GetShipVia.CSCD

MOS156MI.Get.CSCD

EQINFOMI.GetMCOAddress.CSCD/

For Service Order:

SSADRE.HBCSCD; SOS100MI/LstSOAddr

@listID

For Work Order: Set to 'Countries'

For Service Order:

For Service Order: Set to 'Countries'

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Location/Address/PostalCode For Work Order:

For Work Order:

OCUSAD.OPPONO; CRS610MI.GetAddress.PONO

CRS530MI.LstAddress.PONO MOS272MI.GetAddressByld.PONO CRS300MI.GetShipVia.PONO

MOS156MI.Get.PONO

EQINFOMI.GetMCOAddress.PONO/

The field indicates the postal code for the delivery address

For Service Order:

The field indicates the postal code.

For Service Order:

SSADRE.HBPONO; SOS100MI/LstSOAddr

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/ID

For Service Order: For Service Order:

OCUSCO.CCCNPE; CMS055MI/LstByCustomer The field indicates the contact person ID.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; CONO DIVI.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Name For Service Order: For Service Order

CCUCON.CCTX50; CRS618MI/Get The field indicates the contact person name

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication

@preferredIndicator

For Service Order: Set to 'false'.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/ChannelCode

For Service Order:

Set to "Phone" if telephone number 1 or 2 or facsimile number or

mobile

Set to "EMail" if e-mail address.

@listID

For Service Order:

Set to "Communication Channels".

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/UseCode

For Service Order:

Set to "Office" if telephone number 1, telephone number 2 or e-mail

Set to "Fax" if facsimile number Set to "Mobile" if mobile number.

@listID

For Service Order: Set to "Communication Use Codes"

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/DialNumber

For Service Order: For Service Order:

CCUCON.CCPHNO The field indicates the phone number.

CCPHN2; CRS618MI/Get

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/Address/AddressLine

For Service Order For Service Order

CCUCON.CCCUA1, CCCUA2, CCCUA3, CCCUA4; CRS618MI/Get The field indicates the address line

@sequence

For Service Order: The field indicates the sequence number of the address line

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/Address/CityName

For Service Order: For Service Order: CCUCON.CCTOWN; CRS618MI/Get The field indicates the city

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/Address/PostalCode

For Service Order: For Service Order:

CCUCON.CCPONO; CRS618MI/Get The field indicates the postal code

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Contact/Communication/URI For Service Order: For Service Order:

CCUCON.CCEMAL; CRS618MI/Get

The field indicates the e-mail address.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedDeliveryTypeCode

For Service Order: For Service Order:

SSLINE.SFLTYP; SOS100MI/LstLine The field indicates the line type. Set to 'VAN', if warehouse is tech.

Set to 'DEP' if item is stocked.

@accountingEntity

For Service Order:

The field indicates the company and division

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualDeliveryTypeCode

For Service Order For Service Order:

SSLINE.SFLTYP; SOS100MI/LstLine The field indicates the line type.

Set to 'VAN', if warehouse is tech. Set to'DEP' if item is stocked.

@accountingEntity

For Service Order:

The field indicates the warehouse for the material

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference

@type

For Work Order: For Work Order:

MMOMAT.QMRORC; MOS100MI/GetMtrl The field indicates the document reference type.

Alternatives:

1 = ProductionOrder

2 = PurchaseOrder 3 = SalesOrder 4 = RequisitionOrder 5 = DistributionOrder 6 = WorkOrder 7 = ServiceOrder 8 = ProjectOrder 9 = ClaimOrder

For Service Order:

The field indicates the reference order number (RORN). Set to 'ProductionOrder', if reference order number is 1. Set to 'PurchaseOrder', if reference order number is 2. Set to 'SalesOrder', if reference order number is 3. Set to 'RequisitionOrder', if reference order number is 4. Set to 'DistributionOrder', if reference order number is 5. Set to 'WorkOrder', if reference order number is 6. Set to 'ServiceOrder', if reference order number is 7. Set to 'ProjectOrder', if reference order number is 8.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference/DocumentID/ID

For Work Order: For Work Order:

MMOMAT.QMRORN; MOS100MI/GetMtrl

The field indicates the reference order number

For Service Order: For Service Order:

SSLINE.SFRORN; SOS100MI/LstLine The field indicates the reference order number.

@accountingEntity

For Work Order: For Work Order:

MMOMAT.QMCONO+QMDIVI; / The field indicates the company and division

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO DIVI.

@location

For Work Order: For Work Order:

MMOMAT.QMWHLO; / The field indicates the warehouse location

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference/LineNumber

For Work Order: The field indicates the reference order line number

MMOMAT.QMRORL; MOS100MI/GetMtrl

For Service Order:

SSLINE.SFRORL; SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference/Facility/IDs/ID

For Service Order: For Service Order:

SSHEAD.SDFACI; SOS100MI/GetHead The field indicates the facility ID.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO DIVI

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference/Facility/Name
For Service Order:
For Service Order:

CFACIL.CFFACN; CRS008MI/Get The field indicates the facility name.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/DocumentReference/SubLineNumber

For Service Order: For Service Order:

SSLine.SFRORX; SOS100MI/LstLine The field indicates the reference order sub-line number.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/SupplierParty/PartyIDs/ID

For Work Order: For Work Order:

MMOMAT.QMSUNO; MOS100MI/GetMtrl The field indicates the supplier code

For Service Order: For Service Order:

SSLine.SFSUNO; SOS100MI/LstLine The field indicates the supplier number.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the accounting entity.

SSHEAD.DIVI.; /

If SupplierShipFromCarrierRemitToMaster_MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/SupplierParty/PartyIDs/TaxID

For Service Order: For Service Order:

CIDMAS.IDTINO; CRS620MI/GetBasicData

The field indicates the tax ID.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/SupplierParty/Name

For Service Order: For Service Order:

CIDMAS.IDSUNM; CRS620MI/GetBasicData

The field indicates the supplier name.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedWarehouseLocation/ID

For Work Order:

MMOMAT.QMFWHL; MOS100MI/GetMtrl

For Work Order:

The field indicates the warehouse

@accountingEntity

For Work Order: For Work Order:

MMOMAT.QMCONO+QMDIVI; / The field indicates the company and division

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedQuantity

For Work Order: For Work Order:

MMOMAT.QMCNQT; MOS100MI/GetMtrl The field indicates the estimated quantity

For Service Order:

For Service Order: SSLINE.SFORQA; SOS100MI/LstLine The field indicates the estimated quantity.

@unitCode

For Work Order:

For Work Order: MMOMAT.QMPEUN; MOS100MI/GetMtrl

The field indicates the estimated quantity Unit of measure.

For Service Order: For Service Order:

The field indicates the estimated quantity unit of measure. SSLINE.SFALUN; SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedBaseUOMQuantity

For Service Order: For Service Order:

SSLINE.SFORQT; SOS100MI/LstLine The field indicates the estimated quantity in basic unit of measure.

@unitCode

For Service Order: For Service Order:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualQuantity

For Work Order:

MMOMAT.QMRPQT; MOS100MI/GetMtrl The field indicates the actual quantity/reported quantity

For Service Order: For Service Order:

SSLINE.SFDLQA; SOS100MI/LstLine The field indicates the actual quantity/ reported quantity.

@unitCode

For Work Order:

The field indicates the estimated quantity Unit of measure. MMOMAT.QMPEUN; MOS100MI/GetMtrl

For Service Order: For Service Order:

SSLINE.SFALUN; SOS100MI/LstLine The field indicates the estimated quantity unit of measure.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualBaseUOMQuantity

For Service Order: For Service Order:

SSLINE.SFDLQT: SOS100MI/LstLine The field indicates the delivered quantity in basic unit of measure.

@unitCode

For Service Order: For Service Order:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/InvoiceQuantity

For Work Order: For Work Order:

ACUINV.ITTRQT; COS170MI/Get The field indicates the invoice quantity

For Service Order: For Service Order:

SSLINE.SFIVQA; SOS100MI/LstLine The field indicates the actual quantity/ reported quantity.

@unitCode

For Work Order: For Work Order:

ACUINV.ITUNIOT; COS170MI/Get The field indicates the currency

For Service Order: For Service Order:

SSLINE.SFALUN; SOS100MI/LstLine The field indicates the estimated quantity unit of measure.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/InvoiceBaseUOMQuantity

For Service Order: For Service Order:

SSLINE.SFIVQT; SOS100MI/LstLine The field indicates the invoice quantity in basic unit of measure

@unitCode For Service Order:

For Service Order:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualWarehouseLocation/ID For Work Order For Work Order:

MMOMAT.QMWHLO; MOS100MI/GetMtrl The field indicates the warehouse

For Service Order: For Service Order:

SSLINE.SFWHLO; SOS100MI/LstLine The field indicates the warehouse.

@accountingEntity

For Work Order: For Work Order:

MMOMAT.QMCONO+QMDIVI; / The field indicates the company and division

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO DIVI.

@location For Work Order: For Work Order:

MMOMAT.QMWHLO; / The field indicates the warehouse

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualWarehouseLocation/Name

For Service Order For Service Order:

MITWHL.MWWHNM; MMS005MI/GetWarehouse The field indicates the warehouse name.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedCostPriceAmount

For Work Order: For Work Order:

MMOMAT.QMESBU; MOS100MI/GetMtrl The field indicates the estimated cost price amount

For Service Order:

For Service Order:

SSLINE.SFUCOS; SOS100/LstLine The field indicates the estimated cost price amount.

@currencyID

For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the currency for estimated cost price amount.

For Work Order:

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualCostPriceAmount

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100/LstLine The field indicates the actual cost price amount.

@currencyID

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicats the currency.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedSalesPriceAmount

For Work Order: For Work Order:

MMOMAT.QMSAPR: MOS100MI/GetMtrl The field indicates the estimated sales price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine The field indicates the estimated sales price amount.

@currencyID

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the material currency for sales price.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualSalesPriceAmount

For Work Order: For Work Order:

ACUINV.ITAWCO; COS170MI/Get The field indicates the actual sales price amount

For Service Order: For Service Order:

SSLINE.SFSAPR: SOS100MI/LstLine The field indicates the actual sales price amount.

@currencyID

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the material currency for sales price amount.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedInvoicePriceAmount For Work Order: For Work Order:

MMOMAT.QMNEPR; MOS100MI/GetMtrl The field indicates the estimated invoice price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine The field indicates the estimated invoice price amount.

@currencvID

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the material currency for sales price.

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualInvoicePriceAmount

For Work Order: For Work Order:

ACUINV.ITNEPR; COS170MI/Get The field indicates the actual invoice price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine The field indicates the actual invoice price amount.

@currencyID

SSLINE.SFPOSX.

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the material currency for sales price.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineNumber

For Work Order:

MMOOPE.QOOPNO + QOWOSQ; MOS100MI/GetOp The field indicates theoperation.

For Service Order: For Service Order:

SSLINE.SFJOBN The field indicates the labor group line number. SSLINE.SFJBSX SSLINE.SFPONR

May 26, 2023

For Work Order:

SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/CreationDateTime

For Work Order:

MMOOPE.QJRGDT + QJRGTM; MOS100MI/GetOp

The field indicates the entry date time.

For Service Order: SSLINE.SFRGDT SSLINE.SFRGTM. SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Status/Code

For Work Order

MMOOPE.QOWOST; MOS100MI/GetOp

For Service Order:

SSLINE.SFORST; SOS100MI/LstLine

For Work Order:

The field indicates the standard status on service labor group

Alternatives: 80=Closed 20=Open

30, 34, 35, 36, 37, 38, 40, 50, 60, 70=Approved

10=Pending 89, 90=Completed

For Service Order:

The field indicates the line status (ORST).

Set to 'Open', if line status are 22, 23, 24, 25, 26, 32, 33, 34, 35, 36, 42, 43, 44, 45, 46, 52, 53, 54, 55, 56, 62, 63, 64, 65 or 66.

Set to 'Invoiced', if line status is 77

The field indicates the line status.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Status/ReasonCode

For Work Order:

MMOOPE.QOWOST; MOS100MI/GetOp

The field indicates the M3 status code on service labor group

For Service Order:

SSLINE.SFJBST; SOS100MI/LstLine

@name

For Work Order:

MMOOPE.QOWOST; MOS100MI/GetOp

For Work Order:

For Service Order:

The field indicates the M3 status on service labor group

Alternatives: 10=Preliminary 20=Definite

30=Order started/previous operation not started

34=Previous operation ready to begin 35=Preceding operation scheduled 36=Preceding operation started 37-Preceding operation partially reported 38=Preceding operation stopped

40=Ready to begin/preceding operation complete

50=Scheduled 60=Started 70-Partially reported 80=Stopped

89=Flagged as completed, work order not closed

90=Flagged as completed

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Note

For Service Order:

OSYTXL.TLTX60; SOS200MI/LstSOText

@use

For Service Order:

OSYTXL.TLTXEI; SOS200MI/LstSOText

@languagelD

For Service Order:

OSYTXL.TLLNCD; SOS200MI/LstSOText

For Service Order: The field indicates text. For Service Order:

The field indicates if the note is external or internal text.

For Service Order:

The field indicates the language used for the notes

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineCode

For Service Order:

SSLINE.SFITNO; SOS100MI/LstLine

@accountingEntity

For Service Order:

The field indicates the service labor line code.

For Service Order:

For Work Order:

order line

The field indicates the company and division

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Classification/Codes/Code

For Work Order:

MMOOPE.QMWOSQ **QMUMAS**

QMIORN

QMIORL; MOS100MI.GetOp.WOSQ

MOS100MI.GetOp.UMAS MOS100MI.GetOp2.IORL/

For Service Order:

SSLINE.SFSCOD; SOS100MI/LstLine

@sequence

The field indicates the reporting number, labor setup time, interface

For Service Order:

The field indicates the service expense category (SCOD). Set to 'Labor', if the service expense category is 0.

Set to 'Travel time', if the service expense category is 2.

For Work Order:

The field indicates the sequence number

For Service Order:

The field indicates the service labor group sequence.

For Work Order:

The field indicates a fixed value 'Reporting Number'
The field indicates a fixed value 'Labor Setup Time'
The field indicates a fixed value 'Interface Order Line'

For Service Order:

Set to 'Service Expense Category'.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/DocumentReference

@type

@listID

For Service Order:

The field indicates the reference order number (RORN). Set to 'ProductionOrder', if reference order number is 1. Set to 'PurchaseOrder', if reference order number is 2. Set to 'SalesOrder', if reference order number is 3. Set to 'RequisitionOrder', if reference order number is 4. Set to 'DistributionOrder', if reference order number is 5. Set to 'WorkOrder', if reference order number is 6. Set to 'ServiceOrder', if reference order number is 7. Set to 'ProjectOrder', if reference order number is 8.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/DocumentReference/DocumentID/ID

For Service Order:

For Service Order:

SSLINE.SFRORL; SOS100MI/LstLine The field indicates the reference order number.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO_DIVI

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/DocumentReference/LineNumberFor Service Order:
For Service Order:

SSLINE.SFRORL; SOS100MI/LstLine The field indicates the document reference order line number.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/DocumentReference/Facility/IDs/ID

For Service Order: For Service Order:

SSHEAD.SDFACI; SOS100MI/GetHead The field indicates the facility ID.

@accountingEntity

For Service Order:

The field indicates the warehouse

Service Order/Service Order Line/Service Labor Group/Document Reference/Facility/Name

For Service Order: For Service Order:

CFACIL.CFFACN; CRS008MI/Get The field indicates the facility name.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/DocumentReference/SubLineNumber
For Service Order:
For Service Order:

SSLine.SFRORX; SOS100MI/LstLine

The field indicates the reference sub-line number.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/InvoiceDateTime

For Service Order: For Service Order:

SSLINE.SFLIDT; SOS100MI/LstLine

The field indicates the invoice date and time.

Service Order/Service Order Line/Service Labor Group/Estimated Time Duration

For Work Order: For Work Order:

MMOOPE.QOPITI; MOS100MI/GetOp The field indicates the estimated time.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualTimeDuration

For Work Order: For Work Order:

MMOOPE.QOUMAT; MOS100MI/GetOp The field indicates the actual setup time

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedCostPriceAmount

For Work Order: For Work Order:

MMOOPE.QOESBU; MOS100MI/GetOp The field indicates the estimated cost price amount

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100MI/LstLine The field indicates the estimated cost price amount.

@currencyID

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for estimated cost.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedSalesPriceAmount

For Work Order: For Work Order:

MMOOPE.QONEPR; MOS100MI/GetOp

The field indicates the estimated sales price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine

The field indicates the estimated sales price amount.

@currencyID

For Work Order: For Work Order:

CMNDIV.CCLOCD: MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for estimated sales price

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualCostPriceAmount

For Work Order: For Work Order:

MMOOPE.QOESBU; MOS100MI/GetOp The field indicates the actual cost price amount

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100MI/LstLine The field indicates the actual cost price amount.

@currencyID

For Work Order: For Work Order:

The field indicates the currency CMNDIV.CCLOCD; MNS100MI/GetBasicData

For Service Order: For Service Order:

The field indicates the currency for cost price amount. SSHEAD.SDCUCD; SOS100MI/GetHead

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualSalesPriceAmount

For Work Order: For Work Order:

ACUINV.ITASP1; COS170MI/Get The field indicates the actual sales price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine The field indicates the actual sales price amount.

@currencyID For Work Order:

For Work Order: CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for sales price amount.

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/EstimatedLaborRate

For Work Order: For Work Order:

MMOOPE.QOALP1; MOS100MI/GetOp The field indicates the estimated labor rate

@currencyID

For Work Order: For Work Order

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualLaborRate

For Work Order: For Work Order:

ACUINV.ITNEPR/ITTRQT; COS170MI/Get The field indicates the actual labor rate

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100MI/LstLine The field indicates the actual labor rate.

@currencyID

For Work Order: For Work Order:

CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for actual labor rate.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/LineNumber

For Work Order: For Work Order:

ACUMIS.IMMSEQ; COS150MI/LstMisc The field indicates the key to the operation element line

For Service Order: For Service Order: SSLINE.SFJOBN The field indicates the key to the operation element. SSLINE.SFJBSX

SSLINE.SFPONR SSLINE.SFPOSX.

; SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/CreationDateTime

For Work Order: For Work Order:

ACUMIS.QQRGDT + IMRGTM; COS150MI/LstMisc The field indicates the registration date and time

For Service Order: For Service Order:

SSJOBH SERGDT The field indicates the registration date and time.

SSJOBH.SERGTM.; SOS100MI/LstLine

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Status/Code

For Work Order: For Work Order:

The field indicates the status the Misc cost line ACUMIS.IMWMST; COS150MI/LstMisc

Alternatives:

For Service Order: 20, 25, 30, 60, 70, 80=Open

SSJOBH.SEORST; SOS100MI/LstLine 94=Canceled

> For Service Order: The field indicates the line status (ORST).

Set to 'Open', if line status are 22, 23, 24, 25, 26, 32, 33, 34, 35, 36,

ServiceOrder 42, 43, 44, 45, 46, 52, 53, 54, 55, 56, 62, 63, 64, 65 or 66. Set to 'Invoiced', if line status is 77 ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Status/ReasonCode For Work Order: For Work Order: ACUMIS.IMWMST; COS150MI/LstMisc The field indicates the M3 status code on Miscellaneous cost line For Service Order: For Service Order: SSJOBH.SEJBST; SOS100MI/LstLine The field indicates the line status. @name For Work Order: For Work Order: ACUMIS.IMWMST; COS150MI/LstMisc The field indicates the M3 status on Miscellaneous cost liine 10=Preliminary 20=Item is discontinued and replacement is conditional 14=Item is discontinued at this warehouse 20=Definite 25=Approved Misc Cost Line 30=Material issue without picking list (kanban) 60=Requisition created but not allocated 70=Requisition created and allocated 80=Requisition created and picking list printed 90=Material issue reported and flagged as completed 94=Material line status flagged as deleted ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Note For Work Order: For Work Order: ACUMIS.IMREMK; COS150MI/Get The field indicates the remarks For Service Order: For Service Order: OSYTXL.TLTX60; SOS200MI/LstSOText The field indicates additional notes. @use For Service Order: For Service Order: OSYTXL.TLTXEI; SOS200MI/LstSOText The field indicates if the note is external or internal text. @languagelD For Service Order: For Service Order: OSYTXL.TLLNCD; SOS200MI/LstSOText The field indicates the language used for the notes. ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Description For Work Order: For Work Order: ACUMIS.IMTX40; COS150MI/LstMisc The field indicates the description ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Item/ItemID/ID For Work Order: For Work Order: .; COS150MI/LstMisc The field indicates the item ID For Service Order: For Service Order: SSLINE.SFITNO; SOS100MI/LstLine The field indicates the service other group item. @accountingEntity For Work Order: For Work Order: ACUMIS.IMCONO+IMDIVI; / The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is For Service Order: displayed as Company (CONO). Otherwise, this is displayed as SSHEAD.CONO Company and Division (CONO DIVI). SSHEAD.DIVI.; /

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Item/Description

For Service Order:

SSLINE.SFITDS; MMS200MI/GetItmBasic

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Classification/Codes/Code For Work Order:

For Service Order:

For Service Order:

CONO DIVI.

The field indicates the Registration number

The field indicates the interface order line

IMMAUP; COS150MI/Get For Service Order:

For Work Order:

ACUMIS.IMTAIL

@sequence

SSLINE.SFSCOD; SOS100MI/LstLine

For Service Order:

The field indicates the service expense category (SCOD). Set to 'Service kit', if the service expense category is 1. Set to 'Tool', if the service expense category is 3.

The field indicates the company and division, displayed as

The field indicates service other group item description.

The field indicates if the sales price is manually updated

Set to 'Travel expenses compensation', if the service expense

category is 4.

Set to 'Per diem', if the service expense category is 5. Set to 'Subcontract', if the service expense category is 6. Set to 'Paid amount', if the service expense category is 7.

For Work Order:

The field indicates the sequence number starting with 1.

For Service Order:

The field indicates the classification sequence.

@lic#D

For Work Order:

The field indicates the ListId 'Registration Number'
The field indicates the ListID 'Manual Update'
The field indicates the 'interface order line'

For Service Order:

Set to 'Service Expense Category'.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference

@type

For Service Order:

The field indicates the reference order number (RORN). Set to 'ProductionOrder', if reference order number is 1. Set to 'PurchaseOrder', if reference order number is 2. Set to 'SalesOrder', if reference order number is 3. Set to 'RequisitionOrder', if reference order number is 4. Set to 'DistributionOrder', if reference order number is 5. Set to 'WorkOrder', if reference order number is 6. Set to 'ServiceOrder', if reference order number is 7. Set to 'ProjectOrder', if reference order number is 8.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference/DocumentID/ID

For Service Order: For Service Order:

SSLINE.SFRORN; SOS100MI/LstLine The field indicates the reference order number.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO_DIVI

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference/LineNumber
For Service Order:
For Service Order:

SSLINE.SFRORL; SOS100MI/LstLine The field indicates the document reference order line number.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference/Facility/IDs/ID

For Service Order: For Service Order: SSHEAD.SDFACI; SOS100MI/GetHead The field indicates the facility ID.

@accountingEntity

For Service Order: For Service Order:

SSHEAD.CONO The field indicates the company and division, displayed as

SSHEAD.DIVI.; / CONO DIVI.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference/Facility/Name

For Service Order: For Service Order: CFACIL.CFFACN; CRS008MI/Get The field indicates the facility name.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/DocumentReference/SubLineNumber

For Service Order: For Service Order:

SSLine.SFRORX; SOS100MI/LstLine The field indicates the document reference order sub-line number.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/PersonReference/IDs/ID

For Work Order: For Work Order:

ACUMIS.IMUSID; COS150MI/LstMisc The field indicates the user ID

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedCostPriceAmount

For Work Order: For Work Order:

ACUMIS.IMADC3; COS150MI/LstMisc The field indicates the estimated cost price amount

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100MI/LstLine The field indicates the estimated cost price amount.

@currencyID

For Work Order: For Work Order:

ACUMIS.IMLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for estimated cost amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedSalesPriceAmount

For Work Order: For Work Order:

ACUMIS.IMSAPR; COS150MI/LstMisc The field indicates the estimated/actual sales price amount for the

misc cost depending on status of the line For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine For Service Order:

The field indicates the estimated sales price amount.

@currencyID For Work Orde

For Work Order: For Work Order

MITMAS.MMLOCD; MNS100MI/GetBasicData

The field indicates the estimated/actual sales price amount for the

misc cost depending on status of the line

For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead For Service Order:

The field indicates the estimated sales price amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedInvoicePriceAmount

For Work Order: For Work Order:

ACUMIS.IMASP1; COS150MI/LstMisc The field indicates the estimated invoice price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine The field indicates the estimated invoice price amount.

@currencyID

For Work Order:

MITMAS.MMLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for estimated invoice price amount.

For Work Order:

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualCostPriceAmount

For Work Order: For Work Order:

ACUINV.ITAWCO; COS170MI/Get

The field indicates the actual cost price amount

For Service Order: For Service Order:

SSLINE.SFUCOS; SOS100MI/LstLine

The field indicates the actual cost price amount.

@currencyID

For Work Order: For Work Order:

MITMAS.MMLOCD: MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for actual cost price amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualSalesPriceAmount

For Work Order: For Work Order:

ACUINV.ITNEPR; COS170MI/Get

The field indicates the actual sales price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine

The field indicates the actual sales price amount.

@currencyID

For Work Order: For Work Order:

MITMAS.MMLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency for the actual sales price amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualSalesPriceBaseAmount

For Service Order: For Service Order:

SSLINE.SFSACD; SOS100MI/LstLine The field indicates the actual sales price base amount.

@currencyID

For Service Order: For Service Order:

SSHEAD.SDCUCD; SOS100MI/GetHead The field indicates the currency actual sales price base amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualInvoicePriceAmount

For Work Order: For Work Order:

ACUINV.ITNEPR; COS170MI/Get

The field indicates the actual invoice price amount

For Service Order: For Service Order:

SSLINE.SFSAPR; SOS100MI/LstLine

The field indicates the the actual invoice price amount.

@currencyID

For Work Order: For Work Order:

MITMAS.MMLOCD; MNS100MI/GetBasicData

The field indicates the currency

For Service Order: For Service Order:

SSHEAD.SDCUCD; SSHEAD/GetHead The field indicates the currency for the actual invoice price amount.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedQuantity

For Work Order: For Work Order:

ACUMIS.IMCNQT; COS150MI/LstMisc The field indicates the estimated quantity

For Service Order: For Service Order:

SSLINE.SFTIQT; SOS100MI/LstLine The field indicates the estimated quantity.

@unitCode

For Work Order: For Work Order:

ACUMIS.IMUNIT; COS150MI/LstMisc The field indicates the unit of measure

For Service Order: For Service Order:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the estimated quantity unit of measure.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualQuantity

For Work Order: For Work Order:

ACUMIS.IMCNQT; COS150MI/LstMisc The field indicates the estimated quantity

For Service Order: For Service Order:

SSLINE.SFIVQT; SOS100MI/LstLine The field indicates the actual quantity in basic unit of measure.

@unitCode

For Work Order: For Work Order:

ACUMIS.IMUNIT; COS150MI/LstMisc The field indicates the unit of measure

For Service Order: For Service Order:

MITMAS.MMUNMS; MMS200MI/GetItmBasic The field indicates the basic unit of measure.

ServiceOrder/ServiceOrderLine/PriorityCode

For Service Order: For Service Order:

SSJOBH.SEOPRI; SOS500MI/LstAssignmPerSO

The field indicates the priority code.

ServiceOrder/ServiceOrderLine/ActualProblemCode	
For Service Order:	For Service Order:
SSJOBH.SEERCO: SOS500MI/LstAssignmPerSO	The field indicates the actual problem code.

ServiceOrder/ServiceOrderLine/ActualSolutionCode For Service Order: SSJOBH.SEMECO; SOS500MI/LstAssignmPerSO

For Service Order: The field indicates the actual solution code.

ShipFromPartyMaster

Ship From Party Waster	
ShipFromPartyMaster/PartyIDs/ID CIDMAS.IDSUNO.; CRS620MI/GetBasicData @accountingEntity	The field indicates the supplier code.
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
ShipFromPartyMaster/PartyIDs/TaxID CIDMAS.IDVRNO; CRS620MI/GetBasicData	The field indicates the tax registration number of the company, supplier's organization number or VAT registration number.
ShipFromPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC ; CRS620MI/GetBasicData	The field indicates Standard Carrier Alpha Code (SCAC).
ShipFromPartyMaster/LastModificationDateTime	
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipFromPartyMaster/LastModificationPerson/IDs/ID CIDMAS.IDCHID; / @accountingEntity	The field indicates the ID of the person who last modified the record.
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipFromPartyMaster/Name CIDMAS.IDSUNM : CRS620MI/GetBasicData	The field indicates supplier name.
ShipFromPartyMaster/Location/Address @type	
шур е	Set to 'text'.
ShipFromPartyMaster/Location/Address/AddressLine CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4.; CRS620MI/LstAddresses @sequence	The field indicates an address line.
шовециенсе	The field indicates the address line sequence.
ShipFromPartyMaster/Location/Address/CityName CIDADR.SATOWN ; CRS620MI/LstAddresses	The field indicates the city name.
ShipFromPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR ; CRS620MI/LstAddresses @listID	The field indicates an area, province or state within a country.
@13.12	Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departments' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
ShipFromPartyMaster/Location/Address/CountryCode CIDADR.SACSCD; CRS620MI/LstAddresses @listID	The field indicates the country code.
wiisub	Set to 'Countries'.
ShipFromPartyMaster/Location/Address/PostalCode CIDADR.SAPONO ; CRS620MI/LstAddresses	The field indicates a postal code for a specific address.
ShipFromPartyMaster/Contact/ID CIDREF.IRRFTY CIDREF.IRRFID.; CRS620MI/LstSupplierRef	The field indicates the ID of the contact. It is a concatenation of Reference Type (RFTY) <2> and Reference (RFID) <10> with dash '-' as separator. The position of each field is determined by its maximum length, specified in brackets. RFID is trimmed if it does not consume the maximum field length.
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipFromPartyMaster/Contact/Name CIDREF.IRYRE1	The field indicates the name of the contact.
Infor May 26, 20	

ShipFromPartyMaster

ShipFromPartyMaster/Contact/Communication	
@preferredIndicator	
g r	Set to 'false'.
ShipFromPartyMaster/Contact/Communication/ChannelCode	
	Set to "Phone" if telephone number 1 or facsimile number. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
ShipFromPartyMaster/Contact/Communication/UseCode	
	Set to "Office" if telephone number 1, telephone number 2 or e-mail address. Set to "Fax" if facsimile number.
@listID	
	Set to 'Communication Use Codes'.
ShipFromPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO CIDREF.IRTFNO.; CRS620MI/LstSupplierRef	The field indicates the phone number (PHNO). The field indicates the facsimile number (TFNO).
ShipFromPartyMaster/Contact/Communication/URI CIDREF.IREMAL ; CRS620MI/LstSupplierRef	The field indicates the e-mail address.
ShipFromPartyMaster/Contact/Communication/Preference/Indicate	or Set to 'false'.
Shin From Portul Montor / Pruser Contont / ID	Set to Taise.
ShipFromPartyMaster/BuyerContact/ID CIDVEN.IIBUYE ; CRS620MI/GetBasicData @accountingEntity	The field indicates the buyer ID.
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ShipFromPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipFromPartyMaster/BuyerContact/Name CMNUSR.JUTX40 ; MNS150MI/GetUserData	The field indicates the name of the buyer.
ShipFromPartyMaster/UserArea CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status. Set attribute name to 'M3Status'. If STAT=05, set NameValue to 05 - Supplier template. If STAT=10, set NameValue to 10 - Preliminary. If STAT=20, set NameValue to 20 - Approved. If STAT=30, set NameValue to 30 - Stopped. If STAT=90, set NameValue to 90 - Deactivated.
ShipFromPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the supplier status.
	Set to 'Pending' if is status is 10. Set to 'Open' if status is 20. Set to 'Hold' if status is 30. Set to 'Deleted' if status is 90 or if record is deleted in CRS620. Set to 'Closed' if status is 05.
ShipFromPartyMaster/SupplierParty/PartyIDs/ID CIDMAS.IDSUNO.; /	The field indicates the supplier code. The value is retrieved from event data.
@accountingEntity	
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

SniproPartywaster	
ShipToPartyMaster/PartyIDs/ID	
ÓCUSMÁ.OKCUNO CRS610MI/GetBasicData	The field indicates the Customer number when triggered from OCUSMA (Customer) table. When triggered from OCUSAD
OCUSAD.OPCUNO+OCUSAD.OPADID CRS610MI/GetAddress.; /	(Customer Address) table, it is a concatenation of Customer number (CUNO) <10> + Address number (ADID) <6>. The position of each field is determined by its maximum length, specified in brackets. If CUNO does not consume the maximum length, the rest is filled up with spaces. ADID is trimmed if it is less than 6 characters.
@accountingEntity OCUSMA.OKCONO OCUSMA.OKDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
@variationID	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
ShipToPartyMaster/PartyIDs/DisplayID	
OCUSMA.OKCUNO CRS610MI/GetBasicData	The field indicates the Customer number when triggered from OCUSMA (Customer) table. When triggered from OCUSAD
OCUSAD.OPCUNO+OCUSAD.OPADID CRS610MI/GetAddress.; /	(Customer Address) table, it is a concatenation of Customer number (CUNO) <10> + Address number (ADID) <6>. The position of each field is determined by its maximum length, specified in brackets. If CUNO does not consume the maximum length, the rest is filled up with spaces. ADID is trimmed if it is less than 6 characters.
ShipToPartyMaster/PartyIDs/TaxID XRUCUS.OKXKPP	The field indicates the TaxID exists for the customer.
XRUCUS.OKXKPO XRUCUS.OKXINN XRUCUS.OKXKDP.; CRRU02MI /GetCustomerRU	If Country Specific Version (CSVN) is 'RU', display the fields INN code (XINN), KPP code (XKPP), OKPO code (XKPO), OKPD2 code (XKDP).
@schemeAgencyName	The field indicates the following schemeAgencyName.
	If Country Specific Version (CSVN) is 'RU', display the following:
	Set to 'RU_INN' if TaxID is XINN. Set to 'RU_KPP' if TaxID is XKPP. Set to 'RU_OKPO' if TaxID is XKPO. Set to 'RU_OKDP' if TaxID is XKDP.
ShipToPartyMaster/PartyIDs/BICID XRUBAN.BKXBIK; CRRU04MI/GetBankRU	The field indicates the bank account ID to which related bank account information is connected.
	If Country Specific Version (CSVN) is 'RU', display BIK code.
ShipToPartyMaster/LastModificationDateTime OCUSMA.OKLMTS; /	The field indicates the date and time the record was last modified.
ShipToPartyMaster/LastModificationPerson/IDs/ID OCUSMA.OKCHID; /	The field indicates the ID of the person who last modified the record.
@accountingEntity OCUSMA.OKCONO OCUSMA.OKDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipToPartyMaster/Name OCUSMA.OKCUNM CRS610MI/GetBasicData	The field indicates the customer name.
OCUSAD.OPCUNM CRS610MI/GetAddress	If Country Specific Version (CSVN) is 'RU', display Full name RU (XFLN) field.
XRUCUS.OKXFLN CRRU02MI/GetCustomerRU.; /	
ShipToPartyMaster/Location/Address @type	Set to 'text'.
ShipToPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF CRS610MI/GetBasicData	The field indicates the customer's contact person.
OCUSAD.OPYREF	

Ship To Party Masterit Coation / Address / Address / Ine CCLISMA OKCLA' CCLISMA OKTOWN CR86 IMMicella basic Data CCLISMA OKCLA' CR86 IMMicella basic Data CCLISMA OKCLA'	CRS610MI/GetAddress.: /	
COLUSIA OKCUNA COLUSIAN OKCUNA CRESTOMICERIA Sector of the field indicates the address line sequence. The field indicates the city name. COLUSIAN OKTOWN CRESTOMICERIA Sector of the columny okcuna COLUSIAN OKTOWN CRESTOMICERIA Sector of the columny okcuna COLUSIAN OKTOWN CRESTOMICERIA Sector of the columny okcuna COLUSIAN OKCUNA CRESTOMICERIA Sector OKCUNA CRESTOMICERIA SECTOR OKCUNA CRESTOMICERIA SECTOR OKCUNA CRESTOMICERIA SECTOR OKCUNA CRESTOMICERIA COLUSIAN OKCUNA CRESTO	,	
COUSIA OKCUAS OCUSIAN CICCUAS OCUSIAN CICCUAS OCUSIAN OKCUAS OCUSIAN OF CUAS OCUSIAN OF CUAS OCUSIAN OF CUAS OCUSIAN OKCUAS OCUSIAN OF CUAS OCUSIAN OKCUAS O		The field indicates the address line.
CCUSAD OPCUAS OCUSAD OPCUAS Set to "Canadian Provinces" if the country is CA (Canada), Set to "Tenoce - Departments" if the country is CF (Created), Set to "SubDivisions" - Country Codes" for other countries. Set to "SubDivisions" - Country Codes" for other countries. Set to "SubDivisions" if no Country is specified. Ship ToParryMaster/Location/Address/CountryCode OCUSAD OPCSCO CR86 (MMICelAddress.;) Ship ToParryMaster/Location/Address/PostalCode OCUSAD OPCSCO CR86 (MMICelAddress.) Ship ToParryMaster/Location/Address/PostalCode OCUSAD OPCSCO CR86 (MMICelAddress.) Ship ToParryMaster/Location/Address/Preference/Indicator Ship ToParryMaster/Communication/UseCode S		
CRS610MIGelBasicData OCUSAD OPCUAR OCUSAD OPCUAR OCUSAD OPCUAR OCUSAD OPCUAR CRS610MIGelAddress:/ Beaquence The field indicates the address line sequence. The field indicates the city name. CRS610MIGelBasicData OCUSAD OPTOWN CRS610MIGElBasicData OCUSAD OPCSCD CRS610MIGElBasicData OCUSAD OPCSCD CRS610MIGElBasicData OCUSAD OPCSCD CRS610MIGElBasicData OCUSAD OPTOWN CRS610MIGElBasicData The field indicates the postal code. Set to "Donne" if telephone number 1 or 2 or facsimile number. Set to "Emone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates the telephone 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates the telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates the telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates an e-mail address for the customer. The field indicates an e-mail address for the customer. The field indicates an e-mail address for the custom	OCUSMA.OKCUA3	
OCUSAD OPCUAT OCUSAD OC		
OCUSAD OPCUAS OCUSAD OPTOWN CRS610MICelfadsacidata OCUSAD OPTOWN CRS610MICelfadsacidata OCUSAD OPTOWN CRS610MICelfaddress;/ OCUSAD OPCOAR OCUS	CRS610MI/GetBasicData	
OCUSAD OPCIUAS OCUSAD	OCUSAD ODCUA1	
OCUSAD OPCUA ORS60MiGetAddress:// sequence The field indicates the address line sequence. The field indicates the city name. The field indicates the city name. The field indicates the city name. CCUSAD OPTOWN CRS610MiGetAddress:/ CRS610M		
CCUSAD OPCUA CRS610MIGHEAddress./ ### Field indicates the address line sequence. The field indicates the address line sequence. #### Field indicates the city name. CRS610MIGHEAddress./ CUSAD OPTOWN CRS610MIGHEAddress./ CRS610MIGHEAddress./ ##################################		
CRS610MICelAddress:/ Basquence The field indicates the address line sequence. The field indicates the city name. The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. Set to "Canadian Provinces" if the country is CA (Canada). Set to "France - Departments" if the country is CA (Canada). Set to "France - Departments" if the country is FR (France). Set to "US States if the country is FR (France). Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions - Country Code" for other countries. Set to "SubDivisions" if no Country is predied. The field indicates the country code. The field indicates the country code. The field indicates the country code. The field indicates the postal code. Set to "Country Code" of other countries. Set to "Tue". Set to "There" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "There" if telephone number 1, telephone number 2 or facsimile number. Set to "There" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates the telephone 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". The field indicates an e-mail address for the customer. Third ToParry Master/Communication/Use Codes. The field indicates an e-m		
The field indicates the address line sequence. The field indicates the address line sequence. The field indicates the address line sequence. The field indicates the city name. CUSMA ONTOWN CRS610MICGERSacioNat CUSMA CKECAR CRS610MICGERSacioNata CUSMA ONECAR CRS610MICGERSacioNata COUSMA ONECAR		
The field indicates the city name. OCUSAD OPTOWN CRS610MICGetBasicData OCUSAD OPTOWN CRS610MICGetAddress.*/ InitipToParryMaster/Location/Address/CountrySubDivisionCode OCUSAD OPTOWN CRS610MICGetBasicData OCUSAD OPTOWN CRS610MICGetAddress.*/ CRS610MICGetBasicData OCUSAD OPTOCAR CRS610MICGetAddress.*/ District of the country is CA (Canada). Set to 'France - Departments' if the country is CA (Canada). Set to 'Trance - Departments' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is CA (Canada). Set to 'US States' if the country is CA (Canada). Set to 'US States' if the country is FR (France). Set to 'US States' if the country is FR (France). Set to 'US States' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is US (United States). Set to 'US States' if the country is CA (Canada). Set to 'Us States' if the country is CA (Canada). Set to 'Us States' if the country is CA (Canada). Set to 'Us States' if the country is CA (Canada). Set to 'Us States' if the country is CA (Canada). Set to 'Us States' if the country is CA (Canada). Set to 'Us States' if the country is Called. Set to 'Us States' if the country is Called. Set to 'Us States' if the c		
CCUSAD OPTOWN CRS610MICGEBasicData OCUSAD.OPTOWN CRS610MICGEBasicData OCUSAD.OPTOWN CRS610MICGEBasicData OCUSAD.OPTOWN CRS610MICGEBasicData The field indicates the city name. The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. Set to "Canadian Provinces" if the country is CR (Canada). Set to "Canadian Provinces" if the country is CR (Canada). Set to "Canadian Provinces" if the country is CR (Canada). Set to "Canadian Provinces" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "States" if the country is CR (Canada). Set to "Canadian Provinces" if the country is CR (Canada). Set to "Country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the country is CR (Canada). Set to "The set indicates the coun		The field indicates the address line sequence.
CRS610Mi/GetBasicData OCUSAD OPTOWN CRS610Mi/GetAddress.; / **ThirpToPartyMaster/Location/Address/CountrySubDivisionCode** OCUSAD OPECAR CRS610Mi/GetBasicData OCUSAD OPECAR CRS610Mi/GetAddress.; / **BirstD** Set to 'Canadian Province' if the country is CA (Canada). Set to 'France - Departments' if the country is FR (France). Set to 'Us States' if the country is Us (United States). Set to 'SubDivisions - Country Code 'Country Code' OCUSAD OPECAR CRS610Mi/GetBasicData OCUSAD OPECAR CRS610Mi/GetBasicData OCUSAD OPECAR CRS610Mi/GetBasicData OCUSAD OPECAR CRS610Mi/GetBasicData OCUSAD OPTOWN CRS610Mi/GetBasicData OCUSAD OPPONOx CRS610Mi/GetBasicData Set to 'Talea' S		
CUSAD OPTOWN CR8610M/CeRAddress; / / ImpToPartyMaster/Location/Address/CountrySubDivisionCode CUSAD OPECAR CR8610M/CeRBasicData OCUSAD OPECAD CR8610M/CeRBasicData OCUSAD OPETAD COUSAD OPETAD COUSAD OPETAD CR8610M/CeRBasicData OCUSAD OPETAD COUSAD OPETAD CR8610M/CeRBasicData OCUSAD OPETAD COUSAD OPETAD CR8610M/CeRBasicData The field indicates an area, province or state within a country. The field indicates an area, province or state within a country. The field indicates an area, province of the country. The field indicates an area, province of the country of ACCANAD The field indicates an area, province of the country of ACCANAD The field indicates an area, province of the country of ACCANAD The field indicates an area, province of the country of Canada The field indicates an area, province of the country is CA Canada The field indicates an area, province of the country		The field indicates the city name.
CRS610MI/GetAddress; / ImpropertyMaster/Location/Address/CountrySubDivisionCode OCUSMA OKECAR CRS610MI/GetBasicData OCUSAD OPECAR CRS610MI/GetAddress; / IgistD Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'Canadian Provinces' if the country is FR (France). Set to 'SubDivisions' if no Country is specified. OCUSAD OPOSCD CRS610MI/GetBasicData OCUSAD OPOSCD CRS610MI/GetBasicData OCUSAD OPONOX CRS610MI/GetBasicData OCUSAD OPONOX CRS610MI/GetBasicData OCUSAD OPOSCD Set to 'Tales' Set to 'Canadian Provinces' if the country is facility. The field indicates the telephone number 1, telephone number 2 or facsimile number. Set to 'Canadian Provinces' Interface Tales and Set to 'Tales' Set to 'Canadian Unitales' Set to 'Canadian Unit	CRS610MI/GetBasicData	
CRS610M/GetAddress; / ImproPartyMaster/Location/Address/CountrySubDivisionCode CCUSAD.OPECAR CRS610M/GetAddress; / ImproPartyMaster/Location/Address/CountrySubDivisionCode CCUSAD.OPECAR CRS610M/GetAddress; / ImproPartyMaster/Location/Address/CountryCode CCUSAD.OPECAR CRS610M/GetAddress; / ImproPartyMaster/Location/Address/CountryCode CCUSAD.OPECAR CRS610M/GetBasicData CCUSAD.OPECAR CCUSAD.OP	OCUSAD OPTOWN	
CCUSMA OKECAR CRS610MI/GetAddress.; / WistID CUSAD OPECAR CRS610MI/GetAddress.; / WistID Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departments' if the country is FR (France). Set to US States' if the country is PR (France). Set to US States' if the country is US (United States). Set to 'SubDivisions' if no Country is specified. CRS610MI/GetAddress./ WistID CRS610MI/GetAddress./ WistID Set to 'Countries'. The field indicates the country code. CRS610MI/GetAddress./ WistID Set to 'Countries'. The field indicates the postal code. CCUSAD OPCOC CRS610MI/GetAddress./ WistID Set to 'Tourities'. The field indicates the postal code. CCUSAD OPCOC CRS610MI/GetAddress./ Set to 'Itue'.		
CCUSMA OKECAR CRS610Mi/GetAddress.; / ZillistiD Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'Fance - Departments' if the country is PR (France). Set to US States' if the country is PR (France). Set to SubDivisions - Country Code of the country is Specified. CRS610Mi/GetAddress.; / ZillistiD Set to 'Canadian Provinces' if the country is Us (United States). Set to 'SubDivisions' if no Country is specified. The field indicates the country code. CRS610Mi/GetAddress.; / ZillistiD Set to 'Countries'. The field indicates the postal code. CCUSMA OKPONO CRS610Mi/GetAddress.; / ZillistiD Set to 'Ture'. Set to 'Itrue'. Set to 'Phone' if telephone number 1 or 2 or facsimile number. Set to 'Itrue'. Set to 'Tehnail' if e-mail address. Set to 'Tehnail' if e-mail address. Set to 'Communication Channels'. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. CUSMA OKFPINO CU	·	
CRS610MIGetBasicData OCUSAD.OPECAR CRS610MIGetAddress.; / 20/stiD Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departments' if the country is TR (France). Set to 'Us States' if the country is TR (France). Set to 'Us States' if the country is CH (Canada). Set to 'SubDivisions - «Country Code" for other countries. Set to 'SubDivisions' if no Country is specified. The field indicates the country code. CCUSMA OKCSCD CRS610MIGetBasicData OCUSAD.OPCSCD CRS610MIGetBasicData OCUSAD.OPCSCD CRS610MIGetBasicData OCUSAD.OPPONO CRS610MIGetBasicData OCUSAD.OPPONO CRS610MIGetBasicData OCUSAD.OPPONO CRS610MIGetBasicData OCUSAD.OPPONO Set to 'Countries'. Set to 'Tute'. Set to 'Thone' if telephone number 1 or 2 or facsimile number. Set to 'EMail' if e-mail address. Set to 'Email' if e-mail address. Set to 'Communication Channels'. Set to 'Communication Channels'. Set to 'Communication Channels'. Set to 'Communication Channels'. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. COUSMA OKPHNO OCUSMA OKPH		The field indicates an area, province or state within a country
Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departments' if the country is FR (France). Set to 'Subbivisions' if the country is FR (France). Set to 'Subbivisions' if the country is FR (France). Set to 'Subbivisions' if no Country is SR (I/France). Set to 'Subbivisions' if no Country is SR (I/France). Set to 'Subbivisions' if no Country is SR (I/France). Set to 'Subbivisions' if no Country is SR (I/France). Set to 'Subbivisions' if no Country is specified. CCUSMA OKCSCD CRS8 10MI/GetBasicData CCUSAD OPCSCD CRS8 10MI/GetAddress.; / Build D Set to 'Countries'. Set to 'Countries'. Set to 'Countries'. Set to 'Countries'. Set to 'Interior Interior Interio		,,
Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departments' if the country is FR (France). Set to 'Subbivisions' if the country is FR (France). Set to 'Subbivisions' if the country is FR (France). Set to 'Subbivisions' - Country Country. Set to 'Subbivisions' if no Country is Set (United States). Set to 'Subbivisions' if no Country is specified. CUSMA OKCSCD CRS610MI/GetBasicData CUSAD OPCSCD CRS610MI/GetBasicData CUSAD OPCSCD CRS610MI/GetBasicData COUSMA OKPONO CRS610MI/GetBasicData COUSMA OKPONO CRS610MI/GetBasicData COUSMA OKPONO CRS610MI/GetBasicData COUSMA OKPONO CRS610MI/GetBasicData Set to 'Inue'. ShipToPartyMaster/Communication/ChannelCode Set to 'Inue'. ShipToPartyMaster/Communication/ChannelCode Set to 'Thone' if telephone number 1 or 2 or facsimile number. Set to 'Edmail' if e-mail address. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. CRS610MI/GetBasicData CUSAD OPTENO CRS610MI/GetBasicData CRS610MI/GetBasicData The field indicates an e-mail address for the customer. The field indicates an e-mail address for the customer.		
Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'Farance - Department' if the country is CA (Canada). Set to 'Wasteri' if the country is CA (Canada). Set to 'Wasteri' if the country is FR (France). Set to 'Wasteri' if the country is FR (France). Set to 'Wasteri' if the country is perified. Ship ToPartyMasteri' Location/Address/CountryCode OCUSMAD OPCSCD CRS610MI/GetBasicData OCUSAD OPCSCD CRS610MI/GetBasicData OCUSAD OPCSCD CRS610MI/GetBasicData OCUSAD OPCSCD CRS610MI/GetBasicData OCUSAD OPPONOX Set to 'Thone' if telephone number 1 or 2 or facsimile number. Set to 'EMail' if e-mail address. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. Set to 'Phone' if telephone 1, telephone number 2 or facsimile number. CUSMAD OKPHNO OCUSMA OKPHNO		
Set to 'Canadian Provinces' if the country is CA (Canada). Set to France Departments' if the country is CA (Canada). Set to France Departments' if the country is US (United States). Set to 'SubDivisions' if no Country is US (United States). Set to 'SubDivisions' if no Country is specified. The field indicates the country code. CRS610MIGetBasicData OCUSAD.OPCSD CRS610MIGetAddress; / SightToPartyMaster/Location/Address/Postal/Code OCUSAD.OPCNO CRS610MIGetBasicData OCUSAD.OPPONO CRS610MIGetBasicData OCUSAD.OPPONO CRS610MIGetBasicData OCUSAD.OPPONO Set to 'True'. Set to 'Itale'. Set to 'Phone' if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to 'Phone' if telephone number 2 or facsimile number. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. The field indicates an e-mail address for the customer.	_	
Set to 'L'S states' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - Country Code' for other countries. Set to "SubDivisions - Country Code' for other countries. Set to "SubDivisions" if no Country is specified. The field indicates the country code. CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetAddress.; / 20/sttD Set to 'Countries'. Set to 'Countries'. The field indicates the postal code. CCUSAD OPCSCD CRS610MI/GetBasicData CCUSAD.OPPONOx CRS610MI/GetBasicData CCUSAD.OPPONOx CRS610MI/GetBasicData CCUSAD.OPPONOx CRS610MI/GetAddress.; / ShipToPartyMaster/Communication DepreferredIndicator Set to 'true'. Set to 'True'	ໝູເຮັບ	Cot to (Concedion Drayings) if the assume in OA (Od-)
Set to "US States" if the country is US (United States). Set to "SubDivisions - < Country Code" for other countries. Set to "SubDivisions - Variety Country Code" for other countries. Set to "SubDivisions" if no Country is specified. The field indicates the country code. CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetBasicData CS610MI/GetBasicData CCUSAD OPPINO CCUSAD OPPINO CCUSAD OPPINO CCUSAD OPPINO CCUSAD OPPINO CCUSAD COPTINO CCU		
Set to "SubDivisions - Country Codes' for other countries. Set to "SubDivisions" if no Country is specified. The field indicates the country code. CUSAD.OPCSCD CRS610MI/GetBasicData OCUSAD.OPCSCD CRS610MI/GetBasicData OCUSAD.OPCSCD CRS610MI/GetBasicData OCUSAD.OPCSCD CRS610MI/GetBasicData OCUSAD.OPCONO CRS610MI/GetBasicData OCUSAD.OPPONO CRS610MI/GetBasicData OCUSAD.OPPONO CRS610MI/GetBasicData OCUSAD.OPPONO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/ChannelCode Set to "tue". Set to "tue". Set to "false". Set to "The field indicates the postal code. CSUSAD.OPPONO CRS610MI/GetBasicData Set to "false". Set to "false". Set to "false". Set to "Email" if e-mail address. Set to "Email" if e-mail address. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Channels". Set to "Communication Use Codes'. ShipToPartyMaster/Communication/UseCode ShipToPartyMaster/Communication/UseCode CUSMA.OKPHNO		Set to 'US States' if the country is US (United States)
Set to "SubDivisions" if no Country is specified. Set to "SubDivisions" if no Country is specified. The field indicates the country code. CCUSMA OKCSCD CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetBasicData Set to 'Countries'. Set to 'Countries'. The field indicates the postal code. CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetBasicData Set to 'True'. Set to 'True'		Set to 'SubDivisions - < Country Code>' for other countries
Set to 'Countries': The field indicates the country code.		Set to "SubDivisions" if no Country is specified.
CCUSMA OKCSCD CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetAddress.; / ###################################	hinToPartyMaster/Location/Address/CountryCode	Section Substitution in the Section 1, 10 separation.
CRS610MI/GetBasicData CCUSAD OPCSCD CRS610MI/GetAddress.; / Set to 'Countries'. Set to 'Countries'. The field indicates the postal code. CCUSMA OKPONO CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetAddress.; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to 'true'. Set to 'true'. Set to 'true'. Set to 'false'. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. CCUSMA OKPHNO CCUSMA O		The field indicates the country code
CCUSAD OPCSCD CRS610MI/GetAddress.; / 2//stifD Set to 'Countries'. Set to 'Countries'. The field indicates the postal code. CUSAD OPPONOX CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetBasicData CCUSAD OPPONOX CRS610MI/GetAddress.; / Set to 'true'. Set to 'true'. Set to 'true'. Set to 'true'. Set to 'Talse'. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Communication Channels'. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. CUSMA OKPHNO CUS		The held indicates the country code.
CRS610MI/GetAddress.; / ### Set to 'Countries'. Set to 'Countries'. Set to 'Countries'. The field indicates the postal code. CUSAD.OPPONOX CRS610MI/GetBasicData OCUSAD.OPPONOX CRS610MI/GetAddress.; / ### ShipToPartyMaster/Communication ### Set to 'Irue'. ### ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. ### Set to 'Communication Channels'. ### Set to 'Phone" if telephone number 1, telephone number 2 or facsimile number. ### Set to 'Phone" if telephone number 1, telephone number 2 or facsimile number. ### Set to 'Phone" if telephone number 1, telephone number 2 or facsimile number. ### Set to 'Phone" if telephone number 1, telephone number 2 or facsimile number. ### Set to 'Communication Use Codes'. ### Set to 'Com	CI (CO TOWN) COLEGO Data	
Set to 'Countries'. ShipToPartyMaster/Location/Address/PostalCode CCUSMA.OKPONO CRS610MI/GetBasicData OCUSMA.OPPONOX CRS610MI/GetAddress.; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to 'true'. ShipToPartyMaster/Communication DepreferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Channels'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKPHNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPPTFNO CRS610MI/GetAddress; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	OCUSAD.OPCSCD	
Set to 'Countries'. ShipToPartyMaster/Location/Address/PostalCode CCUSMA.OKPONO CRS610MI/GetBasicData CCUSAD.OPPONOX CRS610MI/GetAddress.; / ShipToPartyMaster/Location/Address/Preference/Indicator ShipToPartyMaster/Communication Distrib ShipToPartyMaster/Communication/ChannelCode Set to 'Thone' if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. ShipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber CCUSMA.OKPHNO CCUSMA.OKPHNO CCUSMA.OKPHNO CCUSMA.OKPHNO CCUSMA.OKPHNO CCUSMA.OPPHNO OCUSAD.OPPHNO OCUSAD.OPPTFNO CCUSMA.OPPHNO CCUSMA.OPPHNO CCUSMA.ORPHNO CCUSMA.ORPHNO CCUSMA.OPPHNO CCUSMA.O	CRS610MI/GetAddress.; /	
ShipToPartyMaster/Location/Address/PostalCode CCUSMA.OKPONO CRS610MI/GetBasicData CCUSAD.OPPONOX CRS610MI/GetAddress.; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to "true". ShipToPartyMaster/Communication DepreferredIndicator Set to "lalse". ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKPHNO CRS610MI/GetBasicData OCUSAD.OPPHNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	@listID	
CCUSMA_OKPONO CRS610MI/GetBasicData CCUSAD_OPPONOX CRS610MI/GetAddress.; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to 'true'. ShipToPartyMaster/Communication Distrib ShipToPartyMaster/Communication/UseCode ShipToPartyMaster/Communication/UseCode ShipToPartyMaster/Communication/UseCode Set to 'Tempore' if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to 'Communication Channels'. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Phone' if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber CCUSMA_OKPHNO CCUSMA_OKPHNO CRS610MI/GetBasicData CCUSAD_OPPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CRS610MI/GetBasicData CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CCUSMA_OKPHNO CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		Set to 'Countries'.
CUSAD.OPPONOX CRS610MI/GetAddress; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to 'true'. ShipToPartyMaster/Communication DepreferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Ommunication Channels'. ShipToPartyMaster/Communication/UseCode Set to "Ommunication Use Codes'. ShipToPartyMaster/Communication/DialNumber CUSMA.OKPHNO CUSMA.OKPHNO CRS610MI/GetBasicData CUSMA.OKPHNO CUSMA.OKPHNO CRS610MI/GetBasicData CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPHNO CUSMA.OPPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		-
OCUSAD.OPPONOX CRS610MI/GetAddress; / ShipToPartyMaster/Location/Address/Preference/Indicator Set to 'true'. ShipToPartyMaster/Communication DepreferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "EMail" if e-mail address. Set to "Communication Channels'. ShipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMALL.OEBMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		The field indicates the postal code.
CRS610MI/GetAddress.; / ShipToPartyMaster/Communication @preferredIndicator Set to 'true'. ShipToPartyMaster/Communication @preferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Communication Channels'. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKTENO CRS610MI/GetBasicData OCUSAD_OPPHNO OCUSAD_OPPHNO OCUSAD_OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL_CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	CR5610MI/GetBasicData	
CRS610MI/GetAddress.; / ShipToPartyMaster/Communication @preferredIndicator Set to 'true'. ShipToPartyMaster/Communication @preferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Communication Channels'. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKTENO CRS610MI/GetBasicData OCUSAD_OPPHNO OCUSAD_OPPHNO OCUSAD_OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL_CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	OCUSAD OPPONOX	
Set to 'true'. Set to 'true'. Set to 'talse'. Set to 'false'. Set to 'false'. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSAD_OPPHNO OCUSAD_OPPHNO OCUSAD_OPPHNO OCUSAD_OPTFNO CR8610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL_CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer.		
Set to 'true'. ShipToPartyMaster/Communication DepreferredIndicator Set to 'false'. Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. ShipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes'. Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA_OKPHNO OCUSMA_OKPHNO OCUSMA_OKTFNO CRS610MI/GetBasicData OCUSAD_OPPHNO OCUSAD_OPPHNO OCUSAD_OPTFNO CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/URI CEMAIL_CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer.	·	
Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. ShipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPFNO OCUSAD.OPPFNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		Set to 'true'.
@preferredIndicator Set to 'false'. ShipToPartyMaster/Communication/ChannelCode Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. ShipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKPHNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPTRNO CRS610MI/GetBasicData OCUSAD.OPTRNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	ShipToPartyMaster/Communication	
Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Communication Channels". Set to "Communication Channels". Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". Set to "Communication Use Codes". Set to "Communication Use Codes". The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPTNO OCUSAD.OPPTNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates an e-mail address for the customer.		
Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address. Set to "Communication Channels". Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". Set to "Communication Use Codes". Set to "Communication Use Codes". The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKFFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		Set to 'false'.
Set to "EMail" if e-mail address. Set to "Communication Channels". Set to "Communication Channels". Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to "Communication Use Codes". Set to "Communication Use Codes". Set to "Communication Use Codes". The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	ShipToPartyMaster/Communication/ChannelCode	
Set to 'Communication Channels'. Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTRNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPPHNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		
Set to 'Communication Channels'. Set to 'Phone" if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	91:-41 D	Set to "EMail" if e-mail address.
SchipToPartyMaster/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer.	עווצווע	Set to 'Communication Channels'
Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData ShipToPartyMaster/Communication/Preference/Indicator	ShinToPartyMastor/Communication/HooCode	Section Communication Challings.
facsimile number. Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData facsimile number. ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData facsimile number. Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates an e-mail address for the customer.	omprorartywaster/Communication/UseCode	Sat to "Dhana" if talanhana number 1. talanhana number 2
Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData ShipToPartyMaster/Communication/Preference/Indicator		
Set to 'Communication Use Codes'. ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData Set to 'Communication Use Codes'. The field indicates the telephone 1, telephone number 2 or facsimile number. OCUSAD.OPTFNO CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	@listID	idodilillo lidilipot.
CUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKPHNO OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number.		Set to 'Communication Use Codes'.
OCUSMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / CRS610MI/GetAddress.; / ChipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number. The field indicates the telephone 1, telephone number 2 or facsimile number.	ShipToPartyMaster/Communication/DialNumber	
OCUSMA.OKPHN2 OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ChipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ChipToPartyMaster/Communication/Preference/Indicator		The field indicates the telephone 1, telephone number 2 or facsimile
OCUSMA.OKTFNO CRS610MI/GetBasicData OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		
OCUSAD.OPPHNO OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	OCUSMA.OKTFNO	
OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	CRS610MI/GetBasicData	
OCUSAD.OPTFNO CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		
CRS610MI/GetAddress.; / ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		
ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator		
CEMAIL.CBEMAL; CRS610MI/GetBasicData The field indicates an e-mail address for the customer. ShipToPartyMaster/Communication/Preference/Indicator	·	
ShipToPartyMaster/Communication/Preference/Indicator		The field bulleting and a 19 of 19 of 19
	·	i ne tield indicates an e-mail address for the customer.
	ShipToPartyMaster/Communication/Preference/Indicator	Set to 'false'.

ShipToPartyMaster/Contact/ID CCUCON.CCCNPE; CMS055MI/LstByCustomer	The field indicates the contact ID.
@accountingEntity	
	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipToPartyMaster/Contact/Communication/DialNumber OCUSMA.OKPHNO OCUSAD.OPPHNO .; CRS610MI/GetAddress	The field indicates the telephone 1, telephone number 2 or facsimile number.
ShipToPartyMaster/PaymentTermID OCUSMA.OKTEPY CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo	The field indicates the payment term.
ShipToPartyMaster/PaymentTermCode OCUSMA.OKTEPY CCUDIV.OKTEPY.; CRS610MI/GetOrderInfo @listID	The field indicates the payment term.
when the state of	Set to 'Payment Term'.
ShipToPartyMaster/PaymentMethodCode OCUSMA.OKPYCD; CRS610MI/GetOrderInfo	The field indicates the AR payment method. The payment method code is translated in CRS881 (e.g. Cash, Cheque). If no translation exist in CRS881, the following translation is followed based on the payment class: Set to 'Cash' if payment class (PYCL) is 0. Set to 'Cheque' if payment class (PYCL) is 1 or 2. Set to 'CreditCard/DebitCard' if payment class (PYCL) is 3 and credit card tag (CRDC) is 1. Set to 'ElectronicFundsTransfer' if payment class (PYCL) is 3 and credit card tag (CRDC) is 0. Set to 'BankDraft' if payment class (PYCL) is 4. Set to 'DirectDebit' if payment class (PYCL) is 5. Set to 'Factoring' if payment class (PYCL) is 6.
ShipToPartyMaster/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/LstByAccHolder	The field indicates the Bank ID (BKNO) where Customer bank type is 02 (Customer Bank Accounts), if Country Specific Version (CSVN) is 'RU'. Get the highest Bank Priority (CBPY).
@accountingEntity	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
ShipToPartyMaster/FinancialParty/PartyIDs/BICID XRUBAN.BKXBIK; CRRU04MI/GetBankRU	The field indicates the bank account ID to which related bank account information is connected.
	If Country Specific Version (CSVN) is 'RU', display BIK code.
ShipToPartyMaster/FinancialParty/Name XRUBAN.BKXFLN; CRRU04MI/GetBankRU	The field indicates the Full name RU if Country Specific Version (CSVN) is 'RU'.
ShipToPartyMaster/FinancialParty/FinancialAccount/BBANID CBANAC.BCFIAN; CRS692MI/LstByAccHolder	The field indicates the Financial Institution if the Country Specific Version (CSVN) is 'RU'.
ShipToPartyMaster/FinancialParty/FinancialAccount/IBANID CBANAC.BCIBAN; CRS692MI/LstByAccHolder	The field indicates the International Bank account number if Country Specific Version (CSVN) is 'RU'.
ShipToPartyMaster/UserArea/Property/Namevalue 1) OCUSAD.OPFVDT 2) OCUSAD.OPLVDT 3) OCUSAD.OPADID 4) OCUSAD.OPADRT.; CRS610MI/GetAddress	The field indicates the first valid date. Set attribute name to "EffectiveTimePeriod-StartDateTime".
	The field indicate the last date the record is valid.Set attribute name to "EffectiveTimePeriod-EndDateTime".
	The field indicates the address number.Set attribute name to "Address number".
	The field indicates the address type. Set attribute name to "Address Type".
ShipToPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/GetBasicData	The field indicates the status of the customer.

SnipioPartyMaster	
	Set to 'Pending' if status is 10. Set to 'Open' if status is 20. Set to 'Closed' if status is 90. Set to 'Deleted' if delivery address is removed.
ShipToPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP CRS610MI/GetBasicData	The field indicates the Classification.
2) OCUSMA.OKTEDL CCUDIV.OKTEDL CRS610MI/GetOrderInfo	Customer Types The field indicates the type of customer. Set attribute listID to "Customer Types".
3) OCUSMA.OKSDST CRS610MI/GetOrderInfo .; /	 Incoterms The field indicates delivery terms, which indicate when the responsibility for the transport is transferred from supplier to customer. Set attribute listID to "Incoterms'.
@coguence	District The field indicates the district the customer or payer belongs to. Set attribute listID to 'District'.
@sequence	The field indicates the sequence number for the ordering of elements within a document.
@listID	The field indicates the Classification code listID. 1) Set to 'Customer Types' if Classification/Codes/Code is CUTP. 2) Set to 'Incoterms' if Classification/Codes/Code is TEDL. 3) Set to 'District' if Classification/Codes/Code is SDST.
ShipToPartyMaster/CustomerParty/PartyIDs/ID OCUSMA .OKCUNO; CRS610MI/GetBasicData @accountingEntity	The field indicates the unique identification of the customer.
	The field indicates the company and division, displayed as CONO_DIVI.
	If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, if ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
ShipToPartyMaster/CustomerParty/Name OCUSMA.OKCUNM; CRS610MI/GetBasicData	The field indicates the name of the customer record.
ShipToPartyMaster/PointOfShipmentCode OCUSAD.OPEDES; CRS610MI/GetAddress	The field indicates the ID of a geographic location or a place, such as city, town or airport.
@listID	Set to 'Points Of Shipment'.
ShipToPartyMaster/SalesPersonReference/IDs/ID OCUSMA.OKSMCD CCUDIV.OKSMCD.; CRS610MI/GetOrderInfo @accountingEntity	The field indicates the person responsible for sales to a customer.
CMNDIV.CCCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
	If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

Shipment/ShipmentHeader/DocumentID/ID

For ProcessShipment: MHPICH.PIDLIX MHPICH.PIPLSX MWOMAT.VMMFNO MWOMAT.VMMSEQ.;/

For SyncShipment: DCONSI.DACONN ; DRS100MI/LstShipment

For SyncShipmentDelivery: MHDISH.OQDLIX; MWS410MI/GetHead

@accountingEntity

For ProcessShipment: MHPICH.PICONO CMNDIV.CCDIVI.; /

For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; /

For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI

@location

For ProcessShipment: MHPICH.PIWHLO; /

For SyncShipmentDelivery: MHDISH.OQWHLO; MWS410MI/GetHead

@variationID

@lid

Shipment/ShipmentHeader/AlternateDocumentID/ID

For ProcessShipment:

The field indicates the delivery number and picking list suffix separated by '/'.

If event operation is Delete (Status/Code is 'Deleted'), the DocumentID/ID from the Acknowledge BOD is used.

If the Shipment BOD is for manufacturing order material with issue method not picking list (triggered through table MWOMAT), the field indicates the manufacturing order number concatenated with material sequence number.

If event operation is update (actionCode is Change), and the Shipment BOD is for manufacturing order material with issue method not picking list, the DocumentID/ID from the Acknowledge BOD is used.

For SyncShipment:

The field indicates a shipment number.

For SyncShipmentDelivery:

The field indicates the delivery number.

The field indicates the company and division, displayed as CONO_DIVI.

For ProcessShipment:

The field indicates the warehouse ID.

For SyncShipment:

The field indicates the location ID.

For SyncShipmentDelivery:

The field indicates the location attribute.

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For ProcessShipment:

The field indicates the logical id of the system that is SOR for this noun instance.

For SyncShipment:

The field indicates the logical ID of the system.

For SyncShipmentDelivery:

The field indicates the logical ID of the system

For ProcessShipment:

If the DocumentID is successfully retrieved from the

AcknowledgeShipment, these fields from event data are displayed in this element:

 Delivery number (DLIX) and Picking list suffix (PLSX)in DLIX/PLSX format when MHPICH_DELETE_ProcessShipment rule is triggered (BODStatusCode = Deleted)

- Concatenation of Manufacturing order number (MFNO) and Sequence number (MSEQ) when

MWOMAT_UPDATE_ProcessShipment is triggered (eventData originDocument is MWOMAT)

Shipment/ShipmentHeader/LastModificationDateTime

For ProcessShipment: MHPICH.PILMDT MWOMAT.VMLMTS.; /

For SyncShipment: DCONSI.DALMTS; /

For ProcessShipment:

If triggered from MHPICH rule, this element displays the Change date (LMDT).

If triggered from MWOMAT rule, this element displays the Timestamp (LMTS).

For SyncShipment:

For SyncShipmentDelivery:

MHDÍSH.OQLMTS: /

The field indicates the date and time the record was last modified.

For SyncShipmentDelivery:

The field indicates the last modification date and time.

Shipment/ShipmentHeader/LastModificationPerson/IDs/ID

For ProcessShipment: MHPICH.PICHID; /

For SyncShipment: DCONSI.DACHID; /

For SyncShipmentDelivery:

MHDÍSH.OQCHID; /

@accountingEntity

For ProcessShipment: MHPICH.PICONO

CMNDIV.CCDIVI.; /

For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; /

For SyncShipmentDelivery:

MHDÍSH.OQCONO CMNDIV.CCDIVI

Shipment/ShipmentHeader/DocumentDateTime

MHPICH.PIRGDT

For SyncShipment:

DCONSI.DARGTM.; DRS100MI/GetServerTime

For SyncShipmentDelivery:

MHDISH.OQTRTM.; MWS410MI/GetHead

For ProcessShipment:

The field indicates the person who last modified the record.

For SyncShipment:

The field indicates the user ID of the person who last modified the

object.

For SyncShipmentDelivery:

The field indicates the ID of the person that entered/changed the

The field indicates the company and division, displayed as

CONO DIVI.

For ProcessShipment:

MHPICH.PIRGTM.; MWS422MI/LstPickDetail

DCONSI.DARGDT

MHDISH.OQTRDT

For ProcessShipment:

The field indicates the date and time the document was created.

For SyncShipment:

The field indicates the date and time the document was created.

For SyncShipmentDelivery:

The field indicates the document date and time.

Shipment/ShipmentHeader/Note

For ProcessShipment:

.; OIS100MI/LstHeadText

For ProcessShipment:

The field indicates the text note.

Call OIS100MI.LstHeadText only if TTYP=31. Use the following

inputs:

ORNO = <RIDN>

TYTR = 1/2/3

For ProcessShipment:

The field indicates the text block.

Call OIS100MI.LstHeadText only if TTYP=31

@use

@noteID

For ProcessShipment:

For ProcessShipment:

.; OIS100MI/LstHeadText

CSYTXH.THTXEI; CRS980MI/LstTxtBlocks

For ProcessShipment:

The field indicates the external/internal text.

If TXEI=0/1, set to External. If TXEI=2, set to Internal. Use the following as inputs:

CONO = <CONO>

TXID = <OIS100MI.LstHeadText TXID>

TFIL = OSYTXH

For ProcessShipment:

The field indicates the text type. If TYTR=1, set to 'Pre-text'. If TYTR=2, set to 'Post-text'. If TYTR=3, set to 'Text'.

Call OIS100MI.LstHeadText only if TTYP=31

Shipment/ShipmentHeader/DocumentReference

@type

@type

For ProcessShipment:

For ProcessShipment:

.; OIS100MI/LstHeadText

MITALO.MQTTYP; MWS422MI /LstPickDetail

For SyncShipment:

MHDISH.OQRORC; MWS410MI/GetHead

For SyncShipmentDelivery:

MHDÍSH

For ProcessShipment:

The field indicates the document reference type.

11 - ProductionOrder

31 - SalesOrder

41 - SupplierRMA

51 - Transfer

61 - ServiceOrder

Shipment	
.OQRORC; MWS410MI/GetHead	If the Shipment BOD is for manufacturing order material with issue method not picking list (triggered through table MWOMAT), the field is set to PoductionOrder.
	For SyncShipment: The field indicates the document reference order category (RORC).
	The field is set to the following: If RORC = 1, set to 'ProductionOrder'. If RORC = 2, set to 'PurchaseOrder'. If RORC = 3, set to 'SalesOrder'. If RORC = 4, set to 'Transfer'. If RORC = 5, set to 'Transfer'. If RORC = 6, set to 'WorkOrder'. If RORC = 7, set to 'ServiceOrder'. If RORC = 8, set to 'ProjectOrder'. If RORC = 9, set to 'ClaimOrder'.
	For SyncShipmentDelivery: The field indicates the origin of the reference order category (RORC).
	If RORC = 1, set to 'ProductionOrder'. If RORC = 2, set to 'PurchaseOrder'. If RORC = 3, set to 'SalesOrder'. If RORC = 4, set to 'Transfer'. If RORC = 5, set to 'Transfer'. If RORC = 6, set to 'WorkOrder'. If RORC = 7, set to 'ServiceOrder'. If RORC = 8, set to 'ProjectMaster'. If RORC = 9, set to 'SupplierRMA'.
Shipment/ShipmentHeader/DocumentReference/DocumentID/ID For ProcessShipment: MITALO.MQRIDN; MWS422MI/LstPickDetail MWOMAT.VMMFNO; PMS100MI/GetLine.; /	The field indicates the order number.
For SyncShipment: MHDISH.OQRIDN; MWS411MI/LstDeliveryLine	
For SyncShipmentDelivery: MHDISL.UIRIDN ; MWS411MI/LstDeliveryLine @accountingEntity For ProcessShipment: MHPICH.PICONO	The field indicates the company and division, displayed as CONO_DIVI.
CMNDIV.CCDIVI.; / For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; /	_
For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI .; /	
@location	5 5 0 0
For ProcessShipment: MWOMAT.VMWHLO; PMS100MI/GetLine	For ProcessShipment: The filed indicates the warehouse.
For SyncShipmentDelivery: MHDISH.OQWHLO ; MWS410MI/GetHead	For SyncShipmentDelivery: The field indicates the location attribute.
Shipment/ShipmentHeader/Status/Code For ProcessShipment: MHDISH.OQPGRS; MWS410MI/GetHead	For ProcessShipment: The field indicates the status of a delivery.

MHDISH.OQPGRS; MWS410MI/GetHead MWOMAT.VMWMST; PMS100MI/GetLine.; /

For SyncShipment: DCONSI.DACSTL ; DRS100MI/LstShipment

For SyncShipmentDelivery: MHDISH.OQPGRS ; MWS410MI/GetHead

00, 01 - Open 02, 03 - Hold 05 - Allocated 50 - Released 60 - Shipped 65 - Partially Shipped 90, 95 - Received

This is set to 'Deleted' if record is deleted in MWS420.

If the Shipment BOD is for manufacturing order material with issue method not picking list (triggered through table MWOMAT), the field indicates the manufacturing order material status:

Infor May 26, 2023

CIADDR.OAADR1

33 - Released 39 - PartiallyShipped 99 - Shipped For SyncShipment: The field indicates the status of the shipment. Set to "Open" if status is 00 or 10. Set to 'Allocated' if status is 20 or 30. Set to 'Staged' if status is 40. Set to 'Loaded' if status is 50. Set to 'Shipped' if status is 60. Set to 'Cancelled' if status is 90. For SyncShipmentDelivery: The field indicates the status of a delivery. Set to 'Open' if status is 00 or 01. Set to 'Hold' if status is 02 or 03. Set to 'Allocated' if status is 05 Set to 'Released' if status is 50 Set to 'Shipped' if status is 60 Set to 'PartiallyShipped' if status is 65. Set to 'Shipped' if status is 90 and delivery receipt confirmation (DLCN) = 0.Set to 'Received' if status is 90 and delivery receipt confirmation (DLCN)! = 0.Set to 'Received' if status is 95. If delivery status is 02 and the lowest order status is >= 44, set to 'Released'. Shipment/ShipmentHeader/ShipUnitQuantity For SyncShipmentDelivery: For SyncShipmentDelivery: .; MWS410MI/GetHead The field indicates the ship unit quantity. @unitCode For SyncShipmentDelivery: For SyncShipmentDelivery: MPTRNS.ORPACT; MWS423MI/LstPackDel The field indicates the packaging. The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Packaging Shipment/ShipmentHeader/WarehouseLocation/ID For SyncShipment: For SyncShipment: DCONSI.DAWHLO The field indicates the warehouse ID. ; DRS100MI/LstShipment For SyncShipmentDelivery: The field indicates the location. For SyncShipmentDelivery: MHDÍSH.OQWHLO ; MWS410MI/GetHead @accountingEntity For SyncShipment: The field indicates the company and division, displayed as CONO_DIVI. DCONSI.DACONO DCONSI.DADIVI.; / For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; / Shipment/ShipmentHeader/WarehouseLocation/Name For SyncShipment: For SyncShipment: MITWHL.MWWHNM The field indicates the warehouse description. ; MMS005MI/GetWarehouse For SyncShipmentDelivery: The field indicates the warehouse name. For SyncShipmentDelivery: MITWHL.MWWHNM ; MMS005MI/GetWarehouse Shipment/ShipmentHeader/WarehouseLocation/Address @type Set to 'text'. Shipment/ShipmentHeader/WarehouseLocation/Address/AddressLine

nfor May 26, 2023 56

The field indicates the address line.

CIADDR.OAADR2 CIADDR.OAADR3

CIADDR.OAADR4.; MMS005MI/GetWarehouse

@sequence

The field indicates the address line sequence

Shipment/ShipmentHeader/WarehouseLocation/Address/CityName

CIADDR.OATOWN; MMS005MI/GetWarehouse

The field indicates the city name.

Shipment/ShipmentHeader/WarehouseLocation/Address/CountrySubDivisionCode

CIADDR.OAECAR; MMS005MI/GetWarehouse

The field indicates an area, province or state within a country.

@listID

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France).

Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

Shipment/ShipmentHeader/WarehouseLocation/Address/CountryCode

CIADDR.OACSCD; MMS005MI/GetWarehouse

@listID

The field indicates the country code.

Set to "Countries"

Shipment/ShipmentHeader/WarehouseLocation/Address/PostalCode

CIADDR.OAPONO; MMS005MI/GetWarehouse

The field indicates the postal code

The field indicates the transportation route.

Shipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID

For ProcessShipment:

MHDISH.OQROUT; MWS410MI/GetHead

For SyncShipment: DCONSI DAROUT

; DRS100MI/LstShipment

For SyncShipmentDelivery: MHDISH.OQROUT

; MWS410MI/GetHead

@accountingEntity

For ProcessShipment:

MHPICH.PICONO

CMNDIV.CCDIVI.; /

For SyncShipment:

DCONSI.DACONO

DCONSI.DADIVI.; /

For SyncShipmentDelivery:

MHDISH.OQCONO CMNDIV.CCDIVI.; / CONO DIVI.

For SyncShipment:

CONO_DIVI.

For ProcessShipment:

E.g. 760_AAA

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

CONO DIVI.

Shipment/ShipmentHeader/CarrierRouteReference/RouteStop/ID

For ProcessShipment:

MHDISH.OQEDES; MWS410MI/GetHead

For ProcessShipment:

The field indicates the ID of a geographic location or a place, such as

a city, town, or airport.

Shipment/ShipmentHeader/CarrierRouteReference/RouteStop/RouteDay

For SyncShipmentDelivery:

MHDISH.OQDEWD; MWS410MI/GetHead

For SyncShipmentDelivery:

The field indicates the day of the week when delivery is made to a

customer.

Alternatives: Set '1' if Mondays.

Set '2' if Tuesdays Set '3' if Wednesdays. Set '4' if Thursdays. Set '5' if Fridays.

Set '6' if Saturdays. Set '7' if Sundays

Shipment/ShipmentHeader/ActualShipDateTime

For SyncShipment: DCONSI.DADFDT

DCONSI.DADFHM DCONSI.DADSDT

MWS410MI/GetHead

DCONSI.DADSHM.; DRS100MI/GetShipment

For SyncShipmentDelivery: MHDISH.OQDSDT MHDISH.OQDSHM;

For SyncShipment:

The field indicates the date and time the order is to be shipped by the supplier. Actual departure date and time for Shipment is used if it is set manually. Otherwise, planned Departure date and time for

shipment is used.

Hours from UTC (TGMT) defined for the time zone in DRS045 is used

to convert date and time to UTC.

For SyncShipmentDelivery:

The field indicates the actual departure date and time of the delivery.

Shipment	
MITTRA.MTRGDT MITTRA.MTRGTM; MWS070MI/LstTransByOrder .; /	Agreement control property m3beActualShipDateTime is added to provide flexibility on where to retrieve the information for this element . If value is set to RGDTRGTM, ActualShipDateTime is retrieved from MWS070MI.LstTransByOrder RGDT RGTM. Otherwise, it will be retrieved from MWS410MI.GetHead DSDT DSHM. Default value of m3beActualShipDateTime is set to DSDTDSHM.
Shipment/ShipmentHeader/ScheduledDeliveryDateTime For SyncShipment: DCONSI.DARDDT DCONSI.DARDTM DCONSI.DAARDT DCONSI.DAARHM.; DRS100MI/GetShipment	For SyncShipment: The field indicates the date and time the order is to be delivered by the supplier. Planned Route departure date and time is used if it is set. Otherwise, planned Arrival date and time for shipment is used. For SyncShipmentDelivery:
For SyncShipmentDelivery: MHDISH.OQDEDA MHDISH.OQDLTM; MWS410MI/GetHead or OOLINE.OBCODT OOLINE.OBCOHM;	The field indicates the estimated date and time of arrival at the place of unloading for outbound deliveries. Handling will depend on the agreement control property m3beScheduledDeliveryDateTime. The default value is DEDADLTM. If m3beScheduledDeliveryDateTime is set to DEDADLTM, the data is
OIS100MI.LstLineBOD.; /	retrieved from MWS410MI.GetHead DEDA and DLTM. If m3beScheduledDeliveryDateTime is set to CODZCOHZ, the data is retrieved from the first record returned by the OIS100MI.LstLineBOD CODZ and COHZ in UTC (UTCM field set to 1). Use the first RIDN output from MWS411MI.LstDeliveryLine as OIS100MI.LstLineBOD ORNO input. If m3beScheduledDeliveryDateTime is set to CODZCOHZ but DocumentReference@type is not SalesOrder, the data is retrieved from MWS410MI.GetHead DEDA and DLTM.
Shipment/ShipmentHeader/ActualDeliveryDateTime For SyncShipment: DCONSI.DAARDT DCONSI.DAARHM DCONSI.DADFDT DCONSI.DADFHM.; DRS100MI/GetShipment	For SyncShipment: The field indicates the date and time the order is to be delivered by the supplier. Planned Arrival date and time for shipment is used with exception for situations when manually set Actual departure date and time is later then Planned Arrival date and time, in which case Actual departure date and time is used.
For SyncShipmentDelivery: MITTRA.MTRGDT MITTRA.MTRGTM.; MWS070MI/LstTransByOrder	Hours from UTC (TGMT) defined for the time zone in DRS045 is used to convert date and time to UTC. For SyncShipmentDelivery:
	The field indicates the date and time the goods were delivered.
Shipment/ShipmentHeader/EstimatedWeightMeasure For SyncShipment: DCONSI.DAGWTE ; DRS100MI/LstShipment @unitCode	For SyncShipment: The field indicates the estimated gross weight packed.
For SyncShipment: CSYTAB.CTPARM ; CRS175MI/GetItemFreeFlds	For SyncShipment: The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentHeader/LoadingWeightMeasure For SyncShipment: DCONSI.DAGRW2 ; DRS100MI/LstShipment	For SyncShipment: The field indicates the packed gross weight.
<pre>@unitCode For SyncShipment: CSYTAB.CTPARM ; CRS175MI/GetItemFreeFlds</pre>	For SyncShipment: The field indicates the general unit of measure for all weights within a company.
Shipment/ShipmentHeader/NetWeightMeasure For SyncShipmentDelivery: MHDISH.OQNEWE; MWS410MI/GetHead @unitCode	For SyncShipmentDelivery: The field indicates the weight of item without container or package.
For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For SyncShipmentDelivery: The field indicates the general unit of the weight item.
Shipment/ShipmentHeader/GrossWeightMeasure	The field indicates the general unit of the weight item.
For SyncShipment: DCONSI.DAGRWE ; DRS100MI/LstShipment	For SyncShipment: The field indicates the gross weight.
For SyncShipmentDelivery: MHDISH.OQGRW2; MWS410MI/GetHead	For SyncShipmentDelivery: The field indicates the gross weight of all items in the delivery.

For SyncShipmentDelivery:
MHDISH.OQGRW2; MWS410MI/GetHead
@unitCode
For SyncShipment:
CSYTAB.CTPARM
; CRS175MI/GetItemFreeFlds The field indicates the general unit of measure for all weights within a company.

Infor May 26, 2023 570

For SyncShipmentDelivery:

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

Shipment/ShipmentHeader/TotalVolumeMeasure

For SyncShipment: DCONSI.DAVLME

; DRS100MI/LstShipment

For SyncShipmentDelivery: MHDISH.OQVM32

; MWS410MI/GetHead **@unitCode**

For SyncShipment: CSYTAB.CTPARM

; CRS175MI/GetItemFreeFlds

For SyncShipmentDelivery:

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

Shipment/ShipmentHeader/TransportationMethodCode

For ProcessShipment:

CSYTAB.CTPARM; MWS410MI/GetHead

For SyncShipment: CSYTAB.CTPARM

; CRS070MI/GetDelyMethod

For SyncShipmentDelivery:

MHDISH.OQMODF

MHDISH.OQMODL.; MWS410MI/GetHead

For SyncShipment:

The field indicates the estimated volume.

For SyncShipmentDelivery:

The field indicates the volume of all items in the delivery.

For SyncShipment:

The field indicates the general unit of measure for all volumes within a

company.

For SyncShipmentDelivery:

The field indicates the general unit for total measure of the item.

For ProcessShipment:

The field indicates the delivery method.

Display MODL only if MODF is blank.

For SyncShipment:

The field indicates how the delivery is made.

For SyncShipmentDelivery:

The field indicates the delivery method for a delivery number.

If MODF is blank, use MODL.

The value can be translated in CRS881/882.

Msg std: ION Vers: 1 Message: Generic

I/O: O

Parent element(s): Generic

Data element: TransportationMethodCode

The field indicates the warehouse name

Shipment/ShipmentHeader/ShipFromParty/Name

MITWHL.MWWHNM; MMS005MI/GetWarehouse
Shipment/ShipmentHeader/ShipFromParty/Location

@type
For ProcessShipment:

CSYTAB.CTSTKY; MMS006MI/Get

For ProcessShipment:

The field indicates if the warehouse is a Distribution Center. Set to 'Distribution Center' if DCWH = 1. If DCWH = 0, do not display the

element.

Call MMS005MI/GetWarehouse, use value from ShipFromParty/Location/ID as input to WHLO then retrieve WHTY. Use WHTY as

input to MMS006MI/Get.

For SyncShipmentDelivery: If Facility, set to 'Site'.

Shipment/ShipmentHeader/ShipFromParty/Location/ID

For ProcessShipment:

MHDISH.OQWHLO; MWS410MI/GetHead MWOMAT.VMWHLO; PMS100MI/GetLine.; /

For SyncShipment:

MHDISH.OQWHLO; MWS410MI/GetHead

For SyncShipmentDelivery: 1) MHDISH.OQWHLO; MWS410MI.GetHead

2) OOHEAD.OAFACI; OIS100MI.GetOrderHead.; /

@accountingEntity

For ProcessShipment: MHPICH.PICONO CMNDIV.CCDIVI.; /

For SyncShipment: DCONSI.DACONO

DCONSI.DADIVI.; /
For SyncShipmentDelivery:

For ProcessShipment:

The field indicates the warehouse ID.

For SyncShipment:

The field indicates the warehouse ID.

For SyncShipmentDelivery:

1) Warehouse

The field indicates the warehouse.

2) Facility

The field indicates the facility.

For ProcessShipment:

The field indicates the company and division, displayed as

CONO_DIVI.

For SyncShipment:

The field indicates the company and division, displayed as

CONO DIVI.

E.g. 760_AAA

MHDISH.OQCONO CMNDIV.CCDIVI.; /

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

CONO DIVI

Shipment/ShipmentHeader/ShipFromParty/Location/Address

Set to 'text'

Shipment/ShipmentHeader/ShipFromParty/Location/Address/AddressLine The field indicates the address line.

For SyncShipment: CIADDR.OADR1,

OADR2 OADR3,

OADR4; MMS005MI/GetWarehouse

For SyncShipmentDelivery:

CIADDR.OAADR1 CIADDR.OAADR2 CIADDR.OAADR3

CIADDR.OAADR4.; MMS005MI/GetWarehouse

@sequence

The field indicates the address line sequence

Shipment/ShipmentHeader/ShipFromParty/Location/Address/CityName

CIADDR.OATOWN; MMS005MI/GetWarehouse

For SyncShipment:

The field indicates the city name.

For SyncShipmentDelivery: The field indicates the city.

Shipment/ShipmentHeader/ShipFromParty/Location/Address/CountrySubDivisionCode

CIADDR.OAECAR; MMS005MI/GetWarehouse

The field indicates an area, province or state within a country.

@listID

For SyncShipment:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

For SyncShipmentDelivery: Set to 'US States' if CSCD = US.

Set to 'Canadian Provinces" if CSCD = CA Set to 'France - Departements'if CSCD = FR

Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

Shipment/ShipmentHeader/ShipFromParty/Location/Address/CountryCode

CIADDR.OACSCD; MMS005MI/GetWarehouse

@listID

@listID

@listID

The field indicates the country code.

For SyncShipment: Set to "Countries".

For SyncShipmentDelivery:

Set to 'Countries'

Shipment/ShipmentHeader/ShipFromParty/Location/Address/PostalCode

CIADDR.OAPONO; MMS005MI/GetWarehouse

The field indicates the postal code.

Shipment/ShipmentHeader/ShipFromParty/Communication

@preferredIndicator

Set to 'false'.

Shipment/ShipmentHeader/ShipFromParty/Communication/ChannelCode

For SyncShipment:

Set to 'Phone' if telephone number.

For SyncShipmentDelivery:

Set to "Phone" if telephone number.

Set to 'Communication Channels'

Shipment/ShipmentHeader/ShipFromParty/Communication/UseCode

For SyncShipment: Set to 'Office'.

For SyncShipmentDelivery:

Set to "Office".

Set to 'Communication Use Codes'

Shipment/ShipmentHeader/ShipFromParty/Communication/DialNumber

For SyncShipment:

For SyncShipment:

MITWHL.MWPHNO; MMS005MI/GetWarehouse

The field indicates the phone number.

Shipment For SyncShipmentDelivery: MITWHL.MWPHNO; MMS005MI/GetWarehouse For SyncShipmentDelivery: The field indicates the telephone number Shipment/ShipmentHeader/ShipFromParty/Communication/Preference/Indicator Set to 'false' Shipment/ShipmentHeader/CarrierParty/PartyIDs/ID For ProcessShipment: The field indicates the forwarding agent who can be used for the MHDISH.OQFWNO; MWS410MI/GetHead transport. For SyncShipment: DCONSI.DAFWNO ; DRS100MI/LstShipment For SyncShipmentDelivery: MHDISH.OQFWNO; MWS410MI/GetHead @accountingEntity For ProcessShipment: The field indicates the accounting entity. MHPICH.PICONO If CarrierParty is enabled in BOD Processor Master AE tab, this is CMNDIV.CCDIVI.; / displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI). For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; / For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; / Shipment/ShipmentHeader/CarrierParty/PartyIDs/TaxID CIDMAS.IDVRNO; CRS620MI/GetBasicData For SyncShipment: The field indicates the VAT registration number. For SyncShipmentDelivery: The field indicates the VAT registration number. Use FWNO as input to SUNO. @schemeName For SyncShipment: Set to 'TaxIdentificationNumber'. For SyncShipmentDelivery: Set to 'TaxIdentificationNumber' if TaxID is VRNO Shipment/ShipmentHeader/CarrierParty/Name For SyncShipment: The field indicates supplier name, most often the supplier's company CIDMAS.IDSUNM name. ; CRS620MI/GetBasicData For SyncShipmentDelivery: CIDMAS.IDSUNM; CRS620MI/GetBasicData Shipment/ShipmentHeader/FreightTermCode For ProcessShipment: For ProcessShipment: MHDISH.OQTEDF/ The field indicates the delivery terms. MHDISH.OQTEDL.; MWS410MI/GetHead Display TEDL only if TEDF is blank. For SyncShipmentDelivery: CSYTAB.CTSTKY; CRS065MI/GetDelyTerm For SyncShipmentDelivery: The field indicates the payer of the freight costs. If RCPY = 0, set to 'Sender pays'. If RCPY = 1, set to 'Recipient pays'. If RCPY = 2, set to 'Prepaid'. If RCPY = 3, set to 'Collect'. If RCPY = 4, set to 'Third Party' Shipment/ShipmentHeader/ReturnToShipFromParty/PartyIDs/ID For ProcessShipment: For ProcessShipment: MHDISH.OQCONA; MWS410MI/GetHead The field indicates the supplier.

For SyncShipment:

@accountingEntity For ProcessShipment:

MHPICH.PICONO

CMNDIV.CCDIVI.; /

MHDISH.OQCONA; MWS410MI/LstAdr

For SyncShipmentDelivery:

MHDISH.OQCONA; MWS410MI/GetAdr

For SyncShipment:

The field indicates the consignee. In this case, this is the Supplier.

The field is only available if shipment is for purchase order returns.

For SyncShipmentDelivery:

The field indicates the consignee which in this case is the Supplier.

Display ReturnToShipFromParty elements only for Requisition order

triggered from Purchase order return.

For ProcessShipment:

The field indicates the accounting entity.

If CarrierParty is enabled in BOD Processor Master AE tab, this is

For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; / displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO_DIVI).

For SyncShipment:

The field indicates the company and division, displayed as

CONO DIVI.

E.g. 760_AAA

The field is only available if shipment is for purchase order returns.

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

CONO DIVI.

Shipment/ShipmentHeader/ReturnToShipFromParty/PartyIDs/TaxID

CIDMAS.IDVRNO; CRS620MI/GetBasicData

For SyncShipment:

The field indicates the Tax ID.

The field is only available if shipment is for purchase order returns.

For SyncShipmentDelivery:

The field indicates the VAT registration number.

For SyncShipment:

Set to 'TaxIdentificationNumber'.

For SyncShipmentDelivery:

Set to 'TaxIdentificationNumber' if TaxID is VRNO

Shipment/ShipmentHeader/ReturnToShipFromParty/Name

For SyncShipment:

CIDMAS.IDSUNM; MWS410MI/LstAdr

For SyncShipment:

The field indicates the supplier's name.

The field is only available if shipment is for purchase order returns.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address

@type

@schemeName

Set to 'text'.

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/AddressLine

For SyncShipment: For SyncShipment:

CIDADR.SAADR1 The field indicates the address line.

CIDADR.SAADR2 CIDADR.SAADR3 The field is only available if shipment is for purchase order returns.

CIDADR.SAADR4 .; MWS410MI/LstAdr For SyncShipmentDelivery:

The field indicates the address line.

For SyncShipmentDelivery:

CIADDR.OAADR1 CIADDR.OAADR2 CIADDR.OAADR3

CIADDR.OAADR4.; MWS410MI/GetAdr

@sequence

@listID

The field indicates the address line sequence

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CityName

For SyncShipment: For SyncShipment:

CIDADR.SATOWN; MWS410MI/LstAdr The field indicates the city name.

For SyncShipmentDelivery:

CIADDR.OATOWN; MWS410MI/GetAdr

The field is only available if shipment is for purchase order returns.

For SyncShipmentDelivery: The field indicates the city name

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountrySubDivisionCode

For SyncShipment: CIDADR.SAECAR; MWS410MI/LstAdr For SyncShipment:

The field indicates an area, province or state within a country.

For SyncShipmentDelivery:

CIADDR.OAECAR; MWS410MI/GetAdr

The field is only available if shipment is for purchase order returns.

For SyncShipmentDelivery:

The field indicates an area, province or state within a country.

For SyncShipment:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

For SyncShipmentDelivery:

Setto 'Canadian Provinces' if the country is CA (Canada).

Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).

Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/CountryCode

For SyncShipment: For SyncShipment:

CIDADR.SACSCD; MWS410MI/LstAdr The field indicates a country.

For SyncShipmentDelivery: The field is only available if shipment is for purchase order returns.

CIADDR.OACSCD; MWS410MI/GetAdr For SyncShipmentDelivery:

The field indicates the country code.

@listID

Set to 'Countries'

Shipment/ShipmentHeader/ReturnToShipFromParty/Location/Address/PostalCode

For SyncShipment: For SyncShipment:

The field indicates a postal code. CIDADR.SAPONO; MWS410MI/LstAdr

For SyncShipmentDelivery: The field is only available if shipment is for purchase order returns.

CIADDR.OAPONO; MWS410MI/GetAdr

For SyncShipmentDelivery: The field indicates the postal code

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication

@preferredIndicator

Set to 'false'.

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication/ChannelCode

For SyncShipment:

Set to 'Phone' if Telephone number (PHNO and PHN2) or Facsimile

number (TFNO) is used in the DialNumber and 'EMail' if Email

address (EMAL) is used in URI.

For SyncShipmentDelivery:

Set to "Phone" if telephone number or facsimile number.

Set to "EMail" if e-mail address.

@listID

For SyncShipment:

Set to 'Communication Channels'

For SyncShipmentDelivery: Set to 'Communication Channels'

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication/UseCode

For SyncShipment:

Set to 'Office' if Telephone number (PHNO and PHN2) is used in the DialNumber or email address (EMAL) is used in URI and 'Fax' if

Facsimile number (TFNO) is used in the DialNumber

For SyncShipmentDelivery:

Set to "Office" if telephone number or e-mail.

Set to "Fax" if facsimile number.

@listID

For SyncShipment:

Set to 'Communication Use Codes'

For SyncShipmentDelivery: Set to 'Communication Use Codes'

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication/DialNumber

CIDMAS.IDPHNO For SyncShipment:

CIDMAS.IDPHN2 The field indicates the telephone number or the facsimile number.

CIDMAS.IDTFNO.; CRS620MI/GetBasicData

For SyncShipmentDelivery: The field indicates the telephone number or facsimile number.

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication/URI

For SyncShipment: For SyncShipment:

CEMAIL.CBEMAL; CRS111/Get The field indicates the email address.

For SyncShipmentDelivery: For SyncShipmentDelivery:

CEMAIL.CBEMAL; CRS111MI/Get The field indicates the e-mail address

Shipment/ShipmentHeader/ReturnToShipFromParty/Communication/Preference/Indicator Set to 'false'.

Shipment/ShipmentHeader/ShipToParty/PartyIDs/ID

For ProcessShipment: For ProcessShipment:

MHDISH.OQCONA; The field indicates the consignee's ID. MWS410MI.GetHead

OOHEAD.OAADID; Do not populate for Distribution Order, use ShipToParty/Location/ID OIS100MI.GetOrderHead.; /

instead.

For SyncShipment: MHDISH.OQCONA OQCOAA; MWS410MI/LstAdr

For SyncShipmentDelivery: MHDISH.OQCONA

MHDISH.OQCOAA.; MWS410MI/GetAdr

@accountingEntity

For ProcessShipment: MHDISH.QCCONO CMNDIV.CCDIVI.; /

For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; /

For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

Do not populate if DocumentReference@type='SupplierRMA'. Use ReturnToShipFromParty/PartyIDs/ID instead.

If TTYP=31, concatenate Address number (ADID) to Consignee (CONA) by using RIDN as input to ORNO of OIS100MI/ GetOrderHead.

For SyncShipment:

The field indicates the consignee's ID. If Address ID exists, the field is a concatenation of Consignee (CONA) + Consignee address number (COAA) without separator. If CONA does not consume the maximum length of 10, the rest is filled up with spaces. COAA is trimmed if it is more than 6 characters.

Use OIS100MI.GetHead to check if ADID exists. If ADID exists, ADRT = 11. If ADID is null, ADRT = 10. Applicable only if RORC = 3.

For SyncShipmentDelivery:

The field indicates the consignee's ID. If Address ID exists, the field is a concatenation of Consignee (CONA) + Consignee address number (COAA) without separator. If CONA does not consume the maximum length of 10, the rest is filled up with spaces. COAA is trimmed if it is more than 6 characters.

Use OIS100MI.GetHead to check if ADID exists. If ADID exists, ADRT = 11. If ADID is null, ADRT = 10. Applicable only if RORC = 3.

For ProcessShipment:

The field indicates the company and division, displayed as CONO DIVI.

If Master AE is enabled for the ShipToPartyMaster in the BOD Processor, the attribute will only display the company (e.g., '770'). Otherwise, it will display company and division (e.g., '770_AAA').

For SyncShipment:

The field indicates the accounting entity.

If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.

The field is only available for reference order category (RORC)= 3 - Sales Order.

For SyncShipmentDelivery:

The field indicates the accounting entity.

If ShipToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO_DIVI), e.g. 760_AAA.

Shipment/ShipmentHeader/ShipToParty/PartyIDs/TaxID

For SyncShipment: OCUSMA.OKVRNO; CRS610/GetFinancial

CMNDIV.CCVRNO; MNS100/GetBasicData.; /

For SyncShipmentDelivery: 1) OCUSMA.OKVRNO; CRS610MI/GetFinancial or CMNDIV.CCVRNO MNS100MI.GetBasicData

2) CMNDIV.CCVRNL MNS100MI.GetBasicData.; /

@schemeName

For SyncShipment:

The field indicates the ShipTo Party Tax ID.

For SyncShipmentDelivery: 1) VAT registration number

The field indicates the VAT registration number. Set to 'TaxIdentificationNumber' if TaxID is VRNO.

2) Tax Declaration number

The field indicates the Tax declaration number. Set to 'TaxDeclarationNumber' if TaxID is VRNL.

Call CRS610MI/GetFinancial if RORC = 3. Call MNS100MI/GetBasicData if RORC = 5.

For SyncShipment:

Set to 'TaxIdentificationNumber'.

For SyncShipmentDelivery:

1) Set to 'TaxIdentificationNumber' if TaxID is VRNO.
2) Set to 'TaxDeclarationNumber' if TaxID is VRNL.

Shipment/ShipmentHeader/ShipToParty/Name

For ProcessShipment: OCUSAD.OPCUNM

For ProcessShipment:

The field indicates the name of the customer.

OCUSMA.OKCUNM.: MWS410MI/GetAdr

For SyncShipment: CIADDR.OAWHNM

OOADRE.ODCUNM.; MWS410MI/LstAdr

For SyncShipmentDelivery: OCUŚMA.OKCUNM

For ProcessShipment:

@type

MITWHL.MWWHNM.; MWS410MI/GetAdr

CSYTAB.CTSTKY; MMS006MI/Get

Shipment/ShipmentHeader/ShipToParty/Location

For ProcessShipment:

For SyncShipment:

For SyncShipmentDelivery:

The field indicates the ShipTo party name.

The field indicates the consignee name.

The field indicates if the warehouse is a Distribution Center. Set to 'Distribution Center' if DCWH = 1. If DCWH = 0, do not display the

element.

Call MMS005MI/GetWarehouse, use value from ShipToParty/ Location/ID as input to WHLO then retrieve WHTY. Use WHTY as input to MMS006MI/Get.

Shipment/ShipmentHeader/ShipToParty/Location/ID

For ProcessShipment:

MHDISH.OQCONA; MWS410MI/GetHead

For SyncShipment:

MHDISH.OQCONA; MWS410MI/LstAdr

For SyncShipmentDelivery:

MHDISH.OQCONA; MWS410MI/GetHead

For ProcessShipment:

The field indicates the consignee.

For SyncShipment:

The field indicates the consignee. The field is only available for

reference order category (RORC)= 5 - Distribution.

For SyncShipmentDelivery: The field indicates the location ID.

This element is displayed if RORC = 5. Use ARDT = 11 as input.

@accountingEntity

For ProcessShipment: MHDISH.QCCONO CMNDIV.CCDIVI.; /

For SyncShipment: DCONSI.DACONO DCONSI.DADIVI.; / For ProcessShipment:

The field indicates the company and division, displayed as

CONO DIVI.

For SyncShipment:

The field indicates the company and division, displayed as

CONO DIVI.

E.g. 760_AAA

The field is only available for reference order category (RORC)= 5 -

Distribution.

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

CONO DIVI.

Shipment/ShipmentHeader/ShipToParty/Location/Name

For SyncShipmentDelivery: OCUŚMA.OKCUNM

MITWHL.MWWHNM.; MWS410MI/GetAdr

For SyncShipmentDelivery:

The field indicates the consignee name.

Shipment/ShipmentHeader/ShipToParty/Location/Address @type

For ProcessShipment:

The field indicates the address type. Set to 'text'.

For SyncShipment: Set to 'text'.

For SyncShipmentDelivery:

Set to 'text'.

Shipment/ShipmentHeader/ShipToParty/Location/Address/AddressLine

For ProcessShipment: OCUSAD.OPCUA1 OCUSAD.OPCUA2 OCUSAD.OPCUA3 OCUSAD.OPCUA4/ OCUSMA.OKCUA1 OCUSMA.OKCUA2

OCUSMA.OKCUA3 OCUSMA.OKCUA4.; MWS410MI/GetAdr

For SyncShipment: CIADÓR.OAADR1

The field indicates the address line.

CIADDR.OAADR3

CIADDR.OAADR4

OCUSAD.OPCUA1 OCUSAD.OPCUA2

OCUSAD.OPCUA3

OCUSAD.OPCUA4.; MWS410MI/LstAdr

For SyncShipmentDelivery:

OOADRE.ODCUA1

OOADRE.ODCUA2

OOADRE.ODCUA3

OOADRE.ODCUA4

CIADDR.OAADR1

CIADDR.OAADR2

CIADDR.OAADR3

CIADDR.OAADR4

.; MWS410MI/GetAdr

@sequence

For ProcessShipment:

The field indicates the address line sequence number.

For SyncShipment:

The field indicates the address line sequence.

For SyncShipmentDelivery:

The field indicates the city.

For SyncShipmentDelivery: The field indicates the city name.

The field indicates the city name.

For ProcessShipment:

For SyncShipment:

The field indicates the address line sequence

Shipment/ShipmentHeader/ShipToParty/Location/Address/CityName

For ProcessShipment:

OCUSAD.OPTOWN/

OCUSMA.OKTOWN.; MWS410MI/GetAdr

For SyncShipment: CIADÓR.OATOWN

OCUSAD.OPTOWN.; MWS410MI/LstAdr

For SyncShipmentDelivery: OOADRE.ODTOWN

CIADDR.OATOWN.; MWS410MI/GetAdr

For ProcessShipment:

For SyncShipmentDelivery:

For SyncShipment:

Shipment/ShipmentHeader/ShipToParty/Location/Address/CountrySubDivisionCode

For ProcessShipment:

OCUSAD.OPECAR/ OCUSMA.OKECAR.; MWS410MI/GetAdr

For SyncShipment:

CIADÓR.OAECAR

OCUSAD.OPECAR.; MWS410MI/LstAdr

For SyncShipmentDelivery:

OOADRE.ODECAR

CIADDR.OAECAR.; MWS410MI/GetAdr @listID

For ProcessShipment:

The field indicates the country subdivision code listID.

Set to 'US States' if country is US.

Set to 'Canadian Provinces' if country is CA. Set to 'France - Departements' if country is FR.

The field indicates the country subdivision code.

The field indicates an area, province or state within a country.

The field indicates an area, province or state within a country.

Else, set to 'SubDivisions - <Country>'. Retrieve country using

MMS005MI/GetWarehouse CSCD.

For SyncShipment:

Set to 'Canadian Provinces' if the country is CA (Canada).

Set to 'France - Departements' if the country is FR (France).

Set to 'US States' if the country is US (United States).

Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

For SyncShipmentDelivery:

Setto 'Canadian Provinces' if the country is CA (Canada).

Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States)

Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

Shipment Shipment/ShipmentHeader/ShipToParty/Location/Address/CountryCode For ProcessShipment: For ProcessShipment: OCUSAD.OPCSCD/ The field indicates a country. OCUSMA.OKCSCD.; MWS410MI /GetAdr For SyncShipment: For SyncShipment: The field indicates a country. CIADDR.OACSCD OCUSAD.OPCSCD.; MWS410MI/LstAdr For SyncShipmentDelivery: The field indicates the country code. For SyncShipmentDelivery: OOADRE.ODCSCD CIADDR.OACSCD.; MWS410MI/GetAdr @listID For ProcessShipment: The field indicates the country code listID. Set to 'Countries'. For SyncShipment: Set to 'Countries'. For SyncShipmentDelivery: Set to 'Countries' Shipment/ShipmentHeader/ShipToParty/Location/Address/PostalCode For ProcessShipment: For ProcessShipment: OCUSAD.OPPONO/ The field indicates a postal code. OCUSMA.OKPONO.; MWS410MI /GetAdr For SyncShipment: For SyncShipment: The field indicates a postal code. CIADDR.OAPONO OCUSAD.OPONO.; MWS410MI/LstAdr For SyncShipmentDelivery: The field indicates the postal code. For SyncShipmentDelivery: OOADRE.ODPNO CIADDR.OAPONO.; MWS410MI/GetAdr Shipment/ShipmentHeader/ShipToParty/Communication @preferredIndicator Set to 'false' Shipment/ShipmentHeader/ShipToParty/Communication/ChannelCode For SyncShipment: Set to 'Phone' if Telephone number (PHNO and PHN2) or Facsimile number (TFNO) is used in the DialNumber and 'EMail' if Email address (EMAL) is used in URI. For SyncShipmentDelivery: Set to "Phone" if telephone number or facsimile number. Set to "EMail" if e-mail address. @listID Set to 'Communication Channels'. Shipment/ShipmentHeader/ShipToParty/Communication/UseCode For SyncShipment: Set to 'Office' if Telephone number (PHNO and PHN2) is used in the DialNumber or email address (EMAL) is used in URI and 'Fax' if Facsimile number (TFNO) is used in the DialNumber. For SyncShipmentDelivery: Set to "Office" if telephone number or e-mail. Set to "Fax" if facsimile number. @listID Set to 'Communication Use Codes' Shipment/ShipmentHeader/ShipToParty/Communication/DialNumber For SyncShipment: For SyncShipment: OCUSMA.OKPHNO The field indicates the telephone number or the facsimile number.

OCUSMA.OKPHN2 OCUSMA.OKTFNO; CRS610MI/GetBasicData

OCUSAD.OPPHNO OCUSAD.OPTFNO; CRS610MI/GetAddress

MITWHL.MWPHNO; MMS005MI/GetWarehouse.; /

For SyncShipmentDelivery: OADRE.ODPHNO

OADRE.ODTFNO.; OIS100MI/GetAddress

For SyncShipmentDelivery:

The field indicates the telephone number or facsimile number.

Objects and Objects and Allered and Objects To Books (On account to Asia and Allered	
Shipment/ShipmentHeader/ShipToParty/Communication/URI CEMAIL.CBEMAL; CRS610MI/GetBasicData	For SyncShipment:
CEMAIL.CDEMAL, CR30 IUMI/GeldasicData	The field indicates the email address.
	The field indicates the email address.
	For SyncShipmentDelivery:
	The field indicates the e-mail address.
Shipment/ShipmentHeader/ShipToParty/Communication/Preference	Indicator
	For SyncShipmentDelivery:
	Set to 'false'.
Shipment/ShipmentHeader/ShipToParty/Contact/Communication/Pr	
	For SyncShipment: Set to 'false'.
Chinanaut/Chinanaut/Londow/DogwinodDolinaur/DotoTime	Set to Taise.
Shipment/ShipmentHeader/RequiredDeliveryDateTime For SyncShipmentDelivery:	For SyncShipmentDelivery:
OOHEAD.OARLDZ	The fields indicates the date and time when the customer wants the
OOHEAD.OARHDZ	delivery to arrive at the final destination.
.; OIS100MI/GetOrderHead	This is displayed only if Reference order category (RORC) is 3
	(Customer order).
Shipment/ShipmentHeader/ScheduledShipDateTime	
For SyncShipment:	For SyncShipment:
DCONSI.DARDDT DCONSI.DARDTM	The field indicates the date and time the order is to be shipped by the
DCONSI.DARDTM DCONSI.DADSDT	supplier. Planned Route departure date and time is used if it is set. Otherwise, planned Departure date and time for shipment is used.
DCONSI.DADSHM.; DRS100MI/GetShipment	Otherwise, planned Departure date and time for shipment is used.
2001101127120111111, 21 to 10011111 001011p.110111	For SyncShipmentDelivery:
For SyncShipmentDelivery:	The field indicates the actual ship date.
MHDISH.OQDSDT	
MHDISH.OQDSHM.; MWS410MI/GetHead	
Shipment/ShipmentHeader/RequiredShipDateTime	
For ProcessShipment:	For ProcessShipment:
MHDISH.OQDTDT MHDISH.OQDTHM ; MWS410MI/GetHead	The fields indicate the requested date and time.
MWOMAT.VMRDAT; PMS100MI/GetLine.; /	
Shipment/ShipmentHeader/PlannedDeliveryDateTime	
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MHDÍSH.OQDTDT	The field indicates the Requested Delivery Date and Time.
MHDISH.OQDTHM.; MWS410MI/GetHead	<u> </u>
Shipment/ShipmentHeader/PartialShipmentAllowedIndicator	
	For ProcessShipment:
	The field indicates if partial shipment is allowed. Set to 'true'.
Shipment/ShipmentHeader/PriorityCode	For Dragge Chinagent
For ProcessShipment: MHDISH.OQPRIO; MWS410MI/GetHead	For ProcessShipment: The field indicates the order priority.
Wil Diot. Oq. 100, WWo+10Wil/Oethlead	The field indicates the order priority.
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MHDISH.OQPRIO	The field indicates the priority of the delivery.
; MWS410MI/GetHead	
Shipment/ShipmentHeader/DestinationCountryCode	
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MHDISH.OQCSCD	The field indicates the country code.
; MWS410MI/GetHead @listID	
<u> </u>	For SyncShipmentDelivery:
	Set to 'Countries'.
Shipment/ShipmentHeader/PointOfStagingCode	
, , , , , , , , , , , , , , , , , , ,	For ProcessShipment:
	The value of this element is retrieved from agreement control property
	m3bePointOfStaging with default value PRODLINE1.
Shipment/ShipmentHeader/TransportationTerm/IncotermsCode	5 5 00
For ProcessShipment:	For ProcessShipment:
MHDISH.OQTEDF or OQTEDL; MWS410MI/GetHead	The field indicates the delivery terms.
For SyncShipmentDelivery: MHDISH.MQTEDL	Display TEDL only if TEDF is blank.
MHDISH.MQTEDF.	For SyncShipmentDelivery:
; MWS410MI/GetHead	The field indicates delivery terms, which define when the
	responsibility for a delivery is transferred from the supplier to the
	customer.
	Display Delivery terms (TEDL) only if Final delivery terms (TEDF) is empty.
	The value can be translated in CRS881/882. Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: IncotermsCode

@listID

Set to 'Incoterms'

Shipment/ShipmentHeader/TransportationTerm/PlaceOfOwnershipTransferLocation/Description

For SyncShipmentDelivery

CSYTAB.CTPARM; CRS065MI/GetDelyTerm

For SyncShipmentDelivery:

The field indicates when the liability for a delivery is transferred from

the supplier to the buyer.

Shipment/ShipmentHeader/TrackingID

For ProcessShipment:

MHDISH.OQETRN; MWS410MI/GetHead

For SyncShipmentDelivery: MHDISH.OQETRN

; MWS410MI/GetHead

For ProcessShipment:

The field indicates the external identification or the forwarder's

identification of a

delivery note, bill of lading, or package.

For SyncShipmentDelivery:

For ProcessShipment:

The field indicates the external identification, or the forwarder's identification, of a delivery note, bill of lading, or package

Shipment/ShipmentHeader/UserArea

1) OOHEAD.OAORTP; OIS100MI/GetOrderHead MGHEAD.MGTRTP; MMS100MI/GetHead

2) OOTYPE.OOORTK; OIS010MI/LstOrderTypes

3) MHDISH OOSHI V MWS410MI/GetHead.; /

For SyncShipment:

DCONSI.DACSTH; DRS100MI/GetShipment

For SyncShipmentDelivery:

1) ODHEAD.UAORST; OIS155MI/ListDeliveries

2) MHDISH.OQCONN; MWS410MI/GetHead

3) ODHEAD.UAORS1; OIS350MI/GetDelHead

4) MHDIGV.HDTLLP; MWS418MI/GetGovAppAct

5) MHDIGV.HDE0BH; MWS418MI/GetGovAppAct

6) MHDIGV.HDDRNA; MWS418MI/GetGovAppAct

7) MHDIGV.HDDRID; MWS418MI/GetGovAppAct

8) MHDIGV.HDDRLI; MWS418MI/GetGovAppAct

.; /

For ProcessShipment:

1) Order type

TRNR = RIDN.

The field indicates the Order type. If Property/NameValue = ORTP/ ORTY, set @name='OrderType'.

If TTYP = 31, use OIS100MI/GetOrderHead ORTP where input is

ORNO = RIDN. If TTYP = 41 or 51, use MMS100MI/GetHead TRTP where input is

2) Customer order category

The field indicates the Customer order category. If Property/ NameValue = ORTK, set @name='CustomerOrderCategory'.

1 - Normal Order 2 - Credit Order

4 - Quotation

5 - Cash Order

6 - Adjustment Order

9 - Bonus or Commission

C - Only Charges

3) Packing reporting method

The field indicates whether packing processing is used and how. If Property/NameValue = SHLV, set @name='m3.PackingReporting'.

0 - Not used

1 - Manual simple

2 - Manual advanced

3 - Auto when moved to packing location

4 - Auto when picking list is printed

For SyncShipment:

1) The field indicates the shipment highest status.

Set to 'Open' if shipment highest status is 0 or 10.

Set to 'Allocated' if shipment highest status is 20 or 30.

Set to 'Staged' if shipment highest status is 40. Set to 'Loaded' if shipment highest status is 50.

Set to 'Shipped' if shipment highest status is 60. Set to 'Cancelled' if shipment highest status is 90.

Set attribute name to 'HighestStatus'.

2) The field indicates the BOD Name.

Set to 'Shipment'.

Set attribute name to 'BODNoun'.

For SyncShipmentDelivery:

The field indicates the BOD Name, set to 'ShipmentDelivery'. Set attribute name to 'BODNoun'.

1) Highest status - customer order

The field indicates the customer order highest status.

If Reference order category (RORC) = 3 (Customer Order) and Delivery status (PGRS) >= 60 (Shipped), call OIS155MI LstDeliveries with FACI and CUNO as inputs. Check if DLIX from eventData is equal to DLIX from OIS155MI LstDeliveries. If it matches and ORST = 61, set UserArea/Property/

NameValue@name='SalesOrderDeliveryStatus' to 'Approval Required'.

2) Shipment number

The field indicates the Shipment number. If ShipmentDelivery is connected to Shipment, publish shipment number (CONN). Set attribute name to 'M3Shipment'.

3) Delivery approval required

The field indicates if delivery approval is required. If ORS1 = 1, set to 'true'. Otherwise, set to 'false'. Set attribute name to 'm3.ProofOfDelivery'.

4) Truck registration number

The field indicates the vehicle registration number. Set attribute name to 'lcl.VehiclePlateNumber'.

5) Trailer registration number

The field indicates the trailer registration number. Set attribute name to 'lcl.TrailerPlateNumber'.

6) Driver's name

The field indicates the driver's name. Set attribute name to "Icl.DriversName".

7) Driver's ID

The field indicates the driver's ID.
Set attribute name to 'lcl.DriversNationalIdNumber'.

8) Driver's license number

The field indicates the driver's license number. Set attribute name to 'lcl.DriversLicenseNumber'

Shipment/ShipmentHeader/SpecializedLogisticHeader/Reference @sequence

For ProcessShipment:

Set to '1'.

Shipment/ShipmentHeader/SpecializedLogisticHeader/Reference/NameValue

For ProcessShipment:

OOHEAD.OACUOR; MWS410MI/GetHead

For SyncShipmentDelivery:

DCONSI.DATRCA; MWS410MI/GetHead

For ProcessShipment:

The field indicates the customer's order number.

For SyncShipmentDelivery:

The field indicates transportation equipment which is the unique code identifying a specific mode of transportation. The code may for instance be the license number of a truck, the flight number of an aircraft etc.

For ProcessShipment:

Set to 'CustomerOrderNumber' if NameValue = CUOR.

For SyncShipmentDelivery:

If TRCA, set to 'TransportationEquipment'.

Shipment/ShipmentHeader/CustomerParty/PartyIDs/ID

For SyncShipment:

MHDISH.OQCONA; MWS410MI/LstAdr

For SyncShipmentDelivery:

.OQCONA; MWS410MI/GetAdr

MHDÍSH

@accountingEntity
For SyncShipment:

DCONSI.DACONO

DCONSI.DADIVI.; /

CMNDIV.CCDIVI.; /

For SyncShipmentDelivery: MHDISH.OQCONO

@name

For SyncShipment:

The field indicates the consignee. The field is only available for reference order category (RORC)= 3 - Sales Order.

For SyncShipmentDelivery:

The field indicates the customer.

This element is displayed if RORC = 3.Use ADRT = 10 as input.

For SyncShipment:

The field indicates the accounting entity.

If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO_DIVI), e.g. 760_AAA.

The field is only available for reference order category (RORC)= 3 - Sales Order.

For SyncShipmentDelivery:

The field indicates the accounting entity.

If CustomerPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO), e.g. 760. Otherwise, this is displayed as Company and Division (CONO DIVI), e.g. 760 AAA.

Shipment/ShipmentHeader/CustomerParty/PartyIDs/TaxID

For SyncShipment:

Infor May 26, 2023 58.

OCUSMA.OKVRNO:

CRS610/GetFinancial

CMNDIV.CCVRNO;

MNS100/GetBasicData.; /

For SyncShipmentDelivery: OCUSMA.OKVRNO; CRS610MI/GetFinancial

@schemeName

For SyncShipment:

The field indicates the Customer Party Tax ID.

For SyncShipmentDelivery:

The field indicates the VAT registration number.

Use CONA as input to CUNO.

For SyncShipment:

For SyncShipment:

Set to 'TaxIdentificationNumber'.

For SyncShipmentDelivery:

For SyncShipmentDelivery:

Set to 'TaxIdentificationNumber' if TaxID is VRNO

The field indicates the customer party name.

The field indicates the customer name.

Shipment/ShipmentHeader/CustomerParty/Name

For SyncShipment:

CIADDR.OAWHNM

OCUSMA.OKCUNM.; MWS410MI/LstAdr

For SyncShipmentDelivery:

OCUSMA.OKCUNM; MWS410MI/GetAdr

Shipment/ShipmentHeader/CustomerParty/Location/ID

For SyncShipment:

MHDISH.OQCONA; MWS410MI/LstAdr

For SyncShipmentDelivery:

MHDÍSH

.OQCONA; MWS410MI/GetAdr

@accountingEntity

DCONSI.DACONO

For SyncShipment:

DCONSI.DADIVI.; /

For SyncShipment:

The field indicates the consignee. The field is only available for

reference order category (RORC)= 5 - Distribution.

For SyncShipmentDelivery: The field indicates the location.

This element is displayed if RORC = 5.Use ADRT = 10 as input.

For SyncShipment:

The field indicates the company and division, displayed as

CONO_DIVI. The field is only available for reference order category

(RORC)= 5 - Distribution.

E.g. 760_AAA

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

CONO DIVI

Shipment/ShipmentHeader/CustomerParty/Location/Address @type

Shipment/ShipmentHeader/CustomerParty/Location/Address/AttentionOfName

For SyncShipmentDelivery:

OCUSMA

.OKYREF; MWS410MI/GetHead

Set to 'text'

For SyncShipmentDelivery:

The field indicates the address line.

The field indicates the customer's contact person.

Shipment/ShipmentHeader/CustomerParty/Location/Address/AddressLine

For SyncShipment: CIADDR.OAADR1

CIADDR.OAADR2

CIADDR.OAADR3

CIADDR.OAADR4

OCUSMA.OKADR1

OCUSMA.OKADR2

OCUSMA.OKADR3

OCUSMA.OKADR4.; MWS410MI/LstAdr

For SyncShipmentDelivery:

OOADRE.ODCUA1

OOADRE.ODCUA2

OOADRE.ODCUA3 OOADRE.ODCUA4

CIADDR.OAADR1

CIADDR.OAADR2

CIADDR.OAADR3 CIADDR.OAADR4

.; MWS410MI/GetAdr

@sequence

The field indicates the address line sequence

Shipment/ShipmentHeader/CustomerParty/Location/Address/CityName

For SyncShipment:

CIADDR.OATOWN

OCUSMA.OKTOWN.; MWS410MI/LstAdr

For SyncShipment: The field indicates the city name.

For SyncShipmentDelivery:

OOADRE.ODTOWN

or

CIADDR.OATOWN.; MWS410MI/GetAdr

Shipment/ShipmentHeader/CustomerParty/Location/Address/CountrySubDivisionCode

For SyncShipment: CIADDR.OAECAR

OCUSMA.OKECAR.; MWS410MI/LstAdr

For SyncShipmentDelivery: OOADRE.ODECAR

CIADDR.OAECAR.; MWS410MI/GetAdr

@listID

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries.

The field indicates an area, province or state within a country.

Set to "SubDivisions" if no Country is specified

For SyncShipmentDelivery:

The field indicates the city.

Shipment/ShipmentHeader/CustomerParty/Location/Address/CountryCode

For SyncShipment: CIADDR.OACSCD

OCUSMA.OKCSCD.; MWS410MI/LstAdr

For SyncShipmentDelivery: OOADRE.ODCSCD

CIADDR.OACSCD.; MWS410MI/GetAdr

@listID

Set to 'Countries'

Shipment/ShipmentHeader/CustomerParty/Location/Address/PostalCode For SyncShipment: For SyncShipment:

CIADDR.OAPONO

OCUSMA.OKPONO.; MWS410MI/LstAdr

For SyncShipmentDelivery:

OOADRE.ODPNO

or

@listID

CIADDR.OAPONO.; MWS410MI/GetAdr

Shipment/ShipmentHeader/CustomerParty/Communication

@preferredIndicator

Set to 'false'

Shipment/ShipmentHeader/CustomerParty/Communication/ChannelCode

For SyncShipment:

For SyncShipment:

The field indicates a country.

For SyncShipmentDelivery:

The field indicates the country code.

The field indicates a postal code.

The field indicates the postal code.

For SyncShipmentDelivery:

Set to 'Phone' if Telephone number (PHNO and PHN2) or Facsimile number (TFNO) is used in the DialNumber and 'EMail' if Email

address (EMAL) is used in URI.

For SyncShipmentDelivery:

Set to "Phone" if telephone number or facsimile number.

Set to "EMail" if e-mail address

Set to 'Communication Channels'

Shipment/ShipmentHeader/CustomerParty/Communication/UseCode

For SyncShipment:

Set to 'Office' if Telephone number (PHNO and PHN2) is used in the DialNumber or email address (EMAL) is used in URI and 'Fax' if

Facsimile number (TFNO) is used in the DialNumber.

For SyncShipmentDelivery:

Set to "Office" if telephone number or e-mail.

Set to "Fax" if facsimile number.

@listID Set to 'Communication Use Codes'

Shipment/ShipmentHeader/CustomerParty/Communication/DialNumber For SyncShipment:

For SyncShipment:

OCUŚMA.OKPHNO OCUSMA.OKPHN2 OCUSMA.OKTFNO; CRS610MI/GetBasicData

The field indicates the telephone number or the facsimile number.

For SyncShipmentDelivery:

The field indicates the telephone number or facsimile number.

MITWHL.MWPHNO;

MMS005MI/GetWarehouse.; /

For SyncShipmentDelivery: OCUŚMA.OKPHNO

OCUSMA.OKTFNO: CRS610MI/GetBasicData

MITWHL.MWPHNO;

MMS005MI.GetWarehouse.; /

Shipment/ShipmentHeader/CustomerParty/Communication/URI

CEMAIL.CBEMAL; CRS610MI/GetBasicData

For SyncShipment:

The field indicates the email address.

For SyncShipmentDelivery:

The field indicates the e-mail address

Shipment/ShipmentHeader/CustomerParty/Communication/Preference/Indicator

Set to 'false'

Shipment/ShipmentHeader/CustomerParty/Contact

@type

For SyncShipmentDelivery:

For SyncShipmentDelivery:

CCUCON.CCRFTP; CRS618MI/Get The field indicates the contact type that can be used for

categorization of contacts.

For SyncShipmentDelivery:

The field indicates the contact.

Shipment/ShipmentHeader/CustomerParty/Contact/ID

For SyncShipmentDelivery:

CCUCON.CCCNPE; CRS618MI/Get

@accountingEntity

For SyncShipmentDelivery:

For SyncShipmentDelivery: MHDÍSH.OQCONO

The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI.

Shipment/ShipmentHeader/CustomerParty/Contact/Name

For SyncShipmentDelivery: For SyncShipmentDelivery:

CCUCON.CCTX50; CRS618MI/Get The field indicates the contact name

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/ChannelCode

For SyncShipmentDelivery:

Set to 'Phone' if telephone number 1 or telephone number 2.

Set to 'EMail' if e-mail address.

@listID For SyncShipmentDelivery:

Set to 'Communication Channels'

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/UseCode

For SyncShipmentDelivery:

For SyncShipmentDelivery:

Set to 'Office' if telephone number 1, telephone number 2 or e-mail

address.

Set to 'Communication Use Codes'

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/DialNumber

For SyncShipmentDelivery: For SyncShipmentDelivery:

CCUĆON.CCPHNO CCUCON.CCPHN2 ; CRS618MI/Get

The field indicates the telephone number 1 or telephone number 2.

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address

@tvpe

@listID

For SyncShipmentDelivery:

Set to 'text'

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address/AddressLine

For SyncShipmentDelivery: For SyncShipmentDelivery: CCUCON.CCCUA1 The field indicates the address line.

CCUCON.CCCUA1 CCUCON.CCCUA1 CCUCON.CCCUA1

: CRS618MI/Get

@sequence

For SyncShipmentDelivery:

The field indicates the address line sequence

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address/CityName

For SyncShipmentDelivery: For SyncShipmentDelivery: CCUCON.CCTOWN The field indicates the city.

CRS618MI/Get

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address/CountrySubDivisionCode

For SyncShipmentDelivery: For SyncShipmentDelivery:

CCUCON.CCECAR The field indicates an area, province or state within a country.

CRS618MI/Get

@listID For SyncShipmentDelivery:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States).

Set to 'SubDivisions - < Country Code>' for other countries.

Set to "SubDivisions" if no country is specified

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address/CountryCode

For SyncShipmentDelivery: For SyncShipmentDelivery: CCUCON.CCCSCD The field indicates the country code.

; CRS618MI/Get

@listID

For SyncShipmentDelivery:

Set to 'Countries'

For SyncShipment:

company and division.

For SyncShipmentDelivery:

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/Address/PostalCode

For SyncShipmentDelivery: For SyncShipmentDelivery: CCUCON.CCPONO The field indicates the postal code. CRS618MI/Get

Shipment/ShipmentHeader/CustomerParty/Contact/Communication/URI

For SyncShipmentDelivery: For SyncShipmentDelivery:

CCUCON.CCEMAL The field indicates the e-mail address.

CRS618MI/Get

Shipment/ShipmentHeader/SupplierParty/PartyIDs/ID

For SyncShipment: CMNDIV.CCCONO

CMNDIV.CCDIVI.; MNS100MI/GetBasicData

For SyncShipmentDelivery:

CMNĎIV.CCONO CMNDIV.CCDIVI.; /

@accountingEntity

For SyncShipment:

DCONSI.DACONO

DCONSI.DADIVI.; /

For SyncShipmentDelivery:

MHDISH.OQCONO

CMNDIV.CCDIVI.; /

CONO DIVI. E.g. 760_AAA

For SyncShipment:

separator.

For SyncShipmentDelivery:

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

CONO DIVI.

Shipment/ShipmentHeader/SupplierParty/PartyIDs/TaxID

For SyncShipment: CMNDIV.CCVRNO

CCVRNL; MNS100MI/GetBasicData

For SyncShipmentDelivery: 1) CMNDIV.CCVRNO MNS100MI.GetBasicData

2) CMNDIV.CCVRNL

MNS100MI.GetBasicData.; /

@schemeName

For SyncShipment:

The field indicates the Supplier party Tax ID which is the Supplier's

The field indicates the Supplier party ID, which is the concatenation of

The field indicates the concatenation of company and division without

VAT registration number or Tax Declaration number.

For SyncShipmentDelivery: 1) VAT registration number

The field indicates the VAT registration number. Set to 'TaxIdentificationNumber' if TaxID is VRNO.

2) Tax Declaration number

The field indicates the Tax declaration number. Set to 'TaxDeclarationNumber' if TaxID is VRNL.

For SyncShipment:

Set to 'TaxIdentificationNumber' or 'TaxDeclarationNumber'.

For SyncShipmentDelivery:

1) Set to 'TaxIdentificationNumber' if TaxID is VRNO. 2) Set to 'TaxDeclarationNumber' if TaxID is VRNL

Shipment/ShipmentHeader/SupplierParty/Name

CMNDIV.CCCONM; MNS100MI/GetBasicData

The field indicates the company name

Shipment/ShipmentHeader/SupplierParty/Location/Address

@type

Set to 'text'.

Shipment/ShipmentHeader/SupplierParty/Location/Address/AddressLine

For SyncShipment: CMNDIV.CCCOA1

CMNDIV.CCCOA2 CMNDIV.CCCOA3

CMNDIV.CCCOA4.; MNS100MI/GetBasicData

For SyncShipmentDelivery:

CMNDIV.CCCOA1, CCCOA2, CCCOA3, CCCOA4; MNS100MI/

GetBasicData

@seauence

The field indicates the address line

The field indicates the address line sequence

Shipment/ShipmentHeader/SupplierParty/Location/Address/CityName

For SyncShipment:

CMNDIV.CCTOWN; MNS100MI/GetBasicData

The field indicates the city name.

For SyncShipmentDelivery:

CMNĎIV.CMTOWN; MNŚ100MI/GetBasicData

Shipment/ShipmentHeader/SupplierParty/Location/Address/CountrySubDivisionCode

For SyncShipment:

The field indicates an area, province or state within a country.

CMNDIV.CCECAR; MNS100MI/GetBasicData

For SyncShipmentDelivery:

CMNDIV.CMECAR; MNS100MI/GetBasicData

@listID

For SyncShipment:

Set to 'Canadian Provinces' if the country is CA (Canada). Set to 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States) Set to 'SubDivisions - <Country Code>' for other countries.

Set to "SubDivisions" if no Country is specified.

For SyncShipmentDelivery:

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <Country Code>' for other countries. Set to "SubDivisions" if no Country is specified.

Shipment/ShipmentHeader/SupplierParty/Location/Address/CountryCode

For SyncShipment: For SyncShipment:

CMNDIV.CCCSCD; MNS100MI/GetBasicData The field indicates a country.

For SyncShipmentDelivery: For SyncShipmentDelivery:

CMNDIV.CMCSCD; MNS100MI/GetBasicData The field indicates the country code.

@listID

@listID

@listID

Set to 'Countries'

Shipment/ShipmentHeader/SupplierParty/Location/Address/PostalCode

For SyncShipment: For SyncShipment:

CMNDIV.CCPONO: MNS100MI/GetBasicData The field indicates a postal code.

For SyncShipmentDelivery: For SyncShipmentDelivery: CMNDIV.CMPONO; MNS100MI/GetBasicData The field indicates the postal code

Shipment/ShipmentHeader/SupplierParty/Communication

@preferredIndicator

For SyncShipmentDelivery:

Set to 'false'

Shipment/ShipmentHeader/SupplierParty/Communication/ChannelCode

For SyncShipmentDelivery:

For SyncShipmentDelivery:

Set to "Phone" if telephone number.

Set to 'Communication Channels'.

Shipment/ShipmentHeader/SupplierParty/Communication/UseCode

For SyncShipmentDelivery:

For SyncShipmentDelivery: Set to 'Communication Use Codes'

Set to "Office" if telephone number.

Shipment/ShipmentHeader/SupplierParty/Communication/DialNumber For SyncShipmentDelivery: For SyncShipmentDelivery:

CMNDIV.CCCONM; MNS100MI/GetBasicData The field indicates the telephone number.

Shipment/ShipmentHeader/SupplierParty/Communication/Preference/Indicator

For SyncShipmentDelivery:

Set to 'false'.

Shipment/ShipmentItem/ItemID/ID

For ProcessShipment: For ProcessShipment:

MITALO.MQITNO; MWS422MI/LstPickDetail This field pertains to the Item Numbers belonging to the Shipment. MWOMAT.VMMTNO; PMS100MI/GetLine.; /

For SyncShipment:

For SyncShipment: The field indicates the item numbers that belong to the shipment. MFTRNS.MQITNO

; MWS410MI/LstItem For SyncShipmentDelivery:

The field indicates the item number within the shipment.

For SyncShipmentDelivery: MFTRNS.OSITNO:

If agreement control property m3beGetShipmentItemFromDelivery is

MWS423MI/LstContents set to 'true', MWS411MI.LstDeliveryLine instead of

MWS423MI.LstContents is called for the looping of the ShipmentItem MHDISL.URITNO;

level.

MWS411MI.LstDeliveryLine.; /LstContents

@accountingEntity For ProcessShipment: For ProcessShipment:

The field indicates the accounting entity. MHDISH.QCCONO

For SyncShipment:

DCONSI.DACONO

If ItemMaster is enabled in BOD Processor Master AE tab. this is displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

DCONSI.DADIVI.; /

For SyncShipmentDelivery: MHDÍSH.OQCONO CMNDIV.CCDIVI.; /

For SyncShipment:

The field indicates the accounting entity. If ItemMaster is enabled in BOD Processor Master AE tab, this is

displayed as Company (CONO). Otherwise, this is displayed as

Company and Division (CONO DIVI).

For SyncShipmentDelivery:

The field indicates the accounting entity.

If ItemMaster MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

Shipment/ShipmentItem/Description

MITMAS.MMITDS; MWS423MI/LstContents

For SyncShipment: MFTRNS.MQITDS ; MWS410MI/LstItem For SyncShipment:

The field indicates the description of the item.

For SyncShipmentDelivery:

The field indicates the item description.

For SyncShipmentDelivery: Shipment/ShipmentItem/Note

For ProcessShipment: 1) MGLINE.MRBREM; MMS100MI/GetLine

2) OIS100MI/LstLineText.; /

For ProcessShipment:

1) The field indicates the remark.

Use the following values from MWS422MI/LstPickDetail as input to

MMS100MI/GetLine: RIDN = <TRNR> PONR = <RIDL> POSX = <RIDX>

2) The field indicates the text or note. Call OIS100MI.LstLineText only if TTYP=31.

Use the following inputs: ORNO = <RIDN> PONR = <RIDL>

TYTR = 1/2

@noteID

For ProcessShipment: .: OIS100MI/LstLineText For ProcessShipment: The field indicates the text block.

Call OIS100MI.LstLineText only if TTYP=31.

@use

@type

For ProcessShipment:

CSYTXH.THTXEI; CRS980MI/LstTxtBlocks

For ProcessShipment:

The field indicates the external/internal text.

If TXEI=0/1, set to External. If TXEI=2, set to Internal. Use the following as inputs: CONO = <CONO>

TXID = <OIS100MI.LstLineText TXID>

TFIL = OSYTXH

For ProcessShipment: For ProcessShipment: .; OIS100MI/LstLineText

The field indicates the text or note type.

If TYTR=1, set to 'Pre-text'. If TYTR=2, set to 'Post-text'.

Call OIS100MI.LstLineText only if TTYP=31.

Shipment/ShipmentItem/Classification/Codes/Code

For ProcessShipment: 1) MITALO.MQTWSL; MWS422MI/LstPickDetail 2) MWOOPE.VOPLGR; PMS100MI/GetOperation 3) MITALO MQPLRN MWS422MI/LstPickDetail.; / For ProcessShipment: 1) To location (TWSL)

The field indicates the receiving location. Set attribute listID to 'To Location'.

For SyncShipmentDelivery:

1) OOLINE.OBTEPY; OIS100MI/GetLine2 2) MITFAC.M9CSNO: MMS200MI/GetItmFac.; / 2) Work center of the material line (PLGR)

The field indicates the work center, which is a resource in which labor

operations are performed.

Set attribute listID to 'Work Center'.

3) Reporting number - pick line (PLRN)

The field indicates the ID of a specific picking list line.

Set attribute listID to 'Reporting Number'.

For SyncShipmentDelivery:

1) The field indicates the payment terms. Set attribute listID to 'Payment Term'.

2) The field indicates the customs statistical number.

Set attribute listID to 'CommodityCodes'.

For ProcessShipment:

The field indicates the operation number of the work center.

@sequence

For ProcessShipment:

MWOOPE.VOOPNO; PMS100MI/GetOperation

=	_	-	_	_	_
$\overline{}$	1:		.,	_	

For ProcessShipment:

1) Set to 'To Location' for TWSL. 2) Set to 'Work Center' for PLGR. 3) Set to 'Reporting Number' for PLRN.

The field indicates the ordered quantity.

For SyncShipmentDelivery:

For ProcessShipment:

1) If Code=TEPY, set listID to 'Payment Term'. 2) If Code=CSNO, set listID to 'CommodityCodes'.

Shipment/ShipmentItem/OrderQuantity

For ProcessShipment:

For ProcessShipment:

For SyncShipmentDelivery: MITMAS.MMUNMS;

MMS200MI/GetItmBasic.; /

MWS423MI/LstContents

MITALO.MQTRQT; MWS422MI/LstPickDetail MWOMAT.VMREQA; PMS100MI/GetLine.; /

CSYTAB.CTPARM; MWS422MI/LstPickDetail

For SyncShipmentDelivery:

MHDISL

@unitCode

or

@unitCode

.URTRQT; MWS411MI/LstDeliveryLine

indicates the reserve quantity.

For SyncShipmentDelivery: The field indicates the quantity.

For ProcessShipment:

The field indicates the basic unit of measure.

For SyncShipmentDelivery:

The field indicates the basic unit of measure if quantity is retrieved

If the Shipment BOD is for manufacturing order material with issue

method not picking list (triggered through table MWOMAT), the field

If m3beGetShipmentItemFromDelivery is set to true, call

MMS200MI.GetItmBasic UNMS if MWS423MI.LstContents does not

return a record.

Shipment/ShipmentItem/ShippedQuantity

For ProcessShipment:

MWOMAT.VMRPQA; PMS100MI/GetLine

For SyncShipment: MFTRNS.MQTRQT ; MWS410MI/LstItem

For SyncShipment:

MITMAS.MMUNMS

; MWS410MI/LstItem

For SyncShipmentDelivery:

For SyncShipmentDelivery:

MFTRNS.OSDLQA; MWS423MI/LstContents

For ProcessShipment:

The field indicates the shipped quantity.

For SyncShipment:

The field indicates the delivered quantity.

For SyncShipmentDelivery:

The field indicates delivered quantity expressed in alternate unit of

measure.

If agreement control property m3beGetShipmentItemFromDelivery

and PGRS <= 50, this element is not displayed.

For SyncShipment:

The field indicates the unit of measure.

For SyncShipmentDelivery:

The field indicates the alternate unit of measure.

If agreement control property m3beGetShipmentItemFromDelivery

and PGRS <= 50, this element is not displayed

Shipment/ShipmentItem/ShippedBaseUOMQuantity

MITMAS.MMALUN; MWS423MI/LstContents

For SyncShipment: MFTRNS.MQTRQT

; MWS410MI/LstItem

For SyncShipment:

MITMAS.MMUNMS

; MWS410MI/LstItem

For SyncShipmentDelivery:

MFTRNS.OSDLQT; MWS423MI/LstContents

For SyncShipment:

The field indicates the delivered quantity.

For SyncShipmentDelivery:

The field indicates the delivered quantity expressed in basic unit of

measure.

If agreement control property m3beGetShipmentItemFromDelivery

and PGRS <= 50. this element is not displayed.

For SyncShipment:

The field indicates the unit of measure.

For SyncShipmentDelivery:

The field indicates the basic unit of measure.

If agreement control property m3beGetShipmentItemFromDelivery

and PGRS <= 50, this element is not displayed

Shipment/ShipmentItem/LoadingWeightMeasure

MITMAS.MMUNMS; MWS423MI/LstContents

For SyncShipmentDelivery:

For SyncShipmentDelivery:

MITMAS.MMGRWE; MWS423MI/LstContents

@unitCode

@unitCode

For SyncShipmentDelivery:

CSYTAB.CTPARM; CRS175MI/GetItmFreeField

For SyncShipmentDelivery:

The field indicates the estimated gross weight packed.

For SyncShipmentDelivery:

The field indicates the weight unit of measure

Shipment/ShipmentItem/PurchaseOrderReference/DocumentID/ID

For SyncShipmentDelivery: For SyncShipmentDelivery:

MFTRNS.OSRIDN; MWS423MI/LstContents The field indicates the purchaseorder document ID.

For SyncShipmentDelivery:

For SyncShipmentDelivery:

For SyncShipmentDelivery:

For ProcessShipment:

For SyncShipment:

The field indicates the line suffix

The field indicates an order number.

The field indicates an order number.

For SyncShipmentDelivery:

For SyncShipmentDelivery:

The field indicates the warehouse ID.

characters will be the line suffix (RIDX).

The field indicates the order line number

For ProcessShipment:

For SyncShipment:

CONO_DIVI.

CONO DIVI.

E.g. 760_AAA

CONO DIVI.

Display for transaction type 31 (SalesOrder).

The field indicates the sales order number.

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

The field indicates the company and division, displayed as

The field indicates the order line number and line suffix. The last 3

The field indicates the warehouse ID.

The field indicates the order line number.

@accountingEntity

For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

For SyncShipmentDelivery: The field indicates the company and division, displayed as CONO DIVI.

@location

For SyncShipmentDelivery: MHDISH.OQWHLO; MWS411MI/GetDeliveryLine

Shipment/ShipmentItem/PurchaseOrderReference/LineNumber For SyncShipmentDelivery:

MFTRNS.OSRIDL; MWS423MI/LstContents

Shipment/ShipmentItem/PurchaseOrderReference/SubLineNumber For SyncShipmentDelivery:

MFTRNS.OSRIDX; MWS423MI/LstContents

Shipment/ShipmentItem/SalesOrderReference/DocumentID/ID

For ProcessShipment:

MITALO.MQRIDN; MWS422MI/LstPickDetail

For SyncShipment: MHDÍSH.OQRIDN

; MWS410MI/GetHead

For SyncShipmentDelivery:

MFTRNS.OSRIDN; MWS423MI/LstContents

@accountingEntity For ProcessShipment: MHDISH.QCCONO

CMNDIV.CCDIVI.; /

For SyncShipment: DCOŃSI.DACONO DCONSI.DADIVI.; /

For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

@location

For SyncShipment:

MHDISH.OQWHLO; MWS410MI/GetHead

For SyncShipmentDelivery:

MHDISH.OQWHLO; MWS411MI/GetDeliveryLine

Shipment/ShipmentItem/SalesOrderReference/LineNumber

Shipment/ShipmentItem/SalesOrderReference/SubLineNumber

For ProcessShipment: MITALO.MQRIDL

MITALO.MQRIDX.; MWS422MI/LstPickDetail

For SyncShipmentDelivery:

MFTRNS.OSRIDL; MWS423MI/LstContents

For SyncShipmentDelivery:

MFTRNS.OSRIDX; MWS423MI/LstContents Shipment/ShipmentItem/DocumentReference

For ProcessShipment:

MITALO.MQTTYP; MWS422MI /LstPickDetail

For SyncShipmentDelivery:

MFTRNS.OSRORC; MWS423MI/LstContents

For ProcessShipment:

For ProcessShipment:

For SyncShipmentDelivery:

For SyncShipmentDelivery: The field indicates the line suffix.

The field indicates the type of dcoument reference.

11 - ProductionOrder 31 - SalesOrder

41 - SupplierRMA 51 - Transfer

61 - ServiceOrder

If the Shipment BOD is for manufacturing order material with issue method not picking list (triggered through table MWOMAT), the field is set to PoductionOrder.

For SyncShipmentDelivery:

The field indicates the origin of the reference order category (RORC).

If RORC = 1, set to 'ProductionOrder'. If RORC = 2, set to 'PurchaseOrder'. If RORC = 3, set to 'SalesOrder'.

Silipilielit	
	If RORC = 4, set to 'Transfer'.
	If RORC = 5, set to 'Transfer'.
	If RORC = 6, set to 'WorkOrder'.
	If RORC = 7, set to 'ServiceOrder'.
	If RORC = 8, set to 'ProjectMaster'.
	If RORC = 9, set to 'SupplierRMA'.
Shipment/ShipmentItem/DocumentReference/DocumentID/ID	
For ProcessShipment:	For ProcessShipment:
MITALO.MQRIDN; MWS422MI/LstPickDetail	The field indicates an order number.
MWOMAT.VMMFNO; PMS100MI/GetLine.; /	
	For SyncShipmentDelivery:
For SyncShipmentDelivery:	The field indicates the order number.
MFTRNS.MQRIDN; MWS423MI/LstContents	
@accountingEntity	
For ProcessShipment:	For ProcessShipment:
MHDISH.QCCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO_DIVI.
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MHDISH.OQCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI	CONO_DIVI.
;;/ Oherstore	
@location	For Process Chipments
For ProcessShipment:	For ProcessShipment:
MWOMAT.VMWHLO; PMS100MI/GetLine	The filed indicates the warehouse.
Shipment/ShipmentItem/DocumentReference/LineNumber	T I C. I. C. A. C.
For ProcessShipment:	The field indicates the order line number.
MITALO.MQRIDL; MWS422MI/LstPickDetail	
MWOMAT.VMMSEQ; PMS100MI/GetLine.; /	
For SyncShipmentDelivery:	
MFTRNS.OSRIDN; MWS423MI/LstContents	
Shipment/ShipmentItem/DocumentReference/SubLineNumber	Fan Our - Obia - and Dalis - and
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MFTRNS.OSRIDX; MWS423MI/LstContents	The field indicates the line suffix.
Shipment/ShipmentItem/ExtendedSalePriceAmount	
For SyncShipmentDelivery:	For SyncShipmentDelivery:
.; MWS418MI/BODMIDelLines	The field indicates the sales price.
@currencyID	Fan Our - Obia - and Dalis - and
For SyncShipmentDelivery: .; MWS418MI/BODMIDelLines	For SyncShipmentDelivery: The field indicates the currency.
· · · · · · · · · · · · · · · · · · ·	The field indicates the currency.
Shipment/ShipmentItem/ExtendedSalePriceBaseAmount	Far Cum a Chin ma and Dalis sam s
For SyncShipmentDelivery:	For SyncShipmentDelivery:
.; MWS418MI/BODMIDelLines	The field indicates the sales price in local currency.
@currencyID For SyncShipmentDelivery:	For SyncShipmentDelivery:
; MWS418MI/BODMIDelLines	The field indicates the local currency.
	The field indicates the local currency.
Shipment/ShipmentItem/ExtendedSalePriceReportAmount	Fan Our - Obia - and Dalis - and
For SyncShipmentDelivery:	For SyncShipmentDelivery:
.; MWS418MI/BODMIDelLines	The field indicates the sales price in report currency.
@currencyID For SyncShipmentDelivery:	For SyncShinmentDelivery
For SyncShipmentDelivery: .; MWS418MI/BODMIDelLines	For SyncShipmentDelivery: The field indicates the report currency.
	The hold indicates the report currency.
Shipment/ShipmentItem/UserArea	For Process Shipment
For ProcessShipment: MWOMAT.VMRPQA; PMS100MI/GetLine	For ProcessShipment: The field indicates the reported quantity if
IVIVVOIVIAT. VIVIIAE QA, EIVIO TUUIVII/GELLIITE	nameValue@name='TransactionQuantity'.
Chinmon4(Chinmon4(40m/0	пать у аносупать — ттанзасноподианиту.
Shipment/Shipment/tem/SerializedLot/ItemQuantity	For CynoChinmont
For SyncShipment: MFTRNS.OSDLQT	For SyncShipment:
; MWS410MI/Lstitem	The field indicates the delivered quantity, expressed in the item's basic U/M.
, IVIVYOT IOIVII/LOUIGIII	Dagio U/IVI.
For SyncShipmentDelivery:	For SyncShipmentDelivery:
MFTRNS.OSDLQA; MWS423MI/LstContents	The field indicates delivered quantity expressed in alternate unit of
,	measure.
@unitCode	
For SyncShipment:	For SyncShipment:
MITMÁS.MMUNMS	The field indicates the unit of measure.
; MWS410MI/LstItem	
	For SyncShipmentDelivery:
For SyncShipmentDelivery:	The field indicates the alternate unit of measure.
MITMAS.MMALUN; MWS423MI/LstContents	
Shipment/ShipmentItem/SerializedLot/Lot/Lot/Ds/ID	
For ProcessShipment:	For ProcessShipment:
MITALO.MQBANO; MWS422MI/LstPickDetail	The field indicates the lot number, which is an ID of a manufactured
	or purchased

For SyncShipmentDelivery:

MWS410MI/LstPackageLine.; /

MFTRNS.OSPANR;

For SyncShipmentDelivery: quantity of an item. All units included in a lot have the same MITTRA.MTBANO characteristics. MWS070MI/LstTransByOrder Use only if INDI = 1, 3. MFTRNS.OSBANO; MWS423MI/LstContents. For SyncShipmentDelivery: The field indicates the lot number. Shipment/ShipmentItem/SerializedLot/Lot/Quantity For SyncShipmentDelivery: For SyncShipmentDelivery: MFTRNS.OSDLQT; MWS423MI/DLQT The field indicates the delivered quantity, expressed in the item's basic U/M. @unitCode For SyncShipmentDelivery: For SyncShipmentDelivery: MITMAS.MMUNMS; MWS423MI/LstContents The field indicates the unit in which each item is recorded in inventory, even if alternate inventory units of measure are used Shipment/ShipmentItem/SerializedLot/Lot/SerialNumber For ProcessShipment: For ProcessShipment: MITALO.MQBANO; MWS422MI/LstPickDetail The field indicates the serial number. Display only if INDI=2. Shipment/ShipmentItem/SerializedLot/SerialNumber For SyncShipmentDelivery: For SyncShipmentDelivery: MITTRA.MTBANO The field indicates the lot number. MWS070MI/LstTransByOrder MFTRNS.OSBANO; MWS423MI/LstContents.; / Shipment/ShipmentItem/LineNumber For ProcessShipment: For ProcessShipment: MITALO.MQRIDL; MWS422MI/LstPickDetail The field indicates the line number in increments of 1. For SyncShipment: The field indicates the line number. This is an incrementing number starting from 1. For SyncShipmentDelivery: The field indicates the line number which is an incrementing number starting from 1. Shipment/ShipmentItem/WeightMeasure For SyncShipmentDelivery: For SyncShipmentDelivery: MHDISL.URNEWE; MWS411MI/GetDeliveryLine The field indicates the net weight per basic U/M for an order line. @unitCode For SyncShipmentDelivery: For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds The field indicates the unit code. Shipment/ShipmentItem/VolumeMeasure For SyncShipmentDelivery: For SyncShipmentDelivery: MHDISL.URVOL3; MWS411MI/GetDeliveryLine The field indicates the volume per basic U/M for an order line. For SyncShipmentDelivery: For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds The field indicates the volume unit code Shipment/ShipmentItem/SpecializedLogisticItem/Reference @sequence For ProcessShipment: Set to '1' Shipment/ShipmentItem/SpecializedLogisticItem/Reference/NameValue For ProcessShipment: For ProcessShipment: OOLINE.OBCUOR; OIS100MI/GetLine The field indicates the customer's order number. Use RIDN as input to ORNO, RIDL as input to PONR and RIDX as For SyncShipment: input to POSX. Call only if TTYP = 31. OCUSMA.OKCUSU ; MWS410MI/GetHead For SyncShipment: The field indicates the supplier number at customer. @name For ProcessShipment: Set to 'CustomerOrderNumber' if NameValue = CUOR. For SyncShipment: Set to 'ExternalSupplierNumber'. Shipment/ShipmentUnit/TrackingID For SyncShipment: For SyncShipment: MHDISH.OQDLIX The field indicates the delivery number. ; DRS100MI/LstByDelivery

May 26, 2023

For SyncShipmentDelivery:

The field indicates the identity of a package.

If agreement control property m3beShipmentUnitPerPackage is set to

Silipilient	true, MWS423MI.LstPackDel is called instead of MWS410MI.LstPackageLine for the ShipmentUnit loop. This will display the package structure in the BOD.
Shipment/ShipmentUnit/ContainerID	alopia, are pastage ordetale in the DOD.
For SyncShipmentDelivery: MFTRNS .OSCAMU; MWS410MI/LstPackageLine	For SyncShipmentDelivery: The field indicates the ID of the packaging, and is defined in (MMS050).
	(MIMSOSO).
Shipment/ShipmentUnit/TareWeightMeasure For SyncShipmentDelivery: MITPAC.M4VOMT; MMS050MI/GetPackaging	For SyncShipmentDelivery: The field indicates the tare weight of the package or container.
<pre>@unitCode For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds</pre>	For SyncShipmentDelivery: The field indicates the unit code.
Shipment/ShipmentUnit/NetWeightMeasure	
For SyncShipment: MHDISH.OQNEW2 ; MWS410MI/GetHead	For SyncShipment: The field indicates the total weight of all items entered on the customer order.
For SyncShipmentDelivery: MFTRNS.OSNEWE; MWS410MI/LstPackageLine or	For SyncShipmentDelivery: The field indicates the net weight.
MPTRNS.ORNEWE; MWS423MI/LstPackDel.; / @unitCode	
For SyncShipment: CSYTAB.CTPARM ; CRS175MI/GetItemFreeFlds	For SyncShipment: The field indicates the general unit of measure for all weights within a company.
For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For SyncShipmentDelivery: The field indicates the unit code.
Shipment/ShipmentUnit/GrossWeightMeasure	
For SyncShipment: MHDISH.OQGRW2 ; MWS410MI/GetHead	For SyncShipment: The field indicates the total weight for all items that have been entered on the order.
For SyncShipmentDelivery: MFTRNS.OSGRWE; MWS410MI/LstPackageLine	For SyncShipmentDelivery: The field indicates the gross weight.
or MPTRNS.ORGRWE; MWS423MI/LstPackDel.; / @unitCode	
For SyncShipment:	For SyncShipment:
CSYTAB.CTPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for all weights within a company.
For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For SyncShipmentDelivery: The field indicates the unit code.
Shipment/ShipmentUnit/TotalVolumeMeasure	For Our Ohion out
For SyncShipment: MHDISH.OQVM32 ; MWS410MI/GetHead	For SyncShipment: The field indicates the volume for each item in the item file or for undelivered order lines for a customer order.
For SyncShipmentDelivery: MFTRNS.OSVOL3; MWS410MI/LstPackageLine	For SyncShipmentDelivery: The field indicates the volume.
or MPTRNS.ORVOL3; MWS423MI/LstPackDel.; / @unitCode	
For SyncShipment: CSYTAB.CTPARM ; CRS175MI/GetItemFreeFlds	For SyncShipment: The field indicates the general unit of measure for all volumes within a company.
For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds	For SyncShipmentDelivery: The field indicates the volume unit code.
Shipment/ShipmentUnit/Dimensions/WidthMeasure For SyncShipmentDelivery: MPTRNS.OPPACW; MWS423MI/LstPackages	For SyncShipmentDelivery: The field indicates the width of the packaging.
<pre>@unitCode For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItmFreeFields</pre>	For SyncShipmentDelivery: The field indicates the unit code.
Shipment/ShipmentUnit/Dimensions/LengthMeasure For SyncShipmentDelivery: MPTRNS.OPPACL; MWS423MI/LstPackages @unitCode	For SyncShipmentDelivery: The field indicates the length of the packaging.

Shipment For SyncShipmentDelivery: For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItmFreeFields The field indicates the unit code Shipment/ShipmentUnit/Dimensions/HeightMeasure For SyncShipmentDelivery: For SyncShipmentDelivery: MPTŔNS.OPPACH; MWŚ423MI/LstPackages The field indicates the height of the packaging. @unitCode For SyncShipmentDelivery: For SyncShipmentDelivery: CSYTAB.CTPARM; CRS175MI/GetItmFreeFields The field indicates the unit code Shipment/ShipmentUnit/ShippingMaterial/PackagingCode For SyncShipmentDelivery For SyncShipmentDelivery: MPTRNS.ORGRTP; MWS423MI/LstPackages The field indicates the packing code and is used to select packages. Shipment/ShipmentUnit/ShipmentUnitContainer For SyncShipmentDelivery: For SyncShipmentDelivery: MPTŔNS.ORPACT; MWŚ423MI/LstPackDel The field indicates the packaging. The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: O Parent element(s): Generic Data element: Packaging Shipment/ShipmentUnit/ShipmentUnitContainer/ContainerID For SyncShipment: For SyncShipment: MPTRNS.ORPANR The field indicates the identity of a package. ; MWS410MI/LstPackages For SyncShipmentDelivery: For SyncShipmentDelivery: The field indicates the package number. MPTRNS.ORPANR; MWS423MI/LstPackDel Shipment/ShipmentUnit/ShipmentUnitContainer/ShippingMaterial/ID For SyncShipment: For SyncShipment: MPTRNS.ORPACT The field indicates the ID of the packaging ; MWS410MI/LstPackages @accountingEntity For SyncShipment: For SyncShipment: DCOŃSI.DACONO The field indicates the company and division, displayed as DCONSI.DADIVI.; / CONO DIVI. E.g. 760 AAA Shipment/ShipmentUnit/ShipmentUnitItem/ItemID/ID For SyncShipment: The field indicates the item number. MFTŔNS.OSITNO ; MWS423MI/LstContents For SyncShipmentDelivery: MFTRNS.OSITNO; MWS423MI/LstContents @accountingEntity For SyncShipment: For SyncShipment: DCONSI.DACONO The field indicates the accounting entity. DCONSI.DADIVI.; / If ItemMaster is enabled in BOD Processor Master AE tab, this is

For SyncShipmentDelivery: MHDISH.OQCONO CMNDIV.CCDIVI.; /

displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

For SyncShipmentDelivery:

The field indicates the accounting entity.

If ItemMaster_MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).

Shipment/ShipmentUnit/ShipmentUnitItem/Classification/Codes/Code

For SyncShipmentDelivery:

OOLINE.OBTEPY; OIS100MI/GetLine2

@listID

For SyncShipmentDelivery:

The field indicates the payment terms. Set attribute listID to 'Payment Term'.

For SyncShipmentDelivery:

If Code=TEPY, set listID to 'Payment Term'

Shipment/ShipmentUnit/ShipmentUnitItem/ShippedQuantity

For SyncShipment:

MFTRNS.OSDLQT; MWS423MI/LstContents

For SyncShipmentDelivery:

MFTRNS.OSDLQA; MWS423MI/LstContents

For SyncShipment:

The field indicates the delivered quantity, expressed in the item's

basic U/M.

For SyncShipmentDelivery:

The field indicates delivered quantity expressed in alternate unit of

measure.

@unitCode

For SyncShipment:

MITMAS.MMUNMS: MWS423MI/LstContents For SyncShipment:

The field indicates the unit in which each item is recorded in For SyncShipmentDelivery: inventory, even if alternate inventory units of measure are used. All

MITMAS.MMALUN; MWS423MI/LstContents balance information for the current item is always stored in this unit.

For SyncShipmentDelivery:

The field indicates the alternate unit of measure.

Shipment/ShipmentUnit/ShipmentUnitItem/ShippedBaseUOMQuantity

For SyncShipmentDelivery:

For SyncShipmentDelivery:

MFTRNS.OSDLQT; MWS423MI/LstContents The field indicates the delivered quantity expressed in basic unit of

measure.

@unitCode

For SyncShipmentDelivery: For SyncShipmentDelivery:

MITMAS.MMUNMS; MWS423MI/LstContents The field indicates the basic unit of measure

Shipment/ShipmentUnit/ShipmentUnitItem/EstimatedWeightMeasure

For SyncShipment:

For SyncShipment:

MPTRNS.ORNEWE; MWS423MI/LstContents The field indicates the estimated weight of the item.

For SyncShipmentDelivery: For SyncShipmentDelivery:

MFTRNS.OSNEWE; MWS423MI/LstContents The field indicates the total weight of all items entered on the

customer order.

@unitCode

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds For SyncShipment:

The field indicates the general unit of measure for all weights within a

company.

For SyncShipmentDelivery: The field indicates the unit code.

Shipment/ShipmentUnit/ShipmentUnitItem/LoadingWeightMeasure

For SyncShipment:

MPTRNS.ORGRWE; MWS423MI/LstContents The field indicates the total weight of the item.

For SyncShipmentDelivery: For SyncShipmentDelivery:

MFTRNS.OSGRWE; MWS423MI/LstContents The field indicates the total weight for all items that have been

entered on the order.

For SyncShipment:

@unitCode

CSYTAB.CTPARM; CRS175MI/GetItemFreeFlds

For SyncShipment:

The field indicates the general unit of measure for all weights within a

company.

For SyncShipmentDelivery: The field indicates the unit code.

Shipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID

For SyncShipmentDelivery: For SyncShipmentDelivery:

MITALO.MQRIDN; MWS423MI/LstContents The field indicates the purchase order number.

@accountingEntity

For SyncShipmentDelivery: For SyncShipmentDelivery:

MHDISH.OQCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; / CONO DIVI.

Shipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber For SyncShipmentDelivery: For SyncShipmentDelivery:

MITALO MQRIDL; MWS423MI/LstContents The field indicates the purchase order line number.

Shipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/SubLineNumber

For SyncShipmentDelivery: For SyncShipmentDelivery:

MITALO.MQRIDX; MWS423MI/LstContents The field indicates the purchase order subline number.

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID

For SyncShipment: For SyncShipment:

MFTRNS.OSRIDN; MWS423MI/LstContents The field indicates an order number where item is connected to.

For SyncShipmentDelivery: For SyncShipmentDelivery:

MITALO.MQRIDN; MWS423MI/LstContents The field indicates the sales order number.

@accountingEntity

For SyncShipment: For SyncShipment:

DCONSI.DACONO The field indicates the company and division, displayed as DCONSI.DADIVI.; /

CONO_DIVI.

For SyncShipmentDelivery: E.g. 760 AAA

MHDÍSH.OOCONO CMNDIV.CCDIVI.; / For SyncShipmentDelivery:

The field indicates the company and division, displayed as

CONO_DIVI.

@location

For SyncShipment: For SyncShipment:

MHDISH.OQWHLO; MWS410MI/GetHead The field indicates the warehouse ID

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/LineNumber

For SyncShipment:

MFTRNS.OSRIDL: MWS423MI/LstContents For SyncShipment:

The field indicates an order line where item is connected to.

For SyncShipmentDelivery:

MITALO.MQRIDL; MWS423MI/LstContents For SyncShipmentDelivery:

The field indicates the order line number.

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber

For SyncShipment: For SyncShipment:

MFTRNS.OSRIDX; MWS423MI/LstContents The field indicates an order line suffix where item is connected to.

For SyncShipmentDelivery: For SyncShipmentDelivery: MITALO.MQRIDX; MWS423MI/LstContents The field indicates the line suffix.

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference

For SyncShipmentDelivery: For SyncShipmentDelivery:

MHDISH.OQRORC; MWS423MI/LstContents The field indicates the origin of the reference order category (RORC).

> If RORC = 1. set to 'ProductionOrder'. If RORC = 2, set to 'PurchaseOrder' If RORC = 3, set to 'SalesOrder'. If RORC = 4, set to 'Transfer'. If RORC = 5, set to 'Transfer'. If RORC = 6, set to 'WorkOrder'. If RORC = 7, set to 'ServiceOrder' If RORC = 8, set to 'ProjectMaster'. If RORC = 9, set to 'SupplierRMA'

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID

For SyncShipmentDelivery For SyncShipmentDelivery:

MITALO.MQRIDN; MWS423MI/LstContents The field indicates the order number.

@accountingEntity

For SyncShipmentDelivery: For SyncShipmentDelivery:

MHDISH.OQCONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI CONO DIVI.

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/LineNumber

For SyncShipmentDelivery: For SyncShipmentDelivery:

MITALO.MQRIDL; MWS423MI/LstContents The field indicates the order line number.

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/SubLineNumber

For SyncShipmentDelivery: For SyncShipmentDelivery: MITALO.MQRIDX; MWS423MI/LstContents The field indicates the line suffix.

Shipment/ShipmentUnit/ShipmentUnitItem/UserArea

For SyncShipmentDelivery: For SyncShipmentDelivery: MPTRNS.ORPAII; 1) Included in package

MWS423MI.LstPackDel The field indicates the included in package number. .; / Set attribute name to 'm3.IncludedInPackageNumber'.

2) Outer package number

The field indicates the outermost package number. Set attribute name to 'm3.OuterPackageNumber'.

Shipment/ShipmentUnit/UserArea

For SyncShipmentDelivery: 1) MPTRNS.ORSSCC; MWS423MI/LstPackages 2) MPTRNS.ORPACO: MWS423MI/LstPackDel.; /

For SyncShipmentDelivery:

1) The field indicates the Serial Shipping Container Code.

Set attribute name to 'SSCC'.

2) The field indicates if the package is an outer package.

Set attribute name to 'm3.OuterPackage'.

The NameValue is set to 'true' if PACO = 0. Otherwise, this element is

not displayed.

Shipment/ShipmentUnit/SpecializedLogisticUnit/ShipmentUnitType

For SyncShipmentDelivery:

MPTRNS.ORPACT; MWS423MI/LstPackDel

For SyncShipmentDelivery: The field indicates the packaging.

The value can be translated in CRS881/882.

Msg std: ION Vers: 1

Message: Generic

I/O: O

Parent element(s): Generic Data element: Packaging

Shipment/ShipmentUnit/SpecializedLogisticUnit/Reference/NameValue

For SyncShipment: For SyncShipment:

OCUSMA.OKCUSU; MWS410MI/GetHead The field indicates the supplier number at customer.

For SyncShipmentDelivery:

For SyncShipmentDelivery: MPTRNS.ORETRN; MWS423MI/LstPackDel The field indicates the external identification, or the forwarder's

identification, of the tracking number.

@name

For SyncShipment: Set to 'ExternalSupplierNumber'.

For SyncShipmentDelivery: Set to 'ExternalTrackingNumber'.

SourceSystemGLMovement

SourceSystemGLMovement	
SourceSystemGLMovement/IDs/ID	
For Actual:	For Actual: The field indicates year (YEA4)+ period (PERI)+Accounting string if
1) FBAVAL.RVYEA4 2) FBAVAL.RVPERI	BAKY is equal to 8 then ID will created. Spaces will be underscores
3) FBAKEY.RKBIT1	(_). Delimiter will be dot (.).
4) FBAKEY.RKBIT2	-
5) FBAKEY.RKBIT3	For Budget:
6) FBAKEY.RKBIT4 7) FBAKEY.RKBIT5	The field indicates the document ID. It is a concatenation of Budget Period (BUPE) <6> + Accounting dimension 1 (AIT1) <10> +
8) FBAKEY.RKBIT6	Accounting dimension 2 (AIT2) <10> + Accounting dimension 3
9) FBAKEY.RKBIT7	(AIT3) <10> + Accounting dimension 4 (AIT4) <10> + Accounting
	dimension 5 (AIT5) <10> + Accounting dimension 6 (AIT6) <10> +
.; GLS215MI/GetBitFromPtid	Accounting dimension 7 (AIT7) <10> + Currency (CUCD) <3> + Budget number (BUNO) <3> + Budget version (BVER) <4>. If the data does not consume the maximum length, the rest is filled up with
For Budget:	underscore (). Dot (.) is used as delimiter or separator between
FBUDET.BCBUPE	fields.
FBUDET.BCAIT1	F 000000 44440 004 4 045070 400705
FBUDET.BCAIT2 FBUDET.BCAIT3	E.g. 200606.111100011345678128765 130234
FBUDET.BCAIT4	13023410124300D.102000
FBUDET.BCAIT5	
FBUDET.BCAIT6	
FBUDET.BCAIT7	
FBUDET.BCCUCD FBUDET.BCBUNO	
FBUDET.BCBVER.; /	
@accountingEntity	
For Actual:	For Actual:
FBAVAL.RVCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
GIVINDIV.CODIVI., /	CONO_BIVI.
For Budget:	For Budget:
FBUDET.BCCONO	The field indicates the company and division, displayed as
FBUDET.BCDIVI.; /	CONO_DIVI.
@location	For Actual:
	The field indicates the facility and warehouse.
@variationID	·
	For Actual:
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
	times that the Bob has been published.
	For Budget:
	The field indicates the sequence number that identifies the number of
@lid	times that the BOD has been published.
6.10	For Actual:
	The field indicates the logical ID of the system.
	For Budget
	For Budget: The field indicates the logical ID of the system.
SourceSystemGLMovement/LastModificationDateTime	<u> </u>
For Actual:	The field indicates when the last change was made to the record.
FVABAL.RVLMDT; /	
For Budget:	
FBUDET.BCLMDT; /	
SourceSystemGLMovement/LastModificationPerson/IDs/ID	
For Actual:	The field indicates the user ID associated with the last change made
FBAVAL.RVCHID; /	to the record.
For Budget:	
FBUDET.BCCHID; /	
@accountingEntity	
For Actual:	The field indicates the company and division, displayed as
FBAVAL.RVCONO CMNDIV.CCDIVI.; /	CONO_DIVI.
For Budget:	
FBUDET.BCCONO	
FBUDET.BCDIVI.; /	
SourceSystemGLMovement/DocumentDateTime For Actual:	For Actual:
FBAVAL.RVRGDT	The field indicates the creation date and time.
FBAVAL.RVRGTM.; /	
For Budgets	For Budget:
For Budget:	The field indicates the creation date.

SourceSystemGLMovement	
FBUDET.BCRGDT FBUDET.BCRGTM.; /	
SourceSystemGLMovement/Status/Code	
	For Actual:
	Set to 'Open'.
	For Budget:
	Set to 'Open'.
SourceSystemGLMovement/GLMovementRow/AccountingJourn	alReference/ID For Actual:
	The field indicates the accounting journal reference.
SourceSystemGLMovement/GLMovementRow/LedgerSetupRefe	
For Budget:	For Budget:
FBUDET.BCBVER	The field indicates the ID to the book instance object that is being
FBUDET.BCBUNO.; /	referenced by LedgerSetup. It is a concatenation of Budget version
	(BVER) + Budget number (BUNO) where the last 3 characters
	indicate the BUNO.
SourceSystemGLMovement/GLMovementRow/AccountingBook	
	For Actual:
	Set to 'Actual'.
	For Budget:
	Set to 'Budget'.
SourceSystemGLMovement/GLMovementRow/PostingKey	
For Actual:	For Actual:
1) FBAVAL.RVYEA4	The field indicates year (YEA4)+ period (PERI)+Accounting string if
2) FBAVAL.RVPERI	BAKY is equal to 8 then ID will created. Spaces will be underscores
3) FBAKEY.RKBIT1	(_). Delimiter will be dot (.).
4) FBAKEY.RKBIT2	For Dividuals
5) FBAKEY.RKBIT3 6) FBAKEY.RKBIT4	For Budget: The field indicates the document ID. It is a concatenation of Budget
7) FBAKEY.RKBIT5	Period (BUPE) <6> + Accounting dimension 1 (AIT1) <10> +
8) FBAKEY.RKBIT6	Accounting dimension 2 (AIT2) <10> + Accounting dimension 3
9) FBAKEY.RKBIT7	(AIT3) <10> + Accounting dimension 4 (AIT4) <10> + Accounting
,	dimension 5 (AIT5) <10> + Accounting dimension 6 (AIT6) <10> +
	Accounting dimension 7 (AIT7) <10> + Currency (CUCD) <3> +
.; GLS215MI/GetBitFromPtid	Budget number (BUNO) <3> + Budget version (BVER) <4>. If the
For Budgets	data does not consume the maximum length, the rest is filled up with underscore (_). Dot (.) is used as delimiter or separator between
For Budget: FBUDET.BCBUPE	fields.
FBUDET.BCAIT1	neids.
FBUDET.BCAIT2	E.g. 200606.111100011345678128765
FBUDET.BCAIT3	130234131245USD.152006
FBUDET.BCAIT4	
FBUDET.BCAIT5	
FBUDET.BCAIT6	
FBUDET.BCAIT7 FBUDET.BCCUCD	
FBUDET.BCBUNO	
FBUDET.BCBVER.; /	
SourceSystemGLMovement/GLMovementRow/GLAccount/GLNo	ominalAccount
For Actual:	For Actual:
FBAVAL.RKBIT1; GLS215MI/GetBitFromPtid	The field indicates a balance identity in a balance dimension.
5 B	5. B. L. I
For Budget:	For Budget:
FBUDET.BCAIT1	The field indicates the accounting identity in an accounting dimension
SourceSystemGLMovement/GLMovementRow/GLAccount/GLNo	aminal A account Nama
For Actual:	For Actual:
FCHACC.EATX40; CRS630MI/GetAccountID	The field indicates a description of the current identity.
•	'
For Budget:	For Budget:
FCHACC.EATX15	The field indicates the GL account name.
; CRS630MI/GetAccountID	
SourceSystemGLMovement/GLMovementRow/GLAccount/Acco	
	For Actual:
	The field indicates the AccountingChartStandard.
	For Budget:
	Set to 'AccountingChartStandard'.
@accountingEntity	0
For Actual:	For Actual:
FBAVAL.RVCONO	The field indicates the company and division, displayed as
CMNDIV.CCDIVI.; /	CONO_DIVI.

Infor May 26, 2023 599

For Budget:

For Budget:

SourceSystemGLMovement FBUDET.BCCONO The field indicates the company and division, displayed as FBUDET.BCDIVI.; CONO DIVI. SourceSystemGLMovement/GLMovementRow/AccountType For Actual: For Actual: FCHACC.EAAT01 The field indicates the account type. CRS630MI/GetAccountID Set to 'BalanceSheet' if balance account (AT01) is 1. FCHACC.EAAT02 Set to 'ProfitAndLoss' if profit or loss account (AT02) is 1. CRS630MI/GetAccountID.; / Set to "BalanceSheet" if Balance account (AT01) = 1. Else, set to For Budget: FCHACC.EAAT01 "ProfitAndLoss". CRS630MI/GetAccountID @listID For Actual: Set to 'BalanceSheet'. Set to 'ProfitAndLoss'. For Budget: Set to 'Account Types' SourceSystemGLMovement/GLMovementRow/DimensionCodes/DimensionCode For Actual: For Actual: 1) FBAKEY.RKBIT2 The field indicates a balance identity in a balance dimension. 2) FBAKEY.RKBIT3 A selection may be entered for each of the seven levels. The contents 3) FBAKEY.RKBIT4 of these levels are determined by the heading that is linked to each 4) FBAKEY.RKBIT5 field. 5) FBAKEY.RKBIT6 6) FBAKEY.RKBIT7.; GLS215MI/GetBitFromPtid For Budget: The field indicates the accounting identity in an accounting dimension. For Budget: FBUDET.BCAIT2 FBUDET.BCAIT3 FBUDET.BCAIT4 FBUDET.BCAIT5 FBUDET.BCAIT6 FBUDET.BCAIT7.; / @sequence For Actual: For Actual: 1) FBAKEY.RKBIT2 The field indicates the sequence. 2) FBAKEY.RKBIT3 3) FBAKEY.RKBIT4 For Budget: 4) FBAKEY.RKBIT5 The field indicates the sequence number for the ordering of elements 5) FBAKEY.RKBIT6 within 6) FBAKEY.RKBIT7.; GLS215MI/GetBitFromPtid a document. @listID For Actual: For Actual: CSYTAB.CTPARM; CRS175MI/GetGeneralCode The field indicates the names from CRS012. Fields have a dimension of 10 characters. For Budget: CSYTAB.CTPARM For Budget: ; CRS175MI/GetGeneralCode The field indicates the name for a specific accounting dimension. SourceSystemGLMovement/GLMovementRow/FinancialCalendarReference/DocumentID/ID For Budget: Set to 'Financial Calendar'. @accountingEntity For Budget: For Budget: FBUDET.BCCONO The field indicates the company and division, displayed as FBUDET.BCDIVI.; CONO DIVI. SourceSystemGLMovement/GLMovementRow/AccountingDate/PeriodID For Actual: For Actual: 1) FBAVAL.RVYEA4 The field indicates the period ID. 2) FBAVAL.RVPERI.; GLS215MI/GetPeriodBalance For Budget: For Budget: The field indicates the number of a period in a year, either fiscal or FBUDET.BCBUPE calendar. SourceSystemGLMovement/GLMovementRow/AccountingDate/Year For Actual: The field indicates the accounting date year. FBAKEY.RVYEA4; GLS215MI/GetPeriodBalance

For Budget:

FBUDET.BCBUPE The field indicates the budget period year or a calendar year.

SourceSystemGLMovement/GLMovementRow/DebitMovement/FunctionalAmount

For Actual: For Actual:

FBAVAL.RVACAD; GLS215MI/GetPeriodBalance The field indicates the functional amount.

For Budget: For Budget:

SourceSystemGLMovement

FBUDET.BCBLAM The field indicates the local currency amount if For curr amount

For Actual:

: BUS100MI/LstBudPeriodVal inputted value is greater than zero.

@currencyID

For Actual:

CMNDIV.CCCUCD; MNS100MI/GetBasicData The field indicates the currency ID.

For Budget: For Budget:

CMNDIV.CCLOCD The field indicates the currency code.

; MNS100MI/GetBasicData

SourceSystemGLMovement/GLMovementRow/DebitMovement/Amount

For Actual: For Actual:

FBAVAL.RVCUAD; GLS215MI/GetPeriodBalance The field indicates the foreign currency amount. Only included if

currency connection = 2 on account (currency connection =2= only

the currency code of the account can be used for posting For Budget:

FBUDET.BCBCUA ; BUS100MI/LstBudPeriodVal

The field indicates the foreign currency amount if For curr amount

inputted value is greater than zero.

@currencyID

For Budget:

For Actual:

FCHACC.EACUCD; CRS630MI/GetAccountID The field indicates the included if currency connection = 2 on account

(currency connection =2= only the currency code of the account can

be used for posting.

For Actual:

For Actual:

FBUDET.BCCUCD

; BUS100MI/LstBudPeriodVal For Budget:

The field indicates the abbreviation for the currency.

SourceSystemGLMovement/GLMovementRow/DebitMovement/ReportingCurrencyAmount

For Actual: For Actual:

FBAVAL.RVTCAD; GLS215MI/GetPeriodBalance The field indicates the third currency amount.

@currencyID For Actual:

CSYPAR.PARM; GLS215MI/GetPeriodBalance The field indicates the currency ID

SourceSvstemGLMovement/GLMovementRow/CreditMovement/FunctionalAmount

For Actual: For Actual:

FBAVAL.RVACAC; GLS215MI/GetPeriodBalance The field indicates the local currency amount.

For Budget: For Budget:

FBUDET.BCBLAM The field indicates the local currency amount if For curr amount

; BUS100MI/LstBudPeriodVal inputted value is less than zero.

@currencyID

For Actual: For Actual:

CMNDIV.CCCUCD; MNS100MI/GetBasicData The field indicates the currency ID.

For Budget: For Budget:

CMNDIV.CCLOCD The field indicates the currency code.

; MNS100MI/GetBasicData

SourceSystemGLMovement/GLMovementRow/CreditMovement/Amount

For Actual:

FBAVAL.RVCUAC; GLS215MI/GetPeriodBalance The field indicates the foreign currency amount. Only included if

currency connection = 2 on account (currency connection =2= only the currency code of the account can be used for posting. For Budget:

FBUDET.BCBCUA

; BUS100MI/LstBudPeriodVal For Budget:

The field indicates the currency amount if For curr amount inputted

value is less than zero.

@currencyID For Actual:

For Actual:

FCHACC.EACUCD; CRS630MI/GetAccountID The field indicates the currency ID.

For Budget: For Budget:

FBUDET.BCCUCD The field indicates the abbreviation for the currency. ; BUS100MI/LstBudPeriodVal

SourceSystemGLMovement/GLMovementRow/CreditMovement/ReportingCurrencyAmount

For Actual: For Actual:

FBAVAL.RVTCAC; GLS215MI/GetPeriodBalance The field indicates the third currency amount. Only included if

currency connection = 2 on account (currency connection =2= only

the currency code of the account can be used for posting.

@currencvID

For Actual: For Actual:

CSYPAR.PARM; GLS215MI/GetPeriodBalance The field indicates the currency ID.

SourceSystemGLMovement/GLMovementRow/NetMovement/FunctionalAmount

For Actual: For Actual:

FBAVAL.RVACAD The field indicates the local currency amount.

FBAVAL.RVACAC.; GLS215MI/GetPeriodBalance

For Budget: For Budget: The field indicates the combination of DebitFunctionalAmount and

FBUDET.BCBLAM CreditFunctionalAmount.

SourceSystemGLMovement

: BUS100MI/LstBudPeriodVal NetFunctionalAmount = DebitFunctionalAmount +

CreditFunctionalAmount.

For Actual:

For Actual:

For Actual:

For Actual:

@currencyID For Actual:

CMNDIV.EACUCD; MNS100MI/GetBasicData

The field indicates the currency ID.

For Budget: CMNDIV.CCLOCD For Budget:

The field indicates the Currency code

; MNS100MI/GetBasicData SourceSystemGLMovement/GLMovementRow/NetMovement/Amount

For Actual:

FBAVAL.RVCUAD The field indicates the foreign currency amount. Only included if FBAVAL.RVCUAC.; GLS215MI/GetPeriodBalance currency connection = 2 on account (currency connection =2= only

the currency code of the account can be used for posting.

For Budget: FBUDEŤ.BCBCUA

: BUS100MI/LstBudPeriodVal The field indicates the combination of DebitAmount and CreditAmount.

NetAmount = DebitAmount + CreditAmount.

@currencyID For Actual:

For Budget:

FCHACC.EACUCD; CRS630MI/GetAccountID The field indicates the included if currency connection = 2 on account

(currency connection =2= only the currency code of the account can

be used for posting.

FBUDET.BCCUCD ; BUS100MI/LstBudPeriodVal

For Budget: The field indicates the abbreviation for the currency.

SourceSystemGLMovement/GLMovementRow/GLFullAccount

FBAKEY.RKBIT1; GLS215MI/GetBitFromPtid The field indicates the GLFullAccount.

For Budget: For Budget:

FBUDET.BCAIT1 The field indicates the accounting identity in an accounting dimension. ;/

SourceSystemJournalEntry 5 1 2 1

SourceSystemJournalEntry/JournalEntryHeader/JournalID)
FGLEDG.EGYEA4.	

FGLEDG.EGVSER FGLEDG.EGVONO;

The field indicates a concatenation of Year (YEA4) <4> + Voucher series number (VSER) <3> + Voucher number (VÓNO) <8> without separator. The data in Year always consumes maximum length, data in Voucher series number consumes between 1 and 3 positions (set to '___' if empty), and if the data in Voucher number does not consume the maximum length, the rest is filled up with zeroes on the left side.

2019100001016 means Year=2019, Voucher series number=1 and Voucher number=00001016

@accountingEntity FGLEDG.EGCONO, FGLEDG.EGDIVI;

@lid

@variationID

The field indicates the company and division, displayed as CONO DIVI.

The field indicates the sequence number that identifies the number of times that the BOD has been published.

The field indicates the logical ID of the system.

SourceSystemJournalEntry/JournalEntryHeader/LastModificationDateTime

FGLHED.EGLMDT; The field indicates when the last change was made to the voucher.

SourceSystemJournalEntry/JournalEntryHeader/LastModificationPerson/IDs/ID

FGLHED.EGCHID; The field indicates the user ID associated with the last change made

to the voucher.

@accountingEntity FGLHED.EGCONO

The field indicates the company and division, displayed as FGLHED.EGDIVI; CONO DIVI

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/DocumentDateTime

FGLHED.EGRGTM The field indicates the voucher creation date. FGLHED.EGRGTM;

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PeriodID

FGLEDG.EGCYP6; GLS200MI/LstVoucherLines The field indicates the financial period from the first line of the voucher

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/PostDateTime

FGLEDG.EGACDT; GLS200MI/LstVoucherLines The field indicates the accounting Date from the first line of the

voucher, formatted as yyyy-mm-dd. SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingDate/Year

FGLEDG.EGYEA4; GLS200MI/GetVoucherHead The field indicates the year for the voucher.

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Amount

FGLEDG.EGCUAM; GLS200MI/GetVoucherHead

The field indicates the currency amount, that is, the recorded amount in the appropriate currency.

There are three key currency types in M3 BE:

- 1. Local currency the base, domestic currency used by the company and to which all transactions are converted in the general ledger. A value expressed in this currency is called local amount.
- 2. Foreign currency any other currency used. A value expressed in such a currency is called currency amount.
- 3. Third currency a currency with special status, such as the euro within the Monetary Union (EMU), or the U.S. dollar. A third currency may be useful for reporting and comparison purposes, for example when you wish to present your figures in a stable currency.

@currencvID

FGLEDG.EGCUCD; GLS200MI/GetVoucherHead The field indicates the foreign currency code

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/FunctionalAmount

FGLEDG.EGACAM; GLS200MI/GetVoucherHead

The field indicates the sum of accounted amount.

@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData

The field indicates the local currency code.

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/Description

CSYTAB.EGTX40; CRS175MI/GetGeneralCode

The field indicates the description of FAM function in CRS405/E. Value from field FEID (FAM function) in M3 program CRS405/E is used as inbound field STKY (Key value) for MI transaction CRS175MI/ GetGeneralCode to get the description of FAM function.

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/LedgerType

Set to 'Actual'

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/AccountingJournalReference/ID

The field indicates FAM function ID used on transaction, the FGLEDG.EGFEID; GLS200MI/GetVoucherHead

reference to accounting journal BOD.

@accountingEntity

FGLEDG.EGCONO The field indicates the company and division, displayed as CONO DIVI FGLEDG.EGDIVI;

SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryHeader/LedgerSetupReference/DocumentID/ID

SourceSystem JournalEntry	
SourceSystemJournalEntry FGLEDG.EGCONO, FGLEDG.EGDIVI;	The field indicates the company and division, displayed as CONO DIVI.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry	
@listID	Set to 'Final'.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry	Set to 'Journal Status'. Header/Source System Journal Code
	Set to 'SourceLedger'.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry/ FGLEDG.EGCHID;	Header/EnteredAudit/PersonReference/IDs/ID The field indicates User ID for the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryl CMNUSR.JUTX40; MNS150MI/GetUserData	Header/EnteredAudit/PersonReference/Name The field indicates the full Name from User master of the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry FGLEDG.EGRGDT, FGLEDG.EGRGTM; GLS200MI/LstVoucherLines	
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryl	
FGLEDG.EGCHID;	The field indicates User ID for the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry CMNUSR.JUTX40; MNS150MI/GetUserData	The field indicates the full Name from User master of the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryl FGLEDG.EGLMDT; GLS200MI/LstVoucherLines	Header/ModifiedAudit/DateTime The field indicates the last modified date from the first line of the voucher, formatted as yyyy-mm-dd. E.g. 2019-11-13
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryl FGLEDG.EGCHID;	Header/PostedAudit/PersonReference/IDs/ID The field indicates User ID for the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry/ CMNUSR.JUTX40; MNS150MI/GetUserData	Header/PostedAudit/PersonReference/Name The field indicates the full Name from User master of the user who registered this record.
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntryl	· ·
FGLEDG.EGRGTM; GLS200MI/LstVoucherLines	voucher. E.g. 2019-11-13T09:43:02.000Z
SourceSystemJournalEntry/JournalEntryHeader/BaseJournalEntry	Header/ExchangeRateDateTime
FGLEDG.EGACDT; GLS200MI/LstVoucherLines SourceSystemJournalEntry/JournalEntryLine/JournalEntryLine @sequence	The field indicates the accounting date, formatted as yyyy-mm-dd. The field indicates an incremental value for journal entry line number, starting from 1.
SourceSystemJournalEntry/JournalEntryLine/Amount FGLEDG.EGCUAM; GLS200MI/LstVoucherLines @currencyID	The field indicates the foreign currency amount.
FGLEDG.EGCUCD; GLS200MI/LstVoucherLines	The field indicates the foreign currency code.
SourceSystemJournalEntry/JournalEntryLine/FunctionalAmount FGLEDG.EGACAM; GLS200MI/LstVoucherLines @currencyID	The field indicates the local currency amount.
CMNDIV.CCCUCD; MNS100MI/GetBasicData	The field indicates the local currency code.
SourceSystemJournalEntry/JournalEntryLine/Tax @sequenceNumber	Set to '1', only when Tax section per transaction included, VAT code (VTCD)<2> and VAT account type (AT04)<1> not empty.
SourceSystemJournalEntry/JournalEntryLine/Tax/ID FGLEDG.EGAT04, FGLEDG.EGVTCD; GLS200MI/LstVoucherLine	The field indicates the VAT code (VTCD><2> of the transaction for accounts with VAT account type (AT04)<1> in the interval from 1 to 9 Only when Tax section per transaction included, VAT code (VTCD)<2> and VAT account type (AT04)<1> is not empty. If the data in VAT code does not consume the maximum length, the rest is filled up with zeroes on the left side.
<pre>@accountingEntity FGLEDG.EGCONO, FGLEDG.EGDIVI;</pre>	The field indicates the company and division, displayed as CONO DIVI.

SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/SourceUnitBaseNumeric
CSYTAB.CTPARM; CRS055MI/GetBasicData
The field indicates the rate factor (RAF)

SourceSystemJournalEntry/JournalEntryLine/AmountToFunctionalExchangeRate/RateNumeric

FGLEDG.EGARAT; GLS200MI/LstVoucherLines

The field indicates the rate factor (RAFA) defined in (CRS055/MFS055) of the transaction currency (CUCD) to the local currency.

- If Rate factor = 1: Set to '1000' - If Rate factor = 2: Set to '100'

The field indicates the exchange rate.

SourceSystemJournalEntry

SourceSystemsournalEntry	
	- If Rate factor = 3: Set to '10' - If Rate factor = 4-7: Set to '1'
SourceSystemJournalEntry/JournalEntryLine/AmountToFunction	nalExchangeRate/TargetUnitBaseNumeric
CSYTAB.CTPARM; CRS055MI/GetBasicData	The field indicates the rate factor (RAFA) defined in (CRS055/
	MFS055) of the transaction currency (CUCD) to the local currency.
	- If Rate factor = 1-4: Set to '1'
	- If Rate factor = 5: Set to '10'
	- If Rate factor = 6: Set to '100'
	- If Rate factor = 7: Set to '1000'
SourceSystemJournalEntry/JournalEntryLine/AmountToFunction	
CMNDIV.CCDMCU; MNS100MI/GetBasicData	Set to 'false' if Currency conversion method for Division equals 1
	(Multiplication). Set to 'true' if Currency conversion method for Division equals 2
	(Division).
SourceSystemJournalEntry/JournalEntryLine/AmountToFunction	, ,
FGLEDG.EGCRTP; GLS200MI/LstVoucherLines	The field indicates the exchange rate type, defined in CRS056
TOLLBO.LOOKTI, OLOZOOMI/LOWOGOTOTLINGS	program in M3.
@accountingEntity	program in Mo.
FGLEDG.EGCONO,	The field indicates the company and division, displayed as
FGLEDG.EGDIVI;	CONO DIVI.
SourceSystemJournalEntry/JournalEntryLine/AlternativeCurrence	
FGLEDG.EGTCAM; GLS200MI/LstVoucherLines	The field indicates the third currency amount.
@currencyID	The held indicates the third currency amount.
FGLEDG.EGTHCC; GLS200MI/LstVoucherLines	The field indicates the third currency code from CRS750 program in
. 0 0 1.10 0, 0 0.01 0.01 0.01 0.01	M3.
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNon	ninalAccount
FGLEDG.EGAIT1; GLS200MI/LstVoucherLines	The field indicates the account, accounting dimension 1.
SourceSystemJournalEntry/JournalEntryLine/GLAccount/GLNon	ninalAccountName
FCHACC.EATX40; CRS630MI/GetAccountID	The field indicates the account description.
SourceSystemJournalEntry/JournalEntryLine/GLAccount/Account	ntingChartReference/ID
,,	Set to 'AccountingChartStandard'.
@accountingEntity	•
FGLEDG.EGCONO,	The field indicates the company and division, displayed as
FGLEDG.EGDIVI;	CONO DIVI.
SourceSystemJournalEntry/JournalEntryLine/DimensionCodes/L	DimensionCode
FGLEDG.EGAIT2,	The field indicates the Loop through accounting dimensions, from 2 to
FGLEDG.EGAIT3,	7.
FGLEDG.EGAIT4,	
FGLEDG.EGAIT5,	
FGLEDG.EGAIT6,	
FGLEDG.EGAIT7; GLS200MI/LstVoucherLines	
@sequence	
	Set to incrementing '1' to '6' for accounting dimensions from 2 to 7.
@listID	
CSYTAB.CTAIT2,	The field indicates the accounting dimensions, from 2 to 7, defined on
CSYTAB.CTAIT3,	CRS012 program in M3, middle-length variant (10 characters).
CSYTAB.CTAIT4,	
CSYTAB.CTAIT5,	
CSYTAB.CTAIT6,	
CSYTAB.CTAIT7; CRS175MI/GetGeneralCode	
SourceSystemJournalEntry/JournalEntryLine/UserArea	
1) FGLEDG.EGJRNO,	The field indicates additional information that is not captured in
2) FGLEDG.EGYEA4,	OAGIS but required by an integration. The information are defined in
FGLEDG.EGJRNO,	UserArea/Property/NameValue elements which are determined by
FGLEDG.EGJSNO	different 'name' and 'type' attributes.
3) FPLEDG.EPSINO	
4) FPLEDG.EPSUNO	1) Journal number (JRNO).
5) FGLEDG.EGVRNO	Set name='lcl.JournalNumber'.
6) FSLEDG.ESCUNO	Set type='NumericType'.
7) FPLEDG.EPSUNO	E.g.
8) FPLEDG.EPIVCL	<property><namevalue <="" name="lcl.JournalNumber" td=""></namevalue></property>
FSLEDG.ESIVCL	type='NumericType'>2019038
; GLS200MI.LstVoucherLines	2) If Transaction and (TDCD) - 40 (Complian invaions AD). Unique
APS200MI.GetInvoice	2) If Transaction code (TRCD) = 40 (Supplier invoices - AP): Unique
ARS200MI.GetInvoice	ID set to a concatenation of Year (YEA4) <4> + Journal number
	(JRNO) <7> + Journal sequence number (JSNO) <7> without
	separator, JRNO and JSNO are zero-padded from the left side to
	consume maximum length. Required for the integration to Local.ly as
	DocumentID/ID for SupplierInvoice is not unique.
	Set name='m3_UniqueID'. Set type='IntegerType'.
	Set type=integer rype . E.g.
	⊏.g. <property> <namevalue <="" name="m3_UniqueID" td=""></namevalue></property>
	type='IntegerType'>201920190380000001
	yrgyr3.o_o.oooooooo aaaaaaa aaaaaa
	3) If Transaction code (TRCD) = 40 (Supplier invoices - AP): Supplier
	, , , , , , , , , , , , , , , , , , ,

	Invoice ID (SINO)<24>. Set name='m3_SupplierInvoiceID_SINO'. Set type='StringType'
	Set type='StringType'. E.g. <property> <namevalue name="m3_SupplierInvoiceID_SINO" type="IntegerType">20200115-01</namevalue></property>
	4) If Transaction code (TRCD) = 40 (Supplier invoices - AP): Supplier ID (SUNO)<24>. Set name='m3_SupplierID_SUNO'.
	Set type='StringType'. E.g. <property> <namevalue name="m3_SupplierID_SUNO" type="IntegerType">AFT1001</namevalue></property>
	5) TaxID if Transaction code = 01, 11, 21, 41 or 51: VAT registration number (VRNO) Property name = 'lcl.TaxIdentificationNumber' and Property type =
	'StringType'
	 6) CustomerID if Transaction code (TRCD) = 10 or 20: Customer number (CUNO). - Property name = 'Icl.CustomerID' and Property type = 'StringType'
	7) SupplierID if Transaction code (TRCD) = 40 or 50: Supplier number (SUNO).
	- Property name = 'Icl.SupplierID' and Property type = 'StringType'
	8) InvoiceClass if Transaction code (TRCD) = 10 or 40: Invoice class (IVCL) for customer invoice (ARS200MI) or supplier invoice (APS200MI). - Property name = 'Icl.InvoiceClass' and Property type = 'StringType'
SourceSystemJournalEntry/JournalEntryLine/SourceLine FGLEDG.EGJSNO; GLS200MI/LstVoucherLines	The field indicates the journal sequence number.
SourceSystemJournalEntry/JournalEntryLine/DebitCreditFlag FGLEDG.EGDBCR; GLS200MI/LstVoucherLines	Set to "DEBIT" if LstVoucherLines.DCFG = D. Set to "CREDIT" if LstVoucherLines.DCFG = C.
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate FGLEDG.EGACDT; GLS200MI/LstVoucherLine	
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate FGLEDG.EGACDT; GLS200MI/LstVoucherLines	
SourceSystemJournalEntry/JournalEntryLine/SourceAccountingDate FGLEDG.EGYEA4; GLS200MI/LstVoucherLines	* * * * * * * * * * * * * * * * * * * *
SourceSystemJournalEntry/JournalEntryLine/SourceDocumentRefe @type	·
FGLEDG.EGTRCD; GLS200MI/LstVoucherLines	The field indicates the type of voucher based on the Transaction code (TRCD):
	Set to 'Ínvoice' if TRCD = 10 (Customer invoices - AR) Set to 'ReceivableTransaction' if TRCD = 20 (Payments received - AR)
	Set to 'SupplierInvoice' if TRCD = 40 (Supplier invoices - AP) Set to 'PayableTransaction' if TRCD = 50 (Payments - AP)
SourceSystemJournalEntry/JournalEntryLine/SourceDocumentRefer FGLEDG.EGYEA4, FGLEDG.EGFEID,	erence/DocumentID/ID The field indicates the document ID for the related BODs.
GLS200MI/GetVoucherHead, FGLEDG.EGTRCD, FGLEDG.EGJRNO, FGLEDG.EGJSNO,	If Transaction code (TRCD) = 10 (Customer invoices - AR) and FAM function (GLS200MI/GetVoucherHead.FEID)<4> is one of the following: AR20, CO20, FA50, MF01, OI20, PO20, SO20
GLS200MI/LstVoucherLines, FSLEDX.ESSEXI,	Then { If Original invoice number (ARS251MI/LstInvInfo.SEXI) is not empty,
ARS251MI/LstInvInfo, FPLEDG.EPINYR, FPLEDG.EPSINO, APS200MI/GetInvoice, FSLEDG.ESINYR, ESLEDG.ESINYR,	in case of split due date/manual split (*) Then ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Original invoice number (ARS251MI/ LstInvInfo.SEXI)<45> without separator. Else ID is a concatenation of Invoice year (ARS200MI/ GetInvoice INYR) <4> + Invoice number (ARS200MI/
FPLEDG.EPINYR, FPLEDG.EPSINO, APS200MI/GetInvoice,	Then ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Original invoice number (ARS251MI/ LstInvInfo.SEXI)<45> without separator. Else ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Invoice number (ARS200MI/ GetInvoice.CINO)<15>. (*) If ARS251MI returns a record from table FSLEDX with info
FPLEDG.EPINYR, FPLEDG.EPSINO, APS200MI/GetInvoice, FSLEDG.ESINYR, FSLEDG.ESCINO,	Then ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Original invoice number (ARS251MI/ LstInvInfo.SEXI)<45> without separator. Else ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Invoice number (ARS200MI/ GetInvoice.CINO)<15>.
FPLEDG.EPINYR, FPLEDG.EPSINO, APS200MI/GetInvoice, FSLEDG.ESINYR, FSLEDG.ESCINO,	Then ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Original invoice number (ARS251MI/ LstInvInfo.SEXI)<45> without separator. Else ID is a concatenation of Invoice year (ARS200MI/ GetInvoice.INYR) <4> + Invoice number (ARS200MI/ GetInvoice.CINO)<15>. (*) If ARS251MI returns a record from table FSLEDX with info category (SEXN) = 227 or 228, use additional information (SEXI) =

SourceSystemJournalEntry 5 1 2 1

consume maximum length, from GLS200MI.LstVoucherLines.

If Transaction code (TRCD) = 40 (Supplier invoices - AP) The field indicates unique ID of supplier invoice set to concatenation of Year (YEA4)<4> + Journal number (JRNO)<7> + Journal sequence number (JSNO)<7> without separator. The position of each field is determined by its maximum length, specified in brackets.

JRNO and JSNO 7 are left padded with zeroes to 7 digits.

The element is not created for other transactions (that is other Transaction codes (TRCD) or for Transaction code (TRCD) = 10,

other FAM functions (FEID) than listed above).

The field indicates the company and division, displayed as

CONO DIVI.

The field indicates the location (that is warehouse) of the related

sales invoice (that is TRCD=10).

The location is only applicable for sales invoices (TRCD=10) created with one of the following FAM functions AR20, CO20, FA50, MF01, Ol20, PO20 or SO20 and is only populated for invoices available in (CMS500, table CINHED).

SourceSystemJournalEntry/JournalEntryLine/SourceDocumentReference/AlternateDocumentID/ID

FGLEDG.EGTRCD, GLS200MI/LstVoucherLines,

CIDHED.CIWHLO; INVBODMI/GetHeader

FSLEDG.ESINYR, FSLEDG.ESCINO.

@accountingEntity FGLEDG.EGCONO.

@location

FGLEDG.EGDIVI;

ARS200MI/GetInvoice, FPLEDG.EPINYR, FPLEDG.EPSINO, APS200MI.GetInvoice;

The field indicates the Invoice year and number (as stored in the AP or AR ledger) for Invoice and Payment transactions, depending on Transaction code (TRCD).

If TRCD = 10 OR TRCD = 20

Then ID is a concatenation of Invoice year (INYR) +'-'+ Invoice number (CINO) from ARS200MI/GetInvoice if both (INYR) and (CINO) are not empty, or just one of them without separator if other is empty.

If TRCD = 40 OR TRCD = 50

Then ID is a concatenation of Invoice year (INYR) +'-'+ Invoice

number (SINO) from APS200MI/GetInvoice.

The element is not created for other transactions.

@accountingEntity FGLEDG.EGCONO,

FGLEDG.EGDIVI;

The field indicates the company and division, displayed as CONO DIVI

SourceSystemJournalEntry/JournalEntryLine/SourceDocumentReference/DocumentDateTime

FGLEDG.EGTRCD, GLS200MI/LstVoucherLines,

FPLEDG.EPIVDT.

FPLEDG.EPACDT, APS200MI/GetInvoice,

FSLEDG.ESIVDT, FSLEDG.ESACDT, ARS200MI/GetInvoice;

The field indicates the Invoice date (for invoices) or the Accounting date (for payments), depending on Transaction code (TRCD), formatted as yyyy-mm-dd.

If TRCD = 10 set to Invoice date (ARS200MI/GetInvoice.IVDT). If TRCD = 20 set to Accounting date (ARS200MI/GetInvoice.ÁCDT). If TRCD = 40 set to Invoice date (APS200MI/GetInvoice.IVDT) If TRCD = 50 set to Accounting date (APS200MI/GetInvoice.ACDT).

The element is not created for other transactions.

SourceSystemJournalEntry/JournalEntryLine/Description

FGLEDG.EGVTXT; GLS200MI/LstVoucherLines

The field indicates the voucher text.

SourceSystemJournalEntry/JournalEntryLine/ExchangeRateDateTime

FGLEDG.EGACDT; GLS200MI/LstVoucherLines

The field indicates the accounting date as the exchange rate date, formatted as yyyy-mm-dd.

SourceSystemJournalEntry/JournalEntryLine/GLFullAccount

FGLEDG.EGAIT1; GLS200MI/LstVoucherLines

The field indicates the account, accounting dimension 1.

The field indicates the supplier invoice document types.
a) Alternatives if TotalAmount contains a positive value: - Set to 'DebitMemo' if corrective invoice (PEXN=435 exists for the invoice)
- Otherwise set to 'Invoice'.
b) Alternatives if TotalAmount contains a negative value (which means it reduces the amount owed to the Supplier): - Set to 'CreditMemo'.
The field in disease with south a Union a ID of sounding invariance and
The field indicates either the Unique ID of supplier invoice set to concatenation of Year (YEA4)<4> + Journal number (JRNO)<7> + Journal sequence number (JSNO)<7> without separator. The position of each field is determined by its maximum length, specified in brackets. JRNO and JSNO are left padded with zeroes to 7 digits or the Supplier invoice number (SINO).
The value used depends on the setting of the control property 'm3be_SupplierInvoiceSINOAsDocumentID' as described in KB 2107266 for NCR 11652).
The field indicates the company and division, displayed as CONO_DIVI.
The field indicates the Variation ID. It is retrieved from the message manifest.
The field indicates the Logical ID. System environment code retrieved from IONToolBox
The field indicates the following additional IDs: - Correlation ID (CORI) is a GUID and used in the M3 scanning solution for supplier invoices. The purpose with this key field is to be able to trace back to the invoice images stored in 'Infor Document Management' (IDM) from Business Engine Supplier invoice number (SINO). In case of Split due date invoice (PEXN=416 connected to invoice), the invoice number from field PEXI is used.
Set to 'CorrelationID' if Correlation ID (CORI) exists in the event data.
Set to 'Supplier' for supplier invoice number (SINO or for split due date invoice PEXI).
The field indicates the company and division, displayed as CONO DIVI.
The field indicates the supplier invoice number (SINO).
The field indicates when the record was last modified in M3.
The field indicates the ID of the user (CHID) from the first line of the voucher.
The field indicates the company and division, displayed as CONO DIVI.
The field indicates the Name (NAME) of the user.
The field indicates the Invoice date.
Set to 'SourceSystemJournalEntry' for reference to General Ledger voucher for the supplier invoice.
tID If VONO has a value in the event data then this section is created.
If DocumentReference comes with @type 'SourceSystemJournalEntry' the first three characters in the ID are the voucher number series (book of account) and remaining

<u> </u>	
	division or if BoA should be set to default by M3 BE, three underscore come before the Voucher number e.g. ' 21002595'.
SupplierInvoice/SupplierInvoiceHeader/DocumentReference/Document	ntID/ID
FPLEDG.EPYEA4, FPLEDG.EPVSER,	The field indicates the voucher number. It is a concatenation of Year + Voucher number series + Voucher number
FPLEDG.EPVONO;	The first four characters in the ID contain the year, the next three characters in the ID contain the voucher number series (Book of count, BoA) and remaining characters contain the voucher number. If
	BoA is not used, three underscore is entered before the Voucher number e.g. 'yyyy21002595'.
@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO DIVI.
SupplierInvoice/SupplierInvoiceHeader/ExtendedAmount FPLEDG.EPCUAM, FGLEDG.EPCUAM;	The field indicates the TotalAmount with total Tax/Amount deducted, the amount is in foreign currency.
@currencylD FPLEDG.EPCUCD;	The field indicates the foreign currency code.
SupplierInvoice/SupplierInvoiceHeader/ExtendedBaseAmount FGLEDG.EGACAM;	The field indicates the TotalBaseAmount with total Tax/BaseAmount deducted, the amount is in local currency.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the local currency code.
SupplierInvoice/SupplierInvoiceHeader/TotalAmount FPLEDG.EPCUAM;	The field indicates the Invoice amount in foreign currency.
	In the event, the foreign currency amount for a debit invoice comes as a negative value and a credit invoice as a positive value. Hence the negative sign is removed from the amount for debit invoices in the BOD. For credit invoices a negative sign is added to the amount in the BOD instead. This is done to follow BOD standard.
@currencylD FPLEDG.EPCUCD;	The field indicates the foreign currency code.
SupplierInvoice/SupplierInvoiceHeader/TotalBaseAmount FGLEDG.EGACAM; GLS200MI/GetVoucherLine	The field indicates the Invoice amount in local currency.
	The amount for a debit invoice comes as a negative value and a credit invoice as a positive value, therefore the amount sign must be reversed.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the local currency code.
SupplierInvoice/SupplierInvoiceHeader/SupplierParty/PartyIDs/ID FPLEDG.EPSUNO;	The field indicates the Supplier.
@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI;	The field indicates the accounting entity.
	If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
SupplierInvoice/SupplierInvoiceHeader/SupplierParty/PartyIDs/TaxID FGLEDG.EGVRNO; GLS200MI/LstVoucherLines	The field indicates the VAT Registration number (VRNO) of the supplier retreived from the supplier invoice voucher (value from first transaction found having a VRNO).
@schemeName	Set to 'TaxIdentificationNumber' when VAT registration number (VRNO) used.
SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates the name of the supplier (SUNO).
SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Name; CRS620MI/GetAddrPerDate	The field indicates the supplier name (SUNM) of the postal address (type 01).
	Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).
	(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD: Field ESFV defined with format NN-AAAAAA: - ADTE from position 1-2 of field ESFV - ADID from position 4-9 of field ESFV
SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Addre	
@type	Set to 'text'.
	JELIO IEAL.

Infor May 26, 2023 609

Set to 'text'.

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Address/AddressLine

CRS620MI/GetAddrPerDate

The field indicates the address line 1-4 (ADR1-ADR4) of the postal address (type 01).

Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).

(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD: Field ESFV defined with format NN-AAAAAA:

- ADTE from position 1-2 of field ESFV

- ADID from position 4-9 of field ESFV

Set to sequence number 1-4 for each address line available.

@sequence

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Address/CityName

; CRS620MI/GetAddrPerDate

The field indicates the city (TOWN) of the postal address (type 01).

Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).

(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD: Field ESFV defined with format NN-AAAAAA:

- ADTE from position 1-2 of field ESFV

ADID from position 4-9 of field ESFV

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Address/CountrySubDivisionCode

; CRS620MI/GetAddrPerDate

The field indicates the state code (ECAR) of the postal address (type

Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).

(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD: Field ESFV defined with format NN-AAAAAA:

- ADTE from position 1-2 of field ESFV

- ADID from position 4-9 of field ESFV

@listID ; CRS620MI/GetAddrPerDate

Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'States' if CountryCode is MX (Mexico)

Set to 'SubDivisions - <Country Code'>' for other countries.

Set to "SubDivisions" if no Country is specified

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Address/CountryCode

; CRS620MI/GetAddrPerDate

The field indicates the country code (CSCD) of the postal address (type 01).

Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).

(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD: Field ESFV defined with format NN-AAAAAA:

- ADTE from position 1-2 of field ESFV

- ADID from position 4-9 of field ESFV

Set to 'Countries'.

@listID

; CRS620MI/GetAddrPerDate

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/Location/Address/PostalCode

; CRS620MI/GetAddrPerDate

The field indicates the postal code (PONO) of the postal address (type 01).

Retrieved using Address type (ADTE) and number (ADID) from TXS035 - field 596 (*) and if not defined or address not found, default Address type ADTE) = 01, Address number (ADID) = ' ' (blank) with From Date (DAT1) = Invoice date (IVDT).

(*) TXS035MI.GetAddField with CONO/DIVI from event data, TYPE=7, ESAF=596 and BSCD=MNS100MI.GetBasicData.CSCD:

Oupplicitivoice	Field ESFV defined with format NN-AAAAAA:
	- ADTE from position 1-2 of field ESFV - ADID from position 4-9 of field ESFV
SupplierInvoice/SupplierInvoiceHeader/CustomerParty/Contact/ID FPLEDG.EPAPCD;	The field Authorized user.
SupplierInvoice/SupplierInvoiceHeader/RemitToParty/PartyIDs/ID FPLEDG.EPSPYN;	The indicates the Payee.
@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI:	The field indicates the accounting entity.
TT EEDO.ET DIVI,	If RemitToPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
SupplierInvoice/SupplierInvoiceHeader/RemitToParty/Name CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates the name of the payee (SPYN).
SupplierInvoice/SupplierInvoiceHeader/StructuredCreditorReference FPAPRN.PIPAIN; APS200MI/GetInvoice	The field indicated the parallel invoice number if entered for the invoice.
SupplierInvoice/SupplierInvoiceHeader/PurchaseOrderReference/Doc FPLEDX.EPPEXI; APS251MI/LstInvInfo	
	The purchase order number is the 11th to 20th character of the value in the field PEXI if GL information number (PEXN) = 402.
<pre>@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI;</pre>	The field indicates the company and division, displayed as CONO_DIVI.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Term/ID FPLEDG.EPTEPY; APS200MI/GetInvoice	The field indicates the payment term of the invoice.
@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO DIVI.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/PaymentTermC FPLEDG.EPTEPY; APS200MI/GetInvoice	code The field indicates the payment term of the invoice.
@accountingEntity FPLEDG.EPCONO FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO DIVI.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Term/Description CSYTAB.CTPARM; CRS175MI/GetGeneralCod	-
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Term/DueDateTFPLEDG.EPDUDT;	· · · · · · · · · · · · · · · · · · ·
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/ID FPLEDG.EPTECD; APS200MI/GetInvoice	The field indicated the cash discount term and the level with separator '-' (e.g. 030-1).
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/Descrit CSYTAB.CTPARM; CRS175MI/GetGeneralCode	ription The field indicates the description (position 1-72 of field PARM) of the cash discount term (TECD).
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/DueD FPCASH.PCCDT1, FPCASH.PCCDT1,	ateTime The field indicates the cash discount due date.
FPCASH.PCCDT1; APS200MI/GetCashDiscInfo SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/Amou	mtPaois Code
FPCASH.PCCDAM; APS200MI/GetCashDiscInfo	Set to 'TotalAmount' if Total amount (CUAM - sign reversed) from event data = Cash discount (CDAM - sign reversed) from cash discount table. Otherwise set to 'ExtendedAmount'.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/Disco FPCASH.PCCDP1, FPCASH.PCCDP2, FPCASH.PCCDP3; APS200MI/GetCashDiscInfo	untPercent The field indicates the cash discount percentage.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/Amou FPCASH.PCCDAM; APS200MI/GetCashDiscInfo	Int The field indicates the allowed cash discount for an invoice in foreign currency.
	The amount for a debit invoice comes as a negative value and a credit invoice as a positive value, therefore the amount sign must be reversed.
@currencyID FPLEDG.EPCUCD;	The field indicates the foreign currency code.
SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Discount/Base/ FPCASH.PCCDAM; APS200MI/GetCashDiscInfo	Amount The field indicates the allowed cash discount for an invoice in local currency (converted from cash discount - foreign currency).
	The amount for a debit invoice comes as a negative value and a

@currencyl	D
CMMIDIM	\sim

CMNDIV.CCLOCD; MNS100MI/GetBasicData

SupplierInvoice/SupplierInvoiceHeader/PaymentMethodCode CSYTAB.CTPARM; CRS175MI/GetGeneralCode

credit invoice as a positive value, therefore the amount sign must be reversed.

The field indicates the local currency code.

The field indicates the payment class of the payment method from the invoice (TRCD=40) using APS200MI.GetInvoice.

First Payment method AP is read (STKY = PYME), then the payment type connected to the method is read. Set the following if Payment class (PYCL) in payment type is:

- 0: Set to 'Cash'
- 1: Set to 'Cheque'
- 3: Set to 'ElectronicFundsTransfer'
- 4: Set to 'BankDraft
- 5: Set to 'DirectDebit'

Everything else is set to 'Cash'.

SupplierInvoice/SupplierInvoiceHeader/Tax

This section includes the Tax information per VAT code based on the details in the General Ledger (table FGLEDG) and the VAT method (VATT (CRS030MI.GetBasicData)) of the VAT code (VTCD):

- 1) VAT method 2-Combined (limited information)
- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2.
- 2) VAT method 3-Chain (limited information)
- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2.
- 3) Other VAT method
- a) If Tax/Amount (total CUAM) is = 0:00 but Tax/Calculation/ RateNumeric is not = 0% (this EU VAT or Reversed charge): Two sections of Tax created:

Invoice@type = 'Invoice' and 'DebitMemo':

Tax section 1 (positive amounts):

- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2 and ACAM/CUAM are positive.
- Tax/BasisAmount and /BasisBaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 3-9 (regardless amount sign).

Tax section 2 (negative amounts):

- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2 and ACAM/CUAM are negative.
- Tax/BasisAmount and /BasisBaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 3-9 (regardless amount sign) but amount outputted as negative (same amount as Tax section 1 but with reversed sign). Invoice@type = 'CreditMemo':

Tax section 1 (negative amounts):

- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2 and ACAM/CUAM are negative.
- Tax/BasisAmount and /BasisBaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 3-9 (regardless amount sign).

Tax section 2 (positive amounts):

- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2 and ACAM/CUAM are positive.
- Tax/BasisAmount and /BasisBaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 3-9 (regardless amount sign) but amount outputted as positive (same amount as Tax section 1 but with reversed sign).
- b) Otherwise: One section of Tax created:
- Tax/Amount and /BaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 1-2.
- Tax/BasisAmount and /BasisBaseAmount summarized per VAT code for all transactions with VAT account type (AT04) = 3-9.

Limitation: Invoices with split due date, will get the total VAT amount included for each sub invoice. This will be changed in the next version of the BOD.

@type

Infor May 26, 2023 61.

SupplierInvoice

CMNDIV.CCTATM; MNS100MI/GetBasicData	Set to 'SalesTax' if tax method (TATM) is 2, 3 or 4. Set to 'VAT' if tax method is 1.
SupplierInvoice/SupplierInvoiceHeader/Tax/ID FGLEDG.EGVTCD; GLS200MI/LstVoucherLines @accountingEntity	The field indicates the VAT code (VTCD - 2 digits).
FPLEDG.EPCONO FPLEDG.EPDIVI;	The field indicates the company and division, displayed as CONO DIVI.
SupplierInvoice/SupplierInvoiceHeader/Tax/BasisAmount FGLEDG.EGCUAM; GLS200MI/LstVoucherLines	The field indicates the VAT base amount (AT04 = 3-9) in foreign currency.
	Limitation: The field is not included for VAT method (VATT) 2-Combined or 3-Chain.
@currencyID FPLEDG.EPCUCD;	The field indicates the foreign currency code.
	Limitation: The field is not included for VAT method (VATT) 2-Combined or 3-Chain.
SupplierInvoice/SupplierInvoiceHeader/Tax/BasisBaseAmount FGLEDG.EGACAM; GLS200MI/LstVoucherLines	The field indicates the VAT base amount (AT04 = 3-) in local currency
	Limitation: The field is not included for VAT method (VATT) 2-Combined or 3-Chain.
@currencyID CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the local currency code.
	Limitation: The field is not included for VAT method (VATT) 2-Combined or 3-Chain.
SupplierInvoice/SupplierInvoiceHeader/Tax/Calculation/RateNumeric FGLEDG.EGVTP1; GLS200MI/LstVoucherLines	The field indicates the VAT percentage 1.
	Limitation: The field is not included for VAT method (VATT) 2-Combined or 3-Chain.
SupplierInvoice/SupplierInvoiceHeader/Tax/Description CSYTAB.CTTX40; CRS030MI/GetBasicData	The field indicates the description of the VAT code.
SupplierInvoice/SupplierInvoiceHeader/Tax/Amount FGLEDG.EGCUAM; GLS200MI/LstVoucherLines @currencyID	The field indicates the VAT amount (AT04 = 1-2) in foreign currency.
FPLEDG.EPCUCD;	The field indicates the foreign currency code.
SupplierInvoice/SupplierInvoiceHeader/Tax/BaseAmount FGLEDG.EGACAM; GLS200MI/LstVoucherLines @currencyID	The field indicates the VAT amount (AT04 = 1-2) in local currency.
CMNDIV.CCLOCD; MNS100MI/GetBasicData	The field indicates the local currency code.
SupplierInvoice/SupplierInvoiceHeader/UserArea/NameValue 1) FPLEDG.EPINYR 2) FPLEDG.EPACDT	The field indicates specific values required by an integration: 1) Invoice year (INYR)
3) FAPIBH.E5CORI	2) Accounting date (ACDT)
4) FPLEDG.EPYEA4,	Correlation ID (CORI) a) If CORI (in element AlternateDocument) is not empty, set to
FPLEDG.EPJRNO, FPLEDG.EPJSNO,	"YES".
APS200MI.GetUniqueKey	b) Else Set to "NO".
5) FPLEDX.EPPEXI, APS251MI/LstInvInfo,	Note: CORI (Correlation ID) is used for IDM integration. 4) Unique ID set to Year (YEA4), Journal number (JRNO - 7 digits)
FPLEDG.EPYEA4,	and Journal sequence number (JSNO - 7 digits). Required for the
FPLEDG.EPJRNO,	integration to Local.ly.
FPLEDG.EPJSNO, APS200MI/GetInvTotInfo,	 -Values from event data used as input for APS200MI.GetUniqueKey and TRCD set to "40".
APS200MI.SearchSupInvic	5) Original unique ID set to Year (YEA4), Journal number (JRNO - 7
6)FPLEDG.EPPYME,	digits) and Journal sequence number (JSNO - 7 digits) in case of
APS200MI.GetInvoice 7)FPLEDX.EPPEXI,	original invoice number (Correction/OriginalDocumentID) included for credit note (PEXN=455) and corrective invoice (PEXN=435).
APS251MI/LstInvInfo,	Required for the integration to Local.ly.
FPLEDG.EPSINO 8) FPLEDG.EPIVCL; 8) APS200MI/8) GetInvoice	 Values from event data and original invoice number (from PEXI, including invoice year) as retrieved for element "Correction/ OriginalDocumentID" used as input for APS200MI.GetIntTotInfo and APS200MI.SearchSupInvic (needed when Payee is different for
	original invoice). 6) Payment method (PYME). 7) Original Supplier Invoice (SINO) in case of credit note (PEXN=455) or corrective invoice (PEXN=435) derived from PEXI
@name	or corrective invoice (PEXN=435), derived from PEXI. 8) Invoice class (IVCL) of the invoice.
@name	Set to:
	1) "m3_InvoiceYear", If Invoice year (INYR). 2) Set to "m3_AccountingDate", If Accounting date (ACDT).

SupplierInvoice

4) Set to "m3 UniqueID", if Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO). 5) Set to "m3 OriginalUniqueID", if Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) for original invoice number. 6) Set to "lcl.PaymentMethod", if Payment method (PYME). 7) Set to "m3 OriginalSupplierInvoiceID SINO". 8) Set to "lcl. SubInvoice Type". @type 1) Set to "IntegerType", If Invoice year (INYR). 2) Set to "DateType", If Accounting date (ACDT). 3) Not set. 4) Set to "IntegerType", if Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO). 5) Set to "IntegerType", if Year (YEA4), Journal number (JRNO) and Journal sequence number (JSNO) for original invoice number. 6) Set to "StringType", if Payment method (PYME).
7) Set to "StringType".
8) Set to ""StringType". SupplierInvoice/SupplierInvoiceHeader/Status/Code Set to 'Open'. @listID Set to 'Supplier Invoice Status'. SupplierInvoice/SupplierInvoiceHeader/CurrencyExchangeRate/SourceCurrencyCode FPLEDG.EPCUCD; The field indicates the foreign currency code SupplierInvoice/SupplierInvoiceHeader/CurrencyExchangeRate/TargetCurrencyCode CMNDIV.CCLOCD; MNS100MI/GetBasicData The field indicates the local currency code. SupplierInvoice/SupplierInvoiceHeader/CurrencyExchangeRate/RateNumeric FPLEDG.EPARAT; APS200MI/GetInvoice The field indicates the exchange rate for the chosen currency. SupplierInvoice/SupplierInvoiceHeader/Correction/OriginalDocumentID/ID 1) FPLEDX.EPPEXI The field indicates unique ID of original supplier invoice in case of ÁPS251MI/LstInvInfo, credit note (PEXN=455) or corrective invoice (PEXN=435), set to FPLEDG.EPYEA4, concatenation of Original Year (YEA4)<4> + Original Journal number FPLEDG.EPJRNO, (JRNO)<7> +Original Journal sequence number (JSNO)<7> without FPLEDG.EPJSNO, separator. The position of each field is determined by its maximum APS200MI/GetInvTotInfo. length, specified in brackets. JRNO and JSNO are left padded with zeroes to 7 digits. APS200MI/SearchSupInvoic 2) FPLEDX.EPPEXI, FPLEDG.EPSINO, APS251MI/LstInvInfo; @accountingEntity FPLEDG.FPCONO, The field indicates the company and division, displayed as

CONO DIVI.

FPLEDG.FPDIVI; SupplierInvoice/SupplierInvoiceHeader/Correction/ReasonCode FPLEDX.EPPEXI; APS251MI/LstInvInfo

The field indicates the reason (PEXN=457) for a credit note or corrective invoice (PEXN=435) created for the original invoice, set to PEXI.

May 26, 2023

SupplierPartyMaster SupplierPartyMaster	
@category	TI SILL II
CIDMAS.IDSUTY; CRS620MI/GetBasicData	The field indicates the supplier type (SUTY).
	Set to 'Supplier' if SUTY = 0.
	Set to 'Agent' if SUTY = 1.
	Set to 'Only Payee' if SUTY = 2.
	Set to 'Supplier Group' if SUTY = 3. Set to 'Forwarding Agent' if SUTY = 5.
	Set to 'Insurance Company' if SUTY = 6.
	Set to 'Miscellaneous Suppliers' if SUTY = 8.
	Set to 'Trade-in Supplier' if SUTY = 9.
SupplierPartyMaster/PartyIDs/ID CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
@accountingEntity	The field indicates the accounting outiful
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab,
GWINDIV.GCDIVI., /	this is displayed as Company (CONO). Otherwise, this is displayed a
	Company and Division (CONO DIVI).
@variationID	· · · · · · · · · · · · · · · · · · ·
	The field indicates the sequence number that identifies the number of times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
SupplierPartyMaster/PartyIDs/DisplayID	The hold indicates the logical is of the system.
CIDMAS.IDSUNO; CRS620MI/GetBasicData	The field indicates the unique identity of a supplier.
SupplierPartyMaster/PartyIDs/TaxID	
CIDVEN.IITINO	The field indicates the Organization number (CORG), Organization
CIDMAS.IDCORG	number 2 (COR2), VAT registration number (VRNO), Tax ID for
CIDMAS IDVENIO	Supplier (TINO) and the VAT Code (VTCD).
CIDMAS.IDVRNO CIDVEN.IIVTCD.; CRS620MI/GetBasicData	
@schemeName	
	Set to 'CountryIdentificationNumber2' if PartyIDs/TaxID is CORG.
	Set to 'CountryIdentificationNumber2' if PartyIDs/TaxID is COR2.
	Set to 'TaxIdentificationNumber' if PartyIDs/TaxID is VRNO.
	Set to 'VatCode' if PartyIDs/TaxID is VTCD.
0	Leave blank if PartyIDs/TaxID is TINO.
SupplierPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC; CRS620MI/GetBasicData	The field indicates the Standard Carrier Alpha Code (SCAC).
SupplierPartyMaster/LastModificationDateTime	
CIDMAS.IDLMTS; / SupplierPartyMaster/LastModificationPerson/IDs/ID	The field indicates the date and time the document was last modified.
CIDMAS.IDCHID; /	The field indicates the User ID of the person who last modified the
	record.
@accountingEntity	
CIDMAS.IDCONO	The field indicates the accounting entity.
CMNDIV.CCDIVI.; /	If SupplierPartyMaster is enabled in BOD Processor Master AE tab,
	this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Supplior Party Master / Lost Modification Parson / Name	Company and Division (CONO DIVI).
SupplierPartyMaster/LastModificationPerson/Name CSYUSR.CRRENM; MNS150MI/GetUserData	The field indicates the name of the person who last modified the
COTOCIA. CITALETAM, MINO TOOMIN COLOGOIDALA	record.
SupplierPartyMaster/Name	
CIDMAS.IDSUNM; CRS620MI/GetBasicData	The field indicates the supplier name.
SupplierPartyMaster/Location @type	
CIDADR	The field indicates the type of address to use.
.SAADTE; CRS620MI/LstAddresses	
	Set to 'Postal' if Address Type is 01.
	Set to 'Street' if Address Type is 02.
	Set to 'Pickup' if Address Type is 03.
	Set to 'Origin' if Address Type is 04.
	Set to 'Final' if Address Type is 05. Set to 'Bank' if Address Type is 10.
SupplierPartyMaster/Location/Name	Cotto Built ii Addices Type is 10.
CIDADR.SASUNM; CRS620MI/LstAddresses	The field indicates the supplier name.
SupplierPartyMaster/Location/Address	
@type	Set to 'text'.
SupplierPartyMaster/Location/Address/AddressLine	OU to tok.
CIDADR.SAADR1	The field indicates the address line.
CIDADR.SAADR2	and diddless into
CIDADR.SAADR3	
CIDADR.SAADR4.; CRS620MI/LstAddresses	

@sequence	The field indicates the address line sequence.
SupplierPartyMaster/Location/Address/CityName	
CIDADR.SATOWN; CRS620MI/LstAddresses SupplierPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR; CRS620MI/LstAddresses	The field indicates the city name. The field indicates an area, province or state within a country.
@listID	Setto 'Canadian Provinces' if the country is CA (Canada). Setto 'France - Departements' if the country is FR (France). Set to 'US States' if the country is US (United States). Set to 'SubDivisions - <country code="">' for other countries. Set to "SubDivisions" if no Country is specified.</country>
SupplierPartyMaster/Location/Address/CountryCode	Set to Subdivisions if no Country is specified.
CIDADR.SACSCD; CRS620MI/LstAddresses @listID	The field indicates the country code.
SupplierPartyMaster/Location/Address/PostalCode	Set to 'Countries'.
CIDADR.SAPONO; CRS620MI/LstAddresses	The field indicates the postal code.
SupplierPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT; CRS620MI/LstAddresses	The field indicates the date from which the record is valid.
SupplierPartyMaster/Communication @sequence	
	The field indicates the communication sequence number. Set to '1' if PHNO. Set to '2' if PHN2. Set to '3' if TFNO.
@preferredIndicator	Set to 'false'.
SupplierPartyMaster/Communication/ChannelCode	Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
SupplierPartyMaster/Communication/UseCode	Get to Goriffication Originals.
@listID	Set to "Phone" if telephone number 1, telephone number 2 or facsimile number.
	Set to 'Communication Use Codes'.
SupplierPartyMaster/Communication/DialNumber CIDMAS.IDPHNO CIDMAS.IDPHN2 CIDMAS.IDTFNO.: CRS620MI/GetBasicData	The field indicates the telephone 1, telephone number 2 or facsimile number.
SupplierPartyMaster/Communication/Preference/Indicator	
SupplierPartyMaster/Contact	Set to 'false'.
@type CIDREF.IRRFTY; CRS620MI/LstSupplierRef	Set to 'Purchase' if Reference Type is 10. Set to 'Repair or Subcontract' if Reference Type is 15. Set to 'Delivery Receipt' if Reference Type is 20. Set to 'Claim' if Reference Type is 25. Set to 'Financial' if Reference Type is 30. Set to 'Agreement' if Reference Type is 35.
SupplierPartyMaster/Contact/ID	
CIDREF.IRRFID; CRS620MI/LstSupplierRef @accountingEntity	The field indicates the reference ID.
CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
SupplierPartyMaster/Contact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the name of the person to be contacted for issues regarding customer orders or purchase orders.
SupplierPartyMaster/Contact/Communication @preferredIndicator	Out to Malant
SupplierPartyMaster/Contact/Communication/ChannelCode	Set to 'false'.
	Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
@listID	Set to 'Communication Channels'.
SupplierPartyMaster/Contact/Communication/UseCode	Set to "Phone" if telephone number 1, telephone number 2 or facsimile number.
@listID	

Supplier Farty Master	
	Set to 'Communication Use Codes'.
SupplierPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO CIDREF.IRTFNO .; CRS620MI/LstSupplierRef	The field indicates the telephone 1, telephone number 2 or facsimile number.
SupplierPartyMaster/Contact/Communication/URI CIDREF.IREMAL; CRS620MI/LstSupplierRef	The field indicates the e-mail address.
SupplierPartyMaster/Contact/Communication/Preference/Indicator	Set to 'false'.
SupplierPartyMaster/LanguageCode CIDMAS.IDLNCD; CRS620MI/GetBasicData	The field indicates the language in which external documents are to be printed.
SupplierPartyMaster/PaymentTermID CIDVEN.IITEPY; CRS620MI /GetBasicData	The field indicates how the payment due date is to be calculated.
SupplierPartyMaster/PaymentMethodCode CIDVEN.IIPYME; CRS620MI /GetBasicData	The field indicates the method on how the supplier payment is processed.
@listID	Set to 'Payment Methods'.
SupplierPartyMaster/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/LstByAccHolder2 @accountingEntity CIDMAS.IDCONO	The field indicates the ID for the bank connected with the supplier. The field indicates the accounting entity.
CMNDIV.CCDIVI.; /	The hold indicates the decodrining chary.
SupplierPartyMaster/FinancialParty/BranchParty/PartyIDs/BICID CBANAC.BCBBRN; CRS692MI/LstByAccHolder2	The field indicates the ID of the bank branch.
SupplierPartyMaster/FinancialParty/FinancialAccount/ID CBANAC.BCBKID; CRS692MI/LstByAccHolder2	The field indicates the ID of the bank account.
SupplierPartyMaster/FinancialParty/FinancialAccount/BBANID CBANAC.BCBACN; CRS692MI/LstByAccHolder2	The field indicates the bank account number that is not in the format IBAN (e.g. Basic Bank Account Number).
SupplierPartyMaster/FinancialParty/FinancialAccount/IBANID CBANAC.BCIBAN; CRS692MI/LstByAccHolder2	The field indicates the international bank account number.
SupplierPartyMaster/FinancialParty/FinancialAccount/Name CBANAC.BCBANA; CRS692MI/LstByAccHolder2	The field indicates the bank account name.
SupplierPartyMaster/SalesContact/ID CIDREF.IRRFTY CIDREF IRRED - CRSC20MI/LatSupplierDaf	The field indicates the supplier reference.
CIDREF.IRRFID.; CRS620MI/LstSupplierRef	This is a concatenation of the reference type and reference separated by '-'.
	E.g. 10-Add1
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
SupplierPartyMaster/SalesContact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the contact name.
	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/SalesContact/Communication	
@preferredIndicator	Set to 'false'.
	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/SalesContact/Communication/ChannelCode	Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
@lie4D	Note: Display only if RFTY = 10 (Purchase).
@listID	Set to 'Communication Channels'.
	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/SalesContact/Communication/UseCode	Set to "Phone" if telephone number 1, telephone number 2 or facsimile number.
@listID	Note: Display only if RFTY = 10 (Purchase).
<u></u>	Set to 'Communication Use Codes'.
	Note: Display only if RFTY = 10 (Purchase).

SupplierPartyMaster/SalesContact/Communication/DialNumber CIDREF.IRPHNO CIDREF.IRTFNO .; CRS620MI/LstSupplierRef	The field indicates the telephone 1, telephone number 2 or facsimile number.
., Отсоволительного	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/SalesContact/Communication/URI CIDREF.IREMAL; CRS620MI/LstSupplierRef	The field indicates the e-mail address.
	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/SalesContact/Communication/Preference/Indica	tor Set to 'false'.
	Note: Display only if RFTY = 10 (Purchase).
SupplierPartyMaster/ShippingContact/ID CIDREF.IRRFTY CIDREF.IRRFID.; CRS620MI/LstSupplierRef	The field indicates the supplier reference. This is a concatenation of the reference type and reference separated by '-'.
	E.g. 10-Add1
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).
SupplierPartyMaster/ShippingContact/Name	-
CIDREF.IRYRE1; CRS620MI/LstSupplierRef SupplierPartyMaster/ShippingContact/Communication	The field indicates the contact name.
@preferredIndicator	Set to 'false'.
SupplierPartyMaster/ShippingContact/Communication/ChannelCode	Display only if RFTY = 20 (Delivery receipt).
supplier ary musicing importage of the control of t	Set to "Phone" if telephone number 1 or 2 or facsimile number. Set to "EMail" if e-mail address.
O.C. AID	Note: Display only if RFTY = 20 (Delivery receipt).
@listID	Set to 'Communication Channels'.
	Note: Display only if RFTY = 20 (Delivery receipt).
SupplierPartyMaster/ShippingContact/Communication/UseCode	Set to "Phone" if telephone number 1, telephone number 2 or facsimile number.
0.17.47	Note: Display only if RFTY = 20 (Delivery receipt).
@listID	Set to 'Communication Use Codes'.
	Note: Display only if RFTY = 20 (Delivery receipt).
SupplierPartyMaster/ShippingContact/Communication/DialNumber CIDREF.IRPHNO CIDREF.IRTFNO .; CRS620MI/LstSupplierRef	The field indicates the telephone 1, telephone number 2 or facsimile number.
., от сосотии состария и те	Note: Display only if RFTY = 20 (Delivery receipt).
SupplierPartyMaster/ShippingContact/Communication/URI CIDREF.IREMAL; CRS620MI/LstSupplierRef	The field indicates the e-mail address.
	Note: Display only if RFTY = 20 (Delivery receipt).
SupplierPartyMaster/ShippingContact/Communication/Preference/Inc	<i>licator</i> Set to 'false'.
	Note: Display only if RFTY = 20 (Delivery receipt).
SupplierPartyMaster/CustomerServiceContact/ID	
CIDREF.IRRFTY CIDREF.IRRFID.; CRS620MI/LstSupplierRef	The field indicates the supplier reference. This is a concatenation of the reference type and reference separated by '-'.
@accounting Entity	E.g. 10-Add1
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
SupplierPartyMaster/CustomerServiceContact/Name CIDREF.IRYRE1; CRS620MI/LstSupplierRef	The field indicates the contact name.

aguS	lierParty	Master
------	-----------	--------

SupplierPartyMaster/CustomerServiceContact/Communication Set to "false". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/ChannelCode Set to "Thone" if telephone number 1 or 2 or facsimile number. Set to "Email" if e-mail address. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Channels". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to "Communication Use Codes." Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes." Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dia/Number The feld indicates the telephone 1, telephone number 2 or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dia/Number CIDREF.IRHNO CIDREF		
SupplierPartyMaster/CustomerServiceContact/Communication @ijpreferedIndicator Set to Yalse'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Chameloo @ijsttD @ijsttD SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Sol to "Phone" if telephone number 1 or 2 or facsimile number. Set to "Communication Channels". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Sol to "Phone" if telephone number 1 to lephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Sol to "Phone" if telephone number 1, telephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode The Identification Use Codes: Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode The Identification by Identification or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Note: Display only if RFTY = 15 (Repair or subcontract) or		Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
Set to Talse. Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to Technal if the Idephone number 1, telephone number 2 or facsimile number. Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 36 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to Technolise (Idephone number 1, telephone number 2 or facsimile number. Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 36 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DisPlaymoner (DIRET_IRPHNO OF SEQUIMILALSupplierRef Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DisPlaymoner Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DisPlaymoner Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Perference Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Perference Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). The field indicates the sendence text that can be used for selecting reports or for individual information. SupplierPartyMaster/CustomerServiceContact/Communication/Perference Set to Talse. Note: Display only if RETY = 15 (Repair or subcontract) or 25 (Claim) or 30 (
supplierPartyMaster/CustomerServiceContact/Communication/ChannelCode Set to "Phone" if lelephone number 1 or 2 or faceimile number. Set to "EMail" if e-mail address. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Channels". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Channels". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dalt/union CIDREF.IRTPNO CI	2	Set to 'false'.
Sat to "Phone" if felephone number 1 or 2 or facsimile number. Sot to "Ehalf" if -email address. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Channels". Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to "Phone" if felephone number 1, telephone number 2 or faceimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCodes: Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DisNumber CIDREF.IRENAL; CRS620MIt.asSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseContact/Communica		<u> </u>
and (an included in the context of t	SupplierPartyMaster/CustomerServiceContact/Communication/Cha	Set to "Phone" if telephone number 1 or 2 or facsimile number.
Set to 'Communication Channels'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set by 'Communication Use Codes', Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DisPlanmber CIDREF.IRPHNO CIDREF.IRPHNASter/CustomerServiceContact/Communication/URI SupplierPartyMaster/CustomerServiceContact/Communication/URI CIDREF.IRPHNASter/CustomerServiceContact/Communication/URI CIDREF.IRPHNASTER/	@listID	Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes; Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dis/Number CICIREF.IRPHNO CICIREF.IRPHN		Set to 'Communication Channels'.
SupplierPartyMaster/CustomerServiceContact/Communication/UseCode Set to "Phone" if telephone number 1, telephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). Set to "Communication Use Codes": Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dial/humber CIDREF.IRPHNO CIDREF.IRPHNO CIDREF.IRPHNO CIDREF.IRPHNO On or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Ural number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Ural CIDREF.IREMAL; CRS620MI/LatSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/PreferenceIndicator SupplierPartyMaster/CustomerServiceContact/Communication/PreferenceIndicator SupplierPartyMaster/UserArea 1) CIDMAS.IDCF11 1) CIDMAS.IDCF11 1) CIDMAS.IDCF11 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 3) CIDMAS.IDCF13 CRS620MI/GetBasicData 3) CIDMAS.IDCF14 CRS620MI/GetBasicData 4) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 4) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField3". 6) CIDMAS.IDCF15 CRS620MI/GetBasicData 6) CIDMAS.IDCF16 CRS620MI/GetBasicData 7) CMNUSR.JUEUID MINISTOMI/GetBasicData 8) CIDMAS.IDCF16 CRS620MI/GetBasicData 6) CIDMAS.IDCF16 CRS620MI/GetBa		Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
Set to "Phone" if lelephone number 1, telephone number 2 or facsimile number. Note. Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 30 (Agreement). Set to "Communication Use Codes". Note. Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/DialNumber. CIDREF.IRPNO CIDREF.I	SupplierPartyMaster/CustomerServiceContact/Communication/Use	
### Or 30 (Financial) or 35 (Agreement). Set to 'Communication Use Codes'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). **The field indicates the telephone 1, telephone number 2 or facsimile number.** CIDREF.IRTPNO C		Set to "Phone" if telephone number 1, telephone number 2 or
Set to 'Communication Use Codes'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dial/Number CICIREF IRFNHO The field indicates the telephone 1, telephone number 2 or facsimile number. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/VRI CICIREF IRFNHAL; CRS620MI/LstSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Prerence/Indicator Set to 'false' Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS IDCFII 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField': 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField': 4) CIDMAS IDCFI4 CRS620MI/GetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField': 6) CIDMAS IDCFI5 CRS620MI/GetBasicData 7) CMNUSR JUEUID MMS150MI/GetUserData 8) CIDMAS IDCFI6 CRS620MI/GetBasicData 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField': 6) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports o	@listID	Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Dial/Number CIDREF IRFNHO CIDREF IREMAL; CRS620MI/LstSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Proferror Foreign or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Proferror Set to Yalse*. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS IDCF11 CRS620MI/CetBasicData 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 4) CIDMAS IDCF13 CRS620MI/CetBasicData 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 5) CIDMAS IDCF14 CRS620MI/CetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 6) CIDMAS IDCF15 CRS620MI/CetBasicData 7) CMNUSR JUEUID MNS1CMAS IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField4". 5) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField4". 6) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField4".	w,10112	Set to 'Communication Use Codes'.
CIDREF.IRPHNO CIDREF.IRTFNO CIRCE. IRRTFNO CIRCE. IRRTFNO CIRCE. IRRTFNO CIRCE. IRRTFNO CIRCE. IRRTP = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/URI CIDREF.IREMAL, CRS620MI/LstSupplierRef The field indicates the e-mail address. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator SupplierPartyMaster/UserArea 1) CIDMAS.IDCF1 CRS620MI/CetBasicData 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to "SupplierFreeField2". 4) CIDMAS.IDCF14 CRS620MI/CetBasicData 4) CIDMAS.IDCF15 CRS620MI/CetBasicData 4) CIDMAS.IDCF16 CRS620MI/CetBasicData 4) CIDMAS.IDCF16 CRS620MI/CetBasicData 6) CIDMAS.IDCF17 CRS620MI/CetBasicData 6) CIDMAS.IDCF18 CRS620MI/CetBasicData 7) CMNUSR.JUEUID MNS150MI/CetUserData 8) CIDMAS.IDCF18 CRS620MI/CetBasicData 6) CIDMAS.IDCF19 CRS620MI/CetBasicData 7) CMNUSR.JUEUID MNS150MI/CetUserData 8) CIDMAS.IDCF17 CRS620MI/CetBasicData 7) CMNUSR.JUEUID MNS150MI/CetUserData 8) CIDMAS.IDCF18 CRS620MI/CetBasicData 7) CMNUSR.JUEUID CRS620MI/CetBasicData		Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
CIDREF.IRTFNO CRS620Ml/LstSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/URI CIDREF.IREMAL, CRS620Ml/LstSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator Set to 'fialse'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCF1 CRS620Ml/GetBasicData 2) CIDMAS.IDCF12 CRS620Ml/GetBasicData 3) CIDMAS.IDCF12 CRS620Ml/GetBasicData 4) CIDMAS.IDCF13 CRS620Ml/GetBasicData 4) CIDMAS.IDCF14 CRS620Ml/GetBasicData 5) CIDMAS.IDCF14 CRS620Ml/GetBasicData 4) CIDMAS.IDCF15 CRS620Ml/GetBasicData 5) CIDMAS.IDCF16 CRS620Ml/GetBasicData 6) CIDMAS.IDCF16 CRS620Ml/GetBasicData 7) CMNUSR.JUEUID MNST50Ml/GetBasicData 7) CMNUSR.JUEUID		
Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/URI CIDREF.IREMAL, CRS620Mi/LstSupplierRef The field indicates the e-mail address. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator Set to false'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCF11 CRS620MI/GetBasicData 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField1'. CRS620MI/GetBasicData 4) CIDMAS.IDCF13 CRS620MI/GetBasicData 4) CIDMAS.IDCF14 CRS620MI/GetBasicData 4) CIDMAS.IDCF15 CRS620MI/GetBasicData 5) CIDMAS.IDCF15 CRS620MI/GetBasicData 6) CIDMAS.IDCF16 CRS620MI/GetBasicData 7) CNNUSR.JUEUID MNS150MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 9) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 9) CIDMAS.IDSTAT CRS620MI/GetBasicData 9) CIDMAS.IDSTAT CRS620MI/GetBasicData 9) CIDMAS.IDSTAT CRS620MI/GetBasicData 9) CIDMAS.IDSTAT CRS620MI/GetBasicData 1) CIDMAS.IDSTAT CRS620MI/GetBasicData 1) CIDMAS.IDSTAT CRS620MI/GetBasicData 1) CIDMAS.IDSTAT CRS620MI/GetBasicData 1) CIDMAS.IDSTAT CRS620MI/GetBasicData 2) CIDMAS.IDSTAT CRS620MI/GetBasicData 3) CIDMAS.IDSTAT CRS620MI/GetBasicData 4) CIDMAS.IDSTAT CRS620MI/GetBasicData 3) CIDMAS.IDSTAT CRS620MI/GetBasicData 4) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620	CIDREF.IRTFNO	·
CIDREF.IREMAL; CRS620MI/LstSupplierRef Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator Set to false. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCF11 CRS620MI/GetBasicData 2) CIDMAS.IDCF12 CRS620MI/GetBasicData 3) CIDMAS.IDCF12 CRS620MI/GetBasicData 3) CIDMAS.IDCF13 CRS620MI/GetBasicData 4) CIDMAS.IDCF14 CRS620MI/GetBasicData 5) CIDMAS.IDCF16 CRS620MI/GetBasicData 5) CIDMAS.IDCF16 CRS620MI/GetBasicData 4) CIDMAS.IDCF16 CRS620MI/GetBasicData 5) CIDMAS.IDCF15 CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.IDALSU CRS620MI/GetBasicData 8) CIDMAS.IDALSU CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSUSR.JUEUID Set attribute name to "SupplierFreeField4". 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 6) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMSCR620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData	.; CRS620MI/LstSupplierRef	Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator Set to false'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCF11 CRS620MI/GetBasicData 3) CIDMAS.IDCF12 CRS620MI/GetBasicData 3) CIDMAS.IDCF12 3) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField1'. CRS620MI/GetBasicData 3) CIDMAS.IDCF13 CRS620MI/GetBasicData 4) CIDMAS.IDCF14 CRS620MI/GetBasicData 5) CIDMAS.IDCF14 CRS620MI/GetBasicData 5) CIDMAS.IDCF15 CRS620MI/GetBasicData 5) CIDMAS.IDCF15 CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 5) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 8) CIDMAS.IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 6) Search Key, The field indicates a Search key. Set attribute name to 'SupplierFreeField5'.		
SupplierPartyMaster/CustomerServiceContact/Communication/Preference/Indicator Set to false'. Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCF11 1) User-defined field 1 - supplier. CR68c20MI/GetBasicData 2) CIDMAS.IDCF12 CR69c20MI/GetBasicData 3) CIDMAS.IDCF13 CR69c20MI/GetBasicData 3) CIDMAS.IDCF13 CR69c20MI/GetBasicData 4) CIDMAS.IDCF13 CR69c20MI/GetBasicData 4) CIDMAS.IDCF14 CR69c20MI/GetBasicData 4) CIDMAS.IDCF14 CR69c20MI/GetBasicData 5) CIDMAS.IDCF15 CR69c20MI/GetBasicData 6) CIDMAS.IDCF15 CR69c20MI/GetBasicData 6) CIDMAS.IDALSU CR69c20MI/GetBasicData 6) CIDMAS.IDALSU CR69c20MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetBasicData 5) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 6) CIDMAS.IDALSU CR69c20MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 8) CIDMAS.IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SupplierFreeField5'.		Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
or 30 (Financial) or 35 (Agreement). SupplierPartyMaster/UserArea 1) CIDMAS.IDCFI1 CRS620MI/GetBasicData 1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField1'. 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField2'. 4) CIDMAS.IDCFI3 CRS620MI/GetBasicData 4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 5) CIDMAS.IDCFI5 The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField2'. 6) CIDMAS.IDCFI5 The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 6) CIDMAS.IDALSU CRS620MI/GetBasicData The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 4) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 6) CIDMAS.IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.	SupplierPartyMaster/CustomerServiceContact/Communication/Pre	
1) User-defined field 1 - supplier. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField1'. 2) User-defined field 2 - item. 3) CIDMAS.IDCFI3 CRS620MI/GetBasicData 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField2'. 4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 4) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 4) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		Note: Display only if RFTY = 15 (Repair or subcontract) or 25 (Claim) or 30 (Financial) or 35 (Agreement).
CRS620MI/GetBasicData 2) CIDMAS.IDCFI2 CRS620MI/GetBasicData 3) CIDMAS.IDCFI3 CRS620MI/GetBasicData 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField1'. 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField2'. 4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 5) CIDMAS.IDCFI5 CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetBasicData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 7) CMNUSR.JUEUID Set attribute name to 'SupplierFreeField4'. 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		
CRS620MI/GetBasicData 2) User-defined field 2 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField2'. 4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 6) CIDMAS.IDCFI5 CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 5) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SupplierFreeField5'.		The field indicates the user-defined text that can be used for selecting
The field indicates the user-defined text that can be used for selecting reports or for individual information. 4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. 5) CIDMAS.IDCFI5 CRS620MI/GetBasicData 6) CIDMAS.IDALSU CRS620MI/GetBasicData 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		Set attribute name to 'SupplierFreeField1'.
4) CIDMAS.IDCFI4 CRS620MI/GetBasicData 3) User-defined field 3 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField3'. 4) User-defined field 4 - item. CRS620MI/GetBasicData 4) User-defined field 4 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 8) CIDMAS.IDSTAT CRS620MI/GetBasicData 8) CIDMAS.IDSTAT The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		The field indicates the user-defined text that can be used for selecting reports or for individual information.
reports or for individual information. Set attribute name to 'SupplierFreeField3'. 4) User-defined field 4 - item. CRS620MI/GetBasicData The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField4'. 8) CIDMAS.IDSTAT CRS620MI/GetBasicData S) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		3) User-defined field 3 - item.
The field indicates the user-defined text that can be used for selecting reports or for individual information. 7) CMNUSR.JUEUID MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData .; / 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.	,	reports or for individual information.
MNS150MI/GetUserData 8) CIDMAS.IDSTAT CRS620MI/GetBasicData .; / 5) User-defined field 5 - item. The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		The field indicates the user-defined text that can be used for selecting
8) CIDMAS.IDSTAT CRS620MI/GetBasicData .; / The field indicates the user-defined text that can be used for selecting reports or for individual information. Set attribute name to 'SupplierFreeField5'. 6) Search Key. The field indicates a Search key. Set attribute name to 'SearchKey'.		
The field indicates a Search key. Set attribute name to 'SearchKey'.	CRS620MI/GetBasicData	The field indicates the user-defined text that can be used for selecting reports or for individual information.
7) Buyer Security User ID.		The field indicates a Search key.
		7) Buyer Security User ID.

SupplierPartyMaster	
	The field indicates the user ID of the buyer. Set attribute name to 'BuyerSecurityUserID'.
	8) Status The field indicates the supplier status. Set attribute name to 'M3Status'. If STAT=05, set NameValue to 05 - Supplier template. If STAT=10, set NameValue to 10 - Preliminary. If STAT=20, set NameValue to 20 - Approved. If STAT=30, set NameValue to 30 - Stopped. If STAT=90, set NameValue to 90 - Deactivated.
SupplierPartyMaster/Status/Code CIDMAS.IDSTAT; CRS620MI/GetBasicData	The field indicates the status.
	Set to 'Closed' if status is 05. Set to 'Pending' if status is 10. Set to 'Open' if status is 20. Set to 'Hold' if status is 30. Set to 'Deleted' if status is 90 or if supplier is deleted.
SupplierPartyMaster/CurrencyCode CIDVEN.IICUCD; CRS620MI/GetBasicData	The field indicates the abbreviation for the currency.
SupplierPartyMaster/Classification/Codes/Code 1) CIDVEN.IIORTY 2) CIDVEN.IICOBI 3) CIDVEN.IISCNO	The field indicates the classification code. 1) Order Type
4) CIDVEN.IIOUCN 5) CIDVEN.IITECD 6) CIDVEN.IITEDL 7) CIDVEN.IIMODL	The field indicates the settings that determine how the order is processed during order entry and in the processing flow. Set attribute listID is 'Order type'.
8) CIDVEN.IITEPA 9) CIDVEN.IITEAF 10) CIDVEN.IIPACD 11) CIDVEN.IISUST	Group of Companies The field indicates the company group to which the supplier belongs. Set attribute listID is 'Group of companies'.
12) CIDVEN.IICINP 13) CIDVEN.IITXAP 14) CIDVEN.IICRTP 15) CIDMAS.IDSUCO	Supplier's Customer Number The field indicates the supplier's customer Number. Set attribute listID is 'Supplier's Customer Number'.
16) CIDMAS.IDPPIN 17) CIDVEN.IISUCL 18) CIDVEN.IITAXC 19) CIDVEN.IITDCD 20) CIDVEN.IIPRSU	4) Our Customer Number at Supplier The field indicates the our customer number at supplier, which is the customer number our supplier uses as identity for us. Set attribute listID is 'Our customer Number'.
21) CINMAS.CSCD.; CRS620MI/GetBasicData	 Cash Discount Term The field indicates the terms for cash discount calculation. Set attribute listID is 'Cash Discount Term'.
	6) Delivery Terms The field indicates the delivery terms, which define when the responsibility for a delivery is transferred from supplier to the customer. Set attribute listID is 'Delivery Terms'.
	 Delivery Method The field indicates how the delivery is made. Set attribute listID is 'Delivery Method'.
	 Packaging Terms The field indicates the what terms apply when goods are packed. Set attribute listID is 'Packaging Terms'.
	 Freight Terms The field indicate the freight terms which apply for the delivered goods. Set attribute listID is 'Freight Terms'.
	10) Payment PriorityThe field indicates the payment priority.Set attribute listID is 'Payment Priority'.

Set to 'Highest Priority' if PACD is A.
Set to 'Priority 1' if PACD is 1.
Set to 'Priority 2' if PACD is 2.
Set to 'Priority 3' if PACD is 3.
Set to 'Priority 4' if PACD is 4.
Set to 'Priority 5' if PACD is 5.
Set to 'Priority 6' if PACD is 6.
Set to 'Priority 7' if PACD is 7.
Set to 'Lowest Priority' if PACD is 8.

Set to 'Stopped' if PACD is 9.

11) Supplier Statistics

If set to 1, statistics are to be calculated for the supplier. Set attribute listID is 'Supplier Statistics'.

12) Claim Invoice Permitted

If set to 1, claim invoice is allowed.

Set attribute listID is 'Claim Invoice Permitted'.

13) Tax Applicable

The field indicates whether the supplier is required to declare VAT or sales tax

Set attribute listID is 'Tax Applicable'.

Set to 'No' if Tax applicable is 0.

Set to 'Yes' if Tax applicable is 1 or 2.

14) Exchange Rate type

The field indicates the exchange rate used when prices in the purchase module are converted to local currency or another currency. Set attribute listID is 'Exchange Rate Type'.

15) Supplier Number in Group

The field indicates the supplier number that the company group uses for the supplier.

Set attribute listID is 'Supplier Number in Group'.

16) Print Packing Instruction

The field indicates how to activate the automatic printing of connected packing instructions when purchase orders are printed. Set attribute listID is 'Print Packing Instruction'.

Set to 'No' if PPIN is 0.

Set to 'How to pack and Mark for' if PPIN is 1.

Set to 'How to pack' if PPIN is 2.

Set to 'Mark for' if PPIN is 3.

17) Supplier Group

The field indicates the supplier group specified for each supplier. Set attribute listID is 'Supplier Group'.

18) Tax Code

The field indicates if an item, charge, customer or ship-to location is taxable or not.

Set attribute listID is 'Tax Code'.

19) Trade Code

The field indicates a code that denotes the type of trade.

Set attribute listID is 'Trade Code'.

20) Payee

The field indicates the payee.

Set attribute listID is 'Payee'.

21) Country

The field indicates the country which goods were sent.

The field indicates the sequence attribute identifies the hierarchical position of the identifier in the case of multi-level codes

The field indicates the classification code listID.

- 1) Set to 'Order Type' if Classification/Codes/Code is ORTY.
- 2) Set to 'Group Of Companies 'if Classification/Codes/Code is COBI.
- 3) Set to 'Supplier's Customer Number' if Classification/Codes/Code is SCNO.
- 4) Set to 'Our Customer Number' if Classification/Codes/Code is OUCN.
- 5) Set to 'Cash Discount Term' if Classification/Codes/Code is TECD.
- 6) Set to 'Delivery Terms' if Classification/Codes/Code is TEDL.
- 7) Set to 'Delivery Method' if Classification/Codes/Code is TEPA.
- 8) Set to 'Packaging Terms' if Classification/Codes/Code is MODL.
- 9) Set to 'Freight Terms' if Classification/Codes/Code is TEAF.
- 10) Set to 'Payment Priority' if Classification/Codes/Code is PACD.
- 11) Set to 'Supplier Statistics' if Classification/Codes/Code is SUST.
- 12) Set to 'Claim Invoice Permitted' if Classification/Codes/Code is CINP.
- 13) Set to 'Tax Applicable' if Classification/Codes/Code is TAXP.
- 14) Set to 'Exchange Rate Type' if Classification/Codes/Code is

@sequence

@listID

SupplierPartyMaster	
	CRTP. 15) Set to 'Supplier Number In Group' if Classification/Codes/Code is SUCO. 16) Set to 'Print Packing Instruction' if Classification/Codes/Code is PPIN. 17) Set to 'Supplier Group' if Classification/Codes/Code is SUCL. 18) Set to 'Tax Code' if Classification/Codes/Code is TAXC. 19) Set to 'Trade Code' if Classification/Codes/Code is TDCD.
SupplierPartyMaster/BuyerPersonPeference/IDs	20) Set to 'Payee' if Classification/Codes/Code is PRSU.

SupplierPartyMaster/BuyerPersonReference/IDs/ID CIDVEN.IIBUYE; CRS620MI/GetBasicData @accountingEntity

accountingEntity
CIDMAS.IDCONO
CMNDIV.CCDIVI.; /

The field indicates the buyer.

The field indicates the accounting entity. If SupplierPartyMaster is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

SupplierPartyMaster/BuyerPersonReference/Name CSYUSR.CRRENM; MNS150MI/GetUserData

The field indicates the name of the buyer.

Transfer/TransferHeader/DocumentID/ID	
MGHEAD.MGTRNR ; /	The field indicates the order number for a requisition or distribution order.
@accountingEntity MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO_DIVI.
@location MGHEAD.MGWHLO ; MMS100MI/GetHead	The field indicates the warehouse.
@variationID	The field indicates the sequence number that identifies the number o times that the BOD has been published.
@lid	The field indicates the logical ID of the system.
Transfer/TransferHeader/DisplayID MGHEAD.MGTRNR ; MMS100MI/GetHead	The field indicates the order number for a requisition or distribution order.
Transfer/TransferHeader/LastModificationDateTime MGHEAD.MGLMTS; /	The field indicates the date and time the record was last modified.
Transfer/TransferHeader/LastModificationPerson/IDs/ID MGHEAD.MGCHID; /	The field indicates the last person who modified.
@accountingEntity MGHEAD.MGCONO MGHEAD.MGDIVI :: /	The field indicates the company and division, displayed as CONO_DIVI.
Transfer/TransferHeader/DocumentDateTime MGHEAD.MGTRDT MGHEAD.MGTRTM .; MMS100MI/GetHead	The field indicates the transaction date and time.
Transfer/TransferHeader/Note MGHEAD.MGREMK ; MMS100MI/GetHead	The field indicates the remark.
Transfer/TransferHeader/DocumentReference @type MGHEAD.MGRORC ; MMS100MI/GetHead	The field indicates the origin of the reference order number (RORC).
, WIND TOOM Cent read	Set type to "Transfer" if Country version (CSVN) = RU and RORC != 0.
	Set type to "ProductionOrder" if RORC = 1. Set type to "PurchaseOrder" if RORC = 2. Set type to "SalesOrder" if RORC = 3. Set type to "RequisitionOrder" if RORC = 4. Set type to "DistributionOrder" if RORC = 5. Set type to "WorkOrder" if RORC = 6. Set type to "ServiceOrder" if RORC = 7. Set type to "ProjectOrder" if RORC = 8. Set type to "ClaimOrder" if RORC = 9.
Transfer/TransferHeader/DocumentReference/DocumentID/ID MGHEAD.MGRORN ; MMS100MI/GetHead	The field indicates the reference order number.
@accountingEntity MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO DIVI).
Transfer/TransferHeader/DocumentReference/LineNumber MGHEAD.MGRORL ; MMS100MI/GetHead	The field indicates the reference order line.
Transfer/TransferHeader/DocumentReference/Facility/IDs/ID MGHEAD.MGFACI ; MMS100MI/GetHead @accountingEntity	The field indicates the facility used.
MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO DIVI).
Transfer/TransferHeader/DocumentReference/Facility/Name CFACIL.CFFACN ; CRS008MI/Get	The field indicates the name of the facility.
Transfer/TransferHeader/Status/Code MGHEAD.MGTRSL ; MMS100MI/GetHead	The field indicates the lowest status (TRSL).
	Set to "Open" if TRSL < 66. Set to "Shipped" if TRSL = 66. Set to "Received" if TRSL > 66.
Transfer/TransferHeader/Status/EffectiveDateTime MGHEAD.MGTRDT+MGHEAD.MGTRTM .; MMS100MI/GetHead	The field indicates the transaction date and time.

i i ali Siti	
MGHEAD.MGTWLO ; MMS100MI/GetHead	The field indicates the warehouse to which a transfer of a quantity has been made or is to be made.
Transfer/TransferHeader/ShipFromParty/Location/ID MGHEAD.MGWHLO ; MMS100MI/GetHead	The field indicates the warehouse.
@accountingEntity MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO DIVI).
Transfer/TransferHeader/ShipFromParty/Location/Name MITWHL.MWWHNM ; MMS005MI/GetWarehouse	The field indicates the warehouse name. Display only if Country version (CSVN) = RU.
Transfer/TransferHeader/ShipToParty/Location/ID MGHEAD.MGTWLO ; MMS100MI/GetHead @accountingEntity	The field indicates the warehouse to which a transfer of a quantity has been made or is to be made.
MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO DIVI).
Transfer/TransferHeader/PlannerContact/ID MGHEAD.MGRESP ; MMS100MI/GetHead @accountingEntity	The field indicates the responsible.
MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO_DIVI).
Transfer/TransferHeader/PlannerContact/Name CSYUSR.CRRENM ; MNS150MI/GetUserData	The field indicates the name of the responsible. Use RESP as input to MNS150MI.GetUserData USID.
Transfer/TransferHeader/CarrierParty/PartyIDs/ID MGHEAD.MGFWNO ; MMS100MI/GetHead	The field indicates the forwarding agent.
@accountingEntity MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If CarrierParty is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO DIVI).
Transfer/TransferHeader/CarrierParty/Name CIDMAS.IDSUNM ; CRS620MI/GetBasicData	The field indicates the forwarding agent name. Display if SUTY (Supplier type) = 5 (Forwarding Agent). Use FWNO as input to CRS620MI.GetBasicData SUNO.
Transfer/TransferHeader/PurchaseOrderReference/DocumentID/ID MGHEAD.MGRORN ; MMS100MI/GetHead @accountingEntity	The field indicates the purchase order number. Display RORC (Reference order category) = 2 (Purchase Order).
MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. This is displayed as Company and Division (CONO_DIVI).
Transfer/TransferHeader/PurchaseOrderReference/LineNumber MGHEAD.MGRORL ; MMS100MI/GetHead	The field indicates the purchase order line.
Transfer/TransferHeader/UserArea 1) MGHEAD.MGTRSL MMS100MI/GetHead 2) MGHEAD.MGTWSL	Lowest status The field indicates the lowest line status of a requisition order or distribution order (TRSL). Set attribute name to "LowestStatus".
MMS100MI/GetHead.; /	To Location The field indicates a destination location for a stock transaction (TWSL). Set attribute name to "ToLocation".
Transfer/TransferHeader/TransportMethodCode MGHEAD.MGMODL ; MMS100MI/GetHead	The field indicates the delivery method.
@listID	Set to "Transportation Methods".
Transfer/TransferLine/LineNumber MGLINE.MRPONR ; MMS100MI/LstLines	The field indicates the order line number.
Transfer/TransferLine/Item/ItemID/ID MGLINE.MRITNO ; MMS100MI/LstLines @accountingEntity	The field indicates the item number.
MGHEAD.MGCONO CMNDIV.CCDIVI.; /	The field indicates the accounting entity. If ItemMaster_MAE is enabled in BOD Processor Master AE tab, this is displayed as Company (CONO). Otherwise, this is displayed as Company and Division (CONO_DIVI).

MITMAS.MMECVE	The field indicates the revision number of an item or document.
; MMS200MI/GetItmTech	
Transfer/TransferLine/Item/UPCID	
MITPOP.MPPOPN	The fields indicates the GTIN-12 and UCC-12. It is a 12-digit number
; MMS025MI/LstAlias	used for identifying goods if alias qualifier (ALWQ) = "UPC".
Transfer/TransferLine/Item/GTIN	
MITPOP.MPPOPN	The field indicates the Global Trade Item Number, it is a 14-digit
; MMS025MI/LstAlias	number which includes various EAN/UCC numbering structures if
	alias qualifier (ALWQ) = "GTIN".
Transfer/TransferLine/Item/Description	
MITMAS.MMITDS	The field indicates the item description.
; MMS100MI/LstLines	
Transfer/TransferLine/Item/Classification/Codes/Code	
1) MITMAS.MMITGR	1) Item group
MMS200MI/GetItmBasic	The field indicates the item group (ITGR).
	Set attribute listID to "Item Groups".
2) MITMAS.MMITCL	
MMS200MI/GetItmBasic	2) Product group
	The field indicates the product group (ITCL).

3) MITMAS.MMBUAR MMS200MI/GetItmBasic

4) MITMAS.MMITTY MMS200MI/GetItmBasic

5) MITMAS.MMTPCD MMS200MI/GetItmBasic

6) MITMAS.MMPRGP MMS200MI/GetItmBasic

7) MITMAS.MMDIGI MMS200MI/GetItmPrice

8) MITMAS.MMCHCD MMS200MI/GetItmBasic

9) MITMAS.MMRUID MMS200MI/GetItmBasic

10) MITMAS.MMITNO/ MITMAS.MMHDPR/ MITMAS.MMTPLI MMS200MI/GetItmBasic.; /

Set attribute listID to "Product Groups".

3) Business area

The field indicates the business area which is used to group information for budgeting and statistical purposes (BUAR). Set attribute listID to "Business Sectors".

4) Item types

The field indicates the item type, which determines an item's life cycle (ITTY).

Set attribute listID to "Item Types".

5) Item category

The field indicates the item category that best represents the characteristics of each item (TPCD).

Set attribute listID to "Item Classes".

Alternatives:

00 = Normal item

02 = Phantom item

03 = Subcontracted item

04 = Tool

05 = Fixed machine

07 = Repairable item

08 = Recyclable item

11 = Extended Catalog Item (ECI)

12 = Non-coded Extended Catalog Item

13 = Non-material item

6) Procurement group

The field indicates the procurement group for an item, which is used to facilitate selections by grouping similar items together (PRGP). Set attribute listID to "Buying Groups".

7) Item discount group

The field indicates the Item discount group which may be used as a control object for calculating customer order line discounts (DIGI). Set attribute listID to "Item Rebate Groups".

8) Configuration code

The field indicates if the item is configured when ordered or configured as a maintenance item (CHCD). Set attribute listID to "Configuration Code".

Alternatives:

0 = No

1 = Yes

2 = Yes, as a family item from which product variants with item numbers are created.

3 = No. The item is a product variant with the item number of the family item.

4 = The item is a maintenance item. Regulates the item costing.

5 = The item is a maintenance item. Queries can be answered in order to provide a better planned work order.

The field indicates the identification of the ruleset in PCM (Product Configuration Management) to use when the product is configured

Set attribute listID to "Configured Ruleset".

May 26, 2023

	10) Styles The field indicates the Style item number. For Style, retrieve from ITNO. For SKU, retrieve from HDPR; if HDPR is blank use TPLI. Set attribute listID to "Styles".
@sequence	The field indicates the sequence number for the ordering of elements within a document.
@listID	Set to "Item Groups" if Classification/Codes/Code = ITGR. Set to "Product Groups" if Classification/Codes/Code = ITCL. Set to "Business Sectors" if Classification/Codes/Code = BUAR.
	4) Set to "Item Types" if Classification/Codes/Code = ITTY. 5) Set to "Item Classes" if Classification/Codes/Code = TPCD. 6) Set to "Buying Groups" if Classification/Codes/Code = PRGP. 7) Set to "Item Rebate Groups if Classification/Codes/Code = DIGI. 8) Set to "Configuration Code" if Classification/Codes/Code = CHCD. 9) Set to "Configured Ruleset" if Classification/Codes/Code = RUID. 10) Set to "Styles" if Classification/Codes/Code = ITNO/HDPR/TPLI with CHCD = 2 or 3.
Transfer/TransferLine/Item/Classification/Description	The field indicates a decariotion of the electification it is natural
CSYTAB.CTTX40 CSLGHN.JLTX60; CRS175MI/LstCodesByLng CRS175MI/GetGeneralCode	The field indicates a description of the classification. It is retrieved from table CSYTAB (generic description), table CSLGHN (language-specific description) or hardcoded. Call CRS175MI.LstCodesByLng only for fields ITGR, ITCL, BUAR
.;/	and ITTY. Call CRS175MI.GetGeneralCode only for fields PRGP and DIGI.
@languageID CSYTAB.CTTX40	The field indicates the language ID.
CSLGHN.JLTX60 .JLLNCD ; CRS175MI/LstCodesByLng	
Transfer/TransferLine/Item/SerialNumber MGLINE.MRBANO _; MMS100MI/LstLines	The field indicates the lot number.
Transfer/TransferLine/Quantity MGLINE.MRTRQT ; MMS100MI/LstLines	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the basic unit of measure.
Transfer/TransferLine/QuantityDistribution/LineNumber MGLINE.MRPONR ; MMS100MI/LstLines	The field indicates the order line number.
Transfer/TransferLine/QuantityDistribution/DateTime MGLINE.MRTRDT ; MMS100MI/LstLines	The field indicates the transaction date which may be entered manually during entry of certain transactions.
Transfer/TransferLine/QuantityDistribution/Quantity MGLINE.MRTRQA ; MMS100MI/LstLines @unitCode	The field indicates a quantity, the significance of which is apparent from the field heading.
MGLINE.MRALUN ; MMS100MI/LstLines	The field indicates an alternate unit of measure.
Transfer/TransferLine/QuantityDistribution/BaseUOMQuantity MGLINE.MRTRQT ; MMS100MI/LstLines	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MITMAS.MMUNMS	The field indicates the basic unit of measure.
; MMS200MI/GetItmBasic Transfer/TransferLine/BaseUOMQuantity	
MGLINE.MRTRQT ; MMS100MI/LstLines	The field indicates the quantity, in the basic unit of measure, for the planned or actual transaction.
@unitCode MITMAS.MMUNMS ; MMS200MI/GetItmBasic	The field indicates the basic unit of measure.
Transfer/TransferLine/RequiredDeliveryDateTime MGHEAD.MGRIDT ; MMS100MI/GetHead	The field indicates the transaction date which may be entered manually during entry of certain transactions.
Transfer/TransferLine/ShippedQuantity MGLINE.MRPQT	The field indicates the reported quantity that corresponds to the
MGLINE.MRDPQT .; MMS100MI/LstLines	transactions status or function (RPQT) when RPQT is not != 0. Otherwise, the field indicates Dispatched quantity (DPQT).
@unitCode	Carolinise, the field indicates dispatched quality (DFQ1).

114113161	
MITMAS.MMUNMS ; MMS200MI/GetltmBasic	The field indicates the basic unit of measure.
Transfer/TransferLine/ReceivedQuantity	
MGLINE.MRRPQT	The field indicates the reported quantity that corresponds to the
; MMS100MI/LstLines	transactions status or function.
@unitCode	
MITMAS.MMUNMS	The field indicates the basic unit of measure.
; MMS200MI/GetItmBasic	
Transfer/TransferLine/UserArea	
1) MGLINE.MRTRSH	1) Highest status
MMS100MI/LstLines	The field indicates the highest line status in the order (TRSH).
	Set attribute name to "HighestStatus".
2) MGLINE.MRTWSL	
MMS100MI/LstLines	2) To Location
.;/	The field indicates a destination location for a stock transaction
	(TWSL).
	Set attribute name to "ToLocation".

Workflow

Workflow/WorkflowDefinitionCode CMAILB.CBWFNM; N/A/	The name of the workflow in ION that should be started.
Workflow/Property @sequence	
	Sequence number, starting with 1
Workflow/Property/NameValue	
.; CRS420MI/GetBookmark	M3 publishes NameValues from M3 field value 1) MLID, REC2, MSGT from table CMAILB MSGT is split into multiple parts if necessary (M3 field length is larger than BOD element length)
@name	2) KSTR from table CMAILP, split into multiple M3Key-fields
	M3 publish name attribute from M3 field name 1) 'CBMLID', 'CBREC2', 'CBMSGT1/CBMSGT2/CBMSGT3'
@type	2) M3 field name without the 'table index' e.g. CONO, ITNO
	Always set to 'StringType'