

Infor M3

Inbound BOD Mapping and Descriptions

Copyright © 2023 Infor

All rights reserved.

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor M3

Publication Date: May 26, 2023

Version: 16.0.0.0

List of Nouns

AdvanceShipNotice

AssetMaster

BankStatement

BillOfMaterials

BillToPartyMaster

CarrierRoute

CodeDefinition

ContactMaster

Contract

CurrencyExchangeRateMaster

CustomerPartyMaster

CustomerReturn

EmployeeWorkTime

ExpenseReport

FinancialPartyMaster

InspectDelivery

InspectionOrder

InventoryAdjustment

InventoryCount

InventoryHold

Invoice

ItemMaster

Location

M3EDIAdvanceShipNotice

M3EDICustomerRemittanceAdvice

M3EDICustomerReturn

M3EDIInventoryAdjustment

M3EDIPurchaseOrder

M3EDIReceiveDelivery

M3EDIRemittanceAdvice

M3EDISalesOrder

M3EDIShipmentSchedule

M3EDIShipment

M3EDISupplierInvoice

PayFromPartyMaster

Personnel

Person

ProductionOrder

PurchaseOrder

QualitySpecification

QualityTestMaster

Quote

ReceiveDelivery

RemitToPartyMaster

Requisition

SalesOrder

SecurityUserMaster

ServiceConsumption

ServiceOrder

Shipment

ShipToPartyMaster

SourceSystemGLMovement

SupplierInvoice

SupplierPartyMaster

Transfer

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID

For LoadAdvanceShipNotice:

1) MHIHED.G0SUDO;

MHS850MI/AddWhsHead,

2) MHIPAC.G1SUDO; MHS850MI/AddWhsPack,

3) MHILIN.G2SUDO;

MHS850MI/AddWhsLine

4) PDNHEA.IHSUDO;

PPS360MI/GetHead, DItHead.; /

For ProcessAdvanceShipNotice:

MHIHED.G0SUDO:

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

PDNHEA.IHSUDO;

PPS360MI/GetHead, DltHead.; /

For SyncAdvanceShipNotice:

MHIHED.GOSUDO:

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

PDNHEA.IHSUDO;

PPS360MI/GetHead, DltHead.; /

For LoadAdvanceShipNotice:

The field indicates the Delivery note number. This must be unique in combination with Supplier (SUNO).

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, LoadAdvanceShipNotice may be generated again using the same Delivery note number.

For ProcessAdvanceShipNotice:

The field indicates the Delivery note number. This must be unique in combination with Supplier (SUNO).

If QLFR = 29, actionCode='Change' and partner from logicalID is NEXUS or translated to UniqueDeliveryNote in CRS881/882, call PPS360MI.LstHeadBySup to retrieve SUTY and DNDT from the first record. These fields are used as inputs to PPS360MI.DltHead. Once delivery note is deleted in PPS360, call the MHS850MI transactions to recreate the delivery note with the latest information.

If QLFR = 29, actionCode='Change' and partner from logicalID is not NEXUS or not translated to UniqueDeliveryNote in CRS881/882. PPS360MI.GetHead is called to check if record exists. If record exists, PPS360MI.DltHead is called. MHS850MI transactions are then called to recreate the delivery note with the updated details.

If actionCode='Delete', PPS360MI.DltHead is called. Once PPS360 record is deleted, ProcessAdvanceShipNotice may be generated again using the same Delivery note number.

For SyncAdvanceShipNotice:

The field indicates the Delivery note number. This must be unique in combination with Supplier (SUNO).

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, ProcessAdvanceShipNotice may be generated again using the same Delivery note number.

The field indicates the company and division, displayed as CONO DIVI

@accountingEntity

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDateTime

For LoadAdvanceShipNotice:

1) MHIHED.GODNDT;

MHS850MI/AddWhsHead, 2) MHIHED.G0DNTM;

MHS850MI/AddWhsHead,

3) MHIPAC.G1DNDT; MHS850MI/AddWhsPack,

4) MHILIN.G2DNDT;

MHS850MI/AddWhsLine

5) PDNHEA.IHDNDT;

PPS360MI/GetHead, DltHead.; /

For LoadAdvanceShipNotice:

The field indicates the Delivery Note date and time.

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference @type

For LoadAdvanceShipNotice:

Set to 'Shipper', if DocumentReference/DocumentID input to populate SUDO

For ProcessAdvanceShipNotice:

If set to 'ShipFromPartyMaster', use DocumentReference/ DocumentID input to populate Bill of lading (BOLN). Else, populate Delivery note reference (PUSN).

For SyncAdvanceShipNotice:

If set to 'ShipFromPartyMaster', use DocumentReference/ DocumentID input to populate Bill of lading (BOLN). Else, populate Delivery note reference (PUSN)

AdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference/DocumentID/ID

For LoadAdvanceShipNotice:

1) MHIHED.G0SUDO;

MHS850MI/AddWhsHead,

2) MHIPAC.G1SUDO; MHS850MI/AddWhsPack,

3)MHILIN.G2SUDO;

MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

Set to 'Shipper', if the attribute type field indicates the Delivery note (SUDO).

For ProcessAdvanceShipNotice:

If @type='ShipFromPartyMaster', the field indicates the Bill of lading (BOLN). Otherwise, the field indicates the Delivery note reference

For ProcessAdvanceShipNotice: MHIHED.G0BOLN; MHS850MI/AddWhsHead MHIHED.G0PUSN; MHS850MI/AddWhsHead

.; /

For SyncAdvanceShipNotice: MHIHED.G0BOLN; MHS850MI/AddWhsHead MHIHED.G0PUSN; MHS850MI/AddWhsHead

- -, /

AdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLocation/ID

For LoadAdvanceShipNotice: 1) MHIHED.G0WHLO;

MHS850MI/AddWhsHead,

2) MHIPAC.G1WHLO; MHS850MI/AddWhsPack, CghWhsPack

3) MHILIN.G2WHLO; MHS850MI/AddWhsLine PDNHEA.IHWHLO;

4) PPS360MI/GetHead, DItHead.; /

For ProcessAdvanceShipNotice: 1.) MHIHED.G0WHLO; MHS850MI/AddWhsHead

2.) PDNHEA.IHWHLO; PPS360MI/GetHead, DltHead.; /

For SyncAdvanceShipNotice: 1.) MHIHED.G0WHLO; MHS850MI/AddWhsHead

2.) PDNHEA.IHWHLO;

PPS360MI/GetHead, DItHead, ReceiveHead.; /

(PUSN).

For SyncAdvanceShipNotice:

If @type='ShipFromPartyMaster', the field indicates the Bill of lading (BOLN). Otherwise, the field indicates the Delivery note reference (PUSN).

For LoadAdvanceShipNotice:

The field indicates the warehouse of the company.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, LoadAdvanceShipNotice may be generated again using the same Delivery note number.

If this element is blank, the warehouse will be retrieved from the purchase order line using PPS200MI.GetLine.

For ProcessAdvanceShipNotice:

The field indicates the warehouse of the company.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI.GetHead. If record exists, use PPS360MI.DltHead. Once PPS360 record is deleted, ProcessAdvanceShipNotice may be generated again using the same Delivery note number.

If AdvanceShipNoticeHeader/WarehouseLocation/ID is blank (for drop ship), PPS200MI.GetHead is called to retrieve WHLO. The value from the first AdvanceShipNotice/AdvanceShipNoticeItem/ PurchaseOrderReference/DocumentID/ID is used in case of multiple purchase orders as PPS200MI.GetHead PUNO input. The retrieved WHLO value is used as input to MHS850MI.AddWhsHead, PPS360MI.GetHead and PPS360MI.DltHead.

For SyncAdvanceShipNotice:

The field indicates the warehouse of the company.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, SyncAdvanceShipNotice may be generated again using the same Delivery note number.

Goods receiving in the delivery note header will be performed by calling PPS360MI.ReceiveHead if partner from logical ID is translated to ReceiveByASN in CRS881/882.

AdvanceShipNotice/AdvanceShipNoticeHeader/ActualShipDateTime

For LoadAdvanceShipNotice: 1) MHIHED.GOSHD4; MHS850MI/AddWhsHead, 2) MHIHED.GOSHTM MHS850MI/AddWhsHead.; /

For ProcessAdvanceShipNotice:

MHIHED.G0SHD4

MHIHED.G0SHTM.; MHS850MI/AddWhsHead

For SyncAdvanceShipNotice:

MHIHED.G0SHD4

MHIHED.G0SHTM.; MHS850MI/AddWhsHead

The field indicates the actual ship date of the delivery.

For ProcessAdvanceShipNotice:

For LoadAdvanceShipNotice:

The field indicates the actual ship date and time the goods delivered/received.

For SyncAdvanceShipNotice:

The field indicates the actual ship date and time the goods delivered/ received

AdvanceShipNotice/AdvanceShipNoticeHeader/ScheduledDeliveryDateTime

For LoadAdvanceShipNotice:

MHIHED.G0DLDT

MHIHED.G0DLTM.; MHS850MI/AddWhsHead

For ProcessAdvanceShipNotice:

For LoadAdvanceShipNotice:

The field indicates the Planned delivery date and time.

For ProcessAdvanceShipNotice:

The field indicates the scheduled delivery date.

Infor May 26, 2023

MHIHED.G0ARDT: MHS850MI/AddWhsHead

For SyncAdvanceShipNotice:

MHIHED.GOARDT; MHS850MI/AddWhsHead

If SHD4 exists, the ARDT displayed in PPS360 is calculated based

on internal lead times.

For SyncAdvanceShipNotice:

The field indicates the scheduled delivery date.

AdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMeasure

MHIHED.GOGRWE; MHS850MI/AddWhsHead

For LoadAdvanceShipNotice:

The field indicates the Gross weight for the entire ASN.

For ProcessAdvanceShipNotice: The field indicates the gross weight.

For SyncAdvanceShipNotice: The field indicates the gross weight

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationMethodCode

MHIHED.G0MODL; MHS850MI/AddWhsHead

For LoadAdvanceShipNotice:

The field indicates the Transportation Method Code.

For ProcessAdvanceShipNotice:
The field indicates the delivery method.

For SyncAdvanceShipNotice:

The field indicates the delivery method

AdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty/PartyIDs/ID

For LoadAdvanceShipNotice:

1) MHIHED.G0SUNO;

MHS850MI/AddWhsHead.

2) MHIPAC.G1SUNO; MHS850MI/AddWhsPack,

3) MHILIN.G2SUNO; MHS850MI/AddWhsLine 4) PDNHEA.IHSUNO;

PPS360MI/GetHead, DltHead.; /

For ProcessAdvanceShipNotice:

1.) MHIHED.G0SUNO;

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

2.)PDNHEA.IHSUNO;

PPS360MI/GetHead, DItHead.; /

For SyncAdvanceShipNotice:

1.) MHIHED.GOSUNO;

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

2.)PDNHEA.IHSUNO;

PPS360MI/GetHead, DltHead, ReceiveHead.; /

For LoadAdvanceShipNotice: The field indicates the supplier ID.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DItHead. Once PPS360 record is deleted,

LoadAdvanceShipNotice may be generated again using the same

Delivery note number.

For ProcessAdvanceShipNotice: The field indicates the supplier ID.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted.

ProcessAdvanceShipNotice may be generated again using the same

Delivery note number.

For SyncAdvanceShipNotice: The field indicates the supplier ID.

To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists,

use PPS360MI/DltHead. Once PPS360 record is deleted,

ProcessAdvanceShipNotice may be generated again using the same Delivery note number.

Goods receiving in the delivery note header will be performed by calling PPS360MI.ReceiveHead if partner from logical ID is translated to ReceiveByASN in CRS881/882.

AdvanceShipNotice/AdvanceShipNoticeHeader/ScheduledShipDateTime

1.) MHIHED.G0DNDT;

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

The field indicates the delivery note date and time.

2.)MHIHED.G0DNTM; MHS850MI/AddWhsHead, .; /

AdvanceShipNotice/AdvanceShipNoticeHeader/TransportationTerm/IncotermsCode

MHIHED.GOTEDL; MHS850MI/AddWhsHead The field indicates the delivery terms.

AdvanceShipNotice/AdvanceShipNoticeHeader/UserArea

For LoadAdvanceShipNotice: 1)MHIHED.G0ADID; MHS850MI/AddWhsHead,

2)MHIPAC.G1ADID; MHS850MI/AddWhsPack,

3)MHILIN.G2ADID; MHS850MI/AddWhsLine.; / For LoadAdvanceShipNotice:

The field indicates the address number (ADID). In case ADID is not

given, default value is set to PICKUP.

Retrieve MHS850MI.AddWhsLine ADID input from

MHS850MI.AddWhs. If MHS850MI AddWhsPack ADID is blank,

retrieve value from AddWhsHead to be used as input for

AddWhsPack and AddWhsLine.

If @name='AddressNumber', populate ADID

AdvanceShipNotice/AdvanceShipNoticeItem/ItemID

For LoadAdvanceShipNotice:

MHILIN.G2ITNO MHILIN.G2SITE For LoadAdvanceShipNotice:

The field indicates the item number or the Supplier's item number.

: MHS850MI/AddWhsLine

AdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID

MHILIN.G2ITNO MHILIN.G2SITE

.; MHS850MI/AddWhsLine

@schemeName

The field indicates the item number or supplier item number.

For LoadAdvanceShipNotice:

Set to 'System' or blank, if ItemID is used as M3 Item number (ITNO). Set to 'Supplier' if ItemID is used as Supplier's Item number (SITE).

For ProcessAdvanceShipNotice: If set to 'System' or blank, use ITNO. If set to 'Supplier', use SITE.

For SyncAdvanceShipNotice:

If set to 'System' or blank, use ITNO.

If set to 'Supplier', use SITE.

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity

MHILIN.G2DLQA; MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

The field indicates the delivered quantity expressed in unit of

measure from the order.

For ProcessAdvanceShipNotice:

The field indicates the purchase order quantity expressed in the PO

unit of measure.

For SyncAdvanceShipNotice:

The field indicates the purchase order quantity expressed in the PO

unit of measure.

@unitCode

MHILIN.G2ALUN; MHS850MI/AddWhsLine

The field indicates the same unit of measure as on the order.

AdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity

For LoadAdvanceShipNotice: For LoadAdvanceShipNotice:

MHLIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the shipped quantity.

For ProcessAdvanceShipNotice: For ProcessAdvanceShipNotice:

The field indicates the quantity in local unit of measure. MHILIN.G2DLQT; MHS850MI/AddWhsLine

For SyncAdvanceShipNotice: For SyncAdvanceShipNotice:

MHILIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the quantity in local unit of measure.

@unitCode

For LoadAdvanceShipNotice:

MHLIN.G2ALUN; MHS850MI/AddWhsLine

For ProcessAdvanceShipNotice: MHILIN.G2UNIT; MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

The field indicates the same unit of measure as on the order.

For ProcessAdvanceShipNotice:

The field indicates the local unit of measure.

For SyncAdvanceShipNotice: For SyncAdvanceShipNotice:

MHILIN.G2UNIT; MHS850MI/AddWhsLine The field indicates the local unit of measure

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/DocumentID/ID

MHILIN.G2RIDN; MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

The field indicates the reference purchase order number.

For ProcessAdvanceShipNotice:

The field indicates the purchase order number reference.

For SyncAdvanceShipNotice:

For LoadAdvanceShipNotice:

The field indicates the purchase order number reference.

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/LineNumber

MHILIN.G2RIDL The field indicates the concatenation of order line and line suffix MHILIN.G2RIDX.; MHS850MI/AddWhsLine

where the last 3 digits is the line suffix.

AdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/Quantity

MHILIN.G2RVQA; MHS850MI/AddWhsLine

@unitCode

MHILIN.G2PUUN; MHS850MI/AddWhsLine

The field indicates the received quantity.

The field indicates the purchase order unit of measure.

For ProcessAdvanceShipNotice: The field indicates the unit of measure.

For SyncAdvanceShipNotice:

The field indicates the unit of measure

AdvanceShipNotice/AdvanceShipNoticeItem/UserArea

For SyncAdvanceShipNotice:

1) PDNHEA.IHSUDO

2) PDNHEA.IHDNDT.; PPS360MI/ReceiveHead

For SyncAdvanceShipNotice:

1) Delivery note

The field indicates the supplier's delivery note number.

Populate SUDO with data from Property/NameValue if attribute name

is wm.DeliveryNote.

2) Delivery note date

The field indicates the date the delivery note was printed for the first

Populate DNDT with data from Property/NameValue if attribute name

is wm.DeliveryNoteDate.

Goods receiving in the delivery note header will be performed by calling PPS360MI.ReceiveHead if partner from logical ID is translated

to ReceiveByASN in CRS881/882.

AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/LotIDs/ID

MHILIN.G2BANO; MHS850MI/AddWhsLine The field indicates the lot number.

AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/Quantity

MHILIN.G2DLQA; MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

The field indicates the alternative unit of measure in quantity.

For ProcessAdvanceShipNotice:

The field indicates the quantity in alternative unit of measure.

For SyncAdvanceShipNotice:

The field indicates the quantity in alternative unit of measure.

@unitCode

MHILIN.G2ALUN; MHS850MI/AddWhsLine

The field indicates the alternative unit of measure

AdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/BaseUOMQuantity

MHILIN.G2DLQT; MHS850MI/AddWhsLine

For LoadAdvanceShipNotice:

The field indicates the basic delivered quantity.

For ProcessAdvanceShipNotice:

The field indicates the quantity in basic unit of measure.

For SyncAdvanceShipNotice:

The field indicates the quantity in basic unit of measure.

@unitCode

MHILIN.G2UNIT; MHS850MI/AddWhsLine

The field indicates the basic unit of measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID

For LoadAdvanceShipNotice:

1) MHIPAC.G1PACN; MHS850MI/AddWhsPack, ChgWhsPac

2) MHILIN.G2PACN; MHS850MI/AddWhsLine.; / For LoadAdvanceShipNotice:

The field indicates the package number. A dummy package will be

created in M3 if no package information is sent (i.e. element

AdvanceShipNoticeUnit not available).

For ProcessAdvanceShipNotice:

MHIPAC.G1PACN; MHS850MI/AddWhsPack

For SyncAdvanceShipNotice:

MHIPAC.G1PACN; MHS850MI/AddWhsPack

For ProcessAdvanceShipNotice:

The field indicates package number. A dummy package will be

created in M3 if no package information is sent (i.e. element

AdvanceShipNoticeUnit not available).

For SyncAdvanceShipNotice:

The field indicates package number. A dummy package will be

created in M3 if no package information is sent (i.e. element

AdvanceShipNoticeUnit not available).

AdvanceShipNotice/AdvanceShipNoticeUnit/NetWeightMeasure

For ProcessAdvanceShipNotice:

MHIPAC.G1NEWE; MHS850MI/AddWhsPack

For ProcessAdvanceShipNotice:

AdvanceShipNotice/AdvanceShipNoticeUnit/GrossWeightMeasure

For ProcessAdvanceShipNotice:

MHIPAC.G1GRWE; MHS850MI/AddWhsPack

The field indicates the net weight.

AdvanceShipNotice/AdvanceShipNoticeUnit/TotalVolumeMeasure

For ProcessAdvanceShipNotice:

MHIPAC.G1VOM3; MHS850MI/AddWhsPack

For ProcessAdvanceShipNotice: The field indicates the gross weight

For ProcessAdvanceShipNotice:

The field indicates the volume.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShippingMaterial/ID

MHIPAC.G1PACT; MHS850MI/AddWhsPack

For LoadAdvanceShipNotice:

The field indicates the packaging shipping material.

For ProcessAdvanceShipNotice:

The field indicates the packaging.

For SyncAdvanceShipNotice: The field indicates the packaging

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitContainer/ContainerID

For LoadAdvanceShipNotice:

MHIPAC.G1PACN; MHS850MI/ChgWhsPack

For ProcessAdvanceShipNotice:

MHIPAC.G1PACC; MHS850MI/AddWhsPack

For LoadAdvanceShipNotice:

The field indicates the package included. A list of package

relationship is maintained (Package ID from ShipmentUnitContainer/ ContainerID and Parent Package Id). After all packages are created via MHS850MI, this list will be considered and all child packages are

updated with their parent package.

For SyncAdvanceShipNotice:

For ProcessAdvanceShipNotice:

The field indicates the included in package number.

For SyncAdvanceShipNotice:

The field indicates the included in package number.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitContainer/ParentContainerID The field indicates the parent package. Parent package must be

For LoadAdvanceShipNotice:

MHIPAC.G1PACC; MHS850MI/ChgWhsPack defined as a Container ID first.

For ProcessAdvanceShipNotice:

MHIPAC.G1PACC; MHS850MI/AddWhsPack

For SyncAdvanceShipNotice:

MHIPAC.G1PACC; MHS850MI/AddWhsPack

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ItemID/ID

For LoadAdvanceShipNotice: For LoadAdvanceShipNotice:

MHILIN.G2ITNO

The field indicates the item number or the Supplier's item number. MHILIN.G2SITE

The field indicates the item number or supplier item number.

For ProcessAdvanceShipNotice:

.; MHS850MI/AddWhsLine

MHILIN.G1ITNO; MHS850MI/AddWhsLine

For SyncAdvanceShipNotice: The field indicates the item number or supplier item number.

For SyncAdvanceShipNotice:

MHILIN.G1ITNO; MHS850MI/AddWhsLine

@schemeName

For LoadAdvanceShipNotice:

For ProcessAdvanceShipNotice:

Set to 'Supplier'.

For ProcessAdvanceShipNotice: If set to 'System' or blank, use ITNO. If set to 'Supplier', use SITE.

For SyncAdvanceShipNotice: If set to 'System' or blank, use ITNO. If set to 'Supplier', use SITE

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity

MHILIN.G2DLQA; MHS850MI/AddWhsLine The field indicates the delivered quantity in alternate unit of measure.

@unitCode

MHILIN.G2ALUN; MHS850MI/AddWhsLine The field indicates the alternative unit of measure

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedBaseUOMQuantity

For LoadAdvanceShipNotice: For LoadAdvanceShipNotice:

MHLIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the delivered quantity.

For ProcessAdvanceShipNotice: For ProcessAdvanceShipNotice:

MHILIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the quantity in basic unit of measure for the

specific item in a specific package.

For SyncAdvanceShipNotice:

MHILIN.G2DLQT; MHS850MI/AddWhsLine

For SyncAdvanceShipNotice: The field indicates the quantity in basic unit of measure for the

specific item in a specific package.

@unitCode

MHILIN.G2UNIT; MHS850MI/AddWhsLine For LoadAdvanceShipNotice:

The field indicates the basic unit of measure for the item.

For ProcessAdvanceShipNotice:

The field indicates the basic unit of measure for the item

For SyncAdvanceShipNotice:

The field indicates the basic unit of measure for the item

The field indicates the basic unit of measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/DocumentID/ID

MHILIN.G2RIDN; MHS850MI/AddWhsLine The field indicates the Purchase order number.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

The field indicates the concatenation of order line and line suffix MHILIN.G2RIDL

MHILIN.G2RIDX.; MHS850MI/AddWhsLine where the last 3 digits is the line suffix

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/Lot/IDs/ID

MHILIN.G2BANO; MHS850MI/AddWhsLine The field indicates the lot number.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/Quantity

MHILIN.G2DLQA; MHS850MI/AddWhsLine The field indicates the delivered quantity in alternate unit of measure. @unitCode

MHILIN.G2ALUN; MHS850MI/AddWhsLine The field indicates the alternative unit of measure.

AdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/SerializedLot/Lot/BaseUOMQuantity

MHILIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the delivered quantity in basic unit of measure. @unitCode

MHILIN.G2UNIT; MHS850MI/AddWhsLine AdvanceShipNotice/AdvanceShipNoticeUnit/UserArea

For LoadAdvanceShipNotice:
1)MHIPAC.G1SSCC;
MHS850MI.AddWhsPack
2)MHIHED.G0ADID;
MHS850MI/AddWhsHead
3)MHIPAC.G1ADID; MHS850MI/AddWhsPack
4)MHILIN.G2ADID;
MHS850MI/AddWhsLine.; /

For ProcessAdvanceShipNotice:

MHIPAC.G1SSCC; MHS850MI/AddWhsPack

For SyncAdvanceShipNotice:

MHIPAC G1SSCC; MHS850MI/AddWhsPack

For LoadAdvanceShipNotice:

1)The field indicates the unique serial shipment container code (SSCC).

If attribute name='SSCC', populate SSCC.

2)The field indicates the address number (ADID). In case ADID is not given, default value is set to PICKUP.

Retrieve MHS850MI.AddWhsLine ADID input from MHS850MI.AddWhs. If MHS850MI AddWhsPack ADID is blank, retrieve value from AddWhsHead to be used as input for AddWhsPack and AddWhsLine.

If @name='AddressNumber', populate ADID

For ProcessAdvanceShipNotice:

1.)Serial shipment container code

The field indicates the unique serial shipment container code (SSCC). If attribute names is 'SSCC', populate sercial shipment container code (SSCC).

For SyncAdvanceShipNotice:

1.)Serial shipment container code

The field indicates the unique serial shipment container code (SSCC). If attribute names is 'SSCC', populate sercial shipment container code (SSCC).

AssetMaster

Assetiviastei	
AssetMaster/IDs/ID FFASMA.FMASID FFASMA. FMSBNO.; FAS001MI/Add	The field indicates the unique alpha-numeric ID of a fixed asset.
	A fixed asset can be identified either by the ID or the subnumber. The subnumber is a serial number for identification of one or several fixed assets under a specific fixed asset number.
AssetMaster/Description FFASMA.FMTXT1 FFASMA.FMTXT2.; FAS001MI/Add UpdateAsset	The field indicates an optional text that can be printed on different order documents together with the current material line.
AssetMaster/Note FFASMA.FMPPER FFASMA.FMAPER.; FAS001MI/Add UpdateAsset	The field indicates the acquisition period
AssetMaster/Status/Code FFASMA.FMFAST; FAS001MI/Add UpdateAsset	If add FAST = 5. If update FAST =1 or 5 else error message encountered.
AssetMaster/Name FFASMA.FMFADS; FAS001MI/Add UpdateAsset	The field indicates a shorter name of the fixed asset.
AssetMaster/ItemInstance/ItemID/ID FFASMA.FMITNO; FAS001MI/Add UpdateAsset	The field indicates the Item number.
AssetMaster/ItemInstance/StorageLocation/IDs/ID FFASMA.FMLOC1; FAS001MI/Add UpdateAsset	The field indicates the location of an asset, which enables you to keep track of assets. An asset can be located in different places.
AssetMaster/OwnedQuantity FFASMA.FMFAQT; FAS001MI/Add UpdateAsset	FA Quantity. The field indicates the number of physical objects represented by the fixed asset.
AssetMaster/DocumentReference @type	Set to "Invoice"
AssetMaster/DocumentReference/DocumentID/ID FFASMA.FMVONO FFASMA.FMVSER.; FAS001MI/Add	The field indicates the voucher number + voucher series number.
AssetMaster/CommissionDateTime FFASMA.FMAPER; FAS001MI/Add UpdateAsset	Activation period. The field indicates from which period the fixed asset has been used. If period type Activation period is selected for the depreciation type in the setup, this period is the starting point for depreciation.
AssetMaster/Cost/Amount	Set to 0.00
AssetMaster/Cost/CurrencyExchangeRate/SourceCurrencyCode FFASMA.FMCUCD; FAS001MI/Add UpdateAsset	The field indicates the abbreviation for the currency. The abbreviation must follow ISO standards.
AssetMaster/Cost/CurrencyExchangeRate/RateNumeric FFASMA.FMARAT; FAS001MI/Add UpdateAsset	The field indicates the exchange rate for the chosen currency.
AssetMaster/AssetTypeCode FFASMA.FMFATP; FAS001MI/Add UpdateAsset	This field indicates the fixed asset type.
AssetMaster/DepartmentCode FFASMA.FMCAT; FAS001MI/Add UpdateAsset	The field indicates a user-defined classification. The group enables you to keep track of similar fixed assets. By connecting an asset to a group you can use the group as a selection criterion when creating reports in Fixed Assets.
AssetMaster/CostCenterCode FFASMA.FMAIT2; FAS001MI/Add UpdateAsset	Accounting dimension 2. The field indicates an accounting identity in an accounting dimension.
AssetMaster/WarrantyCoverage/CoverageByDate/ExpireDateTime FFASMA.FMWADT; FAS001MI/Add UpdateAsset	The field indicates the date the warranty expires.

BankStatement/BankStatementHeader/DocumentID/ID

FABHED.V1BSRE; ABS100MI/AddStatmtHead

The field indicates the Transaction reference number - Added for each bank statement created.

BankStatement/BankStatementHeader/Description

FABHED.V1BSTY: ABS100MI/AddStatmtHead

The field indicates the Name of the file format needed in case different settings for different bank formats required for the same bank account.

Bank identifier code (part of BSID, see details for IBANID, BBANID and ID below):

- If CRS881.BankStatmtCode with value of "Description" (*) found: Retrieve code to be set as part of Bank account identifier (BSID) from position 1-6.

Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882.

- If CRS881.BankStatmtCode with value of "Description" (*) missing: No code needed for Bank account identifier (BSID).

(*) Maximum 30 characters of the description is possible (limitation in CRS881). The Bank statement code defined in CRS881 can maximum be 6 characters (BSID = 40 characters with 34 characters reserved for IBAN, BBAN or ID).

Comment about Bank identifier (ABS900 -

ABS100MI.GetBankIdent2):

- Used to find the CONO/DIVI applicable for the bank statement.
- Used in order to retrieve specific setting such as 'Bank statement type' (BSTY), 'Payment details' (PAYD), 'End-to-end ID' (ETEI) and 'Instruction ID' (INID).

BankStatement/BankStatementAccount/LineNumber

FABHED.V1STMN; ABS100MI/AddStatmtHead

The field indicates the Bank statement number (Line number).

Bank statement created (AddStatmtHead) per BankStatement/ BankStatementAccount with Statement number retrieved from first priority "ExternalSequence/ElectronicSequence" (see below) or second priority ExternalSequence/LegalSequence or third priority "LineNumber".

NB: AddStatmtHead.STMN will if existing always be populated, ABS100MI will then update FABHED.STMN depending on the setting for 'Bank statement number' (BSJD) in ABS900.

Comment:

See tab "1_Create Statement" for additional information about how to process the bank statement.

BankStatement/BankStatementAccount/ExternalSequence/ElectronicSequence

FABHED.V1STMN; ABS100MI/AddStatmtHead

The field indicates the Bank statement number.

Bank statement created (AddStatmtHead) per BankStatement/ BankStatementAccount with Statement number retrieved from first priority "ExternalSequence/ElectronicSequence" or second priority ExternalSequence/LegalSequence or third priority "LineNumber" (see above).

NB: AddStatmtHead.STMN will if existing always be populated, ABS100Ml will then update FABHED.STMN depending on the setting for 'Bank statement number' (BSJD) in ABS900.

Comment:

See tab "1_Create Statement" for additional information about how to process the bank statement.

BankStatement/BankStatementAccount/ExternalSequence/LegalSequence

FABHED.V1STMN; ABS100MI/AddStatmtHead

The field indicates the Bank statement number (Line number).

Bank statement created (AddStatmtHead) per BankStatement/ BankStatementAccount with Statement number retrieved from first priority "ExternalSequence/ElectronicSequence" (see above) or second priority ExternalSequence/LegalSequence or third priority "LineNumber" (see above).

NB: AddStatmtHead.STMN will if existing always be populated, ABS100MI will then update FABHED.STMN depending on the setting for 'Bank statement number' (BSJD) in ABS900.

Comment:

See tab "1_Create Statement" for additional information about how to process the bank statement.

BankStatement/BankStatementAccount/StatementPeriod/StartDateTime

Retrieved from: Statement/Period/StartDate Time and if missing from Balanos/State — OPBD or PREO or DPAV and if missing from Lowest AccountEntry/SpokingDate Time where Balanos/Statement/Bank	FARHED V1RSOT: ARS100MI/AddStatmtHead/I IndStatmtHead	The field indicates the Opening balance date.
- Statement/Period/Stat/Date/ Time and if missing from earth-Account/Statement/Period/Endplate/ Time and if missing from BalancaType = CPEID or PERCD or OPAV and if missing from SalancaType = CPEID or PERCD or OPAV and if missing from SalancaType = CPEID or PERCD or OPAV and if missing from SalancaType = CPEID or PERCD or OPAV and if missing from SalancaType = CPEID or PERCD or OPAV and if missing from The field indicates the Closing balance date. Retrieved from SalancaType = CPEID or CPEIV and if missing from SalancaType = CPEID or CLAY and if missing from SalancaType = CPEID or CLAY and if missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY and If missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY and If missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY and If missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY and If missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY and If missing from Highest Account/Endployers and IndiancaType = CPEID or CLAY india	FABHED.V1BSOT; ABS100MI/AddStatmtHead/UpdStatmtHead	
- BankAcount/Bance/Bal		
BalanceType = OPBD or PRCD or OPAV and if missing from - Lowest Account Intrivipolocing Date Time and if missing is set to current date. **RASHED V18SC1, ABS100MiAddSlasmMeteadUpdSlas		
- Lowest AccountEntry/BookingDateTime and if missing - set to current date - FABHED V1BSCT, ABS100Mi/AdStatmit-lead/UpdStatmit-lead - FABHED V1BSCT, ABS100Mi/AdStatmit-lead/UpdStatmit-lead - Retrieved from: - Retrieved from: - BankAccount/Banc@Bal		 BankAccount/AccountBalance/BalanceDateTime where
Set to current date.		BalanceType = OPBD or PRCD or OPAV and if missing from
### FABHED V1BSCT: ABS100MI/AddStarmtHead*** ### FABHED V1BSCT: ABS100MI/AddStarmtHead** ### FABHED V1BSCT: ABS100MI/AddStarmtHead** ### FABHED V1BSCT: ABS100MI/AddStarmtHead** ### FABHED V1BSCD: A		 Lowest AccountEntry/BookingDateTime and if missing
Retrieved from: - Statement/Benit/Statement/Account/BankAccount/ID FABHED.V1BSID, ABS100MI/AddStatmHead Retrieved from: - Statement/BankStatement/BankStatement/BankAccount/ID FABHED.V1BSID, ABS100MI/AddStatmHead The field indicates the Company/division's account ID to retrieve M38E Company/Division from and settings for Bank account identifie (e.g. setting of statement number) Used as 3rd priority if IBAN and IBBAN not available. Comment: - If Bank identifier code from 'BankStatementHeader/Description' was found. Add abank identifier code from 'BankStatementHeader/Description' was found. Add bank identifier code from 'BankStatementHeader/Description' was for found has because the c		те
- Statement/BankStatementAccount/BankAccou	FABHED.V1BSCT; ABS100MI/AddStatmtHead/UpdStatmtHead	•
- BankActount/BankStatement/BankStatementAccount/BankAccount/ID FABHED.V1BSID, ABS100MIAddStatmitHead FABHED.V1BSID, ABS100MIADD FABHED.V1BSID, ABS100MIADD FABHED.V1BSID,		
BalanceType = CLED or CLAV and if missing from - Highest Account/BankStatement/BankStatement/BankStatement/Account/BankAccount/ID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Idvision's account ID to retrieve M3BE Company/IDvision from and settings for Bank account identifie (e.g. setting of statement number) Used as 7d priority if IBAN and BBAN not available. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found; Add bank identifier code from "BankStatementHeader/Description" was found; Add bank identifier code from "BankStatementHeader/Description" was not bound. Add Bank Identifier code from "BankStatementHeader/Description" was not bound. Add Bank ID or max 40 char) bSID. FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Idvision's BBAN to retrieve M3BE Company/Idvision's Bank account identifier (e.g. setting of statement number) Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was not found; and IBAND to retrieve M3BE Company/Idvision's man data settings for Bank account identifier (e.g. setting of statement number). IBANKStatement/BankStatementAccount/BankID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Idvision's BBAN to retrieve M3BE Company/Idvision from and Settings of Bank account identifier (e.g. setting of statement number). IBANKStatement/BankStatementAccount/BankAccount/BankID The field indicates the Company/Idvision's BBAN to retrieve M3BE Company/Idvision from and settings for Bank account identifier (e.g. setting of statement number). IBANKStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Company/Idvision's BBAN to retrieve M3BE Company/Idvision from and settings for Bank account identifier (e.g. setting of statement number). IBANKStatement/BankStatementAccount/BankAccount/CurrencyCode The field indicates		- Statement Pendu/EndDate nine and in missing nom
Highest Account/BankStatement/Account/BankAccount/ID FABHED.V1BSID; ABS100MI/AddStatmHead		
Set to current date.		
The field indicates the Company/division's account 10 to retrieve M3BE Company/Division from and settings for Bank account identifie (e.g. setting of statement number). - Used as 3rd priority if IBAN and IBAN not available. Comment. - If Bank identifier code from "BankStatementHeader/Description" was round and bank identifier code (max 6 char) + IBANID (max 40 bank identifier code (max 6 char) + IBANID (max 40 bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID (max 40 bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID (max 40 bank IBANID (max 40 b		
M3BE Company/Division from and settings for Bank account identifie (e.g. setting of statement number). - Used as 3rd priority if IBAN and BBAN not available. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found; Add bank identifier code (max 6 char) + IBANID (max 40 char) to 85ID. Note: If no rice or de defined in CR5882. - IBank (Identifier code from "BankStatementHeader/Description" was not found; Add IBANID to (max 40 char) BSID. FABHED.V1BSID; ABS100MI/AddStatmiHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found; Add bank identifier code (max 6 char) + IBANID (max 40 char) to 85ID. Note: If no record found in ABS900, a new call is done without the Bank identifier code (max 6 char) + IBANID (max 40 char) to 85ID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR5882. - If Bank identifier code defined in CR5882. - If Bank identifier code from "BankStatementHeader/Description" was found. Add IBANID (max 40 char) bis BID. FABHED.V1BSID; ABS100MI/AddStatmiHead FABHED.V1BSID; ABS100MI/AddStatmiHead - The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. set good by the company) to the company identifier code (max 6 char) + IBANID (max 40 char) bis BID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR5882. - If Bank identifier code defined in CR5882. - If Bank identifier code from "BankStatementHeader/Description" was found; and the properties of the properties of the company's bank account and of the bank statement. - If Bank identifier code from "BankStatementHeader/Description" was found; and IBANID	BankStatement/BankStatementAccount/BankAccount/ID	The field indicates the Company/division's account ID to retrieve
(e.g. setting of statement number). - U-sed as 3rd priority if IBAN and IBAN not available. Comment If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. ABABCASTATEMENT/BankStatementAccount/BankAccount/BANID FABHED V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was onted as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was outled, and bank identifier code from "BankStatementHeader/Description" was outled, and bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID (max 40 char) BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID (max 40 char) BSID. The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID (max 40 char) BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found: Add BANID (max 40 char) BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID (max 40 char) BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found:	FADRED.V IDSID, ADS IOUWI/AQQStatifitheaq	
- Used as 3rd priority if IBAN and BBAN not available. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABSS00, a new call is done without the Bank identifier code defined in CR3882; - IBANEStatement/BankStatementAccount/BankAccount/BaNID FABHED.V1BSID; ABS100MI/AddStatmiHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number); - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add Banid in CR3882; - If Bank identifier code defined in CR3882; - If Bank identifier code (max 6 char) + IBANID (max 40 char) be substanced in CR3882; - If Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID (max 40 char) be substanced in CR3882; - If Bank identifier code defined in CR3882; - If Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID (max 40 char) BSID Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR3882; - If Bank identifier code from "BankAcco		
"If Bank Identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: fin or record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. "If Bank identifier code defined in CRS882. "If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). "Used as second priority if IBAN not available, as last priority ID will be used. Comment: "If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: if no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. "If Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank Identifier code from BankStatementHeader/Description" was not found: Add Bank Identifier code from BankStatementHeader/Description was found: Add bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) s BID. Note: fin or record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) s BID.		
was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new 36 char) + IBANID (max 40 char) to BSID. ItankStatement/BankStatementAccount/BankAccount/BBANID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as second priority if IBANI on available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) basid on the Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) basid. IBANEStatement/BankStatementAccount/BankAccount/BankID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID to (max 40 char) BSID. Note if no record found in ABS900, a new call is done without the Bank identifier code (max 6 char) + IBANID (max 40 char) BSID. Note if no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID to (max 40 char) BSID. Note if no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. It ank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 c		* - · · · · · · · · · · · · · · · · · ·
char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. -If Bank identifier code from BankStatementHeader/Description* was not found: Add IBANID to (max 40 char) BSID. FABHED V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Division BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) to BSID. The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: if no record found in ABS900, a new call is done without the Bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: if no record found in ABS900, a new call is done without the Bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. **IB BANK Identifier code (from "BankStatementHeader/Description" was not found: Add bank identifier code (from BankStatementHeader/Description" was not found: Add bank identifier code (from BankStatementHeader/Description" was not found: Add bank identifier code (from BankStatementHeader/Description" was not found: Add bank identifier code (from BankStatement type) (BSID). **If empty or missing, retrieved from "BankAcco		
Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and estings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. Provided the set of th		
Bank identifier code defined in CRS882. - If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from anskStatementHeader/Description" was not found: Add IBANID to (max 40 char) bSID. FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code form "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. - If Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID to (max 40 char) BSID. Priority order of type to be used for: a) Opening Balance (BSCB) or Closing balance (BSCB) or Closing balance (GBCB) or Closing balance (GBCB) (CLBD, CLAV. - If no or these balance t		
- If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. FABHED.V1BSID, ABS100MI/AddStatmtHead The field indicates the Company/division's BBAN to retrieve M3EE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/BankBankBankBankBankBankBankBankBankBank		
Hank Statement/Bank StatementAccount/BankAccount/BBANID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR5882. - If Bank identifier code defined in CR5882. - If Bank Identifier code defined in CR5882. Company/Division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add Dank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was found: Add IBANID to (max 40 char) BSID. Note: If no record found: Add IBANID to (max 40 char) BSID. The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Balance (BSCB)) - The field indicates the type of balance (BSCB) or Closing balance (BSCB) - The field indicates the type of balance if Bank statement type (DSTY) = 1. Priority order of type to be used for: a) Opening Balance (Rield BSCB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0.00 (must be man		
FABHED.V1BSID; ABS100MI/AddStatmtHead		
The field indicates the Company/division's BBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If n record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. PABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call its done without the Bank identifier code from "BankStatementHeader/Description" was found: Add Bank identifier code from "BankStatementHeader/Description" was found: Add Bank identifier code from "BankStatementHeader/Description" was found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeader/Description" was not found: Add Bank identifier code from "BankStatementHeade	RankStatement/RankStatementAccount/RankAccount/RRANID	was not lound. Add IDANID to (max 40 chai) bolb.
Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code offerine "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/BankID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code effined in CRS882 If Bank identifie		The field indicates the Company/division's BBAN to retrieve M3BF
setting of statement number). - Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/BANID** FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/CurrencyCode* FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/B	TABLES. VIBOLO, ABOTOONIIA kaastatiini laad	
- Used as second priority if IBAN not available, as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. IBANKStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Balance Type - The field indicates the type of balance if Bank statement type (BSTY): - 1. Priority order of type to be used for: a) Opening Balance (field BSCB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated): OPBD, CLAV.		
be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR9882 If Bank identifier code defined in CR9882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/IBANID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CR8882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode - FABHED.V1CUCD: ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/ BSCB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/Balance Type The field indicates the type of balance if Bank statement type (BSTY): - 1. Priority order of type to be used for: a) Opening Balance (field BSCB updated): CPBD, PRCD, OPAV If no not these balance types are available: Opening balance set to 0:00 (must be manually updated): - Others balance (Baca BSCB updated): CLBD, CLAV.		
- If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. PABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. PankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/BanceType" The field indicates the type of balance if Bank statement type (BSCB). The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (Bidd SSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated): CLBD, CLAV.		
was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code form "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. ### SABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. ###################################		
char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. ### Statement/BankStatementAccount/BankAccount/IBANID FABHED.V1BSID; ABS100MI/AddStatmtHead ### The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. ### Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code of from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. ###################################		
Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/IBANID FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) b SBID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode - FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSCB). : -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0.00 (must be manually updated). b) Closing Balance (field BSOB updated): CLBD, CLAV.		
Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number) Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. FABHED.V1CUCD; ABS100MI/AddStatmtHead FABHED.V1CUCD		
- If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/IBANID** FABHED.V1BSID; ABS100MI/AddStatmtHead The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. - If Bank identifier code defined in CRS882. - If Bank identifier code of from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/CurrencyCode** FABHED.V1CUCD; ABS100MI/AddStatmtHead **The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). **The field indicates the type of balance if Bank statement type (BSTY) = 1. **Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. - If non of these balance types are available: Opening balance set to 0.00 (must be manually updated)). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
### Was not found: Add IBANID to (max 40 char) BSID. ### RABHED.V1BSID; ABS100Ml/AddStatmtHead ### The field indicates the Company/division's IBAN to retrieve M3BE Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. #### Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. **Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **HankStatement/BankStatementAccount/BankAccount/CurrencyCode** ##################################		
### Pank Statement/Bank Statement Account/Bank Account/Bank Account/Bank Bank Statement Header / Description was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to Bank identifier code from "Bank Statement Header / Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. #### Pank Identifier code from "Bank Statement Header / Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. #### Pank Identifier code from "Bank Statement Header / Description" was not found: Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Statement Header / Description" was not found: Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Statement Header / Description" was not found: Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to (max 40 char) BSID. #### Pank Identifier code from "Bank Account / Add IBANID to		
Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSCB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSCB updated): OPBD, PRCD, OPAV. - If non of these balance types are available: Opening balance set to 0:00 (must be manually updated)). CLBD, CLAV.	BankStatement/BankStatementAccount/BankAccount/IBANID	was not lound. And ibaniab to (max 40 char) bolb.
Company/Division from and settings for Bank account identifier (e.g. setting of statement number). - Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSCB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		The field indicates the Company/division's IBAN to retrieve M3BE
- Used as first priority (if not available, BBAN and as last priority ID will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		setting of statement number).
will be used. Comment: - If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		- Used as first priority (if not available, BBAN and as last priority ID
- If Bank identifier code from "BankStatementHeader/Description" was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/CurrencyCode** FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). **BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType**; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
was found: Add bank identifier code (max 6 char) + IBANID (max 40 char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. **BankStatement/BankStatementAccount/BankAccount/CurrencyCode** FABHED.V1CUCD; ABS100MI/AddStatmtHead **FABHED.V1CUCD; ABS100MI/AddStatmtHead **The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). **BankStatement/BankStatementAccount/BankAccount/AccountBalance*/BalanceType; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
char) to BSID. Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882 If Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
Note: If no record found in ABS900, a new call is done without the Bank identifier code defined in CRS882. - If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		,
Bank identifier code defined in CRS882 If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
- If Bank identifier code from "BankStatementHeader/Description" was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
was not found: Add IBANID to (max 40 char) BSID. BankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType ; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
### RankStatement/BankStatementAccount/BankAccount/CurrencyCode FABHED.V1CUCD; ABS100MI/AddStatmtHead The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). #### BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. - If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
The field indicates the Currency code of the company's bank account and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). **BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType** ; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. - If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.	RankStatement/RankStatementAccount/RankAccount/CurrencyCode	, ,
and of the bank statement. - If empty or missing, retrieved from "BankAccount/AccountBalance/ Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType ; -/- The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
- If empty or missing, retrieved from "BankAccount/AccountBalance/ Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
Amount@currencyID" for either Opening balance (BSOB) or Closing balance (BSCB). BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceType The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		Amount@currencyID" for either Opening balance (BSOB) or Closing
The field indicates the type of balance if Bank statement type (BSTY) = 1. Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.	BankStatement/BankStatementAccount/BankAccount/AccountBalan	,
Priority order of type to be used for: a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		The field indicates the type of balance if Bank statement type (BSTY)
 a) Opening Balance (field BSOB updated): OPBD, PRCD, OPAV. - If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV. 		
 If non of these balance types are available: Opening balance set to 0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV. 		
0:00 (must be manually updated). b) Closing Balance (field BSCB updated): CLBD, CLAV.		
b) Closing Balance (field BSCB updated): CLBD, CLAV.		
- it non of these balance types are available: Closing balance is		
71 - 9		- it non of these balance types are available: Closing balance is

calculated using Total amount - Debit (BSTD) and Total amount - Credit (BSTC). (See tab "2_AmtExchRateCurr populated" for details).

BankStatement/BankStatementAccount/BankAccount/AccountBalance/DebitCreditFlag

-.-; -/-

The field indicates the Debit/Credit code to indicate amount sign for Opening and Closing balance if Bank statement type (BSTY) = 1.

BankStatement/BankStatementAccount/BankAccount/AccountBalance/Amount

FABHED.V1BSOB

FABHED.V1BSCB.; ABS100MI/AddStatmtHead

The field indicates the Amount for Opening balance (BSOB) or Closing balance BSCB) of the Bank account/Statement if Bank statement type (BSTY) = 1.

Comment about Reverse sign:

To be noted is that amounts in a bank statement can be shown with opposite sign (Debit/Credit code) than they are in M3 General Ledger, this according to bank rules. Bank statement shows the entries as they are on bank side, not on company side. If that is the case, all amounts included must be reversed (see tab "2_AmtExchRateCurr populated" for details).

@currencyID

FABHED.V1CUCD; ABS100MI/AddStatmtHead

The field indicates the Currency code of the Opening and Closing balance for the company's bank account.

- If the currency code for "BankAccount/CurrencyCode" is empty or missing, currency code from the attribute in this element is used. If also this element is empty or missing, the currency code from "BankStatementAccount/AccountryEntry/EntryAmount@currency" is

BankStatement/BankStatementAccount/BankAccount/AccountBalance/BalanceDateTime

FABHED.V1BSCT; ABS100MI/AddStatmtHead/UpdStatmtHead

The field indicates the Opening balance date (BSOT) and Closing balance date (BSCT).

For Opening balance date (BSOT), the date is used in case no StatementPeriod/StartDateTime is included.

Retrieved from:

- Record with BalanceType = OPBD and if missing from
- Record with BalanceType = PRCD and if missing from
- Record with BalanceType = OPAV.

For Closing balance date (BSCT), the date is used in case no StatementPeriod/EndDateTime is included. Retrieved from:

- Record with BalanceType = CLBD and if missing from
- Record with BalanceType = CLAV.

BankStatement/BankStatementAccount/TransactionSummary/CreditSummary/TotalAmount

FABHED.V1BSTD, V1BSTC.-; ABS100MI/AddStatmtHead

The field indicates the Total of credit transactions in Bank statement updated as Total amount Debit or Credit depending on if amounts must be reversed or not.

Comment about Reverse sign:

To be noted is that amounts in a bank statement can be shown with opposite sign (Debit/Credit code) than they are in M3 General Ledger, this according to bank rules. Bank statement shows the entries as they are on bank side, not on company side. If that is the case, all amounts included must be reversed (see tab "2_Amounts populated" for details).

Comment if Debit and CreditSummary missing: Calculated based on AccountEntry/EntryAmount, see tab "2 AmtExchRateCurr populated" for details.

BankStatement/BankStatementAccount/TransactionSummary/DebitSummary/TotalAmount

FABHED.V1BSTD, V1BSTC.-; ABS100MI/AddStatmtHead

The field indicates the Total of credit transactions in Bank statement updated as Total amount Debit or Credit depending on if amounts must be reversed or not.

Comment about Reverse sign:

To be noted is that amounts in a bank statement can be shown with opposite sign (Debit/Credit code) than they are in M3 General Ledger, this according to bank rules. Bank statement shows the entries as they are on bank side, not on company side. If that is the case, all amounts included must be reversed (see tab "2_Amounts populated" for details).

Comment if Debit and CreditSummary missing: Calculated based on AccountEntry/EntryAmount, see tab "2_AmtExchRateCurr populated" for details.

BankStatement/BankStatementAccount/AccountEntry/LineNumber

FABLIN.V2BLSN FABDET.V3BLSN FABDET.V3BLSS.; ABS100MI/AddStatmtLine The field indicates the Line number that is used to indicate that Bank statement line (AddStatmtLine) created when AccountEntry/Status/Code = 'Booked', "LineNumber" used as second priority if

AddStatmtDetail

"EntryNote" (see below) not available.

- If EntryNote and LineNumber missing, use incrementing number starting with 1 (one) for each new bank statement (AddStatmtHead) created.
- Use output parameters from AddStatmtHead as input parameters for AddStatmtLine for the following fields: CONO, DIVI, JBNO, JBDT and JBTM.

NB: Bank statement details (AddStatmtDetail) must also be created in case 'EntryDetails' (EntryBatch and EntryTransactions) missing.

- Use the same input parameters as for AddStatmtLine +
AddStatmtDetail.BLSS = Incrementing number starting with 1 (one)
per each new Line (BLSN).

BankStatement/BankStatementAccount/AccountEntry/EntryNote

FABLIN.V2BLSN FABDET.V3BLSN FABDET.V3BLSS.; ABS100MI/AddStatmtLine AddStatmtDetail The field indicates the Entry note. Bank statement line (AddStatmtLine) created when AccountEntry/Status/Code = 'Booked', "EntryNote "used as first priority (if not available, "LineNumber" will be used).

- If "EntryNote" (*) and "LineNumber" missing, use incrementing number starting with 1 (one) for each new bank statement (AddStatmtHead) created.
- (*) If EntryNote is string use LineNumber.

NB: Bank statement details (AddStatmtDetail) must also be created in case "EntryDetails" (EntryBatch and EntryTransactions) missing.

- Use the same input parameters as for AddStatmtLine +
AddStatmtDetail.BLSS = Incrementing number starting with 1 (one)
per each new Line (BLSN).use line number

BankStatement/BankStatementAccount/AccountEntry/AccountServicerNote

FABLIN.V2BLU1-V2BLU7; ABS100MI/AddStatmtLine

The field indicates the account servicer note, value updated to:

- -User defined field (AIN2)
- -Part of "Additional information Free text" (BLFX) with heading "AccServNote".

Note that the "User defined field" updated depends on the settings in ABS900 (recommended to use "User defined field 3").

BankStatement/BankStatementAccount/AccountEntry/EntryAmount

FANHED.V1BSTD, V1BSTC FABLIN.V2BLLF FABDET.V3BLNF.-; ABS100MI/AddStatmtHead AddStatmtLine AddStatmtDetail The field indicates the amount in the account entry.

If Payment details (PAYD) not selected in ABS900:

- Line amount currency (BLLF) in case InstructedSection/
 Amount@currency> and
 TransactionSection/Amount@currency> included and not differ.
- Net amount (BLNF) if AccountEntry/EntryDetails missing.

If Payment details (PAYD) is selected in ABS900:

- Line amount currency (BLLF) if AccountEntry/Details is missing and in case InstructedSection/Amount@currency> and
- <TransactionSection/Amount@currency> included and not differ.
- Net amount (BLNF) if AccountEntry/EntryDetails missing.

See tab "2_AmtExchRateCurr populated" for details about order of the amount retrieved for updated of (BLLF and BLNF) and comment about Reverse sign.

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

Comment if TransactionSummary/DebitSummary/TotalAmount and TransactionSummary/CreditSummary/TotalAmount missing: The Total debit amount (BSTD) and Total credit amount (BSTC) are calculated based on AccountEntry/EntryAmount.

@currencyID

FABHED.V1CUCD FABLIN.V2CUCD.-; ABS100MI/AddStatmtHead AddStatmtLine

The field indicates the Currency code of the transaction on the bank statement.

If Payment details (PAYD) not selected in ABS900:
- Currency code (CUCD) in case InstructedSection/

Amount@currency> and <TransactionSection/Amount@currency> included and not differ.

If Payment details (PAYD) is selected in ABS900:

 Currency code (CUCD) if AccountEntry/Details is missing and in case InstructedSection/Amount@currency> and <TransactionSection/ Amount@currency> included and not differ.

See tab "2 AmtExchRateCurr populated" for details about order of the currency code retrieved for updated of (CUCD).

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

NOTE: The currency code is also uploaded as Currency code of the header in case both "BankAccount/CurrencyCode" and "BankAccount/ AccountBalance/Amount@currencyID" are empty or missing.

BankStatement/BankStatementAccount/AccountEntry/DebitCreditFlag

FABDET.V3BLDC; ABS100MI/AddStatmtDetail

The field indicates the Debit/Credit code of the transaction on the bank statement line.

Only if "EntryDetail/EntryBatch/DebitCreditFlag" and "EntryDetail/ EntryTransaction/DebitCreditFlag" missing.

Comment:

The value sent (DEBIT/CREDIT) must be converted to fit the "Debit/ Credit code" field (BLDC) on the details of the statement:

- If "DebitCreditFlag" = DEBIT: Set BLDC to 'D'.
 If "DebitCreditFlag" = CREDIT: Set BLDC to 'C'

Exception if BankStatementHeader/Description = 'MT940':

- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = false: Set to 'D'.
- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = true: Set to 'RD'
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator = false: Set to 'C'
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator = true: Set to 'RC'

BankStatement/BankStatementAccount/AccountEntry/BankTransactionCode

FABLIN.V2ABNO FABDET.V3BLTT FABDET.V3BLBC FABDET.V3BLTX

FABLIX.V4BLFX.; ABS100MI/AddStatmtLine

AddStatmtDetail

AddStatmtAdditi

The field indicates the Bank transaction codes (ISO bank transaction codes or Proprietary bank transaction codes).

Codes from BankStatement/AccountEntry/BankTransactionCode used if no information available for BankStatement/AccountEntry/ EntryTransaction/BankTransactionCode:

- 1) BankTransactionCode with listID = "DomainFamilyCode":
- Updated as "Transaction type" (BLTT).
- 2) BankTransactionCode with listID = "DomainSubFamilyCode":
- Updated as "Business transaction code (BLBC).
- 3) BankTransactionCode with listID = "ProprietaryCode":
- Updated as "Bank reference" (ABNO). Note that the "User defined field" updated depends on the settings in ABS900 (recommended to use "User defined field 1").
- Updated as "Transaction text" (BLTX) if no EntryTransaction/ RemittanceInformation/StructuredRemittanceInformation/ DocumentReference type included.
- Also part of "Additional information Free text" (BLFX) with heading "LinePropCd".

Exception if BankStatementHeader/Description = "Leverandorservice" (DK-NETS_LS) and "MT940": BankTransactionCode with listID=""ProprietaryCode": - Updated as "Transaction type" (BLTT).

Exception if Message indicator (BSBF) = "DE_CAMT053" or "DE CAMT054" and Structured (BSUC) = 1 (selected): - First 4 characters of BankTransactionCode with listID = "ProprietaryCode" - Updated as "Transaction type" (BLTT). - 3 characters after the first "+" sign of BankTransactionCode with listID = "ProprietaryCode" - Updated as "Business transaction code" (BLBC).

The field indicates the type of Bank transaction code. The following listID attributes for 'ISO bank transaction codes' used by Local.ly must be considered:

- "DomainFamilyCode"
- "DomainSubFamilyCode"

The following listID attributes for 'Proprietary bank transaction codes'

@listID -.-; -/-

AddStatmtAdditi

	used by Local.ly must be considered: - "ProprietaryCode"
BankStatement/BankStatementAccount/AccountEntry/ReversalIndication FABLIN.V2ECCD; ABS100MI/AddStatmtLine	ator The field indicates the if the transaction is reversed. If indicator = "True", set 'Record code' (ECCD) to "Reversal" else no display.
	Note that the "User defined field" updated depends on the settings in ABS900 (recommended to use "User defined field 6").
BankStatement/BankStatementAccount/AccountEntry/Status/Code ; -/-	The field indicates the Status of the transaction. Available code for Account entry status: "Booked", "Pending" and "Information" Only BankStatement/AccountEntry with Status/Code = "Booked" must be considered.
BankStatement/BankStatementAccount/AccountEntry/BookingDateT FABLIN.V2ACDT; ABS100MI/AddStatmtLine	Time The field indicates the Accounting date of the bank statement transaction.
BankStatement/BankStatementAccount/AccountEntry/ValueDateTim FABLIN.V2CURD; ABS100MI/AddStatmtLine	
BankStatement/BankStatementAccount/AccountEntry/InvolvedAmount FABLIN.V2BLLF FABLIX.V4BLFX; ABS100MI/AddStatmtLine AddStatmtAdditi	Ints/InstructedSection/Amount The field indicates the instructed amount of the account entry. If Payment details (PAYD) not selected in ABS900: - Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs. If Payment details (PAYD) selected in ABS900: - Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs and AccountEntry/Details is missing. Also part of "Additional information - Free text" (BLFX) with heading "InstrAmt" if currency code of the line and the header differs.
@currencyID FABLIN.V2CUCD FABLIX.V4BLFX; ABS100MI/AddStatmtLine AddStatmtAdditi	NOTE: The bank statement line is created per: - AccountEntry if Payment details (PAYD) is not selected in ABS900. - AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900. The field indicates the Currency code of the instructed amount, included as: If Payment details (PAYD) not selected in ABS900: - Currency code (CUCD) in case Currency code of Instructed amount and Transaction amount differs. If Payment details (PAYD) selected in ABS900: - Currency code (CUCD) in case Currency code of Instructed amount code.
	and Transaction amount differs and AccountEntry/Details is missing. Also part of "Additional information - Free text" (BLFX) with heading "InstrAmt" in case currency code of the line and the header differs. NOTE: The bank statement line is created per: - AccountEntry if Payment details (PAYD) is not selected in ABS900 AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.
BankStatement/BankStatementAccount/AccountEntry/InvolvedAmou SourceCurrencyCode FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi	unts/InstructedSection/CurrencyExchangeRate/ The field indicates the Source currency of the instructed amount. Included as part of "Additional information - Free text" (BLFX) with heading "InstrSrcCcy" in case currency code of the line and the
BankStatement/BankStatementAccount/AccountEntry/InvolvedAmou FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi	header differs. unts/InstructedSection/CurrencyExchangeRate/TargetCurrencyCod The field indicates the Target currency of the instructed amount. Included as part of "Additional information - Free text" (BLFX) with heading "InstrTrgtCcy" in case currency code of the line and the header differs.
BankStatement/BankStatementAccount/AccountEntry/InvolvedAmou FABLIN.V2ARAT FABLIX.V4BLFX; ABS100MI/AddStatmtLine	unts/InstructedSection/CurrencyExchangeRate/RateNumeric The field indicates the Exchange rate of the instructed amount, included as:

Infor May 26, 2023 17

Exchange rate (ARAT) in case:
 Currency code of Instructed amount and Transaction amount differs

and
- Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if

@currencyID FABLIN.V2CUCD

AddStatmtAdditi

missing, AccountBalance/Amount@currency). Otherwise exchange rate (ARAT) not uploaded.

2) Also part of "Additional information - Free text" (BLFX) with heading "InstrXchRate" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/TransactionSection/Amount

FABLIN.V2BLLF FABLIN.V2BLLL FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine AddStatmtAdditi

The field indicates the transaction amount of the account entry.

If Payment details (PAYD) not selected in ABS900:

 - Line amount local (BLLL) in case Currency code of Instructed amount and Transaction amount differs and Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency).

Otherwise Line amount local (BLLL) set to 0.

- Line amount currency (BLLF) in case AccountEntry/EntryDetails is missing and only if @currency for both amounts are available (meaning not blank) and <CounterValueSection/Amount@currency> is different from <TransactionSection/Amount@currency>.

If Payment details (PAYD) selected in ABS900:

 Line amount local (BLLL) in case Currency code of Instructed amount and Transaction amount differs and Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency).

Otherwise Line amount local (BLLL) set to 0.

- Line amount currency (BLLF) in case AccountEntry/EntryDetails is missing and only if @currency for both amounts are available (meaning not blank) and <CounterValueSection/Amount@currency> is different from <TransactionSection/Amount@currency>.

Also part of "Additional information - Free text" (BLFX) with heading "TransAmt".

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

The field indicates the Currency code of the transaction amount, included as:

If Payment details (PAYD) not selected in ABS900:

- Currency code (CUCD) in case Currency code of Counter value amount and Transaction amount differs.

If Payment details (PAYD) selected in ABS900:

- Currency code (CUCD) in case Currency code of Counter value amount and Transaction amount differs and AccountEntry/Details is missing.

Also part of "Additional information - Free text" (BLFX) with heading "TransAmt" in case currency code of the line and the header differs.

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

Bank Statement/Bank Statement Account/Account Entry/Involved Amounts/Transaction Section/Currency Exchange Rate/Source Currency Code

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine

The field indicates the Source currency of the transaction amount. Included as part of "Additional information - Free text" (BLFX) with heading "TransSrcCcy".

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/TransactionSection/CurrencyExchangeRate/ TargetCurrencyCode

FABLIX.V4BLFX: ABS100MI/AddStatmtAdditi

The field indicates the Target currency of the transaction amount. Included as part of "Additional information - Free text" (BLFX) with heading "TransTrgtCcy".

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/TransactionSection/CurrencyExchangeRate/RateNumeric

FABLIN.V2ARAT
FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine
AddStatmtAdditi

The field indicates the Exchange rate of the transaction amount, included as:

- 1) Exchange rate (ARAT) in case:
- Currency code of Instructed amount and Transaction amount differs

- Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency).

Otherwise exchange rate (ARAT) not uploaded.

2) Also included as part of "Additional information - Free text" (BLFX) with heading "TransXchRate".

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/CounterValueSection/Amount

FABLIN.V2BLLL

FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine

AddStatmtAdditi

The field indicates the Counter value amount.

If Payment details (PAYD) not selected in ABS900:

 Line amount local (BLLL) in case Currency code of Counter value amount and Transaction amount differs and Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing,

AccountBalance/Amount@currency).

Otherwise Line amount local (BLLL) set to 0.

If Payment details (PAYD) selected in ABS900:

- Line amount currency (BLLF) in case AccountEntry/EntryDetails is missing and in case Currency code of Counter value amount and

Transaction amount differs and Local currency

(MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing,

AccountBalance/Amount@currency).
Otherwise Line amount local (BLLL) set to 0.

Also included as part of "Additional information - Free text" (BLFX) with heading "CntValAmt" in case currency code of the line and the header differs.

@currencyID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Currency code of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValAmt" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/CounterValueSection/CurrencyExchangeRate/

SourceCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Source currency of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValSrcCcy" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/CounterValueSection/CurrencyExchangeRate/ TargetCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Target currency of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValTrgtCcy" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/InvolvedAmounts/CounterValueSection/CurrencyExchangeRate/RateNumeric

FABLIN.V2CUCD

FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine

AddStatmtAdditi

The field indicates the Exchange rate of the counter value amount, included as:

1) Exchange rate (ARAT) in case a) Currency code of Counter value amount and Transaction amount differs and b) Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing,

AccountBalance/Amount@currency).

Otherwise exchange rate (ARAT) not uploaded.

 Part of "Additional information - Free text" (BLFX) with heading "CntValXchRate" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/Charges/TotalAmount

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Charge total amount stored as Additional information - Free text (BLFX) with heading "ChargeAmt".

@currencyID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Currency code of the charge total amount stored as Additional information - Free text (BLFX) with heading "ChargeAmt".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryBatch/MessageID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Message ID of the transaction stored as Additional information - Free text (BLFX) with heading "MessageID".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryBatch/PaymentInformationID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Payment reference number stored as Additional information - Free text (BLFX) with heading "PmtInfoID"

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryBatch/NumberOfTransactions FABDET.V3BLSN

FABDET.V3BLSS.: ABS100MI/AddStatmtDetail

The field indicates the Number of transactions included in the batch. Bank statement details (AddStatmtDetail) created per "EntryDetails/ EntryBatch" if "NumberOfTransactions" = 0 or if no EntryTransaction included (see below).

- Use the same input parameters as for AddStatmtLine + AddStatmtDetail.BLSS = Incrementing number starting with 1 (one) per each new Line (BLSN).

Number of transactions decides if bank statement details must be

- per EntryBatch (NumberOfTransctions = 0) or
- per EntryTransaction (NumberOfTransactions # 0)

NB: In case "Entrybatch/NumberOfTransactions" missing, check if "EntryTransaction" exists or not:

- If yes, Create Bank statement details (AddStatmtDetail) per "EntryTransaction".
- If no, Create Bank statement details (AddStatmtDetail) per "EntryBatch" or if missing per AccountEntry

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryBatch/TotalAmount

FABDET.V3BLNF; ABS100MI/AddStatmtDetail

The field indicates the total amount of the entry batch.

- Net amount for Bank statement details (BLNF) if EntryTransaction missing

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryBatch/DebitCreditFlag

FABDET.V3BLDC; ABS100MI/AddStatmtDetail

The field indicates the Debit/Credit code of the transaction on the bank statement detail.

- Only if "EntryDetail/EntryTransactions/DebitCreditFlag" missing.

Comment:

The value sent (DEBIT/CREDIT) must be converted to fit the "Debit/ Credit code" field (BLDC) on the details of the statement:

- If "DebitCreditFlag" = DEBIT: Set BLDC to 'D'.
 If "DebitCreditFlag" = CREDIT: Set BLDC to 'C'.

Exception if BankStatementHeader/Description = 'MT940':

- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = false: Set to 'D'
- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = true: Set to 'RD'.
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator
- = false: Set to 'C'
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator = true: Set to 'RC'

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/LineNumber

FABDET.V3BLSN

FABDET.V3BLSS.; ABS100MI/AddStatmtDetail

The field indicates the Line number of the batch. Bank statement details (AddStatmtDetail) created per "EntryDetails/EntryTransaction" if "available.

- Use the same input parameters as for AddStatmtLine + AddStatmtDetail.BLSS = Incrementing number starting with 1 (one) per each new Line (BLSN)

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/MessageID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Message ID of the transaction stored as Additional information - Free text (BLFX) with heading "MessageID".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/PaymentInformationID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Payment reference number stored as Additional information - Free text (BLFX) with heading "PmtInfoID".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/InstructionID

FABLIX.V4BLFX

FABDET.V3EXIn, V3EXNn.-; ABS100MI/AddStatmtAdditi AddStatmtDetail

The field indicates the Instruction ID (contains an internal ID from the initiating part of the transaction), included as:

- 1) Additional information free text (BLFX) with heading "InstructionID" if value sent is not "NOTPROVIDED" or "NotProvided".
- 2) GL additional information if ABS100MI.GetBankIdent.INID = 1: InstructionID included in next EXIn-field available with category (EXNn) set to 267 and 467 if value sent is not "NOTPROVIDED" or "NotProvided"

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/TransactionID

FABLIX.V4BLFX

FABDET.V3EXIn, V3EXNn.-; ABS100MI/AddStatmtAdditi AddStatmtDetail

The field indicates the Transaction ID (contains End-to-end ID from the initiating part of the transaction), included as:

- 1) Additional information free text (BLFX) with heading "TransactionID" if value sent is not "NOTPROVIDED" or "NotProvided".
- 2) GL additional information if ABS100MI.GetBankIdent.ETEI = 1: TransactionID included in next EXIn-field available with category

(EXNn) set to 266 and 466 if value sent is not "NOTPROVIDED" or "NotPróvided"

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/ChequeNumber

FABDET.V3EXIn, FBADET.V3EXNn, FABLIX.V4BLFX.; ABS100MI /AddStatmtDetail AddStatmtAdditi

The field indicates the Check number, included as:

- GL additional information: ChequeNumber included in next EXInfield available with category (EXNn) set to '214'. This applies only if ChequeNumber is less or equal 15 characters.

Also part of "Additional information - Free text" (BLFX) with heading "ChequeNo". This applies only if ChequeNumber is greater than 15 characters.

Comment:

- If the bank account identifier is defined with a FAM function for AR having a payment method with payment class 2-Check payment with direct allocation, the check number will be updated in the Check book as well as added as additional information AR with number 215 and GL with number 002.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/Reference @sequence

-.-; -/-

@name

The field indicates the sequenece number of the External reference with value depending on format.

- 1) AccountServicesTransactionID (used by e.g. camt.053):
- All sequence numbers with name="AccountServicesTransactionID" or "lcl.AccountServicesTransactionID" must be considerred.
- 2) CustomerReference (used by "Plus Giro Total IN" or "BGMAX"):
- All sequence numbers with name="CustomerReference" or "Icl.CustomerReference" must be considerred.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ExternalReferences/Reference/NameValue

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

FABLIX.V4BLFX: ABS100MI/AddStatmtAdditi

The field indicates the External reference with value depending on format.

- 1) AccountServicesTransactionID (used by e.g. camt.053):
- If name="AccountServicesTransactionID" or
- "Icl.AccountServicesTransactionID": Included as additional information - Free text (BLFX) with heading 'AccServTransID'
- 2) CustomerReference (used by "Plus Giro Total IN" or "BGMAX"): - If name="CustomerReference" or "Icl.CustomerReference": Included as additional information - Free text (BLFX) with heading 'CustRef'
- 3) FinancialPartyReference (used by e.g. camt.053): If name="FinancialPartyReference" or "Icl.FinancialPartyReference": Included as additional information - Free text (BLFX) with heading 'FinPartyRef'
- 4) ClearingSystemReference (used by e.g. camt.053):
- If name="ClearingSystemReference" or
- "Icl.ClearingSystemReference": Included as additional information Free text (BLFX) with heading 'ClearSysRef'

The field indicates the name attribute for the External reference with value depending on format.

- 1) AccountServicesTransactionID (used by e.g. camt.053):
- If name="AccountServicesTransactionID" or
- "Icl.AccountServicesTransactionID": Included as additional information - Free text (BLFX) with heading "AccServTransID". In case of multiple records, concatenated with blank between.
- 2) CustomerReference (used by "Plus Giro Total IN" or "BGMAX"):
- If name="CustomerReference" or "Icl.CustomerReference": Included as additional information - Free text (BLFX) with heading "CustRef". In case of multiple records, concatenated with blank between.
- 3) FinancialPartyReference (used by e.g. camt.053):
 If name="FinancialPartyReference" or "Icl.FinancialPartyReference":
 Included as additional information Free text (BLFX) with heading 'FinPartyRef'.
- 4) ClearingSystemReference (used by e.g. camt.053):
- If name="ClearingSystemReference" or
- "Icl.ClearingSystemReference": Included as additional information -Free text (BLFX) with heading 'ClearSysRef'.

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/Amount

FABDET.V3BLNF.-; ABS100MI/AddStatmtLine AddStatmtDetail

The field indicates the total amount of the entry transaction.

If Payment details (PAYD) not selected in ABS900:

- Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs. All records for the AccountEntry must be summarized. Only if EntryTransaction/ Amount@currency and AccountEntry/EntryAmount@currency are the same
- Net amount for Bank statement details (BLNF) if EntryTransaction/ Remittance or EntryTransaction/InvolvedAmounts missing.

If Payment details (PAYD) not selected in ABS900:

- Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs. Only if EntryTransaction/ Amount@currency and AccountEntry/EntryAmount@currency are the
- Net amount for Bank statement details (BLNF) if EntryTransaction/ Remittance or EntryTransaction/InvolvedAmounts missing

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/DebitCreditFlag

FABDET.V3BLDC; ABS100MI/AddStatmtDetail

The field indicates the Debit/Credit code of the transaction on the bank statement detail.

- If missing, retrieved from "EntryDetail/EntryBatch/DebitCreditFlag" and if missing from "AccountEntry/DebitCreditFlag".

Comment:

The value sent (DEBIT/CREDIT) must be converted to fit the "Debit/ Credit code" field (BLDC) on the details of the statement.:

- If "DebitCreditFlag" = DEBIT: Set BLDC to 'D'.
 If "DebitCreditFlag" = CREDIT: Set BLDC to 'C'.

Exception if BankStatementHeader/Description = 'MT940':

- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = false: Set to 'D'.
- If "DebitCreditFlag" = DEBIT and AccountEntry/ReversalIndicator = true: Set to 'RD'
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator
- = false: Set to 'C'
- If "DebitCreditFlag" = CREDIT and AccountEntry/ReversalIndicator
- = true: Set to 'RC'

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/InstructedSection/Amount The field indicates the Instructed amount, included as:

FABDET.V3BLNF FABLIN.V2BLLF FABLIX.V4BLFX.-; ABS100MI/AddStatmtDetail AddStatmtLine AddStatmtAdditi

If Payment details (PAYD) not selected in ABS900:

- Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs. All records for the AccountEntry must be summarized.
- Net amount (BLNF) in case Currency code of Instructed amount and Transaction amount differs and amount for EntryTransaction/ RemittanceInformation missing or If EntryTransaction/Charges/ ChargeDetail/ChargeAmount included and EntryTransaction/ InvolvedAmount/InstructedSection/Amount @currency and the Bank statement header currency (*) are the same.

If Payment details (PAYD) selected in ABS900:

- Line amount currency (BLLF) in case Currency code of Instructed amount and Transaction amount differs.
- Net amount (BLNF) in case Currency code of Instructed amount and Transaction amount differs and amount for EntryTransaction/ RemittanceInformation missing or If EntryTransaction/Charges/ ChargeDetail/ChargeAmount included and EntryTransaction/ InvolvedAmount/InstructedSection/Amount @currency and the Bank statement header currency (*) are the same.
- (*) Currency code retrieved from:
- a) BankStatementAccount/BankAccount/CurrencyCode and if missing b) BankStatementAccount/BankAccount/ AccountBalance/ Amount@currency and if missing c) AccountryEntry/ EntryAmount@currency.

Also include as part of "Additional information - Free text" (BLFX) with heading "InstrAmt" in case currency code of the line and the header differs.

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

@currencyID

FABLIN.V2CUCD FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine AddStatmtAdditi The field indicates the Currency code of the instructed amount, include as:

If Payment details (PAYD) not selected in ABS900:

- Currency code (CUCD) in case Currency code of Instructed amount and Transaction amount differs.

If Payment details (PAYD) selected in ABS900:

- Currency code (CUCD) in case Currency code of Instructed amount and Transaction amount differs.

Also part of "Additional information - Free text" (BLFX) with heading "InstrAmt" in case currency code of the line and the header differs.

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/InstructedSection/CurrencyExchangeRate/SourceCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Source currency of the instructed amount. Include as part of "Additional information - Free text" (BLFX) with heading "InstrSrcCcy" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/InstructedSection/CurrencyExchangeRate/TargetCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Target currency of the instructed amount. Include as part of "Additional information - Free text" (BLFX) with heading "InstrTrgtCcy" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/InstructedSection/CurrencyExchangeRate/RateNumeric

FABLÍN.V2ARAT FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine AddStatmtAdditi The field indicates the Exchange rate of the instructed amount, included as:

1) Exchange rate (ARAT) in case a) Currency code of Instructed amount and Transaction amount differs and b) Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency).

Otherwise exchange rate (ARAT) not uploaded.

2) Part of "Additional information - Free text" (BLFX) with heading "InstrXchRate" in case currency code of the line and the header

differs.

not included.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/Transaction/Amount

FABDET.V3BLNF FABLIN.V2BLLL FABLIN.V2BLLF FABLIX.V4BLFX.-; ABS100MI/AddStatmtDetail AddStatmtLine AddStatmtAdditi

If Payment details (PAYD) not selected in ABS900:

The field indicates the Transaction amount, included as:

- Line amount local (BLLL) in case Currency code of Instructed amount and Transaction amount differs and Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency). All records for the AccountEntry must be summarized. Otherwise Line amount local (BLLL) set to 0. - Net amount (BLNF) in case amount for EntryTransaction/ RemittanceInformation missing and EntryTransaction/ InvolvedAmount/InstructedSection/Amount missing or not used. Note that the amount is only uploaded to (BLNF) if AccountEntry/ EntryDetails/EntryTransaction/Charges/ChargeDetail/ChargeAmount

If Payment details (PAYD) selected in ABS900:

- Line amount currency (BLLF) in case /InstructedSection/Amount not used
- Line amount local (BLLL) in case Currency code of Instructed amount and Transaction amount differs and Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing, AccountBalance/Amount@currency). Otherwise Line amount local (BLLL) set to 0.
- Net amount (BLNF) in case amount for EntryTransaction/ RemittanceInformation missing and EntryTransaction/ InvolvedAmount/InstructedSection/Amount missing or not used. Note that the amount is only uploaded to (BLNF) if AccountEntry/ EntryDetails/EntryTransaction/Charges/ChargeDetail/ChargeAmount not included.

Also included as part of "Additional information - Free text" (BLFX) with heading "TransAmt".

NOTE: The bank statement line is created per:

- AccountEntry if Payment details (PAYD) is not selected in ABS900.
- AccountEntry/EntryDetails if Payment details (PAYD) is selected in ABS900.

@currencyID

FABLIN.V2CUCD

FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine

AddStatmtAdditi

The field indicates the Currency code of the transaction amount.

If Payment details (PAYD) selected in ABS900:

- Currency code (CUCD) in case Currency code of Instructed amount

and Transaction amount differs.

Also included as part of "Additional information - Free text" (BLFX) with heading "TransAmt".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/TransactionSection/CurrencyExchangeRate/SourceCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Source currency of the transaction amount. Included as part of "Additional information - Free text" (BLFX) with heading "TransSrcCcy".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/TransactionSection/CurrencyExchangeRate/TargetCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Target currency of the transaction amount. Included as part of "Additional information - Free text" (BLFX) with heading "TransTrgtCcy".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/TransactionSection/CurrencyExchangeRate/RateNumeric

FABLIN.V2ARAT

FABLIX.V4BLFX.-; ABS100MI/AddStatmtLine

AddStatmtAdditi

The field indicates the Exchange rate of the transaction amount, included as:

1) Exchange rate (ARAT) in case a) Currency code of Instructed amount and Transaction amount differs and b) Local currency (MNS100MI.GetBasicData.LOCD) is equal to Bank statement header currency (BankAccount/CurrencyCode and if missing,

AccountBalance/Amount@currency).

Otherwise exchange rate (ARAT) not uploaded.

Part of "Additional information - Free text" (BLFX) with heading "TransXchRate".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/CounterValueSection/Amount

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Counter value amount. Included as part of "Additional information - Free text" (BLFX).

 If missing, retrieved from "AccountEntry/InvolvedAmounts/ TransactionSection/CurrencyExchangeRate/TargetCurrencyCode".

- Only included if Line.CUCD and Head.CUCD differs.

@currencyID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Curreny code of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValAmt" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/CounterValueSection/CurrencyExchangeRate/SourceCurrencyCode

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Source currency of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValSrcCcy" in case currency code of the line and the header differs.

Bank Statement/Bank Statement Account/Account Entry/Entry Detail/Entry Transaction/Involved Amounts/Counter Value Section/Involved Am

CurrencyExchangeRate/TargetCurrencyCode FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Target currency of the counter value amount. Included as part of "Additional information - Free text" (BLFX) with heading "CntValTrgtCcy" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/InvolvedAmounts/CounterValueSection/

CurrencyExchangeRate/RateNumeric FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Exchange rate of the counter value amount, included as part of "Additional information - Free text" (BLFX) with heading "CntValXchRate" in case currency code of the line and the header differs.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/BankTransactionCode

FABLIN.V2ABNO FABDET.V3BLTT

FABDET.V3BLBC.; ABS100MI/AddStatmtLine

AddStatmtDetail

The field indicates the Bank transaction codes (ISO bank transaction codes or Proprietary bank transaction codes).

Codes from /AccountEntry/BankTransactionCode used if no information available for /AccountEntry/EntryTransaction/

BankTransactionCode (see exception for point 3 below):

- 1) BankTransactionCode with listID = "DomainFamilyCode":
- Updated as "Transaction type" (BLTT).
- 2) BankTransactionCode with listID = "DomainSubFamilyCode":
- Updated as "Business transaction code (BLBC).
- 3) BankTransactionCode with listID = "ProprietaryCode":
- If Payment details (PAYD) is selected: Updated as "Bank reference" (ABNO). Note that the "User defined field" updated depends on the settings in ABS900 (recommended to use "User defined field 1").
- Updated as "Transaction text" (BLTX) if no EntryTransaction/ RemittanceInformation/StructuredRemittanceInformation/ DocumentReference type included.
- Also part of "Additional information Free text" (BLFX) with heading "PropCd".

Exception if Message indicator (BSBF) = "DE CAMT053" or "DE CAMT054" and Structured (BSUC) = 1 (selected): - First 4 characters of BankTransactionCode with listID = "ProprietaryCode" - Updated as "Transaction type" (BLTT) - 3 characters after the first "+" sign of BankTransactionCode with listID = "ProprietaryCode" - Updated as "Business transaction code" (BLBC).

The field indicates the type of Bank transaction code. The following listID attributes for 'ISO bank transaction codes" used by Local.ly must be considered:

- "DomainFamilyCode"
- "DomainSubFamilyCode"

The following listID attributes for 'Proprietary bank transaction codes" used by Local.ly must be considered:

"ProprietaryCode"

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ReturnInformation/ReturnReasonCode

FABLIX.V4BLFX: ABS100MI/AddStatmtAdditi

The field indicates the Return reason code from the bank (e.g.

'Rejected' or 'Cancelled'). Included as part of "Additional information -Free text" (BLFX) with heading "ReturnInfo".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/ReturnInformation/ReturnReason

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Return reason text from the bank. Included as part of "Additional information - Free text" (BLFX) with heading "ReturnInfo".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/Charges/TotalAmount

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Charge total amount stored as Additional information - Free text (BLFX) with heading "ChargeAmt".

@currencyID

@listID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Currency code of the charge total amount stored as Additional information - Free text (BLFX) with heading "ChargeAmt".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/Charges/ChargeDetail/ChargeType

FABDET.V3BLTX; ABS100MI/AddStatmtDetail

The field indicates the type of Charge that is uploaded to 'Transaction text' (BLTX) as fixed text set to 'Charge' + value of 'ChargeDetail/ChargeType' (if available) using '-' as separator.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/Charges/ChargeDetail/ChargeAmount

FABLIX.V4BLFX

FABDET.V3BLNF.-: ABS100MI/AddStatmtAdditi

AddStatmtDetail

The field indicates the Charge detail amount stored as:

- Additional information - Free text (BLFX) with heading

"ChargeDetailAmt".

- Net amount (BLNF) uploaded in case ChargeIncludedIndicator not equal 'false', User-defined field 3 (BSF3 in ABS900, temporary field to indicate 'Upload Bank charges) and the currencyID of the Charge amount, Instructed amount and Bank statement header are the same .

@currencyID

FABLIX.V4BLFX: ABS100MI/AddStatmtAdditi

The field indicates the Currency code of the charge total amount stored as Additional information - Free text (BLFX) with heading "ChargeDetailAmt".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/Charges/ChargeDetail/ChargeIncludedIndicator

-.-; -/-

The field indicates if the ChargeDetail is only included as pre-advice (value 'false') and in that case not uploaded, see element EntryTransaction/Charges/ChargeDetail/ChargeAmount for details

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RemittanceInformation/UnstructuredRemittanceText The field indicates the Unstructured text stored as Additional

information - Free text (BLFX) with heading "Unstructured".

- In case of multiple records for "UnstructuredRemittanceText", text must be concatenated (with blank between).

Special handling if "Message indicator" (BSBF) from ABS900 is not

a) If "Message indicator" (BSBF) = BankStatement/

BankStatementHeader/Description and: - Structured (BSUC) checkbox is selected and

- Qualifier sign (BSQS) is not blank and
- User defined field 1 (BSF1) is 0:

if "Qualifier sign" (BSQS) is '/'

- UnstructuredRemittanceText is scanned if "Qualifier sign" (BSQS) (e.g. ?) is found in the text and replaced with one (1) blank and if code word "REMI" is found in the text, retain the "Qualifier sign" (BSQS) (e.g.?) on succeeding characters until the next code word is found (e.g. ACCW).

if "Qualifier sign" (BSQS) is not '/'

- UnstructuredRemittanceText is scanned if "Qualifier sign" (BSQS) (e.g. ?) is found in the text and replaced with one (1) blank
- b) If "Message indicator" (BSBF) = BankStatement/ BankStatementHeader/Description and:
- Structured (BSUC) checkbox is selected and
- Qualifier sign (BSQS) is not blank and
- User defined field 1 (BSF1) is not 0:

if "Qualifier sign" (BSQS) is '/'

- UnstructuredRemittanceText is scanned if "Qualifier sign" (BSQS) (e.g. ?) is found in the text and if so, both "Qualifier sign" (BSQS) + the number of characters as indicated in User defined field 1 (BSF1) must be replaced with one (1) blank and if code word "REMI" is found in the text retain, the "Qualifier sign" (BSQS) (e.g.?) on succeeding characters until the next code word is found (e.g. ACCW).

if "Qualifier sign" (BSQS) is not '/'

- UnstructuredRemittanceText is scanned if "Qualifier sign" (BSQS) (e.g. ?) is found in the text and if so, both "Qualifier sign" (BSQS) + the number of characters as indicated in User defined field 1 (BSF1) must be replaced with one (1) blank

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/RemittanceInformation/ StructuredRemittanceInformation/DocumentReference

@type

FABLIX.V4BLFX

FABDET.V3BLTX.-; ABS100MI/AddStatmtAdditi

AddStatmtDetail

The field indicates the Type of document reference that is stored as:

1) Additional information - Free text (BLFX) with heading "StructDocumentID". In case of multiple records, DocumentReference@type (and DocumentReference/DocumentID/ ID) are concatenated with blank between.

2) Transaction text (BLTX).

- NB: If this tag is not available, the Transaction text (BLTX) is updated with the BankTransactionCode with listID="ProprietaryCode" if available under EntryTransaction or AccountEntry level.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RemittanceInformation/ StructuredRemittanceInformation/DocumentReference/DocumentID/ID

FABLIX.V4BLFX

FABDET.V3CINO, V3SINO.-; ABS100MI/AddStatmtAdditi AddStatmtDetail

The field indicates the Document number (e.g. invoice number) that is stored as:

1) Additional information - Free text (BLFX) with heading "StructDocumentID". In case of multiple records, (DocumentReference@type and) DocumentReference/DocumentID/ ID) are concatenated with blank between.

2) Customer invoice number (CINO) / Supplier invoice number

- The field/-s updated depends on the bank statement type: a) If ABS900MI.GetBankIdent.BSTY= 1 or 2: Updated as Customer invoice number (CINO) and Supplier invoice number (SINO). b) If ABS900MI.GetBankIdent.BSTY= 3: Update Customer invoice number (CINO).

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RemittanceInformation/ StructuredRemittanceInformation/RemittanceReferredDocumentAmounts/RemittedAmount

FABDET.BLNF; ABS100MI/AddStatmtDetail

The field indicates the Remitted amount (paid amount) that is included as Net amount (BLNF)

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/RemittanceInformation/ StructuredRemittanceInformation/RemittanceReferredDocumentAmounts/CreditNoteAmount

FABDET.BLNF; ABS100MI/AddStatmtDetail

The field indicates the Credit note amount (deducted amount) that is included as Net amount (BLNF).

BankStatement/BankStatementAccount/AccountEntry/Entry/Detail/EntryTransaction/RemittanceInformation/ StructuredRemittanceInformation/StructuredCreditorReference

FABLIX.V4BLFX

FABDET.V3PAIN .-; ABS100MI/AddStatmtAdditi

AddStatmtDetail

The field indicates the Structured creditor reference (e.g. OCR, KID etc.), included as:

a) Part of Additional information - Free text (BLFX) with heading "StructCreditorRef" (see tab "3_Structure of BLFX" for details). In case of multiple records, StructuredCreditorReference must be concatenated (with blank between).

b) Updated as Parallel invoice number (PAIN).

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RemittanceInformation/UserArea

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the message specific information that will be stored depending on type of information.

The following Property/NameValue is currently retrieved:

1) name="AdditionalRemittanceInformation" or

"Icl.AdditionalRemittanceInformation": Part of "Additional information -Free text" (BLFX) with heading "AddRemInfo"

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/DebtorParty/Name

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Debtor party name and is included as part of the Additional information - Free text (BLFX) with heading "Debtor".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/DebtorParty/FinancialAccount/ID

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Debtor's bank account ID (other type of bank

account than IBAN and BBAN) - used as third priority if IBAN and BBAN not available. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

- Use DebtorParty/FinancialAccount/ID as 1st priority
- Use DebtorParty/FinancialAccount/IBANID as 2nd priority (normal not included)
- Use DebtorParty/FinancialAccount/BBANID as 3rd priority

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type:

- a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:
- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/DebtorParty/FinancialAccount/ **BBANID**

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Debtor's BBAN - used as first priority if IBAN not available, as last priority ID will be used. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

See FinancialAccount/ID.

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type: a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:

- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/DebtorParty/FinancialAccount/ **IBANID**

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Debtor's IBAN - used as 1st priority (if not available, BBAN and as last priority ID will be used. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

- See FinancialAccount/ID.

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type:

a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:

- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/CreditorParty/PartyIDs/ID FABLIN.V2SPYN; ABS100MI/AddStatmtLine This field indicates the Payee number (SPYN).

NB: Only applicable for LogicalID = infor.gtn.connectivity

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/CreditorParty/Name @languageID

FABLIX.V4BLFX; ABS100MI/AddStatmtAdditi

The field indicates the Creditor party name and is included as part of the Additional information - Free text (BLFX) with heading "Creditor".

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/CreditorParty/FinancialAccount/ID

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Creditor's bank account ID (other type of bank account than IBAN and BBAN) - used as 3rd priority if IBAN and BBAN not available. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

- Use CreditorParty/FinancialAccount/ID as 1st priority
- Use CreditorParty/FinancialAccount/IBANID as 2nd priority (normal not included)
- Use CreditorParty/FinancialAccount/BBANID as 3rd priority

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type:
a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:

- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/CreditorParty/FinancialAccount/BBANID

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Creditor's BBAN - used as 2nd priority if IBAN not available, as last priority ID will be used. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

- See FinancialAccount/ID.

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type:
a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:

- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/RelatedParties/CreditorParty/FinancialAccount/IBANID

FABLIN.V2BLAN; ABS100MI/AddStatmtLine

The field indicates the Creditor's IBAN - used as 1st priority (if not available, BBAN and as last priority ID will be used. The information is only uploaded when 'Payment details' = Yes is used.

Exception if BankStatementHeader/Description = 'Slovenska Sporitelna':

- See FinancialAccount/ID.

Comment:

The related party to use for the bank account (BLAN), must be identified depending on the bank statement type:

a) If ABS900MI.GetBankIdent.BSTY= 1 or 2:

- If Amount updated to FABLIN.BLLF is Positive (after reversed sign): Use information from DebtorParty. If not available, use information from CreditorParty.
- If Amount updated to FABLIN.BLLF is Negative (after reversed sign): Use information from CreditorParty. If not available, use information from DebtorParty.
- b) If ABS900MI.GetBankIdent.BSTY= 3:
- Use information from DebtorParty.

BankStatement/BankStatementAccount/AccountEntry/EntryDetail/EntryTransaction/UserArea

FABLIX.V4BLFX FABDET.V3BLBC FABDET.V3BLTX.-; ABS100MI/AddStatmtAdditi AddStatmtDetail

AddStatmtDetail

The field indicates the message specific information that will be stored depending on type of information.

The following Property/NameValue is currently retrieved:
1) name="AdditionalTransactionInformation" or
"Icl.AdditionalTransactionInformation": Part of "Additional information Free text" (BLFX) with heading "AddTransInfo".

Exception if BankStatementHeader/Description = "MT940": -name="Icl.BusinessCode" update "Business transaction code" (BLBC)

-name="lcl.TransactionType" update "Transaction text" (BLTX) -Information (lcl.AdditionalTransactionInformation) not included.

Comment about lines with name="lcl.ProprietaryAmount" and type="DBIT":

- The information indicates that the transaction refers to a special scenario to handle Swedish BgMax Credit note records sent via CAMT053 or CAMT054 formats. The amount (always sent as a negative Transaction amount) from this type of transaction is added/deducted from the Total amount - Debit and Credit that is received in the file or calculated if missing.

BillOfMaterials/BillOfMaterialsHeader/DocumentID/ID

For ProcessBillOfMaterials:

MPDHED.PHPRTX; PDS001MI/Add, Update

For SyncBillOfMaterials: 1) MPDHED.PHPRTX; PDS001MI/Add, Update 2) MPDHED PHPRNO; PDS001MI/Add, Update MPDOUT.OTPRNO;

PDS029MI/AddOutput, UpdOutput, DltOutput

3) MPDMFD MDMFPC;

PDS023MI/AddAltStructure. UpdAltStructure.; /

@accountingEntity

For ProcessBillOfMaterials: MPDHED.PHCONO CMNDIV.CCDIVI.; /

@variationID

BillOfMaterials/BillOfMaterialsHeader/DocumentID/RevisionID

For ProcessBillOfMaterials:

MPDVER.VRVRSN; PDS028MI/AddVersion, UpdVersion, DltVersion,

PDS002MI/AddComponent, UpdateComponent, Delete /

For SyncBillOfMaterials: MPDVER.VRVRSN;

PDS028MI/AddVersion, UpdVersion, DltVersion, CpyVersion

PDS002MI/AddComponent, UpdateComponent, Delete

MPDHED.PHVRSN;

PDS001MI/CpyProdVersion.; /

For ProcessBillOfMaterials:

The field indicates the product text.

For SyncBillOfMaterials:

1) The field indicates the product text.

If BillOfMaterialType = blank or Discrete, populate PRTX.

2) The field indicates the product.

If BillOfMaterialType != blank or Discrete, populate PDS001MI PRNO.

If BillOfMaterialType = Formula, populate PDS029MI PRNO.

If OutputItem/Type is Alternate Structure, this is used as PRNO input of PDS001MI and PDS002MI transactions.

3) The field indicates the alternate structure.

If actionCode='Delete', BillOfMaterialType != blank or Discrete and

RevisionID blank, delete PDS001 record.

For ProcessBillOfMaterials:

The field indicates the company and division, displayed as

CONO DIVI.

For SyncBillOfMaterials:

The field indicates the sequence number. Sequence number is an

internal number to ensure documents are processed in correct order.

For ProcessBillOfMaterials:

The field indicates a particular form of a product structure record and

reflects any changes to that information.

If actionCode='Delete' and RevisionID != blank or 0, delete the

versionID specified.

For SyncBillOfMaterials:

The field indicates a particular form of a product structure record and

reflects any changes to that information.

If actionCode='Delete' and RevisionID != blank or 0, delete the

versionID specified. Otherwise, delete PDS001 record.

BillOfMaterials/BillOfMaterialsHeader/AlternateDocumentID/RevisionID

For SyncBillOfMaterials: MPDVER.VRVRSN; PDS028MI/CpyVersion

MPDHED.PHVRSN;

PDS001MI/CpyProdVersion.; /

For SyncBillOfMaterials:

The field indicates the copy from version.

BillOfMaterials/BillOfMaterialsHeader/Description

MPDVER.VRTX40; PDS028MI/AddVersion, UpdVersion

BillOfMaterials/BillOfMaterialsHeader/Note For SyncBillOfMaterials:

MPDHED.PHPRTX; PDS001MI/Add, Update

The field indicates the description for the product version description.

For SyncBillOfMaterials:

The field indicates the product text.

If BillOfMaterialType = blank or Discrete, populate PRTX

BillOfMaterials/BillOfMaterialsHeader/Status/Code

For ProcessBillOfMaterials: MPDHED.PHSTAT ; PDS001MI/Add, Update

For SyncBillOfMaterials:

MPDHED.PHSTAT; PDS001MI/Add, Update, CpyProdVersion/

The field indicates the status of the record.

If Pending or Hold, set to 10.

If Closed or Deleted, set to 90.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/ItemID/ID

For ProcessBillOfMaterials: MPDHED.PHPRNO; PDS001MI/Add, Update

MPDMAT.PMMTNO;

PDS002MI/AddComponent, UpdateComponent, Delete

MSUBTF.HPPRNO;

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMPRNO;

PDS360MI/AddSubstitOpt, DltSubstitOpt.;

For SyncBillOfMaterials:

1) MPDHED.PHPRNO;

PDS001MI/Add, Update, Delete, Copy, CpyProdVersion

If Open, set to 20.

For ProcessBillOfMaterials:

The field indicates the product number. The field may also indicate a

component depending on the OutputItem/Type.

If OutputItem/Type = Co-Product or By-Product, populate PDS002MI

MTPL.

For SyncBillOfMaterials:

1) The field indicates the product number.

If BillOfMaterial/Type = blank or Discrete, populate PDS001MI PRNO.

2) The field indicates the material, by-product or co-product

depending on the OutputItem/Type.

If OutputItem/Type = Co-Product or By-Product, populate PDS002MI

3) The field indicates the output item.

MPDMAT.PMPRNO:

PDS002MI/AddComponent, UpdateComponent, Delete

MPDOPE.POPRNO;

PDS002MI/AddOperation, UpdateOperation, Delete

MPDVER.VRPRNO;

PDS028MI/AddVersion, UpdVersion, DltVersion, CpyVersion

2) MPDMAT.PMMTNO;

PDS002MI/AddComponent, UpdateComponent, Delete

MPDOUT.OTOTNO

PDS029MI/AddOutput, UpdOutput, DltOutput

MPDMAA.PAPRNO;

PDS013MI.AddAltMat, UpdAltMat, DltAltMat

3) MPDMFD.MDOTNO;

PDS023MI/AddAltStructure. UpdAltStructure.;

If BillOfMaterial/Type = Formula, populate PDS029MI OTNO. If OutputItem/Type = Alternate Structure, populate PDS023MI OTNO.

If actionCode='Delete', BillOfMaterialType = blank or Discrete and RevisionID blank, delete PDS001 record.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Classification/Codes/Code

For ProcessBillOfMaterials:

1) MPDHED.PHUPCO;

PDS001MI.Add, Update

2) MPDHED.PHPSET;

PDS001MI.Add, Update

3) MPDHED.PHFSCD:

PDS001MI.Add, Update 4) MPDHED.PHSRCD;

PDS001MI.Add, Update

5) MPDHED.PHSCCD;

PDS001MI.Add, Update.; /

For SyncBillOfMaterials:

1) MPDHED.PHUPCO;

PDS001MI.Add, Update

2) MPDHED.PHPSET;

PDS001MI.Add, Update

3) MPDHED.PHFSCD;

PDS001MI.Add, Update

4) MPDHED.PHSRCD;

PDS001MI.Add, Update

5) MPDHED.PHSCCD; PDS001MI.Add, Update

6) MPDHED PHMNPL;

PDS001MI.Add

7) MPDMAT.PMMSEQ;

PDS002MI.AddComponent, UpdateComponent, Delete

8) MPDOPE.POOPNO

AddOperation, UpdateOperation, Delete

9) MPDOPE.POPLGR

AddOperation, UpdateOperation, Delete

For ProcessBillOfMaterials:

1) Cost summation

The field indicates the full cost summation; whether the cost price from each detail line should be totaled to kit line, included quantities

If attribute listID is 'Cost Summation', populate UPCO.

If "true" set to 1

If "false" set to 0.

2) Pricing method

The field indicates how the sales price for the kit item and the detail lines are calculated.

If attribute listID is 'Pricing Method', populate PSET.

If Not used, set to 0.

If Cost price, set to 1.

If Price hierarchy, set to 2.

If Line value, set to 3.

3) Kit control

The field indicates how a product can be used as a kit in a customer order and purchase order.

If attribute listID is 'Kit Control', populate FSCD.

If Not used, set to 0.

If Fixed structure, set to 1.

If Variable structure, set to 2.

If Attribute-controlled, set to 3.

4) Reservation level

The field indicates how the inventory reservation should be performed.

If attribute listID is 'Reservation Level', populate FSCD.

If Not used, set to 0.

If Kit level, set to 1.

If Material level, set to 2.

5) Statistics level

The field indicates the level on which sales statistics and sales account entries are updated. This field determines if bonus/ commission is generated on a kit-item level or component level.

If attribute listID is 'Statistics Level', populate SCCD.

If Not used, set to 0.

If Kit items, set to 1.

If Included items, set to 2.

For SyncBillOfMaterials:

1) Cost summation

The field indicates the full cost summation. Set to '1' if the cost price from each detail line should be totaled to kit line, included quantities considered.

If attribute listID is 'Cost Summation', populate UPCO.

2) Pricing method

The field indicates how the sales price for the kit item and the detail lines are calculated.

If attribute listID is 'Pricing Method', populate PSET.

If Not used, set to 0.

If Cost price, set to 1.

If Price hierarchy, set to 2.

If Line value, set to 3.

3) Kit control

The field indicates how a product can be used as a kit in a customer order and purchase order.

If attribute listID is 'Kit Control', populate FSCD.

If Not used, set to 0.

If Fixed structure, set to 1.

If Variable structure, set to 2.

If Attribute-controlled, set to 3.

4) Reservation level

The field indicates how the inventory reservation should be performed. If attribute listID is 'Kit Control', populate FSCD.

If Not used, set to 0.

If Kit level, set to 1.

If Material level, set to 2.

5) Statistics level

The field indicates the level on which sales statistics and sales account entries are updated. This field determines if bonus/ commission is generated on a kit-item level or component level. If attribute listID is 'Statistics Level', populate SCCD.

If Not used, set to 0.

If Kit items, set to 1.

If Included items, set to 2.

6) Maintained by external system

The field indicates whether the product structure has been created through an interface, typically with a product lifecycle management system. This flag is not changeable after creation.

If attribute listID is 'Maintained by External System', populate MNPL. If true, set MNPL to 1.

If false, set MNPL to 0.

If not given, check partner translation in CRS881/882. If partner is translated as 'PLMforProcessHandling', set MNPL to 1. If none of these are present, set MNPL to 0 by default.

These elements are only applicable if OutputItem/Type = blank or Product.

7) Sequence number

The fields indicates M3 Sequence number.

If attribute listID is 'ERP Line Reference', populate MSEQ.

This is applicable if OutputItem/Type = By-product or Co-product.

8) Operation number

The field indicates the operation number.

If attribute listID is 'Operation Number', populate OPNO.

9) Work center

The field indicates the work center.

If attribute listID is 'Work Center', populate PLGR.

For ProcessBillOfMaterials:

The field indicates the classification code list ID.

- 1) If 'Cost Summation', populate UPCO.
- 2) If 'Pricing Method', populate PSET.
- 3) If 'Kit Control', populate FSCD.
- 4) If 'Reservation Level', populate FSCD.
- 5) If 'Statistics Level', populate SCCD.

For SyncBillOfMaterials:

The field indicates the classification code list ID.

- 1) If 'Cost Summation', populate UPCO.
- 2) If 'Pricing Method', populate PSET.
- 3) If 'Kit Control', populate FSCD.
- 4) If 'Kit Control', populate FSCD.
- 5) If 'Statistics Level', populate SCCD.
- 6) If 'Maintained by External System', populate MNPL.
- 7) If 'ERP Line Reference', populate MSEQ.

This is applicable if OutputItem/Type = By-product or Co-product

- 8) If 'Operation Number', populate OPNO.
- 9) If 'Work Center', populate PLGR

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Type

MITMAS.MMBYPR; /

@listID

The field indicates the product type.

Used to indicate if the OutputItem is Product, Co-Product or By-Product.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/EffectiveTimePeriod/StartDateTime

For SyncBillOfMaterials:

MPDMAT.PMFDAT; PDS002MI/AddComponent

For SyncBillOfMaterials:

The field indicates the start date

BillOfMaterials/BillOfMaterialsHeader/OutputItem/EffectiveTimePeriod/EndDateTime

For SyncBillOfMaterials:

MPDMAT.PMTDAT; PDS002MI/AddComponent, UpdComponent

The field indicates the end date.

 ${\it Bill Of Materials/Bill Of Materials Header/Output I tem/Line Number}$

For ProcessBillOfMaterials:

 $MPDMAT.PMMSEQ;\ PDS002MI/AddComponent,\ UpdateComponent,$

Delete

For SyncBillOfMaterials: 1) MPDMAT.PMMSEQ;

PDS002MI/AddComponent, UpdateComponent, Delete

2) MPDMAT.PMELRF;

PDS002MI/AddComponent, UpdateComponent.; PDS002MI/

AddComponent, UpdateComponent, Delete

BillOfMaterials/BillOfMaterialsHeader/OutputItem/YieldPercent

For ProcessBillOfMaterials:

MPDHED

.PHEXPC; PDS001MI/Add, Update

For SyncBillOfMaterials: MPDHED.PHEXPC; PDS001MI.Add, Update MPDVER.VREXPC;

PDS028MI.AddVersion, UpdVersion .; /

For ProcessBillOfMaterials:

for Add and Update transactions.

For ProcessBillOfMaterials:

For SyncBillOfMaterials:

The field indicates the sequence number.

1) The field indicates the sequence number.

2) The field indicates the external line reference.

The field indicates the yield percentage. It indicates the product's theoretical yield, expressed as a percentage to two decimal places.

This is applicable if OutputItem/Type is By-product or Co-product and

For SyncBillOfMaterials:

The field indicates the yield percentage. It indicates the product's theoretical yield, expressed as a percentage to two decimal places.

If VRNF = 0, use PSDS001MI. If VRNF = 1, use PDS028MI.

If both BAQT and EXPC are given, use BAQT and clear EXPC value.

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Yield

MPDHED.PHBAQT; PDS001MI.Add, Update MPDVER.VRBAQT;

PDS028MI.AddVersion, UpdVersion .; /

For ProcessBillOfMaterials:

The field indicates the yield quantity. It indicates the net outcome of the production process for each production batch.

If blank or 0, set to 1.

Number of decimal places is truncated based on MMS200MI.GetltmBasic DCCD.

For SyncBillOfMaterials:

The field indicates the yield quantity. It indicates the net outcome of the production process for each production batch.

If blank, set to 1.

If VRNF = 0, use PSDS001MI. If VRNF = 1, use PDS028MI.

If both BAQT and EXPC are given, use BAQT and clear EXPC value.

The field indicates the unit of measure.

@unitCode

MPDHED.PHUNMS; PDS001MI/Add, Update

BillOfMaterials/BillOfMaterialsHeader/OutputItem/Quantity

For ProcessBillOfMaterials: 1) MPDHED.PHEOQT; PDS001MI/Add, Update 2) MPDMAT.PMCNQT;

PDS002MI/AddComponent, UpdateComponent.; /

For SyncBillOfMaterials:
1) MPDHED.PHEOQT;
PDS001MI/Add, Update
2) MPDMAT.PMCNQT;
PDS002MI/AddCompage

PDS002MI/AddComponent, UpdateComponent

3) MPDOUT.OTOTQT;

PDS029MI/AddOutput, UpdOutput

.; /

For ProcessBillOfMaterials:

1) The field indicates the Economic Order Quantity (EOQ). It is a type of fixed order-quantity that determines the amount of an item to be purchased or manufactured at one time. If OutputItem/Type = blank or Product, populate PDS001MI EOQT.

2) The field indicates the quantity of each component used in the bill of material/structure of a product. If OutputItem/Type = Co-product or By-product, populate PDS002MI CNQT.

For SyncBillOfMaterials:

1) The field indicates the Economic Order Quantity (EOQ). It is a type of fixed order-quantity that determines the amount of an item to be purchased or manufactured at one time. If OutputItem/Type = blank or Product, populate PDS001MI EOQT.

2) The field indicates the quantity of each component used in the bill of material/structure of a product. If OutputItem/Type = Co-product or By-product, populate PDS002MI CNQT.

3) The field indicates the quantities of output generated by a manufacturing process. If BillOfMaterial/Type = FORMULA and OutputItem/Type != blank or Product, populate PDS029MI OTQT. If

blank, use the value from OutputItem/Yield. Number of decimal places is truncated based on MMS200MI.GetItmBasic DCCD. BillOfMaterials/BillOfMaterialsHeader/OutputItem/UserArea For SyncBillOfMaterials: For SyncBillOfMaterials: MPDOUT.OTVRSN; PDS029MI/AddOutput, UpdOutput, DltOutput The field indicates a particular form of a product structure record and reflects any changes to that information. If @name='Version', populate VRSN BillOfMaterials/BillOfMaterialsHeader/BillOfMaterialType For SyncBillOfMaterials: MPDPSC For SyncBillOfMaterials: The field indicates the product structure class type. .PCPCLT; PDS075MI/GetStructClass If 00, process as Discrete. If 11, process as Formula If 12, process as Routing If 13, process as Bulk Item If 14, process as Packaging Material If 15, process as Packaged Item Use input from PDS001MI/Add PSCL BillOfMaterials/BillOfMaterialsHeader/UsageDescription For ProcessBillOfMaterials: The field indicates the product structure type. MPDHED.PHSTRT; PDS001MI/Add, Update MPDMAT.PMSTRT: PDS002MI/AddComponent, UpdateComponent, Delete MPDOPF POSTRT: PDS002MI/AddOperation, UpdateOperation, Delete MPDVER.VRSTRT: PDS028MI/AddVersion, UpdVersion, DltVersion MSUBTF.HPPRNO; PDS360MI/AddSubstitFeat, DltSubstitFeat MSUBTO.HMPRNO; PDS360MI/AddSubstitOpt, DltSubstitOpt.PHSTRT For SyncBillOfMaterials: MPDHED.PHSTRT; PDS001MI/Add, Update, Delete, Copy, CpyProdVersion MPDMAT.PMSTRT; PDS002MI/AddComponent, UpdateComponent, Delete MPDOPE.POSTRT; PDS002MI/AddOperation, UpdateOperation, Delete MPDVER.VRSTRT; PDS028MI/AddVersion, UpdVersion, DItVersion, CpyVersion MPDOUT.OTSTRT; PDS029MI/AddOutput, UpdOutput, DltOutput MPDMAA.PAFDAT; PDS013MI.AddAltMat, UpdAltMat, DltAltMat MPDMFD.MDSTRT; PDS023MI/AddAltStructure. UpdAltStructure.; BillOfMaterials/BillOfMaterialsHeader/EffectiveTimePeriod/StartDateTime For ProcessBillOfMaterials: The field indicates the start date for the system period. MPDVER.VRFDAT; PDS0028MI/AddVersion. UpdVersion MSUBTE HPFDAT: PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO HMFDAT:

PDS360MI/AddSubstitOpt, DltSubstitOpt.; /

For SyncBillOfMaterials: MPDVER.VRFDAT;

PDS028MI/AddVersion, CpyVersion

PDS001MI/CpyProdVersion

MPDMFD.MDFDAT;

PDS023MI/AddAltStructure. UpdAltStructure.; /

BillOfMaterials/BillOfMaterialsHeader/EffectiveTimePeriod/EndDateTime

For ProcessBillOfMaterials:

MPDVER.VRTDAT; PDS028MI/AddVersion, UpdVersion

For SyncBillOfMaterials: MPDVER.VRTDAT;

PDS028MI/AddVersion, UpdVersion, CpyVersion

PDS001MI/CpyProdVersion MPDMFD.MDTDAT;

PDS023MI/AddAltStructure. UpdAltStructure.; /

BillOfMaterials/BillOfMaterialsHeader/Location/ID

For ProcessBillOfMaterials: MPDHED.PHFACI; PDS001MI/Add, Update

MPDMAT.PMFACI;

PDS002MI/AddComponent, UpdateComponent, Delete

MPDOPE.POFACI:

PDS002MI/AddOperation, UpdateOperation, Delete

MPDVER.VRFACI:

PDS028MI/AddVersion, UpdVersion, DltVersion

MSUBTE HPFACI:

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMFACI;

PDS360MI/AddSubstitOpt, DltSubstitOpt.; /

For SyncBillOfMaterials:

MPDHED.PHFACI;

PDS001MI/Add, Update, Delete, Copy, CpyProdVersion

MPDMAT.PMFACI;

PDS002MI/AddComponent, UpdateComponent, Delete

MPDOPE.POFACI;

PDS002MI/AddOperation, UpdateOperation, Delete

MPDVER.VRFACI;

PDS028MI/AddVersion, UpdVersion, DltVersion, CpyVersion

MPDOUT.OTFACI;

PDS029MI/AddOutput, UpdOutput, DItOutput

MPDMAA.PAFDAT;

PDS013MI/AddAltMat, UpdAltMat, DItAltMat

MPDMFD.MDFACI;

PDS023MI/AddAltStructure. UpdAltStructure.; /

BillOfMaterials/BillOfMaterialsHeader/DrawingAttachment/FileName

MPDHED.PHDWNO

; PDS001MI/Add, Update

BillOfMaterials/BillOfMaterialsHeader/UserArea

For ProcessBillOfMaterials: 1) MPDHED.PHPCBO;

PDS001MI/Add, Update

2) MPDHED.PHVRNF;

PDS001MI/Add

.; /

For SyncBillOfMaterials:

1) MPDHED.PHPCBO:

PDS001MI/Add, Update

2) MPDHED.PHVRNF;

PDS001MI/Add

3) MPDHED.PHFACI;

PDS001MI/Copy, CpyProdVersion

4) MPDHED.PHPRNO:

PDS001MI/Copy, CpyProdVersion

5) MPDHED.PHSTRT:

PDS001MI/Copy, CpyProdVersion

6) PDS001MI/Copy, CpyProdVersion.; /

The field indicates the date when the system period ends.

The field indicates the facility.

The field indicates a unique ID for the drawing used in designing the

For ProcessBillOfMaterials:

1) Percentage BoM

The field indicates whether the BoM is based on percentages or quantity.

If @name='PercentageBoM', populate PCBO.

If "true" set to 1. If "false" set to 0.

2) Version Managed

The field indicates if the product structure is managed by version. Versions may be applied to product structures that represent manufacturing processes

If @name='VersionManaged', populate VRNF.

If "true" set to 1.
If "false" set to 0.

Call PDS028MI only if VRNF = 1.

For SyncBillOfMaterials:

1) Percentage BoM

The field indicates whether the BoM is based on percentages or quantity. Set to 1 to enable Percentage BoM.

If @name='PercentageBoM', populate PCBO.

2) Version Managed

The field indicates if the product structure is managed by version. Versions may be applied to product structures that represent manufacturing processes. If "true" set to 1, if "false" set to 0. If @name='VersionManaged', populate VRNF.

Call PDS028MI only if VRNF = 1.

3) Facility

The field indicates the copy from Facility. If @name='CopyFromFacility', populate FACI.

4) Product number

The field indicates the copy from Product number. If @name='CopyFromProduct', populate PRNO.

5) Structure type

The field indicates the copy from Structure type. If @name='CopyFromStructureType', populate STRT.

6) Copy operation

For ProcessBillOfMaterials:

external line reference (ELRF).

'IgnoreOperation' will be applied.

ELRF as input. Otherwise, use MSEQ.

For SyncBillOfMaterials:

The field indicates if the operations should be copied.

The field indicates the sequence number for material.

If @name='CopyOperation', populate CPOP. If NameValue='true', set CPOP to 1.

If NameValue='false', set CPOP to 0. If not given, retrieve value from control property m3beCopyOperation. Control property value can either be 'true' or 'false'. Default value is set to 'true'

The field indicates the sequence number for material (MSEQ) or the

If partner is translated to 'LineNumberHandling' in CRS881/882, use

If partner is translated to 'PLMforProcessHandling', logic for

'LineNumberHandling', 'GenerateMaterialSequence' and

BillOfMaterials/BillOfMaterialsLine/LineNumber

For ProcessBillOfMaterials: MPDMAT.PMMSEQ;

PDS002MI/AddComponent, UpdateComponent, Delete

MSUBTF.HPMSEQ;

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMMSEQ;

PDS360MI/AddSubstitOpt, DItSubstitOpt.; /

For SyncBillOfMaterials: MPDMAT.PMMSEQ;

PDS002MI.AddComponent, UpdateComponent, Delete

or

MPDMAT.PMELRF:

PDS002MI.AddComponent, UpdateComponent.; /

BillOfMaterials/BillOfMaterialsLine/Note

For SyncBillOfMaterials: CSYTXL.TLTX60; CRS980MI/AddTxtBlockLine

@languageID

For SyncBillOfMaterials:

CSYTXL.TLLNCD; CRS980MI/RtvNewTextID, AddTxtBlockHead, AddTxtBlockLine, DltTxtBlockLins

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/ItemID/ID

For SyncBillOfMaterials: The field indicates the note.

This is only applicable for operations.

Information from this element will only be consumed by M3 if

BillOfMaterialsLine/OperationReference/DocumentID/ID is not empty.

For SyncBillOfMaterials:

The field indicates the note language.

This is only applicable for operations. Information from this element will only be consumed by M3 if

BillOfMaterialsLine/OperationReference/DocumentID/ID is not empty.

The field indicates a component number, which is identical to a

subordinated item number. It is used to enter items that are included during preparation of product structures and orders.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Classification/Codes

MPDMAT.PMMTNO; PDS002MI/AddComponent, UpdateComponent

For ProcessBillOfMaterials:

MPDMAT.PMEXMA; PDS002MI/AddComponent, UpdateComponent

For ProcessBillOfMaterials:

The field indicates whether the material record should be included in

eventual yield calculations.

If 'Yield Component', populate EXMA.

If "true" set to 1. If "false" set to 0.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Classification/Codes/Code

For SyncBillOfMaterials: MPDMAT.PMEXMA; PDS002MI/AddComponent, UpdateComponent

For SyncBillOfMaterials:

If set to 1, material record should be included in eventual yield

calculations.

@listID If 'Yield Component', populate EXMA

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/LineNumber

For ProcessBillOfMaterials:

MPDMAT.PMMSEQ;

PDS002MI/AddComponent, UpdateComponent, Delete

MSUBTF.HPMSEQ;

PDS360MI/AddSubstitFeat, DltSubstitFeat

For ProcessBillOfMaterials:

The field indicates the sequence number for material.

For SyncBillOfMaterials:

The field indicates the sequence number for material.

BillOfMaterials

MSUBTO.HMMSEQ:

PDS360MI/AddSubstiOpt, DltSubstitOpt.; /

For SyncBillOfMaterials: MPDMAT.PMMSEQ;

PDS002MI.AddComponent, UpdateComponent, Delete

MPDMAA.PAFDAT;

PDS013MI.AddAltMat, UpdAltMat, DltAltMat.; /

If partner is translated to 'LineNumberHandling' or

'GenerateMaterialSequence' in CRS881/882, retrieve the value from control property m3beSequenceNumberInterval. For the succeeding

lines, increment based on the value.

If partner is translated to 'PLMforProcessHandling', logic for 'LineNumberHandling', 'GenerateMaterialSequence' and

'IgnoreOperation' will be applied.

If the elements is blank, retrieve value from BillOfMaterials/LineNumber.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/Quantity

MPDMAT.PMCNQT; PDS002MI/AddComponent, UpdateComponent

For ProcessBillOfMaterials:

The field indicates the quantity of each component used in the

bill of material/structure of a product.

For SyncBillOfMaterials:

The field indicates the quantity of each component used in the

bill of material/structure of a product.

Number of decimal places is truncated based on

MMS200MI.GetItmBasic DCCD.

@unitCode

MPDMAT.PMPEUN; PDS002MI/AddComponent, UpdateComponent

The field indicates the unit of measure that is used for an item

quantity in a bill of material.

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/FixedQuantityIndicator

MPDMAT.PMFXCD; PDS002MI/AddComponent, UpdateComponent

For ProcessBillOfMaterials:

The field indicates the relation between the product's ordered quantity

and the material's reserved quantity.

If 'true' set to 1 (Fixed). If 'false' set to 0 (Normal).

For SyncBillOfMaterials:

The field indicates the relation between the product's ordered quantity

The field indicates the start date for the system period.

and the material's reserved quantity.

If true, set to 1 (Fixed). If false, set to 0 (Normal).

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/EffectiveTimePeriod/StartDateTime

For ProcessBillOfMaterials:

MPDMAT.PMFDAT;

PDS002MI/AddComponent, UpdateComponent, Delete

MSUBTF.HPFDAT;

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMFDAT;

PDS360MI/AddSubstitOpt, DltSubstitOpt

.; /

For SyncBillOfMaterials: MPDMAT.PMFDAT;

PDS002MI.AddComponent, UpdateComponent, Delete

MPDMAA.PAFDAT;

PDS013MI.AddAltMat, UpdAltMat, DltAltMat

.: /

BillOfMaterials/BillOfMaterialsLine/ConsumedItem/EffectiveTimePeriod/EndDateTime

MPDMAT.PMTDAT; PDS002MI/AddComponent, UpdateComponent The

The field indicates the date when the system period ends.

BillOfMaterials/BillOfMaterialsLine/Substitutions

@Priority

@Type

For SyncBillOfMaterials:

MPDMAA.PAPREX; PDS013MI/AddAltMat, UpdAltMat

For SyncBillOfMaterials:

The field indicates the priority of alternate material.

For ProcessBillOfMaterials:

MSUBTF.HPXSBT; PDS360MI/AddSubstitFeat

For ProcessBillOfMaterials:

The field indicates how substitutions between features and options for

products and components are made. If 'One-to-one', set XSBT to 1.

If 'One-to-many', set XSBT to 2. If 'No substitution', set XSBT to 4.

If not given, retrieve from agreement control property m3beSubstitutionType. Set default value to 2.

Applicable only for Add transaction.

BillOfMaterials/BillOfMaterialsLine/Substitutions/Components/ItemID/ID

For SyncBillOfMaterials:

MPDMAA.PAMTAL; PDS013MI/AddAltMat, UpdAltMat, DltAltMat

For SyncBillOfMaterials:

The field indicates the alternate material.

BillOfMaterials/BillOfMaterialsLine/Substitutions/Components/Quantity

BillOfMaterials

For SyncBillOfMaterials: MPDMAA.PACNQT; PDS013MI/AddAltMat, UpdAltMat

@unitCode

For SyncBillOfMaterials: MPDMAA.PAPEUN; PDS013MI/AddAltMat, UpdAltMat For SyncBillOfMaterials: The field indicates the quantity.

For SyncBillOfMaterials:

For ProcessBillOfMaterials:

The field indicates the unit of measure.

BillOfMaterials/BillOfMaterialsLine/Substitutions/UserArea

For ProcessBillOfMaterials: 1) MSUBTF.HPPFTI:

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMPFTI;

PDS360MI/AddSubstiOpt, DltSubstitOpt

2) MSUBTF.HPMFTI;

PDS360MI/AddSubstitFeat, DltSubstitFeat

MSUBTO.HMMFTI;

PDS360MI/AddSubstiOpt, DltSubstitOpt

3) MSUBTO.HMPOPT;

PDS360MI/AddSubstiOpt, DltSubstitOpt

4) MSUBTO.HMMOPT;

PDS360MI/AddSubstiOpt, DltSubstitOpt.; /

4) The field indicates the component option. Populate MOPT if attribute name is 'ComponentOption'. Use attribute sequence to pair the POPT and MOPT.

Populate PFTI if attribute name is 'ProductFeature'.

Populate POPT if attribute name is 'ProductOption'. Use attribute sequence to pair the POPT and MOPT.

Populate MFTI if attribute name is 'ComponentFeature'.

2) The field indicates the component feature.

3) The field indicates the product option.

1) The field indicates the product feature. If not given, call MMS017MI

List and retrieve Feature (FTID) with Feature group (FGRP) = Y.

BillOfMaterials/BillOfMaterialsLine/DrawingPosition

MPDMAT.PMDWPO

; PDS002MI/AddComponent, UpdateComponent

The field indicates the drawing position.

BillOfMaterials/BillOfMaterialsLine/OperationReference/DocumentID/ID For ProcessBillOfMaterials:

For ProcessBillOfMaterials:

MPDOPE.POOPNO; PDS002MI/AddOperation, UpdateOperation

The field indicates an operation number.

For SyncBillOfMaterials: For SyncBillOfMaterials:

MPDOPE.POOPNO; PDS002MI/AddOperation, UpdateOperation, DeleteThe field indicates an operation number.

If partner is translated to 'IgnoreOperation' in CRS881/882, add. update and delete of operations will not be handled in the mapping.

If partner is translated to 'PLMforProcessHandling', logic for 'LineNumberHandling', 'GenerateMaterialSequence' and 'IgnoreOperation' will be applied.

BillOfMaterials/BillOfMaterialsLine/OperationReference/Description

For ProcessBillOfMaterials:

MPDOPE.POOPDS; PDS002MI/AddOperation, UpdateOperation

For ProcessBillOfMaterials:

The field indicates a short description of the operation to be carried

out

BillOfMaterials/BillOfMaterialsLine/OperationReference/WorkCenterID

For ProcessBillOfMaterials:

MPDOPE.POPLGR; PDS002MI/AddOperation, UpdateOperation

For SyncBillOfMaterials:

MPDOPE.POPLGR; PDS002MI/AddOperation, UpdateOperation

For ProcessBillOfMaterials:

The field indicates a work center, which is a resource in which labor

operations are performed.

For SyncBillOfMaterials:

The field indicates a work center, which is a resource in which labor

operations are performed.

If partner is translated to "IgnoreOperation" in CRS881/882, add, update and delete of operations will not be handled in the mapping.

If partner is translated to "PLMforProcessHandling", logic for "LineNumberHandling", "GenerateMaterialSequence" and "IgnoreOperation" will be applied

BillOfMaterials/BillOfMaterialsLine/OperationReference/UserArea

For ProcessBillOfMaterials:

1) MPDOPE.POPITI;

PDS002MI/AddOperation, UpdateOperation

2) MPDOPE.POSETI;

PDS002MI/AddOperation, UpdateOperation.; /

For ProcessBillOfMaterials:

1) Run time

The field indicates the time it takes, per unit or batch, to perform a

certain operation.

If @name='RunTime', populate PITI.

2) Setup time

The field indicates the time it normally takes for changes or

preparations for a particular operation. If @name='SetupTime', populate SETI

BillOfMaterials/BillOfMaterialsLine/UserArea

For ProcessBillOfMaterials:

MPDMAT.PMSDCD; PDS002MI/AddComponent, UpdateComponent

For SyncBillOfMaterials: 1) MPDVER.VRVRSN:

PDS002MI/AddComponent, UpdateComponent, AddOperation, UpdateOperation, Delete

For ProcessBillOfMaterials:

The field indicates if the material and/or operation are used in standard. The code controls whether materials and operations should be considered in estimate, requirements calculation and lead time calculation of the product.

If @name='UsedInStandard', populate SDCD.

If NameValue=true, set SDCD to 1.

If NameValue=false, set SDCD to 0.

BillOfMaterials

2) MPDMAT.PMSDCD PDS002MI/AddComponent, UpdateComponent, MPDOPE.POSDCD; PDS002MI/AddOperation, UpdateOperation .; /

In case value is not given, SDCD is retrieved from agreement control property m3beUsedInStandard.

For SyncBillOfMaterials:

1) Version

The field indicates the version.

If @name='Version', populate VRSN.

2) Used in standard

The field indicates if the material and/or operation are used in standard. The code controls whether materials and operations should be considered in estimate, requirements calculation and lead time calculation of the product.

If @name='UsedInStandard', populate SDCD.
If NameValue=true, set SDCD to 1.

If NameValue=false, set SDCD to 0.

In case value is not given, SDCD is retrieved from agreement control property m3beUsedInStandard.

BillToPartyMaster

DiliTOPartywaster	
BillToPartyMaster/PartyIDs/ID OCUSMA.OKCUNO, OCUSAD.OPCUNO, OCUSAD.OPADID; CRS610MI/Add, CRS610MI/AddAddress	The field indicates the customer ID and invoice address number. It is a concatenation of a Customer ID (CUNO) <10> + Address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the ID except for the last one. ADID is trimmed if it is less than 6 characters. To create new customer include only customer ID in this element. You can also leave both this element and BillToPartyMaster/ CustomerParty/PartyIDs/ID element empty, then a new customer will be created with first 6 characters in uppercase of the Name element plus number series. To update existing customer include only customer ID in uppercase
@accountingEntity	(case sensitive). To create new invoice address for existing customer leave this field empty and put customer ID in BillToPartyMaster/CustomerParty/PartyIDs/ID element. To update existing invoice address for an existing customer put both customer ID and invoice address number in this element.
OCUSMA.OKCONO, OCUSMA.OKDIVI;	The field indicates the company and division.
	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760 AAA
BillToPartyMaster/Name OCUSMA.OKCUNM, OCUSAD.OPCUNM; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates customer name for a customer or for a customer invoice address.
BillToPartyMaster/Location/Coordinate/Latitude/DegreeMeasure OCUSAD.OPGEOY; CRS610MI/ AddAddress, CRS610MI/ChgAddress	The field indicates the latitude in the invoice address.
BillToPartyMaster/Location/Coordinate/Longitude/DegreeMeasure OCUSAD.OPGEOX; CRS610MI/ AddAddress, CRS610MI/ChgAddress	The field indicates the longitude in the invoice address.
BillToPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF, OCUSAD.OPYREF; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates the customer's contact person for a customer or for a customer invoice address.
BillToPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1, OCUSMA.OKCUA2, OCUSMA.OKCUA3, OCUSMA.OKCUA4, OCUSAD.OPCUA1, OCUSAD.OPCUA2, OCUSAD.OPCUA3, OCUSAD.OPCUA4 ; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates address lines for a customer or for a customer invoice address.
@sequence	The field indicates the sequence number. Sequence '1' will populate Address line 1. Sequence '2' will populate Address line 2. Sequence '3' will populate Address line 3. Sequence '4' will populate Address line 4.
BillToPartyMaster/Location/Address/CityName OCUSMA.OKTOWN, OCUSAD.OPTOWN; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates the city for a customer or for a customer invoice address.
BillToPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR, OCUSAD.OPECAR; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates state for a customer or for a customer invoice address.
BillToPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD; OCUSAD.OPCSCD; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates the country code for a customer or for a customer invoice address.
BillToPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO, OCUSAD.OPPONO; CRS610MI/Add, CRS610MI/ChgBasicData,	The field indicates the postal code for a customer or for a customer invoice address.

BillToPartyMaster

CRS610MI/AddAddress, CRS610MI/ChgAddress BillToPartyMaster/Location/Address/Preference/Indicator	
Bill or ally master/Location/Address/Freierence/malcator	The field indicates the preferred indicator for the address. Set to 'true'. Otherwise the address is ignored.
BillToPartyMaster/Location/Classification/Codes/Code OCUSAD.OPEALO OCUSAD.OPVRNO; CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates the EAN Code (EALO) if listID attribute is set to 'EAN'. The field indicates the VAT registration number (VRNO) if listID
@listID	attribute is set to 'VAT registrationnumber'. Set to 'EAN' to populate EAN Code (EALO) for the invoice address.
	Set to 'VAT registrationnumber' to populate Vat reg no (VRNO) for the invoice address.
BillToPartyMaster/Location/Status/EffectiveDateTime OCUSAD.OPFVDT; CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates 'Valid from' date for customer invoice address, in format YYYY-MM-DD.
BillToPartyMaster/Communication/ChannelCode	Set to 'Phone' to populate telephone number or fax. Set to 'EMail' to populate email address for the customer.
BillToPartyMaster/Communication/UseCode	The field indicates if the DialNumber is for a telephone or a fax. Used together with ChannelCode = 'Phone'.
	Set to 'Fax' if DialNumber is a facsimile transmission number. Set to 'Phone' if DialNumber is a telephone number.
BillToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO, OCUSMA.OKPHN2, OCUSMA.OKTFNO, OCUSAD.OPPHNO, OCUSAD.OPPHNO, OCUSAD.OPTFNO; CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress	The field indicates the telephone number or the fax. There could be two telephone numbers for a customer, but only one for an invoice address. Used together with ChannelCode = 'Phone'.
BillToPartyMaster/Communication/URI OCUSMA.OKMAIL; CRS610MI/Add, CRS610MI/ChgBasicData	The field indicates the email address for the customer. Used together with ChannelCode = 'EMail'.
BillToPartyMaster/Communication/Preference/Indicator	The field indicates the preferred telephone number. Used together with ChannelCode = 'Phone'.
	Set to 'true' to populate M3 field 'Telephone no 1' with corresponding DialNumber. If preferred indicator is not set, first DialNumber is saved as Telephone no 1 and second DialNumber as Telephone no 2.
BillToPartyMaster/PaymentTermID OCUSMA.OKTEPY; CRS610MI/ChgOrderInfo	The field indicates customer payment term ID.
BillToPartyMaster/UserArea	The field indicates the BODID from the sending application. Set attribute name to 'ProcessBODID'.
BillToPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/Add, CRS610MI/ChgBasicData	The field indicates customer status.
	If 'Pending', set status (STAT) to 10. If 'Open', set status (STAT) to 20. If 'Closed', set status (STAT)to 90.
BillToPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP; CRS610MI/Add, ChgBasicData 2) OCUSMA.OKTEDL; CRS610MI/ChgOrderInfo	Customer type The field indicates the type of customer. If attribute listID is 'Customer Types', populate CUTP.
3) OCUSMA.OKSDST; CRS610MI/ChgOrderInfo;	2) Delivery terms The field indicates the delivery terms. If attribute listID is 'Incoterms', populate TEDL.
	District The field indicates the district the customer or payer belongs to. If attribute listID is 'District', populate SDST.
@listID	Set to 'Customer Types' to populate Customer type (CUTP). Set to 'Incoterms' to populate Delivery terms (TEDL). Set to 'District' to populate District (SDST).
BillToPartyMaster/CustomerParty/PartyIDs/ID OCUSAD.OPCUNO; CRS610MI/AddAddress	The field indicates the unique identification of the customer, customer ID in uppercase (case sensitive). Used only when creating a new invoice address for an existing customer.

CarrierRoute

The field indicates the supplier's delivery note number.
Note that MHS850MI.AddTransNotify will only be called if the partner from LogicalID is gtn, nexus, or if the value is translated to TransportNotification in CRS881/882 of the company's blank division.
The field indicates the registration number for the trailer. If attribute schemeName='LicensePlateNumber', populate E0BH.
 The field indicates the transport identity of for instance the truck that will ship the goods. If attribute schemeName='TrailerID', 'VesselName', 'AirbillNumber', or 'TransportIdentity', populate E0B4.
1) If attribute schemeName='LicensePlateNumber', populate E0BH.
2) If attribute schemeName='TrailerID', 'VesselName', 'AirbillNumber', or 'TransportIdentity', populate E0B4.
The field indicates the actual ship date.
The field indicates when a transfer from a subsidiary company has arrived to the parent company.
The field indicates how the delivery is made.
The field indicates the delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
The field indicates the forwarding agent who is responsible for the shipment.
The field indicates the warehouse ID.
For a drop ship order (RouteStop/StopDetail/ShipToParty/Location/ID does not exist), the warehouse is retrieved from the first purchase order (CarrierRoute/DocumentReference/DocumentID/ID with @type='PurchaseOrder') in case of multiple POs by calling PPS200MI.GetHead.
The field indicates the unique identity of a supplier.
The field indicates the number of the delivery's bill of lading. If attribute name='BillOfLading', populate BOLN.

CodeDefinition/DocumentID/ID

For Business Sectors:

CSYTAB.CTSTKY; CRS036MI/Add, Upd

For Capabilities:

CCADEF.DECABI; CBS004MI/Add,Update

For Customs Statistics Number:

CSYCSN.CKCSNO; CRS128MI/AddBasicData, UpdBasicData

For Feature Options:

MPDFHE.PEFTID

; PDS055MI/Add, Update, Delete

For Item Free Field 1: CSYTAB.CTSTKY ; CRS181MI/Add, Upd

For Item Free Field 3:

CSYTAB.CTSTKY; CRS183MI/Add, Upd

For Item Free Field 4: CSYTAB.CTSTKY; /

For Item Free Field 5: CSYTAB.CTSTKY ; CRS185MI/Add, Upd

For Item Groups: CSYTAB.CTSTKY

; CRS025MI/AddItemGroup,

UpdItemGroup

For Product Groups:

CSYTAB.CTSTKY; CRS035MI/AddProductGroup,

UpdProductGroup

For Roles:

CRODEF.RDROLE CBS010MI.Add/Chg CCADEF.DECABI CBS004MI.Add/Chg.; /

For Seasons:

CSEAMA.HSEA1; CRS912MI/AddSeason, UpdSeason

For Stock Locations: MITPCE.MSWHLO MITPCE.MSWHSL.; /

For Unit Codes:

CSYTAB.CTSTKY; CRS050MI/Add, Update

For Business Sectors:

The field indicates the business area code.

For Capabilities:

The field indicates the Capability.

For Customs Statistics Number:

The field indicates the customs statistic number, which is used for regulating and calculating data for transactions to Intrastat.

For Feature Options:

The field indicates the feature.

For Item Free Field 1:

The field indicates item user-defined field 1.

Constant Value (STCO) = CFI1

If ListID = 'Item Free Field 1', use 'MITMAS' as input in the field Table (FILE)

For Item Free Field 3:

The field indicates the item user-defined field 3 code.

Constant value (STCO) = 'CFI3'

Use 'MITMAS' as input for FILE if ListID is 'Item Free Field 3'.

For Item Free Field 4:

The field indicates the item user-defined field 4.

Constant Value (STCO) = CFI4.

If ListID is set to Item Free Field 4', populate 'MITMAS' as input to FII F

For Item Free Field 5:

The field indicates item user-defined field 5.

Constant Value (STCO) = CFI5

If ListID = 'Item Free Field 5', use 'MITMAS' as input in the field Table (FILE)

For Item Groups:

The field indicates the item group whose items should be included in the forecast adjustment.

For Product Groups:

The field indicates the product groups whose items should be included in the forecast adjustment.

For Roles

The field indicates the Role and Capability value.

Value of agreement control property m3beCapabilityType is used as the Capability type (CATY) which must exist in CBS005. The default value is C01.

For Seasons:

The field indicates the season.

For Stock Locations:

The field indicates the concatenation of warehouse (WHLO) and stock location (WHSL). WHLO and WHSL are concatenated without separator. WHLO has a maximum of 3 characters while WHSL has 10. If WHLO has less than 3 characters, it will be filled up with spaces to the right to consume the maximum length. If WHSL is less than 10 characters, it will be trimmed.

If partner from LogicalID is eam, Warehouse (WHLO) is retrieved from Property/NameValue@name='Warehouse' and Stock location (WHSL) from CodeValue since the ID has a prepend value of STOREBIN.

For Unit Codes:

The field indicates the unit of measure.

Constant value (STCO) = 'UNIT'

@accountingEntity

For Business Sectors:

CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Customs Statistics Number: CSYCSN.CKCONO

CSYTAB.CTDIVI.; /

For Feature Options: MPDFHE.PECONO CMNDIV.CCDIVI.; /

For Item Free Field 1: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 3: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 4: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Free Field 5: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Item Groups: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

For Product Groups: CYSTAB.CTCONO CYSTAB.CTDIVI.; /

For Seasons: CSEAMA.HSCONO CMNDIV.CCDIVI.; /

For Stock Locations: CSYTAB.CTCONO CMNDIV.CCDIVI.: /

For Unit Codes: CSYTAB.CTCONO CSYTAB.CTDIVI.; /

@variationID

@lid

For Business Sectors:

The field indicates the company and division, displayed as CONO DIVI.

For Capabilities:

The field indicates the company and division

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 770 AAA

For Customs Statistics Number:

The field indicates the company and division, displayed as CONO DIVI.

For Feature Options:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 1:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 3:

The field indicates the company and division, displayed as ${\sf CONO_DIVI}$.

For Item Free Field 4:

The field indicates the company and division, displayed as CONO DIVI.

For Item Free Field 5:

The field indicates the company and division, displayed as CONO DIVI.

For Item Groups:

The field indicates the company and division, displayed as CONO DIVI.

For Product Groups:

The field indicates the company and division, displayed as CONO_DIVI.

For Seasons:

The field indicates the company and division, displayed as CONO_DIVI.

For Stock Locations:

The field indicates the company and division.

AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 780_AAA

For Unit Codes:

The field indicates the company and division, displayed as CONO DIVI.

For Capabilities:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Roles:

The field indicates the sequence number that identifies the number of times that the BOD has been published.

For Stock Locations:

The field indicates the sequence number. Sequence number is an internal number to ensure documents are processed in correct order.

For Capabilities:

The field indicates the logical ID of the system that is SOR for this noun instance.

For Roles:

The field indicates the logical ID of the system.

For Stock Locations:

The field indicates the logical ID of the system that is SOR for this noun instance.

CodeDefinition/EffectiveTimePeriod/StartDateTime

For Seasons:

CSEAMA.HSSTDT; CRS912MI/AddSeason, UpdSeason	For Seasons: The field indicates the first valid date.
CodeDefinition/EffectiveTimePeriod/EndDateTime	-
For Seasons:	For Seasons:
CSEAMA.HSLVDT; CRS912MI/AddSeason, UpdSeason CodeDefinition/Status/Code	The field indicates the last validity date for the record.
For Seasons:	For Seasons:
CSEAMA.HSSTAT; CRS912MI/AddSeason, UpdSeason	The field indicates the status.
- A	If 'Pending', set to 10.
For Stock Locations: MITPCE.MSDEST; MMS010MI/AddLocation,	If 'Open', set to 20. If 'Closed', set to 90.
ChgLocation	II Closed, set to 90.
g	For Stock Locations:
	The field indicates the location's default status, which is proposed
	when an item is placed at the location.
	If 'Pending' set to 1. If 'Open' set to 2.
	If 'Closed' set to 3.
odeDefinition/ListID	
	For Business Sectors:
	Set to 'Business Sectors'.
	For Capabilities:
	The field indicates the list ID for Capability. Set to 'Skills'.
	For Customs Statistics Number:
	Set to 'Customs Statistics Number'.
	For Feature Options:
	Set to 'Style Features'.
	For Item Free Field 1: Set to 'Item Free Field 1'.
	Set to item rice ricid r.
	For Item Free Field 3:
	Set to 'Item Free Field 3'.
	For Item Free Field 4:
	Set to 'Item Free Field 4'.
	For Item Free Field 5:
	Set to 'Item Free Field 5'.
	For Item Groups:
	Set to 'Item Groups'.
	For Product Groups:
	Set to 'Product Groups'.
	For Roles:
	The field indicates the list id for Role. Set to 'Competencies'
	F 0
	For Seasons: Set to 'Seasons'.
	OCI IO OCASOTIS.
	For Stock Locations:
	Set to 'Stock Locations'.
	Family: Cadaa.
	For Unit Codes: Set to 'Unit Codes'
CodeDefinition/CodeValue	For Unit Codes: Set to 'Unit Codes'.
CodeDefinition/CodeValue For Stock Locations:	
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation,	Set to 'Unit Codes'.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation	Set to 'Unit Codes'. For Stock Locations:
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors:	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors:
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors:	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors:
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors: CSYTAB.CTTX15; CRS036MI/Add, Upd For Capabilities: CCADEF.DETX15	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors: The field indicates the name of the business area.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors: CSYTAB.CTTX15; CRS036MI/Add, Upd For Capabilities:	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors: The field indicates the name of the business area. For Capabilities: The field indicates the Capability name.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors: CSYTAB.CTTX15; CRS036MI/Add, Upd For Capabilities: CCADEF.DETX15 ; CBS004MI/Add,Update	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors: The field indicates the name of the business area. For Capabilities: The field indicates the Capability name. For Customs Statistics Number:
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors: CSYTAB.CTTX15; CRS036MI/Add, Upd For Capabilities: CCADEF.DETX15 ; CBS004MI/Add,Update For Customs Statistics Number:	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors: The field indicates the name of the business area. For Capabilities: The field indicates the Capability name.
For Stock Locations: MITPCE.MSWHSL; MMS010MI/AddLocation, ChgLocation CodeDefinition/Name For Business Sectors: CSYTAB.CTTX15; CRS036MI/Add, Upd For Capabilities: CCADEF.DETX15 ; CBS004MI/Add,Update	Set to 'Unit Codes'. For Stock Locations: The field indicates the stock location. For Business Sectors: The field indicates the name of the business area. For Capabilities: The field indicates the Capability name. For Customs Statistics Number:

; PDS055MI/Add, Update

For Item Free Field 1: CSYTAB.CTTX15 ; CRS181MI/Add, Upd

For Item Free Field 3:

CSYTAB.CTTX15; CRS183MI/Add, Upd

For Item Free Field 4:

CSYTAB.CTTX15; CRS184MI/Add,

Upd

For Item Free Field 5: CSYTAB.CTTX15; CRS185MI/Add, Upd

For Item Groups: CSYTAB.CTTX15

; CRS025MI/AddItemGroup,

UpdItemGroup

For Product Groups:

CSYTAB.CTTX15; CRS035MI/AddProductGroup,

UpdProductGroup

For Roles:

CRODEF.RDTX15 CBS010MI.Add/Chg CCADEF.RDTX15 CBS004MI.Add/Chg.; /

For Seasons:

CSEAMA.HSTX15; CRS912MI/AddSeason, UpdSeason

For Stock Locations: MITPCE.MSSLDS ; MMS010MI/AddLocation, ChgLocation

For Unit Codes:

CSYTAB.CTTX15; CRS050MI/Add, Update

For Item Free Field 1:

The field indicates the item user-defined field 1 name.

For Item Free Field 3:

The field indicates the name of the item user-defined field 3.

For Item Free Field 4:

The field indicates the item user-defined field 4 name.

For Item Free Field 5:

The field indicates the item user-defined field 5 name.

For Item Groups:

The field indicates the Item group name.

For Product Groups:

The field indicates the product group name.

For Roles:

The field indicates a name of the code.

For Seasons:

The field indicates the season name.

For Stock Locations:

The field indicates the stock location name.

For Unit Codes:

The field indicates the name of the unit of measure.

CodeDefinition/Description

For Business Sectors:

CSYTAB.CTTX40; CRS036MI/Add, Upd

For Capabilities:

CCADEF.DETX40; CBS004MI/Add,Update

For Customs Statistics Number:

CSYCSN.CKTX40; CRS128MI/AddBasicData, UpdBasicData

For Feature Options: MPDFHE.PETX30 ; PDS055MI/Add, Update

For Item Free Field 1: CSYTAB.CTTX40 ; CRS181MI/Add, Upd

For Item Free Field 3:

CSYTAB.CTTX40; CRS183MI/Add, Upd

For Item Free Field 4:

CSYTAB.CTTX40; CRS184MI/Add,

Upd

For Item Free Field 5: CSYTAB.CTTX40 ; CRS185MI/Add, Upd

For Item Groups: CSYTAB.CTTX40

; CRS025MI/AddItemGroup,

UpdItemGroup

For Product Groups:

CSYTAB.CTTX40; CRS035MI/AddProductGroup,

For Business Sectors:

The field indicates the description of the business area.

For Capabilities:

The field indicates the Capability text.

For Customs Statistics Number:

The field indicates the Customs Statistics Number description.

For Feature Options:

The field indicates the description of the feature.

For Item Free Field 1:

The field indicates the item user-defined field 1 description.

For Item Free Field 3:

The field indicates the description of the item user-defined field 3.

For Item Free Field 4:

The field indicates the item user-defined field 4 description.

For Item Free Field 5:

The field indicates the item user-defined field 5 description.

For Item Groups:

The field indicates the Item group description.

For Product Groups:

The field indicates the product group description.

For Roles:

The field indicates Role and Capability text.

For Seasons:

The field indicates the season description.

UpdProductGroup

For Roles: CRODEF.RDTX40 CBS010MI.Add/Chg CCADEF.RDTX40 CBS004MI.Add/Chg.; /

For Seasons:

CSEAMA.HSTX40; CRS912MI/AddSeason, UpdSeason

For Unit Codes:

CSYTAB.CTTX40; CRS050MI/Add, Update

CodeDefinition/Property

@sequence

For Feature Options: MPDVOF.PLSQNU ; PDS056MI/Add, Delete For Feature Options:

For Unit Codes:

The field indicates the sequence number for sorting.

The field indicates the description of the unit of measure.

CodeDefinition/Property/NameValue

For Customs Statistics Number:

- 1) CSYCSN.CKINYN
- 2) CSYCSN.CKSUPL
- 3) CSYCSN.CKSPFA.; CRS128MI/AddBasicData, UpdBasicData

For Feature Options: 1) MPDFHE.PEFGRP; PDS055MI/Add, Update

2) MPDOPT.PFOPTN; PDS056MI/Add, Delete

3) MPDFHE.PEFTTP; PDS055MI/Add, Update, Delete

4) MPDFHE.PEPRFI; PDS055MI/Add, Update

5) MPDFHE.PEPRII; PDS055MI/Add, Update.; /

For Item Groups:

- 1) CSYTAB.CTPARM
- 2) CSYTAB.CTPARM
- 3) CSYTAB CTPARM
- 4) CSYTAB.CTPARM
- .; CRS025MI/AddItemGroup,

UpdItemGroup

For Product Groups: CSYTAB.CTPARM/

CRS035MI.AddProductGroup,

UpdProductGroup

CYSTAB.CTPARM

CRS035MI.AddProductGroup,

UpdProductGroup .; /

For Seasons:

1) CSEAMA.HSFOED

2) CSEAMA.HSLOED.; CRS912MI/AddSeason, UpdSeason

For Stock Locations: MITPCE.MSRESP MITPCE.MSSLTP MITPCE.MSWHLT MITPCE.MSABFC

MITPCE.MSWHLO.; MMS010MI/AddLocation,

ChgLocation

For Unit Codes:

MITPCE.MSPISE

1) CSYTAB.CTPARM; CRS050MI/Add, Update

2) CSYTAB.CTPARM; CRS050MI/Add, Update

3) CSYTAB.CTPARM; CRS050MI/Add, Update

For Customs Statistics Number: 1) INTRASTAT Generating (INYN)

The field indicates if items belonging to the EU customs number are to be included in the basis for INTRASTAT accounting.

Set to 0 if INYN = false. Set to 1 if INYN = true.

If attribute name is 'IntrastatGenerating', populate INYN.

2) Supplementary Unit of Measure (SUPL)

The field indicates the supplementary unit of measure for a customs statistics number.

If attribute name is 'SupplementaryUOM', populate SUPL.

3) Conversion Factor Supplementary Unit Of Measyre (SPFA) The field indicates a recalculation factor for the supplementary unit of measure. It is used when a delivered or received quantity is to be recalculated to the supplementary unit of measure, which is valid for EU customs number.

If attribute name is 'ConversionFactorSupplementaryUOM', populate SPFA.

For Feature Options:

1) The field indicates the feature group which can be used for selection and additional information for a feature. If attribute name is 'StyleFeatureTypes', populate FGRP.

2) The field indicates the option that applies for the feature. If attribute name is 'StyleOption', populate OPTN. If partner from logical ID is 'fashionplm', the messageID PD_0040 (errorMessage=Deletion is not permitted. The option is connected to an existing item.) from PDS056MI.Delete is ignored to avoid XML

3) The field indicates the feature type. This determines what type of options can be used for a feature.

If Alphanumeric, set to 1. If Same Item, set to 2.

If Numeric, set to 3.

If Discrete Numeric, set to 4.

transform failed in the integration process.

If Text, set to 5.

If not given, default to 1.

If attribute name is 'FeatureTypes', populate FTTP.

4) The field indicates what information from the feature/attribute is included in the display and printout.

If None, set to 0.

If ID, set to 1.

If Description, set to 2.

If attribute name is 'PrintFeatureInformation', populate PRFI.

5) The field indicates what information from the option/attribute value is included in the display and printout.

If None, set to 0.

If ID, set to 1.

If Description, set to 2.

4) CSYTAB.CTPARM: CRS050MI/Add, Update

5) CSYTAB.CTPARM; CRS050MI/Add, Update.; / If attribute name is 'PrintOptionInformation', populate PRII.

For Item Groups:

1) Seasonal Curve (SECU)

The field indicates the seasonal curve, which describes how something should be apportioned over the periods of a calendar year. If attribute name is 'SeasonalCurve', populate SECU.

2) Trend Curve (TECU)

The field indicates how the distribution over the periods within a calendar year is to be performed.

If attribute name is 'TrendCurve', populate TECU.

3) Tolerance Catch weight percent (TCWP)

The field indicates the maximum variance tolerated of the expected weight when a stock transaction is reported for a catch weight item. If attribute name is 'ToleranceCatchWeightPercent', populate TCWP.

4) Tolerance catch weight (TCWQ)

The field indicates the maximum variance tolarated of the expected average weight when a stock transaction is reported for a catch weight item.

If attribute name is 'ToleranceCatchWeight', populate TCWQ.

For Product Groups:

1) Seasonal curve (SECU)

The field indicates seasonal curve describes the apportioned over the periods of a calendar year.

If attribute name is 'SeasonalCurve', populate the SECU.

2) Configuration (CONF)

The field indicates items connected to product group enabled for configuration in EQM.

If attribute name is 'Configuration', populate the CONF.

Set to '1' if true.

Set to '0' if false.

For Seasons:

1) First order date

The field indicates the first order date for the season.

If @name='FirstOrderDate', populate FOED.

2) Last order date

The field indicates the last dates orders can be entered for the

If @name='LastOrderDate', populate LOED.

For Stock Locations:

1) The field indicates a unique user ID.

If not given, retrieve value from MMS005MI.GetWarehouse RESP with WHLO as input.

2) The field indicates the ID of a stock zone.

If not given, retrieve from control property m3beStockZone. The value should be existing in MMS040 for the specific warehouse. Set default value to M3.

3) The field indicates the group of locations based on the charactersitics

If not given, retrieve from control property m3beLocationType. The value should be existing in MMS035. Set default value to M3.

4) The field indicates the ABC class - frequency.

If not given, retrieve from control property m3beABCClassFrequency. The value should be existing in CRS015. Set default value to A.

5) The field indicates the warehouse equipment.

If not given, retrieve from control property

m3beWarehouseEquipment. The value should be existing in

MWS023. Set default value to M3.

6) The field indicates the warehouse.

For Unit Codes:

1) Application Identifier (EAIP)

The field indicates the application identifier, which is used to identify data in EAN128 bar codes on printed documents:

Set to '0' if EAIP is 'Not used'.

Set to '37' if EAIP is 'Count'. Set to '310' if EAIP is 'Kilograms'.

Set to '311' if EAIP is 'Meter'.

Set to '320' if EAIP is 'Pounds'. Set to '315' if EAIP is 'Liters'.

Set to '316' if EAIP is 'Cubic meters'.

Set to '360' if EAIP is 'Quarts'. Set to '361' if EAIP is 'Gallons'. Set to '365' if EAIP is 'Cubic feet'. Set to '366' if EAIP is 'Cubic yards'.

If attribute name is 'ApplicationIdentifier', populate EAIP.

2) Number Of Decimal Places (DCCD)

The field indicates how many decimals (0, 1, 2, 3) are used for the values for weights and volumes on the logistics label.

If attribute name is 'NumberOfDecimalPlaces', populate DCCD.

3) ISO Unit Of Measure (STUM)

The field indicates the ISO unit of measure (U/M) that corresponds with the user-defined unit of measure.

If attribute name is 'ISOUnitOfMeasure', populate STUM.

4) Unit Of Measure Category (UMCT)

The field indicates the type of unit of measure (U/M) being defined:

Set to '0' if UMCT is 'Not specified'.

Set to '1' if UMCT is 'Mass'.

Set to '2' if UMCT is 'Volume'

Set to '3' if UMCT is 'Dimension'.

Set to '4' if UMCT is 'Time'.

Set to '99' if UMCT is 'Non-standard'.

If attribute name is 'UnitOfMeasureCategory', populate UMCT.

5) Decimal Rounding Factor (DCRD)

The field indicates the number of decimals (0, 1, 2, 3, 4, 5, 6) that will be allowed for the unit of measure (U/M).

If attribute name is 'DecimalRoundingFactor', populate DCRD.

For Customs Statistics Number:

- 1) Set to 'IntrastatGenerating' if Property/NameValue is INYN.
- 2) Set to 'SupplementaryUOM' if Property/NameValue is SUPL.
- 3) Set to 'ConversionFactorSupplementaryUOM' if Property/ NameValue is SPFA.

For Feature Options:

- 1) If attribute name is 'StyleFeatureTypes', populate FGRP.
- 2) If attribute name is 'StyleOption', populate OPTN
- 3) If attribute name is 'FeatureTypes', populate FTTP
- 4) If attribute name is 'PrintFeatureInformation', populate PRFI.
- 5) If attribute name is 'PrintOptionInformation', populate PRII.

For Item Groups:

- 1) If 'SeasonalCurve', populate SECU.
- 2) If 'TrendCurve', populate TECU.
- 3) If 'ToleranceCatchWeightPercent', populate TCWP.
- 4) If 'ToleranceCatchWeight', populate TCWQ.

For Product Groups:

- 1) 'SeasonalCurve'.
- 2) 'Configuration'.

For Seasons:

- 1) If @name='FirstOrderDate', populate FOED.
- 2) If @name='LastOrderDate', populate LOED.

For Stock Locations:

- 1) If 'Responsible', populate RESP.
- 2) If 'StockZone', populate SLTP
- 3) If 'LocationType', populate WHLT.
- 4) If 'ABCClass-Frequency', populate ABFC. 5) If 'WarehouseEquipment', populate PISE.
- 6) If 'Warehouse', populate WHLO.

For Unit Codes:

- 1) If attribute name is 'ApplicationIdentifier', populate EAIP.
- 2) If attribute name is 'NumberOfDecimalPlaces', populate DCCD.

@name

	3) If attribute name is 'ISOUnitOfMeasure', populate STUM. 4) If attribute name is 'UnitOfMeasureCategory', populate UMCT.
	If attribute name is 'DecimalRoundingFactor', populate DCRD.
CodeDefinition/Property/Description	
For Feature Options:	For Feature Options:
MPDOPT.PFTX30	The field indicates the option description.
; PDS050MI/Add, Update	·
0	

CodeDefinition/AlternateIDs/ID

For Feature Options: MPDFHE.PEATID ; PDS055MI/Add, Update

For Feature Options: The field indicates the unique ID for an attribute.

ContactMaster

ContactMaster/IDs/ID CCUCON.CCCNPE; CRS618MI/Add, Upd	The field indicates the contact.
ContactMaster/Description CCUCON.CCTX40; CRS618MI /Add, Upd	
ContactMaster/Status/Code	The field indicates the description.
CCUCON.CCSTAT; CRS618MI/Add, Upd	The field indicates the status of the record.
	Set to 10 if status is Pending. Set to 20 if status is Open or if input value is null, blank or invalid. Set to 90 if status if Deleted or Closed.
ContactMaster/Name CCUCON.CCTX50; CRS618MI /Add, Upd	The field indicates the name.
ContactMaster/Title CCUCON.CCTITL; CRS618MI /Add, Upd	The field indicates the title.
ContactMaster/SalutationPreferredName CCUCON.CCSALU; CRS618MI /Add, Upd	The field indicates the salutation.
ContactMaster/GivenName CCUCON.CCNAMF; CRS618MI /Add, Upd	The field indicates the first name.
ContactMaster/MiddleName CCUCON.CCNAMM; CRS618MI /Add, Upd	The field indicates the middle name.
ContactMaster/FamilyName CCUCON.CCNAMS; CRS618MI /Add, Upd	The field indicates the surname.
ContactMaster/SuffixName CCUCON.CCNAMX; CRS618MI /Add, Upd	The field indicates the suffix name.
ContactMaster/JobTitle CCUCON.CCJTIT; CRS618MI /Add, Upd	The field indicates the position or designation of a person within an
ContactMaster/DepartmentName	organization.
CCUCON.CCDEPT; CRS618MI /Add, Upd ContactMaster/LanguageCode	The field indicates the department.
CCUCON.CCLHCD; CRS618MI /Add, Upd	The field indicates the language.
ContactMaster/CommunicationDetail @preferredIndicator	Set to 'true' if preferred telephone number.
ContactMaster/CommunicationDetail/ChannelCode	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2).
	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL).
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivisionCCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country. The field indicates the postal code.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/URI CCUCON.CCEMAL; CRS618MI/Add, Upd ContactMaster/EmployerReference	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country. The field indicates the postal code.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCECAR; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/URI CCUCON.CCEMAL; CRS618MI/Add, Upd ContactMaster/EmployerReference @type	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country. The field indicates the postal code. The field indicates the e-mail address. 1. The employer reference type indicates if it is a customer, supplier, or 'other'. Set to '0' if employee reference type is Other. Set to '1' if employee reference type is Customer.
ContactMaster/CommunicationDetail/DialNumber CCUCON.CCPHNO CCUCON.CCPHN2.; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/AddressLine CCUCON.CCCUA1-CCCUA4; CRS618MI/Add, Upd @sequence ContactMaster/CommunicationDetail/Address/CityName CCUCON.CCTOWN; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountrySubDivision CCUCON.CCECAR; CRS618MI /Add, Upd ContactMaster/CommunicationDetail/Address/CountryCode CCUCON.CCCSCD; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/Address/PostalCode CCUCON.CCPONO; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/URI CCUCON.CCEMAL; CRS618MI/Add, Upd ContactMaster/CommunicationDetail/URI CCUCON.CCEMAL; CRS618MI/Add, Upd ContactMaster/EmployerReference @type	If ChannelCode is 'Phone', populate Telephone number 1 (PHNO) or Telephone number 2 (PHN2). If ChannelCode is 'EMail', populate E-mail address (EMAL). The field indicates the telephone number. The field indicates the address line. The field indicates the address line sequence. The field indicates the city. onCode The field indicates the area, province or state within a country. The field indicates the country. The field indicates the postal code. The field indicates the e-mail address.

ContactMaster

The field indicates the BODID from the sending application.
If attribute name is 'ProcessBODID' and actionCode is Add, populate
IEC Correlation Storage

ContactMaster/GenderCode

CCUCON.CCGEND; CRS618MI/Add, Upd

The field indicates the gender.

Set to 0 if gender is Not Specified. Set to 1 if gender is Male. Set to 2 if gender if Female. Set to 3 if gender is Other.

Contract

Contract/ContractHeader/DocumentID @agencyRole	
	For CO Blanket Agreement: Set to 'Customer'
	For PO Agreement: Set to 'Supplier'
Contract/ContractHeader/DocumentID/ID	
For CO Blanket Agreement: OAGRHE.UYAGNO; OIS060MI/AddCustBlkAgr	For CO Blanket Agreement: The field indicates the agreement number connected to a customer.
For PO Agreement: MPAGRH.AHSUNO+ AHAGNB ; PPS100MI/AddAgrHead	For PO Agreement: The field indicates the agreement number connected to a supplier.
@accountingEntity	For CO Planket Agreements
	For CO Blanket Agreement: The field indicates the company and division, displayed as CONO_DIVI.
Contract/ContractHeader/AlternateDocumentID/ID	
For CO Blanket Agreement: OAGRHE.UYOFNO; OIS060MI/AddCustBIkAgr UpdCustBIkAgr	For CO Blanket Agreement: The field indicates the agreement number of the integrating application.
Contract/ContractHeader/DisplayID	
For PO Agreement: MPAGRH.AHAGNB ; PPS100MI/AddAgrHead	For PO Agreement: The field indicates the purchase order agreement number.
Contract/ContractHeader/DocumentDateTime	
For CO Blanket Agreement: OAGRHE.UYAGDT; OIS060MI/AddCustBlkAgr UpdCustBlkAgr	For CO Blanket Agreement: The field indicates the blanket agreement date.
	For PO Agreement:
For PO Agreement: MPAGRH.AHAGRD; PPS100MI/AddAgrHead UpdAgrHead	The field indicates the agreement date.
Contract/ContractHeader/Description	
For CO Blanket Agreement: OAGRHE.UYTX40; OIS060MI/AddCustBlkAgr UpdCustBlkAgr	For CO Blanket Agreement: The field indicates the description of the blanket agreement.
opadasibni igi	For PO Agreement:
For PO Agreement: MPAGRH.AHTX30; PPS100MI/AddAgrHead UpdAgrHead @languageID	The field indicates the name of the agreement.
For CO Blanket Agreement:	For CO Blanket Agreement:
OAGRHE.UYLNCD; OIS060MI/AddCustBlkAgr	The field indicates the language.
UpdCustBlkAgr	The value is translated in CRS881/882.
Contract/ContractHeader/Status/Code	For CO Blanket Armsonanti
For CO Blanket Agreement: OAGRHE.UYAGST; OIS060MI/AddCustBlkAgr UpdCustBlkAgr	For CO Blanket Agreement: The field indicates the status of the blanket agreement. Set to 10 if status is 'Draft'.
For PO Agreement:	Set to 20 if status is 'Open'.
MPAGRH.AHPAST; PPS100MI/AddAgrHead	Set to 80 if status is 'Completed'.
UpdAgrHead	For PO Agreement: The field indicates the status of the agreement. Set to 10 if status is 'Draft'.
	Set to 40 if status is 'Open'.
	Set to 80 if status is 'Completed'.
0 - 1/4 - 1/4 0 - 1/4 -	Set to 90 if status is 'Deleted'.
Contract/ContractHeader/Status/TimePeriod/StartDateTime For CO Blanket Agreement:	For CO Blanket Agreement:
OAGRHE.UYSTDT; OIS060MI/AddCustBlkAgr UpdCustBlkAgr	The field indicates the start date or creation date of the agreement's validity.
Contract/ContractHeader/Status/TimePeriod/EndDateTime	For CO Blanket Agreement
For CO Blanket Agreement: OAGRHE.UYLVDT; OIS060MI/AddCustBlkAgr UpdCustBlkAgr	For CO Blanket Agreement: The field indicates the end date of the agreement's validity.
Contract/ContractHeader/CustomerParty/PartyIDs/ID	
For CO Blanket Agreement: OAGRHE.UYCUNO; OIS060MI/AddCustBIkAgr UpdCustBIkAgr	For CO Blanket Agreement: The field indicates the customer number.
Contract/ContractHeader/ShipToParty/PartyIDs/ID	
For CO Blanket Agreement: OAGRHE.UYCUNO	For CO Blanket Agreement: The field indicates the delivery customer.

Contract

IF address number (ADID) is not blank nublish CLINO + ADID
IF address number (ADID) is not blank, publish CUNO + ADID. It is a concatenation of customer number (CUNO) <10> + address number (ADID) <6> without separator. The position of each field is determined by its maximum length, specified in brackets. If the data does not consume the maximum length, the rest is filled up with spaces. This applies to all fields that are part of the delivery customer code except for the last one. The last field in the concatenation, in this case ADID, is trimmed if it does not consume the maximum length.
For PO Agreement: The field indicates the supplier number.
For CO Blanket Agreement: The field indicates the agreement type. If attribute name is 'AgreementType', populate agreement type (AGTP). IF CO agreement type (AGTP) is not sent THEN get ControlProperty value of m3beCOAgreementType (e.g
'C01').
For PO Agreement: 1) The field indicates the agreement type. If attribute name is 'AgreementType', populate agreement type (AGTP). IF PO agreement type (AGTP) is not sent THEN get ControlProperty value of m3bePOAgreementType (e.g
'A01').
2) The field indicates the agreement priority. If attribute name is 'AgreementPriority', populate agreement priority (AGPT).
The field indicates the currency. If attribute name is 'Currency', populate currency (CUCD).
For CO Blanket Agreement: The field indicates the date or creation date as from when the agreement line is valid.
For PO Agreement: The field indicates the date as from when the agreement line is valid.
The field indicates the last date the record is valid.
For CO Blanket Agreement: The field indicates the item number.
For PO Agreement: The field indicates item number.
For CO Blanket Agreement: The field indicates the company and division, displayed as CONO DIVI.
mumQuantity
For PO Agreement: The field indicates a limit for quantity dependent prices and discounts.
Price/Amount
For CO Blanket Agreement: The field indicates the agreed price when the limit value is reached
For PO Agreement: The field indicates the agreed price when the limit value is reached.
For CO Blanket Agreement: The field indicates the currency. The value is translated in CRS881/882.

Infor May 26, 2023 54

Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/UnitPrice/PerQuantity

Contract

For CO Blanket Agreement: For CO Blanket Agreement:

OAGRPR.OLSACD; OIS060MI/AddAgrLnPrice The field indiccates the quantity to which the sales price applies.

UpdAgrLnPrice

Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/DiscountPercent

For CO Blanket Agreement: The field indicates the discount as a percentage.

OAGRPR.OLDIPC; OIS060MI/AddAgrLnPrice

UpdAgrLnPrice

For PO Agreement:

MPAGPR.AJDIP3; PPS100MI/AddStgPrice

UpdStqPrice

Contract/ContractSchedule/ContractPrice/QuantityBreakPricing/DiscountAmount

For CO Blanket Agreement: For CO Blanket Agreement:

OAGRPR.OLDIPR; OIS060MI/AddAgrLnPrice The field indicates the discount that the customer is to receive.

UpdAgrLnPrice @currencyID

For CO Blanket Agreement:

OAGRHE.UYCUCD; OIS060MI/AddCustBlkAgr The field indicates the currency.

UpdCustBlkAgr

Contract/ContractSchedule/Status/Code

UpdStgPrice

For PO Agreement: For PO Agreement: MPAGRL.AISAGL; PPS100MI/AddStgPrice

The field indicates the status of the agreement.

Set to 20 if status is 'Open'. Set to 80 if status is 'Completed'. Set to 90 if status is 'Deleted'

For CO Blanket Agreement:

Contract/ContractSchedule/AgreedQuantity

For CO Blanket Agreement:

OAGRLN.UWAGQT; OIS060MI/AddCustBlkAgrLn

UpdCustBlkAgrLn

For PO Agreement:

MPAGRL.AIAGQT; PPS100MI/AddStgPrice

UpdStgPrice

@unitCode

For CO Blanket Agreement:

OAGRLN.UWSPUN; OIS060MI/AddCustBlkAgrLn

UpdCustBlkAgrLn

For CO Blanket Agreement:

The field indicates the unit of mreasure.

The value is translated in CRS881/882

Contract/ContractSchedule/UserArea

For PO Agreement:

1) MPAGRL.AIGRPI; PPS100MI/AddAgrLine

2) MPAGRL.AIVOLI;

PPS100MI/AddAgrLine.; /

For PO Agreement:

1) The field indicates the group ID. If attribute name is

'AgreementGroupID', populate agreement group ID (GRPI).

If Group ID is not sent

THEN get control property value of m3bePOAgreementGroupID (e.g.

The field indicates the total agreed quantity of an agreement line.

10).

2) The field indicates the purchase commitment. If attribute name is

'PurchaseCommitment', populate purchase commitment (VOLI).

If PurchaseCommitment is not sent

THEN Set to '1'.

CurrencyExchangeRateMaster

The field indicates the currency.
The field indicates the exchange rate between the currency and the
local currency.
The field indicates the date from which the exchange rate is valid.

CurrencyExchangeRateMaster/CurrencyRateTypeReference/DocumentID/ID CCURRA.CUCRTP; CRS055MI/AddRate The fi

The field indicates the exchange rate type.

CustomerPartvMaster

CustomerPartyMaster	
CustomerPartyMaster/PartyIDs/ID OCUSMA .OKCUNO OKCESA. CRS640MI/Add	The field indicates the customer ID. If m3beM3AsSourceDocumentID is 'true' and PartyIDs/ID is not
OKCESA; CRS610MI/Add	blank , Customer ID is auto generated by M3 and PartyID/ID value is saved in CESA (M3 SMS) field. If m3beM3AsSourceDocumentID is 'true' or 'false' or blank and PartyIDs/ID is blank, Customer ID is auto generated by M3. If m3beM3AsSourceDocumentID is 'false' or blank and PartyIDs/ID is
	not blank, Customer ID is from PartyIDs/ID.
@accountingEntity OCUSMA.OKCONO OKDIVI; /	The field indicates the company and division, displayed as CONO DIVI.
CustomerPartyMaster/PartyIDs/DisplayID	The field is discharged a supplement ID
OCUSMA.OKCUNO; CRS610MI/ CustomerPartyMaster/PartyIDs/TaxID	The field indicates the customer ID.
OCUSMA.OKVRNO, OKCORG, OKVTCD, OKCORG2; CRS610MI/ChgFinancial @schemeName	 The field indicates the organization number 1. The field indicates the VAT registration number. The field indicates the VAT code. The field indicates the organization number 2.
	CountryIdentificationNumber'. TaxIdentificationNumber'. VatCode'. CountryIdentificationNumber2'.
CustomerPartyMaster/Name OCUSMA.OKCUNM; CRS610MI/Add ChgBasicData	The field indicates the customer name.
CustomerPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF; CRS610MI/Add ChgBasicData	The field indicates the reference.
CustomerPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4.; CRS610MI/Add ChgBasicData	The field indicates the address line.
@sequence	The field indicates the address line common
CustomerPartyMaster/Location/Address/CityName OCUSMA.OKTOWN; CRS610MI/Add ChgBasicData	The field indicates the address line sequence. The field indicates the city name.
CustomerPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR; CRS610MI/Add ChgBasicData	The field indicates the state code within a country
CustomerPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD; CRS610MI/Add ChgBasicData	The field indicates an area, province or state within a country.
CustomerPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO; CRS610MI/Add ChgBasicData	The field indicates the postal code.
CustomerPartyMaster/Location/Address/Preference/Indicator	Set to 'true'.
CustomerPartyMaster/Communication/ChannelCode	The field indicates the channel code Phone, Fax or Email.
CustomerPartyMaster/Communication/DialNumber OCUSMA.OKPHNO, OKPHN2, OKTFNO; CRS610MI/Add ChgBasicData	The field indicates the phone and fax number. If ChannelCode is 'Phone' and UseCode is 'Office', populate Phone Number (PHNO). If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
CustomerPartyMaster/Communication/URI CEMAIL.CBEMAL; CRS111MI/Add	The field indicates the e-mail address.
CEMAIL. CRSTTTMI/Add CustomerPartyMaster/Communication/Preference/Indicator	The field indicates the used control of customer phone numbers wher populated. If 'true', DialNumber will populate Phone number 1 (OKPHNO). If 'false', DialNumber will populate Phone number 1 (OKPHNO) if it is
CustomerPartyMaster/PaymentTermID	not already populated, or M3 BE Phone number 2 (OKPHN2).
OCUSMA.OKTEPY; CRS610MI/ChgOrderInfo	The field indicates the customer payment term.

CustomerPartyMaster

CustomerPartyMaster/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/AddBankAccount ChgBasicData	The field indicates the bank ID.
CustomerPartyMaster/FinancialParty/FinancialAccount/IBANID CBANAC.BCIBAN; CRS692MI/AddBankAccount ChgBasicData	The field indicates the International bank account number.
CustomerPartyMaster/FinancialParty/FinancialAccount/AccountIDs/ID CBANAC.BCBKID; CRS692MI/AddBankAccount	The field indicates the bank account ID to which related bank account information is connected. The ID can be connected to the company, customer, supplier, employee, or other kinds of account holders.
@name CBANAC.BCBANA; CRS692MI/AddBankAccount ChgBasicData	The field indicates a user-defined name for the bank account.
CustomerPartyMaster/FinancialParty/FinancialAccount/Name CBANAC.BCACHO: CRS692MI/AddBankAccount	The field indicates the persons bank account ID.
CustomerPartyMaster/FinancialParty/FinancialAccount/Type CBANAC.BCBKIN; CRS692MI/AddBankAccount	The field indicates the identity of a bank account indicator.
CustomerPartyMaster/FinancialParty/FinancialAccount/Status/Code CBANAC.BCSTAT; CRS692MI/AddBankAccount	The field indicates the status (STAT) of financial account. Set to 10 if status is Open. Set to 20 if status is Pending. Set to 90 if status is Closed.
CustomerPartyMaster/UserArea/Property/NameValue OCUSMA.OKCFC1 OKCFC2 OKCFC3 OKCFC4 OKCFC5 OKCFC6 OKCFC7 OKCFC8 OKCFC7 OKCFC8 OKCFC9 OKCFCO; CRS610MI/Add ChgBasicData	1) User-defined field 1 - customer The field indicates the user-define values, setup in CRS191.If attribute name is "ItemFreeField1", populate user-defined field 1 - customer (CFC1). 2) User-defined field 2 - customer The field indicates the user-define values. If attribute name is "ItemFreeField2", populate user-defined field 2 - customer (CFC2). 3) User-defined field 3 - customer The field indicates the user-define values, setup in CRS193. If attribute name is "ItemFreeField3", populate user-defined field 3 - customer (CFC3). 4) User-defined field 4 - customer The field indicates the user-define values, setup in CRS194 If attribute name is "ItemFreeField4", populate user-defined field 4 - customer (CFC4). 5) User-defined field 5 - customer The field indicates the user-define values, setup in CRS195 If attribute name is "ItemFreeField5", populate user-defined field 5 - customer (CFC5). 6) User-defined field 6 - customer The field indicates the user-define values, setup in CRS196 If attribute name is "ItemFreeField6", populate user-defined field 6 - customer (CFC6). 7) User-defined field 7 - customer The field indicates the user-define values. If attribute name is "ItemFreeField7", populate user-defined field 7 - customer (CFC7). 8) User-defined field 8 - customer The field indicates the user-define values, setup in CRS198 If attribute name is "ItemFreeField8", populate user-defined field 6 - customer (CFC8). 9) User-defined field 9 - customer The field indicates the user-define values, setup in CRS199 If attribute name is "ItemFreeField9", populate user-defined field 6 - customer (CFC9). 10) User-defined field 10 - customer The field indicates the user-define values, setup in CRS199 If attribute name is "ItemFreeField9", populate user-defined field 6 - customer (CFC9).
@name	customer (CFC0). 11) The field indicates the BODID from the sending application. Set attribute name to "ProcessBODID". 1) "ItemFreeField1". 2) "ItemFreeField2". 3) "ItemFreeField3". 4) "ItemFreeField5". 6) "ItemFreeField6". 7) "ItemFreeField7". 8) "ItemFreeField8". 9) "ItemFreeField9".

CustomerPartyMaster/Status/Code OCUSMA.OKSTAT; CRS610MI/Add

CustomerPartvMaster

ChgBasicData	The field indicates the status (STAT) of customer.
	Set to 10 if status is Open.
	Set to 20 if status is Pending.
	Set to 90 if status is Closed.
CustomerPartyMaster/CurrencyCode	
OCUSMA.OKCUCD; CRS610MI/ChgFinancial	The field indicates the currency code of the customer.
CustomerPartyMaster/Classification/Codes/Code	
1) OCUSMA.OKCUTP	The field indicates the classification code.
CRS610MI/Add/ChgOrderInfo/ChgFinancial	1) Customer type
2) OCUSMA.OKTEDL	The field indicates the customer type. If attribute listID is 'Customer
CRS610MI/Add/ChgOrderInfo/ChgFinancial	Types', populate customer type (CUTP).
3) OCUSMA.OKSDST	2) Delivery Terms
CRS610MI/Add/ChgOrderInfo/ChgFinancial	The field indicates the delivery terms. If attribute listID is 'Incoterms',
4) OCUSMA.OKTXAP	populate delivery terms (TEDL).
CRS610MI/Add/ChgOrderInfo/ChgFinancial	3) District
5) OCUSMA.OKCUCL	The field indicates the district. If attribute listID is 'District', populate
CRS610MI/Add/ChgOrderInfo/ChgFinancial	district (SDST).
6) OCUSMA.OKMODL	4) Tax applicable
CRS610MI/ChgOrderInfo.; /	The field indicates the tax applicable. If attribute listID is 'Tax
	Applicable', populate tax applicable (TXAP).
	If tax applicable is set to 'No', populate the field to 0.
	If tax applicable is set to 'Yes', populate the field to 1.
	If tax applicable is set to 'VAT Exempt', populate the field to 2.
	5) Customer group
	The field indicates the customer group. If attribute listDI is 'Customer
	groups', populate customer group (CUCL).
	6) Transportation Method
	The field indicates the transportation method. If attribute listID is
	'Transportation Methods', populate delivery method (MODL).
@listID	
	1) 'Customer Types'.
	2) 'Incoterms'.
	3) 'District'.
	4) 'Tax Applicable'.
	5) 'Customer groups'.
CustomerPartyMaster/DefaultShipFromWarehouseLocation/ID	
OCUSMA.WHLO; CRS610/ChgOrderInfo	The field indicates the default warehouse of the customer.
CustomerPartyMaster/CustomerAccount/TotalCreditLimitAmount	
OCUSMA.OKCRL3; CRS610MI/ChgFinancial	The field indicates the Credit Limit 3.
CustomerPartyMaster/SalesPersonReference/IDs/ID	

CustomerReturn

CustomerReturn/CustomerReturnHeader/DocumentID/ID OCHEAD.OCREPN; OIS390MI/AddHead	The field indicates the receiving number which identifies a customer
CustomerReturn/CustomerReturnHeader/DocumentReference	return
дкур с	 Set to 1 if reference order category is 'ProductionOrder'. Set to 2 if reference order category is 'PurchaseOrder'. Set to 3 if reference order category is 'SalesOrder'.
	4) Set to 4 if reference order category is 'RequisitionOrder'.5) Set to 6 if reference order category is 'ServiceOrder'.
CustomerReturn/CustomerReturnHeader/DocumentReference/DocumentRefe	
CustomerReturn/CustomerReturnHeader/CustomerParty/PartyIDs/ID OCHEAD.OCCUNO; OIS390MI/AddHead	The field indicates the customer number.
CustomerReturn/CustomerReturnHeader/ShipToParty/Location @type	
.; OIS390MI/AddHead	1) Warehouse 2) Site
CustomerReturn/CustomerReturnHeader/ShipToParty/Location/ID	,
1) OCHEAD.OCWHLO OIS390MI.AddHead	Warehouse If attribute type is 'Warehouse', populate warehouse (WHLO).
2) OCHEAD.OCFACI OIS390MI.AddHead.; /	Facility If attribute type is 'Site', populate facility (FACI).
CustomerReturn/CustomerReturnHeader/PayFromParty/PartyIDs/ID OCHEAD.OCPYNO; OIS390MI/AddHead	The field indicates the customer ID who receives the invoice.
CustomerReturn/CustomerReturnHeader/ReturnFromShipToParty/Par OCHEAD.OCADID; OIS390MI/AddHead	The field indicates the delivery number.
CustomerReturn/CustomerReturnHeader/RequiredReturnDateTime OCHEAD.OCEPDT + OCRETM; OIS390MI/AddHead	Get last 6 characters if more than 10. The field indicates the required return date and time.
CustomerReturn/CustomerReturnHeader/ReturnReasonCode OCHEAD.OCRSCD; OIS390MI/AddHead	The field indicates the transaction reason code.
CustomerReturn/CustomerReturnLine/LineNumber OCLINE.ODRELI; OIS390MI/ReturnLine	The field indicates the order line number.
CustomerReturn/CustomerReturnLine/DocumentReference/LineNumb OCLINE.ODRORL; OIS390MI/AddLine	per The field indicates the line number.
CustomerReturn/CustomerReturnLine/DocumentReference/SubLineNOCLINE.ODRORX; OIS390MI/AddLine	lumber The field indicates the subline number.
CustomerReturn/CustomerReturnLine/Item/Item/D/ID OCLINE.ODITNO: OIS390MI/AddLine	The field indicates the item number.
CustomerReturn/CustomerReturnLine/Item/SerializedLot/Lot/LotIDs/II OCLINE.ODBANO; OIS390MI/AddLine	D The field indicates the lot number.
CustomerReturn/CustomerReturnLine/Quantity OCLINE.ODREQ0; OIS390MI/AddLine	The field indicates the total quantity advised by the customer.
CustomerReturn/CustomerReturnLine/UnitPrice/Amount OCLINE.ODSAPR; OIS390MI/AddLine	The field indicates the sales price to be credited.
CustomerReturn/CustomerReturnLine/RequiredReturnDateTime OCLINE.ODEPDT + ODRETM; OIS390MI/ReturnLine	The field indicates the required return date and time.
CustomerReturn/CustomerReturnLine/ReturnReasonCode OCLINE.ODRSCD; OIS390MI/AddLine	The field indicates the transaction reason code.
CustomerReturn/CustomerReturnLine/ReceivedQuantity OCLINE.ODREQ1; OIS390MI/ReturnLine	The field indicates the total quantity returned. IF ReceivedQuantity (REQ1) is existing and not equal to 0, call OIS390MI.ReturnLine

EmployeeWorkTime

EmployeeWorkTime/IDs/ID

MMÓPTR.QJCONO MMOPTR.QJMWNO

MMOPTR.QJOPNO MMOOPE.QORPDT

MMOOPE.QORPDT.; MOS070MI/UpdOperation

@accountingEntity

MMOPTR.CONO; MOS070MI/UpdOperation

Work Order, operation, report date, report time.

The field indicates the ID of EmployeeWorkTime concatenated from

The field indicates the company and division, displayed as CONO DIVI.

EmployeeWorkTime/BaseEmployeeWorkTime/Employee/ID

MMOPTR.QJEMNO; MOS070MI/UpdOperation

The field indicates the employee ID.

EmployeeWorkTime/BaseEmployeeWorkTime/WorkTimePeriod/StartDateTime

MMOPTR.QJRPDT MMOPTR.QJRTM1. The field indicates the report date and time.

; MOS070MI/UpdOperation

EmployeeWorkTime/BaseEmployeeWorkTime/WorkTimePeriod/Duration The field indicates the used labor time or travelling time based.

1) MMOPTR.QJUMAT MOS070MI.UpdOperation 2) MMOPTR.QJUMAS

1.) Used labor run time.

MOS070MI.UpdOperation.; MOS070MI/UpdOperation

The field indicates the user labor run time (UMAT). 2) Used labor setup time.

The field indicates the used labor setup time.

EmployeeWorkTime/BaseEmployeeWorkTime/Status/Code

MMOOPS.STMB; MOS104MI/ChgOpElement

The field indicates the status.

ExpenseReport

ExpenseReport/ExpenseReportHeader/DocumentID/ID FAPIBH.E5SINO; APS450MI/AddHead	The field indicates the supplier invoice number.
@accountingEntity FAPIBH.E5CONO	The field indicates the company and division.
E5DIVI; APS450MI/AddHead	AccountingEntity for M3 is defaulted as a combination of CONO_DIVI. E.g. 760 AAA
ExpenseReport/ExpenseReportHeader/DocumentDateTime FAPIBH.E5IVDT FAPIBH.E5DEDA .; APS450MI/AddHead	The field indicates the invoice date or delivery date. If this element is blank or missing, use value from Sync/ActionCriteria/ChangeStatus/ EffectiveDateTime as input to IVDT or DEDA. Populate DEDA only if MNS100/G Tax method (TATM) is 1 or 4 and CRS750/F Date type (VDTT) is 3 or 4.
ExpenseReport/ExpenseReportHeader/PersonnelReference/ID FAPIBH.E5SUNO E5SPYN; APS450MI/AddHead	The field indicates the employee id. The employee is used to retrieve the value for supplier and payee.
ExpenseReport/ExpenseReportHeader/TotalAmount FAPIBH.E5CUAM; APS450MI/AddHead @currencyID	The field indicates the total amount.
FAPIBH.E5CUCD; APS450MI/AddHead	The field indicates the currency code.
ExpenseReport/ExpenseReportLine/PersonalIndicator	The field indicates if expense is personal. If "false" then consume the line, else, ignore it.
ExpenseReport/ExpenseReportLine/ItemizedIndicator	The field indicates if expense is itemized. If "false" then consume the main line, else, cosume the itemized line.
ExpenseReport/ExpenseReportLine/LineItemization/PersonalIndicate	· · ·
ExpenseReport/ExpenseReportLine/LineItemization/ExpenseType/ExFAPIBL.E6AO01; APS450MI/AddLine	rpenseCode The field indicates the expense code.
ExpenseReport/ExpenseReportLine/LineItemization/ExpenseAllocati FAPIBL.E6NLAM; APS450MI/AddLine	ion/BaseAmount The filed indicates the net line amount for line type 8.
ExpenseReport/ExpenseReportLine/LineItemization/ExpenseAllocati FAPIBL.E6AO02; APS450MI/AddLine	ion/CostCenterCode The field indicates the cost center.
ExpenseReport/ExpenseReportLine/LineItemization/ExpenseAllocati FAPIBL.E6AO05 E6AO06; APS450MI/AddLine	ion/ProjectReference/ID The field indicates the project and project element. Project and project element are separated by '/' symbol. First part of is the project and the other is the project element. Ex. PJ001/EL002
ExpenseReport/ExpenseReportLine/LineItemization/Address/Country FAPIBL.E6ECAR; APS450MI/AddLine	
ExpenseReport/ExpenseReportLine/LineItemization/Address/Country FAPIBL.E6FTCO; APS450MI/AddLine	yCode The field indicates the from/to country.
ExpenseReport/ExpenseReportLine/LineItemization/PaymentType	The field indicates the payment type. If payment type is 1 or 5 then consume the line, else, ignore it.
ExpenseReport/ExpenseReportLine/LineItemization/DistributedTax/CFAPIBL.E6VTP1, E6VTP2; APS450MI/AddLine	
	If there are multiple instances, the first instance is used as vat rate 1 and the second is vat rate 2.
ExpenseReport/ExpenseReportLine/LineItemization/DistributedTax/EFAPIBL.E6VTA1, E6VTA2; APS450MI/AddLine	BaseAmount The field indicates the tax amount 1 or tax amount 2, if line type 3. Value 3 indicates VAT code.
	If there are multiple instances, the first instance is used as tax amount 1 and the second is tax amount 2.
ExpenseReport/ExpenseReportLine/ExpenseType/ExpenseCode FAPIBL.E6AO01; APS450MI/AddLine	The field indicates the expense code.
ExpenseReport/ExpenseReportLine/ExpenseType/SpecialCode	The field indicates a special code. If value is "Cash Advance" then the line gross amount is negative. If value is "Cash Advance Request" then the line gross amount is
	positive.
ExpenseReport/ExpenseReportLine/ExpenseAllocation/BaseAmount FAPIBL.E6NLAM; APS450MI/AddLine	The filed indicates the net line amount for line type 8.
	The filed indicates the net line amount for line type 8.

ExpenseReport

	is the project and the other is the project element. Ex. PJ001/EL002
ExpenseReport/ExpenseReportLine/Address/CountrySubDivisionCo FAPIBL.E6ECAR; APS450MI/AddLine	ode The field indicates the state of the from/to country.
ExpenseReport/ExpenseReportLine/Address/CountryCode FAPIBL.E6FTCO; APS450MI/AddLine	The field indicates the from/to country.
ExpenseReport/ExpenseReportLine/PaymentType	
	The field indicates the payment type. If payment type is 1 or 5 then consume the line, else, ignore it.
ExpenseReport/ExpenseReportLine/DistributedTax/Calculation/Rate	eNumeric
FAPIBL.E6VTP1, E6VTP2; APS450MI/AddLine	The field indicates the vat rate 1 or vat rate 2.
	If there are multiple instances, the first instance is used as vat rate 1 and the second is vat rate 2.
ExpenseReport/ExpenseReportLine/DistributedTax/BaseAmount	
FAPIBL.E6VTA1, E6VTA2; APS450MI/AddLine	The field indicates the tax amount 1 or tax amount 2, if line type 3. Value 3 indicates VAT code.
	If there are multiple instances, the first instance is used as tax amoun 1 and the second is tax amount 2.

FinancialPartyMaster

The field Indicates the bank number.
The field indicates the company and division.
The field indicate the SWIC/BIC code.
This Field Indicates the name of the bank.
This Field indicates the address line of the bank.
The field indicates the address line sequence number.
This field indicates the City of the bank.
This field indicates the State of the bank.
This field indicates the Country of the bank.
This field indicates the Postal code of the bank.
The field indicates the channel code Phone or Fax or Email. Set to "Phone" if telephone number 1 or 2 or facsimile number or mobile.
Set to "EMail" if e-mail address.
Set to "Communication Channels".
Set to "Office" if telephone number 1, telephone number 2 or e-mail address. Set to "Fax" if facsimile number.
Set to "Communication Use Codes".
The field indicates the country dialing code.
The field indicates the phone or fax number. IF ChannelCode is Phone, populate Phone Number (PHNO). It is a concatenation of elements CountryDialing, DialNumber and Extension. IF ChannelCode is Fax, populate Fax Number (TFNO). It is a concatenation of elements CountryDialing, DialNumber and Extension.
The field indicates the extension number.
The field indicates the e-mail address.
The field indicates the name of Bank contact person.
This field indicates the Bank Branch ID.
The field indicate the SWIC/BIC code.

FinancialPartyMaster
CBANBR.BRBKA1,BRBKA2,BRBKA

FinancialPartyMaster CBANBR.BRBKA1,BRBKA2,BRBKA3,BRBKA4; CRS691MI/	This field indicates the branch Address Lines.
AddBankBranch, UpdByNumber	This field indicates the Dranch Address Lines.
@sequence	
	The field indicates the address line sequence number.
FinancialPartyMaster/BranchParty/Location/Address/CityName ?CBANBR.?BRTOWN?; CRS691MI/AddBankBranch, UpdByNumber	This field indicates the branch City Name.
FinancialPartyMaster/BranchParty/Location/Address/CountrySubDiv. ?CBANBR.?BRECAR?; CRS691MI/AddBankBranch, UpdByNumber	isionCode This field indicates the branch state.
FinancialPartyMaster/BranchParty/Location/Address/CountryCode ?CBANBR.?BRCSCD?; CRS691MI/AddBankBranch, UpdByNumber	This field indicates the branch Country Code.
FinancialPartyMaster/BranchParty/Location/Address/PostalCode ?CBANBR.?BRPONO; CRS691MI/AddBankBranch, UpdByNumber	This field indicates the branch Postal Code.
FinancialPartyMaster/BranchParty/Communication/ChannelCode	
	The field indicates the channel code Phone or Fax or Email. Set to "Phone" if telephone number 1 or 2 or facsimile number or mobile. Set to "EMail" if e-mail address.
@listID	0.44.80
	Set to "Communication Channels".
FinancialPartyMaster/BranchParty/Communication/UseCode	Set to "Office" if telephone number 1, telephone number 2 or e-mail address.
	Set to "Fax" if facsimile number.
@listID	Set to "Communication Use Codes".
Financial Parts Mactor/Propoble State (Communication (Country Dialing	Set to Communication Ose Codes :
FinancialPartyMaster/BranchParty/Communication/CountryDialing	The field indicates the country dialing code.
FinancialPartyMaster/BranchParty/Communication/DialNumber	The field indicates the country dialing code.
CBANBR.BRPHNO	The field indicates the phone or fax number.
CBANBR.BRTFNO.; CRS691MI/AddBankBranch,	IF ChannelCode is Phone, populate Phone Number (PHNO). It is a
UpdByNumber	concatenation of elements CountryDialing, DialNumber and Extension.
	IF ChannelCode is Fax, populate Fax Number (TFNO). It is a concatenation of elements CountryDialing, DialNumber and Extension.
FinancialPartyMaster/BranchParty/Communication/Extension	Extension.
manotan artymaster/Branom arty/Sommanioadon/Extension	The field indicates the extension number.
FinancialPartyMaster/BranchParty/Communication/URI CBANBR.BREMAL; CRS691MI/AddBankBranch, UpdByNumber	The field indicates the e-mail address.
FinancialPartyMaster/FinancialAccount/Status/Code CBANMA.BKSTAT CBANDR.BRSTAT.; CRS690MI.AddBank, UpdByNumber CRS691MI.AddBankBranch, UpdByNumber/	The field indicates the bank status (STAT). Set to 20 if status is Open or Pending.

Infor May 26, 2023 65

InspectDelivery

mepoct2 cm vo. y	
InspectDelivery/DocumentID/ID @location ORINSP.OFWHLO; OIS390MI/InspectLine	The field indicates the warehouse.
InspectDelivery/DocumentDateTime ORINSP.OFRGDT ORINSP.OFRGTM.; OIS390MI/InspectLine	The field indicates the transaction date and time.
InspectDelivery/DocumentReference/DocumentID/ID ORINSP.OFREPN; OIS390MI/InspectLine	The field indicates the customer return receiving number If InspectDelivery/DocumentReference@type is 'CustomerReturn'.
InspectDelivery/DocumentReference/LineNumber ORINSP.OFRELI; OIS390MI/InspectLine	The field indicates the customer return line number.
InspectDelivery/RejectedQuantity ORINSP.OFREQ9; OIS390MI/InspectLine	The field indicates the rejected quantity. If InspectDelivery/DocumentReference@type is 'CustomerReturn' and if the element exists and has a value greater than 0, set OIS390MI InspectLine IRES to 1. IRES set to 1 means that the quantity is for rejection.
InspectDelivery/AcceptedQuantity ORINSP.OFREQ9; OIS390MI/InspectLine	The field indicates the accepted quantity. If InspectDelivery/DocumentReference@type is 'CustomerReturn' and if the element exists and has a value greater than 0, set OIS390MI InspectLine IRES to 5. IRES set to 1 means that the quantity is approved or accepted.
InspectDelivery/RejectionDetails/RejectedItem/SerializedLot ORINSP.OFBANO; OIS390MI/InspectLine	
InspectDelivery/RejectionDetails/HoldCodes/Code ORINSP.OFWHSL; OIS390MI/InspectLine	The field indicates the stock location for rejected quantity. The field is used only if OIS390MI InspectLine IRES is set to 1.
InspectDelivery/UserArea ORINSP.OFREPN; OIS390MI/InspectLine	If attribute name is set to 'wm.CustomerReturnRecNum', map the value to OIS390MI InspectLine REPN. Override the value in InspectDelivery/DocumentReference/DocumentID/ID@type='CustomerReturn'.

InspectionOrder

inspectionOrder	
InspectionOrder/InspectionOrderHeader/DocumentID/ID MMOOPS.MWNO, OPNO; MOS085MI/RptInsp	The field indicates the work order number and operation number
InspectionOrder/InspectionOrderTask/LineNumber MMQIRS.M7ACTS; MOS085MI/RptInsp	The field indicates the inspection ID and
InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/MMQIRS.M7SPOS, M7INSI; MOS085MI/RptInsp	/LineNumber The field indicates the line number and inspection ID
InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/MMQIRS.M7REMK; MOS085MI/RptInsp	/Note The field indicates the remarks
InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/ MMQIRS.M7RPDT; MOS085MI/RptInsp	/ActualCompletionDateTime The field indicates the reporting date.
InspectionOrder/InspectionOrderTask/InspectionOrderTaskLine/MMQIRS.M7RVAL, M7XERR; MOS085MI/RptInsp @/listID	/Classification/Codes/Code The field indicates the reported value, warning indicator
	The field indicates the following list ID: "Reported Value", " "Warning Indicator"
@sequence	The field indicates the sequence number starting with 1

InventoryAdjustment

InventoryAdjustment/InventoryAdjustmentHeader/DocumentID/ID

For ProcessInventoryAdjustment:

MMIHED.I0PMSN ; MMS850MI/AddAdjust The field indicates the external message number.

For SyncInventoryAdjustment:

MMIHED.I0PMSN; MMS850MI/AddAdjust

@accountingEntity

For ProcessInventoryAdjustment:

For ProcessInventoryAdjustment: MMIHED.I0CONO The field indicates the company and division, displayed as

CMNDIV.CCDIVI.; CONO DIVI.

InventoryAdjustment/InventoryAdjustmentLine/Note

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment: MMIIDE.I1BREM The field indicates the remark. ; MMS850MI/AddAdjust

For SyncInventoryAdjustment: The field indicates an optional remark. For SyncInventoryAdjustment: MMIIDE.I1BREM; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/WarehouseLocation/ID

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment:

MMIHED.I0WHLO The field indicates the warehouse ID. ; MMS850MI/AddAdjust

For SyncInventoryAdjustment: For SyncInventoryAdjustment: The field indicates the warehouse. MMIHED.I0WHLO; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/Item/ItemID/ID

For ProcessInventoryAdjustment: The field indicates the item number.

MMIIDE.I1ITNO ; MMS850MI/AddAdjust

For SyncInventoryAdjustment:

MMIIDE.I1ITNO; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ItemQuantity For ProcessInventoryAdjustment:

For ProcessInventoryAdjustment: The field indicates the item quantity. It is only relevant if: MMIINS.I2QLQT

; MMS850MI/AddAdjust 1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

Lot/Quantity is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ For SyncInventoryAdjustment:

MMIINS.I2QLQT; MMS850MI/AddAdjust ItemBaseUOMQuantity is blank.

For SyncInventoryAdjustment:

The field indicates the quantity. It is only relevant if

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/

Quantity is blank.

@unitCode

@unitCode

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment:

MMIINS.I2QLUN The field indicates the qualifier unit of measure. It is only relevant if: ; MMS850MI/AddAdjust 1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ Lot/Quantity@unitCode is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ For SyncInventoryAdjustment:

MMIINS.I2QLUN; MMS850MI/AddAdjust ItemBaseUOMQuantity@unitCode is blank.

> For SyncInventoryAdjustment: The field indicates the unit of measure.

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ItemBaseUOMQuantity

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment:

MMIINS.12QLQT The field indicates the item quantity. It is only relevant if

; MMS850MI/AddAdjust InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/

Quantity is blank.

For ProcessInventoryAdjustment:

For ProcessInventoryAdjustment: MMIINS.I2QLUN The field indicates the qualifier unit of measure. It is only relevant if InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/ ; MMS850MI/AddAdjust

Quantity@unitCode is blank.

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/LotIDs/ID

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment:

MMIIDE.I1BANO The field indicates the lot number. It is only relevant if SerializedLot/

; MMS850MI/AddAdjust Lot/SerialNumber is blank.

For SyncInventoryAdjustment: For SyncInventoryAdjustment: MMIIDE.I1BANO; MMS850MI/AddAdjust The field indicates the lot number.

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/Quantity

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment:

MMIINS.12QLQT The field indicates the item quantity. It is only relevant if ; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/

BaseUOMQuantity is blank.

InventoryAdjustment

For SyncInventoryAdjustment:

MMIINS.I2QLQT; MMS850MI/AddAdjust For SyncInventoryAdjustment:

The field indicates the quantity. This is the first priority in the retrieval

of quantity.

@unitCode

For ProcessInventoryAdjustment:

For ProcessInventoryAdjustment: MMIINS.I2QLUN The field indicates the qualifier unit of measure. It is only relevant if ; MMS850MI/AddAdjust InventoryAdjustment/InventoryAdjustmentLine/SerializedLot/Lot/

BaseUOMQuantity@unitCode is blank.

For SyncInventoryAdjustment:

MMIINS.12QLUN; MMS850MI/AddAdjust For SyncInventoryAdjustment: The field indicates the unit of measure.

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/BaseUOMQuantity

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment: MMIINS.I2QLQT The field indicates the item quantity.

; MMS850MI/AddAdjust @unitCode

For ProcessInventoryAdjustment:

For ProcessInventoryAdjustment: MMIINS.I2QLUN The field indicates the qualifier unit of measure. ; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/SerialNumber

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment: MMIIDE.I1BANO The field indicates the lot number. ; MMS850MI/AddAdjust

For SyncInventoryAdjustment: For SyncInventoryAdjustment: The field indicates the serial number.

MMIIDE.I1BANO; MMS850MI/AddAdjust

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/SerialNumber

For ProcessInventoryAdjustment: For ProcessInventoryAdjustment: MMIIDE.I1BANO The field indicates the lot number.

; MMS850MI/AddAdjust For SyncInventoryAdjustment:

For SyncInventoryAdjustment: The field indicates the lot number. It is only relevant if:

MMIIDE.I1BANO; MMS850MI/AddAdjust 1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

Lot/SerialNumber is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ Lot/LotIDs/ID is blank.

InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Note

For ProcessInventoryAdjustment:

MMIIDE.I1BREF

MMIIDE.I1BRE2.; MMS850MI/AddAdjust @noteID

For ProcessInventoryAdjustment: The field indicates lot reference 1.

2) The field indicates lot reference 2.

For ProcessInventoryAdjustment: 1) Set to "Lot Reference 1". 2) Set to "Lot Reference 2".

InventoryAdjustment/InventoryAdjustmentLine/Quantity

For ProcessInventoryAdjustment:

MMIINS.I2QLQT ; MMS850MI/AddAdjust

For SyncInventoryAdjustment:

MMIINS.I2QLQT; MMS850MI/AddAdjust

For ProcessInventoryAdjustment:

The field indicates the quantity. It is only relevant if:

1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ Lot/Quantity is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

ItemQuantity is blank. 3) InventoryAdjustment/InventoryAdjustmentLine/BaseUOMQuantity is blank.

For SyncInventoryAdjustment:

The field indicates the quantity. It is only relevant if:

1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ Lot/Quantity is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/ ItemQuantity.

@unitCode

For ProcessInventoryAdjustment:

MMIINS.I2QLUN ; MMS850MI/AddAdjust

For SyncInventoryAdjustment:

MMIINS.I2QLUN; MMS850MI/AddAdjust

For ProcessInventoryAdjustment:

The field indicates the qualifier unit of measure. It is only relevant if: 1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

Lot/Quantity@unitCode is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

ItemQuantity@unitCode is blank.

3) InventoryAdjustment/InventoryAdjustmentLine/

BaseUOMQuantity@unitCode is blank.

For SyncInventoryAdjustment:

The field indicates the unit of measure.

InventoryAdjustment/InventoryAdjustmentLine/BaseUOMQuantity

For ProcessInventoryAdjustment:

MMIINS.12QLQT ; MMS850MI/AddAdjust For ProcessInventoryAdjustment:

The field indicates the quantity. It is only relevant if:

1) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

InventoryAdjustment

Lot/Quantity is blank.

2) InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/

ItemQuantity is blank.

@unitCode

For ProcessInventoryAdjustment:

MMIINS.I2QLUN ; MMS850MI/AddAdjust For ProcessInventoryAdjustment:

The field indicates the qualifier unit of measure. It is only relevant if Item/SerializedLot/Lot/Quantity@unitCode and Item/SerializedLot/

ItemQuantity@unitCode are blank.

InventoryAdjustment/InventoryAdjustmentLine/ReasonCode

For ProcessInventoryAdjustment:

For SyncInventoryAdjustment:

MMIINS.I2RSCD; MMS850MI/AddAdjust

MMIINS.I2RSCD ; MMS850MI/AddAdjust For ProcessInventoryAdjustment:

The field indicates the reason code for the transaction.

For SyncInventoryAdjustment:

The field indicates the reason code for the transaction. The code must be a valid reason code set up in M3BE. Only the first three

characters will be considered.

InventoryAdjustment/InventoryAdjustmentLine/HoldCodes/Code

For ProcessInventoryAdjustment: 1)MMIIDE.I1WHSL; MMS850MI/AddAdjust 2)MITPCE.MSWHSL; MMS010MI/ListLocations.; /

For ProcessInventoryAdjustment: The field indicates the location.

If the element is blank and location is defined for Item/Warehouse in MMS002 BE, it will be used as the default. Otherwise, input in MMS850MI AddMove WHSL will be checked using MMS010MI ListLocations with Warehouse (WHLO) as input. The first location that will match will be used regardless of the status. If there is no match, the API returns "NOK Location must be entered".

For SyncInventoryAdjustment: 1) MMIIDE.I1WHSL MMS850MI/AddAdjust 2) MITPCE.MSWHSL MMS010MI/ListLocations.; /

For SyncInventoryAdjustment: The field indicates the location.

Input in MMS850MI/AddAdjust WHSL will be checked using MMS010MI/ListLocations with input WHLO. The first location that will match will be used. If no match, allow API to return applicable error.

InventoryAdjustment/InventoryAdjustmentLine/UserArea

For ProcessInventoryAdjustment: MMIIDE.I1WHSL; MMS850MI/AddAdjust

For ProcessInventoryAdjustment: The field indicates the location.

For EAM, location is fetched from UserArea field eam.Bin.

InventoryCount

InventoryCount/InventoryCountHeader/DocumentID/ID @accountingEntity	
MITLOC.MLCONO CMNDIV.CCUDIV.; /	The field indicates the company and division in CONO_DIVI format. Retrieve ths only if AccountingEntityID is not given.
InventoryCount/InventoryCountHeader/WarehouseLocation/ID MITLOC.MLWHLO; MMS310MI/Update	The field indicates the warehouse.
InventoryCount/InventoryCountLine/Item/Item/ID/ID MITLOC.MLITNO; MMS310MI/Update	The field indicates the item number.
InventoryCount/InventoryCountLine/Item/SerializedLot/Lot/LotIDs/ID MITLOC.MLBANO; MMS310MI/Update	The field indicates the lot number.
InventoryCount/InventoryCountLine/Quantity MITLOC.MLSTQT; MMS310MI/Update	The field indicates the physical inventory quantity.
InventoryCount/InventoryCountLine/BaseUOMQuantity	
MITLOC.MLSTQT; MMS310MI/Update	The field indicates the physical inventory quantity. Retrieve only if Quantity is null.
InventoryCount/InventoryCountLine/HoldCodes/Code	
MITLOC.MLWHSL; MMS310MI/Update	The field indicate the location.
InventoryCount/InventoryCountLine/UserArea	
MITLOC.MLWHSL; MMS310MI/Update	Location The field indicates the location. Retrieve only if HoldCodes/Code is null. If attribute name is "eam.Bin", populate WHSL.
	Container (CAMU) The field indicates the container. If attribute name is set to "Container", populate CAMU.

InventoryHold

InventoryHold/IDs/ID	
@location MMIHED.I0WHLO	The field indicates the warehouse ID.
; MMS850MI/AddMove	The field indicates the wateriouse iD.
InventoryHold/ItemInstance/ItemID/ID	
MMIIDE.11ITNO ; MMS850MI/AddMove	The field indicates the item number.
InventoryHold/ItemInstance/SerializedLot/Lot/LotIDs/ID	
1) MMIIDE.I1BANO;	The field indicates the lot number. If both InventoryHold/ItemInstance/
MMS850MI/AddMove	SerializedLot/Lot/LotIDs/ID and InventoryHold/ItemInstance/ SerializedLot/Lot/SerialNumber are populated, the latter will be used.
2) MPLIND.ICBANO	conditional contains and population, are nation will be used.
PPS320MI/PutawayPO.; /	
InventoryHold/ItemInstance/SerializedLot/Lot/Quantity 1) MMIINS.I2QLQT:	The field indicates the quantity. It is automatically set to 1 if
MMS850MI/AddMove	InventoryHold/ItemInstance/SerializedLot/Lot/SerialNumber is
2) MPLIND.ICRPQA	populated.
PPS320MI/PutawayPO.; /	
@unitCode MMIINS.I2QLUN	The field indicates the unit code.
; MMS850MI/AddMove	The field indicates the unit code.
InventoryHold/ItemInstance/SerializedLot/Lot/SerialNumber	
1) MMIIDE.I1BANO; MMS850MI/AddMove	The field indicates the lot number. If both InventoryHold/ItemInstance/ SerializedLot/Lot/LotIDs/ID and InventoryHold/ItemInstance/
	SerializedLot/Lot/SerialNumber are populated, the latter will be used.
2) MPLIND.ICBANO PPS320MI/PutawayPO.; /	
InventoryHold/ItemInstance/HoldCodes/Code	
MMIIDE.I1WHSL;	The field indicates the from location.
MMS850MI/AddMove	If agreement control property m3beIntegrateOnStatusLocationLevel is
MITPCE.MSWHSL;	set to false:
MMS010MI/ListLocations.; /	Input in MMS850MI/AddMove WHSL will be checked using MMS010MI/ListLocations with input WHLO. The first location that will
	match will be used. If blank or there is no match, hardcoded value of
	LOCALL is used.
	If agreement control property m3beIntegrateOnStatusLocationLevel is
	set to true: Translation in CRS881/882 is supported.
InventoryHold/HoldCodes/Code	Translation in Ortooo 17002 is supported.
MMIINS.I2TWSL;	The field indicates the to location.
MMS850MI/AddMove	If agreement control property m3beIntegrateOnStatusLocationLevel is
MITPCE.MSWHSL;	set to false:
MMS010MI/ListLocations	Input in MMS850MI/AddMove WHSL will be checked using MMS010MI/ListLocations with input WHLO. The first location that will
MPLIND.ICWSHL;	match will be used. If blank, hardcoded value of LOCALL is used. If
PPS320MI/PutawayPO	there is no match, hardcoded value of LOCNON is used. If first TWSL input is the same as the MMS850MI/AddMove WHSL value, the next
MMIIDE.I1WHSL;	TWSL input is used.
MMS850MI/AddReclass	If the transaction is for PO putaway (PPS320MI.PutawayPO), the field
.; /	is set to 'LOCALL'.
	If agreement central property m2heIntegrateOnStatual cention, evel is
	If agreement control property m3beIntegrateOnStatusLocationLevel is set to true:
	Translation in CRS881/882 is supported.
	If HoldCodes/Code is null, move to the location defined in the M3 data field for the blank Message data in CRS882. If no translation
	exists, move to default location LOCALL.
	MMS850MI.AddReclass is called to set the status of the balance ID according to the status proposal of the location in MMS010.
InventoryHold/HoldQuantity	
1) MMIINS.I2QLQT;	The field indicates the quantity if lot number is not used.
MMS850MI/AddMove	
2) MPLIND.ICRPQA	
PPS320MI/PutawayPO.; / @unitCode	
MMIINS.I2QLUN	The field indicates the unit code.
; MMS850MI/AddMove	
InventoryHold/UserArea 1) PFTRNS.INERCV;	1) If UserArea/Property/NameValue@name='wm.ReceivingNum', the
PPS360MI/LstDetByExtRecN	value of this field is used to retrieve PO number, PO line number and

InventoryHold

2) MPLIND.ICRESP PPS320MI/PutawayPO.; / PO line suffix which will be used as input to get the PO line status in PPS200MI.GetLine. If the line status (PUST) is 50 and the logicalID is WM, PPS320MI.PutawayPO will be called.

The value is also used to retrieve the M3 Receiving Number (REPN) which will be used as input in PPS320MI.PutawayPO.

2) If UserArea/Property/NameValue@name='wm.Responsible, the value of this field indicates the Responsible. If this field is blank, the value from control property m3beResponsible will be used in PPS320MI.PutawayPO.

Invoice

Invoice/InvoiceHeader/DocumentID/ID

CINHED.CIINYR CINHED.CICINO CINERL.CIINYR CINERL.CICINO CINGOV.CIINYR CINGOV.CICINO .-; INVBODMI/UpdGovInv, AddErrorLog, AddGovInfo

The field indicates the invoice year (INYR, position 1-4) and the invoice number (CINO, from position 5) updated with the response.

The processing depends on if the feature ID = 2236845 has been activated or not in CMS975 (*):

- If the feature is not actived (FEAT=0): Additional information in CMS516 is not uploaded.
- If the feature is activated (FEAT=1): Additional information in CMS516 is uploaded. Information and status for output type 'elnvoice' is moved to CMS516 instead of updated in CMS500.
- (*) Retrieved from CMS975MI.Get with field NCRN = 2236845.

When feature ID = 2236845 is activated, the following types of electronic invoices will be processed as following:
For type 'TaxReport' (where Icl.Component = TaxReport OR Tax Report OR TaxReporting OR Tax Reporting or if Icl.Component not available):

- Error log updated in case available in the message.
- Additional information updated in case available in the message (only done for status (GINS) set to 90).
- Government information in (CMS500) updated with available information, this is done as the last step to make sure the Government status (GINS) not update to 90-Approved before additional information is available for the invoice printout if requested. For type 'elnvoice' (lcl.Component = elnvoice):
- Error log updated in case available in the message.
- Additional information updated in case available in the message. NOTE: Currently only available for PEPPOL Access Point.

Invoice/InvoiceHeader/AlternateDocumentID/ID

CINHED.CICGID CINGOV.CIT102.-; INVBODMI/UpdGovInv, AddGovInfo

The field indicates an alternative ID for the invoice. The following types are currently handled:

1) schemeName='lcl.Government' indicates the unique ID assigned to the invoice by the government or authority that is updated as Government ID (CGID) in CMS500. The Government ID is only sent from LSP for type 'TaxReport'.

- If feature ID = 2236845 is activated:
 2) schemeName='lcl.UUID' or 'lcl.MX.UUID' updated as additional information in CMS516 for:
- Type 'TaxReport': Field GVTP set to schemeName and value updated in field T102.
- Type 'elnvoice': Field GVTP set to EINV PEPPOL + schemeName and value updated in field T102.

@schemeName

CINGOV.CIGVTP; INVBODMI/AddGovInfo

The field indicates the type of ID included. The following types are currently handled:

1) schemeName='lcl.Government'.

If feature ID = 2236845 is activated:

2) schemeName='lcl.UUID' or 'lcl.MX.UUID'.

Invoice/InvoiceHeader/UserArea

CINHED.CICIDS CINHED.CIGINS CINHED.CICIST CINHED.CICGIN CINHED.CICGSR CINHED.CICISD CINHED.CICTIM CINERL.CICISD CINERL.CICTIM.-; INVBODMI/UpdGovInv, AddErrorLog

The field indicates additional information included in the response for the invoice if feature ID = 2236845 is not activated.

The following information is currently handled:

- 1) name='lcl.Status' indicates the detail status code of the feedback that is updated as Detailed status (CIDS) in CMS500. This element together with the Validation/Status/Code will also decide the status updated as Government invoice status (GINS) and Customer invoice status (CIST) in CMS500. See Validation/Status/Code for details. 2) name = 'lcl.StatusDate' indicates the date and time of the feedback received for the electronic invoice that is updated as Status date (CISD) and Status time (CTIM) in CMS500 and CMS515 in case Validation/Status/EffectiveDateTime is missing. See Validation/Status/ EffectiveDateTime for details. This applies to both MI transactions UpdGovInv and AddErrorLog.
- 3) name = 'lcl.SequenceNumber' Indicates the external Invoice number given by an external party (authority or other) that is updated as Government invoice number (CGIN) in CMS500.
- 4) name = 'lcl.SequencePrefix' Indicates the external Invoice prefix given by an external party (authority or other) that is updated as Government invoice series (CGSR) in CMS500

Invoice/InvoiceHeader/Validation/Status/Code

CINHED.CIGINS CICIST CICIFS; INVBODMI/UpdGovInv

The field indicates the status for the following fields in CMS500 if feature ID = 2236845 is not activated:

- Government invoice status (GINS) indicates the status of the electronic invoice at the receiving party that is normally the government or authority.
- Customer invoice status (CIST) indicates the status of the electronic

May 26, 2023

invoice at the receiving customer in case the electronic invoice is forwarded by the government or authority.

See details below how to map the fields GINS and CIST.

- Feedback status (CIFS) indicates the validation status code of the feedback received for the electronic invoice that is taken directly from Validation/Status/Code.

The status code of the validation for an invoice together with the value of the UserArea name='lcl.Status' will decide the status updated as GINS and CIST in CMS500. The following status codes are currently handled:

- 'Errors' with Icl.Status = 'Failed': GINS set to 15 (Validation failed), CIST not used. Note: this scenario/status is currently not handled in LSP
- 'Requested' with Icl.Status = 'Sent': GINS set to 20 (Sent), CIST not used.
- 'Requested' with Icl.Status = 'AwaitingConfirmation' or 'Awaiting Confirmation': GINS set to 20 (Sent), CIST not used.
- -'Errors' with Icl.Status = 'Aborted': GINS set to 30 (Delivery failed), CIST not used.
- 'Errors' with Icl.Status = 'NotTransmitted' or 'Not Transmitted': GINS set to 30 (Delivery failed), CIST not used.
- 'Errors' with Icl. Status = 'Rejected': GINS set to 40 (Rejected), CIST not used.
- 'Success' with Icl.Status = 'Forwarded': GINS set to 90 (Accepted), CIST not used.
- 'Success' with Icl.Status = 'Registered': GINS set to 90 (Accepted), CIST not used.
- 'Requested' with Icl.Status = 'Forwarded': GINS set to 90 (Accepted), CIST set to 90 (Accepted/Sent).
- 'Warnings' with Icl.Status = 'FailedDelivery' or 'Failed Delivery': GINS set to 90 (Accepted), CIST set to 30 (Delivery failed).
- 'Warnings' with Icl. Status = 'TransmittedNoDelivery' or 'Transmitted No Delivery': GINS set to 90 (Accepted), CIST set to 30 (Delivery failed).
- 'Warnings' with Icl. Status = 'Partially Accepted' or
- 'PartiallyAccepted': GINS set to 90 (Accepted), CIST not used.
- 'Warnings' with Icl.Status = 'Cancelled': GINS set to 50 (Annulled), CIST not used.

Exception if status code 'Errors' with Icl.Status = 'PartiallyAccepted' or 'Partially Accepted', should be handled as 'Success' with Icl.Status = 'Registered': GINS set to 90 (Accepted), CIST not used. In case of invalid / out-of-scope combination of Icl.Status and Validation/Status/Code, a MeC error message must be created: 'The response file contains an invalid status. Update of invoice is terminated."

Invoice/InvoiceHeader/Validation/Status/EffectiveDateTime

CINHED.CICISD CINHED.CICTIM CINERL.CICISD CINERL.CICTIM.-; INVBODMI/UpdGovInv, AddErrorLog

The field indicates the date and time of the feedback received for the electronic invoice that is updated as Status date (CISD) and Status time (CTIM) in CMS500 and CMS515.

If element not exists, get value from UserArea/Property/NameValue with name = 'lcl.StatusDate'. This applies to both MI transactions UpdGovInv and AddErrorLog.

Input format: YYYY-MM-DDTHH:MM:SS Set CISD to YYYYMMDD. Set CTIM to HHMMSS.

Example: <EffectiveDateTime>2020-05-06T07:51:22</EffectiveDateTime>

Invoice/InvoiceHeader/Validation/Message/Description CINERL.CIMGDA; INVBODMI/AddErrorLog

The field indicates the detailed description for the feedback received of validation errors in the electronic invoice that is updated as Message description (MGD1 - MGD5) in CMS515.

Each MGDx field contains 40 characters. Set first 40 characters to MGD1, and each succeeding 40 characters to MGD2-MGD5 respectively.

In case the entire value exceeds 200 characters, a '+' must be added at the last position of MGD5.

Invoice/InvoiceHeader/Validation/Message/ReasonCode CINERL.CIRCOD; INVBODMI/AddErrorLog

The field indicates the reason code or short description for the feedback received of validation errors in the electronic invoice that is updated as Message reason code (RCOD) in CMS515.

In case the entire value exceeds 40 characters, a '+' must be added at the last position.

ItemMaster	
ItemMaster/ItemMasterHeader/ItemID/ID	
1) MHIMAS.RAITNO; MHS001MI/AddIntItmBasic	The field indicates the identifier for an object.
2) MHIMAS.RAIFIN;	1) The field indicates the item number.
MHS001MI/AddIntItmBasic .: /	2) The field indicates the interface item number.
@schemeName	The field in disease the control Name
	The field indicates the schemeName.
	 If scheme name is blank, populate ITNO. If scheme name is populated with any value other than 'Customer', populate IFIN.
ItemMaster/ItemMasterHeader/ItemID/RevisionID MITMAS.MMECVE	The field indicates the revision number (edition) for an item or
; MHS001MI/AddIntItmMst, ChgintItmMst	document.
ItemMaster/ItemMasterHeader/DisplayID	
MHIMAS.RAITNE; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates the extended item number, which is a prolonged item number used in lists, sorting, viewing information, etc. This is for reference purposes only.
ItemMaster/ItemMasterHeader/UPCID	
MHIALI.RGPOPN MHIALI.RGALWQ MHIALI.RGALWT:	The field correspond to GTIN-12 and UCC-12. This is a 12-digit number used for identifying goods.
MHS025MI/AddIntItmAli, ChgIntItmAli, MITPOP.MPPOPN	Use Alias qualifier (ALWQ) = UPC. Set Alias category (ALWT) to 2 (EAN).
MITPOP.MPALWQ MITPOP.MPALWT:	Use MMS025MI/LstAlias to verify which record is for add, update or
MMS025MI/DItAlias.	delete. Do not call MMS025MI.DltAlias if any of the fields Partner
;/	(E0PA), Season (SEA1) or Valid from (VFDT) have values retrieved from MMS025MI.LstAlias.
ItemMaster/ItemMasterHeader/GTIN MHIALI.RGPOPN;	The field indicates the Global Trade Item Number.
MHS025MI/AddIntItmAli, ChgIntItmAli	
MITPOP.MPPOPN; MMS025MI/DItAlias.; /	Use MMS025MI/LstAlias to verify which record is for add, update or delete.
	Do not call MMS025MI.DItAlias if any of the fields Partner (E0PA), Season (SEA1) or Valid from (VFDT) have values retrieved from MMS025MI.LstAlias.
ItemMaster/ItemMasterHeader/Description 1) MHIMAS.RAFUDS	The field indicates the item name or description.
2) MHIMAS.RAITDS	The field indicates the item hame of description.
.; MHS001MI/AddIntItmMst, ChgIntItmMstFld @type	
	The field indicates the description type. If blank, populate FUDS. If 'ShortName', populate ITDS.
ItemMaster/ItemMasterHeader/Classification/Codes/Code	ii eliotataine, populae 1150.
1) MHIMAS.RAITTY;	1) Item type
MHS001MI/AddIntItmMst,ChgIntItmMst 2) MHIMAS.RAITGR;	The item type is mandatory and cannot be changed after the item is created.
MHS001MI/AddIntItmMst,ChgIntItmMst	If attribute listID is 'Item Types', populate ITTY.
3) MHIMAS.RAITCL; MHS001MI/AddIntItmMst,ChgIntItmMst	2) Item group
4) MHIMAS.RABUAR; MHS001MI/AddIntItmMst.ChqIntItmMst	The field indicates the item group.
MHS001MI/Addintitmivist,Cngintitmivist 5) MHIMAS.RAPRGP;	If attribute listID is 'Item Groups', populate ITGR.
MHS001MI/AddIntItmMst,ChgIntItmMst	3) Product group The field indicates the product group
6) MHIMAS.RADIGI; MHS001MI/AddIntItmMst,ChgIntItmMst	The field indicates the product group. If attribute listID is 'Product Groups', populate ITCL.
7) MHIMAS.RACHCD; MHS001MI/AddintltmMet.ChaintltmMet	A) Business area
MHS001MI/AddIntItmMst,ChgIntItmMst 8)MHIMAH.RGISTY;	Business area The field indicates the business area.
MHS200MI/AddIntSKU MMM076.HHSTYN;	If attribute listID is 'Business Sectors', populate BUAR.
PDS061MI/AddSKUOption, PDS061MI/CreateSKU	5) Procurement group
9) MHIMAS.RASECH; MHS001MI/AddIntItmMst,ChgIntItmMst	The field indicates the procurement group for an item. If attribute listID is 'Buying Groups', populate PRGP.
10) MHIMAS.RAHIE1-RAHIE5;	
MHS001MI/AddIntItmMst,ChgIntItmMst 11) MHIMAS.RAALUC;	 Item discount group The field indicates the item discount group which are entered per item
MHS001MI/AddIntItmMst,ChgIntItmMst	in M3 and may be used as a control object for calculating customer
12) MHIMAS.RAEXPD; MHS001MI/AddIntItmMst,ChgIntItmMst	order line discounts. If attribute listID is 'Item Rebate Groups', populate DIGI.
13) MHIMAS.RAGRP1-RAGRP5;	
MHS001MI/AddIntItmMst,ChgIntItmMst 14) MHIMAS.RAVTCS;	 Configuration code The field indicates if the item is configured when ordered or
MHS001MI/AddIntltmMst,ChgIntltmMst	configured as a maintenance item.

15) MHIMAS.RAVTCD; MHS001MI/AddIntltmMst,ChgIntltmMst 16) MHIMAS.RARESP; MHS001MI/AddIntltmMst,ChgIntltmMst 17) MITFAC.M9CSNO; MMS200MI/UpdItmFac 18) MITFAC.M9ORCO; MMS200MI/UpdItmFac

.; /

- 0 = Not configurable
- 1 = Configurable
- 2 = Family Item
- 3 = Product variant
- 4 = Maint item
- 5 = Maint item WO
- 6 = Style
- 7 = SKU

If attribute listID is 'Configuration Code', populate CHCD.

3) Style

The field indicates the style number of the SKU. If attribute listID is 'Styles', populate ISTY or STYN.

9) Season control

The field indicates whether the season is checked during customer order entry. This sets how the item is processed during entry. If attribute listID is 'Season Control', populate SECH.

10) Hierarchy level 1 - 5

The field indicates item hierarchy, which groups items vertically in a way that describes a company's business. Item hierarchy provides a flexible and logical way to search for items and to group items for statistics and control purposes.

If attribute listID is 'Item Hierarchy', populate HIE1-HIE5.

11) Alternate U/M in use

The field indicates if and how alternate units of measure can be used for an item.

Set to 0 if 'Not Used'.

Set to 1 if 'Standard'.

Set to 2 if 'Item'.

If attribute listID is 'Alternate UOM In Use', populate ALUC.

12) Expiration date method

Set to 0 if 'No Expiry Date'.

Set to 1 if 'Receiving Date'.

Set to 2 if 'Production Date'.

Set to 3 if 'Receiving Date Recalculated'.

Set to 4 if 'Production Date Recalculated'.

If attribute listID is 'Expiration Date Method', populate EXPD.

13) Search group 1-5

The field indicates the search group which can be used as a complement to the item hierarchies. The purpose of the search group is to allow a horizontal search.

If attribute listID is 'Search Group', populate GRP1-GRP5.

14) Vat code sales

The field indicates the VAT code to be used for sold items. If attribute listID is 'VAT Code Sales, populate VTCS.

15) Vat code purchase

The field indicates the VAT code to be used for purchased items. If attribute listID is 'VAT Code Purchase, populate VTCP.

16) Responsible

The field indicates the user ID of the person responsible for the information found in the item file.

If attribute listID is 'Responsible', populate RESP.

17) Customs Statistical Number

The field indicates the customs statistics number, which is specified for each item/facility. It is used in printouts of various shipping documents, such as the unit document. It is also used for regulating and calculating data for transactions to INTRASTAT, the trade statistics of the EU.

If attribute listID is 'Customs Statistical Number', populate CSNO. Input from this element will only be considered if ItemLocation does not exist and partner from logicalID is fashionplm.

18) Country of Origin

The field indicates the item's country of origin.

If attribute listID is 'Country Of Origin', populate ORCO.

Input from this element will only be considered if ItemLocation does not exist and partner from logicalID is fashionplm.

@sequence

.; /

iteiiiwastei	
	The field indicates the classification code sequence attribute. This is used for the ordering of elements within a document. It identifies the hierarchical position of the identifier in case of multi-level codes.
@listID	1) If listID = 'Item Types', populate ITTY. 2) If listID = 'Item Groups', populate ITGR.
	3) If listID ='Product Groups', populate ITCL.
	4) If listID = 'Business Sectors', populate BUAR.
	5) If listID = 'Buying Groups', populate PRGP.
	If listID = 'Item Rebate Groups', populate DIGI.
	7) If listID = 'Configuration Code', populate CHCD.
	8) If listID = 'Styles', populate ISTY.
	9) If listID = 'Season Control', populate SECH. 10) If listID = 'Item Hierarchy', populate HIE1-HIE5.
	11) If listID = 'Alternate UOM In Use', populate ALUC.
	12) If listID = 'Expiration Date Method', populate EXPD.
	13) If listID = 'Search Group', populate GRP1-GRP5.
	14) If listID = 'VAT Code Sales, populate VTCS.
	15) If listID = 'VAT Code Purchase, populate VTCP.
	 If listID = 'Responsible', populate RESP. If listID = 'Customs Statistical Number', populate CSNO.
	18) If listID = 'Country Of Origin', populate ORCO.
ItemMaster/ItemMasterHeader/Specification/ID	,
MHIMAS.RASPE1 MHIMAS.RASPE2	The field indicates the user-specified information.
MHIMAS.RASPE3 MHIMAS.RASPE4	
MHIMAS.RASPE5.; MHS001MI /AddIntItmMst, ChgIntItmMst	
ItemMaster/ItemMasterHeader/Specification/Property/NameValue MHIMAS.RASPGV	1) Specific gravity
MHIMAS.RAPUPR	The field indicates the specific gravity (theoretical) of an item. An
MHIMAS.RASAPR.; MHS001MI/AddIntltmMst, ChgIntltmMst	item's specific gravity is the ratio of its density (mass divided by
	volume) to the density of water.
	If attribtute name is 'Specific Gravity', populate SPGV.
	2) Purchase price
	The field indicates the purchase price.
	If attribtute name is 'Purchase Price', populate PUPR.
	3) Sales price
	The field indicates the sales price.
	If attribtute name is 'Sales Price', populate SAPR.
@name	1) If name = !Specific Crovity! populate SDCV
	If name = 'Specific Gravity', populate SPGV. If name = 'Purchase Price', populate PUPR.
	3) If name = 'Sales Price', populate SAPR.
@currencyID	
MHIMAS.RACUCD	1) Currency
MHIMAS.RACUCS.; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates the currency. If attribute name is 'Purchase Price', populate CUCD.
	2) Currency - sales price
	The field indicates the currency in which the sales price (according to
	the item file) has been entered.
No contract the contract of th	If attribute name is 'Sales Price', populate CUCS.
ItemMaster/ItemMasterHeader/TrackingIndicator MHIMAS.RASTCD	The field indicates whether the stock kept for the item is accounted in
; MHS001MI/AddIntitmMst, ChgIntitmMst	inventory.
, wit 1000 Hill/Addititititivist, Originitititivist	Set to 0 if 'false'.
	Set to 1 if 'true'.
ItemMaster/ItemMasterHeader/ItemStatus/Code	Th. 6.11: P. 4. 41. 9. 4.
MHIMAS.RASTAT ; MHS001MI/AddIntltmMst, ChgIntltmMst	The field indicates the item status.
, wii 1000 Hell/Addittatiilelet, Oligiitatiilelet	Set to 10 if 'Pending'.
	Set to 20 if 'Open'.
	Set to 50 if 'DoNotReorder'.
ItemMaster/ItemMasterHeader/BaseUOMCode	Set to 90 if 'Obsolete'.
MHIMAS.RAUNMS	The field indicates the unit in which each item is recorded in
; MHS001MI/AddIntItmMst, ChgIntItmMst	inventory, even if alternate inventory units of measure are used. All
	balance information for the current item is always stored in this unit.
ItemMaster/ItemMasterHeader/BaseUOMPrecision MHIMAS.RADCCD; MHS001MI/AddIntltmMst, ChgIntltmMst	The field indicates how many decimal places are to be used in
wii inwiao.Nadood, wii 1900 nwii/addintitinwist, Ongintitinwist	connection with processing quantities. Zero to six decimal places may
	be used.
	Set to 0 if 0.
	Set to 1 if 0.1.

Iteminaster	
	Set to 2 if 0.01. Set to 3 if 0.001. Set to 4 if 0.0001. Set to 5 if 0.00001. Set to 6 if 0.000001.
Itam Maatay/Itam Maatay Haaday// IOMCadaCanyayaian/BataNumayia	331333113133331
ItemMaster/ItemMasterHeader/UOMCodeConversion/RateNumeric 1) MHIAUN.RFCOFA 2) MHIAUN.RFDMCF.; MHS015MI/AddIntItmAUM, ChgIntItmAum	Conversion factor The field indicates a factor that is used to convert a basic U/M to an alternate U/M.
	 Conversion form The field indicates how the conversion factor is used when converting from an alternate U/M to a basic U/M. Set DMCF (Conversion form) to 1 (Multiplication).
	Only AUTP (Alternate U/M type) = 1 (Alternate quantity U/M) is supported.
ItemMaster/ItemMasterHeader/UOMCodeConversion/ToUOMPackag	e/UOMCode
MHIAUN.RFALUN MHIALUN.RFAUTP	The field indicates an alternate unit of measure (U/M) for the basic U/M for an item.
.; MHS015MI/AddIntItmAUM, ChgIntItmAum	Set AUTP (Alternate U/M type) to 1 (Alternate quantity U/M).
	Use MMS200MI/LstItmAltUnitMs to verify which record is for add or update. Please note that delete is not yet supported since MMS015MI/Delete is not existing in 13.4.
ItemMaster/ItemMasterHeader/SerialControlIndicator MHIMAS.RAINDI; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates if the item is a serialized item. Value for M3 BE field Lot control method (INDI) is retrieved from agreement control property 'm3beLotControlMethod' with value 'default'. This means M3 logic will dictate the INDI value. If item template exists, INDI for the new item will be based on the item template.
	If SerialControlIndicator is 'true', user can overwrite the default value for m3beLotControlMethod with 2 or 5.
	If SerialControlIndicator is 'true' and m3beLotControlMethod is missing or value is not default, 2 or 5, INDI is set to 2.
ItemMaster/ItemMasterHeader/LotControlIndicator MHIMAS.RAINDI; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates if the item is a lotted item. Value for M3 BE field Lot control method (INDI) is retrieved from agreement control property 'm3beLotControlMethod' with value 'default'. This means M3 logic will dictate the INDI value. If item template exists, INDI for the new item will be based on the item template.
	If LotControlIndicator is 'true' and SerialControlIndicator is 'false' or missing, user can overwrite the default value for m3beLotControlMethod with 1 or 3.
	If LotControlIndicator is 'true', SerialControlIndicator is 'false' or missing and m3beLotControlMethod is missing or value is not default, 1 or 3, INDI is set to 3.
ItemMaster/ItemMasterHeader/ConfiguredItemIndicator MHIMAS.RACHCD; MHS001MI/AddIntltmMst, ChgIntltmMst	The field indicates if the item is configurable. Set to 0 if 'false'. Set to 1 if 'true'. If not given, default configuration code to 0.
ItemMaster/ItemMasterHeader/CatchWeightIndicator MHIMAS.RAACTI; MHS001MI/AddIntltmMst, ChgIntItmMst	The field indicates whether this is an active or a catch weight item. Set to 0 if "false". Set to 2 if "true".
ItemMaster/ItemMasterHeader/UserArea 1) MHIMAS.RACHCD; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates additional information that is not captured in OAGIS. The information are defined in UserArea/Property/NameValue which are determined by different name attributes.
2) MHIMAH.RGOPTX MHIMAH.RGOPTY MHIMAH.RGOPTZ; MHS200MI/AddIntSKU MMM076.HHOPTN; PDS061MI/AddSKUOption	1) If NameValue = Style and @name='StyleItemType', populate CHCD = 6. If NameValue = SKU and @name='StyleItemType', populate CHCD = 7. If @name='StyleItemType' is SKU and @name='CarryoverColor' is Yes, call the following APIs in order: -Set MMS016MI.Update STAT to 20 and retrieve value for SECH and
3) MMODFE.HUFTID MMODFE.HUFTID; MMS017MI/Add, Delete	SEA2 from ItemMasterHeader/ClassificationCodes/ Code@listID='Season Control'.

101111111111111111111111111111111111111	
MMM076.HHFTID; PDS061MI/AddSKUOption	-PDS061MI.AddSKUOption (loop for all feature/option combination) -PDS061MI.CreateSKU
4) MHIMAS.RACFI1; MHS001MI/AddIntltmMst, ChgIntltmMst MMODMA.HHSEA1;	If @name='StyleOptionX', populate OPTX. If @name='StyleOptionY', populate OPTY. If @name='StyleOptionZ', populate OPTZ.
MHS200MI/AddIntSKU MMM076.HHSTYN; PDS061MI/CreateSKU	3) If @name='StyleFeatureX', populate FTID. If @name='StyleFeatureY', populate FTID. If @name='StyleFeatureZ', populate = FTID.
5) MHIMAS.RACFI2-RACFI5; MHS001MI/AddIntltmMst, ChgIntltmMst	Use @sequence input to populate SQNU. 4) If @name = 'SeasonCode', populate CF1 for Style and populate
6) MMODMA.HHFM01-HHFM20; MHS200MI/ChgIntStyle	SEA1 or CF1 for SKU.
7) MHIMAS.RAACRF; MHS001MI/AddIntltmMst, ChgIntltmMst	5) If @name='ItemFreeField2', populate CFI2. If @name = 'Collection', populate CFI3. If @name = 'Gender', populate CF14. If @name = 'Division', populate CF15.
8) MHS200MI/AddIntSKU .; /	6) If @name ='StyleFreeField1' - 'StyleFreeField20', populate FM01-FM20.
	7) If @name = 'AccountingControlObject', populate ACRF.
	8) If @name = 'InterfaceStyleNumber', populate NSTY.
ItemMaster/ItemMasterHeader/SellableIndicator 1) MHIMAS.RASALE; MHS001/AddIntltmMst, ChgIntltmMst 2) MHIMAS.RASPUC; MHS001/AddIntltmMst, ChgIntltmMst.; /	1) Sales item The field indicates if the item is a sales item. Set to 0 if 'false'. Set to 1 if 'true'.
, ,	Fixed or dynamic sales price U/M The field indicates if the sales price U/M is fixed or dynamic If Sales item, set SPUC to 1.
ItemMaster/ItemMasterHeader/PackagingUnit/UnitCode MHIMAS.RAUNMS ; MHS001MI/AddIntItmMst, ChgIntItmMst	The field indicates the packaging unit of measure.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/WidthMeaster/PackagingUnit/Dimensions/WidthMeaster/PackagingUnit/Dimensions/WidthMeaster/PackagingUnit/Dimensions/WidthMeaster/PackagingUnit/Dime	sure The field indicates the item width.
CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for width. It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update width if external system unit code is equal to M3 BE unit code.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/LengthMea MHIMAS.RAILEN; MHS001MI/AddIntItmMst,ChgIntItmMst @unitCode	
CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for length. It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update length if external system unit code is equal to M3 BE unit code.
ItemMaster/ItemMasterHeader/PackagingUnit/Dimensions/HeightMea MHIMAS.RAIHEI; MHS001MI/AddIntItmMst,ChgIntItmMst @unitCode	asure The field indicates the item height.
CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for height. It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update height if external system unit code is equal to M3 BE unit code.
ItemMaster/ItemMasterHeader/PackagingUnit/NetWeightMeasure MHIMAS.RANEWE;	The field indicates the item net weight per basic U/M.
MHS001MI/AddIntItmMst, ChgIntItmMst MITMAS.MMNEWE; MMS200MI/UpdItmBasic.	If interface item number does not exist, MMS200MI.UpdItmBasic is called to update the net weight.
@unitCode CSYPAR.CPPARM ; CRS175MI/GetItemFreeFlds	The field indicates the general unit of measure for weights. It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update net weight if external system unit code is equal to M3 BE unit code.
ItemMaster/ItemMasterHeader/PackagingUnit/GrossWeightMeasure MHIMAS.RAGRWE; MHS001MI/AddIntltmMst, ChgIntltmMst	The field indicates the item weight per basic U/M including the weight of any product packaging material.
MITMAS.MMGRWE; MMS200MI/UpdItmBasic.; /	If interface item number does not exist, MMS200MI.UpdItmBasic is called to update the gross weight.
Infor May 26, 20	

@un	itCode

CSYPAR CPPARM

; CRS175MI/GetItemFreeFlds

The field indicates the general unit of measure for weights. It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update gross weight if external system unit code is equal to M3 BE unit code.

ItemMaster/ItemMasterHeader/PackagingUnit/TotalVolumeMeasure

MHIMAS.RAVOL3

; MHS001MI/AddIntItmMst, ChgIntItmMst

@unitCode

CSYPAR.CPPARM

; CRS175MI/GetItemFreeFlds

The field indicates the item volume per basic U/M including any product packaging material.

The field indicates the general unit of measure for volumes . It is stored in M3 BE, program CRS703 General Units of Measure. Translate unit code to M3 BE unit of measure. Only update total volume if external system unit code is equal to M3 BE unit code

ItemMaster/ItemMasterHeader/ProcurementParameters/ProcurementMethodCode

MHIMAS.RAMABU

; MHS001MI/AddIntItmMst, ChgIntItmMst

The field indicates whether the item is manufactured in-house or purchased.

. 1 = Manufacture 2 = Purchase

ItemMaster/ItemMasterHeader/ProcurementParameters/DefaultSource/SupplierParty/Party/Ds/ID

MHIMAS.RASUNO:

MHS001MI/AddIntItmMst, ChgIntItmMst

MITBAL.MBSUNO;

MMS200MI/UpdItmWhs.; /

The field indicates the supplier.

If ItemLocation element does not exist and partner from LogicalID is fashionplm, MMS200MI.SelltmWhsByltm is called to check the warehouses connected to the item. If record exists, MMS200MI.UpdItmWhs is called to update the Supplier for all the

warehouses connected.

ItemMaster/ItemMasterHeader/ProcurementParameters/LeadTimeDuration

MHIBAL.RBLEA1; MHS002MI/AddIntItmWhs, ChgIntItmWhs

The field indicates the supply lead time in days.

ItemMaster/ItemMasterHeader/SupplierItemSpecifics/SupplierParty/PartyIDs/ID

MITVEN.IDSUNO; PPS040MI/AddItemSupplier, DelItemSupplier

The field indicates the supplier number.

ItemMaster/ItemMasterHeader/Substitutions

@EffectiveDateTime

MHIALT.RHSTDT: MHS020MI/AddIntItmAlt. ChaintItmAlt

The field indicates the start date.

ItemMaster/ItemMasterHeader/Substitutions/Components/ItemID/ID

MHIALT.RHALIT; MHS020MI/AddIntItmAlt

The field indicates the related item number.

ItemMaster/ItemLocation/Classification/Codes/Code

1) MHIBAL.RBABCD

MHS002MI/AddIntItmWhs,ChgIntItmWhs

2) MHIBAL.RBRESP

MHS002MI/AddIntItmWhs, ChgIntItmWhs

3) MHIBAL.RBBUYE

MHS002MI/AddIntItmWhs, ChqIntItmWhs

4) MHIFAC.RCCSNO

MHS003MI/AddIntItmFac,ChgIntItmFac

MITFAC.M9CSNO MMS200MI/UpdItmFac 5) MHIFAC.RCORCO

.: /

@listID

.; /

MHS003MI/AddIntItmFac,ChgIntItmFac

1) ABC Code

The field indicates a code, usually A, B or C, used to group items according to how they affect the total sales volume. If attribute listID is 'ABC Codes', populate ABCD.

The field indicates the person responsible for acquisition of each item. respectively, per warehouse. Order proposals (planned orders) and shortage analyses are sorted and processed per planner. If attribute listID is 'Planner', populate RESP.

The field indicates the buyer normally responsible for purchasing. The buyer can, for example, be responsible for purchase orders, agreements, item/supplier combinations or item/warehouse combinations

If attribute listID is 'Buyer', populate BUYE.

4) Customs Statistical Number

The field indicates the customs statistics number, which is specified for each item/facility. It is used in printouts of various shipping documents, such as the unit document. It is also used for regulating and calculating data for transactions to INTRASTAT, the trade statistics of the EU.

If attribute listID is 'Customs Statistical Number', populate CSNO.

5) Country of Origin

The field indicates the item's country of origin.

If attribute listID is 'Country Of Origin', populate ORCO.

- 1) If listID 'ABC Codes', populate ABCD.
- 2) If listID 'Planner', populate RESP.
- 3) If listID 'Buyer', populate BUYE.
- 4) If list ID 'Customs Statistical Number', populate CSNO.
- 5) If listID 'Country Of Origin', populate ORCO.

ItemMaster/ItemLocation/LotSizeMultipler

MITBAL.MBUNMU; MHS002MI/AddIntItmWhs

ChgIntItmWhs

The field indicates the order multiple quantity. It is used in order to avoid the need to break up packages.

ItemMaster/ItemLocation/ItemStatus/Code

MITBAL.MBSTAT

81 May 26, 2023

itemWaster ; MHS002MI/AddIntitmWhs	The field indicates the item-warehouse status.
ChglntltmWhs	
	If 'Preliminary' or 'Pending', set Status (STAT) to 10.
	If 'Open', set Status (STAT) to 20.
	If 'DoNotReorder', set Status (STAT) to 50.
West Hard West Conference of the National Action Hard Con	If 'Obsolete', set Status (STAT) to 90.
ItemMaster/ItemLocation/ItemValue/CostingMethodCode MITFAC.M9VAMT	The field indicates the inventory accounting method that defines how
; MHS003MI/AddIntItmFac	the cost of an item is determined per item/facility.
ChgintitmFac	the cost of an item is determined per item/racinty.
Ong. Man ac	Set to 'Standard' if Inventory accounting method (VAMT) = 1.
	Set to 'WeightedAverage' if Inventory accounting method (VAMT) = 2
ItemMaster/ItemLocation/ShelfLifeDuration	
MITBAL.MBSLDY	The field indicates the number of days shelf life for a lot or serial
; MHS002MI/AddIntItmWhs	number measured from the production date to expiration date.
ChgIntItmWhs	
ItemMaster/ItemLocation/WarehouseLocation/ID	
MHIBAL.RBWHLO;	This field indicates the warehouse where the item is connected.
MHS002MI/AddIntItmWhs, ChgIntItmWhs	
MITBAL.MBWHLO;	Use MHS002MI/LstIntItmWhs and MMS200MI/LstIntItmWhsByItm to
MMS200MI/DititmWhs	verify which record is for add, update or delete.
• /	
ItemMaster/ItemLocation/ProcurementParameters/ProcurementMetho	dCode
MITBAL.MBPUIT; MHS002MI/AddIntItmWhs	The field indicates how acquisition is performed for requirements
ChgIntItmWhs	(immediate or planned) for each item/warehouse.
	0.44 114 (4.44 144 144 144 144 144 144 144 144 14
	Set to 'Manufacture' if Acquisition code (PUIT) = 1.
	Set to 'Purchase' Acquisition code (PUIT) = 2. Set to 'Transfer' Acquisition code (PUIT) = 3.
	Set to 'Maintenance' Acquisition code (PUIT) = 6.
ItemMaster/ItemLocation/ProcurementParameters/DefaultSource/Supp	· · · · · · · · · · · · · · · · · · ·
MHIBAL.RBSUNO; MHS002MI/AddIntItmWhs,ChgintItmWhs	This field indicates the supplier.
ItemMaster/ItemLocation/ProcurementParameters/OrderPointQuantity	,
MITBAL.MBREOP; MHS002MI/AddIntltmWhs	The field indicates the reorder point. When the on-hand balance is
ChgIntItmWhs	equal to or below the level displayed in this element, a planned order
	is automatically created.
ltemMaster/ltemLocation/ProcurementParameters/OrderPointBaseUO	MQuantity
MHIBAL.RBREOP; MHS002MI/AddIntItmWhs,ChgIntItmWhs	The field indicates the reorder point. When the on-hand balance is
	equal to or below the level displayed in this field, a planned order is
	automatically created.
	The reorder point is calculated either manually or as the safety stock
	plus usage during the lead time.
ItemMaster/ItemLocation/ProcurementParameters/SafetyStockQuantit	
MITBAL.MBREOP; MHS002MI/AddIntitmWhs	The field indicates the safety stock. This is a buffer quantity which is
ChgIntItmWhs	only used during unexpected circumstances such as increased
- J	demand, difficulties in delivery, etc.
ltemMaster/ItemLocation/ProcurementParameters/SafetyStockBaseUC	
MHIBAL.RBSSQT; MHS002MI/AddIntItmWhs,ChgIntItmWhs	The field indicates a buffer quantity which is only used during
	unexpected circumstances such as increased demand, difficulties in
	delivery, etc.
temMaster/ItemLocation/ProcurementParameters/EOQBaseUOMQuar	
MITBAL.MBEOQT; MHS002MI/AddIntItmWhs	The field indicates the Economic Order Quantity (EOQ). It is a type of
ChgIntItmWhs	fixed-order quantity that determines the amount of an item to be
	purchased or manufactured at one time.
ItemMaster/ItemLocation/ProcurementParameters/LeadTimeDuration	
MHIBAL RBI FA1: MHS002MI/AddIntItmWhs. ChaintItmWhs	The field indicates the supply lead time in days

 $MHIBAL.RBLEA1; \, MHS002MI/AddIntItmWhs, \, ChgIntItmWhs$

The field indicates the supply lead time in days.

82 Infor May 26, 2023

Location

LUCATION	
Location/Location @type	
	For Facility: The field indicates the location type. Process this BOD if type = "Site".
	For Warehouse: The field indicates the location type. Process this BOD if type = "Warehouse".
Location/ID	
For Facility: CFACIL.CFFACI; CRS008MI/AddFacility	For Facility: The field indicates the facility.
For Warehouse: MITWHL.MWWHLO; MMS005MI/AddWarehouse, UpdWarehouse,	For Warehouse: The field indicates the warehouse ID.
CIADDR.OAADK2; CRS235MI/Add, Upd, Dlt.; /	Add, update and delete of address will only be applicable if Internal address type (ADTH) = 1 and Address key 2 (ADK2) = WHLO.
	Default ADTH value to 1.
Location/Name For Facility: CFACIL.CFFACN; CRS008MI/AddFacility, ChgFacility	For Facility: The field indicates the facility name.
For Warehouse: MITWHL.MWWHNM; MMS005MI/AddWarehouse, UpdWarehouse	For Warehouse: The field indicates the warehouse name.
Location/Address	
@type	For Warehouse: The field indicates the location address type. Set to "text".
Location/Address/AddressLine	
For Warehouse: CIADDR. OAADR1 CIADDR. OAADR2 CIADDR. OAADR3	For Warehouse: The field indicates the address line.
CIADDR. OAADR4.; CRS235MI/Add, Upd @sequence	For Warehouse:
	The field indicates the address line sequence number.
Location/Address/CityName For Warehouse: CIADDR.OATOWN; CRS235MI/Add, Upd	For Warehouse: The field indicates the city.
Location/Address/CountrySubDivisionCode	
For Warehouse: CIADDR.OAECAR; CRS235MI/Add, Upd	For Warehouse: The field indicates the country subdivision code.
Location/Address/CountryCode For Warehouse: CIADDR.OACSCD; CRS235MI/Add, Upd	For Warehouse: The field indicates a country.
Location/Address/PostalCode For Warehouse:	For Warehouse:
CIADDR.OAPONO; CRS235MI/Add, Upd	The field indicates a postal code for a specific address.
Location/ParentLocation/ID For Facility: CFACIL.CFGFAC; CRS008MI/AddFacility, ChgFacility	For Facility: The field indicates the global facility used to accumulate the balance per item from several facilities.
For Warehouse: MITWHL.MWFACI; MMS005MI/AddWarehouse	For Warehouse: The field indicates the facility.
Location/Classification/Codes/Code	
For Facility:	For Facility:
1) CFACIL.CFWHLO 2) CFACIL.CFACGR	The field indicates the main warehouse. The field is used to restrict access to different objects such as
3) CFACIL.CFPYAD 4) CFACIL.CFFANM.; CRS008MI/AddFacility, ChgFacility	accounting identities, divisions, and facilities. 3) The field indicates the invoicing address. 4) The field indicates a numeric name for the facility. The facility
For Warehouse: 1) MITWHL.MWWHTY 2) MITWHL.MWWHSY	numeric name is a numeric identifier for the facility and can be used as part of the invoice number when the invoice number only allows numbers.
3) MITWHL.MWPHNO 4) MITWHL.MWCOMA 5) MITWHL.MWSDES	For Warehouse: The field indicates the classification code value.
6) MITWHL.MWLNCD 7) MITWHL.MWRESP 8) MITWHL.MWTWSL	Warehouse type The field indicates the grouping of warehouses of the same type.It
9) MITWHL.MWCDYN 10) MITWHL.MWDDLO;	also determines whether the warehouse balance should be accumulated by facility level.

Location

MMS005MI/AddWarehouse. UpdWarehouse 11) CIADDR.OACONM; CRS235MI/Add, Upd .; /

@sequence

@listID

2) Warehouse subtype

The field indicates the warehouse subtype, and is used to differentiate warehouses within each type.

3) Telephone number

The field indicates the warehouse's telephone number that is printed on the freight document in the dispatch routine.

4) Communication address

The field indicates the sender's address printed on digital documents (purchase orders, and such) issued from this warehouse.

5) Place of loading

The field indicates the ID of the geographic location, or place, for the transportation loading operation.

6) Language

The field indicates the language in which external documents are to be printed.

7) Responsible

The field indicates a unique user ID.

The field indicates a destination location for a stock transaction. Only applicable for update for now.

9) Cross-dock

The field indicates if cross-docking is activated or not. Set to "1" if activated.

Only applicable for update for now.

10) Dock Location

The field indicates the default docking location for cross-docking.

11) Company Name

The field indicates the name of the company.

For Facility:

The field indicates the classification code sequence.

For Facility:

- 1) If "Main Warehouse", populate WHLO.
- 2) If "Object Access Group", populate ACGR.
- 3) If "Invoicing Address", populate PYAD.
- 4) If "Facility Numeric Name", populate FANM.

For Warehouse:

The field indicates the classification code listID.

If "Location Type", populate WHTY.
If "Location Sub Type", populate WHSY.
If "Phone", populate PHNO.

If "Communication Address", populate COMA. If "Place Of Load", populate SDES.

If "Language", populate LNCD.

If "Responsible", populate RESP.
If "To Location", populate TWSL.

If "Cross-dock", populate CDYN.

If "Dock Location", populate DDLO. If "Company Name", populate CONM.

May 26, 2023

M3EDIAdvanceShipNotice

M3EDIAdvanceShipNotice/TradingPartnerID	The field indicates the trading partner ID.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentID/ID	The held indicates the trading parties to.
MHIHED.G0SUDO; MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine PDNHEA.IHSUDO;	The field indicates the Delivery note number. This must be unique in combination with Supplier (SUNO).
PPS360MI/GetHead, DltHead.; /	To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DitHead. Once PPS360 record is deleted, LoadAdvanceShipNotice may be generated again using the same Delivery note number.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentDate	
MHIHED.G0DNDT; MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine PDNHEA.IHDNDT; PPS360MI/GetHead, DltHead.; 1) PPS360MI 2) MHS850MI/1) GetHead 2)AddWhsHead	The field indicates the Delivery Note date
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentReference	rence
	If set to 'Shipper', use DocumentReference/DocumentID input to populate SUDO. Else, populate PUSN.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/DocumentRefer	
MHIHED.G0PUSN; MHS850MI/AddWhsHead, MHIHED.G0SUNO; MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine .; 1) PPS360MI/1) GetHead	The field indicates the Delivery note reference (PUSN) if @type is blank. If @type='Shipper', the field indicates the Delivery note (SUDO).
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/WarehouseLoc	ation/ID
MHIHED.GOWHLO;	The field indicates the warehouse of the company.
MHS850MI/AddWhsHead PDNHEA.IHWHLO; PPS360MI/GetHead, DltHead.; PPS360Mi/GetHead	To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, LoadAdvanceShipNotice may be generated again using the same Delivery note number.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ActualShipDate MHIHED.G0SHD4 MHIHED.G0SHTM.; MHS850MI/AddWhsHead	-
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ScheduledDelivMHIHED.G0DLDTMHIHED.G0DLTM.; MHS850MI/AddWhsHead	veryDateTime The field indicates the Planned delivery date and time.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/GrossWeightMo	easure The field indicates the Gross weight for the entire ASN.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/Transportations MHIHED.G0MODL; MHS850MI/AddWhsHead	MethodCode The field indicates the TransportaionMethodCode.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/ShipFromParty. CPAALI.CKPAAL; CRS8866MI/CnvPtrAlias	/PartyIDs/ID The field indicates the supplier ID. The data can be translated in CRS885/CRS886.
MHIHED.G0SUNO; MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine PDNHEA.IHSUNO; PPS360MI/GetHead, DltHead.; CRS620MI/GetBasicData	To handle the update functionality of Supplier Delivery Note, check if PPS360 record exists by using PPS360MI/GetHead. If record exists, use PPS360MI/DltHead. Once PPS360 record is deleted, LoadAdvanceShipNotice may be generated again using the same Delivery note number.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/Transportation	Term/IncotermsCode
MHIHED.G0TEDL; MHS850MI/AddWhsHead	The field indicates the delivery terms.
M3EDIAdvanceShipNotice/AdvanceShipNoticeHeader/UserArea MHIHED.G0E0PA MHIHED.G0E0PB;	If @name='ISASender', input to E0PA. If @name='ISAReceiver', input to E0PB.
MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine	Otherwise, use logicalID as input.
MHIHED.G0ADID; MHS850MI/AddWhsHead.; MHS850MI/AddWhsHead	d If @name='AddressNumber', the element refers to a pickup address ID.
M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ItemID/ID MHILIN.G2ITNO	The field indicates the item number.
.; MHS850MI/AddWhsLine	
@schemeName .; MHS850MI/AddWhsLine	Set to 'System' or blank, use ItemID/ID as M3 Item number. Set to 'Supplier' if ItemID used SITE.
M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ShippedQuantity MHILIN.G2DLQA; MHS850MI/AddWhsLine	The field indicates the purchase order quanity expressed in the PO unit of measure.

M3EDIAdvanceShipNotice @unitCode MHILIN.G2ALUN; MHS850MI/AddWhsLine The field indicates the same unit of measure as on the order. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/ShippedBaseUOMQuantity MHILIN.G2DLQT; MHS850MI/AddWhsLine The field indicates the quantity in local unit of measure. @unitCode MHILIN.G2UNIT; MHS850MI/AddWhsLine The field indicates the local unit of measure. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/DocumentID/ID MHILIN.G2RIDN; MHS850MI/AddWhsLine The field indicates the reference purchase order number. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/LineNumber MHILIN.G2RIDL The field indicates the concantenation of order line and line suffix MHILIN.G2RIDX.; MHS850MI/AddWhsLine where the last 3 digits is the line sufix M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/PurchaseOrderReference/Quantity MHILIN.G2RVQA; MHS850MI/AddWhsLine The field indicates the received quantity. @unitCode MHILIN.G2PUUN; MHS850MI/AddWhsLine The field indicates the unit of measure cod can be translated using the translation table in CRS881. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference @type If set to 'Shipper', use DocumentReference/DocumentID input to populate SUDO. Else, populate PUSN. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/DocumentReference/DocumentID/ID MHIHED.G0PUSN; The field indicates the Delivery note reference (PUSN) if @type is MHS850MI/AddWhsHead, blank. If @type='Shipper', the field indicates the Delivery note MHIHED GOSUNO: (SUDO). MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/Lot/IDs/ID MHILIN.G2BANO; MHS850MI/AddWhsLine The field indicates the lot number. M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/Quantity MHILIN.G2DLQA; MHS850MI/AddWhsLine The field indicates the alternative unit of measure in quantity. @unitCode MHILIN.G2ALUN; MHS850MI/AddWhsLine The field indicates the alternative unit of measure M3EDIAdvanceShipNotice/AdvanceShipNoticeItem/SerializedLot/Lot/BaseUOMQuantity The field indicates the basic unit of measure in quantity. MHILIN.G2DLQT; MHS850MI/AddWhsLine @unitCode MHILIN.G2UNIT; MHS850MI/AddWhsLine The field indicates the basic unit of measure. M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ContainerID MHIPAC.G1PACN; MHS850MI/AddWhsPack The field indicates the alternative unit of measure package number. A dummy package will be created in M3 if no package information is sent (i.e. element AdvanceShipNoticeUnit not available) M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ScheduledDeliveryDateTime MHIHED.G0DLDT The field indicates the Planned delivery date and time. MHIHED.G0DLTM.; MHS850MI/AddWhsHead M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/GrossWeightMeasure MHIHED.G0GRWE; MHS850MI/AddWhsHead The field indicates the Gross weight for the entire ASN M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/TransportationMethodCode MHIHED.G0MODL; MHS850MI/AddWhsHead The field indicates the TransportaionMethodCode. M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/TransportationTerm/IncotermsCode MHIHED.G0TEDL; MHS850MI/AddWhsHead The field indicates the delivery terms M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShippingMaterial/ID MHIPAC.G1PACT; MHS850MI/AddWhsPack The field indicates the alternative unit of measure packaging. M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitContainer/ContainerID The field indicates the package included. A list of package relationship is maintained (Package ID from ShipmentUnitContainer/ ContainerID and Parent Package Id). After all packages are created via MHS850MI, this list will be considered and all child packages are updated with their parent package. M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitContainer/ParentContainerID MHIPAC.G1PACC; MHS850MI/AddWhsPack The field indicates the parent package. Parent package must be defined as a Container ID first M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ItemID/ID MHILIN.G1ITNO; MHS850MI/AddWhsLine The field indicates the item number. @schemeName Set to 'System' or blank, use ItemID/ID as M3 Item number. Set to 'Supplier' if ItemID used SITE. M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedQuantity MHILIN.G2DLQA; MHS850MI/AddWhsLine The field indicates the delivered quantity in alternate unit of measure. @unitCode

M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/ShipmentUnitItem/ShippedBaseUOMQuantity MHILIN.G2DLQT; MHS850MI/AddWhsLine

MHILIN.G2ALUN; MHS850MI/AddWhsLine

The field indicates the quantity in basic unit of measure for the specific item in a specific package.

@unitCode

May 26, 2023

The field indicates the alternative unit of measure

M3EDIAdvanceShipNotice	
MHILIN.G2UNIT; MHS850MI/AddWhsLine	The field indicates the basic unit of measure for the item
M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/Shipmen	tUnitItem/PurchaseOrderReference/DocumentID/ID
MHILIN.G2RIDN; MHS850MI/AddWhsLine	The field indicates the Purchase order number.
M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/Shipmen	tUnitItem/PurchaseOrderReference/LineNumber
MHILIN.G2RIDL	The field indicates the concantenation of order line and line suffix
MHILIN.G2RIDX.; MHS850MI/AddWhsLine	where the last 3 digits is the line sufix.
M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/Shipmen	tUnitItem/SerializedLot/Lot/LotIDs/ID
MHILIN.G2BANO; MHS850MI/AddWhsLine	The field indicates the lot number.
M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/Shipmen	tUnitItem/SerializedLot/Lot/Quantity
MHILIN.G2DLQA; MHS850MI/AddWhsLine	The field indicates the delivered quantity in alternate unit of measure.
@unitCode	
MHILIN.G2ALUN; MHS850MI/AddWhsLine	The field indicates the alternative unit of measure.
M3EDIAdvanceShipNotice/AdvanceShipNoticeUnit/Shipmen	
MHILIN.G2DLQT; MHS850MI/AddWhsLine	The field indicates the delivered quantity in basic unit of measure.
@unitCode	
MHILIN.G2UNIT; MHS850MI/AddWhsLine	The field indicates the basic unit of measure.

Infor May 26, 2023 87

M3EDICustomerRemittanceAdvice

M3EDICustomerRemittanceAdvice/TradingPartnerID

The field indicates the trading partner ID. The value of the element reflects as the partner in MEC. Max length is 40 char.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: M3EDI Vers: 1

Message: Generic

I/O: I

Parent element(s): Generic Data element: TradingPartnerID

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/DocumentID/ID

FABHED.V1STMN

FABHED.V1BSRE.; ABS100MI/AddStatmtHead

The field indicates the number of a statement of account from the customer. It will populate Statement no field in ABS100 if ABS900/E field Bank statm no=1-According to bank for relevant Bank identifier. It will also populate Transaction reference number field in ABS100/E.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/DocumentDateTime

FABHED.V1BSOT

FABHED.V1BSCT.; ABS100MI/AddStatmtHead

The field indicates the bank statement's opening and closing balance dates in fields OB date and Closing bal date in ABS100/F.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/InitiatingParty/Party/Ds/ID

FABLIN.V2PYNO; ABS100MI/AddStatmLine

The field indicates the Customer. If the value for Payer is not provided in PayFromParty/PartyIDs/ID element, Customer value will be used for Payer.

The value can be translated in CRS881/882.

It can be defined on the division or on the company level.

Msg std: M3EDI

Vers: 1

Message: Generic

I/O: I

Parent element(s): CustomerParty

Data element: PartyID

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/PayFromParty/PartyIDs/ID

FABLIN.V2PYNO: ABS100MI/AddStatmLine

The field indicates the Payer.

The value can be translated in CRS881/882.

It can be defined on the division or on the company level.

Msg std: M3EDI Vers: 1

Message: Generic I/O: I

Parent element(s): PayFromParty

Data element: PartyID

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/FinancialParty/FinancialAccount/ID

FABIDE.V5BSID,

FABHED.V1BSID.; ABS100MI/GetBankIdent2,

ABS100MI/AddStatmHead/

The field indicates the Bank identifier (BSID) with Bank stmnt type=2-Payment specif in ABS900 that have to be pre-configured to locate Bank account ID (BKID) and its Company and Division. Bank identifier (BSID) can be defined on Division or on the Company level.

Used as 1st priority.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/FinancialParty/FinancialAccount/BBANID

FABIDE.V5BSID.

FABHED.V1BSID.; ABS100MI/GetBankIdent2,

ABS100MI/AddStatmHead/

The field indicates the Bank identifier (BSID) with Bank stmnt type=2-Payment specif in ABS900 that have to be pre-configured to locate Bank account ID (BKID) and its Company and Division. Bank identifier (BSID) can be defined on Division or on the Company level.

Used as 3rd priority with prefix 'EDIREM' if FinancialAccount/ID and FinancialAccount/IBANID are not provided.

E.g. if BBANID = '50000000058398257466', Bank identifier (BSID) = 'EDIREM50000000058398257466' have to be defined in ABS900, with Bank stmnt type=2-Payment spec, on Division or on Company

If none of FinancialAccount/ID, FinancialAccount/IBANID, FinancialAccount/ID and FinancialAccount/BBANID are provided, Bank identifier (BSID) will be set to hardcoded value 'EDIREM'

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceHeader/FinancialParty/FinancialAccount/IBANID

FABIDE.V5BSID,

FABHED.V1BSID.; ABS100MI/GetBankIdent2,

ABS100MI/AddStatmHead/

The field indicates the Bank identifier (BSID) with Bank stmnt type=2-Payment specif in ABS900 that have to be pre-configured to locate Bank account ID (BKID) and its Company and Division. Bank identifier (BSID) can be defined on Division or on the Company level.

Used as 2nd priority with prefix 'EDIREM' if FinancialAccount/ID is not provided.

May 26, 2023

M3EDICustomerRemittanceAdvice

E.g. if IBANID = 'AT483200000012345864', Bank identifier (BSID) = 'EDIREMAT483200000012345864' have to be defined in ABS900, with Bank stmnt type=2-Payment spec, on Division or on Company level.

${\it M3EDICustomer Remittance Advice/Customer Remittance Advice Header/Total Amount}$

@currencyID

FABHED.V1CUCD; ABS100MI/AddStatmHead

The field indicates the currency.

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: I

Parent element(s): Generic Data element: Currency

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/LineNumber

FABLIN.V2BLSN; ABS100MI/AddStatmLine

The field indicates line number.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/DocumentReference

@type

The field indicates type of the referenced document. Only document reference with type 'Invoice' or document reference without type attribute are consumed.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/DocumentReference/DocumentID/ID

FABDET.V3CINO,

FABDET.V3INYR.; ABS100MI/AddStatmDetail

The field indicates concatenation of customer invoice year INYR<4> and customer invoice number CINO<15> . It references DocumentID

in SyncInvoice BOD.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/PaymentAmount

FABLIN.V2BLLF

FABDET.V3BLNF.; ABS100MI.AddStmLine,

ABS100MI.AddStmDetail/

The field indicates the line amount, after line charges and discounts. E.g. If Invoice amount is 10 USD, Charge amount is 2 USD and Discount amount is -3 USD, Payment amount will be 10 + 2 +(-3) = 9 USD

Payment amount is also used to calculate the Net amount (BLNF) of the first detail line like this: Payment amount - Charge amount + (-1* Discount amount) where Payment amount and Charge amount are expected to be positive and Discount amount expected to be negative.

For the previous example, BLNF = 9 - 2 + (-1*-3) = 9 - 2 + 3 = 10 USD, and this amount is expected to be equal to referenced Invoice amount.

Referenced Invoice will be reconciliated using Business transaction code BLBC = 'EDIPAY' which has to be defined in ABS020 Business Transaction Code. Open and in ABS910 Scenario Number. Prioritize together with Bank account ID (BKID) for provided Bank identifier (BSID) (see FinancialParty/FinantialAccount elements).

Scenario for Invoice reconciliation that is configured in ABS910 for Business transaction code 'EDIPAY' has to be defined in ABS911 Scenario Number. Open.

Sum of all positive line Payment amounts for all lines is used to set Total Debit Amount(ABS100MI/UpdStatmtHead.BSTD) on the statement header (positive amount). Sum of all negative line Payment amounts for all lines is used to set Total Credit Amount (ABS100MI/UpdStatmtHead.BSTC) on the statement header (negative amount).

@currencyID

FABLIN.V2CUCD; ABS100MI/AddStmLine

The field indicates the currency of the Payment Amount .

The value can be translated in CRS881/882. It can be defined on the company level only.

Msg std: ION Vers: 1

Message: Generic

I/O: I

Parent element(s): Generic Data element: Currency

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/DiscountTakenAmount

FABDET.V3BLNF; ABS100MI/AddStmDetail

The field indicates the line Discount amount, put as negative Net amount on the detail line.

Discount amount is also used to calculate the Net amount (BLNF) of the first detail line like this: Payment amount - Charge amount + (-1* Discount amount) where Payment amount and Charge amount are expected to be positive and Discount amount expected to be negative.

Business transaction code BLBC = 'EDIDIS' has to be defined in ABS020 Business Transaction Code. Open and in ABS910 Scenario

M3EDICustomerRemittanceAdvice

Number. Prioritize together with Bank account ID (BKID) for provided Bank identifier (BSID) (see FinancialParty/FinantialAccount

elements).

Scenario that is configured in ABS910 for Business transaction code 'EDIDIS' has to be defined in ABS911 Scenario Number. Open to put

discount amount on an appropriate account.

@currencyID

@currencyID

The field indicates the currency of the Discount amount. It is expected to be the same as currency for Payment Amount .

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/PenaltyTakenAmount

FABDET.V3BLNF; ABS100MI/AddStmDetail

The field indicates the line Charge amount, put as positive Net amount on the detail line.

Charge amount is also used to calculate the Net amount (BLNF) of the first detail line like this: Payment amount - Charge amount + (-1* Discount amount) where Payment amount and Charge amount are expected to be positive and Discount amount expected to be negative.

Business transaction code BLBC = 'EDICHA' has to be defined in ABS020 Business Transaction Code. Open and in ABS910 Scenario Number. Prioritize together with Bank account ID (BKID) for provided Bank identifier (BSID) (see FinancialParty/FinantialAccount elements).

Scenario that is configured in ABS910 for Business transaction code 'EDICHA' has to be defined in ABS911 Scenario Number. Open to put charge amount on an appropriate account.

The field indicates the currency of the Charge amount. It is expected to be the same as currency for Payment Amount

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/BookingDateTime

FABLIN.V2ACDT; ABS100MI/AddStmLine The field indicates the accounting date.

M3EDICustomerRemittanceAdvice/CustomerRemittanceAdviceLine/ValueDateTime

FABLIN.V2CURD; ABS100MI/AddStmLine The field indicates the value date.

May 26, 2023

M3EDICustomerReturn

M3EDICustomerReturn/TradingPartnerID	
-	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDICustomerReturn/CustomerReturnHeader/AlternateDoc	
OCHEAD.OCRORN; OIS390MI/AddHead	The field indicates the customer order number.
M3EDICustomerReturn/CustomerReturnHeader/CustomerPart OCHEAD.OCCUNO; OIS390MI/AddHead	ty/PartyIDs/ID The field indicates the customer number.
M3EDICustomerReturn/CustomerReturnHeader/ShipToParty/I OCHEAD.OCWHLO OCLINE.ODWHLO.; OIS390MI/AddHead, AddLine	Location/ID The field indicates the warehouse.
M3EDICustomerReturn/CustomerReturnHeader/PayFromParty	
OCHEAD.OCPYNO; OIS390MI/AddHead	The field indicates the customer ID who receives the invoice.
M3EDICustomerReturn/CustomerReturnHeader/PromisedReturnCUSTOMERCONTINUES OCHEAD.OCEPDT; OIS390MI/AddHead	urnDateTime The field indicates the promised return date.
M3EDICustomerReturn/CustomerReturnHeader/RequiredReturnOCHEAD.OCEPDT; OIS390MI/AddHead	urnDateTime The field indicates the required return date.
M3EDICustomerReturn/CustomerReturnHeader/ReturnReason OCHEAD.OCRSCD; OIS390MI/AddHead	nCode The field indicates the transaction reason code.
M3EDICustomerReturn/CustomerReturnLine/LineNumber OCLINE.ODRORL; OIS390MI/AddLine	The field indicates the reference order line number.
M3EDICustomerReturn/CustomerReturnLine/Item/ItemID/ID OCLINE.ODITNO; OIS390MI/AddLine	The field indicates the item number.
M3EDICustomerReturn/CustomerReturnLine/Item/Classification	on/Codes/Code
OCLINE.ODWHSL; OIS390MI/AddLine	The field indicates the location where the returned items will be placed.
@listID	Set to 'Location'.
M3EDICustomerReturn/CustomerReturnLine/Item/SerializedLo OCLINE.ODBANO; OIS390MI/AddLine	ot/Lot/LotIDs/ID The field indicates the lot number, which is an ID of a manufactured or purchased quantity of an item.
M3EDICustomerReturn/CustomerReturnLine/Quantity OCLINE.ODREQ0; OIS390MI/AddLine	The field indicates the returned quantity.
M3EDICustomerReturn/CustomerReturnLine/UnitPrice/Amour OCLINE.ODSAPR; OIS390MI/AddLine	· · · · · ·
M3EDICustomerReturn/CustomerReturnLine/PromisedReturn	nDateTime
OCHEAD.OCEPDT; OIS390MI/AddLine	The field indicates the promised return date for the order line.
M3EDICustomerReturn/CustomerReturnLine/RequiredReturnline/CHEAD.OCEPDT; OIS390MI/AddLine	DateTime The field indicates the required return date order line.
M3EDICustomerReturn/CustomerReturnLine/ReturnReasonCo OCLINE.ODRSCD; OIS390MI/AddLine	ode The field indicates the transaction reason code of the order line.

M3EDIInventoryAdjustment

M3EDIInventoryAdjustment/TradingPartnerID	
	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDIInventoryAdjustment/InventoryAdjustmentHeader/DocumentID MMIHED.I0PMSN ; MMS850MI/AddStkHead @Iocation	/ ID The field indicates the external message number.
MMIHED.I0WHLO; MMS850MI/AddStkHead	The field indicates the warehouse ID.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/LineNumber MMIIDE.I1MSLN; MMS850MI/AddStkId	The field indicates the line number.
MMIINS.I2MSLN; MMS850MI/AddStkIns.; /	
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Note MMIINS.I2BREM ; MMS850MI/AddStkIns	The field indicates the remark.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/WarehouseLoc MMIIDE.I1WHLO; MMS850MI/AddStkId	ation/ID The field indicates the warehouse ID.
MMIINS.I2WHLO; MMS850MI/AddStkIns.; /	
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/ItemID/ID MMIIDE.I1ITNO ; MMS850MI/AddStkId	The field indicates the item number.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/CustomerI MMIIDE.I1POPN; MMS850MI/AddStkId	temID/ID The field indicates the customer's item number. If this field is populated set ALWT to 6.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/UPCID MMIIDE.I1POPN; MMS850MI/AddStkId	The field indicates the alias number. If this field is populated set ALWT to 2 and ALWQ to UPC.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/EPCID MMIIDE.I1POPN; MMS850MI/AddStkId	The field indicates the alias number. If this field is populated set ALWT to 2 and ALWQ to EA13.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/Description MMIIDE.I1FUDS; MMS850MI/AddStkld	<i>n</i> The field indicates the item description.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/Classificat MMIIDE.IWHSL; MMS850MI/AddStkId	 tion/Codes/Code 1.) The field indicates the location if attribute @listID = 'Location'. 2.) The field indicates the container ID if attribute @listID = 'Container
MMIIDE.ICAMU; MMS850MI/AddStkId.; MMS850MI/AddStkId @ <i>listID</i>	
	Set to 'Location' to populate location (WHSL). Set to 'Container' to populate container (CAMU).
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/SerializedI MMIIDE.I1BANO ; MMS850MI/AddStkId	Lot/Lot/Lot/Ds/ID The field indicates the lot number.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/SerializedI MMIINS.I2QLQT ; MMS850MI/AddStkIns @unitCode	Lot/Lot/Quantity The field indicates the quantity.
MMIINS.I2QLUN ; MMS850MI/AddStkIns	The field indicates the qualifier unit of measure.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Item/SerializedI MMIINS.I2BREF MMIINS.I2BRE2.; MMS850MI/AddStkIns @noteID	Lot/Note 1) The field indicates lot reference 1. 2) The field indicates lot reference 2.
	1) Set to 'Lot Reference 1'. 2) Set to 'Lot Reference 2'.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/Quantity MMIINS.I2QLQT ; MMS850MI/AddStkIns	The field indicates the quantity. It is only relevant if InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/Quantity is empty.
@unitCode MMIINS.I2QLUN ; MMS850MI/AddStkIns	The field indicates the qualifier unit of measure. It is only relevant if InventoryAdjustment/InventoryAdjustmentLine/Item/SerializedLot/Lot/Quantity@unitCode is blank.
M3EDIInventoryAdjustment/InventoryAdjustmentLine/ReasonCode MMIINS.I2RSCD ; MMS850MI/AddStkIns	The field indicates the reason code for the transaction.

M3EDIPurchaseOrder/TradingPartnerID	
MSEDIF UtchaseOrder/TradingFartherib	The field indicates the trading partner ID. The value of the element reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentID/ID 1) MXHEAD.IAHREF; PPS370MI AddHead 2) MPHEAD.IAPUNO; PPS001MI ConfirmLine.; /	The field indicates the purchase order header reference used by the supplier.
	The field indicates the unique number that is assigned to a purchase order when it is created.
	To determine whether to use PPS001MI Confirm or PPS370MI AddHead, use PPS200MI Get to check if Purchase number (PUNO) already exists. If it does, use Confirm. Otherwise, use PPS370MI AddHead.
@location MXHEAD.IAWHLO; PPS370MI /AddHead	The field indicates the warehouse.
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentReference	The field indicates the warehouse.
@type	
MXHEAD.IAOURT; PPS370MI /AddHead	The field indicates the type of reference to which a reference number refers. 1 - Agreement 2 - Inquiry
	3 - SupplierQuotation 4 - Loan
M3EDIPurchaseOrder/PurchaseOrderHeader/DocumentReference/	/DocumentID/ID
MXHEAD.IAOURR; PPS370MI/AddHead	The field indicates the reference number that is found on the purchase order lines.
M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/PartyIE 1.) MXHEAD.IASUNO; PPS370MI/AddHead 2.) MPHEAD/IASUNO;	Os/ID The field indicates the supplier.
PPS001MI/ConfirmLine.; /	
M3EDIPurchaseOrder/PurchaseOrderHeader/SupplierParty/Custor MXHEAD.IAYRE1; PPS370MI /AddHead	merServiceContact/ID The field indicates the name of the person to be contacted for issues regarding purchase orders.
M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location @type	n Set to 'warehouse'.
M3EDIPurchaseOrder/PurchaseOrderHeader/ShipToParty/Location	
MXHEAD.IAWHLO; PPS370MI /AddHead	The field indicates the warehouse. If attribute type is 'warehouse', populate Warehouse (WHLO).
M3EDIPurchaseOrder/PurchaseOrderHeader/PlannerContact/ID 1.) MXHEAD.IAPURC; PPS370MI/AddHead 2.) MXLINE/IBPURC; PPS370MI/AddLine.; /	The field indicates the user who ordered or required items for purchase.
M3EDIPurchaseOrder/PurchaseOrderHeader/TransportationTerm/l	
MXHEAD.IATEDL; PPS370MI/AddHead	The field indicates the delivery terms.
M3EDIPurchaseOrder/PurchaseOrderHeader/TransportationTerm/I MXHEAD.IATEAF; PPS370MI/AddHead	FreightTermCode The field indicates the freight terms which apply for the delivered goods.
M3EDIPurchaseOrder/PurchaseOrderHeader/PaymentTerm/IDs/ID MXHEAD.IATEPY; PPS370MI /AddHead	The field indicates the payment term.
M3EDIPurchaseOrder/PurchaseOrderHeader/RequestedShipDateT MXHEAD.IADWDT; PPS370MI /AddHead	The field indicates requested delivery date. This refers to either deliveries or purchases. When referring to deliveries, it indicates the requested date for delivery to the customer. When referring to purchases, it indicates the requested date for delivery stated on the purchase order.
M3EDIPurchaseOrder/PurchaseOrderHeader/PaymentMethodCode MXHEAD.IAPYME; PPS370MI /AddHead	
M3EDIPurchaseOrder/PurchaseOrderHeader/OrderDateTime MXHEAD.IAPUDT; PPS370MI /AddHead	The field indicates when the purchase order was placed. When entering a new purchase order, today's date will be proposed as the order date, but it may be changed if necessary.
M3EDIPurchaseOrder/PurchaseOrderHeader/UserArea	, , , , , , , , , , , , , , , , , , , ,
MXHEAD IAUSDS	The field indicates the ff:
MXHEAD.IAUSD5 MXHEAD.IAUCA1	 If NameValue@name is set to 'RequestID' the value of NameValue will be entered in field USD4.
MXHEAD.IAUCA2	2.) If NameValue@name is set to 'RequestNumber' the value of
MXHEAD.IAUCA3 MXHEAD.IAUCA4	NameValue will be entered in field USD5. 3. The fields below represents the free fields (CMS082/CMS083)
WATERD INCORT	o. The helds below represents the field felial (Olvious/Olvious)

UCA1	
UCA2	
UCA3	
UCA4	
UCA5	
UCA6	
UCA7	
UCA8	
UCA9	
UCA0	
UDN1	
UDN2	
UDN3	
UDN4	
UDN5	
UDN6	
UID1	
UID2	
UID3	
UCT1	
	UCA2 UCA3 UCA4 UCA5 UCA6 UCA7 UCA8 UCA9 UCA0 UDN1 UDN2 UDN3 UDN3 UDN4 UDN5 UDN6 UID1 UID2 UID3

- 1) MXHEAD.IAFACI
- 2) MXHEAD.IAORTY
- 3) MXHEAD.IAPROJ
- 4) MXHEAD.IAELNO
- 5) MXHEAD.IACUCD
- 6) MXHEAD.IAHAFE
- 7) MXHEAD.IAMODL; PPS370MI/AddHead
- 8) MPPBOR.ORBAOR; PPS370MI/StartEntry.; /

The field indicates the facility.

2) Order Type

The field indicates the order type.

3) Project Number

The field indicates the unique ID for a project.

4) Project Element

The field indicates an element which is part of a project structure. An element can refer to an activity, a subproject or a main project.

The field indicates the abbreviation for the currency.

The field indicates the ID of the harbor or airport. It is used for reporting purposes in the trade statistics.

7) Delivery Method

The field indicates how the delivery is made.

8) Batch Origin

The field indicates purchase order batch origin. The batch origin is a unique identity for each external or internal system using the PO batch entry in order to create purchase orders in M3. Batch origin will be used as input to PPS370MI StartEntry to automatically generate the Message number. After all PO lines are created, the Message number will be used as input to PPS370MI FinishEntry.

- 1.) 'Facilities'.
- 2.) 'Order Types'.
- 3.) 'Project Numbers'.
- 4.) 'Project Elements' .
- 5.) 'Currencies'.
- 6.) 'Harbor Airports'
- 7.) 'Delivery Methods'.
- 8.) 'Batch Origins'

M3EDIPurchaseOrder/PurchaseOrderHeader/BuyerReference/IDs/ID

MXHEAD.IABUYE; PPS370MI/AddHead

The field indicates the buyer.

M3EDIPurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID

MXHEAD.IAPRSU; PPS370MI /AddHead

The field indicates a valid supplier number for the supplier that should receive the payment. Payee is entered only if the supplier and the payee are not the same legal entity.

M3EDIPurchaseOrder/PurchaseOrderLine/LineNumber

MXLINE.IBPNLI; PPS370MI/AddLine MPLINE.IBPNLI; MPLINE.IBPNLS PPS001MI/ConfirmLine.; /

@listID

The field indicates the concatenated Line number and sub line number. The first 3 decimals refer to Line number. The succeeding decimals refer to sub line number.

M3EDIPurchaseOrder/PurchaseOrderLine/DocumentReference @type

MXLINE.IBRORC; PPS370MI /AddLine

The field indicates the origin of the reference order number (RORC). If attribute type is 'ProductionOrder', populate RORC with 1 If attribute type is 'PurchaseOrder', populate RORC with 2

May 26, 2023

MOLDII dicilascolaci	
	If attribute type is 'SalesOrder', populate RORC with 3 If attribute type is 'RequisitionOrder', populate RORC with 4 If attribute type is 'DistributionOrder', populate RORC with 5 If attribute type is 'WorkOrder', populate RORC with 6 If attribute type is 'ServiceOrder', populate RORC with 7 If attribute type is 'ProjectOrder', populate RORC with 8 If attribute type is 'ClaimOrder', populate RORC with 9
M3EDIPurchaseOrder/PurchaseOrderLine/DocumentReference/Docum MXLINE.IBRORN; PPS370MI /AddLine	nentID/ID The field indicates the reference order number.
M3EDIPurchaseOrder/PurchaseOrderLine/DocumentReference/LineNu MXLINE.IBRORL; PPS370MI/AddLine	umber The field indicates the reference order line number.
M3EDIPurchaseOrder/PurchaseOrderLine/DocumentReference/SubLin MXLINE.IBRORX; PPS370MI/AddLine	neNumber The field indicates the subline number.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/ItemID/ID MXLINE.IBITNO; PPS370MI /AddLine	The field indicates the item number.
M3EDIPurchaseOrder/PurchaseOrderLine/Item/UPCID MITPOP.MPPOPN; MMS025MI/GetItem	The field indicates the alias number for qualifier UPC.
	If Item/ID and Item/GTIN are not populated, use MMS025MI/GetItem to retrieve the Item number (ITNO) with POPN as input together with the following: Alias category (ALWT) = 02 Alias qualifier (ALWQ) = UPC
M3EDIPurchaseOrder/PurchaseOrderLine/Item/GTIN MITPOP.MPPOPN; MMS025MI/GetItem	The field indicates the alias number for qualifier EA13.
5 6,	If Item/ID is not populated, use MMS025MI/GetItem to retrieve the Item number (ITNO) with POPN as input together with the following: Alias category (ALWT) = 02 Alias qualifier (ALWQ) = EA13
M3EDIPurchaseOrder/PurchaseOrderLine/Item/Description MXLINE.IBPITT: PPS370MI/AddLine	The field indicates the purchase order item description.
M3EDIPurchaseOrder/PurchaseOrderLine/Quantity MXLINE.IBORQA; PPS370MI/AddLine MPLINE.IBCQFA; PPS001MI/ConfirmLine.; /	The field indicates the ordered quantity or the confirmed ordered quantity.
M3EDIPurchaseOrder/PurchaseOrderLine/UnitPrice/Amount MXLINE.IBPUPR; PPS370MI/AddLine MPLINE.IBCPPR; PPS001MI/ConfirmLine	The field indicates the purchase price or the confirmed purchase price
M3EDIPurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MXLINE.IBDWDT; PPS370MI/AddLine	The field indicates the required delivery date.
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location @type	
M3EDIPurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MXLINE.IBWHLO; PPS370MI/AddLine	Set to 'warehouse' if ShipToParty/Location/ID refers to the warehous The field indicates the warehouse. If attribute type is 'warehouse', populate Warehouse (WHLO).
M3EDIPurchaseOrder/PurchaseOrderLine/TransportationTerm/Incoter MPLINE.IBTEDL; PPS001MI/ConfirmLine	rmsCode The field indicates the delivery terms.
MPEINE:IBTEDE, PP 300 IMI/COMMILEME M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/Descript	
M3EDIPurchaseOrder/PurchaseOrderLine/DistributedCharge/Amount MPLINE.IBCFD1; MPLINE.IBCFD2; MPLINE.IBCFD3; PPS001MI/ConfirmLine	The field indicates the discount amount and the confirmed discount percentage.
MXLINE.IBODI1; MXLINE.IBODI2; MXLINE.IBODI3; PPS370MI/AddLine.; / M3EDIPurchaseOrder/PurchaseOrderLine/FreightClassification/Codes	s/Code

M3EDIPurchaseOrder	
MPLINE.IBMODL; PPS001MI/ConfirmLine	The field indicates the delivery method.
M3EDIPurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT; PPS001MI/ConfirmLine	The field indicates the confirmed delivery date.
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Line MPLINE.IBPNLI MPLINE.IBPNLS	eNumber The field indicates the line number and the subline number.
.; PPS001MI /ConfirmLine	
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Qua MPLINE.IBCFQA; PPS001MI/ConfirmLine	antity The field indicates the confirmed quantity of the subline .
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Uni	
MPLINE .IBCPPR ; PPS001MI /ConfirmLine	The field indicates the confirmed purchase price.
M3EDIPurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Pro MPLINE.IBCODT; PPS001MI/ConfirmLine	misedDeliveryDateTime The field indicates the confirmed delivery date.
M3EDIPurchaseOrder/PurchaseOrderSubLine/Class	·
MPLIND.ICOEND; PPS001MI/ConfirmLine	The field indicates if the delivery of an order line is completed. Remaining quantity will not be back ordered. The value from the map is boolean and will be converted to 1 or 0 before using as input to MI program. If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
@listID	If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
M3EDIPurchaseOrder/PurchaseOrderLine/UserArea	
MXLINE.IBUSD4	The field indicates the ff:
MXLINE.IBUSD5 MXLINE.IBUCA1	If NameValue@name is set to 'RequestID' the value of NameValue will be entered in field USD4.
MXLINE.IBUCA2	2.) If NameValue@name is set to 'RequestNumber' the value of
MXLINE.IBUCA3	NameValue will be entered in field USD5.
MXLINE.IBUCA4	3. The fields below represents the Userdeifned fields (CMS082/
MXLINE.IBUCA5	CMS083)
MXLINE.IBUCA6	UCA1
MXLINE.IBUCA7	UCA2
MXLINE.IBUCA8	UCA3
MXLINE.IBUCA9	UCA4
MXLINE.IBUCA0	UCA5
MXLINE.IBUDN1	UCA6
MXLINE.IBUDN2	UCA7
MXLINE.IBUDN3	UCA8
MXLINE.IBUDN4	UCA9
MXLINE.IBUDN5	UCA0
MXLINE.IBUDN6	UDN1
MXLINE.IBUID1	UDN2
MXLINE.IBUID2	UDN3
MXLINE.IBUID3	UDN4
MXLINE.IBUCT1	UDN5
.; PPS370MI /AddLine	UDN6 UID1
	UID2
	UID3
	UCT1
M3EDIPurchaseOrder/PurchaseOrderLine/ContractReference/Docume MXLINE.OURR; PPS200MI/AddLine	
M3EDIPurchaseOrder/PurchaseOrderLine/Classification/Codes/Code	<u> </u>
1) MXLINE.IBCOCE	1) Cost Center
PPS370MI/Addline	The field indicates the cost center associated with the record.
	If attribute listID is 'Cost Center', populate Cost center (COCE).
2) MPLIND.ICOEND	. ,
PPS001MI/ConfirmLine	2) Flagged as completed
A) MBI INE IBOMB	The field indicates if the delivery of an order line is completed.
3) MPLINE.IBCIAD	Remaining quantity will not be back ordered. The value from the map
PPS001MI/ConfirmLine	is boolean and will be converted to 1 or 0 before using as input to MI
4) MDI INE IDLIAEE	program.
4) MPLINE.IBHAFE PPS001MI/ConfirmLine.; /	If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
	3) Confirmed pickup address
	The field indicates the confirmed pickup address. If attribute listID is 'Confirmed Pickup Address', populate Confirmed Pickup address (CIAD).

@listID

4) Harbor/airport

The field indicates the ID of the harbor or airport. If attribute listID is 'Harbor Airports', populate Harbor/airport (HAFE).

Note: Attribute listID 'Reservation Level' (SRCD) and 'Pricing Level' (PSET) are checked on when to call PPS001MI ConfirmLine.

PPS001MI ConfirmLine for PurchaseOrderSubLine will only be called when SRCD is not 1 and PSET is not 1 or 2. PPS001MI ConfirmLine for PurchaseOrderLine will only be called when SRCD is not 2 and PSET is not 3.

- 1) If attribute listID is 'Cost Center', populate Cost center (COCE).
- 2) If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
- 3) If attribute listID is 'Confirmed Pickup Address', populate Confirmed Pickup address (CIAD).
- 4) If attribute listID is 'Harbor Airports', populate Harbor/airport (HAFE).

M3EDIReceiveDelivery

M3EDIReceiveDelivery/TradingPartnerID	The Bold in disease about the Policy of the Third Control of the
	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/DocumentID/ID OCHEAD.OCREPN; MHS850MI/AddCOReturn	The field indicates the receiving number if the field is used for CO return.
MMIHED.I0PMSN; MMS850MI/AddAdjust .; /	In case warehouse transactions are not connected to an order in Muse MMS850 instead of MHS850.
	Use Partner from logicalID and translate it in CRS881 to "Internal Stock Transactions" if it is to use MMS850MI.Adjust.
	Use Partner from logicalID and translate it in CRS881 to "OrderStockTransactions" if it is to use MHS850MI transactions with Qualifier 51CR.
@accountingEntity CMNDIV.CCCONO CMNDIV.CCCONO.; /	The field indicates the company and division.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/DocumentDateTime MHILIN.G2GEDT MHILIN.G2GETM; MHS850MI/AddCOReturn MHIHED.G0GEDT MHIHED.G0GETM; MHS850MI/AddWhsHead MHIPAC.G1GEDT MHIPAC.G1GETM; MHS850MI/AddWhsPack.; /	The field indicates the date and time the record was created.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/Note MHIHED.G0SUDO; MHS850MI/AddWhsHead @entryDateTime	The field indicates the delivery note number.
MHIHED.GODNDT; MHS850MI/AddWhsHead	The field indicates the date the delivery note was printed for the first time.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/DocumentReference/De OCHEAD.OCORNO; MHS850MI/AddCOReturn MHIHED.G0RIDN;	The field is used to decide which API transaction to use. If 'Transfer', 'PurchaseOrder' and 'ProductionOrder', use AddWhsHead. If 'CustomerReturn', use AddCOReturn. If 'Maitenance' and with translation "OrderStockTransactions", set to 51CR. If 'ProjectMaster', DocumentID/ID will be used as Project number. CocumentID/ID The field indicates the order number. The field indicates the Project number if Document Reference@type='ProjectMaster'.
MHS850MI/AddWhsHead MHILIN.G2PROJ; MHS850MI/ChgWhsLineX .; /	
M3EDIReceiveDelivery/ReceiveDeliveryHeader/Status/Code	The field indicates the status. It will only process the PO if status is 'Received' or 'Closed'.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/ID MHIHED.G0WHLO; MHS850MI.AddWhsHead, MHIPAC.G1WHLO; MHS850MI.AddWhsPack, MHILIN.G2WHLO; MHS850MI.AddWhsLine, OCHEAD.OCWHLO; MHS850MI.AddCOReturn, MMIHED.I0WHLO; MMS850MI/AddAdjust · /	The field indicates the warehouse.
., / M3EDIReceiveDelivery/ReceiveDeliveryHeader/ActualDeliveryDateTim MHILIN.G2RPDT G2USD5; MHS850MI /AddWhsLine	e The field indicates the date and time the reporting transaction was performed.
M3EDIReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/PartyID MHIHED.G0SUNO; MHS850MI/AddWhsHead MHILIN.G2SUNO; MHS850MI/AddWhsLine	•
Infor May 26 202'	

M3EDIReceiveDelivery MHIPAC.G1SUNO: MHS850MI/AddWhsPack M3EDIReceiveDelivery/ReceiveDeliveryHeader/ReturnFromShipToParty/PartyIDs/ID OCHEAD.OCCUNO; MHS850MI/AddCOReturn The field indicates the customer number. M3EDIReceiveDelivery/ReceiveDeliveryHeader/DeliverToParty/Location/ID OCHEAD.OCWHLO; The field indicates the warehouse. MHS850MI/AddCOReturn MHIHED.G0WHLO; MHS850MI/AddWhsHead MHILIN.G2WHLO; MHS850MI/AddWhsLine MHIPAC.G1WHLO; MHS850MI/AddWhsPack MMIHED.I0WHLO; MMS850MI/AddAdjust.; / M3EDIReceiveDelivery/ReceiveDeliveryHeader/UserArea MGLINE.MRELNO; MHS850MI/ChgWhsLineX The field indicates the Project Element is @name='eam.ProjectBudget'. Use this only if Classification/Codes/ Code@listID='Project Element' does not exist. M3EDIReceiveDelivery/ReceiveDeliveryItem/ItemID/ID OCLINE.ODITNO: The field indicates the item number. MHS850MI/AddCOReturn MHILIN.G2ITNO; MHS850MI/AddWhsLine MMIIDE.I1ITNO; MMS850MI/AddAdjust.; / M3EDIReceiveDelivery/ReceiveDeliveryItem/Classification/Codes/Code 1) MHILIN.G2PROJ; 1) The field indicates the Project number. 2) The field indicates the Project element. MHS850MI.ChgWhsLineX 2) MHILIN.G2ELNO; 3) The field indicates the Department. MHS850MI.ChgWhsLineX 4) The field indicates the Accounting object 2 or Cost Center. Use this 3) MHILIN.G2DEPT: only if Shipment/ShipmentItem/UserArea/Property/ NameValue@name='AccountingObject2' does not exist. MHS850MI.ChgWhsLineX 4) MHILIN.G2ACC2 MHS850MI.ChgWhsLineX @listID 1) If 'Project Number' populate PROJ. 2) If 'Project Element' populate ELNO. 3) If 'Departments' populate DEPT. 4) If 'Cost Centers' populate ACC2 M3EDIReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/DocumentID/ID MHILIN The field indicates the purchase order number. .G2RIDN; MHS850MI/AddWhsLine, AddPOClose M3EDIReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/LineNumber MHILIN.G2RIDL; MHS850MI/AddWhsLine, AddPOClose The field indicates the order line number. M3EDIReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/SubLineNumber MHILIN.G2RIDX; MHS850MI/AddWhsLine, AddPOClose The field indicates the line suffix M3EDIReceiveDelivery/ReceiveDeliveryItem/DocumentReference/DocumentID/ID OCLINE.ODORNO; The field indicates the order number. MHS850MI/AddCOReturn MHILIN.G2RIDN For type 'Transfer', it is a concatenation of order number (RIDN) and MHILIN.G2RIDI; delivery number (RIDI) separated by '/'. MHS850MI/AddWhsLine M3EDIReceiveDelivery/ReceiveDeliveryItem/DocumentReference/LineNumber OCLINE ODRELL: The field indicates the order line number.

MHS850MI/AddCOReturn

MHILIN.G2RIDL:

MHS850MI/AddWhsLine.; /

M3EDIReceiveDelivery/ReceiveDeliveryItem/DocumentReference/SubLineNumber

MHILIN.G2RIDX; The field indicates the line suffix.

MHS850MI/AddWhsLine.; /

M3EDIReceiveDelivery/ReceiveDeliveryItem/ReceivedQuantity

OCLINE.ODREQ1; MHS850MI/AddCOReturn MHILIN.G2RVQA; MHS850MI/AddWhsLine MMIINS.I2QLQT;

The field indicates the returned or received quantity in item's basic unit of measure. Only relevant if SerializedLot/Lot/Quantity is blank.

MMS850MI/AddAdjust

@unitCode MHILIN.G2UNIT; MHS850MI/AddWhsLine

The field indicates the unit of measure

May 26, 2023

M3EDIReceiveDelivery

The field indicates the catch weight in item's basic unit of measure.
The field indicates the location. 1) For EAM, location is fetched from UserArea field eam.Bin. If @name='ToLocation' or 'eam.Bin', populate WHSL.
2) The field indicates the completion flag. If set to 1, the delivery of an order line is completed. Remaining quantity will not be backordered. If @name='FlaggedAsCompleted', populate OEND.
The field indicates the package number. If @name='PackageNumber', populate PACN.
4) The field indicates the accounting objects. Name attributes are 'AccountingObject1'-'AccountingObject7'.
D The field indicates the lot number.
,
The field indicates the returned or received quantity in item's basic unit of measure.
The field indicates the unit of measure.
The field indicates lot reference 1. The field indicates lot reference 2.
1) If noteID = Lot Reference 1, populate BREF.
2) If noteID = Lot Reference 2, populate BRE2.
The field indicates the location.
The field indicates the weakens number
The field indicates the package number.
The field indicates the container.
The field indicates the shipment number. If @name="Shipment", populate CONN.
The field indicates the delivery number. If @name="DeliveryNumber", populate DLIX.
The field indicates the Serial Shipping Container Code. If @name="SSCC", populate SSCC.

M3EDIReceiveDelivery 5) MHILIN.G2WHSL; MHS850MI/AddWhsLine

.; /

If populated, calll MHS850MI/AddDOPackRec instead of AddDOReceipt.

- 4) The field indicates the To location. If @name="ToLocation", populate TWSL.
- 5) The field indicates the Location. If @name="Location", populate WHSL.

Infor May 26, 2023

M3EDIRemittanceAdvice

M3EDIRemittanceAdvice/TradingPartnerID	
	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDIRemittanceAdvice/RemittanceAdviceHeader/DocumentID/ID FABHED.V1STMN; ABS100MI/AddStatmtHead	The field indicates the number of a statement of account from the bank.
M3EDIRemittanceAdvice/RemittanceAdviceHeader/DocumentDateTin FABHED.V1BSOT FABHED.V1BSCT.; ABS100MI/AddStatmtHead	ne The field indicates the bank statement's opening and closing balance date.
M3EDIRemittanceAdvice/RemittanceAdviceHeader/InitiatingParty/Pail FABLIN.V2PYNO; ABS100MI/AddStatmLine	rtyIDs/ID The field indicates the Payer. This element is only valid if element RemittanceAdviceHeader/DebtorParty/PartyIDs/ID does not exist.
M3EDIRemittanceAdvice/RemittanceAdviceHeader/RemitToParty/Par FABHED.V1BSID; ABS100MI/AddStatmHead	rtyIDs/ID The field indicates the BankaccountID (This should be setup in ABS900 - A dedicated BKID is needed).
M3EDIRemittanceAdvice/RemittanceAdviceHeader/DebtorParty/Party FABLIN.V2PYNO; ABS100MI/AddStatmLine	vIDs/ID The field indicates the Payer.
M3EDIRemittanceAdvice/RemittanceAdviceHeader/TotalAmount @currencyID	
FABHED.V1CUCD; ABS100MI/AddStatmHead	The field indicates the currency.
M3EDIRemittanceAdvice/RemittanceAdviceLine/DocumentReference FABDET.V3CINO; ABS100MI/AddStatmDetail	ADocumentID/ID The field indicates the invoice number.
M3EDIRemittanceAdvice/RemittanceAdviceLine/PaymentAmount FABLIN.V2BLLF; ABS100MI/AddStmLine @currencyID	The field indicates the line amount.
FABLIN.V2CUCD; ABS100MI/AddStmLine	The field indicates the currency of the Payment Amount .
M3EDIRemittanceAdvice/RemittanceAdviceLine/DiscountTakenAmou FABDET.V3BLNF; ABS100MI/AddStmDetail @currencyID	unt The field indicates the Discount Taken Amount.
FABDET.V3CUCD; ABS100MI/AddStmDetail	The field indicates the currency of Discount Taken Amount
M3EDIRemittanceAdvice/RemittanceAdviceLine/ChargesTakenAmou FABDET.V3BLNF; ABS100MI/AddStmDetail @currencyID	<i>Int</i> The field indicates the Charge Taken Amount.
FABDET.V3CUCD; ABS100MI/AddStmDetail	The field indicates the currency of Charge Taken Amount.
M3EDIRemittanceAdvice/RemittanceAdviceLine/BookingDateTime FABLIN.V2ACDT; ABS100MI/AddStmDetail	The field indicates the accounting date.
M3EDIRemittanceAdvice/RemittanceAdviceLine/ValueDateTime FABLIN.V2CURD; ABS100MI/AddStmDetail	The field indicates the value date.

M2EDISalasOrdar/Trading Partner ID	
M3EDISalesOrder/TradingPartnerID	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC. The value can be translated in CRS881/882.
M3EDISalesOrder/SalesOrderHeader/DocumentID/ID OXHEAD.OAORNO; OIS100MI/AddLineBatchEnt ChgLineBatchEnt DelLineBatchEnt	The field indicates the order number. This field is used to add, update or delete order line from an existing customer order.
M3EDISalesOrder/SalesOrderHeader/AlternateDocumentID/ID OXHEAD.OACUOR; OIS100MI/AddBatchHead @schemeName	The field indicates the customer's order number.
wschemename	Set to 'customer'.
M3EDISalesOrder/SalesOrderHeader/DocumentDateTime OXHEAD.OAORDT; OIS100MI/AddBatchHead	The field indicates the transaction date and time.
<i>M3EDISalesOrder/SalesOrderHeader/Note</i> OSYTXH.THTX40; OIS100MI/AddBatchText ⊕type	The field indicates notes.
	Set to 'Header' if the note entered is for the header. Set to 'Footer' if the note entered is for the footer.
@languageID OSYTXH.THLNCD; OIS100MI/AddBatchText	The field indicates the language used for the note.
M3EDISalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OXHEAD.OACUNO; OIS100MI/AddBatchHead	The field indicates the customer identity.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OXHEAD.OAADID; OIS100MI/AddBatchHead	The field indicates the Customer number address.
	The value of this field can be translated in M3 CRS881/882.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Name OXADRE.ODCUNM; OIS100MI/AddBatchAddress	The field indicates the customer name.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODYREF OXHEAD.OAYREF.; OIS100MI/AddBatchAddress AddBatchHead	
OXADRE.ODCUA2 OXADRE.ODCUA3 OXADRE.ODCUA4.; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODTOWN; OIS100MI/AddBatchAddress	s/CityName The field indicates the city name.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODECAR; OIS100MI/AddBatchAddress	•
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address	· · · · · · · · · · · · · · · · · · ·
OXADRE.ODCSCD; OIS100MI/AddBatchAddress	
	The field indicates the country code.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress	The field indicates the country code. 5/PostalCode The field indicates the postal code.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress	The field indicates the country code. S/PostalCode The field indicates the postal code. SLocation/ID The field indicates the ship-via address ID.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C	The field indicates the country code. s/PostalCode The field indicates the postal code. sLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO).
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C OXADRE.ODPHNO; OIS100MI/AddBatchAddress	The field indicates the country code. S/PostalCode The field indicates the postal code. SLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO). DialNumber If Channel Code is set to 'Phone', this field indicates the telephone
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C OXADRE.ODPHNO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OXHEAD.OAWHLO; OIS100MI/AddBatchHead M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location	The field indicates the country code. s/PostalCode The field indicates the postal code. sLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO). DialNumber If Channel Code is set to 'Phone', this field indicates the telephone number of the Ship To. The field indicates the warehouse.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C OXADRE.ODPHNO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OXHEAD.OAWHLO; OIS100MI/AddBatchHead M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location	The field indicates the country code. s/PostalCode The field indicates the postal code. sLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO). DialNumber If Channel Code is set to 'Phone', this field indicates the telephone number of the Ship To. The field indicates the warehouse.
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C OXADRE.ODPHNO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID	The field indicates the country code. s/PostalCode The field indicates the postal code. sLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO). DialNumber If Channel Code is set to 'Phone', this field indicates the telephone number of the Ship To. The field indicates the warehouse. If the field is set to 'Warehouse' then the value in element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be used as Warehouse input instead of the value in element
M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Address OXADRE.ODPONO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Location/Logistic OXADRE.ODADVI; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C M3EDISalesOrder/SalesOrderHeader/ShipToParty/Communication/C OXADRE.ODPHNO; OIS100MI/AddBatchAddress M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OXHEAD.OAWHLO; OIS100MI/AddBatchHead M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location	The field indicates the country code. S/PostalCode The field indicates the postal code. SLocation/ID The field indicates the ship-via address ID. ChannelCode The field must be set to 'Phone' to populate the Ship To telephone number (PHNO). DialNumber If Channel Code is set to 'Phone', this field indicates the telephone number of the Ship To. The field indicates the warehouse. If the field is set to 'Warehouse' then the value in element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be used as Warehouse input instead of the value in element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID. If the field is set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used as Warehouse input instead of the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the element M3EDISalesOrder/SalesOrderHeader/ShipFromParty/Location/ID will be Used in Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of Set to 'Site' then the value in the Ship Total Part of

The field indicates the blanket agreement number in the order heade
The field indicates the Invoice Recipient.
The field indicates the name of the invoice recipient.
ttentionOfName The field indicates the Customer responsible.
ddressLine The field indicates the address line.
ityName The field indicates the city name.
ountrySubDivisionCode The field indicates an area, province or state within a country.
ountryCode The field indicates the country code.
ostalCode The field indicates the postal code.
The field indicates the Payer.
The field indicates delivery terms. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: I Parent element(s): Generic Data element: IncotermsCode
The field indicates the delivery method. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: I Parent element(s): Generic Data element: TransportationMethodCode
de The field indicates the payment term ID.
The field indicates the payment term ID.
The field indicates the name or description of the charge. The field indicates the charge amount. RateNumeric The field indicates the calculation factor that is used to calculate the
charge amount.
The field indicates the charge code
The field indicates the charge code. The field indicates if an item, charge, customer or ship-to location is
The field indicates the charge code. The field indicates if an item, charge, customer or ship-to location is taxable or not. The field indicates the Customer's puchase order date.
The field indicates the charge code. The field indicates if an item, charge, customer or ship-to location is taxable or not. The field indicates the Customer's puchase order date. Set to 'PODate'.
The field indicates the charge code. The field indicates if an item, charge, customer or ship-to location is taxable or not. The field indicates the Customer's puchase order date. Set to 'PODate'. The field indicates the last delivery date.
The field indicates the charge code. The field indicates if an item, charge, customer or ship-to location is taxable or not. The field indicates the Customer's puchase order date. Set to 'PODate'.

MIDEDIDATESOTUET	
1) OOHEAD.OAUCA1-OAUCA0 2) OOHEAD.OAUDN1-OAUDN6 3) OOHEAD.OAUID1-OAUID3 4) OOHEAD.OAUCT1.; OIS100MI/AddBatchHead	The field indicates a user-defined field for displaying and storing your own information for Customer order Header. User-defined fields can be viewed and changed in OIS100/K if configuration is done in OIS014/Q per CO type. Standard User-defined fields must be generated in CMS082 for OOHEAD before use. The following Property/NameValue currently supported: 1) 10 alphanumeric fields on CO Header with up to 20 characters, Property/NameValue@name must start with 'm3.OAUCA1-', User-defined alpha field 1 . 'm3.OAUCA9-', User-defined alpha field 9 'm3.OAUCA0-', User-defined alpha field 10
	 6 numeric fields on CO Header with up to 17 positions and 6 decimals. The number of positions and decimals for each field is defined in CMS082 for OOHEAD. m3.OAUDN1-', User-defined numeric 1
	.m3.OAUDN6-', User-defined numeric 6 3) 3 date fields on CO Header, in the format 'YYYY-MM-DD' 'm3.OAUID1-', User-defined date 1 'm3.OAUID2-', User-defined date 2 'm3.OAUID3-', User-defined date 3 4) 1 text field on CO Header with up to 128 characters. 'm3.OAUCT1-', User-defined date 1
M3EDISalesOrder/SalesOrderHeader/SalesPersonReference/IDs/IDOXHEAD.OASMCD; OIS100MI/AddBatchHead	The field indicates the sales person.
M3EDISalesOrder/SalesOrderHeader/OrderTypeCode OXHEAD.OAORTP; OIS100MI/AddBatchHead	The field indicates the sales order type. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: M3EDI Vers: 1 Message: Generic I/O: I Parent element(s): Generic Data element: OrderType
M3EDISalesOrder/SalesOrderHeader/CurrencyCode OXHEAD.OACUCD; OIS100MI/AddBatchHead	The field indicates the currency code.
M3EDISalesOrder/SalesOrderLine/LineNumber OXLINE.OBCUPO; OIS100MI/AddBatchLine	The field indicates the order line number.
OXLINE.OBPONR; OIS100MI/AddLineBatchEnt OXLINE.OBPONR;	
OIS100MI/ChgLineBatchEnt OXLINE.OBPONR;	
OIS100MI/DelLineBatchEnt.; / M3EDISalesOrder/SalesOrderLine/Note OSYTXL.TLTX60; OIS100MI/AddBatchText @noteID	The field indicates notes.
OSYTXL.TLTXVR; OIS100MI/AddBatchText	The field indicates the document class in M3. Document class indentifies which documents should the text be printed on.
@type	Set to 'Header' if the note entered is for the header. Set to 'Footer' if the note entered is for the footer.
M3EDISalesOrder/SalesOrderLine/Status/Code	If status is 'Deleted', the order line will be deleted through OIS100MI.DelLineBatchEnt.
M3EDISalesOrder/SalesOrderLine/Item/ItemID/ID OXLINE.OBITNO; OIS100MI/AddBatchLine AddLineBatchEnt @schemeName	The field indicates the Item Number.
	Set to 'Supplier' for alias category Supplier's Item number. Set to 'Customer' for alias category Customer's Item number.
M3EDISalesOrder/SalesOrderLine/Item/UPCID OXLINE.OBPOPN; OIS100MI/AddBatchLine AddLineBatchEnt	The field indicates the UPC number as the item alias.
M3EDISalesOrder/SalesOrderLine/Item/EPCID OXLINE.OBPOPN; OIS100MI/AddBatchLine AddLineBatchEnt	The field indicates the item alias wiith EA13 qualifier.
M3EDISalesOrder/SalesOrderLine/Item/Description OXLINE.OBITDS; OIS100MI/AddBatchLine AddLineBatchEnt	The field indicates the item description.
Infor May 26, 20	23 10

The field indicates the lot number.
The field indicates the order line quantity.
The field indicates the unit of measure.
The field indicates the sales price.
The field indicates the required delivery date and time.
The field indicates the shipping address ID.
The value of this field can be translated in M3 CRS881/882.
The field indicates the order line delivery method. The value can be translated in CRS881/882. It can be defined on the company level only. Msg std: ION Vers: 1 Message: Generic I/O: I Parent element(s): Generic Data element: TransportationMethodCode
The field indicates the payment term for the order line.
The field indicates the payment term for the order line.
The field indicates the name or description of the charge for the order line.
The field indicates the charge amount for the order line.
teNumeric The field indicates the calculation factor that is used to calculate the charge amount for the order line.
The field indicates the charge code for the order line.
The field indicates the promise or confirm delivery date and time.
The field indicates a user-defined field for displaying and storing your own information for Customer order Line. User-defined fields can be

MSEDISalesOldei	
	3) 3 date fields on CO Line, in the format 'YYYY-MM-DD' 'm3.OBUID1-', User-defined date 1 'm3.OBUID2-', User-defined date 2 'm3.OBUID3-', User-defined date 3
	4) 1 text field on CO Line with up to 128 characters. 'm3.OBUCT1-', User-defined date 1
M3EDISalesOrder/SalesOrderLine/ContractReference/DocumentID/ID OXLINE.OBAGNO; OIS100MI/AddBatchLine	The field indicates the blanket agreement number in the order line.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/PartyIDs/ID OXLINE.OBWHLO; OIS100MI/AddBatchLine AddLineBatchEnt	The field indicates the warehouse where the item is coming from.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location @type	Set to 'Warehouse'.
M3EDISalesOrder/SalesOrderLine/ShipFromParty/Location/ID OXLINE.OBWHLO; OIS100MI/AddBatchLine	The field indicates the warehouse where the item is coming from.
M3EDISalesOrder/SalesOrderLine/Classification/Codes/Code OXLINE.OBEDFP; OIS100MI/AddBatchLine AddLineBatchEnt ChgLineBatchEnt @JistID	The field indicates the EDIFACT price.
who up	Set to 'EDIFACT price'.
M3EDISalesOrder/SalesOrderLine/PricingAmount/UnitPretaxAmount OXLINE.OBSAPR; OIS100MI/AddBatchLine AddLineBatchEnt	The field indicates the sales price.

M3EDISalesOrder/SalesOrderLine/ItemConfiguration/ConfigurationComponent/ConfiguratorLinks/ConfigurationID

MPDCHF.QIEXCN; OIS100MI/AddBatchLine The field indicates the item's external configuration number.

Infor May 26, 2023

M3EDIShipment

MacDianipinient	
M3EDIShipment/TradingPartnerID	The field indicates the trading partner ID. The value of this field reflects as the partner in MEC.
M3EDIShipment/ShipmentHeader/DocumentID/ID MHIHED.GORIDI MMIHED.IOPMSN:	The field indicates the delivery number or Customer Order Number
MHS850MI/AddWhsHead, MMIHED.I0PMSN;	Use Partner from logicalID and translate it in CRS881 to "Internal Stock Transactions" if it is to use MMS850MI.Adjust.
MMS850MI/AddAdjust,.; /	Use Partner from logicalID and translate it in CRS881 to "OrderStockTransactions" if it is to use MHS850MI transactions with Qualifier 51CR. AlternateDocumentID/ID is not required and DocumentID/ID is mapped to PMSN.
	If no translation in CRS881, use MHS850MI transactions wherein Qualifier input is based on the translation of DocumentReference@type.
@accountingEntity	The field indcates the Company/Division
M3EDIShipment/ShipmentHeader/AlternateDocumentID/ID MHILIN.G2DLIX, MHILIN.G2PLSX; MHS850MI/AddWhsLine, ODHEAD.UADLIX; OIS155MI/UpdateQty, Approve .: /	The field indicates the delivery number and picking list suffix separated by '/'.
M3EDIShipment/ShipmentHeader/DocumentReference	
@type MHIHED.G0QLFR; MHS850MI/AddWhsHead	The field indicates the qualifier. If ProductionOrder, set to 11. If SalesOrder, set to 31. If SupplierRMA, set to 41. If Transfer , set to 51. If Transfer and with translation "OrderStockTransactions", set to 51CR. If MaintenanceOrder, set to 61. If Maitenance and with translation "OrderStockTransactions", set to 51CR.
M3EDIShipment/ShipmentHeader/DocumentReference/DocumentID/II)
MHILIN.G2PROJ; MHS850MI/ChgWhsLineX	The field indicates the Project number if Document Reference@type='ProjectMaster'.
M3EDIShipment/ShipmentHeader/Status/Code	Status must be 'Shipped' or 'PartiallyShipped' or 'FullyReported'. Otherwise, abort process. If status is 'FullyReported', the BOD will execute the delivery receipt confirmation functionality (OIS155MI).
M3EDIShipment/ShipmentHeader/WarehouseLocation/ID MHIHED.G0WHLO; MHS850MI/AddWhsHead, MMIHED.I0WHLO; MMS850MI/AddAdjust, ODHEAD.UAWHLO; OIS155MI/UpdateQty, Approve.; /	The field indicates the warehouse.
M3EDIShipment/ShipmentHeader/CarrierRouteReference/MasterBillC MHIHED.G0BOLN; MHS850MI/AddWhsHead	fLadingID The field indicates the Bill of Lading.
M3EDIShipment/ShipmentHeader/ActualShipDateTime MHIHED.G0SHD4 MHIHED.G0SHTM.: MHS850MI/AddWhsHead	The field indicates the actual ship date and time.
M3EDIShipment/ShipmentHeader/GrossWeightMeasure MHIHED.G0GRWE; MHS850MI/AddWhsHead	The field indicates the gross weight.
M3EDIShipment/ShipmentHeader/TotalVolumeMeasure MHIHED.G0VOL3; MHS850MI/AddWhsHead	The field indicates the volume.
M3EDIShipment/ShipmentHeader/TransportationMethodCode MHIHED.G0MODL; MHS850MI/AddWhsHead	The field indicates how the delivery is made.
M3EDIShipment/ShipmentHeader/CarrierParty/PartyIDs/ID MHIHED.G0SUNO; MHS850MI/AddWhsHead	The field indicates the supplier.
M3EDIShipment/ShipmentHeader/ShipToParty/PartyIDs/ID MHIHED.G0CUNO; MHS850MI/AddWhsHead	The field indicates the customer.
M3EDIShipment/ShipmentHeader/PlannedDeliveryDateTime MHIHED.G0DLDT MHIHED.G0DLTM.; MHS850MI /AddWhsHead	The field indicates the planned delivery date and time of delivery.
M3EDIShipment/ShipmentHeader/TransportationTerm/IncotermsCode MHIHED.G0TEDL; MHS850MI/AddWhsHead	The field indicates delivery terms, which define when the responsibility for a delivery is transferred from the supplier to the customer.
M3EDIShipment/ShipmentHeader/UserArea	

M3EDIShipment The field indicates the Project Element is MHIHED.G0USD1 @name='eam.ProjectBudget'. Use this only if Classification/Codes/ MHIHED.G0USD2 Code@listID='Project Element' does not exist. MHIHED.G0USD3 MHIHED.G0USD4 The field indicates a value for a user defined field in MHS850. MHIHED.G0USD5.; MHS850MI/ChgWhsLineX Attribute Name is set to 'HeaderFreeField1'. AddWhsHead M3EDIShipment/ShipmentHeader/CustomerParty/ReceivingContact/ID ODHEAD.UAAPBY; OIS155MI/Approve The field indicates the approver. M3EDIShipment/ShipmentItem/ItemID/ID MHILIN.G2ITNO; The field indicates the item number. MHS850MI/AddWhsLine MMIIDE.I1ITNO; MMS850MI/AddAdjust.; / M3EDIShipment/ShipmentItem/Description MHILIN.G2ITDS; MHS850MI/AddWhsLine The field indicates the item description. M3EDIShipment/ShipmentItem/Note MHILIN.G2BREM; The field indicates the remark. MHS850MI/AddWhsLine MMIIDE.I1BREM; MMS850MI/AddAdjust.; M3EDIShipment/ShipmentItem/Classification/Codes/Code 1) MMIINS.I2STAG: 1) The field indicates the Status of Physical Inventory. 2) The field indicates the Project number. MHS850MI.AddAdjust 2) MHILIN.G2PROJ; 3) The field indicates the Project element. MHS850MI.ChgWhsLineX 4) The field indicates the Department. 5) The field indicates the Accounting object 2 or Cost Center. Use this MHILIN.G2ELNO; MHS850MI.ChgWhsLineX only if Shipment/ShipmentItem/UserArea/Property/ 4) MHILIN.G2DEPT; NameValue@name='AccountingObject2' does not exist. MHS850MI.ChgWhsLineX 6) The field indicates the Issue mode that will be performed. 5) MHILIN.G2ACC2 7) The field indicates the Payment Terms MHS850MI.ChgWhsLineX 6.) ODHEAD. UATEPY OIS155MI/UpdateQty, Approve @listID 1) If 'Status Physical Inventory' populate STAG. 2) If 'Project Number' populate PROJ. 3) If 'Project Element' populate ELNO. 4) If 'Departments' populate DEPT. 5) If 'Cost Centers' populate ACC2. 6) If 'Issue Mode' populate ISMD. 7) If 'Payment Terms' populate TEPY M3EDIShipment/ShipmentItem/ShippedQuantity MHILIN.G2DLQT: The field indicates the shipped quantity. MHS850MI/AddWhsLine, MMIINS.I2QLQT; MMS850MI/AddAdjust, ODLINE.UBDLQA OIS155MI/UpdateQty.; / @unitCode MHILIN.G2UNIT; The field indicates the unit of measure. MHS850MI/AddWhsLine MMIINS.I2QLUN; MMS850MI/AddAdjust.; / M3EDIShipment/ShipmentItem/SalesOrderReference/DocumentID/ID MHILIN.G2RIDN; The field indicates the sales order number. MHS850MI/AddWshLine, ODHEAD.UAORNO; OIS155MI/UpdateQty, Approve.; / M3EDIShipment/ShipmentItem/SalesOrderReference/LineNumber MHILIN.G2RIDL; The field indicates the order line number. MHS850MI/AddWhsLine, ODLINE.UBPONR; OIS155MI/UpdateQty.; / M3EDIShipment/ShipmentItem/SalesOrderReference/SubLineNumber MHILIN.G2RIDX; MHS850MI/AddWhsLine The field indicates the line suffix. M3EDIShipment/ShipmentItem/DocumentReference @type MHILIN.G2QLFR; MHS850MI/AddWhsLine The field indicates the qualifier. M3EDIShipment/ShipmentItem/DocumentReference/DocumentID/ID

Infor May 26, 2023 109

The field indicates the order number.

The field indicates the order line.

MHILIN.G2RIDN; MHS850MI/AddWhsLine

.G2RIDL; MHS850MI/AddWhsLine

MHILIN

M3EDIShipment/ShipmentItem/DocumentReference/LineNumber

M3EDIShipment

indicates the location. If @name='eam.Bin', populate indicates the accounting objects. Name attributes are Object1'-'AccountingObject7'. dicates the lot number.
indicates the accounting objects. Name attributes are Object1'-'AccountingObject7'. dicates the lot number.
Object1'-'AccountingObject7'. dicates the lot number. dicates the reporting number pick line.
dicates the reporting number pick line.
dicates the reporting number pick line.
dicates the package reference.
dicates the package number. dicates the Container
//I AddWhsPack is used, then the element value will be CN.
MI AddAdjust is used, then the element value will be used
dicates the net weight.
dicates the gross weight.
dicates the volume.
dicates the packaging width.
dicates the packaging length.
dicates the packaging height.
dicates the item number.
dicates the item name.
indicates the Status of Physical Inventory. indicates the Project number. indicates the Project element. indicates the Department. indicates the Accounting object 2 or Cost Center. Use the ment/ShipmentUnit/UserArea/Property/ @mame='AccountingObject2' does not exist. indicates the Issue mode that will be performed.
Physical Inventory' populate STAG
Physical Inventory' populate STAG. t Number' populate PROJ. t Element' populate ELNO. tments' populate DEPT. centers' populate ACC2. Mode' populate ISMD
t Number' populate PROJ. t Element' populate ELNO. tments' populate DEPT. centers' populate ACC2.

M3EDIShipment

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber

MHILIN.G2RIDX; MHS850MI/AddWhsLine

The field indicates the line suffix

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID

MHILIN.G2RIDN; MHS850MI/AddWhsLine

The field indicates the order number.

${\it M3EDIShipment/ShipmentUnit/ShipmentUnitltem/DocumentReference/LineNumber}$

MHILIN.G2RIDL; MHS850MI/AddWhsLine

The field indicates the order line.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/SubLineNumber

MHILIN.G2RIDX; MHS850MI/AddWhsLine The field indicates the line suffix.

M3EDIShipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/Lot/LotIDs/ID

MHILIN.G2BANO; MHS850MI/AddWhsLine

The field indicates the line number

M3EDIShipment/ShipmentUnit/UserArea

1) MMIDE.I1WHSL; MHS850MI.AddAdjust MHIPAC.G1WHSL; MHS850MI.AddWhsLine 2) MGLINE.MRACC1 MGLINE.MRACC2-MRACC7; MHS850MI.ChgWhsLineX.;

- 1) The field indicates the location. If @name='eam.Bin', populate WHSL.
- 2) The field indicates the accounting objects. Name attributes are 'AccountingObject1'-'AccountingObject7'.

M3EDIShipmentSchedule

M3EDIShipmentSchedule/TradingPartnerID ORSHED.RAE0PA; RSS110MI/AddHeader	The field indicates the trading partner.
	The value of this element can be translated before it is displayed as the partner in MEC.
M3EDIShipmentSchedule/ShipmentScheduleHeader/DocumentID/ID ORSHED.RADPNR; RSS110MI/AddHeader @accountingEntity	The field indicates the customer's delivery schedule number.
ORSHED.RACONO ORSHED.RADIVI.; RSS110MI/AddHeader AddItem AddAddress AddInstruction	The field indicates the company and division.
M3EDIShipmentSchedule/ShipmentScheduleHeader/DocumentDateT ORSHED.RAGEDT; RSS110MI/AddHeader	ime The field indicates the date the record was created.
M3EDIShipmentSchedule/ShipmentScheduleHeader/DocumentRefer @type	ence
	Set to 'CustomerPurchaseOrder' if DocumentReference/DocumentID ID is the Customer's order number.
M3EDIShipmentSchedule/ShipmentScheduleHeader/DocumentReferd ORSHED.RACUOR; RSS110MI/AddHeader	ence/DocumentID/ID The field indicates the Customer's order number if DocumentReference@type is 'CustomerPurchaseOrder'.
M3EDIShipmentSchedule/ShipmentScheduleHeader/EffectiveTimePe ORSHED.RAEXDT; RSS110MI/AddHeader	The field indicates the start date.
M3EDIShipmentSchedule/ShipmentScheduleHeader/EffectiveTimePe ORSHED.RAENDT; RSS110MI/AddHeader	riod/EndDateTime The field indicates the last valid date of the record.
M3EDIShipmentSchedule/ShipmentScheduleHeader/DateCode ORSHED.RADTTP; RSS110MI/AddHeader	The field indicates the date used in the delivery schedule for the current item.
	Set to '1' for delivery date. Set to '2' fo Ship-via date. Set to '3' for Good receiving date.
M3EDIShipmentSchedule/ShipmentScheduleHeader/Classification/C	
ORSHED.RARSAC; RSS110Ml/AddHeader	The field indicates the update method if Codes@listID is set to 'Update method'.
	If value is 1 - Complete new delivery schedule. It will replace the previous delivery schedule when activated
@listID	If value is 2 - The plan will replace instructions in the existing delivery schedule within the actual date and time range.
	Set to 'Update method' if Classification/Codes/Code is used as the update method.
M3EDIShipmentSchedule/ShipmentScheduleLine/DocumentReferend ORSITM.RBPOPN; RSS110MI/AddItem	ce/Item/CustomerItemID/ID The field indicates the customer's item number. Set field Alias Category (ALWT) to 6.
M3EDIShipmentSchedule/ShipmentScheduleLine/M3EDIDeliveryInstr ORSINS.RCDEMQ; RSS110MI/AddInstruction	ruction/RequiredQuantity
	The field indicates the requested quantity. ruction/DateTime
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Location	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date.
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Location	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date.
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locati @type ORSADR.READRT; RSS110MI/AddAddress	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11)
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @type ORSADR.READRT; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECDEA; RSS110MI/AddAddress	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11) ion/ID The field indicates the address code.
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @type ORSADR.READRT; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECDEA; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.READR1 ORSADR.READR2 ORSADR.READR3 ORSADR.READR4.; RSS110MI/AddAddress	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11) ion/ID The field indicates the address code. ion/Name The field indicates the company name.
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @type ORSADR.READRT; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECDEA; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.READR1 ORSADR.READR1 ORSADR.READR2 ORSADR.READR3 ORSADR.READR4.; RSS110MI/AddAddress @sequence	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11) ion/ID The field indicates the address code. ion/Name The field indicates the company name. ion/Address/AddressLine The field indicates the address lines. The field indicates the address lines.
M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @type ORSADR.READRT; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECDEA; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.READR1 ORSADR.READR2 ORSADR.READR3	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11) ion/ID The field indicates the address code. ion/Name The field indicates the company name. ion/Address/AddressLine The field indicates the address lines. The field indicates the address lines.
ORSINS.RCRLDT; RSS110MI/AddInstruction M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @type ORSADR.READRT; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECDEA; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.RECONM; RSS110MI/AddAddress M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate ORSADR.READR1 ORSADR.READR1 ORSADR.READR2 ORSADR.READR3 ORSADR.READR4.; RSS110MI/AddAddress @sequence M3EDIShipmentSchedule/ShipmentScheduleLine/ShipToParty/Locate @sequence	The field indicates the requested quantity. ruction/DateTime The field indicates the requested delivery date. ion If set to 'Plant', Address type (ADRT = 10). If set to 'Dock', Address type (ADRT = 11) ion/ID The field indicates the address code. ion/Name The field indicates the company name. ion/Address/AddressLine The field indicates the address lines. The field indicates the address lines. The field indicates the address line sequence. ion/Address/CountryCode The field indicates the country code.

M3EDISupplierInvoice/TradingPartnerID	
	The field indicates the trading partner ID. The value of the element reflects as the partner in MEC.
	The value can be translated in CRS881/882.
M3EDISupplierInvoice/SupplierInvoiceHeader/DocumentID/ID FAPIBH.E5SINO; APS450MI/AddHead	The field indicates the Supplier invoice number.
@schemeName	The field is set to 'VoucherNumber' if the value of element AlternateII ID is to be used as input for Voucher number. If the value is to be used as Correlation ID then this field is set to 'CorrelationID'.
M3EDISupplierInvoice/SupplierInvoiceHeader/AlternateDocumentI	
FAPIBH.E5VONO FAPIBH.E5CORI.; APS450MI/AddHead	The field indicates the Voucher number or the Correlation ID. The field used will be dependent on the value of AlternateID/ID@schemeName.
M3EDISupplierInvoice/SupplierInvoiceHeader/DocumentDateTime FAPIBH.E5IVDT; APS450MI/AddHead	The field indicates the Invoice date.
M3EDISupplierInvoice/SupplierInvoiceHeader/DocumentReference @type	
	The field is set to 'Shipment' or 'AdvanceShipNotice'.
M3EDISupplierInvoice/SupplierInvoiceHeader/DocumentReference FAPIBL.E6SUDO; APS450MI/AddLine	e/DocumentID/ID The field indicates the Delivery note number.
M3EDISupplierInvoice/SupplierInvoiceHeader/SubunitRoundingAr	•
FAPIBL.E6NLAM; APS450MI/AddLine	The field indicates the net amount of supplier invoice line. The field is only applicable for Line type 4- Rounding off.
M3EDISupplierInvoice/SupplierInvoiceHeader/TotalAmount FAPIBH.E5CUAM; APS450MI/AddHead	The field indicates the invoice total amount in foreign currency.
@currencyID FAPIBH.E5CUCD; APS450MI/AddHead	The field indicates the currency code.
M3EDISupplierInvoice/SupplierInvoiceHeader/SupplierParty/Partyl	·
CIDALL FAPIBH.E5SUNO	The field indicates the Supplier number.
S2XALT ; APS450MI CRTVSUMI /AddHead	The data in this element is used as an alternative Supplier ID and looked up with the API CRTVSUMI (Retrieve supplier number) in the file CIDALL (set up in CRS627). The exception is if this element comes with @schemeName 'SupplierNumber'. Then the ID is
GetSupplier	expected to be the Supplier number used in M3 and entered in the Supplier number field (SUNO) in APS450.
	The data in the element SupplierParty/PartyIDs/TaxID can also be used as an alternative SupplierID.
	If several Supplier ID's exist in the BOD they will be looked up in the following order and if found, entered in M3. 1. SupplierID with @schemeName 'SupplierNumber 2. TaxID with @schemeName 'TaxIdentificationNumber' 3. TaxID with @schemeName 'CountryIdentificationNumber' 4. SupplierID without @schemeName 5. TaxID without @schemeName
On the weaklesses	If the look up function fails to match an existing supplier record in file CIDALL, then the Supplier field (SUNO) in APS450 is populated with the first 10 positions of the first ID found in the BOD according to the list above.
@schemeName	The field indicates the schemeName which is used to choose which will be inputed in MI as Supplier if several Supplier ID's exist in the BOD. The order is as follows:
	SupplierID with @schemeName 'SupplierNumber TaxID with @schemeName 'TaxIdentificationNumber' TaxID with @schemeName 'CountryIdentificationNumber' SupplierID without @schemeName TaxID without @schemeName
M3EDISupplierInvoice/SupplierInvoiceHeader/SupplierParty/Partyl	IDs/TaxID The field indicates the Supplier number.
FAPIBH.E5SUNO S2XALT; APS450MI CRTVSUMI	Supplier VAT registration number or organization number can be used as an alternative Supplier ID set up in CRS627. See comments

CRTVSUMI /AddHead GetSupplier

used as an alternative Supplier ID set up in CRS627. See comments for the SupplierParty/PartyIDs/ID element above.

If the look up function fails to match a VAT registration number to an existing supplier record in M3 BE another look up will be done. This time with or without a country code for the first two positions in the number depending on if the number came with two letters in the

May 26, 2023 113

beginning or not. If adding a country code this is picked from the element SupplierParty/Location/CountryCode in the BOD, if any.

M3EDISupplierInvoice/SupplierInvoiceHeader/CustomerParty/Contact/ID

FAPIBH.E5APCD; APS450MI/AddHead

The field indicates the authorized user. If this element has no value, then the value in element CustomerParty/Contact/Name will be used.

M3EDISupplierInvoice/SupplierInvoiceHeader/CustomerParty/Contact/Name

FAPIBH.E5APCD; APS450MI/AddHead

The field indicates the authorized user. This element is only valid if element CustomerParty/Contact/ID has no value.

Possible to set up translation in 'Business Message Data Translation. Displ' (CRS881/CRS882) of the contact name to a M3 BE user ID. Translations are defined per company or division.

Message standard: ION

Business message: SupplierInvoice Parent element: CustomerContact

Data element: Name

If no translation is found no Contact name will be sent to M3. Instead the functionality in M3 could be used to automatically select the Authorized user from the Supplier record or Purchase order.

Note; the M3 BE user ID must be set up in 'Authorized User - Suppl Invoice. Open' (CRS650) for the applicable division.

M3EDISupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/ID

FAPIBH.E5BKID; APS450MI/AddHead

The field indicates the Bank account identity. The field is only used if elements FinancialAccount/BBANID and FinancialAccount/IBANID have no value.

M3EDISupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/BBANID

FAPIBH.E5BKID; APS450MI/AddHead

The field indicates the Bank account identity. The field is only used if element FinancialAccount/IBANID have no value.

M3EDISupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/IBANID

FAPIBH.E5BKID; APS450MI/AddHead

The field indicates the Bank account identity.

${\it M3EDISupplier Invoice/Supplier Invoice Header/Structured Creditor Reference}$

FAPIBA.E7PEXI; APS450MI/AddAddInfo

The field indicates AP Additional information.

This element is used for OCR or KID number. Additional Information category 412, 413 and 414 in M3 is used. The first 45 positions is stored in Info category 412 and if it's a longer number the next 45 positions is stored in 413 and so on.

M3EDISupplierInvoice/SupplierInvoiceHeader/PurchaseOrderReference/DocumentID/ID

FAPIBH.E5PUNO;

FAPIBL.E6PUNO:

APS450MI/AddLine .; /

APS450MI/Addhead,

The field indicates the Purchase order number.

The PurchaseOrderReference will be entered in the PO number

(PUNO) field in APS450. The exception is if no PurchaseOrderReference exists in the SupplierInvoiceLines, if any, then the value in this element will be added to all item and charge lines in the field PO number in APS451.

How the Inv matching (IMCD) parameter in APS450 is set:

0 - No matching to purchase order: If no PurchaseOrderReference and no SupplierInvoiceLines exist in the BOD.

1 - Invoice matching on line level: If SupplierInvoiceLines exist in the BOD.

2 - Inv matching on PO header level: If a PurchaseOrderReference exists in this element in the BOD but no SupplierInvoiceLines.

M3EDISupplierInvoice/SupplierInvoiceHeader/PurchaseOrderReference/ReleaseNumber

FAPIBH.E5PPYR; APS450MI/AddHead

The field indicates the reference number.

M3EDISupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Term/DueDateTime

FAPIBH.E5DUDT; APS450MI/AddHead

The field indicates the payment due date.

M3EDISupplierInvoice/SupplierInvoiceHeader/Tax @sequenceNumber

@type

The field indicates the tax sequence number.

The field determines how the VAT is identified. If @type is set to 'VAT' and:

- 1.)@subType is 'COMBINED' then Combined VAT having an even sequence number is identified as first VAT of the pair and Combined VAT having an odd sequence number is identified as second VAT of the pair.
- 2.) @subType is 'CHAIN' then Chain VAT having an even sequence number is identified as first VAT of the pair and Chain VAT having an odd sequence number is identified as second VAT of the pair.

Tax element that has type VAT but subType other then Combined or Chain is handled as single Tax/VAT and added as a separate line on the invoice.

M3EDISupplierInvoice	
@subType	The field determines how the VAT is identified. If @type is set to 'VAT' and:
	1.)@subType is 'COMBINED' then Combined VAT having an even sequence number is identified as first VAT of the pair and Combined VAT having an odd sequence number is identified as second VAT of the pair. 2.) @subType is 'CHAIN' then Chain VAT having an even sequence number is identified as first VAT of the pair and Chain VAT having an odd sequence number is identified as second VAT of the pair.
	Tax element that has type VAT but subType other then Combined or Chain is handled as single Tax/VAT and added as a separate line on the invoice.
M3EDISupplierInvoice/SupplierInvoiceHeader/Tax/ID FAPIBL.E6VTCD; APS450MI/AddLine	The field indicates the VAT code. This is only applicable for invoice line type 3-VAT.
M3EDISupplierInvoice/SupplierInvoiceHeader/Tax/Calculation/RateNu FAPIBL.E6VTP1 E6VTP2; APS450MI/AddLine	Imeric The field indicates the VAT rate. This is only applicable for invoice line type 3-VAT.
M3EDISupplierInvoice/SupplierInvoiceHeader/Tax/TaxAuthorityAmounts FAPIBL.E6GLAM; APS450MI/AddLine	nt The field indicates the gross amount per line. This is only applicable for invoice line type 3-VAT.
M3EDISupplierInvoice/SupplierInvoiceHeader/Tax/Amount FAPIBL.E6VTA1 E6VTA2; APS450MI/AddLine	The field indicates the VAT amount. This is only applicable for invoice line type 3-VAT.
M3EDISupplierInvoice/SupplierInvoiceHeader/Charge @type	The field is set to 'Allowance' if charge type is allowance.
@sequence FAPIBL.E6CDSE; APS450MI/AddLine	The field indicates the sequence number of costing element. The field is applicable for invoice line type 2- Order charge.
M3EDISupplierInvoice/SupplierInvoiceHeader/Charge/ID FAPIBL.E6CEID; APS450MI/AddLine	The field indicates the costing element. The field is applicable for invoice line type 2- Order charge.
M3EDISupplierInvoice/SupplierInvoiceHeader/Charge/Description FAPIBL.E6CHGT; APS450MI/AddLine	The field indicates the Charge text. The field is applicable for invoice line type 2- Order charge.
	If this element comes with @type 'Allowance' (discount) and the charge amount is positive in the BOD then a negative sign will be added to the charge amount in M3 BE.
	Possible to set up translation in CRS882 on company or division level. Translation of Description to Charge description (CHGT). Message standard: ION Business message: SupplierInvoice Parent element: Charge Data element: Description
	If no translation is found the first 30 positions of the Description is entered in the Charge text (CHGT) field in APS451.
M3EDISupplierInvoice/SupplierInvoiceHeader/Charge/Amount FAPIBL.E6NLAM; APS450MI/AddLine	The field indicates the net amount per line. The field is applicable for invoice line type 2- Order charge.
M3EDISupplierInvoice/SupplierInvoiceHeader/Allowance/ID FAPIBL.E6CEID; APS450MI/AddLine	The field indicates the costing element. The field is applicable for invoice line type 2- Order charge.
M3EDISupplierInvoice/SupplierInvoiceHeader/Allowance/Description FAPIBL.E6CHGT ; APS450MI/AddLine	The field indicates the Charge text. The field is applicable for invoice line type 2- Order charge.
	If this element comes with @type 'Allowance' (discount) and the charge amount is positive in the BOD then a negative sign will be added to the charge amount in M3 BE.
	Possible to set up translation in CRS882 on company or division level. Translation of Description to Charge description (CHGT). Message standard: ION Business message: SupplierInvoice Parent element: Charge Data element: Description

MISEDISupplieritivoice	
	If no translation is found the first 30 positions of the Description is entered in the Charge text (CHGT) field in APS451.
M3EDISupplierInvoice/SupplierInvoiceHeader/Allowance/Amount FAPIBL.E6NLAM; APS450MI/AddLine	The field indicates the net amount per line. The field is applicable for invoice line type 2- Order charge.
M3EDISupplierInvoice/SupplierInvoiceHeader/UserArea FAPBIA.E3PEXI FAPBIA.E3PEXN FAPBIA.E3PEXS.; APS450MI/AddAddInfo	The field is used if element NameValue@name is equal to 'm3_AdditionalInformation'.
PAPBIA.ESPEAS., APS450IVII/AddAddIIIIO	The field indicates the AP additional information, AP information category and GL information sequence number.
M3EDISupplierInvoice/SupplierInvoiceLine/DocumentReference @type	The field is not to !Chipment' or !Advance ChipNetice!
M3EDISupplierInvoice/SupplierInvoiceLine/DocumentReference/Doc	The field is set to 'Shipment' or 'AdvanceShipNotice'.
FAPIBL.E6SUDO; APS450MI/AddLine	The field indicates the Delivery note number.
M3EDISupplierInvoice/SupplierInvoiceLine/Item/ItemID/ID FAPIBL.E6POPN; APS450MI/AddLine	The field indicates the item's Alias number.
	Entered for line type 1 - Item line and 5 - Line charge in APS451.
	If several Item IDs or an Item/Description exists in the BOD the following order will be used and the first value found will be entered for the item line in APS451: 1) ItemID with schemeName = 'Customer' (expected to be M3's item number). 2) Item ID with schemeName 'Supplier'. 3) Item ID with schemeName 'Manufacturer' 4) Item ID with no schemeName
	5) Item/Description The first 30 positions of the value (if longer than this) in the BOD are entered in the Alias number (POPN) field in APS451. If the alias is no found in M3 BE the first 15 positions of the alias number are updated into the item number field (ITNO).
	Alias numbers for suppliers are maintained in PPS040.
M3EDISupplierInvoice/SupplierInvoiceLine/Item/Description FAPIBL.E6POPN; APS450MI/AddLine	The field indicates the item's Alias number.
	Entered for line type 1 - Item line and 5 - Line charge in APS451.
	See comments for Item/ItemID/ID.
M3EDISupplierInvoice/SupplierInvoiceLine/Quantity FAPIBL.E6IVQA; APS450MI/AddLine @unitCode	The field indicates the invoiced quantity in alternate unit of measure.
FAPIBL.E6PUUN; APS450MI/AddLine	The field indicates the purchase order unit of measure.
M3EDISupplierInvoice/SupplierInvoiceLine/UnitPrice/Amount FAPIBL.E6GRPR; APS450MI/AddLine	The field indicates the gross price.
M3EDISupplierInvoice/SupplierInvoiceLine/UnitPrice/PerQuantity FAPIBL.E6PUCD; APS450MI/AddLine @unitCode	The field indicates the purchase price per quantity.
FAPIBL.E6PPUN; APS450MI/AddLine	The field indicates the purchase price unit of measure.
M3EDISupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference FAPIBL.E6PUNO; APS450MI/AddLine	e/ DocumentID/ID The field indicates the purchase order number.
M3EDISupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference	e/LineNumber
FAPIBL.E6PNLI; APS450MI/AddLine M3EDISupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference EADIBLEGENII St. ABS450MI/AddLine	
FAPIBL.E6PNLS; APS450MI/AddLine M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceCharge	The field indicates the purchase order subline number.
@sequence FAPIBL.E6CDSE; APS450MI/AddLine	The field indicates the sequence number for costing element. The field is only applicable for invoice line type 5- Line charge.
M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceCharge/ID FAPIBL.E6CEID; APS450MI/AddLine	The field indicates the costing element. The field is only applicable for invoice line type 5-Line charge.
	The value in this element is used if the Charge/Description element does not exist in the BOD.
	The line charge in M3 BE should also be populated with the following fields from the SupplierInvoiceLines if any of them exist in the BOD: POPN - Alias number IVQA - Invoiced quantity - alternate U/M

PUUN - Purchase order U/M PPUN - Purchase price U/M PUNO - Purchase order number PNLI - Purchase order line PNLS - Purchase order line subnumber

SUDO - Delivery note number

M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceCharge/Description

FAPIBL.E6CHGT ; APS450MI/AddLine

The field indicates the charge text. The field is only applicable for invoice line type 5-Line charge.

Possible to set up translation in CRS882 on company or division

level.

Translation of Description to Charge description (CHGT).

Message standard: ION

Business message: SupplierInvoice Parent element: Charge

Data element: Description

If no translation is found the first 30 positions of the Description is

entered in the Charge text (CHGT) field.

Also see comment for InvoiceCharge/ID.

M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceCharge/Amount

FAPIBL.E6GRPR; APS450MI/AddLine

The field indicates the gross price. The field is only applicable for

invoice line type 5-Line charge.

Also see comment for InvoiceCharge/ID

M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceAllowance/Amount

FAPIBL.E6DIAM; APS450MI/AddLine

The field indicates the discount amount

M3EDISupplierInvoice/SupplierInvoiceLine/InvoiceAllowance/Calculation/RateNumeric

FAPIBL.E6DIPC; APS450MI/AddLine

The field indicates the discount.

117 May 26, 2023

PayFromPartyMaster

PayFromPartyWaster	
PayFromPartyMaster/PartyIDs/ID OCUSMA.OKCUNO ; CRS610MI/Add, ChgBasicData, ChgOrderInfo	The field indicates the unique identification of the customer. Record will be created in M3 'Customer. Open' (CRS610), OCUSMA table.
@accountingEntity OCUSMA.OKCONO OCUSMA.OKDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
PayFromPartyMaster/Name OCUSMA.OKCUNM ; CRS610MI/Add, ChgBasicData	The field indicates the customer name.
PayFromPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF ; CRS610MI/Add, ChgBasicData	The field indicates the customer's contact person.
PayFromPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4.; CRS610MI/Add, ChgBasicData	The field indicates the address line.
@sequence	The field indicates the address line sequence.
PayFromPartyMaster/Location/Address/CityName OCUSMA.OKTOWN ; CRS610MI/Add, ChoBasicData	The field indicates the city name.
PayFromPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR ; CRS610MI/Add, ChgBasicData	The field indicates an area, province or state within a country.
PayFromPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD ; CRS610MI/Add, ChgBasicData	The field indicates the country code.
PayFromPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO ; CRS610MI/Add, ChgBasicData	The field indicates the postal code
PayFromPartyMaster/Location/Address/Preference/Indicator	The field indicates which address details will be saved. Set to "true" in the address is the preferred address or the first instance.
PayFromPartyMaster/Communication/ChannelCode	The field indicates the channel code Phone, Fax or EMail.
PayFromPartyMaster/Communication/UseCode	
PayFromPartyMaster/Communication/DialNumber OCUSMA.OKPHNO	The field indicates the use code Office or Fax. The field indicates the phone and fax number.
OCUSMA.OKPHN2 OCUSMA.OKTFNO.; CRS610MI/Add, ChgBasicData	If ChannelCode is "Phone" and UseCode is "Office", populate Phone Number (PHNO/PHN2). If ChannelCode is "Phone" and UseCode is "Fax" populate Fax Number (TFNO).
PayFromPartyMaster/Communication/URI CEMAIL.CBEMAL ; CRS610MI/Add, ChgBasicData	The field indicates the e-mail address.
PayFromPartyMaster/Communication/Preference/Indicator	The field indicates which communication details will be saved. Set to "true" for data that should be stored.
PayFromPartyMaster/PaymentTermID OCUSMA.OKTEPY ; CRS610MI/ChgOrderInfo	The field indicates the payment term.
PayFromPartyMaster/Status/Code OCUSMA.OKSTAT ; CRS610MI/Add,	The field indicates the customer status.
ChgBasicData	Set to 10 if status is Pending. Set to 20 if status is Open. Set to 90 if status is Closed.
PayFromPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP CRS610MI/Add,ChgBasicData	Customer Types The field indicates the type of customer. If attribute listID is "Customer Types", populate Customer type

PayFromPartyMaster

i ayı ronnı artymastor	
2) OCUSMA.OKTEDL CRS610MI/ChgOrderInfo	(CUTP).
•	2) Incoterms
3) OCUSMA.OKSDST	The field indicates delivery terms, which indicate when the
ĆRS610MI/ChgOrderInfo.; /	responsibility for the transport is transferred from supplier to customer.
	If attribute listID is "Incoterms", populate Delivery terms (TEDL).
	3) District
	The field indicates the district the customer or payer belongs to. If attribute listID is "District", populate District (SDST).
@listID	
	 If attribute listID is "Customer Types", populate Customer type (CUTP).
	2) If attribute listID is "Incoterms", populate Delivery terms (TEDL).
	3) If attribute listID is "District", populate District (SDST).
PavFromPartvMaster/BillToPartv/PartvIDs/ID	

PayFromPartyMaster/BillToParty/PartyIDs/ID OCUSMA.OKINRC; CRS610MI/ChgOrderInfo

The field indicates the unique identification of the customer who receives the invoice.

Person

Parcan/ID	
Person/ID CMNUSR.JUUSID; MNS150MI/Add	This field indicates a unique identity of a user in the M3 system. A new user is created automatically in the operating system as well. If the user is already entered in the operating system, the existing name is used.
	This ID must be used when reporting work performed. It is also used as a basis for the Payroll Administration and Time and Attendance modules.
@accountingEntity CMNUSR.JUCONO CMNUSR. JUDIVI.; / @variationID	This attribute indicates the company and division.
	This attribute indicates the number of variations for the object.
@lid	This attribute indicates the lid of the system where the object is maintained.
Person/DisplayID CMNUSR.JUUSID; MNS150MI/Add	This field indicates a unique identity of a user in the M3 system. A new user is created automatically in the operating system as well. If the user is already entered in the operating system, the existing name is used.
	This ID must be used when reporting work performed. It is also used as a basis for the Payroll Administration and Time and Attendance modules.
Person/Name CMNUSR.JUTX40; MNS150MI/Add	This field indicates the name of the user.
Person/GivenName CEAEMP.EAEMNM; CRS530MI/AddEmployee	This field indicates the employee name. The employee name is used in inquiry types and for sorting. It is therefore important that the the last name is entered first followed by the first name.
Person/Description CMNUSR.JUTX40; MNS150MI/Add	This field indicates the description of the current identity.
Person/LanguageCode CMNUSR.JULANC; MNS150MI/Add	This field indicates the code for the languages that this installation covers. It is possible to install M3 with several different system languages in the same installation. The system language is connected to each M3 user to define what language should be used.
Person/Communication @preferredIndicator	Set to 'False'.
Person/Communication/ChannelCode	This field Indicates the communication/Channel code. Set to 'Phone', 'Email'.
@listID	This field Indicates the communication/Channel code. Set to 'Communication Channels'.
Person/Communication/UseCode	This field indicate the Communication use code. Set to 'Mobile(Office)', 'Office' as this is employee mobile number, phone number, and email address.
@listID	This field indicate the Communication use code ListID. Set to 'Communication Use Codes'.
Person/Communication/DialNumber CMNUSR.JUPHNO, CMNUSR.JUCAPH.; CRS530MI.AddEmployee.PHNO CRS530MI.AddEmployee.CAPH/	This field indicates the user's telephone number and mobile phone.
Person/Communication/URI CEMAIL.CBEMAL; CRS111MI/Add	This field indicates an e-mail address for the user/employee entered.
Person/Communication/Preference/Sequence	This field indicate the Communication/Sequence hardcoded to '1' indicating preferred altermative
Person/Communication/Preference/Indicator	This field indicate the Communication/Preference indicator. Set to 'True'.
Person/PersonnelReference/ID CEAEMP.EAEMNO; CRS530MI/AddEmployee	This field indicates the employee number in M3
Person/PersonnelReference/Name	

Person

This field indicates the employee name in M3
This field indicates the classification type of the user.
This field indicates the status of the user.
10 - Pending
20 - Open
90 - Closed
Alternative 10 is used when a user is first created.

Personnel

Personnel/ID CEAEMP.EAEMNO; CRS530MI/AddEmployee, UpdEmplExp,	The field indicates a unique identity for an employee and is used for
UpdServiceOrder, UpdTimeAcc, UpdBasicData, DelEmployeeS3	reporting work performed.
CEMAIL.CBEMKY; CRS111MI/Add, Change, Delete	
CCACAP.CPOBV2; CBS002MI/Add, Chg, Del	
CROEMP.REEMNO; CBS011MI/Add, Chg, Del.; /	
Personnel/Name CEAEMP.EAEMNM;	This field indicates the employee name.
CRS530MI/AddEmployee, UpdBasicData	This field indicates the employee name.
CIDMAS.IDSUNM; CRS620MI/UpdSupplier	
CBANAC.BCBANA; CRS629MI/AddBankAccount, ChgBasicData.; /	
Personnel/GivenName CEAEMP.EAEMNM; CRS530MI/AddEmployee, UpdBasicData	The field indicates the given name of the employee. If element name is blank, this will be used to form the full name.
Personnel/MiddleName CEAEMP.EAEMNM; CRS530MI/AddEmployee, UpdBasicData	The field indicates the middle name of the employee. If element name is blank, this will be added to the Given Name to form the full name.
Personnel/FamilyName CEAEMP.EAEMNM; CRS530MI/AddEmployee, UpdBasicData	The field indicates the family name of the employee. If element name is blank, this will be added to the Given Name and Middle Name to form the full name.
Personnel/SuffixName CEAEMP.EAEMNM; CRS530MI/AddEmployee, UpdBasicData	The field indicates the suffix name of the employee. If element name is blank, this will be this will be added to the Given, Middle and Family name to form the full name.
Personnel/Communication/ChannelCode	Set to the following: 1.) 'Phone' for Phone number, internal phone number and cellular telephone number. 2.) 'EMail' for E-mail address.
Personnel/Communication/UseCode	Set to the following: 1.) 'Office' for phone number and internal phone number. 2.) 'Mobile(Office)' for cellular telephone.
Personnel/Communication/DialNumber CEAEMP.EAPHNO CEAEMP.EACAPH.; CRS530MI/AddEmployee, UpdBasicData	The field indicates the dial number. Depending on ChannelCode and UseCode, the DialNumber can be the phone or mobile phone number.
Personnel/Communication/Extension CEAEMP.EAIPHN; CRS530MI/AddEmployee, UpdBasicData	The field indicates the internal phone number.
Personnel/Communication/URI CEMAIL.CBEMAL; CRS111Ml/Add, Change, Delete	The field indicates the e-mail address.
Personnel/Skill/Code CCACAP.CPCABI; CBS002MI/Add, Chg, Del	The field indicates a person's skill or capability.
	Value of agreement control property m3beCapabilityType is used as the Capability type (CATY) which must exist in CBS005. The default value is C01.
@listID	Set to 'Skills'.
Personnel/Skill/CompetencyCode CROEMP.REROLE; CBS011MI/Add, Chg, Del @/listID	The field indicates a role or an organizational position.
	Set to 'Competencies'.
Personnel/Skill/EffectiveTimePeriod/StartDateTime CCACAP.CPFRDT CROEMP.REFRDT.; CBS002MI, CBS011MI/Add, Chg, Del	The field indicates the start date when the capability or role is valid.
Personnel/Skill/EffectiveTimePeriod/EndDateTime CCACAP.CPTODT CROEMP.RETODT.; CBS002MI, CBS011MI/Add, Chg, Del	The field indicates the end date when the capability or role is valid.
Personnel/Personnel/ManagerPersonnel @primaryIndicator	Sat to true if manager for primary work assignment
Personnel/ManagerPersonnel/ID	Set to true if manager for primary work assignment.
1.1	2000

Personnel

rei Soilliei	
CEAEMP.EAAPID; CRS530MI/UpdTimeAcc	The field indicates the timesheet approver id.
	The value of EmployeeAssignment/ManagerPersonnel/ID will be prioritized. If no input is given, then the value of this element will be used.
Personnel/CurrencyCode CEAEMP.EACUCS; CRS530MI/UpdServiceOrder	The field indicates the currency in which the sales price has been entered.
Personnel/Status/Code CEAEMP.EAACEM; CRS530MI/AddEmployee, UpdBasicData	The field indicates if the employee should be considered active.
	If Code = 'Open' or 'Working' set the field (ACEM) to 1, else, set to 0.
Personnel/EffectiveTimePeriod/StartDateTime CEAEMP.EAEBDT; CRS530MI/AddEmployee, UpdBasicData	The field indicates the date when the current employment of the employee started.
Personnel/EffectiveTimePeriod/EndDateTime CEAEMP.EAEEDT; CRS530MI/AddEmployee, UpdBasicData, DelEmployeeS3	The field indicates the last date of the employee's employment.
Personnel/CostCenterCode CEAEMP.EATACC; CRS530MI/UpdTimeAcc	The field indicates cost centers to which employees, projects or activities are connected.
Personnel/Facility/IDs/ID CEAEMP.EAFACI; CRS530MI/AddEmployee, UpdBasicData	The field indicates the facility.
	Value fo element EmployeeAssignment/Facility/IDs/ID will be prioritized. If no input is given, then the value of this element will be used.
Personnel/DepartmentCode CEAEMP.EADEPT; CRS530MI/AddEmployee, UpdBasicData	The field indicates a department in which the employee works.
Personnel/WorkCenterID CEAEMP.EAPLGR; CRS530MI/AddEmployee, UpdBasicData	The field indicates a work center, which is a resource in which labor operations are performed.
Personnel/DirectDepositInstruction/FinancialParty/PartyIDs/ID CBANAC.BCBKNO; CRS692MI/AddBankAccount, ChgBasicData	The field indicates the ID of the bank.
CBANAC.BCBKIN; CRS692MI/AddBankAccount, ChgBasicData	The field indicates the identity of a bank account indicator. It will be used to determine the bank account indicator via translation in CRS881. If country is blank, bank account indicator will be retrieved by translating message data BANKACCTINDICATOR.
Personnel/DirectDepositInstruction/FinancialParty/FinancialAccount CBANAC.BCBKID; CRS692MI/AddBankAccount, ChgBasicData	
	If id is blank, bank account id will be retrieved by translating message data BANKACCTID.
	As a pre-requisite to having a bank account, an employee must have a connected supplier. The supplier will be auto-generated using a supplier template and a numbering rule for the naming convention. The supplier template and numbering rule will be retrieved by translating message data SUPPLIERTEMPLATE and SUPPLIERNUMRULE respectively.
Personnel/DirectDepositInstruction/FinancialParty/FinancialAccour CBANAC.BCIBAN; CRS692MI/AddBankAccount, ChgBasicData	nt/IBANID The field indicates the international bank account number.
Personnel/DirectDepositInstruction/FinancialParty/FinancialAccount CBANAC.BCBAF2; CRS692MI/AddBankAccount, ChgBasicData	
Personnel/EmployeeAssignment/PrimaryAssignmentIndicator	The field indicates whether the employee assignment is the primary assignment.
Personnel/EmployeeAssignment/ManagerPersonnel/ID CEAEMP.EAAPID; CRS530MI/UpdTimeAcc	The field indicates the timesheet approver id.
	The value of this element will be prioritized. If no input is given, value of ManagerPersonnel/ID will be used.
Personnel/EmployeeAssignment/PayRate CEAEMP.EASPHO; CRS530MI/UpdServiceOrder	The field indicates the hourly price.
Personnel/EmployeeAssignment/PayRateType	The field indicates the pay rate type.
	If PayRateType = 'Hourly', use PayRate as hourly price.
Personnel/EmployeeAssignment/Facility/IDs/ID CEAEMP.EAFACI; CRS530MI/AddEmployee, UpdBasicData	

Personnel

	The field indicates the facility.
	The value of this element will be prioritized. If no input is given, value of element Facility/IDs/ID will be used.
Personnel/EmployeeAssignment/UserArea CEAEMP.EAACEM; CRS530MI/AddEmployee, UpdBasicData	The field indicates if the employee is deactivated. If @name='Active' and NameValue=false, populate ACEM (Active Employee).
	If partner from input logical id is lawson-ghr or its translated value is AllowStatusChangeViaUserArea, use this instead of Status/Code.

ProductionOrder

ProductionOrder	
ProductionOrder/ProductionOrderHeader/DocumentID/ID MWOOPE.VOMFNO; PMS070MI/RptOperation @Jocation	The field indicates the manufacturing order number.
MWOOPE.VOFACI; PMS070MI/RptOperation	The field indicates the facility.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations MWOOPE.VOOPNO; PMS070MI/RptOperation	s/ID The field indicates the operation number.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations	<u> </u>
MWOOPE.VOSCQA; PMS070MI/RptOperation	The field indicates the scrapped quantity.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations MWOOPE.VOPRNO: PMS070MI /RptOperation	s/OutputItem/ItemID/ID The field indicates the product number.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations	s/OutputItem/ProducedQuantity
MWOOPE.VOMAQA; PMS070MI/RptOperation ProductionOrder/ProductionOrderDetail/BillOfResources/Operations	The field indicates the manufactured quantity.
MWOOPE.VOUSET; PMS070MI/RptOperation	The field indicates the reported machine /process time used for setup and preparations before this operation can begin.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations	s/RunTimeDuration
MWOOPE.VOUPIT; PMS070MI/RptOperation	The field indicates the reported machine /process time used for process a piece or lot using this operation.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations MWOPTR.DJEMNO; PMS070MI/RptOperation	s/OperationPersonReference/ResourceID/ID The field indicates the employee number.
ProductionOrder/ProductionOrderDetail/BillOfResources/Operations MWOPTR.DJMSNO; PMS070MI/RptOperation	The field indicates the kind of machine (item with item category 5) in which the operation was performed.

The field indicates the purchase order header reference used by the supplier.
The field indicates the unique number that is assigned to a purchase order when it is created.
To determine whether to use PPS001MI Confirm or PPS370MI AddHead, use PPS200MI Get to check if Purchase number (PUNO) already exists. If it does, use Confirm. Otherwise, use PPS370MI.
The field indicates the warehouse.
The field indicates the note or text.
The field indicates the note ID or text block.
The field indicates the type of reference to which a reference number refers. If attribute type is 'Agreement', populate OURT with 1 If attribute type is 'Inquiry', populate OURT with 2 If attribute type is 'SupplierQuotation', populate OURT with 3
If attribute type is 'Loan', populate OURT with 4
ntID/ID The field indicates the reference number that is found on the purchase order lines.
The field indicates the supplier.
The field indicates the name of the person to be contacted for issues purchase orders.
Warehouse'
The field indicates the warehouse. If attribute type is 'Warehouse', populate Warehouse (WHLO).
The field indicates the user who ordered or required items for purchase.
sCode
The field indicates the delivery terms. The value can be translated in CRS881/882.
Msg std: ION Vers: 1
Message: Generic
I/O: I Parent element(s): Generic
Date element: IncotermsCode
ermCode The field indicates the freight terms which apply for the delivered goods.
The field indicates the payment term.
TI 6 II: II (II)
The field indicates the sequence of charge ID. The field indicates the charge ID.
The field indicates the charge ID.
The field indicates the distributed charge amount.
n/RateNumeric
n/RateNumeric The field indicates the charge percentage.

PurchaseOrder	The Coldination to the control of th
MXHEAD.IAPYME; PPS370MI /AddHead PurchaseOrder/PurchaseOrderHeader/OrderDateTime	The field indicates the payment method.
MXHEAD.IAPUDT; PPS370MI /AddHead	The field indicates when the purchase order was placed. When entering a new purchase order, today's date will be proposed as the order date, but it may be changed if necessary.
PurchaseOrder/PurchaseOrderHeader/UserArea 1) MXHEAD.IAUSD4; PPS370MI/AddHead 2) MXHEAD.IAUSD5; PPS370MI/AddHead 2) MXHEAD.IAUCA1-IAUCA0 MXHEAD.IAUDN1-IAUDN6 MXHEAD.IAUID1-IAUID3 MXHEAD.IAUCT1; PPS370MI/AddHead.; /	1) Request ID The field indicates the reference field (USD4). If attribute name is 'RequestID', populate USD4. 2) Request number The filed indicates the reference field (USD5). If attribute name is 'RequestNumber', populate USD5. 3) User-defined field The field indicates a user-defined field for displaying and storing your own information. Field is populated according to the FLDI value from the attribute name. m3.IA <fldi>-<tx15></tx15></fldi>
PurchaseOrder/PurchaseOrderHeader/Classification/Codes/Code 1) MXHEAD.IAFACI; PPS370MI AddHead 2) MXHEAD.IAORTY; PPS370MI AddHead 3) MXHEAD.IAPROJ; PPS370MI AddHead 4) MXHEAD.IAELNO; PPS370MI AddHead 5) MXHEAD.IACUCD; PPS370MI AddHead 6) MXHEAD.IAHAFE; PPS370MI AddHead 7) MXHEAD.IAMODL; PPS370MI AddHead 8) MPPBOR.ORBAOR; PPS370MI StartEntry.; /	1) Facility The field indicates the facility. If attribute listID is 'Facilities', populate Facility (FACI). 2) Order Type The field indicates the order type.If attribute listID is 'Order Types', populate Order Type (ORTY). 3) Project Number
	The field indicates the unique ID for a project.If attribute listID is 'Project Numbers', populate Project Number (PROJ). 4) Project Element The field indicates an element which is part of a project structure. An element can refer to an activity, a subproject or a main project.If attribute listID is 'Project Elements', populate Project Element (ELNO 5) Currency The field indicates the abbreviation for the currency.If attribute listID is 'Currencies', populate Currency (CUCD).
	6) Harbor/Airport The field indicates the ID of the harbor or airport. It is used for reporting purposes in the trade statistics. If attribute listID is 'Harbor Airports', populate Harbor/Airport (HAFE). 7) Delivery Method The field indicates how the delivery is made. If attribute listID is
	'Delivery Methods', populate Delivery Method (MODL). The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: PurchaseOrder I/O: I Parent element(s): PurchaseOrder Date element: DeliveryMethod
	8) Batch Origin The field indicates purchase order batch origin. The batch origin is a unique identity for each external or internal system using the PO batch entry in order to create purchase orders in M3. If attribute listID is 'Batch Origins', populate Batch Origin (BAOR).
@listID	 1.) 'Facilities'. 2.) 'Order Types'. 3.) 'Project Numbers'. 4.) 'Project Elements' . 5.) 'Currencies'. 6.) 'Harbor Airports'. 7.) 'Delivery Methods'. 8.) 'Batch Origins'.
PurchaseOrder/PurchaseOrderHeader/BuyerReference/IDs/ID MXHEAD.IABUYE; PPS370MI/AddHead	The field indicates the buyer.
PurchaseOrder/PurchaseOrderHeader/RemitToParty/PartyIDs/ID MXHEAD.IAPRSU; PPS370MI /AddHead	The field indicates a valid supplier number for the supplier that should receive the payment. Payee is entered only if the supplier and the

Infor May 26, 2023 127

The field indicates a valid supplier number for the supplier that should receive the payment. Payee is entered only if the supplier and the payee are not the same legal entity.

PurchaseOrder/PurchaseOrderLine/LineNumber	T. 611: 1: 4 11
MPLINE.IBPNLI MPLINE.IBPNLS MXHEAD.IAPNLI	The field indicates the sequence number assigned to the purchase order line. This element may also include the puchase order subline number.
;; PPS001MI PPS370MI/ConfirmLine AddLine	number.
PurchaseOrder/PurchaseOrderLine/Note MXTEXT.TLTXT1, TLTXT2, TLTXT3, TLTXT4, TLTXT5; PPS370MI/	The field indicates the note or text.
AddText @noteID MXTEXT.TLTXVR: PPS370MI/AddText	The field indicates the note ID or text block.
PurchaseOrder/PurchaseOrderLine/DocumentReference	The field indicates the note in of text block.
@type MXHEAD.IBRORC ; PPS370MI /AddLine	The field indicates the origin of the reference order number (RORC). If attribute type is 'ProductionOrder', populate RORC with 1 If attribute type is 'PurchaseOrder', populate RORC with 2 If attribute type is 'SalesOrder', populate RORC with 3 If attribute type is 'RequisitionOrder', populate RORC with 4 If attribute type is 'DistributionOrder', populate RORC with 5 If attribute type is 'WorkOrder', populate RORC with 6 If attribute type is 'ServiceOrder', populate RORC with 7 If attribute type is 'ProjectOrder', populate RORC with 8 If attribute type is 'ClaimOrder', populate RORC with 9
PurchaseOrder/PurchaseOrderLine/DocumentReference/DocumentID/ MXHEAD.IBRORN: PPS370MI /AddLine	//D The field indicates the reference order number.
PurchaseOrder/PurchaseOrderLine/DocumentReference/LineNumber MXHEAD.IBRORL; PPS370MI/AddLine	
PurchaseOrder/PurchaseOrderLine/DocumentReference/SubLineNum MPLINE.IBRORX; PPS370MI/AddLine	·
PurchaseOrder/PurchaseOrderLine/Item/ItemID/ID MXLINE.IBITNO MXLINE.IBSITE.; PPS370MI PPS370MI/AddLine @schemeAgencyID	The field indicates the item number. If the attribute schemeAgencyID is 'Supplier', the item indicates the supplier item number.
	Set to 'Supplier' if ItemID/ID indicates the supplier item number.
PurchaseOrder/PurchaseOrderLine/Item/Description MPLINE.IBPITT; PPS001MI/AddLine	The field indicates the item description.
PurchaseOrder/PurchaseOrderLine/Quantity MXHEAD MPLINE.IBORQA IBCFQA; PPS370MI PPS001MI/AddLine ConfirmLine	The field indicates the ordered quantity .
PurchaseOrder/PurchaseOrderLine/UnitPrice/Amount MXLINE MPLINE .IBPUPR IBCPPR ; PPS370MI PPS001MI /AddLine ConfirmLine	The field indicates the purchase price.
PurchaseOrder/PurchaseOrderLine/RequiredDeliveryDateTime MPLINE.IBCODT; PPS001MI/ConfirmLine	The field indicates the delivery date that is to be specified for the supplier on the purchase order document.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location @type	Set to 'Warehouse' if ShipToParty/Location/ID refers to the warehouse.
PurchaseOrder/PurchaseOrderLine/ShipToParty/Location/ID MXHEAD.IAWHLO; PPS370MI /AddHead	The field indicates the warehouse. If attribute type is 'Warehouse', populate Warehouse (WHLO).
PurchaseOrder/PurchaseOrderLine/TransportationTerm/IncotermsCo. MPLINE.IBTEDL; PPS001MI/ConfirmLine	
	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: I Parent element(s): Generic Date element: IncotermsCode

<u>FulcilaseOluei</u>	
PurchaseOrder/PurchaseOrderLine/DistributedCharge @sequence	
MXOEXP.IVCDSE; PPS370MI/AddCharge	The field indicates the sequence of charge ID.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/ID MXOEXP.IVSUCE; PPS370MI/AddCharge	The field indicates the distributed charge id.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Description	 1.)'Confirmed discount 1',if Confirmed discount 1 field is populate. 2.)'Confirmed discount 2' if Confirmed discount 2 field is populate. 3.)'Confirmed discount 3' if Confirmed discount 3 field is populate. 4.)'Order discount 1' if Order discount 1 field is populate. 5.)'Order discount 2' if Order discount 2 field is populated. 6.)'Order discount 3' if Order discount 3 field is populated.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Amount MPLINE.IBCFD1-IBCFD3 PPS001MI/ConfirmLine MXLINE.IBODI1- IBODI3 PPS370MI/AddBatchLine MXOEXP.IVCEVA PPS370MI/AddCharge.; PPS001MI/ConfirmLine	The field indicates the discounts for an order or the charge amount.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Calculation/RaMXOEXP.IVOVHE; PPS370MI/AddCharge	ateNumeric The field indicates the charge percentage.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Tax	
@type	The field indicates the attribute type equals to 'VAT' set vat code to distributed charge tax id.
PurchaseOrder/PurchaseOrderLine/DistributedCharge/Tax/ID MXLINE.IBVTCD; PPS370MI/AddLine	The field indicates the VAT code.
PurchaseOrder/PurchaseOrderLine/FreightClassification/Codes/Code MPLINE.IBMODL; PPS001MI/ConfirmLine	The field indicates the delivery method.
	The value can be translated in CRS881/882. Msg std: ION Vers: 1 Message: Generic I/O: I Parent element(s): Generic Date element: TransportationMethodCode
PurchaseOrder/PurchaseOrderLine/PromisedDeliveryDateTime MPLINE.IBCODT; PPS001MI/ConfirmLine	The field indicates the confirmed delivery date.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/LineNum MPLINE.IBPNLI MPLINE.IBPNLS .; PPS001MI	The field indicates the line number and the subline number. If value for this element exists and PurchaseOrderLine/Classification/ Codes/Code with attribute listID 'Reservation Level' and 'Pricing Level' do not exist, order line splits will be handled.
/ConfirmLine PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Quantity	
MPLINE.IBCFQA; PPS001MI/ConfirmLine PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/UnitPrice MPLINE .IBCPPR ; PPS001MI /ConfirmLine	The field indicates the confirmed quantity of the subline . 2/Amount The field indicates the confirmed purchase price.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Promised MPLINE.IBCODT; PPS001MI/ConfirmLine	dDeliveryDateTime The field indicates the confirmed delivery date.
PurchaseOrder/PurchaseOrderLine/PurchaseOrderSubLine/Classification MPLIND.ICOEND; PPS001MI/ConfirmLine	ation/Codes/Code The field indicates if the delivery of an order line is completed. Remaining quantity will not be back ordered. The value from the map is boolean and will be converted to 1 or 0 before using as input to MI program. If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
@listID	If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).
PurchaseOrder/PurchaseOrderLine/UserArea 1) MXLINE.IAUSD4; PPS370MI/AddLine 2) MXLINE.IAUSD5; PPS370MI/AddLine 3) MXLINE:IBITNO; PPS370MI/AddLine 4) MXLINE:IBPURC; PPS370MI/AddLine 5) MXCCST.SCAIT1;	1) Request ID The field indicates the reference field (USD4). If attribute name is 'RequestID', populate USD4. 2) Request number The field indicates the reference field (USD5). If attribute name is 'RequestNumber', populate USD5. 3) Punch-out item The field indicates the item number (ITNO) to be translated in CRS881.

PPS370MI/AddAccString 6) MXCCST.SCAIT2: PPS370MI/AddAccString 7) MXCCST.SCAIT3; PPS370MI/AddAccString 8) MXCCST.SCAIT4; PPS370MI/AddAccString 9) MXCCST.SCAIT5; PPS370MI/AddAccString 10) MXCCST.SCAIT6; PPS370MI/AddAccString 11) MXCCST.SCAIT7; PPS370MI/AddAccString 12) MXLINE.IBUCA1-IBUCA0 MXLINE.IBUDN1-IBUDN6 MXLINE.IBUID1-IBUID3 MXLINE.IBUCT1; PPS370MI/AddLine.; /

If attribute name is 'Punch-Out Item', populate ITNO.

4) Requester ID

The field indicates the requisition by id (PURC)

If attribute name is 'RequesterID', populate PURC.

5) Account number

The field indicates the account number (AIT1).

If attribute name is 'fsm.AccountNumber', populate AIT1.

6) Accounting dimension 2

The field indicates the accounting dimension 2 (AIT2).

If attribute name is 'fsm.FinanceDimension1', populate AIT2.

7) Accounting dimension 3

The field indicates the accounting dimension 3 (AIT3).

If attribute name is 'fsm.FinanceDimension2', populate AIT3.

8) Accounting dimension 4

The field indicates the accounting dimension 4 (AIT4).

If attribute name is 'fsm.FinanceDimension3', populate AIT4.

9) Accounting dimension 5

The field indicates the accounting dimension 5 (AIT5).

If attribute name is 'fsm.FinanceDimension4', populate AIT5.

10) Accounting dimension 6

The field indicates the accounting dimension 6 (AIT6).

If attribute name is 'fsm.FinanceDimension5', populate AIT6.

11) Accounting dimension 7

The field indicates the accounting dimension 7 (AIT7).

If attribute name is 'fsm.FinanceDimension6', populate AIT7.

12) User-defined field

The field indicates a user-defined field for displaying and storing your own information.

Field is populated according to the FLDI value from the attribute name

m3.IB<FLDI>-<TX15>

PurchaseOrder/PurchaseOrderLine/ContractReference/DocumentID/ID

MXLINE.OURR; PPS370MI/AddLine

The field indicates the contract or agreement number.

PurchaseOrder/PurchaseOrderLine/Classification/Codes/Code

1) MXLINE.IBCOCE PPS370MI/Addline

2) MPLIND.ICOEND PPS001MI/ConfirmLine

3) MPLINE.IBCIAD PPS001MI/ConfirmLine

4) MPLINE.IBHAFE PPS001MI/ConfirmLine.; / 1) Cost Center

The field indicates the cost center associated with the record. If attribute listID is 'Cost Center', populate Cost center (COCE).

2) Flagged as completed

The field indicates if the delivery of an order line is completed. Remaining quantity will not be back ordered. The value from the map is boolean and will be converted to 1 or 0 before using as input to MI program.

If attribute listID is 'Flag Complete', populate Flagged as completed (OEND).

3) Confirmed pickup address

The field indicates the confirmed pickup address.

If attribute listID is 'Confirmed Pickup Address', populate Confirmed Pickup address (CIAD).

4) Harbor/airport

The field indicates the ID of the harbor or airport.

If attribute listID is 'Harbor Airports', populate Harbor/airport (HAFE).

Note: Attribute listID 'Reservation Level' (SRCD) and 'Pricing Level' (PSET) are checked on when to call PPS001MI ConfirmLine.

PPS001MI ConfirmLine for PurchaseOrderSubLine will only be called when SRCD is not 1 and PSET is not 1 or 2.

PPS001MI ConfirmLine for PurchaseOrderLine will only be called when SRCD is not 2 and PSET is not 3.

- 1) If attribute listID is 'Cost Center', populate Cost center (COCE).
- 2) If attribute listID is 'Flag Complete', populate Flagged as completed
- 3) If attribute listID is 'Confirmed Pickup Address', populate Confirmed Pickup address (CIAD).
- 4) If attribute listID is 'Harbor Airports', populate Harbor/airport (HAFE).

@listID

QualitySpecification

QualitySpecification/QualitySpecificationHeader/SpecificationID/ID QMSSPE.QPSPEC: The field indicates the quality specification ID which are comprised of QMS200MI/AddSpec, quality requirements specific to items. UpdSpec QMSTST.QSSPEC: QMS201MI/AddSpecTest, UpdSpecTest, DltSpecTest QualitySpecification/QualitySpecificationHeader/Description QMSSPE.QPTX40; QMS200MI/AddSpec, UpdSpec The field indicates the description. QualitySpecification/QualitySpecificationHeader/Note QMSSPE.QPSI01 The field indicates the notes or comments. QMSSPE.QPSI02 Each field has a maximum of 50 characters. New line is used as QMSSPE.QPSI03 delimiter. QMSSPE.QPSI04 QMSSPE.QPSI05 Agreement control property m3beNotesHandling is created with .; QMS200MI/AddSpec, UpdSpec default value set to false. This means that the notes handling functionality is disabled by default. Only when the m3beNotesHandling value is set to true are the values of QualitySpecificationHeader/Note mapped to QMS200MI.AddSpec and UpdSpec Comments 1 -5 (SI01-SI05). If QualitySpecificationHeader/LabManagerPerson/IDs/ID has value, retain the mapping to QMS100MI.AddSpec and UpdSpec SI02. The maximum characters for the Note that can be stored in M3 is only 200 in this case since SI02 won't be used for the Note. If actionCode='Change', input '?' to the applicable QMS100MI.UpdSpec SI01-SI05 field to delete the data if no Note data exists in the BOD. QualitySpecification/QualitySpecificationHeader/Status/Code QMSSPE.QPSTAT; QMS200MI/AddSpec, UpdSpec The field indicates the status. Set to 'Preliminary' for status 10 - Preliminary Set to 'Approved' fro status 20 - Approved Set to 'Deactivated' for status 90 - Deactivated QualitySpecification/QualitySpecificationHeader/EffectiveTimePeriod/StartDateTime QMSSPE.QPQSE1 The field indicates the date on which the quality specification will QMSSPE.QPQSE2; start. The first 8 digits will populate effective date field (QSE1). The QMS200MI/AddSpec, next digits will populate effective time field (QSE2). UpdSpec Time component will not be retrieved if partner from logicalID is QMSTST.QSQSE1 translated to PLMforProcessHandling in CRS881/CRS882. QMSTST.QSQSE2; QMS201MI/AddSpecTest, UpdSpecTest, DltSpecTest QPQSE2; QualitySpecification/QualitySpecificationHeader/EffectiveTimePeriod/EndDateTime QMSSPE.QPQSI1, QPQSI2; QMS200MI/AddSpec, UpdSpec The field indicates the date on which the quality specification will end. The first 8 digits will populate inactive date field (QSI1). The next digits will populate inactive time field (QSI2). Time component will not be retrieved if partner from logicalID is translated to PLMforProcessHandling in CRS881/CRS882 QualitySpecification/QualitySpecificationHeader/Name QMSSPE.QPTX40; QMS200MI/AddSpec, UpdSpec The field indicates the description. The field is only applicable if element QualitySpecificationHeader/Description is blank QualitySpecification/QualitySpecificationHeader/Item/ItemID/ID QMSSPE.QPITNO; The field indicates the item number QMS200MI/AddSpec, UpdSpec QMSTST.QSITNO; QMS201MI/AddSpecTest UpdSpecTest, DltSpecTest

QualitySpecification/QualitySpecificationHeader/QualityGroup

QMSSPE.QPQMGP; QMS200MI/AddSpec, UpdSpec The field indicates the quality group which provides a way to classify items that have similar quality specifications.

QualitySpecification QMSTST.QSQMGP; QMS201MI/AddSpecTest UpdSpecTest, DltSpecTest :;/ QualitySpecification/QualitySpecificationHeader/CustomSpecificationIndicator QMSSPE.QPSPET; QMS200MI/AddSpec, UpdSpec The field indicate custom specificationspecification/QualitySpecificationHeader/ValidUses QMSSPE.QPAUAT; QMS200MI/AddSpec, UpdSpec The field indicate QI requests. Set QualitySpecification/QualitySpecificationHeader/AutoAttachIndicator QMSSPE.QPAUAT; QMS200MI/AddSpec, UpdSpec The field indicate QI requests. Set QualitySpecification/QualitySpecificationHeader/ProcessBlockingMethodCode QMSSPE.QPTPSH; QMS200MI/AddSpec, UpdSpec The field indicate quality inspection Set to 'SHIPMEN QualitySpecification/QualitySpecificationHeader/RetestIndicator QMSSPE.QPSRTT; QMS200MI/AddSpec, UpdSpec The field indicate retesting a partice else, set to 'false QualitySpecification/QualitySpecificationHeader/ReclassifyIndicator QMSSPE.QPSRCL; QMS200MI/AddSpec, UpdSpec The field indicate retesting a partice else, set to 'false

QualitySpecification/QualitySpecificationHeader/LabManagerPerson/IDs/ID QMSSPE.QPSI02; QMS200MI/AddSpec, UpdSpec The

ality Cnacification /Ovality Cnacification Handay/Conica Numb

QualitySpecification/QualitySpecificationHeader/CopiesNumber QMSSPE.QPNBEX; QMS200MI/AddSpec, UpdSpec

QualitySpecification/QualitySpecificationHeader/UserArea QMSSPE.QPSBLN, QPSAGN, QPSDOR; QMS200MI/AddSpec, UpdSpec The field indicates if the quality specification is a standard or a custom specification. Set to 'true' for custom and 'false' for standard.

The field indicates if the specification will be automatically attached in QI requests. Set to 'true' to activate the setting, else, set to 'false'.

The field indicates if the specification will be automatically attached in QI requests. Set to 'true' to activate the setting, else, set to 'false'.

The field indicates whether a quality specification will be used on quality inspection request prior to the shipment of the item.

Set to 'SHIPMENT' to activate this setting.

The field indicates whether a quality specification will be used for retesting a particular lot in stock. Set to 'true' to activate the setting, else, set to 'false'.

The field indicates whether a quality specification will be used for reclassification purposes. Set to 'true' to activate the setting, else, set

The field indicates the person responsible for ensuring that the analysis is performed.

The field indicates the number of copies. The number of copies could, for example, refer to the number of batch reports to be printed or the number of copies that should be distributed.

number of copies that should be distributed.

The field indicates the following:

- 1.) NameValue@name = 'Blending' indicates whether the specification is to be used for blended lot. Set element NameValue to 'true' to activate the setting.
- 2.) NameValue@name = 'GrowerAgreement' indicates whether the specification should be available for attachment to an agreement line. Set element NameValue to 'true' to activate the setting.
- 3.) NameValue@name = 'RetestDOReceipt' indicates whether the specification is automatically attached to the Quality Inspection request for the receiving warehouse for a distribution order. Set element NameValue to 'true' to activate the setting.

QualitySpecification/QualitySpecificationLine/QualityTest/IDs/IDQMSTST.QSQTST; QMS201MI/AddSpecTest, UpdSpecTest,
DltSpecTest

The field indicates the specification test.

A test contains the quality measurements or parameters that determine whether items pass or fail quality testing. Quality tests define the frequency in which the test is performed, the sample sizes that are used, and the acceptable values for testing results.

QualitySpecification/QualitySpecificationLine/QualityTest/Description
QMSTST.QSTX40; QMS201MI/AddSpecTest, UpdSpecTest

DltSpecTest

The field indicates the test description.

QualitySpecification/QualitySpecificationLine/QualityTest/EffectiveTimePeriod/StartDateTime
QMSTST.QSQTE1, QSQTE2; QMS201MI/AddSpecTest, UpdSpecTest, The field indicates the di

1MI/AddSpecTest, UpdSpecTest, The field ind start. First 8

The field indicates the date and time on which the quality test will start. First 8 digits refer to the effective date (QTE1). The next digits refer to effective time (QTE2).

Time component will not be retrieved if partner from logicalID is translated to PLMforProcessHandling in CRS881/CRS882.

QualitySpecification/QualitySpecificationLine/QualityTest/EffectiveTimePeriod/EndDateTime

QMSTST.QSQTI1, QSQTI2; QMS201MI/AddSpecTest, UpdSpecTest

The field indicates the date and time on which the quality test will end. First 8 digits refer to the effective date (QTI1). The next digits refer to effective time (QTI2).

Time component will not be retrieved if partner from logicalID is translated to PLMforProcessHandling in CRS881/CRS882.

QualitySpecification/QualitySpecificationLine/QualityTest/TestResultTypeCode

QMSTST.QSTSTY; QMS201MI/AddSpecTest, UpdSpecTest, DltSpecTest

The field indicates if a quality test is of the type quantitative, numeric qualitative, or qualitative.

Qua	litySp	pecific	cation

QuantySpecification	
	Set the field to: '0' for Quantitative '1' for Numeric qualitative '2' for Qualitative
Quality Chaoification/Quality Chaoification Line /Quality Tact/Ta-4/fa-4/fa-4/fa-4/fa-4/fa-4/fa-4/fa-4/f	
QualitySpecification/QualitySpecificationLine/QualityTest/TestValueT QMSTST.QSVLTP; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates how test result values will be set up. Test results may be based on an expected value or by setting a range of values. In addition, if the expected value is not required to be an exact number, there may be a setup where a test result may be less than or greater than the defined target value. Set the field to: '0' for Expected value '1' for Range of values '2' for Target values
QualitySpecification/QualitySpecificationLine/QualityTest/Significant	Diaits
QMSTST.QSDCCD; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates how many decimal places are to be used in connection with processing quantities. Zero to six decimal places may be used.
QualitySpecification/QualitySpecificationLine/QualityTest/DefaultReq QMSTST.QSREQD; QMS201MI/AddSpecTest, UpdSpecTest	uiredIndicator The field indicates whether a test is required to pass in order to pass the related quality specification. Set to 'true' to activate the setting, else, set to 'false'.
QualitySpecification/QualitySpecificationLine/QualityTest/TestPriority	· · · · · · · · · · · · · · · · · · ·
QMSTST.QSQTSP; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates whether the quality test needs to be performed as soon as possible (high priority) or has a lower priority.
QualitySpecification/QualitySpecificationLine/QualityTest/TestOrder QMSTST.QSEXSQ; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the numeric order that a test has in a QI request. The field value determines the order in which the test should be executed in the lab to limit sample size and contamination.
QualitySpecification/QualitySpecificationLine/QualityTest/TestClass QMSTST.QSTCLS; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates a user-defined code used to classify quality tests based on their nature.
QualitySpecification/QualitySpecificationLine/QualityTest/TestAttribu QMSTST.QSATID; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the unique ID for an attribute. Normally attributes are used to store values that are connected to an item. Both the item and attribute are required to describe all the characteristics of the lot/balance identity.
QualitySpecification/QualitySpecificationLine/QualityTest/TestStanda QMSTST.QSINSD; QMS201MI/AddSpecTest, UpdSpecTest	ord The field indicates the generally accepted requirements that are followed by the members of an industry.
QualitySpecification/QualitySpecificationLine/QualityTest/SamplingReQMSTST.QSSMPR; QMS201MI/AddSpecTest, UpdSpecTest	equiredIndicator The field indicates whether the test will require a sample to be taken when the test is performed. Set to 'true' to activate the setting, else, set to 'false'.
QualitySpecification/QualitySpecificationLine/QualityTest/InternalTes	tIndicator
QMSTST.QSINTR; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates whether a test is used for internal purposes only. Set to 'true' to activate the setting, else, set to 'false'.
QualitySpecification/QualitySpecificationLine/QualityTest/TestRate/Fr QMSTST.QSFRPR; QMS201MI/AddSpecTest, UpdSpecTest	requencyType The field indicates the frequency basis on which quality test is performed. Set the field to: '0' for Lot (number of test sequences per lot) '1' for Units (samples taken every certain number of units)
QualitySpecification/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualityTest/TestRate/QualitySpecificationLine/QualitySpec	The field indicates the size of the sample. It only applies in cases where the FrequencyType element value is 1 (Units).
@unitCode OMSTST OSEDLIM: OMS201MI/AddSpaceTest LindSpaceTest	The field indicates the unit of measure of the frequency quantity
QMSTST.QSFRUM; QMS201MI/AddSpecTest, UpdSpecTest QualitySpecification/QualitySpecificationLine/QualityTest/TestRate/Fr	The field indicates the unit of measure of the frequency quantity.
QMSTST.QSFRTI; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates how many times a test is performed based on the value defined in the FrequencyType element.
QualitySpecification/QualitySpecificationLine/QualityTest/SampleTyp QMSTST.QSSMTP; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates a user-defined code used to classify a sample.
QualitySpecification/QualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualityTest/SampleQualitySpecificationLine/QualitySpecification	antity The field indicates the size of the sample that will be taken for use in a quality test.
@unitCode QMSTST.QSSMUM; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the unit of measure of the sample size that will be taken when testing is performed.
QualitySpecification/QualitySpecificationLine/QualityTest/Destructive QMSTST.QSDSSM; QMS201MI/AddSpecTest, UpdSpecTest	

QualitySpecification

QuantySpecification	
QualitySpecification/QualitySpecificationLine/QualityTest/RetainSamp QMSTST.QSRTSM; QMS201MI/AddSpecTest, UpdSpecTest	DieIndicator The field indicates whether the sample will be reserved or stored for further testing. Set to 'true' to activate the setting, else, set to 'false'.
QualitySpecification/QualitySpecificationLine/QualityTest/Measureme QMSTST.QSMSUR; QMS201MI/AddSpecTest, UpdSpecTest	ntMethod The field indicates a user-defined identification that may be used to describe the methods that should be used at inspection.
QualitySpecification/QualitySpecificationLine/QualityTest/Measureme QMSTST.QSMSIN; QMS201MI/AddSpecTest, UpdSpecTest	ntResourceReference/ResourceID/ID The field indicates a user-defined identity that may be used to describe the equipment to use in performing an inspection.
QualitySpecification/QualitySpecificationLine/QualityTest/Measureme	ntResourceReference/Quantity
@unitCode QMSTST.QSTEUM; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the unit in which the test should be measured. The test unit of measure also controls accuracy in the test using the decimal precision set.
QualitySpecification/QualitySpecificationLine/QualityTest/Department QMSTST.QSDEPT; QMS201MI/AddSpecTest, UpdSpecTest	Code The field indicates the name of the department.
QualitySpecification/QualitySpecificationLine/QualityTest/Laboratory/ QMSTST.QSLABO; QMS201MI/AddSpecTest, UpdSpecTest	SupplierParty/PartyIDs/ID The field indicates a user-defined ID that may be used to describe the part of a control department that performs an inspection.
QualitySpecification/QualitySpecificationLine/QualityTest/CalculatedTQMSTST.QSTCAL; QMS201MI/AddSpecTest, UpdSpecTest	
QualitySpecification/QualitySpecificationLine/QualityTest/QualitativeCQMSTST.QSQTCD; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the name given to a quality test that is of numeric qualitative type. Numeric qualitative tests are assigned a certain number of discrete test result values.
QualitySpecification/QualitySpecificationLine/QualityTest/QualitativeTemperature QMSTST.QSQLCD; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates a way to identify tests by reflecting the subjective quality of an item, such as feel, taste, image, or color. Knowledge of these qualitative aspects is gained through observation combined with interpretative understanding of the associated item.
@type	The field indicates where the value limit is inputed. 1.) Set to 'Target' to populate expected target value. 2.) Set to 'Minimum' to populate expected value minimum. 3.) Set to 'Maximum' to populate expected value maximum. 4.) Set to 'ExternalTarget' to populate external target value. 5.) Set to 'ExternalMinimum' to populate external lab minimum value. 6.) Set to 'ExternalMaximum' to populate external lab maximum value. 7.) Set to 'AlarmTarget' to populate alarm target value. 8.) Set to 'AlarmMinimum' to populate alarm limit minimum value. 9.) Set to 'AlarmMaximum' to populate alarm limit maximum value.
QualitySpecification/QualitySpecificationLine/QualityTest/ValueLimit/	
QMSTST.QTEVTG QTEVMN QTEVMX QTTVTG QTEXMN QTEXMN QTEXMX QTAVTG QTAUTG QTALMN QTALMN QTALMX; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the following: 1.) expected target value. 2.) expected value minimum. 3.) expected value maximum. 4.) external target value. 5.) external lab minimum value. 6.) external lab maximum value. 7.) alarm target value. 8.) alarm limit minimum value. 9.) alarm limit maximum value.
QualitySpecification/QualitySpecificationLine/QualityTest/ValueLimit/QMSTST.QSQOP1, QSQOP2, QSQOP3; QMS201MI/AddSpecTest, UpdSpecTest	The field indicates the comparison operator to be entered. 1.) Set to '0' for blank operator. 2.) Set to 'GT' for greater than (>). 3.) Set to 'GE' for greater than or equal (>=). 4.) Set to 'LT" for less than (<). 5.) Set to 'LE' for less than or equal (<=). 6.) Set to 'EQ' for equal (=).
QualitySpecification/QualitySpecificationLine/IncludeTestInPopuestIn	The field that will be populated is based on the ff: 1.) If ValueLimit@type is 'Target', field expected operator (QOP1) will be populated. 2.) If ValueLimit@type is'ExternalTarget', field external operator (QOP2) will be populated. 3.) If ValueLimit@type is 'AlarmTarget', field, alarm operator (QOP3) will be populated.

QualitySpecification/QualitySpecificationLine/IncludeTestInRequestIndicator
QMSTST.QSITQR; QMS201MI/AddSpecTest, UpdSpecTest The fie

The field indicates whether the quality test should be included in the QI request. Set to 'true' to activate the setting, else, set to 'false'.

Infor May 26, 2023 134

QualitySpecification

QualitySpecification/QualitySpecificationLine/PrintTestOnCOAIndicator QMSTST.QSPTCA; QMS201MI/AddSpecTest, UpdSpecTest The field indicates whether the specification test will be printed on the Certificate of Analysis. Set to 'true' to activate the setting, else, set to QualitySpecification/QualitySpecificationLine/PrintTestOnSpecIndicator QMSTST.QSPTSP; QMS201MI/AddSpecTest, UpdSpecTest The field indicates whether the specification test will be printed on the specification document. Set to 'true' to activate the setting, else, set to QualitySpecification/QualitySpecificationLine/SingleUseSampleIndicator QMSTST.QSDUSM; QMS201MI/AddSpecTest, UpdSpecTest The field indicates whether the sample will be shared by more than one test or will be used only for selected test. Set to '0' if used for single test or '1' if shared by more than one test. QualitySpecification/QualitySpecificationLine/UserArea QMSTST.QSCDOR; QMS201MI/AddSpecTest, UpdSpecTest If element NameValue@name = 'CopyDOResults', the field indicates whether quality test results are copied from the shipping warehouse

of a distribution order. Set to 'true' to activate the setting.

QualityTestMaster

Quality restinaster	
QualityTestMaster/IDs/ID QMSTTP.QTQTST; QMS100MI/AddTstTemplate, UpdTstTemplate	This is the Test ID in QMS100. A substring to first 10 characters is taken for the ID.
QualityTestMaster/Description QMSTTP.QTTX40; QMS100MI/AddTstTemplate, UpdTstTemplate	This field is truncated to the first 40 characters.
QualityTestMaster/EffectiveTimePeriod/StartDateTime	This held is truffcated to the first 40 characters.
QMSTTP.QTQTE1, QTQTE2; QMS100MI/AddTstTemplate, UpdTstTemplate	QTE1 is the Date Part of the EffectiveTimePeriod/StartDateTime QTE2 is the Time Part of the EffectiveTimePeriod/StartDateTime
QualityTestMaster/EffectiveTimePeriod/EndDateTime QMSTTP.QTQTI1, QTQTI2; QMS100MI/AddTstTemplate, UpdTstTemplate	QTI1 is the Date Part of the EffectiveTimePeriod/EndDateTime QTI2 is the Time Part of the EffectiveTimePeriod/EndDateTime
QualityTestMaster/TestResultTypeCode QMSTTP.QTTSTY; QMS100MI/AddTstTemplate, UpdTstTemplate	Can have only values of 0, 1 or 2. Works in conjunction with VLTP. With a TSTY value of 0 or 1, only VLTP values of 1 and 2 are allowed. With a TSTY valueof 2, only VLTP value of 2 is allowed.
QualityTestMaster/TestValueTypeCode QMSTTP.QTVLTP; QMS100MI/AddTstTemplate, UpdTstTemplate	Can have only values of 0, 1 or 2. See conditions for TestResultTypeCode.
QualityTestMaster/SignificantDigits QMSTTP.QTDCCD; QMS100Ml/AddTstTemplate, UpdTstTemplate	Mapped to the No. of decimal places
QualityTestMaster/DefaultRequiredIndicator QMSTTP.QTREQD; QMS100MI/AddTstTemplate, UpdTstTemplate	Is Test required or not
QualityTestMaster/TestPriority QMSTTP.QTQTSP; QMS100Ml/AddTstTemplate, UpdTstTemplate	Test Priority - purely informational
QualityTestMaster/TestOrder	
QMSTTP.QTEXSQ; QMS100Ml/AddTstTemplate, UpdTstTemplate QualityTestMaster/TestClass	Test Order - purely informational
QMSTTP.QTTCLS; QMS100Ml/AddTstTemplate, UpdTstTemplate QualityTestMaster/TestAttribute	First 10 characters. This value should be already specified in M3.
QMSTTP.QTATID; QMS100MI/AddTstTemplate, UpdTstTemplate QualityTestMaster/TestStandard	First 15 characters. This value should be already specified in M3.
QMSTTP.QTINSD; QMS100MI/AddTstTemplate, UpdTstTemplate QualityTestMaster/SamplingRequiredIndicator	First 10 characters. This value should be already specified in M3.
QMSTTP.QTSMPR; QMS100MI/AddTstTemplate, UpdTstTemplate QualityTestMaster/InternalTestIndicator	Expecting a true or false. This is an indicator on the M3 program.
QMSTTP.QTINTR; QMS100Ml/AddTstTemplate, UpdTstTemplate	Expecting a true or false. This is an indicator on the M3 program.
QualityTestMaster/TestRate/FrequencyType QMSTTP.QTFRPR; QMS100MI/AddTstTemplate, UpdTstTemplate	If this value is 0, then ignore TestRate/Quantity and TestRate/Quantity@unitCode. Also read and map TestRate/FrequencyNumber. If this value is 1, then read TestRate/Quantity and TestRate/Quantity@unitCode. Also read and map TestRate/FrequencyNumber.
QualityTestMaster/TestRate/Quantity QMSTTP.QTFRQY; QMS100MI/AddTstTemplate, UpdTstTemplate @unitCode	See explanation for FrequencyType.
QMSTTP.QTFRUM; QMS100MI/AddTstTemplate, UpdTstTemplate	See explanation for FrequencyType.
QualityTestMaster/TestRate/FrequencyNumber QMSTTP.QTFRTI; QMS100MI/AddTstTemplate, UpdTstTemplate	See explanation for FrequencyType.
QualityTestMaster/SampleType QMSTTP.QTSMTP; QMS100Ml/AddTstTemplate, UpdTstTemplate	This value is should be a member of a list already specified.
QualityTestMaster/SampleQuantity QMSTTP.QTSMSZ; QMS100MI/AddTstTemplate, UpdTstTemplate	Sample Size
QunitCode QMSTTP.QTSMUM; QMS100MI/AddTstTemplate, UpdTstTemplate	Sample Size UOM
QualityTestMaster/DestructiveTestIndicator QMSTTP.QTDSSM; QMS100MI/AddTstTemplate, UpdTstTemplate	Expecting a true or false. This is an indicator on the M3 program.
QualityTestMaster/RetainSampleIndicator QMSTTP.QTRTSM; QMS100MI/AddTstTemplate, UpdTstTemplate	Expecting a true or false. This is an indicator on the M3 program.
QualityTestMaster/MeasurementMethod QMSTTP.QTMSUR; QMS100MI/AddTstTemplate, UpdTstTemplate	This value is should be a member of a list already specified.
QualityTestMaster/MeasurementResourceReference/ResourceID/ID QMSTTP.QTMSIN; QMS100MI/AddTstTemplate, UpdTstTemplate	This value is should be a member of a list already specified.
QualityTestMaster/MeasurementResourceReference/Quantity QMSTTP.QTTEUM; QMS100MI/AddTstTemplate, UpdTstTemplate	This is the Test UOM.
QualityTestMaster/DepartmentCode QMSTTP.QTDEPT; QMS100MI/AddTstTemplate, UpdTstTemplate	This value is should be a member of a list already specified.
QualityTestMaster/Laboratory/SupplierParty/PartyIDs/ID QMSTTP.QTLABO; QMS100MI/AddTstTemplate, UpdTstTemplate	If this is filled then, populate first 10 characters of the LABO field in the MI with this value, else use the Laboratory/Location/ID.
QualityTestMaster/QualitativeCode QMSTTP.QTQTCD; QMS100MI/AddTstTemplate, UpdTstTemplate	Code list to be used for Numeric Qualitative test.

QualityTestMaster

QualityTestMaster/QualitativeTestCode QMSTTP.QTQLCD; QMS100MI/AddTstTemplate, UpdTstTemplate	Expected value of the Qualitative test.
QualityTestMaster/ValueLimit QMSTTP.QTEVMX, QTEVMN, QTEXMX, QTALMX, QTALMN, QTEVTG, QTTVTG, QTAVTG; QMS100MI/AddTstTemplate, UpdTestTemplate	Will fill the EVMX, EVMN, EXMX, EXMN, ALMX, ALMN, EVTG, TVTG, AVTG values in the MI program. Target - EVTG, ExternalTarget - TVTG, AlarmTarget - AVTG, Maximum - EVMX, Minimum - EVMN, ExternalMaximum - EXMX, ExternalMinimum - EXMN, AlarmMaximum - ALMX, AlarmMinimum ALMN

QMSTTP.QTQOP1, QTQOP2, QTQOP3; QMS100MI/AddTstTemplate, UpdTestTemplate 0 - Blank, 1 - GT, 2 - GE, 3 - LT, 4 - LE, 5 - EQ. BOD will have two character strings. MI has the above numeric equivalents.

	
Quote/QuoteHeader/DocumentID/ID OXHEAD.OAORNO	The field indicates the document ID from the source application.
; OIS100MI/ChgBatchHead,	The field indicates the document ib from the source application.
AddBatchLine, _	For the AcknowledgeQuote:
ChgBatchLine, DelBatchLine,	IF actionCode is 'Rejected' 1) If m3beGeneratedDocID is 'false', set to document ID from the
LstBatchLine,	source application.
AddBatchQuot,	If m3beGeneratedDocID is 'true' , set the the temporary order
ChgBatchQuote	number from the batch order.
O	If actionCode is 'Accepted' The field indicates the document ID generated by M3.
@accountingEntity OXHEAD.OACONO	The field indicates the company and division, displayed as
OXHEAD.OADIVI.; /	CONO DIVI.
Quote/QuoteHeader/AlternateDocumentID/ID	
OOHEAD.CUOR; OIS100MI/AddBatchHead, ChgBatchHead	The field indicates the customer's order number. The customer's order number acts as a reference to the customer's own order number and is printed on external documents.
	If the ProcessQuote is 'Rejected', another AlternateDocument ID will be published containing the document ID from the source application.
Quote/QuoteHeader/DocumentDateTime OXHEAD.OAORDT ; OIS100MI/AddBatchHead	The field indicates the date the order arrived from the customer.
Quote/QuoteHeader/Note OSYTXH.THTX40; OIS100MI/AddBatchText	The field indicates the notes.
@use OSYTXH.THTXEI; OIS100MI/AddBatchText	The field indicates if the text is external or internal. Set to '1' if the use is equals to blank or External. Set to '2' if the use is equals to Internal.
@type OSYTXH.THTYPE; OIS100MI/AddBatchText	The field indicates the type of text. Set to '2' if the type is equals to blank, footer or Post-Text. Set to '1' if the type is equals to header or Pre-Text.
Quote/QuoteHeader/Status/Code	
OOQUOH.STAT; QPS115MI/UpdQuoteInfo	Set to 20 if status is 'Open'. Set to 50 if status is 'Accepted'. Set to 30 if status is 'Lost'.
Quote/QuoteHeader/CustomerParty/PartyIDs/ID OXHEAD.OACUNO ; OIS100MI/AddBatchHead	The field indicates the customer number.
Quote/QuoteHeader/ShipToParty/PartyIDs/ID	
OXHEAD.OADECU	The field indicates the delivery customer. If Address number ID
OIS100MI/AddBatchHead	(ADID) exists, it is concatenated after the Delivery customer (DECU) without separator. If DECU does not consume the maximum length of
OXHEAD.OAADID	10, the rest is filled up with spaces. Maximum length for ADID is 6
OIS100MI/AddBatchHead,ChgBatchHead.;/	characters.
Quote/QuoteHeader/ShipToParty/Name OXADRE.ODCUNM; OIS100MI/AddBatchAddress	The field indicates the delivery customer name.
Quote/QuoteHeader/ShipToParty/Location/Address/AttentionOfName OXADRE.ODYREF: OIS100MI/AddBatchAddress	The field indicates the reference 1
Quote/QuoteHeader/ShipToParty/Location/Address/AddressLine	The field indicates the reference 1.
OXADRE.ODCUA1 OXADRE.ODCUA2 OXADRE.ODCUA3	The field indicates the address line.
OXADRE.ODCUA4.; OIS100MI/AddBatchAddress	
@sequence	The field indicates the address line sequence.
Quote/QuoteHeader/ShipToParty/Location/Address/CityName OXADRE.ODTOWN; OIS100MI/AddBatchAddress	The field indicates the city name.
Quote/QuoteHeader/ShipToParty/Location/Address/CountrySubDivisi OXADRE.ODECAR; OIS100MI/AddBatchAddress	onCode The field indicates an area, province or state within a country.
Quote/QuoteHeader/ShipToParty/Location/Address/CountryCode OXADRE.ODCSCD; OIS100MI/AddBatchAddress	The field indicates the country code.
Quote/QuoteHeader/ShipToParty/Location/Address/PostalCode OXADRE.ODPONO; OIS100MI/AddBatchAddress	The field indicates the postal code.
Quote/QuoteHeader/ShipToParty/Communication/ChannelCode	
Ouoto/OuotoHoador/ShinToParty/Communication/LlooCodo	Set to 'Phone'.
Quote/QuoteHeader/ShipToParty/Communication/UseCode	1) Set to 'Office'. 2) Set to 'Fax'.
Quote/QuoteHeader/ShipToParty/Communication/DialNumber 1) OADRE.ODPHNO	

Quote	
2) OADRE.ODTFNO.; OIS100MI/AddBatchAddress	The field indicates the telephone number. IF ChannelCode is 'Phone' and UseCode is 'Office', populate Phone Number (PHNO).
	The field indicates the facsimile number. If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
Quote/QuoteHeader/ShipFromParty/Location	
@type	If attribute type = 'Warehouse', populate Quote/QuoteHeader/ ShipFromParty/Location/ID with WHLO.
	If attribute type = 'Site', p opulate Quote/QuoteHeader/ShipFromParty/Location/ID with FACI.
Quote/QuoteHeader/ShipFromParty/Location/ID	
1) OXHEAD.OAWHLO ; OIS100MI.AddBatchHead, ChgBatchLine	Warehouse The field indicates the warehouse.
2) OXHEAD.OAFACI ; OIS100MI.AddBatchHead .; /	2) Facility The field indicates the facility.
Quote/QuoteHeader/BillToParty/PartyIDs/ID OOHEAD.OAINRC ; OIS100MI/AddBatchHead, ChgBatchHead	The field indicates the invoice recipient.
Quote/QuoteHeader/BillToParty/Location/Name OXADRE.ODCUNM; OIS100MI/AddBatchHead	The field indicates the name of the invoice recipient.
Quote/QuoteHeader/BillToParty/Location/Address/AttentionOfName OXADRE.ODYREF; OIS100MI/AddBatchAddress	The field indicates the name of customer resposible.
Quote/QuoteHeader/BillToParty/Location/Address/AddressLine OXADRE.ODCUA1 OXADRE.ODCUA2 OXADRE.ODCUA3 OXADRE.ODCUA4.; OIS100MI/AddBatchAddress	The field indicates the address line.
@sequence	The field indicates the address line sequence.
Quote/QuoteHeader/BillToParty/Location/Address/CityName OXADRE.ODTOWN; OIS100MI/AddBatchAddress	The field indicates the city name.
Quote/QuoteHeader/BillToParty/Location/Address/CountrySubDivision OXADRE.ODECAR; OIS100MI/AddBatchAddress	onCode The field indicates an area, province or state within a country.
Quote/QuoteHeader/BillToParty/Location/Address/CountryCode OXADRE.ODCSCD; OIS100MI/AddBatchAddress	The field indicates the country code.
Quote/QuoteHeader/BillToParty/Location/Address/PostalCode OXADRE.ODPONO; OIS100MI/AddBatchAddress	The field indicates the postal code.
Quote/QuoteHeader/BillToParty/Communication/ChannelCode	Set to 'Phone'.
Quote/QuoteHeader/BillToParty/Communication/UseCode	1) Set to 'Office'. 2) Set to 'Fax'.
Quote/QuoteHeader/BillToParty/Communication/DialNumber	2,000.00 1 00.
1) OADRE.ODPHNO 2) OADRE.ODTFNO.; OIS100MI/AddBatchAddress	The field indicates the telephone number. IF ChannelCode is 'Phone' and UseCode is 'Office', populate Phone Number (PHNO).
	The field indicates the facsimile number. If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
Quote/QuoteHeader/PayFromParty/PartyIDs/ID OXHEAD.OAPYNO	
; OIS100MI/AddBatchHead, ChgBatchHead	The field indicates the payer.
	The field indicates the payer. The field indicates the delivery terms, which indicate when the responsibility for a delivery is transferred from the supplier to the customer.
ChgBatchHead Quote/QuoteHeader/TransportationTerm/IncotermsCode OXHEAD.OATEDL ; OIS100MI/AddBatchHead, ChgBatchHead Quote/QuoteHeader/TransportationMethodCode OXHEAD.OAMODL; OIS100MI/AddBatchHead,	The field indicates the delivery terms, which indicate when the responsibility for a delivery is transferred from the supplier to the
ChgBatchHead Quote/QuoteHeader/TransportationTerm/IncotermsCode OXHEAD.OATEDL ; OIS100MI/AddBatchHead, ChgBatchHead Quote/QuoteHeader/TransportationMethodCode	The field indicates the delivery terms, which indicate when the responsibility for a delivery is transferred from the supplier to the customer.

OXHEAD.OAPYCD; OIS100MI/AddBatchHead, ChgBatchHead	The field indicates the payment method code. The payment method code is translated in CRS881.
Quote/QuoteHeader/EffectiveTimePeriod/EndDateTime OOQUOH.QFGIDT ; OIS100MI/AddBatchQuot, ChgBatchQuot	The field indicates the record validity date.
Quote/QuoteHeader/UserArea 1) OOQUOH.QFFFI1 2) OOQUOH.QFFFI2 3) OOQUOH.QFFFI3 4) OOQUOH.QFFFI4 5) OOQUOH.QFFFI5 6) OOQUOH.QFFFI6 8) OXHEAD.OAYREF.; OIS100MI/AddBatchQuot, ChgBatchQuot	1) The field indicates the User-defined field (FFI1). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI1). 2) The field indicates the User-defined field (FFI2). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI2). 3) The field indicates the User-defined field (FFI3). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI3). 4) The field indicates the User-defined field (FFI4). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI4). 5) The field indicates the User-defined field (FFI5). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI5). 6) The field indicates the User-defined field (FFI6). If attribute name is 'QuoteFreeField1', populate user-defined field (FFI6). 7) Set to 'true'. If attribute name is 'ReleaseBatchOrder', call OIS100MI/Confirm with ORNO as input. 8) The field indicates the customer's contact person (YREF). If attribute name is 'AttentionOfName', populate customer's contact person (YREF).
Quote/QuoteHeader/RequiredDeliveryDateTime OXHEAD.OARLDZ+OARLHZ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the required delivery date time.
Quote/QuoteHeader/Classification/Codes/Code 1) OXHEAD.OAORTP OIS100MI/AddBatchHead, ChgBatchHead 2) OOQUOH.QFORCD OIS100MI/AddBatchQuot, ChgBatchQuote 3) OOQUOH.QFBVC1 OIS100MI/AddBatchQuot, ChgBatchQuote 4) OOQUOH. QFBVC2 OIS100MI/AddBatchQuot, ChgBatchQuote 5) OXHEAD.OAFRE1 OIS100MI/AddBatchHead, ChgBatchHead.; /	1) Order Type The field indicates the Order type. If attribute listID is 'Order Types', populate Order type (ORTP). 2) Quotation reason The field indicates why a quotation was given to a customer or why it did not result in an order. If attribute listID is 'Quotation Reasons', populate Quotation reason (ORCD). 3) Follow-up activity 1 The field indicates which follow-up activity to be performed for a quotation. If attribute listID is 'Follow-up Activity 1', populate Follow-up activity 1 (BVC1). 3) Follow-up activity 2 The field indicates which follow-up activity to be performed for a quotation. If attribute listID is 'Follow-up Activity 2', populate Follow-up activity 2 (BVC2). 4) Customer Statistics Identity1 The field indicates a user-defined customer statistics accumulator. 1) If attribute listID is 'Order Types', populate Order type (ORTP). 2) If attribute listID is 'Quotation Reasons', populate Quotation reason (ORCD). 3) If attribute listID is 'Follow-up Activity 1', populate Follow-up activity 1 (BVC1). 4) If attribute listID is 'Follow-up Activity 2', populate Follow-up activity 1 (BVC2). 5) If attribute name is 'Customer Statistics Identity1', populate the customer statistics identity 1 (FRE1).
Quote/QuoteHeader/SalesPersonReference/IDs/ID OXHEAD.OASMCD ; OIS100MI/AddBatchHead, ChgBatchHead	The field indicates the person responsible for sales to customer.
Quote/QuoteLine/LineNumber OXLINE.OBPONR ; OIS100MI/ChgBatchLine, DelBatchLine	The field indicates the order line number.

	
Quote/QuoteLine/Note OSYTXL.TLTX40; OIS100MI/AddBatchText	The field indicates the remarks or notes.
@use OSYTXL.THTXEI; OIS100MI/AddBatchText	The field indicates if the text is external or internal. Set to '1' if the use is equals to blank or External. Set to '2' if the use is equals to Internal.
@type OSYTXL.THTYTR; OIS100MI/AddBatchText	The field indicates the type of text. Set to '2' if the type is equals to blank, footer or Post-Text. Set to '1' if the type is equals to header or Pre-Text.
Quote/QuoteLine/Item/ItemID/ID OXLINE.OBITNO ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the item number.
Quote/QuoteLine/Item/Description OXLINE.OBITDS ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the item description.
Quote/QuoteLine/Item/SerializedLot/Lot/LotIDs/ID OXLINE.OBBANO ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the lot number.
Quote/QuoteLine/Quantity OXLINE.OBORQT ; OIS100MI/AddBatchLine,	The field indicates the ordered quantity in an alternative unit of measure.
ChgBatchLine @unitCode OXLINE.OBALUN ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the alternate unit of measure (U/M) for the basic U/M for an item.
Quote/QuoteLine/UnitPrice/Amount OXLINE.OBSAPR ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the sales price for each sales price quantity.
Quote/QuoteLine/RequiredDeliveryDateTime OXLINE.OBRLDZ+OBRLHZ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the required delivery date and time.
Quote/QuoteLine/ShipToParty/PartyIDs/ID OXLINE.OBADID ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the shipping address ID.
Quote/QuoteLine/PaymentTerm/PaymentTermCode OXLINE.OBTEPY ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates how the due date is to be calculated.
Quote/QuoteLine/PromisedDeliveryDateTime OXLINE.OBCODZ OXLINE.OBCOHZ .; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the confirmed delivery date and time.
Quote/QuoteLine/QuoteSubLine/LineNumber OXLINE.OBPOSX ; OIS100MI/ChgBatchLine, DelBatchLine	The field indicates the line suffix.
Quote/QuoteLine/QuoteSubLine/Item/ItemID/ID OXLINE.OBITNO ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the item number.
Quote/QuoteLine/QuoteSubLine/Item/Description OXLINE.OBITDS ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the item description.
Quote/QuoteLine/QuoteSubLine/Item/SerializedLot/Lot/LotIDs/ID OXLINE.OBBANO ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the lot number.
Quote/QuoteLine/QuoteSubLine/Quantity OXLINE.OBORQT ; OIS100MI/AddBatchLine, ChgBatchLine	The field indicates the ordered quantity in an alternative unit of measure.
@unitCode OXLINE.OBALUN	The field indicates the alternate unit of measure (U/M) for the basic U/

ChgBatchLine

Quote/QuoteLine/ShipFromParty/Location @type

If @type = 'Warehouse', populate Quote/QuoteHeader/ ShipFromParty/Location/ID with WHLO.

Quote/QuoteLine/ShipFromParty/Location/ID
OXLINE.OBWHLO

OXLINE.OBWHLO ; OIS100MI/AddBatchLine, ChgBatchLine The field indicates the warehouse.

ReceiveDelivery

ReceiveDelivery/ReceiveDeliveryHeader/DocumentID/ID

For Process:

1) MMIHED.I0PMSN; MMS850MI/AddAdjust

2) MHILIN.G2RORN; MHS850MI/AddDO.; /

For Sync:

OCHÉAD.OCREPN; MHS850MI/AddCOReturn

PFTRNS.INERCV;

PPS360MI/UpdPackageLine.; /

For Process:

1) The field indicates the external message number.

In case warehouse transactions are not connected to an order in M3, use MMS850 instead of MHS850.

For MMS850MI.Adjust, use Partner from logicalID and translate it in CRS881 to "Internal Stock Transactions".

For MHS850MI transactions, use Partner from logicalID and translate it in CRS881 to "OrderStockTransactions".

2) Reference order number

The field indicates the reference order number.

MHS850MI.AddDO is called instead of MHS850MI.AddWhsHead, AddWhsPack and AddWhsLine if these conditions are met:

- agreement control property m3beReference is set to true
- partner from logical ID is translated to 'OrderStockTransactions'

MHS850MI.AddDO RORN is mapped according to this hierarchy:

- ReceiveDeliveryHeader/DocumentReference/DocumentID/ID with attribute type='MaintenanceOrder' with non-blank value
- Receive Delivery Header/User Area/Property/Name Value with attribute name='eam. Advice Number'
- ReceiveDeliveryHeader/DocumentID/ID (only retrieve value before the '-')

For Sync:

The field indicates the customer return receiving number.

If agreement control property 'm3beInspectCustomerReturn' is true, and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine.

The field indicates the external receiving number (ERCV). The value in this element populates the external receiving number field if Delivery Note is exisiting in element ReceiveDeliveryItem/ UserArea@name='wm.DeliveryNote'.

For Process:

The field indicates the company and division, displayed as

CONO_DIVI.

ReceiveDelivery/ReceiveDeliveryHeader/AlternateDocumentID/ID

For Process: MHILIN.G2REPN; MHS850MI/AddWhsLine MPLIND.ICPREN; PPS330MI/DelPOTrans.; /

@accountingEntity

MHIHED.G0DIVI.;

For Process: MHIHED.G0CONO

For Process:

The field indicates the receiving number.

ReceiveDelivery/ReceiveDeliveryHeader/DocumentDateTime

For Process:
1) MHIHED.GOGEDT
MHIHED.GOGETM;
MHS850MI/AddWhsHead
2) MHIPAC.G1GEDT
MHIPAC.G1GETM;
MHS850MI/AddWhsPack.; /

For Process:

The field indicates the date and time the record was created.

ReceiveDelivery/ReceiveDeliveryHeader/Note

For Process: MHIHED.G0SUDO ; MHS850MI/AddWhsHead For Process:

The field indicates the delivery note number.

@entryDateTime

For Process: MHIHED.G0DNDT ; MHS850MI/AddWhsHead For Process:

The field indicates the date the delivery note was printed for the first time.

ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference @type

For Process:

The field indicates the document reference type.

Set QLFR to '20' and TTYP to "20" if the following conditions are met:

- 1) ReceiveDelivery/ReceiveDeliveryHeader/
- DocumentReference@type is 'PurchaseOrder'.
- 2) ReceiveDelivery/ReceiveDeliveryHeader/Status/Code is 'Received'.
- 3) List of Receive Delivery Items is not empty.

Set QLFR to '20PA' and TTYP to "20" if the following conditions are

- 1) ReceiveDelivery/ReceiveDeliveryHeader/
- DocumentReference@type is 'PurchaseOrder'.
- 2) ReceiveDelivery/ReceiveDeliveryHeader/Status/Code is 'Received'.
- 3) List of Receive Delivery Items is empty.

Set QLFR to '51CR' if the following conditions are met:

- 1) ReceiveDelivery/ReceiveDeliveryHeader/ DocumentReference@type is 'Transfer'.
- 2) LogicalID (partner) is translated to OrderStockTransaction.

Set QLFR to '50' and TTYP to "50" if the following conditions are met:

- 1) ReceiveDelivery/ReceiveDeliveryHeader/ DocumentReference@type is 'Transfer".
- 2) List of Receive Delivery Items is not empty.

Set QLFR to '50PA' and TTYP to "50" if the following conditions are met:

1) ReceiveDelivery/ReceiveDeliveryHeader/ DocumentReference@type is 'Transfer". 2) List of Receive Delivery Items is empty.

Set QLFR to "51CR" if the following conditions are met:

- 1) ReceiveDelivery/ReceiveDeliveryHeader/
- DocumentReference@type is 'MaintenanceOrder'.
- 2) LogicalID (partner) is translated to OrderStockTransaction.

Set QLFR to "10" and TTYP to "10" if ReceiveDelivery/ ReceiveDeliveryHeader/DocumentReference@type is 'ProductionOrder'.

Set QLFR to "30D" and TTYP to "30" if ReceiveDelivery/ ReceiveDeliveryHeader/DocumentReference@type is 'CustomerReturn'.

For Sync:

The field is used to decide which API-transaction to use.

If 'ProductionOrder', use AddMOReceipt.

If 'Transfer', use AddDOReceipt.

If 'CustomerReturn', use AddCOReturn.

If agreement control property 'm3beInspectCustomerReturn' is true,

and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', use MHS850MI/ AddWhsHead, AddWhsPack, and AddWhsLine with qualifier (QLFR) 30A.

If 'PurchaseOrder', use AddPOReceipt. If 'ByProduct', use PMS080MI RptByProduct
If 'CoProduct', use PMS090MI UpdCoProdReport

ReceiveDelivery/ReceiveDeliveryHeader/DocumentReference/DocumentID/ID

For Process: 1) MHIHED.G0RIDN; MHS850MI/AddWhsHead or MHS850MI/AddDO MHILIN.G2RIDN; MHS850MI/AddWhsLine 2) MHILIN.G2PROJ: MHS850MI/ChgWhsLineX 3) MHILIN.G2RORN;

MHS850MI/AddDO .; /

For Process: 1) Order number

The field indicates the order number.

If DocumentReference@type='Transfer':

- Check for RIDN/RIDI format only if partner from LogicalID is not translated to 'Internal Stock Transactions' or 'OrderStockTransactions'.
- If partner from LogicalID is translated to 'OrderStockTransactions',
- append 'R' in the ID if value is not empty.
- 2) Project number

If ReceiveDelivery/ReceiveDeliveryHeader/

DocumentReference@type is 'ProjectMaster', the field indicates the

Project number.

3) Reference order number

The field indicates the reference order number.

ReceiveDelivery/ReceiveDeliveryHeader/Status/Code

For Process:

The field indicates the status.

If 'Received' or 'Closed', MHS850MI will be called.

If 'Deleted', PPS330MI will be called.

For Sync:

The field indicates the status. It will only process the PO if status is 'Received' or 'Closed'.

ReceiveDelivery/ReceiveDeliveryHeader/WarehouseLocation/ID

For Process: MMIHED.IOWHLO; For Process:

The field indicates the warehouse.

May 26, 2023

MMS850MI/AddAdiust

MHILIN.G2RORN; MHS850MI/AddDO.; /

For Sync:

OCHÉAD.OCWHLO; MHS850MI/AddCOReturn

PFTRNS.INWHLO; PPS360MI/StagePackage PPS360MI/UpdPackageLine

MHIHED.G0WHLO: MHS850MI/AddPOReceipt MHS850MI/AddMOReceipt MHS850MI/AddPOClose

For Sync:

The field indicates the warehouse. If this field is empty, the warehouse value will be fetched from element Sync/LocationID.

ReceiveDelivery/ReceiveDeliveryHeader/ActualDeliveryDateTime

For Process MHILIN.G2RPDT MHILIN.G2USD5. ; MHS850MI/AddWhsLine For Process:

The field indicates the transaction reporting date and time.

ReceiveDelivery/ReceiveDeliveryHeader/ShipFromParty/PartyIDs/ID

For Process:

1) MHIHED.G0SUNO; MHS850MI/AddWhsHead 2) MHILIN.G2SUNO; MHS850MI/AddWhsLine 3) MHIPAC.G1SUNO; MHS850MI/AddWhsPack.; /

For Sync:

OCHÉAD.OCCUNO: MHS850MI/AddCOReturn,

MPHEAD.IASUNO: MHS850MI/AddPOReceipt,

MGHEAD.MGWHLO; MHS850MI/AddDOReceipt

PFTRNS.INSUNO;

PPS360MI/UpdPackageLine.; /

For Process:

The field indicates the supplier number.

For Sync:

The field indicates the customer number or supplier number, or the from warehouse.

-If document reference type is 'CustomerReturn', the element is used as Customer Number.

-If document reference type is 'PurchaseOrder', the element is used as Supplier Number.

-If document reference type is 'Transfer', the element is used as the

-If document reference type is 'PurchaseOrder', and the BOD has element ReceiveDeliveryItem/UserArea@name='wm.DeliveryNote', the element is used as Supplier Number.

ReceiveDelivery/ReceiveDeliveryHeader/ReturnFromShipToParty/PartyIDs/ID

For Process:

1) MHIHED.G0CUNO; MHS850MI/AddWhsHead

2) MHILIN.G2CUNO; MHS850MI/AddWhsLine.; /

For Sync:

OCHÉAD.OCCUNO; MHS850MI/AddCOReturn

AddWhsHead

For Process:

The field indicates the customer number.

If document reference type is 'CustomerReturn', the element is used

as Customer Number.

This element is used if ShipFromParty/PartyIDs/ID is empty.

If agreement control property 'm3beInspectCustomerReturn' is true,

the element is mapped to MHS850MI/AddWhsHead

ReceiveDelivery/ReceiveDeliveryHeader/DeliverToParty/Location/ID

For Process:

1) MHIHED.G0WHLO; MHS850MI/AddWhsHead 2) MHILIN.G2WHLO; MHS850MI/AddWhsLine or MHS850MI/AddDO MHIPAC.G1WHLO;

MHS850MI/AddWhsPack 4) MMIHED.I0WHLO; MMS850MI/AddAdjust.; /

MGHEAD.MGTWLO; MHS850MI/AddDOReceipt

ReceiveDelivery/ReceiveDeliveryHeader/UserArea

For Process:

1) MGLINE.MRELNO; MHS850MI/ChgWhsLineX For Process:

The field indicates the warehouse.

The field indicates the destination warehouse. The element is used

only for document reference type 'Transfer'.

For Process:

1) The field indicates the Project Element if

@name='eam.ProjectBudget'.

This is only applicable if Classification/Codes/Code@listID='Project

MHS850MI/AddDO

:/

ReceiveDelivery/ReceiveDeliveryItem/ItemID/ID

For Process: 1) MHILIN.G2ITNO; MHS850MI/AddWhsLine 2) MMIIDE.I1ITNO; MMS850MI/AddAdjust.; /

For Sync:

OCLINE.ODITNO;

MHS850MI/AddCOReturn,

AddWhsLine MPLINE.IBITNO; MHS850MI/AddPOReceipt. MGLINE.MRITNO; MHS850MI/AddDOReceipt, MWOHED.VHPRNO; MHS850MI/AddMOReceipt, MWOCPN.VSCPNO;

PMS090MI/UpdCoProdReport

PFTRNS.INITNO;

PPS360MI/UpdPackageLine

ReceiveDelivery/ReceiveDeliveryItem/Classification/Codes/Code

For Process:

1) MHILIN.G2PROJ;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO

2) MHILIN.G2ELNO;

MHS850MI/ChgWhsLineX MHS850MI/AddDO

3) MHILIN.G2DEPT;

MHS850MI.ChgWhsLineX or MHS850MI/AddDO

4) MHILIN.G2ACC2;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO.; /

For Sync:

OCLINE.ODBREF, ODBRE2; MHS850MI/AddCOReturn, MGLINE.MRBREF, MRBRE2, MHS850MI/AddDOReceipt MPM050.VHBREF, VHBRE2; MHS850MI/AddMOReceipt, MHILIN.G2BREF, G2BREF2 MHS850MI/AddPOReceipt

@listID

Element' does not exist.

2) The field indicates the reference order number if

@name='eam.AdviceNumber'.

For Process:

The field indicates the item number.

The field indicates the item number or the Co-product number.

If agreement control property m3belnspectCustomerReturn is true,

and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this

element is mapped to MHS850MI/AddWhsLine.

For Process:

1) The field indicates the Project number.

2) The field indicates the Project element.

3) The field indicates the Department.

4) The field indicates the Accounting object 2 or Cost Center. Use this only if Shipment/ShipmentItem/UserArea/Property/

NameValue@name='AccountingObject2' does not exist.

For Sync:

The field indicates the lot reference 1 and 2.

For Process:

1) If 'Project Number' populate PROJ.

2) If 'Project Element' populate ELNO.

3) If 'Departments' populate DEPT.

4) If 'Cost Centers' populate ACC2.

For Sync:

Set to 'Lot Reference 1' to populate BREF. Set to 'Lot Reference 2' to populate BRE2

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/DocumentID/ID

For Process: MHILIN.G2RIDN:

MHS850MI/AddWhsLine or AddPOClose

MPLIND.ICPUNO; PPS330MI/DelPOTrans

.G2RIDN

For Sync: MPLINE.IBPUNO;

MHS850MI/AddPOReceipt MHS850MI/AddPOClose

PFTRNS.INRIDN;

PPS360MI/UpdPackageLine.; /

For Process:

The field indicates the purchase order number.

If ReceiveDeliveryHeader/DocumentReference@type is empty but

this element is populated, set ReceiveDeliveryHeader/ DocumentReference@type to 'PurchaseOrder'.

For Sync:

The field indicates the purchase order number. The element is used

for document reference type 'PurchaseOrder'.

ReceiveDelivery/ReceiveDeliveryItem/PurchaseOrderReference/LineNumber

For Process:

MHILIN.G2RIDL;

The field indicates the order line number and line suffix. Last 3 digits

MHS850MI/AddWhsLine, AddPOClose

MHILIN.G2RIDX:

MHS850MI/AddWhsLine, AddPOClose

MPLIND.ICPLNI; PPS330MI/DelPOTrans MPLIND.ICPLNS; PPS330MI/DelPOTrans.; /

For Sync: MPLINE.IBPNLI;

MHS850MI/AddPOReceipt, AddPOClose

MPLINE.IBPNLS;

MHS850MI/AddPOReceipt, AddPOClose.

PFTRNS.INRIDL:

PPS360MI/UpdPackageLine

PFTRNS.INRIDX;

PPS360MI/UpdPackageLine.; /

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/DocumentID/ID

For Sync:

OCLINE.ODORNO: MHS850MI/AddWhsLine The field indicates the order number connected to the customer

ReceiveDelivery/ReceiveDeliveryItem/SalesOrderReference/LineNumber

For Sync: For Sync:

OCLINE.ODPONR; MHS850MI/AddWhsLine The field indicates the order line number connected to the customer

return.

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/DocumentID/ID

For Process: MHILIN.G2RIDN;

MHS850MI/AddWhsLine or AddDO

MHILIN.G2RIDI;

MHS850MI/AddWhsLine.; /

For Sync:

OCLINE.ODORNO;

MHS850MI/AddCOReturn, AddWhsLine,

MGLINE.MRTRNR;

MHS850MI/AddDOReceipt, MWOHED.VHMFNO; MHS850MI/AddMOReceipt,

MWOMAT.VMMFNO; PMS080MI/RptByProduct MWOCPN.VSMFNO;

PMS090MI/UpdCoProdReport

For Process:

represents the line suffix.

The field indicates the purchase order line number.

the remaining as RIDL. Otherwise, use input as RIDL.

If input is more than 3 characters, use the last 3 digits as RIDX and

For Sync:

The field indicates the order number.

If DocumentReference@type='Transfer':

- Check for RIDN/RIDI format only if partner from LogicalID is not translated to 'Internal Stock Transactions' or 'OrderStockTransactions'.

- If partner from LogicalID is translated to 'OrderStockTransactions',

append 'R' in the ID if value is not empty.

The field indicates the order number. If document reference type is 'Transfer', the field indicates combination of order number and

delivery number.

If agreement control property m3belnspectCustomerReturn is true,

and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine. For customer return, this element will only be used if SalesOrderReference/DocumentID/ID

does not exist.

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/LineNumber

For Process:

MHILIN.G2RELI;

MHS850MI/AddWhsLine

MHILIN.G2RIDL:

MHS850MI/AddWhsLine.; /

For Sync:

OCLINE.ODRELI;

MHS850MI/AddCOReturn, AddWhsLine,

MGLINE.MRPONR

MHS850MI/AddDOReceipt,

MPLINE.IBPNLI

MPLINE.IBPNLS;

MHS850MI/AddPOReceipt, MWOMAT.VMMSEQ;

PMS080MI/RptByProduct MWOCPN.VSOPNO:

PMS090MI/UpdCoProdReport

.; /

For Process:

The field indicates the order line number.

For Sync:

The field indicates the order line number.

For PurchaseOrder, if input is more than 3 characters, use the last 3 digits as RIDX and the remaining as RIDL. Otherwise, use input as

RIDL.

For Transfer, use as input to RIDL.

For CustomerReturn, use as input to RELI.

If agreement control property 'm3belnspectCustomerReturn' is true,

and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine. For customer return, this element will only be used if SalesOrderReference/LineNumber

For ByProduct, the field indicates the material sequence number.

For CoProduct, the field indicates the operation number where the

coproduct is included

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/Facility/IDs/ID

For Sync:

MWOMAT.VMFACI:

PMS080MI/RptByProduct MWOCPN.VSFACI;

PMS090MI/UpdCoProdReport

ReceiveDelivery/ReceiveDeliveryItem/DocumentReference/SubLineNumber

For Process:

MHILIN.G2RIDX; MHS850MI/AddWhsLine.; /

For Sync:

For Process:

MGLINE.MRPOSX; MHS850MI/AddDOReceipt

ReceiveDelivery/ReceiveDeliveryItem/ReceivedQuantity

1)MHILIN.G2RVQA; MHS850MI/AddWhsLine MHILIN.G2DLQT;

MHS850MI/AddDO 2)MMIINS.I2QLQT;

MMS850MI/AddAdjust.; /

For Sync:

OCLINE.ODREQ1;

MHS850MI/AddCOReturn, AddWhsLine,

MGLINE.MRRPQT; MHS850MI/AddDOReceipt, MWOHED/VHRVQA;

MHS850MI/AddMOReceipt,

MPLINE.IBRVQA

MHS850MI/AddPOReceipt, MWOMAT.VMRPQA; PMS080MI/RptByProduct MWOCPN.VSMÁQA;

PMS090MI/UpdCoProdReport

@unitCode

For Process: MHILIN.G2UNIT

: MHS850MI/AddWhsLine

ReceiveDelivery/ReceiveDeliveryItem/CatchWeightQuantity

For Process: MHILIN.G2CAWE;

MHS850MI/AddWhsLine.; /

For Sync:

OCLINE.ODCAWE; MHS850MI/AddCOReturn,

MPURST.IHCAWE

MHS850MI/AddPOReceipt, MGLINE.MRCAWE;

MHS850MI/AddDOReceipt,

MPM050.VHCAWE

MHS850MI/AddMOReceipt,

ReceiveDelivery/ReceiveDeliveryItem/UserArea

For Process: 1) MMIIDE.IWSHL; MMS850MI/AddAdjust MHILIN.G2WHSL;

MHS850MI/AddWhsLine or MHS850MI/AddDO

2) MITALO. MQOEND; MHS850MI/AddWhsLine 3) MHILIN.G2PACN;

MHS850MI/AddWhsLine or MHS850MI/AddCOReturn or MHS850MI/

OGbbA

MHIPAC.G1PACN; MHS850MI/AddWhsPack

4) MHILIN.G2ACC1-G2ACC7; MHS850MI/ChgWhsLineX or MHS850MI/ 4) The field indicates the accounting objects. Name attributes are

AddDO.; /

For Sync:

1.) MHILIN.G2USD1 - G2USD5; MHS850MI/AddCOReturn,

AddDOReceipt. AddMOReceipt, AddPOReceipt

For Sync:

1.) The field indicates user-defined fields used to interface M3 with other systems.

If @name='UserField1', populate USD1. If @name='UserField2', populate USD2. If @name='UserField3', populate USD3. If @name='UserField4', populate USD4.

For Process:

The field indicates the returned or received quantity in the item's basic unit of measure. It is only relevant if SerializedLot/Lot/Quantity is blank

For Sync:

For Sync:

The field indicates the facility.

The field indicates the line suffix.

The field indicates the received quantity.

If agreement control property m3beInspectCustomerReturn is true,

and element ReceiveDeliveryHeader/
DocumentReference@type='CustomerReturn', the value in this

element is mapped to MHS850MI/AddWhsLine.

For Process:

The field indicates the unit code.

For Process: The field indicates the catch weight in the item's basic unit of measure.

The field indicates the catch weight in the item's basic unit of measure.

For Process: The field indicates the location.

1) For EAM, location is fetched from UserArea field eam.Bin.

If @name='eam.Bin', populate WHSL.

2) The field indicates the completion flag. If set to 1, the delivery of an order line is completed. Remaining quantity will not be backordered. If @name='FlaggedAsCompleted', populate OEND.

If @name='PackageNumber', populate PACN.

3) The field indicates the package number.

'AccountingObject1'-'AccountingObject7'.

- 2.) PFTRNS.INPACN: PPS360MI/StagePackaging
- 3.) PFTRNS.INSUDO; PPS360MI/StagePackaging PPS360MI/UpdPackageLine
- 4.) OCHEAD.OCREPN; MHS850MI/AddCOReturn
- 5.) PFTRNS.INDNDT; PPS360MI/UpdPackageLine
- 6.) OCHEAD.OCREPN; MHS850MI/AddCOReturn, AddWhsLine.; /

If @name='UserField5', populate USD5.

2.) The field indicates the package number.

If @name='wm.PackageNumber', populate package number.

3.) The field indicates the delivery note.

If @name='wm.DeliveryNote', populate delivery note.

4.) The field indicates the CO return Receiving Number in M3. The value in this element overrides the value entered in element ReceiveDeliveryHeader/DocumentID/ID

If @name='ReceivingNumber', populate Receiving Number (REPN). If agreement control property 'm3beInspectCustomerReturn' is true, and element ReceiveDeliveryHeader/
DocumentReference@type='CustomerReturn', the value in this

element is mapped to MHS850MI/AddWhsLine.

5.) The field indicates the delivery note date.

If @name='wm.DeliveryNoteDate', populate delivery note date.

6.) The field indicates the CO return Receiving Number in M3. The value in this element overrides the value entered in element ReceiveDeliveryHeader/DocumentID/ID and ReceiveDeliveryItem/ UserArea/Property/NameValue@name='ReceivingNumber' If @name='wm.CustomerReturnRecNum', populate Receiving Number (REPN).

If agreement control property 'm3beInspectCustomerReturn' is true,

and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine

ReceiveDelivery/ReceiveDeliveryItem/SerializedLot/Lot/LotIDs/ID

For Process: MHILIN.G2BANO;

MHS850MI/AddWhsLine or MHS850MI/AddDO

MMIIDE.I1BANO; MMS850MI/AddAdjust.; /

For Sync:

OCLINE.ODBANO;

MHS850MI/AddCOReturn, AddWhsLine,

MGLINE.MRBANO; MHS850MI/AddDOReceipt, MWOHED.VHBANO; MHS850MI/AddMOReceipt,

MPLINE.IBBANO;

MHS850MI/AddPOReceipt, MWOMAT.VMBANO; PMS080MI/RptByProduct, MWOCPN VSBANO;

PMS090MI/UpdCoProdReport,

PFTRNS.INBANO;

PPS360MI/UpdPackageLine

For Process:

The field indicates the lot number.

For Sync:

The field indicates the lot number.

If agreement control property 'm3beInspectCustomerReturn' is true, and element ReceiveDeliveryHeader/

DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine.

ReceiveDelivery/ReceiveDelivery/Item/SerializedLot/Lot/EffectiveTimePeriod/EndDateTime

For Sync: For Sync: The field indicates the last usage date for the current item and lot.

MHILIN.G2EXPI; MHS850MI/AddPOReceipt

ReceiveDelivery/ReceiveDeliveryItem/SerializedLot/Lot/Quantity

For Process: MHILIN.G2RVQA; MHS850MI/AddWhsLine MHILIN.G2DLQT: MHS850MI/AddDO MMIINS.I2QLQT;

MMS850MI/AddAdjust.; /

@unitCode

For Process: MHILIN.G2UNIT

; MHS850MI/AddWhsLine

For Process:

The field indicates the returned or received quantity in the item's basic unit of measure.

For Process:

The field indicates the unit code.

ReceiveDelivery/ReceiveDeliveryItem/SerializedLot/Note

For Process:

- 1) MHILIN.G2BREF
- 2) MHILIN.G2BRE2;

MHS850MI/AddWhsLine

- 1) MMIIDE.I1BREF
- 2) MMIIDE.I1BRE2;
- MMS850MI/AddAdjust.; /

@noteID

For Process:

- 1) The field indicates lot reference 1.
- 2) The field indicates lot reference 2.

, Dalivary

ReceiveDelivery	
	For Process: 1) If noteID = Lot Reference 1, populate BREF. 2) If noteID = Lot Reference 2, populate BRE2.
ReceiveDelivery/ReceiveDeliveryItem/LineNumber For Sync: OCLINE.ODRELI; MHS850MI/AddCOReturn AddWhsLine	For Sync: The field indicates the customer return line number. This field is used if ReceiveDeliveryItem/DocumentReference/LineNumber for documentReference@type='CustomerReturn' is empty. If agreement control property 'm3beInspectCustomerReturn' is true,
	and element ReceiveDeliveryHeader/ DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine.
ReceiveDelivery/ReceiveDeliveryItem/HoldCodes/Code For Process: MHILIN.G2WHSL; MHS850MI/AddWhsLine or MHS850MI/AddDO.; / For Sync: OCLINE.ODWHSL; MHS850MI/AddCOReturn, AddWhsLine, MGLINE.MRWHSL; MHS850MI/AddDOReceipt, MWOHED.VHWHSL MHS850MI/AddMOReceipt, MPLIND.ICWHSL MHS850MI/AddPOReceipt, MWOMAT.VMWHSL; PMS080MI/RptByProduct MWOCPN.VSWHSL; PMS090MI/UpdCoProdReport .; /	For Process: The field indicates the location. For Sync: The field indicates the location. If HoldCodes/Code is not empty and not a valid location in M3, allow the API to fail with error message 'Location &1 does not exist'. Since it is possible to have multiple inputs to HoldCodes/Code, MMS850MI/AddMove WHSL will be checked using MMS010MI/ListLocations with input WHLO. The first location that will match will be used. If none of the entries is a valid Location in M3, return error 'Locations do not exist'. If HoldCodes/Code is empty, allow M3 logic to retrieve the location. If agreement control property 'm3beInspectCustomerReturn' is true, and element ReceiveDeliveryHeader/ DocumentReference@type='CustomerReturn', the value in this element is mapped to MHS850MI/AddWhsLine.
ReceiveDelivery/ReceiveDeliveryUnit/TrackingID For Process: MHIPAC.G1PACN; MHS850MI/AddWhsPack MHILIN.G2PACN; MHS850MI/AddDO .:/	For Process: The field indicates the package number.
ReceiveDelivery/ReceiveDeliveryUnit/ContainerID For Process: MHILIN.G2CAMU ; MHS850MI/AddWhsLine	For Process: The field indicates the container.
ReceiveDelivery/ReceiveDeliveryUnit/UserArea For Process: 1) MHIPAC.G1CONN; MHS850MI/AddWhsPack 2) MHILIN.G2DLIX; MHS850MI/AddWhsLine	For Process: 1) The field indicates the shipment number. If @name='Shipment', populate CONN. 2) The field indicates the delivery number.
3) MUIDAC C188CC:	If @name='DeliveryNumber' negulate DLIV

3) MHIPAC.G1SSCC; MHS850MI/AddWhsPack

4) MHILIN.G2TWSL; MHS850MI/AddWhsLine

5) MHILIN.G2WHSL;

MHS850MI/AddWhsLine or MHS850MI/AddDO.; /

If @name='DeliveryNumber', populate DLIX.

3) The field indicates the Serial Shipping Container Code. If @name='SSCC', populate SSCC. If populated, call MHS850MI/AddDOPackRec instead of AddDOReceipt.

4) The field indicates the To location. If @name='ToLocation', populate TWSL.

5) The field indicates the Location. If @name='Location', populate WHSL.

Infor May 26, 2023

RemitToPartyMaster

rtonner or artymaster	
RemitToPartyMaster	
<pre>@category CIDMAS.IDSUTY ; CRS620MI/AddSupplier</pre>	The field indicates the Supplier type.
, CR3020WI/AddSupplier	If attribute type is "Supplier", populate SUTY with 0. If attribute type is "Agent", populate SUTY with 1. If attribute type is "Only Payee", populate SUTY with 2. If attribute type is "Supplier group", populate SUTY with 3. If attribute type is "Insurance Company", populate SUTY with 6. If attribute type is "Miscellaneous Suppliers", populate SUTY with 8. If attribute type is "Trade-in Supplier", populate SUTY with 9.
	Note: If not given, default SUTY to 0. Do not process SupplierPartyMaster BOD if SUTY = 5 (Forwarding agent).
RemitToPartyMaster/PartyIDs/ID CIDMAS.IDSUNO ; CRS620MI/CopyTemplate, AddSupplier,UpdSupplier, AddAddress,UpdAddress, DelAddress,AddSupplierRef, UpdSupplierRef,DelSupplierRef, LstSupplierRef	The field indicates the unique identity of the supplier (SUNO) or supplier item (STEM) . Record will be created in M3 'Supplier. Open' (CRS620), CIDMAS table.
OpuSupplierNet,DelSupplierNet, EstSupplierNet	If the field is left blank, SUNO field will be populated with "????????" which will trigger M3 to automatically generate a supplier number. If Control property: m3beDefaultSupplierPrefix has a value, then the value will be used as the first characters of SUNO, and the remaining characters will be "?".
Quality Maria	e.g. Control property: m3beDefaultSupplierPrefix = M3 Input SUNO: M3???????? Sample generated Supplier number in M3: M300000001
@schemeName	If schemeName = "System" is blank, populate supplier (SUNO). Otherwise, if schemeName = "System" exists, populate supplier template (STEM).
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
RemitToPartyMaster/PartyIDs/TaxID CIDVEN.IITINO CIDMAS.IDCORG CIDMAS.IDCOR2 CIDMAS.IDVRNO .; CRS620MI/AddSupplier, UpdSupplier @schemeName	The field indicates the Organization number (CORG), Organization number 2 (COR2), VAT registration number (VRNO) and Tax ID for Supplier (TINO) .
<u></u>	If attribute type is "CountryldentificationNumber", populate CORG. If attribute type is "CountryldentificationNumber", populate COR2. If attribute type is "TaxIdentificationNumber", populate VRNO. if attribute type blank, populate TINO.
RemitToPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the Standard Carrier Alpha Code (SCAC). The SCAC is a four-letter alpha code that uniquely identifies a forwarder.
RemitToPartyMaster/Name CIDMAS.IDSUNM ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the supplier name.
RemitToPartyMaster/Location @type CIDADR.SAADTE CIDADR.SAADID.; CRS620MI/AddAddress, UpdAddress, DelAddress,	The field indicates the address type.
LstAddress	If attribute type is "Postal", populate ADID with POSTAL and ADTE with 01.
	If attribute type is "Street", populate ADID with STREET and ADTE with 02.
	If attribute type is "Pickup", populate ADID with PICKUP and ADTE with 03. If attribute type is "Origin", populate ADID with ORIGIN and ADTE
	with 04. If attribute type is "Final", populate ADID with FINAL and ADTE with
	05. If attribute type is "Bank", leave ADID blank and populate ADTE with 10.
RemitToPartyMaster/Location/Name CIDADR.SASUNM	The field indicates the supplier name.
; CRS620MI/AddAddress, UpdAddress	Note: This is defaulted to CRS620 supplier name but can be different per address.

RemitToPartyMaster

RemitToPartyMaster/Location/Address/AddressLine CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4 .; CRS620MI/AddAddress, UpdAddress	The field indicates the address line.
@sequence	The field indicates the address line sequence number.
	If sequence = 1, populate ADR1. If sequence = 2, populate ADR2. If sequence = 3, populate ADR3. If sequence = 4, populate ADR4.
RemitToPartyMaster/Location/Address/CityName CIDADR.SATOWN ; CRS620MI/AddAddress, UpdAddress	The field indicates the city.
RemitToPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR ; CRS620MI/AddAddress, UpdAddress,UpdSupplier	The field indicates the state.
RemitToPartyMaster/Location/Address/CountryCode CIDADR.SACSCD ; CRS620MI/AddAddress, UpdAddress, AddSupplier, UpdSupplier	The field indicates the country.
RemitToPartyMaster/Location/Address/PostalCode CIDADR.SAPONO ; CRS620MI/AddAddress, UpdAddress	The field indicates the postal code.
RemitToPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT ; CRS620MI/AddAddress, UpdAddress, DelAddress	The field indicates the date from which the record is valid.
RemitToPartyMaster/Communication	
@sequence	The field indicates the communication sequence number. If sequence = 1, populate PHNO. If sequence = 2, populate PHN2. If sequence = 3, populate TFNO.
RemitToPartyMaster/Communication/ChannelCode	The field indicates the channel code Phone.
RemitToPartyMaster/Communication/UseCode	The field indicates the use code Office or Fax.
RemitToPartyMaster/Communication/CountryDialing CIDMAS.IDPHNO CIDMAS.IDPHN2 CIDMAS.IDTFNO .; CRS620MI/AddSupplier, UpdSupplier	The field indicates the country dialing code for a communication number. If ChannelCode = "Phone" exists, populate CountryDialing value as part of the Phone number.
	If UseCode = "Fax" exists, populate CountryDialing value as part of the Fax number.
RemitToPartyMaster/Communication/AreaDialing CIDMAS.IDPHNO CIDMAS.IDPHN2 CIDMAS.IDTFNO	The field indicates the area dialing code for a communication number.
.; CRS620MI/AddSupplier, UpdSupplier	If ChannelCode is "Phone" exists, populate AreaDialing directly after CountryDialing value as part of the Phone number. If UseCode = "Fax" exists, populate AreaDialing directly after CountryDialing value as part of the Fax number.
RemitToPartyMaster/Communication/DialNumber CIDMAS.IDPHNO CIDMAS.IDPHN2	The field indicates the dial number for communicate.
CIDMAS.IDTFNO CIDMAS.IDTFNO CRS620MI/AddSupplier, UpdSupplier	If ChannelCode is "Phone" and UseCode is "Office", populate Phone Number (PHNO/PHN2). If ChannelCode is "Phone" and UseCode is "Fax" populate Fax Number (TFNO).
RemitToPartyMaster/Contact	,/
<pre>@type CIDREF.IRRFTY ; CRS620MI/AddSupplierRef, UpdSupplierRef</pre>	The field indicates the reference type.
, C. Cozonia, Idaoappiion (ci, opaoappiion (ci	If reference type is "Purchase", populate RFTY with 10. If reference type is "Repair or Subcontract", populate RFTY with 15. If reference type is "Delivery receipt", populate RFTY with 20. If reference type is "Claim", populate RFTY with 25. If reference type is "Financial", populate RFTY with 30. If reference type is "Agreement", populate RFTY with 35.
RemitToPartyMaster/Contact/ID CIDREF.IRRFID ; CRS620MI/AddSupplierRef, UpdSupplierRef	The field indicates the reference ID.

RemitToPartyMaster CIDREF.IRYRE1 The field indicates the name of the person to be contacted for issues CRS620MI/AddSupplierRef, UpdSupplierRef regarding customer orders or purchase orders RemitToPartyMaster/Contact/Communication/ChannelCode The field indicates the channel code Phone or Email. RemitToPartyMaster/Contact/Communication/UseCode The field indicates the use code Office or Fax. RemitToPartyMaster/Contact/Communication/CountryDialing CIDREF.IRPHNO The field indicates the country dialing code for a communication CIDREF.IRTFNO number. .; CRS620MI/AddSupplierRef, UpdSupplierRef If ChannelCode = "Phone" exists, populate CountryDialing value as part of the Phone number. If UseCode = "Fax" exists, populate CountryDialing value as part of the Fax number. RemitToPartyMaster/Contact/Communication/AreaDialing CIDREF.IRPHNO The field indicates the area dialing code for a communication number. CIDREF.IRTFNO If ChannelCode is "Phone" exists, populate AreaDialing directly after .; CRS620MI/AddSupplierRef, UpdSupplierRef CountryDialing value as part of the Phone number. If UseCode = "Fax" exists, populate AreaDialing directly after CountryDialing value as part of the Fax number. RemitToPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO The field indicates the phone and fax number. CIDREF IRTENO .; CRS620MI/AddSupplierRef, UpdSupplierRef If ChannelCode is "Phone" and UseCode is "Office", populate Phone Number (PHNO). If ChannelCode is "Phone" and UseCode is "Fax" populate Fax Number (TFNO). RemitToPartyMaster/Contact/Communication/URI CIDREF IREMAL The field indicates the e-mail address. CRS620MI/AddSupplierRef, UpdSupplierRef RemitToPartyMaster/LanguageCode CIDMAS.IDLNCD The field indicates the language in which external documents are to CRS620MI/AddSupplier, UpdSupplier be printed RemitToPartyMaster/PaymentTermCode CIDVEN.IITEPY The field indicates how the payment due date is to be calculated. CRS620MI /AddSupplier, UpdSupplier RemitToPartyMaster/PaymentMethodCode CIDVEN.IIPYME The field indicates the method on how the supplier payment is ; CRS620MI /AddSupplier, UpdSupplier processed RemitToPartyMaster/FinancialParty/PartyIDs/ID ?CBANAC.?BCBKNO? The field indicates bank number ; CRS692MI/AddBankAccount, ChgBasicData RemitToPartyMaster/FinancialParty/PartyIDs/TaxID CIDVEN.IIVTCD The field indicates the VAT code. CRS620MI/AddSupplier, UpdSupplier RemitToPartyMaster/FinancialParty/Location/Address/CountryCode ?CBANAC.?BCBKIN? The field indicates the identity of the Bank Account Indicator. ; CRS692MI/AddBankAccount, ChgBacsicData, GetBankAccount If CountryCode is blank, populate "BANKACCTINDICATOR". Otherwise, If ListID is "BankIndicatorCountry" or "Countries", populate (BKIN) Bank account indicator that will be translated in CRS881 to

retrieve the correct value in M3.

The value in this element will only be used if element FinancialParty/ BranchParty/Location/Address/CountryCode is blank.

If ListID is "BankIndicatorCountry" or "Countries", populate (BKIN) Bank account indicator that will be translated in CRS881 to retrieve the correct value in M3

RemitToPartyMaster/FinancialParty/BranchParty/PartyIDs/BICID ?CBANAC.BCBBRN

CRS692MI/AddBankAccount, ChgBasicData

The field indicates Bank branch identity

RemitToPartyMaster/FinancialParty/BranchParty/Location/Address/CountryCode

?CBANAC.?BCBKIN?

@listID

@listID

; CRS692MI/AddBankAccount, ChgBacsicData, GetBankAccount

The field indicates the identity of the Bank Account Indicator.

If CountryCode is blank, populate "BANKACCTINDICATOR" Otherwise, if ListID is "BankIndicatorCountry", populate (BKIN) Bank account indicator country code that can be retrieved in M3 "Bank Account Indicator. Open" (CRS072), CBANAC table.

If ListID is "BankIndicatorCountry" or "Countries", populate (BKIN) Bank account indicator that will be translated in CRS881 to retrieve the correct value in M3.

RemitToPartyMaster

RemitToPartyMaster/FinancialParty/FinancialAccount/ID ?CBANAC.BCBKID; CRS692MI/AddBankAccount, ChgBasicData,	The field indicates the Bank Account ID.
DelBankAccount	If this element is blank, the value of BKID will be set to 'BANKACCTID' which is translated in CRS881.
RemitToPartyMaster/FinancialParty/FinancialAccount/IBANID ?CBANAC.?BCIBAN? ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates ?International bank account number?. The external system should send an encrypted IBANID and M3 will decrypt it before storing in the M3 table.
RemitToPartyMaster/FinancialParty/FinancialAccount/Name ?CBANAC.BCBANA ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates the Bank account name.
RemitToPartyMaster/FinancialParty/FinancialAccount/Status/Code	Set to "Deleted" if the bank account ID is to be deleted.
RemitToPartyMaster/UserArea 1) CIDMAS.IDCFI1 2) CIDMAS.IDALSU 3) CIDMAS.IDCSCD .; CRS620MI/AddSupplier, UpdSupplier	User defined field The field indicates the User defined field (CFI1). If attribute name is "SupplierFreeField1", populate User-defined field 1 (CFI1).
	Search key The field indicates a Search key (ALSU). If attribute name is "SearchKey", populate Search key (ALSU).
	3) Vat country code. The field indicates the Vat country code (CSCD) which will be used to retrieve the VAT registration number. If attribute name is "VATCountryCode", populate Vat country code (CSCD).
RemitToPartyMaster/Status/Code CIDMAS.IDSTAT	The field indicates the status.
; CRS620MI/AddSupplier, UpdSupplier	If code is "Pending" status is 10. Else, status is 05 if SupplierPartyMaster/PartyIDs/ID is STEM (Supplier Template). If code is Open or Approved status is set to 20. If code is Hold status is 30. If code is Closed or Deleted status is 90. If code is blank during an update of a supplier, the current status will be retatined.
RemitToPartyMaster/Classification/Codes/Code 1) CIDVEN.IIORTY 2) CIDVEN.IICOBI	The field indicates the classification code.
3) CIDVEN.IISCNO 4) CIDVEN.IIOUCN 5) CIDVEN.IITECD 6) CIDVEN.IITEDL	Order type The field indicates the settings that determine how the order is processed during order entry and in the processing flow. If attribute listID is "Order type", populate Customer type (ORTY).
7) CIDVEN.IIMODL 8) CIDVEN.IITEPA 9) CIDVEN.IITEAF 10) CIDVEN.IIPACD 11) CIDVEN.IISUST	Group of companies The field indicates the company group to which the supplier belongs. If attribute listID is "Group Of Companies", populate Group of companies (COBI).
12) CIDVEN.IICINP 13) CIDVEN.IITXAP 14) CIDVEN.IICRTP 15) CIDMAS.IDSUCO 16) CIDMAS.IDPIIN	Supplier's customer number The field indicates the supplier's customer number. If attribute listID is "Supplier's Customer Number", populate Supplier's customer number (SCNO).
17) CIDVEN.IDSUCL 18) CIDVEN.IDTAXC 19) CIDVEN.IITDCD 20) CIDVEN.IICUCD 21) CIDVEN.IIBUYE.; CRS620MI/AddSupplier, UpdSupplier	4) Our customer number at supplier The field indicates the our customer number at supplier, which is the customer number our supplier uses as identity for us. If attribute listID is "Our Customer Number", populate Our Customer number (OUCN).
	5) Cash discount term The field indicates the terms for cash discount calculation. If attribute listID is "Cash Discount Term", populate Cash Discount Term (TECD).
	6) Delivery terms The field indicates the delivery terms, which define when the responsibility for a delivery is transferred from supplier to the customer. If attribute listID is "Delivery Terms", populate Delivery Terms (TEDL).

7) Delivery method
The field indicates how the delivery is made.
If attribute listID is "Delivery Method", populate Delivery Method

Infor

May 26, 2023

154

(MODL).

8) Packaging tems

The field indicates the what terms apply when goods are packed. If attribute listID is "Packaging Terms", populate Packaging Terms (TEPA).

9) Freight terms

The field indicate the freigh terms which apply for the delivered goods. If attribute listID is "Freight Terms", populate Packaging Terms (TEAF).

10) Payment priority

The field indicates the payment priority.

If attribute listID is "Payment Priority", populate Packaging Terms (PACD).

If Highest Priority, populate PACD with A.

If Priority 1, populate PACD with 1.

If Priority 2, populate PACD with 2.

If Priority 3, populate PACD with 3.

If Priority 4, populate PACD with 4.

If Priority 5, populate PACD with 5.

If Priority 6, populate PACD with 6.

If Priority 7, populate PACD with 7.

If Lowest Priority, populate PACD with 8.

If Stopped, populate PACD with 9.

11) Supplier statistics

Set to 1 if statistics are to be calculated for the supplier.

If attribute listID is "Supplier Statistics", populate Supplier statistics (SUST).

12) Claim invoice permitted

Set to 1 if claim invoice is allowed.

If attribute listID is "Claim Invoice Permitted", populate Claim invoice permitted (CINP).

13) Tax applicable

The field indicates whether the supplier is required to declare VAT or sales tax.

If attribute listID is "Tax Applicable", populate Tax applicable (TAXP). If No, populate TAXP with 0.

If Yes, populate TAXP with 2.

14) Exchange rate type

The field indicates the exchange rate used when prices in the purchase module are converted to local currency or another currency. If attribute listID is "Exchange Rate Type", populate Exchange rate type (CRTP).

15) Supplier number within group

The field indicates the supplier number that the company group uses for the supplier.

If attribute listID is "Supplier Number In Group", populate Supplier number within group (SUCO).

16) Print packing instruction

The field indicates how to activate the automatic printing of connected packing instructions when purchase orders are printed.

If attribute listID is "Print Packing Instruction", populate Print packing instruction (PPIN).

If No, populate PPIN with 0.

If How to pack and Mark for, populate PPIN with 1.

If How to pack, populate PPIN with 2.

If Mark for, populate PPIN with 3.

17) Supplier group or Vendor group

The field indicates the supplier group or vendor group specified for each supplier.

If attribute listID is "Supplier Group", populate Supplier group (SUCL). If attribute listID is "VendorGroup", populate Vendor group (SUCL).

18) Tax code

The field indicates if an item, charge, customer or ship-to location is taxable or not.

If attribute listID is "Tax Code", populate Tax Code (TAXC).

19) Trade code

The field indicates a code that denotes the type of trade.

@listID

If attribute listID is "Trade Code", populate Trade Code (TDCD).

20) Currency

The field indicates the currency code used by the supplier.

21) Ruve

The field indicates the buyer.

- 1) If attribute listID is "Order type", populate Customer type (ORTY).
- 2) If attribute listID is "Group Of Companies", populate Group of companies (COBI).
- 3) If attribute listID is "Supplier's Customer Number", populate Supplier's customer number (SCNO).
- 4) İf attribute listlD is "Our Customer Number", populate Our Customer number (OUCN).
- 5) If attribute listID is "Cash Discount Term", populate Cash Discount Term (TECD).
- 6) If attribute listID is "Delivery Terms", populate Delivery Terms (TEDL).
- 7) If attribute listID is "Delivery Method", populate Delivery Method (MODL).
- 8) If attribute listID is "Packaging Terms", populate Packaging Terms (TEPA).
- 9) If attribute listID is "Freight Terms", populate Packaging Terms (TEAF).
- 10) If attribute listID is "Payment Priority", populate Packaging Terms (PACD).
- 11) If attribute listID is "Supplier Statistics", populate Supplier statistics (SUST).
- 12) If attribute listID is "Claim Invoice Permitted", populate Claim invoice permitted (CINP).
- 13) If attribute listID is "Tax Applicable", populate Tax applicable (TAXP).
- 14) If attribute listID is "Exchange Rate Type", populate Exchange rate type (CRTP).
- 15) If attribute listID is "Supplier Number In Group", populate Supplier number within group (SUCO).
- 16) If attribute listID is "Print Packing Instruction", populate Print packing instruction (PPIN).
- 17) If attribute listID is "Supplier Group", populate Supplier group (SUCL) else, If attribute listID is "VendorGroup", populate Vendor group (SUCL).
- 18) If attribute listID is "Tax Code", populate Tax Code (TAXC)
- 19) If attribute listID is "Trade Code", populate Trade Code (TDCD). 20) If attribute listID is "Currency Code", populate Currency Code
- (CUCD).
- 21) 20) If attribute listID is "Buyer", populate Buyer (BUYE).

Requisition

Requisition/RequisitionHeader/DocumentID/ID MPOPLP.PORORN; PPS170MI/CrtPOP	The field indicates the reference order number. Use reference order category 0.
@accountingEntity CSYTAB.CTCONO CSYTAB.CTDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.
Requisition/RequisitionHeader/Note CSYTXH.THTX40; CRS980MI/AddTxtBlockHead	The field indicates the note.
	CRS980MI/RtvNewTextID is called first to get the value of TXID. CRS980MI/AddTxtBlockHead is then called. TXID from RtvNewTextID transaction is used as input. User is retrieved from RequesterParty/PartyIDs/ID.
	Hardcoded values: File = MSYTXH Table = MPOPLP00
Requisition/RequisitionHeader/RequesterParty/PartyIDs/ID MPOPLP.PORESP; PPS170MI/CrtPOP	The field indicates the planner.
Requisition/RequisitionHeader/Classification/Codes/Code MPOPLP.POCOCE MPOPLP.POORTY.; PPS170MI/CrtPOP	1) The field indicates the Cost Center. If Code@listID = "Cost Centers", populate all lines without a cost center using the same data from the header. Prioritize Cost Center from RequisitionLine, then from RequisitionLine/Item, and lastly from RequisitionHeader.
	2) The field indicates the Purchase Order Type. If Code@listID ="Purchase Order Types", value should be used as Order Type (ORTY). If Requisition/RequisitionLine/Item/Classification/Codes/ Code@listID='Item Categories' is set to "FAS", use value from agreement control property m3beFixedAssetOrderType as input to ORTY. Default value for m3beFixedAssetOrderType is FAS. This should exist as PO Type in M3 PPS095 with defined Fixed asset type
@listID	1) "Cost Centers" 2) "Purchase Order Types"
Requisition/RequisitionLine/LineNumber MPOPLP.POPLPS MPOPLP.PORORL.; PPS170MI/CrtPOP	The field indicates the line number.
Requisition/RequisitionLine/Note CSYTXL.TLTX60; CRS980MI/AddTxtBlockLine	The field indicates the note.
	CRS980MI/RtvNewTextID is called first to get the value of TXID. Call CRS980MI/AddTxtBlockLine with TXID as one of the inputs.
	Hardcoded values: File = MSYTXH Table = MPOPLP00
	CRS980MI/SetTextID is then called. Use the following as inputs: FILE = MPOPLP00 TXID = TXID from RtvNewTextID KV01 = CONO KV02 = PLPN (with leading zeroes if less than 6 characters) KV03 = PLPS
@languagelD CSYTXL.TLLNCD; CRS980MI/AddTxtBlockLine	The field indicates the language for the note.
Requisition/RequisitionLine/Status/Code MPOPLP.POPSTS; PPS170MI/CrtPOP	The field indicates the status of the planned order. Set to "05" if status is Pending. Set to "20" if status is Open. Set to "60" if status is Approved. Set to "90" if status is Closed.
	Control property m3beStatusOverride is used if its value is not equal to "default".
Requisition/RequisitionLine/Item/Item/D/ID MPOPLP.POITNO; PPS170MI/CrtPOP	The field indicates the item number.
Requisition/RequisitionLine/Item/Description MPOPLP.POPITT; PPS170MI/CrtPOP	The field indicates the item description.
Requisition/RequisitionLine/Item/Classification/Codes/Code MPOPLP.POCOCE; PPS170MI/CrtPOP	The field indicates the cost center. Only relevant if RequisitionLine/Classification/Codes/Code is blank. If attribute listID is "Cost Centers", populate Cost Center (COCE). Prioritize Cost Center from RequisitionLine, then from RequisitionLine.

		-	
\mathbf{D}	\sim 1	110	 $^{\circ}$
Re	u	115	w

Roquiottion	
	Item, and lastly from RequisitionHeader.
	2) If Requisition/RequisitionLine/Item/Classification/Codes/ Code@listID='Item Categories' is set to "FAS", use value from agreement control property m3beFixedAssetOrderType as input to ORTY. Default value for m3beFixedAssetOrderType is FAS. This should exist as PO Type in M3 PPS095 with defined Fixed asset type.
@listID	 "Cost Centers" "Item Categories" - If Code=FAS, input to ORTY will be retrieved from agreement control property m3beFixedAssetOrderType.
Requisition/RequisitionLine/Quantity MPOPLP.POPPQT; PPS170MI/CrtPOP	The field indicates the planned quantity.
	If ProcessRequisition comes from EAM and attribute unitCode of Quantity is "LS", the value of the element will be swapped to the value of element Requisition/RequisitionLine/UnitPrice/Amount.
Requisition/RequisitionLine/UnitPrice/Amount MPOPLP.POPUPR; PPS170MI/CrtPOP	The field indicates the purchase price.
0	If ProcessRequisition comes from EAM and attribute unitCode of Quantity is "LS", the value of the element will be swapped to the value of element Requisition/RequisitionLine/Quantity.
@currencyID MPOPLP.POCUCD; PPS170MI/CrtPOP	The field indicates the currency.
Requisition/RequisitionLine/RequiredDeliveryDateTime MPOPLP.POPLDT; PPS170MI/CrtPOP	The field indicates the planned delivery date.
Requisition/RequisitionLine/ShipToParty/Location/ID MPOPLP.POWHLO; PPS170MI/CrtPOP	The field indicates the warehouse.
Requisition/RequisitionLine/RequesterParty/PartyIDs/ID MPOPLP.PORESP; PPS170MI/CrtPOP	The field indicates the planner.
Requisition/RequisitionLine/UserArea MPOPLP.POORTY; PPS170MI/CrtPOP	If the name attribute is "eam.ReqLineType" and name value is "PD", use value from m3beDirectPurchaseOrderType Agreement Control Property as PO type.
Requisition/RequisitionLine/SupplierParty/Party/Ds/ID MPOPLP.POSUNO; PPS170MI/CrtPOP	The field indicates the supplier. If not sent, retrieve default supplier from MITMAS.
Requisition/RequisitionLine/Classification/Codes/Code MPOPLP.POCOCE; PPS170MI/CrtPOP	The field indicates the cost center. If attribute listID is "Cost Centers", populate Cost Center (COCE). Prioritize Cost Center from RequisitionLine, then from RequisitionLine/ Item, and lastly from RequisitionHeader.
@listID	"Cost Centers"

<u> </u>	
SalesOrder/SalesOrderHeader/DocumentID/ID OXHEAD.OAORNO; OIS100MI/AddBatchHead	The field indicates the customer order number.
@accountingEntity OXHEAD.OACONO+OADIVI; /	The field indicates the company and division, displayed as CONO DIVI.
SalesOrder/SalesOrderHeader/AlternateDocumentID/ID OXHEAD.OACUOR; OIS100MI/AddBatchHead	The field indicates the alternate document number as customer ordenumber.
@schemeName	Set to 'Customer'.
SalesOrder/SalesOrderHeader/DocumentDateTime OXHEAD.OAORDT; OIS100MI/AddBatchHead	The field indicates the document date and time.
SalesOrder/SalesOrderHeader/Note OSYTXH.THTX40; OIS100MI/AddBatchText	The field indicates the notes.
@use OSYTXH.THTXEI; OIS100MI/AddBatchText	The field indicates if the text is external or internal. Set to '1' if the use is equals to blank or External. Set to '2' if the use is equals to Internal.
@type	The field indicates the type of text. Set to '2' if the type is equals to blank and footer. Set to '1' if the type is equals to header.
SalesOrder/SalesOrderHeader/DocumentReference @type	Set to 'Quote'
SalesOrder/SalesOrderHeader/DocumentReference/DocumentID/ OXHEAD.OFNO; OIS100MI/AddBatchHead	
SalesOrder/SalesOrderHeader/CustomerParty/PartyIDs/ID OXHEAD.OACUNO; OIS100MI/AddBatchHead	The field indicates the customer number.
SalesOrder/SalesOrderHeader/ShipToParty/PartyIDs/ID OXHEAD.OADECU; OIS100MI/AddBatchHead	The field indicates the delivery customer.
SalesOrder/SalesOrderHeader/ShipToParty/Name OXADRE.ODCUNM; OIS100MI/AddBatchAddress	The field indicates the customer name.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Att OXADRE.ODYREF; OIS100MI/AddBatchAddress	tentionOfName The field indicates the reference 1.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Ad OXADRE.ODCUA1 OXADRE.ODCUA2 OXADRE.ODCUA3 OXADRE.ODCUA4.; OIS100MI/AddBatchAddress	IdressLine The field indicates the address line.
@sequence	The field indicates the address line sequence.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Cit OXADRE.ODTOWN; OIS100MI/AddBatchAddress	tyName The field indicates the city name.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Co OXADRE.ODECAR; OIS100MI/AddBatchAddress	The field indicates an area, province or state within a country.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Co OXADRE.ODCSCD; OIS100MI/AddBatchAddress	ountryCode The field indicates the country code.
SalesOrder/SalesOrderHeader/ShipToParty/Location/Address/Po OXADRE.ODPONO: OIS100MI/AddBatchAddress	ostalCode The field indicates the postal code.
SalesOrder/SalesOrderHeader/ShipToParty/Communication/Char	·
SalesOrder/SalesOrderHeader/ShipToParty/Communication/Use	Code 1) Set to 'Office'. 2) Set to 'Fax'.
Sales Order/Sales Order Header/Ship To Party/Communication/Diall 1) OADRE.ODPHNO 2) OADRE.ODTFNO.; OIS 100 MI/Add Batch Address	•
	The field indicates the facsimile number. If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
SalesOrder/SalesOrderHeader/ShipFromParty/PartyIDs/ID OXHEAD.OAWHLO; OIS100MI/AddBatchHead	The field indicates the warehouse.
SalesOrder/SalesOrderHeader/ShipFromParty/Location @type	
	Set to 'Warehouse'. Set to 'Site'.
SalesOrder/SalesOrderHeader/ShipFromParty/Location/ID OXHEAD.OAWHLO OAFACI; OIS100MI/AddBatchHead	

	If attribute type is 'Warehouse', the field indicates the warehouse
	code. If attribute type is 'Site', the field indicates the facility.
SalesOrder/SalesOrderHeader/ContractReference/DocumentID/ID OXHEAD.OAAGNO; OIS100MI/AddBatchHead	The field indicates the blanket agreement number.
SalesOrder/SalesOrderHeader/BillToParty/PartyIDs/ID OXHEAD.OAINRC; OIS100MI/AddBatchHead	The field indicates the invoice recipient.
SalesOrder/SalesOrderHeader/BillToParty/Name OXADRE.ODCUNM; OIS100MI/AddBatchHead	The field indicates the name of the invoice recipient.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Attention OXADRE.ODYREF; OIS100MI/AddBatchAddress	<u> </u>
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Address OXADRE.ODCUA1 OXADRE.ODCUA2 OXADRE.ODCUA3 OXADRE.ODCUA4.; OIS100MI/AddBatchAddress	•
@sequence	The field indicates the address line sequence.
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/CityName	· · · · · · · · · · · · · · · · · · ·
SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Country	ySubDivisionCode
OXADRE.ODECAR; OIS100MI/AddBatchAddress SalesOrder/SalesOrderHeader/BillToParty/Location/Address/Country	The field indicates an area, province or state within a country. /Code
OXADRE.ODCSCD; OIS100MI/AddBatchAddress SalesOrder/SalesOrderHeader/BillToParty/Location/Address/PostalO	The field indicates the country code.
OXADRE.ODPONO; OIS100MI/AddBatchAddress	The field indicates the postal code.
SalesOrder/SalesOrderHeader/PayFromParty/PartyIDs/ID OXHEAD.OAPYNO; OIS100MI/AddBatchHead	The field indicates the payer.
SalesOrder/SalesOrderHeader/TransportationTerm/IncotermsCode OXHEAD.OATEDL; OIS100MI/AddBatchHead	The field indicates the delivery terms.
SalesOrder/SalesOrderHeader/TransportationMethodCode OXHEAD.OAMODL; OIS100MI/AddBatchHead	The field indicates the delivery methods.
SalesOrder/SalesOrderHeader/PaymentTerm/PaymentTermCode OXHEAD.OATEPY; OIS100MI/AddBatchHead	The field indicates the payment terms.
SalesOrder/SalesOrderHeader/PaymentTerm/Term/ID OXHEAD.OATEPY; OIS100MI/AddBatchHead	The field indicates the payment term ID.
SalesOrder/SalesOrderHeader/DistributedCharge/Description OXCHRG.OECRD0; OIS100MI/AddBatchHeadChg	The field indicates the description of the charge.
SalesOrder/SalesOrderHeader/DistributedCharge/Amount OXCHRG.OECRAM; OIS100MI/AddBatchHeadChg	The field indicates the charge amount.
SalesOrder/SalesOrderHeader/DistributedCharge/Calculation/RateNo	· · · · · · · · · · · · · · · · · · ·
OXCHRG.OECRFA; OIS100MI/AddBatchHeadChg	The field indicates the calculation factor that is used to calculate the charge amount.
SalesOrder/SalesOrderHeader/DistributedCharge/ReasonCode OXCHRG.OECRID; OIS100MI/AddBatchHeadChg @listID	The field indicates the charge code.
المالية	Set to 'false', if listID is Promotions. Set to 'true'.
SalesOrder/SalesOrderHeader/DistributedCharge/Tax/ID OXCHRG.OETAXC; OIS100MI/AddBatchHead	The field indicates if an item, charge, customer or ship-to location is taxable or not.
SalesOrder/SalesOrderHeader/EarliestDeliveryDateTime OXHEAD.OAFDED; OIS100MI/AddBatchHead	The field indicates the first valid delivery date for a customer order.
SalesOrder/SalesOrderHeader/RequiredDeliveryDateTime OXHEAD.OARLDZ+OARLHZ; OIS100MI/AddBatchHead	The field indicates the required delivery date time.
SalesOrder/SalesOrderHeader/PaymentMethodCode OXHEAD.OAPYCD; OIS100MI/AddBatchHead	The field indicates the payment method code. The payment method code is translated in CRS881.
	COGO IS translated in OrtOOOT.
SalesOrder/SalesOrderHeader/UserArea 1) OXHEAD.OAFRE1 2) OXHEAD.OAYREF	If attribute name is 'm3.CustomerStatisticsIdentity1', populate the
1) OXHEAD.OAFRE1	If attribute name is 'm3.CustomerStatisticsIdentity1', populate the customer statistics identity 1 (FRE1). 2) The field indicates the customer's contact person.
2) OXHEAD.OAYREF OIS100MI.AddBatchHead	customer statistics identity 1 (FRE1). 2) The field indicates the customer's contact person. If attribute name is 'AttentionOfName', populate the your reference

The field indicates the sales person ID
The field indicates the project number. If attribute listID is 'Project Numbers', populate project number (PROJ).
2) The field indicates the project element. If attribute listID is 'Project Elements', populate project element (ELNO)
(ELNO). 3) The field indicates the supply model.
If attribute listID is 'Supply Model', populate supply model (SPLM).
4) The field indicates a user-defined customer statistics accumulator. If attribute name is 'Customer Statistics Identity1', populate the customer statistics identity 1 (FRE1).
1) 'Project Numbers'
2) 'Project Elements'
3) 'Supply Model'
The field indicates the sales order type.
ironment/AcquirerIdentification The field indicates the acquirer identification.
nsaction/TransactionIdentification/ID The field indicates the reference number.
The field indicates the description.
The field indicates the remarks or notes.
The field indicates the item number.
The field indicates the item description.
The field indicates the lot number.
The field indicates the ordered quantity.
The field indicates the unit of measure.
The field indicates the unit price.
The field indicates the required delivery date and time.
The field indicates the shipping address ID.
The field indicates the delivery terms.
The field indicates the delivery methods.
The field indicates the payment term per item.
The field indicates the payment term ID.
The field indicates the name or description of the charge.
The field indicates the charge amount.
eric The field indicates the calculation factor that is used to calculate the charge amount.
The field indicates the charge code.
Set to 'false', if the listID is equals to Promotions. Set to 'true'.
The field indicates the promise or confirm delivery date and time.

<u> </u>	
OXLINE.OBAGNO; OIS100MI/AddBatchLine	The field indicates the blanket agreement number.
SalesOrder/SalesOrderLine/ShipFromParty/PartyIDs/ID	
OXLINE.OBWHLO; OIS100MI/AddBatchLine	The field indicates the warehouse where the item is coming from.
SalesOrder/SalesOrderLine/ShipFromParty/Location	
@type	
	Set to 'Warehouse'.
SalesOrder/SalesOrderLine/ShipFromParty/Location/ID	
OXLINE.OBWHLO; OIS100MI/AddBatchLine	The field indicates the warehouse code.
SalesOrder/SalesOrderLine/Classification/Codes/Code	
1) OXLINE.OBJDCD	1) The field indicates the joint delivery code.
OIS100MI.AddBatchLine	If attribute is 'Joint Delivery Code', populate joint delivery code
	(JDCD).
2) OXLINE.OBCUOR	
OIS100MI.AddBatchLine.; /	2) The field indicates the customer's order number.
	If attribute is 'Customer's Order Number', populate customer's order
	number (CUOR).
@listID	
	1) 'Joint Delivery Code'
	2) 'Customer's Order Number'
SalesOrder/SalesOrderLine/PricingAmount/UnitPretaxAmount	
OXLINE.OBSAPR; OIS100MI/AddBatchLine	The field indicates sales price.
SalesOrder/SalesOrderLine/ItemConfiguration/ConfigurationCompo	nent/ConfiguratorLinks/ConfigurationID
MPDCHF.QIEXHE; OIS100MI/AddBatchLine	The field indicates the external configuration number.
SalesOrder/SalesOrderLine/ItemConfiguration/ConfigurationCompo	nent/ConfiguratorLinks/ConfigurationDetailID
MPDCHF.QIEXCN; OIS100MI/AddBatchLine	The field indicates the external configuration number.
SalesOrder/SalesOrderLine/ProjectReference/ID	· ·
OXLINE.OBPROJ; OIS100MI/AddBatchLine	The field indicates the project number.
SalesOrder/SalesOrderLine/ProjectReference/ProjectElement/ID	
OXLINE.OBELNO; OIS100MI/AddBatchLine	The field indicate the project element number.
	b. electronic

SecurityUserMaster

SecurityUserMaster/IDs/ID	
CMNUSR.JUEUID; MNS150MI/Add	This is the User GUID set by IFS. It is an immutable id to be used for synchronizing other user id's in different Infor applications. M3 validates that it exists, if not, the BOD is rejected.
SecurityUserMaster/Status/Code CMNUSR.JUUSTA; MNS150MI/Add, MNS150MI/ChgDefaultValue/	This is the status of the User. M3 checks that the element exists and is valid, if not the BOD is rejected. BOD status is translated to M3 status according to: 'Enabled' = 20 'Disabled' = 90 'Removed' = 90 Also, if Security Role "M3UI-User" is removed from user in IFS, the M3 user is deactivated, i.e. status is set to 90.
@listID	This is the status listID. M3 checks that this is set to 'Security User Status'. If not, mapping is rejected.
SecurityUserMaster/Name CMNUSR.JUTX40; MNS150MI/Add, MNS150MI/ChgDefaultValue/	This is the users name.
SecurityUserMaster/UserAlias CMNUSR.JUUSID, CSYUSR.CRRESP.; MNS150MI/Add MNS150MI/AddUsrPerCmpDiv/	This is a user alias from IFS. The user alias will be used to set the M3 Application user Id in MNS150, as well as the M3 Business user Id in MNS151.
SecurityUserMaster/EMailAddress CEMAIL.CBEMAL; CRS111MI/Add & Change	This is the users email address. It is added in CRS111 with email type '04'.
SecurityUserMaster/SecurityRole/ID CMNRUS.KUROLL;CMNRUS.KUUSID.; MNS410MI/Add	This is used to check if the Ming.le user record sent via BOD should be added as user into M3. The Ming.le/IFS user must have security role "M3UI-User" for M3 to acknowledge it as a valid user.
	IFS Security Roles with same logical id as M3 and schemeName blank, will be used for adding or removing records for the user in MNS410 in M3.

ServiceConsumption

ServiceConsumption	
ServiceConsumption/ServiceConsumptionHeader/WarehouseLocation MHIHED.G0WHLO ; MHS850MI/AddPOReceipt	n/ID The field indicates the warehouse.
ServiceConsumption/ServiceConsumptionHeader/ShipFromParty/Par MHIHED.G0SUNO ; MHS850MI/AddPOReceipt	tyIDs/ID The field indicates the supplier number.
ServiceConsumption/ServiceConsumptionItem/ItemID/ID MHILIN.G2ITNO ; MHS850MI/AddPOReceipt	The field indicates the item number.
ServiceConsumption/ServiceConsumptionItem/Classification/Codes/MHILIN.G2WHSL MHILIN.G2OEND MHILIN.G2SUDO.; MHS850MI/AddPOReceipt	1) The field indicates the location If attribute listID is "Location", populate WHSL. 2) The field indicates if the line is flagged as completed. Set to '1' if the delivery of an order line is completed. Remaining quantity will not be backordered. Otherwise, the delivery is not completed and remaining quantity will be backordered. If attribute listID is "Flagged As Completed", populate OEND. If Code = "true" or "1", set OEND to 1. Otherwise, set OEND to 0. 3) The field indicates the supplier's delivery note number. If attribute listID is "Delivery Note", populate SUDO.
	1) "Location" for WHSL. 2) "Flagged As Completed" for OEND. 3) "Delivery Note" for SUDO.
ServiceConsumption/ServiceConsumptionItem/PurchaseOrderRefere MHILIN.G2PUNO ; MHS850MI/AddPOReceipt	nce/DocumentID/ID The field indicates the purchase order number.
ServiceConsumption/ServiceConsumptionItem/PurchaseOrderRefere MHILIN.G2RIDL MHILIN.G2RIDX.; MHS850MI/AddPOReceipt	nce/LineNumber The field indicates the concatenation of purchase order line and line suffix. The last 3 characters indicate the line suffix.
ServiceConsumption/ServiceConsumptionItem/SerializedLot/Lot/LotII MHILIN.G2BANO ; MHS850MI /AddPOReceipt	Ds/ID The field indicates the lot number.
ServiceConsumption/ServiceConsumptionItem/SerializedLot/Note MHILIN.G2BREF MHILIN.G2BRE2 .; MHS850MI/AddPOReceipt	1) The field indicates lot reference 1. If attribute noteID is "Lot Reference 1", populate BREF. 2) The field indicates lot reference 2. If attribute noteID is "Lot Reference 2", populate BRE2.
@notelD	1) "Lot Reference 1" for BREF. 2) "Lot Reference 2" for BRE2.
ServiceConsumption/ServiceConsumptionItem/ReceivedQuantity MHILIN.G2RVQA; MHS850MI/AddPOReceipt	The field indicates the quantity received.
ServiceConsumption/ServiceConsumptionItem/CatchWeightQuantity MHILIN.G2CAWE; MHS850MI/AddPOReceipt	The field indicates the catch weight.
ServiceConsumption/ServiceConsumptionItem/UserArea MHILIN.G2OEND; MHS850MI/AddPOReceipt	The field indicates if the line is flagged as completed. If attribute name is "eam.UDFCHKBOX01", populate OEND. If NameValue = "true" or "1", set OEND to 1. Otherwise, set OEND to 0.

ServiceOrder/ServiceOrderHeader/DocumentID/ID

For Work Order: For Work Order:

MMOHED.QHMWNO; MOS100MI/Get The field indicates the work order number.

For Service Order:

SSHEAD.SDORNO; SOS300MI/AddBatchHead The field indicates the work order number.

ChgSoHead @location

> For Work Order: For Work Order:

MMOHED.QHWHLO; MOS170MI/AddProp The field indicates the warehouse

ServiceOrder/ServiceOrderHeader/AlternateDocumentID/ID

For Work Order: For Work Order:

MMOHED.QHIORN; MOS170MI/AddProp The field indicates the interface order number

For Service Order: For Service Order:

SSHEAD.CUOR; SOS300MI/AddBatchHead The field indicates the customers order reference.

ChgSOHead

ServiceOrder/ServiceOrderHeader/DocumentDateTime

For Service Order: For Service Order:

SSHEAD.OSDT; SOS300MI/AddBatchHead The field indicates the document date and time.

ChgSOHead

ServiceOrder/ServiceOrderHeader/Description

For Work Order: For Work Order:

MMOHED.QHTX40 The field indicates the description. QHTXT1

QHTXT2; MOS170MI/AddProp For Service Order: The field indicates the work order description.

For Service Order:

SSHEAD.DLRM; SOS300MI/AddBatchHead

ChgSOHead

ServiceOrder/ServiceOrderHeader/DocumentReference

@type

For Work Order: For Work Order:

The field indicates the reference order category. MMOHED.QHRORC; MOS170MI/AddProp

If "ProductionOrder", set to 1 If "PurchaseOrder", set to 2 If "SalesOrder", set to 3 If "Transfer", set to 5 IF "WorkOrder", set to 6 If "ServiceOrder", set to 7 If "ProjectOrder", set to 8 If "ClaimOrder", set to 9

For Service Order:

ServiceOrder/ServiceOrderHeader/DocumentReference/DocumentID/ID

For Work Order: For Work Order:

MMOHED.QHRORN; MOS170MI/AddProp The field indicates the reference order number

For Service Order: For Service Order:

SSHEAD.RORN; SOS300MI/AddBatchHead The field indicates the reference order number.

ChgSOHead

ServiceOrder/ServiceOrderHeader/DocumentReference/DisplayID

For Service Order: For Service Order:

SSHEAD.RORL; SOS300MI/AddBatchHead The field indicates the reference line number

ChgSOHead

ServiceOrder/ServiceOrderHeader/DocumentReference/Facility/IDs/ID

For Work Order: The field indicates the facility

MMOHED.QHFACI: /

For Service Order:

SSHEAD.FACI; SOS300MI/AddBatchHead

ChgSOHead

ServiceOrder/ServiceOrderHeader/DocumentReference/SubLineNumber

For Service Order: For Service Order:

SSHEAD.RORX; SOS300MI/AddBatchHead The field indicates the reference sub-line number

ChgSOHead

ServiceOrder/ServiceOrderHeader/PriorityCode

For Work Order: For Work Order:

MMOHED.QHPRIO; MOS170MI/AddProp The field indicates the priority

ServiceOrder/ServiceOrderHeader/Status/Code

For Service Order: For Service Order:

SSHEAD.ORSL; SOS300MI/AddBatchHead The field indicates the status.

ChgSOHead ServiceOrder/ServiceOrderHeader/Status/EffectiveDateTime

For Service Order: For Service Order:

SSHEAD.RGDT; SOS300MI/AddBatchHead The field indicates the effectivity date and time. ChgSOHead

ServiceOrder/ServiceOrderHeader/Status/ReasonCode For Work Order: For Work Order: MMOHED.QHRSCD; MOS170MI/AddProp The field indicates the reason code ServiceOrder/ServiceOrderHeader/CustomerParty/PartyIDs/ID For Work Order For Work Order: MMOHED.QHCUNO; MOS170MI/AddProp The field indicates the customer number For Service Order: For Service Order: SSHEAD.CUNO; SOS300MI/AddBatchHead The field indicates the customer number. ServiceOrder/ServiceOrderHeader/CustomerParty/Name For Service Order: For Service Order: SSADRE.CUNM; SOS300MI/AddServBatchAdr The field indicates the customer name. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AttentionOfName For Service Order: For Service Order: SSADRE.YREF; SOS300MI/AddServBatchAdr The field indicates the contact person for the customer. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/AddressLine For Service Order: For Service Order: SSADRE.CUA1 The field indicates the address line. SSADRE.CUA2 SSADRE.CUA3 SSADRE.CUA4.; SOS300MI/AddServBatchAdr ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CityName For Service Order: For Service Order: SSADRE.TOWN; SOS300MI/AddServBatchAdr The field indicates the city name. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CountrySubDivisionCode For Service Order: For Service Order: SSADRE.ECAR; SOS300MI/AddServBatchAdr The field indicates an area, province or state within a country. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/CountryCode For Service Order: For Service Order: SSADRE.CSCD; SOS300MI/AddServBatchAdr The field indicates the country code. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/PostalCode For Service Order: For Service Order: SSADRE.PONO; SOS300MI/AddServBatchAdr The field indicates the postal code. ServiceOrder/ServiceOrderHeader/CustomerParty/Location/Address/Preference/Indicator For Service Order: The field indicates the preferred address ServiceOrder/ServiceOrderHeader/CustomerParty/Contact/ID For Work Order: For Work Order: CCUCON.CCCNPE; COS119MI/AddConnection The field indicates the contact ID. ServiceOrder/ServiceOrderHeader/ShipToParty/PartyIDs/ID For Service Order: For Service Order: SSADRE.CUNO+ADID; SOS300MI/AddServBatchAdr The field indicates the ship to party ID. ServiceOrder/ServiceOrderHeader/ShipToParty/Name For Service Order For Service Order: SSADRE.CUNM; SOS300MI/AddServBatchAdr The field indicates the ship to party name. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/AttentionOfName For Service Order: For Service Order: SSADRE.YREF; SOS300MI/AddServBatchAdr The field indicates the attention of name. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/AddressLine For Service Order: For Service Order: SSADRE.CUA1 The field indicates the address line. SSADRE.CUA2 SSADRE.CUA3 SSADRE.CUA4.; SOS300MI/AddServBatchAdr ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CityName For Service Order: For Service Order: SSADRE.TOWN; SOS300MI/AddServBatchAdr The field indicates the city name. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CountrySubDivisionCode For Service Order: For Service Order: SSADRE.ECAR; SOS300MI/AddServBatchAdr The field indicates an area, province or state within a country. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/CountryCode For Service Order: For Service Order: SSADRE.CSCD; SOS300MI/AddServBatchAdr The field indicates the country code. ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/PostalCode For Service Order: For Service Order: The field indicates the postal code SSADRE.PONO; SOS300MI/AddServBatchAdr ServiceOrder/ServiceOrderHeader/ShipToParty/Location/Address/Preference/Indicator For Service Order: The field indicates the preferred address ServiceOrder/ServiceOrderHeader/ConfiguredAsset/ID For Work Order: For Work Order: MMOHED.QHITNO + QHBANO; MOS170MI/AddProp The field indicates the product number and serial number.

ServiceOrder/ServiceOrderHeader/Classification/Codes/Code	
For Work Order: MMOHED.QHRTRO,	For Work Order: The field indicates the retro order, responsible, error code1, error
QHRESP,	code 2, error code3, estimated downtime, warranty type, customer
QHFCLA, QHFCL2.	order number, customer order line number, contact person, agreement number, agreement order type
QHFCL3,	agreement names, agreement order type
QHEDWT QHWATP.	
QHGWAR,	
QHCUOR,	
QHCUPO+QHCUSX, QHYREF	
QHAAGN,	
QHAOTY; MOS170MI/AddProp @ <i>listID</i>	
	For Work Order:
	The field indicates the following ListID: "Retro Order"
	"Responsible"
	"Error Code 1s" "Error Code 2s"
	"Error Code 3s"
	"Estimated Downtime" "Warranty Type"
	"Generic Warranty"
	"Customer Order Number" "Customer Order Line Number"
	"Contact Person"
	"Agreement Number" "Agreement Order Type"
ServiceOrder/ServiceOrderHeader/ReportedDateTime	Agreement Order Type
For Service Order:	For Service Order:
SSHEAD.PMDT SSHEAD.PMTM.; SOS300MI/AddBatchHead	The field indicates the reported date and time.
ChgSOHead	
ServiceOrder/ServiceOrderHeader/FailureDateTime For Work Order:	For Work Order:
MMOHED.QHBRDT + QHBRTI; MOS170MI/AddProp	The field indicates the breakdown date and time
For Service Order: SSHEAD.PMDT	For Service Order: The field indicates the failure date and time.
SSHEAD.PMTM.; SOS300MI/AddBatchHead	The field indicates the failure date and time.
ChgSOHead Time Time Time Time Time Time Time Time	
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/StartDateTime For Work Order:	For Work Order:
MMOHED.QHSTDT+QHMSTI; MOS170MI/AddProp	The field indicates the planned start date
For Service Order:	For Service Order:
SSHEAD.RQSR	The field indicates the plan start date and time.
SSHEAD.RQST.; SOS300MI/AddBatchHead ChgSOHead	
ServiceOrder/ServiceOrderHeader/PlannedTimePeriod/EndDateTime	
For Work Order: MMOHED.QHFIDT+QHMFTI; MOS170MI/AddProp	For Work Order: The field indicates the planned finish date.
For Service Order:	For Service Order:
SSHEAD ROET: SOS200MI/AddPatabHood	The field indicates the planned finish date and time.
SSHEAD.RQFT.; SOS300MI/AddBatchHead ChgSOHead	
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/StartDateTime	
For Service Order: SSHEAD.CSDT	For Service Order: The field indicates the actual start date and time
SSHEAD.CSTM.; SOS300MI/AddBatchHead	and the second s
ChgSOHead SorviceOrder/ServiceOrderHeader/ActualTimePeriod/EndPateTime	
ServiceOrder/ServiceOrderHeader/ActualTimePeriod/EndDateTime For Service Order:	For Service Order:
SSHEAD.CFDA	The field indicates the actual finish date and time.
SSHEAD.CFTM.; SOS300MI/AddBatchHead ChgSOHead	
ServiceOrder/ServiceOrderHeader/EstimatedDuration	
For Work Order: MMOHED.QHPITI; MOS170MI/AddProp	For Work Order: The field indicates the estimated duration.
ServiceOrder/ServiceOrderHeader/PreventiveMaintenanceID	The nota indicates the estimated duration.
For Work Order:	For Work Order:
MMOHED.QHSUFI+QHSTRT; MOS170MI/AddProp	The field indicates the service

ServiceOrder ServiceOrder/ServiceOrderHeader/UserArea/Property/NameValue For Service Order: For Service Order: MMOHED.QHCFI1 The field indicates the user defined fields 1 to 5 QHCFI2 QHCFI3 QHCFI4 QHCFI5; MOS170MI/AddProp ServiceOrder/ServiceOrderHeader/SupervisorID For Service Order: For Service Order: SSHEAD.SRES; SOS300MI/AddBatchHead The field indicates the service manager. ChgSOHead ServiceOrder/ServiceOrderHeader/ProjectReference/ID For Service Order: For Service Order: SSHEAD.PROJ; SOS300MI/AddBatchHead The field indicates the project number. ChgSOHead ServiceOrder/ServiceOrderHeader/ProjectReference/ProjectElement/ID For Service Order: For Service Order: SSHEAD.ELNO; SOS300MI/AddBatchHead The field indicates the project element number. ChgSOHead ServiceOrder/ServiceOrderHeader/SalesPersonReference/IDs/ID For Service Order For Service Order: SSHEAD.SMCD; SOS300MI/AddBatchHead The field indicates the sales person. ChqSOHead ServiceOrder/ServiceOrderHeader/PreferredEngineerPerson/ID For Work Order For Work Order: MMOHED.QHEMNO; MOS170MI/AddProp The field indicates the preferred engineer. For Service Order: For Service Order: SSHEAD.TECH; SOS300MI/AddBatchHead The field indicates the preffered engineer. ChgSOHead ServiceOrder/ServiceOrderHeader/SiteLocation/ID For Work Order: For Work Order: MMOHED.QHADID; MOS170MI/AddProp The field indicates the address number. ServiceOrder/ServiceOrderHeader/SiteLocation/Classification/Codes/Code For Work Order: For Work Order: MMOHED.QHADRT The field indicates the address type, address file QHADRR; MOS170MI/AddProp @listID For Work Order: The field indicates the following ListID: "Address Type" "Address File" ServiceOrder/ServiceOrderHeader/ServiceTypeCode For Service Order For Service Order: SSHEAD.SDSOTP; SOS300MI/AddBatchHead The field indicates the service type code. ServiceOrder/ServiceOrderHeader/CustomerTimePeriod/StartDateTime For Work Order: For Work Order: MMOHED.QHRRSD + QHRRST; MOS170MI/AddProp The field indicates the requested start date For Service Order: For Service Order: SSHEAD.CUDT; SOS300MI/AddBatchHead This field indicates the customer requiered requested start date-time. ChgSOHead ServiceOrder/ServiceOrderHeader/CustomerTimePeriod/EndDateTime For Work Order: MMOHED.QHRRFD + QHRRFT; MOS170MI/AddProp The field indicates the requested finish date ServiceOrder/ServiceOrderHeader/BillToParty/PartyIDs/ID For Service Order: For Service Order: SSHEAD.PYNO; SOS300MI The field indicates the bill to party ID. SOS300MI/AddBatchHead AddServBatchAdr ChgSOHead ServiceOrder/ServiceOrderHeader/BillToParty/PartyIDs/TaxID For Service Order: For Service Order: SSADRE.CUNM; SOS300MI/AddServBatchAdr The field indicates the bill to party tax ID. ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/AttentionOfName For Service Order: For Service Order SSADRE.YREF; SOS300MI/AddServBatchAdr The field indicates the attention of name.

SSADRE.YREF; SOS300MI/AddServBatchAdr The field indicates the attention of nan

Service Order/Service Order Header/Bill To Party/Location/Address/Address Line

For Service Order: For Service Order:

SSADRE.CUA1 The field indicates the address line.

SSADRE.CUA2 SSADRE.CUA3

SSADRE.CUA4.; SOS300MI/AddServBatchAdr

ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/CityName

ServiceOrder	
For Service Order: SSADRE.TOWN; SOS300MI/AddServBatchAdr	For Service Order: The field indicates the city name.
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/Court	
For Service Order:	For Service Order:
SSADRE.ECAR; SOS300MI/AddServBatchAdr ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/County	The field indicates an area, province or state within a country.
For Service Order:	For Service Order:
SSADRE.CSCD; SOS300MI/AddServBatchAdr	The field indicates the country code.
ServiceOrder/ServiceOrderHeader/BillToParty/Location/Address/Post For Service Order:	alCode For Service Order:
SSADRE.PONO; SOS300MI/AddServBatchAdr	The field indicates the postal code.
ServiceOrder/ServiceOrderHeader/PayFromParty/PartyIDs/ID	For Soniag Order
For Service Order: SSHEAD.PYNO; SOS300MI/AddServBatchAdr	For Service Order: The field indicates the pay from party ID.
ServiceOrder/ServiceOrderHeader/PayFromParty/Name	
For Service Order: SSADRE.CUNM: SOS300MI/AddServBatchAdr	For Service Order: The field indicates the customer name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/A	
For Service Order:	For Service Order:
SSADRE.YREF; SOS300MI/AddServBatchAdr	The field indicates the attention of name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/A For Service Order:	For Service Order:
SSADRE.CUA1	The field indicates the address line.
SSADRE.CUA2 SSADRE.CUA3	
SSADRE.CUA4.; SOS300MI/AddServBatchAdr	
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/C For Service Order:	ityName For Service Order:
SSADRE.TOWN; SOS300MI/AddServBatchAdr	The field indicates the city name.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/C	
For Service Order: SSADRE.ECAR; SOS300MI/AddServBatchAdr	For Service Order: The field indicates an area, province or state within a country.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/C	
For Service Order:	For Service Order:
SSADRE.CSCD; SOS300MI/AddServBatchAdr ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/P	The field indicates the country code.
For Service Order:	For Service Order:
SSADRE.PONO; SOS300MI/AddServBatchAdr	The field indicates the postal code.
ServiceOrder/ServiceOrderHeader/PayFromParty/Location/Address/P	rererence/indicator For Service Order:
	The field indicates the preferred address
ServiceOrder/ServiceOrderLine/LineNumber For Work Order:	For Work Order:
MMOOPE.QOOPNO; MOS100MI/AddOp,	The field indicates the operation number
ChgOp,	
DelOp	For Service Order: The field indicates the line number.
For Service Order:	
SSJOBH.JOBN SSJOBH.JBSX.; SOS300MI/ChgSOAssignm	
ServiceOrder/ServiceOrderLine/Description	
For Work Order: MMOOPE.QOOPDS; MOS100MI/AddOp,	For Work Order: The field indicates the description
ChgOp	тто пом шиновно вно чезоприон
ServiceOrder/ServiceOrderLine/Note	
For Work Order: MMOOPE.QOTXT1 + QOTXT2; MOS100MI/AddOp,	For Work Order: The field indicates text1 and text2
ChgOp	
ServiceOrder/ServiceOrderLine/ProjectReference/ID	For Soniag Order
For Service Order: SSJOBH.PROJ; SOS300MI/ChgSOAssignm	For Service Order: The field indicates the project reference ID.
ServiceOrder/ServiceOrderLine/EstimatedDuration	· ·
For Work Order: MMOOPE.PITI; MOS100MI/AddOp, ChgOp	For Work Order: The field indicates the run time
ServiceOrder/ServiceOrderLine/ReportedDateTime	THE HEIGH HIGHEST THE FULL WHITE
For Service Order:	For Service Order:
SSJOBH.PMDT	The field indicates the error reporting date and time.
SSJOBH PMTM : SOS300MI/ChaSOAssianm	
SSJOBH.PMTM.; SOS300MI/ChgSOAssignm ServiceOrder/ServiceOrderLine/CompletionDateTime	
ServiceOrder/ServiceOrderLine/CompletionDateTime For Service Order:	For Service Order:
ServiceOrder/ServiceOrderLine/CompletionDateTime	For Service Order: The field indicates the actual start date and time.

169 Infor May 26, 2023

ServiceOrder For Work Order: For Work Order: MROOPS.MSMVA0; MOS160MI/UpdMeterValue The field indicates the meter value @unitCode For Work Order: For Work Order: MROOPS.MSMES0; MOS160MI/UpdMeterValue The field indicates the meter ServiceOrder/ServiceOrderLine/MeterRecording/RecordingDateTime For Work Order: For Work Order: MROOPS.MSSTDT, MSSTTI; MOS160MI/UpdMeterValue The field indicates the meter recording start date and time ServiceOrder/ServiceOrderLine/Failure/Problem/ID For Work Order: For Work Order: MMOSER.SEITNO.; MOS057MI/Add, Upd The field indicates the item number. ServiceOrder/ServiceOrderLine/Failure/Problem/Type For Work Order: For Work Order: The field is used to indicate the main service error report when MMOSER.SEMAIN; MOS057MI/Add, Upd several error reports exist for the same reference order. ServiceOrder/ServiceOrderLine/Failure/Problem/Note For Work Order: For Work Order: MMOSER.SEERQT + SETXL1 + SETXL2; MOS057MI/Add, Upd The field indicates the quantity and problem notes @author For Work Order: For Work Order: MMOSER.SEREPR; MOS057MI/Add, Upd The field indicates the user ID of the person that reported the record. ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/ID For Work Order: For Work Order: MMOSER.SEFCLA; MOS100MI.AddOp.FCLA, The field indicates the symptom code MOS100MI.ChgOp.FCLA, MOS820MI.StopOp.FCLA, For Service Order: MOS057MI.Add.FCLA, The field indicates the Failure/Problem/Symptom/ID. MOS057MI.Upd.FCLA/ For Service Order: SSJOBH.ESCO; SOS300MI/ChgSOAssignm ServiceOrder/ServiceOrderLine/Failure/Problem/Symptom/Note For Work Order: For Work Order: MMOSER.SETXL3 + SETXL4; MOS057MI/Add, Upd The field indicates the symptom notes @entryDateTime For Work Order: For Work Order: MMOSER.SEBRDT + SEBRTI; MOS057MI/Add, Upd The field indicates the date and time the equipment broke down. ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/ID For Work Order: For Work Order: MMOOPE.QOFCL3; MOS100MI.AddOp.FCL2, The field indicates the problem cause code MOS100MI.ChgOp.FCL2, MOS820MI.StopOp.FCL2, For Service Order: MOS057MI.Add.FCL2 The field indicates the Failure/Problem/Cause/ID. MOS057MI.Upd.FCL2/ For Service Order: SSJOBH.ERCO; SOS300MI/ChgSOAssignm ServiceOrder/ServiceOrderLine/Failure/Problem/Cause/Note For Work Order: For Work Order: MMOSER.SETXL5 + SETXL6; MOS057MI/Add, Upd The field indicates the problem cause notes ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/ID For Work Order: For Work Order: MMOOPE.QOSMC0-QOSMC9; MOS100MI.AddOp.FCL3, The field indicates the remedy. MOS100MI.ChgOp.FCL3, MOS057MI.Add.FCL3, MOS057MI.Upd.FCL3/ ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/Description For Work Order: For Work Order: MMOSER.SETXL7 + SETXL8; MOS057MI/Add, Upd The field indicates the remedy description ServiceOrder/ServiceOrderLine/Failure/Problem/Remedy/Note For Work Order: For Work Order: MMOSER.SETXL9 + SETXL0; MOS057MI/Add, Upd The field indicates the repair comment text. @entryDateTime For Work Order: The field indicates the date the object was ready to be put back in MMOSER.SEMRDT + SEMRTI; MOS057MI/Add, Upd operation after a failure. @status For Work Order: For Work Order:

MMOSER.SESTAT; MOS057MI/Add, Upd

The field indicates the status of the error report

ServiceOrder/ServiceOrderLine/Status/Code
For Service Order:
For Service Order:

SSJOBH.JBST; SOS300MI/ChgSOAssignm

The field indicates the valid Status/Code for an operation.

ServiceOrder/ServiceOrderLine/ConfiguredAsset/ID
For Service Order:
For Service Order:

SSJOBH.INNO The field indicates the equipment ID, (PRNO + BANO).

SSJOBH.SERI.; SOS300MI/ChgSOAssignm	
ServiceOrder/ServiceOrderLine/ConfiguredAsset/Description For Service Order:	Ear Santiag Order
For Service Order: SSJOBH.MODE; SOS300MI/ChgSOAssignm	For Service Order: The field indicates the equipment description.
ServiceOrder/ServiceOrderLine/EstimatedDownTimeDuration	The note interested the equipment description.
For Work Order:	For Work Order:
MMOOPE.QODOWT; MOS100MI/AddOp, ChgOp	The field indicates the estimated downtime of the equipment.
ServiceOrder/ServiceOrderLine/CustomerTimePeriod/StartDateTime	
For Service Order:	For Service Order:
SSJOBH.SERQSD+	The field indicates the customer requested start date and time.
SERQST; SOS300MI/ChgSOAssignm	
ServiceOrder/ServiceOrderLine/CustomerTimePeriod/EndDateTime For Service Order:	For Service Order:
SSJOBH.SERQFD+	The field indicates the customer requested end date and time.
SERQFT; SOS300MI/ChgSOAssignm	'
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/StartDateTime	
For Work Order:	For Work Order:
MMOOPE.STDT + MSTI; MOS100MI/AddOp, ChgOp	The field indicates the plan start date and time
For Service Order:	For Service Order:
SSJOBH.SEPSDJ+	The field indicates the planned start date and time.
SEPSTJ; SOS300MI/ChgSOAssignm	
ServiceOrder/ServiceOrderLine/PlannedTimePeriod/EndDateTime	
For Work Order:	For Work Order:
MMOOPE.FIDT + MFTI; MOS100MI/AddOp, ChgOp	The field indicates the plan end date and time
For Service Order:	For Service Order:
SSJOBH.SEPFDJ+	The field indicates the planned end date and time.
SEPFTJ; SOS300MI/ChgSOAssignm	,
ServiceOrder/ServiceOrderLine/PlannedTravelTimePeriod/Duration	
For Work Order:	For Work Order:
MMOOPE.SETI; MOS100MI/AddOp, ChgOp	The field indicates the travel time duration
ServiceOrder/ServiceOrderLine/SupplierParty/PartyIDs/ID	5 W 1 O 1
For Work Order: MMOOPE.QOSUNO; MOS100MI/AddOp,	For Work Order:
ChgOp	The field indicates the supplier number on the operation
ServiceOrder/ServiceOrderLine/RequiredServiceSkills/Code	
For Service Order:	For Service Order:
SSJOBH.QUNO; SOS300MI/ChgSOAssignm	The field indicates the qualification code.
ServiceOrder/ServiceOrderLine/RequiredServiceSkills/Name	
For Work Order:	For Work Order:
MMOOPE.QOPLGR; MOS100MI/GetOp	The field indicates the RequiredServiceSkills/Workcewnter from operation
ServiceOrder/ServiceOrderLine/AssignmentGroup/LineNumber	ореганоп
For Work Order:	For Work Order:
MMOOPS.QQACTS+ QQACTT; MOS104MI/AddOpElement,	The field indicates the operation element/assignment line
ChgOpElement	· · · · · · · · · · · · · · · · · · ·
DelOpElement	
ServiceOrder/ServiceOrderLine/AssignmentGroup/ActivityEngineerPe	
For Work Order: MMOOPS.QQEMNO; MOS104MI/AddOpElement,	The field indicates the employee number.
ChgOpElement	
For Service Order:	
SSJOBH.SETECH; SOS300MI/ChgSOAssignm DaccountingEntity	
yaccounting_muty	For Work Order:
	The field indicates the company and division.
ServiceOrder/ServiceOrderLine/AssignmentGroup/Status/Code	
For Work Order:	For Work Order:
MMOOPS.QQSTMB; MOS104MI/AddOpElement,	The field indicates the standard status
	If "Assigned", set to 20
ChgOpElement	
	If "Accepted", set to 40 If "Travel Started", set to 41
	If "Travel Started", set to 41
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46 If "Stopped", set to 80
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46 If "Stopped", set to 80 If "Completed", set to 90
ChgOpElement	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46 If "Stopped", set to 80 If "Completed", set to 90 If "Rejected", set to 99
	If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46 If "Stopped", set to 80 If "Completed", set to 90 If "Rejected", set to 99

ServiceOrder/ServiceOrderLine/AssignmentGroup/Status/ReasonCode For Work Order: For Work Order: MMOOPS.QQSTMB; MOS104MI/AddOpElement, The field indicates the mobility status If "Assigned", set to 20 If "Accepted", set to 40 ChgOpElement If "Travel Started", set to 41 If "Travel Stopped", set to 42 If "Arrived on Site", set to 44 If "Started", set to 45 If "Pending", set to 46 If "Stopped", set to 80 If "Completed", set to 90 If "Rejected", set to 99 ServiceOrder/ServiceOrderLine/AssignmentGroup/RejectionDatetime For Work Order: For Work Order: MMOLOG.DMTRDT + DMTRTM; MOS102MI/Add The field indicates the rejection date and time ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTimePeriod/StartDateTime For Service Order: For Service Order SSJOBH.PSDW+PSTW; SOS300MI/ChgSOAssignm The field indicates the planned start date time. ServiceOrder/ServiceOrderLine/AssignmentGroup/PlannedTimePeriod/EndDateTime For Service Order For Service Order: SSJOBH.PFDW+PFTW; SOS300MI/ChgSOAssignm The field indicates the planned finish date time. ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/StartDateTime For Work Order: For Work Order: MMOOPE.STDT + OSTM; MOS070MI/ReportStartStop The field indicates the actual start date and time For Service Order: For Service Order: SSJOBH.RSDW+RSTW; SOS300MI/ChgSOAssignm The field indicates the actual start date time. ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/Duration For Work Order: For Work Order: MMOPTR.QJUMAT; MOS070MI/UpdOperation The field indicates the actual time duration ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTimePeriod/EndDateTime For Work Order: For Work Order: MMOOPE.FIDT + OFTM; MOS070MI/ReportStartStop The field indicates the actual end date and time ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTravelTimePeriod/StartDateTime For Work Order: For Work Order: MMOOPE.STDT + OSTM; MOS070MI/ReportTravelTime The field indicates the actual start date and time travel time ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTravelTimePeriod/Duration For Work Order: For Work Order: MMOPTR.QJUMAS; MOS070MI/UpdOperation The field indicates the actual travel duration ServiceOrder/ServiceOrderLine/AssignmentGroup/ActualTravelTimePeriod/EndDateTime For Work Order: For Work Order: MMOOPE.FIDT + OFTM; MOS070MI/ReportTravelTime The field indicates the actual end date and time travel time ServiceOrder/ServiceOrderLine/AssignmentGroup/Note For Work Order: For Work Order: MMOOPS.QQACDS + QQACTR + QQCATY + QQRSCD + QQEVTE + The field is a concatenation of operation element description, work QQTXT1 + QQINSI; MOS104MI/AddOpElement, element, capability type, reason code, event type, text and inspection ChgOpElement result values ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/LineNumber For Work Order: For Work Order: MMOMAT.QMMSEQ; MOS100MI/AddMtrl, The field indicates the material line sequence number ChgMtrl, DelMtrl For Service Order: The field indicates the material line sequence number. For Service Order: SSLINE.JOBN+JBSX+ PONR+POSX; SOS300MI/ChgSOLine AddSOLine ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialEngineerPerson/IDs/ID For Service Order: For Service Order: SSLINE.TECH; SOS300MI/ChgSOLine The field indicates the technician. AddSOLine ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Status/Code For Work Order: For Work Order: MMOMAT.QMWMST; MOS100MI/AddMtrl, The field indicates the material status code. If "Open", set to 20 ChgMtrl If "Canceled", set to 94 ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Status/ReasonCode

For Work Order

For Work Order:

MMOMAT.QMWMST; MOS100MI/AddMtrl, The field indicates the material status code.

If "Open", set to 20 If "Canceled", set to 94 ChgMtrl

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Note For Work Order:

ServiceOrder MMOMAT.QMFMT1; MOS100MI/AddMtrl,	For Work Ordon
ChgMtrl	For Work Order: The field indicates the text
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/MaterialItem/Ite	
For Work Order:	The field indicates the material id/item number.
MMOMAT.QMMTNO; MOS100MI/AddMtrl,	
ChgMtrl	
For Service Order:	
SSLINE.SFITNO; SOS300MI/AddSOLine	
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/Classification/C	
For Work Order: MMOMAT.QMIORL	For Work Order: The field indicates the interface order line
MMOMAT.QMWHSL	The field indicates the flag as completed.
MMOMAT.QMPRMO	The filed indicates the stock location.
MMOMAT.ACWA	The field indicates the price origin
MMOMAT.MAUP MMOMAT.BANO.; MOS100MI.AddMtrl.IORL	The field indicates the claim warranty The field indicates if the sales price is manually updated
MOS100MI.AReportUsedMtrl.OEND	The field indicates serial or lot number of the item
MOS100MI.AddMtrl/ChgMtrl.WHSL	
MOS100MI.ChgMtrl.PRMO	
MOS100MI.ChgMtrl.ACWA MOS100MI.ChgMtrl.MAUP	
MOS100MI.AddMtrl/ChgMtrl.BANO/	
@listID	F. W. I.O. I
	For Work Order: The field indicates the following ListID:
	"Interface Order Line"
	"Manual Completion Flag"
	"Stock Location"
	"Price Origin" "Claim Warranty"
	"Manual Update"
	"Lot Number"
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Na	
For Work Order: MOADDR.OYCUNM; /	For Work Order: The field indicates the customer name.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order:	For Work Order:
MMOMAT.QMADRR + QMADRT + QMADID + QMLTYP; MOS100MI/	The field indicates the delivery address for the material (if populated)
AddMtrl ChgMtrl	Else take from WO header +
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	ocation/Name
For Work Order:	For Work Order:
MOADDR.OYDSTX + OYEDES; MOS156MI/Add	The field indicates the delivery comment and place.
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order: MOADDR.OYYREF; MOS156MI/Add	For Work Order: The field indicates the attention of name
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order:	For Work Order:
MOADDR.OYCUA1 + OYCUA2 + OYCUA3 + OYCUA4; MOS156MI/Add	d The field indicates the address lines.
@sequence	For Work Order:
	The field indicates the address line sequence number starting with 1
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	· · · · · · · · · · · · · · · · · · ·
For Work Order:	For Work Order:
MOADDR.OYTOWN; MOS156MI/Add	The field indicates the city name
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order: MOADDR.OYECAR; MOS156MI/Add	For Work Order: The field indicates the state
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order:	For Work Order:
MOADDR.OYCSCD; MOS156MI/Add	The field indicates the country code
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Lo	
For Work Order: MOADDR.OYPONO; MOS156MI/Add	For Work Order: The field indicates the postal code
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Co	·
	For Work Order:
	Set to ""Phone"
ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ShipToParty/Co	
	For Work Order:
	Set to "Office" if PHNO is not blank
	Set to "Office" if PHNO is not blank. Set to "Fax" if TFNO is not blank.

MOADDR.OYPHNO + OYTFNO: MOS156MI/Add For Work Order:

The field indicates the phone and fax number

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/SupplierParty/PartyIDs/ID

For Work Order: For Work Order:

MMOMAT.QMSUNO; MOS100MI/AddMtrl, ChgMtrl The field indicates the supplier code

For Service Order: For Service Order:

SSLine.SUNO; SOS300MI/ChgSOLine The field indicates the supplier number.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedWarehouseLocation/ID

For Work Order For Work Order:

MMOMAT.QMFWHL; MOS100MI/AddMtrl, ChgMtrl The field indicates the warehouse

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedQuantity

For Work Order For Work Order:

MMOMAT.QMCNQT; MOS100MI/AddMtrl, The field indicates the estimated quantity

ChgMtrl

@unitCode

For Work Order: For Work Order:

MMOMAT.QMPEUN; MOS100MI/AddMtrl, The field indicates the unit of measure.

ChaMtrl

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedBaseUOMQuantity

For Service Order: For Service Order:

SSLINE.ORQT; SOS300MI/ChqSOLine The field indicastes base quantity.

AddSOI ine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualQuantity

For Work Order: For Work Order:

MMOMAT.QMRPQT: MHS850MI The field indicates the actual quantity/reported quantity

MOS100MI/AddPickViaRepNo ReportUsedMtrl

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualWarehouseLocation/ID

For Work Order: For Work Order:

MMOMAT.QMWHLO; MHS850MI The field indicates the warehouse

MOS100MI/AddPickViaRepNo

AddMtrl For Service Order:

The field indicates the warehouse.

For Service Order:

SSLINE.WHLO; SOS300MI/AddSOLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualCostPriceAmount

For Service Order: For Service Order:

SSLINE.UCOS; SOS300MI/ChgSOLine The field indicates the actual cost price.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/EstimatedSalesPriceAmount For Work Order: For Work Order:

MMOMAT.QMSAPR; MOS100MI/AddMtrl, The field indicates the estimated sales price.

ChgMatrl

ServiceOrder/ServiceOrderLine/ServiceMaterialGroup/ActualSalesPriceAmount

For Service Order: For Service Order:

SSLINE.SAPR; SOS300MI/ChgSOLine The field indicates the actual sales price.

AddSOI ine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineNumber

For Service Order: For Service Order

SSLINE.JOBN+JBSX+PONR+POSX; SOS300MI/ChgSOLine The field indicates the service labor group.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/LineCode

For Work Order:

MMOOPE.LCDE + PCTP; MOS070MI/UpdOperation The field indicates the labor charge code and costing type ReportStartStop

ReportTravel

For Service Order: The field indicates the item number.

For Service Order:

SSLINE.ITNO; SOS300MI/ChgSOLine

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/Classification/Codes/Code

For Work Order: For Work Order:

MMOOPE.QOREND The field indicates the manual completion flag, operation date and

QOEQDT + QOEQTI, QOIORL time, interface order line, equipment number

QOEQNO; MOS095MI.UpdOperation.REND

MOS057MI.Add.EQDT + EQTI MOS100MI.AddOp,IORL

MOS070MI.UpdOperation.EQNO/

@listID

For Work Order:

The field indicates a fixed value "Manual Completion Flag", "Operational Date", "Interface Order Line", "Equipment Number"

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualCostPriceAmount

For Service Order: For Service Order:

SSLINE.UCOS; SOS300MI/ChgSOLine The field indicates the company / division number.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceLaborGroup/ActualSalesPriceAmount

For Service Order: For Service Order:

SSLINE.SAPR; SOS300MI/ChgSOLine The field indicates the actual sales price amount.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/LineNumber

For Work Order:

ACUMAS.IMMSEQ; COS150MI/Add

UpdByMSEQ For Service Order:

For Service Order: SSLINE.JOBN+JBSX+

PONR+POSX; SOS300MI/ChgSOLine

AddSOLine

The field indicates the key to the operation element line.

The field indicates the key to the operation element line

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Status/ReasonCode

For Work Order:

For Work Order:

The field indicates the reason code.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Note

For Work Order: For Work Order:

ACUMAS.IMREMK; COS150MI/Add The field indicates the remarks

UpdByMSEQ

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Item/ItemID/ID

For Work Order: For Work Order: ACUMAS.IMAMTY; COS150MI/Add The field indicates the miscellaneous cost type

UpdByMSEQ

For Service Order:

SSLINE.ITNO; SOS300MI/ChgSOLine

AddSOLine

For Service Order:

The field indicates the item number.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/Classification/Codes/Code

For Work Order: For Work Order:

ACUMAS.IMTAIL, IMMAUP, IMAIST; COS150MI.Add. TAIL, MAUP,

IORL. AIST

COS150MI.UpdByMSEQ.TAIL, MAUP, UPGL, AIST

The field indicates the registration number.

The field indicates if the sales price is manually updated.

The field indicates the interface order line. The field indicates the update general ledger. The field indicates the transaction status.

@listID

For Work Order:

The field indicates the following ListID:

"Registration Number" "Manual Update" "Interface Order Line" "Update General Ledger" "Transaction Status"

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/PersonReference/IDs/ID

For Work Order:

ACUMAS.IMUSID; COS150MI/Add The field indicates the user/employee number

UpdByMSEQ

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedCostPriceAmount

For Work Order: For Work Order:

ACUMAS.IMAWCO; COS150MI/Add The field indicates the estimated/ actual cost price amount depending

UpdByMSEQ of status of the line

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/EstimatedSalesPriceAmount

For Work Order: For Work Order:

ACUMAS.IMASP1; COS150MI/Add The field indicates the estimated/actual sales price amount for the

UpdByMSEQ misc cost depending on status of the line

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualCostPriceAmount

For Service Order: For Service Order:

SSLINE.UCOS; SOS300MI/ChgSOLine The field indicates the actual cost price amount.

AddSOI ine

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualSalesPriceAmount

For Service Order: For Service Order:

SSLINE.SAPR; SOS300MI/ChgSOLine The field indicates the actual sales price amount.

AddSOLine

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualSalesPriceBaseAmount

For Service Order: For Service Order:

SSLINE.SACD; SOS300MI/ChgSOLine The field indicates the sales price.

ServiceOrder/ServiceOrderLine/ServiceOtherGroup/ActualQuantity

For Work Order:

ACUMAS.IMTRQT; COS150MI/Add The field indicates the estimated quantity

UpdByMSEQ

May 26, 2023

For Work Order:

For Service Order: SSLINE.ORQT; SOS300MI/ChgSOLine For Service Order:

The field indicates the actual quantity.

AddSOLine @unitCode

For Work Order:

For Work Order: ACUMAS.IMUNIT; COS150MI/Add The field indicates the unit of measure.

UpdByMSEQ

ServiceOrder/ServiceOrderLine/PriorityCode

For Service Order: SSLINE.OPRI; SOS300MI/ChgSOLine

<u>AddSOLine</u>

For Service Order:

The field indicates the priority.

Service Order/Service Order Line/Actual Solution Code

For Service Order:

SSLINE.MECO; SOS300MI/ChgSOAssignm

For Service Order:

The field indicates the action performed for service order assignments

or its service order lines.

ShipToPartyMaster

ShipToPartyMaster	
ShipToPartyMaster/PartyIDs/ID 1) OCUSMA.OKCUNO CRS610MI/Add, CRS610MI/ChgBasicData 2) OCUSAD.OPCUNO+OPADID CRS610MI/AddAddress CRS610MI/ChgAddress.; /	1) The field indicates the unique identification of the customer. Record will be created in M3 'Customer. Open' (CRS610), OCUSMA table. 2) The field indicates the customer ID and delivery address. It is a concatenation of Customer number (CUNO) <10> + Address number (ADID) <6>. If CUNO does not consume the maximum length, the rest is filled up with spaces. ADID is trimmed if it is greater than 6 characters. Record will be created in M3 'Customer.Connect Addresses' (OIS002), OCUSAD table.
@accountingEntity	The field indicates the company and division, displayed as CONO DIVI.
ShipToPartyMaster/Name OCUSMA.OKCUNM CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the customer name.
ShipToPartyMaster/Location/Coordinate/Latitude/DegreeMeasure OCUSAD.OPGEOY CRS610MI/AddAddress, CRS610MI/ChgAddress .; /	The field indicates the Latitude of the location.
ShipToPartyMaster/Location/Coordinate/Longitude/DegreeMeasure OCUSAD.OPGEOX CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the Longitude of the location.
ShipToPartyMaster/Location/Address/AttentionOfName OCUSMA.OKYREF CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress .; /	The field indicates the customer's contact person.
ShipToPartyMaster/Location/Address/AddressLine OCUSMA.OKCUA1 OCUSMA.OKCUA2 OCUSMA.OKCUA3 OCUSMA.OKCUA4 CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the address line.
@sequence	The field indicates the address line sequence.
ShipToPartyMaster/Location/Address/CityName OCUSMA.OKTOWN CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the city name.
ShipToPartyMaster/Location/Address/CountrySubDivisionCode OCUSMA.OKECAR CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates an area, province or state within a country.
ShipToPartyMaster/Location/Address/CountryCode OCUSMA.OKCSCD CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the country code.
ShipToPartyMaster/Location/Address/PostalCode OCUSMA.OKPONO CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the postal code
ShipToPartyMaster/Location/Address/Preference/Indicator	The field indicates the address details with PreferenceIndicator set to "true" or the first instance will be saved.
ShipToPartyMaster/Location/Classification/Codes/Code 1) OCUSAD.OPEALO	

<u>ShipToPartyMaster</u>	
2) OCUSAD.OPVRNO CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	EAN location code The field indicates the EAN (European Article Numbering) code for the company. If attribute listID is "EAN", populate EAN location code (EALO).
@lia4D	 VAT reg no The field indicates the VAT Registration number. If attribute listID is "VAT registrationnumber", populate VAT reg no (VRNO).
@listID	 If attribute listID is "EAN", populate EAN location code (EALO). If attribute listID is "VAT registrationnumber", populate VAT reg no (VRNO).
ShipToPartyMaster/Location/Status/EffectiveDateTime OCUSAD.OPFVDT CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	The field indicates the date and time the document becomes effective
ShipToPartyMaster/Communication/ChannelCode	The field indicates the channel code Phone, Fax or EMail.
ShipToPartyMaster/Communication/UseCode	The field indicates the use code Office, Fax, Mobile.
ShipToPartyMaster/Communication/DialNumber OCUSMA.OKPHNO CRS610MI/Add, CRS610MI/ChgBasicData,	The field indicates the phone and fax number. If ChannelCode is 'Phone' and UseCode is 'Office', populate Phone
CRS610MI/AddAddress, CRS610MI/ChgAddress OCUSMA.OKPHN2	Number (PHNO/PHN2). If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
CRS610MI/Add, CRS610MI/ChgBasicData,	
OCUSMA.OKTFNO CRS610MI/Add, CRS610MI/ChgBasicData, CRS610MI/AddAddress, CRS610MI/ChgAddress.; /	
ShipToPartyMaster/Communication/URI CEMAIL.CBEMAL CRS610MI/Add, CRS610MI/ChqBasicData.; /	The field indicates the e-mail address.
ShipToPartyMaster/Communication/Preference/Indicator	Set to 'true'.
ShipToPartyMaster/PaymentTermID OCUSMA .OKTEPY; CRS610MI/ChgOrderInfo	The field indicates the payment term.
ShipToPartyMaster/UserArea	The field indicates the BODID from the sending application. Set attribute name to 'ProcessBODID'.
ShipToPartyMaster/Status/Code OCUSMA.OKSTAT CRS610MI/Add,	The field indicates the customer status.
CRS610MI/ChgBasicData.; /	Set to 10 if status is Pending. Set to 20 if status is Open. Set to 90 if status is Closed.
ShipToPartyMaster/Classification/Codes/Code 1) OCUSMA.OKCUTP CRS610MI/Add, CRS610MI/ChgBasicData	Customer Types The field indicates the type of customer. If attribute listID is "Customer Types", populate Customer type (CUTP).
2) OCUSMA.OKTEDL CRS610MI/AddAddress, CRS610MI/ChgAddress, CRS610MI/ChgOrderInfo	Incoterms The field indicates delivery terms, which indicate when the responsibility for the transport is transferred from supplier to customer.
3) OCUSMA.OKSDST CRS610MI/ChgOrderInfo.; /	If attribute listID is "Incoterms", populate Delivery terms (TEDL). 3) District The field indicates the district the customer or payer belongs to. If attribute listID is "District", populate District (SDST).
@listID	1) If attribute listID is "Customer Types", populate Customer type (CUTP). 2) If attribute listID is "Incoterms", populate Delivery terms (TEDL). 3) If attribute listID is "District", populate District (SDST).

ShipToPartyMaster

ShipToPartyMaster/CustomerParty/PartyIDs/ID

The field indicates the unique identification of the customer.

Shipment

Shipment/ShipmentHeader/DocumentID/ID

For ProcessShipment: 1) MHIHED.G0RIDI; MHS850MI/AddWhsHead

2) MMIHED.I0PMSN; MMS850MI/AddAdjust

3) ODHEAD.UADLIX; OIS155MI/UpdateQty, Approve

4) MHILIN.G2RORN; MHS850MI/AddDO.; /

For ProcessShipmentNumber: DCONSI.DACONN; DRS100MI/LstByDelivery, CloseShipment, GetShipment MHDISH.OQCONN; MWS410MI/ConnectShipment.; /

@accountingEntity

For ProcessShipment: CMNDIV.CCCONO CMNDIV.CCDIVI.; /

Shipment/ShipmentHeader/AlternateDocumentID/ID

For ProcessShipment: 1) MHILIN.G2DLIX MHILIN.G2PLSX; MHS850MI/AddWhsLine

2) ODHEAD.UADLIX; OIS155MI/Approve OIS155MI/UpdateQtv

MHDIGV.HDDLIX; MWS418MI/Approve MWS418MI/UpdGovAppAct MWS418MI/Reject MHDIGL.HLDLIX; MWS419MI/AddGovAppLog

3) MHDIGV.HDGVNO; MWS418MI/Approve

.; /

For SyncShipment:

For ProcessShipment:

1) Delivery number

The field indicates the delivery number.

If translated partner from logicalID is "OrderStockTransactions" in CRS881/882, MHS850MI transactions are used with Qualifier 51CR. AlternateDocumentID/ID is not required. If no translation exists, MHS850MI transactions are used wherein Qualifier input is based on the translation of DocumentReference@type.

2) External message number

The field indicates the sender's message number.

If translated partner from logicalID is "Internal Stock Transactions" in CRS881/882, the value is used as input for External Message Number (PMSN) in MMS850MI AddAdjust.

3.) Delivery number

The field indicates the delivery number. Call OIS155MI UpdateQty and Approve if Customer order number (ORNO) exist in OIS155MI LstDeliveries.

If partner from LogicalID is pod or translated to ProofOfDelivery in CRS881/882, only OIS155MI is called and calls to MHS850MI are skipped.

4) Reference order number

The field indicates the reference order number.

MHS850MI.AddDO is called instead of MHS850MI.AddWhsHead, AddWhsPack and AddWhsLine if these conditions are met:

- agreement control property m3beReference is set to true
- partner from logical ID is translated to 'OrderStockTransactions'

MHS850MI.AddDO RORN is mapped according to this hierarchy:

- ShipmentHeader/DocumentReference/DocumentID/ID with attribute type='MaintenanceOrder' with non-blank value
- ShipmentHeader/UserArea/Property/NameValue with attribute name='eam.AdviceNumber'
- ShipmentHeader/DocumentID/ID (only retrieve value before the '-')

For ProcessShipmentNumber:

The field indicates the shipment number.

If actionCode="Add", DocumentID/ID is the integrating application's shipment number. M3 generates its own shipment number and displays it in the AcknowledgeShipment/DocumentID/ID. The integrating application's shipment number is displayed in the AcknowledgeShipment/AlternateDocumentID/ID. The application must store the M3 Shipment number and send it as the DocumentID/ID for actionCode="Change".

If actionCode is Change and Status/Code is Canceled, DRS100MI.CloseShipment is called.

For ProcessShipment:

The field indicates the company and division, displayed as CONO DIVI.

For ProcessShipment:

- 1) The field indicates the delivery number and picking list suffix separated by $^{\prime\prime}$.
- 2) The field indicates the delivery number.
- 3) The field indicates the number assigned by authority. @schemeName='lcl.Government'

For SyncShipment:

The field contains the M3 delivery number and picking list suffix separated by a '/'.

The first part will populate DLIX and the second part will populate PLSX.

MHILIN.G2DLIX

MHILIN.G2PLSX.; MHS850MI/AddWhsLine

@schemeName

For ProcessShipment:

If @schemeName='lcl.Government', populate MWS418MI/Approve

Shipment/ShipmentHeader/DocumentReference @type

For ProcessShipment: MHIHED.GOQLFR MHIPAC.G1QLFR MHILIN.G2QLFR

MHILIN.G2TTYP.; MHS850MI/AddWhsHead

AddWhsPack AddWhsLine

For SyncShipment: MHIHED.G0QLFR MHIPAC.G1QLFR

MHILIN.G2QLFR.; MHS850MI/AddWhsHead

AddWhsPack AddWhsLine For ProcessShipment:

The field indicates the qualifier and the transaction type. If 'ProductionOrder', set qualifier and transaction type to 11. If 'SalesOrder', set qualifier and transaction type to 31. If 'SupplierRMA', set qualifier and transaction type to 41. If 'Transfer', set qualifier and transaction type to 51.

If 'Transfer' and with translation "OrderStockTransactions", set

qualifier to 51CR.

If 'MaintenanceOrder', set qualifier and transaction type to 61. If 'MaintenanceOrder' and with translation "OrderStockTransactions", set qualifier to 51CR.

For SyncShipment:

The field indicates the qualifier and the transaction type. If 'ProductionOrder', set qualifier and transaction type to 11. If 'SalesOrder', set qualifier and transaction type to 31. If 'SupplierRMA', set qualifier and transaction type to 41. If 'Transfer', set qualifier and transaction type to 51.

If 'MaintenanceOrder', set qualifier and transaction type to 61.

If QLFR = 11, call MWS422MI.LstPickDetail to retrieve RIDO and use it as input to MHS850MI.AddWhsLine RIDO.

If QLFR = 61, call MMS005MI.GetWarehouse to retrieve FACI and use it as input to MHS850MI.AddWhsLine.

Otherwise, throw MeCError 'DocumentReference attribute type <iQLFR> is not supported'.

For ProcessShipmentNumber:

Set to 'Shipment'.

The ShipmentHeader/DocumentReference@type='Shipment' together with BOD Type 'Shipment' are used as detection for this inbound ProcessShipmentNumber BOD.

Shipment/ShipmentHeader/DocumentReference/DocumentID/ID

For ProcessShipment: 1) MHILIN.G2PROJ; MHS850MI/ChgWhsLineX

2) MHILIN.G2RORN; MHS850MI/AddDO.; /

For ProcessShipmentNumber:

MHDISH.OQDLIX; MWS410MI/ConnectShipment, DisconnShipment

For ProcessShipment:

1) Project number

The field indicates the Project number if Document Reference@type='ProjectMaster'.

2) Reference order number

The field indicates the reference order number.

For ProcessShipmentNumber:

The field indicates the delivery number.

Shipment/ShipmentHeader/Status/Code

For SyncShipment:

MHILÍN.G2ISMD; MHS850MI/AddWhsLine

For ProcessShipment:

The field is set to 'Shipped' or 'PartiallyShipped'.

Otherwise, the process is aborted.

Status/Code validation is skipped if ApplicationArea/Sender/

ComponentID = Local.ly.

For SyncShipment:

The field is set to Shipped, PartiallyShipped or Staged. Otherwise, the process is aborted.

If value of this element is Staged and ShipmentDeliveryHeader/ UserArea/Property/NameValue@name='wm.OrderStatus' is Pack Complete, set MHS850MI.AddWhsLine ISMD (Issue/move mode) to 1 (Move toPack).

If ShipmentHeader/Status/Code is Staged and ShipmentDeliveryHeader/UserArea/Property/
NameValue@name='wm.OrderStatus' is Staged, call
MWS423MI.LstPackDel with DLIX as input. If MWS423MI.LstPackDel returns NOK, call MHS850MI.AddWhsHead, AddWhsPack and
AddWhsLine. Otherwise, call MHS850MI.AddPickViaPack. Set
MHS850MI.AddWhsLine or MHS850MI.AddPickViaPack ISMD (Issue/move mode) to 2 (Move to Dock).

For ProcessShipmentNumber:

If actionCode is Change and Status/Code is Canceled, the deliveries retrieved from DRS100MI.LstByDelivery are disconnecetd from the shipmnet by calling MWS410MI.DisconnShipment then the shipment is closed by calling DRS100MI.CloseShipment.

Shipment/ShipmentHeader/Validation/Status/Code

For ProcessShipment:

MHDIGV.HDGVFS; MWS418MI/UpdGovAppAct

Approve Reject For ProcessShipment:

The field indicates the validation or feedback status.

If Validation/Status/Code = Requested and UserArea/Property/
NameValue@lcl.OutputFlag = 'Yes', call MWS418MI.UpdGovAppAct.
If Validation/Status/Code = Requested and UserArea/Property/
NameValue@lcl.OutputFlag = 'No', call MWS418MI.Approve.
If Validation/Status/Code = Success, call MWS418MI.Approve.
If Validation/Status/Code = Errors, call MWS418MI.Reject.

Shipment/ShipmentHeader/Validation/Message/Description

For ProcessShipment: MHDIGV.HDGVMG; MWS418MI/Reject MHDIGL.HLGVMG;

MWS419MI/AddGovAppLog.; /

For ProcessShipment:

The field indicates the validation message description.

First instance of the Description element is used for the Reject transaction. The succeeding Description elements are used for the AddGovAppLog transaction.

Call MWS419MI.AddGovAppLog only if Validation/StatusCode = Errors.

Set to '-' if Validation/Status/Code = Success.

Shipment/ShipmentHeader/Validation/Message/ReasonCode

For ProcessShipment: MHDIGV.HDGVRC; MWS418MI/Reject MHDIGL.HLGVRC;

MWS419MI/AddGovAppLog.; /

For ProcessShipment:

The field indicates the validation reason code.

First instance of the ReasonCode element is used for the Reject transaction. The succeeding ReasonCode elements are used for the AddGovAppLog transaction.

Call MWS419MI.AddGovAppLog only if Validation/StatusCode = Errors.

Set to '-' if Validation/Status/Code = Success

Shipment/ShipmentHeader/WarehouseLocation/ID

For ProcessShipment: MHIHED.G0WHLO MHIPAC.G1WHLO MHILIN.G2WHLO;

MHS850MI/AddWhsHead, AddWhsPack, AddWhsLine

MMIHED.I0WHLO; MMS850MI/AddAdjust

ODHEAD.UAWHLO;

OIS155MI/UpdateQty, Approve

MPCLAH.CHWHLO; PPS390MI/AddClaimHead

MHILIN.G2WHLO; MHS850MI/AddDO.; /

For SyncShipment: MHIHED.G0WHLO MHIHED.G0CUNO MHIPAC.G1WHLO MHIPAC.G1CUNO MHILIN.G2WHLO

MHILIN.G2CUNO.; MHS850MI/AddWhsHead

AddWhsPack AddWhsLine

For ProcessShipmentNumber:

DCONSI.DAWHLO; DRS100MI/CreateShipment

Shipment/ShipmentHeader/CarrierRouteReference/DocumentID/ID

For ProcessShipmentNumber:

DCONSI.DAROUT; DRS100MI/CreateShipment

For ProcessShipment:

The field indicates the warehouse.

For SyncShipment:

The field indicates the warehouse.

If ShipmentHeader/DocumentReference@type='SupplierRMA', use value from ShipmentHeader/WarehouseLocation/ID as input to CUNO.

CONO.

For ProcessShipmentNumber: The field indicates the warehouse.

Use the value from this element as the first 3 characters for ROUT if ShipmentHeader/CarrierRouteReference/DocumentID/ID does not

exist

For ProcessShipmentNumber: The field indicates the route.

If ShipmentHeader/CarrierRouteReference/DocumentID/ID element is blank, set Route (ROUT) by concatenating input from

ShipmentHeader/WarehouseLocation/ID and the translated value in CRS881/882 of ShipmentHeader/TransportationMethodCode. Set Route departure (RODN) to 1. Shipment/ShipmentHeader/ActualShipDateTime For ProcessShipment: For ProcessShipment: MHIHED.G0SHD4 The field indicates the actual ship date and time. MHIHED.G0SHTM.; MHS850MI/AddWhsHead For SyncShipment: For SyncShipment: The field indicates the date and time of shipment. Note that time is MHIHED.GOSHD4 sent in UTC MHIHED.G0SHTM.; MHS850MI/AddWhsHead timezone. For ProcessShipmentNumber: For ProcessShipmentNumber: DCONSI.DADFDT The field indicates the forwarder's actual departure date and time. DCONSI.DADFHM.; DRS100MI/CreateShipment, Update Shipment/ShipmentHeader/ScheduledDeliveryDateTime For ProcessShipmentNumber: For ProcessShipmentNumber: DCONSI.DAARDT The field indicates the arrival date and time for the shipment. DCONSI.DAARHM.; DRS100MI/Update Shipment/ShipmentHeader/ActualDeliveryDateTime For ProcessShipment: For ProcessShipment: ODHEAD.UAAPDT; OIS155MI/Approve The field indicates the date when the consignee approved the contents of a delivery. Shipment/ShipmentHeader/GrossWeightMeasure MHIHED.GOGRWE For ProcessShipment: MHIPAC.G1GRWE.; MHS850MI/AddWhsHead The field indicates the gross weight. AddWhsPack For SyncShipment: The field indicates the Gross Weight. Shipment/ShipmentHeader/TotalVolumeMeasure MHIHED.G0VOL3; MHS850MI/AddWhsHead The field indicates the volume. Shipment/ShipmentHeader/TransportationMethodCode For ProcessShipment: For ProcessShipment: MHIHED.G0MODL; MHS850MI/AddWhsHead The field indicates how the delivery is made. For ProcessShipmentNumber: For ProcessShipmentNumber: DCONSI.DAMMDL; DRS100MI/CreateShipment The field indicates the delivery method. Use the translation value from CRS881/882 as the 4th-6th character input for ROUT if ShipmentHeader/CarrierRouteReference/ DocumentID/ID does not exist. If DRS100MI.GetShipment MMDL output is different from the ShipmentHeader/TransportationMethodCode input (use the translated value if it exists), MWS410MI. DisconnShipment is called followed by DRS100MI.CreateShipment then MWS410MI.ConnectShipment if ShipmentHeader/ DocumentReference/DocumentID/ID exists. Otherwise, only DRS100MI.CreateShipment is called. Shipment/ShipmentHeader/CarrierParty/PartyIDs/ID For ProcessShipment: For ProcessShipment: MHIHED.G0SUNO The field indicates the supplier. MHIPAC.G1SUNO MHILN.G2SUNO.; MHS850MI/AddWhsHead For SyncShipment: AddWhsPack The field indicates the forwarding agent. AddWhsLine For ProcessShipmentNumber: For SyncShipment: The field indicates which fowarding agent should be used for MHIHED.G0SUNO transport. MHIPAC.G1SUNO MHILN.G2SUNO.; MHS850MI/AddWhsHead AddWhsPack AddWhsLine For ProcessShipmentNumber: DCONSI.DAFWNO; DRS100MI/CreateShipment, Update Shipment/ShipmentHeader/ShipToParty/PartyIDs/ID For ProcessShipment: The field indicates the customer. MHIHED.G0CUNO MHIPAC.G1CUNO MHILN.G2CUNO: MHS850MI/AddWhsHead, AddWHsPack, AddWhsLine MPCLAH.CHSUNO;

Infor May 26, 2023 183

PPS390MI/AddClaimHead.; MHS850MI/AddWhsHead

AddWhsPack

For SyncShipment: MHIHED.GOCUNO MHIPAC.G1CUNO

MHILN.G2CUNO.; MHS850MI/AddWhsHead

AddWhsPack AddWhsLine

Shipment/ShipmentHeader/ShipToParty/Location/ID

For SyncShipment: MHIHED.GOCUNO MHIPAC.G1CUNO

MHILN.G2CUNO.; MHS850MI/AddWhsHead

AddWhsPack AddWhsLine

The field indicates the receiving warehouse for DocumentReference

type = 'Transfer'.

For SyncShipment:

Shipment/ShipmentHeader/ScheduledShipDateTime

For ProcessShipmentNumber:

DCONSI.DADSDT

DCONSI.DADSHM.; DRS100MI/CreateShipment,

Update

For ProcessShipmentNumber:

The field indicates the planned departure date and time.

Shipment/ShipmentHeader/PlannedDeliveryDateTime

For ProcessShipment:

MHIHED.G0DLDT

MHIHED.G0DLTM.; MHS850MI /AddWhsHead

For ProcessShipment:

The field indicates the planned delivery date and time of delivery.

Shipment/ShipmentHeader/TransportationTerm/IncotermsCode

For ProcessShipment:

MHIHED.G0TEDL; MHS850MI/AddWhsHead

For ProcessShipment:

responsibility for a delivery is transferred from the supplier to the

Shipment/ShipmentHeader/UserArea

For ProcessShipment:

1.) MHIHED.GOCUNO;

MHS850MI/AddWhsHead

MHIPAC.G1CUNO;

MHS850MI/AddWhsPack

MHILN.G2CUNO:

MHS850MI/AddWhsLine

2.)MHILN.G2ELNO;

MMS850MI/AddAdjust

3) MHDIGV.HDGVII;

MWS418MI/Approve MWS418MI/UpdGovAppAct

4) MHDIGV.HDGVDS;

MWS418MI/Approve

MWS418MI/UpdGovAppAct

MWS418MI/Reject

5) MHDIGV.HDGVDT;

MWS418MI/Approve

MWS418MI/UpdGovAppAct

MWS418MI/Reject

6) MHDIGV.HDGVTM;

MWS418MI/Approve

MWS418MI/UpdGovAppAct

MWS418MI/Reject

7) MHDIGV.HDGVST;

MWS418MI/Approve

8) MHILIN.G2RORN;

MHS850MI/AddDO.: /

For SyncShipment:

1) MHILIN.G2ISMD:

MHS850MI/AddWhsLine

2) MHDISH.OQSHLV: MWS410MI/GetHead.; /

The field indicates delivery terms, which define when the

For ProcessShipment:

The field indicates the ff.:

- 1) Destination warehouse
- @name='eam.ToWarehouseLocation'
- 2) Flement number
- @name='eam.ProjectBudget'
- 3) Unique number assigned by LPS or 3rd party
- @name='lcl.SequenceNumber
- 4) Local.ly status
- @name='lcl.Status'
- 5) Status update date
- @name='lcl.StatusDate'
- 6) Status update time
- @name='lcl.StatusDate'
- 8) 2) Reference order number

@name='eam.AdviceNumber'

For SyncShipment:

1) Issue/move mode

If ShipmentHeader/Status/Code is Staged and ShipmentHeader/ UserArea/Property/NameValue@name='wm.OrderStatus' is Pack Complete, set MHS850MI.AddWhsLine ISMD (Issue/move mode) to 1.

If ShipmentHeader/Status/Code is Staged and ShipmentDeliveryHeader/UserArea/Property/

NameValue@name='wm.OrderStatus' is Staged, call

MWS423MI.LstPackDel with DLIX as input. If MWS423MI.LstPackDel returns NOK, call MHS850MI.AddWhsHead, AddWhsPack and AddWhsLine. Otherwise, call MHS850MI.AddPickViaPack. Set MHS850MI.AddWhsLine or MHS850MI.AddPickViaPack ISMD to 2.

2) Packing reporting

Retrieve SHLV from ShipmentHeader/UserArea/Property/NameValue with @name='wm.HostHeader1'.

If 'Not used', set SHLV to 0.

If 'Manual simple', set SHLV to 1.

If 'Manual advanced', set SHLV to 2.

If 'Auto when moved to packing location', set SHLV to 3.

If 'Auto when picking list is printed', set SHLV to 4.

	Call MWS410MI.GetHead if SHLV is empty or not any of the values mentioned above.
Shipment/ShipmentHeader/CustomerParty/ReceivingContact/ID	
For ProcessShipment: ODHEAD.UAAPBY; OIS155MI/Approve	For ProcessShipment: The field indicates the consignee responsible for approving the contents of the delivery.
Shipment/ShipmentHeader/CustomerParty/ReceivingContact/Name	,
For ProcessShipment: ODHEAD.UAAPBY; OIS155MI/Approve	For ProcessShipment: The field indicates the consignee responsible for approving the contents of the delivery.
	If this element exists, use as input to OIS155MI. Approved APBY. Otherwise, use input from ShipmentHeader/CustomerParty/ReceivingContact/ID.
Shipment/ShipmentHeader/ShipmentPurposeCode	
For ProcessShipment: ODHEAD.UARSCD; OIS155MI/Approve	For ProcessShipment: The field indicates the user-defined reason code that is used to describe why the transaction was entered.
Shipment/ShipmentItem/ItemID/ID	
For ProcessShipment: MHILIN.G2ITNO; MHS850MI/AddWhsLine or MHS850MI/AddDO	The field indicates the item number.
MIIDE.I1ITNO; MMS850MI/AddAdjust	
MPCLAL.CLITNO; PPS390MI.AddClaimLine.; /	
For SyncShipment: MHILIN.G2ITNO; MHS850MI/AddWhsLine	
Shipment/ShipmentItem/Description MHILIN.G2ITDS; MHS850MI/AddWhsLine	For ProcessShipment: The field indicates the item description.
	For SyncShipment: The field indicates the description of the Item.
Shipment/ShipmentItem/Note	
For ProcessShipment: MHILIN.G2BREM;	For ProcessShipment: The field indicates the remark.
MHS850MI/AddWhsLine	The hold indicates the femalik.
MMIIDE.I1BREM; MMS850MI/AddAdjust.; /	For SyncShipment: The field indicates an optional remark for the balance identity.
For SyncShipment: MHILIN.G2BREM; MHS850MI/AddWhsLine	
Shipment/ShipmentItem/Classification/Codes/Code	
For ProcessShipment:	For ProcessShipment:
1) MMIINS.I2STAG; MMS850M/AddAdjust	The field indicates the ff.: 1) The field indicates the Physical Inventory status. 2) The field indicates the Project number.
2) MHILIN.G2PROJ; MHS850MI/ChgWhsLineX or MHS850MI/AddDO	 3) The field indicates the Project element. 4) The field indicates the Department. 5) The field indicates the Accounting object 2 or Cost Center. Use this
3) MHILIN.G2ELNO; MHS850MI/ChgWhsLineX or MHS850MI/AddDO	only if Shipment/ShipmentItem/UserArea/Property/ NameValue@name='AccountingObject2' does not exist. 6) The field indicates the payment term.
4) MHILIN.G2DEPT; MHS850MI/ChgWhsLineX or MHS850MI/AddDO	For SyncShipment: 1) The field indicates the pick list line reporting number. Attribute
5) MHILIN.G2ACC2; MHS850MI/ChgWhsLineX or MHS850MI/AddDO	listID is 'Reporting Number'. 2) The field indicates the destination location for the stock transaction.
6) ODHEAD.UATEPY; OIS155MI/UpdateQty, Approve .; /	Attribute listID is 'To Location'. If element does not exist or its value is empty, TWSL value is retrieved from agreement control property m3bePackLocation or m3beDockLocation.
For SyncShipment: 1) MHILIN.G2PLRN; MHS850MI/AddWhsLine 2) MHILIN.G2TWSL; MHS850MI/AddWhsLine.; / @JistID	
wiisub	For ProcessShipment: 1) If 'Status Physical Inventory', populate STAG. 2) If 'Project Number', populate PROJ.

Shipment 3) If 'Project Element', populate ELNO. 4) If 'Departments', populate DEPT.5) If 'Cost Centers', populate ACC2. 6) If 'Payment Term', populate TEPY. For SyncShipment: 1) If listID='Reporting Number', Reporting number (PLRN) field will be populated. 2) If listID='To Location', To Location (TWSL) field will be populated. Shipment/ShipmentItem/ShippedQuantity For ProcessShipment: For ProcessShipment: MHILIN.G2DLQA The field indicates the delivered quantity in alternate unit of measure. MHILIN.G2DLQT; MHS850MI/AddWhsLine or MHS850MI/AddDO For SyncShipment: The field indicates the delivered quantity. MMIINS.I2QLQT; MMS850MI/AddAdjust If value is 0, read the ShipmentItem level regardless of the SHLV ODLINE.UBDLQA; OIS155MI/UpdateQty If this element is set to 0, Flagged as Completed (OEND) is set to 1. MPCLAL.CLRJQA; PPS390MI/AddClaimLine.; / For SyncShipment: MHILÍN.G2DLQT; MHS850MI/AddWhsLine @unitCode For ProcessShipment: The field indicates the unit of measure. MHILIN.G2UNIT; MHS850MI/AddWhsLine MMIINS.I2QLUN; MMS850MI/AddAdjust.; / For SyncShipment: MHILIN.G2UNIT; MHS850MI/AddWhsLine Shipment/ShipmentItem/ShippedBaseUOMQuantity For ProcessShipment: For ProcessShipment: MHILIN.G2DLQT: The field indicates the delivered quantity in basic unit of measure. MHS850MI/AddWhsLine or MHS850MI/AddDO ODLINE.UBDLQT OIS155MI.UpdateQty Shipment/ShipmentItem/PurchaseOrderReference/DocumentID/ID For ProcessShipment: For ProcessShipment: MPCLAH.CHPUNO; PPS390MI/AddClaimHead The field indicates the purchase order number. PPS390MI will only be called if input to this element exists Shipment/ShipmentItem/SalesOrderReference/DocumentID/ID For ProcessShipment: For ProcessShipment: MHILIN.G2RIDN: The field indicates the order number. Element exists if Qualifier is 31. MHS850MI/AddWhsLine For SyncShipment: ODHEAD.UAORNO: The field indicates the reference sales order number. OIS155MI/UpdateQty, Approve.; / Note: Element is used only for qualifier 31. For SyncShipment: MHILIN.G2RIDN; MHS850MI/AddWhsLine Shipment/ShipmentItem/SalesOrderReference/LineNumber For ProcessShipment: For ProcessShipment: MHILIN.G2RIDL: The field indicates the order line. Element exists if Qualifier is 31. MHS850MI/AddWhsLine For SyncShipment: ODLINE.UBPONR: The field indicate the order line number and line suffix. OIS155MI/UpdateQty.; / Note: Element is used only for qualifier 31. For SyncShipment: MHILIN.G2RIDL MHILIN.G2RIDX.; MHS850MI/AddWhsLine

MHS850MI/AddWhsLine or MHS850MI/AddDO.; /
Infor May 26, 2023 18

For ProcessShipment:

For ProcessShipment:

The field indicates the order number.

The field indicates the line suffix. Element exists if Qualifier is 31

Shipment/ShipmentItem/SalesOrderReference/SubLineNumber

Shipment/ShipmentItem/DocumentReference/DocumentID/ID

MHILIN.G2RIDX; MHS850MI/AddWhsLine

For ProcessShipment:

For ProcessShipment:

MHILIN.G2RIDN;

Ompinioni	For SyncShipment:
For SyncShipment: MHILIN.G2RIDN; MHS850MI/AddWhsLine	The field indicates a reference order number.
Shipment/ShipmentItem/DocumentReference/LineNumber For ProcessShipment: MHILIN .G2RIDL; MHS850MI/AddWhsLine For SyncShipment: MHILIN.G2RIDL MHILIN.G2RIDL MHILIN.G2RIDX.; MHS850MI/AddWhsLine	For ProcessShipment: The field indicates the order line. For SyncShipment: The field indicate the order line number and line suffix.
Shipment/ShipmentItem/DocumentReference/SubLineNumber For ProcessShipment: MHILIN.G2RIDX; MHS850MI/AddWhsLine	For ProcessShipment: The field indicates the line suffix.
Shipment/ShipmentItem/PlannedShipQuantity For SyncShipment: MHILIN.G2DLQT; MHS850MI/AddWhsLine	For SyncShipment: The field indicates the Delivered Quantity. Data from this element is used if ShipmentItem/ShippedQuantity is empty.
@unitCode For SyncShipment: MHILIN.G2UNIT; MHS850MI/AddWhsLine	For SyncShipment: The field indicates the unit of measure.
Shipment/ShipmentItem/UserArea For ProcessShipment: 1) MMIIDE.11WHSL; MHS850MI/AddAdjust MHILIN.G2WHSL; MHS850MI/AddWhsLine or MHS850MI/AddDO	For ProcessShipment: The field indicates the ff.: 1) Location. If @name='eam.Bin', populate WHSL. 2) Accounting objects. Name attributes are 'AccountingObject1' to
2) MHILIN.G2ACC1 to G2ACC7; MHS850MI/ChgWhsLineX or MHS850MI/AddDO.; /	'ÁccountingObject7'.
Shipment/ShipmentItem/SerializedLot/Lot/LotIDs/ID For ProcessShipment: MHILIN.G2BANO; MHS850MI/AddWhsLine or MHS850MI/AddDO MMIIDE.I1BANO; MMS850MI/AddAdjust	The field indicates the lot number.
.; / For SyncShipment: MHILIN.G2BANO; MHS850MI/AddWhsLine Shipment/Shipment/tem/LineNumber For ProcessShipment:	For ProcessShipment:
MHILIN.G2PLRN; MHS850MI/AddWhsLine Shipment/ShipmentItem/HoldCodes/Code	The field indicates the reporting number pick line.
For SyncShipment: MHILIN.G2WHSL; MHS850MI/AddWhsLine	For SyncShipment: The field indicates the location. If HoldCodes/Code is not empty and not a valid location in M3, allow the API to fail with error message 'Location &1 does not exist'. Since it is possible to have multiple inputs to HoldCodes/Code, MHS850MI.AddWhsLine WHSL will be checked using MMS010MI.ListLocations with input WHLO. The first location that will match will be used. If none of the entries is a valid Location in M3,
	return error 'Locations do not exist'. If HoldCodes/Code is empty, call MWS422MII.LstPickDetail to retrieve WHSL. If ShipmentHeader/DocumentReference@type='SupplierRMA' and input to Location (WHSL) is blank, retrieve WHSL from MMS100MI.GetLine.
Shipment/ShipmentUnit/TrackingID For ProcessShipment: MHIPAC.G1PARE; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the package reference.
For SyncShipment: MHIPAC.G1PARE; MHS850MI/AddWhsPack	For SyncShipment: The field indicates a reference to the package.
For ProcessShipmentNumber: MPTRNS.ORETRN; MWS423MI/ChangePackage or	For ProcessShipmentNumber: The field indicates the external tracking number. If ShipmentUnit/TrackingID@schemeName is TrackingNumber,
	1

MHDISH.OQETRN; MWS410MI/UpdPlanSts.; /	MWS423MI.ChangePackage is called. If ShipmentUnit/TrackingID@schemeName is ProNumber, MWS410MI.UpdPlanSts is called.		
@schemeName	For ProcessShipmentNumber: The field indicates if the TrackingID is a Pro number or a Tracking number for parcel.		
Shipment/ShipmentUnit/ContainerID	•		
For ProcessShipment:	For ProcessShipment:		
MHIPAC.G1PACN; MHS850MI/AddWhsPack	The field indicates the package number or the container ID.		
MITSOSUMI/Add WITSF ack	If MHS850MI AddWhsPack is used, then the element value will be		
MHILIN.G2PACN;	used as PACN.		
MHS850MI/AddWhsLine or	If MMS850MI AddAdjust is used, then the element value will be used		
MHS850MI/AddDO	as CAMU.		
MMIIDE.I1CAMU; MMS850MI/AddAdjust .; /	For SyncShipment: The field indicates a package number (PACN) or the included in package number (PACC).		
For SynoShipment	If partner from legicalID is way		
For SyncShipment: MHIPAC.G1PACN	If partner from logicalID is wm: - Use as PACN input.		
MHIPAC.G1PACC;	 If ShipmentUnit/ShipmentUnitContainer/ContainerID exists, use 		
MHS850MI /AddWhsPack, ChgWhsPack	ShipmentUnit/ContainerID as MHS850MI ChgWhsPack PACC input		
MHILIN.G2PACN;	whereas ShipmentUnit/ShipmentUnitContainer/ContainerID is the		
MHS850MI/AddWhsPack.; /	PACN input .		
For ProcessShipmentNumber:	If SHLV = 0, ShipmentUnit elements will not be read.		
MPTRNS.ORPANR; MWS423MI/ChangePackage	If SHLV != 0, ShipmentItem elements will only be read if		
	ShipmentUnit elements do not exist. SHLV is the Packing reporting method.		
	SHLV is the Facking reporting method.		
	For ProcessShipmentNumber:		
Shipment/ShipmentUnit/NetWeightMeasure	The field indicates the package number.		
For ProcessShipment:	For ProcessShipment:		
MHIPAC.G1NEWE; MHS850MI/AddWhsPack	The field indicates the net weight.		
Shipment/ShipmentUnit/GrossWeightMeasure MHIPAC.G1GRWE; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the gross weight.		
	For SyncShipment: The field indicates the total weight for all items that have been entered on the order.		
	The basis for this calculation is the gross weight of each item in the item file multiplied by the quantity.		
Shipment/ShipmentUnit/TotalVolumeMeasure	5 D 01: 4		
For ProcessShipment: MHIPAC.G1VOM3; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the volume.		
Shipment/ShipmentUnit/Dimensions/WidthMeasure	The hera maleates the volume.		
MHIPAC.G1PACW; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the packaging width.		
	For SyncShipment:		
	The field indicates the width of the packaging.		
Shipment/ShipmentUnit/Dimensions/LengthMeasure MHIPAC.G1PACL; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the packaging length.		
	For SyncShipment:		
	The field indicates the length of the packaging.		
Shipment/ShipmentUnit/Dimensions/HeightMeasure MHIPAC.G1PACH; MHS850MI/AddWhsPack	For ProcessShipment: The field indicates the packaging height.		
	For SyncShipment: The field indicates the height of the packaging.		
Shipment/ShipmentUnit/ShippingMaterial/ID MHIPAC.G1PACT; MHS850MI/AddWhsPack	The field indicates the packaging ID.		
Shipment/ShipmentUnit/ShipmentUnitContainer/ContainerID	For SynoShipmont		
For SyncShipment: MHIPAC.G1PACN; MHS850MI/AddWhsPack, ChgWhsPack	For SyncShipment: The field indicates a package identifier, one for each package.		
· · · · ·	тне него пноговлее а раскаде поенинет, оне пот еасті раскаде.		
Shipment/ShipmentUnit/ShipmentUnitContainer/ParentContainerID For SyncShipment: MHIPAC.G1PACC; MHS850MI/ChgWhsPack			
Infor May 26, 20	22		

For SyncShipment:

The field indicates the package number where the package (PACN) is

included.

Shipment/ShipmentUnit/ShipmentUnitItem/ItemID/ID

For ProcessShipment: MHILIN.G2ITNO; MHS850MI/AddWhsLine or

MHS850MI/AddDO

MIIDE.I1ITNO;

MMS850MI/AddAdjust.; /

For SyncShipment:

MHILIN.G2ITNO; MHS850MI/AddWhsLine

For ProcessShipment:

The field indicates the item number.

For SyncShipment:

The field indicates the item number connected to the package.

Shipment/ShipmentUnit/ShipmentUnitItem/Description

MHILIN.G2ITDS; MHS850MI/AddWhsLine

For ProcessShipment:

The field indicates the item name.

For SyncShipment:

The field indicates the description of the Item.

Shipment/ShipmentUnit/ShipmentUnitItem/Note

For SyncShipment:

MHILIN.G2BREM; MHS850MI/AddWhsLine

For SyncShipment:

The field indicates an optional remark for the balance identity.

Shipment/ShipmentUnit/ShipmentUnitItem/Classification/Codes/Code

For ProcessShipment: 1.) MMIINS.I2STAG;

MMS850M/AddAdjust

2.) MHILIN.G2PROJ;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO

3.) MHILIN.G2ELNO;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO

4.) MHILIN.G2DEPT;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO

5.)MHILIN.G2ACC2;

MHS850MI/ChgWhsLineX or MHS850MI/AddDO.; /

For SyncShipment:

1) MHILIN.G2PLRN; MHS850MI/AddWhsLine

2) MHILIN.G2TWSL;

MHS850MI/AddWhsLine.; /

@listID

For ProcessShipment:

The field indicates the ff.:

1.) Physical Inventory.

- 2.) The field indicates the Project number.
- 3.) The field indicates the Project element.
- 4.) The field indicates the Department.
- 5.) The field indicates the Accounting object 2 or Cost Center. Use this only if Shipment/ShipmentItem/UserArea/Property/ NameValue@name='AccountingObject2' does not exist.

For SyncShipment:

- 1) The field indicates the picklist line reporting number. Attribute listID is 'Reporting Number'.
- 2) The field indicates the destination location for the stock transaction. Attribute listID is 'To Location'. If element does not exist or value is empty, TWSL value is retrieved from agreement control property

For ProcessShipment:

1) If 'Status Physical Inventory' populate STAG.

m3bePackLocation or m3beDockLocation.

- 2) If 'Project Number' populate PROJ.3) If 'Project Element' populate ELNO.
- 4) If 'Departments' populate DEPT. 5) If 'Cost Centers' populate ACC2.

For SyncShipment:

1) If listID='Reporting Number', Reporting number (PLRN) field will be

populated.

2) If listID='To Location', To Location (TWSL) field will be populated.

Shipment/ShipmentUnit/ShipmentUnitItem/ShippedQuantity

For ProcessShipment: MHILIN.G2DLQA MHILIN.G2DLQT;

MHS850MI/AddWhsLine or MHS850MI/AddDO

MMIINS.I2QLQT; MMS850MI/AddAdjust.; /

For SyncShipment:

MHILIN.G2DLQT; MHS850MI/AddWhsLine

@unitCode

For ProcessShipment: MHILIN.G2UNIT: MHS850MI/AddWhsLine MMIINS.I2QLUN; MMS850MI/AddAdjust.; /

For SyncShipment:

MHILIN.G2UNIT; MHS850MI/AddWhsLine

For ProcessShipment:

The field indicates the delivered quantity in alternate unit of measure.

For SyncShipment:

The field indicates the Delivered Quantity.

If this element is set to 0, Flagged as Completed (OEND) is set to 1.

The field indicates the unit of measure.

Shipment/ShipmentUnit/ShipmentUnitItem/ShippedBaseUOMQuantity

For ProcessShipment:

For ProcessShipment:

MHILIN.G2DLQT; MHS850MI/AddWhsLine or MHS850MI/AddDO The field indicates the delivered quantity in basic unit of measure.

ODLINE.UBDLQT OIS155MI/UpdateQty.; /

Shipment/ShipmentUnit/ShipmentUnitItem/PurchaseOrderReference/LineNumber

For ProcessShipment: For ProcessShipment:

MPCLAL.CLPNLI; PPS390MI/AddClaimLine The field indicates the purchase order line

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/DocumentID/ID

MHILIN.G2RIDN; MHS850MI/AddWhsLine

For ProcessShipment:

The field indicates the order number. Element exists if Qualifier is 31.

For SyncShipment:

For SyncShipment:

The field indicates the reference sales order number.

Note: Element is used only for qualifier 31

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/LineNumber

For ProcessShipment: For ProcessShipment:

MHILIN.G2RIDL The field indicates the order line. Element exists if Qualifier is 31.

; MHS850MI/AddWhsLine

For SyncShipment: The field indicate the order line number and line suffix.

MHILÍN.G2RIDL Note: Element is used only for qualifier 31.

MHILIN.G2RIDX.; MHS850MI/AddWhsLine

Shipment/ShipmentUnit/ShipmentUnitItem/SalesOrderReference/SubLineNumber

For ProcessShipment: For ProcessShipment:

MHILIN.G2RIDX; MHS850MI/AddWhsLine The field indicates the line suffix. Element exists if Qualifier is 31.

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference

@type

For ProcessShipmentNumber: This should be set to Shipment

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/DocumentID/ID

For ProcessShipment: For ProcessShipment

MHILIN.G2RIDN; The field indicates the order number.

MHS850MI/AddWhsLine or MHS850MI/AddDO.; /

For SyncShipment: For SyncShipment: The field indicates a reference order number.

MHILÍN.G2RIDN; MHS850MI/AddWhsLine

For ProcessShipmentNumber: For ProcessShipmentNumber: The field indicates the delivery number.

MPTRNS.ORDLIX;

MWS423MI/ChangePackage If ShipmentUnit/TrackingID@schemeName is TrackingNumber,

MWS423MI.ChangePackage is called.

MHDISH.OQDLIX; If ShipmentUnit/TrackingID@schemeName is ProNumber, MWS410MI.UpdPlanSts is called. MWS410MI/UpdPlanSts.; /

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/LineNumber

For ProcessShipment: For ProcessShipment:

MHILIN.G2RIDL: MHS850MI/AddWhsLine The field indicates the order line.

For SyncShipment: For SyncShipment:

MHILÍN.G2RIDL The field indicate the order line number and line suffix.

MHILIN.G2RIDX.; MHS850MI/AddWhsLine

Shipment/ShipmentUnit/ShipmentUnitItem/DocumentReference/SubLineNumber

For ProcessShipment: For ProcessShipment:

MHILIN.G2RIDX; MHS850MI/AddWhsLine The field indicates the line suffix

Shipment/ShipmentUnit/ShipmentUnitItem/SerializedLot/Lot/LotIDs/ID

For ProcessShipment: The field indicates the lot number.

MHILIN.G2BANO: MHS850MI/AddWhsLine or

MHS850MI/AddDO.; /

For SyncShipment:

MHILIN.G2BANO; MHS850MI/AddWhsLine

Shipment/ShipmentUnit/UserArea

For ProcessShipment: 1) MMIIDE.I1WHSL; MHS850MI/AddAdjust MHILIN.G2WHSL;

MHS850MI/AddWhsLine or MHS850MI/AddDO

2) MHILIN.G2ACC1 to G2ACC7; MHS850MI/ChgWhsLineX or MHS850MI/AddDO.: /

For ProcessShipment: The field indicates the ff.:

1) Location. If @name='eam.Bin', populate WHSL.

2) Accounting objects. Name attributes are 'AccountingObject1' to

'AccountingObject7'.

Shipment/ShipmentUnit/SpecializedLogisticUnit/ShipmentUnitType For SyncShipment: MHIPAC.G1PACT; MHS850MI/AddWhsPack

For SyncShipment: The field indicates the packaging.

SourceSystemGLMovement

SourceSystemGLMovement/IDs/ID @lid

FBUDEF.BDTX15; BUS100MI.AddBudgetHeader,

BUS100MI.UpdBudgetHeader

The field indicates budget name. If the lid is equal to "lid://infor.cpm." the name will be hardcoded to cpm, otherwise it will consist of the first 15 characters from budget description.

SourceSystemGLMovement/Description

FBUDEF.BDTX40; BUS100MI.AddBudgetHeader,

BUS100MI.UpdBudgetHeader

The field indicates the description in the budget header, it will be used for all GLMovementRow records that have no value in

LedgerSetupReference/Description

SourceSystemGLMovement/GLMovementRow/LedgerSetupReference/Description

FBUDEF.BDTX40; BUS100MI.AddBudgetHeader,

BUS100MI.UpdBudgetHeader

The field indicates the description in the budget header. If no value is provided then description from SourceSystemGLMovement/ Description will be used.

SourceSystemGLMovement/GLMovementRow/LedgerSetupReference/BookInstanceID

FBUDEF.BDBUNO

FBUDEF.BDBVER; BUS100MI.AddBudgetHeader,

BUS100MI.AddBudgetLnPer, BUS100MI.UpdBudgetHeader, BUS100MI.UpdBudgetLnPer, BUS100MI.DelBudgetHeader

The field indicates a concatenation of Budget version (BVER) <4> + Budget number (BUNO) <3> without separator, BVER have to be filled up with spaces on the right side and BUNO have to be filled up with zeroes on the left side to consume the maximum length.

SourceSystemGLMovement/GLMovementRow/GLAccount/GLNominalAccount

FBUDET.BCAIT1; BUS100MI.AddBudgetLnPer,

The field indicates the account, accounting dimension 1.

BUS100MI.UpdBudgetLnPer

SourceSystemGLMovement/GLMovementRow/DimensionCodes/DimensionCode

FBUDET.BCAIT2 FBUDET.BCAIT3 FBUDET.BCAIT4

FBUDET.BCAIT5

FBUDET.BCAIT6

FBUDET.BCAIT7; BUS100MI.AddBudgetLnPer,

BUS100MI.UpdBudgetLnPer

@sequence

Set to incrementing from "1" to "6" for accounting dimensions from 2

The field indicates the accounting dimensions 2, 3, 4, 5, 6, and 7.

SourceSystemGLMovement/GLMovementRow/AccountingDate/PeriodID

FBUDET.BCBUPE; BUS100MI.AddBudgetHeader,

BUS100MI.AddBudgetLnPer, BUS100MI.UpdBudgetLnPer

The field indicates the budget period number.

This value will be used to determine budget Start period (for new Budget only, if not found in M3) if value for Start period (BSPR) is not found in UserArea and Template budget (BUNO=999; BVER=9999)

for given CONO and DIVI is missing in M3.

E.g.

<PeriodID>1</PeriodID>

SourceSystemGLMovement/GLMovementRow/AccountingDate/Year

FBUDET.BCBUPE; BUS100MI.AddBudgetHeader,

BUS100MI.AddBudgetLnPer, BUS100MI.UpdBudgetLnPer

The field indicates the budget period year.

This value will be used to determine budget Start period if value for Start period (BSPR) is not found in UserArea and Template budget (BUNO=999; BVER=9999) for given CONO and DIVI is missing in M3.

E.g.

<Year>2019</Year>

SourceSvstemGLMovement/GLMovementRow/NetMovement/FunctionalAmount

FBUDET.BCBCUA; BUS100MI.AddBudgetLnPer,

BUS100MI.UpdBudgetLnPer

The field indicates foreign currency amount - budget.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the

FunctionalAmount and currency code.

@currencyID

FBUDET.BCCUCD; BUS100MI.AddBudgetLnPer,

BUS100MI.UpdBudgetLnPer

The field indicates the currency.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the

FunctionalAmount and currency code.

SourceSystemGLMovement/GLMovementRow/NetMovement/Amount

FBUDET.BCBCUA; BUS100MI.AddBudgetLnPer,

BUS100MI.UpdBudgetLnPer

The field indicates foreign currency amount - budget.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the

FunctionalAmount and currency code.

@currencyID

FBUDET.BCCUCD; BUS100MI.AddBudgetLnPer,

BUS100MI.UpdBudgetLnPer

The field indicates the currency.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the

FunctionalAmount and currency code

SourceSystemGLMovement/GLMovementRow/NetMovement/ReportingCurrencyAmount

FBUDET.BCBCUA; BUS100MI.AddBudgetLnPer,

SourceSystemGLMovement

BUS100MI.UpdBudgetLnPer

@currencyID

FBUDET.BCCUCD; BUS100MI.AddBudgetLnPer, BUS100MI.UpdBudgetLnPer

SourceSystemGLMovement/GLMovementRow/UserArea

- 1) FBUDEF.BDBSPR
- 2) FBUDEF.BDNPAM,
- 3) FBUDEF.BDCRTP,
- 4) FBUDEF.BDUPDB; BUS100MI.AddBudgetHeader,

BUS100MI.UpdBudgetHeader

The field indicates foreign currency amount - budget.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the FunctionalAmount and currency code.

E.a.

<ReportingCurrencyAmount currencyID="SEK">11.11</

ReportingCurrencyAmount>

The field indicates the currency.

If no value in ReportingCurrencyAmount, check if there is a value in

Amount. If yes, use this amount and currency code.

If no value in ReportingCurrencyAmount or Amount, use the

FunctionalAmount and currency code.

The field indicates additional information that is not captured in OAGIS but required by an integration. The information is defined in UserArea/Property/NameValue elements which are determined by different "name" and "type" attributes.

If values are found in UserArea they are used to create or update budget header. If values are not found in UserArea they are going to be retrieved from Template budget (BUNO=999; BVER=9999) for given CONO and DIVI. If no Template budget is found in M3, default values are used for NPAM, CRTP and UPDB, and for BSPR values from Year and Period elements are used.

1) Start Period (BSPR)<6>

Set name="m3BudgetStartPeriod".

Formatted as a concatenation of Year<4> and Period number<2> without separator, Period number has to be zero-padded from the left side to consume maximum length.

E.g. <Property><NameValue name="m3BudgetStartPeriod"

>201908</NameValue> </Property>

2) Number of Periods (NPAM), default value is "12".

Set name="m3BudgetNumberOfPeriods".

E.g. <Property><NameValue name="m3BudgetNumberOfPeriods" >12</NameValue> </Property>

>12</NameValue> </Property>
3) Exchange Rate Type (CRTP), default value is "1".

Set name="m3BudgetExchangeRateType".

Need to exist in M3.

E.g. <Property><NameValue name="m3BudgetExchangeRateType" >1</NameValue> </Property>

4) Update Balance File (UPDB), allowed values are "1" or "0", default value is "1".

Set name="m3BudgetUpdateBalanceFile".

E.g. <Property><NameValue name="m3BudgetUpdateBalanceFile" >1</NameValue> </Property>

Supplierl	nvoice
@type	

For ProcessSupplierInvoice:

FAPIBH.E5IBTP; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the type of invoice batch.

If SupplierInvoice@type is equal to 'Prepaid', invoice batch type will be set to 05- Prepayment Invoice, else, invoice batch type will be set to 20 - Normal Supplier Invoice.

SupplierInvoice/SupplierInvoiceHeader/DocumentID/ID

FAPIBH.E5SINO; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the supplier invoice number.

The supplier invoice number is the name that the supplier uses to identify an invoice.

For LoadSupplierInvoice:

The field indicates the Supplier invoice number

SupplierInvoice/SupplierInvoiceHeader/AlternateDocumentID/ID

FAPIBH.E5VONO

FAPIBH.E5CORI.; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the voucher number or the correlation ID. If AlternateDocumentID/ID@schemename = 'VoucherNumber' then the field refers to voucher number.

If AlternateDocumentID/ID@schemename = 'CorrelationID', then the field refers to correlation ID.

If AlternateDocumentID/ID@schemename = 'AlternateDocumentID', then the field refers to an alternate supplier invoice number in the source system. The original supplier invoice number in Nexus is provided when adjustments for the original invoice are created in Nexus and sent as a separate supplier invoice with new invoice number and Accounting lines (lines of type 8 in M3), with a Reason Code for each adjustment as an Accounting Object on line level.

For LoadSupplierInvoice:

The field indicates the Voucher number or the Correlation ID. If AlternateDocumentID/ID@schemename = 'VoucherNumber' then the field refers to voucher number.

If AlternateDocumentID/ID@schemename = 'CorrelationID', then the field refers to correlation ID.

If AlternateDocumentID/ID@schemename = 'AlternateDocumentID', then the field refers to an alternate supplier invoice number in the source system. The value is not retained in M3.

@schemeName

For ProcessSupplierInvoice:

Set to 'VoucherNumber' or 'CorrelationID' or 'AlternateDocumentID'.

For LoadSupplierInvoice:

Set to 'VoucherNumber' or 'CorrelationID' or 'AlternateDocumentID'.

SupplierInvoice/SupplierInvoiceHeader/DocumentDateTime

FAPIBH.E5IVDT; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the date from which the invoice is valid.

For LoadSupplierInvoice:

The field indicates the Invoice date.

SupplierInvoice/SupplierInvoiceHeader/DocumentReference @type

For ProcessSupplierInvoice:

Set to 'Shipment' or 'AdvanceShipNotice' to set the value for the element DocumentReference/DocumentID/ID as Delivery Note.

For LoadSupplierInvoice:

The field is set to 'Shipment' or 'AdvanceShipNotice'.

SupplierInvoice/SupplierInvoiceHeader/DocumentReference/DocumentID/ID

FAPIBL.E6SUDO; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the supplier's delivery note number. The field is only applicable if DocumentReference@type is 'Shipment' or 'AdvanceShipNotice'.

For LoadSupplierInvoice:

The field indicates the Delivery note number.

SupplierInvoice/SupplierInvoiceHeader/SubunitRoundingAmount

FAPIBL.E6NLAM; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the net amount for an invoice line. The field is used for invoice line type = 4 - Rounding Off.

For LoadSupplierInvoice:

The field indicates the net amount of supplier invoice line. The field is only applicable for Line type 4- Rounding off.

SupplierInvoice/SupplierInvoiceHeader/TotalAmount

FAPIBH.E5CUAM; APS450MI/AddHead

@currencyID

FAPIBH.E5CUCD; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the invoice total.

For LoadSupplierInvoice:

The field indicates the invoice total amount in foreign currency.

For ProcessSupplierInvoice:

The field indicates the abbreviation for the currency. The abbreviation must follow ISO standards.

For LoadSupplierInvoice:

The field indicates the currency code.

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/PartyIDs/ID

For ProcessSupplierInvoice: FAPIBH.E5SUNO; APS450MI

/AddHead

For LoadSupplierInvoice: CIDALL.S2XALT CRTVSUMI/GetSupplier

FAPIBH.E5SUNO APS450MI/AddHead.; / For ProcessSupplierInvoice:

The field indicates the Supplier number.

Retrieval of Supplier Number depends on attribute schemeName:

- 1.) If 'SupplierNumber' directly populate the field SUNO
- 2.) If 'TaxIdentificationNumber' use the value as input for XALT in API CRTVSUMI to retrieve SUNO.
- 3.) If 'CountryldentificationNumber' use the value as input for XALT in API CRTVSUMI to retrieve SUNO.
- 4.) If blank use the value as input for XALT in API CRTVSUMI to retrieve SUNO.
- 5.) If 'TaxID' blank' use the value as input for XALT in API CRTVSUMI to retrieve SUNO.

If the look up function fails to match an existing supplier record in file CIDALL, then the Supplier field (SUNO) in APS450 is populated with the first 10 positions of the first ID found in the BOD according to the list above.

For LoadSupplierInvoice:

The field indicates the Supplier number.

The data in this element is used as an alternative Supplier ID and looked up with the API CRTVSUMI (Retrieve supplier number) in the file CIDALL (set up in CRS627). The exception is if this element comes with @schemeName 'SupplierNumber'. Then the ID is expected to be the Supplier number used in M3 and entered in the Supplier number field (SUNO) in APS450.

The data in the element SupplierParty/PartyIDs/TaxID can also be used as an alternative SupplierID.

If several Supplier ID's exist in the BOD they will be looked up in the following order and if found, entered in M3.

- SupplierID with @schemeName 'SupplierNumber
 TaxID with @schemeName 'TaxIdentificationNumber'
- 3. TaxID with @schemeName 'CountryIdentificationNumber'
- 4. SupplierID without @schemeName
- 5. TaxID without @schemeName

If the look up function fails to match an existing supplier record in file CIDALL, then the Supplier field (SUNO) in APS450 is populated with the first 10 positions of the first ID found in the BOD according to the list above.

For ProcessSupplierInvoice:

Set to the following:

- 1.) 'SupplierNumber'
- 2.) 'TaxIdentificationNumber'
- 3.) 'CountryIdentificationNumber'
- 4.) blank
- 5.) 'TaxID blank'

For LoadSupplierInvoice:

The field indicates the schemeName which is used to choose which will be used in MI as Supplier if several Supplier ID's exist in the BOD. The order is as follows:

- 1. SupplierID with @schemeName 'SupplierNumber
- 2. TaxID with @schemeName 'TaxIdentificationNumber'
- 3. TaxID with @schemeName 'CountryIdentificationNumber'
- 4. SupplierID without @schemeName
- 5. TaxID without @schemeName

@schemeName

SupplierInvoice/SupplierInvoiceHeader/SupplierParty/PartyIDs/TaxID

For ProcessSupplierInvoice: FAPIBH.E5SUNO; APS450MI

/AddHead

For LoadSupplierInvoice: CIDALL.S2XALT CRTVSUMI/GetSupplier

FAPIBH.E5SUNO APS450MI/AddHead.; /

@schemeName

For LoadSupplierInvoice:

SupplierInvoice/SupplierInvoiceHeader/CustomerParty/Contact/ID

FAPIBH.E5APCD; APS450MI/AddHead

SupplierInvoice/SupplierInvoiceHeader/CustomerParty/Contact/Name FAPIBH.E5APCD; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the Supplier Number.

This element can also be used as an alternative Supplier ID to retrieve the Supplier ID from API CRTVSUMI.

Retrieval of Supplier Number depends on TaxID@schemeName:

1) If blank, handle the same way as SupplierPartvIDs/ID with

1.) If blank, handle the same way as SupplierPartyIDs/ID with schemeName 'TaxID' blank'.

 If 'TaxIdentificationNumber', handle the same way as SupplierPartyIDs/ID with schemeName 'TaxIdentificationNumber'.
 If 'CountryIdentificationNumber' handle the same way as SupplierPartyIDs/ID with schemeName 'CountryIdentificationNumber'.

If the look up function fails to match a VAT registration number to an existing supplier record in M3 another look up will be done. This time with or without a country code for the first two positions in the number depending on if the number came with two letters in the beginning or not. If adding a country code this is picked from the element SupplierParty/Location/CountryCode in the BOD.

For LoadSupplierInvoice:

The field indicates the Supplier number.

Supplier VAT registration number or organization number can be used as an alternative Supplier ID set up in CRS627. See comments for the SupplierParty/PartyIDs/ID element above.

If the look up function fails to match a VAT registration number to an existing supplier record in M3 BE another look up will be done. This time with or without a country code for the first two positions in the number depending on if the number came with two letters in the beginning or not. If adding a country code this is picked from the element SupplierParty/Location/CountryCode in the BOD, if any.

For ProcessSupplierInvoice:

Set to the following:

- 1.) blank
- 2.) 'TaxIdentificationNumber'
- 3.) 'CountryIdentificationNumber'

For LoadSupplierInvoice:

The field indicates the schemeName which is used to choose which will be used in MI as Supplier if several Supplier ID's exist in the BOD. The order is as follows:

- 1. SupplierID with @schemeName 'SupplierNumber
- 2. TaxID with @schemeName 'TaxIdentificationNumber'
- 3. TaxID with @schemeName 'CountryIdentificationNumber'
- 4. SupplierID without @schemeName
- 5. TaxID without @schemeName

For LoadSupplierInvoice:

The field indicates the authorized user. If this element has no value, then the value in element CustomerParty/Contact/Name will be used.

For ProcessSupplierInvoice:

The field indicates the person who can authorize a specific invoice.

Possible to set up translation of the contact name to an authorized user code in CRS882 on company or division level.

Message standard: ION

Business message: SupplierInvoice Parent element: CustomerContact

Data element: Name

If no translation is found no Contact name will be sent to M3. Instead the functionality in M3 could be used to automatically select the Authorized user from the Supplier record or Purchase order.

For LoadSupplierInvoice:

The field indicates the authorized user. This element is only valid if element CustomerParty/Contact/ID has no value.

Possible to set up translation in 'Business Message Data Translation. Displ' (CRS881/CRS882) of the contact name to a M3 BE user ID. Translations are defined per company or division.

Message standard: ION

Business message: SupplierInvoice Parent element: CustomerContact

Data element: Name

If no translation is found no Contact name will be sent to M3. Instead the functionality in M3 could be used to automatically select the Authorized user from the Supplier record or Purchase order.

Note; the M3 BE user ID must be set up in 'Authorized User - Suppl Invoice. Open' (CRS650) for the applicable division.

SupplierInvoice/SupplierInvoiceHeader/CreditorParty/PartyIDs/ID

For ProcessSupplierInvoice:

FAPIBH.E5SPYN; APS450MI/AddHead

For ProcessSupplierInvoice: The field indicates the payee

SupplierInvoice/SupplierInvoiceHeader/CreditorParty/FinancialAccount/ID

For ProcessSupplierInvoice: FAPIBH.E5BKID; APS450MI/AddHead For ProcessSupplierInvoice:

The field indicates the bank account identity.

Possible to set up translation in CRS882 on company or division

Message standard: ION

Business message: SupplierInvoice Parent element: CreditorParty Data element: FinancialAccount

If no translation is found the Bank account identity connected to the Supplier record in M3 will defaulted.

If several bank account numbers exists in the BOD the following order

will be used to check if a translation exists in CRS882:

1 IBANID 2. BBANID

3. ID

SupplierInvoice/SupplierInvoiceHeader/CreditorParty/FinancialAccount/BBANID

For ProcessSupplierInvoice:

FAPIBH.E5BKID; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the bank account identity.

Possible to set up translation in CRS882 on company or division

level.

Message standard: ION

Business message: SupplierInvoice Parent element: CreditorParty Data element: FinancialAccount

If no translation is found the Bank account identity connected to the

Supplier record in M3 will defaulted.

If several bank account numbers exists in the BOD the following order

will be used to check if a translation exists in CRS882:

1. IBANID

2. BBANID

3. ID

SupplierInvoice/SupplierInvoiceHeader/CreditorParty/FinancialAccount/IBANID

For ProcessSupplierInvoice: FAPIBH.E5BKID; APS450MI/AddHead For ProcessSupplierInvoice:

The field indicates the bank account identity.

Possible to set up translation in CRS882 on company or division

level.

Message standard: ION

Business message: SupplierInvoice Parent element: CreditorParty Data element: FinancialAccount

If no translation is found the Bank account identity connected to the

Supplier record in M3 will defaulted.

If several bank account numbers exists in the BOD the following order

will be used to check if a translation exists in CRS882:

1 IBANID

2. BBANID

3. ID

SupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/ID

For LoadSupplierInvoice:

FAPIBH.E5BKID; APS450MI/AddHead

For LoadSupplierInvoice:

The field indicates the Bank account identity. The field is only used if elements FinancialAccount/BBANID and FinancialAccount/IBANID

have no value

SupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/BBANID

For LoadSupplierInvoice:

FAPIBH.E5BKID: APS450MI/AddHead

For LoadSupplierInvoice:

The field indicates the Bank account identity. The field is only used if element FinancialAccount/IBANID have no value

SupplierInvoice/SupplierInvoiceHeader/RemitToParty/FinancialParty/FinancialAccount/IBANID

For LoadSupplierInvoice:

For LoadSupplierInvoice:

The field indicates the Bank account identity.

SupplierInvoice/SupplierInvoiceHeader/StructuredCreditorReference

For ProcessSupplierInvoice:

FAPIBA.E7PEXI; APS450MI/AddAddInfo

FAPIBH.E5BKID; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates AP Additional information.

For LoadSupplierInvoice: FAPIBA.E7PEXI; APS450MI/AddAddInfo

This element is used for OCR or KID number. Additional Information category 412, 413 and 414 in M3 is used. The first 45 positions is stored in Info category 412 and if it's a longer number the next 45

FAPIBH.E5PAIN; APS450MI/AddHead.; / positions is stored in 413 and so on.

For LoadSupplierInvoice:

If schemeName attribute is 'ParallelInvoiceNumber', parallel invoice number (PAIN) is populated. The parallel invoice number can be used as a payment reference when paying the invoice, for example KID code in Norway.

If schemeName attribute is blank, the AP additional information (PEXI) is populated. This is the old way of entering a payment reference. Additional Information category 412, 413 and 414 in M3 is used. The first 45 positions are stored in Info category 412 and if it's a longer number the next 45 positions is stored in 413 and so on.

@schemeName

For LoadSupplierInvoice:

The field is set to 'ParallelInvoiceNumber' if Parallel invoice number (PAIN) is to be populated with the value in element StructuredCreditorReference.

SupplierInvoice/SupplierInvoiceHeader/PurchaseOrderReference/DocumentID/ID

For ProcessSupplierInvoice:

FAPIBH.E5PUNO

FAPIBL.E6PUNO .; APS450MI/AddHead

AddLine

For LoadSupplierInvoice: FAPIBH.E5PUNO; APS450MI/Addhead,

FAPIBL.E6PUNO; APS450MI/AddLine .; / For ProcessSupplierInvoice:

The field indicates the purchase order number.

The PurchaseOrderReference will be entered in the PO number (PUNO) field in APS450. The exception is if no PurchaseOrderReference exists in the SupplierInvoiceLines, if any,

then the value in this element will be added to all item and charge lines in the field PO number in APS451.

How the Inv matching (IMCD) parameter in APS450 is set:

- 0 No matching to purchase order: If no PurchaseOrderReference and no SupplierInvoiceLines exist in the BOD.
- 1 Invoice matching on line level: If SupplierInvoiceLines exist in the BOD.
- 2 Inv matching on PO header level: If a PurchaseOrderReference exists in this element in the BOD but no SupplierInvoiceLines.

For LoadSupplierInvoice:

The field indicates the Purchase order number.

The PurchaseOrderReference will be entered in the PO number (PUNO) field in APS450. The exception is if no

PurchaseOrderReference exists in the SupplierInvoiceLines, if any, then the value in this element will be added to all item and charge lines in the field PO number in APS451.

How the Inv matching (IMCD) parameter in APS450 is set:

- 0 No matching to purchase order: If no PurchaseOrderReference and no SupplierInvoiceLines exist in the BOD.
- 1 Invoice matching on line level: If SupplierInvoiceLines exist in the BOD.
- 2 Inv matching on PO header level: If a PurchaseOrderReference exists in this element in the BOD but no SupplierInvoiceLines

SupplierInvoice/SupplierInvoiceHeader/PaymentTerm/Term/DueDateTime

FAPIBH.E5DUDT; APS450MI/AddHead

For ProcessSupplierInvoice:

The field indicates the date the invoice is due for payment according to payment or cash discount terms.

For LoadSupplierInvoice:

The field indicates the payment due date

SupplierInvoice/SupplierInvoiceHeader/Tax @sequenceNumber

For LoadSupplierInvoice:

The field indicates the tax sequence number.

@type

For ProcessSupplierInvoice:

Set to the following:

- 1.) 'COMBINEDVAT1
- 2.) 'COMBINEDVAT2'
- 3.) 'CHAINVAT1'
- 4.) 'CHAINVAT2'
- 5.) blank

This element determines the values of VAT amount 1 and 2 and VAT rate 1 and 2.

For LoadSupplierInvoice:

The field determines how the VAT is identified. If @type is set to 'VAT' and:

- 1.)@subType is 'COMBINED' then Combined VAT having an even sequence number is identified as first VAT of the pair and Combined VAT having an odd sequence number is identified as second VAT of the pair
- 2.) @subType is 'CHAIN' then Chain VAT having an even sequence number is identified as first VAT of the pair and Chain VAT having an odd sequence number is identified as second VAT of the pair.

Tax element that has type VAT but subType other then Combined or Chain is handled as single Tax/VAT and added as a separate line on the invoice.

For LoadSupplierInvoice:

The field determines how the VAT is identified. If @type is set to 'VAT' and:

- 1.)@subType is 'COMBINED' then Combined VAT having an even sequence number is identified as first VAT of the pair and Combined VAT having an odd sequence number is identified as second VAT of the pair.
- 2.) @subType is 'CHAIN' then Chain VAT having an even sequence number is identified as first VAT of the pair and Chain VAT having an odd sequence number is identified as second VAT of the pair.

Tax element that has type VAT but subType other then Combined or Chain is handled as single Tax/VAT and added as a separate line on the invoice.

SupplierInvoice/SupplierInvoiceHeader/Tax/ID

FAPIBL.E6VTCD; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates a VAT code. The VAT code controls what VAT method and VAT rate to apply

For LoadSupplierInvoice:

The field indicates the VAT code. This is only applicable for invoice line type 3-VAT.

SupplierInvoice/SupplierInvoiceHeader/Tax/Calculation/RateNumeric

For ProcessSupplierInvoice:

FAPIBL.E6VTP1 E6VTP2; APS450MI/AddLine

For LoadSupplierInvoice: FAPIBL.E6VTP1

@subType

FAPIBL.E6VTP2.; APS450MI/AddLine

For ProcessSupplierInvoice: The field indicates the VAT rate.

For LoadSupplierInvoice:

The field indicates the VAT rate. This is only applicable for invoice

line type 3-VAT.

SupplierInvoice/SupplierInvoiceHeader/Tax/TaxAuthorityAmount

For LoadSupplierInvoice:

FAPIBL.E6GLAM; APS450MI/AddLine

For LoadSupplierInvoice:

The field indicates the gross amount per line. This is only applicable

for invoice line type 3-VAT.

SupplierInvoice/SupplierInvoiceHeader/Tax/Amount

For ProcessSupplierInvoice:

FAPIBL.E6VTA1 E6VTA2; APS450MI/AddLine

For LoadSupplierInvoice:

FAPIBL.E6VTA1 FAPIBL.E6VTA2.; APS450MI/AddLine

For ProcessSupplierInvoice: The field indicates the VAT amount.

For LoadSupplierInvoice:

The field indicates the VAT amount. This is only applicable for invoice

line type 3-VAT.

SupplierInvoice/SupplierInvoiceHeader/Charge @type

For ProcessSupplierInvoice:

Set to 'Allowance' to change the amount to negative.

For LoadSupplierInvoice:

The field is set to 'Allowance' if charge type is allowance.

J	u	μ	וץ	ICI	111	ΙV	U	C	C
@	sec	าม	enc	e					

FAPIBL.E6CDSE; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the sequence number of the costing element.

Entered for line type 2 - Order charges in APS451.

For LoadSupplierInvoice:

The field indicates the sequence number of costing element. The field is applicable for invoice line type 2- Order charge.

SupplierInvoice/SupplierInvoiceHeader/Charge/ID

FAPIBL.E6CEID; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates a costing element to use in purchase costing or

distribution costing.

Entered for line type 2 - Order charges in APS451 if

SupplierInvoiceLines exist in the BOD which means invoice matching

on line level in M3 BE.

The value in this element is used if the Charge/Description element

does not exist in the BOD.

For LoadSupplierInvoice:

The field indicates the costing element. The field is applicable for

invoice line type 2- Order charge.

SupplierInvoice/SupplierInvoiceHeader/Charge/Description

For ProcessSupplierInvoice:

FAPIBL.E6CHGT; APS450MI/AddLine

For LoadSupplierInvoice:

FAPIBL.E6CHGT; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the charge text.

Entered for line type 2 - Order charges in APS451 if invoice matching

on line level in M3 BE.

If this element comes with @type 'Allowance' (discount) and the charge amount is positive in the BOD then a negative sign will be

added to the charge amount in M3 BE.

Possible to set up translation in CRS882 on company or division

level.

Translation of Description to Charge description (CHGT).

Message standard: ION

Business message: SupplierInvoice

Parent element: Charge Data element: Description

If no translation is found the first 30 positions of the Description is

entered in the Charge text (CHGT) field in APS451.

For LoadSupplierInvoice:

The field indicates the Charge text. The field is applicable for invoice

line type 2- Order charge.

If this element comes with @type 'Allowance' (discount) and the charge amount is positive in the BOD then a negative sign will be

added to the charge amount in M3 BE.

Possible to set up translation in CRS882 on company or division

level.

Translation of Description to Charge description (CHGT).

Message standard: ION

Business message: SupplierInvoice

Parent element: Charge

Parent element: Charge Data element: Description

If no translation is found the first 30 positions of the Description is

entered in the Charge text (CHGT) field in APS451.

SupplierInvoice/SupplierInvoiceHeader/Charge/Amount

FAPIBL.E6NLAM; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the net amount for an invoice line.

Entered for line type 2 - Order charges in APS451 if

SupplierInvoiceLines exist in the BOD which means invoice matching

on line level in M3 BE.

For LoadSupplierInvoice:

The field indicates the net amount per line. The field is applicable for

invoice line type 2- Order charge.

SupplierInvoice/SupplierInvoiceHeader/Allowance/ID

For LoadSupplierInvoice:

FAPIBL.E6CEID; APS450MI/AddLine	For LoadSupplierInvoice:
TATIBELEGGEIB, AT G-900MI/Addellife	The field indicates the costing element. The field is applicable for invoice line type 2- Order charge.
SupplierInvoice/SupplierInvoiceHeader/Allowance/Description	
For LoadSupplierInvoice:	For LoadSupplierInvoice:
FAPIBL.E6CHGT; APS450MI/AddLine	The field indicates the Charge text. The field is applicable for invoice line type 2- Order charge.
	If this element comes with @type 'Allowance' (discount) and the charge amount is positive in the BOD then a negative sign will be
	added to the charge amount in M3 BE.
	Possible to set up translation in CRS882 on company or division level.
	Translation of Description to Charge description (CHGT). Message standard: ION Business message: SupplierInvoice
	Parent element: Charge Data element: Description
	If no translation is found the first 30 positions of the Description is entered in the Charge text (CHGT) field in APS451.
SupplierInvoice/SupplierInvoiceHeader/Allowance/Amount	5 J 10 II J
For LoadSupplierInvoice: FAPIBL.E6NLAM; APS450MI/AddLine	For LoadSupplierInvoice: The field indicates the net amount per line. The field is applicable for invoice line type 2- Order charge.
SupplierInvoice/SupplierInvoiceHeader/UserArea/Property/NameValue	
For LoadSupplierInvoice:	For ProcessSupplierInvoice:
FAPBIA.E3PEXI FAPBIA.E3PEXN	Set to "true" if invoice lines are going to be Accounting lines (of line type 8) in M3 and Accounting Objects or Accounting String will be
FAPBIA.E3PEXS.; APS450MI/AddAddInfo	provided. In Nexus, this functionality is used in invoices for adjustments done on supplier invoices.
	For LoadSupplierInvoice: 1) The field is used if element NameValue@name is equal to
	"m3_AdditionalInformation". The field indicates the AP additional information, AP information category and GL information sequence
	number. 2) Set to "true" if invoice lines are going to be Accounting lines (of line type 8) in M3 and Accounting Objects or Accounting String will be provided.
@name	For ProcessSupplierInvoice: Set to "AccountingLine" if invoice lines are going to be Accounting lines (of line type 8) in M3 and Accounting Objects or Accounting String will be provided. This functionality is used in invoices for adjustments done on supplier invoices in Nexus.
	For LoadSupplierInvoice: 1) Set to "m3_AdditionalInformation" if element NameValue indicates the AP additional information, AP information category and GL information sequence number. 2) Set to "AccountingLine" if invoice lines are going to be Accounting lines (of line type 8) in M3 and Accounting Objects or Accounting String will be provided.
SupplierInvoice/SupplierInvoiceLine/DocumentReference	
@type	For ProcessSupplierInvoice: Set to 'Shipment' or 'AdvanceShipNotice' to update Delivery Note.
	For LoadSupplierInvoice: The field is set to 'Shipment' or 'AdvanceShipNotice'.
SupplierInvoice/SupplierInvoiceLine/DocumentReference/DocumentIl	
FAPIBL.E6SUDO; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates the supplier's delivery note number.
	If the DocumentReference is sent together with the @type attribute 'Shipment' or 'AdvanceShipNotice' in the BOD this number will be entered for line type 1 - item line and 5 - Line charge in APS451.
	For LoadSupplierInvoice: The field indicates the Delivery note number.
SupplierInvoice/SupplierInvoiceLine/Item/ItemID/ID	
FAPIBL.E6POPN; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates the alias number which is an alternative ID for an individual item.

Infor May 26, 2023 201

individual item.

Entered for line type 1 - Item line and 5 - Line charge in APS451.

If several Item IDs or an Item/Description exists in the BOD, the following order will be used and the first value found will be entered for the item line in APS451:

- 1) ItemID with schemeName = 'Customer' (expected to be M3's item number).
- 2) Item ID with schemeName 'Supplier'.
- 3) Item ID with schemeName 'Manufacturer'
- 4) Item ID with no schemeName
- 5) Item/Description

The first 30 positions of the value (if longer than this) in the BOD are entered in the Alias number (POPN) field in APS451.

Alias numbers for suppliers are maintained in PPS040.

For LoadSupplierInvoice:

The field indicates the item's Alias number.

Entered for line type 1 - Item line and 5 - Line charge in APS451.

If several Item IDs or an Item/Description exists in the BOD the following order will be used and the first value found will be entered for the item line in APS451:

- 1) ItemID with schemeName = 'Customer' (expected to be M3's item number).
- 2) Item ID with schemeName 'Supplier'.
- 3) Item ID with schemeName 'Manufacturer'
- 4) Item ID with no schemeName
- 5) Item/Description

The first 30 positions of the value (if longer than this) in the BOD are entered in the Alias number (POPN) field in APS451. If the alias is not found in M3 BE the first 15 positions of the alias number are updated into the item number field (ITNO).

Alias numbers for suppliers are maintained in PPS040.

For ProcessSupplierInvoice:

Set to the following:

- 1.) 'Customer'
- 2.) 'Supplier'
- 3.) 'Manufacturer'
- 4.) no schemeName

SupplierInvoice/SupplierInvoiceLine/Item/Description

FAPIBL.E6POPN; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the alias number which is an alternative ID for an individual item. The value for this field is the least priority to be inputted as Alias number.

For LoadSupplierInvoice:

The field indicates the item's Alias number.

Entered for line type 1 - Item line and 5 - Line charge in APS451.

See comments for Item/ItemID/ID.

SupplierInvoice/SupplierInvoiceLine/Quantity

FAPIBL.E6IVQA; APS450MI/AddLine

For ProcessSupplierInvoice:

The field indicates the total quantity reported as invoiced on the purchase order line.

Entered for line type 1 - Item line and 5 - Line charge in APS451.

For LoadSupplierInvoice:

The field indicates the invoiced quantity in alternate unit of measure.

For ProcessSupplierInvoice:

The field indicates the unit of measure (U/M) in which the quantity on the purchase order is expressed.

Entered for line type 1 - Item line and 5 - Line charge in APS451.

Possible to set up translation in CRS882 on company or division

level. Message standa

Message standard: ION Business message: Generic Parent element: Generic

@unitCode

@schemeName

FAPIBL.E6PUUN; APS450MI/AddLine

	For LoadSupplierInvoice: The field indicates the purchase order unit of measure.
SupplierInvoice/SupplierInvoiceLine/UnitPrice/Amount	·
FAPIBL.E6GRPR; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates the gross price.
	Entered for line type 1 - Item line.
	For LoadSupplierInvoice: The field indicates the gross price.
SupplierInvoice/SupplierInvoiceLine/UnitPrice/PerQuantity	
FAPIBL.E6PUCD; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates the purchase price per item when purchased in a specific quantity.
	Entered for line type 1 - Item line.
O	For LoadSupplierInvoice: The field indicates the purchase price per quantity.
@unitCode	For ProcessSupplierInvoice:
FAPIBL.E6PPUN; APS450MI/AddLine	The field indicates the purchase price unit, U/M, which is the U/M in which the purchase price has been expressed.
	Entered for line type 1 - Item line and 5 - Line charge in APS451.
	Possible to set up translation in CRS882 on company or division
	level.
	Message standard: ION Business message: Generic
	Parent element: Generic
	Data element: UOMCode
	For LoadSupplierInvoice:
	The field indicates the purchase price unit of measure.
SupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference/Docu	
FAPIBL.E6PUNO; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates the Purchase order number.
	For LoadSupplierInvoice: The field indicates the purchase order number.
SupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference/LineN	
FAPIBL.E6PNLI; APS450MI/AddLine	For ProcessSupplierInvoice:
	The field indicates the purchase order line.
	Entered for line type 1 - Item line and 5 - Line charge in APS451.
	For LoadSupplierInvoice: The field indicates the purchase order line.
	If Control Property 'm3beParsePOLineNumber' is set to true, and the value of the element is more than 3 digits, the last 3 digits of the value will be removed and the remaining will be mapped to the PO line number field (PNLI).
	The last 3 digits which are removed will then be mapped to the PO subline number field (PNLS) if element SupplierInvoiceLine/PurchaseOrderReference/SubLineNumber is not existing.
	If Control Property 'm3beParsePOLineNumber' is not set to true, the value of the element will be mapped as it is in PO line number field (PNLI).
SupplierInvoice/SupplierInvoiceLine/PurchaseOrderReference/SubLi	
FAPIBL.E6PNLS; APS450MI/AddLine	For ProcessSupplierInvoice: The field indicates Purchase order subline number.
	Entered for line type 1 - Item line and 5 - Line charge in APS451.
	For LoadSupplierInvoice: The field indicates the purchase order subline number.
	If Control Property 'm3beParsePOLineNumber' is set to true, and the value of the element is more than 3 digits, the last 3 digits of the value will be mapped to the PO subline number field (PNLS).
SupplierInvoice/SupplierInvoiceLine/ExtendedAmount	

Data element: UOMCode

SupplierInvoice FAPIBL.E6GLAM; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates the gross total in an invoice line. Entered for line type 1 - Item line. For LoadSupplierInvoice: The field indicates the gross total in an invoice line. Entered for line type 8 - Accounting line. Not used for other line types. SupplierInvoice/SupplierInvoiceLine/InvoiceCharge @sequence FAPIBL.E6CDSE; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates the sequence number of the costing element. Entered for line type 5 - Line charge. For LoadSupplierInvoice: The field indicates the sequence number for costing element. The field is only applicable for invoice line type 5- Line charge. SupplierInvoice/SupplierInvoiceLine/InvoiceCharge/ID FAPIBL.E6CEID; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates a costing element to use in purchase costing or distribution costing. Entered for line type 5 - Line charge in APS451. The value in this element is used if the Charge/Description element does not exist in the BOD. The line charge in M3 BE should also be populated with the following fields from the SupplierInvoiceLines if any of them exist in the BOD: POPN - Alias number IVQA - Invoiced quantity - alternate U/M PUUN - Purchase order U/M PPUN - Purchase price U/M PUNO - Purchase order number PNLI - Purchase order line PNLS - Purchase order line subnumber SUDO - Delivery note number For LoadSupplierInvoice: The field indicates the costing element. The field is only applicable for invoice line type 5-Line charge.

The value in this element is used if the Charge/Description element does not exist in the BOD.

The line charge in M3 BE should also be populated with the following fields from the SupplierInvoiceLines if any of them exist in the BOD:

POPN - Alias number

IVQA - Invoiced quantity - alternate U/M

PUUN - Purchase order U/M PPUN - Purchase price U/M PUNO - Purchase order number PNLI - Purchase order line

PNLS - Purchase order line subnumber

SUDO - Delivery note number

SupplierInvoice/SupplierInvoiceLine/InvoiceCharge/Description

For ProcessSupplierInvoice:

FAPIBL.E6CHGT; APS450MI/AddLine

For LoadSupplierInvoice:

FAPIBL.E6CHGT; APS450MI/AddLine

For ProcessSupplierInvoice: The field indicates the charge text.

Entered for line type 5 - Line charge in APS451.

Possible to set up translation in CRS882 on company or division level.

Translation of Description to Charge description (CHGT).

Message standard: ION

Business message: SupplierInvoice

Parent element: Charge Data element: Description

If no translation is found the first 30 positions of the Description is entered in the Charge text (CHGT) field.

Also see comment for InvoiceCharge/ID.

For LoadSupplierInvoice:

The field indicates the charge text. The field is only applicable for

invoice line type 5-Line charge. Possible to set up translation in CRS882 on company or division Translation of Description to Charge description (CHGT). Message standard: ION Business message: SupplierInvoice Parent element: Charge Data element: Description If no translation is found the first 30 positions of the Description is entered in the Charge text (CHGT) field. Also see comment for InvoiceCharge/ID. SupplierInvoice/SupplierInvoiceLine/InvoiceCharge/Amount FAPIBL.E6GRPR; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates the gross price. Entered for line type 5 - Line charge in APS451. Also see comment for InvoiceCharge/ID. For LoadSupplierInvoice: The field indicates the gross price. The field is only applicable for invoice line type 5-Line charge. Also see comment for InvoiceCharge/ID. SupplierInvoice/SupplierInvoiceLine/InvoiceAllowance/Amount FAPIBL.E6DIAM; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates the discount amount. Entered for line type 1 - Item line in APS451. For LoadSupplierInvoice: The field indicates the discount amount. SupplierInvoice/SupplierInvoiceLine/InvoiceAllowance/Calculation/RateNumeric FAPIBL.E6DIPC; APS450MI/AddLine For ProcessSupplierInvoice: The field indicates the discount as a percentage. Entered for line type 1 - Item line in APS451. For LoadSupplierInvoice: The field indicates the discount SupplierInvoice/SupplierInvoiceLine/UserArea/Property/NameValue For ProcessSupplierInvoice: For ProcessSupplierInvoice: 1) FAPIBL.E6AO01 The field indicates specific values required by an integration for 2) FAPIBL.E6AO02 incoming supplier invoices with Accounting lines (lines of type 8) in 3) FAPIBL.E6AO03 4) FAPIBL.E6AO04 1) Value for Accounting object 1 5) FAPIBL.E6AO05 2) Value for Accounting object 2 6) FAPIBL.E6AO06 3) Value for Accounting object 3 4) Value for Accounting object 4 7) FAPIBL.E6AO07 8) FAPIBL.E6AIT1 5) Value for Accounting object 5 9) FAPIBL.E6AIT2 6) Value for Accounting object 6 10) FAPIBL.E6AIT3 7) Value for Accounting object 7 11) FAPIBL.E6AIT4 8) Value for Accounting dimension 1 12) FAPIBL.E6AIT5 9) Value for Accounting dimension 2 10) Value for Accounting dimension 3 13) FAPIBL.E6AIT6 14) FAPIBL.E6AIT7 11) Value for Accounting dimension 4 15) FAPIBL.E6VTXT 12) Value for Accounting dimension 5 16) FAPIBL.E6FADS 13) Value for Accounting dimension 6 17) FAPIBL.E6FAQT 14) Value for Accounting dimension 7 18) FAPIBL.E6TXT1 15) Value for Voucher text 16) Value for preliminary Fixed asset name (mandatory for FA) 17) Value for preliminary Fixed asset quantity (mandatory for FA) 19) FAPIBL.E6TXT2.; APS450MI/AddLine For LoadSupplierInvoice: 18) Value for preliminary Fixed asset text line 1 (optional for FA) 19) Value for preliminary Fixed asset text line 2 (optional for FA) 1) FAPIBL. E6AO01 2) FAPIBL.E6AO02 For incoming supplier invoices with Accounting lines (lines of type 8) 3) FAPIBL.E6AO03 in M3, Accounting String can be provided for the line: values for Accounting dimension 1 - Accounting dimension 7, or Accounting Objects can be provided instead: values for Accounting object 1 -4) FAPIBL.E6AO04 5) FAPIBL.E6AO05 Accounting object 7, to find correct accounting string by setting up 6) FAPIBL.E6AO06 7) FAPIBL.E6AO07 Accounting Rule exceptions in CRS395 for AP50-218 (Batch supplier invoices - Accounting line). 8) FAPIBL.E6AIT1 If values are provided for Accounting objects and Accounting 9) FAPIBL.E6AIT2 10) FAPIBL.E6AIT3 dimensions - values for Accounting dimensions are used in M3. 11) FAPIBL.E6AIT4 If no values are provided for Accounting objects or Accounting

- 12) FAPIBL.E6AIT5
- 13) FAPIBL.E6AIT6
- 14) FAPIBL.E6AIT7
- 15) FAPIBL.E6VTXT.; APS450MI/AddLine

dimensions, accounting string for AP50-218 in CRS395 will be used. Voucher text can be also provided, but in some cases it is overridden

Name, quantity and Text line 1 and 2 can be also provided to create preliminary Fixed assets in FAS001.

In Nexus, this functionality is used to invoice adjustments done on supplier invoices.

For LoadSupplierInvoice:

The field indicates specific values required by an integration for incoming supplier invoices with Accounting lines (lines of type 8) in

- 1) Value for Accounting object 1
- 2) Value for Accounting object 2
- 3) Value for Accounting object 3
- 4) Value for Accounting object 4
- 5) Value for Accounting object 5
- 6) Value for Accounting object 6
- 7) Value for Accounting object 7
- 8) Value for Accounting dimension 1
- 9) Value for Accounting dimension 2
- 10) Value for Accounting dimension 3
- 11) Value for Accounting dimension 4
- 12) Value for Accounting dimension 5
- 13) Value for Accounting dimension 6
- 14) Value for Accounting dimension 7
- 15) Value for Voucher text

For incoming supplier invoices with Accounting lines (lines of type 8) in M3, Accounting String can be provided for the line: values for Accounting dimension 1 - Accounting dimension 7, or Accounting Objects can be provided instead: values for Accounting object 1 -Accounting object 7, to find correct accounting string by setting up Accounting Rule exceptions in CRS395 for AP50-218 (Batch supplier invoices - Accounting line).

If values are provided for Accounting objects and Accounting dimensions - values for Accounting dimensions are used in M3. If no values are provided for Accounting objects or Accounting dimensions, accounting string for AP50-218 in CRS395 will be used. Voucher text can be also provided, but in some cases it is overridden

For ProcessSupplierInvoice:

- 1) "AccountingLine_Object1"
- 2) "AccountingLine_Object2"
- 3) "AccountingLine_Object3"
- 4) "AccountingLine Object4"
- 5) "AccountingLine_Object5" 6) "AccountingLine Object6"
- 7) "AccountingLine_Object7"
- 8) "AccountingLine_Dim1"
- 9) "AccountingLine_Dim2"
- 10) "AccountingLine Dim3" 11) "AccountingLine_Dim4"
- 12) "AccountingLine_Dim5"
- 13) "AccountingLine Dim6"
- 14) "AccountingLine_Dim7"
 15) "AccountingLine_VoucherText"
- 16) "AccountingLine FA Name"
- 17) "AccountingLine_FA_Quantity"
 18) "AccountingLine_FA_TXT1"
 19) "AccountingLine_FA_TXT2"

For LoadSupplierInvoice:

- 1) "AccountingLine_Object1"
- 2) "AccountingLine_Object2"
- 3) "AccountingLine_Object3"
- 4) "AccountingLine_Object4" 5) "AccountingLine_Object5"
- 6) "AccountingLine_Object6"
- 7) "AccountingLine_Object7" 8) "AccountingLine_Dim1"
- 9) "AccountingLine_Dim2"
- 10) "AccountingLine Dim3"
- 11) "AccountingLine Dim4"
- 12) "AccountingLine_Dim5"
- 13) "AccountingLine Dim6"

@name

14) "AccountingLine_Dim7" 15) "AccountingLine_VoucherText"

SupplierPartyMaster

Ouppliell artymaster			
SupplierPartyMaster			
@category CIDMAS.IDSUTY ; CRS620MI/AddSupplier	The field indicates the Supplier type.		
, Ortoozowii/Audouppilei	If attribute type is 'Supplier', populate SUTY with 0. If attribute type is 'Agent', populate SUTY with 1. If attribute type is 'Only Payee', populate SUTY with 2. If attribute type is 'Supplier group', populate SUTY with 3. If attribute type is 'Insurance Company', populate SUTY with 6. If attribute type is 'Miscellaneous Suppliers', populate SUTY with 8. If attribute type is 'Trade-in Supplier', populate SUTY with 9.		
	Note: If not given, default SUTY to 0. Do not process SupplierPartyMaster BOD if SUTY = 5 (Forwarding agent).		
SupplierPartyMaster/PartyIDs/ID CIDMAS.IDSUNO ; CRS620MI/CopyTemplate, AddSupplier,UpdSupplier, AddAddress,UpdAddress, DelAddress,AddSupplierRef, UpdSupplierRef,DelSupplierRef, LstSupplierRef	The field indicates the unique identity of the supplier (SUNO) or supplier item (STEM) . Record will be created in M3 'Supplier. Open' (CRS620), CIDMAS table.		
	If the field is left blank, SUNO field will be populated with '????????' which will trigger M3 to automatically generate a supplier number. If Control property: m3beDefaultSupplierPrefix has a value, then the value will be used as the first characters of SUNO, and the remaining characters will be '?'.		
	e.g. Control property: m3beDefaultSupplierPrefix = M3 Input SUNO: M3???????? Sample generated Supplier number in M3: M300000001		
@schemeName	If schemeName='System' does not exist, populate supplier (SUNO). If schemeName='System' exists, populate supplier template (STEM).		
@accountingEntity CIDMAS.IDCONO CMNDIV.CCDIVI.; /	The field indicates the company and division, displayed as CONO DIVI.		
SupplierPartyMaster/PartyIDs/TaxID CIDVEN.IITINO CIDMAS.IDCORG CIDMAS.IDCOR2 CIDMAS.IDVRNO .; CRS620MI/AddSupplier, UpdSupplier	The field indicates the Organization number (CORG), Organization number 2 (COR2), VAT registration number (VRNO) and Tax ID for Supplier (TINO).		
@schemeName	If attribute type is 'CountryldentificationNumber', populate CORG. If attribute type is 'CountryldentificationNumber', populate COR2. If attribute type is 'TaxIdentificationNumber', populate VRNO. if attribute type blank, populate TINO.		
SupplierPartyMaster/PartyIDs/SCACID CIDMAS.IDFWSC ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the Standard Carrier Alpha Code (SCAC). The SCAC is a four-letter alpha code that uniquely identifies a forwarder.		
SupplierPartyMaster/Name CIDMAS.IDSUNM ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the supplier name.		
SupplierPartyMaster/Location @type			
CIDADR.SAADTE CIDADR.SAADID.; CRS620MI/AddAddress, UpdAddress, DelAddress,	The field indicates the address type.		
LstAddress	If attribute type is 'Postal', populate ADID with POSTAL and ADTE with 01. If attribute type is 'Street', populate ADID with STREET and ADTE with 02.		
	with 02. If attribute type is 'Pickup', populate ADID with PICKUP and ADTE with 03. If attribute type is 'Origin', populate ADID with ORIGIN and ADTE with 04.		
	If attribute type is 'Final', populate ADID with FINAL and ADTE with 05. If attribute type is 'Bank', leave ADID blank and populate ADTE with 10.		
SupplierPartyMaster/Location/Name CIDADR.SASUNM	The field indicates the supplier name.		
CIDADK.SASUNM	The held indicates the supplier hame.		

SupplierPartyMaster	
CIDADR.SAADR1 CIDADR.SAADR2 CIDADR.SAADR3 CIDADR.SAADR4 .; CRS620MI/AddAddress, UpdAddress	The field indicates the address line.
@sequence	The field indicates the address line sequence number.
	If sequence = 1, populate ADR1. If sequence = 2, populate ADR2. If sequence = 3, populate ADR3. If sequence = 4, populate ADR4.
SupplierPartyMaster/Location/Address/CityName CIDADR.SATOWN ; CRS620MI/AddAddress, UpdAddress	The field indicates the city.
SupplierPartyMaster/Location/Address/CountrySubDivisionCode CIDADR.SAECAR ; CRS620MI/AddAddress, UpdAddress,UpdSupplier	The field indicates the state.
SupplierPartyMaster/Location/Address/CountryCode CIDADR.SACSCD ; CRS620MI/AddAddress, UpdAddress, AddSupplier, UpdSupplier	The field indicates the country.
SupplierPartyMaster/Location/Address/PostalCode CIDADR.SAPONO ; CRS620MI/AddAddress, UpdAddress	The field indicates the postal code.
SupplierPartyMaster/Location/Status/EffectiveDateTime CIDADR.SASTDT ; CRS620MI/AddAddress, UpdAddress, DelAddress	The field indicates the date from which the record is valid.
SupplierPartyMaster/Communication @sequence	
	The field indicates the communication sequence number. If sequence = 1, populate PHNO. If sequence = 2, populate PHN2. If sequence = 3, populate TFNO.
SupplierPartyMaster/Communication/ChannelCode	The field indicates the channel code Phone.
SupplierPartyMaster/Communication/UseCode	The field indicates the use code Office or Fax.
SupplierPartyMaster/Communication/CountryDialing CIDMAS.IDPHNO CIDMAS.IDPHN2 CIDMAS.IDTFNO	The field indicates the country dialing code for a communication number.
.; CRS620MI/AddSupplier, UpdSupplier	If ChannelCode = 'Phone' exists, populate CountryDialing value as part of the Phone number. If UseCode = 'Fax' exists, populate CountryDialing value as part of the Fax number.
SupplierPartyMaster/Communication/AreaDialing CIDMAS.IDPHNO	The field indicates the area dialing code for a communication number.
CIDMAS.IDPHN2 CIDMAS.IDTFNO .; CRS620MI/AddSupplier, UpdSupplier	If ChannelCode is 'Phone' exists, populate AreaDialing directly after CountryDialing value as part of the Phone number. If UseCode = 'Fax' exists, populate AreaDialing directly after CountryDialing value as part of the Fax number.
SupplierPartyMaster/Communication/DialNumber CIDMAS.IDPHNO	The field indicates the dial number for communicate.
CIDMAS.IDPHN2 CIDMAS.IDTFNO .; CRS620MI/AddSupplier, UpdSupplier	If ChannelCode is 'Phone' and UseCode is 'Office', populate Phone Number (PHNO/PHN2). If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
SupplierPartyMaster/Contact @type	, ,
CIDREF.IRRFTY ; CRS620MI/AddSupplierRef, UpdSupplierRef	The field indicates the reference type.
	If reference type is 'Purchase', populate RFTY with 10. If reference type is 'Repair or Subcontract', populate RFTY with 15. If reference type is 'Delivery receipt', populate RFTY with 20. If reference type is 'Claim', populate RFTY with 25. If reference type is 'Financial', populate RFTY with 30. If reference type is 'Agreement', populate RFTY with 35.
SupplierPartyMaster/Contact/ID CIDREF.IRRFID ; CRS620MI/AddSupplierRef, UpdSupplierRef	The field indicates the reference ID.
SupplierPartyMaster/Contact/Name CIDREF.IRYRE1	

SupplierPartyMaster ; CRS620MI/AddSupplierRef, UpdSupplierRef The field indicates the name of the person to be contacted for issues regarding customer orders or purchase orders. SupplierPartyMaster/Contact/Communication/ChannelCode The field indicates the channel code Phone or Email. SupplierPartyMaster/Contact/Communication/UseCode The field indicates the use code Office or Fax. SupplierPartyMaster/Contact/Communication/CountryDialing

CIDREF.IRPHNO CIDREF.IRTFNO .; CRS620MI/AddSupplierRef, UpdSupplierRef	The field indicates the country dialing code for a communication number.
	If ChannelCode = 'Phone' exists, populate CountryDialing value as part of the Phone number. If UseCode = 'Fax' exists, populate CountryDialing value as part of the Fax number.
SupplierPartyMaster/Contact/Communication/AreaDialing CIDREF.IRPHNO CIDREF.IRTFNO	The field indicates the area dialing code for a communication number.
.; CRS620MI/AddSupplierRef, UpdSupplierRef	If ChannelCode is 'Phone' exists, populate AreaDialing directly after CountryDialing value as part of the Phone number. If UseCode = 'Fax' exists, populate AreaDialing directly after CountryDialing value as part of the Fax number.
SupplierPartyMaster/Contact/Communication/DialNumber CIDREF.IRPHNO	The field indicates the phone and fax number.
CIDREF.IRTFNO .; CRS620MI/AddSupplierRef, UpdSupplierRef	If ChannelCode is 'Phone' and UseCode is 'Office', populate Phone Number (PHNO). If ChannelCode is 'Phone' and UseCode is 'Fax' populate Fax Number (TFNO).
SupplierPartyMaster/Contact/Communication/URI CIDREF.IREMAL ; CRS620MI/AddSupplierRef, UpdSupplierRef	The field indicates the e-mail address.
SupplierPartyMaster/LanguageCode CIDMAS.IDLNCD ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the language in which external documents are to be printed.
SupplierPartyMaster/PaymentTermCode CIDVEN.IITEPY ; CRS620MI /AddSupplier, UpdSupplier	The field indicates how the payment due date is to be calculated.
SupplierPartyMaster/PaymentMethodCode CIDVEN.IIPYME ; CRS620MI /AddSupplier, UpdSupplier	The field indicates the method on how the supplier payment is processed.
SupplierPartyMaster/FinancialParty/PartyIDs/ID ?CBANAC.?BCBKNO? ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates bank number
SupplierPartyMaster/FinancialParty/PartyIDs/TaxID CIDVEN.IIVTCD ; CRS620MI/AddSupplier, UpdSupplier	The field indicates the VAT code.
SupplierPartyMaster/FinancialParty/BranchParty/PartyIDs/BICID ?CBANAC.BCBBRN ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates Bank branch identity
SupplierPartyMaster/FinancialParty/BranchParty/Location/Address/ ?CBANAC.?BCBKIN? ; CRS692MI/AddBankAccount, ChgBacsicData, GetBankAccount	CountryCode The field indicates the identity of the Bank Account Indicator.
	If CountryCode is blank, populate 'BANKACCTINDICATOR'. Otherwise, if ListID is 'BankIndicatorCountry', populate (BKIN) Bank account indicator country code that can be retrieved in M3 'Bank Account Indicator. Open' (CRS072), CBANAC table.
@listID	If ListID is 'BankIndicatorCountry', populate (BKIN) Bank account indicator that can be retrieved in M3 'Bank Account Indicator. Open' (CRS072), CBANAC table.
SupplierPartyMaster/FinancialParty/FinancialAccount/ID ?CBANAC.BCBKID; CRS692MI/AddBankAccount,	The field indicates the bank account ID.
SupplierPartyMaster/FinancialParty/FinancialAccount/IBANID ?CBANAC.?BCIBAN? ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates ?International bank account number?. The external system should send an encrypted IBANID and M3 will decrypt it before storing in the M3 table.
SupplierPartyMaster/FinancialParty/FinancialAccount/Name ?CBANAC.BCBANA ; CRS692MI/AddBankAccount, ChgBasicData	The field indicates the Bank account name.
SupplierPartyMaster/UserArea/Property/NameValue 1) CIDMAS.IDCFI1 2) CIDMAS.IDALSU 3) CIDMAS.IDCSCD	User defined field The field indicates the User defined field (CFI1). If attribute name is "SupplierFreeField1", populate User-defined field
.; CRS620MI/AddSupplier, UpdSupplier Infor May 26, 20	1 (CFI1). 023 210

SupplierPartyMaster

2) Search key

The field indicates a Search key (ALSU).

If attribute name is "SearchKey", populate Search key (ALSU).

3) Vat country code.

The field indicates the Vat country code (CSCD) which will be used to retrieve the VAT registration number.

If attribute name is "VATCountryCode", populate Vat country code

(CSCD)

SupplierPartyMaster/Status/Code

CIDMAS.IDSTAT

; CRS620MI/AddSupplier, UpdSupplier

The field indicates the status.

If code is Pending, actionCode is Add and STEM is empty, set status to 05. Else, set status to 10.

If code is Pending and actionCode is Change, set status to 10.

If code is Open or Approved, set status to 20.

If code is Hold, set status to 30.

If code is Closed or Deleted, set status to 90

SupplierPartyMaster/CurrencyCode

CIDVEN.IICUCD

CRS620MI/AddSupplier, UpdSupplier

The field indicates the abbreviation for the currency.

SupplierPartyMaster/Classification/Codes/Code

- 1) CIDVEN.IIORTY
- 2) CIDVEN.IICOBI
- 3) CIDVEN.IISCNO
- 4) CIDVEN.IIOUCN
- 5) CIDVEN.IITECD
- 6) CIDVEN.IITEDL
- 7) CIDVEN.IIMODL
- 8) CIDVEN.IITEPA
- 9) CIDVEN.IITEAF
- 10) CIDVEN.IIPACD
- 11) CIDVEN.IISUST
- 12) CIDVEN.IICINP
- 13) CIDVEN.IITXAP
- 14) CIDVEN.IICRTP
- 15) CIDMAS.IDSUCO 16) CIDMAS.IDPPIN
- 17) CIDVEN.IDSUCL 18) CIDVEN.IDTAXC
- 19) CIDVEN.IITDCD
- ; ĆRS620MI/AddSupplier,

UpdSupplier

The field indicates the classification code.

1) Order type

The field indicates the settings that determine how the order is processed during order entry and in the processing flow. If attribute listID is 'Order type', populate Customer type (ORTY).

2) Group of companies

The field indicates the company group to which the supplier belongs. If attribute listID is 'Group Of Companies', populate Group of companies (COBI).

3) Supplier's customer number

The field indicates the supplier's customer number.

If attribute listID is 'Supplier's Customer Number', populate Supplier's customer number (SCNO).

4) Our customer number at supplier

The field indicates the our customer number at supplier, which is the customer number our supplier uses as identity for us.

If attribute listID is 'Our Customer Number', populate Our Customer number (OUCN).

5) Cash discount term

The field indicates the terms for cash discount calculation. If attribute listID is 'Cash Discount Term', populate Cash Discount Term (TECD).

6) Delivery terms

The field indicates the delivery terms, which define when the responsibility for a delivery is transferred from supplier to the customer.

If attribute listID is 'Delivery Terms', populate Delivery Terms (TEDL).

7) Delivery method

The field indicates how the delivery is made.

If attribute listID is 'Delivery Method', populate Delivery Method (MODL).

8) Packaging tems

The field indicates the what terms apply when goods are packed. If attribute listID is 'Packaging Terms', populate Packaging Terms (TEPA).

9) Freight terms

The field indicate the freigh terms which apply for the delivered goods. If attribute listID is 'Freight Terms', populate Packaging Terms (TEAF).

10) Payment priority

The field indicates the payment priority.

If attribute listID is 'Payment Priority', populate Packaging Terms

If Highest Priority, populate PACD with A.

If Priority 1, populate PACD with 1.

If Priority 2, populate PACD with 2. If Priority 3, populate PACD with 3. If Priority 4, populate PACD with 4. If Priority 5, populate PACD with 5. If Priority 6, populate PACD with 6. If Priority 7, populate PACD with 7. If Lowest Priority, populate PACD with 8. If Stopped, populate PACD with 9.

11) Supplier statistics

Set to 1 if statistics are to be calculated for the supplier. If attribute listID is 'Supplier Statistics', populate Supplier statistics (SUST).

12) Claim invoice permitted

Set to 1 if claim invoice is allowed.

If attribute listID is 'Claim Invoice Permitted', populate Claim invoice permitted (CINP).

13) Tax applicable

The field indicates whether the supplier is required to declare VAT or sales tax.

If attribute listID is 'Tax Applicable', populate Tax applicable (TAXP). If No, populate TAXP with 0.

If Yes, populate TAXP with 2.

14) Exchange rate type

The field indicates the exchange rate used when prices in the purchase module are converted to local currency or another currency. If attribute listID is 'Exchange Rate Type', populate Exchange rate type (CRTP).

15) Supplier number within group

The field indicates the supplier number that the company group uses for the supplier.

If attribute listID is 'Supplier Number In Group', populate Supplier number within group (SUCO).

16) Print packing instruction

The field indicates how to activate the automatic printing of connected packing instructions when purchase orders are printed.

If attribute listID is 'Print Packing Instruction', populate Print packing instruction (PPIN).

If No, populate PPIN with 0.

If How to pack and Mark for, populate PPIN with 1.

If How to pack, populate PPIN with 2.

If Mark for, populate PPIN with 3.

17) Supplier group or Vendor group

The field indicates the supplier group or vendor group specified for each supplier.

If attribute listID is 'Supplier Group', populate Supplier group (SUCL). If attribute listID is 'VendorGroup', populate Vendor group (SUCL).

18) Tax code

The field indicates if an item, charge, customer or ship-to location is taxable or not

If attribute listID is 'Tax Code', populate Tax Code (TAXC).

19) Trade code

The field indicates a code that denotes the type of trade. If attribute listID is 'Trade Code', populate Trade Code (TDCD).

- 1) If attribute listID is 'Order type', populate Customer type (ORTY).
- 2) If attribute listID is "Group Of Companies", populate Group of companies (COBI).
- 3) If attribute listID is "Supplier's Customer Number", populate Supplier's customer number (SCNO).
- 4) If attribute listID is "Our Customer Number", populate Our Customer number (OUCN).
- 5) If attribute listID is "Cash Discount Term", populate Cash Discount Term (TECD).
- 6) If attribute listID is "Delivery Terms", populate Delivery Terms (TEDL).
- 7) If attribute listID is "Delivery Method", populate Delivery Method (MODL).
- if attribute listID is "Packaging Terms", populate Packaging Terms (TEPA).
- 9) If attribute listID is "Freight Terms", populate Packaging Terms

@listID

SupplierPartyMaster

(TEAF).

- 10) If attribute listID is "Payment Priority", populate Packaging Terms (PÁCD).
- 11) If attribute listID is "Supplier Statistics", populate Supplier statistics (SUST).
- 12) If attribute listID is "Claim Invoice Permitted", populate Claim invoice permitted (CINP).
- 13) If attribute listID is "Tax Applicable", populate Tax applicable (TÁXP).
- 14) If attribute listID is "Exchange Rate Type", populate Exchange rate type (CRTP).
- 15) If attribute listID is "Supplier Number In Group", populate Supplier
- number within group (SUCO).

 16) If attribute listID is "Print Packing Instruction", populate Print packing instruction (PPIN).
- 17) If attribute listID is "Supplier Group", populate Supplier group (SUCL) else, If attribute listID is "VendorGroup', populate Vendor group (SUCL).
- 18) If attribute listID is "Tax Code', populate Tax Code (TAXC).
- 19) If attribute listID is "Trade Code", populate Trade Code (TDCD).

SupplierPartyMaster/BuyerPersonReference/IDs/ID

CIDVEN.IIBUYE ; CRS620MI/AddSupplier, UpdSupplier The field indicates the buyer.

Transfer

Transfer/TransferHeader/DocumentID/ID MHIHED.G0RIDN: The field indicates the order number for a requisition order or MHS850MI/AddWhsHead distribution order. MHILIN.G2RIDN; MHS850MI/AddWhsLine @location MHIHED.G0FACI; The field indicates the facility. MHS850MI/AddWhsHead MHILIN.G2FACI; MHS850MI/AddWhsLine Transfer/TransferHeader/ShipFromParty/Location/ID MHIHED.G0WHLO: The field indicates the warehouse MHS850MI/AddWhsHead MHIPAC.G1WHLO; MHS850MI/AddWhsPack MHILIN.G2WHLO; MHS850MI/AddWhsLine Transfer/TransferHeader/ShipToParty/Location/ID MHIHED.G0CUNO; MHS850MI/AddWhsHead The field indicates the receiving warehouse. Transfer/TransferHeader/UserArea 1) MHILIN.G2TTYP; 1) The field indicates the stock transaction type. MHS850MI/AddWhsLine If "Distribution order issue", set to 51. If "Requistion order issue", set to 41. 2) MHILIN.G2TRTP: MHS850MI/AddWhsLine If "Requisition order receipt, set to 40. 2) MHIHED.G0RESP; If listID="StockTransactionType", populate TTYP. 2) The field indicates the order type. MHS850MI/AddWhsHead If listID="OrderType", populate TRTP. MHILIN.G1RESP; MHS850MI/AddWhsLine 3) The field indicates the responsible. MHIPAC.G2RESP; If listID="Responsible", populate RESP. MHS850MI/AddWhsPack.; / Transfer/TransferLine/Item/ItemID/ID MHILIN.G1ITNO; MHS850MI/AddWhsLine The field indicates the item number. Transfer/TransferLine/Item/SerializedLot/Lot/Lot/Ds/ID MHILIN.G2BANO; MHS850MI/AddWhsLine The field indicates the lot number. Transfer/TransferLine/Quantity MHILIN.G0ALQT; MHS850MI/AddWhsLine The field indicates the allocated quantity. Transfer/TransferLine/ShippedQuantity MHIHED.G0DLQT; MHS850MI/AddWhsLine The field indicates the picked/delivered quantity.