如何制作 linux 模板

1. 安装

安装虚拟机设置:

点击这里	点击 这里	点击这里	点击这里	点击 这里
	СРИ	内存大小 (MB)	硬盘方式、大小 (G)	网卡 方式
Centos 5.x 系列	2个	2048	virtio、20G、 qcow2	virti o
Centos 6.x 系列	2个	2048	virtio、20G、 qcow2	virti o


安装方法:

用操作系统 iso 镜像安装,按照过程要点如下:


分区选择手动分区





先创建一个标准分区,



大小 200M, 文件系统 ext2, 挂载点是/boot









名字统一叫 vmvg



在创建一个大小为 16180M 的 lv, 名字为 root, 挂载点为/, 文件系统为 ext4



在创建一个大小为 4096M 的 lv, 名字为 swap, 挂载点为 swap, 文件系统为 swap

Make Logical Volume				
<u>M</u> ount Point:	<not applicable=""></not>	~		
File System Type:	swap	0		
<u>L</u> ogical Volume Name:	swap			
<u>S</u> ize (MB):	4096			
□ <u>E</u> ncrypt	(Max size is 9216 MB)	com		
••		COI		

注意:因为后面需要通过 guestfish 扩展分区和文件系统, vg,lv 的名字和文件系统需要严格统一操作。 2. 时钟设置

因为虚拟机的时间会发生漂移,为了尽量修正虚拟机时间,需要做以下两项设置: 给虚拟机设置一个 NTP 服务器,目前统一设置成公司的 NTP 服务器 61.172.254.29。 根据版本不同,设置方法也不同,请参考下表设置。

点击这里	点击这里
Red Hat Enterprise Linux version	Additional guest kernel parameters
6.0 AMD64/Intel 64 with the para-virtualized clock	Additional parameters are not required
6.0 AMD64/Intel 64 without the para-virtualized clock	notsc lpj=n
5.5 AMD64/Intel 64 with the para-virtualized clock	divider=10[1]
5.5 AMD64/Intel 64 without the para-virtualized clock	divider=10 notsc lpj=n
5.5 x86 with the para-virtualized clock	Additional parameters are not required
5.5 x86 without the para-virtualized clock	divider=10 clocksource=acpi_pm

	lpj=n
5.4 AMD64/Intel 64	divider=10 notsc
5.4 x86	divider=10 clocksource=acpi_pm
5.3 AMD64/Intel 64	divider=10 notsc
5.3 x86	divider=10 clocksource=acpi_pm
4.8 AMD64/Intel 64	notsc divider=10
4.8 x86	clock=pmtmr divider=10
3.9 AMD64/Intel 64	Additional parameters are not required
3.9 x86	Additional parameters are not required

3. 6.x 系列的 udev 设置

6.x 系列 udev 会记录旧的网卡信息,需要将相关信息删除,负责会造成网卡使用不正常,操作过程如下:

rm /etc/udev/rules.d/70-persistent-net.rules –f

rm /etc/sysconfig/network-scripts/ifcfg-eth0 –f

rm /etc/sysconfig/network-scripts/ifcfg-eth1 –f

shutdown –h now

注意:如果因为需要重新开启了虚拟机镜像,关闭的时候需要重新删除以上文件。