## Icinga2 Provider

The Icinga2 provider is used to configure hosts to be monitored by Icinga2 (https://www.icinga.com/products/icinga-2/) servers. The provider needs to be configured with the API URL of the Icinga2 server and credentials for an API user with the appropriate permissions.

#### Example Usage

#### Authentication

#### Static credentials

Static credentials can be provided by adding an api\_user and api\_password in-line in the icinga2 provider block:

Usage:

#### **Environment variables**

You can provide your credentials via ICINGA2\_API\_USER and ICINGA2\_API\_PASSWORD, environment variables, storing your lcinga2 API user and password, respectively. ICINGA2\_API\_URL and ICINGA2\_INSECURE\_SKIP\_TLS\_VERIFY are also used, if applicable:

```
provider "icinga" {}
```

Usage:

```
$ export ICINGA2_API_URL=https://192.168.33.5:5665/v1
$ export ICINGA2_API_USER=root
$ export ICINGA2_API_PASSWORD=icinga
$ export ICINGA2_INSECURE_SKIP_TLS_VERIFY=true
$ terraform plan
```

#### **Argument Reference**

- api\_url (Required) The root API URL of an Icinga2 server. May alternatively be set via the ICINGA2\_API\_URL environment variable.
- api\_user (Required) The API username to use to authenticate to the Icinga2 server. May alternatively be set via the ICINGA2\_API\_USER environment variable.
- api\_password (Required) The password to use to authenticate to the Icinga2 server. May alternatively be set via the ICINGA2\_API\_PASSWORD environment variable.
- insecure\_skip\_tls\_verify (optional) Defaults to false. If set to true, verification of the Icinga2 server's SSL certificate is disabled. This is a security risk and should be avoided. May alternatively be set via the ICINGA2\_INSECURE\_SKIP\_TLS\_VERIFY environment variable.

## icinga2\_checkcommand

Configures an Icinga2 checkcommand resource. This allows checkcommands to be configured, updated, and deleted.

#### **Example Usage**

```
# Configure a new checkcommand on an Icinga2 Server, that can be used to monitor hosts and/or services
provider "icinga2" {
    api_url = "https://192.168.33.5:5665/v1"
}

resource "icinga2_checkcommand" "apache_status" {
    name = "apache_status"
    templates = ["apache-status", "plugin-check-command", "plugin-check-command", "ipv4-or-ipv6"]
    command = "/usr/lib64/nagios/plugins/check_apache_status.pl"

arguments = {
    "-H" = "$apache_status_address$"
    "-c" = "$apache_status_critical$"
    "-p" = "$apache_status_port$"
}
```

#### **Argument Reference**

- arguments (Optional) A mapping of arguments to include with the command.
- command (Required) Path to the command te be executed.
- name (Required) Name by which to reference the checkcommand
- templates (Optional) A list of Icinga2 templates to assign to the host.

## icinga2\_host

Configures an Icinga2 host resource. This allows hosts to be configured, updated, and deleted.

#### **Example Usage**

```
# Configure a new host to be monitored by an Icinga2 Server
provider "icinga2" {
    api_url = "https://192.168.33.5:5665/v1"
}

resource "icinga2_host" "host" {
    hostname = "terraform-host-1"
    address = "10.10.10.1"
    check_command = "hostalive"
    templates = ["bp-host-web"]

vars {
    os = "linux"
    osver = "1"
    allowance = "none"
    }
}
```

#### **Argument Reference**

- address (Required) The address of the host.
- check\_command (Required) The name of an existing Icinga2 CheckCommand object that is used to determine if the host is available or not.
- hostname (Required) The hostname of the host.
- templates (Optional) A list of Icinga2 templates to assign to the host.
- vars (Optional) A mapping of variables to assign to the host.

# icinga2\_hostgroup

Configures an Icinga2 hostgroup resource. This allows hostgroup to be configured, updated, and deleted.

## **Example Usage**

## **Argument Reference**

- name (Required) The name of the hostgroup.
- display\_name (Required) The name of the hostgroup to display in the Icinga2 interface.

## icinga2\_notification

Configures an Icinga2 notification resource. This allows notifications to be configured, updated, and deleted.

#### **Example Usage**

```
# Configure a new host notification

provider "icinga2" {
    api_url = "https://192.168.33.5:5665/v1"
}

resource "icinga2_notification" "host-notification" {
    hostname = "docker-icinga2"
    command = "mail-host-notification"
    users = ["user"]
}
```

```
# Configure a new service notification

provider "icinga2" {
    api_url = "https://192.168.33.5:5665/v1"
}

resource "icinga2_notification" "ping-service-notification" {
    hostname = "docker-icinga2"
    command = "mail-service-notification"
    users = ["user"]
    servicename = "ping"
}
```

#### **Argument Reference**

- hostname (Required) The hostname the notification applies to.
- command (Required) Notification command to use.
- users (Required) List of users to notification.
- servicename (Optional) Service to send notification for.

# icinga2\_service

Configures an Icinga2 service resource. This allows service to be configured, updated, and deleted.

## **Example Usage**

## **Argument Reference**

- name (Required) The name of the Service object.
- check\_command (Required) The name of an existing Icinga2 CheckCommand object that is used to determine if the service is available on the host.
- hostname (Required) The host to check the service's status on

# icinga2\_user

Configures an Icinga2 user resource. This allows users to be configured, updated, and deleted.

## **Example Usage**

```
# Configure a new user

provider "icinga2" {
    api_url = "https://192.168.33.5:5665/v1"
}

resource "icinga2_user" "terraform" {
    name = "terraform"
    email = "terraform@dev.null"
}
```

## **Argument Reference**

- name (Required) The user.
- email (Optional) An email string for this user. Useful for notification commands.